

ADARES JCL/JCS Requirements and Examples

This section describes the job control information required to run the Delta Save functions of ADARES with BS2000, OS/390, z/OS, z/VM, and VSE/ESA systems, and shows examples of each of the job streams.

Note:

When running with the optional Recovery Aid (RLOG), all temporary datasets must also be cataloged in the job control.

This chapter covers the following topics:

- BS2000
 - OS/390 or z/OS
 - z/VM
 - VSE/ESA
-

BS2000

Dataset	Link Name	Storage	More Information
Associator	DDASSORn	disk	
Delta Save images (DSIM)	DDDSIMR1	disk	required when ADARUN DSF=YES
Sequential protection log (PLOG)	DDSIIN	tape/disk	input log for COPY
Dual/multiple PLOG	DDPLOGRn	disk	input log for PLCOPY
Copied log	DDSIAUS1	tape/disk	output of COPY, CLCOPY, PLCOPY
Extra copied log	DDSIAUS2	tape/disk	required if a copy function is used with TWOCOPIES
Recovery log (RLOG)	DDRLOGR1	disk	required for RLOG function
ADARES parameters	SYSDTA/DDKARTE		
ADARUN parameters	SYSDTA/DDCARD		<i>Adabas Operations</i>
ADARES messages	SYSLST/DDDRUCK		<i>Adabas Messages and Codes</i>
ADARUN messages	SYSOUT/DDPRINT		<i>Adabas Messages and Codes</i>

Rebuild DSIM Dataset from Sequential Protection Log (ADARES COPY)

```

/.COPY           LOGON
/MOD-JOB-OPTIONS LISTING=YES
/MOD-TEST        DUMP=YES
/ASS-SYSLST      DO.PLCOPY.LST
/ASS-SYSOUT      DO.PLCOPY.OUT
/SET-JOB-STEP
/ASS-SYSDTA      *SYSCMD
/SET-FILE-LINK   DDASSOR1,
ADABAS.DB010.ASSOR1,SUP=DISK(SHARE-UPD=YES)
/SET-FILE-LINK   DDDSIMR1, ADABAS.DB010.DSIM
,SUP=DISK(SHARE-UPD=NO)
/SET-FILE-LINK   DDSIIN , ADABAS.DB010.PLOG0310
/SET-FILE-LINK   DDSIAUS1, *DUMMY
/SET-FILE-LINK   DDLIB    , ADABAS.MOD
/REMARK
/START-PROGRAM   FROM-FILE=*MOD(ADABAS.MOD,ADARUN)
ADARUN PROG=ADARES,DSF=YES...
ADARES COPY ...
ADARES DSIMSIZE=...
/ASS-SYSLST      *PRIM
/ASS-SYSOUT      *PRIM
/ASS-SYSDTA      *PRIM
/LOGOFF          SYS-OUTPUT=DEL

```

Copy Dual/Multiple Protection Log/Build DSIM Dataset (ADARES PLCOPY)

```

/.PLCOPY          LOGON
/MOD-JOB-OPTIONS LISTING=YES
/MOD-TEST         DUMP=YES
/ASS-SYSLST       DO.PLCOPY.LST
/ASS-SYSOUT       DO.PLCOPY.OUT
/CREATE-FILE      ADABAS.DB010,PLOG.COPY,

```

```
/           ( SPACE=RELA(PRIM-ALLOC=960,SEC-ALLOC=96) )

/SET-JOB-STEP

/ASS-SYSDTA      *SYSCMD

/SET-FILE-LINK   DDASSOR1,
                  ADABAS.DB010.ASSOR1,SUP=DISK(SHARE-UPD=YES)

/SET-FILE-LINK   DDDSIMR1, ADABAS.DB010.DSIM
                  ,SUP=DISK(SHARE-UPD=YES)

/SET-FILE-LINK   DDPLOGR1, ADABAS.DB010.PLOGR1

/SET-FILE-LINK   DDPLOGR2, ADABAS.DB010.PLOGR2

/SET-FILE-LINK   DDSIIN  , ADABAS.DB010.PLOG.COPY,OPEN-MODE=OUTIN,
/
                  BUFFER-LENGTH=STD(16)

/SET-FILE-LINK   DDLIB    , ADABAS.MOD

/REMARK

/START-PROGRAM   FROM-FILE=*MOD(ADABAS.MOD,ADARUN)

ADARUN   PROG=ADARES,DSF=YES...
```

ADARES PLCOPY ...

```
ADARES      DSIMSIZE=...

/ASS-SYSLST   *PRIM

/ASS-SYSOUT   *PRIM

/ASS-SYSDTA   *PRIM

/LOGOFF      SYS-OUTPUT=DEL
```

OS/390 or z/OS

Dataset	DD Name	Storage	More Information
Associator	DDASSORn	disk	
Delta Save images (DSIM)	DDDSIMR1	disk	required when ADARUN DSF=YES
Sequential protection log (PLOG)	DDSIIN	tape/disk	input log for COPY
Dual/multiple PLOG	DDPLOGRn	disk	input log for PLCOPY
Copied log	DDSIAUS1	tape/disk	output of COPY and PLCOPY
Extra copied log	DDSIAUS2	tape/disk	required if a copy function is used with TWOCOPIES
Recovery log (RLOG)	DDRLOGR1	disk	required for RLOG option
ADARES parameters	DDKARTE		
ADARUN parameters	DDCARD		<i>Adabas Operations</i>
ADARES messages	DDDRUCK		<i>Adabas Messages and Codes</i>
ADARUN messages	DDPRINT		<i>Adabas Messages and Codes</i>

Rebuild DSIM Dataset from Sequential Protection Log (ADARES COPY)

```

//COPY      EXEC   PGM=ADARUN

//DDASSOR1 DD  DSN=ADABAS.DB010.ASSOR1,DISP=SHR

//DDDSIMR1 DD  DSN=ADABAS.DB010.DSIMR1,DISP=OLD

//DDSIIN    DD  DSN=ADABAS.DB010.PLOG0310,DISP=SHR

//DDSIAUS1 DD  DUMMY

//DDCARD    DD  *

ADARUN PROG=ADARES,DSF=YES, ...

//DDKARTE  DD  *

ADARES COPY ...

ADARES      DSIMSIZE=...

//DDPRINT   DD  SYSOUT=*

//DDDRUCK  DD  SYSOUT=*

```

Copy Dual/Multiple Protection Log/Build DSIM Dataset (ADARES PLCOPY)

```
//PLCOPY    EXEC   PGM=ADARUN

//DDASSOR1 DD   DSN=ADABAS.DB010.ASSOR1,DISP=SHR

//DDPLOGR1 DD   DSN=ADABAS.DB010.PLOGR1,DISP=SHR

//DDPLOGR2 DD   DSN=ADABAS.DB010.PLOGR2,DISP=SHR

//DDDSIMR1 DD   DSN=ADABAS.DB010.DSIMR1,DISP=SHR

//DDSIAUS1 DD   DSN=ADABAS.DB010.PLOG1310,DISP=(NEW,CATLG),

//               UNIT=CASS, ...

//DDCARD    DD   *

ADARUN PROG=ADARES,DSF=YES, ...

//DDKARTE   DD   *

ADARES PLCOPY ...

ADARES          DSIMSIZE=...

//DDPRINT   DD   SYSOUT=*

//DDDRUCK   DD   SYSOUT=*
```

z/VM

Dataset	DD Name	Storage Type	More Information
Associator	DDASSORn	disk	
Delta Save images (DSIM)	DDDSIMR1	disk	required when ADARUN DSF=YES
Sequential protection log (PLOG)	DDSIIN	tape/disk	input log for COPY
Dual/multiple PLOG	DDPLOGRn	disk	input log for PLCOPY
Copied log	DDSIAUS1	tape/disk	output of COPY and PLCOPY
Extra copied log	DDSIAUS2	tape/disk	required if a copy function is used with TWOCOPIES
Recovery log (RLOG)	DDRLOGR1	disk	required for RLOG option
ADARES parameters	DDKARTE	disk/ terminal/ reader	
ADARUN parameters	DDCARD	disk/ terminal/ reader	<i>Adabas Operations</i>
ADARES messages	DDDRUCK	disk/ terminal/ printer	<i>Adabas Messages and Codes</i>
ADARUN messages	DDPRINT	disk/ terminal/ printer	<i>Adabas Messages and Codes</i>

Rebuild DSIM Dataset from Sequential Protection Log (ADARES COPY)

```

DATADEF DDASSOR1,DSN=ADABASVv.ASSO,VOL=ASSOV1

DATADEF DDDSIMR1,DSN=ADABASVv.DSIM,VOL=DSIM

DATADEF DDSIIN,DSN=ADABASVv.SIBA,MODE=A

DATADEF DDSIAUS1,DSN=ADABASVv.SIAUS1,UNIT=181,VOL=SIBA01

DATADEF DDPRINT,DSN=ADARES.DDPRINT,MODE=A

DATADEF DDDRUCK,DSN=ADARES.DDDRUCK,MODE=A

DATADEF DDCARD,DSN=RUNRES.CONTROL,MODE=A

DATADEF DDKARTE,DSN=ADARES.CONTROL,MODE=A

ADARUN

```

Contents of RUNRES CONTROL A1:

```
ADARUN PROG=ADARES,DSF=YES...
```

Contents of ADARES CONTROL A1:

```
ADARES COPY ...  
ADARES DSIMSIZE=...
```

Copy Dual/Multiple Protection Log/Build DSIM Dataset (ADARES PLCOPY)

```
DATADEF DDASSOR1,DSN=ADABASVv.ASSO,VOL=ASSOV1  
DATADEF DDPLOGR1,DSN=ADABASVv.PLOGR1,VOL=PLOGR1  
DATADEF DDPLOGR2,DSN=ADABASVv.PLOGR2,VOL=PLOGR2  
DATADEF DDSIMR1,DSN=ADABASVv.DSIM,VOL=DSIM  
DATADEF DDSIAUS1,DSN=ADABASVv.SIAUS1,UNIT=181,VOL=SIBA01  
DATADEF DDPRINT,DSN=ADARES.DDPRINT,MODE=A  
DATADEF DDDRUCK,DSN=ADARES.DDDRUCK,MODE=A  
DATADEF DDCARD,DSN=RUNRES.CONTROL,MODE=A  
DATADEF DDKARTE,DSN=ADARES.CONTROL,MODE=A  
ADARUN
```

Contents of RUNRES CONTROL A1:

```
ADARUN PROG=ADARES,DSF=YES...
```

Contents of ADARES CONTROL A1:

```
ADARES PLCOPY ...  
ADARES DSIMSIZE=...
```

VSE/ESA

Dataset	Symbolic	Storage	Logical Unit	More Information
Associator	ASSORn	disk		see note
Delta Save images (DSIM)	DSIMR1	disk		required when ADARUN DSF=YES
Sequential protection log (PLOG)	SIIN	tape/disk		input log for COPY
Dual/multiple PLOG	PLOGRn	disk	*	input log for PLCOPY
Copied log	SIAUS1	tape disk	SYS021 *	output of COPY and PLCOPY
Extra copied log	SIAUS2	tape disk	SYS022 *	required if a copy function is used with TWOCOPIES
Recovery log (RLOG)	RLOGR1	disk		required for RLOG option
ADARES parameters		reader	SYSIPT	
ADARUN parameters	- CARD CARD	reader tape disk	SYSRDR SYS000 *	<i>Adabas Operations</i>
ADARES messages		printer	SYS009	<i>Adabas Messages and Codes</i>
ADARUN messages		printer	SYSLST	<i>Adabas Messages and Codes</i>

* Any programmer logical unit can be used.

See the VSE/ESA-related job information in section Adabas Utility Functions for Delta Save .

Rebuild DSIM Dataset from Sequential Protection Log (ADARES COPY)

```
// EXEC PROC=ADAVvFIL
// EXEC PROC=ADAVvLIB
// EXEC ADARUN,SIZE=ADARUN
ADARUN PROG=ADARES,DSF=YES,...
/*
ADARES COPY
ADARES DSIMSIZE=...
/*
```

Copy Dual/Multiple Protection Log/Build DSIM Dataset (ADARES PLCOPY)

```
// EXEC PROC=ADAVvFIL  
  
// EXEC PROC=ADAVvLIB  
  
// EXEC ADARUN,SIZE=ADARUN  
  
ADARUN PROG=ADARES,DSF=YES,...  
  
/*  
  
ADARES PLCOPY  
  
ADARES DSIMSIZE=...  
  
/*
```