

Local User Information

The Local User Information option provides information from the TM proxy component in the Adabas link module that your ATM Online Services session is currently using. For example, if your session is executing in a CICS region, information is provided about users in that CICS system who are using the same Adabas link module.

- Local User Information Menu
- List Local Users
- Display Zap Information

Local User Information Menu

▶ To display the User Information menu

- Select service 3 from the Online Services main menu.

The following menu will appear:

```

16:08:30  ***** A D A B A S TRANSACTION MANAGER 7.5.1 *****                2004-03-05
                                     - User Information -                          T13000M1

Job Name: DAEFCI18

          Code      Service
          ----      -
          1         Local Users
          2         Display Zap Information
          .         Exit
          ----      -
Code .. _

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12
      Help           Exit                                     Menu

```

From this menu, you can	Code	Command
list local users	1	3.1
display zap information	2	3.2

List Local Users

This function produces a list of all users of the TM proxy currently being used by your session.

```

16:08:43 ***** A D A B A S TRANSACTION MANAGER 7.5.1 *****                2004-03-05
- Local Users -                                                                T13100M1

Job Name: DAEFCI18

<-----Terminal ID----->      <-----ETID/TCID----->  T
C  Char  Hex                      T      Char  Hex                      Typ  C  Status
-  E000  C5F0F0F000000000 T          0000000000000000 NTR  A  804000 GT
-  E000  C5F0F0F000000000 T          0000000000000000 DTP  A  806000 GT
-  E001  C5F0F0F100000000 T          0000000000000000 NTR  A  804000 GT
-  E001  C5F0F0F100000000 E      05  F0F5404040404040 DTP  A  802000 GT
-  E002  C5F0F0F200000000 T          0000000000000000 NTR  A  804000 GT
-  E002  C5F0F0F200000000 E  PD03 D7C4F0F340404040 DTP  A  002000 TRN OPEN

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF9---PF10--PF11--PF12
      Help           Exit Refr                      Top                               Net   Menu

```

The following information is provided:

Field	Description
C	Enter a non-blank character and press Enter to obtain more detailed information about a particular user.
Terminal ID	The environment-dependent identifier of the user session in character and hexadecimal format. For example, the identifier for a CICS user is usually the user's CICS terminal ID. Use PF11 to toggle between Terminal ID and Net Name.
Net Name	The environment-dependent identifier of the user session. For example, the identifier for a CICS user is usually the session's VTAM LName. Use PF11 to toggle between Terminal ID and Net Name.
T	The value T indicates the presence of a TM Client ID (TCID). The value E indicates an ETID. A user who did not open with an ETID is represented by a unique, reusable identifier known as a TM Client ID (TCID).
ETID/TCID	The ETID or TCID for each user, in character and hexadecimal format.
Typ	The user type. Possible values are: <ul style="list-style-type: none"> ● DTP: a normal DTP-mode user ● SER: a user that is operating in serial ET/BT mode ● NTR: a user for whom the TM proxy does not invoke transparent global transaction processing

Field	Description
TC	<p>The transaction coordinator that has control of the user's global transactions. Possible values are:</p> <ul style="list-style-type: none"> ● A: the local ATM daemon has control ● C: the local client-side transaction coordinator has control ● H: the host system transaction coordinator has control
Status	<p>The user's current status values together with a summary interpretation, as known by the TM proxy. Possible values are:</p> <ul style="list-style-type: none"> ● CLT SYNC: syncpoint requested by client-side transaction coordinator ● FORCE BT: forced backout in progress ● GT: global transaction status ● IN BKOUT: an attempt to back out has not yet completed ● IN CMIT: an attempt to commit has not yet completed ● IN ET/BT: prepare/commit/backout in progress ● SESS ERR: the user is not in session with ATM ● TM DOWN: TM unavailable ● TRN OPEN: transaction in progress ● UNKNOWN: transaction status not known ● XH ET: in extended hold (ET) status ● XH BT: in extended hold (BT) status

Display User Details

Whenever the C column for a particular user is marked, a screen similar to the following will be displayed:

```

16:09:34 ***** A D A B A S TRANSACTION MANAGER 7.5.1 *****                2004-03-05
                                     - User Details -                               T13110M1

Job Name: DAEFCI18          Co-ordinator: ATM  User Type: 00 - DTP
Terminal ID:  E002          C5F0F0F200000000 Net Name: TPXGE002 E3D7E7C7C5F0F0F2
ID Type:  E ETID/TCID:PD03 D7C4F0F340404040 Status: 0020000000 - TRN OPEN
CommID: 000F7100 20640000 B902C560 B53A6482 00000001 C3C9C3E2 C5F0F0F2
      XID: C1C4C101 00000050 00000002 1B98000F 71002064 0000B902 C560B53A 64820000
          0001C3C9 C3E2C5F0 F0F2D7C4 F0F34040 4040C4C1 C5C6C3C9 F1F8B902 C7FCD5C9
          D5010000 00000000 00000000 00000000 00000000 00000000 00000000 C2D80000
          00000000 00000000 00000000 00000000 00000000 00000000 00000000 00000000
Adabas Calls: 862  Transactions: 3          UAB: 1B0287B8 GUQE: 1A9C3840
Last Function Call: 24 - NEW TRGT          Transaction model: MESSAGE

DBNo. L/R DTP Status          | Pending Response Codes
   135 L  N  8067 ET          | Resp. Subcode
47163 R  Y  0064 CHANGED      |
   7161 L  Y  0265 CHANGED      |

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF9--PF10--PF11--PF12
      Help          Exit Refr          Top          ErrI Menu

```

The following information is provided:

Field	Description
Jobname	The name of the job under which this Online Services session is running.
Coordinator	The transaction coordinator that has control of the user's global transactions. Possible values are: <ul style="list-style-type: none"> ● ATM: the local ATM daemon has control ● CLIENT SIDE TC: the user's client-side transaction coordinator has control ● HOST TC: the host system transaction coordinator has control
User Type	The internal type code for the user, followed by a summary interpretation. Possible values are: <ul style="list-style-type: none"> ● DTP: a normal DTP-mode user ● SER: a user that is operating in serial ET/BT mode ● NTR: a user for whom the TM proxy does not invoke transparent global transaction processing
Terminal ID	Environment-specific identifier of the user session in character and hexadecimal format.
ETID/TCID	The ETID or TCID for each user, in character and hexadecimal format.
Net-Name	Environment-specific identifier of the user session.
ID Type	Indicates whether the user has an ETID (E) or a TCID (T).

Field	Description
SETID/TCID	The ETID or TCID in character and hexadecimal format.
Status	<p>The user's status code in hexadecimal followed by a summary interpretation in character format.</p> <p>Possible values are:</p> <ul style="list-style-type: none"> ● CLT SYNC: synpoint requested by client-side transaction coordinator ● FORCE BT: forced backout in progress ● GT: global transaction status ● IN BKOUT: an attempt to back out has not yet completed ● IN CMIT: an attempt to commit has not yet completed ● IN ET/BT: prepare/commit/backout in progress ● SESS ERR: the user is not in session with ATM ● TM DOWN: TM unavailable ● TRN OPEN: transaction in progress ● UNKNOWN: transaction status not known ● XH ET: in extended hold (ET) status ● XH BT: in extended hold (BT) status
CommID	The user's 28-byte Adabas Communication ID.
XID	The Transaction ID of the current global transaction. This field contains binary zeros if the user has no transaction in progress.
Adabas Calls	The number of Adabas calls issued by the user.
Transactions	The number of global transactions executed by the user.
UAB	This field contains internal information which might be useful to Software AG's support staff in problem resolution.
GUQE	This field contains internal information which might be useful to Software AG's support staff in problem resolution.
Last Function Call	The type of the most recent internal call sent by the TM proxy to ATM daemon for the user. Included for diagnostic purposes.
Transaction Model	The transaction model that is currently in use for the user.

The remainder of the screen displays:

- a list of databases with which the user is in session; and
- a list of up to five pairs of pending Adabas response codes and subcodes in reverse chronological order.

If the list of databases is too long to fit on the display, “More” appears at the foot of the screen. Use PF7 to return to the top of the list and PF8 to scroll down the list.

List of Databases

Field	Description
DBNo.	Database ID.
L/R	Indicates whether the database is local to or remote from the user; that is, whether or not the database is executing in the same operating system instance.
DTP	Indicates whether distributed transaction processing is enabled for the database; that is, whether it is running with the runtime parameter ADARUN DTP=RM.
Status	<p>A summary of the current status of the database with respect to the current user. Possible summary values are:</p> <ul style="list-style-type: none"> ● ET: the user has no pending updates on this database ● CHANGED: the user has uncommitted updates on this database ● XH: the database is in extended hold status ● BT RQD: backout must be performed on this database

Client TC Display

If the user has an open transaction under the control of the local environment’s client-side transaction coordinator (CLIENT SIDE TC), PF9 at the foot of the screen is labeled “TC”. Pressing PF9 invokes the Client TC Display window showing the identifier used by the client-side transaction coordinator for the transaction.

Error Information

Press PF10 to display the contents of the feedback block returned by the local ATM daemon when the TM proxy last sent a command to it on behalf of the user.

The format of the resulting pop-up window is the same as described in section Display Error Information.

Display Zap Information

This function can be used to determine the zaps that have been applied to the ATM kernel module that is being used by the TM proxy executing in the Adabas link module that your session is currently using.

This function is invoked by selecting option 2, Display Zap Information, on the User Information menu.

The resulting screen output has the same format as that described for displaying zaps for an ATM daemon.

Use PF9 to produce a similar display that shows which zaps have been applied to the Adabas System Coordinator kernel (CORKRN) that is being used by your current session.