

Caching Facility

The Adabas Caching Facility is used to define caching parameter settings and also to monitor caching operations. For detailed information, see the *Caching Facility* section in the *Adabas for Mainframes* documentation.

When the Adabas Caching Facility is installed on your system, the Adabas Manager provides easy access to the optional caching facilities.

Note:

If the Adabas Caching Facility is not installed on your system, the icon will not be displayed in your Adabas Manager tree-view.

 **To view the files with caching for a database:**

1. Select an Adabas database in tree-view and expand it.
2. Select **Caching Facility** in tree-view.

In detail-view, a table displays file names and numbers of the files with caching as well as their cache type and status.

To change the status of a file, select the file by checking the appropriate box in the table and click on **Enable**, **Disable** or **Delete**.

Defining a File Cache

▶ To define a file cache:

1. Select **Caching Facility** in the tree-view and right-click on it.
2. Select **Define File Cache** on the drop-down menu.

In detail-view, the **Define File Cache** table is displayed and allows you to define one or more files to be cached.

Note:

Files already cached are displayed in a second table together with their cache type and status.

3. The following specifications can be set in the table:
 - **Cache Type**
Files may be cached in **ASSO**, **ASSO and DATA**, and **DATA** space.
 - **Memory Type**
The memory type can be **Extended**, **Hiperspace**, **Dataspace**, or **Virtual 64**. The choices available depend on the operating system configuration under which Adabas is running. **Virtual 64** is only available for systems running z/OS version 1.2 or above on the appropriate hardware.
 - **File Number From... To**
Specifying the start file number and the end file number defines a file range to be cached in the defined cache space. If only one file is to be cached, it is not necessary to specify an ending file number.
 - **Class of Service**
Allows you to define the percentage of the file you want to be cached (100%, 75%, 50%, 25%, or 10%).

Enter your specifications in the table and click **OK** or **CANCEL**.

The files you have successfully cached are displayed in a second table together with their cache type and status, i.e, added to the table where cached files already existed.

Maintaining Cache Parameters

▶ To maintain cache parameters:

1. Select **Caching Facility** in the tree-view and right-click on it.
2. Select **Maintain Cache Parameters** on the drop-down menu.

In detail-view, the **Maintain Cache Parameters** table displays the current setting of the Adabas Caching (ADARUN) parameter values and allows you to change them.

3. The following specifications can be set in the table:

- Display Cache Space Statistics - Yes or No
- Minimum Buffer Efficiency
- Elapsed Time (GETMAIN)
- Time of Inactivity
- Maximum Number Permitted
- Maximum ASSO Cache Size
- Maximum DATA Cache Size
- WORK Memory Type
- Percent WORK2 RABNs
- Percent WORK3 RABNs
- **Read Ahead Caching**
 - Number of Buffers
 - Command Types Excluded

Note:

Values for Max. ASSO Cache Size and Max. DATA Cache Size represent bytes, but may be marked with a K (1 kilobyte=1024 bytes), M (1 megabyte=1,048,576 bytes), or G (1 gigabyte=1,073,741,824 bytes) indicator when the size of the value requires it.

For more information about these parameters, see *Adabas Caching Parameters* in the *Caching Facility* section in the *Adabas for Mainframes* documentation.

Enter your specifications in the table and click **OK** or **CANCEL**.

Cache Session Summary

▶ **To view the cache session summary:**

1. Select **Caching Facility** in the tree-view and right-click on it.
2. Select **Cache Session Summary** on the drop-down menu.

In detail-view, the **Cache Session Summary** table displays a summary of information for the Adabas Caching session including cache statistics, read-ahead statistics, and allocation statistics for active and inactive cache spaces.