

ADACM* - ADATCP Messages

Overview of Messages

ADACM007E	ADACM008E	ADACM009E	ADACM010E	ADACM011I	ADACM012E
ADACM013E	ADACM014E	ADACM015E	ADACM016E	ADACM017I	ADACM018E
ADACM019E	ADACM020E	ADACM021E	ADACM022E	ADACM023E	ADACM024E
ADACM025E	ADACM026E	ADACM027E	ADACM028E	ADACM029E	ADACM030E
ADACM031E	ADACM032E	ADACM034E	ADACM035E	ADACM036E	ADACM037E
ADACM038E	ADACM039E				

ADACM007E PARM ERROR

Explanation One of the parameters passed within the URL was incorrect.

Action Ensure that the URL includes valid values for all required elements: the API name (protocol), stack ID, and port number. Correct the URL and try again.

ADACM008E INVALID VALUE IN PORT= PARAMETER

Explanation The port that was specified in the URL was not valid.

Action The port number can be 1-5 bytes; it cannot be zero (0) or greater than 65535.

ADACM009E URL=url ALREADY {ACTIVE | CLOSED}

Explanation Either the URL is already opened (ACTIVE) or already closed (CLOSED).

Action Ensure that the URL includes valid values for all required elements: the API name (protocol), stack ID, and port number. Correct the URL and try again.

ADACM010E URL=url NOT FOUND

Explanation The URL itself was not found.

Action Ensure that the URL includes valid values for all required elements: the API name (protocol), stack ID, and port number. Correct the URL and try again.

ADACM011I URL=url HAS BEEN {CLOSED | OPENED}

Explanation Either the URL was successfully closed or opened.

Action None. This message is for information only.

ADACM012E THE NETWORK IS DOWN

Explanation ADATCP cannot be started because the network is not active.

Action Check that the stack specified in the URL is active. If it is, contact your systems administrator.

ADACM013E NO BUFFER SPACE IS AVAILABLE

Explanation No buffer space is available to ADATCP to allocate its control blocks.

Action Ensure that sufficient storage is available on the system.

ADACM014E THE LINK HAS BEEN SEVERED

Explanation An error caused TCP/IP or ADATCP to terminate.

Action This message is issued along with another message that explains the reason for the termination. Refer to the other message.

ADACM015E TCP/IP IS NOT INSTALLED OR ACTIVE

Explanation The TCP/IP stack specified in the URL is not installed or not active.

Action Check that the specified URL is the one intended. If so, either install the specified stack or start it.

ADACM016E THE SOCKET DESCRIPTOR TABLE IS FULL

Explanation The maximum number of socket descriptors has been reached: no more sockets can be created.

Action Increase the maximum number of sockets that can be created.

ADACM017I TCP/IP HAS TERMINATED

Explanation Unless this message is accompanied by an error message, TCP/IP has terminated normally.

Action If an error message accompanies this message, refer to that message. Otherwise, this message is for information only.

ADACM018E THE API CANNOT LOCATE THE TCP/IP SPECIFIED

Explanation The stack specified in the URL is not valid: TCP/IP cannot initialize.

Action Ensure that the stack is available on the system and that it is active.

ADACM019E THE TCP/IP NAME SPECIFIED IS NOT VALID

Explanation The TCP/IP name specified in the URL is not valid.

Action Check that the URL contains the correct stack name. If so, ensure that the stack is available on the system and that it is active.

ADACM020E TCP/IP FAILED TO LOAD

Explanation The TCP/IP stack specified in the URL cannot be initialized.

Action Ensure that the TCP/IP stack specified is correct and that it is active. If it is correct and active, contact the systems administrator.

ADACM021E UNABLE TO ALLOCATE STORAGE FOR SOCKETCB

Explanation ADATCP is unable to allocate the necessary storage.

Action Ensure that adequate storage is available on the system.

ADACM022E INVALID OPERATING SYSTEM FOR API=HPS

Explanation The operating system specified in the URL is incorrect.

Action The only operating systems currently supported are OES, HPS, and Computer Associates' Unicenter TCPaccess Communications Server (ILK).

ADACM023E UNABLE TO INITIALIZE TCP/IP INTERFACE

Explanation The TCP/IP stack specified in either the URL or the protocol that was used is invalid.

Action Check that the URL or protocol contains the correct stack name. If so, ensure that the stack is available on the system and that it is active.

ADACM024E UNABLE TO GET A SOCKET

Explanation The system is unable to create a new socket. This may be caused by an incorrect stack. If an error number accompanies this message, it will inform you if the problem is inadequate system resources (ENOBUFS) or access denied (EACCES).

Action Ensure that the correct stack is being used. If the problem is inadequate system resources, contact your systems administrator. Contact your security administrator for system access problems.

ADACM025E UNABLE TO BIND SOCKET TO LOCAL SYSTEM

Explanation ADATCP was unable to bind the socket to the local system. Another application may be using the port specified in the URL.

Action Use the TSO NETSTAT command to check current use of the specified port. If something else is using the port, terminate ADATCP and change the port in the URL.

ADACM026E UNABLE TO ACCEPT CONNECTIONS

Explanation ADATCP is unable to accept connections from client applications. This may indicate a shortage of buffer space or that the maximum number of socket descriptors have already been created/opened.

Action Ensure that adequate buffer space is available to the system. If necessary, increase the maximum number of sockets available to the system.

ADACM027E UNABLE TO LISTEN FOR NEW CONNECTIONS

Explanation ADATCP is unable to listen for new connections. This usually indicates that the system resources available to complete the call are inadequate. If an error number is supplied with this message, it will help to identify the problem.

Action If system resources are inadequate, contact your systems administrator.

ADACM028E UNABLE TO SET SOCKOPT REUSEADDR OPTION

Explanation An attempt to allow currently used local addresses to be bound failed. This may indicate inadequate system resources. If an error number is supplied with this message, it will help to identify the problem.

Action If system resources are inadequate, contact your systems administrator.

ADACM029E UNABLE TO GIVESOCKET TO NEW THREAD

Explanation ADATCP was unable to give control of a socket to a different process. This error occurs only if there is a problem with the socket itself. If an error number is supplied with this message, it will help to identify the problem.

ADACM030E UNABLE TO CREATE A NEW THREAD

Explanation The system was unable to create a new thread. This indicates inadequate system resources or memory to create the thread.

Action Contact your systems administrator.

ADACM031E UNABLE TO CLOSE THE REQUESTED SOCKET

Explanation ADATCP attempted to close a socket that was being used by another thread in the same process. This occurs only when the system is terminating due to some other error.

Action Check the console for other messages.

ADACM032E UNABLE TO MALLOC STORAGE

Explanation ADATCP was unable to allocate storage. This may indicate that inadequate storage is available on the system.

Action Contact your systems administrator.

ADACM034E UNABLE TO RECEIVE DATA

Explanation ADATCP cannot receive data from a client. This may indicate that the connection between ADATCP and the client has been severed during a transaction or that system resources are inadequate to complete the call. The error number supplied with this message will identify the problem.

Action Contact your systems administrator.

ADACM035E UNABLE TO TAKE THE SOCKET

Explanation The process that send requests to and from Adabas was unable to take control of the socket that was passed to it by the listening task.

Action Check the error number and the return code that accompany this message.

ADACM036E UNABLE TO SET THE CANCEL TYPE

Explanation The main request task is unable to set the cancel type for the thread that is currently running.

Action Check the error number and the return code that accompany this message.

ADACM037E UNABLE TO SEND DATA

Explanation ADATCP is unable to send data from a client. The error number issued with this message indicates whether the problem is a severed connection between ADATCP and the client or insufficient system resources to complete the call.

Action Check the error number issued with this message.

ADACM038E UNABLE TO CLOSE THE SOCKET

Explanation ADATCP attempted to close a socket while it was being used by another thread in the same process. This occurs if the system has tried to terminate due to another error.

Action Check for other messages issued to the console.

ADACM039E CONTEXT TABLE FULL

Explanation The number of connections has reached a predefined limit; no entries can be added to the user context table.

Action Increase the ADARUN NU parameter value to the required number of entries and restart ADATCP.