

JCL/JCS Requirements and Examples

This section describes the job control information required to run ADAACK with BS2000, z/OS , and z/VSE systems and shows examples of each of the job streams.

This chapter covers the following topics:

- BS2000
- z/OS
- z/VSE

BS2000

| Data Set | Link Name | Storage | More Information |
|-------------------|-----------------|---------|---------------------------|
| Associator | DDASSORn | disk | |
| Data Storage | DDDATARn | disk | |
| ADARUN parameters | SYSDTA/ DDCARD | | <i>Operations</i> |
| ADAACK parameters | SYSDTA/ DDKARTE | | |
| ADARUN messages | SYSOUT DDPRINT | | <i>Messages and Codes</i> |
| ADAACK messages | SYSLST DDRUCK | | <i>Messages and Codes</i> |

ADAACK JCL Examples (BS2000)

In SDF Format:

```

/.ADAACK LOGON
/MODIFY-TEST-OPTIONS DUMP=YES
/REMARK *
/REMARK * A D A A C K ADDRESS CONVERTER CHECK
/REMARK *
/REMARK *
/ASS-SYSLST L.ACK.DATA
/ASS-SYSDTA *SYSCMD
/SET-FILE-LINK DDLIB,ADAvrs.MOD
/SET-FILE-LINK DDASSOR1,ADAYyyyy.ASSO,SHARE-UPD=YES
/SET-FILE-LINK DDDATAR1,ADAYyyyy.DATA,SHARE-UPD=YES
/START-PROGRAM *M(ADA.MOD,ADARUN),PR-MO=ANY
ADARUN PROG=ADAACK,DB=yyyyy, IDTNAME=ADABAS5B
ADAACK ACHECK FILE=ffff
/LOGOFF SYS-OUTPUT=DEL

```

In ISP Format:

```

/.ADAACK LOGON
/OPTION MSG=FB,DUMP=YES
/REMARK *
/REMARK * A D A A C K ADDRESS CONVERTER CHECK
/REMARK *

```

```

/REMARK *
/SYSFILE SYSLST=L.ACK.DATA
/FILE ADAvrs.MOD ,LINK=DDLIB
/FILE ADAyyyyy.ASSO ,LINK=DDASSOR1,SHARUPD=YES
/FILE ADAyyyyy.DATA ,LINK=DDDATAR1,SHARUPD=YES
/EXEC (ADARUN,ADA.MOD)
ADARUN PROG=ADAACK,DB=yyyyyy, IDTNAME=ADABAS5B
ADAACK ACCHECK FILE=ffff
/LOGOFF NOSPOOL

```

z/OS

| Data Set | DD Name | Storage | More Information |
|-------------------|----------|---------|---------------------------|
| Associator | DDASSORn | disk | |
| Data Storage | DDDATARn | disk | |
| ADAACK messages | DDDRUCK | printer | <i>Messages and Codes</i> |
| ADARUN messages | DDPRINT | printer | <i>Messages and Codes</i> |
| ADARUN parameters | DDCARD | reader | <i>Operations</i> |
| ADAACK parameters | DDKARTE | reader | |

ADAACK JCL Example (z/OS)

```

//ADAACK JOB
//*
//* ADAACK:
//* ADDRESS CONVERTER CHECK
//*
//ACK EXEC PGM=ADARUN
//STEPLIB DD DISP=SHR,DSN=ADABAS.ADAvrs.LOAD <=== ADABAS LOAD
//*
//DDASSOR1 DD DISP=SHR,DSN=EXAMPLE.DByyyyyy.ASSOR1 <=== ASSO
//DDDATAR1 DD DISP=SHR,DSN=EXAMPLE.DByyyyyy.DATAR1 <=== DATA
//DDDRUCK DD SYSOUT=X
//DDPRINT DD SYSOUT=X
//SYSUDUMP DD SYSOUT=X
//DDCARD DD *
ADARUN PROG=ADAACK,SVC=xxx,DEVICE=dddd,DBID=yyyyyy
/*
//DDKARTE DD *
ADAACK ACCHECK FILE=ffff
/*

```

Refer to ADAACK in the JOBS data set for this example.

z/VSE

| File | Symbolic Name | Storage | Logical Unit | More Information |
|-------------------|---------------|------------------------|-----------------------|---------------------------|
| Associator | ASSORn | disk | * | |
| Data Storage | DATARn | disk | * | |
| ADAACK messages | | printer | SYS009 | <i>Messages and Codes</i> |
| ADARUN messages | | printer | SYSLST | <i>Messages and Codes</i> |
| ADARUN parameters | | reader tape disk | SYSRDR SYS000 * | |
| ADAACK parameters | | reader | SYSIPT | |

* Any programmer logical unit may be used.

ADAACK JCS Example (z/VSE)

See Library and File Procedures for z/VSE Examples for descriptions of the z/VSE procedures (PROCs).

```
* $$ JOB JNM=ADAACK,CLASS=A,DISP=D
* $$ LST CLASS=A,DISP=D
*     ADDRESS CONVERTER CHECK
// JOB ADAACK
// EXEC PROC=ADAVvLIB
// EXEC PROC=ADAVvFIL
// EXEC ADARUN,SIZE=ADARUN
ADARUN PROG=ADAACK,SVC=xxx,DEVICE=dddd,DBID=yyyyy
/*
ADAACK ACCHECK FILE=27
/*
/&
* $$ EOJ
```

Refer to member ADAACK.X for this example.