

Adabas System Coordinator

Export and Import XML Tool

Version 8.6.1

September 2025

This document applies to Adabas System Coordinator Version 8.6.1 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 2025 Software GmbH, Darmstadt, Germany and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software GmbH product names are either trademarks or registered trademarks of Software GmbH and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software GmbH and/or its subsidiaries is located at <https://softwareag.com/licenses>.

Use of this software is subject to adherence to Software GmbH's licensing conditions and terms. These terms are part of the product documentation, located at <https://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software GmbH Products / Copyright and Trademark Notices of Software GmbH Products". These documents are part of the product documentation, located at <https://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software GmbH.

Document ID: COR-CONFIG-861-20250929

Table of Contents

1 About this Documentation	1
Document Conventions	2
Online Information and Support	2
Data Protection	3
2 Export and Import XML Tool	5
CORXML in Batch Mode	6
CORXML Control Input	7
EXPORT	7
IMPORT	10
Check	11
Sample XML Document Output File	11

1 About this Documentation

- Document Conventions 2
- Online Information and Support 2
- Data Protection 3

Document Conventions

Convention	Description
Bold	Identifies elements on a screen.
Monospace font	Identifies service names and locations in the format <code>folder.subfolder.service</code> , APIs, Java classes, methods, properties.
<i>Italic</i>	Identifies: Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies: Text you must type in. Messages displayed by the system. Program code.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the symbol.
[]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

Online Information and Support

Product Documentation

You can find the product documentation on our documentation website at <https://documentation.softwareag.com>.

Product Training

You can find helpful product training material on our Learning Portal at <https://learn.software-ag.com>.

Tech Community

You can collaborate with Software GmbH experts on our Tech Community website at <https://tech-community.softwareag.com>. From here you can, for example:

- Browse through our vast knowledge base.
- Ask questions and find answers in our discussion forums.
- Get the latest Software GmbH news and announcements.
- Explore our communities.
- Go to our public GitHub and Docker repositories at <https://github.com/softwareag> and <https://hub.docker.com/publishers/softwareag> and discover additional Software GmbH resources.

Product Support

Support for Software GmbH products is provided to licensed customers via our Empower Portal at <https://empower.softwareag.com>. Many services on this portal require that you have an account. If you do not yet have one, you can request it at <https://empower.softwareag.com/register>. Once you have an account, you can, for example:

- Download products, updates and fixes.
- Search the Knowledge Center for technical information and tips.
- Subscribe to early warnings and critical alerts.
- Open and update support incidents.
- Add product feature requests.

Data Protection

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.

2 Export and Import XML Tool

- CORXML in Batch Mode 6
- CORXML Control Input 7
- EXPORT 7
- IMPORT 10
- Check 11
- Sample XML Document Output File 11

This document describes the Export and Import XML tool.

The Adabas System Coordinator XML tool provides facilities to:

- Export configuration file settings
- Import configuration file settings
- Export configuration file historical information
- Export live statistics
- Verify XML documents according to CORXML syntax

CORXML runs in a standard batch Natural job.

CORXML in Batch Mode

In a batch Natural environment

- Use CORXML as the program name;
- Define Natural work file 1 (CMWKF01). The file must have fixed records of length 80 and the Natural parameters for work file 1 must specify `OPEN=OBJ,CLOSE=CMD`.
- Execute the utility from the required `SYSMPvars` library.

Example:

```
LOGON SYSMP821
CORXML
CHECK
STOP
FIN
```

Normal execution is indicated by condition code 0.

Errors are reported in CMPRINT and accompanied by execution termination code 4.

CORXML Control Input

The following functions are available specified through CMSYNIN control input:

EXPORT	Export selected data to an XML document in Natural's work file 1 (CMWKF01)
IMPORT	Update configuration file objects according to the XML document in work file 1
CHECK	Syntax check the XML document in work file 1

Each execution of CORXML performs a single function beginning with a CMSYNIN line stating "CORXML".

Control input for the function must be specified on a separate CMSYNIN line.

Each function requires a CMSYNIN line containing "STOP" to terminate it.

Optional comments are allowed and should be preceded by "/*".

You can execute CORXML more than once in a single CMSYNIN input file.

The following example shows multiple CORXML operations in one submission of control input (an XML syntax check followed by an import):

```
CORXML
CHECK
STOP
CORXML
IMPORT
REPLACE=YES TRANSACTION-RATE=1000
STOP
FIN
```

EXPORT

EXPORT writes output information as an XML document.

The CORXML control input for export has the format:

```
CODE OBJECT-TYPE SELECTION-CRITERIA /* optional comment
```

Each control input must start on a separate CMSYNIN line. If required, control input can be split across several lines by entering a “+” at the end of the line (before the comment, if there is one). For example here is a Vista partitioned file control input continued on a second CMSYNIN line also with comments:

```
PARTITIONED-FILE + /* Export Vista partitioned files  
DATABASE=1:100      /* for databases 1 to 100
```



Note: You must not split control input in the middle of an object type or selection criterion.

Selection criteria are of the format **KEYWORD=inclusive-from-value:inclusive-to-value** and are interpreted as follows:

- If no values are specified, all objects are selected for this criterion.

Example, select all databases:

```
DATABASE=
```

- If both values are specified, objects in that inclusive range are selected.

Example, select databases 1 through 100:

```
DATABASE=1:100
```

- If only an end value is specified, all objects up to and including the end value are selected.

Example, select all databases up to and including 200:

```
DATABASE=:200
```

- If only a starting value (with the through colon) is specified, objects greater than or equal the starting value are selected.

Example, select databases 100 through all the rest higher that are present:

```
DATABASE=100:
```

- If a single value is specified, with no colon, only objects that match that value are selected.

Example, select database 25:

```
DATABASE=25
```

- If a value you wish to select actually contains the colon character, enclose the whole value in single quotation marks.

Example, selects names ABC:DEF through ZZZZZZZZ:

```
NAME='ABC:DEF':ZZZZZZZ
```

Examples:

```
CORXML
EXPORT
AFP BUFFER-FILE NAME=ABC DATABASE=:100 /* All files for databases 1 to 100 in "ABC"
AVI PARTITIONED-FILE DATABASE= FILE=21:30 /* partitioned files 21 to 30 in all
databases
AVI TRANSLATION NAME=*ACTIVE + /* translations from the active
generation
PAGE=PROD0010:PROD0020 + /* for pages PROD0010
to PROD0020
DATABASE=1 /* in database
1
COR CLIENT TYPE=CICS NAME= /* all CICS runtime controls
STOP
```

Some selection criteria are mandatory; others are optional (see the table below). If an optional criterion is omitted, all objects are selected for that criterion.

Code	Object	Keyword	Description
ALL			Exports all configuration objects in the configuration file.
AFP	BUFFER	NAME	Export Adabas Fastpath buffer parameters for the buffers selected according to the NAME criteria. NAME is mandatory.
AFP	BUFFER-FILE	NAME DATABASE FILE	Export Adabas Fastpath file parameters for the selected buffers, databases and files. NAME is mandatory, DATABASE and FILE are optional.
AVI	PARTITIONED-FILE	DATABASE FILE	Export Adabas Vista partitioned file definitions for the selected databases and files. DATABASE is mandatory, FILE is optional.
AVI	TRANSLATION	NAME PAGE MODE DATABASE FILE	Export Adabas Vista translation rules according to the specified criteria. NAME is mandatory and specifies the generations for which rules are to be exported or it may specify *ACTIVE to export rules from the current active generation. PAGE, MODE, DATABASE and FILE are optional and are used to select which pages, source databases and files are to be exported. MODE may only specify a single value. Omit MODE to export rules for all categories.

Code	Object	Keyword	Description
COR	GROUP	NAME	Export System Coordinator group and daemon definitions for the selected groups. NAME is mandatory.
COR	CLIENT	NAME TYPE	Export runtime control base and override definitions for the selected runtime controls. NAME and TYPE are both mandatory. TYPE may only specify a single value. Specify TYPE= to select runtime controls of all types. These types are valid: <ul style="list-style-type: none"> ■ BATCH ■ COMPLETE ■ CICS ■ CICS-DTR ■ IMS ■ UTM ■ TSO ■ TIAM ■ MULTITCB ■ SINGLTCB ■ MISCDTR ■ SPATS ■ API-1 ■ API-2

IMPORT

Import reads an XML document and updates the configuration file accordingly.

The following control inputs may be specified in CMSYNIN, if required:

Keyword	Values	Description
REPLACE	YES NO	Whether or not to replace existing configuration file objects. The default is YES.
TRANSACTION-RATE	1 – 65535	Number of updates per transaction. The default is 1.

Example:

```
CORXML
IMPORT
REPLACE=NO, TRANSACTION-RATE=100
STOP
```

Check

Check reads an XML document and checks the syntax of the XML.

It has no control input.

Example:

```
CORXML
CHECK
STOP
```

Sample XML Document Output File

Here is an extract of an XML document produced by EXPORT, followed by an explanation of the contents.



Note: The display here is taken from a mainframe editor session. It shows sequence numbers for each line in the editor. The sequence numbers are not part of the XML document.

```
0001 <?xml version="1.0"?>
0002 <EXPORT-IMPORT>
0003   <PARTITIONED-FILE PRODUCT-CODE="AVI" FUNCTION="ADD" REPLACE="">
0004     <DATABASE>1</DATABASE>
0005     <FILE>999</FILE>
0006     <NAME>DB1</NAME>
0007     <FIELD>AA</FIELD>
0008     <FORMAT>A</FORMAT>
0009     <LENGTH>8</LENGTH>
...
0044   <PARTITION>
0045     <COLLATION-ORDER>1</COLLATION-ORDER>
0046     <DATABASE>12</DATABASE>
0047     <FILE>1</FILE>
0048     <NAME></NAME>
0049     <ACCESS>FULL</ACCESS>
0050     <TOP- ISN>16777215</TOP- ISN>
0051     <CRITICAL>Y</CRITICAL>
```

```

0052     <SHARED>N</SHARED>
0053     <HIGH-VALUE>
0054         <DATA>I</DATA>
0055     </HIGH-VALUE>
0056 </PARTITION>
...
0808 </PARTITIONED-FILE>
0809 </EXPORT-IMPORT>
    
```

Line	Description
0001 XML options	This is optional and only for documentation purposes. If specified, it must be at the start of the file.
0002 Root start	This must be the first record in the file, other than XML options.
0003 Configuration file object	This specifies the object type, owning product code, whether to add or delete this object and, for add, whether or not to replace this object if it already exists. FUNCTION defaults to ADD and REPLACE to null, which causes the import to use the REPLACE setting specified in the CMSYNIN input. Specify REPLACE="YES" or REPLACE="NO" to override the CMSYNIN setting.
0004 to 0009 Object data	Data values for this object. Each data item is expressed as a start tag, a value and an end tag (the value may be missing if the item has no value). See the relevant product's parameter documentation for a list of valid data items and values.
0044 Configuration file object component	A "child" of the current configuration file object. For example, partitioned files consist of one or more partition definitions.
0045 to 0055 Object component data and subordinate component	Data items for the component and any subordinate components.
0056 Component end tag	Each component definition must be terminated correctly.
0808 Object end tag	Each object definition must be terminated correctly.
0809 Root end	This must be the last record in the file.