

Natural under BS2000/OSD Batch Error Messages

This section lists error messages that may be issued by the Natural BS2000/OSD batch driver.

Unlike Natural system messages, the explanatory long texts to these error messages are only available in this document, not online.

NB20001 - NATURAL PARAMETER MODULE NOT FOUND

Expl.	Natural parameter module in front-end and reentrant part not found.
-------	---

NB20002 - ERROR IN ENABLE CMP FOR BUFFER POOL MANAGER

Expl.	An error has occurred when trying to enable the memory pool for the Natural buffer pool. The return code contains the SVC return code from register 15.
-------	---

NB20003 - ERROR IN REQUEST CMP FOR BUFFER POOL MANAGER

Expl.	An error has occurred when trying to request the memory pool for the Natural buffer pool. The return code contains the SVC return code from register 15.
-------	--

NB20004 - ERROR IN ENABLE CMP FOR REENTRANT PART

Expl.	An error has occurred when trying to enable the memory pool for the Natural load pool. The return code contains the SVC return code from register 15.
-------	---

NB20005 - ERROR IN ENABLE CMP FOR GLOBAL BUFFER POOL

Expl.	An error has occurred when trying to enable the memory pool for the global buffer pool. The return code contains the SVC return code from register 15.
-------	--

NB20006 - ERROR IN LOAD OF REENTRANT PART OF Natural

Expl.	An error has occurred when trying to load the Natural nucleus. The return code contains the SVC return code from register 15.
-------	---

NB20007 - ERROR IN ENABLE SERIALIZATION ITEM

Expl.	An error has occurred when trying to enable the serialization item for the Natural start-up. The return code contains the SVC return code from register 15.
-------	---

NB20008 - ERROR IN ENQUEUE ACCESS REQUEST

Expl.	An error has occurred when trying to enqueue the serialization queue for the Natural session initialization.
-------	--

NB20009 - ERROR IN DEQUEUE ACCESS REQUEST

Expl.	An error has occurred when trying to dequeue the serialization queue for the Natural session initialization.
-------	--

NB20010 - UNABLE TO ESTABLISH ADABAS COMMUNICATION

Expl.	The link module ADALNK or ADAUSER specified with the ADACOM generation parameter is neither linked to the Natural front-end nor could it be dynamically reloaded.
-------	---

NB20020 - SESSION TERMINATED DUE TO SEVERE ERROR(S)

Expl.	Session could not be initialized because resources were not available.
-------	--

NB20022 - ERROR DURING INITIALIZATION OF NAF CMP

Expl.	An error has occurred when trying to initialize the memory pool for Natural Advanced Facilities. No reports can be output via NATSPOOL.
-------	---

NB20023 - NAF PARAMETER MODULE NOT LINKED IN

Expl.	The Natural Advanced Facilities parameter module could not be located.
-------	--

NB20025 - MODULE NATINV NOT LINKED FIRST TO NUCLEUS

Expl.	The NATINV module was not included as the first one when linking the Natural nucleus.
-------	---

NB20026 - MODULE NATLAST NOT LINKED TO THE NUCLEUS

Expl.	The NATLAST module was not included in the link of the Natural nucleus. NATLAST must be included as the last module.
-------	--

NB20027 - LINK ERROR FOR ADDRESS: nnnnnnnn

Expl.	The module "nnnnnnnn" specified in LINK or LINK2 of the NATBS2BATCH generation parameters could not be located. The module was probably not linked to the Natural TIAM front-end.
-------	---

NB20030 - ERROR DURING READ OF DYNAMIC PARAMETER FILE

Expl.	A DVS error has occurred when trying to read the parameter file.
-------	--

NB20031 - ERROR DURING OPEN OF DYNAMIC PARAMETER FILE

Expl.	A DVS error has occurred when trying to open the parameter file.
-------	--

NB20032 - REENTRANT PART OF Natural BATCH DRIVER NOT FOUND

Expl.	Reentrant part of batch driver found neither in the reentrant nor in the front-end part.
-------	--

NB20040 - FRONT-END REENTRANT PART EXHIBIT A DIFFERENT ADDRESS MODE

Expl.	The value (either 24 or 31) specified for the PARMOD parameter for the Natural reentrant part does not correspond to the one specified for the front-end part.
-------	--

NB20041 - INVALID VERSION OF MODULE NATINV

Expl.	Invalid version of module NATINV which is linked at first in the front-end part.
-------	--

NB20042 - INVALID VERSION OF MACRO BS2STUB

Expl.	Invalid version of module BS2STUB which is linked at in the front-end part.
-------	---