

# WORK - Work-File Assignments

This Natural profile parameter allows you to define the maximum number of work files to be used during the session. Within a session, up to 32 logical work files (numbered 1 to 32) can be used.

WORK corresponds to the NETWORK macro in the parameter module NATPARM. To provide different work file definitions, WORK or NETWORK can be specified multiple times.

|                                     |     |   |
|-------------------------------------|-----|---|
| <b>Possible settings</b>            |     | See <i>Keyword Subparameters</i> below.   |
| <b>Default setting</b>              |     | See below. Depending on the access method and the environment, there may be different default settings. |
| <b>Dynamic specification</b>        | yes | The parameter WORK can only be specified dynamically. In NATPARM, the macro NETWORK must be used.       |
| <b>Specification within session</b> | no  |   |

The software components for accessing work files in different environments are called access methods. For the duration of a Natural session, each logical work file can be assigned to one access method only. The access method for a work file is determined by the keyword subparameter AM (see below).

In z/OS under TSO and in batch mode, work files need not be predefined in the JCL. Provided they are defined by subparameter AM=STD, they can be allocated dynamically during the session by a Natural program using the DEFINE WORK FILE statement or the application programming interface USR2021, which is located in library SYSEXT.

This document covers the following topics:

- WORK Parameter Syntax
- NETWORK Macro Syntax
- Keyword Subparameters for All Environments
- Keyword Subparameters for AM=STD in All Environments
- Keyword Subparameters for AM=STD in z/OS Environments
- Keyword Subparameters for AM=STD in z/VSE Environments
- Keyword Subparameters for AM=STD in BS2000/OSD Environments
- Keyword Subparameters for AM=CICS
- Keyword Subparameters for AM=COMP
- Keyword Subparameters for AM=SMARTS

See also *Print and Work File Handling with External Datasets in a Server Environment* in the *Operations* documentation).

## WORK Parameter Syntax

With the WORK parameter, you first specify one or more logical work file numbers, and then several keyword subparameters, which define the characteristics for these work files:

```
WORK=((work-file-numbers),keyword-subparameters,...)
```

### *work-file-numbers*

The file numbers must be specified first and enclosed in parentheses. The numbers can be from 1 to 31. They can be specified in any sequence. Multiple numbers must be separated from one another by commas or blanks. To specify a range of numbers, you can use a hyphen (-).

### *keyword-subparameters*

The various types of keyword subparameters are described below.

For work files with different characteristics, you specify different WORK parameters. If any previous definition (or default) for the same work file exists, only the values for the specified keyword subparameters are overwritten, all other values remain unchanged.

### **Examples:**

```
WORK=( ( 2 , 12 , 18 ) , AM=STD , DEST=' WORK** ' )
WORK=( ( 1 , 3 , 6-11 , 15 ) , AM=COMP , OPEN=INITOBJ , CLOSE=CMD )
```

## NETWORK Macro Syntax

With an NETWORK macro, you first specify one or more logical work file numbers, and then several keyword subparameters, which define the characteristics for these work files:

```
NETWORK (work-file-numbers),keyword-subparameters,...
```

### *work-file-numbers*

The file numbers must be specified first and enclosed in parentheses. The numbers can be from 1 to 31. They can be specified in any sequence. Multiple numbers must be separated from one another by commas. To specify a range of numbers, you can use a hyphen (-).

### *keyword-subparameters*

The various types of keyword subparameters are described below.

For work files with different characteristics, you specify different NETWORK macros. If any previous definition (or default) for the same work file exists, only the values for the specified keyword subparameters are overwritten, all other values remain unchanged.

**Examples:**

```
NTWORK ( 2, 12, 18 ), AM=STD, DEST='WORK**'
NTWORK ( 1, 3, 6-11, 15 ), AM=COMP, OPEN=INITOBJ, CLOSE=CMD
```

**Keyword Subparameters for All Environments**

The following keyword subparameters are available: AM | DEST | OPEN | CLOSE | LRECL | TRUNC | PAD | PADCHRO | PADCHRI

**AM - Type of Access Method**

AM=xxx specifies the type of access method to be used.

For an online session, all work files to be used have to be assigned to a specific access method.

For a batch session, any work files not assigned to a specific access method will be automatically detected and assigned by the standard batch access method (AM=STD), provided that they have been predefined in the JCL. See also *FAMSTD - Overwriting of Print and Work File Access Method Assignments*.

|        |  |
|--------|--|
| STD    | Standard sequential files (batch, TSO, TIAM, CMS OS simulation).                   |
| COMP   | Com-plete work files.  |
| SMARTS | SMARTS work files. Work file on a SMARTS Portable File System (PFS).               |
| CICS   | CICS transient data or temporary storage.  |
| CMS    | CMS Disk and SFS files.  |
| PC     | Entire Connection.   |
| USER   | Third-party vendor work-file interface.  |
| OFF    | Unassigned. No automatic assignments if FAMSTD=OFF is set.                         |
| 0      | Unassigned. Automatic assignments if FAMSTD=OFF is set. This is the default value. |

**Note:**

WORK=OFF is equivalent to: WORK=( ( 1-32 ) , AM=OFF ). It does not affect any of the other keyword subparameter specifications.

**DEST - External Dataset Name**

DEST=name specifies the external dataset name (1 - 8 characters).

This corresponds to the *operand1* of the DEFINE WORK FILE statement (and can be overwritten by a DEFINE WORK FILE specification).

The meaning of this keyword subparameter depends on the access method.

|         |   |
|---------|---|
| AM=STD  | <p>DEST is the logical dataset name (DDNAME, LINK name, DTF name).</p> <p>If the destination is to be for multiple files, two asterisks (**) have to be specified for the file number. These will be replaced by the corresponding logical file number for each work file. A DEST value including two asterisks must be enclosed in apostrophes when using it as a dynamic parameter.</p> <p>The default value is DEST= ' CMWKF** ' for IBM and DEST= ' W** ' for SIEMENS environments.</p> <p>Under z/VSE, only 7-character names are supported.</p> |
| AM=CICS | <p>There is no default value for work files under CICS. Here, the DEST subparameter is mandatory; that is, CICS work files defined without a valid DEST specification are ignored.</p> <p>The Natural CICS interface also supports a variable (see TERMVAR parameter in the NCIPARM generation macro; &amp;TID is the default) as part of the DEST value which, when being specified, is replaced by the actual CICS terminal ID; see also <i>Natural Print and Work Files under CICS</i> in the <i>TP Monitor Interfaces</i> documentation).</p>     |
| AM=CMS  | <p>For usage of DEST under CMS, refer to <i>Natural under VM/CMS</i> in the <i>Operations</i> documentation).</p>   |
| AM=COMP | <p>DEST defines the name of the Com-plete SD-file. The length is restricted to a maximum of 8 characters. If the file is defined with TYPE=TID, the DEST value is appended by the Com-plete stack level. The length is restricted to a maximum of 7 characters accordingly. SD-file names starting with '&amp;&amp;' are treated as temporary files which are deleted automatically after Natural termination.</p>  |

## OPEN - Time of File Opening

OPEN=xxx determines when the file is to be opened:

| <b>Value</b> | <b>The file is opened</b>   |
|--------------|---|
| INIT         | for output at session initialization.   |
| OBF          | according to the default OPEN value for the different environments (Batch, CICS, Com-plete, TSO).   |
| OBJ          | when the execution of the first object which accesses the file starts. This is the default value.   |
| INITOBF      | for output at session initialization. Any subsequent re-opening of the file sets the default OPEN value for the different environments (Batch, CICS, Com-plete, TSO). |
| OBJ1         | when the execution of the first object on level 1 which accesses the file starts. Otherwise, it is opened when it is first accessed.                                  |
| ACC          | when it is first accessed by a statement.   |
| INITOBJ      | for output at session initialization. Any subsequent re-opening of the file will be performed when the execution of the first object which accesses the file starts.  |
| INITOBJ1     | when the execution of the first object on level 1 which accesses the file starts. Otherwise, it is opened when it is first accessed.                                  |
| INITACC      | for output at session initialization. Any subsequent re-opening of the file will be performed when it is first accessed by a statement.                               |

## CLOSE - Time of File Closure

CLOSE=xxx determines when the file is to be closed:

| <b>Value</b> | <b>The file is closed</b>  |
|--------------|--|
| OBJ          | either when processing of the object in which it was first accessed is finished, or when command mode, NEXT mode or MAINMENU is reached.   |
| CMD          | when command mode, NEXT mode or MAINMENU is reached. This is the default value.  |
| FIN          | at session end. With CLOSE=FIN, a DEFINE WORK FILE statement causes an error if the work file was opened already. A CLOSE WORK FILE statement for the work file is ignored. When the end-of-file condition occurs during the READ WORK FILE statement, Natural closes the work file immediately.       |
| USER         | This value specifies that a work file is closed only if the file is open and one of the following conditions is true: <ul style="list-style-type: none"> <li>● a CLOSE WORK FILE statement is issued,</li> <li>● a DEFINE WORK FILE statement is issued,</li> <li>● at session termination.</li> </ul> |

## LRECL - Default and Maximum Record Length of Dataset

LRECL=*nnn* determines the record length (in bytes) of the dataset.

|                         |                |
|-------------------------|----------------|
| <b>Possible values:</b> | 0 or 5 - 32767 |
| <b>Default value:</b>   | 0              |

This subparameter is used particularly to check for truncation and padding. For more information on AM=STD, see the keyword subparameter LRECL in the section *WORK Keyword Subparameters for AM=STD in All Environments* below.

## TRUNC - Truncation of Output Records

TRUNC=*xxx* determines whether the output records are truncated or not:

|     |   |
|-----|---|
| ON  | Output records that are longer than the record length (LRECL) of the dataset will be truncated.                       |
| OFF | Error NAT1512 will be issued if an output record is longer than the dataset record length. This is the default value. |

## PAD - Padding of Output Records

PAD=*xxx* determines whether the output records are padded or not (applies only to datasets of fixed record length):

|     |  |
|-----|--|
| ON  | Output records that are shorter than the record length (LRECL) of the dataset will be padded with padding characters defined by keyword subparameter PADCHRO. This is the default value. |
| OFF | Error NAT1510 will be issued if an output record is shorter than the dataset record length.  |

## PADCHRO - Padding Character of Output Records

This subparameter defines the character which is used for padding of output records if PAD=ON is defined for the work file.

|                         |                        |   |
|-------------------------|------------------------|---|
| <b>Possible values:</b> | ' <i>x</i> '           | (one character <i>x</i> within single quotes) |
|                         | <i>x</i> ' <i>xx</i> ' | (one hex character <i>xx</i> )                |
| <b>Default value:</b>   | <i>x</i> '00'          |   |

## PADCHRI - Padding Character of Input Records

This subparameter defines the character which is used for padding of input records.

|                         |                        |   |
|-------------------------|------------------------|---|
| <b>Possible values:</b> | ' <i>x</i> '           | (one character <i>x</i> within single quotes) |
|                         | <i>x</i> ' <i>xx</i> ' | (one hex character <i>xx</i> )                |
| <b>Default value:</b>   | <i>x</i> '40'          | (blank)                                       |

## Keyword Subparameters for AM=STD in All Environments

The following keyword subparameters are available: RECFM | BLKSIZE | LRECL

### RECFM - Default Record Format of Dataset

RECFM=xxxx determines the default record format of the dataset.

The following formats are supported:

|   |                            |
|---|----------------------------|
| F | Fixed                      |
| V | Variable                   |
| U | Undefined                  |
| B | Blocked                    |
| S | Spanned                    |
| A | ASA                        |
| M | Machine control characters |

The following values and also combinations of values are possible:

|                        |  |
|------------------------|--|
| <b>Possible value:</b> | F, FA, FM, FB, FBA, FBM, V, VA, VM, VB, VBA, VBM, VBS, VBSA, VBSM, U, UA, UM |
| <b>Default value:</b>  | RECFM=VB (variable blocked).   |

The RECFM specification only applies if no record format is predefined in the JCL or (z/OS only) in the dataset DCB.

### BLKSIZE - Default Block Size of Dataset

BLKSIZE=nnnnn determines the default block size (in bytes) of the dataset.

|                         |                |
|-------------------------|----------------|
| <b>Possible values:</b> | 0 or 8 - 32767 |
| <b>Default value:</b>   | 4628           |

The BLKSIZE specification only applies if no block size is predefined in the JCL or (z/OS only) in the dataset DCB.

### LRECL - Default and Maximum Record Length of Dataset

LRECL=nnn determines the record length (in bytes) of the dataset.

|                         |                |
|-------------------------|----------------|
| <b>Possible values:</b> | 0 or 5 - 32767 |
| <b>Default value:</b>   | 0              |

This subparameter is used particularly to check for truncation and padding.

- For RECFM=V (B) the LRECL value includes a 4-byte record descriptor word.
- If LRECL=0 is defined, the following applies:
  - With RECFM=V (B), LRECL defaults to BLKSIZE-4.
  - With RECFM=U, LRECL defaults to BLKSIZE.
  - With RECFM=F (B), the maximum record length in the Natural program being executed is taken when the file is opened. If no record length from a program is available when the file is opened, for example with OPEN=INIT, this leads to an error.

The LRECL specification only applies if no record length is predefined in the JCL or (z/OS only) in the dataset DCB.

## Keyword Subparameters for AM=STD in z/OS Environments

The following keyword subparameters are available: REREAD | FREE | BUFNO | DISP | VMAX

### REREAD - Closing of Tape File Datasets

REREAD=xxx sets the REREAD option for the closing of the tape file:

|     |  |
|-----|--|
| ON  | The REREAD option is set for the CLOSE SVC. This causes the volume to be repositioned to reprocess the dataset. This is the default value. |
| OFF | The REREAD option is not set for the CLOSE SVC.  |

### FREE - Dataset De-allocation at File Closure

FREE=xxx determines whether the dataset is de-allocated when the file is closed:

|     |   |
|-----|---|
| ON  | The FREE option is set for the CLOSE SVC, which means that the dataset is de-allocated when it is closed (and not at step termination). |
| OFF | The FREE option is not set for the CLOSE SVC. This is the default value.  |

### BUFNO - Default Number of z/OS I/O Buffers of Dataset

BUFNO=nnn defines the default number of z/OS I/O buffers of the dataset.

|                        |  |
|------------------------|--|
| <b>Possible values</b> | 0 - 255  |
| <b>Default value</b>   | 0  |
|                        | In this case, z/OS allocates five I/O buffers per default. |



The number of I/O buffers can improve the performance of work file access dramatically. Note that the storage for I/O buffers is allocated below the 16 MB line.

The BUFNO specification applies only if the BUFNO parameter is not specified in the JCL for the dataset.

## DISP - Open Work File for Modification

DISP=xxx determines that the work file is opened for modification.

This corresponds to the JCL DD statement subparameter DISP=MOD.

|              |   |
|--------------|---|
| <b>MOD</b>   | New records are added at the end of the file.                         |
| <b>NOMOD</b> | The work file is rewritten from the start. This is the default value. |

## VMAX - Control LRECL for Variable Record Format

VMAX=xxx controls the LRECL setting for an output file with variable record format (RECFM=V).

|     |   |
|-----|---|
| ON  | Providing a nonzero BLKSIZE value exists for the file, VMAX=ON sets LRECL=BLKSIZE-4 for variable record format, regardless of the LRECL setting in the DCB or the LRECL subparameter. |
| NAT | LRECL is set to the length +4 of the largest record in the application program if this value is less than LRECL in the DCB for the dataset.   |
| OFF | LRECL from the DCB for the dataset is used. This is the default value.  |

## Keyword Subparameters for AM=STD in z/VSE Environments

The following keyword subparameters are available: SYSNR | LABEL | REWIND | BLOCKS | DISP

### SYSNR - Logical VSE SYS Number

SYSNR=nn determines the logical VSE SYS number.

|                         |  |
|-------------------------|--|
| <b>Possible values:</b> | 1 - 99   |
| <b>Default value:</b>   | By default, the SYS number is identical to the work file number. |

### LABEL - Tape Label Processing

LABEL=xxx d determines the tape label processing:

|      |  |
|------|--|
| ON   | The tape is in standard label format. This is the default value. |
| OFF  | The tape is unlabeled with front tape mark.                      |
| NOTM | The tape is unlabeled without front tape mark.                   |

## REWIND - Action at File Closure

REWIND=xxx determines the action to be taken when a tape file is closed:

|        |   |
|--------|---|
| ON     | The tape is rewound when the file is closed. This is the default value. |
| OFF    | The tape is not rewound when the file is closed.                        |
| UNLOAD | The tape is unloaded when the file is closed.                           |

## BLOCKS - Number of Storage Blocks

BLOCKS=nnnn specifies the number of file blocks or file tracks to be allocated for a dynamic NATVSE work file.

|                         |          |
|-------------------------|----------|
| <b>Possible values:</b> | 1 - 9999 |
| <b>Default value:</b>   | 20       |

See *NATVSE Dynamic Work File Allocation (DYNALLOC) Support* in the *Operations* documentation.

## DISP - Work File Disposition for VSAM/SAM

DISP=( xxx , xxx ) specifies the disposition of a dynamic NATVSE work file controlled by VSAM/SAM.

Possible value pairs are:

|                  |   |
|------------------|---|
| ( NEW , KEEP )   | File is to be reset at OPEN and to be kept at CLOSE. This is the default value. |
| ( NEW , DELETE ) | File is to be reset at OPEN and to be made inaccessible at CLOSE.               |
| ( OLD , DELETE ) | File is not to be reset at OPEN and to be made inaccessible at CLOSE.           |
| ( OLD , KEEP )   | File is not to be reset at OPEN and to be kept at CLOSE.                        |

See *NATVSE Dynamic Work File Allocation (DYNALLOC) Support* in the *Operations* documentation.

## Keyword Subparameters for AM=STD in BS2000/OSD Environments

The following keyword subparameter is available: DISP

### DISP - File Open Mode

DISP=xxx determines the open mode of the file:

|       |  |
|-------|--|
| EXT   | The open mode is set to EXTEND.  |
| NOEXT | The open mode is set to the default value OUTPUT. This is the default value. |

## Keyword Subparameters for AM=CICS

The following keyword subparameters are available: TYPE | DISP

### TYPE - Type of CICS Storage Medium

TYPE=xxxx specifies the type of CICS storage medium to be used:

|      |                              |
|------|------------------------------|
| MAIN | Temporary main storage.      |
| AUX  | Temporary auxiliary storage. |
| TD   | Transient data.              |

The default value used depends on the DEST keyword subparameter setting. If the DEST subparameter value matches a valid CICS transient data queue, the TYPE subparameter defaults to TD, otherwise MAIN will be taken as the default value.

### DISP - CICS Temporary Storage Queue Disposition

DISP=( xxx , xxx ) specifies the CICS temporary storage queue disposition.

Possible value pairs are:

|                  |  |
|------------------|--|
| ( NEW , KEEP )   | The storage queue is deleted when the file is opened. This is the default value. |
| ( NEW , DELETE ) | The storage queue is deleted when the file is opened and when it is closed.      |
| ( OLD , DELETE ) | The storage queue is deleted when the file is closed.                            |
| ( OLD , KEEP )   | The storage queue is not deleted.  |

#### Note:

The DISP specification does not apply to CICS extra-partition transient data queues.

## Keyword Subparameters for AM=COMP

The following keyword subparameters are available: TYPE | BLOCKS | BLKSIZE

### TYPE - Type of Storage Access

TYPE=xxx specifies the type of storage access to be used:

|     |   |
|-----|---|
| SHR | Shared access, that is, the work file is accessible by all users.     |
| TID | The work file is only available to the current Com-plete terminal ID. |
| DYN | The work file is only available to the current terminal stack level.  |

## BLOCKS - Number of Storage Blocks

BLOCKS=*nnnn* specifies the number of storage blocks to be allocated.

|                         |          |
|-------------------------|----------|
| <b>Possible values:</b> | 1 - 9999 |
| <b>Default value:</b>   | 20       |

## BLKSIZE - Size of Storage Blocks

BLKSIZE=*nnnn* determines the default block size (in bytes) of the dataset.

|                         |                 |
|-------------------------|-----------------|
| <b>Possible values:</b> | 0, or 8 - 32767 |
| <b>Default value:</b>   | 4628            |

## Keyword Subparameters for AM=SMARTS

The following keyword subparameters are available: DEST | TYPE | DISP

### DEST - Work File Name

DEST=*name* specifies the workfile name (1-8 characters).

Since the DEST clause is restricted to an 8 character maximum, it is useless to define a file with absolute PFS path specification.

The name specified in the DEST clause is relative to the workfile root directory. The work file root directory is specified with the environment variable NAT\_WORK\_ROOT.

To specify a file with absolute path definition, the DEFINE WORK FILE statement must be used.

### TYPE - Type of Storage Access

TYPE=*xxx* specifies the type of storage access to be used. Possible values are:

|     |   |
|-----|---|
| BIN | Each line is written to the work file without terminating end-of-line character. This is the default value. |
| TXT | Each line is written to the work file with a terminating end-of-line character (x'15').                     |

### DISP - File Open Mode

DISP=(*Disp1,Disp2,Disp3*) specifies the mode of the work file. Possible values are:

|                  |  |   |
|------------------|--|---|
| <i>Disp1=xxx</i> | Specifies whether an existing file should be deleted or new data should be appended to the file. |   |
|                  | NEW  | An existing file will be deleted if the file is opened for writing. This is the default value.  |
|                  | OLD or MOD   | New data written are appended at the end of the file.   |
| <i>Disp2=xxx</i> | Specifies whether a file should be kept or removed after access.                                 |   |
|                  | KEEP   | Permanent file that will be kept after close. This is the default value.  |
|                  | DELETE   | Temporary file that will be removed after close.  |
| <i>Disp3=xxx</i> | Specifies whether a user has exclusive access to the file or not.                                |   |
|                  | SHR  | Shared access, that is, the work file is accessible by all users. This is the default value.  |
|                  | OWN  | Exclusive access, the work file is accessible to the current Comp-lete user ID. Files with exclusive access are located in an additional directory which has the name of the current user ID. |