

Natural System Error Messages 1051-1100

NAT1070: Buffer pool initialization not linked.

Text	Buffer pool initialization is not linked.
Expl.	Driver entry CMBPGETS is missing. Natural environment is incomplete.
Actn.	Check your Natural environment.

NAT1071: Incompatible version for :1: buffer pool :2:.

Text	Incompatible version for ... buffer pool
Expl.	The version of the buffer pool already initialized is not supported by the current Natural version.
Actn.	Ensure that the buffer pool is allocated and initialized by a compatible Natural version.

NAT1072: Incompatible type for :1: buffer pool :2:.

Text	Incompatible type for ... buffer pool
Expl.	Natural has various buffer pools to share common virtual memory.: For example: - type Natural for Natural programs, - type SORT for common external sort space, - type EDIT for common external editor buffers and - type MONITOR for common monitor data. Because the buffer pool types have different storage layouts, it is not possible to use the buffer pool types interchangeably.
Actn.	Check NTBPI macro settings in your NATPARM file for local buffer pools or the parameter settings in you startup JCL for global buffer pools.

NAT1073: Initialization of :1: buffer pool failed. (:2:).

Text	Initialization of ... buffer pool failed. (...).
Expl.	The indicated buffer pool could not be initialized for one of the following reasons: - GETMAIN for the local buffer pool storage failed - specified buffer pool size (BPSIZE parameter) is too small - missing LINK for the EDTSTUB (installation error)
Actn.	Please check installation and correct the problem.

NAT1074: Global :1: buffer pool :2: not found.

Text	Global :1: buffer pool :2: not found.
Expl.	The global buffer pool :2: of type :1: could not be found. Either the global buffer pool is not yet allocated or the used name of the global buffer pool is wrong. If the buffer pool could not be found because the Natural subsystem does not exist, the name of the Natural subsystem is appended to the name of the global buffer pool, separated by a slash (/).
Actn.	Check the name of the global buffer pool (Natural profile parameter BPNNAME or NTBPI/BPI subparameter NAME) and/or the name of the Natural subsystem (Natural profile parameter SUBSID).

NAT1076: Error :1: while loading preload list :2: :3:.

Text	Error :1: while loading preload list :2: :3:.
Expl.	Natural error :1: has occurred when Natural tried to load the buffer pool preload list :2: at the start of the Natural session. If the Natural error occurs when the preload list is being read, the information :3: is blank. If the Natural error occurs when an object named in the preload list is being loaded, :3: contains library and program name of the object. The typical Natural error will be NAT0082, which means that either the preload list or one the named objects could not be found.
Actn.	Check the object names in your preload list.

NAT1077: Buffer pool propagation failed.

Text	Buffer pool propagation failed.
Expl.	The propagation of changes to the currently used Natural buffer pool is requested by the current setting of the Natural profile parameter BPPROP, but the propagation failed. Possible reasons: - The Natural Authorized Services Manager is not started for the Natural subsystem ID used by the current Natural session. - The Natural Authorized Services Manager is started without an XCF group name and BPPROP=PLEX or BPPROP=GPLEX is requested by the current Natural session.
Actn.	Contact the Natural administrator and/or check the setting of the Natural profile parameter BPPROP.

NAT1078: Allocation of local buffer pool cache failed.

Text	Allocation of local buffer pool cache failed.
Expl.	A buffer pool cache has been requested for a local Natural buffer pool, but the cache could not be allocated. The local Natural buffer pool is operational, but runs without a cache. This error message is preceded by other error messages which indicate the reason.
Actn.	Check the preceding error messages.

NAT1080: Cache creation failure :1: :2: :3: Reason= :4:.

Text	Cache creation failure :1: :2: :3: Reason= :4:.
Expl.	The cache create function has failed. The message shows the failing operating-system macro and the macro function (:1:). It also indicates the type of macro-request failure (:2:), that is, whether the macro failed due to macro failure (RC=) or ABEND (CC=). Parameter :3: is the ABEND code or macro-request return code respectively. Parameter :4: is the associated reason code.
Actn.	See the relevant operating-system manuals for the reason of the failure.

NAT1081: Cache deletion failure :1: :2: :3: Reason= :4:.

Text	Cache deletion failure :1: :2: :3: Reason= :4:.
Expl.	The cache delete function has failed. The message shows the failing operating-system macro and the macro function (:1:). It also indicates the type of macro request failure (:2:), that is, whether the macro failed due to macro failure (RC=) or ABEND (CC=). Parameter :3: is the ABEND code or macro-request return code respectively. Parameter :4: is the associated reason code.
Actn.	See the relevant operating-system macros for the reason of the failure.

NAT1100: Input value for a numeric field is not numeric.

Text	Input value for a numeric field is not numeric.
Expl.	The input value for a numeric field must contain a valid numeric value. The value may be preceded and/or followed by one or more blanks. Only one sign and decimal character are permitted. The value must not be longer than the field.
Actn.	Enter a valid numeric value.