

Natural System Error Messages 8201-8250

NAT8201: Invalid program switch to a conversational transaction.

Text	Invalid program switch to a conversational transaction.
Expl.	A direct switch to a conversational transaction from a non-conversational one is not allowed. Module(s): NIIDIRTX
Actn.	Check the transaction codes used. OR Use the appropriate switching module.

NAT8210: No free work PCBs.

Text	No free work PCBs.
Expl.	You cannot create a report because there is no free work PCB. Note: A work PCB is allocated to each open report. Module(s): NATAM06
Actn.	Increase the number of work PCBs in the transaction code table (WRKPCBS parameter in the NIMTRNTG macro). OR Decrease the number of parallel reports.

NAT8211: Destination :1: for printing the report is not defined.

Text	Destination :1: for printing the report is not defined.
Expl.	The destination specified in the NTPRINT macro or in the OUTPUT parameter of the DEFINE PRINTER statement is not a valid IMS/TM destination. Module(s): NATAM06
Actn.	Check your destination. OR Contact your system programmer.

NAT8212: Line length larger than block size.

Text	Line length larger than block size.
Expl.	The current print line is larger than the block size for the printer destination used. Module(s): NATAM06
Actn.	Increase the block size (BLKSIZE parameter in the NTPRINT macro). OR Decrease the line size for the report.

NAT8250: Not enough space for the command in the command buffer.

Text	Not enough space for the command in the command buffer.
Expl.	The length of the command passed is larger than the size of the command buffer. Note: The command buffer is used as I/O area when CMCMMND sends the command to IMS/TM. Module(s): CMCMMND
Actn.	Check the length of the command passed to CMCMMND OR Increase the size of the command buffer in the environment table (CMBSIZE parameter in the NIMPARM macro).