

# Support of Different Character Sets with *NATCONV.INI*

The settings in the configuration file *NATCONV.INI* apply to the A format. For the U format, the ICU library is used.

This chapter describes how Natural supports different character sets. It covers the following topics:

- Why is the Support of Different Character Sets Important?
  - How to Use Different Character Sets
- 

## Why is the Support of Different Character Sets Important?

The support of multiple languages with different character sets represents Natural's approach towards internationalization. It can help you when using:

- upper-/lower-case translation of language-specific characters;
- language-specific characters in Natural identifiers, object names and library names;
- language-specific characters in an operand compared with a mask definition (see *MASK Option* in the *Programming Guide*).

## How to Use Different Character Sets

All check, translation and classification tables used by Natural to support language-specific characters reside in the configuration file *NATCONV.INI*. By default, this file is located in Natural's *etc* directory.

You can modify *NATCONV.INI* to support local or application-specific character sets.

In a standard application, *NATCONV.INI* need not and should not be modified, because this could lead to serious inconsistencies, in particular if Natural objects and database data are already present.

Any modifications of *NATCONV.INI* should be well considered and carefully performed, otherwise problems might occur that are difficult to locate.

*NATCONV.INI* is subdivided in sections and subsections. The following sections are defined:

| Section                  | Description   |
|--------------------------|---|
| CHARACTERSET-DEFINITION  | <p>This section defines the name of the internal character set. The default is "ISO8859_1".</p> <p>If you choose a different character set, subsections for this character set must be contained in the sections described below.</p>   |
| CASE-TRANSLATION         | <p>This section contains the tables required for the conversion from upper-case to lower-case which is performed when one of the following is specified:</p> <ul style="list-style-type: none"> <li>● the terminal command %U,</li> <li>● the field attribute AD=T,</li> <li>● the statement EXAMINE TRANSLATE.</li> </ul> <p>This conversion is done within the internal character set. If the internal character set is, for example, "ISO8859_5", the following two subsections must be contained in this section:</p> <ul style="list-style-type: none"> <li>● [ ISO8859_5-&gt;UPPER ]</li> <li>● [ ISO8859_5-&gt;LOWER ]</li> </ul>  |
| IDENTIFIER-VALIDATION    | <p>This section contains the tables required for the validation of identifiers (that is, user-defined variables in source programs), object names and library names. It contains a subsection for each defined internal character set.</p> <p>The special characters "#" (for non-database variables), "+" (for application-independent variables), "@" (for SQL and Adabas null or length indicators) and "&amp;" (for dynamic source generation) can be redefined in this section. In addition, the set of valid first and subsequent characters for identifiers, object names and library names can be modified.</p> <p><b>Note:</b><br/>When extending the set of valid characters for object names with values greater than "x7f" (decimal 127), the sorting sequence of the objects (for example, during a LIST * command) may not be in the numerical order.</p> |
| CHARACTER-CLASSIFICATION | <p>This section contains the tables required for the classification of characters, which, for example, are used when evaluating the MASK option. It contains a subsection for each defined internal character set.</p>  |

The section CHARACTERSET-DEFINITION and each subsection contain lines which describe how characters are to be converted and which characters are related with which attributes. These lines are represented as follows:

```

line      ::= key = value
key       ::= name_key | range_key
name_key  ::= keyword{ CHARS }
keyword   ::= INTERNAL-CHARACTERSET | NON-DB-VARI | DYNAMIC-SOURCE |
            GLOBAL-VARI | FIRST-CHAR | SUBSEQUENT-CHAR |
            LIB-FIRST-CHAR | LIB-SUBSEQUENT-CHAR | ALTERNATE-CARET
            ISASCII | ISALPHA | ISALNUM | ISDIGIT | ISXDIGIT |
            ISLOWER | ISUPPER | ISCNTRL | ISPRINT | ISPUNCT |
            ISGRAPH | ISSPACE
range_key ::= hexnum | hexnum-hexnum
value     ::= val { , val }
val       ::= hexnum | hexnum-hexnum
hexnum    ::= xhexdighexdigit | xhexdighexdigit

```

**Notes:**

1. If the `range_key` variable is specified on the left-hand side, the number of values specified on the right-hand side must correspond to the number of values specified in the key range, unless only one value is specified on the right-hand side, which is then assigned to each element of the key range.
2. When the `name_key` variable is specified on the left-hand side and the corresponding list of character codes does not fit in one line, it can be continued on the next line by specifying "name\_key =" again. You must not start the lines with leading blanks or tabulators.

**Examples of Valid Lines**

|  |   |
|--|---|
| <code>x00-x1f = x00</code>   | All characters between "x00" and "x1f" are converted to "x00".  |
| <code>x00-x7f = x00-x7f</code>   | All characters between "x00" and "x7f" are not converted.   |
| <code>x00-x08 = x00,x01-x07,x00</code>   | The characters "x00" and "x08" are converted to "x00" and characters between "x01" and "x07" are not converted. |
| <code>ISALPHA =<br/>x41-x5a,x61-x7a,xc0-xd6,xd8<br/>ISALPHA = xd9-xf6,xf8-xff</code> | The attribute ISALPHA is assigned to all characters specified in these two lines.                               |

**Examples of Invalid Lines**

|                                |  |
|--------------------------------|--|
| <code>x41 = 'A'</code>         | All characters must be specified in hexadecimal format.  |
| <code>0x00-0x1f = 0x00</code>  | Hexadecimal values have to be specified in either of the following ways:<br><br><i>xdigitdigit</i><br><i>Xdigitdigit</i> |
| <code>x00-x0f = x00,x01</code> | The number of specified values does not correspond to the number of elements in the key range.                           |