

General Information for Starting the Daemons

This chapter applies to the Natural Development Server daemon and the Natural Web I/O Interface daemon. It covers the following topics:

- IMPERSONATE Privilege
- SYSUAF Limits
- Command Procedure `STARTUP_DAEMONS.COM`

Note:

For information on the Natural Web I/O Interface daemon, see *Installing and Configuring the Natural Web I/O Interface Server* in the *Natural Web I/O Interface* documentation.

IMPERSONATE Privilege

The account from which a daemon is started requires the `IMPERSONATE` privilege.

SYSUAF Limits

The following `SYSUAF` limits need to be adapted for the account from which the daemon is started.

Name	Default Value	Description
<code>FILLM</code>	128	The open file limit is the maximum number of files that can be open at one time, including active network logical links.
<code>BIOLM</code>	150	The buffered I/O count limit is the maximum number of buffered I/O operations.
<code>DIOLM</code>	150	The direct I/O count limit is the maximum number of direct I/O operations (usually disk) that can be outstanding at one time.
<code>BYTLM</code>	128000	The buffered I/O byte limit is the maximum number of bytes of non-paged system dynamic memory that a user's job can consume at one time.

The sizes of `FILLM`, `BIOLM`, `BYTLM` and `PRCLM` depend on the number of started sessions. Make sure to increase these values so that they meet your requirements.

Command Procedure `STARTUP_DAEMONS.COM`

After the installation of Natural, the command procedure `STARTUP_DAEMONS.COM` can be found in the directory `SAG$ROOT:[NATURAL]`.

This command procedure ensures that a daemon is started in the correct account during the startup of a machine. To use the command procedure, you have to adapt the following lines to your requirements:

```

$ l_user      = "SAG"
$ l_ndv_para = ""START""
$ l_nwo_para = ""2800""

```

Variable	Description
l_user	The name of the account under which the daemons are to run.
l_ndv_para	<p>You can specify all start parameters that are valid for the Natural Development Server daemon. These parameters are described in the <i>Natural Development Server for OpenVMS</i> documentation.</p> <p>Example:</p> <pre>\$ l_ndv_para = ""-port=1234","parm=test""</pre> <p>Instead of the above parameters, you can also specify START. In this case, the values defined in <i>START_NATDVSrv.COM</i> are used.</p>
l_nwo_para	The port number for the Natural Web I/O Interface daemon.

When you have adapted all required lines, you have to copy the command procedure *STARTUP_DAEMONS.COM* to *SYSS\$STARTUP*.

Using the following command, you can add the command procedure *STARTUP_DAEMONS.COM* to the startup database:

```
$mcr sysman startup file /mode=direct /phase=end STARTUP_DAEMONS.COM /parameter=P1:<parameter-value>
```

<parameter-value> defines the daemon(s) to be started. It can be one of the following:

Parameter Value	Description
NDV	Starts only the daemon for the Natural Development Server.
NWO	Starts only the daemon for the Natural Web I/O Interface server.
ALL	Starts all of the above daemons.