

Natural System Error Messages 1051-1100

NAT1073: Initialization of :1: buffer pool failed. (:2:).

Text	Initialization of ... buffer pool failed. (...).
Expl.	The indicated buffer pool could not be initialized for one of the following reasons: - GETMAIN for the local buffer pool storage failed - specified buffer pool size (BPSIZE parameter) is too small - missing LINK for the EDTSTUB (installation error)
Actn.	Please check installation and correct the problem.

NAT1074: Global :1: buffer pool :2: not found.

Text	Global :1: buffer pool :2: not found.
Expl.	The global buffer pool :2: of type :1: could not be found. Either the global buffer pool is not yet allocated or the used name of the global buffer pool is wrong. If the buffer pool could not be found because the Natural subsystem does not exist, the name of the Natural subsystem is appended to the name of the global buffer pool, separated by a slash (/).
Actn.	Check the name of the global buffer pool (Natural profile parameter BPNAME or NTBPI/BPI subparameter NAME) and/or the name of the Natural subsystem (Natural profile parameter SUBSID).

NAT1075: Global :1: buffer pool :2: allocated in system key.

Text	Global ... buffer pool ... allocated in system key.
Expl.	The indicated global buffer pool has been allocated in system key, but the authorized services manager (ASM) has not been started or is not of the required minimum version. To process a buffer pool that has been allocated in system key, the ASM is required.
Actn.	Start an authorized services manager of the required minimum version for the Natural subsystem in use.

NAT1076: Error :1: while loading preload list :2: :3:.

Text	Error :1: while loading preload list :2: :3:.
Expl.	<p>Natural error :1: has occurred when Natural tried to load the buffer pool preload list :2: at the start of the Natural session.</p> <p>If the Natural error occurs when the preload list is being read, the information :3: is blank.</p> <p>If the Natural error occurs when an object named in the preload list is being loaded, :3: contains library and program name of the object.</p> <p>The typical Natural error will be NAT0082, which means that either the preload list or one the named objects could not be found.</p>
Actn.	Check the object names in your preload list.

NAT1080: Cache creation failure :1: :2: :3: Reason= :4:.

Text	Cache creation failure :1: :2: :3: Reason= :4:.
Expl.	<p>The cache create function has failed.</p> <p>The message shows the failing operating-system macro and the macro function (:1:).</p> <p>It also indicates the type of macro-request failure (:2:), that is, whether the macro failed due to macro failure (RC=) or ABEND (CC=).</p> <p>Parameter :3: is the ABEND code or macro-request return code respectively.</p> <p>Parameter :4: is the associated reason code.</p>
Actn.	See the relevant operating-system manuals for the reason of the failure.

NAT1081: Cache deletion failure :1: :2: :3: Reason= :4:.

Text	Cache deletion failure :1: :2: :3: Reason= :4:.
Expl.	<p>The cache delete function has failed.</p> <p>The message shows the failing operating-system macro and the macro function (:1:).</p> <p>It also indicates the type of macro request failure (:2:), that is, whether the macro failed due to macro failure (RC=) or ABEND (CC=).</p> <p>Parameter :3: is the ABEND code or macro-request return code respectively.</p> <p>Parameter :4: is the associated reason code.</p>
Actn.	See the relevant operating-system macros for the reason of the failure.

NAT1100: Input value for a numeric field is not numeric.

Text	Input value for a numeric field is not numeric.
Expl.	<p>The input value for a numeric field must contain a valid numeric value. The value may be preceded and/or followed by one or more blanks.</p> <p>Only one sign and decimal character are permitted.</p> <p>The value must not be longer than the field.</p>
Actn.	Enter a valid numeric value.