9 software

Natural for OpenVMS

Messages and Codes

Version 6.3.8 for OpenVMS

February 2010

Natural

This document applies to Natural Version 6.3.8 for OpenVMS.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 1984-2010 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, United States of America, and/or their licensors.

The name Software AG, webMethods and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at http://documentation.softwareag.com/legal/ and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices and license terms, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". This document is part of the product documentation, located at http://documentation.softwareag.com/legal/ and/or in the root installation directory of the licensed product(s).

Table of Contents

| 1 Messages and Codes | 1 |
|--|-----|
| 2 Natural System Error Messages 0001-0050 | 9 |
| 3 Natural System Error Messages 0051-0100 | 23 |
| 4 Natural System Error Messages 0101-0150 | 37 |
| 5 Natural System Error Messages 0151-0200 | 49 |
| 6 Natural System Error Messages 0201-0250 | |
| 7 Natural System Error Messages 0251-0300 | 71 |
| 8 Natural System Error Messages 0301-0350 | 85 |
| 9 Natural System Error Messages 0351-0400 | 99 |
| 10 Natural System Error Messages 0401-0450 | 111 |
| 11 Natural System Error Messages 0451-0500 | |
| 12 Natural System Error Messages 0551-0600 | |
| 13 Natural System Error Messages 0601-0650 | 135 |
| 14 Natural System Error Messages 0651-0700 | |
| 15 Natural System Error Messages 0701-0750 | |
| 16 Natural System Error Messages 0751-0800 | |
| 17 Natural System Error Messages 0801-0850 | |
| 18 Natural System Error Messages 0851-0900 | |
| 19 Natural System Error Messages 0901-0950 | |
| 20 Natural System Error Messages 0951-1000 | |
| 21 Natural System Error Messages 1001-1050 | |
| 22 Natural System Error Messages 1051-1100 | |
| 23 Natural System Error Messages 1101-1150 | |
| 24 Natural System Error Messages 1151-1200 | |
| 25 Natural System Error Messages 1201-1250 | |
| 26 Natural System Error Messages 1251-1300 | |
| 27 Natural System Error Messages 1301-1350 | |
| 28 Natural System Error Messages 1351-1400 | |
| 29 Natural System Error Messages 1451-1500 | |
| 30 Natural System Error Messages 1501-1550 | |
| 31 Natural System Error Messages 1551-1600 | |
| 32 Natural System Error Messages 1601-1650 | |
| 33 Natural System Error Messages 1651-1700 | |
| 34 Natural System Error Messages 1701-1750 | |
| 35 Natural System Error Messages 1751-1800 | |
| 36 Natural System Error Messages 1801-1850 | |
| 37 Natural System Error Messages 1851-1900 | |
| 38 Natural System Error Messages 1901-1950 | |
| 39 Natural System Error Messages 1951-2000 | |
| 40 Natural System Error Messages 2001-2050 | |
| 41 Natural System Error Messages 2051-2100 | |
| 42 Natural System Error Messages 2101-2150 | |
| 43 Natural System Error Messages 2151-2200 | 345 |

| 44 Natural System Error Massa and 2201 2250 | 252 |
|---|-----|
| 44 Natural System Error Messages 2201-2250 | |
| 45 Natural System Error Messages 2251-2300 | |
| 46 Natural System Error Messages 2301-2350 | |
| 47 Natural System Error Messages 2351-2400 | |
| 48 Natural System Error Messages 2401-2450 | |
| 49 Natural System Error Messages 2451-2500 | |
| 50 Natural System Error Messages 2501-2550 | |
| 51 Natural System Error Messages 2551-2600 | |
| 52 Natural System Error Messages 2601-2650 | |
| 53 Natural System Error Messages 2651-2700 | |
| 54 Natural System Error Messages 2701-2750 | |
| 55 Natural System Error Messages 2751-2800 | |
| 56 Natural System Error Messages 2801-2850 | |
| 57 Natural System Error Messages 2851-2900 | |
| 58 Natural System Error Messages 2901-2950 | |
| 59 Natural System Error Messages 2951-3000 | |
| 60 Natural System Error Messages 3001-3050 | |
| 61 Natural System Error Messages 3051-3100 | |
| 62 Natural System Error Messages 3101-3150 | |
| 63 Natural System Error Messages 3151-3200 | |
| 64 Natural System Error Messages 3201-3250 | |
| 65 Natural System Error Messages 3251-3300 | |
| 66 Natural System Error Messages 3301-3350 | |
| 67 Natural System Error Messages 3351-3400 | |
| 68 Natural System Error Messages 3401-3450 | |
| 69 Natural System Error Messages 3451-3500 | |
| 70 Natural System Error Messages 3501-3550 | |
| 71 Natural System Error Messages 3551-3600 | |
| 72 Natural System Error Messages 3601-3650 | |
| 73 Natural System Error Messages 3701-3750 | |
| 74 Natural System Error Messages 3951-4000 | |
| 75 Natural System Error Messages 4001-4050 | |
| 76 Natural System Error Messages 4051-4100 | |
| 77 Natural System Error Messages 4101-4150 | |
| 78 Natural System Error Messages 4151-4200 | |
| 79 Natural System Error Messages 4201-4250 | |
| 80 Natural System Error Messages 4251-4300 | |
| 81 Natural System Error Messages 4301-4350 | |
| 82 Natural System Error Messages 4351-4400 | |
| 83 Natural System Error Messages 4401-4450 | |
| 84 Natural System Error Messages 4451-4500 | |
| 85 Natural System Error Messages 4501-4550 | |
| 86 Natural System Error Messages 4551-4600 | |
| 87 Natural System Error Messages 4601-4650 | |
| 88 Natural System Error Messages 4651-4700 | 677 |
| | |

| 89 Natural System Error Messages 4701-4750 689 90 Natural System Error Messages 4701-4750 689 90 Natural System Error Messages 4801-4850 701 91 Natural System Error Messages 4801-4950 731 93 Natural System Error Messages 4901-4950 731 94 Natural System Error Messages 5201-5250 741 95 Natural System Error Messages 521-5300 745 97 Natural System Error Messages 521-5500 763 198 Natural System Error Messages 5401-5450 755 99 Natural System Error Messages 551-5500 763 100 Natural System Error Messages 551-5500 767 101 Natural System Error Messages 561-5700 787 102 Natural System Error Messages 571-5750 797 103 Natural System Error Messages 571-5700 787 104 Natural System Error Messages 581-5800 805 105 Natural System Error Messages 581-5800 813 107 Natural System Error Messages 581-5800 813 107 Natural System Error Messages 581-5800 813 107 Natural System Error Messages 581-5800 813 108 Natural System Error Messages 601-6100 843 110 Natural System Error | 90 Natural System Error Messages 4751-4800 701 91 Natural System Error Messages 4801-4950 705 92 Natural System Error Messages 4901-4950 731 93 Natural System Error Messages 4951-5000 737 95 Natural System Error Messages 5201-5250 741 96 Natural System Error Messages 521-5300 745 97 Natural System Error Messages 521-5400 745 97 Natural System Error Messages 5401-5450 755 99 Natural System Error Messages 5401-5500 767 100 Natural System Error Messages 551-5600 773 102 Natural System Error Messages 561-550 767 101 Natural System Error Messages 561-5700 773 102 Natural System Error Messages 561-5700 779 103 Natural System Error Messages 571-5750 797 104 Natural System Error Messages 571-570 797 105 Natural System Error Messages 581-5900 819 106 Natural System Error Messages 591-590 819 107 Natural System Error Messages 591-590 827 109 Natural System Error Messages 591-590 827 109 Natural System Error Messages 601-610 843 110 Natural System Error Messages 601-6100 843 112 Nat | 00 Nieka | rel Crestore France Massa and 4701 4750 | (00 |
|---|---|----------|---|-----|
| 91 Natural System Error Messages 4801-4850 705 92 Natural System Error Messages 4851-4900 719 93 Natural System Error Messages 4951-5000 731 94 Natural System Error Messages 5201-5250 741 96 Natural System Error Messages 5201-5200 745 97 Natural System Error Messages 531-5400 747 98 Natural System Error Messages 541-5500 763 100 Natural System Error Messages 5501-5500 763 101 Natural System Error Messages 551-5500 763 102 Natural System Error Messages 551-5500 773 103 Natural System Error Messages 551-5500 773 104 Natural System Error Messages 551-5500 777 103 Natural System Error Messages 5701-5750 787 104 Natural System Error Messages 571-5780 805 105 Natural System Error Messages 581-5800 805 106 Natural System Error Messages 591-5950 827 109 Natural System Error Messages 601-6050 837 110 Natural System Error Messages 601-6050 837 111 Natural System Error Messages 611-6100 843 112 Natural System Error Messages 621-6200 853 113 Natural System Error Messages 631-6400 863 <td< td=""><td>91 Natural System Error Messages 4801-4850 705 92 Natural System Error Messages 4851-4900 719 93 Natural System Error Messages 4901-4950 731 94 Natural System Error Messages 4901-4950 731 95 Natural System Error Messages 5201-5250 741 96 Natural System Error Messages 521-5300 745 97 Natural System Error Messages 531-5400 747 98 Natural System Error Messages 551-5500 767 101 Natural System Error Messages 551-5500 767 101 Natural System Error Messages 551-5500 767 101 Natural System Error Messages 551-5600 773 102 Natural System Error Messages 551-5500 767 101 Natural System Error Messages 551-5500 767 102 Natural System Error Messages 551-5500 779 103 Natural System Error Messages 551-5600 779 104 Natural System Error Messages 571-5800 805 106 Natural System Error Messages 581-5900 819 107 Natural System Error Messages 591-5950 827 109 Natural System Error Messages 601-6050 831 110 Natural System Error Messages 6201-6250 837 111 Natural System Error Messages 6201-6250 857</td><td></td><td></td><td></td></td<> | 91 Natural System Error Messages 4801-4850 705 92 Natural System Error Messages 4851-4900 719 93 Natural System Error Messages 4901-4950 731 94 Natural System Error Messages 4901-4950 731 95 Natural System Error Messages 5201-5250 741 96 Natural System Error Messages 521-5300 745 97 Natural System Error Messages 531-5400 747 98 Natural System Error Messages 551-5500 767 101 Natural System Error Messages 551-5500 767 101 Natural System Error Messages 551-5500 767 101 Natural System Error Messages 551-5600 773 102 Natural System Error Messages 551-5500 767 101 Natural System Error Messages 551-5500 767 102 Natural System Error Messages 551-5500 779 103 Natural System Error Messages 551-5600 779 104 Natural System Error Messages 571-5800 805 106 Natural System Error Messages 581-5900 819 107 Natural System Error Messages 591-5950 827 109 Natural System Error Messages 601-6050 831 110 Natural System Error Messages 6201-6250 837 111 Natural System Error Messages 6201-6250 857 | | | |
| 92 Natural System Error Messages 4851-4900 719 93 Natural System Error Messages 4901-4950 731 94 Natural System Error Messages 5201-5250 741 96 Natural System Error Messages 5251-5300 745 97 Natural System Error Messages 5251-5400 747 98 Natural System Error Messages 531-5400 747 99 Natural System Error Messages 541-550 763 100 Natural System Error Messages 551-5500 767 101 Natural System Error Messages 561-5500 773 102 Natural System Error Messages 561-5600 773 103 Natural System Error Messages 561-5700 787 104 Natural System Error Messages 571-5800 805 105 Natural System Error Messages 581-5800 803 106 Natural System Error Messages 581-5800 813 107 Natural System Error Messages 581-5900 819 108 Natural System Error Messages 591-5950 827 109 Natural System Error Messages 601-6050 831 110 Natural System Error Messages 601-6050 837 111 Natural System Error Messages 601-6050 837 113 Natural System Error Messages 6201-6250 857 114 Natural System Error Messages 631-6400 843 1 | 92 Natural System Error Messages 4851-4900 719 93 Natural System Error Messages 4901-4950 731 94 Natural System Error Messages 4901-5000 737 95 Natural System Error Messages 521-520 741 96 Natural System Error Messages 5251-5300 745 97 Natural System Error Messages 531-5400 745 99 Natural System Error Messages 5401-5450 755 99 Natural System Error Messages 5401-5500 763 100 Natural System Error Messages 551-5500 767 101 Natural System Error Messages 5601-5650 779 103 Natural System Error Messages 561-5700 787 104 Natural System Error Messages 571-5800 805 105 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 581-5900 819 108 Natural System Error Messages 581-5900 819 108 Natural System Error Messages 5951-6000 831 107 Natural System Error Messages 601-6050 837 110 Natural System Error Messages 601-6100 843 112 Natural System Error Messages 601-6100 843 113 Natural System Error Messages 601-620 857 114 Natural System Error Messages 601-6450 895 | | | |
| 93 Natural System Error Messages 4901-4950 731 94 Natural System Error Messages 4951-5000 737 95 Natural System Error Messages 5201-5250 741 96 Natural System Error Messages 5351-5400 745 97 Natural System Error Messages 5401-5450 755 99 Natural System Error Messages 5401-5500 763 100 Natural System Error Messages 551-5500 767 101 Natural System Error Messages 551-5500 773 102 Natural System Error Messages 551-5500 777 103 Natural System Error Messages 551-5500 777 103 Natural System Error Messages 551-5500 777 103 Natural System Error Messages 5701-5750 797 104 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 581-5800 805 106 Natural System Error Messages 5901-5950 813 107 Natural System Error Messages 591-5900 819 108 Natural System Error Messages 601-6100 831 109 Natural System Error Messages 601-6100 843 110 Natural System Error Messages 621-6300 857 113 Natural System Error Messages 621-6300 869 114 Natural System Error Messages 6401-6450 873 | 93 Natural System Error Messages 4901-4950 731 94 Natural System Error Messages 4951-5000 737 95 Natural System Error Messages 5201-5250 741 96 Natural System Error Messages 521-5300 745 97 Natural System Error Messages 5351-5400 747 98 Natural System Error Messages 5401-5450 753 100 Natural System Error Messages 541-5500 763 101 Natural System Error Messages 551-5500 767 101 Natural System Error Messages 561-5550 767 101 Natural System Error Messages 561-5500 779 103 Natural System Error Messages 561-5700 787 104 Natural System Error Messages 571-5800 805 106 Natural System Error Messages 581-5900 813 107 Natural System Error Messages 581-5900 813 108 Natural System Error Messages 591-6950 827 109 Natural System Error Messages 601-610 833 110 Natural System Error Messages 601-610 843 111 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 621-6200 853 114 Natural System Error Messages 621-6300 867 115 Natural System Error Messages 631-6400 863 1 | | | |
| 94 Natural System Error Messages 4951-5000 737 95 Natural System Error Messages 5211-5250 741 96 Natural System Error Messages 5251-5300 745 97 Natural System Error Messages 541-5400 747 98 Natural System Error Messages 541-5500 763 100 Natural System Error Messages 5501-5500 763 101 Natural System Error Messages 5501-5500 773 102 Natural System Error Messages 5601-5650 779 103 Natural System Error Messages 5601-5650 779 103 Natural System Error Messages 5701-5700 787 104 Natural System Error Messages 5701-5700 787 105 Natural System Error Messages 5701-5800 805 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5951-6000 811 108 Natural System Error Messages 5951-6000 837 110 Natural System Error Messages 6151-6100 843 110 Natural System Error Messages 6151-6200 853 111 Natural System Error Messages 6151-6200 853 113 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6201-650 857 115 Natural System Error Messages 6201-6250 857 < | 94 Natural System Error Messages 4951-5000 737 95 Natural System Error Messages 5251-5300 741 96 Natural System Error Messages 5251-5300 745 97 Natural System Error Messages 541-5400 747 98 Natural System Error Messages 541-550 763 100 Natural System Error Messages 551-5600 763 101 Natural System Error Messages 551-5600 773 102 Natural System Error Messages 561-5600 779 103 Natural System Error Messages 561-5600 779 104 Natural System Error Messages 571-5800 805 106 Natural System Error Messages 571-5800 805 106 Natural System Error Messages 581-5900 819 108 Natural System Error Messages 581-5900 819 108 Natural System Error Messages 5951-6000 831 100 Natural System Error Messages 5951-6000 831 100 Natural System Error Messages 601-6050 837 111 Natural System Error Messages 611-6100 843 112 Natural System Error Messages 621-6200 845 113 Natural System Error Messages 621-6300 869 114 Natural System Error Messages 621-6300 869 115 Natural System Error Messages 621-6300 863 | | | |
| 95 Natural System Error Messages 5201-5250 741 96 Natural System Error Messages 5251-5300 745 97 Natural System Error Messages 5351-5400 747 98 Natural System Error Messages 5401-5450 755 99 Natural System Error Messages 5501-5500 763 100 Natural System Error Messages 5501-5500 767 101 Natural System Error Messages 5601-5650 779 102 Natural System Error Messages 5601-5600 773 103 Natural System Error Messages 5701-5750 787 104 Natural System Error Messages 571-5700 787 105 Natural System Error Messages 581-5900 819 106 Natural System Error Messages 581-5900 819 107 Natural System Error Messages 591-5950 827 108 Natural System Error Messages 591-6900 831 110 Natural System Error Messages 601-6050 837 111 Natural System Error Messages 601-6150 843 112 Natural System Error Messages 611-6150 845 113 Natural System Error Messages 6201-6250 857 114 Natural System Error Messages 621-6300 869 116 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 641-6500 907 | 95 Natural System Error Messages 5201-5250 741 96 Natural System Error Messages 5251-5300 745 97 Natural System Error Messages 5351-5400 747 98 Natural System Error Messages 5401-5450 755 99 Natural System Error Messages 5401-5500 763 100 Natural System Error Messages 5501-5550 767 101 Natural System Error Messages 5601-5550 779 103 Natural System Error Messages 5601-5650 779 103 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 5701-5750 797 106 Natural System Error Messages 5701-5700 805 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5801-5800 805 108 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 6051-6100 833 110 Natural System Error Messages 6016-6050 837 111 Natural System Error Messages 611-6200 843 112 Natural System Error Messages 6251-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6451-6400 883 118 Natural System Error Messages 6451-6400 883 | | | |
| 96 Natural System Error Messages 5251-5300 745 97 Natural System Error Messages 5351-5400 747 98 Natural System Error Messages 5401-5450 755 99 Natural System Error Messages 5451-5500 763 100 Natural System Error Messages 5551-5600 767 101 Natural System Error Messages 5551-5600 779 102 Natural System Error Messages 5651-5700 787 104 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 571-5750 797 105 Natural System Error Messages 5851-5900 813 107 Natural System Error Messages 5851-5900 813 107 Natural System Error Messages 591-5950 827 109 Natural System Error Messages 591-5950 827 109 Natural System Error Messages 6101-6050 831 110 Natural System Error Messages 6101-6150 843 112 Natural System Error Messages 6151-6200 833 113 Natural System Error Messages 621-6250 857 113 Natural System Error Messages 631-6400 863 114 Natural System Error Messages 6401-6450 863 115 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6451-6500 907 <t< td=""><td>96 Natural System Error Messages 5251-5300 745 97 Natural System Error Messages 5401-5450 747 98 Natural System Error Messages 5401-5500 763 100 Natural System Error Messages 551-5500 767 101 Natural System Error Messages 551-5500 767 101 Natural System Error Messages 551-5500 779 102 Natural System Error Messages 561-5700 787 104 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 571-5750 797 105 Natural System Error Messages 571-5750 797 105 Natural System Error Messages 571-5800 805 106 Natural System Error Messages 581-5900 819 107 Natural System Error Messages 5951-6000 813 108 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 601-6050 837 111 Natural System Error Messages 6151-6100 843 112 Natural System Error Messages 6151-6200 853 113 Natural System Error Messages 621-6200 853 114 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 651-6400 895</td><td></td><td></td><td></td></t<> | 96 Natural System Error Messages 5251-5300 745 97 Natural System Error Messages 5401-5450 747 98 Natural System Error Messages 5401-5500 763 100 Natural System Error Messages 551-5500 767 101 Natural System Error Messages 551-5500 767 101 Natural System Error Messages 551-5500 779 102 Natural System Error Messages 561-5700 787 104 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 571-5750 797 105 Natural System Error Messages 571-5750 797 105 Natural System Error Messages 571-5800 805 106 Natural System Error Messages 581-5900 819 107 Natural System Error Messages 5951-6000 813 108 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 601-6050 837 111 Natural System Error Messages 6151-6100 843 112 Natural System Error Messages 6151-6200 853 113 Natural System Error Messages 621-6200 853 114 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 651-6400 895 | | | |
| 97 Natural System Error Messages 5351-5400 747 98 Natural System Error Messages 5401-5450 755 99 Natural System Error Messages 5501-5500 763 100 Natural System Error Messages 5501-5500 773 101 Natural System Error Messages 5501-5600 773 102 Natural System Error Messages 5601-5650 779 103 Natural System Error Messages 5601-5600 787 104 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5801-5950 813 107 Natural System Error Messages 5801-5950 813 107 Natural System Error Messages 5901-5950 827 108 Natural System Error Messages 6001-6050 831 110 Natural System Error Messages 6001-6050 831 110 Natural System Error Messages 611-6100 843 112 Natural System Error Messages 621-6200 853 113 Natural System Error Messages 621-6200 857 115 Natural System Error Messages 631-6400 863 116 Natural System Error Messages 631-6400 863 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 651-6500 907 120 Natural System Error Messages 651-6600 907 <tr< td=""><td>97 Natural System Error Messages 5351-5400 747 98 Natural System Error Messages 5401-5450 755 99 Natural System Error Messages 551-5500 763 100 Natural System Error Messages 5501-5550 767 101 Natural System Error Messages 5601-5650 779 103 Natural System Error Messages 5651-5700 787 104 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 5801-5850 813 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 601-6050 831 110 Natural System Error Messages 6051-6100 843 110 Natural System Error Messages 611-6150 845 113 Natural System Error Messages 621-6200 853 114 Natural System Error Messages 621-6200 853 115 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 651-6700 907 120 Natural System Error Messages 651-6700 907 120 Natural System Error Messages 651-6500 907</td><td></td><td>· ·</td><td></td></tr<> | 97 Natural System Error Messages 5351-5400 747 98 Natural System Error Messages 5401-5450 755 99 Natural System Error Messages 551-5500 763 100 Natural System Error Messages 5501-5550 767 101 Natural System Error Messages 5601-5650 779 103 Natural System Error Messages 5651-5700 787 104 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 5801-5850 813 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 601-6050 831 110 Natural System Error Messages 6051-6100 843 110 Natural System Error Messages 611-6150 845 113 Natural System Error Messages 621-6200 853 114 Natural System Error Messages 621-6200 853 115 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 651-6700 907 120 Natural System Error Messages 651-6700 907 120 Natural System Error Messages 651-6500 907 | | · · | |
| 98 Natural System Error Messages 5401-5450 755 99 Natural System Error Messages 5501-5500 763 100 Natural System Error Messages 5501-5550 767 101 Natural System Error Messages 5501-5500 773 102 Natural System Error Messages 5501-5500 779 103 Natural System Error Messages 5501-5700 787 104 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5801-5950 813 108 Natural System Error Messages 5951-6000 813 109 Natural System Error Messages 6001-6050 837 110 Natural System Error Messages 601-6100 843 112 Natural System Error Messages 601-6100 843 112 Natural System Error Messages 6201-6250 857 113 Natural System Error Messages 621-6200 853 114 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 641-6450 895 119 Natural System Error Messages 641-6450 895 114 Natural System Error Messages 641-6500 907 120 Natural System Error Messages 651-6700 901 <tr< td=""><td>98 Natural System Error Messages 5401-5450 755 99 Natural System Error Messages 5451-5500 763 100 Natural System Error Messages 5501-5550 767 101 Natural System Error Messages 5501-5550 779 102 Natural System Error Messages 5501-5550 779 103 Natural System Error Messages 5611-5650 779 103 Natural System Error Messages 5711-5750 787 104 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5811-5900 819 108 Natural System Error Messages 5951-6000 819 108 Natural System Error Messages 601-6050 837 111 Natural System Error Messages 601-6050 837 112 Natural System Error Messages 601-6150 843 112 Natural System Error Messages 621-6200 853 114 Natural System Error Messages 621-6250 857 115 Natural System Error Messages 621-6400 883 118 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 651-6500 907 120 Natural System Error Messages 651-6500 907 120 Natural System Error Messages 651-6500 907</td><td></td><td></td><td></td></tr<> | 98 Natural System Error Messages 5401-5450 755 99 Natural System Error Messages 5451-5500 763 100 Natural System Error Messages 5501-5550 767 101 Natural System Error Messages 5501-5550 779 102 Natural System Error Messages 5501-5550 779 103 Natural System Error Messages 5611-5650 779 103 Natural System Error Messages 5711-5750 787 104 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5811-5900 819 108 Natural System Error Messages 5951-6000 819 108 Natural System Error Messages 601-6050 837 111 Natural System Error Messages 601-6050 837 112 Natural System Error Messages 601-6150 843 112 Natural System Error Messages 621-6200 853 114 Natural System Error Messages 621-6250 857 115 Natural System Error Messages 621-6400 883 118 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 651-6500 907 120 Natural System Error Messages 651-6500 907 120 Natural System Error Messages 651-6500 907 | | | |
| 99 Natural System Error Messages 5451-5500 763 100 Natural System Error Messages 5501-5550 767 101 Natural System Error Messages 5501-5500 773 102 Natural System Error Messages 5651-5700 778 103 Natural System Error Messages 5751-5800 787 104 Natural System Error Messages 5751-5800 805 105 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5801-5950 827 108 Natural System Error Messages 5951-6000 819 108 Natural System Error Messages 6001-6050 831 110 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6201-6250 853 114 Natural System Error Messages 6201-6250 853 115 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 6451-6500 907 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6551-6600 907 120 Natural System Error Messages 651-650 909 121 Natural System Error Messages 6751-6800 933 | 99 Natural System Error Messages 5451-5500 763 100 Natural System Error Messages 5501-5550 767 101 Natural System Error Messages 5501-5500 773 102 Natural System Error Messages 561-5700 787 103 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5751-5800 805 107 Natural System Error Messages 5851-5900 819 108 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 601-6050 837 111 Natural System Error Messages 601-6150 843 112 Natural System Error Messages 611-6100 843 113 Natural System Error Messages 621-6200 853 114 Natural System Error Messages 621-6250 857 115 Natural System Error Messages 621-6300 869 116 Natural System Error Messages 6451-6400 883 118 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 651-6400 873 117 Natural System Error Messages 651-6500 907 120 Natural S | | | |
| 100 Natural System Error Messages 5501-5550 767 101 Natural System Error Messages 5551-5600 773 102 Natural System Error Messages 5601-5700 779 103 Natural System Error Messages 5651-5700 787 104 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 5701-5750 797 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5901-5950 827 108 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 601-6150 843 111 Natural System Error Messages 601-6100 843 112 Natural System Error Messages 6201-6200 853 114 Natural System Error Messages 621-6200 853 115 Natural System Error Messages 621-6300 869 116 Natural System Error Messages 621-6300 869 116 Natural System Error Messages 651-6500 907 120 Natural System Error Messages 651-6500 907 120 Natural System Error Messages 651-6500 907 121 Natural System Error Messages 651-6500 901 121 Natural System Error Messages 651-6650 923 <tr< td=""><td>100 Natural System Error Messages 5501-5550 767 101 Natural System Error Messages 5551-5600 773 102 Natural System Error Messages 5601-5650 779 103 Natural System Error Messages 5651-5700 787 104 Natural System Error Messages 5651-5750 797 105 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6051-6100 833 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 611-6150 845 113 Natural System Error Messages 6201-6250 853 114 Natural System Error Messages 6251-6300 869 116 Natural System Error Messages 6251-6400 883 118 Natural System Error Messages 6251-6400 883 118 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6451-6500 907 121 Natural System Error Messages 6451-6500 907 121 Natural System Error Messages 651-6600 917 122 Natural System Error Messages 651-6600 917</td><td></td><td></td><td></td></tr<> | 100 Natural System Error Messages 5501-5550 767 101 Natural System Error Messages 5551-5600 773 102 Natural System Error Messages 5601-5650 779 103 Natural System Error Messages 5651-5700 787 104 Natural System Error Messages 5651-5750 797 105 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6051-6100 833 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 611-6150 845 113 Natural System Error Messages 6201-6250 853 114 Natural System Error Messages 6251-6300 869 116 Natural System Error Messages 6251-6400 883 118 Natural System Error Messages 6251-6400 883 118 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6451-6500 907 121 Natural System Error Messages 6451-6500 907 121 Natural System Error Messages 651-6600 917 122 Natural System Error Messages 651-6600 917 | | | |
| 101 Natural System Error Messages 5551-5600 773 102 Natural System Error Messages 5601-5650 779 103 Natural System Error Messages 5651-5700 787 104 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5801-5900 819 108 Natural System Error Messages 5951-6000 831 107 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 601-6050 837 111 Natural System Error Messages 601-6100 843 112 Natural System Error Messages 6151-6200 853 113 Natural System Error Messages 621-6200 853 114 Natural System Error Messages 621-6200 853 115 Natural System Error Messages 621-6300 869 116 Natural System Error Messages 6401-6450 883 117 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 651-6500 907 120 Natural System Error Messages 651-6500 907 121 Natural System Error Messages 651-6650 923 123 Natural System Error Messages 651-6600 917 <t< td=""><td>101 Natural System Error Messages 5551-5600 773 102 Natural System Error Messages 5601-5650 779 103 Natural System Error Messages 5571-5700 787 104 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5751-5800 805 107 Natural System Error Messages 5851-5800 813 107 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5951-6000 813 108 Natural System Error Messages 5951-6000 831 100 Natural System Error Messages 601-6050 837 111 Natural System Error Messages 601-6100 843 112 Natural System Error Messages 6151-6200 843 113 Natural System Error Messages 621-6250 857 115 Natural System Error Messages 621-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 661-6550 909 121 Natural System Error Messages 661-6550 903 122 Natural System Error Messages 661-6500 923 123 Natural System Error Messages 661-6650 923 <</td><td></td><td></td><td></td></t<> | 101 Natural System Error Messages 5551-5600 773 102 Natural System Error Messages 5601-5650 779 103 Natural System Error Messages 5571-5700 787 104 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5751-5800 805 107 Natural System Error Messages 5851-5800 813 107 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5951-6000 813 108 Natural System Error Messages 5951-6000 831 100 Natural System Error Messages 601-6050 837 111 Natural System Error Messages 601-6100 843 112 Natural System Error Messages 6151-6200 843 113 Natural System Error Messages 621-6250 857 115 Natural System Error Messages 621-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 661-6550 909 121 Natural System Error Messages 661-6550 903 122 Natural System Error Messages 661-6500 923 123 Natural System Error Messages 661-6650 923 < | | | |
| 102 Natural System Error Messages 5601-5650 779 103 Natural System Error Messages 5651-5700 787 104 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5801-5900 819 108 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6101-6150 843 112 Natural System Error Messages 6101-6150 843 113 Natural System Error Messages 6201-6250 857 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6301-6350 869 116 Natural System Error Messages 6401-6450 883 118 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 651-6600 917 122 Natural System Error Messages 661-650 923 123 Natural System Error Messages 651-6600 917 124 Natural System Error Messages 651-6600 917 | 102 Natural System Error Messages 5601-5650 779 103 Natural System Error Messages 5651-5700 787 104 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5851-5900 813 107 Natural System Error Messages 5851-5900 819 108 Natural System Error Messages 5951-6000 831 109 Natural System Error Messages 601-6050 837 111 Natural System Error Messages 601-6100 843 112 Natural System Error Messages 6151-6100 843 112 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 621-6250 857 115 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6401-6450 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 661-650 923 121 Natural System Error Messages 661-650 923 122 Natural System Error Messages 661-6700 931 124 Natural System Error Messages 661-6700 931 <t< td=""><td></td><td></td><td></td></t<> | | | |
| 103 Natural System Error Messages 5651-5700 787 104 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5851-5900 819 108 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 601-6050 837 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 843 113 Natural System Error Messages 6201-6250 853 114 Natural System Error Messages 621-6300 869 115 Natural System Error Messages 631-6400 863 116 Natural System Error Messages 631-6400 863 117 Natural System Error Messages 631-6400 863 118 Natural System Error Messages 631-6400 863 119 Natural System Error Messages 651-6500 907 120 Natural System Error Messages 651-6600 907 121 Natural System Error Messages 6601-6650 923 122 Natural System Error Messages 671-6700 931 124 Natural System Error Messages 661-6700 931 <tr< td=""><td>103 Natural System Error Messages 5651-5700 787 104 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5801-5850 819 108 Natural System Error Messages 5951-6000 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6151-6200 853 113 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6301-6350 869 116 Natural System Error Messages 6301-6350 869 117 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 651-6600 907 120 Natural System Error Messages 651-6600 917 121 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 661-6700 931 124 Natural System Error Messages 661-6700 933 125 Natural System Error Messages 661-6700 933</td><td></td><td></td><td></td></tr<> | 103 Natural System Error Messages 5651-5700 787 104 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5801-5850 819 108 Natural System Error Messages 5951-6000 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6151-6200 853 113 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6301-6350 869 116 Natural System Error Messages 6301-6350 869 117 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 651-6600 907 120 Natural System Error Messages 651-6600 917 121 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 661-6700 931 124 Natural System Error Messages 661-6700 933 125 Natural System Error Messages 661-6700 933 | | | |
| 104 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5851-5900 819 108 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6001-6050 833 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 843 113 Natural System Error Messages 6201-6250 853 114 Natural System Error Messages 621-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6401-6450 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 651-6700 931 124 Natural System Error Messages 671-6750 933 125 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6651-6700 933 125 Natural System Error Messages 6751-6800 933 | 104 Natural System Error Messages 5701-5750 797 105 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5851-5900 819 108 Natural System Error Messages 5951-6000 831 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 601-6050 837 111 Natural System Error Messages 601-6050 843 112 Natural System Error Messages 6151-6100 843 112 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 631-6400 869 116 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6551-6600 917 120 Natural System Error Messages 6701-6750 933 121 Natural System Error Messages 671-6600 917 122 Natural System Error Messages 671-6600 917 122 Natural System Error Messages 671-670 933 125 Natural System Error Messages 671-6700 933 <t< td=""><td></td><td></td><td></td></t<> | | | |
| 105 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5851-5900 819 108 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6201-6250 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6251-6300 869 116 Natural System Error Messages 6401-6450 873 117 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 651-6600 907 120 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6701-6750 933 <td>105 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5851-5900 819 108 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 621-6300 869 116 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 631-6400 883 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6551-6600 901 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 671-6700 931 124 Natural System Error Messages 6751-6600 917 122 Natural System Error Messages 6751-6600 933 125 Natural System Error Messages 6751-6700 933</td> <td></td> <td></td> <td></td> | 105 Natural System Error Messages 5751-5800 805 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5851-5900 819 108 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 621-6300 869 116 Natural System Error Messages 631-6400 883 118 Natural System Error Messages 631-6400 883 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6551-6600 901 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 671-6700 931 124 Natural System Error Messages 6751-6600 917 122 Natural System Error Messages 6751-6600 933 125 Natural System Error Messages 6751-6700 933 | | | |
| 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5851-5900 819 108 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6101-6150 853 114 Natural System Error Messages 6201-6250 853 115 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6301-6450 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 661-6700 911 122 Natural System Error Messages 671-6700 931 124 Natural System Error Messages 6751-6800 933 125 Natural System Error Messages 6751-6800 933 126 Natural System Error Messages 6751-6800 933 | 106 Natural System Error Messages 5801-5850 813 107 Natural System Error Messages 5851-5900 819 108 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6101-650 853 114 Natural System Error Messages 6201-620 853 115 Natural System Error Messages 6301-6350 869 116 Natural System Error Messages 631-6400 883 117 Natural System Error Messages 6401-6450 873 118 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 651-6600 917 122 Natural System Error Messages 651-6600 911 124 Natural System Error Messages 671-6750 933 125 Natural System Error Messages 671-6750 933 126 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6751-6700 933 | | | |
| 107 Natural System Error Messages 5851-5900 819 108 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6101-6150 845 114 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6401-6450 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 6601-6650 923 124 Natural System Error Messages 6751-6800 933 125 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6801-6850 943 <td>107 Natural System Error Messages 5851-5900 819 108 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 843 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6101-6250 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6301-6350 869 116 Natural System Error Messages 6401-6450 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6551-6600 907 120 Natural System Error Messages 6651-6700 911 121 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6751-6800 939 125 Natural System Error Messages 6751-6800 933 124 Natural System Error Messages 6651-6700 933 125 Natural System Error Messages 6851-6900 953 126 Natural System Error Messages 6851-6900 953 <td></td><td></td><td></td></td> | 107 Natural System Error Messages 5851-5900 819 108 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 843 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6101-6250 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6301-6350 869 116 Natural System Error Messages 6401-6450 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6551-6600 907 120 Natural System Error Messages 6651-6700 911 121 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6751-6800 939 125 Natural System Error Messages 6751-6800 933 124 Natural System Error Messages 6651-6700 933 125 Natural System Error Messages 6851-6900 953 126 Natural System Error Messages 6851-6900 953 <td></td> <td></td> <td></td> | | | |
| 108 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6251-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6351-6400 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6501-6500 907 120 Natural System Error Messages 651-6600 917 121 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 6701-6750 933 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 681-6900 933 126 Natural System Error Messages 681-6900 953 128 Natural System Error Messages 691-6950 953 128 Natural System Error Messages 691-6900 953 | 108 Natural System Error Messages 5901-5950 827 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6151-6200 845 113 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6251-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6301-6450 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6551-6600 917 121 Natural System Error Messages 6651-6700 931 123 Natural System Error Messages 6651-6700 933 124 Natural System Error Messages 6751-6800 933 125 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6801-6650 933 128 Natural System Error Messages 6801-6900 953 128 Natural System Error Messages 6801-6950 955 <td></td> <td></td> <td></td> | | | |
| 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6251-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6351-6400 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 651-6500 907 20 Natural System Error Messages 6551-6600 917 21 Natural System Error Messages 6551-6600 917 22 Natural System Error Messages 6651-6700 931 24 Natural System Error Messages 671-6750 933 125 Natural System Error Messages 6751-6800 933 125 Natural System Error Messages 6851-6900 933 126 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6951-7000 963 | 109 Natural System Error Messages 5951-6000 831 110 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6251-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6351-6400 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6551-6600 917 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6651-6700 933 125 Natural System Error Messages 6701-6750 933 126 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6751-6800 933 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 691-6950 955 <td></td> <td></td> <td></td> | | | |
| 110 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6201-6250 857 116 Natural System Error Messages 6201-6250 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6301-6450 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6501-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 671-6750 933 125 Natural System Error Messages 6801-6650 923 126 Natural System Error Messages 6851-6900 933 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 691-6950 955 | 110 Natural System Error Messages 6001-6050 837 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6201-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6301-6400 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6501-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6651-6700 917 122 Natural System Error Messages 6651-6700 933 125 Natural System Error Messages 6801-6650 923 126 Natural System Error Messages 6801-6650 933 127 Natural System Error Messages 6801-6650 933 128 Natural System Error Messages 6801-6650 933 129 Natural System Error Messages 6801-6650 943 127 Natural System Error Messages 6801-6650 943 <td></td> <td></td> <td></td> | | | |
| 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6251-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6351-6400 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6501-6500 907 120 Natural System Error Messages 6501-6500 909 121 Natural System Error Messages 6651-6700 917 122 Natural System Error Messages 671-6700 933 123 Natural System Error Messages 671-6700 933 124 Natural System Error Messages 6801-6650 933 125 Natural System Error Messages 6801-6650 933 126 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6801-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 691-7000 963 130 Natural System Error Messages 7001-7050 975 | 111 Natural System Error Messages 6051-6100 843 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6201-6250 869 116 Natural System Error Messages 6201-6300 869 117 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6301-6400 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6501-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6651-6700 917 122 Natural System Error Messages 6651-6700 933 125 Natural System Error Messages 6801-6650 923 126 Natural System Error Messages 6801-6650 933 127 Natural System Error Messages 6801-6650 933 128 Natural System Error Messages 6801-6650 933 129 Natural System Error Messages 6801-6650 943 127 Natural System Error Messages 6801-6900 955 <td></td> <td></td> <td></td> | | | |
| 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6251-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6351-6400 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6551-6600 909 121 Natural System Error Messages 6651-6700 917 122 Natural System Error Messages 671-6750 933 123 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 933 127 Natural System Error Messages 6801-6850 933 128 Natural System Error Messages 6751-6800 933 127 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 691-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 | 112 Natural System Error Messages 6101-6150 845 113 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6251-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6351-6400 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6601-6650 917 122 Natural System Error Messages 6651-6600 917 122 Natural System Error Messages 6651-6600 913 124 Natural System Error Messages 6651-6700 933 125 Natural System Error Messages 6701-6750 933 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 953 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 701-7050 975 <td></td> <td>• •</td> <td></td> | | • • | |
| 113 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6251-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6351-6400 883 118 Natural System Error Messages 6401-6450 883 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6651-6700 917 122 Natural System Error Messages 6701-6750 933 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6801-6850 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 681-6900 953 128 Natural System Error Messages 6901-6950 953 128 Natural System Error Messages 691-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 | 113 Natural System Error Messages 6151-6200 853 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6251-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6301-6400 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6651-6600 917 123 Natural System Error Messages 6651-6600 923 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6901-6950 953 128 Natural System Error Messages 6901-6950 953 128 Natural System Error Messages 6901-6950 953 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7051-7100 975 131 Natural System Error Messages 7051-7100 983 132 Natural System Error Messages 7051-7100 983 <td></td> <td></td> <td></td> | | | |
| 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6251-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6351-6400 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6651-6700 917 123 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 933 127 Natural System Error Messages 6801-6850 933 128 Natural System Error Messages 6801-6900 933 127 Natural System Error Messages 6901-6950 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 701-7050 963 130 Natural System Error Messages 701-7050 975 131 Natural System Error Messages 7051-7100 983 | 114 Natural System Error Messages 6201-6250 857 115 Natural System Error Messages 6251-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6351-6400 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 691-6900 953 128 Natural System Error Messages 691-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 701-700 983 132 Natural System Error Messages 701-700 983 132 Natural System Error Messages 701-700 983 < | | | |
| 115 Natural System Error Messages 6251-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6351-6400 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6751-6800 933 125 Natural System Error Messages 6801-6650 933 125 Natural System Error Messages 6801-6650 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6851-6900 953 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 | 115 Natural System Error Messages 6251-6300 869 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6351-6400 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6651-6700 923 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6801-6850 933 127 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 691-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 132 Natural System Error Messages 7051-7100 983 132 Natural System Error Messages 7051-7100 983 <td></td> <td></td> <td></td> | | | |
| 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6351-6400 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6401-6450 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6501-6650 917 122 Natural System Error Messages 6601-6650 913 123 Natural System Error Messages 6601-6670 923 123 Natural System Error Messages 6701-6750 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6801-6850 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6901-6950 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 | 116 Natural System Error Messages 6301-6350 873 117 Natural System Error Messages 6351-6400 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6651-6700 923 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6801-6650 933 126 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6851-6900 933 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7051-7000 975 131 Natural System Error Messages 7051-7000 983 132 Natural System Error Messages 7051-7000 983 132 Natural System Error Messages 7051-7000 983 132 Natural System Error Messages 7051-7000 983 <td></td> <td></td> <td></td> | | | |
| 117 Natural System Error Messages 6351-6400 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6651-6600 913 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 933 127 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6901-6950 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 | 117 Natural System Error Messages 6351-6400 883 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6951-7000 953 128 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 132 Natural System Error Messages 7051-7100 983 132 Natural System Error Messages 7051-7100 983 | | | |
| 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6801-6850 939 126 Natural System Error Messages 6801-6850 933 127 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 | 118 Natural System Error Messages 6401-6450 895 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 132 Natural System Error Messages 7051-7100 983 | | | |
| 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6901-6950 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 | 119 Natural System Error Messages 6451-6500 907 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 933 127 Natural System Error Messages 6801-6850 933 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 132 Natural System Error Messages 7051-7100 983 | | | |
| 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 | 120 Natural System Error Messages 6501-6550 909 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 132 Natural System Error Messages 7051-7200 987 | | | |
| 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 | 121 Natural System Error Messages 6551-6600 917 122 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 132 Natural System Error Messages 7051-7100 983 | | 5 | |
| 122 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 | 122 Natural System Error Messages 6601-6650 923 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 132 Natural System Error Messages 7151-7200 987 | | 5 | |
| 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7051-7100 975 131 Natural System Error Messages 7051-7100 983 | 123 Natural System Error Messages 6651-6700 931 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7051-7100 975 131 Natural System Error Messages 7151-7200 983 | | | |
| 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 | 124 Natural System Error Messages 6701-6750 933 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 132 Natural System Error Messages 7151-7200 987 | | | |
| 125 Natural System Error Messages 6751-6800939126 Natural System Error Messages 6801-6850943127 Natural System Error Messages 6851-6900953128 Natural System Error Messages 6901-6950955129 Natural System Error Messages 6951-7000963130 Natural System Error Messages 7001-7050975131 Natural System Error Messages 7051-7100983 | 125 Natural System Error Messages 6751-6800 939 126 Natural System Error Messages 6801-6850 943 127 Natural System Error Messages 6851-6900 953 128 Natural System Error Messages 6901-6950 955 129 Natural System Error Messages 6951-7000 963 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7151-7200 983 132 Natural System Error Messages 7151-7200 987 | | | |
| 126 Natural System Error Messages 6801-6850943127 Natural System Error Messages 6851-6900953128 Natural System Error Messages 6901-6950955129 Natural System Error Messages 6951-7000963130 Natural System Error Messages 7001-7050975131 Natural System Error Messages 7051-7100983 | 126 Natural System Error Messages 6801-6850943127 Natural System Error Messages 6851-6900953128 Natural System Error Messages 6901-6950955129 Natural System Error Messages 6951-7000963130 Natural System Error Messages 7001-7050975131 Natural System Error Messages 7051-7100983132 Natural System Error Messages 7151-7200987 | | | |
| 127 Natural System Error Messages 6851-6900953128 Natural System Error Messages 6901-6950955129 Natural System Error Messages 6951-7000963130 Natural System Error Messages 7001-7050975131 Natural System Error Messages 7051-7100983 | 127 Natural System Error Messages 6851-6900953128 Natural System Error Messages 6901-6950955129 Natural System Error Messages 6951-7000963130 Natural System Error Messages 7001-7050975131 Natural System Error Messages 7051-7100983132 Natural System Error Messages 7151-7200987 | | | |
| 128 Natural System Error Messages 6901-6950955129 Natural System Error Messages 6951-7000963130 Natural System Error Messages 7001-7050975131 Natural System Error Messages 7051-7100983 | 128 Natural System Error Messages 6901-6950955129 Natural System Error Messages 6951-7000963130 Natural System Error Messages 7001-7050975131 Natural System Error Messages 7051-7100983132 Natural System Error Messages 7151-7200987 | | | |
| 129 Natural System Error Messages 6951-7000963130 Natural System Error Messages 7001-7050975131 Natural System Error Messages 7051-7100983 | 129 Natural System Error Messages 6951-7000963130 Natural System Error Messages 7001-7050975131 Natural System Error Messages 7051-7100983132 Natural System Error Messages 7151-7200987 | | • • | |
| 130 Natural System Error Messages 7001-7050975131 Natural System Error Messages 7051-7100983 | 130 Natural System Error Messages 7001-7050 975 131 Natural System Error Messages 7051-7100 983 132 Natural System Error Messages 7151-7200 987 | | 5 | |
| 131 Natural System Error Messages 7051-7100 | 131 Natural System Error Messages 7051-7100983132 Natural System Error Messages 7151-7200987 | | | |
| | 132 Natural System Error Messages 7151-7200 987 | | • • | |
| | | | | |
| | 133 Natural System Error Messages 7201-7250 | | | |
| 133 Natural System Error Messages 7201-7250 | | 133 Nat | ural System Error Messages 7201-7250 | 989 |

| 134 Natural System Error Messages 7251-7300 |
|--|
| 135 Natural System Error Messages 7301-7350 |
| 136 Natural System Error Messages 7351-7400 |
| 137 Natural System Error Messages 7401-7450 |
| 138 Natural System Error Messages 7501-7550 1001 |
| 139 Natural System Error Messages 7551-7600 1005 |
| 140 Natural System Error Messages 7601-7650 1007 |
| 141 Natural System Error Messages 7651-7700 1009 |
| 142 Natural System Error Messages 7701-7750 1015 |
| 143 Natural System Error Messages 7801-7850 1021 |
| 144 Natural System Error Messages 7951-8000 1023 |
| 145 Natural System Error Messages 8251-8300 1025 |
| 146 Natural System Error Messages 8301-8350 1027 |
| 147 Natural System Error Messages 8351-8400 1033 |
| 148 Natural System Error Messages 8401-8450 1035 |
| 149 Natural System Error Messages 8951-9000 1039 |
| 150 Natural System Error Messages 9901-9950 1041 |
| 151 Natural System Error Messages 9951-9999 1053 |

1 Messages and Codes

This documentation explains the system error messages that may be issued by the Natural nucleus. Library-specific messages and messages relating to other Software AG products are not included.

Natural System Error Messages 0001-0050 Natural System Error Messages 0051-0100 Natural System Error Messages 0101-0150 Natural System Error Messages 0151-0200 Natural System Error Messages 0201-0250 Natural System Error Messages 0251-0300 Natural System Error Messages 0301-0350 Natural System Error Messages 0351-0400 Natural System Error Messages 0401-0450 Natural System Error Messages 0451-0500 Natural System Error Messages 0551-0600 Natural System Error Messages 0601-0650 Natural System Error Messages 0651-0700 Natural System Error Messages 0701-0750 Natural System Error Messages 0751-0800 Natural System Error Messages 0801-0850

| ٩ | Natural System Error Messages 0851-0900 |
|---|---|
| ٩ | Natural System Error Messages 0901-0950 |
| 9 | Natural System Error Messages 0951-1000 |
| 0 | Natural System Error Messages 1001-1050 |
| 0 | Natural System Error Messages 1051-1100 |
| 0 | Natural System Error Messages 1101-1150 |
| ٩ | Natural System Error Messages 1151-1200 |
| 0 | Natural System Error Messages 1201-1250 |
| ٩ | Natural System Error Messages 1251-1300 |
| ٩ | Natural System Error Messages 1301-1350 |
| ٩ | Natural System Error Messages 1351-1400 |
| 0 | Natural System Error Messages 1451-1500 |
| ٩ | Natural System Error Messages 1501-1550 |
| 0 | Natural System Error Messages 1551-1600 |
| ٩ | Natural System Error Messages 1601-1650 |
| ٩ | Natural System Error Messages 1651-1700 |
| ٩ | Natural System Error Messages 1701-1750 |
| ٩ | Natural System Error Messages 1751-1800 |
| 0 | Natural System Error Messages 1801-1850 |
| 0 | Natural System Error Messages 1851-1900 |
| 0 | Natural System Error Messages 1901-1950 |
| 0 | Natural System Error Messages 1951-2000 |
| 0 | Natural System Error Messages 2001-2050 |
| ٩ | Natural System Error Messages 2051-2100 |
| ٩ | Natural System Error Messages 2101-2150 |
| ۲ | Natural System Error Messages 2151-2200 |

Natural System Error Messages 2201-2250 Natural System Error Messages 2251-2300 Natural System Error Messages 2301-2350 Natural System Error Messages 2351-2400 Natural System Error Messages 2401-2450 Natural System Error Messages 2451-2500 Natural System Error Messages 2501-2550 Natural System Error Messages 2551-2600 Natural System Error Messages 2601-2650 Natural System Error Messages 2651-2700 Natural System Error Messages 2701-2750 Natural System Error Messages 2751-2800 Natural System Error Messages 2801-2850 Natural System Error Messages 2851-2900 Natural System Error Messages 2901-2950 Natural System Error Messages 2951-3000 Natural System Error Messages 3001-3050 Natural System Error Messages 3051-3100 Natural System Error Messages 3101-3150 Natural System Error Messages 3151-3200 Natural System Error Messages 3201-3250 Natural System Error Messages 3251-3300 Natural System Error Messages 3301-3350 Natural System Error Messages 3351-3400 Natural System Error Messages 3401-3450 Natural System Error Messages 3451-3500

| • | Natural System Error Messages 3501-3550 |
|---|---|
| ٩ | Natural System Error Messages 3551-3600 |
| ٩ | Natural System Error Messages 3601-3650 |
| ٩ | Natural System Error Messages 3701-3750 |
| ٩ | Natural System Error Messages 3951-4000 |
| ٩ | Natural System Error Messages 4001-4050 |
| ٩ | Natural System Error Messages 4051-4100 |
| 0 | Natural System Error Messages 4101-4150 |
| 0 | Natural System Error Messages 4151-4200 |
| 0 | Natural System Error Messages 4201-4250 |
| ٩ | Natural System Error Messages 4251-4300 |
| ٩ | Natural System Error Messages 4301-4350 |
| ٩ | Natural System Error Messages 4351-4400 |
| ٩ | Natural System Error Messages 4401-4450 |
| ٩ | Natural System Error Messages 4451-4500 |
| 0 | Natural System Error Messages 4501-4550 |
| 0 | Natural System Error Messages 4551-4600 |
| 0 | Natural System Error Messages 4601-4650 |
| ٩ | Natural System Error Messages 4651-4700 |
| ٩ | Natural System Error Messages 4701-4750 |
| ٩ | Natural System Error Messages 4751-4800 |
| ٩ | Natural System Error Messages 4801-4850 |
| ٩ | Natural System Error Messages 4851-4900 |
| 0 | Natural System Error Messages 4901-4950 |
| 0 | Natural System Error Messages 4951-5000 |
| ٩ | Natural System Error Messages 5201-5250 |
| | |

Natural System Error Messages 5251-5300 Natural System Error Messages 5351-5400 Natural System Error Messages 5401-5450 Natural System Error Messages 5451-5500 Natural System Error Messages 5501-5550 Natural System Error Messages 5551-5600 Natural System Error Messages 5601-5650 Natural System Error Messages 5651-5700 Natural System Error Messages 5701-5750 Natural System Error Messages 5751-5800 Natural System Error Messages 5801-5850 Natural System Error Messages 5851-5900 Natural System Error Messages 5901-5950 Natural System Error Messages 5951-6000 Natural System Error Messages 6001-6050 Natural System Error Messages 6051-6100 Natural System Error Messages 6101-6150 Natural System Error Messages 6151-6200 Natural System Error Messages 6201-6250 Natural System Error Messages 6251-6300 Natural System Error Messages 6301-6350 Natural System Error Messages 6351-6400 Natural System Error Messages 6401-6450 Natural System Error Messages 6451-6500 Natural System Error Messages 6501-6550 Natural System Error Messages 6551-6600

| ٩ | Natural System Error Messages 6601-6650 |
|---|---|
| ٩ | Natural System Error Messages 6651-6700 |
| ٩ | Natural System Error Messages 6701-6750 |
| 0 | Natural System Error Messages 6751-6800 |
| 0 | Natural System Error Messages 6801-6850 |
| 0 | Natural System Error Messages 6851-6900 |
| ٩ | Natural System Error Messages 6901-6950 |
| ٩ | Natural System Error Messages 6951-7000 |
| 0 | Natural System Error Messages 7001-7050 |
| ٩ | Natural System Error Messages 7051-7100 |
| ٩ | Natural System Error Messages 7151-7200 |
| ٩ | Natural System Error Messages 7201-7250 |
| ٩ | Natural System Error Messages 7251-7300 |
| ٩ | Natural System Error Messages 7301-7350 |
| 0 | Natural System Error Messages 7351-7400 |
| ٩ | Natural System Error Messages 7401-7450 |
| 0 | Natural System Error Messages 7501-7550 |
| 0 | Natural System Error Messages 7551-7600 |
| ٩ | Natural System Error Messages 7601-7650 |
| ٩ | Natural System Error Messages 7651-7700 |
| ٩ | Natural System Error Messages 7701-7750 |
| ٩ | Natural System Error Messages 7801-7850 |
| ٩ | Natural System Error Messages 7951-8000 |
| ٩ | Natural System Error Messages 8251-8300 |
| ٩ | Natural System Error Messages 8301-8350 |
| ۲ | Natural System Error Messages 8351-8400 |

- Natural System Error Messages 8401-8450
- Natural System Error Messages 8951-9000
- Natural System Error Messages 9901-9950
- Matural System Error Messages 9951-9999

2 Natural System Error Messages 0001-0050

NAT0001: Missing/invalid syntax; undefined variable name/keyword.

| Text | Missing/invalid syntax; undefined variable name/keyword. |
|-------|---|
| | The syntax checker detected an invalid statement name or keyword. Probable cause is a misspelling of a statement name, keyword or variable name, or an error in a sub-clause of the |
| | previous statement. |
| Actn. | Correct error. |

NAT0002: No file is available with specified name or number.

| Text | No file is available with specified name or number. |
|-------|--|
| Expl. | The file name was misspelt; or the file is not defined in the data dictionary; or you are not authorized to access the file. |
| Actn. | Use a correct file name; or define the file in the data dictionary; or contact your Natural administrator for access authorization to the file. |

NAT0003: Invalid character string for file name or file number.

| Text | Invalid character string for file name or file number. |
|-------|--|
| 10/10 | invalue character stang for the name of the number. |

| Expl. | An invalid syntax has been supplied where Natural |
|-------|---|
| | expected to locate a file name or number. |
| | Only characters that are available in the construction of |
| | variable names may be used for the construction of a file name, |
| | i.e., alphabetical characters (first character must be alphabetical), |
| | numeric characters, and the following special characters: |
| | - hyphen-minus 🛛 underscore |
| | @ commercial at / slash |
| | # number sign \$ dollar sign |
| | & ampersand |
| | On mainframe platforms, "@" is the character with the hexadecimal |
| | value H"7C". |
| Actn. | value H"7C". Eliminate invalid characters from file identification. |

NAT0004: DEFINE DATA must be the first statement if present.

| Text | DEFINE DATA must be the first statement if present. |
|-------|---|
| · · | If DEFINE DATA is used in a program, it must always be the first statement. |
| Actn. | Correct error. |

NAT0005: Closing parenthesis missing in arithm/logical expression.

| Text | Closing parenthesis missing in arithmetic/logical expression. |
|-------|--|
| | Parentheses may be used to control the evaluation of arithmetic and logical expressions. If parentheses are used, they must always be paired (opening and closing parentheses). |
| Actn. | Check the use of parentheses in the arithmetic or logical expression. |

NAT0006: ESCAPE statement used when no processing loop active.

| Text | ESCAPE statement used when no processing loop active. |
|-------|---|
| Expl. | The ESCAPE statement may only be used within an active processing loop. |
| Actn. | Check structure of processing loops and place ESCAPE statement correctly within an active loop. |

NAT0007: Invalid THRU or TO clause in READ LOGICAL or HISTOGRAM.

| Text | Invalid THRU or TO clause in READ LOGICAL or HISTOGRAM. |
|-------|---|
| Expl. | In a READ LOGICAL or HISTOGRAM statement, when specifying a - THRU clause, an ending value must be supplied; - TO clause, a starting value and an ending value must be supplied. A starting or ending value must be either a constant or the content of a variable. |
| Actn. | Correct error in program. |

NAT0008: Invalid search syntax.

| Text | Invalid search syntax. |
|-------|---|
| Expl. | A field used in a WITH clause must be a descriptor. A group notation is not permitted. When the ENDING AT clause of a READ statement uses a superdescriptor as the search key, the superdescriptor must be defined with the VIEW in the data area (if present). When the READ statement is related to DB2, the search variable must be part of the VIEW. |
| Actn. | The LIST FILE command may be used to ascertain whether a field is defined as a descriptor in the data dictionary. Add the superdescriptor to the VIEW. |

NAT0009: Invalid relational operator in a relational expression.

| Text | Invalid relational operator in a relational expression. |
|-------|--|
| Expl. | A relational expression in a logical criterion contains an invalid |
| | relational operator. The following relational operators may be used |
| | in a relational expression: |
| | = or EQ or EQUAL TO |
| | ⇔ or NE or NOTEQUAL |
| | < or LT or LESS THAN |
| | <= or LE or LESS EQUAL |
| | > or GT or GREATER THAN |
| | >= or GE or GREATER EQUAL |
| | See the Natural documentation, Logical Condition Criteria, for further |
| | information. |
| Actn. | Correct the construction of the relational expression. |

NAT0010: Error in value specification in a relational expression.

| Text | Error in value specification in a relational expression. |
|-------|---|
| Expl. | The search criterion is correct up to the relational operator, but the specification of the value to be compared is either missing or invalid. If the value was specified using a variable, the variable must have been previously defined. |
| Actn. | Ensure that alpha descriptor values are enclosed in apostrophes and that numeric values are not. Reference only variables that have been defined previously. |

NAT0011: Invalid format combination in a relational expression.

| Text | Invalid format combination in a relational expression. |
|-------|---|
| | In a relational expression, values being compared with a relational operator must have the same format, that is: alpha rel-operator alpha numeric rel-operator numeric binary rel-operator binary |
| Actn. | Correct error. |

NAT0012: Length adjustment of search variable not possible.

| Text | Length adjustment of search variable not possible. |
|-------|---|
| | The value supplied in the relational expression is longer than the length defined for the search variable. The length of the search variable can be dynamically adjusted to the length of the value supplied if only one value exists. (This is not true for expressions using the "OR =", "THRU" or "BUT NOT" operations.) |
| Actn. | If more than one value exists, use appropriate length specification for search variable. |

NAT0013: Descriptor name or ISN missing after "BY" in READ.

| Text | Descriptor name or ISN missing after "BY" in READ. |
|-------|---|
| Expl. | The word "BY" is specified to express a sequence for a READ operation. If BY is used, either the word "ISN" or the name of a descriptor must be specified to express the sequence in which the records are to be read. |
| Actn. | Either do not specify BY, or specify either ISN or the name of a descriptor. |

NAT0014: Error in SORTED BY clause of FIND statement.

| Text | Error in SORTED BY clause of FIND statement. |
|-------|---|
| | The field specified for an Adabas sort is not a descriptor; or no sort descriptor was specified; or more than 3 sort fields were specified. |
| Actn. | Correct error. |

NAT0015: Parenthesis missing in Natural system function notation.

| Text | Parenthesis missing in Natural system function notation. |
|-------|---|
| Expl. | The argument for a Natural system function must be enclosed in parentheses. If a variable has been given a name which is also the name of a Natural system function, this error message will also occur. |
| Actn. | Either enclose the argument for the function in parentheses; or change the name of the variable so that it does not conflict with the name of a Natural system function. |

NAT0016: Invalid parameter in INCLUDE statement or copycode.

| Text | Invalid parameter in INCLUDE statement or copycode. |
|-------|---|
| Expl. | The number of a parameter in the copycode |
| Actn. | Correct error in INCLUDE statement or in copycode. |

NAT0017: MASK or SCAN used incorrectly, or incorrect mask length.

| Text | MASK or SCAN used incorrectly, or incorrect mask length. |
|-------|---|
| Expl. | MASK and SCAN can only be specified following an EQ or NE operator. The length of the mask must be less than or equal to the length of the field. Only the following characters may be used in a mask: . ignore position in variable DD check for valid day in month U check for upper-case alpha MM check for valid month in year N check for numeric YY check for valid current year H check for hexadec. character YYYY check for valid year in century P check for printable char. JJJ check for valid Julian day L check for lower-case alpha N1-N2 check against range of values C check for alphanumeric S check for special printable A check for upper/lower alpha X check against position in value |
| Actn. | Ensure that the mask is specified correctly. |

NAT0018: Error in construction of arithmetic operand.

| Text | Error in construction of arithmetic operand. |
|-------|--|
| | The name of a variable has been misspelt in an arithmetic expression; or a wrong character has been used in the construction of a numeric constant; or the argument of a square root function has been constructed incorrectly. |
| Actn. | Check program and correct error. |

NAT0019: Error in receiving field of arithmetic statement.

| Text | Error in receiving field of arithmetic statement. |
|-------|--|
| Expl. | The receiving field of an arithmetic operation must consist of a valid variable reference. The error may be caused by a misspelt variable name or by not supplying the character "=" in ASSIGN/COMPUTE. It can also appear if the target variable is a system function like INT, SIN, etc. Ensure that the target field of MULTIPLY/DIVIDE is not a constant. |
| Actn. | Check program and correct error. |

NAT0020: Word "BY" missing in MULTIPLY statement.

| Text | Word "BY" missing in MULTIPLY statement. |
|-------|---|
| - | In a MULTIPLY statement, the word "BY" is required between the two operands to be multiplied, for example: MULTIPLY 1 BY 2 GIVING #RESULT |
| Actn. | Check program and correct error. |

NAT0021: Word "INTO" missing in DIVIDE statement.

| Text | Word "INTO" missing in DIVIDE statement. |
|-------|---|
| | In a DIVIDE statement, the two operands must be separated by the word "INTO", for example: DIVIDE 2 INTO 7 GIVING #RESULT |
| Actn. | Check program and correct error. |

NAT0022: Word "TO" missing in MOVE statement.

| Text | Word "TO" missing in MOVE statement. |
|-------|---|
| | The word "TO" is required in a MOVE statement to indicate the result field(s) into which the values are to be moved. Examples: MOVE 1 TO #A MOVE #B TO #C #D #E #F |
| Actn. | Check program and correct error. |

NAT0023: Error in specification of format element.

| Text | Error in specification of format element. |
|-------|--|
| Expl. | Error in the specification of a format element: either in the FORMAT statement, or in a format specification following an input/output statement or an individual element. Format elements must be identified using the proper format element keywords. See the Natural session parameters documentation for details. |
| Actn. | Check program and correct error. |

NAT0024: In VERT mode, "AS" must be followed by "text" or "CAP".

| Text | In VERT mode, "AS" must be followed by "text" or "CAP". |
|-------|--|
| Expl. | DISPLAY VERTICALLY AS indicates that a special option is desired for |
| | the vertical display of elements. |
| | No such option was encountered, either because of a misspelling |
| | or because no options were provided. |
| | Possible options are: |
| | - DISPLAY VERTICALLY AS "header text" |
| | - DISPLAY VERTICALLY AS CAPTIONED (or DISPLAY VERTICALLY AS CAP) |
| | - DISPLAY VERTICALLY AS "header text" CAPTIONED |
| | See the Natural statements documentation for details. |
| Actn. | Check program and correct error. |

NAT0025: Closing parenthesis missing in system function argument.

| Text | Closing parenthesis missing in system function argument. |
|-------|---|
| Expl. | In a SORT statement, multiple argument variables can be specified for the same Natural system function. The list of argument variables must be enclosed in parentheses for all argument fields that are to be evaluated for the same system function. |
| Actn. | Check program and correct error. |

NAT0026: Output element after "VERT" is missing or invalid.

| Text | Output element after "VERT" is missing or invalid. |
|-------|--|
| Expl. | "VERT(ICALLY)" was specified in a DISPLAY statement to indicate that output elements are to be displayed underneath one another; however, no valid output element was encountered after the "VERT". You have probably misspelt a variable name or forgotten an apostrophe at the beginning of a text string. |
| Actn. | Check program and correct error. |

NAT0027: Error in value specification.

| Text | Error in value specification. |
|-------|---|
| Expl. | A value may be specified either as a constant or as the reference to an already existing variable or database field. |
| | Either a misspelt variable name was supplied, or the leading apostrophe for a constant was omitted. |
| Actn. | Correct error. |

NAT0028: READ LOGICAL used without required descriptor.

| Text | READ LOGICAL used without required descriptor. |
|-------|--|
| Expl. | A READ LOGICAL statement requires the specification of a |
| | descriptor which is to be used to control the read sequence. |
| | If no sequence is specified in the READ LOGICAL statement, |
| | Natural attempts to use the default sequence as defined for the file |
| | in the Data Dictionary. |
| | If no descriptor is specified in the READ LOGICAL statement, |
| | and no default sequence is defined in the Data Dictionary, |
| | this error message will be displayed. |
| Actn. | Ensure that the sequence descriptor is specified by either |
| | of the methods described above. |

NAT0029: Descriptor field missing/invalid syntax in HISTOGRAM.

| Text | Descriptor field missing/invalid syntax in HISTOGRAM. |
|-------|--|
| | A HISTOGRAM statement reads the values for a descriptor. The values are read using the database inverted list. Therefore, only descriptor fields may be specified. |
| Actn. | Supply a valid descriptor. |

| Text | A relational expression is missing or invalid. |
|-------|--|
| Expl. | The following relational expressions are valid: = or EQ or EQUAL TO <> or NE or NOTEQUAL < or LT or LESS THAN <= or LE or LESS EQUAL > or GT or GREATER THAN >= or GE or GREATER EQUAL |
| | See the Natural documentation, Logical Condition Criteria, for further information. |
| Actn. | Correct the construction of the relational expression. |

NAT0030: A relational expression is missing or invalid.

NAT0031: Opening/closing parenthesis missing in REDEFINE.

| Text | Opening/closing parenthesis missing in REDEFINE. |
|-------|--|
| | Opening and closing parentheses are required to begin/end the definition of a new variable using REDEFINE. Example: REDEFINE #A (#A(N3) #A2(A7)) |
| Actn. | Correct error. |

NAT0032: Invalid break control field in AT BREAK or IF BREAK.

| Text | Invalid break control field in AT BREAK or IF BREAK. |
|-------|---|
| Expl. | In an AT BREAK statement or IF BREAK condition, a database field or user-defined variable may be used to indicate the break control field. If a user-defined variable is used, it must have been previously defined. A break control variable can have any format, except format "C" (attribute control). The maximum length of a break variable is 253 bytes for alphanumeric and 126 bytes for binary variables. If you wish to use an alphanumeric variable with a larger size, you have to reduce the number of break positions with an explicit "/n/" clause. The same applies for variables defined as alpha DYNAMIC. Example: assume definitions #A300(A300) #DYN(A) DYNAMIC AT BREAK OF #A300 /10/ IF BREAK OF #DYN /177/ |
| Actn. | Correct error. |

NAT0034: Numeric field for number of lines invalid or missing.

| Text | Numeric field for number of lines invalid or missing. |
|-------|--|
| | The number of lines to be skipped in a SKIP, EJECT or NEWPAGE statement must be specified with a numeric constant or variable. |
| | statement must be specified with a numeric constant of variable. |
| Actn. | Check program and correct error. |

NAT0035: "DATA" not in AT START OF DATA/"PAGE" in AT TOP OF PAGE.

| Text | "DATA" not in AT START OF DATA/"PAGE" in AT TOP OF PAGE. |
|-------|--|
| Expl. | The word "DATA" is required in the construction of an AT START OF DATA statement; the word "PAGE" is missing in an AT TOP OF PAGE statement. It has either been misspelt or forgotten. |
| Actn. | Check program and correct error. |

NAT0037: Name missing or specified incorrectly.

| Text | Name missing or specified incorrectly. |
|-------|---|
| Expl. | This error occurs under one of the following conditions: At compilation time, if the object name (e.g. subprogram, dialog) specified in the statement is incorrect, either by format or length. At runtime, if a dynamic alphanumeric variable is used to specify the object name and the current length of the variable exceeds the maximum of 8 characters. |
| Actn. | Specify the name as a 1- to 8-character constant or variable (A1-A8) or do not use a dynamic variable which is longer than 8 characters. |

NAT0038: Invalid field reference in REDEFINE base field.

| Text | Invalid field reference in REDEFINE base field. |
|-------|---|
| | The field to be used as the base field in a REDEFINE statement may be a user-defined variable or a database field. |
| | If it is a database field, it must be a field within an active loop. |
| Actn. | Check program and correct error. |

NAT0039: Sum of field lengths in REDEFINE > length of base field :1:.

| Text | Sum of field lengths in REDEFINE > length of base field |
|-------|--|
| | The accumulated length of all new fields in a REDEFINE statement must be less than or equal to the length of the base field, counted in bytes. |
| | When a group contains a field of type HANDLE or DYNAMIC, you can only redefine the fields before the HANDLE or DYNAMIC variable. |
| Actn. | Check program and correct error. |

NAT0040: Only one AT TOP OF PAGE statement allowed per report.

| Text | Only one AT TOP OF PAGE statement allowed per report. |
|-------|--|
| Expl. | The AT TOP OF PAGE statement may only be specified once for the same report. If multiple actions are to be executed at the top of a page depending on various conditions, they must be specified within the same AT TOP OF PAGE statement and separated by the appropriate logical conditions. |
| Actn. | Check program and correct error. |

NAT0041: Only one AT END OF PAGE statement allowed per report.

| Text | Only one AT END OF PAGE statement allowed per report. |
|-------|---|
| Expl. | The AT END OF PAGE statement may be specified only once per report. If multiple actions are desired under the same end-of-page condition, they must be specified within the same AT END OF PAGE statement and separated by the appropriate logical conditions. |
| Actn. | Check program and correct error. |

NAT0042: Invalid specification of CIPHER code.

| Text | Invalid specification of CIPHER code. |
|-------|---|
| Expl. | The cipher code for a database file may be specified either as a numeric constant (8 digits) or the content of a numeric variable. The numeric variable must be defined with format/length N8. An equal sign (=) must be specified between the word CIPHER and the value. If the value is supplied via a numeric variable, this numeric variable cannot be a REDEFINE variable. |
| Actn. | Check program and correct error. |

NAT0043: Invalid password construction.

| Text | Invalid password construction. |
|-------|--|
| | The Adabas password may be provided as an alphanumeric constant or by using an alphanumeric variable. An equal sign (=) must be specified between the word PASSWORD and the value for the password. |
| Actn. | Check program and correct error. |

NAT0044: Output element not defined, or indexes incorrect.

| Text | Output element not defined, or indexes incorrect. |
|-------|---|
| Expl. | This error may be caused by: - an error in the construction of the name of an output element; - a reference to a variable that has not been previously defined; - a misspelling of a keyword; - an invalid index specification. |
| Actn. | Check program and correct error. |

NAT0045: Invalid reference in UPDATE or DELETE statement.

| Text | Invalid reference in UPDATE or DELETE statement. |
|-------|--|
| Expl. | Either the construction of the reference is wrong or the reference is not allowed. A reference can only be made to a FIND, GET or READ statement. An UPDATE, GET or DELETE statement must not be on the same line as a FIND statement. No reference is possible to a GET SAME statement. In this case, use a reference to the statement that made the first access to the record. |
| Actn. | Check for the above causes and correct any errors. |

NAT0046: Error in parameter field list for UPDATE or STORE.

| Text | Error in parameter field list for UPDATE or STORE. |
|-------|--|
| - | Only fields from one file may be updated with one UPDATE or STORE statement. Values for fields may be constants, the contents of user-defined variables, or the contents of a database fields. |
| Actn. | Check the parameter list and correct any errors. |

NAT0047: Error in variable definition.

| Text | Error in variable definition. |
|-------|--|
| Expl. | One of the following errors was detected: |
| | - In an OBTAIN statement, the field referenced was not contained |
| | within a database array. |
| | - An error in a statement reference and/or field length notation |
| | was detected. |
| | - An error in the index notation was detected. |
| | OBTAIN ARRAY (1:5) -> valid |
| | OBTAIN ARRAY (#I:#J) -> INVALID |
| | OBTAIN ARRAY (#I:#I + 9) -> valid |
| Actn. | Correct error. |

NAT0048: Illegal format combination of field/value in UPDATE/STORE.

| Text | Illegal format combination of field/value in UPDATE/STORE. |
|-------|--|
| | The value assignment for field/value combinations in the parameter list is performed individually for each combination according to the general rules for value assignment. An attempt was made to assign a value of one format to a field of incompatible format. |
| Actn. | Check program and correct error. |

NAT0049: Error in value entry for UPDATE or STORE.

| Text | Error in value entry for UPDATE or STORE. |
|-------|--|
| | The value in an UPDATE or STORE statement may be specified as a constant or as the content of a user-defined variable or database field. If a database field is used as a value, it must reference a currently active FIND/READ/GET loop. |
| Actn. | Check program and correct error. |

NAT0050: Error in reference for GET SAME statement.

| Text | Error in reference for GET SAME statement. |
|-------|--|
| | The GET SAME statement refers by default to the last active access to the database; a reference to another specific database access may be explicitly specified. If an explicit reference is used, the database access must still be active. |
| Actn. | Correct the error in the GET SAME reference. |

Natural System Error Messages 0051-0100

NAT0051: Error in field reference in GET statement.

| Text | Error in field reference in GET statement. |
|-------|--|
| | One of the following errors was detected in a GET statement: - A field referenced is not contained in the specified file. - An invalid index notation for a database array was used. |
| Actn. | Check program and correct error. |

NAT0052: Invalid ISN value specified in GET or READ statement.

| Text | Invalid ISN value specified in GET or READ statement. |
|-------|---|
| | The ISN value in a GET or READ statement must be specified as an integer numeric constant, a user-defined variable, or via the Natural system variable *ISN. If you use *ISN, you must specify the statement label or source-code line number (r) of the database statement that was used to originally read the record with that ISN. |
| Actn. | Correct error in program. |

NAT0053: No more than one WRITE TITLE/TRAILER allowed per report.

| Text | No more than one WRITE TITLE/TRAILER allowed per report. |
|-------|---|
| | Only one WRITE TITLE statement and one WRITE TRAILER statement may be specified per report. |
| Actn. | Check the report references of the WRITE TITLE/TRAILER statements. |

NAT0054: Error in entry for Natural system function.

| Text | Error in entry for Natural system function. |
|-------|---|
| | A Natural system function is indicated by an asterisk (*). The name of a valid Natural system function must follow the asterisk. Example: MOVE *MAX (SALARY) TO RICHPERSON |
| Actn. | Check program and correct error. |

NAT0055: Error in argument variable for Natural system function.

| Text | Error in argument variable for Natural system function. |
|------|---|
| | The argument entry for a Natural system function may be a previously defined user-defined variable, or a database field. |
| | Check program and correct error. |

NAT0056: SORT statement used incorrectly.

| Text | SORT statement used incorrectly. |
|-------|--|
| Expl. | The SORT statement may only be used within an active processing |
| | loop. |
| | A SORT statement may not be placed within a processing loop |
| | that was initiated by another SORT statement. |
| | If a program contains multiple SORT statements, all must include |
| | a USING clause. |
| Actn. | Correct error. |

NAT0057: Invalid number specified in WITH LIMIT clause.

| Text | Invalid number specified in WITH LIMIT clause. |
|-------|--|
| Expl. | The number representing the limit of records selected for further processing was specified incorrectly. It may be specified either as a numeric constant or as the content of a numeric variable that has been previously defined; for example: WITH LIMIT (123) or WITH LIMIT (#LMT) |
| Actn. | Correct error in program. |

NAT0058: Number of records to be processed not specified correctly.

| Text | Number of records to be processed not specified correctly. |
|-------|---|
| Expl. | The number of records to be processed in a processing loop initiated by FIND, READ or HISTOGRAM statement may be limited. The limit is specified as (n) where n is either a numeric constant or the name of a previously defined numeric variable. |
| Actn. | Correct error. |

NAT0059: Incorrect field specification in WHERE clause.

| Text | Incorrect field specification in WHERE clause. |
|-------|--|
| | Probable causes of this message are: - an error in the specified name; - a reference to a Natural system function which has not yet been evaluated; - a new variable has been defined where not allowed. |
| Actn. | Correct error. |

NAT0060: Incorrect variable specification in logical criteria.

| Text | Incorrect variable specification in logical criteria. |
|-------|--|
| - | The left portion of a relational expression was specified incorrectly. This error may be caused by misspelling a variable name or keyword in a statement that follows the relational expression. |
| Actn. | Check program and correct error. |

NAT0061: Error in GIVING value of ADD/MULTIPLY/SUBTRACT/DIVIDE.

| Text | Error in GIVING value of ADD/MULTIPLY/SUBTRACT/DIVIDE. |
|-------|---|
| | After the word "GIVING" in an ADD, MULTIPLY, SUBTRACT or DIVIDE statement, a valid notation for a variable reference must be specified. A user-defined variable or a database field may be used. |
| Actn. | Correct error. |

NAT0062: Invalid receiving field in MOVE statement.

| Text | Invalid receiving field in MOVE statement. |
|-------|--|
| Expl. | A valid notation for a variable reference must be specified after the word "TO" in a MOVE statement. A user-defined variable or a database field may be used. MOVE LEFT/RIGHT JUSTIFIED is not allowed if the receiving field is a system variable. For MOVE with SUBSTR() operand(s) the following applies: - The SUBSTR argument field must be alphanumeric or binary. - Move of numeric field (type N) to binary SUBSTR() not allowed. - Parameter "(PM=I)" not allowed if the receiving field is binary. - Move of SUBSTR() to receiving field other than type A/B not allowed. - Use of option LEFT/RIGHT JUSTIFIED is not allowed. |
| Actn. | Correct the error. |

NAT0063: Error in the argument for a Natural system function.

| Text | Error in the argument for a Natural system function. |
|-------|--|
| Expl. | The argument for a system function in a WRITE or DISPLAY statement following an AT BREAK/END DATA condition was specified incorrectly. Either a user-defined variable or a database field may be used. If a user-defined variable is used, it must have been previously defined. If a database field is used, it must be available within an active processing loop. For a database field which is contained within an array, a single index (one-dimensional array) or a range of indexes (two-dimensional array) may be used. |
| Actn. | Check program and correct error. |

NAT0064: Invalid parameter operand.

| Text | Invalid parameter operand. |
|-------|---|
| Expl. | In a CALL or SEND METHOD statement an invalid operand was specified as parameter. In a PROCESS GUI or PROCESS REPORTER statement the parameter operand violates the required parameter description of the appropriate action. In a OPEN DIALOG or SEND EVENT statement the parameter operand does not match the parameter definition of the appropriate dialog. |
| Actn. | Check parameter operand. |

NAT0065: Group or periodic group referenced in VERT mode.

| Text | Group or periodic group referenced in VERT mode. |
|-------|---|
| Expl. | Groups and periodic groups may only be referenced in a DISPLAY statement in HORIZONTAL mode because a group needs a layout of columns that requires multiple lines. Make sure that the display mode is set to "HORIZ" before referencing a group or periodic group. |
| Actn. | Check program and correct error. |

NAT0066: Error in constant specification for LIMIT statement.

| Text | Error in constant specification for LIMIT statement. |
|-------|---|
| Expl. | The value for the LIMIT statement may be specified as a numeric |
| | constant only. |
| Actn. | Check program and correct error. |

NAT0067: Error in control value specification of FOR statement.

| Text | Error in control value specification of FOR statement. |
|-------|---|
| Expl. | The control value must be numeric and may be specified as a constant, user-defined variable or database field. The TO value may be specified as a numeric constant, user-defined variable, or database field. Any database field used must be available via an active processing loop. |
| Actn. | Check program and correct error. |

NAT0068: Parameter error in GLOBALS command.

| Text | Parameter error in GLOBALS command. |
|-------|--|
| | Parameters in the GLOBALS command must be specified with a parameter identification and a valid argument for the parameter. See the Natural system commands and session parameters documentation for further information. |
| Actn. | Check program and correct error. |

NAT0069: Error in search criteria involving COUPLED clause.

| Text | Error in search criteria involving COUPLED clause. |
|-------|---|
| | The COUPLED clause of a FIND statement may be used to specify a search which involves the Adabas coupling facility. A maximum of four COUPLED clauses may be used. See the Natural FIND statement documentation for further information. |
| Actn. | Check program and correct error. |

NAT0070: GIVE SYSTEM FUNCTIONS allowed only once per report.

| Text | GIVE SYSTEM FUNCTIONS allowed only once per report. |
|-------|---|
| | The GIVE SYSTEM FUNCTIONS clause, which is used to cause the evaluation of Natural system functions for subsequent use in an AT END OF PAGE condition, may only be used once for a given report. See the Natural DISPLAY statement documentation for further information. |
| Actn. | Check program and correct error. |

NAT0071: Invalid name defined.

| Text | Invalid name defined. |
|-------|--|
| Expl. | The name of a subroutine must conform to the same rules which |
| | apply to user-defined variables (as described in the Natural |
| | documentation under "User-Defined Variables"). |
| | The name of a class, a prototype or a function must also conform |
| | to these rules, except that it is allowed to use a period in a |
| | class/prototype name. |
| Actn. | Correct the name definition. |

NAT0072: A subroutine with the same name already exists.

| Text | A subroutine with the same name already exists. |
|------|--|
| | You have used one subroutine name for two subroutines. However, subroutine names within a program must be unique. Or, you have tried to pass a parameter to an internal subroutine. You can only pass parameters to external subroutines. |
| | Check names of defined subroutines. Check parameter passing. |

NAT0073: Sort field error; field has not previously been defined.

| Text | Sort field error; field has not previously been defined. |
|-------|---|
| Expl. | The fields used as sort criteria in a SORT statement must be user-defined variables which have been previously defined, or database fields which are available within an active processing loop. The same field may not be referenced twice in the SORT key fields or the USING clause. See the Natural SORT statement documentation for further information. |
| Actn. | Check program and correct error. |

NAT0074: Incorrect specification of PERFORM SUBROUTINE statement.

| Text | Incorrect specification of PERFORM SUBROUTINE statement. |
|-------|--|
| Expl. | The name of the subroutine must not be enclosed in apostrophes. If the PERFORM statement is used to invoke an inline subroutine, explicit parameters to be passed to the subroutine must not be specified with the statement. |
| Actn. | Check program and correct error. |

NAT0075: RETURN or END-SUBROUTINE misplaced.

| Text | RETURN or END-SUBROUTINE misplaced. |
|-------|--|
| | This error occurs under one of the following conditions: 1) A RETURN or END-SUBROUTINE was found, although there is no corresponding DEFINE SUBROUTINE. 2) A subroutine is empty, that is, there is no statement within the DEFINE SUBROUTINE statement block. |
| Actn. | Check program and correct error. |

NAT0076: The assigned work file is not available or not defined.

| Text | The assigned work file is not available or not defined. |
|-------|---|
| Expl. | In a batch environment, work files must be defined by providing JCL statements which identify the referenced work file. In an online environment that supports work files, work files must be defined via the setup parameters when starting the Natural session. |
| Actn. | Check program to determine if work file specified correctly. If so, contact your Natural administrator for further information on work file assignment/availability. |

NAT0077: Error in data field for READ/WRITE WORK FILE statement.

| Text | Error in data field for READ/WRITE WORK FILE statement. |
|-------|---|
| Expl. | Data fields may be specified as database fields or as user-defined variables. If the RECORD option is used, the variables must not have been previously defined and dynamic variables (if available) are not allowed. If the SELECT option is used, the variables may have been previously defined. Numeric constants may also be used with WRITE WORK FILE. |
| Actn. | Check program and correct error. |

NAT0078: Error in "FILLER nX" specification for READ WORK FILE.

| Text | Error in "FILLER nX" specification for READ WORK FILE. |
|-------|---|
| | A filler may be specified in the definition of the data layout by using the notation "FILLER nX", where n is an integer number. |
| Actn. | Check program and correct error. |

NAT0079: Invalid specification of AT END OF FILE clause.

| Text | Invalid specification of AT END OF FILE clause. |
|-------|---|
| Expl. | The specification of the AT END OF FILE clause in a READ WORK FILE statement is only permitted if the ONCE option has also been specified. If the ONCE option is not specified, a normal processing loop is created with the end-of-file condition being handled as normal loop termination. |
| Actn. | Check program and correct error. |

NAT0080: Command / program name must start with a letter.

| Text | Command / program name must start with a letter. |
|-------|---|
| | The command - or the name of the program to be executed - you entered began with an invalid character. The first character of a system command or program name must be an alphabetical character, not a number or a special character. |
| Actn. | Enter a valid command or program name. |

NAT0081: Program name missing in READ command.

| Text | Program name missing in READ command. |
|-------|--|
| Expl. | The READ command reads a source object from the active Natural library |
| | (or optionally from the library specified with the command) |
| | into the editor work area appropriate for the object type. |
| | The correct syntax of the command is: |
| | READ object-name <library id=""></library> |
| | library ID must not be specified if Natural Security is active. |
| | library ID must not begin with "SYS" (except SYSTEM). |
| Actn. | Enter READ command with a valid object name. |

NAT0082: Invalid command, or :1: :2: does not exist in library.

| Text | Invalid command, or does not exist in library. |
|-------|---|
| Expl. | One of the following has occurred: |
| | - You entered a value in the command line which is neither a |
| | Natural command nor the name of a Natural program contained |
| | in the active library or in a library defined as a steplib. |
| | - An object which is required during execution of a program, |
| | subprogram, subroutine or helproutine is not contained in |
| | the active library or in a library defined as a steplib. |
| | - Your Natural session is currently applying system files other |
| | than those containing the object you specified. |
| Actn. | Check to ensure that you entered a valid Natural command or the name of an existing Natural object. Use the command SYSPROF to check whether you are using the correct system file. |

NAT0083: SAVE or CATALOG command issued when work area empty.

| Text | SAVE or CATALOG command issued when work area empty. |
|-------|---|
| Expl. | An object can only be SAVEd/CATALOGed from the editor work area. An object can be brought into the work area with a READ or EDIT command. (The command "RUN program-name" will also read the source of the program called "program-name" into the editor work area, before compiling and executing it.) |
| Actn. | Use READ or EDIT prior to using SAVE/CATALOG. |

NAT0084: Object name already exists; SAVE/CATALOG not executed.

| Text | Object name already exists; SAVE/CATALOG not executed. |
|-------|--|
| | Natural requires that object names be unique. An object cannot be SAVEd or CATALOGed under a name which has already been given to another object. |
| Actn. | Either choose a different name for the object to be SAVEd/CATALOGed, or RENAME/PURGE/UNCATALOG/SCRATCH the existing object of that name before issuing the SAVE/CATALOG command. |

NAT0085: Invalid program name specified in SAVE/CATALOG command.

| Text | Invalid program name specified in SAVE/CATALOG command. |
|-------|--|
| | A program name must begin with an alphabetical character and must not be longer than 8 characters. |
| Actn. | Enter a valid program name. |

NAT0086: READ WORK FILE ONCE not allowed in AT END OF FILE.

| Text | READ WORK FILE ONCE not allowed in AT END OF FILE. |
|-------|---|
| Expl. | A READ WORK FILE ONCE statement is not permitted within an AT END OF FILE clause. See the Natural READ WORK FILE statement documentation for more information. |
| Actn. | Correct error. |

NAT0087: Invalid parameters for USING in DEFINE DATA statement.

| Text | Invalid parameters for USING in DEFINE DATA statement. |
|-------|--|
| Expl. | The USING clause of the DEFINE DATA statement contains invalid |
| | parameters. |
| Actn. | Correct error. |

NAT0088: RUN command issued without program in work area.

| Text | RUN command issued without program in work area. |
|-------|--|
| Expl. | If there is a program in the editor work area, you can issue the RUN command without program name so as to compile and execute that program. If the editor work area is empty, you must specify a program name with the RUN command, so as to read a program into the work area, from where it is compiled and executed. |
| Actn. | Specify a program name with the RUN command, or read the source program into the work area with a READ or EDIT command before issuing RUN. |

NAT0089: CHECK command issued, but no program in work area.

| Text | CHECK command issued, but no program in work area. |
|-------|---|
| Expl. | The CHECK command can only be used after a source program has been read into the source work area with an EDIT, READ, or RUN command. |
| | Use EDIT or READ to place program in source work area before issuing a CHECK command. |

NAT0090: Sub-/superdescriptor cannot be used in THRU clause.

| Text | Sub-/superdescriptor cannot be used in THRU clause. |
|-------|---|
| Expl. | A subdescriptor or superdescriptor must not be used in a THRU clause. The REDEFINE statement may be used to create a variable which may be used in the THRU clause. A HISTOGRAM statement may be used to read the values of the sub- or superdescriptor in sequence, followed by a FIND statement using each value read to retrieve the records. |
| Actn. | Check program and correct error. |

NAT0091: Only "ON" or "OFF" allowed with UPDATE command.

| Text | Only "ON" or "OFF" allowed with UPDATE command. |
|-------|--|
| | The UPDATE command may be used to disable or enable database updating: - "UPDATE ON" enables updating of the database. - "UPDATE OFF" disables updating of the database. Other command options are not allowed with the UPDATE command. |
| Actn. | Enter the command "UPDATE ON" or "UPDATE OFF". |

NAT0092: Invalid/missing block name in DEFINE DATA statement.

| Text | Invalid/missing block name in DEFINE DATA statement. |
|-------|--|
| | One of the following errors was detected while processing the block name of a data block contained within a global data area: - An error in block naming conventions was detected. - The data block specified was not found in the current global data area. |
| Actn. | Check program and correct error. |

NAT0094: Invalid initial value definition in DEFINE DATA statement.

| Text | Invalid initial value definition in DEFINE DATA statement. |
|-------|---|
| Expl. | The definition of initial values in the DEFINE DATA statement |
| | is invalid. Note in particular that the Natural |
| | session parameter DTFORM must correspond to the |
| | value definition in the DEFINE DATA statement. |
| | For example: |
| | DTFORM=U and a D"YYYY-MM-DD" constant would cause an error. |
| | Moreover, a numeric initial value must not have more precision or |
| | scale digits than defined in the variable. |
| | For example: 1 #FLD1 (N2.2) INIT <12.345> causes an error. |
| | 1 #FLD2 (N2.2) INIT <123.45> causes an error. |
| Actn. | Correct error. |

NAT0095: Only alpha constant/field allowed for text in (RE)INPUT.

| Text | Only alpha constant/field allowed for text in (RE)INPUT. |
|-------|--|
| Expl. | The "text" in an INPUT or REINPUT statement can be specified with an alphanumeric constant, a previously defined alphanumeric variable, or an alphanumeric database field. |
| Actn. | Check that the variable used is defined as alphanumeric format or that the text constant is enclosed in apostrophes. |

NAT0096: Invalid use of GLOBAL in DEFINE DATA statement.

| Text | Invalid use of GLOBAL in DEFINE DATA statement. |
|-------|--|
| | "USING gda-name" is required after the keyword "GLOBAL" when referencing a global data area in a DEFINE DATA statement. |
| Actn. | Correct error. |

NAT0097: Invalid variable definition in REDEFINE statement.

| Text | Invalid variable definition in REDEFINE statement. |
|-------|---|
| | The variable definition is invalid for one or both of the following reasons: - invalid format specification; - invalid field length specification. |
| Actn. | Correct error. |

NAT0098: At least one field required for RESET statement.

| Text | At least one field required for RESET statement. |
|-------|---|
| | The RESET statement requires that at least one variable be specified after the keyword RESET (or after the keyword INITIAL, if this is used). |
| Actn. | Correct error. |

NAT0099: Field error in a COMPRESS statement.

| Text | Field error in a COMPRESS statement. |
|-------|---|
| | The COMPRESS statement compresses multiple field/literal values into another field. At least one value to be compressed must be specified. The value specified must be either a literal constant or an alphanumeric field. |
| Actn. | Correct error. |

NAT0100: Format "C" or "L" not allowed with COMPRESS or MOVE ALL.

| Text | Format "C" or "L" not allowed with COMPRESS or MOVE ALL. |
|-------|---|
| Expl. | Multiple values may be compressed into one receiving field by use of a COMPRESS statement. The field whose values are compressed must not be of format "C" or "L". One value may be moved more than once to a receiving field with a MOVE ALL statement. The value to be moved must be of alphanumeric (A) or unpacked numeric (N) format. |
| Actn. | Correct error. |

4

Natural System Error Messages 0101-0150

NAT0102: Error in reference to Natural system function in SORT.

| Text | Error in reference to Natural system function in SORT. |
|-------|---|
| | Only the system functions MAX, MIN, AVER, TOTAL may be evaluated. The values of these functions may be referenced after the sort operation in the form *FUNCTION(variable). Example: MOVE *TOTAL(SALARY) TO PAYROLL-TOTAL(N8) |
| Actn. | Correct error. |

NAT0103: Error in receiving field for COMPRESS statement.

| Text | Error in receiving field for COMPRESS statement. |
|-------|---|
| | In a COMPRESS statement, the word "INTO" (or "TO") must be followed by a valid field name to indicate where the result is to be placed. The receiving field must be of alphanumeric (A) format. |
| Actn. | Correct error. |

NAT0104: Multiple loop-initiating statements in the same line.

| Text | Multiple loop-initiating statements in the same line. |
|-------|---|
| - | Only one loop-initiating statement may be specified in a single source code line. |
| Actn. | Enter each loop-initiating statement in a separate line. |

NAT0105: Database updating not permitted.

| Text | Database updating not permitted. |
|-------|--|
| | The Natural administrator has disabled updating of the specified database. No programs with database-update functions can be created. |
| Actn. | Contact your Natural administrator. |

NAT0106: SAVE/CATALOG/STOW/PURGE/UNCATALOG/SCRATCH not available.

| Text | SAVE/CATALOG/STOW/PURGE/UNCATALOG/SCRATCH not available. |
|-------|--|
| | Your Natural administrator has set the profile parameters ROSY and/or RECAT so that the system commands SAVE, CATALOG, STOW, PURGE, UNCATALOG, SCRATCH cannot be used. |
| Actn. | Contact your Natural administrator. |

NAT0107: No more than 2000 bytes may be specified for ET data.

| Text | No more than 2000 bytes may be specified for ET data. |
|-------|--|
| Expl. | An END TRANSACTION statement was issued in which more than the |
| | maximum of 2000 bytes of user data were provided. |
| Actn. | Reduce the amount of ET data. |

NAT0108: Error in group reference in WRITE WORK FILE statement.

| Text | Error in group reference in WRITE WORK FILE statement. |
|-------|--|
| | An error was detected during the processing of individual fields that are referenced via a group name. |
| Actn. | Check group definition. |

NAT0109: Invalid reference in GET SAME or UPDATE statement.

| Text | Invalid reference in GET SAME or UPDATE statement. |
|-------|--|
| | The GET SAME or UPDATE statement can only refer back to a database-access statement, such as FIND, READ or GET, which is currently active; that is, the processing loop for that database access must still be open. |
| Actn. | Correct error. |

NAT0110: No source text allowed after the END statement.

| Text | No source text allowed after the END statement. |
|-------|--|
| Expl. | The END statement indicates the end of the source of a Natural object. |
| | No other statements or comment lines are allowed after the END |
| | statement. |
| | A probable cause of this error is the misspelling of a name or the |
| | omission of "PAGE", "DATA", "TRANSACTION" from the statements |
| | AT END OF PAGE, AT END OF DATA, END TRANSACTION respectively; |
| | or a missing hyphen in END-DEFINE, END-FIND, END-IF etc. |
| Actn. | Correct error. |

NAT0111: Function only available with :1:.

| Text | Function only available with |
|-------|---|
| Expl. | You have specified a function which is currently not available, because the required Software AG product or component is - not installed in your Natural FNAT system file or - not linked to your Natural nucleus or - not available for dynamic invoking. For example, the use of the system command MAIL would lead to this error if Natural Security is not installed. |
| Actn. | Contact your Natural administrator. |

NAT0112: Invalid use of group name.

| Text | Invalid use of group name. |
|-------|---|
| | A group name must not be specified in this statement; specify elementary fields instead. |
| Actn. | Correct error in program. |

NAT0114: Error in SET KEY statement construction.

| Text | Error in SET KEY statement construction. |
|-------|--|
| | See the Natural documentation for information on the valid syntax for the SET KEY statement. |
| Actn. | Correct error in program. |

NAT0115: Error in variable definition for GET TRANSACTION DATA.

| Text | Error in variable definition for GET TRANSACTION DATA. |
|-------|--|
| Expl. | This error is usually the result of a misspelt variable name. In the GET TRANSACTION DATA statement, all types of variables of all formats are allowed. Variables may either be newly defined in the GET TRANSACTION DATA statement or may be referenced from a previous definition. |
| Actn. | Check program and correct error. |

NAT0116: Incorrect "/n/" specification in AT BREAK statement.

| Text | Incorrect "/n/" specification in AT BREAK statement. |
|-------|--|
| Expl. | The "/n/" notation in an AT BREAK statement or an IF BREAK condition was specified incorrectly. "n" must be specified as a numeric constant, with a value in the range 1-253, enclosed in slashes (/) without any leading or trailing blank characters. Example: AT BREAK OF POST-CODE /5/ . IF BREAK OF BIRTH /2/ |
| Actn. | Correct error. |

NAT0117: Word "IDENTICAL" missing in SUSPEND IDENTICAL SUPPRESS.

| Text | Word "IDENTICAL" missing in SUSPEND IDENTICAL SUPPRESS. |
|-------|---|
| - | The word "IDENTICAL" specifies the action to be taken for the suppress operation and is therefore required. |
| Actn. | Correct error. |

NAT0118: Value assigned to function key not format "A".

| Text | Value assigned to function key not format "A". |
|-------|--|
| | The value to be assigned to a function key must be specified as a literal constant, or by a user-defined variable with format "A". |
| Actn. | Correct error. |

NAT0119: Invalid format for UNTIL value in MOVE ALL statement.

| Text | Invalid format for UNTIL value in MOVE ALL statement. |
|-------|--|
| | The format of the value provided with the UNTIL option must be either - a positive integer constant value or - a variable of type "Integer" or - a variable of type "Numeric/Packed" without decimal digits. The usage of system-variables is not permitted. |
| Actn. | Correct error. |

NAT0121: This statement is not permitted in structured mode.

| Text | This statement is not permitted in structured mode. |
|-------|---|
| Actn. | Do not use this statement, or switch to reporting mode. |

NAT0122: Only format A, C or L allowed for fields in IF SELECTION.

| Text | Only format A, C or L allowed for fields in IF SELECTION. |
|-------|---|
| | The IF SELECTION statement may only be used to check the content of alphanumeric, attribute control and logical fields for non-blank contents. Only operands of the same type can be checked. |
| Actn. | Correct error. |

NAT0123: Error in field specification for IF SELECTION statement.

| Text | Error in field specification for IF SELECTION statement. |
|-------|---|
| Expl. | At least one field must be specified in the IF SELECTION statement. |
| Actn. | Correct error. |

NAT0124: Error in index notation for MOVE INDEXED statement.

| Text | Error in index notation for MOVE INDEXED statement. |
|-------|--|
| | The index must be specified as a numeric constant or a user-defined variable defined with format "N". Examples: MOVE INDEXED #A <5> TO #B <2> MOVE INDEXED #A <#INDEX> TO #B <#INDEX> |
| Actn. | Correct error. |

NAT0125: No or invalid output element following DISPLAY/WRITE/INPUT.

| Text | No or invalid output element following DISPLAY/WRITE/INPUT. |
|-------|---|
| - | At least one element must be specified in a DISPLAY, WRITE or INPUT statement. |
| | A possible cause for the error is a misspelt variable name that conflicts with the name of a Natural statement. |
| Actn. | Check program and correct error. |

NAT0126: Error in qualification of variable.

| Text | Error in qualification of variable. |
|-------|---|
| Expl. | Only one level of qualification is allowed. |
| Actn. | Check program and correct error. |

NAT0127: The word "AS" is missing in FIND AND RETAIN AS.

| Text | The word "AS" is missing in FIND AND RETAIN AS. |
|-------|---|
| Expl. | The word "AS" identifies that a RETAIN SET operation is to be performed and it must therefore be specified. |
| Actn. | Add the word "AS" to the RETAIN clause of the FIND statement. |

NAT0128: Value to be used to identify set must be of format "A".

| Text | Value to be used to identify set must be of format "A". |
|-------|--|
| Expl. | The value used in a RETAIN clause to identify a set of records may be specified either as an alphanumeric constant or the content of an alphanumeric variable. This error may also occur if the WITH clause of a FIND statement contains a non-descriptor. |
| Actn. | Check program and correct error. |

NAT0129: The specified set name is longer than 32 characters.

| Text | The specified set name is longer than 32 characters. |
|-------|---|
| Expl. | The name for a set in a RETAIN AS clause may be specified as an alphanumeric constant or the content of an alphanumeric variable. The set name must not be longer than 32 characters. |
| Actn. | Check program and correct error. |

NAT0130: No "/" allowed immediately before keywords HORIZ or VERT.

| Text | No "/" allowed immediately before keywords HORIZ or VERT. |
|-------|---|
| Expl. | The keywords HORIZ(ONTALLY) and VERT(ICALLY) indicate the initiation of |
| | a new output column. As a new column cannot be placed underneath an |
| | already processed column, the character "/" - which indicates that the |
| | next element is to be placed under the previous one - cannot be used |
| | before the keywords HORIZ, VERT, HORIZONTALLY, VERTICALLY. |
| Actn. | Check program and correct error. |

NAT0131: GET TRANSACTION DATA needs at least one variable.

| Text | GET TRANSACTION DATA needs at least one variable. |
|-------|---|
| | The GET TRANSACTION DATA statement must contain at least one variable in which the transaction data can be placed. This error may be caused by a misspelt variable name or by an invalid character in a variable name. |
| Actn. | Check program and correct error. |

NAT0132: Operand not defined or not of alphanumeric/binary format.

| Text | Operand not defined or not of alphanumeric/binary format. |
|-------|---|
| - | The variable that is examined in an EXAMINE statement must have been defined before, and it must be of alphanumeric or binary format. |
| Actn. | Check program and correct error. |

NAT0134: Error in NUMBER option of EXAMINE statement.

| Text | Error in NUMBER option of EXAMINE statement. |
|-------|---|
| | The error may be caused by misspelling a variable name. The NUMBER variable must be of a numeric format ("N", "P" or "I"). The NUMBER variable must be an integer. See the Natural EXAMINE statement documentation for further information. |
| Actn. | Correct error in program. |

NAT0135: DELETE/REPLACE/GIVING clause missing in EXAMINE statement.

| Text | DELETE/REPLACE/GIVING clause missing in EXAMINE statement. |
|-------|--|
| Expl. | The EXAMINE statement requires at least one of the following |
| | clauses: |
| | REPLACE |
| | DELETE |
| | GIVING NUMBER |
| | GIVING POSITION |
| | GIVING LENGTH |
| | GIVING INDEX |
| | See the Natural EXAMINE statement documentation for further |
| | information. |
| Actn. | Correct error in program. |

NAT0136: Error in EXAMINE TRANSLATE statement.

| Text | Error in EXAMINE TRANSLATE statement. |
|-------|--|
| | In an EXAMINE TRANSLATE statement, the keyword "TRANSLATE" must be followed by "INTO UPPER", "INTO LOWER", or a USING clause. See the Natural documentation for further information on the EXAMINE TRANSLATE statement. |
| Actn. | Correct error in program. |

NAT0137: No object specified in RELEASE statement.

| Text | No object specified in RELEASE statement. |
|-------|---|
| | Possible objects to be released are: STACK - release all data items from the stack. PARAMETERS - release all parameters built during the session. SETS - release all FIND sets. SET set name - release one specific FIND set. |
| Actn. | Check program and correct error. |

NAT0138: Identifier for FIND set must be alpha and <= 32 bytes.

| Text | Identifier for FIND set must be alpha and <= 32 bytes. |
|-------|--|
| Expl. | The identifier may be specified as an alphanumeric constant or the contents of an alphanumeric variable. The contents of the variable will be used to identify the FIND set. The alphanumeric value can only be up to 32 bytes long because this is the maximum length of a FIND set identification. |
| Actn. | Check program and correct error. |

NAT0139: At least 1 data item must be specified in STACK statement.

| Text | At least 1 data item must be specified in STACK statement. |
|-------|---|
| | Constants or variables of the formats "A", "N" or "B" may be used as data items in a STACK statement. At least one of these items must be present in a STACK statement. |
| Actn. | Check program and correct error. |

NAT0140: "NOT" is only possible after "AND" operation.

| Text | "NOT" is only possible after "AND" operation. |
|-------|--|
| Expl. | Exclusion of a set can only be done when the set name is preceded by the logical operator "AND" and followed by the operator "NOT". The set will then be excluded from the number of records that were selected up to that point. |
| Actn. | Restructure the logical criteria to place the set to be excluded after an AND operation. |

NAT0141: Invalid keyword specified in SET GLOBALS statement.

| Text | Invalid keyword specified in SET GLOBALS statement. |
|-------|--|
| | The valid keywords for the SET GLOBALS statement are described in the Natural documentation. |
| Actn. | Check program and correct error. |

NAT0142: Invalid value for keyword in SET GLOBALS statement.

| Text | Invalid value for keyword in SET GLOBALS statement. |
|-------|---|
| Expl. | The value for a SET GLOBALS keywords can be supplied as a constant or as a variable. If a constant is supplied, it must be alphanumeric or numeric and have a correct value; for example: PS must be numeric and in the range from 0 to 250. If a variable is supplied, it must also be of the correct type. If it is numeric, it must be an integer. See the Natural documentation for further information on the SET GLOBALS statements. |
| Actn. | Check program and correct error. |

NAT0143: Invalid format for value in SET GLOBALS statement.

| Text | Invalid format for value in SET GLOBALS statement. |
|-------|---|
| - | The SET GLOBALS keyword in question requires an alphanumeric value. The alphanumeric value can be specified as a constant or as the content of an alphanumeric variable (format A). |
| Actn. | Check program and correct error. |

NAT0145: Invalid format for value in SET GLOBALS statement.

| Text | Invalid format for value in SET GLOBALS statement. |
|-------|--|
| Expl. | See the Natural session parameters documentation to determine the possible values for the SET GLOBALS keywords. Valid formats are integer numeric for keywords whose values are numeric and alphanumeric for keywords whose possible values are "ON/OFF" or alphanumeric characters. The values "T/F" may be used as synonyms for "ON/OFF" respectively. For example: SET GLOBALS EJ=OFF has the same meaning as SET GLOBALS EJ=F |
| Actn. | Check program and correct error. |

NAT0146: Invalid syntax in SET GLOBALS statement.

| Text | Invalid syntax in SET GLOBALS statement. |
|-------|---|
| | The syntax of the SET GLOBALS statement requires that each parameter be followed by the assignment character "=", which in turn is to be followed by the value for the parameter. |
| Actn. | Check program and correct error. |

NAT0147: No command supplied in STACK statement.

| Text | No command supplied in STACK statement. |
|-------|---|
| | The COMMAND option of the STACK statement was specified, but no command was provided. |
| Actn. | Check program and correct error. |

NAT0148: Invalid format for variable in TERMINATE statement.

| Text | Invalid format for variable in TERMINATE statement. |
|-------|--|
| | Only variables of format "N", "I" or "P" are permitted with the TERMINATE statement. The value must lie between 0 and 255. |
| Actn. | Check program and correct error. |

NAT0149: Format error in MOVE EDITED statement.

| Text | Format error in MOVE EDITED statement. |
|-------|---|
| - | A field used in a MOVE EDITED statement for which an edit mask has not been defined, must be defined with alphanumeric (A), binary (B) or Unicode (U) format. |
| Actn. | Check program and correct error. |

NAT0150: Edit mask missing in MOVE EDITED statement.

| Text | Edit mask missing in MOVE EDITED statement. |
|-------|--|
| - | A MOVE EDITED statement requires the specification of an |
| | edit mask for the sending field or the receiving field. |
| Actn. | Check program and correct error. |

Natural System Error Messages 0151-0200

NAT0151: Invalid map name in INPUT statement.

| Text | Invalid map name in INPUT statement. |
|-------|--|
| | The name of a map to be used in an INPUT statement can be specified as a literal constant or the content of an alphanumeric variable. If a variable is used, it must have been previously defined. |
| Actn. | Check program and correct error. |

NAT0152: Invalid map format in INPUT statement.

| Text | Invalid map format in INPUT statement. |
|-------|---|
| | The name of a map to be used in an INPUT statement may be specified as a literal alphanumeric constant or the content of an alphanumeric variable. If a variable is used, it must have been previously defined. |
| Actn. | Check program and correct error. |

NAT0153: Format definition not allowed for a group name.

| Text | Format definition not allowed for a group name. |
|-------|--|
| Expl. | A group name is used to refer to a collection of fields as a single structure. Since this structure is defined by the formats of these fields, the group name need not have a format definition. If a field of one format is to be redefined as fields of differing formats, the REDEFINE statement should be used. Another possible cause of this error is that the level number of the next variable definition is higher than that of the variable marked, although both variables should probably be at the same level. |
| Actn. | Remove the format definition at the group name level, or make sure that the level numbers are correct. |

NAT0155: Map name must not be longer than 7 characters.

| Text | Map name must not be longer than 7 characters. |
|-------|---|
| - | A map name can be specified as a literal constant or the content of an alphanumeric variable. The maximum length of a map name is 7 characters. |
| Actn. | Check program and correct error. |

NAT0158: Invalid group specification in MOVE BY NAME statement.

| Text | Invalid group specification in MOVE BY NAME statement. |
|-------|---|
| | The operands to be specified in a MOVE BY NAME statement must be valid and existing group names. They may also be user views. Individual field names cannot be specified. If a user view is used, it must not be qualified with a statement label or source-code line number. |
| Actn. | Check program and correct error. |

NAT0159: Fields in MOVE BY NAME or MOVE BY POSITION do not match.

| Text | Fields in MOVE BY NAME or MOVE BY POSITION do not match. |
|-------|---|
| Expl. | For MOVE BY NAME no matching names were found. At least one field with the same name must exist in both groups. For MOVE BY POSITION the number of fields in the referenced groups do no match. |
| Actn. | Check program and correct error. |

NAT0160: Invalid descriptor in READ LOGICAL statement.

| Text | Invalid descriptor in READ LOGICAL statement. |
|-------|---|
| Expl. | Descriptors that are multiple-valued are not permitted in the THRU or ENDING AT clause of a READ statement. Phonetic descriptors must not be used in a READ statement. A field contained in a PE-group may not be used as search-field in a READ statement. |
| Actn. | Check program and correct error. |

NAT0161: ROUNDED clause not allowed with DIVIDE REMAINDER.

| Text | ROUNDED clause not allowed with DIVIDE REMAINDER. |
|-------|--|
| Expl. | In a DIVIDE statement, you can use either the ROUNDED option to have the result of the division rounded, or the REMAINDER option to have the remainder of the division placed into a separate field. As there can be no remainder with a rounded result, it obviously makes no sense to use both options at the same time and is therefore not permitted. |
| Actn. | Use ROUNDED option or REMAINDER option, but not both. |

NAT0162: Floating format not allowed for DIVIDE REMAINDER.

| Text | Floating format not allowed for DIVIDE REMAINDER. |
|-------|---|
| | When you use the REMAINDER option in a DIVIDE statement, the format of the divisor and the dividend must not be "F" (floating point). |
| Actn. | Check program and correct error. |

NAT0163: Specification of level missing in DEFINE DATA statement.

| Text | Specification of level missing in DEFINE DATA statement. |
|-------|---|
| | In a DEFINE DATA statement, there must be an integer level number before each variable, group, view, REDEFINE definition. |
| Actn. | Check program and correct error. |

NAT0164: Illegal syntax for variable name.

| Text | Illegal syntax for variable name. |
|-------|--|
| Expl. | In a DEFINE DATA statement, the level specification must be followed by a valid name of a variable, group or view. In a DEFINE DATA INDEPENDENT statement, a variable name has to start with a "+" character (AIV variable); the name of a field resulting from the redefinition of an AIV variable must not start with a "+" character. A variable name starting with "+" (AIV) cannot be used in a |
| | PARAMETER, OBJECT, LOCAL or CONTEXT clause of a DEFINE DATA statement. See Natural Statements / Statement Usage Related Topics / User-Defined Variables / Naming Conventions and DEFINE DATA statement, for rules on naming variables. |
| Actn. | Correct error in program. |

NAT0165: Inconsistency in data structure of variable definition.

| Text | Inconsistency in data structure of variable definition. |
|-------|--|
| Expl. | An inconsistency in the data structure of a statement has been detected. This error may occur in the following statements: - DEFINE DATA - DEFINE FUNCTION (RETURNS clause) - DEFINE PROTOTYPE (RETURNS clause) |
| Actn. | Check the specifications of levels and variable definitions. |

NAT0166: Invalid variable definition in DEFINE DATA statement.

| Text | Invalid variable definition in DEFINE DATA statement. |
|-------|---|
| Expl. | An invalid definition of the DEFINE DATA statement has been detected. |
| Actn. | Check and correct variable definition. |

NAT0167: Duplicate specification of a view name detected.

| Text | Duplicate specification of a view name detected. |
|-------|--|
| Expl. | View names in the data structure of a program must be unique. |
| Actn. | Check view names of each GLOBAL, PARAMETER and LOCAL data structure. |

NAT0168: INTO constant not allowed in DIVIDE without GIVING clause.

| Text | INTO constant not allowed in DIVIDE without GIVING clause. |
|-------|---|
| | If your DIVIDE statement does not have a GIVING clause, the result will be place into the operand after keyword "INTO"; in this case, the INTO operand cannot be a constant. If you require the INTO operand to be a constant, use a GIVING clause to specify a result field. |
| Actn. | Check program and correct error. |

NAT0169: Error in format/length or in EM, HD, PM definition.

Text Error in format/length or in EM, HD, PM definition.

| Expl. | One of the following is invalid for a field definition in the |
|-------|--|
| | DEFINE DATA statement: |
| | - format (valid formats are A,U,B,C,D,F,I,L,N,P,T) |
| | - specified length, |
| | - combination of format and length |
| | (valid lengths for formats A and B are 1-1073741824; for format U |
| | is 1-536870912; for format F is 4 or 8; for format I is 1, 2 or 4; |
| | no length value may be specified for formats C, D, L, T) |
| | - number of positions before or after the decimal point for formats N,P |
| | (in the notation Nnn.m or Pnn.m, valid values for nn are 0-29, valid |
| | values for m are 0-7, and the sum nn+m must be in the range 1-29) |
| | Or one of the parameters EM (edit mask), HD (header), or |
| | PM (presentation mode) has not been specified correctly. |
| | See the Natural DEFINE DATA statement documentation for details. |
| Actn. | See the Natural DEFINE DATA statement documentation for details. Check program and correct |
| | error. |

NAT0170: A variable must be specified in INTO clause of SEPARATE.

| Text | A variable must be specified in INTO clause of SEPARATE. |
|-------|---|
| | A variable, not a constant, must be specified with the INTO clause of the SEPARATE statement. |
| Actn. | Check program and correct error. |

NAT0172: The INTO clause is missing in a SEPARATE statement.

| Text | The INTO clause is missing in a SEPARATE statement. |
|-------|--|
| | The keyword "INTO", followed by one or more operands, is required in a SEPARATE statement. |
| Actn. | Check program and correct error. |

NAT0173: The keyword "NUMBER" is missing in a GIVING clause.

| Text | The keyword "NUMBER" is missing in a GIVING clause. |
|-------|---|
| Expl. | If "GIVING" is used, the keyword "NUMBER" is also required. |
| Actn. | Check program and correct error. |

NAT0174: The field after NUMBER must be a numeric integer (N,I,P).

| Text | The field after NUMBER must be a numeric integer (N,I,P). |
|-------|---|
| Expl. | The field specified in the GIVING NUMBER clause of a SEPARATE statement |
| | must be a numeric integer; that is, its format must be one of the |
| | following: I |
| | N (without decimal digits) |
| | P (without decimal digits) |
| Actn. | Check program and correct error. |

NAT0175: Source field and at least one target field are required.

| Text | Source field and at least one target field are required. |
|-------|--|
| Expl. | The source field in a SEPARATE statement may be an alphanumeric constant or variable. At least one target field, which must be an alphanumeric variable, must be specified. |
| Actn. | Check program and correct error. |

NAT0176: Error in POSITION field of EXAMINE statement.

| Text | Error in POSITION field of EXAMINE statement. |
|-------|--|
| Expl. | The error may be caused by misspelling a variable name used as a reference to the POSITION variable. The variable must be of numeric format (N, I or P), and it must also be an integer (no decimal digits). |
| Actn. | Check program and correct error. |

NAT0177: Error in LENGTH field of EXAMINE statement.

| Text | Error in LENGTH field of EXAMINE statement. |
|-------|---|
| | The error may be caused by misspelling a variable name used as reference to the LENGTH variable. This variable must be of numeric format (N,I,B or P), and it must be an integer (no decimal digits). |
| Actn. | Check program and correct error. |

NAT0178: Error in INDEX field of EXAMINE statement.

| Text | Error in INDEX field of EXAMINE statement. |
|-------|--|
| | The error may be caused by misspelling a variable name used as reference to an INDEX variable. The variables must be of numeric format (N,I,B or P), and they must be integers (no decimal digits). The number of INDEX variables must equal the number of dimensions contained in the examined array. |
| Actn. | Check program and correct error. |

NAT0179: Invalid keyword in GIVING clause of EXAMINE statement.

| Text | Invalid keyword in GIVING clause of EXAMINE statement. |
|-------|--|
| Expl. | The following keywords are valid after GIVING: |
| | NUMBER |
| | POSITION |
| | LENGTH |
| | INDEX |
| | If more than one keyword is specified, they must be specified in the |
| | order indicated above. |
| Actn. | Check program and correct error. |

NAT0180: Word "TEXT" missing after "WITH" in INPUT statement.

| Text | Word "TEXT" missing after "WITH" in INPUT statement. |
|-------|---|
| Expl. | The word "TEXT" is a required part of the WITH TEXT clause. |
| Actn. | Check program and correct error. |

NAT0181: Error in specification of a variable in WITH TEXT clause.

| Text | Error in specification of a variable in WITH TEXT clause. |
|-------|---|
| Expl. | See the Natural documentation, INPUT or REINPUT statement, for details. |
| Actn. | Correct error in program. |

NAT0182: Invalid parameter list for WITH TEXT clause.

| Text | Invalid parameter list for WITH TEXT clause. |
|-------|---|
| Expl. | See the Natural documentation, INPUT or REINPUT statement, for details. |
| Actn. | Correct error in program. |

NAT0183: No more than 9 parameters allowed in WITH TEXT clause.

| Text | No more than 9 parameters allowed in WITH TEXT clause. |
|-------|--|
| Actn. | Check program and correct error. |

NAT0184: Specification error in variable of MARK clause.

| Text | Specification error in variable of MARK clause. |
|-------|---|
| - | The variable must be a numeric integer and must have been previously defined. |
| Actn. | Check program and correct error. |

NAT0185: Keyword "ALARM" is required after "AND" or "SOUND".

| Text | Keyword "ALARM" is required after "AND" or "SOUND". |
|-------|--|
| | The keyword "ALARM" is a required keyword to identify the ALARM option; the keywords "AND" and "SOUND" may be omitted. |
| Actn. | Check program and correct error. |

NAT0186: Keywords DO and DOEND not permitted in structured mode.

| Text | Keywords DO and DOEND not permitted in structured mode. |
|-------|--|
| Expl. | You wanted to use a DO/DOEND statement group in structured mode; however, DO/DOEND statement groups are only permitted in reporting mode. In structured mode, explicit END statements are used to indicate the |
| | end of a statement block; for example: AT BREAK DODOEND becomes AT BREAKEND-BREAK AT END OF DATA DODOEND becomes AT END OF DATAEND-ENDDATA AT END OF PAGE DODOEND becomes AT END OF PAGEEND-ENDPAGE AT START OF DATA DODOEND becomes AT START OF DATAEND-START AT TOP OF PAGE DODOEND becomes AT TOP OF PAGEEND-TOPPAGE IFDODOEND ELSE DODOEND becomes IFTHENELSEEND-IF ON ERROR DODOEND becomes ON ERROREND-ERROR BEFORE BREAK DODOEND becomes BEFORE BREAKEND-BEFORE |
| Actn. | PERFORM BREAK DODOEND becomes DEFORE DREAKEND-DEFORE PERFORM BREAK DODOEND becomes PERFORM BREAKEND-BREAK Select reporting mode or use the correct syntax. |

NAT0187: The LOOP statement is not permitted in structured mode.

| Text | The LOOP statement is not permitted in structured mode. |
|-------|---|
| Expl. | You wanted to use the statement LOOP in structured mode; however, the LOOP statement is only permitted in reporting mode. In structure mode, a loop is not closed with a LOOP statement but with an explicit loop-closing END statement; for example: Reporting Mode: FIND LOOP Structured Mode: FIND END-FIND |
| Actn. | Select reporting mode or use structured mode syntax. |

NAT0188: SORT without END-ALL is not permitted in structured mode.

| Text | SORT without END-ALL is not permitted in structured mode. |
|-------|---|
| Expl. | In structured mode, a processing loop initiated with a SORT statement must be closed with an END-ALL statement. |
| Actn. | Check program and correct error. |

NAT0189: END-ALL must be followed by SORT in structured mode.

| Text | END-ALL must be followed by SORT in structured mode. |
|-------|--|
| Actn. | Check program and correct error. |

NAT0190: Invalid placement of UNTIL or WHILE clause.

| Text | Invalid placement of UNTIL or WHILE clause. |
|-------|---|
| Expl. | An UNTIL or WHILE clause must be specified either immediately after the keyword "REPEAT" or immediately before the "END-REPEAT". Examples: 1. REPEAT UNTIL logical-condition statements END-REPEAT 2. REPEAT statements UNTIL logical-condition END-REPEAT |
| Actn. | Check program and correct error. |

NAT0191: Loop-ending statement missing after UNTIL/WHILE.

| Text | Loop-ending statement missing after UNTIL/WHILE. |
|-------|---|
| | In structured mode, a REPEAT UNTIL/WHILE processing loop must be closed with "END-REPEAT". In reporting mode, it must be closed with "LOOP". |
| Actn. | Check program and correct error. |

NAT0192: Destination missing in ESCAPE statement.

| Text | Destination missing in ESCAPE statement. |
|-------|---|
| | The ESCAPE statement requires extra keywords to specify the destination: - ESCAPE TOP - ESCAPE BOTTOM or ESCAPE BOTTOM IMMEDIATE - ESCAPE ROUTINE or ESCAPE ROUTINE IMMEDIATE See the Natural documentation for more information. |
| Actn. | Correct error in program. |

NAT0193: Keyword "ON" or "FOR" missing in DECIDE statement.

| Text | Keyword "ON" or "FOR" missing in DECIDE statement. |
|-------|---|
| Expl. | The keyword "DECIDE" must be followed either by "ON" or by "FOR". |
| Actn. | Check program and correct error. |

NAT0194: Invalid syntax in DECIDE FOR statement.

| Text | Invalid syntax in DECIDE FOR statement. |
|-------|--|
| Expl. | See the Natural documentation for information on the correct syntax of the DECIDE FOR statement. |
| Actn. | Correct error in program. |

NAT0195: Specified field must not be an array range.

| Text | Specified field must not be an array range. |
|-------|---|
| Actn. | Check program and correct error. |

NAT0196: GIVING INDEX is only allowed for indexable variables.

| Text | GIVING INDEX is only allowed for indexable variables. |
|-------|---|
| Actn. | Check program and correct error. |

NAT0197: Variable format not permitted in this statement.

| Text | Variable format not permitted in this statement. |
|-------|--|
| | A variable of format "C" is not permitted in a DISPLAY, WRITE, INPUT, PRINT, STACK, RUN and FETCH statement. A variable of format HANDLE OF OBJECT can not be used in this statement. |
| Actn. | Check program and correct error. |

NAT0198: No more than 128 parameters allowed in CALL statement.

| Text | No more than 128 parameters allowed in CALL statement. |
|-------|--|
| Expl. | The maximum number of parameters in a CALL statement is 128. |
| Actn. | Check program and correct error. |

NAT0199: Label defined twice or same as view/level-1-variable name.

| Text | Label defined twice or same as view/level-1-variable name. |
|-------|---|
| | Within a Natural module, a label must not be equal to another label, a view name or a variable name defined on level 1. |
| Actn. | Check program and correct error. |

NAT0200: Error in INCLUDE source lines.

| Text | Error in INCLUDE source lines. |
|-------|---|
| Expl. | See Natural INCLUDE statement documentation for more information. |
| Actn. | Check program and correct error. |

6

Natural System Error Messages 0201-0250

NAT0207: REDEFINE group not allowed in DEFINE DATA PARAMETER.

| Text | REDEFINE group not allowed in DEFINE DATA PARAMETER. |
|-------|---|
| - | Only elementary fields may be defined in a DEFINE DATA PARAMETER statement. |
| Actn. | Check program and correct error. |

NAT0214: Specify "FIRST" or "EVERY" in DECIDE statement.

| Text | Specify "FIRST" or "EVERY" in DECIDE statement. |
|-------|---|
| - | See the Natural documentation for detailed information on the DECIDE statement. |
| Actn. | Check program and correct error. |

NAT0215: Keyword "VALUE" missing in DECIDE ON statement.

| Text | Keyword "VALUE" missing in DECIDE ON statement. |
|-------|---|
| | The keyword "VALUE" (or "VALUES") is a required part of the DECIDE ON syntax. |
| Actn. | Check program and correct error. |

NAT0216: Invalid field specification in DECIDE ON statement.

| Text | Invalid field specification in DECIDE ON statement. |
|-------|--|
| | See the Natural documentation for information on how to specify fields correctly in a DECIDE ON statement. |
| Actn. | Check program and correct error. |

NAT0218: Error in construction of DECIDE ON/DECIDE FOR statement.

| Text | Error in construction of DECIDE ON/DECIDE FOR statement. |
|-------|--|
| | See the Natural documentation for information on the correct syntax for the statements DECIDE FOR and DECIDE ON. |
| Actn. | Check program and correct error. |

NAT0219: ALL clause is only allowed with DECIDE FOR/ON EVERY.

| Text | ALL clause is only allowed with DECIDE FOR/ON EVERY. |
|-------|---|
| | The ALL clause can only be used with DECIDE FOR EVERY and DECIDE ON EVERY, not for DECIDE FOR FIRST or DECIDE ON FIRST. |
| Actn. | Check program and correct error. |

NAT0220: Invalid statement :1:.

| Text | Invalid statement |
|-------|---|
| Expl. | Possible reasons: |
| | 1. Depending on the programming mode (structured/reporting mode), |
| | keywords are missing (e.g., "COMPUTE" and "ASSIGN" must not be |
| | omitted when using ROUNDED in structured mode). |
| | 2. The statement is not suitable for this object type |
| | (e.g., DEFINE SUBROUTINE must not be the first statement in |
| | an object of type function). |
| | 3. A compatibility switch is set (e.g., the profile parameter |
| | V41MFCOMP), which causes some statements to be disallowed. |
| Actn. | 1. Add the missing keywords. |
| | 2. Change the object type or the statement. |
| | 3. Switch off the compatibility switch. |

NAT0222: Syntactical errors prevent execution of program.

| Text | Syntactical errors prevent execution of program. |
|-------|--|
| | In batch mode, Natural always continues the syntax checking of a program even after an error has been detected. A program containing a syntactical error cannot be executed because the compiled code does not agree with the source input. |
| Actn. | Check program and correct error. |

NAT0223: Keyword "MAP" or "FORM" is required after "USING".

| Text | Keyword "MAP" or "FORM" is required after "USING". |
|-------|--|
| Actn. | Check program and correct error. |

NAT0224: Input map in WRITE or write map in INPUT statement.

| Text | Input map in WRITE or write map in INPUT statement. |
|-------|---|
| | Either you have specified in a WRITE USING MAP statement the name of a map which is an input map, not an output map; or you have specified in an INPUT USING MAP statement the name of a map which is an output map, not an input map. Whether a map is an input or output (write) map is indicated in its Map Settings. |
| Actn. | Check program and correct error. |

NAT0225: GIVING LENGTH is only valid for non-indexable variables.

| Text | GIVING LENGTH is only valid for non-indexable variables. |
|-------|--|
| Actn. | Check program and correct error. |

NAT0226: An empty statement block is not allowed.

| Text | An empty statement block is not allowed. |
|-------|--|
| | The only way of having a statement block which does nothing is by filling it with an IGNORE statement. |
| Actn. | Correct error in program. |

NAT0227: Invalid variable/constant in DELIMITER clause.

| Text | Invalid variable/constant in DELIMITER clause. |
|-------|--|
| - | If the receiving field of the COMPRESS statement is of format - alphanumeric or binary, the delimiter format has to be A1, B1 or U1. - Unicode, the delimiter format has to be A1, B2 or U1. |
| Actn. | Check program and correct error. |

NAT0228: Block structure of GDA must be specified in WITH clause.

| Text | Block structure of GDA must be specified in WITH clause. |
|-------|--|
| | In this GDA, a block structure is defined. The block structure must be specified in the WITH clause of DEFINE DATA GLOBAL USING. |
| Actn. | Check program and correct error. |

NAT0229: Invalid use of WITH clause in UPDATE or STORE statement.

| Text | Invalid use of WITH clause in UPDATE or STORE statement. |
|-------|---|
| | If an UPDATE or STORE statement is based on a view defined with DEFINE DATA or within a data area, the use of the WITH clause is not permitted. An UPDATE or STORE statement always includes all fields when it applies to a view. |
| Actn. | Remove the WITH clause from the UPDATE/STORE statement. |

NAT0230: Operand type not supported.

| Text | Operand type not supported. |
|-------|--|
| Expl. | Operands defined as - HANDLE or UNICODE, - alphanumeric/binary DYNAMIC, - alphanumeric with a length of more than 253 bytes, or - binary with a length of more than 126 bytes are not supported at this position. |
| Actn. | Check program and correct error. |

NAT0231: Only NSD in linkage attributes allowed here.

| Text | Only NSD in linkage attributes allowed here. |
|-------|--|
| Expl. | An NSD attribute is an element associated with a view. |
| | In a FIND statement, one expects an attribute name after the "VIA" keyword in a REFERENCED, REFERENCING or RECURSIVELY clause. |
| | In a SHOW statement, one expects attributes after |
| | SHOW, or SHOW RECURSIVELY, in brackets as follows: |
| | SHOW ATTR1(ATTR2(ATTR3)) |
| | Check that the attribute is found in the view specified by |
| | "L F <view-name>" and correct the source accordingly.</view-name> |

NAT0232: Operand of type DYNAMIC not allowed at this position.

| Text | Operand of type DYNAMIC not allowed at this position. |
|-------|---|
| Expl. | Alphanumeric or binary operands defined as DYNAMIC cannot be used at this position. |
| Actn. | Replace DYNAMIC field with FIXED length field. |

NAT0233: Level number must be numeric integer.

| Text | Level number must be numeric integer. |
|-------|--|
| | This refers to the level of recursion a FIND statement execution is to go to. The level number must be numeric. For further information, please refer to the FIND statement, UNTIL clause, in the Entire DB Programmer's Guide. |
| Actn. | Correct error in program. |

NAT0234: "ERE SET" must start with a category name.

| Text | "ERE SET" must start with a category name. |
|-------|---|
| Expl. | In a FIND statement, after the FIND header for an Entire view, the syntax logic searches for components called "ERE SET"s. An "ERE SET" begins with a view name and ends with a search criterion. The search criterion finishes when a Natural keyword or the view name of the next "ERE SET" is encountered. When neither of these conditions is met, this error appears; and the syntax analysis cannot proceed. |
| Actn. | Check source code and correct error. |

NAT0235: ISN must be an integer value.

| Text | ISN must be an integer value. |
|-------|---|
| Expl. | In a FIND statement, ISN values in the RELATIONSHIP or ISN clauses of the basic search criterion must be integer values. The ISNs found are numeric, but not integer values. For further information, please refer to the FIND statement, RELATIONSHIP and ISN clauses of the basic search criterion, in the Entire DB Programmer"s Guide. |
| Actn. | Correct error in program. |

NAT0236: Equal sign "=" missing after Entire keyword.

| Text | Equal sign "=" missing after Entire keyword. |
|-------|---|
| Expl. | This error can occur in two Entire statements: |
| | 1) FIND view-name WITH ISN = 12335 |
| | The equal sign is necessary in the ISN clause of the basic search |
| | criterion of the FIND statement. |
| | 2) DLOGON USER = "XXX" PASSWORD = "YYY" LIBRARY = "LLL" |
| | APPLICATION = "AER" AUTHORIZATION = A |
| | In this syntax form of the DLOGON statement, the equal sign must |
| | follow each keyword. |
| | For further information, see FIND and DLOGON statements in the |
| | Entire DB Programmer"s Guide. |
| Actn. | Correct error in program. |

NAT0237: Unmatched closing parenthesis.

| Text | Unmatched closing parenthesis. |
|-------|---|
| | Entire DB checks whether each opening parenthesis is paired with a corresponding closing parenthesis. |
| Actn. | Correct error in program. |

NAT0238: Invalid operator in descriptor search criterion.

| Text | Invalid operator in descriptor search criterion. | |
|------|--|--|
|------|--|--|

| Expl. | In a FIND statement, the following relational operators are valid in a |
|-------|--|
| | descriptor search criterion: |
| | = (equal to) |
| | |
| | < (less than) |
| | <= (less than or equal to) |
| | > (greater than) |
| | >= (greater than or equal to) |
| | In descriptor search criteria (following WITH), only the above operators |
| | are allowed after the attribute (NAME or LINE-NUMBER). |
| | See the description of the FIND statement the in Entire DB Programmer's |
| | Guide for further information. |
| Actn. | Correct descriptor search criterion. |

NAT0239: Move values for Entire must be integer values.

| Text | Move values for Entire must be integer values. |
|-------|--|
| Expl. | A move value is a constant or variable moved into the search buffer of an Entire call at runtime. When this message appears, a numeric value is expected: integer, numeric unpacked or packed without decimal digits, but not binary. |
| Actn. | Correct error in program. |

NAT0240: Operand format invalid. Format :1: expected.

| Text | Operand format invalid. Format expected. |
|-------|--|
| | The format of this operand is invalid. For further information on valid formats, see the operand definition table of this statement. |
| Actn. | Supply a valid operand format. |

NAT0242: Open bracket "(" expected.

| Text | Open bracket "(" expected. |
|-------|---|
| Expl. | Entire DB checks for open parentheses in the NATIVE and RELATIONSHIP clauses of the FIND statement. Clause elements must be enclosed in parentheses. See FIND statement in the Entire DB Programmer's Guide for further information. |
| Actn. | Correct error in program. |

NAT0243: Syntax error in DEFINE DATA statement/structure.

| Text | Syntax error in DEFINE DATA statement/structure. |
|-------|---|
| 1 1 | See the Natural documentation for information on the correct syntax of the DEFINE DATA statement. |
| Actn. | Check program and correct error. |

NAT0244: "GLOBAL" must be followed by "USING" and GDA name.

| Text | "GLOBAL" must be followed by "USING" and GDA name. |
|-------|---|
| Expl. | A global data area (GDA) is always a separate object, never part of the data definition within the DEFINE DATA statement of a program. The GDA is referenced in the GLOBAL clause of the DEFINE DATA statement with the following syntax: DEFINE DATA GLOBAL USING name-of-gda END-DEFINE |
| Actn. | Check program and correct error. |

NAT0245: Invalid use/order of clauses in DEFINE DATA statement.

| Text | Invalid use/order of clauses in DEFINE DATA statement. |
|-------|---|
| | The sequence of clauses in the DEFINE DATA statement is: DEFINE DATA GLOBAL USING PARAMETER OBJECT LOCAL In a subsequent validation rule, only DEFINE DATA LOCAL is allowed. |
| Actn. | Make sure that the clauses are in the correct order. |

NAT0246: Formats "C", "L" and HANDLE OF OBJECT not allowed here.

| Text | Formats "C", "L" and HANDLE OF OBJECT not allowed here. |
|-------|---|
| Expl. | Data types "C" (control) and "L" (logical) cannot be used in: - GET TRANSACTION DATA statement, - END TRANSACTION statement, - sort criteria of a SORT statement. Data type HANDLE OF OBJECT cannot be used in: - GET TRANSACTION DATA statement, - END TRANSACTION statement, - SORT statement. |
| Actn. | Check program and correct error. |

NAT0247: Error during processing of parameter :1:.

| Text | Error during processing of parameter |
|-------|---|
| Expl. | When an INPUT/WRITE USING MAP or a PROCESS PAGE USING statement is used with a constant map or adapter name and without explicit parameters, the names of the fields to be processed are taken dynamically from the map or adapter source at compilation. This requires that the same field names with the same array structure be defined in both the program and the map or adapter. The indicated variable name is either not defined or the number of array dimensions does not match. |
| Actn. | Check the indicated data field. The variable definition in the program should be same as in the map or adapter. |

NAT0248: Invalid USING variable in PROCESS statement.

| Text | Invalid USING variable in PROCESS statement. |
|-------|--|
| | The left part of the ASSIGN variable in the USING clause of the PROCESS statement must be part of the view defined to Natural PROCESS. |
| Actn. | Check program and correct error. |

NAT0249: Error in "ASSIGN" of Natural PROCESS "USING" clause.

| Text | Error in "ASSIGN" of Natural PROCESS "USING" clause. |
|-------|--|
| Actn. | Check program and correct error. |

NAT0250: Error in GIVING clause of Natural "PROCESS" statement.

| Tex | ĸt | Error in GIVING clause of Natural "PROCESS" statement. |
|-----|-----|--|
| Ac | tn. | Check program and correct error. |

Natural System Error Messages 0251-0300

NAT0251: File/DDM not defined for PROCESS statement.

| Text | File/DDM not defined for PROCESS statement. |
|-------|---|
| Actn. | Check program and correct error. |

7

NAT0252: Library must not be specified in security environment.

| Text | Library must not be specified in security environment. |
|-------|---|
| | In an environment which is protected by Natural Security, the specification of a library is not possible. |
| Actn. | Do not specify a library. |

NAT0253: Statement not allowed for DB2 access.

| Text | Statement not allowed for DB2 access. |
|-------|---|
| Expl. | The following statements and constructions are not supported by DB2: 1. FIND UNIQUE 2. FIND COUPLED 3. FIND FIRST 4. FIND RETAIN AS 5. GET 6. any reference to *ISN 7. END TRANSACTION within an open database loop 8. BACKOUT TRANSACTION within an open database loop |
| Actn. | Correct error in program. |

NAT0254: Receiving field of VAL function has invalid format.

| Text | Receiving field of VAL function has invalid format. |
|-------|---|
| Expl. | The format and length must be the same as that of the target. This mathematical function extracts the numeric value from an alphanumeric field. The content of the alphanumeric field must be the character representation of a numeric value. Leading or trailing blanks are permitted. Decimal point and leading sign character will be processed. |
| Actn. | Do not use formats A (alphanumeric) or B (binary). |

NAT0255: General syntax error detected in program.

| Text | General syntax error detected in program. |
|-------|--|
| Expl. | A general syntax error was detected while syntax checking a source |
| | program. This message is output for various miscellaneous syntax errors |
| | for which Natural does not provide specific error messages. |
| Actn. | Check program and correct error. |

NAT0256: Invalid entry in command line.

| Text | Invalid entry in command line. |
|-------|--|
| Expl. | The structure of the command does not require the parameters that have been specified in the command line. Natural checks that the parameter specification agrees with the parameter structure expected by the individual command. Another reason for this error is that ADHOC is missing in batch mode. |
| Actn. | Check command structure and resubmit. |

NAT0257: Only operators "EQUAL", "NOTEQUAL" valid with MASK/SCAN.

| Text | Only operators "EQUAL", "NOTEQUAL" valid with MASK/SCAN. |
|-------|--|
| Expl. | It is not possible to evaluate the operators GREATER or LESS THAN for a value when only certain positions are included in the comparison. Therefore, the only logical operator that are allowed with the special compare function MASK and SCAN are "EQUAL" and "NOTEQUAL". |
| Actn. | Restructure the logical criteria to only use operators "EQUAL" or "NOTEQUAL" with the functions MASK and SCAN. |

NAT0258: Incorrect MASK argument construction.

| Text | Incorrect MASK argument construction. |
|-------|--|
| 1 | The mask value must be enclosed in parentheses and may only contain the elements as described in the Natural documentation; see also extended error message NAT0017. |
| Actn. | Check program and correct error. |

NAT0259: Invalid MASK construction for date check.

| Text | Invalid MASK construction for date check. |
|-------|--|
| 1 | When a date check is to be performed, the specification for month/day/year must be 2 characters each (MM/DD/YY); for year, 4 characters (YYYY) may also be used. |
| Actn. | Check program and correct error. |

NAT0260: Error in text list construction; contact administrator.

| Text | Error in text list construction; contact administrator. |
|-------|---|
| Expl. | A discrepancy was detected in the number of alternative entries in the text list and the syntax list. The error is caused by an invalid modification of the text list. New entries can only be inserted in the text list by using the macro CSYN for synonym, not the macro CALT for alternative. |
| Actn. | Retain the keyword on which the error has been detected and contact your Natural administrator. |

NAT0261: END statement missing.

| Text | END statement missing. |
|-------|---|
| | The last statement of a Natural program must always be END. Alternatively, a period "." may be used. |
| Actn. | Check program and correct error. |

NAT0262: Incorrect number of digits/value out of range.

| Text | Incorrect number of digits/value out of range. |
|-------|---|
| Expl. | For a field of format N or P, the overall maximum number of digits is 29, and the maximum number of digits after the decimal point is 7. For a field of format F the value specified must be in the range of values as described in the Natural documentation on floating-point constants. |

Actn. Correct error in program.

NAT0263: Invalid MASK construction for range check.

| Text | Invalid MASK construction for range check. |
|-------|---|
| Expl. | If a range check is to be performed, both values for the supplied |
| | range must have the same number of positions. |
| | Leading zeros must be supplied, as it is a check for positions in |
| | the value and the number of digits supplied in the range value. |
| | The number of positions to be included in the range check must also |
| | be specified. |
| Actn. | Check program and correct error. |

NAT0264: Length of alphanumeric or unicode constant is zero.

| Text | Length of alphanumeric or unicode constant is zero. |
|-------|--|
| · · | The length of an alphanumeric or unicode constant must be greater than zero. |
| Actn. | Check program and correct error. |

NAT0265: Error in hexadecimal constant: :1:.

| Text | Error in hexadecimal constant: |
|-------|---|
| Expl. | Invalid hexadecimal character found. A hexadecimal constant may consist only of characters 0-9 or A-F. Invalid number of characters specified. The hexadecimal notation for constants of format A (H"") requires characters to represent one byte. Therefore, the number of |
| | hexadecimal characters supplied must be a multiple of 2. - The hexadecimal notation for constants of format U (UH"") requires 4 characters to represent one Unicode code unit. Therefore, the number of hexadecimal characters supplied must be a multiple of 4. |
| Actn. | Correct error. |

NAT0266: Number of bytes defined by hexadecimal constant > 80.

| Text | Number of bytes defined by hexadecimal constant > 80. |
|-------|--|
| Expl. | Hexadecimal constants are converted to internal byte representation in an intermediate buffer of 80 bytes. If literal constants of more than 80 bytes internal representation are to be defined, use the notation "XXXXXX"-"XXXXXX" to enter the value in multiple segments. |
| Actn. | Check program and correct error. |

NAT0267: Invalid file specification in COUPLED clause.

| Text | Invalid file specification in COUPLED clause. |
|------|---|
| - | The file specified in a COUPLED clause must be an Adabas file which has been physically coupled using the appropriate Adabas utility program. The file must not be a logical Natural system file. |
| | Check program and correct error; or contact your Natural administrator about the file status. |

NAT0268: Invalid format/length for database count variable.

| Text | Invalid format/length for database count variable. |
|-------|---|
| | The format of the count variable for a periodic-group name or multiple-value field must be N or P. No decimal digits are permitted. |
| Actn. | Check program and correct error. |

NAT0269: Invalid descriptor in SORTED BY clause.

| Text | Invalid descriptor in SORTED BY clause. |
|-------|---|
| | The descriptor specified in the SORTED BY clause cannot be within a periodic group. If the descriptor is a multiple-value field, an index value must not be used. |
| Actn. | Check program and correct error. |

NAT0270: Invalid use of variable index notation.

| Text | Invalid use of variable index notation. |
|-------|---|
| | Variable index notation is not permitted with a search variable in the WITH clause of a FIND statement. A variable array index (1:V) must not be used for redefine fields. |
| Actn. | Check program and correct error. |

NAT0271: Page width (line size) exceeded in DISPLAY statement.

| Text | Page width (line size) exceeded in DISPLAY statement. |
|-------|---|
| | The total number of positions required for all columns resulting from a DISPLAY statement must not exceed the logical page size. |
| Actn. | Reduce number of fields being displayed, or reduce spacing between columns, or increase the logical page size (where applicable), or place multiple values vertically in the same column. |

NAT0272: Invalid value format or incompatible field format.

| Text | Invalid value format or incompatible field format. |
|-------|--|
| Expl. | In a SCAN condition, the - format of the value to be scanned for must be "A", "B" or "U"; - format of the field to be scanned must be "A", "N", "P" or "U"; |
| | length of the value must be less than the length of the field. In a MASK condition, the format of the field to be tested must be "A", "N", "P" or "U"; format combination of first and second operand must be compatible; first operand must not be smaller than the mask. |
| Actn. | Check program and correct error. |

NAT0273: Error :1: in line :2: of data area :3: processing :4:.

| Text | Error in line of data area processing |
|-------|---|
| | As indicated in the error message, an error has occurred in a specific line of a data area while processing a variable. |
| Actn. | Correct error in data area. |

NAT0274: Error :1: in line :2: of copycode :3: processing :4:.

| Text | Error in line of copycode processing |
|-------|--|
| · · | As indicated in the error message, an error has occurred in a specific line of a copycode while processing a variable. |
| Actn. | Correct error in copycode. |

NAT0275: RETRY statement only allowed in ON ERROR statement block.

| Text | RETRY statement only allowed in ON ERROR statement block. |
|-------|--|
| - | The RETRY statement can only be used as a response to error NAT3145, which indicates that a record to be read for update is currently in "hold" status for another user. |
| Actn. | Check program and correct error. |

NAT0276: Invalid reference to count of field in periodic group.

| Text | Invalid reference to count of field in periodic group. |
|-------|--|
| | When referencing the count of the number of occurrences of an elementary field within a periodic group, the name of the periodic group must be used, not the name of the elementary field. |
| Actn. | Check program and correct error. |

NAT0277: A global variable must not redefine another variable.

| Text | A global variable must not redefine another variable. |
|-------|---|
| | For reasons of addressability, parameter variables must not be defined by redefining an already existing variable. |
| Actn. | Check program and correct error. |

NAT0278: Value to be used in SET CONTROL must be format "A".

| Text | Value to be used in SET CONTROL must be format "A". |
|-------|--|
| Expl. | The value (constant or variable) used to specify a terminal command with a SET CONTROL statement must be alphanumeric. |
| Actn. | Check program and correct error. |

NAT0279: Count requested for a non-array field.

| Text | Count requested for a non-array field. |
|-------|---|
| Expl. | The count field only exists for database fields that are defined as multiple-value fields, periodic groups, or multiple-value fields within a periodic group. If the count of a multiple-value field within a periodic group is to be accessed, an index must be specified to indicate the occurrence of the multiple-value field in the periodic group for which the count is being requested. The field for which you have requested a count of occurrences is neither a multiple-value field nor a periodic group. |
| Actn. | Check program and correct error. |

NAT0280: Index entry incorrectly specified for field.

| Text | Index entry incorrectly specified for field. |
|-------|--|
| Expl. | An index was specified for a variable for which indexing is not permitted. Index specifications may only be used when defining/referencing an array. A database array can only be defined for a multiple-value field and for fields within a periodic group. When referencing an array, an index range specification was detected which exceeds the index range defined for one of its dimensions. |
| Actn. | Check program and correct error. |

NAT0281: Index entry missing or invalid for an array.

| Text | Index entry missing or invalid for an array. |
|-------|---|
| Expl. | When a multiple-value field or a field within a periodic group is referenced, an index must be specified to indicate the occurrence of the value to be selected. Default indices are created in WRITE or DISPLAY statements based on the setting of the session parameters MC and PC. A variable to be used as a variable index must have been previously defined before it can be used as an index notation. If a non-database field has been defined as an array, an index for each dimension must be specified when referencing the field. |
| Actn. | Check program and correct error. |

NAT0282: Only one index/range specification allowed.

| Text | Only one index/range specification allowed. |
|-------|---|
| | For multiple-value fields, or fields within a periodic group, only one index or range of indices may be specified. Two indices are only allowed for multiple-value fields within a periodic group. |
| Actn. | Check program and correct error. |

NAT0283: Field or variable :1: defined more than once.

Text Field or variable ... defined more than once.

| Expl. | If DEFINE DATA is used: |
|-------|---|
| | A variable declared on level 1 must not be defined a second time, |
| | neither on level 1 nor on any other level. |
| | Without DEFINE DATA: |
| | A variable or database field can only be defined once using a |
| | format/length specification. When the variable is referenced in the |
| | program, no further format/length specification is possible. |
| | If the first field definition was made in a data area (LDA,GDA) |
| | which was included with a "DEFINE DATA USING" statement, a further |
| | message (NAT0297) is put on the error stack, which indicates the data |
| | area name, the library and DB/FNR from which the field was included |
| | first. This message can be displayed with the system command LASTMSG. |
| Actn. | Check program and correct error. |

NAT0285: Field reference error; reference invalid or missing.

| Text | Field reference error; reference invalid or missing. |
|-------|--|
| | Probable reasons for this error message: You mistyped the variable name. The variable name you specified has not yet been declared. A specific database reference has been supplied, but the field is not present in the file referenced. The value of a Natural system function has been referenced in the form *FUNCTION(FIELD), but no evaluation of the referenced system function has occurred for the field. |
| Actn. | Check program and correct error. |

NAT0286: Invalid use of function, system function or sys. variable.

| Text | Invalid use of function, system function or sys. variable. |
|-------|--|
| Expl. | Natural system functions and Natural system variables may only be used in a specific statement syntax within a Natural program. The value of a system function or system variable may be assigned to a variable and then referenced. In an INPUT statement, most system functions can only be used as output fields, but not as input fields. The only system variable that can be used as an argument in the system function POS is *COM. A Natural function call is not allowed in this context. For further information on Natural functions, Natural system functions or Natural system variables, see the Natural documentation. |
| Actn. | Correct error in program. |

NAT0287: No access to database field; or REDEFINE variable exists.

| Text | No access to database field; or REDEFINE variable exists. |
|-------|---|
| Expl. | Either the access to a database field is not possible at this point; or a variable to be used in a REDEFINE statement has previously been defined. A database field can only be referenced within an active processing loop. If the loop has been closed, a reference to fields from that database access is no longer possible. If you wish to use a value of a database field outside an active processing loop, assign the value to a user-defined variable. This error also occurs if a 4-digit array occurrence is incorrectly specified. 4-digit array occurrences must be preceded by a slash; for example, #ARRAY(/1000), not #ARRAY(1000). |
| Actn. | Correct error in program. |

NAT0288: Index/format not permitted in Natural system function.

| Text | Index/format not permitted in Natural system function. |
|-------|--|
| - | Format or length must not be specified for the reference to a Natural system function that had been previously evaluated nor for the reference to a Natural system variable. |
| Actn. | Check program and correct error. |

NAT0289: Referenced field is not a descriptor.

| Text | Referenced field is not a descriptor. |
|-------|---|
| Expl. | The reference to a database field at this point requires that the field is a descriptor. Descriptors are required in the WITH clause of a FIND statement, as sequence fields in a READ LOGICAL statement, or when indicating the field for which values are to be provided in a HISTOGRAM statement. Under Adabas Version 5, this error also occurs if a field that is marked in the DDM as a "non-descriptor" is used as a search variable |
| Actn. | in a READ or HISTOGRAM statement. Correct error in program. |

NAT0290: Sub/super/hyper/phonetic descriptor field improperly used.

| Text | Sub/super/hyper/phonetic descriptor field improperly used. |
|-------|--|
| | A sub/superfield or sub/superdescriptor may be read from the database with an access statement (READ, FIND, HISTOGRAM, GET), but cannot be referenced in an update statement (STORE, UPDATE). The value for a hyper- and phonetic descriptor can only be used in a search criterion, but cannot be read from the database. |
| Actn. | Correct error in program. |

NAT0291: Format for database field incompatible.

| Text | Format for database field incompatible. |
|-------|--|
| | The format used for a database field is not compatible with the format of the field as defined in the data dictionary. |
| Actn. | Check program and correct error. |

NAT0292: Requested field is not integer or has invalid length.

| Text | Requested field is not integer or has invalid length. |
|-------|---|
| Expl. | The operation requires the value of an integer field. This can be an integer constant, or a user-defined variable or database field of integer format. This error occurs if: - the field is of a format other than integer, or - the length of the field is not valid. |
| Actn. | Use an integer format/length valid for the operand. |

NAT0293: Index range entry specified where not allowed.

| Text | Index range entry specified where not allowed. |
|-------|---|
| Expl. | A single index entry is required for this type of function; an index range is not permitted. Single index entries are required, for example, in the WITH clause of a FIND statement to indicate a specific occurrence of a periodic group field, or to specify the descriptor to be used for sequence control in a READ LOGICAL statement. |
| Actn. | Check program and correct error. |

NAT0294: Intermediate storage overflow in arithmetic statement.

| Text | Intermediate storage overflow in arithmetic statement. |
|-------|---|
| Expl. | An overflow of an internal stack has occurred during the evaluation of an arithmetic expression. The internal stack is used to sequence the execution of arithmetic operations according to the parenthetical structure. |
| Actn. | Reduce the number of operations to be performed within a single arithmetic operation. |

NAT0295: Operand in arithmetic statement is not numeric.

| Text | Operand in arithmetic statement is not numeric. |
|-------|--|
| | Only operands of format "N" (numeric unpacked) or "P" (packed numeric) are allowed in arithmetic expression. A numeric operand can be defined as a constant or as the content of a variable. |
| Actn. | Check program and correct error. |

NAT0296: Invalid search criteria in FIND statement.

| Text | Invalid search criteria in FIND statement. |
|-------|---|
| | When evaluating complex search criteria, such as one with logical operator "OR", several separate database calls may be required. For a single FIND statement, a maximum of 64 database calls can be generated internally. |
| Actn. | Reduce the number of search criteria. |

NAT0297: Field :1: previously defined in (:2:/:3:/:4:/:5:).

| Text | Field :1: previously defined in (:2:/:3:/:4:/:5:). |
|-------|--|
| | The variable :1: was declared twice. The first definition of the field was included via data area :2:, which was loaded from library :3:, database :4:, file number :5:. |
| Actn. | Correct error in program. |

NAT0298: Incorrect parameters specified in SET KEY statement.

| Text | Incorrect parameters specified in SET KEY statement. |
|-------|---|
| | A push-button (PB=), menu (ME=), or bitmap (BM=) clause was detected in a SET KEY statement, but the corresponding parameters were incorrectly specified. |
| Actn. | See the Natural documentation for detailed information. |

NAT0299: Total length of intermediate result exceeds 31 digits.

| Text | Total length of intermediate result exceeds 31 digits. |
|-------|--|
| Expl. | Natural supports operands up to a length of 31 digits. The length of intermediate results as operands is evaluated according to the rules for arithmetic operations. See the Natural documentation for details. |
| Actn. | Check the digits of intermediate results according to the rules. Separate the arithmetic expression into several statements using explicit intermediate results. |

NAT0300: Operands are not data transfer compatible.

| Text | Operands are not data transfer compatible. |
|-------|---|
| Expl. | According to the format rules for data transfer, the source operand cannot be assigned to the destination field. For more information, see the Natural documentation, topic "Rules for Arithmetic Assignment". |
| Actn. | Check program and correct error. |

8

Natural System Error Messages 0301-0350

NAT0301: Edit mask too long or not specified correctly.

| Text | Edit mask too long or not specified correctly. |
|-------|--|
| | Possible reasons for this error: The specified edit mask contains no character that would cause any digit of the value to be output (e.g., for a numeric edit mask no "Z" or "9" was specified; for an alphanumeric edit mask no "X" was specified). The number of output digits in a numeric edit mask exceeds 31. The number of output characters resulting from the edit mask string exceeds the maximum size of 1073741824 characters. The edit mask string you have specified is too long. It must not exceed 80 source characters on mainframes and 244 on open systems. You have specified an edit mask at statement level in a DISPLAY, FORMAT, INPUT or WRITE statement. At statement level in these statements, you can only specify "EM=OFF", but no specific edit mask. |
| Actn. | Correct edit mask specification. |

NAT0302: Element in WRITE/INPUT statement does not fit on 1 line.

| Text | Element in WRITE/INPUT statement does not fit on 1 line. |
|------|---|
| | The size of an element specified in a WRITE/INPUT statement exceeds the current line size. |
| | Either increase the line size (parameter LS), or reduce the size of the element (for example, by using a REDEFINE statement). |

NAT0303: Page overflow, too many vertical entries.

| Text | Page overflow, too many vertical entries. |
|------|---|
| 1 1 | The number of vertical entries specified within one INPUT, WRITE or DISPLAY statement exceeded the current page size. |
| 1 | Either increase the page size (parameter PS) or reduce the number of vertical entries. |

NAT0304: Invalid printer reference number.

| Text | Invalid printer reference number. |
|-------|---|
| | A printer number must be specified as a numeric constant or symbolic constant defined with DEFINE PRINTER enclosed in parentheses. There is no additional printer support within a map (processing rule). |
| Actn. | Check program and correct error. |

NAT0305: Text string must begin and end on the same line.

| Text | Text string must begin and end on the same line. |
|-------|---|
| Expl. | A text string is initiated with an apostrophe and must be ended on the same line with another apostrophe. If a text string longer than one line is required, enter the text in two portions (each within apostrophes) in two consecutive lines and with a hyphen (-) between the two portions. At execution time, the two portions will be concatenated. |
| Actn. | Correct error in program. |

NAT0306: DO or DOEND either missing or misplaced.

| Text | DO or DOEND either missing or misplaced. |
|-------|--|
| Expl. | A group of statements initiated with a DO statement must be terminated with a DOEND statement. The omission of a DOEND statement may only be detected at the end of a source program. |
| | The position of the error in the program does not necessarily correspond to the position where the DOEND should be placed. |
| Actn. | Ensure that each DO statement has a corresponding DOEND statement. |

| Text | Loop in line not closed within conditional block. |
|-------|---|
| Expl. | A processing loop which is initiated within a conditional statement block must be closed within that block. Valid example: Invalid example: |
| | IF IF DO DO FIND FIND DISPLAY DISPLAY LOOP DOEND DOEND END END |
| Actn. | Check program and correct error. |

NAT0307: Loop in line :1: not closed within conditional block.

NAT0308: Attempt to close a non-existent processing loop.

| Text | Attempt to close a non-existent processing loop. |
|-------|---|
| Expl. | The LOOP statement can only be used to close an active processing loop. |
| | Either the processing loop to be closed was not properly initiated, or the processing loop had already been closed. |
| Actn. | Check program and correct error. |

NAT0309: Invalid positioning of AT BREAK/END condition.

| Text | Invalid positioning of AT BREAK/END condition. |
|-------|---|
| Expl. | An AT BREAK/END condition cannot be used within a block of |
| | statements which is dependent on another special condition. |
| | Blocks are: AT BREAK |
| | AT END/TOP OF PAGE |
| | AT START/END OF DATA |
| | ON ERROR |
| | IF |
| Actn. | Re-position the AT BREAK/END condition. |

NAT0310: AT END OF or AT BREAK requires active processing loop.

| Text | AT END OF or AT BREAK requires active processing loop. |
|-------|---|
| Expl. | An AT BREAK/END statement can only be used within an active |
| | processing loop. |
| Actn. | Check program and correct error. |

NAT0311: Error occurred in user exit for source/object programs.

| Text | Error occurred in user exit for source/object programs. |
|-------|--|
| | A non-zero response code was received from the user exit which is used to store source/object programs in a user-controlled file. |
| Actn. | Check the coding of the user exit (response code in register 15 when returning to Natural). |

NAT0312: Reference invalid in AT START/END OF DATA or AT BREAK.

| Text | Reference invalid in AT START/END OF DATA or AT BREAK. |
|-------|---|
| | A reference number was used to refer one of the above conditional statements to a specific processing loop. However, the specified reference number refers to a line which does not contain the correct loop-initiating statement. |
| Actn. | Check program and correct error. |

NAT0313: Only one BEFORE BREAK/AT START OF DATA allowed in a loop.

| Text | Only one BEFORE BREAK/AT START OF DATA allowed in a loop. |
|-------|---|
| Expl. | Only one AT START OF DATA condition can be specified for a single processing loop. If multiple statements are to be made dependent on the AT START OF DATA condition, use a DO/DOEND construction (see example below). Example: READ AT START OF DATA DO IF DO DEND IF DO DOEND DISPLAY LOOP END |
| Actn. | Check program and correct error. |

NAT0314: No more than one ON ERROR statement allowed per program.

| Text | No more than one ON ERROR statement allowed per program. |
|-------|--|
| Expl. | Only one ON ERROR condition can be specified in a given program. |
| | To check multiple conditions in an ON ERROR condition, use IF |
| | statements within the ON ERROR condition. |
| | Example: |
| | |
| | READ |
| | UPDATE |
| | ON ERROR IF END-IF |
| | IF END-IF |
| | END-ERROR |
| | END-READ |
| | END |
| Actn. | Check program and correct error. |

NAT0315: Inconsistent usage of "/n/" clause.

| Text | Inconsistent usage of "/n/" clause. |
|-------|--|
| Expl. | The notation "/n/" can be used to specify how many positions of a |
| | variable are to be examined in the evaluation of an AT BREAK |
| | statement or an IF BREAK condition. |
| | A "/n/" clause may only be specified for break variables of format |
| | alphanumeric, binary, numeric or packed. |
| | The value for "n" cannot be greater than the number of positions |
| | defined for the variable, that is, the number of bytes (for |
| | an alphanumeric or binary break variable) or the number of digits |
| | (for a numeric or packed break variable). |
| | Moreover, the value specified must not exceed 253 for alphanumeric |
| | fields and 126 bytes for binary fields. |
| Actn. | Check program and correct error. |

NAT0316: Statement not permitted within specified condition.

| Text | Statement not permitted within specified condition. |
|-------|--|
| | Certain restrictions exist for the use of statements within certain conditions. The specified statement is not allowed in this type of condition. Within an external subroutine object, for example, only DEFINE SUBROUTINE statements and DEFINE DATA statements are allowed. |
| Actn. | Check program and correct error. |

NAT0317: 1 element (column width) must not exceed 250 characters.

| Text | 1 element (column width) must not exceed 250 characters. |
|-------|--|
| Expl. | The maximum length of elements that can be output in a DISPLAY column is 250 characters. |
| Actn. | Redefine element into smaller elements, or have the fields displayed in vertical mode. |

NAT0318: "FULL VALUE" must not be specified in EXAMINE TRANSLATE.

| Text | "FULL VALUE" must not be specified in EXAMINE TRANSLATE. |
|-------|--|
| | Unlike in an EXAMINE statement, "FULL VALUE" must not be specified in an EXAMINE TRANSLATE statement. An EXAMINE TRANSLATE statement always processes the entire content of the field. |
| Actn. | Correct error in program. |

NAT0319: Argument for AVER, TOTAL, SUM must be numeric.

| Text | Argument for AVER, TOTAL, SUM must be numeric. |
|-------|--|
| | The argument for the evaluation of the Natural system functions AVER, TOTAL and SUM must be defined with numeric format. |
| Actn. | Check program and correct error. |

NAT0320: Edit mask permitted for output elements only.

| Text | Edit mask permitted for output elements only. |
|-------|---|
| Expl. | In an INPUT statement, edit masks can only be used for output elements (attribute = M or O). For input elements (attribute = A), edit masks cannot be used. Note that if you use hexadecimal edit masks for output elements, you cannot use attribute M = modify. |
| Actn. | Check program and correct error. |

NAT0322: Type of variable invalid as system function argument.

Text Type of variable invalid as system function argument.

| Expl. | 1) A Natural system variable cannot be used as an argument for a |
|-------|---|
| | Natural system function. |
| | If a system function is to be evaluated from a system variable, |
| | assign the value of the system variable to a user-defined variable |
| | and use this variable as the argument. |
| | 2) A variable used as a password/cipher variable cannot be used as an |
| | argument for a Natural system function. |
| | If the same variable as used for password/cipher is to be used as |
| | an argument for a Natural system function, assign the value to a |
| | user-defined variable, and use that variable as the argument. |
| Actn. | Check program and correct error. |

NAT0323: ON ERROR statement not allowed within condition.

| An ON ERROR statement must not be placed within any of the following statement blocks: • AT START/END OF DATA • AT TOP/END OF PAGE |
|---|
| AT BREAK BEFORE BREAK PROCESSING IF |
| IF NO RECORDS FOUND AT END OF FILE DEFINE SUBROUTINE Check program and correct error. |
| - I - I - I |

NAT0324: DOEND missing for DO statement in line :1:.

| Text | DOEND missing for DO statement in line |
|-------|--|
| Expl. | A statement block initiated with a DO statement must be terminated with a DOEND statement. |
| Actn. | Correct error in program. |

NAT0325: Inconsistent naming of fields in the data dictionary.

| Text | Inconsistent naming of fields in the data dictionary. |
|------|--|
| - | The same field name was used twice in a database view definition in the data dictionary. |
| 1 | Inform your Natural administrator, or use the LIST FILE command to check the view definition. |

NAT0327: Numeric edit mask specifies no valid positions in value.

| Text | Numeric edit mask specifies no valid positions in value. |
|-------|---|
| 1 1 | The specified numeric edit mask does not contain any positions which actually exist in the value to which the edit mask is applied. |
| Actn. | Check program and correct error. |

NAT0328: Maximum number/length of sort fields exceeded.

| Text | Maximum number/length of sort fields exceeded. |
|-------|--|
| Expl. | Either the total length of the fields to be sorted was greater than 253, or the total number of fields to be sorted was greater than 10. |
| Actn. | Reduce the size of the sort criteria. |

NAT0329: AT BREAK required with PERFORM BREAK PROCESSING.

| Text | AT BREAK required with PERFORM BREAK PROCESSING. |
|-------|--|
| Expl. | After a PERFORM BREAK PROCESSING statement, no AT BREAK statement was |
| | issued. |
| | This error can also occur if the PERFORM BREAK PROCESSING is within an |
| | IF condition and the PERFORM BREAK PROCESSING and subsequent AT BREAK |
| | are not explicitly bounded by DO and DOEND statements. |
| Actn. | Check program and correct error. |

NAT0330: AT END OF DATA specified more than once for a loop.

| Text | AT END OF DATA specified more than once for a loop. |
|-------|---|
| Expl. | Only one AT END OF DATA statement is allowed per processing loop. |
| Actn. | Check program and correct error. |

NAT0332: The parameters LC and IC cannot be used together.

| Text | The parameters LC and IC cannot be used together. |
|------------------|---|
| Expl. The LC and | The LC and IC characters are mutually exclusive. |
| Actn. | Check program and correct error. |

NAT0333: Alphanumeric edit mask may not be used for numeric value.

| Text | Alphanumeric edit mask may not be used for numeric value. |
|-------|---|
| - | The error may be caused by an incorrect definition of the edit mask in the data dictionary. |
| Actn. | Check program or data dictionary and correct edit mask specification. |

NAT0335: Text string for SCAN must be enclosed within apostrophes.

| Text | Text string for SCAN must be enclosed within apostrophes. |
|-------|---|
| | The text string to be used for a SCAN operation must be enclosed within apostrophes, and it must be contained on a single source code line. |
| Actn. | Check program and correct error. |

NAT0336: Field to be examined must be a variable if it is modified.

| Text | Field to be examined must be a variable if it is modified. |
|-------|--|
| Expl. | In an EXAMINE statement, the field to be examined must not be a constant if it is to be modified, that is, if a DELETE/REPLACE clause is used. This error also occurs if a constant is specified in an EXAMINE TRANSLATE statement; the field to be TRANSLATEd must be a variable. |
| Actn. | Correct error in program. |

NAT0337: Format/length of translate table must be A2, B2 or U2.

| Text | Format/length of translate table must be A2, B2 or U2. |
|-------|--|
| | The format/length of the translate table specified in the USING clause of an EXAMINE TRANSLATE statement must be A2, B2 or U2. |
| Actn. | Correct error in program. |

NAT0338: A database field with no active reference was used.

| Text | A database field with no active reference was used. |
|-------|---|
| · · | A database field can be referenced only within an active processing loop. If the processing loop has been closed, reference to fields made available by the processing loop is no longer allowed. |
| Actn. | Ensure that all references to database fields are contained within an active processing loop. |

NAT0339: No specific heading allowed for group names in WRITE.

| Text | No specific heading allowed for group names in WRITE. |
|-------|---|
| | If a group name is used in a WRITE (or INPUT) statement, no specific header text may be specified for the group. |
| Actn. | Check program and correct error. |

NAT0340: Invalid tab setting; occupied column overlaid.

| Text | Invalid tab setting; occupied column overlaid. |
|-------|--|
| | The tabulation "nT" can only be used to position forward in a line. The tabulator notation must not position the new value over an already occupied output position. |
| Actn. | Check program and correct error. |

NAT0341: Repetition factor for text string > 250 or invalid.

| Text | Repetition factor for text string > 250 or invalid. |
|-------|---|
| | The repetition factor may be used to cause a one-character text string to be repeated. The repetition factor must be a numeric integer constant enclosed in parentheses. The maximum repetition factor allowed is 250. |
| Actn. | Check program and correct error. |

NAT0342: AT BREAK not possible in this type of processing loop.

| Text | AT BREAK not possible in this type of processing loop. |
|-------|--|
| | The AT BREAK statement may only be used in processing loops that are initiated by a FIND, READ, HISTOGRAM or SORT statement. User-initiated break processing can be done with the statement PERFORM BREAK PROCESSING. |
| Actn. | Check program and correct error. |

NAT0343: Only literal of one character can be used for repetition.

| Text | Only literal of one character can be used for repetition. |
|-------|--|
| | A character string that is to be repeated using a repetition factor may consist of only one single character. |
| Actn. | Check program and correct error. |

NAT0344: WRITE TITLE/TRAILER is not allowed within condition.

| Text | WRITE TITLE/TRAILER is not allowed within condition. |
|-------|--|
| Expl. | A WRITE TITLE or WRITE TRAILER statement must not be placed within any |
| | of the following statement blocks: |
| | - IF |
| | - AT START/END OF DATA |
| | - AT TOP/END OF PAGE |
| | - AT BREAK |
| | - BEFORE BREAK PROCESSING |
| | - AT END OF FILE |
| | - ON ERROR |
| | - IF NO RECORDS FOUND |
| | - DEFINE SUBROUTINE |
| Actn. | Place WRITE TITLE/WRITE TRAILER outside such a statement block. |

NAT0345: Edit mask definition error in data dictionary.

| Text | Edit mask definition error in data dictionary. |
|------|---|
| - | The edit mask for a database field, as defined in the data dictionary, is incorrect. |
| 1 | Contact your Natural administrator. A temporary by-pass may be to override the edit mask definition in the program. |

NAT0346: Data definition module (DDM) :1: cannot be loaded.

| Text | Data definition module (DDM) cannot be loaded. |
|-------|---|
| | The data definition module (DDM) for the requested file cannot be loaded, because the internal DDM load buffer could not be allocated with a sufficient size. |
| Actn. | Start Natural in a larger thread/partition/region/task environment. |

NAT0347: SORT statement must not be placed within condition.

| Text | SORT statement must not be placed within condition. |
|------|---|
|------|---|

| Expl. | The SORT statement closes all existing processing loops and initiates |
|-------|---|
| | a new processing loop to process all records after they have been |
| | sorted. The SORT statement, therefore, cannot be placed within any |
| | of the following statement blocks: |
| | - AT START/END OF DATA |
| | - AT TOP/END OF PAGE |
| | - AT BREAK |
| | - BEFORE BREAK PROCESSING |
| | - AT END OF FILE |
| | - IF |
| | - IF NO RECORDS FOUND |
| | - ON ERROR |
| | - DEFINE SUBROUTINE |
| Actn. | Check program and correct error. |

NAT0348: AT TOP/END OF PAGE must not be placed within condition.

| Text | AT TOP/END OF PAGE must not be placed within condition. |
|-------|---|
| Expl. | The statements AT TOP OF PAGE and AT END OF PAGE can only be used |
| | outside the following statement blocks: |
| | - AT START/END OF DATA |
| | - AT TOP/END OF PAGE |
| | - AT BREAK |
| | - BEFORE BREAK PROCESSING |
| | - AT END OF FILE |
| | - IF |
| | - IF NO RECORDS FOUND |
| | - ON ERROR |
| | - DEFINE SUBROUTINE |
| Actn. | Place AT TOP/END OF PAGE outside such a statement block. |

NAT0349: Invalid parameter value in (SET) GLOBALS statement/cmd.

| Text | Invalid parameter value in (SET) GLOBALS statement/command. |
|-------|--|
| | The value for a parameter specified in a SET GLOBALS statement (or GLOBALS command) was invalid. Possible values for the parameter in question are "ON" and "OFF" (or "T" and "F" respectively). |
| Actn. | Check program and correct error. |

NAT0350: Too many vertical entries in one INPUT/WRITE/DISPLAY.

| Text | Too many vertical entries in one INPUT/WRITE/DISPLAY. |
|-------|---|
| · · | One INPUT, WRITE or DISPLAY statement can generate a maximum of 250 |
| | lines vertically. |
| | The row value in the notation "X/Y" must not exceed 250. |
| | The number of header lines must not exceed 14. |
| Actn. | Check program and correct error. |

9

Natural System Error Messages 0351-0400

NAT0351: No header text allowed for VERT, NOHDR, second DISPLAY.

| Text | No header text allowed for VERT, NOHDR, second DISPLAY. |
|-------|--|
| Expl. | Header text is not allowed for any other than the first DISPLAY statement of a report. In VERT mode, header text for individual fields can only be specified if the option "CAPTIONED" is used; the header texts for the fields will then be placed vertically above the column as header text. If the option AS "text" is used together with CAPTIONED, the text specified for an individual field will be placed in the same line as as the field value before the field value in the column. No header text is allowed for a DISPLAY statement which refers to the same report as a previous DISPLAY statement which has already created a header. |
| Actn. | Check program and correct error. |

NAT0352: SF parameter in FORMAT/SET GLOBALS > 30 or not numeric.

| Text | SF parameter in FORMAT/SET GLOBALS > 30 or not numeric. |
|-------|--|
| | The value for the parameter SF must be specified as a numeric integer constant. The maximum value is 30. |
| Actn. | Check program and correct error. |

NAT0353: Parameter must not be previously defined.

| Text | Parameter must not be previously defined. |
|-------|---|
| Expl. | Only the first parameter address is passed to the called program. All other parameters must be physically positioned immediately after the first parameter. This can only be achieved if the parameter variables are newly defined in the CALL FILE or READ WORK FILE statement respectively. |
| Actn. | Do not refer to previously defined variables in a CALL FILE statement. |

NAT0354: Filler character for input field specified incorrectly.

| Text | Filler character for input field specified incorrectly. |
|-------|--|
| Expl. | The character which is to be used to fill the empty part of an input field must be specified as a single character enclosed in apostrophes. It may be specified anywhere in the list of values of the AD parameter. Example: INPUT (AD="<") #FIELDA #FIELDB |
| Actn. | Correct error in program. |

NAT0355: Invalid attribute definition element after "AD=".

| Text | Invalid attribute definition element after "AD=". |
|-------|--|
| | See the Natural documentation, session parameter AD, for information on valid values for the AD parameter. Furthermore, this error appears in a INPUT statement if - (AD=M) is specified for a system variable other than *COM; - (AD=T) is specified for a system variable. |
| Actn. | Check program and correct error. |

NAT0357: Invalid entry for OFFSET/FILLER in READ WORK FILE.

| Text | Invalid entry for OFFSET/FILLER in READ WORK FILE. |
|-------|---|
| Expl. | The OFFSET/FILLER in a record layout for READ WORK FILE |
| | must be specified as an integer numeric constant. |
| | The filler entry may be specified in the form "nX". |
| | This error also occurs if the OFFSET or FILLER option is placed |
| | in the wrong position within the READ WORK FILE statement. |
| | See the Natural documentation for the valid |
| | READ WORK FILE statement syntax. |
| Actn. | Correct error in program. |

NAT0358: No attribute definition specified after "AD=".

| Text | No attribute definition specified after "AD=". |
|-------|--|
| Expl. | At least one attribute setting is required when using "AD=". |
| Actn. | Check program and correct error. |

NAT0359: Processing loop in subroutine not closed.

| Text | Processing loop in subroutine not closed. |
|-------|--|
| | If a processing loop is initiated in a subroutine, it must be closed within the same subroutine with a LOOP statement. The LOOP statement must precede the RETURN statement. |
| Actn. | Check program and correct error. |

NAT0360: No executable statement in IF condition.

| Text | No executable statement in IF condition. |
|-------|---|
| Expl. | Statements such as REDEFINE or FORMAT do not generate executable code; therefore, they are not allowed as the only statements in an IF condition. A redefinition of a variable is true under all conditions; it is therefore not recommended to place a REDEFINE or FORMAT statement within an IF condition. |
| Actn. | Check program and correct error. |

NAT0361: Printer number not allocated.

| Text | Printer number not allocated. |
|-------|---|
| - | Either a corresponding JCL statement for the specified printer was not specified; |
| | or, if a TP monitor is used, either the TP monitor does not support offline printers or the necessary parameter module was not generated. |
| Actn. | Correct the printer number or contact your Natural administrator. |

NAT0362: Recursive definition of a subroutine.

| Text | Recursive definition of a subroutine. |
|-------|--|
| Expl. | A subroutine definition, which is initiated with a DEFINE SUBROUTINE statement, must be terminated with an END-SUBROUTINE or RETURN statement before another subroutine definition can be initiated. A DEFINE SUBROUTINE statement within another DEFINE SUBROUTINE statement block is not possible. |
| Actn. | Check program and correct error. |

NAT0363: Invalid definition of a subroutine.

| Text | Invalid definition of a subroutine. |
|-------|---|
| Expl. | A DEFINE SUBROUTINE statement must not be placed within any of the following condition statement blocks: - AT START OF DATA - AT END OF DATA - AT TOP OF PAGE |
| | - AT END OF PAGE - AT BREAK - BEFORE BREAK PROCESSING - AT END OF FILE - IF NO RECORDS FOUND - ON ERROR |
| Actn. | Correct error in program. |

NAT0364: Inconsistency in multiple writing to the same work file.

| Text | Inconsistency in multiple writing to the same work file. |
|-------|--|
| | This error occurs if one program contains two (or more) WRITE WORK FILE statements that write data to the same work file: - Writing to the same work file must be either all in fixed length or all in variable length; that is, the keyword "VARIABLE" must be specified either in every WRITE WORK FILE statement concerned or in none. (Please note that in this context an EXPORT statement corresponds to a WRITE WORK FILE (1) VARIABLE statement.) - If writing to the same work file is all in fixed length, the sum of field lengths must be the same for every WRITE WORK FILE statement concerned. |
| Actn. | Correct error in program. |

NAT0366: Invalid use of Natural system function.

| Text | Invalid use of Natural system function. |
|-------|---|
| | Natural system functions like MAX, MIN, SUM or AVER can only be used with the conditions AT BREAK, AT END DATA, AT END PAGE. |
| Actn. | Check program and correct error. |

NAT0367: Invalid reference of Natural system function.

| Text | Invalid reference of Natural system function. |
|-------|--|
| | Natural system functions like MAX, MIN, SUM and AVER may only be used in an AT END OF PAGE condition if their evaluation per page has been requested with the GIVE SYSTEM FUNCTIONS clause of a DISPLAY or WRITE statement. |
| Actn. | Check program and correct error. |

NAT0368: Search field for a descriptor is too long.

| Text | Search field for a descriptor is too long. |
|-------|---|
| Expl. | The maximum length for a search field is 126 bytes. |
| Actn. | Check program and correct error. |

NAT0369: Parameter DY may only be used with alphanumeric fields.

| Text | Parameter DY may only be used with alphanumeric fields. |
|-------|---|
| | Dynamic attributes (blinking, intensified, underlined, color, etc.) may only be applied to alphanumeric fields. |
| Actn. | Check program and correct error. |

NAT0370: Invalid concatenation of alphanumeric constants.

| Text | Invalid concatenation of alphanumeric constants. |
|-------|---|
| Expl. | A concatenation character ("-") was found, but the linked constant segment is missing or of an incorrect format. |
| | When an alphanumeric constant ("text" or H"") is followed by a |
| | hyphen character ("-"), another alphanumeric constant has to follow. Example: "ABC"-"DEF"-H"F1F2F3"-"XYZ" |
| | When a constant of format Unicode (U"text" or UH"") is followed by a hyphen character ("-"),another constant of format Unicode has to follow. |
| | Example: U"ABC"-U"DEF"-UH"00310032"-U"XYZ" |
| | A mix of alphanumeric and Unicode constant segments is not permitted. |
| Actn. | Check program and correct error. |

NAT0373: Error in increment specification for RENUMBER.

| Text | Error in increment specification for RENUMBER. |
|-------|---|
| Expl. | The line editor allows an increment, in the form (nnnn), to be specified for renumbering. The increment you have specified would cause line numbers greater than 9999. |
| Actn. | Choose an increment for renumbering that does not cause the line numbers to exceed 9999. |

NAT0375: Invalid value for format element.

| Text | Invalid value for format element. |
|-------|---|
| | For this type of format element, the only possible values are "ON" and "OFF" (or "T" and "F" respectively). |
| Actn. | Check program and correct error. |

NAT0376: Global variables :1: do not match.

| Text | Global variables do not match. |
|-------|---|
| Expl. | The global variables that are to be passed between programs do not agree in format and/or length. Global variables with the same name must agree in format and length to allow for a value transfer of the global variable across multiple programs when referenced as data as "+NAME". |
| Actn. | Check the currently existing global variables with the EDIT VARIABLES command and compare them to the reference in the current program. Adjust format/length or clear global variables with the LOGON command. |

NAT0378: Field must not be placed under group using "/" notation.

| Text | Field must not be placed under group using "/" notation. |
|-------|--|
| | If a group of fields is referenced in a DISPLAY statement, the group creates a layout of multiple columns for all individual fields in the group. No individual field can be placed under the group layout. |
| Actn. | Place individual field in a separate column. |

NAT0379: Error in construction of print positioning of form "x/y".

| Text | Error in construction of print positioning of form "x/y". |
|-------|--|
| | The positioning notation "x/y" can only be used with constants for "x" and "y". The positioning must not place the current print position outside the range of line and column positions that are available with the current line size and page size limits. The line position must not overlay an already occupied print position. |
| Actn. | Check program and correct error. |

NAT0380: Error in the construction of a dynamic source variable.

| Text | Error in the construction of a dynamic source variable. |
|-------|---|
| | The character "&", which indicates a dynamic source variable, was found, but the "&" was not followed by a valid variable name. |
| | found, but the & was not followed by a valid variable name. |
| Actn. | Check program and correct error. |

NAT0383: Source program in source work area incorrectly numbered.

| Text | Source program in source work area incorrectly numbered. |
|-------|---|
| | To ensure that all references in a program can be resolved correctly, it is necessary that the source code lines are numbered in ascending order. |
| Actn. | Use the RENUMBER command to renumber the program, check all references for consistency with intended reference (when duplicate numbers exist). All references will be renumbered automatically. |

NAT0384: Explicit format specification required.

| Text | Explicit format specification required. |
|-------|---|
| | The FS parameter has been set with a SET GLOBALS statement or GLOBALS command to indicate that no default format/length is to be used. Therefore the format/length of all user-defined variables must be explicitly specified. |
| Actn. | Check program and correct error. |

NAT0385: Values for DC, IA, ID parameters must exclude one another.

| Text | Values for DC, IA, ID parameters must exclude one another. |
|------|---|
| | The values for the session parameters DC, IA and ID must exclude one another. The value for each of these parameters must be different from the values for the other two. |
| | Use the GLOBALS command to check the values for DC, IA and ID and make sure that the 3 parameter have 3 different values. |

NAT0386: Undefined global variable used for source reference.

| Text | Undefined global variable used for source reference. |
|-------|---|
| Expl. | All global variables that are to be referenced for source parameters in the form "&NAME" must have been previously defined from the execution of a program that assigns a value to this global variable. If a source program using global notations is to be created, this can be done without control of the syntax checker, using the EDIT command. When the syntax checker is to be active during the creation of such program, the proper global variable environment must be created prior to any "&NAME" reference. |
| Actn. | Either create program in EDIT mode or establish proper global variable environment by executing programs that define the global variables prior to any "&NAME" reference. |

NAT0387: Modification of a named constant not allowed.

| Text | Modification of a named constant not allowed. |
|-------|--|
| | If a variable is to have an initial value, which will be changed in the program, and the original value is to be used again later in the program, use the INIT clause of the DEFINE DATA statement and a RESET INITIAL statement. |
| Actn. | Check program and correct error. |

NAT0389: Invalid reference "0000" specified.

| Text | Invalid reference "0000" specified. |
|-------|--|
| · · | When you reference a database access statement by specifying the line number, the line number can never be "0000". |
| Actn. | Check program and correct error. |

| Text | Variable of format/length F16 is not allowed here. |
|-------|--|
| Expl. | A floating-point variable of length 16 is not allowed with |
| | the following statements: |
| | - DISPLAY |
| | - WRITE |
| | - PRINT |
| | - INPUT |
| Actn. | Do not use an F16 variable in any of the above statements. |

NAT0390: Variable of format/length F16 is not allowed here.

NAT0392: Invalid operation with date or time variable.

| Text | Invalid operation with date or time variable. |
|-------|---|
| Expl. | This error may be caused by the following: An arithmetic operator other than "+","-","*" or "-" was used between a date/time operand and/or a numeric operand. An arithmetic operator with one date/time operand and one floating-point operand was used. A field of a format other than date is assigned to a date variable. See Natural documentation, Arithmetic Operations with Date and Time, for further information. |
| Actn. | Check program and correct error. |

NAT0393: Program cannot be executed.

| Text | Program cannot be executed. |
|-------|---|
| Expl. | An attempt was made to execute a Natural programming object or load a GDA, LDA, PDA or map at compilation which is not supported by the current version of Natural. For a list of supported Natural program versions, see the corresponding Natural documentation. The program to be executed is contained in the blacklist of the current buffer pool (see the SYSBPM utility documentation). |
| Actn. | Re-compile the program under the current version of Natural. Remove the program from the blacklist. |

NAT0394: Invalid format specification.

| Text | Invalid format specification. |
|---------------------|---|
| Expl. See the Natur | See the Natural session parameters documentation for details. |
| Actn. | Check program and correct error. |

NAT0395: Attribute "CV" must be defined before "HE" definition.

| Text | Attribute "CV" must be defined before "HE" definition. |
|-------|--|
| Actn. | Check program and correct error. |

NAT0396: Roman edit mask for input fields not allowed.

| Text | Roman edit mask for input fields not allowed. |
|-------|--|
| 1 | A roman edit mask can be used in an INPUT statement, but only for output fields. Example: INPUT #D (EM=R AD=O) |
| Actn. | Check program and correct error. |

NAT0397: Invalid index range in INPUT or WRITE statement.

| Text | Invalid index range in INPUT or WRITE statement. |
|-------|--|
| Expl. | In an INPUT or WRITE statement, the index range notation of an array is invalid because the number of occurrences is not known during compilation. Examples of invalid index ranges: - range with different variables : (#I:#J) - range with constant and variable : (1:#i) - complete range notation of an X array: (*) Examples of valid index ranges: - range with constants : (1:5) - range with the same variables : (#I:#I+5) |
| Actn. | Supply a valid index range. |

NAT0398: Label definition must be coded at beginning of line.

| Text | Label definition must be coded at beginning of line. |
|-------|--|
| Actn. | Check program and correct error. |

NAT0399: INCLUDE statement must be only statement in source line.

| Text | INCLUDE statement must be only statement in source line. |
|------------|---|
| _ _ | The INCLUDE statement must be the only statement contained in a given source code line. |
| Actn. | Check program and correct error. |

NAT0400: Invalid library ID.

| Text | Invalid library ID. |
|-------|---|
| Expl. | A library ID must not be longer than 8 characters. |
| | It can consist of upper-case alphabetical characters, numeric digits, |
| | and certain special characters. It must not contain any blank |
| | characters. |
| | Its first character must be an upper-case alphabetical character. |
| | For more information on library naming conventions, see the |
| | Natural documentation. |
| Actn. | Use a correct library ID. |

10 Natural System Error Messages 0401-0450

NAT0401: Invalid program name.

| Text | Invalid program name. |
|-------|--|
| - | A program name must begin with an alphabetical character and must not be longer than 8 characters. |
| Actn. | Use correct program name. |

NAT0402: "text" for EDIT command does not end with apostrophe.

| Text | "text" for EDIT command does not end with apostrophe. |
|-------|---|
| | "text" can be used in the line editor to position to a specific line beginning with that text string. "S"text" can be used to scan the source program for the specified text and select all lines containing the text. |
| Actn. | Check command and correct error. |

NAT0403: Invalid line editor subcommand.

| lext Invalid line editor subcommand. | Text Inva | lid line editor subcommand. |
|--------------------------------------|-----------|-----------------------------|
|--------------------------------------|-----------|-----------------------------|

| Expl. | The following subcommands may be used in the line editor: |
|-------|--|
| | .B position to bottom |
| | .Cn(m) copy m lines starting from line identified with n |
| | .C"text"(m) copy the line beginning with "text" to position m |
| | .D delete line |
| | .D(n) delete n lines |
| | .E terminate line |
| | .I insert line |
| | .I(program) insert program |
| | .Mn move lines identified by n |
| | .M"text"(n) move n lines starting from line beginning with "text" |
| | .R(n) renumber with increment n default n=10 |
| | .S"text" scan for text |
| | See Natural documentation, EDT command, for use of PF keys. |
| Actn. | See Natural documentation, EDT command, for use of PF keys. Issue a valid command. |

NAT0404: Number for "+/-" in EDIT command invalid.

| Text | Number for "+/-" in EDIT command invalid. |
|-------|---|
| | "+/-n" can be used to position forward/backward in the line editor. "n" must be a numeric constant, and must immediately follow "+/-". |
| Actn. | Enter a valid command. |

NAT0406: Explicit index range not allowed with SORT.

| Text | Explicit index range not allowed with SORT. |
|-------|--|
| Expl. | Only complete arrays can be specified in the USING clause of the SORT statement. This can be achieved by specifying "*" as index or by explicitly specifying the complete range of constants. Example: 01 ARRAY (A5/1:20) SORT BY USING ARRAY(*) or SORT BY USING ARRAY(1:20) |
| Actn. | Check program and correct error. |

NAT0407: Invalid tab notation "nT".

| Text | Invalid tab notation "nT". |
|-------|--|
| | The "nT" positioning must be within the useable line size. "n" must not be zero or a value greater than the currently specified line size. |
| Actn. | Check program and correct error. |

| Text | Tab notation "nT" duplicated or invalid in VERT mode. |
|-------|---|
| Expl. | The "nT" positioning can be used to position to a specific output position. In VERT mode, positioning can only be done once between two columns. It cannot be specified for individual fields in VERT mode, because the column position can only be defined once before the VERT entry. If indentation is required, use the "nX" notation within a column. |
| Actn. | Check program and correct error. |

NAT0408: Tab notation "nT" duplicated or invalid in VERT mode.

NAT0409: Position ref. to field only allowed once between columns.

| Text | Position reference to field only allowed once between columns. |
|-------|--|
| Expl. | The position reference of the form "T*NAME" can only be used to position to a new column in a DISPLAY statement. Within a column in VERT mode, it is not possible to position individual fields with the "T*NAME" notation. If indentation is required within a column, use the "nX" notation. |
| Actn. | Check program and correct error. |

NAT0411: Print position reference must be in first DISPLAY.

| Text | Print position reference must be in first DISPLAY. |
|-------|---|
| | Only the first DISPLAY statement creates a print position reference. Reference to print positions (columns) in the form "T*NAME" can only be made to variables that have been defined as columns in the first DISPLAY statement defined in the program. The short-form notation (2 characters) for database fields is not permitted. |
| Actn. | Correct error. |

NAT0412: "nX" or "nT" notation positions beyond line size.

| Text | "nX" or "nT" notation positions beyond line size. |
|-------|--|
| | The notation "nX" or "nT" resulted in an output position that lies |
| | beyond the currently specified line size. |
| Actn. | Either correct the nX/nT notation or increase line size parameter. |

NAT0413: Module in source library does not exist for .I(name).

| Text | Module in source library does not exist for .I(name). |
|-------|---|
| | The source module to be copied from the source library cannot be located in the current library, or the entry ".I(name)" was not specified correctly. |
| Actn. | Re-issue command using correct source module name. |

NAT0415: "T*" and "P*" notation not permitted in PRINT statement.

| | "T*" and "P*" notation not permitted in PRINT statement. |
|-------|--|
| Actn. | Do not use "T*" or "P*" in a PRINT statement. |

NAT0416: "x/y" notation not permitted with PRINT statement.

| Text | "x/y" notation not permitted with PRINT statement. |
|-------|---|
| Actn. | Do not use the notation "x/y" in a PRINT statement. |

NAT0417: Variable index range not permitted with READ WORK FILE.

| Text | Variable index range not permitted with READ WORK FILE. |
|-------|---|
| Actn. | Check program and correct error. |

NAT0418: "RETURN" is not permitted in structured mode.

| Text | "RETURN" is not permitted in structured mode. |
|-------|---|
| | The RETURN statement is permitted in reporting mode only. In structured mode, the end of a subroutine definition must be indicated with the statement END-SUBROUTINE. |
| Actn. | Check program and correct error. |

NAT0419: "USING" is required in structured mode.

| Text | "USING" is required in structured mode. |
|-------|---|
| Expl. | When the SORT statement is used in structured mode, the USING clause has to be used to indicate the fields which are to be written to intermediate storage. If USING KEYS is specified, all sort-key fields are written to intermediate storage. USING operand2 may be used to indicate fields in addition to the sort-key fields which are to be written to intermediate storage. By default in structured mode, the fields specified in the BY clause are NOT written to intermediate sort storage. |

Actn. Check program and correct error.

NAT0422: Invalid or misplaced statement in external subroutine.

| Text | Invalid or misplaced statement in external subroutine. |
|-------|--|
| Expl. | An external subroutine must not contain more than one DEFINE SUBROUTINE statement. The DEFINE SUBROUTINE statement block must be closed with END-SUBROUTINE (or RETURN, in reporting mode). |
| | The only statements allowed outside the DEFINE SUBROUTINE block are DEFINE DATA LOCAL/GLOBAL, which must precede the DEFINE SUBROUTINE statement, and END at the end of the subroutine. |
| Actn. | Correct error in external subroutine. |

NAT0423: Invalid GIVING LENGTH clause in READ WORK FILE statement.

| Text | Invalid GIVING LENGTH clause in READ WORK FILE statement. |
|-------|---|
| Expl. | Possible reasons for this error are: |
| | 1. The keyword "LENGTH" is missing after "GIVING". |
| | 2. The operand is either missing or defined with |
| | an incorrect format/length (format/length must be I4). |
| Actn. | Check program and correct error. |

NAT0424: Invalid operand for PC "COMMAND" option.

| Text | Invalid operand for PC "COMMAND" option. |
|-------|---|
| | The operand for the COMMAND option of the WRITE WORK FILE/WRITE PC/DOWNLOAD statement must be of alphanumeric format and its length must not exceed 80 characters. |
| Actn. | Check program and correct error. |

NAT0425: Invalid use of a qualified variable name.

| Text | Invalid use of a qualified variable name. |
|-------|--|
| | Qualified variable names may only be used when referencing data variables. They cannot be used when defining variables in a DEFINE DATA statement. |
| Actn. | Check program and correct error. |

NAT0426: Invalid use of variable name in data structure.

| Text | Invalid use of variable name in data structure. |
|-------|--|
| | In the DEFINE DATA statement, a variable name was used in defining a data structure that currently exists. The earlier variable definition was not part of another data structure. |
| Actn. | Check program and correct error. |

NAT0428: Invalid variable name definition in a data structure.

| Text | Invalid variable name definition in a data structure. |
|-------|---|
| Expl. | A variable name used in the DEFINE DATA statement already exists. |
| | The earlier definition of this variable name describes a data |
| | element that is contained within the current data structure. |
| | Non-unique variable names in a DEFINE DATA statement are referenced |
| | by qualifying the variable with the level 1 structure name. |
| | Therefore, two data structure variables with the same variable name |
| | can not co-exist if they share the same level 1 structure name. E.g.: |
| | 1 GROUP |
| | 2 STRUCTURE-1 |
| | 3 SAME-NAME (A1) |
| | 2 STRUCTURE-2 |
| | 3 SAME-NAME (N7) <== cannot be uniquely referenced. |
| | 1 OTHER-STRUCTURE |
| | 2 SAME-NAME (P4) <== unique reference as "OTHER-STRUCTURE.SAME-NAME" |
| Actn. | 2 SAME-NAME (P4) <== unique reference as "OTHER-STRUCTURE.SAME-NAME" Check program and correct error. |

NAT0429: Index for database array incorrectly specified.

| Text | Index for database array incorrectly specified. |
|-------|--|
| Expl. | When defining an array, the index specification for each |
| | dimension must not include a non self-defining range. |
| | A range which is not self-defining includes any of the |
| | following index specifications: |
| | #FIELD(#I + 1) or #FIELD(#J - 1) |
| | #FIELD(*) |
| | #FIELD(#I + #J) |
| Actn. | Check program and correct error. |

NAT0431: Qualifiers must be structure names on level 1.

| Text | Qualifiers must be structure names on level 1. |
|-------|---|
| Expl. | To identify a variable which is defined inside a data structure, you may prefix the variable name with the name of the level-1 structure field, separated with a period. Only level-1 structure field names can be used as field qualifiers; fields defined on level 2 or higher are not permitted. |
| Actn. | Supply a valid qualifier field. |

NAT0434: Qualification does not uniquely identify variable.

| Text | Qualification does not uniquely identify variable. |
|-------|---|
| | The qualified name list does not uniquely describe the current variable name. |
| Actn. | Check program and correct error. |

NAT0435: Index for database array incorrectly specified.

| Text | Index for database array incorrectly specified. |
|-------|---|
| Expl. | The Natural Version 1.2 notation of defining an index range with the "-" character cannot be used to reference a database array which was defined using the Version 2.1 notation, that is the character ":". The converse is not permitted either. Neither is it permitted to mix the two notations when defining a database array. Neither are the index notations "I + 1" or "I - 2" etc. permitted when referencing a database array that was defined with the Version 1.2 notation. |
| Actn. | Check program and correct error. |

NAT0436: The internal size of a data structure is too big.

| Text | The internal size of a data structure is too big. |
|-------|---|
| 1 | The size of a data structure in the DEFINE DATA statement is too big. |
| Actn. | Reduce number of variables or number of occurrences for a variable. |

NAT0437: Constant definition missing for current structure.

| Text | Constant definition missing for current structure. |
|-------|---|
| - | If a variable is defined as a named constant via the keyword "CONST" in a DEFINE DATA statement, each elementary field of that structure must be defined as a constant. |
| Actn. | Check program and correct error. |

NAT0438: Record length must not exceed 1073741824 bytes.

| Text | Record length must not exceed 1073741824 bytes. |
|-------|--|
| | The length of a record read/written with a READ/WRITE WORK FILE statement must not exceed 1073741824 bytes (= 1 GB). |
| Actn. | Check program and correct error. |

NAT0439: Variable-length field only allowed in WRITE WORK VARIABLE.

| Text | Variable-length field only allowed in WRITE WORK VARIABLE. |
|-------|---|
| | Fields with variable length cannot be used in a WRITE WORK FILE statement without VARIABLE clause. Incorrect example: WRITE WORK FILE 1 array(1:j) Correct example : WRITE WORK FILE 1 VARIABLE array(1:j) |
| Actn. | Check program and correct error. |

NAT0440: DISPLAY and NEWPAGE not allowed in AT TOP/END OF PAGE.

| Text | DISPLAY and NEWPAGE not allowed in AT TOP/END OF PAGE. |
|-------|---|
| Expl. | A DISPLAY or a NEWPAGE statement must not be placed within an AT TOP OF PAGE or AT END OF PAGE statement block. |
| Actn. | Correct error in program. |

NAT0441: RETURN or END-SUBROUTINE not allowed within a condition.

| Text | RETURN or END-SUBROUTINE not allowed within a condition. |
|-------|--|
| Expl. | A RETURN or END-SUBROUTINE statement must not be placed within any of the following statement blocks: - AT START/END OF DATA - AT TOP/END OF PAGE - AT BREAK - BEFORE BREAK PROCESSING - AT END OF FILE - IF NO RECORDS FOUND - ON ERROR |

Actn. Correct error in program/subroutine.

NAT0442: RETRY statement is not allowed within condition.

| Text | RETRY statement is not allowed within condition. |
|-------|--|
| Expl. | A RETRY statement must not be placed within any of the following |
| | statement blocks: |
| | - AT START/END OF DATA |
| | - AT TOP/END OF PAGE |
| | - AT BREAK |
| | - BEFORE BREAK PROCESSING |
| | - AT END OF FILE |
| | - IF NO RECORDS FOUND |
| | - DEFINE SUBROUTINE |
| Actn. | Correct error in program. |

NAT0443: C routine name not found in jump table.

| Text | C routine name not found in jump table. |
|-------|--|
| Expl. | CALL <module> <routine> <arguments></arguments></routine></module> |
| | The routine declared by <routine> is not found by the jump table</routine> |
| | look-up routine declared in the module header csect <module>.</module> |
| | Note that the jump table look-up routine is also written in C. |
| Actn. | This is an internal Natural Expert error. Please contact |
| | Software AG and describe how the error was produced. |

NAT0444: LFILE directive for Entire system file is not type Entire.

| Text | LFILE directive for Entire system file is not type Entire. |
|-------|--|
| Expl. | Check the LFILE directives for the Entire system files (249,250). Check the Entire NTDB macro entry for validity. In the NATPARM module, the NTDB macro determines the database type: - NTDB ENTIRE,xyz (where "xyz" is the database ID) The NTLFILE macro in the NATPARM module describes the Entire cross-reference and data files: - NTLFILE 249,xyz,10 (SYS1) - NTLFILE 250,xyz,11 (SYS2) Alternatively, LFILE can be specified as dynamic parameter; for example: - LFILE=(249,xyz,10),LFILE=(250,xyz,11) In both cases, the database handler must be declared as being of type ENTIRE. See the Natural documentation for further information. |
| Actn. | Contact your Entire DB administrator. |

NAT0445: C buffer being used by another application.

| Text | C buffer being used by another application. |
|-------|--|
| Expl. | Two applications are using the same Natural buffer. This error is detected on starting the second application and as it is desirable to protect data, the second application is not allowed to start. |
| Actn. | The problem could be resolved if the two applications were to use separate buffers - please contact Software AG. |

NAT0446: Statement name found in attribute expression.

| Text | Statement name found in attribute expression. |
|-------|--|
| · · | This error occurs if you have defined an attribute to a category which has the same name as a Natural keyword. |
| Actn. | Rename the attribute. |

NAT0447: FIND UNIQUE not allowed for Entire files.

| Text | FIND UNIQUE not allowed for Entire files. |
|-------|--|
| Expl. | This statement is not supported by Entire. |
| Actn. | Correct error in program. |

NAT0448: C interface - get memory buffer failed.

| Text | C interface - get memory buffer failed. |
|-------|--|
| Expl. | When a function written in C performs a MALLOC operation to get a work buffer, this is supplied to it by the GETMAIN# entry in the environment interface NICMAIN, which in turn gets it from the second buffer declared in the C module header. This buffer has not been defined in the Natural environment. With Natural Expert this means that no EXRSIZE or EXCSIZE could be allocated. |
| Actn. | Check whether there is enough space for the EXRSIZE or EXCSIZE as defined in the NATPARM module or increase the buffer size(s). |

NAT0449: C work buffer too small.

| Text | C work buffer too small. |
|-------|---|
| | CALL <module> <routine> <arguments> On initialization of the C work buffer, the minimum size required is <size extern="" of="" static=""> + 4K.</size></arguments></routine></module> |
| Actn. | This is an internal Natural Expert error, please contact Software AG. |

NAT0450: Not enough memory to run C subroutines.

| Text | Not enough memory to run C subroutines. |
|------|--|
| | This is an internal Natural Expert error, please contact Software AG. |

11 Natural System Error Messages 0451-0500

NAT0451: Entire DB Request Handler not loaded or cannot be found.

| Text | Entire DB Request Handler not loaded or cannot be found. |
|-------|--|
| | The Entire DB Request Handler is contained for Natural Version 2.1 in the module "AERNAT", and for Natural Version 2.2 in the module "NATDREQ". Most likely, this module is not linked to Natural. |
| Actn. | Check the link job and re-link Natural with the required module. |

NAT0452: Entire cannot be initialized.

| Text | Entire cannot be initialized. |
|-------|---|
| | The cause is either that - there was not enough space to satisfy the request; - the Entire buffer (ZSIZE) is too small - minimum is 44; - the Adabas/Entire nucleus (AERNUC) is not accessible, because it is not linked or cannot be loaded dynamically. |
| Actn. | Contact your Entire DB administrator. |

NAT0454: Relocatability error in Entire DB.

| Text | Relocatability error in Entire DB. |
|-------|------------------------------------|
| Actn. | Check program and correct error. |

NAT0455: First command to Entire not "DLOGON".

| Text | First command to Entire not "DLOGON". |
|-------|---|
| | Before accessing the Entire data in any way, a DLOGON statement must be successfully executed. This allows the user identity to be determined, the application to be set, and security check and accessibility of data to be determined. |
| Actn. | Ensure that the system calls a DLOGON before access, and correct code. |

NAT0456: Invalid function code for Entire.

| Text | Invalid function code for Entire. |
|-------|--|
| Expl. | Entire has received a control block (same format as Adabas) which has a function code field (offset 2 in the CB) that cannot be interpreted by Entire. This is most likely caused by an incompatibility of systems and/or overwriting of the Entire work area. |
| Actn. | Produce an application dump and contact Software AG support. |

NAT0457: Entire version incompatibility.

| Text | Entire version incompatibility. |
|------|---|
| | This is caused by linking the interface CSECT DDIPFNAT (AERNUC) with another version of the initialization module ADDINIT (AERNAT). |
| | Check the Natural/Entire link job for "INCLUDE" datasets, or contact your system administrator. |

NAT0458: No "RETAIN AS" set with the given name exists.

| Text | No "RETAIN AS" set with the given name exists. |
|-------|---|
| | This occurs when, for example, a FIND references a non-existent or released ISN set. See FIND statement, RETAIN clause, in the Entire DB Programmer''s Guide for further information. |
| Actn. | Make sure that usage of ISN sets in application program is correct. |

NAT0459: Control Block is not aligned.

| Text | Control Block is not aligned. |
|-------|--|
| Expl. | The Control Block in direct command must be full-word aligned. |
| Actn. | Check the program and align the Control Block. |

NAT0460: Record length is greater than Open length.

| Text | Record length is greater than Open length. |
|-------|--|
| | Entire DB has attempted to write a record via EXPORT/IMPORT to work file 1. This work file has already been opened with a record of length less than 4096 bytes. |
| Actn. | Check program for reads/writes and make sure that the first read or write is at least 4096 bytes. Alternatively, check the DCB. |

NAT0461: Error in CONTROL clause of DEFINE WINDOW statement.

| Text | Error in CONTROL clause of DEFINE WINDOW statement. |
|-------|--|
| Expl. | The CONTROL clause of the DEFINE WINDOW statement must be specified as follows: CONTROL SCREEN, or CONTROL WINDOW. If the CONTROL clause is omitted, CONTROL WINDOW will apply by default. |
| Actn. | Check program and correct error. |

NAT0462: Error in SYMBOL clause of DEFINE WINDOW statement.

| Text | Error in SYMBOL clause of DEFINE WINDOW statement. |
|-------|--|
| - | See the Natural documentation for the correct syntax of the DEFINE WINDOW statement. |
| Actn. | Check program and correct error. |

NAT0463: Invalid color or invalid attribute specified.

| Text | Invalid color or invalid attribute specified. |
|------|---|
| | You have specified an invalid attribute or an invalid color code, either in the REVERSED clause or the FRAMED clause of the DEFINE WINDOW statement. The only attribute you may specify in a REVERSED or FRAMED clause is CD (color definition). The color definition must be specified as (CD=cc), where "cc" is the color code. For information on valid color codes, see the Natural documentation. |

Actn. Check program and correct error.

NAT0464: Window name in DEFINE/SET WINDOW missing or invalid.

| Te | xt | Window name in DEFINE/SET WINDOW stmt. missing or invalid. |
|----|------|---|
| Ex | | In a DEFINE/SET WINDOW statement, the name of the window must be specified directly after the keywords "DEFINE/SET WINDOW". For window names, the same rules apply as for names of user-defined variables (as described in the Natural documentation). |
| Ac | ctn. | Check program and correct error. |

NAT0465: Inconsistent usage of WINDOW :1:.

| Text | Inconsistent usage of WINDOW |
|-------|--|
| Expl. | Either the window name has been defined twice in two DEFINE WINDOW statements. or a window is referenced in the program (e.g. with an INPUT WINDOW statement), but the window has not been defined in a DEFINE WINDOW statement. |
| Actn. | Check program and correct error. |

NAT0466: Error in SIZE clause of DEFINE WINDOW statement.

| Text | Error in SIZE clause of DEFINE WINDOW statement. |
|-------|---|
| Expl. | The SIZE clause of a DEFINE WINDOW statement must be specified as one of the following: SIZE AUTO SIZE QUARTER SIZE lines * columns If the SIZE clause is omitted, SIZE AUTO will apply by default. For an explanation of the DEFINE WINDOW syntax, see the Natural documentation. |
| Actn. | Check program and correct error. |

NAT0467: Error in BASE clause of DEFINE WINDOW statement.

Text Error in BASE clause of DEFINE WINDOW statement.

| Expl. | The BASE clause of the DEFINE WINDOW statement must be specified as |
|-------|---|
| | one of the following: |
| | - BASE CURSOR |
| | - BASE TOP LEFT |
| | - BASE TOP RIGHT |
| | - BASE BOTTOM LEFT |
| | - BASE BOTTOM RIGHT |
| | - BASE line-position / column-position |
| | If the BASE clause is omitted, BASE CURSOR will apply by default. |
| | For an explanation of the DEFINE WINDOW syntax, see the Natural |
| | documentation. |
| Actn. | Check program and correct error. |

NAT0468: Error in TITLE clause of DEFINE WINDOW statement.

| Text | Error in TITLE clause of DEFINE WINDOW statement. |
|-------|---|
| | In the TITLE clause of a DEFINE WINDOW statement, an alphanumeric variable or constant must be specified immediately after the keyword "TITLE". |
| Actn. | Check program and correct error. |

NAT0469: CLOSE WORK FILE statement has been invalidly placed.

| Text | CLOSE WORK FILE statement has been invalidly placed. |
|-------|---|
| | A CLOSE WORK FILE statement must not be placed within a READ WORK FILE loop that refers to the same work file. |
| Actn. | Place the CLOSE WORK FILE statement outside the READ WORK FILE loop. |

NAT0470: Operand for RET, SORTKEY or VAL function is not valid.

| Text | Operand for RET, SORTKEY or VAL function is not valid. |
|-------|--|
| | The operand for RET, SORTKEY or VAL must be alphanumeric. In addition, the length of the SORTKEY operand should not exceed 253. |
| Actn. | Specify an alphanumeric program name with the RET function. Do not apply the system function SORTKEY or VAL to a non-alphanumeric field. Ensure the length of the SORTKEY operand does not exceed 253. |

NAT0471: Invalid operands in SUBSTRING option.

| Text | Invalid operands in SUBSTRING option. |
|-------|---|
| Expl. | The field name specified in the SUBSTRING option must have alphanumeric (A), binary (B) or Unicode (U) format. The starting position in the field and the length of the substring must be numeric. They must not position beyond the physical length of the underlying field. |
| Actn. | Correct error in program. |

NAT0472: This user-defined name is a Natural reserved word.

| Text | This user-defined name is a Natural reserved word. |
|-------|--|
| | The Natural profile parameter KC=ON (keyword check) has been set, which means that a user-defined name (identifier) must not be the same as a Natural reserved word. |
| Actn. | Use a different name. |

NAT0473: Error in parameter of DEFINE PRINTER statement.

| Text | Error in parameter of DEFINE PRINTER statement. |
|-------|---|
| Expl. | This error occurs if one of the following conditions is not met: The operand after "PROFILE", "FORMS" or "NAME" must be of alphanumeric format, and its length must not exceed 8. The operand after "DISP" must be of alphanumeric format, and its length must not exceed 4. The operand after "COPIES" must be a numeric integer (format N, P or I; without decimal digits). Each of the above clauses must not be specified more than once. |
| Actn. | Correct error in program. |

NAT0474: Field attribute DF cannot be used for this type of field.

| Text | Field attribute DF cannot be used for this type of field. |
|-------|--|
| - | The field attribute DF can only be used for fields of type date. |
| Actn. | Correct error in program. |

NAT0475: INCLUDE statements must be nested on less than 20 levels.

| Text | INCLUDE statements must be nested on less than 20 levels. |
|-------|---|
| Expl. | This program has INCLUDE statements nested on at least 20 levels. |
| | Reduce the number of levels on which INCLUDE statements are nested to less than 20. |

NAT0476: Data size of :1: must not exceed :2:.

| Text | Data size of must not exceed |
|-------|--|
| | The size of a variable or a data structure exceeds the maximum size allowed. |
| Actn. | Reduce the size of the variable or data structure. |

NAT0477: Numeric value supplied is out of valid range :1:.

| Text | Numeric value supplied is out of valid range |
|-------|---|
| Expl. | The value specified is out of the permitted bounds. |
| Actn. | Supply a correct numeric value. |

NAT0478: Incorrect usage or specification of CODEPAGE clause.

| Text | Incorrect usage or specification of CODEPAGE clause. |
|-------|---|
| Expl. | The CODEPAGE clause can only be used for operands of format A or B. |
| Actn. | Correct error in program. |

NAT0479: Invalid operand type combination in MOVE ENCODED statement.

| Text | Invalid operand type combination in MOVE ENCODED statement. |
|-------|---|
| Expl. | The MOVE ENCODED statement is used to convert data from one code page encoding into another encoding. Therefore you have to either supply one of the operands as an alphanumeric or binary field with a CODEPAGE clause appended, or specify one operand as alphanumeric or binary and the other operand as type Unicode. Valid operand combinations are: MOVE ENCODED A/B IN CODEPAGE <cp1> TO U MOVE ENCODED A/B IN CODEPAGE <cp1> TO A/B MOVE ENCODED A/B IN CODEPAGE <cp1> TO A/B MOVE ENCODED A/B IN CODEPAGE <cp1> TO A/B IN CODEPAGE <cp2> MOVE ENCODED U TO A/B IN CODEPAGE <cp2> MOVE ENCODED A/B TO A/B IN CODEPAGE <cp2> MOVE ENCODED A/B TO A/B IN CODEPAGE <cp2></cp2></cp2></cp2></cp2></cp1></cp1></cp1></cp1> |
| Actn. | Correct error in program. |

NAT0480: Incorrect usage of field attribute SB.

| Text | Incorrect usage of field attribute SB. |
|-------|--|
| Expl. | A selection-box clause (SB=) may only be used for alphanumeric fields. Moreover, - the parameter fields specified have to be alphanumeric as well, - the number of parameter fields must not exceed 20. A selection-box clause (SB=) must NOT be used for - fields defined as named constants (see CONST clause in DEFINE DATA), - system variables (e.g. *PROGRAM, *COM), - multiple-value fields (e.g. #ARRAY(1:10)). |
| Actn. | Check program and correct error. |

NAT0481: Multiple usage of a SB= or RB= clause not permitted.

| Text | Multiple usage of a SB= or RB= clause not permitted. |
|-------|--|
| | You may not define more than one Selection-Box (SB=) or Radio-Button (RB=) clause for an INPUT field. |
| Actn. | Check program and correct error. |

NAT0482: Length indicator cannot be referenced in UPDATE or STORE.

| Text | Length indicator cannot be referenced in UPDATE or STORE. |
|-------|--|
| | A length indicator field may be used to retrieve the length of an Adabas |
| | Long-Alpha or LOB field (LA/LOB) in a read (READ/FIND) operation. |
| | It must not be referenced in a view used in a STORE or UPDATE statement. |
| | Example: DEFINE DATA LOCAL |
| | 1 V1 V1 VIEW OF MYFILE |
| | 2 L@LA-FIELD (I4) < Length indicator field |
| | 2 LA-FIELD (A) DYNAMIC |
| | END-DEFINE |
| | STORE V1 |
| | If an LA or LOB field is part of the STORE/UPDATE field list, the |
| | corresponding length field information is automatically added by the |
| | Natural runtime system, based on the current length of the dynamic |
| | variable. To prevent a duplicate length setting for the same |
| | LA/LOB field, length fields are not allowed in the STORE/UPDATE fields. |
| Actn. | LA/LOB field, length fields are not allowed in the STORE/UPDATE fields. Remove length fields |
| | from data view used in UPDATE or STORE. |

| Text | Index missing for sub-/super-descriptor field |
|-------|---|
| Expl. | A sub-/super-descriptor field containing a periodic-group field (or parts thereof) was specified in a data view without index. This is not permitted by Adabas for database calls other than HISTOGRAM (L9). With a HISTOGRAM you cannot read more than a single field. This view definition consists of multiple fields and thus cannot be used for a HISTOGRAM. Furthermore, due to the missing index, it cannot be used for other database calls. What to do? 1. Reduce the number of view fields to only the sub-/super-descriptor - without index to make the view usable for HISTOGRAM only; - with an index to make the view usable for all browsing statements. 2. If multiple fields are defined in the view, supply an index or index-range for the sub-/super-descriptor to make it usable for all database browsing statements other than HISTOGRAM. |
| Actn. | database browsing statements other than HISTOGRAM. See description. |

NAT0483: Index missing for sub-/super-descriptor field :1:.

NAT0484: Field structure of view :1: only usable for HISTOGRAM.

| Text | Field structure of view only usable for HISTOGRAM. |
|-------|--|
| Expl. | The view referenced is only applicable to a HISTOGRAM statement, as it consists of only a single sub-/super-descriptor field containing a periodic-group field (or parts thereof) without an index specification. This is not permitted by Adabas and will cause Adabas errors when used with a database statement other than HISTOGRAM. |
| Actn. | Supply index or index-range for the sub-/super-descriptor field, or use the view only for HISTOGRAM statements. |

12 Natural System Error Messages 0551-0600

NAT0600: "END-IF" missing for IF statement in line :1:.

| Text | "END-IF" missing for IF statement in line |
|-------|---|
| Expl. | In structured mode, an IF statement block must be terminated with |
| | a corresponding END-IF statement. |
| | Example: |
| | READ |
| | IF |
| | COMPUTE |
| | COMPUTE |
| | END-IF |
| | DISPLAY |
| | END-READ |
| | END |
| Actn. | Correct error in program. |

13 Natural System Error Messages 0601-0650

NAT0601: "END-START" missing for AT START OF DATA in line :1:.

| Text | "END-START" missing for AT START OF DATA in line |
|-------|---|
| Expl. | In structured mode, an AT START OF DATA statement block must be terminated with a corresponding END-START statement. Example: READ AT START OF DATA MOVE DISPLAY END-START DISPLAY END-READ END |
| Actn. | Correct error in program. |

NAT0602: "END-ENDDATA" missing for AT END OF DATA in line :1:.

| Text | "END-ENDDATA" missing for AT END OF DATA in line |
|-------|---|
| Expl. | In structured mode, an AT END OF DATA statement block must be |
| | terminated with a corresponding END-ENDDATA statement. |
| | Example: |
| | READ |
| | AT END OF DATA |
| | COMPUTE |
| | DISPLAY |
| | END-ENDDATA |
| | DISPLAY |
| | END-READ |
| | END |
| Actn. | Correct error in program. |

NAT0603: "END-BREAK" missing for AT BREAK statement in line :1:.

| Text | "END-BREAK" missing for AT BREAK statement in line |
|-------|---|
| Expl. | In structured mode, an AT BREAK statement block must |
| | be terminated by a corresponding END-BREAK statement. |
| | Example: |
| | READ |
| | AT BREAK |
| | DISPLAY |
| | END-BREAK |
| | DISPLAY |
| | END-READ |
| | END |
| Actn. | Correct error in program. |

NAT0604: "END-TOPPAGE" missing for AT TOP OF PAGE in line :1:.

| Text | "END-TOPPAGE" missing for AT TOP OF PAGE in line |
|-------|--|
| Expl. | In structured mode, an AT TOP OF PAGE statement block must |
| | be terminated by a corresponding END-TOPPAGE statement. |
| | Example: |
| | READ |
| | DISPLAY |
| | AT TOP OF PAGE |
| | WRITE |
| | END-TOPPAGE |
| | DISPLAY |
| | END-READ |
| | END |
| Actn. | Correct error in program. |

NAT0605: "END-ENDPAGE" missing for AT END OF PAGE in line :1:.

| Text | "END-ENDPAGE" missing for AT END OF PAGE in line |
|-------|--|
| Expl. | In structured mode, an AT END OF PAGE statement block must |
| | be terminated by a corresponding END-ENDPAGE statement. |
| | Example: |
| | READ |
| | AT END OF PAGE |
| | DISPLAY |
| | WRITE TRAILER |
| | END-ENDPAGE |
| | DISPLAY |
| | END-READ |
| | END |
| Actn. | Correct error in program. |

NAT0606: "END-BEFORE" missing for BEFORE BREAK in line :1:.

| Text | "END-BEFORE" missing for BEFORE BREAK in line |
|-------|---|
| - | In structured mode, a BEFORE BREAK PROCESSING statement block must be terminated by a corresponding END-BEFORE statement. |
| Actn. | Correct error in program. |

NAT0607: "END-NOREC" missing for IF NO RECORDS FOUND.

| Text | "END-NOREC" missing for IF NO RECORDS FOUND. |
|-------|---|
| Expl. | In structured mode, an IF NO RECORDS FOUND clause must |
| | be terminated with a corresponding END-NOREC statement. |
| | Example: |
| | FIND |
| | IF NO RECORDS FOUND |
| | DISPLAY |
| | END-NOREC |
| | DISPLAY |
| | END-FIND |
| Actn. | Correct error in program. |

NAT0608: "END-ENDFILE" missing for AT END OF FILE in line :1:.

| Text | "END-ENDFILE" missing for AT END OF FILE in line |
|-------|--|
| Expl. | In structured mode, an AT END OF FILE statement block must be terminated by a corresponding END-ENDFILE statement. Example: READ WORK FILE AT END OF FILE COMPUTE DISPLAY END-ENDFILE DISPLAY END |
| Actn. | Correct error in program. |

NAT0609: "END-ERROR" missing for ON ERROR statement in line :1:.

| Text | "END-ERROR" missing for ON ERROR statement in line |
|-------|---|
| Expl. | In structured mode, an ON ERROR statement block must |
| | be terminated by a corresponding END-ERROR statement. |
| | Example: |
| | FIND |
| | UPDATE |
| | ON ERROR |
| | RETRY |
| | END-ERROR |
| | END TRANSACTION |
| | END-FIND |
| | END |
| Actn. | Correct error in program. |

NAT0610: This statement is not permitted in reporting mode.

| Text | This statement is not permitted in reporting mode. |
|-------|--|
| · · | An attempt was made to issue a statement which is valid in structured mode only. |
| Actn. | Make sure you are working in the correct programming mode. |

NAT0611: Loop/condition not properly closed.

| Text | Loop/condition not properly closed. |
|-------|---|
| | An active loop or condition was not properly closed. For example, in structured mode, a FIND statement was issued without a corresponding END-FIND statement. |
| Actn. | Check program and correct error. |

NAT0612: Specified close loop only permitted in structured mode.

| Text | Specified close loop only permitted in structured mode. |
|-------|---|
| Actn. | Check programming mode, program, and correct error. |

NAT0613: END-FIND/END-SELECT missing for FIND/SELECT in line :1:.

| Text | END-FIND/END-SELECT missing for FIND/SELECT in line |
|-------|---|
| Expl. | In structured mode, a loop initiated with a FIND/SELECT statement must be closed with a corresponding END-FIND/END-SELECT statement. Examples: FIND * SELECT UPDATE * DISPLAY END TRANSACTION * END-SELECT END-FIND * |
| Actn. | Supply END-FIND/END-SELECT to close the FIND/SELECT loop. |

NAT0614: END-READ missing for READ in line :1:.

| Text | END-READ missing for READ in line |
|-------|---|
| Expl. | In structured mode, a READ statement must be followed by a corresponding END-READ statement. Example: READ DISPLAY COMPUTE END-READ |
| Actn. | Supply END-READ to close the READ loop. |

NAT0615: END-HISTOGRAM missing for HISTOGRAM in line :1:.

| Text | END-HISTOGRAM missing for HISTOGRAM in line |
|-------|--|
| | In structured mode, a HISTOGRAM statement must be followed by a corresponding END-HISTOGRAM statement. Example: HISTOGRAM DISPLAY END-HISTOGRAM |
| Actn. | Supply END-HISTOGRAM to close the HISTOGRAM loop. |

NAT0616: END-SORT missing for SORT in line :1:.

Text END-SORT missing for SORT in line

| Expl. | In structured mode, a SORT statement must be followed by |
|-------|--|
| | a corresponding END-SORT statement. |
| | Example: |
| | FIND |
| | |
| | END-ALL |
| | SORT |
| | DISPLAY |
| | END-SORT |
| Actn. | Supply END-SORT to close the SORT loop. |

NAT0617: END-REPEAT missing for REPEAT in line :1:.

| Text | END-REPEAT missing for REPEAT in line |
|-------|---|
| Expl. | In structured mode, a REPEAT statement must be followed by a corresponding END-REPEAT statement. Example: REPEAT |
| Asha | END-REPEAT |
| Actn. | Supply END-REPEAT to close the REPEAT loop. |

NAT0618: END-FOR missing for FOR in line :1:.

| Text | END-FOR missing for FOR in line |
|-------|---|
| Expl. | In structured mode, a FOR statement must be followed by a corresponding END-FOR statement. Example: FOR END-FOR |
| Actn. | Supply END-FOR to close the FOR loop. |

NAT0619: END-WORK missing for READ WORK FILE in line :1:.

| Text | END-WORK missing for READ WORK FILE in line |
|-------|---|
| Expl. | In structured mode, a READ WORK FILE statement must be followed by a corresponding END-WORK statement. Example: READ WORK FILE |
| | END-WORK |
| Actn. | Supply END-WORK to close the READ WORK FILE loop. |

NAT0620: END-FILE missing for CALL FILE in line :1:.

| Text | END-FILE missing for CALL FILE in line |
|-------|---|
| Expl. | In structured mode, a CALL FILE statement must be followed by a corresponding END-FILE statement. Example: CALL FILE |
| Actn. | END-FILE Supply END-FILE to close the CALL FILE loop. |

NAT0621: END-LOOP missing for CALL LOOP in line :1:.

| Text | END-LOOP missing for CALL LOOP in line |
|-------|---|
| Expl. | In structured mode, a CALL LOOP statement must be followed by a corresponding END-LOOP statement. Example: CALL LOOP END-LOOP |
| Actn. | Supply END-LOOP to close the CALL LOOP loop. |

NAT0622: RETURN/END-SUBROUTINE missing for DEFINE SUBROUTINE in line :1:.

| Text | RETURN/END-SUBROUTINE missing for DEFINE SUBROUTINE in line |
|-------|---|
| Expl. | This error occurs under one of the following conditions: 1) A subroutine was started in a conditional statement block (e.g. IF, DECIDE) or in a loop-initiating statement (e.g. REPEAT, FIND), but it was not closed at the end of this statement (e.g. END-IF, END-REPEAT,). Examples: IF FIELD = "A" THEN REPEAT DEFINE SUBROUTINE ABC DEFINE SUBROUTINE ABC WRITE "HELLO" WRITE "HELLO" END-IF END-REPEAT 2) A subroutine was started, but it was still not closed at program end. Example: DEFINE SUBROUTINE ABC END |
| Actn. | Supply RETURN or END-SUBROUTINE to close the subroutine. |

NAT0623: Variable/field/view must be defined in DEFINE DATA.

| Text | Variable/field/view must be defined in DEFINE DATA. |
|-------|---|
| | If a DEFINE DATA statement is present, all variables/fields to be used must be defined in the DEFINE DATA statement in an LDA, GDA or PDA, which are referenced with the keyword USING in the DEFINE DATA statement. |
| | If this error occurs for a DDM and a DEFINE DATA statement is present, a view of the DDM (and of any database field referenced in the program) must be defined in the DEFINE DATA statement. |
| Actn. | Check program and correct error. |

NAT0624: Statement END-... either missing or misplaced.

| Text | Statement END either missing or misplaced. |
|-------|--|
| Expl. | Example: READ IF AGE > 65 THEN COMPUTE DISPLAY END-READ END-IF END The statement END-IF must be before the END-READ and after the last statement to be executed in the THEN-clause of the IF-statement. This could be after the COMPUTE or the DISPLAY statement, depending on the actual function the program is to perform. Statements with the syntax "xxx END-xxx" must be correctly paired. |
| Actn. | Make sure that all statement blocks are terminated with corresponding "END" statements, and that the "xxx" and "END-xxx" statements are correctly paired. |

NAT0625: END-DECIDE missing for DECIDE statement.

| Text | END-DECIDE missing for DECIDE statement. |
|-------|--|
| | A statement block initiated with a DECIDE ON or DECIDE FOR statement must be terminated with an END-DECIDE statement. This error may also occur if an END-DECIDE statement is misplaced. |
| Actn. | Make sure that each DECIDE statement is correctly paired with a corresponding END-DECIDE statement. |

NAT0626: Statement not supported with :1:.

| Text | Statement not supported with |
|-------|--|
| | The statement cannot be used with the database type you are using. For details as to which statements support which database types, see the Natural documentation. |
| Actn. | Check program and correct error. |

NAT0627: Value range with keyword "TO" not supported for :1:.

| Text | Value range with keyword "TO" not supported for |
|-------|---|
| Expl. | The statement option "TO" cannot be used with the database |
| | type you are using. |
| | When "TO" is used to specify a value range in a READ |
| | or HISTOGRAM statement, the end-value check will not be done |
| | by Natural, but is performed by the database. However, this |
| | requires a corresponding capability of the accessed database. |
| | Therefore, option "TO" can only be used if the underlying |
| | database is Adabas Version 7 (or above), VSAM, DL/I or DB2. |
| | For details as to which statements support which database |
| | types, see the Natural documentation. |
| Actn. | Check program and correct error. |

NAT0628: Invalid usage of MULTI-FETCH option for :1:.

| Text | Invalid usage of MULTI-FETCH option for |
|-------|--|
| Expl. | The MULTI-FETCH option can only be used if the underlying database is Adabas Version 5.3 (or above). Moreover, if a READ or HISTOGRAM statement contains a "DYNAMIC SEQUENCE" clause, the use of a MULTI-FETCH option is not permitted. For further details, see the Natural documentation. |
| Actn. | Check program and correct error. |

NAT0629: Incompatible range combinations in relational expression.

Text Incompatible range combinations in relational expression.

| Expl. | When two arrays are compared in a relational expression, |
|-------|---|
| | the number of occurrences in each dimension of the one array |
| | must match the number of occurrences in the corresponding |
| | dimension of the other array. |
| | If no corresponding dimension is defined for the other array, |
| | the dimension is assumed to be 1. |
| | A variable number of occurrences in one dimension must not |
| | be compared with a fixed number of occurrences in the |
| | corresponding dimension of the other array. |
| Actn. | Correct error in program. |

NAT0630: Error in RESET INITIAL statement.

| Text | Error in RESET INITIAL statement. |
|-------|---|
| - | See the Natural documentation for information on the correct usage of the RESET INITIAL statement. Note in particular that a RESET INITIAL of fields resulting from a redefinition is not possible, and RESET INITIAL cannot be applied to database fields. |
| Actn. | Check program and correct error. |

NAT0631: Invalid index specified in arithmetic/ASSIGN statement.

| Text | Invalid index specified in arithmetic/ASSIGN statement. |
|-------|---|
| Actn. | Check program and correct error. |

NAT0632: Invalid view structure defined for HISTOGRAM statement.

| Text | Invalid view structure defined for HISTOGRAM statement. |
|-------|--|
| | When using the HISTOGRAM statement with a view, it must be defined with only one variable: the search variable. |
| Actn. | Check program and correct error. |

NAT0633: Invalid use of view which contains super-/subdescriptor.

| Text | Invalid use of view which contains super-/subdescriptor. |
|-------|---|
| | Depending on the Adabas version, a sub- or superdescriptor may be read with a HISTOGRAM statement only or with all database access statements. However, an UPDATE or STORE statement must not be applied to a sub- or superdescriptor. |
| Actn. | Correct error in program. |

NAT0634: Access criterion not supported for this type of database.

| Text | Access criterion not supported for this type of database. |
|------|---|
| | The DBID of this DDM identifies a non-Adabas database. Non-Adabas databases introduce certain restrictions for Natural''s database-access statements. |
| | See the Natural documentation for restrictions which apply to the type of database you wish to access. |

NAT0635: Incorrect use of "BY VALUE" or "OPTIONAL" in DEFINE DATA.

| Text | Incorrect use of "BY VALUE" or "OPTIONAL" in DEFINE DATA. |
|-------|---|
| | The keyword "BY VALUE" or "OPTIONAL" may only be supplied for fields defined in a DEFINE DATA PARAMETER clause. However, this is not permitted for REDEFINE fields or groups. |
| Actn. | Correct error in program. |

NAT0636: Incorrect usage of STARTING WITH ISN clause for :1:.

| Text | Incorrect usage of STARTING WITH ISN clause for |
|-------|---|
| | A STARTING WITH ISN clause can only be used for - Adabas access : FIND READ logical READ physical - VSAM access : READ physical |
| Actn. | Correct error in program. |

NAT0637: Invalid USING clause specified.

| Text | Invalid USING clause specified. |
|-------|--|
| | Invalid USING clause specified in OPEN CONVERSATION statement. Possible reasons for this error are: 1. Keyword USING missing. 2. Incorrect object name specified. Either a constant or a variable of type alpha and length <= 8 is expected. |
| Actn. | Correct error in program. |

NAT0638: Invalid clause in CLOSE CONVERSATION statement.

| Text | Invalid clause in CLOSE CONVERSATION statement. |
|-------|--|
| | The operand in a CLOSE CONVERSATION statement is incorrect. Please specify keyword ALL or *CONVID or a variable of type (I4). |
| Actn. | Correct error in program. |

NAT0640: Label reference not permitted for this statement type.

| Text | Label reference not permitted for this statement type. |
|-------|---|
| - | Labels may be used to reference the following statements only: FIND, READ, GET, HISTOGRAM, SORT, FOR, CALL FILE, CALL LOOP, STORE and REPEAT. |
| Actn. | Check program and correct error. |

NAT0641: Invalid DEFINE PRINTER statement syntax.

| Text | Invalid DEFINE PRINTER statement syntax. |
|-------|--|
| Expl. | The correct syntax is: DEFINE PRINTER (logical-name = n) OUTPUT operand1 where "logical-name" is the name allocated to printer, "n" is the printer number in range from 1 to 31, "operand1" is the destination within the online spooling system. Additional reports can be assigned for default with the following names: SOURCE - Output in the Natural source area. CONNECT - Output into a Con-nect folder. DUMMY - Output to be deleted. HARDCOPY - Output to the current hardcopy device. |
| Actn. | Check program and correct error. |

NAT0642: Invalid definition of OUTPUT variable/constant.

| Text | Invalid definition of OUTPUT variable/constant. |
|-------|---|
| Expl. | This field must be specified with format A8. |
| Actn. | Check program and correct error. |

NAT0643: END-PROCESS missing for PROCESS PAGE MODAL in line :1:.

| Text | END-PROCESS missing for PROCESS PAGE MODAL in line |
|-------|---|
| | This error occurs under one of the following conditions: 1) A PROCESS PAGE MODAL statement was started in a conditional statement block (e.g. IF, DECIDE) or in a loop-initiating statement (e.g. REPEAT, FIND), but it has not been closed yet at the end of this statement (e.g. END-IF or END-REPEAT). Examples: IF FIELD = "A" THEN * REPEAT PROCESS PAGE MODAL * PROCESS PAGE MODAL MOVE #A TO #B * MOVE #A TO #B END-IF * END-REPEAT 2) A PROCESS PAGE MODAL statement was started, but not yet closed at program end. Example: PROCESS PAGE MODAL |
| Actn. | END Supply END-PROCESS to close the PROCESS PAGE MODAL block. |

NAT0648: Parameter :1: inconsistently specified. Reason code :2:.

| Text | Parameter inconsistently specified. Reason code |
|-------|--|
| Expl. | The parameter supplied in a CALLNAT statement is not compatible with the corresponding parameter definition in the subprogram. Reason codes: 04 : The CALLNAT parameter is specified as an empty parameter ("nX"), but the definition in the subprogram is not "OPTIONAL". 08 : Mandatory parameter in the subprogram is missing in the CALLNAT statement. 12 : Parameters do not match in format. 16 : Parameters do not match in length. 20 : Parameters do not match in array definitions. |
| Actn. | Supply compatible parameter specifications. |

14 Natural System Error Messages 0651-0700

NAT0651: Number of parameters (:1: / :2:) do not match.

| Text | Number of parameters (CALLNAT NBR/SUBPGM NBR) do not match. |
|------|---|
| | The number of parameters defined in the referenced subprogram |
| | and supplied in the CALLNAT do not match. |

NAT0652: Sequence clause not valid for :1:.

| Text | Sequence clause not valid for |
|-------|--|
| Expl. | The specified database defined by the view name does not support the processing of records in the specified sequence in a READ or HISTOGRAM statement. In a READ IN LOGICAL SEQUENCE and HISTOGRAM statement, the use of DESCENDING requires Adabas Version 6.1 (or above), VSAM or DB2; VARIABLE requires Adabas Version 6.2 (or above), VSAM or DB2; DYNAMIC requires Adabas Version 7 (or above), or DB2; In a READ BY ISN statement, the use of DESCENDING, VARIABLE or DYNAMIC is not allowed. In a READ IN PHYSICAL SEQUENCE statement, the use of DESCENDING or VARIABLE requires VSAM or DB2; DYNAMIC requires DB2. |
| Actn. | Correct the specified database view or sequence clause. |

NAT0653: Invalid direction operand specified.

| Text | Invalid direction operand specified. |
|-------|---|
| Expl. | The field (#DIR) used to control the read direction in a READ IN VARIABLE #DIR SEQUENCE or |
| | READ IN DYNAMIC #DIR SEQUENCEstatement is not correctly specified. The expected format/length is (A1). |
| Actn. | Check program and correct error. |

NAT0654: Invalid use or definition of NULL indicator field.

| Text | Invalid use or definition of NULL indicator field. |
|-------|---|
| Expl. | One of the following situations was encountered: |
| | 1. A NULL indicator field (N§) is not defined in the DDM with |
| | format/length (I2). |
| | 2. A NULL indicator field used as search variable can only be |
| | used with the equal value operator ("=",EQ). Other operations |
| | (like NE,LT,) are not permitted. |
| | 3. A NULL indicator field may not be used as sort field in a |
| | FIND SORTED BY clause. |
| | 4. If the FIND statement is generated for a DB2 access, the |
| | search value supplied must be a numeric constant. |

NAT0655: Incorrect use of WITH REPOSITION clause for :1:.

| Text | Incorrect use of WITH REPOSITION clause for |
|-------|--|
| Expl. | Repositioning in an active loop by using READ WITH REPOSITION is only allowed for a READ logical statement if the underlying database is Adabas Version 7 (or above), VSAM or DL/I. |
| Actn. | Remove the WITH REPOSITION clause, or correct the database type definition (see also profile parameter DB). |

NAT0666: Continue with creation of program after help request.

| Text | Continue with creation of program after help request. |
|-------|--|
| | This message does not indicate that an error condition exists. It is used only to re-display the last program line for modification, and to indicate that program creation may continue now that the help function was terminated normally. |
| Actn. | Carry on programming. |

NAT0667: Online help not available in batch mode.

| Text | Online help not available in batch mode. |
|-------|--|
| Actn. | Check program and correct error. |

NAT0668: Invalid block name specified or block does not exist.

| Text | Invalid block name specified or block does not exist. |
|------|---|
| Acti | . Check program and correct error. |

NAT0670: "SELECT" missing after "UNION".

| Text | "SELECT" missing after "UNION". |
|-------|---|
| | The SELECT statement contains the keyword "UNION", which indicates that the SELECT statement is to be continued with a further sub-SELECT. The keyword "UNION" must be followed by the keyword "SELECT", which indicates the beginning of the subsequent sub-SELECT. |
| Actn. | Correct error in program. |

NAT0671: "INTO" or "FROM" missing or misplaced.

| Text | "INTO" or "FROM" missing or misplaced. |
|-------|---|
| | The first SELECT statement of a UNION-concatenated SELECT construct must contain an INTO clause after the selection list. Any subsequent SELECT must not contain an INTO clause. |
| Actn. | Correct error in program. |

NAT0672: Invalid specification of order element.

| Text | Invalid specification of order element. |
|-------|--|
| Expl. | Only integer-type constants and column variables are allowed as order elements. If the SELECT construct includes a "UNION", only integer-type constants are allowed. If the SELECT contains receiving dynamic fields, integer-type constants are not allowed, because receiving values might be truncated. |
| Actn. | Correct error in program. |

NAT0673: Number of :1: and :2: elements do not match.

| Text | Number of list-1 and list-2 elements do not match. |
|-------|---|
| | The elements of list-1 and list-2 do not match. The number of specified list-1 elements must be the same as the number of list-2 elements. Where a view can be used instead of a list, only the actual data variables are considered, whereas redefined fields and groups are ignored. |
| Actn. | Correct the number of elements in lists involved in the SQL statement. |

NAT0674: Invalid expression definition in SELECT list.

| Text | Invalid expression definition in SELECT list. |
|-------|---|
| Expl. | The specified SELECTION-list element is an invalid scalar expression. |
| Actn. | Correct error in program. |

NAT0675: Invalid definition of INTO list/indicator variable.

| Text | Invalid definition of INTO list/indicator variable. |
|-------|---|
| | The specification of an INTO-list variable or an indicator variable is not valid. If an INTO-list variable has either not yet been defined or been defined more than once, Natural requires a proper format/length definition. An indicator variable must be of format/length (B2) or (I2). |
| Actn. | Correct error in program. |

NAT0676: Invalid view name definition or view not found.

| Text | Invalid view name definition or view not found. | |
|-------|--|--|
| Expl. | The specified view name is invalid or the view is not found in the | |
| | program. | |
| Actn. | Correct error in program. | |

NAT0677: Invalid scalar-function expression.

| Text | Invalid scalar-function expression. |
|-------|-------------------------------------|
| Actn. | Correct error in program. |

NAT0678: Invalid aggregate-function expression.

| Text | Invalid aggregate-function expression. | |
|-------|---|--|
| - | The argument specified for a COUNT, SUM, AVG, MAX or MIN function is incorrect. | |
| Actn. | Correct error in program. | |

NAT0679: Invalid table name specified, or database is not DB2.

| Text | Invalid table name specified, or database is not DB2. |
|-------|--|
| Expl. | The specified table name is not a valid identifier. |
| | The database ID of the referenced DDM is not labeled as |
| | a DB2 database in the NTDB macro. |
| | Another reason for this error may be that the table specification |
| | includes an explicit authorization identifier, and the table name |
| | contains a hyphen; for example: |
| | SELECT FROM SQL.SQL-TABLE |
| | This is invalid. When a table name that contains a hyphen is used, |
| | it must not be prefixed with an explicit authorization identifier. |
| Actn. | Use valid table name; or do not use this statement for this type of database, or contact your Natural administrator. |

NAT0680: The specified condition is invalid.

| Text | The specified condition is invalid. |
|-------|--|
| | Within the specified search-condition, Natural cannot resolve the specified condition, because the condition does not exist or is specified incompletely or incorrectly. |
| Actn. | Correct error in program. |

NAT0681: Invalid condition specified.

| Text | Invalid condition specified. |
|-------|--|
| Expl. | This error may be caused by one of the following situations:The subquery in an EXISTS condition is specified incorrectly.For an opening parenthesis in a search-condition, the corresponding closing parenthesis is missing. |
| Actn. | Correct error in program. |

NAT0682: Invalid LIKE condition specified.

| Text | Invalid LIKE condition specified. |
|-------|--|
| | One of the "atoms" specified after "LIKE" or after "ESCAPE" in a LIKE condition is invalid: an atom must be a constant or a valid user-defined variable. |
| Actn. | Correct error in program. |

NAT0683: Keyword "NULL" missing in "IS <NOT> NULL" condition.

| Text | Keyword "NULL" missing in "IS <not> NULL" condition.</not> |
|------|--|
| Actr | . Correct error in program. |

NAT0684: Invalid BETWEEN or IN condition specified.

| Text | Invalid BETWEEN or IN condition specified. |
|-------|--|
| Expl. | This error may be caused by one of the following situations: The scalar-expression after "BETWEEN" or after "AND" in a BETWEEN condition is invalid. The keyword "AND" in a BETWEEN condition is missing. In an IN condition, the specified subquery is invalid, or the specified atoms are invalid, or the list of atoms is not enclosed correctly in parentheses. |
| Actn. | Correct error in program. |

NAT0685: Wrong subquery in ALL/ANY/SOME condition.

| Text | Wrong subquery in ALL/ANY/SOME condition. |
|-------|---|
| | The subquery after the keyword "ALL", "ANY" or "SOME" is either missing or incorrect. |
| Actn. | Correct error in program. |

NAT0686: Invalid subquery.

| Text | Invalid subquery. |
|-------|--|
| | After the opening parenthesis and the keyword "SELECT" in a subquery, the selection or table-expression is missing or invalid, or the closing parenthesis at the end of the subquery is missing. |
| Actn. | Correct error in program. |

NAT0687: Invalid column-reference in GROUP BY clause.

| Text | Invalid column-reference in GROUP BY clause. |
|-------|--|
| Actn. | Correct error in program. |

NAT0688: Invalid INTO fields for "SELECT *".

| Text | Invalid INTO fields for "SELECT *". |
|-------|--|
| Expl. | If "SELECT *" is used, all variable names specified in the INTO clause must be table variables: If a view is specified in the INTO clause, all fields defined in that view must be contained in the corresponding table(s). If individual fields are specified in the INTO clause, all these fields must be contained in the corresponding table(s). |
| Actn. | Correct error in program. |

NAT0689: The specified view is empty.

| Text | The specified view is empty. |
|-------|---|
| Expl. | The view specified in the INTO VIEW clause does not contain any "real" database fields. |
| Actn. | Correct error in program. |

NAT0690: Master field for indicator :1: not in view.

| Text | Master field for indicator not in view. |
|-------|---|
| Expl. | The view specified in the INTO clause contains an invalid indicator variable name: when a name of field in a view is prefixed with "LS" or "NS", Natural treats this field as an indicator field, which means that the name following the prefix must be the name of a database field already defined in that view. This master field is missing. |
| Actn. | Correct error in data area. |

NAT0691: Invalid format/length def. for indicator :1:.

| Text | Invalid format/length def. for indic. variable |
|-------|--|
| | The format/length of an INDICATOR or LINDICATOR variable must be either (B2) or (I2). This applies even if the master is not alphanumeric or binary. |
| Actn. | Correct error in program. |

NAT0692: Range variable :1: incorrectly specified.

| Text | Range variable incorrectly specified. |
|-------|---|
| Expl. | Possible reasons for this error: |
| | 1) A range variable cannot be qualified. |
| | 2) The same range variable has been used twice. |
| | 3) An alias range variable specified for a view is not assigned |
| | to a table. |
| Actn. | Correct error in program. |

NAT0693: Indicator variable not allowed as a column reference.

| Text | Indicator variable not allowed as a column reference. |
|-------|--|
| | Special DDM fields with the name prefix N§ or L§ cannot be used as column references because they are unknown to the database. |
| Actn. | Correct error in program. |

NAT0694: Field :1: must not be used in SELECT or SQL UPDATE view.

| Text | Field must not be used in SELECT or SQL UPDATE view. |
|-------|--|
| | Views referenced in a SELECT or SQL UPDATE statement must not contain periodic-group fields or count-variable fields (C*), as neither of these are supported by DB2. |
| Actn. | Remove the above-mentioned fields from the view. |

NAT0695: User-defined variables not permitted in SELECT list.

| Text | User-defined variables not permitted in SELECT list. |
|-------|--|
| | Each field specified in the SELECT list must be either a column of a table specified in the corresponding FROM clause or a constant; user-defined variables are not permitted. |
| Actn. | Correct error in program. |

NAT0696: UPDATE only possible with "SELECT * INTO VIEW".

| Text | UPDATE only possible with "SELECT * INTO VIEW". |
|-------|--|
| Expl. | When you use an UPDATE statement in conjunction with a SELECT statement, the SELECT statement must be of the form "SELECT * INTO VIEW"; with any other form of the SELECT statement, UDPATE is not possible. In reporting mode, you must specify "UPDATE SAME" to update a view read with a SELECT statement; an explicit specification of the columns to be updated is not possible. |
| Actn. | Use the correct combination of SELECT and UPDATE in the program. |

NAT0697: Inconsistent setting of parentheses in SELECT UNION.

| Text | Inconsistent setting of parentheses in SELECT UNION. |
|-------|--|
| - | The grouping of multiple SELECT expressions that are concatenated with "UNION" contains an error: either there is an opening parenthesis without a corresponding closing parenthesis, or vice versa. |
| Actn. | Correct error in program. |

NAT0698: Field :1: must be qualified as it exists in both tables.

| Text | Field must be qualified as it exists in both tables. |
|-------|---|
| | The SELECT statement accesses more than one table, and one of the fields referenced is contained in two (or more) tables; the reference is therefore ambiguous. |
| Actn. | Specify a qualifier with the field. |

NAT0699: Column :1: not found within table.

| Text | Column not found within table. |
|------------|--|
| 1 1 | The column specified in the SQL statement could not be found in the table specified. |
| Actn. | Specify a valid or defined column or omit the reference mentioned. |

NAT0700: Keyword "SET" missing or invalid range-variable specified.

| Text | Keyword "SET" missing or invalid range-variable specified. |
|-------|---|
| | In the SQL UPDATE statement after the table specification, either |
| | the keyword "SET" is missing, or the range-variable is incorrect. |
| Actn. | Correct error in program. |

15 Natural System Error Messages 0701-0750

NAT0701: Invalid assignment clause in SQL UPDATE statement.

| Text | Invalid assignment clause in SQL UPDATE statement. |
|-------|---|
| Expl. | The specified column does not exist in the referenced table that is to be updated; or the equal sign (=) after the column specification is missing; or the scalar-expression after the equal sign contains an error. |
| Actn. | Correct error in program. |

NAT0702: With a view, only "SET *" is allowed in SQL UPDATE.

| Text | With a view, only "SET *" is allowed in SQL UPDATE. |
|-------|--|
| | When a view is referenced in an SQL UPDATE statement, "SET *" must be specified; an explicit assignment list is only allowed and required when a DDM is referenced in the SQL UPDATE statement. |
| Actn. | Correct error in program. |

NAT0703: Invalid range-variable specified in SQL INSERT/DELETE.

| Text | Invalid range-variable specified in SQL INSERT/DELETE. |
|-------|---|
| | In an SQL INSERT or SQL DELETE statement, an invalid range-variable (identifier) has been specified after the DDM (table) name. |
| | (Identifier) has been specified after the DDM (table) name. |
| Actn. | Correct error in program. |

NAT0704: Opening or closing parenthesis missing in INSERT.

| Text | Opening or closing parenthesis missing in INSERT. |
|-------|---|
| | In an INSERT statement, either the list of field names or the list of values is not correctly enclosed in parentheses. |
| Actn. | Correct error in program. |

NAT0705: Field to be INSERTed is not in specified DDM/table.

| Text | Field to be INSERTed is not in specified DDM/table. |
|-------|--|
| | The field specified in the column list of the INSERT statement |
| | does not exist in the referenced DDM/table. |
| Actn. | Correct error in program. |

NAT0706: Invalid value specified in VALUES clause of INSERT.

| Text | Invalid value specified in VALUES clause of INSERT. |
|-------|---|
| Expl. | Values specified in the VALUES clause of an INSERT statement must be one of the following: - the keyword "NULL" (to assign a null value); - a special register (USER, CURRENT TIMEZONE, CURRENT DATE, CURRENT TIME, CURRENT TIMESTAMP); - a constant or a user-defined variable. |
| Actn. | Correct error in program. |

NAT0708: VALUES clause missing or invalid SELECT clause specified.

| Text | VALUES clause missing or invalid SELECT clause specified. |
|-------|--|
| | In an INSERT statement, either a valid VALUES clause or a valid SELECT clause must be specified. |
| Actn. | Correct error in program. |

NAT0709: Incorrect usage of index range field.

| Text | Incorrect usage of index range field. |
|------|---------------------------------------|
| | 0 |

| Expl. | 1) When an array range is used as a parameter in an |
|-------|---|
| | SQL statement (e.g. SELECT, INSERT), the lower |
| | index of the specified range must be 1. |
| | Example: |
| | INSERT INTO table (col) VALUES (arr(1:3)) |
| | 2) The data type of a field specified with an index range |
| | must be alphanumeric or binary. |
| | In the example of 1) arr must be defined as A or B. |
| | 3) Arrays must be one-dimensional. That is, arrays that are |
| | defined in DEFINE DATA as (A10/1:3;1:5) are not permitted. |
| | 4) Variable index ranges, such as (1:I), are not permitted. |
| Actn. | Check syntax and correct error. |

NAT0710: The CLSID was not found in the registry (DCOM code :1:).

| Text | The CLSID was not found in the registry (DCOM code). |
|------|--|
| - | The CLSID associated with the given class name was not found in the registry. |
| 1 | Make sure that the class name used in the CREATE OBJECT statement is correctly registered. |

NAT0711: The object :1: could not be created (DCOM code :2:).

| Text | The object :1: could not be created (DCOM code :2:). |
|-------|--|
| Expl. | The object of the class specified in the CREATE OBJECT statement could not be created. Common reasons are:1) The class is not correctly registered.2) You are not authorized to create the object.3) The specified node does not exist or could not be reached. |
| Actn. | Check if one of the above conditions applies. |

NAT0712: A library name must be specified for Natural Security.

| Text | A library name must be specified for Natural Security. |
|-------|---|
| Expl. | If Natural Security is installed, the system commands REGISTER and UNREGISTER can only be used for a single library. Therefore the library name must not be "*". The library name can be omitted when applying the commands to all classes of the current logon library. If the commands are to be applied to classes in another library, the name of this library has to be specified. |
| Actn. | Either omit the library name or enter the name of an existing library. |

NAT0714: Internal error (DCOM code :1:).

| Text | Internal error (DCOM code). |
|-------|---|
| Expl. | An internal error occurred because of one of the following reasons: |
| | 1) A string could not be converted from Ansi to Unicode. |
| | 2) An automation interface function failed to execute. |
| | 3) The default dispatch interface was not returned during |
| | object creation. |
| | 4) Analyzing the type information failed. |
| | 5) A dispatch interface could not be retrieved. |
| Actn. | Check if the used class is correctly registered. |

NAT0715: Registry entry could not be changed.

| Text | Registry entry could not be changed. |
|------|---|
| | Natural could not change or create entries in the system registry which are needed to register the DCOM class. |
| 1 | Check, if you have permission to change the system registry. If this is not the case, you cannot register classes. |

NAT0716: Registry entry could not be deleted.

| Text | Registry entry could not be deleted. |
|-------|--|
| Expl. | Natural could not delete entries in the system registry which are no longer needed when the DCOM class is unregistered. 1. Check if you have permission to delete entries from the system registry. If this is not the case, you cannot unregister classes. 2. Check if the CLSID of the class to be unregistered was changed after registering the class. In this case it is not possible to find the class in the registry. |
| Actn. | See explanation. |

NAT0717: Registry entry could not be read.

| Text | Registry entry could not be read. |
|-------|---|
| Expl. | Natural could not read entries in the system registry, which is needed to register/unregister the DCOM class. |
| Actn. | Check, if you have permission to read the system registry. If this is not the case, you cannot register/unregister the DCOM class. |

NAT0718: Internal error during registration.

| Text | Internal error during registration. |
|-------|--|
| Expl. | Internal error during registration. |
| Actn. | Unregister the class first and try to register it again. |

NAT0719: Registration files could not be created correctly.

| Text | Registration files could not be created correctly. |
|-------|--|
| - | It was not possible to create the server and client registration files (.reg) for the class. |
| Actn. | Check, if you have permission to create these files. |

NAT0720: DCOM server message: :1:.

| Text | DCOM server message: |
|-------|---|
| - | The DCOM server, which was called by the Natural client, returns the message displayed above. |
| Actn. | None. |

NAT0721: INCDIR error: :1:.

| Text | INCDIR error: |
|-------|--|
| Expl. | This message appears only if compiler option CHKRULE=ON is set. During compilation, the DDM and field names referenced in INCDIR statements are checked for existence. If either the DDM or the field cannot be found, this message is issued. INCDIR statements are automatically created if a database field is included in a map. When the map is catalogued, these instructions will effect an automatic incorporation of processing rules which might exist for this field on Predict. |
| Actn. | Deactivate the message with CHKRULE=OFF. Correct the DDM/field name in the INCDIR statement. |

NAT0723: Interactive I/O not possible in server environment.

| Text | Interactive I/O not possible in server environment. |
|------|---|
| | An attempt was made to execute an interactive I/O (I/O to report 0), while Natural is acting as a server. |
| | Check and correct the program. Input data for the Natural INPUT statement may be supplied via the Natural stack. Any output to report 0 may be redirected using the MAINPR parameter. |

NAT0724: Invalid object handle used.

| Text | Invalid object handle used. |
|------|--|
| | An object handle can only be used after the object has been created with a CREATE OBJECT statement, or after a valid handle has been assigned to it. |
| | Make sure that the object has been successfully created before it is used in a SEND METHOD statement or property access. |

NAT0725: Invalid placement of :1: statement.

| Text | Invalid placement of statement. |
|-------|--|
| Expl. | An invalid statement has been specified in the current Natural object. |
| | Possible reasons are, for example: |
| | 1. A DEFINE CLASS statement may only be specified in a |
| | Natural class object and only specified once per class object. |
| | 2. The first statement of a Natural function object must be |
| | DEFINE FUNCTION END-FUNCTION. |
| | 3. An END statement must not be used in a copycode object. |
| Actn. | Check the placement of the statement or check the object type. |

NAT0726: Invalid :1: name specified.

| Text | Invalid name specified. |
|-------|--|
| Expl. | In a DEFINE CLASS statement the following rules apply to various names: 1. The class, interface, property or method name must not have more than 32 characters. 2. The class name may contain periods. Each identifier separated by a period must conform to the naming conventions for user-defined variables. 3. Interface, property or method names must conform to the naming conventions for user-defined variables. The interface name must not be identical to the class name. 4. The copy code or subprogram name must not have more than 8 characters. |
| Actn. | Check the name and correct error. |

NAT0727: :1: name is not defined.

| Text | name is not defined. |
|-------|---|
| Expl. | In a PROPERTY statement |
| | - the interface is not defined or |
| | - the property name is not defined for the interface specified. |
| | In a METHOD statement |
| | - the interface name is not defined or |
| | - the method name is not defined for the interface specified. |
| | Concerning Natural functions |
| | - there is no return value defined in the RETURNS clause inside |
| | the function prototype. |
| Actn. | Check the name and correct the error. |

NAT0728: Keyword :1: expected.

| Text | Keyword expected. |
|-------|--------------------------------------|
| Expl. | The appropriate keyword is expected. |
| Actn. | Check the keyword and correct error. |

NAT0729: :1: name already defined.

| Text | name already defined. |
|-------|--|
| | The interface name is not unique in the specified class or |
| | the property or method name is not unique for the specified interface. |
| Actn. | Check the name and correct error. |

NAT0730: Property and assigned object var. not data-transfer compatible.

| Text | Property and assigned object var. not data-transfer compatible. |
|-------|---|
| Expl. | The format/length specifications of the property and the assigned object variable are not data-transfer compatible. If the attribute READONLY is specified, the rule for data transfer of the object variable as sending field and the property as receiving field apply. Otherwise the data transfer rules for the property and the assigned object variable as sending and receiving fields apply. |
| Actn. | Check the format/length specifications and correct error. |

NAT0731: No object variable assigned to property :1:.

| Text | No object variable assigned to property |
|-------|---|
| Expl. | No object variable is assigned to the property. |
| Actn. | Assign an object variable to the property. |

NAT0732: Invalid globally unique ID specified.

| Text | Invalid globally unique ID specified. |
|-------|--|
| Expl. | The specified value is not a valid globally unique ID. |
| Actn. | Check the value of the valid globally unique ID and correct error. |

NAT0733: The type information of class :1: could not be retrieved :2:

| Text | The type information of class :1: could not be retrieved :2: |
|-------|--|
| Expl. | In certain situations Natural needs type information about a class to use it. The type information for the class could not be found. A common reason is that the class is not correctly registered on the server side. |
| Actn. | Make sure that the class is correctly registered and type information exists. |

NAT0735: The method or property :1: was not found (DCOM code :2:).

| Text | The method or property :1: was not found (DCOM code :2:). |
|-------|---|
| Expl. | The specified method or property was not found in any of the object"s interfaces. |
| | Check the specified interface name (if any), the method or the |
| | property name. |

NAT0736: The Natural object of class :1: could not be created.

| Text | The Natural object of class could not be created. |
|-------|--|
| Expl. | With the class name specified in the CREATE OBJECT statement it was not possible to create the object. A possible reason is that the corresponding Natural class module was not found at the place where it was registered. |
| Actn. | Check the class name used in the CREATE OBJECT statement and check if the corresponding Natural class module is available. |

NAT0737: The method or property :1: was not found.

| Text | The method or property :1: was not found. |
|------|---|
| · · | The specified method or property was not found in any of the object"s interfaces. |
| | Check the specified interface name (if any), the method or the property name. |

NAT0738: A class named :1: already exists as member :2:.

| Text | A class named already exists as member |
|-------|---|
| · · | You have used a class name which already exists in another class module. Class names within a library must be unique. |
| Actn. | Change the class name. |

NAT0739: READONLY property :1: must not be modified.

| Text | READONLY property must not be modified. |
|-------|--|
| Expl. | If a property is declared as read-only, it must not be modified. |
| Actn. | Correct error in program. |

NAT0740: Invalid dispatch ID of :1: :2: in interface :3:.

| Text | Invalid dispatch ID of in interface |
|-------|---|
| Expl. | Methods and properties of classes have numeric identifiers, called dispatch IDs, assigned. Normally these IDs are assigned internally and automatically by Natural. If you explicitly assign an ID to a method or property using the ID clause, you have to assign the numbers uniquely per interface. Dispatch IDs must be positive integer values. |
| Actn. | Assign a different ID to ensure uniqueness and correct format, or do not assign an ID at all. |

NAT0741: No globally unique ID defined for interface :1: of class :2:.

| Text | No globally unique ID defined for interface of class |
|-------|--|
| | The globally unique ID for the given interface is missing in the Natural class definition. The ID is needed to enter information for this interface in the registry. |
| Actn. | Define a globally unique ID for the interface. |

NAT0742: Type Library creation for class :1: failed.

| Text | Type Library creation for class failed. |
|-------|--|
| Expl. | The type library (.TLB) which is created during registration of a Natural class in the Natural etc directory could not be created. A possible reason is that a type library for the given class already exists and has been opened by another tool. So Natural cannot modify it. |
| Actn. | Check, if the type library is being used by another tool. |

NAT0743: No registry information entered for :1:.

| Text | No registry information entered for |
|-------|---|
| Expl. | If a Natural class is to be accessible with DCOM, it must be entered in the registry. If the class is to be used only locally in Natural, this is not necessary. |
| Actn. | If you do not want to use the class with DCOM, you can ignore this error message. Otherwise, define a valid ID for the class and define at least one interface for the class. |

NAT0744: Conflicting number of parameters in SEND METHOD.

| Text | Conflicting number of parameters in SEND METHOD. |
|-------|---|
| Expl. | The number of parameters which are specified with the SEND METHOD statement must be identical to both: - the number of parameters, that are defined in the method, - the number of parameters, that are declared in the method declaration of the DEFINE CLASS statement. |
| Actn. | Check the parameter definitions in the class module, in the method and the parameters in the SEND METHOD statement. |

NAT0745: Error during conversion of parameter :1: in SEND METHOD.

| Text | Error during conversion of parameter in SEND METHOD. |
|-------|--|
| Expl. | The parameter could not be converted to an appropriate VARIANT format, or the VARIANT format returned from the server could not be converted to an appropriate Natural format. Some possible reasons are: - A Natural variable of format "C" cannot be passed as a method parameter. - Arrays passed as arguments must match the corresponding method parameter in number of dimensions and number of occurrences per dimension. |
| Actn. | Consult the data conversion rules in the NaturalX documentation. |
| | |

NAT0746: Class name :1: already defined in the registry.

| Text | Class name already defined in the registry. |
|-------|---|
| · · | The class cannot be registered, because a class with the same name but a different CLSID has been found in the system registry. |
| Actn. | Change the class name so that it is unique. |

NAT0747: No classes are registered under server ID :1:.

| Text | No classes are registered under server ID |
|-------|--|
| | The UNREGISTER command was used to unregister all classes that are registered under a given server ID, or under the current server ID. Currently there are no classes registered under this server ID. |
| Actn. | None. |

NAT0748: Error during conversion of property value or return value.

| Text | Error during conversion of property value or return value. |
|-------|--|
| Expl. | The property value or return value could not be converted to an appropriate VARIANT format, or the VARIANT format passed back from the server could not be converted to an appropriate Natural format. Some possible reasons are: - A Natural variable of format "C" cannot be passed as property value or received as return value. - Arrays passed as property value or received as return value must match the corresponding property or return parameter in number of dimensions and number of occurrences per dimension. |
| Actn. | Consult the data conversion rules in the NaturalX documentation. |

NAT0750: ACTION name missing or invalid.

| Text | ACTION name missing or invalid. |
|-------|--|
| | The keyword ACTION of the PROCESS statement is not followed by a valid action name. Valid action names are those that are declared in the ACTION clause of the View Program. |
| Actn. | Check and correct ACTION name. |

16 Natural System Error Messages 0751-0800

NAT0751: Illegal combination of PROCESS quantifier and access type.

| Text | Illegal combination of PROCESS quantifier and access type. |
|-------|--|
| | The PROCESS quantifier can be ALL, (qty) or missing. Action type can be explicitly given by TYPE attribute. If the TYPE attribute is missing, the action type is implicitly given for the standard actions SELECT, STORE, UPDATE, DELETE. Otherwise the action type defaults to "X". Only the following combinations are valid: Action Type Quantifier Program Type X missing DEFINE SERVER/DEFINE VIEW A ALL, (Qty) DEFINE VIEW M,O missing DEFINE VIEW |
| Actn. | Check and correct program. |

NAT0752: Invalid TYPE/DEST specification.

| Text | Invalid TYPE/DEST specification. |
|-------|--|
| Expl. | The TYPE/DEST specification is incorrect because: - the given TYPE is not one of A (Access), M (Modify), O (Output) X (eXchange); or - the given DEST is not one of LOCAL, NET, DEBUG; or - neither TYPE nor DEST is given inside the brackets of the TYPE/DEST specification; or |
| Actn. | DEST is given in front of TYPE; or TYPE or DEST not followed by "="; or the closing bracket is missing. Correct TYPE/DEST specification. |

NAT0753: WHERE/ORDER BY clause only allowed for action type Access

| Text | WHERE/ORDER BY clause only allowed for action type Access |
|-------|--|
| - | The WHERE clause and the ORDER BY clause of a PROCESS statement accessing an Active View require action type Access. This may be implicitly given by the standared action SELECT or explicitly given by the type specification TYPE=A. |
| Actn. | Check and correct program. |

NAT0754: Invalid search variable specified in WHERE clause.

| Text | Invalid search variable specified in WHERE clause. |
|-------|--|
| Expl. | A search variable denoted in the WHERE clause of a PROCESS statement is not defined in the view referred to by the PROCESS statement, or the search variable is used in combination with a local block field that has been mapped to another view field via a JOIN VALUE clause. |
| Actn. | Check and correct program. |

NAT0755: Nested PROCESS loops refer to the same view.

| Text | Nested PROCESS loops refer to the same view. |
|-------|--|
| Expl. | There are two nested PROCESS loops in the program which refer to the same Natural view. This is not possible because each view corresponds to an instance of an Active View and each instance can only maintain one loop context. |
| Actn. | Use a copy of the view for the innermost loop. |

NAT0756: Illegal PROCESS statement against a native database.

| Text | Illegal PROCESS statement against a native database. |
|-------|--|
| Expl. | PROCESS with action type M, O or X refers to a native |
| | database view; or a program other than a View Program contains |
| | a PROCESS statement referring to a native database view; or |
| | a PROCESS statement referring to a native database view is |
| | closed by an END-PROCESS. |
| Actn. | Check and correct program. |

NAT0757: PROCESS with action type Modify without Access loop.

| Text | PROCESS with action type Modify without surrounding Access loop. |
|-------|---|
| | An update against an Active View via PROCESS needs a surrounding loop much like the Natural statement UPDATE does. The surrounding PROCESS loop must refer to the same Natural view as the PROCESS statement for update. |
| Actn. | Make sure there is a surrounding loop. |

NAT0758: Error in ORDER BY clause.

| Text | Error in ORDER BY clause. |
|-------|---|
| | The ORDER BY clause is invalid because: - it appears in front of the WHERE clause; or - the given sort field is not a field of the view referred to by the PROCESS statement; or - there are more than three sort fields. |
| Actn. | Check and correct program. |

NAT0759: Handle/dynamic variables and X-arrays cannot be redefined.

| Text | Handle/dynamic variables and X-arrays cannot be redefined. |
|-------|--|
| Expl. | A variable declared DEFINE DATA LOCAL |
| | - with type HANDLE, -> 1 #H HANDLE OF OBJECT |
| | - as an alphan. or binary field -> 1 #AD (A) DYNAMIC |
| | with a dynamic length, |
| | - as an array with a variable -> 1 #VA (A10/1:*) |
| | number of occurrences END-DEFINE |
| | cannot be redefined, and it must not result from a redefinition. |
| | If a group contains one of these fields in the first position, the |
| | group cannot be redefined. |
| Actn. | Check and correct the variable definitions. |

NAT0762: UPDATE/DELETE table mismatch with SELECT statement.

| Text | UPDATE/DELETE table mismatch with SELECT statement. |
|-------|---|
| Expl. | The table referenced in an |
| | UPDATE table WHERE CURRENT CURSOR or |
| | DELETE FROM table WHERE CURRENT CURSOR statement |
| | is not the table specified in the corresponding SELECT statement. |
| Actn. | Check and correct syntax. |

NAT0763: Incorrect alphanumeric constant specified in <<...>>.

| Text | Incorrect alphanumeric constant specified in <<>>. |
|-------|---|
| | The constant specified in <<>> does not adhere to the rules for Natural constants. For example, alpha constants must be enclosed in apostrophes. |
| Actn. | Check and correct syntax. |

NAT0764: Variable reference in <<...>> cannot be resolved.

| Text | Variable reference in <<>> cannot be resolved. |
|-------|---|
| | The token directly following the variable indicator (:) does not adhere to the rules for variable names. The variable specified is not defined in the program. |
| Actn. | Check and correct syntax. |

NAT0768: No valid table reference found in FROM clause.

| Text | No valid table reference found in FROM clause. |
|-------|---|
| | The FROM clause contains no valid table name. Either specify a table name or a subquery of a joined table expression. |
| Actn. | Correct the FROM clause by specifying a valid table name. |

NAT0776: Program cannot be executed.

| Text | Program cannot be executed. |
|-------|---|
| | While loading the Natural program, an internal, non-recoverable error has occurred. The program could not be loaded into the Natural buffer pool. |
| Actn. | Check program and/or contact your Natural administrator. |

NAT0777: Buffer pool full.

| Text | Buffer pool full. |
|-------|--|
| | The Natural buffer pool is full. With Natural Version 2, the cataloged Natural program must be loaded into the Natural buffer pool. If there is not enough space available, the program cannot be executed. |
| Actn. | Contact your Natural administrator. |

NAT0778: Program not ready for execution.

| Text | Program not ready for execution. |
|-------|---|
| | The program to be executed is in the process of being cataloged by another user. When loading this program into the Natural buffer pool, Natural can not guarantee that the program code is in a correct and executable state. |
| Actn. | Execute the program at a later point in time. |

NAT0779: Program cannot be executed.

| Text | Program cannot be executed. |
|-------|---|
| | This message appears if Natural has tried unsuccessfully 32 times to load the program into the Natural buffer pool. |
| Actn. | Contact your Natural administrator. |

NAT0781: Internal Natural DB2 error.

| Text | Internal Natural DB2 error. |
|-------|---|
| Actn. | Provide the Natural source and object program and contact |
| | Software AG support. |

NAT0782: No fields were selected by a FIND or READ statement.

| Text | No fields were selected by a FIND or READ statement. |
|-------|---|
| Expl. | A FIND or READ statement does not retrieve any fields (empty view), but is directed to access an SQL database (e.g. DB2). This will result in the generation of an SQL SELECT statement with an empty column list. However, this is not permitted. |
| Actn. | Retrieve at least one field in the FIND or READ statement. |

NAT0783: Invalid Natural statement for DB2 access.

| Text | Invalid Natural statement for DB2 access. |
|-------|---|
| | The following Natural statements are not supported when accessing a DB2 database: - GET - STORE USING NUMBER (ISN) |
| Actn. | Check program and correct error. |

NAT0784: Insufficient space for SQL :1: generation.

| Text | Insufficient space for SQL generation. |
|-------|--|
| Expl. | During the generation, the corresponding buffer has overflowed. Either provide a greater thread/partition/region, or split the program"s SQL parts and put them into different programs. The message relates either to the buffer containing the SQL statements or to the buffer containing the SQL XREF data. |
| Actn. | Start Natural in greater thread/partition/region, or reduce the number or size of SQL statements. |

NAT0785: Internal Natural DB2 error.

| Text | Internal Natural DB2 error. |
|-------|--|
| Actn. | Provide the Natural source and object program, and contact |
| | Software AG support. |

NAT0786: No fields assigned for an UPDATE statement.

| Text | No fields assigned for an UPDATE statement. |
|-------|---|
| | Natural DB2: An UPDATE statement is present, but no database fields are specified for the view. |
| Actn. | Assign a value to a DB2 column. |

NAT0787: A read-only field may not be modified.

| Text | A read-only field may not be modified. |
|-------|--|
| | Natural DB2: Read-only fields were specified in an UPDATE statement. This is not allowed, because these fields may not be modified. |
| Actn. | Check program and correct error. |

NAT0788: UPDATE/DELETE must not be used in conj. with FIND SORTED.

| Text | UPDATE/DELETE must not be used in conj. with FIND SORTED. |
|-------|--|
| Expl. | UPDATE/DELETE must not be used in conjunction with READ BY, FIND ORDER BY, SELECT ORDER BY or READ RESULT SET according to DB2 processing logic. |
| Actn. | Correct error in program. |

NAT0789: Field in SORTED BY clause is not referenced.

| Text | Field in SORTED BY clause is not referenced. |
|------|--|
| | Natural DB2: A field referenced in the SORTED BY clause is not referenced anywhere in the program. |
| | Check program and correct error. |

NAT0790: No primary key in an IMS access.

| Text | No primary key in an IMS access. |
|-------|---|
| Expl. | Natural DB2 needs a primary key for UPDATE or DELETE if the loop contains a terminal statement. |
| Actn. | Change program according the Natural DB2 file-server logic. |

NAT0791: Data type not supported.

| Text | Data type not supported. |
|-------|---|
| Expl. | The search criterion contains a Natural variable or constant |
| | of a format that is not supported by the DB2 database manager. |
| | Unsupported formats are: |
| | N (numeric unpacked) |
| | I1 (integer with length of 1) |
| | L (logical) |
| | D (date) |
| | T (time) |
| Actn. | Do not use the above formats in a program that accesses a DB2 database. |

NAT0792: Null or length referenced without the master field.

| Text | Null or length referenced without the master field. |
|-------|--|
| | When referencing a length-indicator or null-indicator field, the corresponding master field to which the length or null indicator applies must also be referenced. |
| Actn. | Correct program. |

NAT0793: Null or length indicator cannot be used as descriptor.

| Text | Null or length indicator cannot be used as descriptor. |
|-------|--|
| | A null indicator or length indicator cannot be used as a descriptor, only master fields can be used as search criteria. |
| Actn. | Change search criterion in Natural program. |

NAT0794: SELECT FOR UDPATE, but UPDATE not allowed.

| Text | SELECT FOR UDPATE, but UPDATE not allowed. |
|-------|---|
| Expl. | This message also appears with the statement SELECT SINGLE FOR UPDATE where UPDATE is not allowed. |
| Actn. | Check and correct program. |

NAT0797: Invalid use of set name in search criterion.

| Text | Invalid use of set name in search criterion. |
|-------|---|
| Expl. | A set name has been specified in the basic search criterion of a |
| | FIND statement; however |
| | - the file to be accessed is not an Adabas file, or |
| | - the search criterion belongs to a COUPLED criterion. |
| | In either case, a set name must not be used. |
| | See the Natural documentation, FIND statement, for information on |
| | the use of a set name. |
| Actn. | Change the search criterion in your program. |

NAT0798: Invalid common table expression.

| Text | Invalid common table expression. |
|-------|--|
| Expl. | The specified common table expression is invalid. A common table expression has to follow the keyword WITH@CTE and has the syntax: cte-name (colname,) AS (fullselect). Most likely, parentheses, the keyword AS or commas are missing or specified too often. |
| Actn. | Correct the common table expression. |

NAT0799: Scalar fullselect has to consist of a single column value.

| Text | Scalar fullselect has to consist of a single column value. |
|-------|---|
| Expl. | Scalar fullselect can be used as scalar values in expressions. Scalar fullselect is a fullselect enclosed in parentheses which returns a single row consisting of a single column value. The specified fullselect result set consists of more than one column. |
| Actn. | Specify only one column in the selection list of the fullselect. |

NAT0800: Logon failed after :1: consecutive errors.

| Text | Logon failed after consecutive errors. |
|------|--|
| | The Natural session has been terminated as a result of too many unsuccessful logon attempts. |
| | Start a new Natural session after verifying your user ID and/or password. |

17 Natural System Error Messages 0801-0850

NAT0801: No access rights defined for this utility.

| Text | No access rights defined for this utility. |
|-------|---|
| Expl. | The utility is for restricted use only. |
| Actn. | Please contact your security administrator. |

NAT0802: Access to system file :1: denied, reason :2:.

| Text | Access to system file denied, reason |
|-------|---|
| Expl. | Reason: |
| | 1 - Natural for UNIX: The system file is not in NATCONF.CFG. |
| | 2 - The use of the system file is restricted in a Natural |
| | Development Server environment. |
| | 4 - Access denied to this system-file combination. |
| | 9 - Natural utility system-file combination is not defined. |
| | 10 - Environment profile is not defined. |
| | 12 - You are not allowed to use this library session profile. |
| Actn. | Contact your Natural Security administrator. |

NAT0803: Libraries SYSLIB and SYSLIBS reserved for system usage.

| Text | Libraries SYSLIB and SYSLIBS reserved for system usage. |
|-------|---|
| Actn. | Log on to another library. |

NAT0804: Re-enter new password to confirm password change.

| Text | Re-enter new password to confirm password change. |
|-------|---|
| Expl. | If you wish to change your password, you must type in the new password a second time so as to confirm the password change. This confirmation is necessary to prevent typing errors in passwords (which may occur as the password and new password are not visible on the logon screen). |
| Actn. | If password modification was intended, enter your new password again. If password modification was not intended, press ENTER to resume the logon procedure. |

NAT0805: New password was not confirmed; logon failed.

| Text | New password was not confirmed; logon failed. |
|------|---|
| Exp | The logon procedure required that you enter your new password a second time so as to confirm the password change. However, the second time you entered either no new password at all or one which was different from that entered the first time; this means that the password change was not confirmed. |
| Acti | . Log on again. |

NAT0806: Library not found.

| Text | Library not found. |
|-------|---|
| | The library to which you wish to log on is not defined to Natural Security. Under Natural Security, any Natural library which is to be used must have been defined to Natural Security. |
| Actn. | Contact your Natural Security administrator. |

NAT0807: Logon to this library is not permitted.

| Text | Logon to this library is not permitted. |
|-------|--|
| | The library to which you wish to log on is protected. To be able to log on to this library, you must be linked to it, but you are not. |
| Actn. | Contact your Natural Security administrator. |

NAT0808: No restartable library found.

| Text | No restartable library found. |
|------------|--|
| 1 1 | You have specified "RESTART" in the logon procedure, but no restart library was available. |
| Actn. | Use the RESTART option only after having been active in a library; and/or contact your Natural Security administrator. |

NAT0809: Terminal ID not permitted for logon.

| Text | Terminal ID not permitted for logon. |
|-------|--|
| | A terminal ID was entered as a user ID. This is not permitted. Access to a terminal-protected library may be gained by using the library ID. |
| Actn. | Use the appropriate library ID and no user ID. |

NAT0810: Group ID not permitted for logon.

| Text | Group ID not permitted for logon. |
|-------|--|
| | A group ID was entered as a user ID in the logon procedure. However, group IDs cannot be used in the logon procedure; they are only relevant for links to libraries. |
| Actn. | Log on with your correct user ID. |

NAT0811: A user ID must be entered.

| Text | A user ID must be entered. |
|-------|--|
| Expl. | A Natural session cannot be activated if no user ID is specified for the initial logon to Natural. For subsequent logons, a user ID need not be specified. Natural internally uses the initial user ID until another user ID is specified. If Natural Security is installed, a user ID must be specified with each logon. |
| Actn. | Enter a valid user ID. |

NAT0812: User security profile has been illegally manipulated.

| Te | ext | User security profile has been illegally manipulated. |
|----|------|---|
| E> | - | The Natural Security logon procedure has detected an internal inconsistency in the security profile for the specified user ID. The user security profile was modified by a direct manipulation of the data record. |
| A | ctn. | Contact your Natural Security administrator. |

NAT0813: Logon to default library not permitted.

| Text | Logon to default library not permitted. |
|-------|---|
| Expl. | Your default library is not available to you. |
| Actn. | Contact your Natural Security administrator. |

NAT0814: Library ID and/or user ID must be entered.

| Text | Library ID and/or user ID must be entered. |
|-------|--|
| Expl. | On the logon screen, you must enter a library ID, or a user ID, or both. |
| Actn. | Enter user ID and/or library ID. |

NAT0815: Please enter a library ID.

| Text | Please enter a library ID. |
|-------|---|
| Expl. | There is neither a default library defined for you nor have you a private library. Therefore you must explicitly specify the library to which you wish to log on. |
| Actn. | Enter a library ID; or enter a "?" to get a list of the libraries that are available to you. |

NAT0816: The library may not be accessed from this terminal.

| Text | The library may not be accessed from this terminal. |
|-------|---|
| | You have tried to access a library which may be accessed only from certain terminals, but not from the one you are using. |
| Actn. | Contact your Natural Security administrator. |

NAT0817: Logon with a batch user ID not permitted in nonbatch mode.

| Text | Logon with a batch user ID not permitted in nonbatch mode. |
|-------|---|
| | You attempted to log on using a batch user ID although batch mode is not active. This is not permitted. |
| Actn. | Log on using a user ID with type not equal to "batch". |

NAT0818: User ID is missing or this terminal is not defined.

| Text | User ID is missing or this terminal is not defined. |
|-------|---|
| | Either you have forgotten to enter your user ID, or you have tried to |
| | log on from a terminal which is not defined to Natural Security. |
| Actn. | Enter your user ID, or contact your Natural Security administrator. |

NAT0819: Logon unsuccessful (batch mode execution).

| Text | t Logon unsuccessful (batch mode execution). |
|------|--|
| Exp | An unsuccessful attempt to log on in a batch Natural session was detected. This error message follows the detailed error message that describes the reason for the failed logon. |
| Act | n. Act according to explanation of detailed message. |

NAT0820: Terminal security profile was illegally manipulated.

| Text | Terminal security profile was illegally manipulated. |
|-------|--|
| | The Natural Security logon procedure detected an internal inconsistency in the security profile of the terminal from which you have tried to log on. The security profile was modified by a direct manipulation of the database record. |
| Actn. | Contact your Natural Security administrator. |

NAT0821: Library available only for :1:.

| Text | Library available only for |
|-------|--|
| 1 1 | You have attempted to log on to a library which may only be used from the device type indicated. |
| Actn. | Use the library only from the allowed device type. |

NAT0822: User"s private library only available for :1:.

| Text | User"s private library only available for |
|-------|---|
| - | You have attempted to log on to a private library which may only be used from the device type indicated. |
| Actn. | Use the private library only from the allowed device type. |

NAT0823: Logon with a batch user ID is not permitted.

| Text | Logon with a batch user ID is not permitted. |
|-------|--|
| | You attempted to log on using a batch user ID. This user |
| | ID cannot be used to log on directly in batch mode. |
| Actn. | Log on using a user ID with type not equal to "batch". |

NAT0824: Library security profile was illegally manipulated.

| Text | Library security profile was illegally manipulated. |
|-------|---|
| · · | The Natural Security logon procedure has detected an internal |
| | inconsistency in the security profile of the specified library. |
| | The security profile was modified by a direct manipulation of |
| | the database record. |
| Actn. | Contact your Natural Security administrator. |

NAT0825: Security profile has been illegally manipulated.

| Text | Security profile has been illegally manipulated. |
|-------|---|
| Expl. | The Natural Security logon procedure has detected an internal inconsistency in a security profile invoked. The security profile was modified by a direct manipulation of the database record. |
| Actn. | Contact your Natural Security administrator. |

NAT0826: Invalid number. Please enter valid number.

| Text | Invalid number. Please enter valid number. |
|-------|--|
| Expl. | Only one of the displayed numbers may be entered during the logon procedure. |
| Actn. | Enter a valid number. |

NAT0827: No available library found.

| Text | No available library found. |
|-------|--|
| Expl. | No library for this user ID is available from this terminal. |
| Actn. | Contact your Natural Security administrator. |

NAT0828: You may not logon to "SYSSEC".

| Text | You may not logon to "SYSSEC". |
|-------|---|
| Expl. | You have no permission to log on the Natural Security library "SYSSEC". |
| Actn. | Contact your Natural Security administrator. |

NAT0829: Password change not permitted.

| Text | Password change not permitted. |
|-------|---|
| · · | You cannot change your password because updating of the Natural Security system file has been prohibited. |
| Actn. | Contact your Natural Security administrator. |

NAT0830: Help screen not confirmed.

| Text | Help screen not confirmed. |
|-------|---|
| | An attempt was made to enter logon processing, but the requested confirmation was not provided. |
| Actn. | Continue logon. |

NAT0831: ***** Natural LOGON PROCEDURE *****

| Text | ***** Natural LOGON PROCEDURE ***** |
|-------|--|
| Expl. | Text displayed in line 1 during Natural logon procedure. |

NAT0832: **** YOU ARE LINKED DIRECTLY TO: ... ****

| Text | **** YOU ARE LINKED DIRECTLY TO: **** |
|-------|--|
| Expl. | Text displayed in line 2 during Natural logon procedure. |

NAT0833: **** YOU ARE LINKED VIA A GROUP TO: ... ****

| Text | **** YOU ARE LINKED VIA A GROUP TO: **** |
|-------|--|
| Expl. | Text displayed in line 3 during Natural logon procedure. |

NAT0834: *** YOUR TERMINAL IS LINKED TO: ... ***

| Text | *** YOUR TERMINAL IS LINKED TO: *** |
|-------|--|
| Expl. | Text displayed in line 2 during Natural logon procedure. |

NAT0835: *** PUBLIC LIBRARIES ARE: ... ***

| Text | *** PUBLIC LIBRARIES ARE: *** |
|------|--|
| | Text displayed on line 2 as a result of entering a "?" as library ID |
| | during Natural logon procedure. |

NAT0836: Press ENTER for next page, or enter "." for logon screen.

| Text | Press ENTER for next page, or enter "." for logon screen. |
|-------|--|
| Expl. | Text displayed during logon processing for trailer line 1. |

NAT0837: Or select a library by entering its number ==>

| Text | Or select a library by entering its number ==> |
|-------|---|
| Expl. | Text displayed as trailer line 2 during logon processing. |

NAT0838: Change your password. Enter the old and a new password.

| Text | Change your password. Enter the old and a new password. |
|------|--|
| | According to your Natural Security profile, you must change your password periodically. |
| | Enter your old password in the "Password" field and a new password in the "New Password" field. When prompted to confirm the new password, enter the new password again in the "New Password" field. |

NAT0839: The library "SYSSEC" has not been found.

| Text | The library "SYSSEC" has not been found. |
|-------|---|
| Expl. | The library "SYSSEC" is indispensable for a security environment. |
| Actn. | Contact your Natural Security administrator. |

NAT0840: Private library not found.

| Text | Private library not found. |
|-------|---|
| - | The security profile of the private library specified for you could not be found. The Natural Security logon procedure has found an internal inconsistency: a private library is specified in your user security profile but there is no security profile for the private library. |
| Actn. | Contact your Natural Security administrator. |

NAT0841: This user has no private library.

| Text | This user has no private library. |
|-------|---|
| Expl. | A logon to a private library is only possible for users of type "ADMINISTRATOR" or "PERSON" and only if these users have a private library defined in their security profile. |
| Actn. | Enter a library ID, or a "?" to get a list of libraries that are available to you. |

NAT0842: Logon to a private library is not allowed.

| Text | Logon to a private library is not allowed. |
|------|---|
| | You have attempted to log on to somebody else"s private library. You cannot log on to another user"s private library, only to your own (if there is one defined for you). |
| | Enter a library ID, or a "?" to get a list of libraries that are available to you. |

NAT0843: Invalid user ID; only user ID from TP monitor accepted.

| Text | Invalid user ID; only user ID from TP monitor accepted. |
|-------|--|
| | If "Automatic Logon" is active (that is, the Natural parameter AUTO=ON has been set), only the user ID used to log on to your TP monitor will be accepted for your logon to Natural. |
| Actn. | Enter the user ID with which you have logged on to your TP monitor. |

NAT0844: This user is not defined. Restart not allowed.

| Text | This user is not defined. Restart not allowed. |
|-------|--|
| Expl. | The last library of a user is stored in his/her security record. A user who has not been defined to Natural Security does not have such a record. Restart is only allowed for a user who is defined to Natural Security. However, you are not defined to Natural Security. |
| Actn. | Contact your Natural Security administrator. |

NAT0845: Command mode prohibited, no startup transaction specified.

| Text | Command mode prohibited, no startup transaction specified. |
|-------|--|
| Expl. | If command mode is not allowed, either a startup transaction must have |
| | been specified or a command/program must be in the Natural stack. |
| Actn. | Contact your Natural Security administrator. |

NAT0846: Group not found.

| Text | Group not found. |
|-------|---|
| Expl. | You are linked via a group to the library, but the group cannot be found. |
| Actn. | Contact your Natural Security administrator. |

NAT0847: Library ID must start with an alphabetical character.

| Text | Library ID must start with an alphabetical character. |
|-------|--|
| Expl. | The first character of a library ID must be an alphabetical character. |
| Actn. | Enter a library ID which starts with an alphabetical character. |

NAT0848: Startup transaction :1: cannot be found.

| Text | Startup transaction cannot be found. |
|-------|--|
| Expl. | The startup transaction specified in the security profile of the used library cannot be found, neither in the library itself nor in any steplib. |
| Actn. | Contact your Natural Security administrator. |

NAT0849: A library with that ID already exists.

| Text | A library with that ID already exists. |
|-------|---|
| Expl. | User/library IDs must be unique. |
| Actn. | Enter a user ID which is not equal to any library ID. |

NAT0850: Restart program :1: cannot be found.

| Text | Restart program cannot be found. |
|-------|--|
| | The restart program specified in the security profile of the library used cannot be found, neither in the library itself nor in any steplib. |
| Actn. | Contact your Natural Security administrator. |

18 Natural System Error Messages 0851-0900

NAT0851: Error program :1: cannot be found.

| Text | Error program cannot be found. |
|-------|---|
| | The error program specified - either in the security profile of the library used or with the parameter ETA - cannot be found, neither in the library itself nor in any steplib. |
| Actn. | Contact your Natural Security administrator. |

NAT0852: Incomplete security profile; call security administrator.

| Text | Incomplete security profile; call security administrator. |
|-------|---|
| | Either you are defined to Natural Security as a user of type MEMBER. Users of this type must be contained in at least one group. You have not been added to any group, or your user type should be changed. Or your terminal is defined to Natural Security, but is not contained in any group. |
| Actn. | Contact your Natural Security administrator. |

NAT0853: Logon accepted to library :1:. This library is empty.

| Text | Logon accepted to library This library is empty. |
|-------|--|
| Actn. | No action required. |

NAT0854: Logon accepted to library :1:.

| | Logon accepted to library |
|-------|---------------------------|
| Actn. | No action required. |

NAT0855: New password must be at least :1: characters long.

| Text | New password must be at least characters long. | |
|-------|---|--|
| Expl. | Natural Security requires that passwords have a minimum length. | |
| Actn. | Choose a longer password. | |

NAT0856: Automatic logon with invalid logon data; logon failed.

| Text | Automatic logon with invalid logon data; logon failed. |
|-------|--|
| Actn. | Contact your Natural Security administrator. |

NAT0857: This user is currently locked.

| Text | This user is currently locked. |
|-------|--|
| Actn. | Contact your Natural Security administrator. |

NAT0858: Format of expiration date must be as in top right corner.

| Text | Format of expiration date must be as in top right corner. |
|-------|---|
| | The expiration date for a mailbox must be entered in the same format as the date displayed in the top right hand corner of the screen. |
| Actn. | Enter valid expiration date in valid format. |

NAT0859: Expiration date may not be a date in the past.

| Text | Expiration date may not be a date in the past. |
|-------|--|
| Actn. | Enter a valid date. |

NAT0860: Invalid code.

| Text | Invalid code. |
|-------|-------------------|
| Actn. | Enter valid code. |

NAT0861: User has no special link to library.

| Text | User has no special link to library. |
|-------|--|
| Actn. | Contact your Natural Security administrator. |

NAT0862: This Natural session is not under Natural Security.

| Text | This Natural session is not under Natural Security. |
|------|---|
| | In order to perform the desired function, your Natural session must be running under Natural Security. |
| | Invoke Natural under Natural Security (ask your Natural administrator if necessary) before you perform the desired function. If Natural Security is not installed, that function is not available. |

NAT0863: Logon to this library not allowed via link ID ":1:".

| Text | Logon to this library not allowed via link ID "". |
|------|--|
| | Log on with a valid user ID; contact your Natural Security administrator if necessary. |

NAT0864: No. Lib. ID Library Name*Type*Linked via*Spec.

| Text | No. Lib. ID Library Name*Type*Linked via*Spec. |
|-------|--|
| Expl. | Text displayed by Natural Security. |

NAT0865: Invalid security file. Please contact your DBA.

| Text | Invalid security file. Please contact your DBA. |
|-------|---|
| Actn. | Contact your database administrator. |

NAT0866: Your Natural nucleus is not a Natural Security nucleus.

| Text | Your Natural nucleus is not a Natural Security nucleus. |
|-------|--|
| Expl. | There is an inconsistency between your Natural nucleus and your Natural system file (FNAT). The nucleus is marked as non-Security, but the Natural system file contains Natural Security-specific programs. Possible reasons for this inconsistency are: - the nucleus has been illegally zapped. - the Natural master control record has been illegally zapped. - the Natural Security NATLOAD has not been performed successfully. |
| Actn. | Contact your Natural administrator. Repeat the NATLOAD for Natural, and - if your system is a Natural Security one - also repeat the NATLOAD for Natural Security. |

NAT0867: Mailbox does not exist / not assigned to your environment.

| Text | Mailbox does not exist / not assigned to your environment. |
|-------|---|
| Actn. | Choose another mailbox ID; or contact your Natural Security |
| | administrator. |

NAT0868: The expiration date of mailbox :1: is already reached.

| Text | The expiration date of mailbox is already reached. |
|-------|--|
| Actn. | If necessary, change the expiration date. |

NAT0869: The file security record has been directly manipulated.

| Text | The file security record has been directly manipulated. |
|-------|---|
| Actn. | Contact your Natural Security administrator. |

NAT0870: Upload is not permitted.

| Text | Upload is not permitted. |
|-------|--|
| Actn. | Contact your Natural Security administrator. |

NAT0871: Download is not permitted.

| Text | Download is not permitted. |
|-------|--|
| Actn. | Contact your Natural Security administrator. |

NAT0872: Invalid function code.

| Text | Invalid function code. |
|-------|----------------------------|
| Actn. | Enter valid function code. |

NAT0873: User ID or password invalid.

| Text | User ID or password invalid. |
|-------|---|
| Actn. | Enter correct user ID and correct password. |

NAT0874: Press ENTER for next page, or "." to terminate session.

Text Press ENTER for next page, or "." to terminate session.

NAT0875: This user is currently not active.

| Text | This user is currently not active. |
|-------|--|
| Actn. | Contact your Natural Security administrator. |

NAT0876: New password is not valid. Please choose a different one.

| Text | New password is not valid. Please choose a different one. |
|-------|--|
| - | The new password was denied for one of the following reasons:1) The new password is too similar to previous passwords.2) The new password does not conform to the rules for passwords. |
| Actn. | Contact your Natural Security administrator. |

NAT0877: Utility access denied by Security. Contact your DBA.

| Text | Utility access denied by Security. Contact your DBA. |
|-------|--|
| Expl. | The utility is for restricted use only. |
| Actn. | Please contact your security administrator. |

NAT0878: Assigned group :1: is currently not active.

| Text | Assigned group is currently not active. |
|-------|---|
| Expl. | In a Natural Security (NSC) environment: - The NSC group ID shown in the message is defined with a date which marks this group ID as currently inactive. Additional information for NSF environments: - The group ID, for the user ID defined in the security system, is not defined in NSC, or the NSC group profile is inactive, or the NSC user profile is of another user type. |
| Actn. | Contact your Natural Security administrator. |

NAT0879: No active group assigned.

| Text | No active group assigned. |
|-------|---|
| | The user is not assigned to a group with a valid activation date. |
| Actn. | Contact your Natural Security administrator. |

NAT0880: More than 10 syntax errors occurred in BATCH compile.

| Text | More than 10 syntax errors occurred in BATCH compile. |
|-------|---|
| Actn. | Correct syntax errors and re-compile. |

NAT0884: Internal error, save area chain destroyed.

| Text | Internal error, save area chain destroyed. |
|-------|---|
| Expl. | The relocatable save area in Natural is destroyed. Natural resets the chain and restarts. Natural always tests the correct chains of its save areas. The error is caused by a wrong register 13, a save area overflow, or a wrong relocated user area. One reason for a save area overflow may be too many recursive program calls. |
| Actn. | Natural corrects automatically and restarts. If need be, reduce the number of recursive program calls. |

NAT0885: Internal error, I/O buffer overwritten.

| Text | Internal error, I/O buffer overwritten. |
|-------|--|
| 1 1 | The buffer area that is used to generate output to the screen/printer is also used for other purposes. |
| | A condition has arisen where the contents of this I/O buffer have been destroyed, and the buffer has not been re-initialized. |
| Actn. | Note down the command sequence and contact your Natural administrator. |

NAT0886: Storage overflow in extended buffer.

| Text | Storage overflow in extended buffer. |
|-------|---|
| Expl. | Certain tables during processing and compilation of Natural programs are stored in the extended buffer. The size of the extended buffer is defined by the Natural administrator with the ESIZE profile parameter. This error may also be caused by an attempt to write too many data to the Natural stack. |

Actn. Reduce size of source program, or contact your Natural administrator.

NAT0887: Internal stack overflow.

| Text | Internal stack overflow. |
|------|--|
| | Excessive program recursion has caused an internal overflow of the program-storage stack during program execution. |
| | Reduce the number of nested subroutines; or contact your Natural administrator. |

NAT0888: Storage overflow during compilation or execution.

| Text | Storage overflow during compilation or execution. |
|-------|--|
| Expl. | This error is caused by an overflow situation: - At compilation time, this error is issued if the length of an arith- metic expression in an IF condition exceeds the maximum of 32 KB. - At execution time, this error is due to a relocation of the DATSIZE buffer at execution of a Natural subprogram from a 3GL program (Natural 3GL program interface). |
| Actn. | Compilation: Reduce the number of arithmetic operations in the condition. Execution: Use the CALLNAT interface INTERFACE4. |

NAT0890: Invalid source parameter construction.

| Text | Invalid source parameter construction. |
|-------|--|
| | A possible cause for the error is the construction of a parameter source notation within another source parameter. Natural supports only one level of parameter source processing. |
| Actn. | Check program and correct error. |

NAT0894: Invalid format/length for operand.

| Text | Invalid format/length for operand. |
|-------|--|
| Expl. | An invalid format/length definition is used for an operand. This can have the following reasons: MINVAL/MAXVAL: The combination of operands with their format/length definitions does not comply with the rules for the generation of intermediate formats. Use the IR clause to set a certain format/length as result. |
| Actn. | Change the format/length of the operands. |

NAT0899: Internal error in structure of DDM :1:.

| Text | Internal error in structure of DDM |
|-------|--|
| Expl. | The DDM was not correctly generated and contains an internal |
| | inconsistency. |
| Actn. | Re-generate the DDM. |

NAT0900: Storage overflow while assigning data area.

| Text | Storage overflow while assigning data area. |
|-------|---|
| Expl. | The storage area that contains the data area for the program overflowed during address assignment for data fields. or: There are more than 50 external subroutines referenced in the program. or: There was an overflow while composing an executable object. |
| Actn. | Reduce the data areas in the program or use fewer database fields or ask your Natural administrator to review the USIZE parameter value. |

19 Natural System Error Messages 0901-0950

NAT0901: Length of record to be sorted exceeds 10240 bytes.

| Text | Length of record to be sorted exceeds 10240 bytes. |
|-------|---|
| Expl. | The total length of the record to be sorted must not exceed 10240 bytes. Note: The fields written to sort storage are not only those fields specified in the SORT statement, but all database fields and user-defined variables defined before the SORT statement. |
| Actn. | Ensure that the sort record does not exceed 10240 bytes. |

NAT0902: Storage overflow while creating format buffers.

| Text | Storage overflow while creating format buffers. |
|-------|--|
| Expl. | An overflow condition has occurred in the buffer used to store format buffers which define the fields to be read from the database. |
| | Reduce the number of files or number of fields referenced from the database, reduce the program size, or ask your Natural administrator if the USIZE parameter value can be increased. |

NAT0903: Storage overflow at execution time.

| Text | Storage overflow at execution time. |
|-------|---|
| Expl. | Storage overflow while creating a loop-table entry. |
| Actn. | Divide program into segments using "structured programming" techniques. |

NAT0904: Too many <MOVE " " TO variable> in program.

| Text | Too many <move "="" to="" variable=""> in program.</move> |
|-------|--|
| - | The program contains too many <move "="" to="" variable=""> statements.</move> |
| Actn. | Replace the statements with <reset variable="">.</reset> |

NAT0906: Natural nucleus does not support Version 1.2 runtime.

| Text | Natural nucleus does not support Version 1.2 runtime. |
|------|---|
| | The Natural nucleus was linked without the Version 1.2 runtime system. Only Natural objects cataloged/stowed with Natural Version 2 or above can be executed. |
| | Relink Natural nucleus with Version 1.2 runtime system and activate the new copy in your environment. |

NAT0907: Generation of record buffer failed. Reason code :1:.

| Text | Generation of record buffer failed. Reason code <rc>.</rc> |
|-------|--|
| | The maximum size of a view depends on the database which is used. During the generation of a database statement, the following error situation occurred. RC - description: 4 - For ADABAS/VSAM access statements record buffer size (view size) exceeds the maximum of 64K (Mainframe/ OpenVMS/ UNIX/ Windows). 8 - For DB2/SQL access statements the record buffer size (view size) exceeds the maximum of 32K (Mainframe) |
| Actn. | Reduce the size of the corresponding view. |

NAT0910: Insufficient core for CALL, SORT, WORK FILE statements.

| Text | Insufficient core for CALL, SORT, WORK FILE statements. |
|-------|---|
| | The processing of CALL, SORT and WORK FILE statements requires buffers in the partition. |
| | The partition does not have enough memory allocated for the storage requirements of the program. |
| Actn. | Re-submit in larger partition or contact your Natural administrator. |

NAT0911: :1: incompatible to mainframe version :2: (see :3:).

| Text | incompatible to mainframe version (see). |
|-------|---|
| | The statement/keyword used is not compatible with the corresponding mainframe version of Natural. You can avoid this error by setting the compatibility switch referred to in the error message (e.g., the profile parameter V41MFCOMP=ON/OFF). |
| Actn. | Use only compatible statements/keywords, or switch off the compatibility switch. |

NAT0916: Return code :1: from :2: user exit :3:.

| Text | Return code from user exit that caused Natural to discontinue program execution. |
|------|--|
| | The user exit detected a condition that prevented the completion of the operation. The condition has been indicated to Natural by means of a return code. The return code is specific to the user exit. Natural program execution has been terminated. |
| | Contact your Natural administrator or the author of the specified user exit. |

NAT0917: Error :1: in :2: :3:.

| Text | Error in |
|-------|--|
| Expl. | An error occurred in a statement of a copycode. This message is added to the initial error to show the object and line of the INCLUDE statement. In case of nested INCLUDEs, the message is added for each INCLUDE level. The messages can be displayed with the system command LASTMSG. Example: Program MAIN includes copycode COPYC at line 100. COPYC calls subprogram SUB1 at line 200. SUB1 does not exists. - Initial error message: COPYC 0200 NAT0923 Invalid program call (Callnat Program SUB1/ - Additional error message: MAIN 0100 NAT0917 Error 923 in Copycode COPYC. |
| Actn. | Check program and correct error. |

NAT0918: ESCAPE (TOP) not allowed in ON ERROR or AT block.

| Text | ESCAPE (TOP) not allowed in ON ERROR or AT block. |
|-------|--|
| Expl. | This error may be caused by one of the following: 1. An ESCAPE statement was used to exit from a currently active ON ERROR block. However, an ON ERROR block must be exited with a FETCH, STOP, TERMINATE or RETRY statement. 2. An ESCAPE TOP statement was used within one of the following conditions: |
| | - AT BREAK - AT START OF DATA - AT END OF DATA |
| Actn. | Correct error in program. |

NAT0919: Too many parameters used.

| Text | Too many parameters used. |
|-------|--|
| | For some statements, the number of parameters which can be specified is limited. For example, there is a limit for the CALL statement and the system functions *MINVAL and *MAXVAL. |
| Actn. | Reduce the number of parameters. |

NAT0920: Program :1: cannot be loaded :2:.

| Text | Program cannot be loaded |
|-------|--|
| Expl. | The specified external subprogram could not be loaded dynamically |
| | or located statically for one of the following reasons: |
| | - For dynamic subprograms only: The program was not contained in the |
| | load libraries currently defined to Natural. |
| | - There was not enough storage available for the dynamic loading of |
| | the subroutine. Check the operating system return code supplied. |
| | - The limit for the number of user subroutines to be dynamically |
| | loaded was exceeded. |
| | - Under Com-plete, the thread into which the program was to be |
| | loaded was too small. |
| | - For static subprograms only: The program is not defined in NATPARM |
| | by the "CSTATIC" parameter or not linked to the NATPARM module. |
| Actn. | Ensure that the subroutine is contained in a library available |
| | or linked to Natural. Contact your Natural administrator concerning |
| | the setting of the Natural parameters "CDYNAM" or "CSTATIC". |

NAT0921: Maximum call level reached.

| Text | Maximum call level reached. |
|-------|--|
| Expl. | Natural supports calls to other Natural objects up to level 99. Whenever a Natural object invokes another Natural object (e.g. via CALLNAT, INPUT MAP, PERFORM, FETCH RETURN), the level counter *LEVEL is incremented by one. When *LEVEL exceeds 99, this error is issued. This error usually occurs when an object calls itself recursively. |
| Actn. | Check program and correct error. |

NAT0922: Buffer pool not active.

| Text | Buffer pool not active. |
|-------|---|
| Expl. | Natural Version 2 requires an active buffer pool manager. |
| Actn. | Contact your Natural administrator. |

NAT0923: Invalid program call (:1: :2: :3:/:4:/:5:/:6:).

| Text | Invalid program call (:1: :2: :3:/:4:/:5:/:6:). |
|-------|---|
| | The Natural object :3: (of type :2:, loaded from library :4:, database :5:, file number :6:) cannot be invoked by statement or command :1:. |
| Actn. | Invoke Natural objects by the appropriate statements/commands. |

NAT0924: Command invalid in this context (:1: :2: :3:).

| Text | Command invalid in this context (:1: :2: :3:). |
|-------|--|
| Expl. | The command :1: is invalid for object :3: of type :2:. |
| Actn. | Consult the documentation and try again. |

NAT0925: GDA does not correspond to using program.

| Text | GDA does not correspond to using program. |
|-------|--|
| Expl. | Each time a program uses a GDA (global data area), Natural checks whether the compilation time of the program is later than the compilation time of the GDA. If it is not, Natural assumes that the GDA may not correspond to the layout generated into the program and produces this error. |
| Actn. | Recompile program and restart system. |

NAT0926: Only objects of type "program" can be "RUN".

| Text | Only objects of type "program" can be "RUN". |
|-------|--|
| Expl. | A RUN command was issued for a Natural object which is not a source |
| | program; |
| | or the RUN command was issued without a program name, and the editor |
| | work area was not empty and set to a type other than "PROGRAM". |
| | To test the execution of a subprogram or subroutine, you have to |
| | catalog/stow this object and write a program that calls this |
| | object (with a CALLNAT or PERFORM statement respectively). |
| | A map can be tested in the map editor, as can helproutines and helpmaps. |
| | GDA, LDA and PDA define data areas and their initialization values and |
| | only become executable when referenced in the DEFINE DATA statement |
| | of a Natural object. |
| Actn. | Check that the work area contains a program, and that the editor type |
| | is set to "PROGRAM", or that the specified object is a program, or |
| | follow the above hints to test objects of other types. |

NAT0927: FETCH RETURN statement rejected by Natural Security.

| Text | FETCH RETURN statement rejected by Natural Security. |
|-------|--|
| | A program called via a FETCH RETURN statement is security protected and, therefore, cannot be called from another Natural program. |
| Actn. | Contact your Natural or Natural Security administrator. |

NAT0928: Program can only be executed from a SYS* library.

| Text | Program can only be executed from a SYS* library. |
|-------|---|
| Expl. | This program is security protected and can only be executed from a SYS* library. (SYSTEM is not treated as a SYS* library.) |
| Actn. | Log on to the correct library. |

NAT0929: Program cannot be executed in batch mode.

| Text | Program cannot be executed in batch mode. |
|-------|---|
| | An attempt was made to execute in batch mode a program that contains online functions/features. |
| Actn. | Execute the program in interactive mode. |

NAT0930: Program cannot be executed online.

| Text | Program cannot be executed online. |
|------------|---|
| _ _ | An attempt was made to execute in interactive mode a program that contains functions/features only available in a batch mode environment. |
| Actn. | Execute the program in batch mode. |

NAT0931: CMSYNIN job control definition is missing.

| Te | ext | CMSYNIN job control definition is missing. |
|----|------|--|
| E | | In batch mode execution, the DD statement for the definition of the main command and source input for Natural is missing. No commands can be read. |
| A | ctn. | Specify definition for the CMSYNIN file in the job control. |

NAT0932: Program version error.

| Text | Program version error. |
|-------|---|
| | The executing program has been recataloged by another user between screen I/Os (that is, it is possible that the program has been stowed by a second user while a first user is still using it). |
| Actn. | Contact your Natural administrator. |

NAT0933: GDA time-stamp conflict.

| Text | GDA time-stamp conflict. |
|-------|---|
| Expl. | This error occurs if a program references a global data area (GDA) which was recataloged or a GDA that has been moved from another environment after the program has been cataloged. Also the program that references the GDA could have been moved from a different environment into the current one causing a GDA time-stamp conflict. If a GDA is cataloged again, all objects which reference the GDA must also be cataloged again. |
| Actn. | Check the program structure and recatalog if necessary, or use the profile parameter RECAT=ON. RECAT=ON is not possible for programs cataloged with the Natural Optimizer Compiler. |

NAT0934: GDA conflict :1: active :2: structure :3:.

| Text | GDA conflict active structure |
|-------|---|
| Expl. | There are two reasons for this error: a) GDA names differ: A Natural object attempted to use a GDA which is different from the one already in use. This is allowed only for CALLNAT and FETCH. b) GDA names are identical: A Natural object attempted to use block(s) in a GDA in a way which conflicts with the blocks already in use. |
| Actn. | Compare GDA usage in the object which was being called with the object which created the current structure of the active GDA. The structure creation object is shown behind the word "structure". |

NAT0935: Conflicting number of parameters (:1: :2:/:3:/:4:/:5:).

| Text | Conflicting number of parameters (:1: :2:/:3:/:4:/:5:). |
|-------|---|
| - | The number of parameters defined in object :2: (of type :1:, loaded from library :3:, database :4:, file number :5:) does not correspond to the number of parameters used to invoke the object. |
| Actn. | Check program and correct error. |

NAT0936: Format/length conflict in parameter :1: (:2: :3:/:4:/:5:/:6:).

| Text | Format/length conflict in parameter :1: (:2: :3:/:4:/:5:/:6:). |
|-------|---|
| Expl. | The parameter defined at position :1: in object :3: (of type :2:, loaded from library :4:, database :5:, file number :6:) does not match the format/length of the corresponding parameter used to invoke it. The following conditions must be met: - The formats must be equal. - The lengths must be equal. - The precisions must be equal. |
| Actn. | Check program and correct error. |

NAT0937: Wrong array defined in param. :1: (:2: :3:/:4:/:5:/:6:).

Text Wrong array defined in param. :1: (:2: :3:/:4:/:5:/:6:).

| Expl. | The array defined as parameter at position :1: in object :3: (of |
|-------|---|
| | type :2:, loaded from library :4:, database :5:, file number :6:) |
| | does not match the array or array range used as corresponding parameter |
| | to invoke it. |
| | The following conditions must be met: |
| | - The ranks must be equal. |
| | - The occurrences of each dimension must be equal. |
| | This error also occurs if a 3GL routine calls a subprogram, and |
| | the subprogram"s PDA specifies a variable array range (1:V). |
| Actn. | Check program and correct error. |

NAT0938: Prot. param. :1: used as target field (:2: :3:/:4:/:5:/:6:/).

| Text | Prot. param. :1: used as target field (:2: :3:/:4:/:5:/:6:/). |
|------|--|
| Expl | . The parameter defined at position :1: in object :3: (of type :2:, loaded from library :4:, database :5:, file number :6:) is used as a target operand. However, this parameter is protected: it is a constant, or it has the attribute (AD=ON), and must not be modified. |
| Actr | . Check program and correct error. |

NAT0939: Natural editor is not linked and cannot be loaded.

| Text | Natural editor is not linked and cannot be loaded. |
|-------|---|
| Expl. | The Natural editor modules are not linked and cannot be loaded. |
| Actn. | Contact your database administrator. |

NAT0940: This terminal command is not supported.

| Text | This terminal command is not supported. |
|-------|--|
| - | Terminal commands for screen paging cannot be used under every TP monitor. |
| Actn. | Enter a valid command. |

NAT0941: Invalid size for screen-paging system file.

| Text | Invalid size for screen-paging system file. |
|-------|---|
| | A screen-paging command was entered, but the size of the system file used for screen paging was "0", which means that no screens can be stored. |
| Actn. | Restart Natural session with valid size for screen-paging system file. |

NAT0942: Invalid use of hardcopy facility.

| Text | Invalid use of hardcopy facility. |
|-------|---|
| | The Natural hardcopy facility is only available under the TP monitor Com-plete. |
| Actn. | Enter a valid Natural command. |

NAT0943: Screen paging open function failed.

| Text | Screen paging open function failed. |
|------|--|
| Actn | Check the status of the screen-paging system file. |

NAT0944: Screen paging record overflow.

| Text | Screen paging record overflow. |
|-------|---|
| | An attempt was made to write to the screen-paging system file a record which was larger than the screen page size. |
| Actn. | Increase the size of the physical terminal buffer. |

NAT0946: Screen paging write failed.

| Text | Screen paging write failed. |
|-------|---|
| | An error occurred during an attempt to write a screen to the screen-paging system file. |
| Actn. | Check the status of the screen-paging system file. |

NAT0947: Screen paging read failed.

| Text | Screen paging read failed. |
|-------|--|
| Expl. | An error occurred during an attempt to read a screen from the screen-paging system file. |
| Actn. | Check the status of the screen-paging system file. |

NAT0950: Abnormal end due to unhandled LE condition :1:.

| Text | Abnormal end due to unhandled LE condition |
|-------|---|
| Expl. | During the execution of an LE (IBM Language Environment) subprogram, |
| | an error condition has occurred. As no condition handler was active |
| | in the subprogram to handle the error, control has been passed to the |
| | Natural LE condition handler, which calls LE services to write an LE |
| | snap dump to CEEDUMP and to issue more detailed LE error messages. |

| Actn. | Check the LE error condition, the messages and the snap dump to find |
|-------|---|
| | out the reason of the error. If necessary, correct the LE subprogram. |

20 Natural System Error Messages 0951-1000

NAT0951: Normal end of execution.

| Text | Normal end of execution. |
|-------|---|
| | This message indicates the successful execution or completion of a Natural batch job. |
| Actn. | No action required. |

NAT0952: Database loop processing limit exceeded.

| Text | Database loop processing limit exceeded. |
|-------|--|
| Expl. | The processing limit of a HISTOGRAM/FIND/READ database loop is specified via a numeric constant or a numeric user-defined variable. When this limit is exceeded, this does not necessarily indicate an error condition; however, the records which met the search criteria in a database loop but which are beyond the limit have not been processed. Note: The general limit for processing loops may also be set with the Natural session parameter LT. |
| Actn. | Increase the limit value or ignore this error message. |

NAT0953: Time limit exceeded.

| Text | Time limit exceeded. |
|-------|---|
| Expl. | In TP mode, this message means that the time-out parameter specified |
| | for the TP monitor at system generation time is not sufficient to |
| | handle current program requirements. In batch mode, after determining |
| | that the program is not in an endless loop, the MT parameter (via a |
| | SET GLOBALS statement or GLOBALS command) can be used to increase the |
| | CPU-time factor. |

| A | .ctn. | Check program and correct it if necessary. |
|---|-------|--|
| | | If program is correct, contact your Natural administrator. |

NAT0954: Abnormal termination :1: during program execution.

| Text | Abnormal termination during program execution. |
|------|--|
| Expl | . An abnormal termination has occurred during the execution of a Natural object program. |
| | A common cause of this error is the use of an arithmetic operand which does not contain valid numeric data at execution time. |
| Actr | . Check program and correct error. |

NAT0955: Abnormal termination :1: during program compilation.

| Text | Abnormal termination during program compilation. |
|-------|--|
| - | An internal abnormal termination has occurred during the Natural syntax/compilation phase. |
| Actn. | Contact your Natural administrator. |

NAT0956: Abnormal termination :1: during command analysis.

| Text | Abnormal termination during command analysis. |
|-------|--|
| · · | An abnormal termination of the Natural system has occurred during the evaluation of a command. |
| Actn. | Contact your Natural administrator. |

NAT0957: Database loop limit reached with "LE=ON".

| Text | Database loop limit reached with "LE=ON". |
|-------|--|
| Expl. | The limit specified for a database processing loop in a FIND, READ or HISTOGRAM statement was reached. This leads to a termination of the loop statement and the program flow continues normally with the statement following the aborted loop. At the end of the program, error message NAT0957 is encountered, if parameter "LE=ON" is set. The limit may be either set with an explicit value supplied in the database loop statement (e.g. FIND (10)) or, if no explicit limit was given, globally in a program with the LIMIT statement (e.g. LIMIT 10). In batch mode, Natural will continue processing only if the session parameter CC is set to "OFF". |
| Actn. | Increase the limit value or set "LE=OFF". |

NAT0958: Invalid usage of ODA (object data area) in method :1:.

| Text | Invalid usage of ODA (object data area) in method |
|-------|---|
| Expl. | Object data areas (ODAs) are defined in methods to use class-specific data. If an ODA is defined in a subprogram, this subprogram can only be called as a method of a class (statement SEND METHOD). Also the ODA defined in a method must be compatible to the ODA defined in the class. The method is either being called without using SEND METHOD, or the ODA defined in the method contains a different number of variables than the ODA defined in the class. |
| Actn. | Activate the method using SEND METHOD. Ensure that the ODA defined in the method contains the same number of variables as the ODA defined in the class. |

NAT0959: Inconsistent ODA structure in class :1: and method :2: (:3:).

| Text | Inconsistent ODA structure in class and method (). |
|-------|--|
| Expl. | Object data areas (ODAs) are defined in methods to use class-specific data. Therefore, the structure of the ODA defined in the class must match the structure of the ODA defined in the method. An inconsistency was detected for the variable shown in brackets. |
| Actn. | Ensure that the variables contained in the ODA of a method and its class have the same format and length. |

NAT0960: SAVE/CATALOG/PURGE/UNCATALOG terminated unsuccessfully.

| Text | SAVE/CATALOG/PURGE/UNCATALOG terminated unsuccessfully. |
|-------|--|
| Expl. | The operation was attempted repeatedly and a response code of "9" for transaction back-out was received from Adabas when XREF data were processed. |
| Actn. | Ask your Natural administrator to review the maximum transaction duration time setting for Adabas. |

NAT0961: Concurrent SAVE/CAT/PURGE/UNCAT; or hold queue full.

| Text | Concurrent SAVE/CAT/PURGE/UNCAT; or hold queue full. |
|-------|---|
| Expl. | The same source program/object module is currently being processed |
| | for update by another user. |
| | This error condition can also be produced when Adabas response code |
| | "145" is received while attempting to delete the "old" copy of the |
| | Natural source or object program. A common reason for this error is |
| | an overflow of the Adabas hold queue. |

| Actn. | Retry operation later. |
|-------|---|
| | If problem persists, notify your Natural administrator. |

NAT0962: Invalid access to Natural system library.

| Text | Invalid access to Natural system library. |
|-------|--|
| | An attempt was made to access/replace a program in the Natural system library "SYSLIB". The use of "SYSLIB" is restricted to Natural system routines; a user must not use library ID "SYSLIB". |
| Actn. | Do not attempt to access the system library "SYSLIB". |

NAT0963: Security violation during program execution (:1:).

| Text | Security violation during program execution (). |
|-------|--|
| | The current user has attempted to execute a Natural program which has a restricted status. |
| Actn. | Contact your Natural administrator. |

NAT0964: Subroutine/Function :1: already exists as member :2:.

| Text | Subroutine/Function already exists as member |
|-------|---|
| Expl. | Names of subroutines/functions within a library must be unique. |
| Actn. | Choose another name for the subroutine/function. |

NAT0965: ConvError returning RESULT parameter :1: (:2: :3:/:4:/:5:/:6:)

| Text | Conversion error returning RESULT parameter :1: (:2: :3:/:4:/:5:/:6:) |
|-------|--|
| | While returning the value of parameter :1:, which was defined with the attributes BY VALUE RESULT in object :3: (of type :2:, loaded from library :4: from database :5: file number :6:), a conversion error has occurred. Check if the current value complies with the "Rules for Arithmetic Assignment" described in the Natural documentation. |
| Actn. | Correct error in program. |

NAT0966: ConvError assign BY VALUE parameter :1: (:2: :3:/:4:/:5:/:6:)

| Text | Convs. error assigning BY VALUE parameter :1: (:2: :3:/:4:/:5:/:6:) |
|-------|--|
| Expl. | During assignment of the value of parameter :1:, which is defined with the attributes BY VALUE (RESULT) in object :3: (of type :2:, loaded from library :4: from database :5: file number :6:), a conversion error has occurred. Check if the current value complies with the "Rules for Arithmetic Assignment" described in the Natural documentation. |
| Actn. | Correct error in program. |

NAT0967: Function :1: not permitted in current context.

| Text | Function not permitted in current context. |
|-------|---|
| | The function indicated is not permitted in a certain context, e.g. while the 3GL callnat interface, a SEND METHOD or a PARSE is active. |
| Actn. | Correct error in program. |

NAT0968: Mandatory parameter :1: not specified (:2: :3:/:4:/:5:/:6:)

| Text | Mandatory parameter not specified (//) |
|-------|--|
| | The parameter, which is not specified as optional in the PDA, was not passed. The called object is described by type, name, database ID, and file number. This error can occur also if too few parameters are passed. |
| Actn. | Check program(s) and correct the error. |

NAT0969: Dynamic parameter :1: mismatch (:2: :3:/:4:/:5:/:6:)

| Text | Dynamic parameter mismatch (//) |
|-------|---|
| | The parameters, which are used by reference, must be either both dynamic in caller and declaration, or both non-dynamic in both caller and declaration. The parameter number is given and the called object is described by type, name, database ID, and file number. |
| Actn. | Check program(s) and correct the error. |

NAT0970: Source line limit for program creation is zero.

| Text | Source line limit for program creation is zero. |
|-------|--|
| - | When the security authorization for this user in this application was defined, the user was allowed to create source programs but the limit for the number of source lines to be created was erroneously set to "0". |
| Actn. | Contact your Natural Security administrator. |

NAT0971: Source line limit reached.

| Text | Source line limit reached. |
|-------|---|
| Expl. | In the security authorization for this user in this application, a limit of source lines to be created in new programs has been defined. The user cannot exceed this limit when creating new programs. |
| Actn. | Either reduce program size or ask your Natural Security administrator to increase the limit of source lines. |

NAT0972: User is not authorized to use this command: :1:.

| Text | User is not authorized to use this command: |
|------|---|
| | In the security authorization for this user in this application, only specific commands have been made available. The user is not allowed to use the command specified. |
| 1 | Do not use this command in this environment, or contact your Natural Security administrator for authorization. |

NAT0973: User is not authorized to use this statement.

| Text | User is not authorized to use this statement. |
|-------|--|
| | In the security authorization for this user in this application, only certain statements have been made available. The user is not allowed to use the specified statement. |
| Actn. | Do not use this statement, or ask your Natural Security administrator for authorization. |

NAT0974: User is not authorized to use this file.

| Text | User is not authorized to use this file. |
|------|--|
| | In the security authorization for this user in this application, only certain files have been made available. The user is not allowed to use the specified file. |
| | Either do not use this file or contact your Natural Security administrator for authorization. |

NAT0975: User is not authorized to update this file.

| Text | User is not authorized to update this file. |
|-------|--|
| | In the security authorization for this user in this application, only certain files have been made available for updating. The user is not allowed to update the specified file. |
| Actn. | Do not update this file, or contact your Natural Security administrator for authorization. |

NAT0976: Inconsistent security definition for command selection.

| Text | Inconsistent security definition for command selection. |
|-------|--|
| | An inconsistent definition may occur if the Natural administrator has selected commands on the selection screen in the Natural Security system that are not defined to the system. |
| Actn. | Contact your Natural administrator. |

NAT0977: Inconsistent security definition for statement selection.

| Text | Inconsistent security definition for statement selection. |
|-------|--|
| | An inconsistent security definition may occur if the Natural |
| | administrator selects statements that are not defined to the system. |
| Actn. | Contact the Natural administrator. |

NAT0978: Invalid use of default format definition (N7).

| Text | Invalid use of default format definition (N7). |
|-------|---|
| | Natural Security allows specification of the user characteristics; one option of these is whether the user is allowed to use the default format definition (N7). For this user in this application, the option is not allowed. |
| Actn. | You must explicitly specify the format/length of variables. |

NAT0979: Specification of the library not allowed.

| Text | Specification of the library not allowed. |
|-------|--|
| | In a security-protected environment, a user may not access a library by merely specifying the library ID in a command. The user must properly log on to the library and may then access it. This protection is also valid in a non-security environment for a library ID that starts with "SYS". |
| Actn. | Log on to the desired library and then re-issue the command. |

NAT0980: Invalid use of database file number.

| Text | Invalid use of database file number. |
|-------|---|
| | The use of a file number in a database access statement is not allowed. |
| Actn. | Use the view name instead of a file number. |

NAT0981: Use of 2-character database short-name field not allowed.

| Text | Use of 2-character database short-name field not allowed. |
|-------|--|
| | A reference to a 2-character database short-name field is not permitted, 1)- when running under Natural Security; 2)- inside the definition of a data-view (DEFINE DATA); 3)- when a DEFINE DATA LOCAL was previously used to define variables; 4)- when the compiler option DBSHORT=OFF is set. |
| Actn. | Do not use 2-character database short-name fields. |

NAT0982: Internal error; invalid system command requested.

| Text | Internal error; invalid system command requested. |
|-------|--|
| | A system command was requested that requires a Natural program which is not defined. |
| Actn. | Contact your Natural administrator. |

NAT0983: Update commands not authorized by Natural Security.

| Text | Update commands not authorized by Natural Security. |
|-------|--|
| Expl. | You are not allowed to issue update commands. |
| | Contact your Natural administrator concerning Natural Security definition/authorization. |

NAT0984: This file is not defined in Natural Security.

| Text | This file is not defined in Natural Security. |
|-------|--|
| Actn. | Check program and correct error, or contact your Natural Security administrator. |

NAT0985: Return value not defined in function :1: (:2:/:3:/:4:).

| Text | Return value not defined in function (/). |
|-------|--|
| - | A return value is required by the calling object, but not defined in the called function. The name of the function, its library, DBID and FNR are indicated in the error message. |
| Actn. | Check program and correct error. |

NAT0986: Format/length conflict in return variable (:1:/:2:/:3:/:4:).

| Text | Format/length conflict in return variable (//). |
|-------|--|
| | The return variable specified in the DEFINE PROTOTYPE statement is defined with a format/length different from that of the corresponding return variable defined in the called function. The name of the function, its library, DBID and FNR are indicated in the error message. |
| Actn. | Check program/function and correct error. |

NAT0987: Conversion error in BY VALUE variable (:1:/:2:/:3:/:4:).

| Text | Conversion error in BY VALUE variable (//). |
|-------|--|
| Expl. | While returning the value of a return variable which is defined with the attribute BY VALUE in a function, a conversion error has occurred. Make sure that the value specified in the DEFINE PROTOTYPE statement matches the "Rules for arithmetic assignment" described in the Natural documentation. The name of the function, its library, DBID and FNR are indicated in the error message. |
| Actn. | Correct error in program. |

NAT0988: Dynamic return variable mismatch (:1:/:2:/:3:/:4:).

| Text | Dynamic return variable mismatch (//). |
|-------|---|
| Expl. | A return variable which is used by reference must be either dynamic in both the DEFINE PROTOTYPE statement and the function declaration, or non-dynamic in both the DEFINE PROTOTYPE statement and the function declaration. The name of the function, its library, DBID and FNR are indicated in the error message. |
| Actn. | Check program/function and correct error. |

NAT0997: Invalid format buffer for STORE/UPDATE statement.

| Text | Invalid format buffer for STORE/UPDATE statement. |
|-------|---|
| Expl. | Natural has detected a format buffer for a STORE/UPDATE statement with a length of zero. This is invalid. |
| Actn. | Check program and correct error. |

NAT0998: Internal error :1:.

| Text | Internal error |
|-------|-------------------------------------|
| Actn. | Contact your Natural administrator. |

NAT0999: Internal error.

| Text | Internal error. |
|-------|-------------------------------------|
| Actn. | Contact your Natural administrator. |

NAT1000: FIND set name not found in RETAIN table.

| Text | FIND set name not found in RETAIN table. |
|-------|---|
| | A reference was made to a set name which had not been placed in the FIND set table by a FIND RETAIN statement. |
| Actn. | Enter correct set name. |

21 Natural System Error Messages 1001-1050

NAT1001: DBID or file number of set do not agree with current file.

| Text | DBID or file number of set do not agree with current file. |
|-------|---|
| Expl. | If a FIND set is to be used in another FIND statement as a logical criterion, the set must have been selected from the same set that is currently being processed in the FIND statement. However, in the case of this error, the database ID and/or file number of the previously retained set is different from that of file that is currently being processed. |
| Actn. | Check program and correct error. |

NAT1003: Global limit for database calls reached -> LT parameter.

| Text | Global limit for database calls reached -> LT parameter. |
|-------|--|
| Expl. | The maximum number of records permitted to be read from the database was exceeded. The number is set with the profile and session parameter LT. When a record is read from a database, with a FIND, READ or HISTOGRAM statement, a counter field is first incremented and then compared with the current value of the LT parameter. If the actual LT value is exceeded, runtime error NAT1003 is issued. When a Level 1 program is newly started, the counter field is reset and starts again with zero. When another object is called which runs on a level higher than 1, the counter is not reset and continues with the value that was already reached by the previous program. |
| Actn. | Increase the value of the LT parameter. |

NAT1004: In FIND UNIQUE, 0 records or more than 1 record found.

| Text | In FIND UNIQUE, 0 records or more than 1 record found. |
|-------|---|
| | The FIND UNIQUE statement requires that exactly one record be |
| | found in the database. |
| Actn. | Check program and correct error. |

NAT1005: More records found than specified in search limit.

| Text | More records found than specified in search limit. |
|-------|---|
| · · | The "WITH LIMIT = nnn" clause may be used to specify that a WHERE condition is only to be evaluated if fewer than "nnn" records have been selected after the evaluation of the basic search criteria. |
| Actn. | Increase the WITH limit, or redefine the basic search criteria. |

NAT1006: Value specified for index is "0" or greater than maximum.

| Text | Value specified for index is "0" or greater than maximum. |
|-------|---|
| Expl. | The value specified for an index of a multiple-value field or a periodic group is either greater than the maximum or less than 1. For Adabas, the maximum index value may be up to 65534, depending on the Adabas version and definition of the FDT. For VSAM and DL/I, the maximum index value is 191. For DDMS, the maximum index value is 9999. |
| Actn. | Check program and correct error. |

NAT1007: Integer value supplied is not in valid range.

| Text | Integer value supplied is not in valid range. |
|-------|--|
| Expl. | The integer value supplied is either negative or greater than 4GB-1. This is not permitted. |
| Actn. | Supply an integer value in the range from 0 to 4294967295. |

NAT1008: Variable index defined in a RETAIN-List-Record-Buffer.

| Text | Variable index defined in a RETAIN-List-Record-Buffer. |
|-------|--|
| Expl. | A variable index is not allowed for a RETAIN-list record buffer, because the format buffer will not be released with EC command. |
| Actn. | Check program and correct error. |

NAT1009: Program interrupted after too many database calls.

| Text | Program interrupted after too many database calls. |
|-------|--|
| Expl. | Natural counts all database calls and compares the result with the setting of the parameter MADIO. When this value is reached, a loop is assumed and the program terminated. The database-call count is reset to 0 after a screen I/O operation. |
| Actn. | Correct error in program. |

NAT1010: STORE/UPDATE/DELETE rejected due to UPDATE OFF command.

| Text | STORE/UPDATE/DELETE rejected due to UPDATE OFF command. |
|-------|--|
| Expl. | The program is being executed while "UPDATE OFF" is in effect. Whenever the program issues an STORE/UPDATE/DELETE statement for |
| | the database, this warning message is used to indicate that a database-updating statement was encountered but not executed. |
| Actn. | Contact your Natural administrator. |

NAT1011: Requested function key not allocated.

| Text | Requested function key not allocated. |
|-------|--|
| Expl. | A user can only request a function by pressing a function key if the key has been defined in the program with a SET KEY statement. If this error message appears in response to NEXT, the KEY command may be used to assign a value to the function key. |
| Actn. | Define the function key as described above. |

NAT1012: Update not allowed for system file.

| Text | Update not allowed for system file. |
|-------|---|
| Expl. | The user is not authorized to issue SAVE or CATALOG commands. |
| Actn. | Contact your Natural administrator. |

NAT1013: Illegal terminal command requested.

| Text | Illegal terminal command requested. |
|-------|--|
| Expl. | For information on valid terminal commands, see the Natural documentation. |
| Actn. | Enter a correct terminal command, or press ENTER. |

NAT1016: Application interrupted by a user action.

| Text | Application interrupted by a user action. |
|-------|---|
| Expl. | One of the following actions caused an application interrupt: - The mainframe terminal user interrupted the Natural program via an attention interrupt: RESETting the terminal and pressing the ENTER key. - Closing the Entire Connection upload or download dialog box by clicking on the CANCEL button caused an attention interrupt. - The application was interrupted via the typical system-interrupt key combination (e.g., CTRL+BREAK for Windows, CTRL+C for UNIX). |
| Actn. | No action required. |

NAT1017: Update not allowed for read-only database (:1:).

| Text | Update not allowed for read-only database (). |
|-------|--|
| | The database indicated is set to "read-only" via the NTDB macro or the dynamic parameter DB. |
| Actn. | Check program and correct error. |

NAT1019: Magnetic card reader must be activated with SET KEY.

| Text | Magnetic card reader must be activated with SET KEY. |
|-------|--|
| | Before reading data via a magnetic card reader, the magnetic card reader must have been made program-sensitive via a SET KEY statement (SET KEY MGID, SET KEY CDID, or SET KEY ALL). |
| Actn. | Correct error in program. |

| Text | Not permitted to invoke recursive database loop. |
|-------|--|
| Expl. | An already active database loop may not be started |
| | a second time. |
| | Example: PERFORM SUB001 |
| | DEFINE SUBROUTINE SUB001 |
| | FIND view-name WITH field = "any-value" |
| | DISPLAY *ISN *COUNTER *NUMBER |
| | PERFORM SUB001 < recursive call |
| | END-FIND |
| | END-SUBROUTINE |
| Actn. | Correct error in program. |

NAT1028: Not permitted to invoke recursive database loop.

NAT1029: Interrupt after too many Natural program calls.

| Text | Interrupt after too many Natural program calls. |
|-------|--|
| Expl. | Every FETCH, CALLNAT, PERFORM statement is counted. This count is compared against the value supplied in the Natural parameter module or set via the dynamic parameter facility for MAXCL. If this value is less than or equal to the counted value, Natural destroys the name of the error transaction and issues this error. |
| Actn. | Check program and correct error, or set MAXCL to "0" or to a large enough value. |

NAT1030: Internal error; invalid access to Natural system file.

| Text | Internal error; invalid access to Natural system file. |
|-------|--|
| Actn. | Contact your Natural administrator, and, if necessary, |
| | Software AG support. |

NAT1031: Invalid access to a VSAM dataset.

| Text | Invalid access to a VSAM dataset. |
|-------|---|
| | Access to a VSAM dataset was requested, but the Natural system does not include support for VSAM. |
| Actn. | Contact your Natural administrator. |

NAT1032: Invalid access to a DL/I database.

| Text | Invalid access to a DL/I database. |
|-------|--|
| - | Access to a DL/I database was requested, but the Natural system does not include support for DL/I. |
| Actn. | Contact your Natural administrator. |

NAT1049: Invalid contents of direction operand.

| Text | Invalid contents of direction operand. |
|-------|--|
| Expl. | The variable-direction operand (#op), used in a READ IN VARIABLE #op SEQUENCE |
| | or HISTOGRAM IN VARIABLE #op SEQUENCE statement contains an invalid character. Only the following values are permitted: "D" or "d" for DESCENDING "A" or "a" for ASCENDING. |
| Actn. | Fill the direction operand with a valid character. |

22 Natural System Error Messages 1051-1100

NAT1073: Initialization of :1: buffer pool failed. (:2:).

| Text | Initialization of buffer pool failed. (). |
|-------|--|
| | The indicated buffer pool could not be initialized for one of the following reasons: - GETMAIN for the local buffer pool storage failed - specified buffer pool size (BPSIZE parameter) is too small - missing LINK for the EDTSTUB (installation error) |
| Actn. | Please check installation and correct the problem. |

NAT1074: Global :1: buffer pool :2: not found.

| Text | Global :1: buffer pool :2: not found. |
|-------|--|
| Expl. | The global buffer pool :2: of type :1: could not be found. Either the global buffer pool is not yet allocated or the used name of the global buffer pool is wrong. If the buffer pool could not be found because the Natural subsystem does not exist, the name of the Natural subsystem is appended to the name of the global buffer pool, separated by a slash (/). |
| Actn. | Check the name of the global buffer pool (Natural profile parameter BPNAME or NTBPI/BPI subparameter NAME) and/or the name of the Natural subsystem (Natural profile parameter SUBSID). |

NAT1075: Global :1: buffer pool :2: allocated in system key.

| Text | Global buffer pool allocated in system key. |
|-------|---|
| | The indicated global buffer pool has been allocated in system key, but the authorized services manager (ASM) has not been started or is not of the required minimum version. To process a buffer pool that has been allocated in system key, the ASM is required. |
| Actn. | Start an authorized services manager of the required minimum version for the Natural subsystem in use. |

NAT1076: Error :1: while loading preload list :2: :3:.

| Text | Error :1: while loading preload list :2: :3:. |
|-------|---|
| Expl. | Natural error :1: has occurred when Natural tried to load the buffer pool preload list :2: at the start of the Natural session. If the Natural error occurs when the preload list is being read, the information :3: is blank. If the Natural error occurs when an object named in the preload list is being loaded, :3: contains library and program name of the object. The typical Natural error will be NAT0082, which means that either the preload list or one the named objects could not be found. |
| Actn. | Check the object names in your preload list. |

NAT1080: Cache creation failure :1: :2: :3: Reason= :4:.

| — · | |
|------------|--|
| lext | Cache creation failure :1: :2: :3: Reason= :4:. |
| Expl. | The cache create function has failed. |
| | The message shows the failing operating-system macro and the macro |
| | function (:1:). |
| | It also indicates the type of macro-request failure (:2:), that is, |
| | whether the macro failed due to macro failure (RC=) or ABEND (CC=). |
| | Parameter :3: is the ABEND code or macro-request return code |
| | respectively. |
| | Parameter :4: is the associated reason code. |
| Actn. | See the relevant operating-system manuals for the reason of the failure. |

NAT1081: Cache deletion failure :1: :2: :3: Reason= :4:.

| Text | Cache deletion failure :1: :2: :3: Reason= :4:. |
|-------|--|
| Expl. | The cache delete function has failed. The message shows the failing operating-system macro and the macro function (:1:). It also indicates the type of macro request failure (:2:), that is, whether the macro failed due to macro failure (RC=) or ABEND (CC=). Parameter :3: is the ABEND code or macro-request return code |
| | respectively. Parameter :4: is the associated reason code. |
| Actn. | See the relevant operating-system macros for the reason of the failure. |

NAT1100: Input value for a numeric field is not numeric.

| Text | Input value for a numeric field is not numeric. |
|-------|---|
| Expl. | The input value for a numeric field must contain a valid numeric value. The value may be preceded and/or followed by one or more blanks. Only one sign and decimal character are permitted. The value must not be longer than the field. |
| Actn. | Enter a valid numeric value. |

23 Natural System Error Messages 1101-1150

NAT1101: The specified maximum page count has been exceeded.

| Text | The specified maximum page count has been exceeded. |
|------|---|
| | The value for the maximum number of pages, as specified in the Natural session parameter MP, has been exceeded. |
| | Increase the value for the MP parameter, or reduce the number of pages produced. |

NAT1102: Input hexadec. value does not contain hexadec. characters.

| Text | Input hexadecimal value does not contain hexadecimal characters. |
|-------|--|
| | For the specification of hexadecimal input, only the characters "0" to "9" and "A" to "F" may be used. |
| Actn. | Enter valid hexadecimal characters. |

NAT1103: Field number in REINPUT statement must not exceed 255.

| Text | Field number in REINPUT statement must not exceed 255. |
|-------|--|
| | The field number to mark a field in the REINPUT statement may be specified as a numeric constant or the content of a numeric integer variable with a value of 255 or less. |
| Actn. | Check program and correct error. |

NAT1104: Classical I/O not permitted while modal window is active.

| Text | Classical I/O not permitted while modal window is active. |
|-------|--|
| Expl. | When a modal window has been activated by a PROCESS PAGE MODAL statement, a classical I/O (WRITE, PRINT, DISPLAY, INPUT) is not permitted. In a modal window, only rich GUI processing initiated by a PROCESS PAGE statement is allowed. |
| Actn. | Check program and correct error. |

NAT1105: Undefined keyword :1: in input.

| Text | Undefined keyword in input. |
|-------|--|
| Expl. | In keyword/delimiter input mode, individual fields can be selected via keywords, that is, the field name or the text that was specified preceding the field name in the INPUT statement. The specified value cannot be identified as a keyword from the INPUT statement. |
| Actn. | Either use %F or IM=F for forms mode in order to be prompted with keyword text, or use the correct keyword value. |

NAT1106: Value (length :2:) too long for input field (length :1:).

| Text | Value (length) too long for input field (length). |
|-------|---|
| | The data string entered for a field in delimiter mode is longer than the internal length definition of the field. |
| Actn. | Enter a data string of correct length. |

NAT1107: PROCESS PAGE (MODAL) not supported.

| Text | PROCESS PAGE (MODAL) not supported. |
|-------|---|
| | The execution of a PROCESS PAGE (MODAL) statement is only supported when Natural is running as a Rich GUI server. |
| Actn. | Purchase/install/configure the appropriate components. |

| Text | REINPUT statement not preceded by INPUT statement. |
|-------|---|
| Expl. | When a REINPUT statement is to be executed, the last communication |
| | with the screen must have been via an INPUT statement. |
| | REINPUT is not permitted for a screen that was produced by a WRITE |
| | or DISPLAY statement. |
| | Neither is REINPUT permitted for an INPUT statement inside a loop, |
| | subroutine or special condition block, when the loop, subroutine or |
| | special condition block has already been terminated. |
| | e.g.: REPEAT |
| | INPUT |
| | ESCAPE |
| | LOOP |
| | REINPUT will produce this error because at execution of the |
| | REINPUT statement the loop which contains the respective |
| | INPUT statement has already been closed. |
| Actn. | INPUT statement has already been closed. Check program and correct error. |

NAT1109: REINPUT cannot be executed in batch mode.

| Text | REINPUT cannot be executed in batch mode. |
|-------|--|
| | A program containing a REINPUT statement cannot be executed in batch mode. |
| Actn. | Do not execute REINPUT in batch mode. |

NAT1110: Restart after synchronizing OBJIN and SYNIN.

| Text | Restart after synchronizing OBJIN and SYNIN. |
|-------|---|
| Expl. | If an input error occurs, Natural must terminate the current program. The restart point is defined as the next "%%" (that is, the current terminal-control function value) in both OBJIN and SYNIN. After flushing input from both OBJIN and SYNIN until the next "%%", Natural resumes processing with the next command after "%%" in SYNIN and reads input data after the next "%%" in OBJIN. Note: The first "%" is the character indicating a terminal command. It may be any special character, as defined by the Natural administrator with the Natural session parameter CF or by the GLOBALS command or a SET GLOBALS statement. |
| Actn. | Check input data and correct error. |

NAT1111: Error in input data stream.

| Text | Error in input data stream. |
|-------|---|
| 1 1 | An invalid character was detected after the equal sign "=" in the input data stream. |
| Actn. | Check the usage of assign characters in the input data stream. |

NAT1112: No data entered for a mandatory input field.

| Text | No data entered for a mandatory input field. |
|-------|--|
| | Input fields can be defined with the option that an input value is required, in which case it must be supplied with the INPUT statement. |
| Actn. | Enter a valid value. |

NAT1113: Subroutine was not entered via PERFORM.

| Text | Subroutine was not entered via PERFORM. |
|-------|--|
| | The REINPUT statement refers to a previous INPUT statement that is located in a subroutine; or a RETRY statement refers to a database statement that is located in a subroutine. |
| Actn. | Check program and correct error. |

NAT1114: Internal output buffer overflow.

| Text | Internal output buffer overflow. |
|------|--|
| - | An overflow condition occurred during the writing of information to an output area. |
| | Reduce the program-defined page size and then re-run the program, or start the Natural session with an increased page size (PS). |

NAT1115: Invalid alphabetic value for SET GLOBALS statement.

| Text | Invalid alphabetic value for SET GLOBALS statement. |
|------|---|
|------|---|

| Expl. | Permitted values are: |
|-------|--|
| | CC ON/OFF CF any character |
| | DU ON/OFF DC any character |
| | EJ ON/OFF IA any character |
| | FS ON/OFF ID any character |
| | LE ON/OFF IM F/D |
| | RECAT ON/OFF PM C/I/N |
| | SA ON/OFF DFSTACK S/I/C |
| | WH ON/OFF DFOUT S/I |
| | ZD ON/OFF |
| | ZP ON/OFF |
| | Note: "T" and "F" are synonyms of "ON" and "OFF" respectively. |
| Actn. | Check program and correct error. |

NAT1116: Invalid numeric value for SET GLOBALS statement.

| Text | Invalid numeric value for SET GLOBALS statement. |
|-------|---|
| Expl. | Valid values are: |
| - | LS 0-250 |
| | LT 0-2147483647 but must not exceed default LT value supplied |
| | at session start. |
| | MT 0-maximum determined by operating environment. |
| | PD 0-255 |
| | PS 0-250 |
| | SF 1-30 |
| | SL 20-80 |
| Actn. | Check program and correct error. |

NAT1117: Requested map not available.

| Text | Requested map not available. |
|-------|---|
| | A map to be used in an INPUT USING MAP must exist in object form in the current library; however, the requested map was not found in the current library. |
| Actn. | Make sure you are using the correct library and the correct map name. |

NAT1118: Format/length conflict in loaded map.

| Text | Format/length conflict in loaded map. |
|------|---|
| | The fields specified in the INPUT USING MAP statement must agree in sequence, format and length with the fields defined in the map. |
| L | Check program and map and correct error. |

NAT1119: The loaded map is incompatible with the variable list.

| Text | The loaded map is incompatible with the variable list. |
|-------|--|
| | The fields in the INPUT USING MAP statement must agree in sequence and number with the fields defined in the map. However, the number of elements in the loaded map is not the same as in the supplied variable list. |
| Actn. | Check program and correct error. |

NAT1120: Positional parameter must not override pre-entered value.

| Text | Positional parameter must not override pre-entered value. |
|-------|--|
| Expl. | To a positional parameter entered in delimiter mode no more than one value may be assigned. For example: %1=VALUE1,VALUE2 -> will produce this error. VALUE1,%1=VALUE2 -> is a correct specification, as Natural allows specified positions or keys to override values entered in positional mode. |
| Actn. | Check input and correct error. |

NAT1121: Number in "%nnn" out of range.

| Text | Number in "%nnn" out of range. |
|-------|--|
| - | The field position requested by "%nnn" is not defined in the INPUT statement. The highest possible number is determined by the number of input fields defined. |
| Actn. | Enter valid number for input field. |

NAT1122: No "=" found after "%nnn".

| Text | No "=" found after "%nnn". |
|-------|---|
| | Natural treats "%nnn" as a keyword. A value must be specified after the assign character: %nnn=value. |
| Actn. | Use valid syntax construct for input value. |

NAT1123: Number in "%nnn" not numeric.

| Text | Number in "%nnn" not numeric. |
|-------|---|
| Actn. | Enter integer field number for field selection. |

NAT1124: End of file in input after continuation.

| Text | End of file in input after continuation. |
|-------|--|
| | A data concatenation was requested in the data stream for an INPUT statement, but no data were found in the next line. |
| Actn. | Enter data in continuation line. |

NAT1125: Too many significant digits in numeric input value.

| Text | Too many significant digits in numeric input value. |
|-------|---|
| Expl. | The integer part of a numeric input value contains more significant digits than defined in the variable definition. |
| Actn. | Enter valid input data. |

NAT1126: PROCESS PAGE UPDATE not preceded by PROCESS PAGE statement.

| Text | xt PROCESS PAGE UPDATE not preceded by PROCESS PAGE statement. | |
|--|--|--|
| Expl. | When a PROCESS PAGE UPDATE statement is to be executed, the last communication with an external rendering engine must have been via a PROCESS PAGE statement. No INPUT, WRITE, PRINT or DISPLAY statements may be executed between a PROCESS PAGE statement and its corresponding PROCESS PAGE UPDATE statement. It is not possible, however, to place a PROCESS PAGE statement within a loop, subroutine or special condition block, and then execute the PROCESS PAGE UPDATE statement when the status under which the PROCESS PAGE statement was executed has already been terminated. | |
| Actn. Check program and correct error. | | |

NAT1127: Error during assignment of floating point variable(s).

| Text 1 | ext Error during assignment of floating point variable(s). | |
|--------|---|--|
| | The most likely cause of this error is that one of the variables overflowed. Single-precision floating-point variables can only represent values of a precision of 7 digits or less. Double-precision floating-point variables may be used for approximately 19 digits. Extended precision must be used for values of 20 digits or more. | |

Actn. Check program and correct error.

NAT1128: Values for "DC", "IA", "ID" must exclude one another.

| Text | Values for "DC", "IA", "ID" must exclude one another. |
|-------|--|
| | A value for one of the parameters DC, IA or ID has been specified with a SET GLOBALS statement which is the same as the value for one of the other two parameters. |
| Actn. | Specify values for DC, IA, and ID which are different from one another. |

NAT1129: Physical terminal buffer overflow.

| Text | t Physical terminal buffer overflow. | |
|-------|---|--|
| - | The physical terminal buffer has overflowed during execution of an INPUT statement. As the execution of an INPUT statement implies immediate writing of the resulting map to the terminal, an overflow condition is regarded as an error. | |
| Actn. | Decrease the number of fields to be displayed; or ask your Natural administrator to increase, if possible, the size of the physical terminal buffer (in the TP-driver source). | |

NAT1130: Unintended century switch when stacking date string.

| Text | Unintended century switch when stacking date string. |
|-------|--|
| | DFSTACK=C has been specified, i.e. date strings are put on the stack without the century information (Natural V22 mode). When recovering this information (under control of a Sliding Window or the current century), an unintended century switch would occur: the year is not within the range of the sliding window or not in the current century. |
| Actn. | Correct error in program or specify DFSTACK=I. |

NAT1131: Screen input/output error.

| Text | Screen input/output error. |
|------------|---|
| 1 1 | The terminal driver has returned an error during a read/write operation to a terminal device. |
| Actn. | Ensure that the terminal device being used is supported by Natural. |

NAT1132: Line size mismatch in IOPATTR buffer at offset :1:.

| Text | Line size mismatch in IOPATTR buffer at offset |
|-------|--|
| Expl. | A mismatch between page buffer and page-attribute buffer has been detected. This error most probably occurs because not all lines of the page buffer have been generated with the same line size. |
| Actn. | Check your programs for FORMAT statements with different line sizes. |

NAT1133: Invalid terminal function requested.

| | | Invalid terminal function requested. |
|--|-------|--------------------------------------|
| | Actn. | Enter valid terminal function. |

NAT1134: Terminal function not supported.

| Text | Terminal function not supported. |
|------|--------------------------------------|
| Actn | Press ENTER to continue the session. |

NAT1135: Hardcopy function not supported.

| Text | Hardcopy function not supported. |
|-------|--|
| | The hardcopy (%H) function requires a spooling subsystem and a valid device address. These are not available for the active terminal/TP monitor. |
| Actn. | Contact your Natural administrator concerning hardcopy support. |

NAT1136: More than 250 lines in an output page.

| Text | More than 250 lines in an output page. |
|-------|--|
| | An output statement was executed which results in more than 250 lines in the current output page. The maximum value for the PS parameter is 250. |
| Actn. | Check program and correct error. |

NAT1137: Date is outside valid range.

| Text | Date is outside valid range. |
|-------|---|
| | A date or time field contains a value which does not represent a valid date. Possible reasons are: - The date value is less than 1582 or greater than 9999. - The date value is to be edited as Roman numerals, but the date value is greater than 2887. - The value is negative or not a valid packed number. |
| Actn. | Check program and correct error. |

NAT1138: SKIP value is invalid.

| Text | SKIP value is invalid. |
|-------|---|
| Expl. | A value greater than 250 must not be specified in a SKIP statement. |
| Actn. | Enter a valid value. |

NAT1139: Input for "mandatory full" field is not complete.

| Text | Input for "mandatory full" field is not complete. |
|-------|---|
| - | The value for a field that is defined as "mandatory full" must fill the field completely. |
| Actn. | Enter a valid value. |

NAT1140: Input is not a floating point number.

| Text | Input is not a floating point number. |
|-------|--|
| | The input entered was not a valid floating point number. A valid floating point number starts with an optional sign (+,-), followed by a mantissa with at most one decimal point and an optional exponent. The exponent has to start with the character "E", followed by an optional sign (+,-), followed by one or two decimal digits. |
| Actn. | Enter a valid number. |

NAT1141: Input results in floating point overflow.

| Text | Input results in floating point overflow. |
|-------|---|
| | A positive or negative floating point number was entered, which is too large for floating point processing. |
| Actn. | Enter a valid number. |

NAT1142: Input results in integer value overflow.

| | Text | Input results in integer value overflow. |
|---|-------|---|
| | | An integer value was entered which is too large to be processed as indicated in the program. |
| ſ | Actn. | Enter a valid integer value. |

NAT1143: Input does not correspond to input edit mask.

| Text | Input does not correspond to input edit mask. |
|-------|--|
| | Data were input which do not correspond to the input mask as defined within the program. |
| Actn. | Correct error. |

NAT1144: Data to be assigned/output do not correspond to edit mask.

| Text | Data to be assigned/output do not correspond to edit mask. |
|-------|--|
| | One of the following errors occurred: - A MOVE EDITED statement was issued with a target edit mask, and the source data do not correspond to the target edit mask. - A DISPLAY/INPUT/PRINT/WRITE statement was issued with an edit mask, and the source data do not correspond to the specified edit mask. |
| Actn. | Check program and correct error. |

NAT1145: Input does not match edit mask :1:.

| Text | Input does not match edit mask |
|-------|---|
| | The data value entered for an input field does not correspond to the edit mask assigned to the field. |
| Actn. | Enter a value which is suitable for the edit mask displayed. |

NAT1147: Illegal use of DISPLAY GIVING SYSTEM FUNCTIONS.

| Text | Illegal use of DISPLAY GIVING SYSTEM FUNCTIONS. |
|-------|--|
| - | Only one DISPLAY GIVING SYSTEM FUNCTIONS may be used per report. This applies also to external routines such as CALLNATS, external subroutines, etc. |
| Actn. | Check program and called routines and remove duplicate DISPLAY GIVING SYSTEM FUNCTIONS. |

NAT1148: No help available for this data field.

| Text | No help available for this data field. |
|-------|---|
| | The help key was pressed or the help character was entered for a field for which no error text or error routine has been defined. |
| Actn. | Ask your Natural administrator for assistance. |

NAT1149: Requested message is not available.

| Text | Requested message is not available. |
|-------|---|
| | A user-defined message, which was requested by a REINPUT statement, is not contained in the database. |
| Actn. | Contact your Natural administrator. |

NAT1150: Attribute buffer overflow.

| Text | Attribute buffer overflow. |
|-------|--|
| | An overflow of the attribute buffer is caused by too many attributes for one logical page. |
| Actn. | Reduce the number of fields on one page. |

24 Natural System Error Messages 1151-1200

NAT1151: Invalid access to Natural system function.

| Text | Invalid access to Natural system function. |
|-------|---|
| - | An invalid access to a Natural system function was attempted. For example, an attempt was made to assign a value to a read-only function. |
| Actn. | Check program and correct error. |

NAT1152: Invalid function in screen paging.

| Text | Invalid function in screen paging. |
|-------|---|
| Expl. | An invalid function code was entered during screen-page processing. |
| Actn. | Enter a valid function code. |

NAT1153: Requested screen pages are not available.

| Text | Requested screen pages are not available. |
|-------|--|
| - | Screen pages were requested during screen paging, but these pages are not available. |
| Actn. | Correct error. |

NAT1155: Reporting mode not permitted.

| Text | Reporting mode not permitted. |
|-------|--|
| | Switching to reporting mode is not permitted if Natural was started with structured mode (parameter SM=ON). Switching to reporting mode can be done via the GLOBALS command. |
| Actn. | Make sure you are using the correct programming mode. |

NAT1156: Statement not possible within TOP OF PAGE or END OF PAGE.

| Text | Statement not possible within TOP OF PAGE or END OF PAGE. |
|-------|---|
| | The specified statement must not be specified within an AT TOP OF PAGE or AT END OF PAGE statement block. |
| Actn. | Correct error in program. |

NAT1157: Invalid format of operand.

| Text | Invalid format of operand. |
|-------|---|
| Expl. | During runtime, the format of an operand is not contained in the list of valid formats. |
| Actn. | Contact SAG support. |

NAT1160: Error in "Recording" activation.

| Text | Error in "Recording" activation. |
|-------|---|
| | This error is caused by one of the following: The requested recording has not been found. You have specified no recording name. For a new recording, you have specified the name of an already existing recording. |
| Actn. | Make sure you use the right recording name in the right library. |

NAT1161: DBCS: Invalid SO/SI pair in line :1: column :2:.

| Text | DBCS: Invalid SO/SI pair in line column |
|-------|---|
| | Natural checks the correct pairing of SO/SI for DBCS (double-byte character set) terminals. |
| Actn. | Check program logic and generate correct SO/SI pairs. |

| Text | Invalid character or shift character in DBCS-only field. |
|-------|---|
| Expl. | A DBCS-only field is an alphanumeric field for which the session parameter PM=D is set. It must contain only valid DBCS characters; shift-out/shift-in characters (SO/SI) are not allowed within such a field. If either - a shift-out/shift-in character (SO/SI) or - a character code that is not a valid DBCS character is detected, this error is issued. Shift-out/shift-in characters (SO/SI) are always detected. Because the detection of non-DBCS characters requires ICU, it will not be performed if ICU is not available (that is, if the profile parameter CFICU=OFF has been set). |
| Actn. | Correct the content of the DBCS-only field. |

NAT1162: Invalid character or shift character in DBCS-only field.

NAT1165: The WINDOW statements are no longer consistent.

| Text | The WINDOW statements are no longer consistent. |
|-------|---|
| | Natural tried to execute the internal reference to the DEFINE WINDOW statement during the execution of an INPUT WINDOW=window-name or SET WINDOW window-name. The reference is not the correct statement anymore. Probably the generated program has been destroyed. |
| Actn. | Clear the buffer pool and restart Natural. Recatalog the program. |

NAT1166: Invalid window width specified in SIZE clause.

| Text | Invalid window width specified in SIZE clause. |
|-------|--|
| Expl. | The value for the number of columns in the SIZE clause of the DEFINE WINDOW statement is outside the valid range. The minimum number of columns if the FRAME clause is used is 13. The minimum number of columns if the FRAME clause is not used is 10. The maximum number of columns is the physical screen size. |
| Actn. | Correct program. |

NAT1167: Invalid window length specified in SIZE clause.

| Text | Invalid window length specified in SIZE clause. |
|-------|--|
| | The value for the number of lines in the SIZE clause of the DEFINE WINDOW statement is outside the valid range. The minimum number of lines if the FRAME clause is used is 4. The minimum number of lines if the FRAME clause is not used is 2. The maximum number of lines is the physical screen size. |
| Actn. | Correct program. |

NAT1168: Invalid window start line (:1:).

| Text | Invalid window start line (). |
|-------|---|
| | The current size of the window inhibits the position of the window at the specified line in the screen. |
| Actn. | Reduce the size of the window, or use a smaller line value. |

NAT1169: Invalid window start column (:1:).

| Text | Invalid window start column (). |
|-------|---|
| | The current window size is too large to start the window at the specified column on the screen. |
| Actn. | Reduce the window size, or use a smaller column value. |

NAT1170: PC access method not available.

| Text | PC access method not available. |
|-------|--|
| | Natural checks to see if the terminal command "%+" is valid in the current environment. The PC access method is not linked to the Natural nucleus. |
| Actn. | Do not use "%+", or contact your Natural administrator. |

NAT1171: The required terminal converter module is missing.

| Text | The required terminal converter module is missing. |
|-------|---|
| Expl. | This error occurs if the terminal command "%T=nnnn" has been entered, |
| | but the specified terminal type is not defined by the macro NTDVCE in |
| | source module NATCONFG, or the required converter module NATnnnn has |
| | not been linked to the Natural nucleus. |
| | This error also occurs if the terminal command "%+" has been entered |
| | from a PC running in ASYNCH (TTY) mode to activate Natural Connection |
| | full-screen support, but the required module NATTTY has not been linked |
| | to the Natural nucleus. |

| Actn. | Specify a correct terminal type, or link the required terminal |
|-------|--|
| | converter module to the Natural nucleus. |

NAT1172: PC connection already active.

| Text | PC connection already active. |
|-------|---|
| Expl. | The terminal command "%+" has been entered, but PC connection was already active. |
| Actn. | No action required. |

NAT1173: PC connection not active.

| Text | PC connection not active. |
|-------|--|
| | The terminal command "%-" has been entered, but the PC connection was not active or had already been de-activated. |
| Actn. | No action required. |

NAT1174: Not in lower case for upload.

| Text | Not in lower case for upload. |
|-------|--|
| · · | For uploads, Natural has to be in lower case to be able to compute the right check sum and to upload binary data. |
| Actn. | Set lower case on and try again. |

NAT1175: Upload aborted due to check sum errors.

| Text | Upload aborted due to check sum errors. |
|-------|---|
| Expl. | The sent check sum is different from the one computed by Natural. |
| Actn. | Try upload again later. |

NAT1176: Terminal type :1: cannot be used in this environment.

| Text | Terminal type cannot be used in this environment. |
|-------|---|
| Expl. | The terminal type specified by the TTYPE profile parameter or by the terminal command %T= cannot be used in this environment. For example, an online terminal type cannot be used in a batch environment. The terminal type specified by the terminal command %T= or in a SET CONTROL "T=" statement does not support MBCS code pages. |
| Actn. | Specify a correct terminal type for this environment. |

NAT1177: Unsupported format type found.

| Text | Unsupported format type found. |
|-------|--|
| Expl. | Supported format types for the old PC access method are alphanumeric and numeric. Supported format types for the new PC access method are: - alphanumeric - numeric - packed - logical - floating point - integer - binary. |
| Actn. | Correct your program and retry. |

NAT1178: Uploaded data are not a DDM or Natural 2 source/object.

| Text | Uploaded data are not a DDM or Natural 2 source/object. |
|-------|---|
| | The data used when uploading a DDM or a source binary or an object are not of the appropriate type. The used file on the PC does not hold a binary downloaded DDM or source or object. |
| Actn. | Use an appropriate file and retry. |

NAT1179: Used work file number not assigned to PC or PCNEW.

| Text | Used work file number not assigned to PC or PCNEW. |
|-------|---|
| | The work file number used in the subprogram for the current up-/download is either not assigned to PCNEW if up/downloading binary or not assigned to PC or PCNEW if up-/downloading as source. Use SYSFILE to check which work files are assigned to PC and PCNEW. |
| Actn. | Use correct work file number and retry. |

NAT1180: Invalid type entered for "Upload from PC".

| Text | Invalid type entered for "Upload from PC". |
|-------|--|
| Expl. | Valid types for "Upload from PC" are: P, N, S, H, C, K, T, M, 4. |
| Actn. | Use appropriate type. |

NAT1181: Source or object for download does not exist.

| Text | Source or object for download does not exist. |
|-------|--|
| Expl. | An attempt was made to download a non-existing source or object. |
| Actn. | Check the name and the library of the source or object you want to download and retry. |

NAT1182: Source to download is of invalid type.

| Text | Source to download is of invalid type. |
|-------|--|
| | An attempt was made to download a data area as source. Sources of data areas can only be downloaded binary. |
| Actn. | Download source of data area binary. |

NAT1183: Specified work file cannot be used for COMMAND download.

| Text | Specified work file cannot be used for COMMAND download. |
|-------|--|
| | The specified work file cannot be used for a WRITE/DOWNLOAD PC/WORK 5 COMMAND statement, for one of the following reasons: - The work file is not defined for the new PC access method. - The work file is already being used. |
| Actn. | Define the work file correctly, or use a different work file. |

NAT1184: Downloaded command rejected by PC.

| Text | Downloaded command rejected by PC. |
|-------|---|
| | The command that was downloaded has been rejected by the PC, because the command is not valid. See the Natural Connection documentation for information on which commands can be downloaded. |
| Actn. | Correct program and retry download. |

NAT1185: Catalog the object before you download/upload it.

| Text | Catalog the object before you download/upload it. |
|-------|---|
| Expl. | The object contains an error or inconsistency which prevents its being downloaded/uploaded. |
| Actn. | Catalog the object to be downloaded/uploaded; then try again to download/upload it. |

NAT1186: Buffer overflow due to too many or too long field names.

| Text | Buffer overflow due to too many or too long field names. |
|-------|--|
| Expl. | While downloading/uploading data with field names, a buffer overflow has occurred. The reason that the field names do not fit into the corresponding buffer, either because too many fields are sent or because the field names are too long. |
| | Upload/download the data without field names (see PC profile parameter), or reduce the number of fields to be uploaded/downloaded. |

NAT1187: GETMAIN for PC Connection work area failed.

| Text | GETMAIN for PC Connection work area failed. |
|-------|--|
| - | During upload or download processing the transferred data are stored intermediately in the PC Connection work area. An increase of this buffer failed. |
| Actn. | Contact your database administrator. |

NAT1188: Maximum record length (32 KB) for PC file access exceeded.

| Text | Maximum record length (32 KB) for PC file access exceeded. |
|-------|---|
| Expl. | The maximum allowed record length for an access to a PC file is 32 KB. |
| | Reduce the number or size of the operands in the appropriate READ/WRITE WORK FILE statement. |

NAT1190: Type "unformatted" is not supported for PC work files.

| Text | Type "unformatted" is not supported for PC work files. |
|-------|--|
| - | Unformatted file transfer between PC and mainframe is currently not supported. |
| Actn. | Use a different type of file transfer. |

NAT1200: I/O error during external sort.

| Text | I/O error during external sort. |
|-------|--|
| | The system sort program to be used for the external sort function could not be found in any of the libraries defined to the Natural program as load libraries. |
| Actn. | Check if SORTNAM in NATPARM or dynamic parameters contain a valid sort-program name and that the load library available to Natural contains that module. |

25 Natural System Error Messages 1201-1250

NAT1201: External sort control fields total exceeds 256 bytes.

| Text | External sort control fields total exceeds 256 bytes. |
|-------|--|
| Expl. | The external sort used via the SORT statement supports a maximum of 256 bytes for the sort fields. |
| Actn. | Reduce the number or length of sort fields specified in the SORT statement. |

NAT1202: Error in external sort; core/disk space insufficient.

| Text | Error in external sort; core/disk space insufficient. |
|-------|--|
| Expl. | For the external sort function, either a system sort program is invoked (in batch mode) or an incore sort is invoked (in online mode). In batch mode, the reason for the error message is either insufficient disk space or a missing DD card. In online mode, the reason for the message is insufficient memory in the file buffer which is used for intermediate storage in the sort process. |
| Actn. | Contact your Natural administrator. |

NAT1205: No more sort work space.

| Text | No more sort work space. |
|-------|---|
| Expl. | There is no more space in the core; or the work files cannot be accessed, are full, or cannot be supported; or the record size is greater than the maximum buffer size. |
| Actn. | Decrease the number of records to be sorted, or the number of fields per sort record; or enlarge the incore sort work area or sort work files (if present). |

NAT1212: Internal error - no more space in quicksort work area.

| Text | Internal error - no more space in quicksort work area. |] |
|-------|--|---|
| Actn. | Contact your Natural administrator. | 1 |

NAT1214: SORT/NTSORT option STORAGE=SD only allowed under Com-plete.

| Text | SORT/NTSORT option STORAGE=SD only allowed under Com-plete. |
|-------|--|
| | The SORT/NTSORT option STORAGE=SD can only be used for the Natural |
| | internal sort if the Natural session is running under Com-plete. |
| Actn. | Use STORAGE=MAIN or STORAGE=BP. |

NAT1220: Multiple active SORTs are not allowed.

| Text | Multiple active SORTs are not allowed. |
|-------|---|
| | No more than one SORT loop may be active at a time. This error occurs if within an active processing loop initiated with a SORT statement another program, subprogram or subroutine is invoked, and within this invoked object another SORT statement is executed. |
| Actn. | Correct error in application. |

NAT1222: Memory required for statement execution not available.

| Expl. | The memory required to execute the statement is not available. |
|-------|--|
| | Possible reasons are: |
| | - The amount of memory allocated to a dynamic variable or an X-array had |
| | to be increased, but this caused the total memory available to the |
| | Natural session to be exceeded. |
| | - The amount of work memory required to execute the statement caused |
| | the total memory available to the Natural session to be exceeded. |
| | - Natural environment constraints (e.g. the settings of profile |
| | parameters) limit the total amount of memory available to the Natural |
| | session. |
| | - Operating or TP system restrictions (e.g. the total memory available) |
| | limit the amount of memory that is available to the Natural session. |
| Actn. | Use the system command LASTMSG * to find out what exactly caused the |
| | memory request to fail. |
| | Check program and correct error, or contact your Natural administrator. |

NAT1223: A numeric field contains a non-numeric digit.

| Text | A numeric field contains a non-numeric digit. |
|-------|--|
| Expl. | At least one of the digits in a numeric field is not a numeric digit and cannot be processed in a numeric context. |
| | Check if the numeric field in question is redefined as alphanumeric or binary. If so, make sure it contains only numeric digits. Otherwise, input data (from the database) could be erroneous. |

26 Natural System Error Messages 1251-1300

NAT1254: Invalid size value for REDUCE/EXPAND/RESIZE: :1:.

| Text | Invalid size value for REDUCE/EXPAND/RESIZE: |
|-------|---|
| Expl. | A size value is specified with the REDUCE/EXPAND/RESIZE statement, in order to reallocate the memory for the given dynamic operand. The following conditions must be kept for the size value: 1. The size value must not be negative. 2. The size value must not exceed 1 gigabyte. The size value which caused the error is shown in the error message. |
| Actn. | Make sure the size value meets the conditions mentioned above. |

NAT1255: Invalid value in ARRAY clause for REDUCE/EXPAND/RESIZE: :1:.

| Text | Invalid value in ARRAY clause for REDUCE/EXPAND/RESIZE: |
|-------|--|
| Expl. | The ARRAY clause of the REDUCE/EXPAND/RESIZE statement is provided in |
| | order to allow the number of occurrences of an X-array to be adjusted. |
| | The lower and upper bound values specified with the bound notation, or |
| | the number of occurrences specified with the occurrence notation, must |
| | meet the following conditions: |
| | 1. The fixed bound value must not be changed. |
| | 2. The number of occurrences must not be negative. |
| | 3. The number of occurrences must not exceed 1073741824. |
| | The value which caused the error is shown in the error message. |
| Actn. | Make sure the value meet the conditions above. |

NAT1256: Value of system variable :1: is undefined.

| Text | Value of system variable is undefined. |
|------|---|
| | A Natural statement references a system variable in order to get its value. The value of the system variable is currently undefined, due to the following reason: 1. The value of the system variable *UBOUND or *LBOUND is undefined if the corresponding X-array is not materialized (i.e. occurrences are not allocated). The system variable which caused the error is shown in the error message. |
| 1 | Allocate occurrences of the corresponding X-array with the REDUCE/EXPAND/RESIZE statement before referencing *UBOUND or *LBOUND. |

NAT1257: Access to a non-materialized X-array field not permitted.

| Text | Access to a non-materialized X-array field not permitted. |
|-------|--|
| | An X-array is an array field with an alterable number of occurrences. At runtime, an X-array is empty by default. It does not have any accessible occurrences, unless they were allocated before with an explicit EXPAND ARRAY statement. |
| Actn. | Allocate X-array occurrences with EXPAND ARRAY statement. |

NAT1300: Negative exponent not allowed.

| Text | Negative exponent not allowed. |
|-------|--|
| | Natural performs an exponentiation via repetitive multiplication. Negative exponents are not permitted. |
| Actn. | Use only positive exponent values. |

27 Natural System Error Messages 1301-1350

NAT1301: Intermediate result too large.

| Text | Intermediate result too large. |
|-------|---|
| Expl. | The construct of the arithmetic expression generates an intermediate result with too many digits. |
| Actn. | Separate the arithmetic expression into several statements with defined lengths for intermediate results. |

NAT1302: Division by zero not permitted by parameter ZD=ON.

| Text | Division by zero not permitted by parameter ZD=ON. |
|-------|---|
| Expl. | The ZD session parameter is set to "ON". This causes |
| | an error when a division by zero is attempted. |
| | If a result of zero is desired when attempting a division |
| | by zero, change the setting of the ZD session parameter to "OFF". |
| Actn. | Set "ZD=OFF" if desired. |

NAT1303: Numeric truncation caused by adding/subtracting 1.

| Text | Numeric truncation caused by adding/subtracting 1. |
|-------|---|
| | In the evaluation of a relational expression, the operators GREATER and LESS THAN are evaluated by adding/subtracting "1" from the value. |
| Actn. | Increase length of field used in relational expression. |

NAT1304: Value has been rounded and does not fit into field.

| Text | Value has been rounded and does not fit into field. |
|-------|---|
| Expl. | Rounding has caused the value to exceed the number of digits defined for the field. |
| Actn. | Increase length of field being rounded. |

NAT1305: Numeric value truncated in MOVE/ASSIGN operation.

| Text | Numeric value truncated in MOVE/ASSIGN operation. |
|-------|--|
| | The receiving field in a MOVE/ASSIGN operation is not long enough to hold the result of the value. |
| Actn. | Increase the length of the receiving field. |

NAT1306: Error in STEP value in FOR statement.

| Text | Error in STEP value in FOR statement. |
|-------|--|
| · · | The end value cannot be reached by incrementing the start value because STEP value = 0 was detected. |
| Actn. | Check program and correct error. |

NAT1307: Resulting element address in MOVE INDEXED out of range.

| Text | Resulting element address in MOVE INDEXED out of range. |
|-------|--|
| | The target address of the MOVE INDEXED operation lies outside the Natural data area. |
| Actn. | Check index value or length of base field in MOVE INDEXED. |

NAT1308: Replace string does not fit into variable.

| Text | Replace string does not fit into variable. |
|-------|---|
| Expl. | In an EXAMINE statement, one of the strings to be examined and replaced resulted in a total string length that is larger than the variable length. A truncation of a value is not allowed in an EXAMINE statement. |
| Actn. | Adjust length of field in EXAMINE statement. |

NAT1309: Overflow in NUMBER variable of EXAMINE statement.

| Text | Overflow in NUMBER variable of EXAMINE statement. |
|-------|---|
| | The number of strings found in the source variable is too large to be represented in the NUMBER variable of the EXAMINE statement. |
| Actn. | Adjust the length of the NUMBER variable. |

NAT1310: RETRY statement not allowed for this error number.

| Text | RETRY statement not allowed for this error number. |
|-------|--|
| Expl. | 1. A RETRY is only possible for database response code "145". This |
| | response code indicates that a record which is to be read for update is |
| | currently in "hold" status for another user. NAT3145 can only occur when |
| | the global option WH=OFF (wait hold) is in effect. |
| | 2. NAT1310 can also occur under one of the following conditions if the |
| | response code is in fact "145": |
| | - The object module which was active when "145" was received does not |
| | contain an ON ERROR statement. |
| | - The RETRY statement executed in reaction to "145" is not contained in |
| | the same object module as was active when the response code was |
| | received. |
| | Response code "145" can only be handled by the object module which is |
| | active when the response code is received. When control is returned from |
| | that module, Natural automatically converts NAT3145 to NAT1310. |
| Actn. | that module, Natural automatically converts NAT3145 to NAT1310. Check program and correct error. |

NAT1311: Index in MOVE INDEXED statement is zero or negative.

| Text | Index in MOVE INDEXED statement is zero or negative. |
|-------|---|
| Expl. | The index in a MOVE INDEXED statement must be positive. |
| Actn. | Correct program. |

NAT1312: Number of elements too large for number field.

| Text | Number of elements too large for number field. |
|-------|--|
| | The NUMBER clause was used in the SEPARATE statement, but the number of elements to be returned does not fit into the field specified. |
| Actn. | Increase the length of the field which is to contain the resulting number of elements. |

NAT1313: Not enough receiving fields available in SEPARATE.

| Text | Not enough receiving fields available in SEPARATE. |
|-------|---|
| | The source field contained so many delimiter characters that there were not enough target fields available in the SEPARATE statement to receive all values. |
| Actn. | Check program and correct error. |

NAT1314: Target field too small for field portion.

| Text | Target field too small for field portion. |
|-------|--|
| - | In a SEPARATE statement, a portion of a field to be transferred is larger than the target field specified. |
| Actn. | Increase the length of the target field. |

NAT1315: Source field and target field in SEPARATE overlap.

| Text | Source field and target field in SEPARATE overlap. |
|-------|--|
| Actn. | Avoid overlapping of source and target fields. |

NAT1316: Index not within array structure.

| Text | Index not within array structure. |
|-------|--|
| | The index specified for an array is not within the dimensions defined for the array. |
| Actn. | Check program and correct error. |

NAT1317: Array range operation on invalid ranges.

| Text | Array range operation on invalid ranges. |
|-------|---|
| | An arithmetic operation may operate on array ranges with identical range structures, or on array ranges with single values (scalar values). Two or three ranges were defined for an arithmetic operation, which do not have identical range structures. |
| Actn. | Check program and correct error. |

NAT1318: Overlap during ASSIGN.

| Text | Overlap during ASSIGN. |
|-------|--|
| | During assignment of alphanumeric or binary operands, an invalid overlap was detected. This condition occurs when an attempt is made to move a byte which has already been moved during the execution of the statement. |
| Actn. | Check program and correct error. |

NAT1319: Invalid date operation.

| Text | Invalid date operation. |
|-------|---|
| Expl. | The result of an operation (date integer) is a negative date. |
| Actn. | Check program and correct error. |

NAT1320: Invalid operand for system function VAL.

| Text | Invalid operand for system function VAL. |
|-------|---|
| Expl. | The operand of the VAL system function does not contain a valid alphanumeric representation of the resulting value. The VAL system function is similar to the INPUT statement: what is accepted by the INPUT statement is also accepted by the VAL system function. |
| Actn. | Check program and correct error. |

NAT1321: Invalid UNTIL parameter in MOVE ALL statement.

| Text | Invalid UNTIL parameter in MOVE ALL statement. |
|-------|--|
| | This error may be caused by one of the following: The UNTIL parameter contains a negative value. The UNTIL parameter contains a value with more than 7 valid decimal digits or more than 31 valid binary digits. |
| Actn. | Correct error. |

NAT1322: Parameter :1: missing (invoked at line :2: by :3:/:4:/:5:/:6:).

| Text | Parameter missing (invoked at line by//). |
|-------|--|
| Expl. | Natural tried to execute a statement which contained a reference to parameter which was not supplied by the object// This occurs if the invoking statement at line has not supplied a parameter which was defined as optional by the invoked object (DEFINE DATA PARAMETER). |
| Actn. | Specify the missing parameter in the invoking statement. |

NAT1323: ACCEPT, REJECT, REINPUT not allowed in end-data condition.

| Text | ACCEPT, REJECT, REINPUT not allowed in end-data condition. |
|-------|--|
| Expl. | The statements ACCEPT and REJECT are not allowed in an end-of-data condition (loop is already closed). The same restriction applies for a REINPUT statement if the corresponding INPUT statement is contained within a loop which has been closed. |
| Actn. | Check program and correct error. |

NAT1324: Loop must be active if this statement is used.

| Text | Loop must be active if this statement is used. |
|-------|--|
| Expl. | An ESCAPE TOP, ESCAPE BOTTOM, ACCEPT, REJECT or PERFORM BREAK PROCESSING |
| | statement cannot be executed, because |
| | - no loop is active for an ESCAPE TOP, ESCAPE BOTTOM or |
| | PERFORM BREAK PROCESSING statement; |
| | - no FIND, READ, HISTOGRAM, CALL FILE, SORT or READ WORK FILE loop is |
| | active for an ACCEPT or REJECT statement. |
| Actn. | Check program and correct error. |

NAT1325: Too many asterisks "*" found in pattern.

| Text | Too many asterisks "*" found in pattern. |
|-------|---|
| | A maximum of 10 asterisks "*" may be supplied in a pattern. If more "*" are found in the pattern, a table overflow occurs and therefore the execution is stopped. However, "**" is recognized as "*". |
| Actn. | Decrease the number of asterisks "*" in the pattern. |

NAT1326: Range specified with FROM/LENGTH clause is outside field.

| Text | Range specified with FROM/LENGTH clause is outside field. |
|-------|---|
| | Error in FROM/LENGTH clause of EXAMINE or SEPARATE statement: - The FROM position is not within the field; or - the specified LENGTH exceeds the length of the field; or - the LENGTH value is negative. |
| Actn. | Check program and correct error. |

NAT1328: No default code page available.

| Text | No default code page available. |
|-------|--|
| - | The execution of the current statement requires that a default code page is defined. |
| Actn. | Define a default code page, using the CP parameter. |

28

Natural System Error Messages 1351-1400

NAT1392: PCHECK=ON validation has found :1: inconsistencies.

| Text | PCHECK=ON validation has found inconsistencies. |
|-------|---|
| Expl. | During the PCHECK=ON validation more than one inconsistency was found. |
| | This message is displayed to indicate that several parts of the Natural |
| | object need to be inspected. The original messages related to the |
| | actual errors can be displayed with the system command LASTMSG. |
| | For example, program MAIN contains: |
| | PERFORM SUBR1 at line 100 with an inconsistent parameter list. |
| | CALLNAT "CLN1" at line 200 with an inconsistent parameter list. |
| | The initial error messages would be: |
| | MAIN 0100 NAT0936 Format/length conflict in parameter 1 (Subroutine |
| | MAIN 0200 NAT0936 Format/length conflict in parameter 1 (Subprogram |
| | In addition, the following message would be displayed: |
| | MAIN 0200 NAT1392 PCHECK=ON validation has found 2 inconsistencies. |
| Actn. | MAIN 0200 NAT1392 PCHECK=ON validation has found 2 inconsistencies. Check program and |
| | correct error. |

NAT1393: Object :1: (:2:/:3:/:4:) cataloged with unsupported version.

| Text | Object (/) cataloged with unsupported version. |
|-------|--|
| Expl. | An attempt was made to execute a Natural programming object or load a GDA, LDA, PDA or map at compilation which is not supported by the current version of Natural. For a list of supported Natural versions, see the Natural documentation. |
| Actn. | Re-compile the object under the current version of Natural. |

NAT1395: Reporting mode of object :1: (:2:/:3:/:4:) not permitted.

| Text | Reporting mode of object :1: (:2:/:3:/:4:) not permitted. |
|-------|---|
| Expl. | Switch to reporting mode by object :1: loaded from library :2: |
| | (database :3:/file :4:) is not permitted. |
| | Switching to reporting mode is not permitted if Natural was started |
| | with structured mode (parameter SM=ON). |
| | When a Natural source program is read into the source area, Natural |
| | automatically switches to the mode in which the program was stored. |
| | The program can be edited, but before a STOW command can be executed, |
| | you have to ensure that the program structure is in accordance with |
| | the appropriate programming mode. |
| Actn. | Make sure you are using the correct programming mode. |

NAT1396: In the meantime :1: :2: was saved unmodified by user :3:.

| Text | In the meantime :1: :2: was saved unmodified by user :3:. |
|-------|--|
| | It is not possible to save object :2: of type :1:, because it was saved - although not modified - in the meantime by user :3:. |
| Actn. | Delete the source and save it again. |

NAT1397: In the meantime :1: :2: was modified and saved by :3:.

| Text | In the meantime :1: :2: was modified and saved by :3:. |
|-------|---|
| | It is not possible to save object :2: of type :1:, because it was modified and saved in the meantime by user :3:. |
| Actn. | Delete the source and save it again. |

NAT1398: :1: :2: is locked for :3:.

| Text | :1: :2: is locked for :3:. |
|-------|--|
| | It is not possible to save object :2: of type :1:, because it is currently locked for a different purpose denoted as :3:. |
| Actn. | Unlock the object before saving it. |

NAT1399: :1: :2: is locked by user :3: (session ID :4:).

| Text | :1: :2: is locked by user :3: (session ID :4:). |
|-------|--|
| Expl. | It is not possible to save object :2: of type :1:, because it is currently locked by user :3: in session :4:. |
| | The user who locked the object, or an authorized administrator, has to unlock the object. |

NAT1400: Overflow for total/sum in Natural system function.

| Text | Overflow for total/sum in Natural system function. |
|-------|---|
| Expl. | The value that resulted from the addition of values from all processed records caused an overflow of the value for a Natural system function. The number of positions for a Natural system function is derived from the length of the argument field. |
| Actn. | Increase the length of the argument field. |

29 Natural System Error Messages 1451-1500

NAT1500: Open for work file :1: failed.

| Text | Open for work file failed. Possible reasons: - The file does not exist (READ WORK). |
|-------|---|
| Expl. | An existing file cannot be accessed because the user does not have access (read/write) privileges for the file. The file cannot be created because the user does not have privileges to write to the directory (WRITE WORK). The file cannot be created because either the file system is full or the list of files of the file system is full (inodes list). The user does not have privileges to access one of the directories in the path leading to the file. One of the directories in the path leading to the file does not exist. There is a network error, the file server, the name server, etc. does not respond or is not active. Entire Connection data transfer not implemented in Natural for Windows Several operating-system specific reasons. See your operating-system documentation for more information. |
| Actn. | documentation for more information While trying to write to an Entire Connection file (.NCD file), the maximum field length of 255 was exceeded. Contact your Natural administrator. |

30

Natural System Error Messages 1501-1550

NAT1501: Insufficient control information for :1: file :2:.

| Text | Insufficient control information for file |
|-------|---|
| Expl. | Either there is insufficient DCB for a READ statement, or a RECFM=F parameter has been specified for a variable WRITE operation. A possible reason is an incompatible DCB specification in job control. |
| Actn. | Ensure that the referenced work file has previously been used as an output file. If the file is unlabelled, ensure that the characteristics of the files agree with previous WRITE. |

NAT1502: Permanent physical I/O error.

| Text | Permanent physical I/O error. |
|-------|---|
| 1 1 | The work file cannot be processed because of permanent I/O errors. Possible reason is a physical damage to the file. |
| Actn. | Contact your Natural administrator. |

NAT1503: Work file :1: closed within READ WORK FILE loop.

| Text | Work file closed within READ WORK FILE loop. |
|-------|--|
| Expl. | Within a READ WORK FILE processing loop, another Natural program or subprogram has caused the closing of the work file, either by an explicit CLOSE WORKFILE statement or implicitly due to an end-of-file condition during a READ WORK FILE processing loop. If the work file has been closed, an open READ WORK FILE loop for the work file must be exited with an ESCAPE BOTTOM statement. |
| Actn. | Correct error. |

NAT1504: READ end-of-file reached but no AT END processing coded.

| Text | READ end-of-file reached but no AT END processing coded. |
|-------|--|
| | The READ WORK FILE ONCE option was specified and the file has reached the end-of-file condition. This condition should be checked with an AT END OF FILE clause. |
| Actn. | Correct program. |

NAT1505: Invalid data for numeric input field.

| Text | Invalid data for numeric input field. |
|-------|--|
| | The READ WORK FILE SELECT option checks all data fields for valid input data. A non-numeric value was found in a field defined as numeric. |
| Actn. | Check program and correct error. |

NAT1506: Packed numeric value and variable definition do not match.

| Text | Packed numeric value and variable definition do not match. |
|-------|--|
| Expl. | A READ WORK FILE statement without the RECORD option is attempting to read a packed variable that is defined with an even number of digits (e.g. P6, P5.1). However, the numeric data in the work file does not fit into the variable, but would require an odd number of digits where the number of digits is one more than the current definition. A possible reason is that the data has been written to the work file using another variable definition or using redefinitions. |
| Actn. | Increase the number of digits in the variable definition by one so that the number of digits is odd, or check the application that wrote the data to the work file. |

NAT1507: The output work file :1: is full.

| Text | The output work file is full. |
|-------|---|
| | The space allocated for an output work file is not large enough to hold all the records written by the Natural program. |
| Actn. | Ask your Natural administrator to increase the size of the output work file. |

NAT1508: The :1: file :2: is already open for another user.

| Text | The file is already open for another user. |
|-------|---|
| | The print or work file is being used by another user and cannot be shared by users. |
| Actn. | Check concurrent programs to ensure that they are not using the same file. |

NAT1510: Record too small for :1: file :2:.

| Text | Record too small for file |
|-------|---|
| Expl. | For z/VSE systems, this message indicates that the WLRERR exit was entered for a reader using DTFDI or a work file using DTFMT or DTFSD. For z/OS systems, this message indicates that for RECFM=F the record is shorter than the dataset record length and padding by blanks (print files) or nulls (work files) is not allowed. Record padding is controlled by the subparameter PAD of the PRINT or WORK parameter. |
| Actn. | Contact your Natural administrator to ensure that the Natural JCL has been specified correctly. For z/OS systems, start the session with subparameter PAD=ON to allow record padding or correct your application. |

NAT1511: WRITE WORK FILE issued after READ WORK FILE.

| Text | WRITE WORK FILE issued after READ WORK FILE. |
|-------|--|
| Expl. | A work file can be created within a Natural program and subsequently read within it, but not vice versa. If a work file has been opened as a result of executing a READ WORK FILE statement, the execution of a WRITE WORK FILE statement will generate a runtime error. |
| Actn. | Check program and correct error. |

NAT1512: Record too large for :1: file :2:.

| Text | Record too large for file |
|-------|--|
| Expl. | The length of the record to be written exceeds the output dataset record length and truncation by blanks (print files) or nulls (work files) is not allowed. Record truncation is controlled by the subparameter TRUNC of the PRINT or WORK profile parameter. |
| Actn. | Start the session with subparameter TRUNC=ON to allow record truncation or correct your application program or correct the output dataset record length, e.g. by profile subparameter LRECL. |

NAT1513: Error occurred when closing work file :1:.

| | Error occurred when closing work file |
|-------|---------------------------------------|
| Actn. | Contact your Natural administrator. |

NAT1514: Not supported file organization for :1: file :2:.

| Text | Not supported file organization for file |
|-------|---|
| Expl. | Currently, Natural only supports sequential files as work files. |
| Actn. | Check file organization of the file to be processed and correct it. |

NAT1515: Too many work files open in parallel.

| Text | Too many work files open in parallel. |
|-------|--|
| Expl. | This Natural version is active under Com-plete. Com-plete has the restriction that not more than 5 work files (SD-files) can be processed in parallel by one transaction. Therefore, Natural checks to ensure that not more than 5 are opened at the same time. It is possible that in a set of subsequent transactions more than 5 work files can be processed, but not more than 5 at a time. |
| Actn. | Reduce number of work files in use. |

NAT1516: GETMAIN error on open for :1: file :2:.

| Text | GETMAIN error on open for file |
|-------|---|
| Expl. | There is not enough main storage to satisfy a GETMAIN request that is issued when the specified file is opened. |
| | Increase the size of the storage thread. For non-thread environments increase the available region or partition size. |

NAT1517: FREEMAIN error on close for :1: file :2:.

| Text | FREEMAIN error on close for file |
|-------|--|
| Expl. | A FREEMAIN request failed when closing the specified file. |
| Actn. | Contact your Natural administrator. |

NAT1518: GET or PUT to not opened :1: file :2:.

| Text | GET or PUT to not opened file |
|-------|--|
| Expl. | An internal error condition may have occurred. |
| Actn. | Contact your Natural administrator. |

NAT1519: Invalid device type.

| Text | Invalid device type. |
|-------|--|
| Expl. | The device type for a printer is not a printer, or the device type for a work file is neither a tape nor a disk. |
| | Check JCL and correct error; if necessary, contact your Natural administrator. |

NAT1520: Device or logical printer :1: not available.

| Text | Device or logical printer not available. |
|-------|--|
| 1 1 | The device used to process a work file has not been assigned to the Natural program. |
| Actn. | Check JCL and correct error, or contact your Natural administrator. |

NAT1521: Invalid variable record.

| Text | Invalid variable record. |
|-------|--|
| Expl. | The first 4 bytes of a variable input-work-file record do not constitute a valid record descriptor-word. The setting of the Natural parameter BWORKD may be incorrect. |
| Actn. | Check JCL or file and correct error, or contact your Natural administrator. |

NAT1522: NATAMUSR: Access method exit NATAM9EX not installed.

| Text | NATAMUSR: Access method exit NATAM9EX not installed. |
|------|---|
| | The User Access Method exit entry point NATAM9EX is not resolved in User Access Method module NATAMUSR. |
| | Check if the exit has an entry point NATAM9EX. Check if the exit is linked to module NATAMUSR. |

NAT1525: This work file cannot be accessed with dynamic variables.

| Text | This work file cannot be accessed with dynamic variables. |
|-------|---|
| | Dynamic variables are only allowed in a READ WORK ONCE statement for a TYPE=STREAM work file. |
| Actn. | Do not use dynamic variables with this type of work file. |

NAT1526: OFFSET keyword not allowed for an UNFORMATTED work file.

| Text | OFFSET keyword not allowed for an UNFORMATTED work file. |
|-------|---|
| Expl. | OFFSET specifies a read position relative to the start of a work-file record. In an UNFORMATTED work file, however, there is no concept of records, therefore the OFFSET keyword is not allowed. To position forward relative to the end of the field processed last, use the FILLER keyword. |
| Actn. | Correct error in program. |

NAT1527: TYPE=UNFORMATTED work files not supported for this object.

| Text | TYPE=UNFORMATTED work files not supported for this object. |
|-------|--|
| Expl. | Work files of TYPE=UNFORMATTED can only be read and written by |
| | Natural programs that are compiled (CATALOGed, STOWed) under Natural |
| | Version 4 and above. |

NAT1528: Invalid TYPE specified in DEFINE WORK statement.

| Text | Invalid TYPE specified in DEFINE WORK statement. |
|-------|--|
| - | Valid work-file types are: "FORMATTED" for a regular, record-oriented work file. "UNFORMATTED" for a work file to be read or written as a byte stream. |
| Actn. | Specify a valid work-file type. |

NAT1529: Name in DEFINE WORK not allowed for this work file.

| Text | Name in DEFINE WORK not allowed for this work file. |
|-------|--|
| | The work-file access method specified for this work file does not accept a name operand. The name operand is optional and can be omitted if the work file TYPE is specified. |
| Actn. | Correct error in program. |

NAT1530: Invalid ASA control character for print file :1:.

| Text | Invalid ASA control character for print file |
|-------|--|
| Expl. | An invalid ASA control character has been found in the output record for the print file indicated in the error message. This occurs most likely with ASA=OFF in the Natural print-file definition, in which case it is the user"s responsibility to set a valid ASA control character. |
| Actn. | Check program and correct error. |

NAT1531: Data transfer to/from Entire Connection failed.

| Text | Data transfer to/from Entire Connection failed. |
|-------|---|
| | Writing output to the additional report TRANSFER requires Entire Connection protocol mode TCP/IP. Entire Connection data transfer is not implemented in Natural for Windows. |
| Actn. | Set profile parameter ECPMOD to "ON" (the TCP/IP protocol is used). |

NAT1532: Record length must not exceed 32 KB.

| Text | Record length must not exceed 32 KB. |
|-------|--|
| · · | The length of a record read/written with a READ/WRITE WORK FILE statement must not exceed 32 KB. |
| Actn. | Check program and correct error. |

NAT1533: Invalid attribute value :1: in DEFINE WORK statement.

| Text | Invalid attribute value in DEFINE WORK statement. |
|-------|--|
| | One of the attribute values specified for the ATTRIBUTES clause of the DEFINE WORK statement is invalid. |
| Actn. | Specify a valid attribute value. |

NAT1548: TPS spool request failure.

| Text | TPS spool request failure. |
|-------|---|
| Expl. | A non-zero return code on a TPS spool request has occurred. |
| Actn. | See the appropriate TPS documentation for details. |

NAT1549: TPS spooling interface not available.

| Text | TPS spooling interface not available. |
|-------|---|
| Expl. | For online environments: Module TPSSPINO is not available in the TP environment. For batch environments: TPSSPINB is not linked to NSITPS. |
| Actn. | Depending on your environment, either make TPSSPINO available, or link TPSSPINB to NSITPS. |

NAT1550: Natural ADVANCED FACILITIES has not been initialized.

| Text | Natural ADVANCED FACILITIES has not been initialized. |
|-------|--|
| | WRITE or DISPLAY has been requested, but Natural ADVANCED FACILITIES has not been initialized. Most probably the session was started with an invalid PRINTER parameter. |
| Actn. | Install Natural ADVANCED FACILITIES correctly, and restart the session. |

31 Natural System Error Messages 1551-1600

NAT1551: Error on NATSPOOL file.

| Text | Error on NATSPOOL file. |
|------------|---|
| 1 1 | A response code different from 0 was returned when accessing the NATSPOOL file. |
| Actn. | Check status of the NATSPOOL file and correct error. |

NAT1552: NATSPOOL: Record not found for a report being printed.

| Text | NATSPOOL: Record not found for a report being printed. |
|-------|---|
| - | To store a report on the NATSPOOL file, NATSPOOL tries to read the current DETAIL record (for update). This request failed because the record could not be found. |
| Actn. | Re-run the Natural program which generates the report. |

NAT1553: NATSPOOL: Invalid output length in WRITE (rep) statement.

| Text | NATSPOOL: Invalid output length in WRITE (rep) statement. |
|-------|--|
| | The NATSPOOL nucleus receives lines of output from the Natural |
| | nucleus. The length of one of these lines is not positive. |
| Actn. | Contact Software AG support. |

NAT1554: NATSPOOL: No message group record found for a queue.

| Text | NATSPOOL: No message group record found for a group. |
|-------|--|
| | To store a queue on the NATSPOOL file, NATSPOOL reads a free group, updates the DETAIL record and then tries to read the previous group record (for update). This request failed because the record could not be found. |
| Actn. | Re-run the Natural program which generates the queue. |

NAT1555: :1: occurred during work- or print file access.

| Text | DMS error DXXX occurred during work- or print file access. |
|-------|--|
| Actn. | Check file command settings for work- or print file. |

NAT1556: NATSPOOL file is full.

| Text | NATSPOOL file is full. |
|-------|---|
| Expl. | The NATSPOOL file, which is used as the physical spool file for all reports produced by Natural programs, is full. The maximum number of reports that may be contained in the NATSPOOL file, is defined via the formatting function of the Spool File Maintenance. |
| Actn. | (1) Print some reports with disposition D; or (2) Delete some reports; or (3) Increase the spool file (see Spool File Maintenance). |

NAT1557: NATSPOOL: Job number record not found on checkpoint.

| Text | NATSPOOL: Job number record not found on checkpoint. |
|-------|---|
| Expl. | The NATSPOOL environment (user profiles, logical printer profiles) has been correctly defined, but the part of the file which is to contain the printout queues has not been pre-formatted. |
| Actn. | Format the NATSPOOL file, using the F-function of the NATSPOOL operator commands. |

NAT1558: NATSPOOL: Interval control error.

| Text | NATSPOOL: Interval control error. |
|-------|---|
| | The NATSPOOL printer task could not be started because an invalid type of request was received for processing by the CICS interval control program. |
| Actn. | Contact your system programmer. |

NAT1559: NATSPOOL: GETMAIN for work area failed.

| Text | NATSPOOL: GETMAIN for work area failed. |
|-------|--|
| Expl. | This error may be caused by one of the following:1) During initialisation, the Natural Advanced Facilities work area(2 KB) could not be allocated.2) During execution, the size of this work area was not sufficient. |
| Actn. | Increase the thread size. Contact Software AG support. |

NAT1560: NATSPOOL: Index record not found for a queue.

| Text | NATSPOOL: Index record not found for a queue. |
|------|---|
| | This error is caused by an internal error within the NATSPOOL nucleus. |
| | Contact your Natural adminstrator; if necessary, contact Software AG support. |

NAT1561: NATSPOOL: Invalid form or destination.

| Text | NATSPOOL: Invalid form or destination. |
|-------|--|
| Expl. | An internal error has occurred in the NATSPOOL nucleus. |
| | Contact your Natural administrator; if necessary, contact Software AG support. |

NAT1562: NATSPOOL: Index record not found during close processing.

| Text | NATSPOOL: Index record not found during close processing. |
|-------|--|
| | To close a report on the NATSPOOL file, the index record is updated with "number of pages" and status "to be printed". This request failed because the index record could not be found. |
| Actn. | Re-run the Natural program which creates the report. |

NAT1563: NATSPOOL: EXEC CICS START, invalid SYSID.

| Text | NATSPOOL: EXEC CICS START, invalid SYSID. |
|-------|--|
| | The SYSID of the printer associated with the NATSPOOL printer task could not be found. |
| Actn. | Contact your Natural administrator. |

NAT1564: NATSPOOL: EXEC CICS START, invalid transaction ID.

| Text | NATSPOOL: EXEC CICS START, invalid transaction ID. |
|-------|--|
| · · | The transaction ID of the NATSPOOL printer task could not be found in the CICS Program Control Table. |
| Actn. | Contact your Natural administrator. |

NAT1565: NATSPOOL: EXEC CICS START, invalid printer ID.

| Text | NATSPOOL: EXEC CICS START, invalid printer ID. |
|-------|---|
| Expl. | The terminal ID of the printer associated with the NATSPOOL printer task could not be found in the CICS Terminal Control Table. Possible reasons are: - a misspelt printer name in the NATSPOOL Allocation Table; or - the terminal ID of the printer is not contained in the CICS TCT. |
| Actn. | Check NATSPOOL Allocation Table or contact your Natural administrator. |

NAT1566: NATSPOOL: Printer not defined in CICS, or LOCATE failed.

| Text | NATSPOOL: Printer not defined in CICS, or LOCATE failed. |
|-------|--|
| | When scanning the CICS Terminal Control Table (DFHTC CTYPE=LOCATE), the terminal ID specified in TCATPTA could not be located. |
| Actn. | Contact your Natural administrator. |

NAT1567: NATSPOOL: CICS locate failed.

| Text | NATSPOOL: CICS locate failed. |
|------|---|
| · · | When scanning the CICS Terminal Control Table (DFHTC CTYPE=LOCATE), an error occurred. |
| | Contact your Natural administrator. See program NATAF in the Natural ADVANCED FACILITIES source library. |

NAT1568: NATSPOOL: Open printer for hardcopy output failed.

| Text | NATSPOOL: Open printer for hardcopy output failed. |
|-------|--|
| 1 1 | The hardcopy system was invoked with the request "OPEN PRINTER FOR OUTPUT", but the OPEN failed. |
| Actn. | Contact your Natural administrator. |

NAT1569: Duplicate index record on NATSPOOL file.

| Text | Duplicate index record on NATSPOOL file. |
|-------|--|
| | To close a queue on the NATSPOOL file, NATSPOOL updates the index record with "number of pages" and status "to be printed". This request failed because more than one index record with the same key was found. |
| Actn. | Re-run the Natural program which generates the print queue. |

NAT1570: NATSPOOL: CSECT "NOMPUT" is missing.

| Text | NATSPOOL: CSECT "NOMPUT" is missing. |
|-------|--|
| | The CSECT "NOMPUT", which is used when routing reports from NAF to NOM is either missing in the link-edit stream or the name of the CSECT "NOMPUT" has been changed. |
| Actn. | Check for the presence of NOMPUT in the link-edit stream. |

NAT1572: Logical printer profile :1: not found on spool file.

| Text | Logical printer profile not found on spool file. |
|-------|--|
| | When using RSO direct support for printing, NAF reads the corresponding LPF from the spool file. During CLOSE processing, this LPF could not be read, either because it did not exist or because an Adabas error occurred. |
| Actn. | Check why the LPF could not be read. |

NAT1573: Logical printer profile :1: not found on spool file.

| Text | Logical printer profile not found on spool file. |
|-------|--|
| Expl. | (1) The logical printer referred to in the user"s Natural program, has not been associated with the user profile. (2) The Natural session was not started with a correct PRINTER parameter for NATSPOOL, i.e. PRINTER=(NATSPOOL,). (3) The OUTPUT operand of a DEFINE PRINTER statement references a logical printer profile which does not exist on the spool file. |
| Actn. | (1) Define a logical printer profile for the user, using the U function of the NATSPOOL operator command. (2) Define a correct PRINTER parameter for NATSPOOL. |

NAT1574: NATSPOOL: No physical printer allocated to hardcopy.

| Text | NATSPOOL: No physical printer allocated to hardcopy. |
|-------|--|
| Expl. | A hardcopy was requested (%H), but no physical printer is allocated. When hardcopies are requested, an allocation between the logical printer DESTINATION: TERMID of the user"s terminal FORM: A and at least one physical printer must be defined. The allocated printer(s) must be added to the NATSPOOL file. |
| Actn. | Define an allocation between logical and physical printer, by using the hardcopy allocation function of SYSPOOL. |

NAT1575: NATSPOOL: Invalid function code in hardcopy write.

| Text | NATSPOOL: Invalid function code in hardcopy write. |
|-------|--|
| | The hardcopy system was invoked with a request different from OPEN, PUT, or CLOSE. |
| Actn. | Contact your Natural administrator. |

NAT1576: NATSPOOL: Hardcopy system not available.

| Text | NATSPOOL: Hardcopy system not available. |
|-------|--|
| Expl. | A hardcopy was requested (%H), but NATSPOOL did not provide support for hardcopy due to one of the following reasons: (1) The module NATSPOOL is not included in the link-edit of Natural. (2) During initialization of Natural, the GETMAIN for the hardcopy system has failed. |
| Actn. | (1) Include NATSPOOL in the link-edit of Natural.(2) Ensure that sufficient storage is available. |

NAT1577: NATSPOOL: CSECT "NAFPARM" is missing.

| Text | NATSPOOL: CSECT "NAFPARM" is missing. |
|------|---|
| | This error may be caused by one of the following: The Natural Advanced Facilities parameter module NAFPARMC/NAFPARMI is missing in the link-edit stream. The CSECT instruction is missing in the source of the parameter module. The name in the CSECT instruction has been changed; the name must be "NAFPARM". |
| | Check for the presence of the parameter module in the link-edit stream; check if the source of the parameter module is correct/complete. |

NAT1578: No logical printer profile for hardcopy found.

| Text | No logical printer profile for hardcopy found. |
|-------|---|
| Expl. | When the user issues %H, NAF needs a logical printer profile (LPF). The name of this LPF is built from CMTERMID or USRID, depending on NAF customization. This LPF was not found during session initialization - probably it has been deleted from the spool file. |
| Actn. | Provide such an LPF or issue %Hxyz where xyz is the name of an existing LPF. |

NAT1581: NATSPOOL: CSECT :1: is missing.

| Text | NATSPOOL: CSECT :1: is missing. |
|------|--|
| | The CSECT specified in this error message is missing in the link-edit stream. |
| | If NAFIO is missing, check for the presence of module NAFAF. If NAFBS2FC is missing, check for the presence of module NAFSERVR. |

NAT1582: NATSPOOL: Job number record not found during "close".

| Text | NATSPOOL: Job number record not found during "close". |
|-------|--|
| | When closing a report, NATSPOOL has to update the job number record. However, this record was not found. |
| Actn. | Contact Software AG support. |

NAT1583: Unable to open or write to Natural spool file.

| Text | Unable to open or write to Natural spool file. |
|-------|---|
| Expl. | Printing was not successful for one of the following reasons: - the temporary file cannot be opened or created; - not enough memory is available; - printer initialization was not successful. |
| Actn. | Check the temporary file path TMP®PATH in the Natural.INI file. If printing directly to a file, please check that the file name is correctly set, and that the specified path (if any) exists. |

NAT1584: NATSPOOL: Unable to start printer.

| Text | NATSPOOL: Unable to start printer. |
|-------|--|
| | To start a printer, NATSPOOL has to update the printer status. If this record is in "hold" by another user, NATSPOOL retries 10 times; thereafter, processing is terminated with this error. |
| Actn. | Try to restart the printer. Increase ADARUN NH parameter to prevent Adabas response code 145. |

NAT1585: NATSPOOL: Unable to set printer to status HUNG.

| Text | NATSPOOL: Unable to set printer to status HUNG. |
|-------|--|
| | When assigning status HUNG to a printer, NATSPOOL has to update the printer status. When this record is in "hold" by another user, NATSPOOL retries 10 times; thereafter, processing is terminated with this error. |
| Actn. | Check why the printer record is in "hold". |

NAT1586: Unable to submit print job.

| Text | Unable to submit print job. |
|------|--|
| | The print job could not be submitted for one of the following reasons: - the printer name is unknown; - printer initialization was not successful. |
| | Check your physical printer settings in NATPARM to ensure that they agree with the actual printer name. |

NAT1588: NATSPOOL: NAFEXIT4 completed with errors.

| Text | NATSPOOL: NAFEXIT4 completed with errors. |
|-------|---|
| Expl. | The user written exit NAFEXIT4 returns with error(s). |
| Actn. | Please check program. |

NAT1589: NATSPOOL: NAFEXIT4 not found.

| Text | NATSPOOL: NAFEXIT4 not found. |
|-------|--|
| Expl. | The module NAFEXIT4 was not linked to the Natural nucleus. |
| Actn. | Please check you installation. |

NAT1590: NATSPOOL: Getmain for RSO buffer failed.

| Text | NATSPOOL: Getmain for RSO buffer failed. |
|-------|--|
| | To support RSO directly, Natural Advanced Facilities needs a buffer with a size of approximately 3700 bytes. This buffer could not be allocated. |
| Actn. | Please check your installation. |

NAT1591: NATSPOOL: WRLST macro failed using RSO support.

| Text | NATSPOOL: WRLST macro failed using RSO support. |
|-------|---|
| | Reports to be created using the RSO support of Natural Advanced Facilities are written to a BS2000 *SYSLST dataset. |
| 1 | Execution of the WRLST macro failed. |
| Actn. | Please switch on protocol and check for any errors. |

NAT1592: NATSPOOL: PRNT macro failed using RSO support.

| Text | NATSPOOL: PRNT macro failed using RSO support. |
|-------|--|
| | Reports closed for printout are spooled to RSO using the PRNT macro. Execution of this macro failed. |
| Actn. | Please switch on protocol and check for any errors. |

NAT1593: NATSPOOL: Invalid printer no. for RSO support (internal).

| Text | NATSPOOL: Invalid printer no. for RSO support (internal). |
|-------|---|
| Expl. | The internal printer number given to module NAFRSO was invalid. |
| Actn. | Please check assembly of NAFRSO and take dump. |

NAT1594: NATSPOOL: Invalid func. code for RSO support (internal).

| Text | NATSPOOL: Invalid func. code for RSO support (internal). |
|-------|--|
| | The module to handle the RSO direct support was called |
| | using an incorrect internal function code. |
| Actn. | Please check assembly of NAFRSO and take dump. |

NAT1595: NATSPOOL: No device name found for RSO support (internal)

| Text | NATSPOOL: No device name found for RSO support (internal) |
|-------|---|
| · · | The module to handle the RSO direct support was called without setting a device name. |
| Actn. | Please check assembly of NAFRSO and take dump. |

NAT1596: NATSPOOL: Allocate SYSLST failed for RSO support.

| Text | NATSPOOL: Allocate SYSLST failed for RSO support. |
|-------|--|
| Expl. | The allocation of the *SYSLST dataset failed. |
| Actn. | Please switch on protocl and check for any errors. |

NAT1597: NATSPOOL: Line starts with invalid control character.

| Text | NATSPOOL: Line starts with invalid control character. |
|-------|---|
| | One or more lines of the report spooled by RSO direct support do not contain a valid control character (line feed, form feed, etc.) |
| Actn. | Please check program. |

NAT1598: NATSPOOL: Release SYSLST failed for RSO support.

| Text | NATSPOOL: Release SYSLST failed for RSO support. |
|-------|---|
| | Resetting the *SYSLST allocation to the primary one has failed. |
| Actn. | Please switch on protocol and check for any errors. |

NAT1599: Attempt to execute READ/WRITE WORK to non-existent file.

| Text | Attempt to execute READ/WRITE WORK to non-existent file. |
|-------|--|
| Expl. | The work file specified in the job control does not exist. |
| Actn. | Check allocation of work files. |

NAT1600: Invalid stack function requested.

| Text | Invalid stack function requested. |
|-------|--|
| 1 1 | See Natural Programmer"s Guide for information on available stack functions. |
| Actn. | Correct error. |

32 Natural System Error Messages 1601-1650

NAT1601: Length of data to be stacked is zero or negative.

| Text | Length of data to be stacked is zero or negative. |
|-------|--|
| | The length of data to be stacked must be specified as non-zero and positive. |
| Actn. | Check program and correct error. |

NAT1602: Stack destroyed, command was expected.

| Text | Stack destroyed, command was expected. |
|-------|--|
| · · | Natural tried to read a command from the top of the stack, but none was found. |
| Actn. | Check program and correct error. |

NAT1603: Stack destroyed, data expected.

| Text | Stack destroyed, data expected. |
|-------|---|
| | Natural tried to read data from the top of the stack, but no information was available (can be produced by specifying: STACK=(EX pgm:)). Data must be specified for an INPUT statement. If default data are to be passed to INPUT fields, specify data for a non-existent INPUT field. The data will be ignored in delimiter mode. |
| Actn. | Check program and correct error. |

NAT1604: Stack empty.

| Text | Stack empty. |
|-------|--|
| | Natural tried to read data from the stack, but the stack was empty. Either an internal error has occurred, or the stack was destroyed. |
| Actn. | Check program and correct error. |

NAT1605: Stack data overflow.

| Text | Stack data overflow. |
|-------|--|
| · · | The amount of stack data does not fit into the stack area. You can stack a maximum of 999 elements. |
| Actn. | Check program and reduce the number or size of fields to be stacked. |

NAT1606: Invalid UTF-16 data.

| Text | Invalid UTF-16 data. |
|-------|--|
| Expl. | The data to be stacked do not represent a valid UTF-16 encoding. |
| | Ensure that the length of the UTF-16 character string in bytes is a multiple of 2. |

NAT1610: SET KEY error, function key bit not supplied.

| Text | SET KEY error, function key bit not supplied. |
|-------|---|
| Actn. | Check program and correct error. |

NAT1611: SET KEY error, function key not available.

| Text | SET KEY error, function key not available. |
|-------|---|
| | The selected function key in a SET KEY statement is not defined to Natural. |
| Actn. | Check program and correct error. |

NAT1612: Error in SET KEY statement.

| Text | Error in SET KEY statement. |
|-------|--|
| Expl. | A variable has been specified after "SET KEY", and the variable contains an invalid value. Valid values are: "PA1" to "PA3", "PF1" to "PF24", "CLR", |
| | and "ENTR". This error may also occur if the variable contains "ENTR" but a SET KEY statement option other than the NAMED clause is applied to the key. |
| Actn. | Correct error in program. |

33 Natural System Error Messages 1651-1700

NAT1681: NSF server communication error response :1:.

| Text | NSF server communication error response |
|-------|--|
| Expl. | Natural NSF - NSF server communication is not working. |
| Actn. | Please contact your administrator. |

NAT1682: NSF :1: system error, reason :2:.

| Text | NSF system error, reason |
|-------|------------------------------------|
| Expl. | A general problem has occurred. |
| Actn. | Please contact your administrator. |

NAT1683: NSF: Logon to library :1: is denied.

| Text | NSF: Logon to library is denied. |
|-------|---|
| Expl. | You do not have the permission to log on to this library. |
| | Possible reasons are: |
| | - The access to the system files (FUSER/FDIC/FSEC/FNAT) was denied. |
| | - The access to the library was denied. |
| Actn. | Contact your administrator. |

NAT1684: Logon to library :1: failed. No access to steplib :2:.

| Text | Logon to library failed. No access to steplib |
|-------|--|
| | The logon is rejected due to missing access rights to steplibs defined in the library profile. |
| Actn. | Contact your administrator. |

NAT1685: User is revoked.

| Text | User is revoked. |
|-------|--------------------------------------|
| Expl. | No further explanation available. |
| Actn. | Contact your security administrator. |

NAT1686: NSFSIZE parameter not specified or not available.

| Text | NSFSIZE parameter not specified or not available. |
|------------|--|
| 1 1 | Either the NSFSIZE parameter was not specified or NATGWSAF failed to acquire the storage specified by NSFSIZE. |
| | Ensure that the NSFSIZE parameter is specified correctly and that the Natural region/thread is large enough. |

NAT1690: Your password has expired :1: day(s) ago.

| Text | Your password has expired day(s) ago. |
|-------|---|
| | According to your security profile, you have to change your password periodically. Your password has now expired. |
| Actn. | Change your password. |

NAT1691: Your password will expire on :1:.

| Text | Your password will expire on |
|-------|---|
| · · | As of the date indicated in the message, your current password will no longer be valid. |
| Actn. | Change your password. |

NAT1692: User :1: is not authorized.

| Text | User is not authorized. |
|-------|---|
| Expl. | You have tried to log on to a library via Natural RPC in a client/server environment. In the security profile of the library, the option "Logon Option" (Natural RPC Restrictions) is set to "E" or "S". This means that Natural Security checks if the Natural user ID used for the access to the RPC server (for example, via user exit USR1071) is identical to the EntireX user ID (supplied, for example, via user exit USR2071). This error message is issued if both user IDs are found to be not identical. |
| Actn. | Contact your Natural administrator. |

NAT1694: Password changed successfully.

NAT1696: Logon to library :1: for user :2: denied, reason :3:, :4:.

| Text | Logon to library for user denied, reason |
|-------|---|
| Expl. | Cause of error as indicated by reason code shown in error message: |
| | 1 - NAT0873: User ID or password is invalid. |
| | 2 - NAT0818: User is not found. |
| | 7 - NAT0806: Library is not found. |
| | 8 - NAT0807: Logon to library ID is denied. |
| | 9 - NAT0963: Security violation during program execution. |
| | 10 - RPC logon terminated by user. |
| | 12 - Logoff from library failed. |
| | 14 - Impersonation failed. |
| | 16 - Internal error. |
| | 20 - NAT0857: This user is currently locked. |
| | 21 - NAT1685: This user is revoked. |
| | 22 - NAT0812: User ID profile illegally manipulated. |
| | 31 - NAT0807: Logon to library ID is denied in static mode. |
| Actn. | 31 - NAT0807: Logon to library ID is denied in static mode. Contact your Natural Security |
| | administrator. |

NAT1697: System file can only be accessed under Natural Security.

| Text | System file can only be accessed under Natural Security. |
|-------|--|
| Expl. | You have attempted to access a development server file whose security has been activated in Natural Security. Access to such a file is only possible in a Natural environment protected by Natural Security. However, the Natural environment in which you have tried to access the development server file is a non-Security environment. |
| Actn. | Please contact your Security administrator. |

NAT1698: You are not authorized to execute the specified function.

| Text | You are not authorized to execute the specified function. |
|-------|---|
| Expl. | You are not authorized to execute the specified function. |
| Actn. | Please contact your Security administrator. |

NAT1699: Automatic logon failed due to invalid default library.

| Text | Automatic logon failed due to invalid default library. |
|-------|---|
| Expl. | The default library is not correctly assigned to your user profile. |
| Actn. | Contact your Natural Security administrator. |

NAT1700: This application is currently not available to you.

| Text | This application is currently not available to you. |
|-------|--|
| | In Natural Security, the availability of the application has been restricted to certain periods of time only; outside these times, the application cannot be used. |
| Actn. | Ask your Natural Security administrator at what times the application is available to you. |

34 Natural System Error Messages 1701-1750

NAT1701: Non-activity time limit exceeded; press ENTER.

| Text | Non-activity time limit exceeded; press ENTER. |
|-------|--|
| | For this application/user, a non-activity time limit is defined. The elapsed time between the last screen I/O and the current I/O exceeded the defined limit. Natural Security requires the user to log on again. |
| Actn. | Press ENTER; then log on again. |

NAT1702: User is not authorized to use update statements.

| Text | User is not authorized to use update statements. |
|-------|--|
| | An UPDATE/STORE/DELETE statement was issued, but the user |
| | is not currently authorized to issue such update commands. |
| Actn. | Contact your Natural administrator. |

NAT1703: Maximum transaction duration exceeded.

| Text | Maximum transaction duration exceeded. |
|-------|---|
| Expl. | For this application/user, a maximum transaction duration has been |
| | defined in Natural Security. |
| | The time elapsed between the start of transaction and a subsequent |
| | database call or screen I/O has exceeded the defined limit. |
| | This limit is checked independently from the transaction time limit |
| | defined in Adabas. |
| | The transaction has been backed out. |
| | The Natural system variable *TIME-OUT contains the time remaining |
| | before a time-out will occur. |
| Actn. | Restart the transaction. |

NAT1704: Invalid dialog source header.

| Text | Invalid dialog source header. |
|-------|--|
| - | The first lines of the Natural source do not constitute a valid dialog header. |
| Actn. | Consult the documentation on the dialog format. |

NAT1705: Unknown dialog source format :1:.

| Text | Unknown dialog source format |
|-------|--|
| | The format identifier (as shown in the message) in the Natural dialog source does not identify one of the known formats. |
| Actn. | Consult the documentation on the dialog format. |

NAT1706: Invalid value for attribute :1:.

| Text | Invalid value for attribute |
|-------|---|
| Expl. | The value that has been assigned to the attribute is not allowed in this context. |
| Actn. | Assign a valid attribute value. |

NAT1707: Attribute :1: is invalid for element type :2:.

| Text | Attribute is invalid for element type |
|-------|--|
| | The attribute is not in the set of allowed attributes for this type of dialog element. |
| Actn. | Choose an allowed attribute for this dialog element type. |

NAT1708: Error occurred while scanning for :1:.

| Text | Error occurred while scanning for |
|-------|--|
| | The dialog source does not conform to the format expected by the dialog editor. The expected format is indicated in the error message. |
| Actn. | Correct the dialog source. |

NAT1709: The name :1: is already in use.

| Text | The name is already in use. |
|------|---|
| | An attempt was made to re-use a variable name which is already in use for some other dialog element or pre-defined constant. |
| | Use another name. The dialog editor usually suggests a unique replacement. |

NAT1710: Error opening source window.

| Text | Error opening source window. |
|-------|---|
| Expl. | The dialog source window could not be opened. |

NAT1711: Invalid dialog element name :1:.

| Text | Invalid dialog element name :1:. |
|------|---|
| - | The specified dialog element name is either syntactically invalid or undefined. |

NAT1712: Invalid index for dialog element.

| Text | Invalid index for dialog element. |
|------|--|
| | The index specified for this dialog element is either syntactically incorrect or out of range. |

NAT1713: Control :1: not found.

| Text | Control :1: not found. |
|-------|--|
| Expl. | The specified control name is undefined at this point in the dialog. |

NAT1714: Invalid OLE control property :1:.

| Text | Invalid OLE control property :1:. |
|-------|---|
| Expl. | The specified property is not appropriate for this control. |

NAT1715: This dialog cannot be saved in non-enhanced format.

| Text | This dialog cannot be saved in non-enhanced format. |
|-------|--|
| 1 1 | This dialog uses features which require the enhanced source format, for example custom controls. |
| Actn. | To save the dialog with these features, select the enhanced format in the Save As dialog box. |

NAT1716: Invalid event name :1:.

| Text | Invalid event name :1:. |
|------|--|
| | The specified event name is either syntactically invalid or undefined for this dialog element. |

NAT1717: Failure creating control :1:.

| Text | Failure creating control :1:. |
|-------|--|
| Expl. | The indicated control could not be created. If this error occurs when inserting an ActiveX control into a dialog in the dialog editor, a common reason for this failure is that there is no development license available for the ActiveX control on this machine. A development license is usually available from the vendor of the ActiveX control. |
| Actn. | Please check if the ActiveX control is correctly installed and registered. Also check if you have a development license or only a runtime license for the ActiveX control. |

NAT1718: Incomplete code section.

| Text | Incomplete code section. |
|-------|---|
| Expl. | A user-code section is not terminated as defined in the dialog source |
| | syntax. |

NAT1719: Operation cancelled by user.

| Text | Operation cancelled by user. |
|-------|--|
| Expl. | The operation was not completed because the user cancelled it. |

NAT1720: Invalid object type.

| Text | Invalid object type. |
|-------|---|
| Expl. | It is not possible to emded this type of object. |
| Actn. | Please choose a created embedded object (i.e. *.neo). |

NAT1721: Error in dialog source at line :1:, column :2:: :3:

| Text | Error in dialog source at line :1:, column :2:: :3: |
|-------|--|
| | The dialog editor has detected the Natural error with text :3: in the dialog source at the line :1:, column :2:. |
| Actn. | Correct the source. |

NAT1750: An unknown preprocessor directive has been encountered.

| Text | An unknown preprocessor directive has been encountered. |
|-------|--|
| Expl. | The Natural Preprocessor encountered a source line which appears to be |
| | a directive, but has an invalid directive keyword. |

35 Natural System Error Messages 1751-1800

NAT1751: Argument(s) to a preprocessor directive are missing or invalid.

| Text | Argument(s) to a preprocessor directive are missing or invalid. |
|-------|--|
| Expl. | The Natural Preprocessor encountered a source line which is a directive, |
| | but one of the mandatory arguments is missing or has an invalid format o |
| | value. |

NAT1752: The directives "if", "else", or "end-if" do not properly match up.

| Text | The preprocessor directives "if", "else", or "end-if" do not properly match up. |
|------|---|
| | The Natural Preprocessor encountered a source line which is one of the |
| | conditional directives "else" of "end-if", but the corresponding "if" |
| | directive is missing, or the end of the source while an "end-if" |
| | directive is missing. |

NAT1753: The requested preprocessor function is unknown.

| Text | The requested preprocessor function is unknown. |
|-------|--|
| Expl. | A Natural Preprocessor function was called with an invalid subfunction |
| | number. |

NAT1754: A preprocessor fct argument is missing or has an invalid format.

| Text | A preprocessor fct argument is missing or has an invalid format. |
|-------|--|
| Expl. | A Natural Preprocessor function was called with one of the mandatory |
| | arguments missing or with an invalid format. |

NAT1755: An argument to a preprocessor function has an invalid value.

Text An argument to a preprocessor function has an invalid value.

NAT1756: The specified preprocessor memory buffer already exists.

| Text | The specified preprocessor memory buffer already exists. |
|-------|--|
| Expl. | An attempt was made to create a Natural Preprocessor memory buffer |
| | with a number which is already in use by another memory buffer. |

NAT1757: The specified preprocessor memory buffer does not exist.

| Text | The specified preprocessor memory buffer does not exist. |
|-------|---|
| Expl. | An attempt was made to reference a Natural Preprocessor memory buffer |
| | with a number which does not exist. |

NAT1770: Too many search keys were selected. Additional keys ignored.

| Text | Too many search keys were selected. Additional keys ignored. |
|------|--|
| | SQL only: Only five search keys can be selected. Initially all |
| | elementary fields are in the search key list. The user has to select |
| | the search keys from the list. |

NAT1771: No search key has been selected.

| Text | No search key has been selected. |
|-------|--|
| Expl. | SQL only: All fields have been removed from the search key list. |

NAT1772: Creation of object view :1: failed. Error :2:.

| Text | Creation of object view :1: failed. Error :2:. |
|------|---|
| Exp | I. An internal error occurred while creating the object view :1:. |

NAT1773: Object view info module :1: is not valid. Error :2:.

| | Text | Object view info module :1: is not valid. Error :2:. |
|---|------|---|
| - | - | An internal error has occurred while accessing the object view info module :1:. |
| | | info module :1:. |

NAT1774: Version of object view info :1: is not valid.

| Text | Version of object view info :1: is not valid. |
|-------|---|
| | It is not possible to read the object view info module with the current version of Natural. |
| Actn. | Recreate the object view. |

NAT1775: Object view name :1: already used in info module :2:.

| Text | Object view name :1: already used in info module :2:. |
|-------|---|
| Expl. | An object view"s name must be unique. |
| | Change the object view name or the info module's name so that there is a one-to-one correspondence between object view name and info module name. |

NAT1776: SQL table name is required.

| Text | SQL table name is required. |
|-------|---|
| Expl. | An SQL table name is necessary for this function. |

NAT1777: No object view selected.

| Text | No object view selected. |
|-------|---|
| Expl. | An object view is necessary for the selected frame. |
| Actn. | Create a new object view if none exists. |

NAT1778: A value <= 0 has been entered for the parameter "max. objects".

| Text | A value <= 0 has been entered for the parameter "max. objects". |
|-------|---|
| Expl. | Only values > 0 are allowed for this parameter. |

NAT1779: Module :1: already exists in another object view.

| Text | Module :1: already exists in another object view. |
|------|---|
| | One or more modules exist in another object view. All module names listed in object view info modules must be unique. |
| | Change the module name(s) and/or the info module name so that the list of module names is unique for the object view. |

NAT1780: Object view :1: does not exist.

| Text | Object view :1: does not exist. |
|-------|---|
| | The object view name which has been entered does not exist in one of the available libraries. |
| Actn. | Select one of the existing object views. |

NAT1781: DDM :1: does not contain descriptor fields.

| Text | DDM :1: does not contain descriptor fields. |
|-------|--|
| | It is not possible to define an object view based on a DDM which does not contain at least one descriptor field. Reason: the object view needs a search key which has to be a descriptor field. |
| Actn. | Change the DDM definition or use another DDM. |

NAT1782: DDM contains superdescriptors without descriptor information.

| Text | DDM contains superdescriptors without descriptor information. |
|-------|---|
| | The DDM contains superdescriptors without descriptor information. These superdescriptors are not available as search keys. The descriptor information is needed to get the component fields of the superdescriptor. |
| Actn. | Use a DDM which contains the descriptor information for superdescriptors. |

NAT1783: Object view name is not unique.

| Text | Object view name is not unique. |
|-------|--|
| - | The object view contains a field which has the same name as the object view. |
| Actn. | Change the object view name. |

NAT1790: A generated dialog was executed without the application shell.

| Text | A generated dialog was executed without the application shell. |
|-------|--|
| | The dialog was generated with the frame gallery and requires the application shell to execute. |
| Actn. | Start the dialog after starting the application shell. |

NAT1800: Parameter mismatch in PROCESS GUI statement.

| Text | Parameter mismatch in PROCESS GUI statement. |
|------|--|
| - | The number of parameters specified in a PROCESS GUI statement does not match the expected number. |
| | Check program syntax against documentation syntax. In most cases, the specified action requires more parameters than expected. |

36 Natural System Error Messages 1801-1850

NAT1801: The maximum number of CLIENT-KEY values was exceeded.

| Text | The maximum number of CLIENT-KEY values was exceeded. |
|-------|---|
| | Only a limited number of values are allowed for the attribute CLIENT-KEY. |
| Actn. | Reuse CLIENT-KEY values which are not needed. |

NAT1802: Invalid value specified for attribute COLUMN-TYPE.

| Text | Invalid value specified for attribute COLUMN-TYPE. |
|-------|---|
| | An invalid value was specified for the attribute COLUMN-TYPE of a table control. This attribute specifies the type of column to be used in a column specification control. For example, INPUTFIELD, SELECTIONBOX. |
| Actn. | Valid column types are: INPUTFIELD, SELECTIONBOX, TEXTCONSTANT, TOGGLEBUTTON. |

NAT1803: Table field not found.

| Text | Table field not found. |
|-------|--|
| 1 1 | The PROCESS-GUI-statement action TABLE-FIND-FIELD failed because |
| | the field title passed was not present in the table. |
| Actn. | Check the passed field title against existing field titles. |

NAT1804: Invalid row/column range specified in PROCESS GUI statement.

| Text | Invalid row/column range specified in PROCESS GUI statement. |
|------|--|
| Expl | The row/column range specified in the PROCESS GUI statement for a table control is invalid. The row or column number specified exceeds the current table size. |
| Actn | . Use attribute ROW-COUNT and/or COLUMN-COUNT to check the current size of the table. |

NAT1805: No selection is active in table control.

| Text | No selection is active in table control. |
|-------|--|
| Expl. | A PROCESS-GUI-statement action was performed to inquire the |
| | current selection in a table control, but no selection was active. |

NAT1806: PROCESS-GUI-statement action failed.

| Text | PROCESS-GUI-statement action failed. |
|-------|---|
| | The PROCESS-GUI-statement action was not completed successfully either because the parameters passed were invalid or because the windowing system could not process the function. |
| Actn. | Check parameters. |

NAT1807: File not found.

| Text | File not found. |
|-------|---|
| Expl. | The specified file was expected in the path specified by the environment variable NATGUI®BMP, but it was not found. |
| Actn. | Check whether the file name is misspelled or whether the file is located in a directory other than NATGUI®BMP. |

NAT1808: Edit area overflow.

| Text | Edit area overflow. |
|-------|---|
| Expl. | It is not possible to insert any more characters or lines into an edit area. The number of characters which can be entered into an edit area is approximately 64 KB under Windows 95/98/Me and approximately 4 GB under Windows NT and Windows 2000. This error also occurs when attempting to insert a new line beyond the end of the edit area window, if the edit area is not autoscrollable (i.e., neither has a vertical scroll bar nor is explicitly marked as autoscrollable). |
| Actn. | Reduce the text written to the edit area, or (if the edit area does not have a vertical scroll bar) set the "autoscroll" style. |

Natural System Error Messages 1851-1900

NAT1900: Couldn"t create a connection point (SOCKET code :1:).

| Text | Couldn"t create a connection point. (SOCKET code :1:). |
|-------|--|
| Expl. | The socket function "socket" failed to execute because - No more socket descriptors are available - No buffer space is available - The network subsystem or the associated service provider has failed |
| Actn. | check your system for 1) socket descriptors already in use 2) enough buffer space 3) correctly installed network system |

38

Natural System Error Messages 1901-1950

NAT1901: Couldn"t bind to a connection point (SOCKET code :1:).

| Text | Couldn"t bind to a connection point (SOCKET code :1:). |
|-------|--|
| Expl. | The socket function "bind" failed to execute because - The network subsystem has failed - Not enough buffers available, too many connections |
| Actn. | check your system for - correctly installed network system - enough buffer space |

NAT1902: Socket error :1: : Couldn"t resolve service port.

| Text | TODO |
|-------|------|
| Expl. | TODO |
| Actn. | TODO |

NAT1903: Couldn"t connect to remote debugging service (SOCKET code :1:).

| Text | Couldn"t connect to remote debugging service (SOCKET code :1:). |
|------|---|
|------|---|

| Expl. | Natural cannot create a connection to the remote debugging service |
|-------|--|
| | because of one of the following reasons: |
| | - the specified remote debugging node is not accessible |
| | - the remote debugging service is not active |
| | - the used port id does not match the port of the remote |
| | debugging service |
| | - the remote debugging service did not initialise correctly |
| | Check that |
| | - the NT machine where the remote debugging service |
| | is running is accessible (e.g. via the "ping" command) |
| | - the remote debugging service is installed and |
| | running |
| | - the port used to install the service (default=2500) |
| | matches the port number specified in the RDPORT parameter |
| Actn. | matches the port number specified in the RDPORT parameter - the remote debugging service |
| | initialised correctly |
| | (take a look at NT"s event viewer for any remote debugging |
| | service related error entry) |

NAT1904: The node name :1: could not be resolved (SOCKET code :2:).

| Text | The node name :1: could not be resolved (SOCKET code :2:). |
|-------|---|
| | the node name where the remote debugging service is supposed to run could not be resolved |
| Actn. | check that the specified node name is available in the network system |

NAT1905: Remote Debugging: Error while receiving data (SOCKET code :1:).

| Text | Remote Debugging: Error while receiving data (SOCKET code :1:). |
|------------|--|
| _ _ | The connection between Natural and the remote debugging service has been broken. |
| Actn. | Set up debugging session again. |

NAT1906: Remote debugging: Error while sending data (SOCKET code :1:).

| Text | Remote debugging: Error while sending data (SOCKET code :1:). |
|-------|--|
| Expl. | The connection between Natural and the remote debugging service has been broken. |
| Actn. | Set up debugging session again. |

NAT1907: Establishing a local debugging session failed.

| Text | Establishing a local debugging session failed. |
|-------|---|
| Expl. | This platform does not provide a Natural Debugger |
| Actn. | Use Natural's remote debugging facility to debug the application. |

39 Natural System Error Messages 1951-2000

NAT1999: :1:.

| Text | |
|-------|---------------------|
| Expl. | Error has occurred. |

NAT2000: Invalid option selection.

| | Invalid option selection. |
|-------|----------------------------------|
| Actn. | Check program and correct error. |

40 Natural System Error Messages 2001-2050

NAT2001: User ID required.

TextUser ID required.Expl.Check program and correct error.

NAT2002: Please enter name of public library.

| 1 | Please enter name of public library. |
|-------|--------------------------------------|
| Expl. | Check program and correct error. |

NAT2003: Public library not found.

| | Public library not found. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2004: Function not allowed for public library.

| | Function not allowed for public library. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2005: Function invalid.

| Text | Function invalid. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2006: Invalid - please enter "Y" or "N".

| Text | Invalid - please enter "Y" or "N". |
|-------|------------------------------------|
| Actn. | Check program and correct error. |

NAT2008: Invalid command.

| Text | Invalid command. |
|-------|---------------------------------|
| Expl. | Check program and correct error |

NAT2009: Name must not be changed when copying into public library.

| Text | Name must not be changed when copying into public library. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2010: Transaction not found.

| Text | Transaction not found. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2011: Transaction ID required.

| Text | Transaction ID required. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2012: TRANSACTION IS CORRUPT

| | TRANSACTION IS CORRUPT |
|-------|---------------------------------|
| Expl. | Check program and correct error |

NAT2013: Transaction created under an incompatible version.

| Text | Transaction created under an incompatible version. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2014: Transaction has errors and cannot be run.

| Text | Transaction has errors and cannot be run. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2015: Transaction already present.

| Text | Transaction already present. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2016: You are not authorized to use DISPLAY inquiries.

| Text | You are not authorized to use DISPLAY inquiries. |
|------|--|
|------|--|

Expl. Check program and correct error.

NAT2017: You are not authorized to use TABULAR inquiries.

| | You are not authorized to use TABULAR inquiries. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2018: You are not authorized to use WORK-FILE/PC inquiries.

| Text | You are not authorized to use WORK-FILE/PC inquiries. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2019: JCL-ID may not exceed 8 characters.

| Text | JCL-ID may not exceed 8 characters. |
|-------|-------------------------------------|
| Expl. | Check program and correct error. |

NAT2020: You are not authorized to use GRAPHICS(PGF) inquiries.

| Text | You are not authorized to use GRAPHICS(PGF) inquiries. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2021: You are not authorized to use GRAPHICS(ICU) inquiries.

| Text | You are not authorized to use GRAPHICS(ICU) inquiries. |
|------|--|
| Expl | Check program and correct error. |

NAT2022: You are not authorized to run ON-LINE inquiries.

| Text | You are not authorized to run ON-LINE inquiries. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2023: You are not authorized to run BATCH transactions.

| Text | You are not authorized to run BATCH transactions. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2024: You are not authorized to run EDIT transactions.

| Text | You are not authorized to run EDIT transactions. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2025: You are not authorized to run PRINTER transactions.

| Text | You are not authorized to run PRINTER transactions. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2026: You are not authorized to submit BATCH transactions.

| Text | You are not authorized to submit BATCH transactions. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2027: Transaction number required.

| | Transaction number required. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2028: Invalid number.

| Text | Invalid number. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2029: If ACCEPT/REJECT used, no further action allowed.

Expl. Check program and correct error.

NAT2030: Please enter primary file number.

| | Please enter primary file number. |
|-------|-----------------------------------|
| Expl. | Check program and correct error. |

NAT2031: Primary and secondary file must not be the same.

| Text | Primary and secondary file must not be the same. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2032: Superfile - may not be selected with another.

TextSuperfile - may not be selected with another.

Expl. Check program and correct error.

NAT2033: File number missing or invalid.

| Text | File number missing or invalid. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2034: File number not in valid range.

| | File number not in valid range. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2035: This file is not defined.

| Text | This file is not defined. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2036: You are not authorized to access this file.

| | You are not authorized to access this file. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2037: File is not a superfile.

| Text | File is not a superfile. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2038: File is a superfile.

| Text | File is a superfile. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2039: Invalid format combination.

| Text | Invalid format combination. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2040: Invalid - mark only one field.

| | Invalid - mark only one field. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2041: Link field must be entered.

| | Link field must be entered. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2042: Start position outside primary link field.

| Text | Start position outside primary link field. |
|------------|--|
| T 1 | |

Expl. Check program and correct error.

NAT2043: End position outside primary link field.

| Text | End position outside primary link field. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2044: End position before start position is invalid.

| Text End position before st | tart position is invalid. |
|-----------------------------|---------------------------|
|-----------------------------|---------------------------|

Expl. Check program and correct error.

NAT2045: Invalid processing sequence characters.

| Text | Invalid processing sequence characters. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2046: No selection criteria input.

TextNo selection criteria input.Expl.Check program and correct error.

NAT2047: Selection criteria not completed.

| Text | Selection criteria not completed. |
|-------|-----------------------------------|
| Expl. | Check program and correct error. |

NAT2048: Field name or reference invalid.

| | Field name or reference invalid. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2049: Sequential READ only on key fields.

| | Sequential READ only on key fields. |
|-------|-------------------------------------|
| Expl. | Check program and correct error. |

NAT2050: Operator missing/invalid.

| Text | Operator missing/invalid. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

41 Natural System Error Messages 2051-2100

NAT2051: Invalid numeric value.

TextInvalid numeric value.Expl.Check program and correct error.

NAT2052: Too many characters in value.

| | Too many characters in value. | |
|-------|----------------------------------|--|
| Expl. | Check program and correct error. | |

NAT2053: Invalid THRU syntax.

| | Invalid THRU syntax. | |
|-------|----------------------------------|--|
| Expl. | Check program and correct error. | |

NAT2054: Logical operator not AND or OR.

| Text | Logical operator not AND or OR. | |
|-------|----------------------------------|--|
| Expl. | Check program and correct error. | |

NAT2055: Unmatched right parenthesis.

| | Unmatched right parenthesis. | |
|-------|---------------------------------------|--|
| Expl. | Expl. Check program and correct error | |

NAT2056: Right parenthesis missing.

| | Right parenthesis missing. | |
|-------|---------------------------------|--|
| Expl. | Check program and correct error | |

NAT2057: Group field invalid in selection.

| | Group field invalid in selection. | |
|-------|-----------------------------------|--|
| Expl. | Check program and correct error | |

NAT2058: Invalid fields in non-key criterion.

| Text | Invalid fields in non-key criterion. | |
|-------|--------------------------------------|--|
| Expl. | Check program and correct error. | |

NAT2059: Invalid use of super/sub/phonetic key.

| | Invalid use of super/sub/phonetic key. | |
|-------|--|--|
| Expl. | Check program and correct error. | |

NAT2060: Invalid use of multiple-value or periodic-group field.

| L | | Invalid use of multiple-value or periodic-group field. |
|---|-------|--|
| | Expl. | Check program and correct error. |

NAT2061: MORE must be Y or N.

| Text | MORE must be Y or N. | |
|-------|----------------------------------|--|
| Expl. | Check program and correct error. | |

NAT2062: Whole file must be read - not permitted.

| Text | Whole file must be read - not permitted | |
|-------|---|--|
| Expl. | Check program and correct error. | |

NAT2063: Field type not allowed in selection.

| | not allowed in selection. |
|------|---------------------------|
| | |

Expl. Check program and correct error.

NAT2064: Maximum number of conditions exceeded.

| Text | Maximum number of conditions exceeded. |
|------|--|
| | |

Expl. Check program and correct error.

NAT2065: Non-key conditions are not permitted.

| Text | Non-key conditions are not permitted. |
|------|---------------------------------------|
|------|---------------------------------------|

Expl. Check program and correct error.

NAT2066: ST not allowed for numeric fields.

| | ST not allowed for numeric fields. |
|-------|------------------------------------|
| Expl. | Check program and correct error. |

NAT2067: Further criteria not allowed with ALL.

Text Further criteria not allowed with ALL.Expl. Check program and correct error.

NAT2068: Index not allowed.

| Text | Index not allowed. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2069: Invalid index value.

| | Invalid index value. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2070: Sub-conditions must be on same file.

| | Sub-conditions must be on same file. |
|-------|--------------------------------------|
| Expl. | Check program and correct error. |

NAT2071: Too many levels of parentheses.

| | Too many levels of parentheses. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2072: Invalid MASK/SCAN value.

| Text | Invalid MASK/SCAN value. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2073: Result field name/reference invalid.

| Text | Result field name/reference invalid. |
|-------|--------------------------------------|
| Expl. | Check program and correct error. |

NAT2074: Calculation not completed.

| Text | Calculation not completed. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2075: "=" operator missing.

| | "=" operator missing. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2076: Invalid alphanumeric constant.

| Text | Invalid alphanumeric constant. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2077: Group field may not be used.

| Text | Group field may not be used. |
|-------|---|
| | A reason for this error message my be: - SET/GET of property arrays require, that the values of all array elements are available in contiguous order. Group arrays do not fulfil this requirement in any case. |
| Actn. | Check program and correct error. |

NAT2078: Super/sub/phonetic key may not be used.

| | Super/sub/phonetic key may not be used. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2079: Second index must be greater than first.

| Text | Second index must be greater than first. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2080: Operator not allowed with alpha fields.

| | Operator not allowed with alpha fields. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2081: Constant is too long.

| | Constant is too long. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2082: Field is too long.

| | Field is too long. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2083: Summation not allowed for alphanumeric fields.

| Text | Summation not allowed for alphanumeric fields. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2084: Invalid display number.

| | Invalid display number. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2085: Control/sort level already used.

| Text | Control/sort level already used. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2086: Field may not be a text field.

| | Field may not be a text field. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2087: Number already used for a display field.

| | Number already used for a display field. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2088: Invalid field function.

| | Invalid field function. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2089: May not be a control/sort field.

| | May not be a control/sort field. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2090: Field is not numeric.

| Text | Field is not numeric. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2091: "=" field already given for calculation.

| Text | "=" field already given for calculation. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2092: Field may not be a display field.

| | Field may not be a display field. |
|-------|-----------------------------------|
| Expl. | Check program and correct error. |

NAT2093: Field may not be used for lookup.

| | Field may not be used for lookup. |
|-------|-----------------------------------|
| Expl. | Check program and correct error. |

NAT2094: Invalid sort/control specification.

TextInvalid sort/control specification.Expl.Check program and correct error.

NAT2095: Only one field may be specified as the lookup key.

| | Only one field may be specified as the lookup key. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2096: Field is not a key field.

| | Field is not a key field. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2097: This field may only be used as a key.

| | This field may only be used as a key. |
|-------|---------------------------------------|
| Expl. | Check program and correct error. |

NAT2098: Field mark must be D or K.

| Т | | Field mark must be D or K. |
|---|-------|----------------------------------|
| | Expl. | Check program and correct error. |

NAT2099: A superfile may not be used as a lookup file.

| | A superfile may not be used as a lookup file. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2100: Invalid control specification.

| | Invalid control specification. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

42 Natural System Error Messages 2101-2150

NAT2101: Invalid display specification.

TextInvalid display specification.Expl.Check program and correct error.

NAT2102: Must be Y, N, or blank (default).

| | Must be Y, N, or blank (default). |
|-------|-----------------------------------|
| Expl. | Check program and correct error. |

NAT2103: Decimal positions must be in range 0 - 7.

| | positions must be in range 0 - 7. |
|--|-----------------------------------|
| | _ |

Expl. Check program and correct error.

NAT2104: Length plus decimal positions must be in range 1 - 27.

| 1 | Length plus decimal positions must be in range 1 - 27. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2105: "/" not permitted in heading lines.

| Text | "/" not permitted in heading lines. |
|-------|-------------------------------------|
| Expl. | Check program and correct error. |

NAT2106: Invalid edit mask.

| | Invalid edit mask. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2107: Only one of FLOAT and LEADING may be entered.

| Text | Only one of FLOAT and LEADING may be entered. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2108: Occurrences must be in range 1 - 191.

| | Occurrences must be in range 1 - 191. |
|-------|---------------------------------------|
| Expl. | Check program and correct error. |

NAT2109: Occurrences invalid - not a multiple value field.

| Text | Occurrences invalid - not a multiple value field. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2110: Occurrences invalid - not a two level multiple value field.

| | Occurrences invalid - not a two level multiple value field. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2111: Second occurrence may not be entered without first.

| Text | Second occurrence may not be entered without first. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2112: Length must be in range 1 - 79.

| | Length must be in range 1 - 79. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2113: Occurrences not in valid range.

| Text | Occurrences not in valid range. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2114: Group field may not be displayed as a text field.

| Text Group field may not be displayed as a text field. |
|--|
|--|

Expl. Check program and correct error.

NAT2115: Occurrences invalid - not a periodic group.

| Text | Occurrences invalid - not a periodic group. |
|------|---|
|------|---|

Expl. Check program and correct error.

NAT2116: Invalid reply - please re-enter.

TextInvalid reply - please re-enter.Expl.Check program and correct error.

NAT2117: Format must be A, N, or P.

TextFormat must be A, N, or P.Expl.Check program and correct error.

NAT2118: Format must not be changed.

| Text | Format must not be changed. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2119: Control field may not have text display.

| | Control field may not have text display. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2120: Embedded spaces not allowed in name or value.

| Text | Embedded spaces not allowed in name or value. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2121: Invalid name.

| Text | Invalid name. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2122: Value may not be more than 18 characters.

| | Value may not be more than 18 characters. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2123: Value has too many integer positions.

| | Value has too many integer positions. |
|-------|---------------------------------------|
| Expl. | Check program and correct error. |

NAT2124: Value has too many decimal positions.

| | Value has too many decimal positions. |
|-------|---------------------------------------|
| Expl. | Check program and correct error. |

NAT2125: Length may not exceed 20.

| | Length may not exceed 20. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2126: Length may not exceed 249.

| | Length may not exceed 249. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2127: Decimal positions must be zero.

| Text | Decimal positions must be zero. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2128: Length and decimal positions may not both be zero.

| | | Length and decimal positions may not both be zero. |
|---|-------|--|
| Ì | Expl. | Check program and correct error. |

NAT2129: Length plus offset exceeds base field length.

| | Text | Length plus offset exceeds base field length. |
|--|-------|---|
| | Expl. | Check program and correct error. |

NAT2130: Output length may not exceed length.

| | Output length may not exceed length. |
|-------|--------------------------------------|
| Expl. | Check program and correct error. |

NAT2131: Limit exceeded.

TextLimit exceeded.Expl.Check program and correct error.

NAT2132: Must be Y or N.

| Text | Must be Y or N. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2133: Occurrences must be in range 1 - 99.

| Text | Occurrences must be in range 1 - 99. |
|-------|--------------------------------------|
| Expl. | Check program and correct error. |

NAT2134: Must be in range 1 - 5.

| Text | Must be in range 1 - 5. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2135: Must be P or 1 - 5.

| Text | Must be P or 1 - 5. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2136: May not be less than 12.

| Text | May not be less than 12. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2137: Must be in range 80 - 250.

| | Must be in range 80 - 250. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2138: No more transactions allowed.

| I | | No more transactions allowed. |
|---|-------|----------------------------------|
| | Expl. | Check program and correct error. |

NAT2139: Free-format transaction cannot be modified in fixed-format mode.

| Text | Free-format transaction cannot be modified in fixed-format mode. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2140: No IF conditions entered.

| | No IF conditions entered. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2141: IF conditions are not completed.

| | IF conditions are not completed. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2142: Mixed field formats not allowed.

| Text | Mixed field formats not allowed | |
|-------|----------------------------------|--|
| Expl. | Check program and correct error. | |

NAT2143: OR not permitted between linked files.

| Text | OR not permitted between linked files. |
|------|--|
|------|--|

Expl. Check program and correct error.

NAT2144: Unknown error.

TextUnknown error.Expl.Check program and correct error.

NAT2145: Error in NATTAB.

TextError in NATTAB.Expl.Check program and correct error.

NAT2146: Error in NATDDR.

| Text | Error in NATDDR. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2147: System file record missing when it should be present.

| Text | System file record missing when it should be present. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2148: Selection error found during program generation.

| Text | Selection error found during program generation. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2149: Calculation error found during program generation.

| Text Calculation err | Calculation error found during program generation. |
|----------------------|--|
| Expl. | Check program and correct error. |

NAT2150: Must be an elementary field.

| Text | Must be an elementary field. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

43 Natural System Error Messages 2151-2200

NAT2151: Must be an elementary numeric field.

| | Must be an elementary numeric field. |
|-------|--------------------------------------|
| Expl. | Check program and correct error. |

NAT2152: Invalid system function indicator.

| | Invalid system function indicator. |
|-------|------------------------------------|
| Expl. | Check program and correct error. |

NAT2153: Range not allowed for non-numeric fields.

| Τ | Text | Range not allowed for non-numeric fields. |
|---|-------|---|
| | Expl. | Check program and correct error. |

NAT2154: Mark one graphic type.

| Text | Mark one graphic type. |
|-------------|----------------------------------|
| Expl. Check | Check program and correct error. |

NAT2155: Must be P, H, Q, or S.

| Text | Must be P, H, Q, or S. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2156: Must be B, M, T, or blank.

| Text | Must be B, M, T, or blank. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2157: Must be blank for PAGE graph.

| | Must be blank for PAGE graph. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2158: Must be L, C, R, or blank.

| Text | Must be L, C, R, or blank. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2159: Don"t enter both B/M/T and L/C/R.

| Text | Don"t enter both B/M/T and L/C/R. |
|-------|-----------------------------------|
| Expl. | Check program and correct error. |

NAT2160: Must be B, M or T.

| | Must be B, M or T. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2161: Must be L, C or R.

| Text | Must be L, C or R. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2162: No graph on overlay.

| Text | No graph on overlay. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2163: Must be B, T or N.

| | Must be B, T or N. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2164: Invalid value.

Text Invalid value.

Expl. Check program and correct error.

NAT2165: Must be L, R or N.

TextMust be L, R or N.Expl.Check program and correct error.

NAT2166: Valid only for LINE or SURFACE graphs.

TextValid only for LINE or SURFACE graphs.Expl.Check program and correct error.

NAT2167: FROM and TO values required (or neither).

Text FROM and TO values required (or neither).

Expl. Check program and correct error.

NAT2168: FROM must be less than TO value.

| | FROM must be less than TO value. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2169: Work field/lookup field not allowed.

| Text | Work field/lookup field not allowed. |
|-------|--------------------------------------|
| Expl. | Check program and correct error. |

NAT2170: Field must be in the primary file.

| Text | Field must be in the primary file. |
|-------|------------------------------------|
| Expl. | Check program and correct error. |

NAT2171: No ranges specified.

| 1 | No ranges specified. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2172: Page width exceeded.

| | Page width exceeded. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2173: Don"t specify both CHARACTERS and INCREMENT.

| Text | Don"t specify both CHARACTERS and INCREMENT. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2174: Invalid CHARACTERS value.

| | Invalid CHARACTERS value. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2175: Increment not allowed for non-numeric field.

| Text | Increment not allowed for non-numeric field. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2176: Invalid increment value.

| Text | Invalid increment value. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2177: Overlapping ranges.

| | Overlapping ranges. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2178: Invalid range start value.

Text Invalid range start value.

Expl. Check program and correct error.

NAT2179: Invalid range end value.

TextInvalid range end value.Expl.Check program and correct error.

NAT2180: End value must not be before start value.

| Text | End value must not be before start value. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2181: Select at least one system function.

TextSelect at least one system function.Expl.Check program and correct error.

NAT2182: Name or reference must be entered.

| Text | Name or reference must be entered. |
|-------|------------------------------------|
| Expl. | Check program and correct error. |

NAT2183: Must be O, B, E, or P.

| Text | Must be O, B, E, or P. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2184: Mode not allowed.

| | Mode not allowed. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2185: Must be in range 1 - 32.

| | Must be in range 1 - 32. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2186: Must be D, T, G, I, or W.

| | Must be D, T, G, I, or W. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2187: You are not authorized for this destination.

| | You are not authorized for this destination. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2188: Run mode and destination are incompatible.

| | Run mode and destination are incompatible. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2189: Destination not allowed for batch use.

| Text | Destination not allowed for batch use. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2190: Destination not allowed for online use.

| Text | Destination not allowed for online use. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2191: Invalid operator.

| Text | Invalid operator. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2192: Value(s) missing.

| | Value(s) missing. |
|-------|----------------------------------|
| Actn. | Check program and correct error. |

NAT2193: Two values required for BT or OU.

| | Two values required for BT or OU. |
|-------|-----------------------------------|
| Expl. | Check program and correct error. |

NAT2194: One value only allowed.

| | One value only allowed. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2195: Value is too long.

| | Value is too long. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2196: Sort level already used.

| | Sort level already used. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2197: May not be a sort field.

| | May not be a sort field. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2198: Phonetic key cannot be used.

| Text | Phonetic key cannot be used. |
|-------|---------------------------------|
| Expl. | Check program and correct error |

NAT2199: Group field must not be used in vertical display.

| Text | Group field must not be used in vertical display. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2200: No help page specified - please try again.

| | No help page specified - please try again. |
|-------|--|
| Expl. | Check program and correct error. |

44 Natural System Error Messages 2201-2250

NAT2201: Invalid selection - please try again.

| | Invalid selection - please try again. |
|-------|---------------------------------------|
| Expl. | Check program and correct error. |

NAT2202: Prefix must be entered.

| | Prefix must be entered. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2203: Library ID must be entered.

| | Library ID must be entered. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2204: TO may not be the same as FROM.

| | TO may not be the same as FROM. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2205: Object overflow - cannot continue copy function.

| Text | Object overflow - cannot continue copy function. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2206: No qualifying transaction found.

| Text | No qualifying transaction found. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2207: Line number invalid.

| | Line number invalid. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2208: ONLINE or BATCH must be allowed.

| | ONLINE or BATCH must be allowed. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2209: Must be O, B or blank (default).

| | Must be O, B or blank (default). |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2210: Must be in range 1 - 191 or zero (default).

Text Must be in range 1 - 191 or zero (default).Expl. Check program and correct error.

NAT2211: Must be in range 1 - 99 or zero (default).

| | Must be in range 1 - 99 or zero (default). |
|-------|--|
| Expl. | Check program and correct error. |

NAT2212: User not found.

| Text | User not found. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2213: Must be in range 1 - 31.

| | Must be in range 1 - 31. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2214: Help ID required.

| | Help ID required. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2215: Invalid ID format.

| Text | Invalid ID format. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2216: Description required.

| | Description required. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2217: Must be specified.

TextMust be specified.Expl.Check program and correct error.

NAT2218: May not be the same as private library prefix.

| Text | May not be the same as private library prefix. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2219: Must be Y, N, O, or B.

| Text | Must be Y, N, O, or B. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2220: Must be O or B.

| Text | Must be O or B. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2221: Must be E, A, G, I, or N.

| | Must be E, A, G, I, or N. |
|-----|-----------------------------------|
| Exp | . Check program and correct error |

NAT2222: Copy failed - hit ENTER to try again.

| | Copy failed - hit ENTER to try again. |
|-------|---------------------------------------|
| Expl. | Check program and correct error. |

NAT2223: File not found.

| Text | File not found. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2224: Object invalid.

| 1 | Object invalid. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2225: This function is not available for the selected object.

| Text | This function is not available for the selected object. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2226: Object name/ID required.

| | Object name/ID required. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2227: User ID must not exceed 7 characters.

| Text | User ID must not exceed 7 characters. |
|-------|---------------------------------------|
| Expl. | Check program and correct error. |

NAT2228: User already present.

TextUser already present.Expl.Check program and correct error.

NAT2229: File already present.

TextFile already present.Expl.Check program and correct error.

NAT2230: File not defined under Natural Security.

| Text | File not defined under Natural Security. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2231: Number already used.

TextNumber already used.Expl.Check program and correct error.

NAT2232: ID must not exceed 9 characters.

| Text | ID must not exceed 9 characters. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2233: ID already present.

| Text | ID already present. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2234: ID not found.

| Text | ID not found. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2235: This function is not available for superfiles.

| Text | This function is not available for superfiles. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2236: This function is not available for transactions.

| | This function is not available for transactions. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2237: Must be in range 1 - 9.

| | Must be in range 1 - 9. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2238: Never change *-characters.

| | Never change *-characters. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2239: Record-type format must be entered.

| | Record-type format must be entered. |
|-------|-------------------------------------|
| Expl. | Check program and correct error. |

NAT2240: Invalid format.

| Text | Invalid format. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2241: Record-type length must be entered.

| | Record-type length must be entered. |
|-------|-------------------------------------|
| Expl. | Check program and correct error. |

NAT2242: Record-type value must be entered.

| Text | Record-type value must be entered. |
|-------|------------------------------------|
| Expl. | Check program and correct error. |

NAT2243: Value must be numeric.

| | Value must be numeric. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2244: Value is too long.

| | Value is too long. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2245: Subfield offset must be entered.

TextSubfield offset must be entered.Expl.Check program and correct error.

NAT2246: Subfield format must be entered.

| Text | Subfield format must be entered. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2247: Record type overrides subfield.

| | Record type overrides subfield. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2248: Exit library must be entered.

| | Exit library must be entered. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2249: Exit program must be entered.

| | Exit program must be entered. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2250: Exit location must be entered.

| Text | Exit location must be entered. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

45 Natural System Error Messages 2251-2300

NAT2251: Exit location out of range 1 - 5.

TextExit location out of range 1 - 5.Expl.Check program and correct error.

NAT2252: Selection criteria must be entered.

| | Selection criteria must be entered. |
|-------|-------------------------------------|
| Expl. | Check program and correct error. |

NAT2253: Please use a PF-key to continue.

| | Please use a PF-key to continue. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2254: Unacceptable change - must be left as B.

| Text | Unacceptable change - must be left as B. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2255: Must be BLANK (DON"T), "B" (BEFORE) or "A" (AFTER).

| Text | Must be BLANK (DON"T), "B" (BEFORE) or "A" (AFTER). |
|------|---|
| Expl | Check program and correct error. |

NAT2256: No field in secondary file with same name as primary field.

| Text | No field in secondary file with same name as primary field. |
|------|---|
| Expl | . Check program and correct error. |

NAT2257: Invalid mode.

| Text | Invalid mode. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2258: Must be in range 0 - 254.

| Text | Must be in range 0 - 254. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2259: Must be in range 0 - 255.

| | Must be in range 0 - 255. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2260: Transaction type and destination are incompatible.

| | Transaction type and destination are incompatible. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2261: Report type and report level are incompatible.

| Text | Report type and report level are incompatible. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2262: Selection mode and run mode are incompatible.

| Text | Selection mode and run mode are incompatible. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2263: Change mode and run mode are incompatible.

| Text Change mode and run mode are | incompatible. |
|-----------------------------------|---------------|
|-----------------------------------|---------------|

Expl. Check program and correct error.

NAT2264: Transaction type and run mode are incompatible.

| Text | Transaction type and run mode are incompatible. |
|------|---|
| г 1 | |

Expl. Check program and correct error.

NAT2265: Run mode and report type are incompatible.

| Text | Run mode and report type are incompatible. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2266: Run mode and destination are incomaptible.

| Text | Run mode and destination are incomaptible. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2267: Change mode and destination are incompatible.

| | Change mode and destination are incompatible. |
|---------|---|
| Terra 1 | Charle and some at some at |

Expl. Check program and correct error.

NAT2268: Report type and destination are incompatible.

| Text | Report type and destination are incompatible. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2269: Unacceptable mode change.

| Text | Unacceptable mode change. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2270: You are not authorized for this transaction type.

| Text | You are not authorized for this transaction type. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2271: You are not authorized for this transaction selection mode.

| Text | You are not authorized for this transaction selection mode. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2272: You are not authorized for this transaction change mode.

| Text | You are not authorized for this transaction change mode. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2274: You are not authorized for this transaction"s destination.

| Text | You are not authorized for this transaction's destination. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2275: You are not authorized for this transaction"s report level.

| | You are not authorized for this transaction"s report level. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2276: You are not authorized to use online transactions.

| Text | You are not authorized to use online transactions. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2277: You are not authorized for batch transactions.

| Text | You are not authorized for batch transactions. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2278: This is not a fixed-format mode transaction.

| Text | This is not a fixed-format mode transaction. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2279: You are not authorized to run batch transactions.

| | You are not authorized to run batch transactions. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2280: No user files available within your allocation.

| | No user files available within your allocation. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2281: User file number greater than maximum allocated.

| | User file number greater than maximum allocated. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2282: User file already in use.

TextUser file already in use.Expl.Check program and correct error.

NAT2283: User file does not exist.

| Text | User file does not exist. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2284: File name required.

| Text | File name required. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2285: File number or name required.

| | File number or name required. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2286: File name is not unique.

| | File name is not unique. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2287: You have no user files in use.

| Text | You have no user files in use. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2288: Invalid file name format.

| | Invalid file name format. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2289: Expiry date reached; file not accessible.

| Text | Expiry date reached; file not accessible. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2290: Sequence number already used.

| | Sequence number already used. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2291: Field may not be selected for data change.

| | Field may not be selected for data change. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2292: Invalid sequence number.

| | Invalid sequence number. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2293: Sequence number already used.

Text Sequence number already used.

Expl. Check program and correct error.

NAT2294: Field may not be selected for extract.

Text Field may not be selected for extract.

Expl. Check program and correct error.

NAT2295: Report level and destination are incompatible.

| Text | Report level and destination are incompatible. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2296: Invalid option code.

TextInvalid option code.Expl.Check program and correct error.

NAT2297: Field may not be a key.

| Text | Field may not be a key. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2298: Lookup not allowed for this transaction type.

| Text | Lookup not allowed for this transaction type. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2299: Requested function has been executed.

| | Requested function has been executed. |
|-------|---------------------------------------|
| Expl. | Check program and correct error. |

NAT2300: Must be D.

| Text | Must be D. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

46 Natural System Error Messages 2301-2350

NAT2301: Blank character not allowed in field name.

| Text | Blank character not allowed in field name. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2302: Invalid character in field name.

| | Invalid character in field name. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2303: Format must be specified.

| | Format must be specified. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2304: Length must be specified.

| Text | Length must be specified. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2305: Format not allowed without name.

| Text | Format not allowed without name. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2306: Length not allowed without name.

| Text | Length not allowed without name. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2307: Invalid format code.

| | Invalid format code. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2308: Invalid length specification.

| | Invalid length specification. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2309: Maximum alphanumeric field length is 253.

| | Maximum alphanumeric field length is 253. |
|-----|---|
| Exp | . Check program and correct error. |

NAT2310: Decimal positions not allowed for alphanumeric field.

| Text | Decimal positions not allowed for alphanumeric field. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2311: Maximum integer length is 20.

| | Maximum integer length is 20. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2312: Maximum for decimal positions is 7.

| | Maximum for decimal positions is 7. |
|-------|-------------------------------------|
| Expl. | Check program and correct error. |

NAT2313: Sequence number must be specified.

| Text | Sequence number must be specified. |
|-------|------------------------------------|
| Expl. | Check program and correct error. |

NAT2314: Sequence number already used.

| | Sequence number already used. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2315: Invalid Library ID.

| Text | Invalid Library ID. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2316: Invalid program ID.

| Text | Invalid program ID. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2317: Invalid exit location code.

TextInvalid exit location code.Expl.Check program and correct error.

NAT2318: Line cannot be inserted.

| | Line cannot be inserted. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2319: Must be R.

| Text | Must be R. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2320: Field does not exist.

| Text | Field does not exist. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2321: Field is not a primary file.

| | Field is not a primary file. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2322: Field may not be used as a link field.

| | Field may not be used as a link field. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2323: Field is not in secondary file.

| | Field is not in secondary file. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2324: Secondary file link field must be a key field.

| | Secondary file link field must be a key field. |
|-----|--|
| Exp | l. Check program and correct error. |

NAT2325: Subfield length less than permitted for this file.

| Text | Subfield length less than permitted for this file. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2326: Secondary field shorter than primary field.

| Text | Secondary field shorter than primary field. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2327: Name length must not be less than 3.

| Text | Name length must not be less than 3. |
|------|--------------------------------------|
| - 1 | |

Expl. Check program and correct error.

NAT2328: No add or delete of fields in field line possible

| Te | xt | No | add | or delete | of fiel | ds in i | field lin | e possible | e |
|----|----|----|-----|-----------|---------|---------|-----------|------------|---|
| - | 1 | 01 | | | | | | | |

Expl. Check program and correct error

NAT2329: Index required for non-key multiple/periodic field.

| Text | Index required for non-key multiple/periodic field. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2330: Please enter one of the options.

| | Please enter one of the options. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2331: No selection criteria with current selection mode.

TextNo selection criteria with current selection mode.

Expl. Check program and correct error.

NAT2332: No fields have been selected.

| Text | No fields have been selected. |
|-------|----------------------------------|
| Actn. | Check program and correct error. |

NAT2333: Current transaction does not have data change.

| Text | Current transaction does not have data change. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2334: No output fields have been chosen.

| Text | No output fields have been chosen. |
|-------|------------------------------------|
| Expl. | Check program and correct error. |

NAT2335: Current transaction is not extract type.

| | Current transaction is not extract type. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2336: Mode change not available.

| Text Mode change not available. | |
|---------------------------------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2337: Command not appropriate to current transaction modes.

| Text | Command not appropriate to current transaction modes. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2338: No vertical fields allowed with REPORT EDITOR

| Text | No vertical fields allowed with REPORT EDITOR |
|-------|---|
| Expl. | Check program and correct error |

NAT2340: ACCEPT/REJECT not when FLATTENING BEFORE; Log. Stmt.:

| Text | ACCEPT/REJECT not when FLATTENING BEFORE; Log. Stmt.: |
|-------|---|
| Expl. | Check program and correct error. |

NAT2341: Key sequence number already used.

| Text | Key sequence number already used. |
|------|-----------------------------------|
| | |

Expl. Check program and correct error.

NAT2342: Don"t enter a start value without key reference.

| Text Don"t enter a start value without key reference | e. |
|--|----|
|--|----|

Expl. Check program and correct error.

NAT2343: Don"t enter an end value without key reference.

| Text Don"t e | enter an end value without key reference. |
|--------------|---|
|--------------|---|

Expl. Check program and correct error.

NAT2344: Invalid field reference.

| 1 | | Invalid field reference. |
|---|-------|---------------------------------|
| | Expl. | Check program and correct error |

NAT2345: Field is not a key.

TextField is not a key.Expl.Check program and correct error.

NAT2346: READ BY KEY not permitted on this field.

 Text
 READ BY KEY not permitted on this field.

Expl. Check program and correct error.

NAT2347: End value not permitted for this key.

| Text End value not permitted for this | |
|---------------------------------------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2348: Start value must be numeric for this key.

| | Start value must be numeric for this key. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2349: End value must be numeric for this key.

| 1 | End value must be numeric for this key. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2350: Start value longer than field length.

| Text | Start value longer than field length. |
|-------|---------------------------------------|
| Expl. | Check program and correct error. |

47 Natural System Error Messages 2351-2400

NAT2351: End value longer than field length.

| Text | End value longer than field length. |
|-------|-------------------------------------|
| Expl. | Check program and correct error. |

NAT2352: End value must not be lower than start value.

| Text | End value must not be lower than start value. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2353: Invalid start value.

| | Invalid start value. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2354: Invalid end value.

| Text | Invalid end value. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2355: .

| Expl. Che | ck program and correct error |
|-----------|------------------------------|
|-----------|------------------------------|

NAT2357: Minimum edit mask length of 6 characters required for COUNT.

| Text | Minimum edit mask length of 6 characters required for COUNT. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2358: Minimum output length of 6 characters required for COUNT.

| Text | Minimum output length of 6 characters required for COUNT. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2359: No control fields specified for report level SUMMARY.

| Text | No control fields specified for report level SUMMARY. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2360: Error in selection criteria line:

| Text | Error in selection criteria line: |
|-------|-----------------------------------|
| Expl. | Check program and correct error. |

NAT2361: Error in selection criteria.

| Text E | Error in selection criteria. |
|--------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2362: Selection criteria incomplete.

| | Selection criteria incomplete. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2363: No selection criteria entered.

| Text No selection criteri | No selection criteria entered. |
|---------------------------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2364: Entire file must be read to satisfy your selection criteria.

| Text | Entire file must be read to satisfy your selection criteria. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2365: - This is not allowed.

| Text | - This is not allowed. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2366: Error in calculation line.

| Text | Error in calculation line. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2367: Calculations incomplete.

TextCalculations incomplete.Expl.Check program and correct error.

NAT2368: Error in logic statement number.

TextError in logic statement number.Expl.Check program and correct error.

NAT2369: Report specification contains error(s) on page:

| Text | Report specification contains error(s) on page: |
|-------|---|
| Expl. | Check program and correct error. |

NAT2370: Field specification contains error(s) on page:

| | Field specification contains error(s) on page: |
|-------|--|
| Expl. | Check program and correct error. |

NAT2371: Data change specification contains error(s) on page:

| Text | Data change specification contains error(s) on page: |
|-------|--|
| Expl. | Check program and correct error. |

NAT2372: Extract specification contains error(s) on page:

| Text | Extract specification contains error(s) on page: |
|-------|--|
| Expl. | Check program and correct error. |

NAT2373: No system functions (SUM etc.) for control break output.

| - L | | No system functions (SUM etc.) for control break output. |
|-----|-------|--|
| ſ | Expl. | Check program and correct error. |

NAT2374: Error in tabular report specification.

| | Error in tabular report specification. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2375: GRAPH report type selected but no graph specified.

Text GRAPH report type selected but no graph specified.Expl. Check program and correct error.

NAT2376: Graph definition error for graph number:

| | Graph definition error for graph number: |
|-------|--|
| Expl. | Check program and correct error. |

NAT2377: Input fields contain error(S) on page:

| Text | Input fields contain error(S) on page: |
|-------|--|
| Expl. | Check program and correct error. |

NAT2378: Number of errors =

| Text | Number of errors = |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2379: Maximum records may not exceed:

| - 1 | | Maximum records may not exceed: |
|-----|-------|----------------------------------|
| | Expl. | Check program and correct error. |

NAT2380: Tabular report type selected but no tabular data specified.

| Text | Tabular report type selected but no tabular data specified. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2381:.

Expl. Check program and correct error.

NAT2382:.

Expl. Check program and correct error

NAT2385: User-file directory record not found.

| | User-file directory record not found. |
|-------|---------------------------------------|
| Expl. | Check program and correct error. |

NAT2386: CMDDP error.

| Text | CMDDP error. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2388: Field must not be a key.

| | Field must not be a key. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2389: No more fields allowed.

| | No more fields allowed. |
|-------|----------------------------------|
| Expl. | Check program and correct error. |

NAT2390: Transaction type and change mode are incompatible.

| | Transaction type and change mode are incompatible. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2391: Selection mode and destination are incompatible.

| Text | Selection mode and destination are incompatible. |
|-------|--|
| Expl. | Check program and correct error. |

NAT2392: Change mode and report type are incompatible.

| Text | Change mode and report type are incompatible. |
|-------|---|
| Expl. | Check program and correct error. |

NAT2400: Function:1:interrupted.

| Text | Function:1:interrupted. |
|------|---|
| Expl | The execution of the last function was stopped with a PF key. |

48

Natural System Error Messages 2401-2450

NAT2401: Function:1:terminated normally.

Text Function:1: terminated normally.

NAT2402: No xref data for this selection available.

Text No xref data for this selection available.

NAT2403: Type of referenced program and invoking mode do not match.

| Text | Type of referenced program and invoking mode do not match. |
|-------|--|
| Expl. | Valid combinations: |
| | Natural program: FETCH, RUN, STACK, FETCH RETURN |
| | Subprogram: CALLNAT |
| | Subroutine: PERFORM |
| | Helproutine: HELP |
| | Map: MAP |
| | External Program: CALL |
| | Expert model: INVESTIGATE |

NAT2404: Program:1:of type:2:not found.

Text Program:1:of type:2:not found.

NAT2405: Enter a valid:1:.

Text Enter a valid:1:.

NAT2406: Error on data base. Adabas response code:1:.

| Text | Error on data base. Return code =:1:. |
|-------|---------------------------------------|
| Expl. | An Adabas response code was received. |

NAT2407: Program type and data area type do not match.

| | Program type and data area type do not match. |
|-------|---|
| Expl. | A parameter data area can only occur in a subprogram. |

NAT2408: Data area:1:of type:2:not found.

Text Data area:1:of type:2:not found.

NAT2409: Valid input for:1:::2:.

Text Valid input for:1:::2:.

NAT2410: Warning::1::2:.

| Text | Warning::1::2:. |
|-------|---|
| Expl. | A function was not executed completely due to an internal error |
| | or internal restrictions. |

NAT2411: Internal table overflow during:1:.

| Text | Internal table overflow during:1:. |
|-------|---|
| Expl. | There are two different situations, where this message my appear: 1. The function "list programs not referenced starting from one program" has some restrictions concerning the number of objects which can be handled. The message specifies the concerned retrieval object. 2. In the function "operate on sets" the result of any union or intersection operation may not exceed 9999 records (approximate 600000 members). |

NAT2412: Shortage of sort space. Restrict search. Object::2:.

| Text | Shortage of sort space. Restrict search. Object::1:. |
|-------|---|
| Expl. | The output may be not completely sorted due to shortage of internal |
| | sort space. The message specifies the concerned retrieval object. |

NAT2413: No:1:found.

Text No:1:found.

NAT2414: Syntax error in command line.

| Text | Syntax error in command line. |
|-------|---|
| Expl. | The text entered in the command line was no valid LIST XREF |
| | command. |

NAT2415: Function not available for library:1:.

| Text | Function not available for library:1: |
|-------|---|
| Expl. | The function is only applicable to Natural libraries. |

NAT2416: Please select reports.

| Text | Please select reports. |
|-------|---|
| Expl. | At least one report must be selected for this function. |
| Actn. | Select report. |

NAT2417: PF key is already assigned.

| Text | PF key is already assigned. |
|-------|---|
| Expl. | The PF key is already assigned to another function. |
| Actn. | Assign a different PF key to this function. |

NAT2418: PF key is assigned for function "Show PF keys".

| Text | PF key is assigned to function "Show PF keys". |
|-------|---|
| | The PF key is already assigned to the function "Show PF keys". If the function "Show PF keys" is assigned to one PF key, it will be automatically assigned to the corresponding PF key on the other level. |
| Actn. | Select other PF key. |

NAT2419: Command not allowed in online mode.

| Text | Command not allowed in online mode. |
|-------|--|
| Expl. | The selected command can only be used in batch mode. |

NAT2420: Valid values: *SYSCOB*, *SYSBAL*, *SYSPLI* and *SYSFOR*.

| Text | Valid values: *SYSCOB* , *SYSBAL* , *SYSPLI* and *SYSFOR* . |
|-------|---|
| Expl. | An invalid value was entered for the library name. |
| Actn. | Enter a valid value. |

NAT2421: Profile:1:updated.

TextProfile:1:updated.Expl.The function "Update profile" terminated successfully.

NAT2422: Updated profile is valid only for this session.

| Text | Updated profile is valid only for this session. |
|------------|---|
| _ _ | The updated user profile is valid only for this session because the user is not defined in Predict. |
| Actn. | Ask the Data Dictionary Administrator to define your user ID in Predict. |

NAT2423: Profile saved with name:1:.

| Text | Profile saved with name:1:. |
|-------|--|
| Expl. | The updated profile is saved in Predict under this name. |

NAT2424: Help displayed.

| Text | Help displayed. |
|-------|--------------------------------|
| Expl. | The Help system has been used. |

NAT2425: Function:1:terminated with error.

| Text | Function:1:terminated with error. |
|-------|--|
| Expl. | The execution of function was terminated with error. |
| Actn. | Check error and reexecute function. |

NAT2426: Profile with name:1:not found.

| Text | Profile with name:1:not found. |
|-------|--|
| Expl. | The selected profile was not found in Predict. |
| Actn. | Select other profile. |

NAT2427: Entered command is ambiguous.

| Text | Entered command is ambigous. |
|-------|--|
| · · | The entered command could not be uniquely identified by the command processor. |
| Actn. | Correct the command. |

NAT2428: Active library structure is::1:.

| Text | Active library structure is::1:. |
|------|---|
| | This message is shown to inform about the currently active library structure which is set in the LIST XREF profile of an user or the default profile. |

NAT2429: :1:set(s) marked with:2:.

| Text | :1:set(s) marked with:2:. |
|-------|---|
| Expl. | The listed number of sets is marked with the listed operation. |
| | To finish the operation, mark a second with "X" or "Y" if a set is already marked with "Y" or "X" or confirm the action with the corresponding PF-KEY is two or more sets marked with "U" or "I". |

NAT2430: Name of startup program must be entered for this function.

| Text | Name of startup program must be entered. |
|-------|--|
| Expl. | This function checks for programs references / implementation starting with the specified program. |
| Actn. | Enter the program name. |

NAT2432: Set not saved. Error in editor:1:.

| Text | Set not saved. Error in editor. |
|------|--|
| | An internal error occurred in the handling of the Natural editor. The set could not be saved. |
| | The set could not be saved. |

NAT2434: Resulting set is empty.

| Text | Resulting set is empty. |
|-------|---|
| Expl. | The result of executed operations was empty. Set has not been saved |
| | in Predict. |

NAT2435: Set nr:1:has been saved.

| Text | Set is saved. |
|-------|---|
| Expl. | The result of the executed function has been saved in Predict |
| | for later operation. |

NAT2436: Operations terminated normally.

Text Operations terminated normally.

NAT2437: User is not defined in Predict. Set can not be saved.

| Text | This option requires that the user is defined in Predict. |
|-------|--|
| | You attempted to save the result of a LIST XREF function in Predict. This is only possible if your user ID is defined in Predict. |
| Actn. | Ask the Data Dictionary Administrator to define your user ID in Predict. |

NAT2438: Maximum number of sets exist. A new set can not be created.

| Text | Maximum number of sets exist. A new set can not be created. |
|-------|--|
| Expl. | Since Predict version 4.4.1, up to 99 sets can exist at the same |
| | time per user and application. |
| | With Predict versions below 4.4.1, up to 12 sets can exist at the same |
| | time per user and application. |
| Actn. | Purge sets that are no longer needed. |

NAT2439: *-notation is not allowed for this function.

| Text | *-notation is not allowed for this function. |
|-------|--|
| Actn. | Enter a complete program name. |

NAT2440: :1:keyword not defined.

| Text | Keyword is not defined. |
|-------|---|
| | A keyword must exist within the dictionary before it can be assigned to other dictionary objects. |
| Actn. | Enter a valid keyword or define the keyword in Predict. |

NAT2441: Invalid:1:.

| Text | Invalid object. |
|-------|---|
| Expl. | An attempt was made to reference a nonexisting object type. |
| Actn. | Enter a correct object type. |

NAT2442: From map editor only verification status free allowed.

| Text | For map editor only verification status free allowed. |
|-------|---|
| | It was tried to define a verification with a status other than "free". Only free processing rules can be defined from within the map editor. |
| Actn. | Enter status "free". |

NAT2443: No set found.

| Text | No set found. |
|------|---|
| | Sets of Natural members can be created using several LIST XREF functions. At the moment, no set exists in this application under your user ID. |

NAT2444: Only 24 keywords supported.

| Text | Only 24 keywords supported. |
|------|--|
| 1 1 | It is not possible to enter more than 24 keywords for one Predict entry. |

NAT2445: Duplicate keywords defined.

| Text | Duplicate keywords are entered. |
|------|---|
| - | It is not possible to enter the same keyword twice for one Predict entry. |

NAT2446: Userexit activated, but not available in SYSLIB.

| Text | User exit activated, but not available in SYSLIB. |
|-------|--|
| Expl. | In the "Special functions" of Predict, the user exit for the maintenance of verifications from within the map editor was activated, but the user exit program is not available in SYSLIB. |
| Actn. | Copy the program SUMPRDEX to SYSLIB. |

NAT2447: More than 1 set exists, but no set number was specified.

| Text | More than one set exists, but no set number was specified. |
|-------|---|
| Expl. | There is more than one set saved for this user. The number of |
| | the set to be catalogued or stowed must be specified. |

NAT2448: Please enter a valid value: "CATALOG" or "STOW".

Text Please enter valid value.

Expl. Valid values are "CATALOG" and "STOW".

NAT2449: Specified set number not found.

Text Specified set number not found.

NAT2450: Specified startup program not found in application.

Text Specified startup program not found in application.

49

Natural System Error Messages 2451-2500

NAT2451: Please enter startup program name.

| Text | Please enter startup program name. | |
|-------|--|--|
| Expl. | For this function the name of a startup program is required. | |

NAT2452: Please mark only one restriction.

Text Please mark only one restriction.

NAT2453: Rule status and rule usage do not match.

| Text | Rule status and rule usage do not match. |
|------|---|
| | An automatic processing rule can also be used as free rule, |
| | but for free rules status and usage are always the same. |

NAT2454: Target user ID has max. no. of sets.Function can not be executed.

| Text | Target user ID has maximum number of sets. Function can not be executed. |
|------|--|
| | Since Predict version 4.4.1, up to 99 sets can exist at the same time per user and application. With Predict versions below 4.4.1, up to 12 sets can exist at the same time per user and application. |
| | Before using the function, make sure that the target user does not have more than 99 sets stored for this application. |

NAT2455: Mode "Invoke return" only valid with functions "E", "I", "X", "Y".

| Text | Mode "Invoke return" only valid with functions "E", "I", "X", "Y". |
|-------|--|
| Expl. | The invoking mode "Invoke return" comprises all invoking modes that return control to the invoking program, i. e. CALL, CALLNAT, PERFORM, FETCH RETURN, HELP, MAP, STATIC SQL, INVESTIGATE. It is used to restrict the output of the recursive reports. |

NAT2456: Please enter "W" for stow or "C" for catalog.

Text Please enter "W" for stow or "C" for catalog.

NAT2457: Invalid option.

| Text | Invalid option. |
|-------|-------------------------|
| Actn. | Enter a correct option. |

NAT2458: No set to process found.

Text No set to process found.

NAT2459: No set found.

| Text | No set found. |
|-------|--|
| Expl. | Sets of Natural members can be created using several LIST XREF |
| | functions. |
| | At the moment, no set exists in this application for your |
| | user ID. |

NAT2460: User is not defined in Predict. Function is not possible.

| Text | User is not defined in Predict. Function is not possible. |
|-------|--|
| - | This function can only be executed if your user ID is defined in Predict. |
| Actn. | Contact your Data Dictionary Administrator. |

NAT2461: No object type to be verified marked.

| Text | No object to be verified marked. |
|-------|---|
| Expl. | The function can only be executed if objects to be verified are marked in the currently active profile. In batch the used profile can be specified using the command LIST XREF PROFILE <user id="">, otherwise the SYSTEM profile will be used.</user> |
| Actn. | Mark objects to be verified in the LIST XREF profile. |

NAT2462: Warning: Table is full, new set can not be saved or created.

| | Text | Warning: table is full, new set can not be saved or created. |
|--|------|---|
| Durge sets which are no longer needed. | 1 | There is a maximum of 99 sets per library and user. Before creating new set with the "UNION", "INTERSECTION" or "DIFFERENCE" operation purge sets which are no longer needed. |

NAT2463: Specification is not allowed.

| Text | Specification is not allowed. |
|-------|---|
| Expl. | Entered function and specifications are not compatible. |
| Actn. | Check entered parameter. |

NAT2464: If status = "A" only format "A", "B" or "N" allowed.

| Text | If status = "A" only format "A", "B" or "N" allowed. |
|-------|---|
| | The Format of AUTOMATIC RULES, which are connected to fields, must be "A", "N" or "B", because the field formats "L", "D" and "K" in Predict not allowed. |
| Actn. | Change format. |

NAT2465: If you want to edit rules, rule format must be entered.

| Text | If you want to edit rules, rule format must be entered. |
|-------|--|
| | The rules are only be activated, if the format of the rule and the field format are compatible. |
| Actn. | Enter rule format. |

NAT2466: Rule format must be "A", "N", "B", "D" OR "K".

| Text | Rule format must be "A", "N", "B", "D" OR "K". |
|-------|--|
| Expl. | A rule must have one of this formats: A - Alpha-numeric |
| | N - Numeric B - Binary D - Date/Time K - Function key |
| Actn. | Enter correct rule format. |

NAT2467: :1:set(s) exist.

Text The given number of sets exist in this application under your user ID.

NAT2470: For a free rule at least one modifier required.

| Text | For a free rule at least one modifier required. |
|-------|--|
| | The DDA has set one of the rule protection switches to "force". For MIGRATION utility this message is only a warning. |
| Actn. | For MIGRATION utility: add later the required modifier to the verification. |

NAT2471: User/Group:1: is not defined in Natural Security.

| Text | The marked user or group is not defined in Natural Security. |
|-------|--|
| Expl. | All modifiers of a free rule must be defined in Natural Security. |
| Actn. | Define user or group in Natural Security before using it in Predict or correct name. |

NAT2472: :1:not allowed for this:2:.

| Text | Object of this type not allowed in this case. |
|-------|--|
| Actn. | Select one type shown in the pop-up-menu, or change function-code. |

NAT2473: You are not in the list of modifiers.

| Text | You are not in the list of modifiers. |
|-------|---|
| Expl. | If modifiers are entered then you must be member of the list. |
| Actn. | Enter correct language. |

NAT2474: Function not allowed for this language.

| Text | Function not allowed for this language. |
|------|--|
| | Function "DISPLAY" (D) and "RENAME" (N)" not allowed for DDM, SUPER Natural and Verification rule. |

NAT2475: Sets are sorted differently.

| Text | Sets are sorted differently. |
|-------|--|
| - | All sets included in the set operation should be sorted in the |
| | same manner (e.g either by name or by type). |
| Actn. | Sort all sets by name or by type. |

NAT2476: Function not supported in this Natural version.

| Text | Function not supported in this Natural version. |
|-------|---|
| | Functions are only supported in Natural V2: - Generate Verification rules - Edit rule of verification |
| Actn. | Contact your DDA. |

NAT2477: ADAMINT not installed.

| Text | ADAMINT not installed. |
|-------|--|
| Expl. | ADAMINT is a "selectable unit", which may not be available in your installation. |
| Actn. | Please contact your DBA. |

NAT2478: Invalid edit command: EDIT "object1" "object2".

| Text | Invalid edit command: EDIT "object1" "object2". |
|-------|---|
| Expl. | Function EDIT "object1" of "object2" not implemented. |
| Actn. | Change function or correct command. |

NAT2479: Invalid object: for command.

| Text | Invalid object: for command. |
|-------|--|
| Expl. | The direct command is not allowed in connection to the entered object. |
| Actn. | Change direct command. |

NAT2480: No format, length allowed for 2. redefinition.

| Text | No format, length allowed for 2. redefinition. |
|-------|---|
| Expl. | If multiple redefinitions of a field exist (field-type = "RE" and field-name = "FILLER") no format and length definitions allowed. The format and length definitions of the basic field are already valid. |
| Actn. | Delete format and length definitions. |

NAT2481: Starting position out of field.

| Text | Starting position out of field. |
|---|---------------------------------------|
| Expl. The starting position of an VSAM primary key or alter is out of the source field. | |
| Actn. | Correct error or change source field. |

NAT2482: Source field format "F" or "I" not allowed.

| Text | Source field format "F" or "I" not allowed. |
|-------|--|
| Expl. | The field formats "F" or "I" are not valid in Adabas V4.1. |
| Actn. | Change descriptor or change source field format. |

NAT2483: Only one MU-field as source field allowed.

| Text | Only one MU-field as source field allowed. |
|-----------------------------|---|
| Expl. Only one source field | Only one source field of a superdescriptor can be of field type "MU". |
| Actn. | Change the superdescriptor |

NAT2484: One source field must be entered.

| Text | One source field must be entered. |
|-------|--|
| Expl. | One and only one source field must entered to a sub- or phonetic- descriptor. |
| Actn. | Enter name of source field |

NAT2485: Related file deleted.

| Text | Related file deleted. | |
|-------|---|--|
| Expl. | l. If a MASTER file (FILE TYPE Adabas or VSAM) is replaced by the MIGRATE | |
| | utility, the old related USER VIEWS will be deleted. | |

NAT2486: A rule of status "A" may not be replaced

| Text | A rule of status "A" may not be replaced |
|-------|---|
| Expl. | with a rule of status "F" or BLANK. |
| Actn. | The loading of this verification is rejected. |

NAT2487: Migration utility failed by error.

| Text | Migration utility failed by error. |
|-------|------------------------------------|
| Expl. | Check message and correct error. |

NAT2488: Internal error in "program". Restart with "MENU".

| Text Internal error in "program". Restart with "N | |
|---|----------------------|
| Expl. | Restart with "MENU". |

NAT2489: Owner/keyword not allowed for unload keywords.

| Text | Owner/keyword not allowed for unload keywords. |
|-------|--|
| Expl. | Correct error |

NAT2490: Only all-option "N" allowed for object "ALL".

| Text | Only all-option "N" allowed for object "ALL". |
|-------|---|
| Expl. | Correct error |

NAT2491: Code "Y" not allowed for command "VERSIONS".

| Text | Code "Y" not allowed for command "VERSIONS". |
|-------|--|
| Expl. | Correct error |

NAT2492: ENTER "Y" OR "N" OR "L".

| Text | ENTER "Y" OR "N" OR "L". |
|-------|---------------------------------|
| Expl. | Check program and correct error |

NAT2493: ENTER "Y" OR "N" OR "S".

| | ENTER "Y" OR "N" OR "S". |
|-------|---------------------------------|
| Expl. | Check program and correct error |

NAT2494: Function not allowed for files which have DDM"s.

| Text | Function not allowed for files which have DDM"s. |
|-------|--|
| Expl. | The RENAME function is not allowed for files which have DDM"s. |
| | Also it is not allowed to change the file type of such a file to "C" (conceptional) or to "Z" (standard). Use the copy function. |

NAT2495: File is a SUPER Natural USER FILE.

| Text | File is a SUPER Natural USER FILE. |
|-------|---|
| | The user-files of SUPER Natural can only be maintained in SUPER Natural and not in Predict. |
| Actn. | For prototyping user-files of SUPER Natural can be incorporated to predict. |

NAT2496: Function not supported in Natural VMS.

| Text | Function not supported in Natural VMS. |
|-------|---|
| | VSAM is not supported in a VMS environment. Therefore no DDM generation is allowed for VSAM files (file type "V","W","L","R") and no VSAM DDMs can be incorporated. However, you may maintain your descriptions of VSAM files in your dictionary. |
| Actn. | Incorporate COBOL is also not available in a VMS environment. |

NAT2497: Library name may not start with "SYS".

| Text | Library name may not start with "SYS". |
|-------|---|
| - | The Natural Librarys starting with "SYS" are reserved for usage by the products of the Software AG. |
| Actn. | Enter a valid library name. |

NAT2498: Member name not valid.

| Text | Member name not valid. |
|-------|---|
| Expl. | The entered member name is not valid. The member name for the generated code must confirm the following rules: - first character must be alfa (A-Z) - the other characters must be alfa-numeric (A-Z,0-9) or hyphen (-) - no imbedded blanks are allowed |
| Actn. | Enter a valid member name or "*". If "*" is entered Predict will build a valid member name. |

NAT2499: Library name not valid.

| Text | Library name not valid. |
|-------|--|
| Expl. | The library name for the generated code is not valid according the following rules: - the first character must be alfa (A-Z) - the other characters must be alfa-numeric (A-Z,0-9) or hyphen (-) - no imbedded blanks are allowed |
| Actn. | Enter a valid library name. |

NAT2500: Different error messages of the function "INCORPORATE COBOL".

| Text | Different error messages of the function "INCORPORATE COBOL". |
|-------|--|
| | These messages describe especially COBOL data definitions, which are not supported by the selectible unit "INCORPORATE COBOL". |
| Actn. | See message. |

50 Natural System Error Messages 2501-2550

NAT2501: Object added successfully.

| | Object added successfully. |
|-------|------------------------------------|
| Expl. | The object was added successfully. |

NAT2502: Object copied successfully.

| Text | Object copied successfully. |
|-------|--|
| Expl. | The copy function was successfully executed. |

NAT2503: Object modified successfully.

| | Object modified successfully. |
|-------|--|
| Expl. | The modify function was successfully executed. |

NAT2504: Owner not defined.

| Text | Owner not defined. |
|-------|--|
| · · | The owner record must be successfully added to the dictionary before the owner may be declared as an owner for other dictionary objects. |
| Actn. | Enter a valid owner id or leave blank. |

NAT2505: Keyword is not defined.

| Text | Keyword is not defined. |
|-------|--|
| | A keyword must exist within the dictionary before it can be assigned to any other dictionary objects. |
| Actn. | Enter a valid keyword or leave blank. |

NAT2506: Unable to edit object if editor is active.

| Text | Unable to edit object if editor is active. |
|-------|---|
| | Extended descriptions, verifications or owner lists cannot be modified while a list of subsequent objects is being modified. |
| Actn. | Enter "N" for edit-description, edit-verification or edit-owners. |

NAT2507: Database is not of type ...

| Text | Database is not of type |
|-------|---|
| - | At generation DDM the file type will be checked against the type of the database. Since Natural V2.1 the VSAM database number is no longer restricted to 254. The database type to file type "A" and "U" must be "A" and to file type "V", "L", "W" and "R" must be "V". |
| Actn. | Enter correct database id. |

NAT2508: Object in use.

| Text | Object in use. |
|-------|--|
| | Conflict during editing function due to multiple updates to the same object by another user. |
| Actn. | Restart the edit session. |

NAT2509: No more than XXX objects supported.

| Text | No more than XXX objects supported. |
|-------|---|
| Expl. | An attempt was made to add more than XXX objects to an other object. You may define up to 500 subsequent objects to an object, 99 owners to any object and 30 different codes for a file. Further additions will be rejected. |
| Actn. | Establish whether all objects (e.g., files) are necessary. Delete all unnecessary objects. |

NAT2510: Correct the error or hit "enter" to edit object list.

| Text | Correct the error or hit "enter" to edit object list. |
|-------|--|
| Expl. | If an error was detected during the catalog or check function, the error may be corrected immediately or the user may return to the full screen editor by hitting enter. |
| Actn. | Hit enter or correct the error. |

NAT2511: Object structure cataloged.

| Text | Object structure cataloged. |
|-------|---|
| Expl. | The catalog function terminated successfully. |

NAT2512: Duplicate object found.

| Text | Duplicate object found. |
|-------|--|
| | In editing the elements of an object, duplicated element names have been found during the catalog or check process. |
| Actn. | Correct the duplicate name or hit enter to return to the full screen editor. |

NAT2513: First character of name not alpha.

| Text | First character of name not alpha. |
|-------|---|
| - | All object names must start with an alpha character and must be at least 3 characters long. |
| Actn. | Correct the object name. |

NAT2514: Object displayed successfully.

| Text | Object displayed successfully. |
|------|---|
| Expl | The display function has been successfully completed. |

NAT2515: Invalid object.

| Text | Invalid object. | |
|-------|---|--|
| Expl. | An attempt was made to reference a nonexistent object type. | |
| Actn. | Enter a correct object type. | |

NAT2516: Invalid function code.

| | Invalid function code. |
|-------|---------------------------------|
| Expl. | Enter a valid Predict function. |

NAT2517: Function terminated.

| Text | Function terminated. |
|-------|---|
| Expl. | The Predict function has been completed successfully. |

NAT2518: No OBJECT specified.

| | No OBJECT specified. |
|-------|-------------------------------|
| Expl. | An Object ID must be entered. |
| Actn. | Enter a valid Object ID. |

NAT2519: Object does not exist.

| Text | Object does not exist. |
|-------|--|
| Expl. | The specified object does not exist in the dictionary. |
| Actn. | Enter a valid Object ID. |

NAT2520: More than one object found. See DBA.

| Text | More than one object found. See DBA. |
|-------|--|
| 1 1 | More than one object was found in the dictionary. The objects in the dictionary should be unique. This is a serious error. |
| Actn. | Stop activity immediately and contact your DBA. |

NAT2521: Object name already exists.

| Text | Object name already exists. |
|------|---|
| | The Object ID entered already exists in the dictionary. All ID's entered in Predict (except for the field name) must be unique. |
| | Note also that the field names in a given file must be unique. Enter a valid Object ID. |

NAT2522: First character of new Object ID is not alpha.

| Text | First character of new Object ID is not alpha. |
|-------|--|
| - | The first character of an Object ID must be a valid alpha-character. |
| | The object name must be at least 3 characters long. |
| Actn. | Enter a valid new Object ID. |

NAT2523: The function was not performed.

| Text | The function was not performed. |
|------|--|
| | The function was not performed because either an invalid input was |
| | made or a field was left blank. |

NAT2524: File ID must be specified.

| Text | File ID must be specified. |
|-------|---|
| Expl. | A field is uniquely defined only via the field and file name. |
| Actn. | Enter the File ID also. |

NAT2525: Object explosion listed.

| Text | Object explosion listed. |
|-------|---|
| Expl. | The explosion of an object has been displayed successfully. |

NAT2526: Object listed successfully.

| Text | Object listed successfully. |
|-------|--|
| Expl. | The requested objects have been successfully listed. |

NAT2527: OBJECT IMPLOSION listed.

| Text | OBJECT IMPLOSION listed. |
|-------|---|
| Expl. | The IMPLOSION of an OBJECT has been displayed successfully. |

NAT2528: Object RENAMED successfully.

| Text | Object RENAMED successfully. |
|-------|--|
| Expl. | The RENAME of an object has been performed successfully. |

NAT2529: No XREF DATA found.

| Text | No XREF DATA found. |
|-------|---|
| | This message is issued by the function "DELETE XREF DATA". If the search criteria did not agree with any XREF DATA, this message is issued. |
| Actn. | Enter valid search criteria. |

NAT2530: Invalid file type, file not loaded.

| Text | Invalid file type, file not loaded. |
|-------|--|
| · · | The file type encountered in the file record is not known to Predict. Therefore the file description has not been loaded. |
| Actn. | Create a correct file description record. |

NAT2531: Maximum file number must be less than 256.

| Text | Maximum file number must be less than 256. |
|-------|--|
| | One Adabas DATABASE contains max. 255 FILES, i.e. the MAX-FILE parameter must less than 256. |
| Actn. | Enter a number less than 256 or set the field to BLANK. |

NAT2532: Default conversion performed.

| Text | Default conversion performed. |
|------------|--|
| 1 1 | If the neccessary conversions from version 1 data are executed the message will be sent |

NAT2533: No object in hold.

| Text | No object in hold. |
|-------|--|
| Expl. | The rename / renumber function issues several ETs to prevent an overflow of the Adabas hold queue. Control records are written to the Predict file every time an ET is made. If the function abends, Predict is able to backup all transactions of this function successfully. After the whole function is performed, the control records are deleted. This message is issued if no control record was found in the RECOVERY function. |

NAT2534: Checkpoint file number must be less than or equal to max-file-no.

| Text | Checkpoint file number must be less than or equal to max-file-no. |
|------------|--|
| _ _ | The Adabas Checkpoint file number must be less than or equal to the maximum number of files specified for the data base. |
| | Enter a valid file number or leave the field blank. |

NAT2535: Security file number must be less than or equal to max-file-no.

| Text | Security file number must be less than or equal to max-file-no. |
|-------|---|
| Expl. | The Adabas security file number must be less than or equal to the |
| | maximum number of files specified for the data base. |
| Actn. | Enter a valid file number or leave the field blank. |

NAT2536: System file number must be less than or equal to max-file-no.

| Text | System file number must be less than or equal to max-file-no. |
|-------|---|
| Expl. | The Adabas system file number entered must be less than or equal to |
| | the maximum number of files specified for the data base. |
| Actn. | Enter a valid file number or leave the field blank. |

NAT2537: Natural, security and checkpoint files not different.

| Text | Natural, security and checkpoint files not different. |
|-------|--|
| Expl. | The Adabas checkpoint file, security file, and the Natural system file must be unique, i.e. different file numbers must be specified for each file-type. |
| Actn. | Enter different file numbers or leave the fields BLANK. |

NAT2538: Natural Security file number must be less than or equal to

| Text | Natural Security file number must be less than or equal to |
|-------|--|
| Expl. | max-file-nr. |
| | The Natural Security file number must be less than or equal to the maximum number of files specified for the data base. Enter a valid file number or leave the field blank. |

NAT2539: End of file reached.

| Text | End of file reached. |
|------|--|
| | During processing of the browse function, the end of the file has been reached. All of the fields have been processed successfully. |
| 1 | Note: the browse function may be terminated by hitting the correct PF key. Default is PF1. |

NAT2540: Predict file number must be le max-file-no.

| Text | Predict file number must be le max-file-no. |
|-------|---|
| Expl. | Predict file number must be le max-file-no. |
| Actn. | Enter a valid file number or leave blank. |

NAT2541: Source field name missing.

| Text | Source field name missing. |
|-------|---|
| Expl. | At least one field name must be entered when a phonetic, super- or sub-descriptor is defined. |
| Actn. | Enter a valid field name. |

NAT2542: A superdescriptor must contain 2 - 5 fields.

| Text | A superdescriptor must contain 2 - 5 fields. |
|-------|---|
| - | 2 - 5 fields must be entered when defining a superdescriptor in a file. Note that a superdescriptor containing only one field is a subdescriptor. |
| Actn. | Enter 2 - 5 fields. |

NAT2543: Ending position not entered.

| Text | Ending position not entered. |
|------|--|
| | For every field in a sub- or super-descriptor, an ending position must be entered. No default values are assumed. |
| - | Enter a valid ending position. |

NAT2544: No VSAM database in Natural defined.

| Text | No VSAM database in Natural defined. |
|-------|---|
| | If no database id specified at generation DDM for VSAM file or USER VIEW, the first VSAM database number, which is defined in Natural will be assigned. In this case no VSAM database number is defined in Natural. |
| Actn. | Contact your DBA. |

NAT2545: Starting position not entered.

| Text | Starting position not entered. |
|------------|--|
| _ _ | The starting position of a field contained in a sub- or super-descriptor must be entered. No defaults are assumed. |
| Actn. | Enter a valid starting position. |

NAT2546: Starting position > ending position.

| Text | Starting position > ending position. |
|-------|--|
| Expl. | The starting position entered is greater than the ending position. |
| Actn. | Enter valid positions. |

NAT2547: Field is a periodic group.

| Text | Field is a periodic group. |
|-------|--|
| - | A superdescriptor may not contain a field which is defined as a periodic group. However, an element of a periodic group may be contained in a superdescriptor. |
| Actn. | Correct the field name. |

NAT2548: Field is a group.

| Text | Field is a group. |
|-------|---|
| | A super-, sub-, or phonetic-descriptor may not contain a field which has been defined as a group. However, elements of the group may be part of a descriptor. |
| Actn. | Enter a valid field name. |

NAT2549: Field is a REDEFINE.

| Text | Field is a REDEFINE. |
|-------|--|
| | A super-, sub-, or phonetic-decriptor cannot be defined by means of a redefined field. The field must be an Adabas field. |
| Actn. | Enter a valid field name. |

NAT2550: Field is a counter field.

| Text | Field is a counter field. |
|-------|--|
| | A super-, sub-, or phonetic-descriptor may not contain a counter field, e.g., a field which is marked as a counter field (PE-count = "C"). |
| Actn. | Correct the field name used. |

51 Natural System Error Messages 2551-2600

NAT2551: Filler may not be used.

| Text | Filler may not be used. |
|-------|--|
| | A SUPER-, SUB-, OR PHONETIC-DESCRIPTOR may not be defined out of a field with name "FILLER". |
| Actn. | Enter a valid field name. |

NAT2552: Length of superdescriptor > 126.

| Text | Length of superdescriptor > 126. |
|-------|---|
| | The maximum length of a superdescriptor must be less than or equal to 126 characters, i.e., the sum of the length of all fields contained in a superdescriptor must not exceed 126. |
| Actn. | Correct length. |

NAT2553: Field is a sub-, super-, or phonetic-descriptor.

| Text | Field is a sub-, super-, or phonetic-descriptor. |
|-------|--|
| | No recursive description can be used for a super-, sub-, or phonetic-descriptor. |
| Actn. | Change SOURCE-FIELD of descriptor. |

NAT2554: Field not alphanumeric.

| Text | Field not alphanumeric. |
|-------|--|
| Expl. | The field was defined as a phonetic descriptor. The source field of a phonetic descriptor must always be alphanumeric. |
| Actn. | Enter a field which is alphanumeric. |

NAT2555: Specify only one field for subdescriptors.

| Text | Specify only one field for subdescriptors. |
|-------|---|
| | Only one field can be used to define a subdescriptor. A subdescriptor is a descriptor which contains a subfield of one Adabas field only. |
| Actn. | Enter only one field name. |

NAT2556: Specify only one field for phonetic descriptor.

| Text | Specify only one field for phonetic descriptor. |
|-------|---|
| | A phonetic descriptor contains one field only; this field must be alphanumeric. |
| Actn. | Enter only 1 field. |

NAT2557: Files found are not Adabas or VSAM files.

| Text | Files found are not Adabas or VSAM files. |
|-------|---|
| | The "related-fields/files-function" can only be executed for an Adabas-file or an Userview (file type "A" or "U"), for a VSAM file or its userview (file type "V" or "W") or for a LOGICAL VSAM file or its userview (file type "L" or "R"). |
| Actn. | Enter a valid file name. |

NAT2558: File entered is not a standard file.

| Text | File entered is not a standard file. |
|-------|---|
| Expl. | The function "standard file related field" refers to standard files (file type = "Z"). The file entered is not a standard file. |
| Actn. | Enter a standard file name or leave blank. |

NAT2559: Member not found.

| Text | Member not found. |
|-------|---|
| - | The Natural member cannot be found in the specified source library. |
| Actn. | Restart the punch-job with valid member and library names. |

NAT2560: Enter "Y", "N", or blank for ciphered.

| Text | Enter "Y", "N", or blank for ciphered. |
|-------|--|
| Expl. | Ciphered flag can only be yes (Y) or no (N). Note that a blank |
| | means no. |
| Actn. | Enter a valid ciphered flag. |

NAT2561: No preprocessor abend data found.

| Text | No preprocessor abend data found. |
|-------|---|
| Expl. | The preprocessor writes control records to the dictionary. Should |
| | the preprocessor abend for any reason, the active reference records must be deleted. This records can be deleted under the control of Predict. No control record was found in the dictionary with the specified search criteria. |
| Actn. | Enter valid search criteria. |

NAT2562: Invalid file-number (n001-n255).

| Text | Invalid file-number (n001-n255). |
|-------|--|
| | A file must be numbered with a number from 1 to 255. The first digit (n) may be used in Predict as an identifier which identifies the files. |
| Actn. | Enter a valid file number. |

NAT2563: Security level must be 0-15.

| Text | Security level must be 0-15. |
|-------|--|
| 1 1 | The Adabas security level for access or update must be between 0 and 15; "0" means "not protected", and "15" gives the highest protection level. |
| Actn. | Enter a valid security level. |

NAT2564: Invalid file type.

| Text | Invalid file type. |
|-------|---|
| Expl. | An invalid file type was entered. Valid file types are: |
| | A-Adabas file |
| | C-conceptual file |
| | I-ISAM |
| | L-logical VSAM file |
| | O-operating system file |
| | P-partitioned data set |
| | R-userview on VSAM file |
| | S-sequential data set |
| | U-user view on Adabas file |
| | V-user view on VSAM file |
| | W-user view on logical VSAM file |
| | Z-standard file |
| Actn. | Enter a valid file type. |

NAT2565: Member name already used.

| Text | Member name already used. |
|-------|---|
| | At generation time the user requested to store the generated code in a member which is already used for some other file. To prevent the user from overwriting code Predict issues this message and prompts the user to enter a new member and / or library name where the generated code is to be stored. |
| Actn. | Enter valid member and library names. |

NAT2566: Invalid record format.

| Text | Invalid record format. |
|-------|--|
| Expl. | An invalid RECFM was specified. Valid RECFM"s are: |
| | Ffixed |
| | FBfixed block |
| | Vvariable |
| | VBvariable blocked |
| | VBS-variable blocked standard |
| | FBS-fixed block standard |
| | Uundefined |
| Actn. | Enter a valid RECFM. |

NAT2567: File number already exists. New file number assigned.

| Text | File number already exists. New file number assigned. |
|-------|--|
| Expl. | During the load process of files Predict checks whether the file number of the file to be loaded is available. If the file number is already assigned to another file Predict seeks for the next free file number and assignes this one to the file to be loaded. |

NAT2568: Duplicate file number on input data set.

| Text Duplicate file number on input data set. | |
|---|-----------|
| Expl. If two master files were found on the input data set have same number, this message is issued. To prevent incons the attribute "file type" of the second master file is chang to "conceptual". | istencies |

NAT2569: Table overflow.

| Text | Table overflow. |
|-------|---|
| Expl. | The function "LIST Adabas FIELDS USED BY PROGRAMS" is restricted by the following conditions: no more than 50 user views may be defined to one Adabas file no more than 100 DDMs generated with prefixes are supported no more than 100 fields with same Adabas short name are supported. This message appears if mentioned limits are reached and the process stops. |

NAT2570: Natural specification only if language = "N".

| Text | Natural specification only if language = "N". |
|-------|---|
| Expl. | The specification of Natural-program Natural-library Natural-file number Natural-database number is only allowed if the language = "N" is entered. |
| Actn. | Enter language = "N". |

NAT2571: File number already exists.

| Text | File number already exists. |
|-------|---|
| | An attempt was made to add a file which number already exists in the dictionary. The first digit of the file number may be |
| | used to distinguish between files in different DATABASES. (Remember: in Predict the file numbers range from n001 to n255). |
| Actn. | Change the file number. |

NAT2572: User views can only be copied from file type A, U, V, R, L or W.

| Text | User views can only be copied from file type A, U, V, R, L or W. |
|-------|---|
| | An User view can only be created cia the COPY function from another User view or an Adabas or VSAM file. Valid file types are "A", "U", "V", "R", "L" or "W". |
| Actn. | Enter a valid file type. |

NAT2573: If language = "N" only Natural parameters allowed.

| Text | If language = "N" only Natural parameters allowed. |
|-------|---|
| Expl. | If you specify language = "N" only natural program natural library natural file number natural database number could be entered. |
| Actn. | Enter only the natural parameters. |

NAT2574: File does not exist.

| Text | File does not exist. |
|-------|--|
| · · | If you want to display the elements which are used and not defined the entered file must exist. |
| Actn. | Enter a existing file. |

NAT2575: Member- and library name must be specified.

| Text | Member- and library name must be specified. |
|-------|---|
| · · | In this function of the subsystem "Maintenance generated code" the Member- and library name must be specified. |
| Actn. | Enter Member- and/or library name. |

NAT2576: Unknown programming language.

| Text | Unknown programming language. |
|-------|---|
| Expl. | An invalid language was entered during program or module addition or modification. Valid languages are: BBAL(assembler) CCOBOL PPL/1 NNatural (only for a program entry) " "(blank) other |
| Actn. | Enter a valid language. |

NAT2577: Only "B", "O" or blank allowed.

| Text | Only "B", "O" or blank allowed. |
|-------|---|
| Expl. | The mode can only be O (online) or B (batch). |
| Actn. | Enter a valid mode. |

NAT2578: The related Adabas field does not exist.

| Text | The related Adabas field does not exist. |
|-------|---|
| - | An attempt was made to reference an Adabas field that does not exist in the related Adabas file. |
| Actn. | Enter a valid Field ID or leave blank. |

NAT2579: File is not an Adabas file.

| Text | File is not an Adabas file. |
|-------|--|
| Expl. | The related Adabas file must be a file of file type "A". |
| Actn. | Enter a valid File ID or leave blank. |

NAT2580: A filler may be used in REDEFINEs only.

| Text | A filler may be used in REDEFINEs only. |
|-------|---|
| | Predict recognizes the field type filler, but it may only be specified in a REDEFINE. It is not possible to define fillers for basic fields. |
| Actn. | Do not use fillers when defining basic (real) fields. |

NAT2581: Only "C", "I", and blank are valid types.

| Text | Only "C", "I", and blank are valid types. |
|-------|--|
| · · | For a relationship entry, the type may only be C (coupled in Adabas), I (implicit) or blank (implicit). |
| Actn. | Enter a valid type. |

NAT2582: File 1 or 2 missing.

| Text | File 1 or 2 missing. |
|-------|--|
| - | A relationship can only be established between 2 files: enter a file name. |
| Actn. | Enter a file name. |

NAT2583: Purge for automatic rule not allowed.

| Text | Purge for automatic rule not allowed. |
|-------|---|
| Expl. | Before a automatic rule can be purged, all connections to the fields must be released and the DDM"s of the corresponding files must be regenerated. If no connection between verification and field is active, the status will be changed to conceptual. Then the rule can be purged. |
| Actn. | Release connection between verification and fields and regenerate DDM"s of corresponding files. |

NAT2584: Relation field 1 or 2 does not exist.

| Text | Relation field 1 or 2 does not exist. |
|-------|--|
| | A relationship can only be established between 2 fields within 2 different files. If the file exists, the field must exist in the file, too. |
| Actn. | Enter a valid relationship field. |

NAT2585: In BATCH needed countersignatures not possible.

| Text | In BATCH needed countersignatures not possible. |
|-------|--|
| - | You are authorized to modify this file, but you need a countersignature. This is in Batch not possible. |
| Actn. | Generate DDM online. |

NAT2586: Field 1 or 2 missing.

| Text | Field 1 or 2 missing. |
|-------|--|
| 1 | A relationship can only be established between 2 fields: Enter a field name. |
| Actn. | Enter a relationship field. |

NAT2588: File is not a predict file.

| Text File is not a predict file. | |
|----------------------------------|---|
| Expl. | The specified file is not a predict file. |
| Actn. | Enter the correct filenumber. |

NAT2589: Formatbuffer for input file is empty.

| Text | Formatbuffer for input file is empty. |
|-------|--|
| | At generation ADACMP definitions an input file id was entered. This file should describe the input data for the ADACMP utility, but no formatbuffer was generated. |
| Actn. | Check input file for corresponding fields to the Adabas file. |

NAT2590: Usage must be "ACC" or "UPD".

| Text | Usage must be "ACC" or "UPD". |
|-------|--|
| Expl. | The usage of a user can only be ACC (access only) or UPD (update). |
| Actn. | Enter a valid usage code. |

NAT2591: Invalid verification type.

| Text | Invalid verification type. |
|-------|------------------------------------|
| Expl. | The verification type can only be: |
| | R-range |
| | E-equal |
| | L-less |
| | G-greater |
| | U-user routine |
| | T-table |
| Actn. | Enter a valid verification type. |

NAT2592: Type = blank required for REDEFINE group.

| Text | Type = blank required for REDEFINE group. |
|-------|--|
| Expl. | The field-type of a REDEFINE member must be BLANK. |
| Actn. | Enter a blank. |

NAT2593: Standard field name is...

| Text | Standard field name is |
|-------|--|
| | The field referenced is a standard field. i.e. the field name cannot be changed. By using the RENAME function, the name of the standard field can be changed and now all related field names are rippled. |
| Actn. | Either do not change the field name or use the RENAME function. |

NAT2594: Formats "I" and "F" require option "FI".

| Text | Formats "I" and "F" require option "FI". |
|-------|--|
| | By Adabas definition, an integer field requires the option "FI". The same is true for a floating point field. |
| Actn. | Enter option "FI". |

NAT2595: No Adabas name allowed for REDEFINITIONS.

| Text | No Adabas name allowed for REDEFINITIONS. |
|-------|--|
| Expl. | A member of a REDEFINE group may not contain an Adabas name. |
| Actn. | Delete Adabas short name. |

NAT2596: Length of descriptor is greater than 126.

| Text | Length of descriptor is greater than 126. |
|-------|--|
| Expl. | By Adabas definition, the maximum length for a descriptor field is 126 bytes. |
| Actn. | Either make the field length less than or equal to 126, or do not flag it as a descriptor. |

NAT2597: New user id assigned.

| Т | ext | New user id assigned. |
|---|------|--|
| E | xpl. | During the loading of Predict version 1 data this message will be |
| | | sent because the concept of users has changed in Predict version 2 and a new userid is assigned to the user entry. |

NAT2598: Binary length > 126 not allowed.

| Text | Binary length > 126 not allowed. |
|-------|---|
| Expl. | By Adabas definition, the maximum length of a binary field cannot exceed 126. |
| Actn. | Enter a length less than or equal to 126. |

NAT2599: Adabas field is not a descriptor.

| Text | Adabas field is not a descriptor. |
|-------|--|
| Expl. | The related field in the Adabas file is not defined as a descriptor. |
| Actn. | Do not enter the descriptor option. |

NAT2600: REDEFINE group cannot have option.

| Text | REDEFINE group cannot have option. |
|-------|---|
| · · | The SUPPRESSION option can only be defined for an existing Adabas field, not for a redefined field. |
| Actn. | Clear the SUPPRESSION option. |

52 Natural System Error Messages 2601-2650

NAT2601: Level may only be incremented by 1.

| Text | Level may only be incremented by 1. |
|-------|--|
| | The Adabas level number can be incremented only after a group, a PE-group, or a REDEFINE definition. The increment may not exceed 1. |
| Actn. | Enter a valid level number. |

NAT2602: Group without field found.

| Text | Group without field found. |
|-------|---|
| Expl. | The group defined does not contain any elementary fields. |
| Actn. | Hit enter to return to the editor. |

NAT2603: Field type must be "GR","MU","PE","RE" or blank.

| Text | Field type must be "GR","MU","PE","RE" or blank. |
|-------|---|
| | An invalid field type was entered. Valid field types are: GR (group) MU (multiple value field) PE (periodic group) RE (redefined field) |
| | " " (elementary field) |
| Actn. | Enter a valid type. |

NAT2604: Format must be A, F, N/U, B, P, US, PS, NS.

| Text | Format must be A, F, N/U, B, P, US, PS, NS. |
|-------|---|
| Expl. | An invalid format was specified. Valid field formats are: |
| | Aalphanumeric |
| | Ffixed point |
| | Nnumeric |
| | Uunpacked (same as numeric) |
| | Bbinary |
| | Ppacked |
| | Iinteger |
| | PS-packed signed |
| | NS-numeric signed |
| | US-unpacked signed |
| Actn. | Enter a valid format. |

NAT2605: Option must be "NU", "FI", or blank.

| Text | Option must be "NU", "FI", or blank. |
|-------|--|
| · · | The valid Adabas SUPPRESSION options are only the following: |
| | NU null suppression |
| | FI fixed |
| | " " normal suppression |
| Actn. | Enter a valid SUPPRESSION option. |

NAT2606: Descriptor must be DE, SB, SP, PH, UQ, PR, AL, SV, SA, blank.

| Text | Descriptor must be DE, SB, SP, PH, UQ, PR, AL, SV, SA, blank. |
|-------|---|
| Expl. | For Adabas, the following descriptor types exist: |
| | DE descriptor |
| | SP superdescriptor |
| | SB subdescriptor |
| | PH phonetic descriptor |
| | UQ unique descriptor |
| | " " field is not a descriptor |
| | and for VSAM the descriptor types known are: |
| | PR primary key |
| | AL alternate key |
| | SV super/sub descriptor |
| | SA alternate super/sub descriptor. |
| Actn. | Either enter a valid descriptor type or leave blank. |

NAT2607: The level number is not numeric.

| Text | The level number is not numeric. |
|-------|---|
| 1 1 | The level number must be a numeric value; do not enter a nonnumeric value for the level number. |
| Actn. | Enter a valid level number, i.e., a number between 0 and 9. |

NAT2608: Offset name missing.

| Text | Offset name missing. |
|-------|--|
| Expl. | Offset name for equivalence statement must be specified. |
| Actn. | Enter valid offset name. |

NAT2609: No more than 7 trailing decimal digits allowed.

| Text | No more than 7 trailing decimal digits allowed. |
|-------|---|
| - | More than seven (7) decimal digits have been entered to the right of the decimal point; the maximum is 7. |
| Actn. | Truncate. |

NAT2610: Maximum number of numeric digits is 27.

| Text | Maximum number of numeric digits is 27. |
|-------|---|
| | The number of significant digits exceeds 27, i.e. sum of digits to the right and to the left of the decimal point greater 27. |
| Actn. | Reduce the number of significant digits. |

NAT2611: Field not found in master file.

| Text | Field not found in master file. |
|-------|--|
| Expl. | The corresponding field with the given ABABAS short name in the user view was not found in the related master file. A master file for an user view (file type = "U") is the corresponding Adabas file, for a VSAM user view (file type = "W") is the corresponding VSAM file and for a view of a logical VSAM file (file type = "R") the corresponding logical vsam file. Only GROUP-fields may not have corresponding fields in the master file. |
| Actn. | Correct error. |

NAT2612: Error in CMRNS - Response code:

| Text | Error in CMRNS - Response code: |
|-------|---|
| | The rule, which should be activated, is stored with the module CMRNS. In this module an error occurred. If the first 3 character are "NAT", a Natural error occurred. |
| Actn. | Check error or see DBA. |

NAT2613: Duplicate field name found.

| Text | Duplicate field name found. |
|-------|--|
| Expl. | The field name must be unique within a file. |
| Actn. | Select a unique field name. |

NAT2614: No rule of verification found.

| Text | No rule of verification found. |
|-------|--|
| | At generation DDM a verification of status conceptual or automatic should be generated/regenerated, but to the verification no rule is stored. |
| Actn. | Contact DBA. |

NAT2615: Objects unloaded completely.

| Text | Objects unloaded completely. |
|-------|--|
| Expl. | All objects of a class unloaded successfully on work file 1. |

NAT2616: Length must be given.

| Text | Length must be given. |
|-------|---|
| | Predict does not support fields of length zero with the exception of PE-group and group definitions, which must be defined with no length definition. The elementary fields in a group must have a length attribute. |
| Actn. | Enter a valid length defintion. |

NAT2617: Decimal digits not allowed for alpha field.

| Text | Decimal digits not allowed for alpha field. |
|-------|---|
| - | Decimal digits only allowed for fields of format "NUMERIC" or "PACKED". |
| Actn. | Enter a valid length definition. |

NAT2618: Maximum field length for alpha is 253.

| Text | Maximum field length for alpha is 253. |
|-------|--|
| Expl. | Correct error. |

NAT2619: No Adabas name specified.

| Text | No Adabas name specified. |
|-------|---|
| | With the exception of members of REDEFINE groups, all fields either in an Userview or in an Adabas file must have an Adabas short name. |
| Actn. | Specify a short name. |

NAT2620: Standard descriptor is ...

| Text | Standard descriptor is |
|-------|---|
| Expl. | This field is related to a standard file. Its descriptor attribute is defined in the standard file and cannot be changed. Examples of the descriptor attributes which can be given are as follows: |
| Actn. | UQ, DE, SP, SB, and PH. Do not change this standard attribute; enter the option shown in the message. |

NAT2621: Master field descriptor is ...

| Text | Master field descriptor is |
|-------|---|
| Expl. | The type of the Adabas descriptor is invalid. Super-, sub- or phonetic- descriptors cannot be altered in an Userview. These descriptors must be identical to those defined in the original file, except for the descriptor types "UQ" and "DE", which may be erased in an Userview. The VSAM descriptor type in an USER VIEW must be the same as in the physical/logical VSAM file. |
| Actn. | Enter the descriptor type shown is the message. |

NAT2622: Descriptor must be same as Adabas.

| Text | Descriptor must be same as Adabas. |
|-------|---|
| 1 1 | The field has been copied from an Adabas file. It must therefore have the same descriptor option as the original field in the Adabas file. |
| Actn. | Do not change the descriptor option. |

NAT2623: Standard option is ...

| Text | Standard option is |
|-------|---|
| Expl. | The entered option differs from the standard field. |
| Actn. | Enter the displayed standard option or mark the field as nonstandard. |

NAT2624: Adabas suppression option entered not valid.

| Text | Adabas suppression option entered not valid. |
|-------|--|
| 1 1 | The Adabas SUPPRESSION option in the Userview is not the same as in the Adabas file. |
| Actn. | Enter the displayed option. |

NAT2625: Format "A" cannot be changed.

| Text | Format "A" cannot be changed. |
|-------|--|
| | Adabas does not support data conversion from alphanumeric to numeric. The format of field in the master file is "A" (alphanumeric), i.e. the format of the corresponding fields in the USER VIEWs must be also "A". |
| Actn. | Enter "A" in the format definition. |

NAT2626: Field cannot be a descriptor.

| Text | Field cannot be a descriptor. |
|-------|--|
| 1 1 | Fields of a REDEFINE group or COUNTER fields can not be defined as descriptor. |
| Actn. | Correct error. |

NAT2627: Option "U" only for files allowed.

| Text | Option "U" only for files allowed. |
|-------|---|
| - | The entered option is not allowed for this object type. Take a look at the help screens for the allowed options combination. |
| Actn. | Check file options. |

NAT2628: Adabas NAME not valid.

| Text | Adabas NAME not valid. |
|-------|--|
| | The first character of an Adabas name must be alpha. The second character can be either numeric or alpha. Note that the Adabas name is two characters long, and remember: Adabas short names "E0" through "E9" are not valid because these short names specify edit masks. |
| Actn. | Enter a valid Adabas name. |

NAT2629: Duplicate Adabas field name found.

| Text | Duplicate Adabas field name found. |
|-------|---|
| | A duplicate Adabas field name was encountered during the CATALOG function. The field names must be unique in the Adabas file. In an Userview, however, the Adabas short names may be specified more than once. |
| Actn. | Enter an unique Adabas field name. |

NAT2630: Adabas name cannot be "E0" through "E9".

| Text | Adabas name cannot be "E0" through "E9". |
|-------|--|
| 1 1 | The Adabas short names cannot be E0 through E9. E0-E9 are reserved words which specify edit masks. |
| Actn. | Enter a short name different from E0-E9. |

NAT2631: Unpacked field may not be fixed.

| Text | Unpacked field may not be fixed. |
|-------|---|
| Expl. | With Adabas, unpacked fields may not have a fixed format. |
| Actn. | Change the option. |

NAT2632: Level must be ...

| Text | Level must be |
|-------|--|
| | The maximal level number for a field is 7, if an Adabas file or Adabas USER VIEW is involved. The field level of other files may be 1-9. |
| Actn. | Enter a correct level number. |

NAT2633: Active References not installed.

| Text | Active References not installed. |
|-------|---|
| Expl. | The selectable unit ACTIVE REFERENCES is not installed in your environment. This message is issued because you tried to invoke the active reference menues via the main menu or via the command processor. |
| Actn. | Install the selectable unit ACTIVE REFERENCES. |

NAT2634: Length of REDEFINITION longer than basic field.

| Text | Length of REDEFINITION longer than basic field. |
|-------|--|
| | A REDEFINE group cannot be longer than the basic field, i.e. the sum of the field lengths must equal to the length of the redefined field. |
| Actn. | Correct error. |

NAT2635: REDEFINE group shorter than basic field.

| Text | REDEFINE group shorter than basic field. |
|-------|--|
| | A REDEFINE should be at least as long as the basic field, i.e., the sum of the lengths of all fields in the basic field must equal the sum of the lengths of all fields of the REDEFINE. |
| Actn. | Check redefinition and define fillers if necessary. |

NAT2636: Standard format is ...

| Text | Standard format is |
|-------|--|
| Expl. | The format entered for the field differs from the format in the standard file. |
| Actn. | Enter the standard format or mark the field as nonstandard. |

NAT2637: Standard length is ...

| Text | Standard length is |
|-------|---|
| Expl. | The length entered for the field is different to the standard length. |
| Actn. | Enter the correct length or mark the field as non-standard. |

NAT2638: Standard adabas name is ..

| Text | Standard adabas name is |
|-------|---|
| Expl. | The name entered for the field is not the one specified in the standard file. |
| Actn. | Enter the standard name or mark the field as nonstandard. |

NAT2639: Standard field type is ...

| Text | Standard field type is |
|-------|---|
| Expl. | The field type entered is not the one specified in the standard file. |
| | Enter the standard field type or mark the field as nonstandard. |

NAT2640: An invalid command was entered.

| Text | An invalid command was entered. |
|-------|---|
| | The command entered is invalid. Use the help function to obtain |
| | information about the valid commands. |
| Actn. | Enter a valid command or use the help function by entering "?". |

NAT2641: No object found.

| Text | No object found. |
|-------|--|
| Expl. | In a retrieval or display, objects in the dictionary are selected. |
| | No object satisfied the specified search criteria. |

NAT2642: File not in database.

| Text | File not in database. |
|-------|--|
| Expl. | The file requested does not belong to the specified data base. |
| Actn. | Enter a valid file name. |

NAT2643: Requested user incorporated.

| Text | Requested user incorporated. |
|-------|---|
| Expl. | A user has been incorporated into the dictionary. |

NAT2644: MODULES / REPORTS without FILES listed successfully.

| [| Text | MODULES / REPORTS without FILES listed successfully. |
|---|-------|---|
| ſ | Expl. | A retrievel was made to find all MODULES or REPORTS without |
| | | FILES. |

NAT2645: File is not a standard file or was not found.

| Text | File is not a standard file or was not found. |
|-------|--|
| - | Either the file referenced is not a standard file or it is not defined in the dictionary. |
| Actn. | Enter the standard file name. |

NAT2646: Field not in file.

| Text | Field not in file. |
|-------|---|
| Expl. | The field entered does not belong to the file. This field cannot be copied. |
| Actn. | Enter a valid field name. |

NAT2647: Field not found.

| Text | Field not found. |
|-------|----------------------------------|
| Expl. | The field entered was not found. |
| Actn. | Enter a valid Field ID. |

NAT2648: Pf-key must be < 25.

| Text | Pf-key must be < 25. |
|-------|--------------------------------------|
| Expl. | Only pf-key 1 thru 24 are supported. |
| Actn. | Check pf-key and correct error. |

NAT2649: Member already exists.

| Text | Member already exists. |
|-------|---|
| · · | Generation of copy code did not take place, because the member name of the copy element already exists and the REPLACE option was not set to "Y". |
| Actn. | Specify a new member name or use the REPLACE option. |

NAT2650: Comment lines range between 0 and 16.

| Text | Comment lines range between 0 and 16. |
|-------|--|
| - | No more than 16 comment lines are supported by Predict. The mimimum is zero. |
| Actn. | Enter a value between zero and 16. |

53 Natural System Error Messages 2651-2700

NAT2651: If gen. FB = "Y", DSECT = "N" and DS/DC = "DC" must entered.

| Text | If gen. FB = "Y", DSECT = "N" and DS/DC = "DC" must entered. |
|-------|--|
| 1 4 | If a format buffer should be generated, then DSECT="N" must be declared and the DS/DC option must set to "DC". |
| Actn. | Enter "N" for DSECT option and "DC" for "DS/DC" option. |

NAT2652: Format buffer only for file-type "A" or "U".

| Text | Format buffer only for file-type "A" or "U". |
|-------|---|
| Expl. | Format buffers can only be generated for Adabas files or Userviews. |
| Actn. | Enter "N" for format buffer. |

NAT2653: File not found.

| Text | File not found. |
|-------|---|
| Expl. | To generate copy code, a valid file name must be entered. |
| Actn. | Enter a valid file name. |

NAT2654: Key not allowed for VSAM "RRDS" files.

| Text | Key not allowed for VSAM "RRDS" files. |
|-------|---|
| - | The specification of a descriptor type for a VSAM "RRDS" file is not allowed. |
| Actn. | Use another file organization or delete the specified key. |

NAT2655: Date is invalid.

| Text | Date is invalid. |
|-------|---|
| · · | The entered date has wrong format or values. The date must be specified in the following format : JJ-MM-DD. |
| Actn. | Enter a valid date. |

NAT2656: Enter "DS" or "DC".

| Text | Enter "DS" or "DC". |
|-------|---|
| | In the assembler generation, either the "DC" or the "DS" statements are used to define storage. Select the desired statement. |
| Actn. | Enter "DS" or "DC". |

NAT2657: Enter "Y" or "N".

| Text | Enter "Y" or "N". |
|-------|---|
| Expl. | Only "Y" or "N" allowed for this Input-field. |
| Actn. | Correct error. |

NAT2658: Generated code saved.

| Text | Generated code saved. |
|-------|---|
| Expl. | The generated code has been saved as member in the specified library. |

NAT2659: Code generated in source area.

| Text | Code generated in source area. |
|------|--|
| · · | The generated code is stored in the source area for further editing. The GENERATION function terminates successfully. |

NAT2660: Generation terminated abnormally.

| Text | Generation terminated abnormally. |
|-------|---|
| | An error occurred during the generation either of COBOL copy code, of PL/1 include code, of assembler copy code, or of Data Definition Modules. The error has been displayed on the screen preceding this message. |
| Actn. | Correct the error and restart the generation. |

NAT2661: Duplicate names found.

| Text | Duplicate names found. |
|-------|--|
| | Duplicate names were found during generation of copy code. For example, field names are truncated when they are too long. |
| Actn. | Correct field names in the file. |

NAT2662: Copycode generation for conceptual and standard files impossible.

| Text | Copycode generation for conceptual and standard files impossible. |
|-------|--|
| | An attempt was made to generate copy code for a conceptual or a standard file. This is not possible since copy code can be generated only for real file types, i.e., Adabas files, Userviews, VSAM, etc. |
| Actn. | Do not generate copy code for conceptual or standard files. |

NAT2663: Level increment is a number from 1 to 40.

| Text | Level increment is a number from 1 to 40. |
|-------|---|
| Expl. | The specified level increment must be in the value range 1 thru 40. |
| Actn. | Correct the value of the level increment. |

NAT2664: Start level is a number from 1 to 40.

| Text | Start level is a number from 1 to 40. |
|-------|--|
| Expl. | Enter a start level greater than zero. |

NAT2665: More than one primary key found.

| Text | More than one primary key found. |
|-------|---|
| Expl. | Only one element can be specified as primary key. |
| Actn. | Modify the primary key definition. |

NAT2666: No primary key found.

| Text | No primary key found. |
|-------|--|
| Expl. | One primary key must defined for this VSAM file. |
| Actn. | Specify one primary key. |

NAT2667: Generated code replaced.

| Text | Generated code replaced. |
|-------|--|
| Expl. | At generation time Predict checks whether the target library / member where the generated code is to be stored, exists or not. As you told Predict to replace the old code by the recently generated one and Predict found an old code, it has been replaced. |

NAT2668: No files need to be regenerated.

| | No files need to be regenerated. |
|-------|------------------------------------|
| Expl. | No file modified after generation. |

NAT2669: Format may not be alpha for counter field.

| Text | Format may not be alpha for counter field. |
|-------|--|
| Expl. | A counter field is a numeric field. The format must be "N", "P", "U", "B" or "I". |
| Actn. | Change the format to numeric. |

NAT2670: Input file is not an USER VIEW or SEQ. file.

| Text | Input file is not an USER VIEW or SEQ. file. |
|------------|---|
| 1 1 | In Adabas V5.1 the input data of the ADACMP utility can be described as USER VIEW of the Adabas file or as file of type "S" (sequentiell). |
| Actn. | Enter correct file name. |

NAT2671: DDM already exists.

| Text | DDM already exists. |
|-------|--|
| Expl. | This message is a warning. It has been issued because REPLACE option = "N" has been entered and an older Data Definition Module was found. The existing DDM has not been replaced. |
| Actn. | Enter REPLACE option = "Y". |

NAT2672: No keys allowed for "PE" or "MU".

| Text | No keys allowed for "PE" or "MU". |
|-------|--|
| - | No key definition for periodic groups and multiple fields in vsam files are allowed. |
| Actn. | Enter blank in the key field. |

NAT2673: Field is not connected to a standard file.

| Text | Field is not connected to a standard file. |
|-------|---|
| · · | If you mark a field as non-standard and the field is not connected to a standard file this message will be sent. |
| Actn. | Delete the non-standard flag. |

NAT2674: Database number invalid.

| Text | Database number invalid. |
|-------|---|
| - | The Adabas database number must not exceed 254. Database number 255 are reserved for internal use. In Natural V1.2 the database number 254 is reserved for the VSAM database. |
| Actn. | Enter a valid database number. |

NAT2675: File number (FNR) invalid.

| Text | File number (FNR) invalid. |
|-------|---|
| Expl. | Adabas supports only 255 different files. |
| Actn. | Enter a number less than 256. |

NAT2676: Primary sequence field not in file.

| Text | Primary sequence field not in file. |
|-------|--|
| | The primary sequence field specifies the default descriptor with which the file should be read. This field must belong to the file. |
| Actn. | Correct the primary sequence field. |

NAT2677: Target database not active.

| Text | Target database not active. |
|-------|---|
| Expl. | The target database must be active if Data Definition Modules are generated for it. |
| Actn. | Initiate the target database. |

NAT2678: Input file is not a USER VIEW of the Adabas file.

| Text | Input file is not a USER VIEW of the Adabas file. |
|------|--|
| | In Adabas V5.1 the input data of the ADACMP utility can be described as corresponding USER VIEW of the entered Adabas file. |
| | Enter correct INPUT File ID or define input data as USER VIEW of the Adabas file or as sequentiell file. |

NAT2679: File ID must be entered.

| Text | File ID must be entered. |
|-------|---|
| Expl. | The File ID is a mandatory parameter for this function. |
| Actn. | Enter a valid File ID. |

NAT2680: Database has no number.

| Text | Database has no number. |
|-------|--|
| Expl. | At GENERATION DDM from a file, the specified database-id must have a number, because the DDM depends on the database number. If no database-id is entered, database number 0 is set in the DDM. In this case the database number will be taken at runtime out of the parameter facilities (ADAPARM module, dynam. Natural parameter,). |
| Actn. | Enter a database with a valid number or set database-id to BLANK. |

NAT2681: Primary sequence field is not a descriptor.

| Text | Primary sequence field is not a descriptor. |
|-------|--|
| Expl. | The primary sequence field defines the default descriptor by which the file should be read. If the primary sequence field is not a descriptor, no valid READ statement results for the default. The Data Definition Module was not generated for this reason. |
| Actn. | Enter a valid primary sequence field, i.e., a descriptor. |

NAT2682: An Adabas error occurred.

| Text | An Adabas error occurred. |
|-------|---|
| Expl. | The listed Adabas response code occurred. |
| Actn. | See the DBA. |

NAT2683: Enter program name or "*".

| Text | Enter program name or "*". |
|-------|---|
| | If you want to delete the xref data of a program you have to specify the program name or "*". The asterisk should be entered if preprocessor abends data should be deleted. |
| Actn. | Enter program name or "*". |

NAT2684: Missing command.

| Text | Missing command. |
|-------|---|
| | The conversion for Predict Version 1 data to Predict Version 2 data was invoked in batch mode. As no command was supplied the command processor isssues this message. |
| Actn. | Restart the batch session and supply some valid commands. |

NAT2685: The DDM to be incorporated is not a VSAM DDM.

| Text | The DDM to be incorporated is not a VSAM DDM. |
|-------|--|
| Expl. | You have tried to incorporate a DDM which is not of type VSAM. |
| Actn. | Check type of DDM. |

NAT2686: File is not security protected.

| Text | File is not security protected. |
|-------|--|
| | The file is not security protected. Therefore, no security definitions |
| | can be generated. |
| Actn. | Do not generate security definitions for unprotected files. |

NAT2687: Source field for sub-/super-descriptor not in DDM.

| Text | Source field for sub-/super-descriptor not in DDM. |
|-------|---|
| | The field specified in the sub-/super-descriptor definition is not defined as field in the DDM. The sub-/super-descriptor is only allowed to refer fields defined in the DDM. |
| Actn. | Check source field names of the sub-/super-descriptor. |

NAT2688: File is of wrong type.

| Text | File is of wrong type. |
|------|---|
| | Data Definition Modules can only be generated for Adabas files and Userviews of the Adabas file or VSAM files and their Userviews. |
| | (only files of type "A","U","V","R","L" or "W" allowed) Enter a valid file. |

NAT2689: Max. 90 sub-/super-descriptors can be incorporated.

| Text | Max. 90 sub-/super-descriptors can be incorporated. |
|------|---|
| 1 | The incorporated VSAM DDM contains more than 90 sub-/super-descriptors. Only 90 descriptors can be incorporated. |

NAT2690: File is not an Adabas file.

| Text | File is not an Adabas file. |
|-------|---|
| | The generation of ADAWAN/ADACMP or Adabas security definitions can only be executed for Adabas files. |
| Actn. | Check file type. |

NAT2691: Only F, FB, V, VB, U or blank allowed.

| Text | Only F, FB, V, VB, U or blank allowed. |
|-------|--|
| Expl. | The RECORD FORMAT at GENERATION ADAWAN/ADACMP definitions must be: Ffixed FBfixed blocked Vvariable VBvariable blocked Uunblocked " "not specified |
| Actn. | Correct error. |

NAT2692: Duplicate file record found.

| Text | Duplicate file record found. |
|-------|--|
| Expl. | Predict does not allow duplicate names within the same object types This message is issued, if such an inconsistency is encountered. The duplicate records are deleted by the MIGRATE utility during the unload file process. |
| Actn. | Unload and load your file by the MIGRATE utility. |

NAT2693: Security definition already exists.

| Text | Security definition already exists. |
|-------|--|
| | If you want to generate a DDM for which a security definition exists this message will be sent. |
| Actn. | Change security definiton if necessary. |

NAT2694: Cipher-code must be entered.

| Text | Cipher-code must be entered. |
|-------|---|
| Expl. | The data should be loaded into the database in ciphered form. |
| Actn. | Enter cipher-code or contact your DBA. |

NAT2695: The specified objects have been unloaded successfully.

| Text | The specified objects have been unloaded successfully. |
|------|---|
| Expl | The objects have been unloaded successfully to work file 1. |

NAT2696: No object was found.

| Text | No object was found. |
|------|---|
| - | To perform an unload or a load, an Object ID and an object type must be |
| | entered. No objects that meet the conditions were found. |

NAT2697: Cipher-code is not allowed.

| Text | Cipher-code is not allowed. |
|-------|---|
| Expl. | The data should not be laoded into the database in ciphered form. |
| Actn. | Reset cipher-code or contact your DBA. |

NAT2698: Field length in VSAM file different to field length user view.

| Text | Field length in VSAM file different to field length user view. |
|-------|---|
| | Generally no format overwrite is allowed when using VSAM files. However, you may define an alphanumeric field in a user view which is shorter than the original field, but never a longer one. Numeric fields must have the same attributes as the master field. |
| Actn. | Correct error. |

NAT2699: Format defined in VSAM file is of a different type.

| Text | Format defined in VSAM file is of a different type. |
|-------|---|
| Expl. | When defining a VSAM user view the format of the field can"t be changed, it has to be the same as the format of the field in the master file. |
| Actn. | Do not change the format of a field in a user view of a VSAM file. |

NAT2700: No ".I", ".W" between X and Y marks.

| Text | No ".I", ".W" between X and Y marks. |
|-------|--|
| | This message is issued, if you are trying to misuse the line commands ".I" or ".W" and ".MX-Y" or ".CX-Y". You may not copy or move the lines between the X and Y mark and try to insert some lines between these two marks at the same time. |
| Actn. | Do not try to insert lines between the lines you want to copy or move. |

54 Natural System Error Messages 2701-2750

NAT2701: Line subcommand is outside of source lines.

| Text | Line subcommand is outside of source lines. |
|-------|---|
| Expl. | The line subcommand entered is outside of the source lines. |
| Actn. | Commands may not be entered outside of the source lines. |

NAT2702: Line command ".M" without "X" or "Y" found.

| Text | Line command ".M" without "X" or "Y" found. |
|-------|---|
| Expl. | This command tells you that the editor recognized the line command ".M" but is missing "X", "Y" or "X-Y". The line command ".M" has three valid forms, namely .MX .MY .MX-Y All other forms are flagged as invalid. |
| Actn. | Enter one of the three commands mentioned above when you want to move data. |

NAT2703: No line marked "X".

| Text | No line marked "X". |
|-------|---|
| | An edit command referring to a line marked with "X" was entered without any line being so marked. |
| Actn. | Mark the desired line with "X". |

NAT2704: No line marked "Y".

| Text | No line marked "Y". |
|-------|---|
| 1 1 | An edit command referring to a line marked with "Y" was entered without any line being so marked. |
| Actn. | Mark the desired line with "Y". |

NAT2705: Y-position not behind X-position.

| Text | Y-position not behind X-position. |
|-------|---|
| Expl. | A line command was entered with two marked lines involved. The line marked with "X" is behind the one marked with "Y". |
| Actn. | Reverse the order of the marks. |

NAT2706: Copied/moved lines overlap target line.

| Text | Copied/moved lines overlap target line. |
|-------|---|
| - | An attempt was made to copy source lines into an area between the source lines. |
| Actn. | Do not enter a line command between the lines marked "X" and "Y". |

NAT2707: ".J" entered in last line.

| Text | ".J" entered in last line. |
|-------|---|
| Expl. | The ".J" line command (JOIN) can not be entered in the last line. |

NAT2708: An invalid edit command was entered.

| Text | An invalid edit command was entered. |
|-------|---|
| | An invalid edit command was entered. Valid commands are explained in the help screen. |
| Actn. | Enter a valid command or "?" for help. |

NAT2709: Do not replace to same data.

| Text | Do not replace to same data. |
|-------|---|
| Expl. | Do not scan for data and replace it with same data. |
| Actn. | Enter different scan and replace strings. |

NAT2710: All objects from work file 1 loaded.

| | Text | All objects from work file 1 loaded. |
|---|-------|---|
| ĺ | Expl. | All Predict objects, which are on the work file 1, are loaded |
| | | by the MIGRATE utility. |

NAT2711: Missing DDNAME for VSAM file.

| Text | Missing DDNAME for VSAM file. |
|-------|--|
| Expl. | To generate a DDM for a VSAM file a DDNAME must be supplied. |
| Actn. | Add the DDNAME to the file definition in Predict. |

NAT2712: Rule of mode "REPORT" may not be generated.

| Text | Rule of mode "REPORT" may not be generated. |
|-------|---|
| · · | The mode is set to "STRUCT" (SM=ON) and it is not permitted to change to "REPORT" mode. |
| Actn. | Contact your DDA. |

NAT2713: Editing terminated.

| Text | Editing terminated. |
|-------|--|
| Expl. | The edit session was terminated due to a user-issued edit command. |
| | No update was performed. |

NAT2714: No Adabas short name available.

| Text | No Adabas short name available. |
|-------|---|
| 1 1 | The generation of Adabas short names terminated abnormally, because no more Adabas short names available. |
| Actn. | Reduce fields of file. |

NAT2715: Standard file updated.

| Text | Standard file updated. |
|------|--|
| I - | The standard file has been updated. All elements which are connected to the standard file were updated too (RIPPLING |
| | process.) |

NAT2716: All fields already in standard file.

| Text | All fields already in standard file. |
|-------|---|
| Expl. | You have tried to execute the PUSH BACKWARD function using a file whose |
| | fields are already linked to another standard file. No field has been |
| | copied to the standard file, because one field can only be linked |
| | to one standard file. |

NAT2717: Invalid program type.

| Text | Invalid program type. |
|-------|---|
| | Allowed program types are: "F" Fetch program "M" Map "N" Call Subroutine "S" Perform Subroutine |
| Actn. | Correct program type. |

NAT2718: Source field for sub-/super-/phon- descriptor missing.

| Text | Source field for sub-/super-/phon- descriptor missing. |
|-------|---|
| Expl. | During DDM generation an error occured. Either a super descriptor with no source field was found or a source field for a super descriptor was not found in the file. Therefore the generation of the DDM has been aborted. |
| Actn. | Check file and correct error. |

NAT2719: Do not misuse "change" command.

| Text | Do not misuse "change" command. |
|-------|--|
| | This powerful edit command allows you to change a character string or to replace it with a null value, but not both at the same time. |
| Actn. | Either replace with a null value or with a new string. |

NAT2720: No RENAME function for standard fields.

| Text | No RENAME function for standard fields. |
|-------|---|
| Expl. | Standard fields may not be renamed. |
| Actn. | Do not RENAME a standard field. |

NAT2721: File is locked by user.

| · | Text | File is locked by user. |
|---|------|---|
| | - | If the function RENAME or RENUMBER a file terminates abnormally, the file is not released from the locked status. |
| - | | Start the RECOVERY function of Predict. |

NAT2722: Cursor outside source line.

| Text | Cursor outside source line. |
|------|--|
| | When using the ".S" line command a test is made if the cursors position is in the source line. If not, this message is issued. |
| | When splitting a line, position the cursor to the split point of the source line. |

NAT2723: Input-file is locked by user.

| Text | Input-file is locked by user. |
|-------|---|
| | The file, which describes the input data of the ADACMP utility, is lock by the listed user. |
| Actn. | Use the Predict RECOVERY function to release the file. |

NAT2724: Do not modify deleted lines.

| Text | Do not modify deleted lines. |
|-------|--|
| | In the editor you may delete some fields. These fields remain on the screen, marked as deleted. You may not modify those fields. |
| Actn. | Do not modify deleted fields. |

NAT2725: Second "REDEFINE" on wrong level.

| Text | Second "REDEFINE" on wrong level. |
|-------|---|
| - | The additional "REDEFINE" with the field name "FILLER" has not the same level as the basic field. |
| Actn. | Correct error. |

NAT2726: Maintain AUTOMATIC or FREE RULE with Natural V2 only.

| Text | Maintain AUTOMATIC or FREE RULE with Natural V2 only. |
|-------|---|
| | Rules with status "AUTOMATIC" or "FREE" are features of Natural V2 and they can only maintained in a Natural V2 environment. |
| Actn. | Use Natural V2. |

NAT2727: No "SCRATCH" in Natural Security.

| Text | No "SCRATCH" in Natural Security. |
|-------|--|
| Expl. | If Natural Security is active, only the function "PURGE DATABASE" is possible. The connected files of the database must be explicitly deleted. |
| Actn. | Enter PURGE for function code. |

NAT2728: Command .J may not be used in first line of screen.

| Text | Command .J may not be used in first line of screen. |
|-------|---|
| Expl. | The command .J joins the current line with the line immediately preceding it. Since no preceding line exists in this case, the command is not executable. |
| Actn. | Do not enter command .J in the first line. |

NAT2729: Position the cursor to the split point.

| Text | Position the cursor to the split point. |
|-------|--|
| Expl. | In order to split a line, the cursor must be positioned to the split point. Hit ENTER to split the line. |
| Actn. | Position the cursor to the split point and hit ENTER. |

NAT2730: No shift direction specified (+NN,-NN).

| Text | No shift direction specified (+NN,-NN). |
|-------|---|
| | The edit command shift requires one parameter, the direction. This parameter is a signed number which may be omitted; in this case the default value "+3" is assumed. |
| Actn. | Enter a shift parameter (+NN, or -NN). |

NAT2731: Invalid parameter in line command.

| Text | Invalid parameter in line command. |
|-------|--|
| | Some line commands may have parameter. For example, the line command ".C(NNN)" will copy a line "NNN" times; however the line command ".C(0)" means "copy this line zero times", which makes no sense. Therefore the message above is issued. |
| Actn. | Enter a valid parameter for line command. |

NAT2732: X-line must be on the screen for shift.

| Text | X-line must be on the screen for shift. |
|-------|---|
| | To shift a text, it is required that the X-line be on the screen. After the text has been shifted, part of the text should be seen on the screen. |
| Actn. | Position to the X-line by entering .X in the command line. |

NAT2733: DDM does not exist.

| Text | DDM does not exist. |
|------|---|
| | DDM specified does not exist; no incorporation can be performed. Either the DDM does not exist or it is cataloged in another Natural system file. |
| | Enter a valid DDM. Ensure that the correct Natural system file has been specified. |

NAT2734: Objects loaded completely.

| Text | Objects loaded completely. |
|-------|---|
| Expl. | The objects have been loaded into the dictionary. |

NAT2735: No Object from work file 1 loaded.

| Text | No Object from work file 1 loaded. |
|-------|---|
| | No object on the input file (Natural work file 1) has been loaded. Possibly the search criteria did not match to any object on the input file or the input file is empty. |
| Actn. | Verify the load criteria. |

NAT2736: Unkown object-type in group on work file 1.

| Text | Unkown object-type in group on work file 1. |
|-------|--|
| | Each group of objects on the work file is preceeded by a control record. If this control record was not found, this error message has been issued. |
| Actn. | Check that the correct control records are written to the sequential file. |

NAT2737: All objects from work file 1 loaded.

| Text | All objects from work file 1 loaded. |
|-------|--|
| Expl. | This message indicates that all objects have been loaded successfully. |

NAT2738: Name + Prefix + Suffix > 32 Characters.

| Text | Name + Prefix + Suffix > 32 Characters. |
|-------|---|
| Expl. | The new name of the object has been truncated to 32 characters because the resulting name, the concatenation of name prefix and suffix, was too long. |
| Actn. | Do not use such a large prefix and/or suffix. |

NAT2739: Warning: no owner loaded.

| Text | Warning: no owner loaded. |
|-------|---|
| - | The DDA has set the owner switch to "force". The loaded object must have some owner attributes, but it did not. This message is only a warning. |
| Actn. | Please add the required owners to the object. |

NAT2740: No description for the object was found.

| Text | No description for the object was found. |
|-------|---|
| Expl. | For the specified object no description exists. |
| Actn. | Add later the required description to the object. |

NAT2741: Object already exists.

| Text | Object already exists. |
|-------|---|
| Expl. | An object with the same object-id exists. |
| Actn. | Check the object id and correct error. |

NAT2742: No available file number found.

| Text | No available file number found. |
|-------|---|
| | An attempt was made to define more than 10 files with the same Adabas file number. The Predict file number is a four-digit number, i.e. a number of the form N001 through N255. The first digit of the Predict file number "N", is used to distinguish between files. The last three digits specify the Adabas file number. |
| Actn. | Check whether all files are necessary; delete nonessential files. |

NAT2743: DDM incorporated successfully.

| Text | DDM incorporated successfully. |
|-------|---|
| Expl. | A DDM not generated by Predict has been incorporated into the |
| | dictionary. |

NAT2744: File buffer too small.

| Text | File buffer too small. |
|-------|--|
| | The file buffer must be large enough to incorporate a DDM. Since the buffer was too small, the DDM was not incorporated. The file buffer size is specified in the dynamic parameter FSIZE. |
| Actn. | Increase the size of the file buffer. |

NAT2745: No Object Loaded.

| Text | No Object Loaded. |
|-------|---------------------------------|
| Expl. | There was no object qualified. |
| Actn. | Check program and correct error |

NAT2746: Object Loaded.

| Text | Object Loaded. |
|-------|------------------------------------|
| Expl. | The object is successfully loaded. |

NAT2747: Invalid record found.

| Text | Invalid record found. |
|-------|--|
| Expl. | The record, which was read, is invalid, e.g. the length was wrong. |
| | Generate correct records. If the input file was generated by the unload function of MIGRATE utility contact SAG. |

NAT2748: File number must be entered.

| Text | File number must be entered. |
|-------|--|
| | In order to incorporate an FDT, a file number is required to establish the relationship between the FDT and the file. |
| Actn. | Enter a valid file number. |

NAT2749: Warning: KEYWORD not defined.

| Text | Warning: KEYWORD not defined. |
|-------|---|
| - | The Predict data are checked during loading. if at that moment no key exists a warning will be send. The KEYWORDs belonging to this data set could be laoded later. |
| Actn. | Check the keys after all data loaded. |

NAT2750: Warning: OWNER not defined.

| Text | Warning: OWNER not defined. |
|-------|---|
| | During load of Predict data it will be checked that the OWNERS of the loaded object are defined. This message is a warning. Possibly the OWNER records will be loaded afterwards. They must belong to the same data set. |
| Actn. | Check the data after all records are loaded. |

55 Natural System Error Messages 2751-2800

NAT2751: Object replaced.

| Text | Object replaced. |
|------|---|
| - | During the load process an object description in Predict has been replaced. |

NAT2752: File type for file changed to "S".

| Text | File type for file changed to "S". |
|-------|--|
| Expl. | If you load a VSAM file, which was stored in Predict Version 1, the file type is set to "S" in Predict Version 2, because some attributes of the VSAM file definition are missing. |
| Actn. | Change manually the SEQUENTIAL FILE in a VSAM FILE and add the required attributes. |

NAT2753: Adabas field name missing.

| Text | Adabas field name missing. |
|-------|--|
| Expl. | During the load process a field without an Adabas short name was laoded. This message is a warning. Some files require to all fields an Adabas short name. The field was loaded, but the file contains now incorrect data. Please define to those fields the Adabas short names. |
| Actn. | Correct the invalid field. |

NAT2754: FDT incorporated.

| Text | FDT incorporated. |
|-------|---|
| Expl. | The FDT has been incorporated successfully. |

NAT2755: Master field missing.

| Text | Master field missing. |
|-------|--|
| · · | If you load a userview and no related Adabas field in Predict Exists, this message will be sent. |
| Actn. | Load first the related Adabas file. |

NAT2756: Natural Security not installed.

| Text | Natural Security not installed. |
|-------|---|
| Expl. | The Natural Security feature is not installed. No Security options are available. |
| | Either do not specify Security options or install the Natural Security System. |

NAT2757: First character of PREFIX not alpha.

| Text | First character of PREFIX not alpha. |
|-------|--|
| Expl. | The PREFIX must start with an alpha character. |
| Actn. | Check prefix and correct error. |

NAT2758: Only command VERSIONS allowed.

| Text | Only command VERSIONS allowed. |
|-------|---|
| Expl. | Message occurres, if you want to unload predict version 1 data with command "UNLOAD". |
| Actn. | Enter command VERSIONS. |

NAT2759: No related master file found. File not loaded.

| Text | No related master file found. File not loaded. |
|-------|---|
| | If you want to load a User view and no related Adabas file exists, this message will be sent. |
| Actn. | Please load first the Adabas file. |

NAT2760: User exit program missing.

| Text | User exit program missing. |
|-------|---|
| 1 1 | IF a USER EXIT should be activated via the Predict DDA SERVICES the USER EXIT program must exist. |
| Actn. | Catalog the user exit program. |

NAT2761: Enter "O", "N", "Y", or "F".

| Text | Enter "O", "N", "Y", or "F". |
|------|---|
| | The possible values of general system default parameters EDIT OWNER/DESCRPTION are O, N, Y or F. See documentation for further information. |

NAT2762: File is not locked.

| Text | File is not locked. |
|-------|--|
| | If you use the RECOVER function for a file which is not locked, This message will be sent. |
| Actn. | Check FILE-ID. |

NAT2763: USER VIEW not loaded, because related MASTER FILE was rejected.

| Text | USER VIEW not loaded, because related MASTER FILE was rejected. | |
|-------|---|--|
| Expl. | A USER VIEW should be laoded, but the related MASTER FILE was | |
| | rejected, because its file number was not unique. | |
| Actn. | Check the used file numbers. | |

NAT2764: If pre-processor specified, no Natural data allowed.

| Text | If pre-processor specified, no Natural data allowed. | |
|-------|---|--|
| Expl. | Natural parameter data may not be used when deleting active | |
| | cross references using the Predict pre-processor. | |
| Actn. | Do not specify Natural data. | |

NAT2765: If PROGRAM-ID is specified, LIBRARY-ID must be specified too.

| Text | If PROGRAM-ID is specified, LIBRARY-ID must be specified too. |
|-------|--|
| Expl. | If you want an evaluation by PROGRAM name, you must also specify the LIBRARY NAME. Its allowed to specify only a LIBRARY name. |
| Actn. | Specify library name. |

NAT2766: Abend data of preprocessor deleted.

| Text | Abend data of preprocessor deleted. | |
|-------|--|--|
| Expl. | Active references will also be stored in the data dictionary if the | |
| | preprocessor terminates with condition code greater zero. | |
| | These abend data can be deleted by a special function of DDA SERVICES. | |

NAT2767: More than 130 fields are undefined.

| Text | More than 130 fields are undefined. | |
|-------|---|--|
| Expl. | Maximal 130 fields, which are used but not defined in Predict, are displayed. | |
| Actn. | Define the used fields in Predict. | |

NAT2768: Xref data deleted.

| Text | Xref data deleted. |
|-------|--|
| Expl. | This message tells you that active crossreference records have |
| | been deleted successfully. |

NAT2769: Please enter User ID or ".".

| Text | Please enter User ID or ".". |
|-------|---|
| Expl. | When using the owner editor, you may enter the owners of an object. If an owner has no users defined, it will be marked with a "?". |
| | To define one or more users for such an owner, enter .E in the respective editor line; then enter a User ID for the new user description. |
| Actn. | Enter a new User ID or a ".". |

NAT2770: SUPER Natural only possible, if file has security definitions.

| Text | UPER Natural only possible, if file has security definitions. | |
|-------|---|--|
| Expl. | IF Natural Security is active, the generation of a SUPER Natural file entry is only possible if also Security definitions for the file are available. | |
| Actn. | Generate also Security definition. Enter "Y" for Natural Security. | |

NAT2771: Copy-field ID or Copy-file ID missing.

| Text | Copy-field ID or Copy-file ID missing. |
|-------|--|
| | An attempt was made to copy a field without having specified a Copy-field ID. A field can be copied from one file to another or into the same file by changing its name. |
| Actn. | Enter either a Field ID or a File ID. |

NAT2772: Start-field ID not found.

| Text | Start-field ID not found. |
|-------|--|
| | The Start-field ID was not found in the file. A valid Start-field ID must be entered in order to copy fields. |
| Actn. | Enter a valid Start-field ID. |

NAT2773: Start-field ID missing.

| Text | Start-field ID missing. |
|-------|--------------------------------|
| Expl. | No Start-field ID was entered. |
| Actn. | Enter a Start-field ID. |

NAT2774: Do not specify both Field ID and File ID for start field.

| Text | Do not specify both Field ID and File ID for start field. |
|-------|---|
| | The selection can be performed in two ways: either all fields from one file are displayed for selection, or all files containing the field entered are displayed. |
| Actn. | Enter either a Field ID or a File ID; do not enter both. |

NAT2775: No SUPER Natural possible if status private.

| Text | No SUPER Natural possible if status private. |
|-------|---|
| | If Natural Security is active and a file is declared as private no generation of a SUPER Natural file entry is possible. |
| Actn. | Change status of the file, if necessary. |

NAT2776: SUPER Natural file added.

| Text | SUPER Natural file added. |
|------|--|
| Expl | At generation DDM for the file a SUPER Natural entry has been generated. |

NAT2777: Hit enter to return to menu.

| Text | Hit enter to return to menu. |
|------|---|
| | This message is issued when an error is encountered during the generation of a Data Definition Module; a specific error message is also returned with this message. |
| | Hit enter and the menu will be displayed. Hit enter to go back to menu; correct error. |

NAT2778: Invalid offset or length of primary key.

| Text | Invalid offset or length of primary key. |
|-------|---|
| Expl. | This error message occurres at generation DDM of logical VSAM file. Offset and length of the primary key in the logical VSAM file must be equate to the offset and length of the primary key in the physical VSAM file in consideration with the length of the Prefix. If the VSAM prefix was not specified at maintenance logical VSAM file, |
| | the standard VSAM prefix "file number" will be taken. |
| Actn. | Correct offset or length of the primary key in the logical or physical VSAM file. |

NAT2779: Incorrect length for primary key.

| Text | Incorrect length for primary key. |
|-------|------------------------------------|
| Expl. | Correct length of the primary key. |

NAT2780: Field moved successfully.

| Text | Field moved successfully. |
|-------|---|
| Expl. | The field was moved successfully within the file. |

NAT2781: Object purge was not confirmed.

| Text | Object purge was not confirmed. |
|-------|--|
| Expl. | When an object should be deleted in Predict, the system needs an additional confirmation. In the present case, the user abends the PURGE function and the object still remains in the dictionary. |

NAT2782: Object purged successfully.

| Text | Object purged successfully. |
|------|--|
| 1 1 | The object description was deleted from the dictionary. All other entries belonging to the object remain in the dictionary. |

NAT2783: Object scratched successfully.

| Text | Object scratched successfully. |
|-------|---|
| Expl. | The object and all objects belonging to that object have been |
| | deleted from the dictionary. |

NAT2784: Enter "DELETE" or "SCRATCH" or ".".

| Text | Enter "DELETE" or "SCRATCH" or ".". |
|-------|--|
| | The user has been prompted for an confirmation: if "DELETE" is entered, only the specified object will be deleted; if "SCRATCH" is entered, the object and all its dependent objects will be deleted; if input is ".", no object will be deleted. |
| Actn. | Enter the desired option. |

NAT2785: Alternate index not on that offset.

| Text | Alternate index not on that offset. |
|-------|---|
| Expl. | The defined offset of the alternate index is wrong. |
| Actn. | Check offset. |

NAT2786: Invalid length of alternate index.

| Text | Invalid length of alternate index. |
|-------|---|
| Expl. | The defined length of the alternate index is wrong. |
| Actn. | Check length of the alternate index. |

NAT2787: No generation for conceptual or standard file allowed.

| Text | No generation for conceptual or standard file allowed. |
|-------|---|
| | The generation of copy code is not allowed for conceptual and standard files. You must copy the file definition to another file, which is not of type standard or conceptual, then you can start the generation. |
| Actn. | Check file type or use another file. |

NAT2788: No file number available, file not loaded.

| Text | No file number available, file not loaded. |
|-------|--|
| - | All file numbers with the same last 3 digits of the specified file number are used. For example the file numbers 0001, 1001, 2001, 3001,, 9001 all used. |
| Actn. | Use another file number. |

NAT2789: Invalid Adabas file number, not loaded.

| Text | Invalid Adabas file number, not loaded. |
|-------|---|
| Expl. | The last 3 digits of the file number greater 255. |
| Actn. | Check file-number and correct error. |

NAT2790: Enter "DELETE" or ".".

| Text | Enter "DELETE" or ".". |
|-------|---|
| | The user has been prompted for an confirmation: if "delete" is entered, the specified object will be deleted; if "." is entered, no object will be deleted. |
| Actn. | Enter the desired option. |

NAT2791: All keywords have relations.

| Text | All keywords have relations. |
|-------|---|
| Expl. | Every keyword defined in Predict has relations. |

NAT2792: No object was selected.

| Text | No object was selected. |
|------------|--|
| 1 1 | A menu for selecting an object from a list was displayed, and the user was prompted to select one of the objects. None was marked. |

NAT2793: An object was selected.

| Text | An object was selected. |
|------|---|
| | The user was prompted to select an object from a list. An object was marked by the user. This message indicates that Predict has carried out the selection. |

NAT2794: The RENAME function was not performed.

| Text | The RENAME function was not performed. |
|------|--|
| | After the RENAME function has been invoked, the user did not enter the new name for the object. Therefore, the RENAME function did not take place. |

NAT2795: For copy a user view file number cannot change.

| Text | For copy a user view file number cannot change. |
|-------|--|
| Expl. | If you copy a user view from an Adabas master file, the file number cannot be changed. |
| Actn. | Enter the file number of the master file. |

NAT2796: Indicator not "+" OR "-".

| Text | Indicator not "+" OR "-". |
|-------|---|
| Expl. | The indicator tells the editor whether the entered line command should be performed after the line ("+") or before the line ("-") where the command was entered. For example, the line command ".W" will open a window after the line where this command has been entered if the value of the indicator is "+" and will open the window before the mentioned line if the value of the indicator is "-". |
| Actn. | Enter "+" or "-" for the indicator. |

NAT2797: Target file does not exist.

| Text | Target file does not exist. |
|-------|---|
| Expl. | An attempt was made to copy a field to a non-existant file. |
| Actn. | Enter a valid File ID. |

NAT2798: File tested successfully.

| Text | File tested successfully. |
|------|--|
| - | The file was tested against the FDT: no differences between the FDT and the file were found. |

NAT2799: File tested with error.

| Text | File tested with error. |
|-------|---|
| | During a test of a file against the FDT, differences were found (for example, a field name in the file was not found in the FDT). |
| Actn. | Check file and correct error. |

NAT2800: The file entered is not accessible.

| Text | The file entered is not accessible. |
|-------|---|
| - | Adabas was unable to gain access to a file. Probable reasons are: - file not in data base; or - authorization level too low to gain access; or - file is locked. |
| Actn. | Correct error and retry. |

56 Natural System Error Messages 2801-2850

NAT2801: File must be regenerated.

| Text | File must be regenerated. |
|------------|---|
| _ _ | The defined Adabas file is not equivalent to the Adabas FDT. Regenerate the Adabas file or change the file definition in Predict. |
| Actn. | Regenerate the file. |

NAT2802: MODULES/REPORTS do not belong to a PROGRAM.

| Text | MODULES/REPORTS do not belong to a PROGRAM. |
|------|--|
| | The subobject entered does not belong to any object. This message is issued when, for example, a report declared in the dictionary has no relation to any program. |

NAT2803: From-date greater than to-date.

| Text | From-date greater than to-date. |
|-------|--|
| Expl. | The specified to-date must always be greater than from-date. |
| Actn. | Check entered dates and correct error. |

NAT2804: Physical/logical file for userview does not exist.

| Text | Physical/logical file for userview does not exist. |
|-------|--|
| Expl. | No physical or logical file for a userview exists. |
| Actn. | Create a physical or logical file. |

NAT2805: Execution of program stopped with PF-key.

| Text | Execution of program stopped with PF-key. |
|-------|--|
| Expl. | The execution of the program has been stopped with a PF-key. |

NAT2806: Phys. VSAM file for incorporate LOGICAL VSAM file does not exist.

| Text | Phys. VSAM file for incorporate LOGICAL VSAM file does not exist. |
|-------|--|
| | The physical VSAM file (FILE-TYPE "V") must be defined in the dictionary before the related LOGICAL VSAM file (FILE-TYPE "L") can be incorporated. |
| Actn. | Define or INCORPORATE physical VSAM file. |

NAT2807: File does not exist.

| Text | File does not exist. |
|-------|--|
| | An attempt was made to RECOVER a non-existent file. Please enter the correct name of the file which is to be recovered. |
| Actn. | Enter a valid file name. |

NAT2808: File cannot be recovered.

| Text | File cannot be recovered. |
|------------|---|
| _ _ | The file is intact. No inconsistencies were detected; therefore, no RECOVER is permitted/necessary. |
| Actn. | Do not RECOVER intact files. |

NAT2809: Subobjects having no related objects listed successfully.

| Text | Subobjects having no related objects listed successfully. |
|-------|--|
| Expl. | At RETRIEVAL, The sub-objects which have no relation to an object were listed, for example: all files which have no related database are listed. |

NAT2810: All sub-objects have related objects.

| Text | All sub-objects have related objects. |
|-------|--|
| Expl. | At RETRIEVAL, all subobjects, which do not have any related objects |
| | were requested. No subobjects met the required condition. For example: |
| | all files defined in the dictionary have a relation to a report or a |
| | module. |

NAT2811: All objects have related subobjects.

| Text | All objects have related subobjects. |
|------|---|
| | At RETRIEVAL, all objects that do not have any subobjects were requested. No object met the condition. For example: all programs have reports and/or modules. |

NAT2812: The object entered has no subobjects.

| Text | The object entered has no subobjects. |
|------|---|
| | In a RETRIEVAL, an object"s subobjects were requested. This message |
| | informes the user that the object has no sub-objects, for example: |
| | that a file has no fields. |

NAT2813: Objects without subobjects listed successfully.

| Text | Objects without subobjects listed successfully. |
|------|---|
| Exp | . At RETRIEVAL, all objects having no relation to a subobject |
| | were requested. These objects have been displayed successfully. |

NAT2814: Too many continuation cards. Input skipped:

| Text | Too many continuation cards. Input skipped: |
|-------|---|
| | The command input for Predict in batch is delimited. Under special circumstances some input cards are skipped. The skipped parameters are listed. |
| Actn. | Reduce command input. |

NAT2815: Overflow occurred. Parameter possibly skipped:

| Text | Overflow occurred. Parameter possibly skipped: |
|-------|---|
| Expl. | The command input for Predict in batch is delimited. Under some circumstances an overflow may have occurred and not all parameters are recognized by the command processor. The skipped parameters are listed. |
| Actn. | Reduce command input in batch. |

NAT2816: Error description displayed.

| Text | Error description displayed. |
|------|---|
| | In the command line a help request was entered. The error description |
| | for the requested error has been displayed. |

NAT2817: Command help displayed.

| Text | Command help displayed. |
|-------|---|
| Expl. | In the command line a help request was entered. The help description will be displayed. |

NAT2818: Internal error in command processor.

| Text | Internal error in command processor. |
|-------|--|
| Expl. | An internal error has occurred. |
| Actn. | Document the command sequence and contact SAG support. |

NAT2819: Object converted.

| Text | Object converted. |
|------|---|
| 1 1 | The conversion of an object from version 1 format into version 2 format was executed. |

NAT2820: Object has got an old description.

| Text | Object has got an old description. |
|------|--|
| · · | Before the conversion is started an old description for the object has been found. |

NAT2821: Object has got a new description.

| Text | Object has got a new description. |
|-------|--|
| · · | Before the conversion is started a description in version 2 format has been found. |
| Actn. | Delete the new description or do not start the conversion. |

NAT2822: Object conversion listed successfully.

| Text | Object conversion listed successfully. |
|-------|---|
| Expl. | The converted objects have been displayed successfully. |

NAT2823: For object class "ALL" no ID allowed.

| Text | For object class "ALL" no ID allowed. |
|-------|---|
| - | No identification (ID) may be defined when all data of the dictionary should be unloaded or when all unloaded data on the sequential data set should be loaded. |
| Actn. | Do not specify any ID when using the command "ALL". |

NAT2824: System points to a different library.

| Text | System points to a different library. |
|-------|--|
| Expl. | The program implementation pointer consisting of - program id - library - fnr - dbid is not equivalent to the implementation pointer of the system which the program belongs to. The system implementation consists of - library id - fnr - dbid. |
| Actn. | Change the implementation pointer of the program. |

NAT2825: Keys must be different.

| Text | Keys must be different. |
|-------|---|
| Expl. | The specified keywords for an object must be different. |
| Actn. | Check specified keys. |

NAT2826: Synonyms must be different.

| Text | Synonyms must be different. |
|-------|--|
| Expl. | The specified synonyms for an element must be different. |
| Actn. | Enter different synonyms. |

NAT2827: PF-KEY must be less than 25.

| Text | PF-KEY must be less than 25. |
|-------|---|
| Expl. | Predict supports PF-KEY 1 thru PF-KEY 24. |
| Actn. | Enter a valid PF-KEY. |

NAT2828: Maximum page size is 250.

| Text | Maximum page size is 250. |
|-------|---|
| Expl. | The specified page size must be less 251. |
| Actn. | Enter a valid page size. |

NAT2829: Synonym must be 1...9.

| Text | Synonym must be 19. |
|-------|------------------------------------|
| Expl. | Up to 9 synomyms can be specified. |
| Actn. | Use only synonym1 thru synonym9. |

NAT2830: This user is not defined or was purged.

| Text | This user is not defined or was purged. |
|-------|---|
| Expl. | The specified user is not known in Security. For details, consult the |
| | Natural Security documentation and the security notes in the Predict |
| | Reference documentation. |

NAT2831: Invalid password entered.

| Text | Invalid password entered. |
|-------|--|
| Expl. | An invalid password was entered. Either an unauthorized user tried to violate the system or the password was misspelled. For details, consult the Natural Security documentation and the security notes in the Predict documentation. |
| Actn. | Enter the correct password. |

NAT2832: The user is not an authorized owner.

| Text | The user is not an authorized owner. |
|------|---|
| | An attempt was made to execute a function with an object for which the user must be an authorized owner. For details, see the Natural Security documentation and the security notes in the Predict documentation. |

NAT2833: No authorized owners signed with passwords.

| Text | No authorized owners signed with passwords. |
|-------|--|
| Expl. | An authorized owner must sign with his password when a function is |
| | performed on an object not belonging to the user. For details, |
| | see the Natural Security documentation and the security notes in the |
| | Predict documentation. |

NAT2834: Authorized owners must sign.

| Text | Authorized owners must sign. |
|------|--|
| Expl | If a function is to be performed on an object not belonging to the |
| | user and the user is linked to that object, authorized owners |
| | must sign with their passwords. For details, see Natural Security |
| | documentation and the security notes in the Predict documentation. |

NAT2835: User not authorized to generate this DDM.

| Text | User not authorized to generate this DDM. |
|-------|--|
| Expl. | In Natural Security the user is not authorized to generate the Data |
| | Definition Module. For details, see the Natural Security documentation |
| | and the security notes in the Predict documentation. |

NAT2836: No "SCRATCH" because of activated user-exit.

| Text | No "SCRATCH" because of activated user-exit. |
|-------|--|
| | If the user-exit for the purge function is activated, "SCRATCH" of objects is not possible any longer. |
| Actn. | Use the "PURGE" function. |

NAT2837: Not enough owners available.

| Text | Not enough owners available. |
|-------|--|
| Expl. | This message occurs during the purge of an Adabas file, if Security is active. Predict determines the minimum number of security owners of the DDMs related to this Adabas file. For every DDM the owners must sign. Sometimes it might happen, that the established list is not sufficient for Natural Security. In this case, please purge first all related user views and then the Adabas file. |
| Actn. | Delete the userviews. |

NAT2838: Renumber not allowed for user views.

| Text | Renumber not allowed for user views. |
|-------|--|
| Expl. | The function renumber is not allowed for files of type "U" (Userview). |
| Actn. | Renumber the Adabas file. |

NAT2839: No line marked with ".N".

| Text | No line marked with ".N". |
|-------|--|
| Expl. | The edit command "POINT" only makes sense, if a line has been marked with ".N" before. |
| Actn. | Mark a line with ".N" before issuing the edit command "POINT". |

NAT2840: The fields related to the standard file have been listed.

| Text | The fields related to the standard file have been listed. |
|-------|---|
| Expl. | All fields related to the standard file have been displayed |
| | on the screen. |

NAT2841: File number required.

| Text | File number required. |
|-------|---|
| Expl. | The specification of the file number is required. |
| Actn. | Enter a file number. |

NAT2842: File is not a VSAM file.

| Text | File is not a VSAM file. |
|-------|---|
| Expl. | The referenced file is not a VSAM file. |
| Actn. | Check input and correct error. |

NAT2843: Logical VSAM files only for "KSDS" files.

| Text | Logical VSAM files only for "KSDS" files. |
|-------|---|
| | The creation of logical VSAM files are only allowed if the physical file is of type "KSDS". |
| Actn. | Check file type. |

NAT2844: No library specified.

| Text | No library specified. |
|-------|---|
| Expl. | A member and a library must be specified for the PUNCH command. |
| Actn. | Enter a library. |

NAT2845: Related File number only allowed for logical VSAM files.

| Text | Related File number only allowed for logical VSAM files. |
|-------|---|
| | If you add a new file the specification of the related file number is only allowed for logical VSAM files. |
| Actn. | Enter blank for related file number. |

NAT2846: Member punched out on work file 1.

| Text | Member punched out on work file 1. |
|-------|--|
| Expl. | The member specified was punched out on work file 1. |

NAT2847: Number of lines processed.

| Text | Number of lines processed. |
|-------|--|
| Expl. | This message informs the user how many lines were processed. |

NAT2848: File number must change.

| Text | File number must change. |
|-------|--|
| | If you change the file type of a userview, the file number must be changed too. |
| Actn. | Enter a new file number. |

NAT2849: Object not unique.

| Text | Object not unique. |
|-------|---|
| - | The truncated object name, which was checked by the command-processor, is not unique. |
| Actn. | Correct error. |

NAT2850: Do not modify standard attributes.

| Text | Do not modify standard attributes. |
|-------|--|
| - | The currently modified field contains standard attibutes. You may not modify those standards unless you mark the field as nonstandard. |
| Actn. | Enter the correct attribute or mark the field as nonstandard. |

57 Natural System Error Messages 2851-2900

NAT2851: PE-count must be blank or "C".

| Text | PE-count must be blank or "C". |
|-------|--|
| | If "C" is entered, a PE-count field is specified; a blank means that the field is not a counter field. This field-type is used by COBOL, ASM or PL/1 and it contains the number of occurrences of the respective PE-group or MU-field. |
| Actn. | Enter blank or "C". |

NAT2852: Too many parameters. Retry.

| Text | Too many parameters. Retry. |
|-------|--|
| | More than five commands / parameters have been entered in the editor command line at once. |
| Actn. | Do not enter more than five commands / parameters at once. |

NAT2853: The nonstandard flag can only be blank or "N".

| Text | The nonstandard flag can only be blank or "N". |
|-------|--|
| 1 1 | The nonstandard flag defines whether the field is a standard field (flag = " ") or a nonstandard field (flag = "N"). |
| Actn. | Enter "N" or leave blank. |

NAT2854: Field in standard file may not be marked as nonstandard.

| Text | Field in standard file may not be marked as nonstandard. |
|-------|---|
| Expl. | If you mark a standard field as nostandard this message will be sent. |
| Actn. | Enter the standard option. |

NAT2855: Occurrences for multiple value field exceed 191.

| Text | Occurrences for multiple value field exceed 191. |
|-------|--|
| Expl. | By Adabas definition, the number of occurrences must not exceed 191. |
| Actn. | Enter a number less than 192. |

NAT2856: Occurrences for periodic group exceed 99.

| Text | Occurrences for periodic group exceed 99. |
|-------|--|
| Expl. | By Adabas definition, the number of occurrences for a periodic group must not exceed 99. |
| Actn. | Enter a number less than 100. |

NAT2857: Field not found in the file.

| Text | Field not found in the file. |
|-------|---|
| | The field specified does not belong to the file. This message is a warning. The field entered belongs to a group or to a REDEFINE. It is not a real Adabas field. |
| Actn. | Enter a valid field name. |

NAT2858: Field not of type "PE" or "MU".

| Text | Field not of type "PE" or "MU". |
|-------|--|
| | If the PE-count of a field is flagged with a "C", a second field must be defined as PE- or MU-field with the same Adabas short name or the field must be of type PE or MU. |
| Actn. | Correct error. |

NAT2859: Invalid line command found.

| Text | Invalid line command found. |
|-------|--|
| 1 1 | During the edit session an unknown line command has been entered. The valid line commands of each editor are documented in the help screens. |
| Actn. | Enter valid line commands. |

NAT2860: SP/SB/PH Adabas files descriptors must be defined on level 1.

| Text | SP/SB/PH Adabas files descriptors must be defined on level 1. |
|-------|---|
| Expl. | Super-, sub- or phonetic-descriptors must always be defined on level 1 in an Adabas file. Other levels are invalid. |
| Actn. | Enter level 1. |

NAT2861: Adabas name already exists.

| Text | Adabas name already exists. |
|-------|--|
| 1 1 | The entered Adabas name is already in use. The Adabas short name within the file must be unique. |
| Actn. | Enter an unique Adabas short name. |

NAT2862: Format/length option not allowed for group.

| Text | Format/length option not allowed for group. |
|-------|---|
| | For groups, the attributes describing format, length, or suppression options are not allowed. |
| Actn. | Leave these fields blank. |

NAT2863: Descriptor option not allowed for any group.

| Text | Descriptor option not allowed for any group. |
|-------|--|
| Expl. | A group cannot be declared as descriptor. |
| Actn. | Leave the field blank. |

NAT2864: Adabas Short name cannot be changed.

| Text | Adabas Short name cannot be changed. |
|-------|--|
| | After a short name has been defined, it cannot be changed. The short names are used by Adabas and may belong to several files (i.e., master file and Userviews). |
| Actn. | Do not alter the short name. |

NAT2865: Related VSAM file already exists.

| Text | Related VSAM file already exists. |
|-------|--|
| Expl. | The specified new related VSAM file number already exists. |
| Actn. | Enter another related VSAM file number. |

NAT2866: Option must not differ from Adabas-option.

| Text | Option must not differ from Adabas-option. |
|-------|---|
| Expl. | The suppression option entered in the Userview differs from the option entered in the MASTER Adabas FILE. |
| Actn. | Enter the same option as the Adabas-option. |

NAT2867: Field type must be equal to the field type in the Adabas file.

| Text | Field type must be equal to the field type in the Adabas file. |
|-------|---|
| | The field type entered for the Userview is not the same as defined in the master Adabas file. |
| Actn. | Enter the same field type as in the Adabas file. |

NAT2868: Scan value too long or delimiter missing.

| Text | Scan value too long or delimiter missing. |
|-------|---|
| | The "SCAN" command expects a scan value which is not larger than 32 characters or a scan value which is embedded in special characters. The most probable reason for this error is that the scan value begins or ends with a special character. In this case you should enter a scan value which is embedded in delimiter characters. |
| Actn. | Enter a valid scan value. |

NAT2869: Verification not defined.

| Text | Verification not defined. |
|-------|--|
| Expl. | The entered verification-id is not defined in Predict. |
| Actn. | Enter a valid verification. |

NAT2870: You are not authorized to execute this function.

| Text | You are not authorized to execute this function. |
|-------|--|
| Expl. | If Natural Security is active, it is possible that you are not authorized to execute one of the following functions. Add security Purge file Use SUPER Natural Generation of DDM Incorporation DDM |
| Actn. | Contact your DDA. |

NAT2871: DDM of Physical / Logical VSAM file not yet generated.

| Text | DDM of Physical / Logical VSAM file not yet generated. |
|-------|---|
| | Before you may generate DDMs of user views on VSAM files you must generate the DDM of the master VSAM file. |
| Actn. | Generate the DDM of the master VSAM file. |

NAT2872: Physical / Logical VSAM file does not exist.

| Text | Physical / Logical VSAM file does not exist. |
|-------|---|
| | The specified file of type "R" (userview of logical VSAM file) has no related Logical VSAM file or the specified file of type "L" or "W" (logical VSAM file or userview of a VSAM file) has no related physical VSAM file. |
| Actn. | Check file name. |

NAT2873: Physical VSAM DDM must be regenerated.

| Text | Physical VSAM DDM must be regenerated. |
|-------|---|
| | If you want to generate a VSAM DDM for a userview or a logical file and the physical VSAM file has been modified, this message will be sent. |
| Actn. | Generate first the DDM for the physical file. |

NAT2874: LOGICAL VSAM DDM must be regenerated.

| Text | LOGICAL VSAM DDM must be regenerated. |
|-------|---|
| | If you want to generate a DDM of a user view of a LOGICAL VSAM FILE and the LOGICAL VSAM FILE was modified, this message will be send. |
| Actn. | Generate the DDM of the LOGICAL VSAM FILE again. |

NAT2875: DDM is not an Adabas DDM.

| Text | DDM is not an Adabas DDM. |
|-------|--|
| | If you tried to incorporate a non Adabas DDM with the function incorporate DDM, this message will be sent. If the DDM is of type VSAM, use the function incorporate VSAM DDM . |
| Actn. | Check type of DDM. |

NAT2876: Type = application required if lib is specified.

| Text | Type = application required if lib is specified. |
|-------|--|
| Expl. | If the library is specified, the type = application is required. |
| Actn. | Set type to application |

NAT2877: For DBID, FNR: only "*", " " or number allowed.

| Text | For DBID, FNR: only "*", " " or number allowed. |
|-------|--|
| Expl. | The specified DBID or FNR contains an invalid character. |
| Actn. | Enter valid value. |

NAT2878: Improper combination of dbid, fnr, lib and map

| Text | Improper combination of dbid, fnr, lib and map |
|-------|---|
| | The specified search criteria is not allowed. Please look at the help screens for the allowed combinations. |
| Actn. | Enter valid combination of dbid, fnr, lib and map. |

NAT2879: Field without field name found.

| Text | Field without field name found. |
|-------|---|
| | Predict encountered a field definition without a field name. This message is a warning. The record for this field was not unloaded. |
| Actn. | Please added the elements of the file containing this field and enter a valid field name before unloading this file again. |

NAT2880: DDMs compared.

| Text | DDMs compared. |
|-------|--|
| Expl. | The Predict Adabas FILE or User view are compared with the generated |
| | Natural DDM. |

NAT2881: All DDMs documented in Predict.

| Text | All DDMs documented in Predict. |
|-------|--|
| | This message tells you that all DDMs on the Natural system file are documented in the dictionary and the generation log coincides with the data. |
| Actn. | None. |

NAT2882: Invalid validation character.

| Text | Invalid validation character. |
|-------|---|
| | The entered validation character is invalid for this language. Look at the help screen for the valid characters. |
| Actn. | Enter a valid validation character. |

NAT2883: File can only be purged.

| Text | File can only be purged. |
|-------|---|
| 1 4 | After the copy or load of a file this message occurs. Please delete the file and restart the function. |
| Actn. | Delete the file. |

NAT2884: Validation characters are....

| Text | Validation characters are |
|-------|---|
| | The possible validation characters are "©" , "*" , " " and "A" thru "9" for PL/1 "-" , "*" , " " and "A" thru "9" for COBOL |
| Actn. | Enter one of the validation characters shown before. |

NAT2885: Error in editor. Response code received.

| Text | Error in editor. Response code received. |
|-------|--|
| | While manipulating data in the source area (the buffer used by the editor) an error occured. This error is not recoverable and therefore the execution of the currently active program is stopped. |
| Actn. | Document the response code and contact Software AG Technical Support. |

NAT2886: Source Area exhausted.

| Text | Source Area exhausted. |
|-------|--|
| | Some functions of Predict write into the editor buffer in order to store there intermediate results. If this buffer is not large enough to hold all data, this message is issued and the execution of the currently active program is stopped. The size of this buffer is determined by the dynamic parameter ESIZE. |
| Actn. | Start a new Natural session with a larger ESIZE. |

NAT2887: All used files or fields defined.

| Text | All used files or fields defined. |
|-------|--|
| Expl. | No file/field is displayed because all used files/fields |
| | (active references are existing) are defined. |

NAT2888: No field used.

| Text | No field used. |
|-------|--|
| Expl. | No field displayed because no field is used. |

NAT2889: Implementation pointer already exists.

| Text | Implementation pointer already exists. |
|-------|---|
| Expl. | The specified implementation pointer consisting of |
| | - program-name |
| | - library |
| | - fnr |
| | - dbid |
| | already exists. If you want a unique implementation pointer |
| | you must change the specified values. |
| Actn. | Check the specified implementation pointer and correct it. |

NAT2890: All SUPER Natural files defined in Predict.

| Text | All SUPER Natural files defined in Predict. |
|-------|--|
| Expl. | All existing SUPER Natural files are defined in Predict. |

NAT2891: Description must be added.

| Text | Description must be added. |
|------------|--|
| 1 1 | The extended description must be added, if the general system default parameter (DDA services) of the extended description is set. |
| Actn. | Add description. |

NAT2892: Description can not be purged.

| Text | Description can not be purged. |
|-------|---|
| | If the general system default parameter of the extended description is set to "FORCE", no deletion of the description is possible. |
| Actn. | Change general system default parameter if necessary. |

NAT2893: At least three lines must be entered.

| Text | At least three lines must be entered. |
|-------|---|
| | If the general system default parameter for the extended description (DDA services) is set, at least 3 lines must be added. |
| Actn. | Add 3 lines or change system default parameter. |

NAT2894: At least one owner must be added.

| Text | At least one owner must be added. |
|-------|---|
| | If the general system parameter "EDIT OWNER" (via DDA services) is set, at least one owner must be added. |
| Actn. | Add one owner or change system default parameter. |

NAT2895: Owner list must be cataloged.

| Text | Owner list must be cataloged. |
|-------|---|
| Expl. | The added owner list must be confirmed through a CATALOG command. |
| Actn. | Enter CATALOG or SAVE. |

NAT2896: Owner has no users.

| Text | Owner has no users. |
|-------|--|
| | The general system parameter "Edit Owners of an object" is set to "FORCE". In this case you must link via the editor at least one owner to the DD object. For every owner linked to the DD object at least one user has to be linked to the owner, too. |
| Actn. | Enter only owners which have users defined. |

NAT2897: Owner id / user name not unique, user id missing.

| Text | Owner id / user name not unique, user id missing. |
|-------|--|
| Expl. | Predict requires that the userid, which should be maintained, is unique. |
| | Enter a user id. You may use the select function to determine the correct user id. |

NAT2898: No SUPER Natural file.

| Text | No SUPER Natural file. |
|-------|---|
| Expl. | The specified file is not a SUPER Natural file. |
| Actn. | Check the specified file. |

NAT2899: File is not a Natural file.

| Text | File is not a Natural file. |
|-------|---|
| Expl. | The specified file is not a Natural file. |
| Actn. | Check the entered file. |

NAT2900: Object cross-reference displayed.

| Text | Object cross-reference displayed. |
|-------|--|
| Expl. | The cross-reference of the requested objects has been displayed. |

58

Natural System Error Messages 2901-2950

NAT2901: Internal error.

| Text | Internal error. |
|-------|--------------------------------|
| Expl. | An internal error has occured. |
| Actn. | Contact sag support. |

NAT2902: Unknown language in preprocessor found.

| Text | Unknown language in preprocessor found. |
|-------|--|
| Expl. | A unknown language was found by the preprocessor. The preprocessor |
| | terminates abnormally. |
| | The preprocessor accepts two input data fields: |
| | 1. language |
| | 2. program id |
| | valid languages are : BAL and ASM,ASSEMBLER |
| | COBOL |
| | P,PLI,PL1,PL/1,PL/I |
| | COBOL, BAL and ASSEMBLER may be truncated. |
| Actn. | Correct input data and restart the preprocessor. |

NAT2903: No source code as input found.

| Text | No source code as input found. |
|-------|--------------------------------------|
| Expl. | No source code found on work file 1. |
| Actn. | Check work file 1. |

NAT2904: No defaults defined. See DDA.

| Text | No defaults defined. See DDA. |
|-------|---|
| Expl. | For an unknown reason the default record is missing. |
| Actn. | See DDA. The DDA can add the default record via the DDA services. |

NAT2905: To many entries for this command.

| Text | To many entries for this command. |
|-------|--|
| | The number of parameters for a command is restricted. Possibile missing end-exec. The command COPY,FORMAT-BUFFER has 2 parameters The command GENERATE has 12 parameters The command PROGRAM-ID has 1 parameter. |
| Actn. | Check parameters. |

NAT2906: Entry name to long.

| Text | Entry name to long. |
|-------|--|
| Expl. | The given entry was to long. The entry is skipped. |
| Actn. | Check entry name. |

NAT2907: Invalid command in preprocessor.

| Text | Invalid command in preprocessor. |
|-------|--|
| - | Valid preprocessor commands are only : COPY GENERATE FORMAT-BUFFER PROGRAM |
| Actn. | Verify command. |

NAT2908: Unknown keyword.

| Text | Unknown keyword. |
|-------|---|
| Expl. | The entered keyword was not correct. Keyword skipped. |
| Actn. | Verify keyword. |

NAT2909: No program name found.

| Text | No program name found. |
|-------|--|
| | The preprocessor needs a program name to store the active records. The program name can be specified via: INPUT (second parameter) Preprocessor statement (EXEC Adabas PROGRAM-ID) Source language statement (see documentation) |
| Actn. | Check source code or specify a program name via input. |

NAT2910: Numeric data expected.

| Text | Numeric data expected. |
|-------|---|
| - | The preprocessor expected a numeric data field, but it was not numeric. |
| Actn. | Check input data. |

NAT2911: Keyword out of sequence.

| Text | Keyword out of sequence. |
|-------|---|
| Expl. | The keywords of a PREPROCESSOR command are in the wrong sequence. |
| Actn. | Correct sequence of keywords. |

NAT2912: File not found.

| Text | File not found. |
|-------|---|
| Expl. | The given file-id is not (or no longer) defined in Predict. |
| Actn. | Verify the file-id. |

NAT2913: No member generated.

| Text | No member generated. |
|------|--|
| - | For the file was no member generated in Predict. So the copy function could not be executed. |
| | Generate a member for the file and restart the preprocessor or use the generate option of the preprocessor. |

NAT2914: More than 1 member generated.

| Text | More than 1 member generated. |
|-------|--|
| | For this file more than 1 members are generated, but the member, which should be taken, not specified. |
| Actn. | Specify a member and restart the preprocessor. |

NAT2915: Member for this file must be regenerated.

| Text | Member for this file must be regenerated. |
|-------|---|
| | The file is modified after generation and so the member(s) must be regenerated. |
| Actn. | Regenerate member and restart the preprocessor. |

NAT2916: Member not generated for this file.

| Text | Member not generated for this file. |
|-------|---|
| Expl. | The specified member name is not in the generated copy code list of the file. |
| Actn. | Verify which members are generated for the file and restart the preprocessor. |

NAT2917: No change allowed by DDA.

| Text | No change allowed by DDA. |
|-------|---|
| Expl. | The DDA has decided that this value should not be overwritten by the user. The preprocessor has set the value to the default value. |
| Actn. | If necessary modify the default value. |

NAT2918: Buffer name invalid.

| Text | Buffer name invalid. |
|-------|---|
| | The specified buffer name in the command GENERATE or FORMAT-BUFFER must be vaild according to the rules of the used language in the preprocessor. |
| Actn. | Specify a correct buffer name and restart the preprocessor. |

NAT2919: Duplicate field names generated.

| Text | Duplicate field names generated. |
|-------|--|
| Expl. | During generation one or more fields with the same name have been generated. This error may occure because the resulting length of the field name including prefix and suffix is longer than 32 characters and is truncated to 32 characters. |
| Actn. | Regenerate with a shorter prefix and a shorter suffix. |

NAT2920: Invalid level number generated.

| Text | Invalid level number generated. |
|-------|---|
| Expl. | The generate level was to high for cobol(greater than 49). |
| Actn. | Do not specify such a high start-level and level-increment. |

NAT2921: Invalid field name generated.

| Text | Invalid field name generated. |
|------|--|
| | The generated field names are not correct for the source language and the validation character was set to blank. |
| | Specify a synonym for the invalid fields or specify a validation character. |

NAT2922: Field without occurrences found.

| Text | Field without occurrences found. |
|-------|---|
| Expl. | At least 1 periodic group or multiple value field has been found without an explicit occurrence number. If the file is an Adabas file or an userview the default occurrence number of 99 or 191 is assumed for periodic groups or multiple value fields respectively. In all other cases a default of 1 is assumed. |
| Actn. | Supply a value for maximum number of occurrences on field level if defaults are not suitable. |

NAT2923: Fields not initialised.

| Text | Fields not initialised. |
|------|---|
| 1 1 | Periodic-group-field and multiple-value-fields can not be initialised by the value clause. |

NAT2924: Fields with wrong format generated.

| Text | Fields with wrong format generated. |
|-------|---|
| | Fields with wrong format are generated. For example in COBOL the BIT format is not allowed and therefore a CHARACTER format is generated. This message is a warning. Check the generated formats and change it if necessary. |
| Actn. | Check generated format. |

NAT2925: Field names truncated.

| Text | Field names truncated. |
|------|--|
| | If the names are to long they have been truncated. If you want |
| | to eliminate the truncation use only short names. |

NAT2926: Filler generated.

| Text | Filler generated. |
|-------|--|
| Expl. | If no name could be found for an object, because there are only invalide characters, a filler is generated. This message is a warning. |
| Actn. | Check object name and change it if necessary. |

NAT2927: The generated code is missing.

| Text | The generated code is missing. |
|------|--|
| | The generated code for the copy function was not found. Possibily the code is purged by the user. |
| | Generate/regenerate the member for the file in Predict and restart the preprocessor. |

NAT2928: More than one file found.

| Text | More than one file found. |
|-------|---|
| | For the specified search criteria more than one file was found. This message is a warning. |
| Actn. | Specify the search criteria. |

NAT2929: File name not specified.

| Text | File name not specified. |
|-------|---|
| 1 | For the commands COPY,GENERATE,FORMAT-BUFFER the file name must be specified. |
| Actn. | Restart the preprocessor with a specified file name. |

NAT2930: File must be recovered.

| Text | File must be recovered. |
|-------|---|
| · · | A transaction is aborted and therefore the file must be recovered. Use the DDA services to recover the file. |
| Actn. | Use the DDA service function to recover the file. |

NAT2931: No generation for conceptual file.

| Text | No generation for conceptual file. |
|-------|--|
| Expl. | With a conceptual file you cannot start the generation function. |
| Actn. | Use another file type for generation. |

NAT2932: Start level must be 1 thru 40.

| Text | Start level must be 1 thru 40. |
|-------|---|
| Expl. | It is not possible to specify a start level greater 40. |
| Actn. | Verify the value for the start level. |

NAT2933: Level increment must be 1 thru 40.

| Text | Level increment must be 1 thru 40. |
|-------|--|
| Expl. | The specify level increment must be in the value range 1 thru 40. |
| Actn. | Correct the value of the level increment and restart preprocessor. |

NAT2934: Number of comments must be less than or equal to 16.

| Text | Number of comments must be less than or equal to 16. |
|-------|--|
| Expl. | The maximal number of comments is 16. More comments are not allowed. |
| Actn. | Modify the number of comments and restart the preprocessor. |

NAT2935: Please enter "Y" or "N".

| Text | Please enter "Y" or "N". |
|-------|---|
| Expl. | You must specify for the input data "Y" or "N". |
| Actn. | Correct input data. |

NAT2936: Truncation may only be left, rigth or middle.

| Text | Truncation may only be left, rigth or middle. |
|-------|--|
| | The truncation of object name is possible in following ways: "R" - right positions are truncated "L" - left positions are truncated "M" - middle positions are truncated. |
| Actn. | Specify one of this 3 truncation modes. |

NAT2937: Format buffer only possible for files of type "A" or "U".

| Text | Format buffer only possible for files of type "A" or "U". |
|-------|---|
| | Only for Adabas files and userviews a format buffer can be generated. |
| Actn. | Do not try to generate a format buffer for other files. |

NAT2938: Increment + start level must be < 49.

| Text | Increment + start level must be < 49. |
|-------|--|
| Expl. | The sum of the specified values for the start and increment level must less than 49. |
| Actn. | Modify the values of start and increment level. |

NAT2939: Invalid truncation character.

| Text | Invalid truncation character. |
|-------|---|
| Expl. | A invalid truncation character was specified. |
| Actn. | Verify the truncation character. |

NAT2940: No program documentation available.

| Text | No program documentation available. |
|-------|--|
| - | The DDA specified in the system defaults that every entry must be described. The preprocessor checks this constraint and rejects the function, if no documentation is available. |
| Actn. | Enter a Predict documentation. |

NAT2941: Object must be edited.

| Text | Object must be edited. |
|-------|--|
| | If you modify an object and the variable for the edit object in the DDA-Service is set to "Y" or "F", you must edit this object. |
| Actn. | Change variable in DDA-services or edit this object |

NAT2942: Field will be marked non standard.

| Text I | Field will be marked non standard. |
|--------|--|
| t | A field will be marked as NON-STANDARD, i.e. it is no longer connected to a standard file and the field will not be modified via rippling process. |

NAT2943: Type must be blank for PE counter.

| | Type must be blank for PE counter. |
|-------|------------------------------------|
| Expl. | Enter blank for element type. |

NAT2944: No override in VSAM.

| Text | No override in VSAM. |
|-------|--|
| Expl. | No override of format and length in VSAM is allowed. |

NAT2945: Edit mask only allowed for Adabas files and its Userviews.

| Text | Edit mask only allowed for Adabas files and its Userviews. |
|-------|--|
| - | The definition of edit masks is only allowed for Adabas files and Userviews. |
| Actn. | Enter the edit masks in the Adabas file or in the Userview. |

NAT2946: Edit mask must be E1 thru E15.

| Text | Edit mask must be E1 thru E15. |
|-------|---|
| Expl. | Only edit mask E1 thru E15 allowed. |
| Actn. | Check used edit mask and correct error. |

NAT2947: VSAM requires occurrence for PE/MU-FIELDS.

| Text | VSAM requires occurrence for PE/MU-FIELDS. |
|-------|--|
| Expl. | The number of occurrences for a periodic group or a multiple field of VSAM file is required. |
| Actn. | Specify number of occurrences. |

NAT2948: Occurrence number must be same as in master-field.

| Text | Occurrence number must be same as in master-field. |
|-------|--|
| | The number of element-occurrences in a VSAM userview must equal to the occ. of the master-field. |
| Actn. | Enter the valid number of occurrences. |

NAT2949: No occurrence allowed.

| Text | No occurrence allowed. |
|-------|--|
| | The specification of occurrences is only allowed, if the field type is MU or PE. |
| Actn. | Enter blank for number of occurrences. |

NAT2950: Only PR, AL, SA, SV allowed for VSAM files.

| Text | Only PR, AL, SA, SV allowed for VSAM files. |
|-------|---|
| Expl. | In a VSAM file only PR, AL, SA, SV for the descriptor option allowed. |
| Actn. | Change descriptor type. |

59 Natural System Error Messages 2951-3000

NAT2951: Primary key only allowed for "KSDS" files.

| Text | Primary key only allowed for "KSDS" files. |
|-------|---|
| Expl. | The descriptor type "PR" is only allowed for VSAM "KSDS" files. |
| Actn. | Change descriptor type. |

NAT2952: No key allowed for RRDS file.

| Text | No key allowed for RRDS file. |
|-------|---|
| Expl. | Descriptor type must be blank for RRDS files. |
| Actn. | Enter blank for descriptor. |

NAT2953: Descriptor or PE count only allowed for Adabas files.

| Text | Descriptor or PE count only allowed for Adabas files. |
|-------|--|
| - | The definition of a descriptor or a PE count is only allowed for Adabas files. |
| Actn. | Check file type or definiton of descriptor or PE count. |

NAT2954: GR-STRUCT only allowed for PE-GROUPS in Adabas files.

| Text | GR-STRUCT only allowed for PE-GROUPS in Adabas files. |
|-------|---|
| | The option GR-STRUCT defines the FORMAT BUFFER layout of the PE-GROUP. GR-STRUCT = " " indicates that a PE-GROUP is to generated as a group which occurs N times as a whole. GR-STRUCT = "N" indicates that the group is to be generated as a group in which each member occurs N times. Option only valid if the file type is "A" (Adabas) or "U" (Userview). |
| Actn. | Correct error. |

NAT2955: Field not found. hit enter to continue.

| Text | Field not found. hit enter to continue. |
|-------|--|
| Expl. | The specified field not found in Predict. |
| | Enter another field, or hit enter to continue. ATTENTION: if you don"t change it an error occured if you want |

NAT2956: Field name must be specified.

| Text | Field name must be specified. |
|-------|--|
| Expl. | The specified function requires the specification of a field name. |
| Actn. | Enter a field name. |

NAT2957: Alternate index name (DD name) missing.

| Text | Alternate index name (DD name) missing. |
|-------|---|
| Expl. | The name of the alternate index is not specified. |
| Actn. | Enter alternate index name. |

NAT2958: Transaction backout.

| Text | Transaction backout. |
|-------|--|
| | During the adding of a new file another user stores a file with the same file number. Therefore a transaction backout occurred. |
| Actn. | Enter a new file number. |

NAT2959: Security access level must be less security update level.

| Text | Security access level must be less security update level. |
|-------|---|
| · · | The specified security access level of an Adabas file must be less than entered security update level. |
| Actn. | Check the entered security level. |

NAT2960: Primary sequence field not defined.

| Text | Primary sequence field not defined. |
|-------|--|
| Expl. | The primary key of a VSAM file is not defined. |
| Actn. | Enter a primary key for the VSAM file. |

NAT2961: Primary sequence field not inverted.

| Text | Primary sequence field not inverted. |
|-------|---|
| | The defined primary key is not inverted. May be that you have specified the wrong field as primary key. |
| Actn. | Check field. |

NAT2962: PREFIX only allowed for FILE TYPE "L".

| Text | PREFIX only allowed for FILE TYPE "L". |
|-------|--|
| | VSAM PREFIX only allowed for files of type "L" (LOGICAL VSAM FILES). The VSAM PREFIX plus the PRIMARY KEY must be equal in length and offset to the PRIMARY KEY of the physical VSAM file (FILE TYPE "V"). |
| Actn. | Correct error. |

NAT2963: VSAM DD name must be specified.

| Text | VSAM DD name must be specified. |
|-------|---|
| Expl. | The used function requires the specification of the VSAM DD name. |
| Actn. | Enter VSAM DD name. |

NAT2964: File has logical files.

| Text | File has logical files. |
|-------|--|
| Expl. | Only KSDS files may have related logical VSAM files. You have tried to modify the file organisation attribute of a VSAM file from KSDS to ESDS or RRDS. This attribute change is only allowed, if the KSDS file has no logical files. |
| Actn. | Do not change the file organisation attribute of a KSDS file if this file has some related logical files. |

NAT2965: Minimum must be less maximum.

| Text | Minimum must be less maximum. |
|-------|--|
| Expl. | The entered minimum record size is greater than the maximum record size. |
| Actn. | Check entered record size. |

NAT2966: Only KSDS files can be compressed.

| Text | Only KSDS files can be compressed. |
|-------|--|
| Expl. | The specification of COMPRESSION = "Y" is only allowed for KSDS files. |
| Actn. | Enter COMPRESSION = "N". |

NAT2967: Invalid VSAM organization.

| Text | Invalid VSAM organization. |
|-------|--|
| Expl. | Only KSDS, RRDS or ESDS organizations of VSAM files are allowed. |
| Actn. | Enter a valid VSAM organization. |

NAT2968: Invalid file compression.

| Text | Invalid file compression. |
|-------|--|
| Expl. | Only "Y" or "N" could be specified for the file compression. |
| Actn. | Enter "Y" or "N". |

NAT2969: Invalid zone specification.

| Text | Invalid zone specification. |
|------------|---|
| 1 1 | Only the numeric zone specification "F" or "C" of a VSAM file is allowed. |
| Actn. | Enter "F" or "C". |

NAT2971: Blocksize must be greater than record size.

| Text | Blocksize must be greater than record size. |
|-------|--|
| Expl. | It is not allowed to specify a recsize greater blksize for a file. |
| Actn. | Check recsize and correct error. |

NAT2972: Related number must be specified.

| Text | Related number must be specified. |
|-------|---|
| | If you want to add a new logical VSAM file the specification of the related file number is required. |
| Actn. | Enter the related file number. |

NAT2973: Related number not found.

| Text | Related number not found. |
|-------|--|
| Expl. | The specified related file number of a logical VSAM file could not be found. |
| Actn. | Enter the valid related file number. |

NAT2974: Related file not a "KSDS" file.

| Text | Related file not a "KSDS" file. |
|-------|--|
| Expl. | The specified related file of a logical VSAM file must be a "KSDS" file. |
| Actn. | Enter the file number of the related KSDS file. |

NAT2975: Related file number only if file-type = "L".

| Text | Related file number only if file-type = "L". |
|-------|--|
| | The specification of a related file number is only allowed if the file is of type "L" (LOGICAL VSAM FILE). |
| Actn. | Enter blank for related file number. |

NAT2976: Entry point already used.

| Text | Entry point already used. |
|-------|--|
| Expl. | Another module with the same entry point already exists. |
| Actn. | Modify the entry point name. |

NAT2977: Entry points not unique.

| | Entry points not unique. |
|-------|---|
| Expl. | An entry point with that name already exists. |

NAT2978: Invalid Natural pgm,lib name.

| Text | Invalid Natural pgm,lib name. |
|-------|--|
| Expl. | The specified program or library name contains an invalid character. |
| Actn. | Enter a valid program or library name. |

NAT2979: Natural lib only allowed if pgm specified.

| Text | Natural lib only allowed if pgm specified. |
|-------|---|
| Expl. | The Natural implementation pointer consisting of - program-id - library - file number - database number could be incompletely specified. But if the library is defined the program-id must exist. |
| Actn. | Check Natural implementation pointer. |

NAT2980: Natural fnr only allowed if library specified.

| Text | Natural fnr only allowed if library specified. |
|-------|---|
| Expl. | The Natural implementation pointer consisting of - program-id - library - file number - database number could be specified incompletely, but if the file number is defined the library name must exist. |
| Actn. | Check Natural implementation pointer. |

NAT2981: Natural dbid only allowed if fnr specified.

| Text | Natural dbid only allowed if fnr specified. |
|-------|---|
| | The Natural implementation pointer consisting of - program - id - library - file number - database number could be incompletely specified. But if dbid is defined the file number must exist. |
| Actn. | Check Natural implementation pointer. |

NAT2982: COBOL preprocessor terminates abnormally.

| Text | COBOL preprocessor terminates abnormally. |
|-------|---|
| Expl. | PROCEDURE DIVISION not found in the COBOL source program. |
| Actn. | Check COBOL source program and correct error. |

NAT2983: Punch only allowed if member name specified.

| Text | Punch only allowed if member name specified. |
|-------|---|
| · · | If direct punch is required the name of the member must be specified. |
| Actn. | Enter the name of the member. |

NAT2984: SUPER Natural files compared.

| Text | SUPER Natural files compared. |
|-------|--|
| Expl. | The SUPER Natural file has been compared with the stored file definition |
| | in Predict. |

NAT2985: SUPER Natural not installed.

| Text | SUPER Natural not installed. |
|-------|--|
| | If you use a function for which SUPER Natural must be installed this message will be sent. |
| Actn. | Install SUPER Natural. |

NAT2986: Enter "X" or leave blank.

| Text | Enter "X" or leave blank. |
|-------|---|
| Expl. | Each system default marked with "X" can be modified by the user. |
| | A space in this field indicates that the default may not be modified. |

NAT2987: To file does not exist.

| Text | To file does not exist. |
|-------|--|
| Expl. | If you want to copy the file definition from one file to another file, the "TO FILE" must exist. |
| Actn. | Add a new file. |

NAT2988: TO FILE ID must be specified.

| Text | TO FILE ID must be specified. |
|-------|--|
| Expl. | The "TO FILE" must be specified for the copy function. |
| Actn. | Enter a valid "TO FILE". |

NAT2989: To file must be a standard file.

| Text | To file must be a standard file. |
|-------|---|
| | The copy of a standard file is only allowed if the "TO FILE" is also a standard file. |
| Actn. | Enter a valid "TO FILE". |

NAT2990: Push backward not allowed for user views.

| Text | Push backward not allowed for user views. |
|-------|--|
| Expl. | The push backward function is only allowed for Adabas files. |
| Actn. | Modify Adabas file and than use "PUSH BACKWARD". |

NAT2991: You are not owner of the DDM.

| Text | You are not owner of the DDM. |
|-------|---|
| - | If Natural Security is installed and you are not declared as owner of the DDM, this message will be sent. |
| Actn. | Change the Security definition if necessary. |

NAT2992: Enter valid function code or valid command.

| Text | Enter valid function code or valid command. |
|------|---|
| | Enter in the XREF menu one of the indicated function codes or one of the valid commands as described in the help map of the XREF command. |

NAT2993: XREF request disallowed by security definition.

| Text | XREF request disallowed by security definition. |
|------|---|
|------|---|

| Expl. | In a Natural security environment the XREF switch can only be set to a value more detailed as defined in the appropriate |
|-------|---|
| | security profile. |
| | The following table shows the valid combinations: |
| | definition request by the XREF command |
| | in the sec. |
| | profile off on force |
| | ++ |
| | off + + + |
| | on - + + |
| | force ⊚ ⊗ + |
| Actn. | Check data and correct error or contact the DBA to modify the appropriate security profile. |

NAT2994: XREF switch set to FORCE.

| Text | XREF switch set to FORCE. |
|-------|--|
| Expl. | For all following catalog processes Natural will check if the program is documented in Predict and CROSS REFERENCE data will be generated. |

NAT2995: XREF switch set on.

| Text | XREF switch set on. |
|------|---|
| - | For all following catalog processes Natural will generate CROSS REFERENCE data. |

NAT2996: XREF switch set off.

| Text | XREF switch set off. |
|------|--|
| - | For all following catalog processes Natural will not generate any CROSS REFERENCE data. ATTENTION. Existing CROSS REFERENCE DATA of new cataloged programs will be deleted. |

NAT2997: Installed Predict version does not support the function.

| Text | Installed Predict version does not support the function. |
|-------|---|
| 1 1 | The CROSS REFERENCE function will be only supported by a Predict version 2 or higher. |
| Actn. | Please contact the DBA to install an appropriate Predict version. |

NAT2998: Function not possible with DBID = 0.

| Text | Function not possible with DBID = 0. |
|------|---|
| | To generate the Natural cross references the DBID of the Natural system file, where the module is to be stored, must not be zero. |
| | Contact the DBA to generate a valid Natural parameter module or invoke Natural and overwrite the value of the data base identification dynamically. |

NAT2999: Program is not documented in Predict.

| Text | Program is not documented in Predict. |
|-------|--|
| | In case the XREF switch is set to FORCE the Natural program to be cataloged must be documented in Predict. |
| Actn. | Document the program in Predict. |

NAT3000: A non-zero response code was received from the database.

| Text | A non-zero response code was received from the database. |
|-------|---|
| Expl. | The Natural error messages NAT3001 - NAT3999 deal with database response codes; that is, an error message "NAT3nnn" indicates that the database has replied to a command with a response code "nnn". The error may be caused by one of the following: - An invalid request was made to the database. - A malfunction occurred in the database. |
| Actn. | Retain the number of the response code and contact your database administrator. |

60

Natural System Error Messages 3001-3050

NAT3001: ISN list not sorted. DB/FNR :1:/:2:. Subcode :3:.

| Text | ISN list not sorted. DB/FNR/ Subcode |
|-------|---|
| | An ISN list could not be sorted because of either an excessive number of resulting ISNs or a discrepancy between the number of ISNs returned and the actual number of records found (the latter is only possible only if "security by value" is being used). |
| Actn. | Reduce number of ISNs in SORT. |

NAT3002: Not completely executed. DB/FNR/subc/field :1:/:2:/:3:/:4:.

| Text | Not completely executed. DB/FNR/subc/field/// |
|-------|---|
| | The required function has not been executed completely. For an OP command with command option 2 = E or for an RE command, the specified record buffer length was shorter than the length of the ET data read. The record buffer has been truncated. |
| Actn. | Increase the record buffer length or ignore the warning. |

NAT3003: An end-of-file or end-of-list condition detected. DB/FNR :1:/:2:.

Text An end-of-file or end-of-list condition detected. DB/FNR .../....

NAT3004: S2/S9 issued before minimum time betw.synchr.checkpoints.

| Text | S2/S9 issued before minimum time between synchronized checkpoints. |
|-------|---|
| Expl. | Either a S2/S9 command was issued before the minimum time between synchronized checkpoints has elapsed, or the minimum number of commands was not issued. |
| Actn | Check program and correct error. |

NAT3005: Synchronized checkpoint pending.

| Text | Synchronized checkpoint pending. |
|-------|--|
| | Notification is given that a synchronized checkpoint is about to be taken. |
| Actn. | Issue a valid C2/C3 command. |

NAT3007: Sx command interrupted due to time limit. DB/FNR :1:/:2:.

| Text | Sx command interrupted due to time limit. DB/FNR/ |
|-------|--|
| | An Sx command has been interrupted because the maximum amount of time permitted has been exceeded. |
| Actn. | Contact your database administrator. |

NAT3008: Command interrupted to prevent WORK overflow. DB/FNR :1:/:2:.

| Text | Command interrupted to prevent WORK overflow. DB/FNR/ |
|------|--|
| | The command was interrupted to prevent a WORK overflow because of a pending backout operation. |
| | The value specified for the LP parameter might have to be increased. |

NAT3009: Last transaction backed out of database :1:. Subcode :2:.

Text Last transaction backed out of database Subcode

| Expl. | This response is caused by one of the following: |
|-------|--|
| | - The last user transaction has been backed out by Adabas (ET |
| | logic users only) or an exclusive control user (non-ET user) |
| | or an access-only user exceeded the non-activity time limit; |
| | - The nucleus was abnormally terminated and the user issued a |
| | command; |
| | - The protection log area was too small and an internal BT was |
| | executed. |
| | The ADDITIONS 2 field in the CB contains additional information: |
| | Transaction timeout : 0 - TT Security : 5 - SE |
| | Non-activity timeout: 1 - TN Hold queue deadlock : 6 - DL |
| | STOP user : 2 - ST Read consistency : 7 - RC |
| | LP overflow : 3 - LP OP during transaction : 8 - OP |
| | AUTO-RESTART : 4 - AR Open required for user: 9 - OR |
| Actn. | AUTO-RESTART : 4 - AR Open required for user: 9 - OR Check the appropriate reason. |

NAT3010: Too many occurrences for periodic group. DB/FNR :1:/:2:.

| Text | Too many occurrences for periodic group. DB/FNR/ |
|-------|--|
| Expl. | Too many occurrences for a periodic group. |
| Actn. | Check program and correct error. |

NAT3017: Invalid file number. DB/FNR :1:/:2:. Subcode :3:.

| Text | Invalid file number. DB/FNR/ Subcode |
|-------|--|
| Expl. | The file number was invalid. Possible causes are: The file number was either 0 or greater than 255. The file was not in the database. The file was locked. A required Adabas system file was not loaded. |
| Actn. | Make sure that you use the correct file number. |

NAT3018: Incorrect usage of file number. DB/FNR :1:/:2:.

| Text | Incorrect usage of file number. DB/FNR/ |
|-------|--|
| Expl. | The file number was modified between successive L2/L5 calls. |
| Actn. | Check program and correct error. |

NAT3019: Update not permitted for access-only file. DB/FNR :1:/:2:.

| Text | Update not permitted for access-only file. DB/FNR/ |
|-------|--|
| Expl. | An attempt was made to update a file which was opened for access only. |
| Actn. | Check program and correct error. |

NAT3020: Incorrect entry made for a CID value. DB/FNR :1:/:2:.

| Text | Incorrect entry made for a CID value. DB/FNR/ |
|-------|---|
| | One of the following incorrect entries was used for a CID value: - X"00000000" - X"40404040" - X"FFxxxxxx" |
| Actn. | Check program and correct error. |

NAT3021: An invalid CID value was detected. DB/FNR :1:/:2:. Subcode :3:.

| Text | An invalid CID value was detected. DB/FNR/ Subcode |
|-------|--|
| | A time-out occurred because a command ID was not found. This program error can be caused by: - CMD ID being assigned to another Ln command (n = 1,9); - CMD ID being assigned to another file; - CMD ID not found for an S8 command. |
| Actn. | Check program and correct error. |

NAT3022: Invalid command. DB/FNR :1:/:2:. Subcode :3:. Command :4:.

| Text | Invalid command. DB/FNR/ Subcode Command |
|-------|---|
| Expl. | The command entered was invalid: - invalid command code; - access-only user attempted to issue update command; - non-ET-logic user issued BT command; - CLU user issued ET command. |
| Actn. | Check program and correct error. |

NAT3023: Invalid starting ISN specified. DB/FNR :1:/:2:.

| Text | Invalid starting ISN specified. DB/FNR/ |
|-------|---|
| | The starting ISN specified for an L2/L5 command sequence was invalid: - the ISN is not assigned to a record in the file; - the ISN was larger than the MAXISN in effect for the file. |
| Actn. | Check program and correct error. |

NAT3024: Invalid ISN found in ISN buffer. DB/FNR :1:/:2:.

| Text | Invalid ISN found in ISN buffer. DB/FNR/ |
|-------|---|
| - | An ISN = 0 or => the first free ISN or ISN > 16777216 was found in the ISN buffer. |
| Actn. | Correct the ISN buffer. |

NAT3025: ISN in ISN lower limit for S1/S4 not found. DB/FNR :1:/:2:.

| Text | ISN in ISN lower limit for S1/S4 not found. DB/FNR/ |
|-------|---|
| 1 1 | The ISN specified in ISN Lower Limit for an S1/S4 (or S2/S9) command was not found. |
| Actn. | Check program and correct error. |

NAT3026: Invalid ISN buffer length for S9 command. DB/FNR :1:/:2:.

| Text | Invalid ISN buffer length for S9 command. DB/FNR/ |
|-------|---|
| | Either the number of ISNs to be sorted as provided in ISN Quantity was 0, or an incorrect SVC number was specified in the link routine. |
| Actn. | Check program and correct error. |

NAT3027: Search/value buffer overflow. DB/FNR :1:/:2:.

| Text | Search/value buffer overflow. DB/FNR/ |
|-------|--|
| | There was not enough work space available to accommodate the combined sizes of the search and value buffers as indicated in the Search Buffer Length and Value Buffer Length fields. |
| Actn. | Check program and correct error. |

NAT3028: Incorrect descriptor. DB/FNR :1:/:2:. Subcode :3:.

| Text | Incorrect descriptor. DB/FNR/ Subcode |
|-------|---|
| Expl. | Descriptor was invalid for an L3/L6 or S2/S9 command: The field was not a descriptor. The descriptor was changed between successive calls. The descriptor is contained within a periodic group. The ADDITIONS1 field contained a different descriptor than the descriptor contained in the search buffer. |
| Actn. | Check program and correct error. |

NAT3029: Incorrect value repositioning attempted. DB/FNR :1:/:2:.

| Text | Incorrect value repositioning attempted. DB/FNR/ |
|-------|--|
| - | A value repositioning was attempted with an L3/L6 command (bytes 7-8 of the Additions 1 field contain spaces) and the Command Option 2 field did not contain the value "V". The command ID is released. |
| Actn. | Check program and correct error. |

NAT3031: The record does not meet ADASTAR distribution criteria.

| Text | The record does not meet ADASTAR distribution criteria. |
|-------|---|
| Actn. | Correct error in program, or contact your database administrator. |

NAT3032: The ADASTAR NETTAB table does not contain the logical ID.

| Text | The ADASTAR NETTAB table does not contain the logical ID. |
|-------|--|
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3033: ADASTAR has passed the command to the physical node.

| Text | ADASTAR has passed the command to the physical node. |
|-------|--|
| Actn. | No action required. |

| Text | Syntax error detected in format buffer. DB/FNR/ |
|-------|--|
| Expl. | The syntax error may be one of the following: |
| | - The terminating period was missing. |
| | - The first position contains a period. |
| | - Length and/or format was specified with a range definition. |
| | - An invalid element was detected. |
| | - The L9 descriptor name in the search buffer did not agree with |
| | the name in the format buffer. |
| Actn. | Check program and correct error. |

NAT3040: Syntax error detected in format buffer. DB/FNR :1:/:2:.

NAT3041: Error in format buffer. DB/FNR/subc/field :1:/:2:/:3:/:4:.

| Text | Error in format buffer. DB/FNR/subc/field// |
|-------|--|
| Expl. | This error may be caused by one or more of the following: A phonetic descriptor was specified. A field was specified incorrectly. An index for a periodic group or multiple-value field was specified incorrectly. A periodic group was referenced incorrectly. A count was specified for a field which is not a multiple-value field. A multiple-value field was indexed incorrectly. |
| Actn. | Check program and correct error. |

NAT3042: Internal format buffer too small. DB/FNR :1:/:2:.

| Text | Internal format buffer too small. DB/FNR/ |
|-------|--|
| · · | The internal format buffer is too small to generate a format according to the user format buffer definition. |
| Actn. | Increase size of Adabas parameter LFP. |

NAT3043: Descriptor in format and search buffer not equal. DB/FNR :1:/:2:.

| Text | Descriptor in format and search buffer not equal. DB/FNR/ |
|------------|---|
| 1 1 | The descriptor specified in the format buffer did not agree with the descriptor specified in the search buffer. |
| Actn. | Check program and correct error. |

NAT3044: The format buffer was invalid. DB/FNR :1:/:2:.

| Text | The format buffer was invalid. DB/FNR/ |
|------------|---|
| 1 1 | The format buffer was invalid for use with an update command (A1/A4) or an add command (N1/N2). |
| Actn. | Check program and correct error. |

NAT3045: PE/MU overflowed when using N-option for update. DB/FNR :1:/:2:.

| Text | PE/MU overflowed when using N-option for update. DB/FNR/ |
|------------|--|
| 1 1 | Multiple-value field or periodic group overflowed when using the N |
| | option for update. |

NAT3046: Mismatch of format buffer usage for supplied CID. DB/FNR :1:/:2:.

| Text | Mismatch of format buffer usage for supplied CID. DB/FNR/ |
|-------|---|
| Expl. | Mismatch of format buffer usage for the supplied command ID. A test option user has supplied a different format buffer than that of the previous Adabas call. A non-test option user, using global command IDs, may receive this response when a test option user has supplied an incorrect format buffer for the global command ID. A command ID of global ID format buffer has been found in the format pool and has a different file number than the file supplied by the caller.; The file number was changed in subsequent Adabas calls with the same normal or global command ID, independent of the test option. |
| Actn. | Check the usage of the command IDs. |

NAT3047: Maximum value for Adabas parm NISNHQ exceeded. DB/FNR :1:/:2:.

| Text | Maximum value for Adabas parm NISNHQ exceeded. DB/FNR/ |
|-------|--|
| Actn. | Contact your database administrator. |

NAT3048: File / USERID not available at open time. DB/Subcode :1:/:2:.

| Text | File / USERID not available at open time. DB/Subcode/ |
|-------|---|
| Expl. | OP command : |
| | - The requested usage of one or more files conflicts with the |
| | current usage of a file by another user or Adabas utility. |
| | - The USERID provided during the OP command was already |
| | assigned to another user. |
| | - A previously executed Natural session stopped abnormally |
| | without closing the database. The USERID still exists in |
| | the user queue of Adabas. |
| Actn. | The DBA should check for USERID in Adabas user queue and remove it, |
| | if a previously executed Natural session stopped abnormally. |

NAT3049: Compressed record too long. DB/FNR :1:/:2:. Subcode :3:.

| Text | Compressed record too long. DB/FNR/ Subcode |
|-------|--|
| | The compressed record was too long for the protection area (WORK) or the data storage disk device. |
| Actn. | Review possible record sizes of the file concerned. |

NAT3050: A syntax error in the record buffer was detected. DB :1:.

| Text | A syntax error in the record buffer was detected. DB |
|------------|--|
| 1 1 | A syntax error in the record buffer was detected during processing of an OP command. |
| Actn. | Correct the record buffer by changing the OPRB parameter. |

61 Natural System Error Messages 3051-3100

NAT3051: An error in the record buffer was detected. DB :1:.

| Text | An error in the record buffer was detected. DB |
|-------|--|
| | An error in the record buffer was detected during processing of an OP command. |
| Actn. | Correct the record buffer by changing the OPRB parameter. |

NAT3052: Error when processing a buffer. DB/FNR/Subcode :1:/:2:/:3:.

| Text | Error when processing a buffer. DB/FNR/Subcode// |
|-------|---|
| Expl. | An error occurred while processing the record buffer, value buffer, or search buffer: - The value of a P format field was not in packed decimal format. - The value of a U format field was not in unpacked decimal format. - A variable-length field was specified without a length parameter. |
| Actn. | Check program and correct error. |

NAT3053: Record buffer too small. DB/FNR/Subcode :1:/:2:/:3:.

| Text | Record buffer too small. DB/FNR/Subcode// |
|-------|--|
| - | The record buffer must be large enough to contain all required Adabas values in compressed form. |
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3054: Record buffer too long. DB :1:.

| Text | Record buffer too long. DB |
|-------|--|
| | The record buffer for a C5 or ET command was too long. A maximum of 2000 bytes can be written to the checkpoint file. |
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3055: Conversion not possible. DB/FNR/Subcode :1:/:2:/:3:.

| Text | Conversion not possible. DB/FNR/Subcode// |
|-------|--|
| Expl. | An attempted format conversion was not possible due to incompatible data formats or other compatibility problems. During a read-type operation, a field defined with the SQL null (NC) option contained a null value, but the format buffer held no "S" (significant null) indicator field. Additions 2 may contain the field name in the leftmost two bytes; the rightmost two bytes may contain the offset into the record buffer. |
| Actn. | Correct error in program, or contact your database administrator. |

NAT3056: Descriptor value too long. DB/FNR :1:/:2:.

| Text | Descriptor value too long. DB/FNR/ |
|-------|---|
| | The descriptor value was too long: - greater than 126 for a descriptor; - greater than 253 for a superdescriptor. |
| Actn. | Check program and correct error. |

NAT3057: Invalid descriptor specified in search buffer. DB/FNR :1:/:2:.

| Text | Invalid descriptor specified in search buffer. DB/FNR/ |
|-------|--|
| | The descriptor specified in the search buffer of the L9 command was invalid. |
| Actn. | Check program and correct error. |

NAT3058: The format could not be found. DB/FNR :1:/:2:.

| Text | The format could not be found. DB/FNR/ |
|-------|--|
| | The format, as defined within format selection criteria, could not be found. |
| Actn. | Check program and correct error. |

NAT3059: Format conversion of a subfield not possible. DB/FNR :1:/:2:.

| Text | Format conversion of a subfield not possible. DB/FNR/ |
|-------|---|
| Actn. | Check program and correct error. |

NAT3060: Syntax error in search buffer. DB/FNR/subc/field :1:/:2:/:3:/:4:.

| Text | Syntax error in search buffer. DB/FNR/subc/field// |
|-------|--|
| Actn. | Check program and correct error. |

NAT3061: Error in search buffer. DB/FNR/Subcode :1:/:2:/:3:.

| Text | Error in search buffer. DB/FNR/Subcode// |
|-------|--|
| Expl. | The cause of error may be: |
| | - The order of elements was invalid. |
| | - The specified field was not a descriptor. |
| | - An index was missing or invalid. |
| | - Invalid connection of partial criteria. |
| | - Invalid use of a phonetic descriptor. |
| | - The length of a descriptor value was greater than 253. |
| | - An invalid file number. |
| | - An invalid range specification. |
| Actn. | Check program and correct error. |

NAT3062: Search/value buffer length too short. DB/FNR :1:/:2:.

| Text | Search/value buffer length too short. DB/FNR/ |
|-------|---|
| Expl. | The length of the search buffer and/or value buffer, as specified in the search and value buffer length fields, was too short to accommodate the search criteria specified; or the first character in the search buffer was a "."; or the search buffer does not contain a ".". |
| Actn. | Check program and correct error. |

NAT3063: CID specified in search buffer not found. DB/FNR/Sub :1:/:2:/:3:.

| Text | CID specified in search buffer not found. DB/FNR/Sub/ |
|-------|---|
| Expl. | The CID value specified in the search buffer was not found. |
| Actn. | Check program and correct error. |

NAT3064: Requested function cannot be performed. DB/FNR :1:/:2:.

| Text | Requested function cannot be performed. DB/FNR/ |
|-------|--|
| Expl. | The requested function cannot be performed on Adabas system files. |
| Actn. | Refer to the ADAREP output report for a list of the system files. |

NAT3065: Internal error. DB/FNR :1:/:2:.

| Text | Internal error. DB/FNR/ |
|-------|--|
| Expl. | An internal error has occurred: the Adabas nucleus has detected an error in space calculation. |
| Actn. | Contact your database administrator. |

NAT3067: Internal error executing Adabas Sx command. DB/FNR :1:/:2:.

| Text | Internal error executing Adabas Sx command. DB/FNR/ |
|-------|---|
| - | An internal error has occurred while an Adabas Sx command was being executed. |
| Actn. | Retain all related information, and contact Software AG support. |

NAT3070: Overflow in table of sequential commands. DB/FNR :1:/:2:.

| Text | Overflow in table of sequential commands. DB/FNR/ |
|-------|--|
| | The database administrator may increase the value used for the LQ parameter, and/or RC commands may be used to release elements. |
| Actn. | Contact your database administrator. |

NAT3071: Overflow in table of resulting ISN lists. DB/FNR :1:/:2:.

| Text | Overflow in table of resulting ISN lists. DB/FNR/ |
|-------|--|
| | The database administrator may increase the size of the value used for the LI parameter, and/or RC commands may be used to release elements. |
| Actn. | Contact your database administrator. |

NAT3072: An overflow occurred in the user queue. DB/FNR :1:/:2:.

| Text | An overflow occurred in the user queue. DB/FNR/ |
|-------|--|
| - | The database administrator may increase the value used for the NU parameter. |
| Actn. | Contact your database administrator. |

NAT3073: Overflow in WORK dataset for resulting ISN lists.DB/FNR :1:/:2:.

| Text | Overflow in WORK dataset for resulting ISN lists.DB/FNR/ |
|-------|--|
| Expl. | An overflow occurred in the section of the WORK dataset in which resulting ISN lists are stored. The database administrator may increase the size of the WORK dataset, and/or the number of ISN lists saved during an Adabas session may be decreased. |
| Actn. | Contact your database administrator. |

NAT3074: No space on WORK dataset for complex FIND commands.DB/FNR :1:/:2:

| Text | No space on WORK dataset for complex FIND commands.DB/FNR/ |
|-------|--|
| | No space was available on the WORK dataset for complex FIND commands. The database administrator may increase the size of the WORK dataset. |
| Actn. | Contact your database administrator. |

NAT3075: Extent overflow in file control block (FCB). DB/FNR :1:/:2:.

| Text | Extent overflow in file control block (FCB). DB/FNR/ |
|-------|---|
| Expl. | An additional associator or data storage extent was required for a file and the maximum of 4 extents in the FCB had already been allocated. The fifth extent is used only for a command which is being backed out and for AUTORESTART. |
| Actn. | Unload the file and reload it with appropriate initial allocations. |

NAT3076: Overflow in an inverted list index. DB/FNR :1:/:2:.

| Text | Overflow in an inverted list index. DB/FNR/ |
|-------|---|
| Expl. | An overflow occurred in an inverted list index. |
| 1 | Unload/reload the file with an appropriate padding factor for the associator. |

NAT3077: ASSO/DATA - no space available. DB/FNR/Subcode :1:/:2:/:3:.

| Text | ASSO/DATA - no space available. DB/FNR/Subcode// |
|-------|---|
| Expl. | Sufficient space was not available for a required associator or |
| | data storage extent. |
| Actn. | Contact your database administrator. |

NAT3078: Free space table (FST) overflow. DB/FNR :1:/:2:.

| Text | Free space table (FST) overflow. DB/FNR/ |
|------|--|
| | An overflow occurred in the free space table (FST) as a result of ASSO/DATA fragmentation. |
| | Unload files that have allocations adjacent to free blocks and reload them with appropriate initial allocations. |

NAT3079: Hyperexit not available to nucleus. DB/FNR :1:/:2:.

| Text | Hyperexit not available to nucleus. DB/FNR/ |
|-------|---|
| Expl. | Hyperexit not available to nucleus. The following information will be returned in the Additions 2 field of the control block: The two low-order bytes will contain the number of the hyperexit. The two high-order bytes will contain the name of the hyperdescriptor. |
| Actn. | Define the hyperexit and restart the nucleus. |

NAT3080: No user data stored for given user.

| Text | No user data stored for given user. |
|-------|--|
| Expl. | An RE command was issued and no user data was stored for the |
| | user. |

NAT3081: Change to file cluster table prevented successful backout.

| Text | Change to file cluster table prevented successful backout. |
|-------|---|
| | A change made to the file cluster table prevented successful backout of a cluster during Adabas initialization following an abnormal termination. |
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3082: Attempt made to update locked cluster.

| Text | Attempt made to update locked cluster. |
|-------|--|
| Expl. | An attempt was made to update a cluster which was locked. |
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3083: A hyperexit routine returned an invalid ISN. DB/FNR :1:/:2:.

| Text | A hyperexit routine returned an invalid ISN. DB/FNR/ |
|-------|---|
| · · | A hyperexit routine returned an invalid ISN. The following information will be returned in the Additions 2 field of the control block: - The first two bytes will contain the name of the hyperdescriptor. |
| Actn. | Correct the hyperexit routine and restart the database. |

NAT3084: Too many values for a sub-/superdescriptor. DB/FNR :1:/:2:.

| Text | Too many values for a sub-/superdescriptor. DB/FNR/ |
|-------|--|
| Expl. | Too many values were present for a subdescriptor or a superdescriptor. |
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3085: Too many descriptor values for UPDATE/ADD RECORD. DB/FNR :1:/:2:.

| Text | Too many descriptor values for UPDATE/ADD RECORD. DB/FNR/ |
|-------|--|
| - | Too many descriptor values were present for an UDPATE or ADD RECORD command. |
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3086: Hyperdescriptor exit return error. DB/FNR :1:/:2:.

| Text | Hyperdescriptor exit return error. DB/FNR/ |
|-------|---|
| | Possible causes of this error are: - An incorrect sign for a packed descriptor value was created. - A value with an incorrect length byte was returned. |
| Actn. | Contact your database administrator. |

NAT3087: The Adabas buffer pool is locked. DB/FNR :1:/:2:.

| Text | The Adabas buffer pool is locked. DB/FNR/ |
|-------|--|
| Expl. | The length of the Adabas buffer pool (LBP) has to be checked with the operator command DPARM; then the LBP has to be increased with ADARUN. |
| | Contact your database administrator to have the LBP increased; then retry the operation. If the error occurs again, contact Software AG support. |

NAT3088: Insufficient core available. DB/FNR :1:/:2:.

| Text | Insufficient core available. DB/FNR/ |
|-------|---|
| | Sufficient core was not available, although only one user was active. The PARM values relating to core allocation should be verified by the database administrator. |
| Actn. | Contact your database administrator. |

NAT3089: UQE already used. DB/FNR :1:/:2:.

| Text | UQE already used. DB/FNR/ |
|-------|--|
| | The UQE was already in use, and an attempt was made to execute two commands and the same time for the same user. |
| Actn. | Contact your database administrator. |

NAT3090: The ADASTAR NETTAB table exceeds 32 KB.

| Text | The ADASTAR NETTAB table exceeds 32 KB. |
|-------|---|
| Actn. | Contact your database administrator. |

NAT3091: No space available for increasing ADASTAR NETTAB table.

| Text | No space available for increasing ADASTAR NETTAB table. |
|-------|---|
| Expl. | The space for increasing the ADASTAR NETTAB table is not available. |
| Actn. | Contact your database administrator. |

NAT3094: An I/O error occurred on DDWORKR4. DB/FNR :1:/:2:.

| Text | An I/O error occurred on DDWORKR4. DB/FNR/ |
|-------|--|
| Expl. | An I/O error occurred on DDWORKR4. |
| Actn. | Contact your database administrator. |

NAT3095: An I/O error occurred in the WORK LP area. DB/FNR :1:/:2:.

|] | Гext | An I/O error occurred in the WORK LP area. DB/FNR/ |
|---|-------|--|
| I | Actn. | Contact your database administrator. |

NAT3096: An error occurred during repair execution. DB/FNR :1:/:2:.

| Text | An error occurred during repair execution. DB/FNR/ |
|-------|--|
| Actn. | Contact your database administrator. |

NAT3097: An I/O error occurred during buffer flush. DB/FNR :1:/:2:.

| Tex | An I/O error occurred during buffer flush. DB/FNR/ |
|-----|--|
| Act | n. Contact your database administrator. |

NAT3098: Value to be added already exists. DB/FNR :1:/:2:.

| Text | Value to be added already exists. DB/FNR/ |
|-------|---|
| | An attempt was made to add to a unique descriptor a value which already exists. |
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3099: An I/O error occurred. DB/FNR :1:/:2:.

| Text | An I/O error occurred. DB/FNR/ |
|-------|--------------------------------------|
| Actn. | Contact your database administrator. |

62 Natural System Error Messages 3101-3150

NAT3101: Error in Adabas FASTPATH processing. DB/FNR :1:/:2:.

| Text | Error in Adabas FASTPATH processing. DB/FNR/ |
|-------|---|
| Expl. | For explanation of this error, please refer to Adabas |
| | response code 101 in the Adabas Messages and Codes documentation. |

NAT3102: Space calculation error. DB/FNR :1:/:2:.

| Text | Space calculation error. DB/FNR/ |
|-------|----------------------------------|
| Actn. | Retry the OPEN operation. |

NAT3103: An Adabas STAR call was sent to an isolated database.

| Text | An Adabas STAR call was sent to an isolated database. |
|------|---|
| | Stop the database and restart it with the ADARUN |
| | parameter ADASTAR=YES or ADASTAR=NO. |

NAT3104: Program tried to call an Adabas STAR replicated file.

| Text | Program tried to call an Adabas STAR replicated file. |
|-------|--|
| | The program attempted to make a logical call to a physical file defined as an Adabas STAR replicated file. |
| Actn. | Use only the logical file number when issuing calls. |

NAT3106: Record buffer specified in CB too small. DB/FNR :1:/:2:.

| Text | Record buffer specified in CB too small. DB/FNR/ |
|-------|---|
| - | The Prefetch record buffer, as specified in the user control block, is too small. |
| Actn. | Contact your database administrator. |

NAT3107: GETMAIN error or not enough space for Prefetch. DB/FNR :1:/:2:.

| Text | GETMAIN error or not enough space for Prefetch. DB/FNR/ |
|------|--|
| | When performing Prefetch, either a GETMAIN error occurred or there was not enough space available. Prefetch is switched off. |
| | Contact your database administrator. |

NAT3110: The Command ID pool is full. DB/FNR :1:/:2:.

| Text | The Command ID pool is full. DB/FNR/ |
|-------|---|
| Actn. | Increase the size of either or both the ADARUN NQCID or |
| | NU parameters. |

NAT3113: The specified ISN was invalid. DB/FNR :1:/:2:.

| Text | The specified ISN was invalid. DB/FNR/ |
|-------|---|
| Expl. | This error may have one of the following reasons: An HI command was issued with ISN less than MINISN. An N2 command was issued with ISN either equal to 0 or greater than the MAXISN in effect for file. An N2 command was issued and the specified ISN was assigned to another record in file. An A1/A4, L1/L4, E1/E4, or S1/S2/S4 (with FB) command was issued for a non-xistent ISN. |
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3114: E1 command not allowed or specified with ISN=0. DB/FNR :1:/:2:.

| Text | E1 command not allowed or specified with ISN=0. DB/FNR/ |
|------|--|
| Expl | . Either a Refresh File function using the E1 command was issued and not allowed or else ISN=0 was specified for the E1 command. |

| Text | Error from Adabas cluster service. DB/FNR/Subcode// |
|-------|--|
| Expl. | An error was reported by the Adabas cluster messaging service on the |
| | sender"s side. The message was not sent. One of the following subcodes |
| | may be present: |
| | 4 No valid destination(s). |
| | 8 Too many destinations. |
| | 12 Invalid message type. |
| | 16 Invalid environment. |
| | 20 Send buffer length exceeded. |
| | 24 Receive buffer length exceeded. |
| | 28 No replies or acknowledgement(s). |
| | 32 Unable to allocate AXMCB. |
| | 36 Timed out on originating system. |
| | 40 Timed out on destination system. |
| | Further possible subcodes can be found in the Adabas documentation. |
| Actn. | Further possible subcodes can be found in the Adabas documentation. If you are unable to resolve |
| | the problem, contact your Software AG |
| | technical support representative. |

NAT3123: Error from Adabas cluster service. DB/FNR/Subcode :1:/:2:/:3:.

NAT3124: Error from Adabas cluster service. DB/FNR/Subcode :1:/:2:/:3:.

| Text | Error from Adabas cluster service. DB/FNR/Subcode// |
|-------|---|
| Expl. | An error was reported by the Adabas cluster messaging service on the receiver"s side. The message was sent. One of the subcodes described for response code 123 may be present. |
| Actn. | If you are unable to resolve the problem, contact your Software AG technical support representative. |

NAT3125: Internal error from one cluster nucleus. DB/FNR :1:/:2:.

| Text | Internal error from one cluster nucleus. DB/FNR/ |
|-------|--|
| Expl. | An internal error occurred when one cluster nucleus attempted to issue an inter-nucleus command to one or more of the other cluster nuclei. This condition usually leads to an abnormal termination. For an explanation of this response code for non-mainframe databases, see the Adabas documentation. |
| Actn. | Contact your Software AG technical support representative. |

NAT3126: Error during inter-nucleus communication. DB/FNR :1:/:2:.

| Text | Error during inter-nucleus communication. DB/FNR/ |
|-------|--|
| Expl. | A messaging error occurred during inter-nucleus communication: - The nucleus did not respond within the allotted time (see the ADARUN MXMSG parameter); or - one or more problems occurred in what could be a broadcast; that is, a communication with multiple targets. In this case, each individual ACB contains either response code 0, 123 or 124. |
| Actn. | If you are unable to resolve the problem, contact your Software AG technical support representative. |

NAT3129: Attempt to perform unsupported function. DB/FNR :1:/:2:.

| Text | Attempt to perform unsupported function. DB/FNR/ |
|-------|---|
| | In an Adabas cluster environment, the user attempted to perform an Adabas function that is not yet supported by Adabas cluster nuclei. |
| Actn. | Do not attempt to perform an unsupported function. |

NAT3130: Internal error. DB/FNR/Subcode :1:/:2:/:3:.

| Text | Internal error. DB/FNR/Subcode// |
|-------|--|
| Expl. | An internal error identified by one of the following subcodes occurred |
| | in an Adabas Sysplex cluster environment: |
| | 2 User-table entry (UTE) not found in MPM 8 call. |
| | 3 Command-queue entry (CQE) not found in MPM 8 call. |
| | 4 Intermediate user buffer (IUB) not found in MPM 8 call. |
| | 5 Adabas control block not found in MPM 8 call. |
| | 6 Invalid UTE on nucleus chain. |
| | 7 Invalid UTE on user chain add. |
| | 8 Invalid UTE on the "lura" chain (that is, the linked list of UTEs |
| | representing local users remotely assigned) delete. |
| | 23 Invalid CQE. |
| Actn. | Contact your Software AG technical support representative. |

NAT3131: Replication-related error :4:. DB/FNR/Subc. :1:/:2:/:3:.

| Text | Replication-related error DB/FNR/Subc/ |
|-------|--|
| Expl. | During Adabas Event Replicator processing, a response code qualified as shown in the error message was returned. The subcode indicates the reported error condition. See the "Replication Response Codes" section of the Event Replicator documentation. |

| Actn. | The appropriate reaction depends on the specific error condition | 1 |
|-------|---|---|
| | indicated by the response subcode, as given in the documentation. | 1 |

NAT3132: Error while processing LB-field. DB/FNR/Subc :1:/:2:/:3:.

| Text | Error while processing LB-field. DB/FNR/Subc :1:/:2:/:3:. |
|-------|---|
| Expl. | Error while processing LB-field. DB/FNR/Subcode// For the detailed reason see the subcode. |
| Actn. | Contact your database administrator. |

NAT3133: Replication processing error. DB/FNR/Sub :1:/:2:/:3:.

| Text | Replication processing error. DB/FNR/Sub/ |
|-------|--|
| Expl. | An error was detected when an attempt was made to replicate a compressed |
| | record. |
| | The subcode identifies the kind of error: |
| | 1 The function is not permitted for this type of file. The file is an |
| | LOB file. |
| | 2 The compressed input record length is invalid. |
| | 11 The record structure is invalid. |
| | 12 An invalid elementary empty field was encountered. The structure |
| | does not agree with the FDT definition. |
| | 13 An invalid multiple-value field count was encountered. |
| | 14 An invalid periodic group count was encountered. |
| | 15 An invalid structure of an elementary field was encountered. |
| Actn. | Check program and correct error. |

NAT3143: A requested lock could not be granted. DB/FNR :1:/:2:.

| Text | A requested lock could not be granted. DB/FNR/ |
|-------|---|
| | A requested lock could not be granted, because a deadlock situation was detected. |
| Actn. | Contact your database administrator. |

NAT3144: Specified ISN was not in "hold" status. DB/FNR :1:/:2:.

| Text | Specified ISN was not in "hold" status. DB/FNR/ |
|-------|---|
| - | The ISN specified with an UPDATE command was not in "hold" status for the user. |
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3145: ISN already held by another user. DB/FNR/Subcode :1:/:2:/:3:.

| Text | ISN already held by another user. DB/FNR/Subcode// |
|------|--|
| | An attempt was made to hold an ISN which was in hold status for another user and the R option is specified. Hold queue is full and the R option is specified. Hold queue overflow. |

NAT3146: Invalid buffer length. DB/FNR/Subcode :1:/:2:/:3:.

| Text | Invalid buffer length. DB/FNR/Subcode// |
|-------|--|
| Expl. | An invalid buffer length was detected by the Adabas interface routine. |
| Actn. | Contact your database administrator. |

NAT3147: User buffer not accessible. DB/FNR/Subcode :1:/:2:/:3:.

| Text | User buffer not accessible. DB/FNR/Subcode/ |
|-------|---|
| Expl. | User buffer not accessible by the Adabas interface routine. |
| | Check whether the control block, format buffer, value buffer, record buffer and ISN buffer have valid addresses and lengths. Check whether the control block, ISN buffer and record buffer are write protected. |

NAT3148: Database :1: is not active or not accessible

| Text | Adabas is not active or not accessible. |
|-------|--|
| - | The Adabas nucleus was not active or not accessible when the command was issued. |
| Actn. | Start the database or contact your database administrator |

NAT3149: System communication error.

| Text | System communication error. |
|-------|--|
| | A communication error was detected. The additions 2 field contains the system service completion code which caused the error response (for example, exceeded quota, no privilege). |
| Actn. | Check the additions 2 field. |

NAT3150: Too many nuclei used in parallel. DB/FNR :1:/:2:.

| Text | Too many nuclei used in parallel. DB/FNR/ |
|-------|---|
| Expl. | Too many nuclei have been used in parallel. |
| Actn. | Do not use more than 16 different database IDs in a single program. |

63 Natural System Error Messages 3151-3200

NAT3151: A command queue overflow occurred. DB/FNR :1:/:2:.

| Text | A command queue overflow occurred. DB/FNR/ |
|-------|---|
| | The database administrator may increase the value for the NC parameter, and/or the command may be issued when a lower level of command activity is in effect. |
| Actn. | Contact your database administrator. |

NAT3152: Internal user buffer too small. DB/FNR :1:/:2:.

| Text | Internal user buffer too small. DB/FNR/ |
|-------|---|
| | The internal user buffer was not large enough to contain the user buffer areas. The database administrator should increase the value of the LU parameter. |
| Actn. | Contact your database administrator. |

NAT3153: Previous Adabas call still in process. DB/FNR :1:/:2:.

| Text | Previous Adabas call still in process. DB/FNR/ |
|-------|---|
| 1 1 | A "CALL Adabas" was issued by a user while a previous call for the user was still being processed. |
| Actn. | Contact your database administrator. |

NAT3154: Adabas call has been cancelled. DB/FNR :1:/:2:.

| Text | Adabas call has been cancelled by the user. DB/FNR/ |
|-------|---|
| Actn. | No action required. |

NAT3160: Too many ASSO/DATA blocks active in buffer pool. DB/FNR :1:/:2:.

| Text | Too many ASSO/DATA blocks active in buffer pool. DB/FNR/ |
|-------|---|
| | Too many Associator and Data Storage blocks were marked as active in the Adabas buffer pool for a single command. |
| Actn. | Contact your database administrator. |

NAT3161: Invalid RABN chain in header list. DB/FNR :1:/:2:.

| Text | Invalid RABN chain in header list. DB/FNR/ |
|-------|--|
| 1 1 | The RABN chain in the header list of the Adabas buffer pool was invalid. |
| Actn. | Contact your database administrator. |

NAT3162: No space for Adabas buffer pool header blocks. DB/FNR :1:/:2:.

| Text | No space for Adabas buffer pool header blocks. DB/FNR/ |
|-------|---|
| Expl. | No additional space was available for Adabas buffer pool header blocks. |
| Actn. | Contact your database administrator. |

NAT3163: RABN was already in chain. DB/FNR :1:/:2:.

| Text | RABN was already in chain. DB/FNR/ |
|-------|---|
| Expl. | The RABN to be linked into the RABN header chain was already in |
| | the chain. |
| Actn. | Contact your database administrator. |

NAT3164: Too many work areas allocated for command. DB/FNR :1:/:2:.

| Text | Too many work areas allocated for command. DB/FNR/ |
|-------|--|
| Actn. | Contact your database administrator. |

NAT3165: Descriptor invalid or non-existent. DB/FNR :1:/:2:.

| Text | Descriptor invalid or non-existent. DB/FNR/ |
|-------|---|
| 1 | A descriptor name was either invalid or did not exist in the Descriptor Value Table. |
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3166: Error detected in inverted list index. DB/FNR :1:/:2:.

| Text | Error detected in inverted list index. DB/FNR/ |
|-------|---|
| Expl. | An error was detected in an inverted list index; a descriptor |
| | value was not found during a delete operation. |
| | o Locate the descriptor that caused the error in the |
| | additions 2 field of the user control block. |
| | o Run the VERIFY option of ADAINV for this descriptor and save |
| | the output. |
| | o Reinvert the descriptor. |
| | o If necessary, restart the database (if this is possible). |
| | o Send the following information to your nearest support |
| | centre: |
| | the output of the VERIFY option of ADAINV; |
| | - all available PLOGs; |
| | - the FDT of the file containing the error; |
| | - if the nucleus crashed, the crash directory. |
| Actn. | - if the nucleus crashed, the crash directory. See explanation. |

NAT3167: Error detected in inverted list index. DB/FNR :1:/:2:.

| Text | Error detected in inverted list index. DB/FNR/ |
|-------|---|
| Expl. | An error was detected in an inverted list index; a descriptor |
| | value was already present during an insert operation. |
| | o Locate the descriptor that caused the error in the |
| | additions 2 field of the user control block. |
| | o Run the VERIFY option of ADAINV for this descriptor and save |
| | the output. |
| | o Reinvert the descriptor. |
| | o If necessary, restart the database (if this is possible). |
| | o Send the following information to your nearest support |
| | centre: |
| | - the output of the VERIFY option of ADAINV; |
| | - all available PLOGs; |
| | - the FDT of the file containing the error; |
| | - if the nucleus crashed, the crash directory. |
| Actn. | - if the nucleus crashed, the crash directory. See explanation. |

NAT3168: Internal CID for coupling processing not found. DB/FNR :1:/:2:.

| Text | Internal CID for coupling processing not found. DB/FNR/ |
|-------|--|
| Expl. | An internal "CID" required during coupling processing was not found. |
| Actn. | Contact your database administrator. |

NAT3170: Adabas RABN for the command not found. DB/FNR :1:/:2:.

| Text | Adabas RABN for the command not found. DB/FNR/ |
|-------|--|
| Expl. | The Adabas RABN required for the command could not be found. |
| Actn. | Contact your database administrator. |

NAT3171: Constant set used by Adabas not found. DB/FNR :1:/:2:.

| Text | Constant set used by Adabas not found. DB/FNR/ |
|-------|--|
| Actn. | Contact your database administrator. |

NAT3172: ISN less than MINISN or greater than MAXISN. DB/FNR :1:/:2:.

| Text | ISN less than MINISN or greater than MAXISN. DB/FNR/ |
|-------|--|
| | An ISN was either less than the MINISN setting or greater than the |
| | MAXISN setting in effect for the file. |
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3173: An invalid data storage RABN was detected. DB/FNR :1:/:2:.

| Text | An invalid data storage RABN was detected. DB/FNR/ |
|-------|--|
| Actn. | Contact your database administrator. |

NAT3174: Starting RABN for L2/L5 not in address converter. DB/FNR :1:/:2:.

| Text | Starting RABN for L2/L5 not in address converter. DB/FNR/ |
|-------|--|
| | The starting data storage RABN for an L2/L5 command was not contained in the address converter for the file. |
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3176: Error in call to Adabas subroutine/inverted list. DB/FNR :1:/:2:.

| Text | Error in call to Adabas subroutine/inverted list. DB/FNR/ |
|------|---|
| - | An incorrect call to an Adabas subroutine or an inconsistency in an inverted list was detected. |
| | Check program and correct error, or contact your database administrator. |

NAT3177: Record not found in indicated DATA storage block. DB/FNR :1:/:2:.

| Text | Record not found in indicated DATA Storage block. DB/FNR/ |
|-------|--|
| · · | A record could not be found in the Data Storage block which should |
| | have contained it as indicated by the Address Converter. |
| Actn. | Contact your database administrator. |

NAT3178: FDT and internal format buffer not consistent. DB/FNR :1:/:2:.

| Text | FDT and internal format buffer not consistent. DB/FNR/ |
|-------|---|
| - | An inconsistency was detected between the Field Description Table (FDT) and the internal format buffer; or an internal occurred when updating a multiple-value field. |
| Actn. | Contact your database administrator. |

NAT3181: Start of transaction not found on autobackout. DB/FNR :1:/:2:.

| Text | Start of transaction not found on autobackout. DB/FNR/ |
|-------|--|
| | The start of a transaction could not be found when an "autobackout" was executed. |
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3182: Necessary ET data not found in WORK block. DB/FNR :1:/:2:.

| Text | Necessary ET data not found in WORK block. DB/FNR/ |
|-------|---|
| Expl. | The necessary ET data were not found in the appropriate WORK block. |
| Actn. | Correct error or contact your database administrator. |

NAT3183: Internal no. for database I/O operation invalid. DB/FNR :1:/:2:

| Text | Internal no. for database I/O operation invalid. DB/FNR/ |
|-------|---|
| | An internally assigned number for a database I/O operation was found to be invalid. |
| Actn. | Contact your database administrator. |

NAT3184: A phonetic field name could not be found. DB/FNR :1:/:2:.

| Text | A phonetic field name could not be found. DB/FNR/ |
|-------|--|
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3185: ADAM field not found in compressed record. DB/FNR :1:/:2:.

| Text | ADAM field not found in compressed record. DB/FNR/ |
|-------|--|
| Actn. | Contact your database administrator. |

NAT3197: Pool for unique descriptor values too small. DB/FNR :1:/:2:.

| Te | ext | Pool for unique descriptor values too small. DB/FNR/ |
|----|------|--|
| A | ctn. | Contact your database administrator. |

NAT3198: Value for unique descriptor already exists. DB/FNR :1:/:2:.

| Text | Value for unique descriptor already exists. DB/FNR/ |
|-------|--|
| Expl. | An attempt was made to duplicate a value for a unique descriptor. |
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3199: Inconsistency in inverted list index. DB/FNR :1:/:2:.

| Text | Inconsistency in inverted list index. DB/FNR/ |
|-------|---|
| | During an UPDATE opertion, an inconsistency was detected in an inverted list index. |
| Actn. | Contact your database administrator. |

NAT3200: Security violation or invalid cipher code. DB/FNR :1:/:2:.

| Text | Security violation or invalid cipher code. DB/FNR/ |
|-------|--|
| Actn. | Check program and correct error, or contact your database administrator. |

64 Natural System Error Messages 3201-3250

NAT3201: The specified password was not found. DB/FNR :1:/:2:.

| Text | The specified password was not found. DB/FNR/ |
|-------|--|
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3202: Incorrect Adabas password for secured file. DB/FNR :1:/:2:.

| Text | Incorrect Adabas password for secured file. DB/FNR/ |
|-------|---|
| | The specified Adabas password does not allow you to access/update the desired Adabas secured file. Adabas backs out any open transaction. |
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3203: User not authorized to access secured file. DB/FNR :1:/:2:.

| Text | User not authorized to access secured file. DB/FNR/ |
|-------|--|
| Expl. | The file to be accessed is protected by Adabas Security. |
| | To delete a record from that file, you must provide the correct |
| | Adabas password. |
| | Adabas backs out any open transaction. |
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3204: Password already in use. DB/FNR :1:/:2:.

| Text | Password already in use. DB/FNR/ |
|-------|---|
| Expl. | The password supplied is already in use. |
| Actn. | A password name cannot be changed to an existing one. |

NAT3207: Logon phase 1 completed for Adabas ESI interface. DB/FNR :1:/:2:.

| Text | Logon phase 1 completed for Adabas ESI interface. DB/FNR/ |
|------------|--|
| 1 1 | The Adabas ESI interface completed phase 1 of logon and requested phase 2. |
| Actn. | Send a phase-2 logon request to ADAESI. |

NAT3208: Execute a phase 1 logon. DB/FNR :1:/:2:.

| Text | Execute a phase 1 logon. DB/FNR/ |
|-------|---|
| Expl. | As an ESI remote user, you should execute a phase 1 logon. The logon ID and your password will be sent to ADAESI. |
| Actn. | The platform does not have the correct Adabas link routine installed. The response code is intercepted by the workstation Adabas link routine and phase 1 logon is performed. |

NAT3210: Receive buffer lost in NETRDI. DB/FNR :1:/:2:.

| Text | Receive buffer lost in NETRDI. DB/FNR/ |
|-------|---|
| Expl. | A receive buffer was lost in NETRDI. |
| 1 | The DBA may increase the value of the NAB or NC parameter in the NETRDI in the target node. |

NAT3211: Only local utility usage allowed. DB/FNR :1:/:2:.

| Text | Only local utility usage allowed. DB/FNR/ |
|-------|---|
| Expl. | A remote utility cannot be executed because OPTIONS=REMOTE@UTILITIES is set for the database. |
| Actn. | Contact the DBA of the remote database. |

NAT3212: Function not implemented in target architecture. DB/FNR :1:/:2:.

| Text | Function not implemented in target architecture. DB/FNR/ |
|-------|--|
| Expl. | Function not implemented in the target architecture. |
| Actn. | Execute the utility on the target node. |

NAT3213: ID table not found; SVC not properly installed. DB/FNR :1:/:2:.

| Text | ID table not found; SVC not properly installed. DB/FNR/ |
|-------|--|
| Expl. | The Adabas installation procedure was not properly executed. |
| Actn. | Inform your database administrator. |

NAT3214: Internal command issued from ADA V4 ADALINK. DB/FNR :1:/:2:.

| Text | Internal command issued from ADA V4 ADALINK. DB/FNR/ |
|-------|--|
| Actn. | Contact your database administrator. |

NAT3215: Adabas version inconsistency. DB/FNR :1:/:2:.

| Text | Adabas version inconsistency. DB/FNR/ |
|-------|---|
| | SVC 04/16 call received from Adabas Version 4 ADALINK, with Adabas Version 5 user buffer or AMODE=31. |
| Actn. | Contact your database administrator. |

NAT3216: Command rejected by Adabas user exit. DB/FNR :1:/:2:.

| Text | Command rejected by Adabas user exit. DB/FNR/ |
|-------|---|
| Actn. | Contact your database administrator. |

NAT3217: Command rejected by Adabas user exit. DB/FNR :1:/:2:.

| Text | Command rejected by Adabas user exit. DB/FNR/ |
|-------|---|
| Actn. | Contact your database administrator. |

NAT3218: Not enough memory to allocate user buffer. DB/FNR :1:/:2:.

| Text | Not enough memory to allocate user buffer. DB/FNR/ |
|-------|---|
| Expl. | The program/utility has to be run again in a larger region/partition. |
| Actn. | Contact your database administrator. |

NAT3219: Response code from ATM. DB/FNR/Subcode :1:/:2:/:3:.

| Text | Response code from ATM. DB/FNR/Subcode// |
|-------|--|
| | This response code should only occur when Adabas Transaction Manager is being used. 2 The global transaction does not have the status that allows the call. 3 No transaction ID (XID) entries exist. 4 The "R" and "J" options are not supported; or this is not a global transaction. The transaction ID (XID) either does not exist or cannot be found (for example, when the given XID does not belong to the UQE). 5 The record or value buffer definition may be invalid (for example, the length size may be invalid); or the value buffer content may be invalid (for example, it may not contain a valid transaction ID (XID)). 6 The user is not an update or ET user or is already involved in a global transaction. |
| | For further subcodes, see the Adabas documentation |
| Actn. | For further subcodes, see the Adabas documentation Check program and correct error. |

NAT3220: Receiving/relay node unable to allocate buffer. DB/FNR :1:/:2:.

| Text | Receiving/relay node unable to allocate buffer. DB/FNR/ |
|-------|--|
| | The receiving/relay node was unable to allocate a buffer to read the command. If this response is recurrent, the size of the receiving/relay node"s Attached Buffer pool should be increased (see the execution parameter NAB in the NET-WORK CTCS documentation). |
| Actn. | Contact your database administrator. |

NAT3221: Receiving node intercepted abend at SVC 4-call. DB/FNR :1:/:2:.

| Text | Receiving node intercepted abend at SVC 4-call. DB/FNR/ |
|-------|--|
| | The receiving node intercepted an abnormal termination during the Adabas SVC 4-call for the command. |
| Actn. | Contact your database administrator. |

NAT3222: No CQE could be allocated on a relay node. DB/FNR :1:/:2:.

| Text | No CQE could be allocated on a relay node. DB/FNR/ |
|-------|--|
| | No CQE could be allocated on a relay node |
| | (same as Natural error NAT3151 on a receiving node). |
| Actn. | Contact your database administrator. |

NAT3223: CTCS response code: node loop. DB/FNR :1:/:2:.

| Text | CTCS response code: node loop. DB/FNR/ |
|-------|--|
| Actn. | Contact your database administrator. |

NAT3224: Adabas command timed out by receiving/relay node. DB/FNR :1:/:2:.

| Text | Adabas command timed out by receiving/relay node. DB/FNR/ |
|-------|--|
| Expl. | The Adabas command has been timed out by the receiving/relay node. |
| Actn. | Check program and correct error, or contact your database administrator. |

NAT3225: Response code from Entire Net-Work.

| Text | Response code from Entire Net-Work. |
|-------|---|
| Expl. | Response code from Entire Net-Work. |
| | See the Entire Net-Work documentation for more information on the meanings and use of these response codes. |

NAT3226: Response code from Entire Net-Work.

| Text | Response code from Entire Net-Work. |
|-------|---|
| Expl. | Response code from Entire Net-Work. |
| 1 | See the Entire Net-Work documentation for more information on the meanings and use of these response codes. |

NAT3227: Response code from Entire Net-Work.

| Text | Response code from Entire Net-Work. |
|-------|---|
| Expl. | Response code from Entire Net-Work. |
| | See the Entire Net-Work documentation for more information on the meanings and use of these response codes. |

NAT3228: SVC or database not UES-enabled. DB/FNR/Subcode :1:/:2:/:3:.

| Text | SVC or database not UES-enabled. DB/FNR/Subcode// |
|-------|---|
| | ADALCO is UES-enabled, but - the SVC is not UES-enabled (the subcode in Additions 2 is x"01"), or - the target database is not UES-enabled (the subcode in Additions 2 is x"02"). |
| Actn. | Make sure that Adabas and the SVC are at the V712 level and that the database is UES-enabled. |

NAT3229: Command queue element ignored, user already active.DB/FNR :1:/:2:

| | Text | Command queue element ignored, user already active.DB/FNR/ |
|--|-------|--|
| | Actn. | Try again later or cancel the current user. |

NAT3230: Protocol violation of X/Open XA specification. DB/FNR :1:/:2:.

| Text | Protocol violation of X/Open XA specification. DB/FNR/ |
|-------|--|
| | The protocol defined by the X/Open XA specification has been violated. This happens, for example, if a user tries to issue an ET call for an XA transaction. |
| Actn. | Follow the XA specification. |

NAT3231: Response code from Adabas user exit.

| Text | Response code from Adabas user exit. |
|-------|--|
| | This response code is assigned in an Adabas user exit, and its meaning is defined by the user. One example is the response code in the ADALOG log data field issued by user exit 4. |
| Actn. | Refer to the description of user exits in the Adabas User Exits documentation for more information. |

NAT3232: Response code from Adabas user exit.

| Text | Response code from Adabas user exit. |
|-------|--|
| Expl. | This response code is assigned in an Adabas user exit, and its meaning is defined by the user. One example is the response code in the ADALOG log data field issued by user exit 4. |
| Actn. | Refer to the description of user exits in the Adabas User Exits documentation for more information. |

NAT3233: Response code from Adabas user exit.

| Text | Response code from Adabas user exit. |
|-------|--|
| | This response code is assigned in an Adabas user exit, and its meaning is defined by the user. One example is the response code in the ADALOG log data field issued by user exit 4. |
| Actn. | Refer to the description of user exits in the Adabas User Exits documentation for more information. |

NAT3234: Response code from Adabas user exit.

| Text | Response code from Adabas user exit. |
|-------|--|
| Expl. | This response code is assigned in an Adabas user exit, and its meaning is defined by the user. One example is the response code in the ADALOG log data field issued by user exit 4. |
| Actn. | Refer to the description of user exits in the Adabas User Exits documentation for more information. |

NAT3235: Response code from Adabas user exit.

| Text | Response code from Adabas user exit. |
|-------|--|
| | This response code is assigned in an Adabas user exit, and its meaning is defined by the user. One example is the response code in the ADALOG log data field issued by user exit 4. |
| Actn. | Refer to the description of user exits in the Adabas User Exits documentation for more information. |

NAT3236: Response code from Adabas user exit.

| Text | Response code from Adabas user exit. |
|-------|--|
| Expl. | This response code is assigned in an Adabas user exit, and its meaning is defined by the user. One example is the response code in the ADALOG log data field issued by user exit 4. |
| Actn. | Refer to the description of user exits in the Adabas User Exits documentation for more information. |

NAT3237: Response code from Adabas user exit.

| Text | Response code from Adabas user exit. |
|-------|--|
| Expl. | This response code is assigned in an Adabas user exit, and its meaning is defined by the user. One example is the response code in the ADALOG log data field issued by user exit 4. |
| Actn. | Refer to the description of user exits in the Adabas User Exits documentation for more information. |

NAT3238: Response code from Adabas user exit.

| Text | Response code from Adabas user exit. |
|-------|--|
| Expl. | This response code is assigned in an Adabas user exit, and its meaning is defined by the user. One example is the response code in the ADALOG log data field issued by user exit 4. |
| Actn. | Refer to the description of user exits in the Adabas User Exits documentation for more information. |

NAT3239: Response code from Adabas user exit.

| Text | Response code from Adabas user exit. |
|-------|--|
| - | This response code is assigned in an Adabas user exit, and its meaning is defined by the user. One example is the response code in the ADALOG log data field issued by user exit 4. |
| Actn. | Refer to the description of user exits in the Adabas User Exits documentation for more information. |

NAT3240: ATM encountered error :3:. DB/FNR/Subcode :1:/:2:/:4:.

| Text | ATM encountered error DB/FNR/Subcode// |
|-------|---|
| Expl. | ATM encountered an error. The error code can be found in the Additions 2 field of the Adabas control block. The response code may be in the first two bytes of the Additions 2 field. |
| Actn. | Check the meaning of the error code. If the cause of the problem is not apparent, contact your Software AG technical support representative. |

NAT3241: ATM received response code :3:. DB/FNR/Subc. :1:/:2:/:4:.

| Text | ATM received response code DB/FNR/Subc// |
|-------|---|
| Expl. | ATM received an unexpected Adabas response code. The subcode and response code can be found, in that order, in the Additions 2 field of the Adabas control block. If a negative value appears in the Additions 2 field, take its complement: this is the response code returned to the proxy by ATM. For non-mainframe systems, see the Adabas documentation for response codes. |
| Actn. | Check the meaning of the Adabas response code and subcode. If the cause of the problem is not apparent, contact your Software AG technical support representative. |

NAT3242: Double allocation error. DB/FNR :1:/:2:.

| Text | Double allocation error. DB/FNR/ |
|-------|--|
| | A double allocation has been detected between two or more files or a file and the free space table. |
| Actn. | Run ADAVFY without any options to find out which parts of which files are affected. Contact your nearest support centre with the output from ADAVFY. |

NAT3243: Invalid FCB extent detected for file. DB/FNR :1:/:2:.

| Text | Invalid FCB extent detected for file. DB/FNR/ |
|-------|---|
| Expl. | An invalid FCB extent has been detected for a file. |
| Actn. | Contact your nearest support centre. |

NAT3244: Overflow in checkpoint block (CPB). DB/FNR :1:/:2:.

| Text | Overflow in checkpoint block (CPB). DB/FNR/ |
|-------|---|
| Expl. | Overflow in checkpoint block (CPB). |
| Actn. | Start the nucleus to process the entries in the checkpoint block. |

NAT3245: Pending utility entries in UCB. DB/FNR :1:/:2:.

| Text | Pending utility entries in UCB. DB/FNR/ |
|-------|---|
| Expl. | Pending utility entries in UCB. |
| Actn. | Delete the entries with RESET = UCB before executing RECOVER. |

NAT3246: Utility communicaton block (UCB) overflow. DB/FNR :1:/:2:.

| Text | Utility communicaton block (UCB) overflow. DB/FNR/ |
|-------|---|
| Expl. | Utility communication block (UCB) overflow. |
| | Execute the RESET function of ADADBM to remove unused entries from the utility communication block. |

NAT3247: Correct ID not found in UCB. DB/FNR :1:/:2:.

| Text | Correct ID not found in UCB. DB/FNR/ |
|-------|---|
| Expl. | Correct ID not found in the utility communication block. |
| | The utility cannot be restarted. Delete the utility communication block entry and re-run the utility. |

NAT3248: User PID not found in user queue. DB/FNR :1:/:2:.

| Text | User PID not found in user queue. DB/FNR/ |
|-------|---|
| Expl. | User PID not found in the user queue. |
| Actn. | Supply the correct PID. |

NAT3249: User TID not found in user queue. DB/FNR :1:/:2:.

| Text | User TID not found in user queue. DB/FNR/ |
|-------|---|
| Expl. | User TID not found in the user queue. |
| Actn. | Supply the correct TID. |

NAT3250: Function not yet implemented. DB/FNR :1:/:2:.

| Text | Function not yet implemented. DB/FNR/ |
|-------|---------------------------------------|
| Expl. | Function not yet implemented. |
| Actn. | Wait for a later version of Adabas. |

65 Natural System Error Messages 3251-3300

NAT3251: Invalid utility call - versions conflict. DB/FNR :1:/:2:.

| Text | Invalid utility call - versions conflict. DB/FNR/ |
|-------|---|
| Expl. | Invalid utility call - versions conflict. |
| | Check whether utilities and database nuclei are of the same version. Contact your nearest support centre. |

NAT3252: Invalid subroutine call - coding error. DB/FNR :1:/:2:.

| Text | Invalid subroutine call - coding error. DB/FNR/ |
|-------|---|
| Expl. | Invalid subroutine call - coding error. |
| Actn. | Contact your nearest support centre. |

NAT3253: System file not loaded or inconsistent. DB/FNR :1:/:2:.

| Text | System file not loaded or inconsistent. DB/FNR/ |
|-------|---|
| Expl. | System file not loaded or inconsistent. |
| Actn. | Check the system files. |

NAT3254: Command time-out or overflow of attached buffer. DB/FNR :1:/:2:.

| Text | Command time-out or overflow of attached buffer. DB/FNR/ |
|-------|--|
| | One of the following has occurred: - The time limit set by the Adabas parameter CT was exceeded. - A buffer overflow occurred while an attached buffer was being processed. |
| Actn. | Contact your database administrator. |

NAT3255: Attached buffers exhausted. DB/FNR :1:/:2:.

| Text | Attached buffers exhausted. DB/FNR/ |
|-------|--|
| - | All attached buffers were allocated at the time the command was processed. |
| Actn. | Contact your database administrator. |

NAT3288: Invalid column name list of correlation clause.

| Text | Invalid column name list of correlation clause. |
|-------|--|
| | The column name list of the correlation clause has to be enclosed in round brackets and the column names have to be separated by comma. Each column name is a long identifier and has to be unique within the column name list. |
| Actn. | Correct the column name list. |

NAT3289: Invalid table locator reference in FROM clause.

| Text | Invalid table locator reference in FROM clause. |
|-------|--|
| Expl. | A table locator reference has to conform to the following syntax: TABLE (table@locator@variable LIKE table@name) The table@locator@variable has to be of format I4. The table@name has to be the name of a valid DB2 DDM. |
| Actn. | Correct the table locator reference in the FROM clause. |

NAT3290: Invalid table function reference in FROM clause.

| Text | Invalid table function reference in FROM clause. |
|-------|--|
| Expl. | A table function reference has to conform to the following syntax: |
| | TABLE (function@name (expr ,)) correlation@clause |
| | Check for matching opening and closing parentheses. |
| | Table function references must have a correlation clause. |
| | The function@name is a long identifier; it can be qualified by a |
| | schema@name, which is a short identifier. |
| Actn. | Correct the table function reference in the FROM clause |

NAT3291: Invalid CAST expression.

| Text | Invalid CAST expression. |
|-------|---|
| - | A CAST expression has to conform to the following syntax: CAST (expression AS data@type) Check the correct setting of parentheses and keywords. The data@type can be either a built-in data type or a distinct@type, which is a long identifier that can be qualified by a schema name (short identifier). |
| Actn. | Correct the CAST expression. |

NAT3292: Invalid value specified as QUERYNO.

| Text | Invalid value specified as QUERYNO. |
|-------|---|
| Expl. | The QUERYNO has to be specified as a non-negative integer number. |
| Actn. | Specify a non-negative integer number as QUERYNO. |

NAT3293: Content of scroll variable is invalid at offset :1:.

| Text | Content of scroll variable is invalid at offset |
|-------|---|
| Expl. | |
| | rule: <sensitivity> <direction> <integer></integer></direction></sensitivity> |
| | - <sensitivity> is optional and can be either INSENSITIVE or SENSITIVE.</sensitivity> |
| | - <direction> can be one of the following: NEXT, PRIOR, FIRST, LAST,</direction> |
| | CURRENT, BEFORE, AFTER, RELATIVE, ABSOLUTE. The default is NEXT. |
| | - <integer> has to specified if <direction> is RELATIVE or ABSOLUTE.</direction></integer> |
| | It has to be a integer number, like -5 or 0 or 6. It cannot be |
| | specified with any <direction> other than RELATIVE or ABSOLUTE.</direction> |
| | The specifications of <sensitivity> <direction> <integer></integer></direction></sensitivity> |
| | have to be separated from one another by one or more spaces. |
| Actn. | Correct the content of the scroll variable. |

NAT3294: SENSITIVE STATIC not allowed for READ-ONLY cursors.

| Text | SENSITIVE STATIC not allowed for READ-ONLY cursors. |
|-------|--|
| Expl. | SENSITIVE STATIC SCROLLABLE cursors are only allowed if the associated query is not READ-ONLY. Queries are READ-ONLY if they contain UNION, GROUP BY, HAVING, or nested TABLE expressions, and if they are used in a READ RESULT SET statement. |
| Actn. | Either change the query, or change to INSENSITIVE STATIC SCROLL cursors. |

NAT3295: Conversion of DATE/TIME string :1: failed with error :2:.

| Text | Conversion of DATE/TIME string failed with error |
|-------|--|
| Expl. | The conversion of a DB2 DATE/TIME string failed with the Natural error indicated in this message, because the DATE/TIME string received from DB2 could not be converted to a Natural date/time variable. This could happen if, for example, a date prior to 01.01.1582 stored in DB2 is to be placed into a Natural date variable. This also occurs if a DB2 TIME string is retrieved which is either "00:00 AM" or "24.00.00". See the Natural error code for further information. |
| Actn. | Do not use DATE/TIME strings which cannot be handled by Natural. |

NAT3296: Limit of successive "not found" conditions exceeded.

| Text | Limit of successive "not found" conditions exceeded. |
|-------|---|
| Expl. | The limit of successive "not found" (sqlcode +100) conditions has been exceeded. This occurs if, within a processing loop involving scrollable cursors, the number of "not found" conditions exceeds its limit. The limit is 5. The processing loop is closed. The counter of successive "not found" conditions is reset when a condition other than "not found" occurs, or when a terminal I/O occurs. The limit check is performed to avoid undesired database loops. |
| Actn. | Change program logic to avoid this condition. |

NAT3297: NDB :1: conversion failed with FC :2: / RC :3: :4: :5:

| Text | NDB :1: conversion failed with FC :2: / RC :3: :4: :5: |
|-------|---|
| Expl. | NDB Stored Procedures encoded with UNICODE using Natural alphanumeric fields (A) receive UTF8 encoded data which have to be converted to EBCDIC. This conversion failed with the specified function and reason code. :4: is the destination length, and :5: is the destination length necessary to fully convert the UTF8 data to EBCDIC. |
| Actn. | Contact technical support. |

NAT3298: Error during Multifetch: :1:.

| Text | Error during Multifetch: |
|-------|--|
| Expl. | During creation of the NDB Multifetch buffer (DB2SIZE6) an error has occurred; the error message indicates which kind of error. Usually, this is a getmain error or an internal error. |
| Actn. | In the case of a getmain error, either increase the thread size or decrease the multifetch factor specified in the program. In the case of an internal error, contact Natural support. |

| Text | Rowset positioning requires integer value or variable. |
|-------|---|
| Expl. | The Rowset positioning clause requires the specification of an integer value or variable which determines the size (number of rows) of the multi-fetch buffer. The Rowset positioning clause has the following syntax: WITH ROWSET POSITIONING FOR int ROWS where "int" can be an integer numeric constant or a variable of format/length I4. |
| Actn. | Correct the Rowset positioning clause accordingly. |

NAT3299: Rowset positioning requires integer value or variable.

NAT3300: Internal Adabas error :1: occurred.

| Text | Internal Adabas error :1: occurred. |
|-------|---|
| Expl. | Adabas has encountered an internal error. |
| Actn. | For more information see: Internal Adabas Error Messages. |

66 Natural System Error Messages 3301-3350

NAT3301: The version of Adabas is not valid for database.

| Text | The version of Adabas is not valid for database. |
|-------|---|
| | This version of Adabas is obsolete, it does not correspond to the database. The version of Adabas is too old to run with the database. The database was created with a newer version of Adabas or it was upgraded. |
| Actn. | A newer version of Adabas must be used. |

NAT3302: Database obsolete for this Adabas version. Use Upgrade utility.

| Text | Database obsolete for this Adabas version. Use Upgrade utility. |
|-------|--|
| Expl. | The version of Adabas does not correspond to the database. |
| 1 | Use the upgrade function of Database Services for nonactive databases to convert the database. |

NAT3303: Access denied. A single user database is being used.

| Text | Access denied. Database already used in single user mode. |
|-------|--|
| - | A database which is used in single user mode cannot be accessed by another user. |
| Actn. | Synchronize usage of database. |

NAT3304: Multi user database can not be used in single user mode.

| Text | Multi user database can not be used in single user mode. |
|-------|--|
| - | A database being used in multi user mode cannot be accessed by another user in single user mode. |
| Actn. | Synchronize usage of database. |

NAT3305: Path or filename not found.

| | Path or filename not found. |
|-------|----------------------------------|
| Actn. | Check specified path / filename. |

NAT3306: The version of Adabas is already valid for database.

| Text | The version of Adabas is already valid for database. |
|-------|--|
| · · | The version of Adabas already corresponds to the database. It is not neccessary to run the Upgrade utility. |
| Actn. | Do not run the Upgrade utility. |

NAT3350: Internal Entire DB error :1: occurred.

| Text | Internal Entire DB error :1: occurred. |
|-------|---|
| Expl. | Entire DB has encountered an internal error. |
| Actn. | For more information see: Entire DB Error Messages. |

67 Natural System Error Messages 3351-3400

NAT3400: The defined database handler is not available.

| Text | The defined database handler is not available. |
|-------|--|
| Expl. | The database has been defined to be handled by a specific database handler. However, the handler specified is not available. |
| Actn. | Make the specific database handler available or change the database assignment in the global configuration file using the NATPARM utility. |

68

Natural System Error Messages 3401-3450

NAT3401: NAT object STOWed for :1: but executed under :2:.

| Text | NAT object STOWed for but executed under |
|-------|--|
| | The DBID used when stowing the Natural object is assigned to database type .1. but at runtime this DBID is assigned to database type .2. |
| Actn. | The DBID used at stow time and at runtime must be assigned to the same database type. |

NAT3402: Unknown DB response code :4:. DB/FNR/Subcode :1:/:2:/:3:.

| Text | Unknown DB response code DB/FNR/Subcode// |
|-------|--|
| Expl. | An unknown response code was received from the Adabas interface. |
| Actn. | Check program and correct error. |

NAT3403: ADAMODE was changed from :1: to :2:.

| Text | ADAMODE was changed from :1: to :2:. |
|-------|---|
| | Natural was started with ADAMODE=:1:. This mode is not supported by the database, or Natural could not allocate the resources required to execute in this mode. Natural has switched automatically to ADAMODE=:2:. The original error message, the technical reason, was issued prior to this message, and can be viewed with the LASTMSG command. |
| Actn. | Contact your Natural/Adabas administrator. |

NAT3410: No Natural ICU handler available.

| Text | No Natural ICU handler available. |
|-------|---|
| Expl. | The Natural ICU handler is not available. Possible reasons are: The ICU handler module is not linked to Natural or cannot be loaded. The session profile parameter CFICU is set to OFF. An error occurred during the initialization of the Natural ICU. |
| Actn. | Depends on the reason of the error. If an initialization error has occurred, check the session initialization error messages. |

NAT3411: Code page :1: not available.

| Text | Code page not available. |
|-------|---|
| Expl. | ICU (International Components for Unicode) is the engine to support code pages and Unicode in Natural. Code pages are defined in ICU in a data file that is linked to the nucleus or loaded dynamically. If the code page is not available, it is not part of the data file used. |
| Actn. | Please contact Software AG support. |

NAT3412: Internal error from ICU: :1:.

| Text | Internal error from ICU: |
|-------|---|
| Expl. | ICU (International Components for Unicode) is the engine to support code pages and Unicode in Natural. Possible reasons for internal errors of ICU are: - memory allocation errors, - internal program errors, - corrupted definition files of converters, - missing resources in data files. |
| Actn. | Please contact Software AG support. |

NAT3413: Conversion error, at least 1 code point not translated. H":1:"

| Text | Conversion error, at least 1 code point not translated. H"" |
|-------|---|
| Expl. | If, during Unicode conversion or the conversion from one code page to another, a code point or character cannot be converted to the desired destination code page, a code-page-specific substitution character is used instead. The generation of this message depends on the CPCVERR=ON/OFF option in the SET GLOBALS statement. The first failed code point of the source string is displayed in hexadecimal format at the end of the message. |

Actn. Check the content of the input/target field of the conversion.

NAT3415: Conversion result is truncated.

| Text | Conversion result is truncated. |
|-------|---|
| - | During Unicode conversion or the conversion from one code page to another, the result in the target field has been truncated. |
| Actn. | Check the length of the target field. |

NAT3416: Length/format of operand is incompatible with code page.

| Text | Length/format of operand is incompatible with code page. |
|-------|--|
| Expl. | For a Unicode conversion, or a conversion from one code page to another, the format and length of source/target fields must be compatible with the corresponding code page. Example 1: The source/target field is defined as (Bn), but the value of <minimum bytes="" code="" per="" point=""> of the relevant code page is > n; this means that not even one code point could be stored in the field. Example 2: For many code points, the minimum and maximum bytes per code point are identical. Before the conversion, it is checked whether the code points fit into the defined length. If they do not, this message is issued. This is to avoid the truncation of code point values.</minimum> |
| Actn. | Check the lengths of the source and target operands. |

NAT3417: The used code page name is ambiguous in this context.

| Text | The used code page name is ambiguous in this context. |
|-------|---|
| | The target code page specified in MOVE ENCODED statement must be unambiguous. However, specifying "UTF-16" or "UTF-32" does not uniquely identify a target code page. |
| Actn. | Instead of "UTF-16" and "UTF-32", specify "UTF-16BE" or "UTF-16LE", and "UTF-32BE" or "UTF-32LE" respectively. |

NAT3418: ICU Data Library :1: cannot be loaded (:2:).

Text ICU Data Library ... cannot be loaded (...).

| Expl. | The data library is treated like an external program. |
|-------|---|
| | The specified external data library could be neither loaded dynamically |
| | nor located statically. See the supplied operating-system/TP-monitor |
| | return code of the failing LOAD request for details. |
| | Possible reasons: |
| | - The data library to be loaded dynamically is not contained in the |
| | load libraries currently defined to Natural. |
| | - Under CICS: The data library is not defined to CICS. |
| | - There was not enough storage available to load the data library |
| | dynamically (under Com-plete: the Com-plete thread was too small). |
| | - The limit for the number of programs (data libraries) to be |
| | dynamically loaded was exceeded. |
| | - For static data library: The data library is not defined in NATPARM |
| | with the CSTATIC parameter or not linked to the NATPARM module. |
| Actn. | with the CSTATIC parameter or not linked to the NATPARM module. Make sure that the data library |
| | is contained in a library available |
| | to or linked to Natural. Contact your Natural administrator concerning |
| | the setting of the Natural profile parameter CDYNAM and CSTATIC. |
| 1 | |

NAT3419: Local ICU buffer pool cannot be used. RC=:1:

| Text | Local ICU buffer pool cannot be used. RC= |
|-------|--|
| Expl. | The message is displayed at session start if the local ICU buffer pool cannot be used. The reason code (RC) indicates the reason for this message: RC=1 - Local ICU buffer pool is not available. RC=2 - Size of local ICU buffer pool is too small. RC=3 - Local ICU buffer pool is already used by a different ICU nucleus. If CFICU subparameter BPONLY=ON, the message leads to a termination of the ICU initialization with the consequence that no ICU handler is available for the current Natural session. If CFICU subparameter BPONLY=OFF, the required buffers are allocated in the Natural thread. |
| Actn. | Make local ICU buffer pool available or increase size of the local ICU buffer pool. |

NAT3420: Source area conflict between code point :1: and code page :2:.

Text Source area conflict between code point ... and code page

| Expl. | A conversion error occurs either when the source is loaded to the |
|-------|--|
| | source area or when a changed source area is saved. |
| | The source area has Unicode format; conversions between Unicode and |
| | code page are necessary for several commands. Possible conflicts: |
| | 1. The source is opened with the wrong code page: Define the correct |
| | code page either by changing the CP profile parameter or by |
| | defining a dedicated code page for this source. |
| | 2. The source, which was changed, contains characters which are not in |
| | the code page: Either remove characters or change the code page of |
| | the source (e.g. to UTF-8) so that all characters can be converted. |
| Actn. | See explanation. |

NAT3421: Source with code page :1: cannot be opened.

| Text | Source with code page cannot be opened. |
|-------|---|
| Expl. | This Natural source was saved with a code page which differs from the default code page of the current Natural session. The native Unix editors cannot open this source. You have to open this source with Natural Studio in a SPoD environment. |
| Actn. | Open the source with Natural Studio. |

NAT3422: Character :1: is not in code page :2:.

| Text | Character is not in code page |
|-------|--|
| Expl. | During compilation a character was detected which is not contained in the code page. Keywords, variable names, constants of format A (""), etc., must be in the denoted code page. Unicode characters may only be used in the following context: - constants of format U (U"") or - characters within the EMU, ICU, LCU and TCU parameters or - within comments. |
| Actn. | Either use the corresponding syntax for Unicode characters or check the code page. |

NAT3423: Maximum line length exceeded in line :1:.

| Text | Maximum line length exceeded in line |
|-------|--|
| | The source area has Unicode UTF-16 format. When you save a source, it is converted from UTF-16 to the source encoding, which can change the size (in code points) of a character. This error occurs because the current source contains a line which, after the conversion, exceeds the maximum line length. |
| Actn. | Either split the line or choose another encoding for saving the source. |

Natural System Error Messages 3451-3500

NAT3493: ETP database driver not available.

69

| Text | ETP database driver not available. |
|-------|--|
| Expl. | The ETP database driver was not installed. |
| Actn. | Contact your natural administrator. |

NAT3494: Update to destribution key not allowed.

Text Update to destribution key not allowed.

NAT3495: ETP internal table overflow.

| Text | ETP internal table overflow. |
|-------|------------------------------|
| Expl. | Internal program error. |
| Actn. | Call the SAG support. |

NAT3496: Simultaneous update to more than one database not allowed

| Text | Simultaneous update to more than one database not allowed |
|-------|---|
| Expl. | This is an ETP restriction. |
| Actn. | revise your Natural program. |

NAT3499: LFILE 200 for administration file not defined or ETPSIZE=0

| Text | LFILE 200 for administration file not defined or ETPSIZE=0 |
|-------|---|
| Expl. | LFILE 200 and ETPSIZE must be specified in NATPARM |
| | Specify LFILE 200 and ETPSIZE in NATPARM Contact your natural administrator. |

NAT3500: Statement not allowed for SQL databases.

| Text | Statement not allowed for SQL databases. |
|-------|---|
| Expl. | The following Natural statements are not supported when accessing a SQL database: - GET, GET SAME, GET TRANSACTION DATA, GET RECORD - STORE USING/GIVING NUMBER (ISN) - READ BY ISN |
| Actn. | Check program and correct error. |

70

Natural System Error Messages 3501-3550

NAT3501: Statement clause not allowed for SQL and XML databases.

| Text | Statement clause not allowed for SQL and XML databases. |
|-------|--|
| Expl. | The following Natural statement clauses are not supported when accessing SQL or XML databases: - CIPHER - COUPLED - PASSWORD - RETAIN |
| Actn. | Check program and correct error. |

NAT3502: Multiple-value field is not allowed for SQL databases.

| Text | Multiple-value field is not allowed for SQL databases. |
|-------|--|
| Actn. | Check program and correct error. |

NAT3503: Internal Natural SQL driver error.

| Text | Internal Natural SQL driver error. |
|-------|---|
| Expl. | Natural SQL driver has encountered an internal error. |
| | Provide the Natural source and object program and contact Software AG support. |

NAT3504: LFILE support is not available for SQL database.

| Text | LFILE support is not available for SQL database. |
|-------|---|
| Expl. | A DDM, that is used to access a SQL database, contains database id 255. Valid values are 1254. |
| | Change the database id in the DDM and recatalog the Natural program or check the database assignment in the global configuration file, to make sure that database id 255 is not assigned to a SQL database. |

NAT3505: Invalid SQLOPTION specified.

| Text | Invalid SQLOPTION specified. |
|-------|---|
| Expl. | A invalid SQLOPTION was specified with PROCESS SQL << SET SQLOPTION >>. |
| Actn. | Check program and correct error. |

NAT3506: Invalid value supplied for SQLOPTION.

| Text | Invalid value supplied for SQLOPTION. |
|-------|---|
| Expl. | An invalid value was specified with PROCESS SQL << SET SQLOPTION >>. |
| Actn. | Check program and correct error. |

NAT3507: Datatype not supported for SQL databases.

| Text | Datatype not supported for SQL databases. |
|-------|--|
| | A variable with an invalid datatype has been used in a statement, that accesses an SQL database. For SQL databases only variables of type A, B, F, I, N and P may be used. |
| Actn. | Check program and correct error. |

NAT3508: DBPROCESS still in use.

| Text | DBPROCESS still in use. |
|-------|--|
| Expl. | An SQL statement could not be executed, because the DBPROCESS is still executing another SELECT statement. |
| Actn. | Check program and correct error. |

NAT3509: Statement not allowed for XML databases.

| Text | Statement not allowed for XML databases. |
|-------|---|
| Expl. | The following Natural statements are not supported when accessing an XML database: |
| | - GET SAME, GET TRANSACTION DATA, - HISTOGRAM, - FIND FIRST, FIND UNIQUE, - UPDATE, - any SQL statements. |
| Actn. | Check program and correct error. |

NAT3510: Adabas D error :1: occurred.

| Text | Internal Adabas D error :1: occurred. |
|-------|--|
| Expl. | Adabas D has encountered an internal error. |
| Actn. | For more information see: Adabas D Error Messages. |

NAT3520: ORACLE error :1: occurred.

| Text | Internal ORACLE error :1: occurred. |
|-------|---|
| Expl. | ORACLE has encountered an internal error. |
| Actn. | For more information see: Internal ORACLE Error Messages. |

NAT3530: IBM DB2 error :1: occurred.

| Text | Internal IBM DB2 error :1: occurred. |
|-------|---|
| Expl. | IBM DB2 has encountered an internal error. |
| Actn. | For more information see: IBM DB2 Error Messages. |

NAT3540: SYBASE error :1: occurred.

| Text | Internal SYBASE error :1: occurred. |
|-------|--|
| Expl. | SYBASE has encountered an internal error. |
| Actn. | For more information see: SYBASE Error Messages. |

NAT3550: INFORMIX error :1: occurred.

| Text | Internal INFORMIX error :1: occurred. |
|-------|--|
| Expl. | INFORMIX has encountered an internal error. |
| Actn. | For more information see: INFORMIX Error Messages. |

71 Natural System Error Messages 3551-3600

NAT3560: INGRES error :1: occurred.

| Text | Internal INGRES error :1: occurred. |
|-------|--|
| Expl. | INGRES has encountered an internal error. |
| Actn. | For more information see: INGRES Error Messages. |

NAT3570: ODBC error :1: occurred.

| Text | Internal ODBC error :1: occurred. |
|-------|--|
| Expl. | ODBC has encountered an internal error. |
| Actn. | For more information see: ODBC Error Messages. |

NAT3571: Functionality cannot be used with ODBC.

| Text | Functionality cannot be used with ODBC. |
|-------|---|
| 1 | The following statements cannot be used with ODBC: - CALLDBPROC, - READ RESULT. |
| Actn. | Check program and global DBMS assigments. |

NAT3580: Rdb error :1: occurred.

| Text | Internal Rdb error :1: occurred. |
|-------|---|
| Expl. | Rdb has encountered an internal error. |
| Actn. | For more information see: Rdb Error Messages. |

NAT3590: ESQ error :1: occurred.

| | Text | Internal ESQ error :1: occurred. |
|--|-------|---|
| | Expl. | ESQ has encountered an internal error. |
| | Actn. | For more information see: ESQ Error Messages. |

72 Natural System Error Messages 3601-3650

NAT3610: RMS error :1: occurred.

| Text | Internal RMS error :1: occurred. |
|-------|---|
| Expl. | RMS has encountered an internal error. |
| Actn. | For more information see: RMS Error Messages. |

73

Natural System Error Messages 3701-3750

NAT3739: SQLDISCONNECT not allowed while a transaction is open.

| Text | SQLDISCONNECT not allowed while a transaction is open. |
|-------|--|
| Expl. | SQLDISCONNECT cannot be executed while a transaction is open. |
| | Issue END TRANSACTION or BACKOUT TRANSACTION before executing SQLDISCONNECT. |

NAT3740: Syntax error found in SQLDISCONNECT statement.

| Text | Syntax error found in SQLDISCONNECT statement. |
|-------|--|
| Expl. | A syntax error was detected in an SQLDISCONNECT statement. |
| Actn. | Correct the SQLDISCONNECT statement. |

NAT3741: Already connected to SQL database.

| Text | Already connected to SQL database. |
|-------|--|
| | SQLCONNECT failed, because a connection to an SQL database is already established. |
| Actn. | Close the existing connection with SQLDISCONNECT before executing SQLCONNECT. |

NAT3742: Syntax error found in SQLCONNECT statement.

| Text | Syntax error found in SQLCONNECT statement. |
|-------|---|
| Expl. | A syntax error was detected in an SQLCONNECT statement. |
| Actn. | Correct the SQLCONNECT statement. |

NAT3743: SQL date/time conversion failed.

| Text | SQL date/time conversion failed. |
|-------|---|
| Expl. | SQL date/time conversion failed, because the data to be converted do not correspond to the date/time conversion mask. |
| Actn. | Check the mask for SQL date/time conversion which is specified for this DBID. |

74 Natural System Error Messages 3951-4000

NAT4000: Natural error text 4nnn cannot be displayed.

| Text | Natural error text 4nnn cannot be displayed. |
|-------|--|
| Expl. | For error NAT4nnn, there is no specific error message available. |

75 Natural System Error Messages 4001-4050

NAT4001: Control characters DC, ID, IA must exclude one another.

| Text | Control characters DC, ID, IA must exclude one another. |
|-------|---|
| | These characters for decimal character (DC), input delimiter (ID) and input assign character (IA) must be different from one another, so that they can be distinguished from one another when an input data stream is processed. |
| Actn. | Enter different values for DC, ID, IA. |

NAT4002: Enter "OFF", "ON", "OPT" or "*".

| Text | Enter "OFF", "ON", "OPT" or "*". |
|-------|---|
| Expl. | To set the MCG parameter on the GLOBALS screen, the following options are allowed: - "OFF" de-activates the Natural Optimizer Compiler (NOC). - "ON" activates the NOC without any additional options. - "OPT" or "*" causes a window to be displayed, in which you can activate the NOC and also active/de-activate any additional options (overflow checking, index checking, mixed mode, optimization of I/O statements). |
| Actn. | Enter "ON", "OFF", "OPT" or "*" in MCG field on GLOBALS screen. |

NAT4003: Additional Options = "Y" only possible with "ON" ="Y".

| Text | Additional Options = "Y" only possible with "ON" ="Y". |
|-------|---|
| | If you wish to activate any additional options of the Natural Optimizer Compiler (NOC) to "Y", you must first activate the NOC itself (set "ON" to "Y"). If you wish to de-activate the NOC (set "ON" to "N"), you must also de-activate any additional options that have been activated. |
| Actn. | Also set "ON" to "Y" when you set any additional option to "Y"; or set all additional options to "N" when you set "ON" to "N". |

NAT4004: The line size must be between 2 and 250.

| Text | The line size must be between 2 and 250. |
|-------|--|
| | The maximum output in one logical line is 250 characters. If the LS parameter is greater than the physical line size, the text will be wrapped around. |
| Actn. | Enter a value of no more than 250 for line size. |

NAT4005: The page size must be either from 10 to 250, or 0.

| Text | The page size must be either from 10 to 250, or 0. |
|-------|---|
| | Up to 250 lines can be produced by one statement and can be placed on one logical page. |
| Actn. | Enter a correct value for the PS parameter. |

NAT4006: Only "D" or "F" allowed as values for IM parameter.

| Text | Only "D" or "F" allowed as values for IM parameter. |
|-------|--|
| - | Only "D" (for delimiter mode) or "F" (for forms mode) may be used as values for the IM (input mode) parameter. |
| Actn. | Enter "D" or "F" for IM parameter. |

NAT4007: Only "ON" or "OFF" allowed for this type of parameter.

| Text | Only "ON" or "OFF" allowed for this type of parameter. |
|-------|---|
| Expl. | The only possible values for this type of parameter are "ON" and "OFF". |
| Actn. | Enter either "ON" or "OFF" for this parameter. |

NAT4008: The SL parameter value must be between 20 and 250.

| Text | The SL parameter value must be between 20 and 250. |
|-------|---|
| | Source lines can only be from 20 to 250 characters long if they are input in batch mode. The Natural full-screen editor allows lines of up to 72 characters. |
| Actn. | Enter a correct value for SL parameter. |

NAT4009: The spacing factor must be between 1 and 30.

| Text | The spacing factor must be between 1 and 30. |
|-------|---|
| Expl. | 30 spaces are the maximum which can be placed between output columns. |
| Actn. | Enter correct value (1 - 30) for SF parameter. |

NAT4010: Incorrect construction of library ID.

| Text | Incorrect construction of library ID. |
|-------|---|
| · · | Library identifications must start with a character and may consist of up to eight alphanumeric characters. |
| Actn. | Enter correct value for library ID. |

NAT4011: You cannot specify a limit which exceeds default limit.

| Text | You cannot specify a limit which exceeds default limit. |
|-------|---|
| | You cannot set the limit to a value which is greater than the default limit value displayed. You may, however, reduce the value for the limit. The default limit value is defined during the Natural installation. |
| Actn. | Enter a value which is lower than the current limit value. |

NAT4012: Previous contents of source area has been deleted.

| Text | Previous contents of source area has been deleted. |
|-------|---|
| | You have attempted to catalog a DDM while another object was in the source area. This object has been deleted from the source area, and the source area is now empty. |
| Actn. | Before you catalog a DDM, read it into the source area. |

NAT4013: The Generate function is only valid for Adabas files.

| Text | The Generate function is only valid for Adabas files. |
|-------|---|
| Expl. | To generate a DDM from a DB2 or SQL/DS table, you use the function "DB2, SQL/DS Services". To generate a DDM from a DL/I segment description, you use the function "DL/I Services". A DDM for a VSAM file cannot be generated; you use the Edit function and enter the specifications by hand. |
| Actn. | Use appropriate function for database type. |

NAT4014: Please enter an Adabas DBID other than "0".

| | Text | Please enter an Adabas DBID other than "0". |
|--|-------|---|
| | Actn. | Enter valid DBID. |

NAT4015: Read DDM into source area before you catalog it.

| Text | Read DDM into source area before you catalog it. |
|-------|--|
| Expl. | Before you can catalog a DDM, you must read it into the source area. |
| Actn. | Read DDM into source area. |

NAT4016: This function is not available.

| Text | This function is not available. |
|-------|---|
| Expl. | The functions "DB2, SQL/DS Services" and "DL/I Services" are only available if Natural for DB2, Natural for SQL/DS or Natural for DL/I respectively has been installed. |
| Actn. | Select another function; or contact your database administrator. |

NAT4017: Object renamed successfully.

| | Object renamed successfully. |
|-------|------------------------------|
| Actn. | No action required. |

NAT4018: User :1: is cataloging this library with CATALL.

| Text | User is cataloging this library with CATALL. |
|-------|--|
| Expl. | CATALL of a library is allowed for only one user at a time. |
| | You can 1) try later; 2) contact the person who issued the CATALL and ask him/her to complete the job, or if this person is not available, you can 3) delete the object 0CATALL. |

NAT4019: File :1: does not exist on database :2:.

| Text | File does not exist on database |
|-------|---|
| | While checking a DDM against Adabas with an LF call, response code 17, subcode 11 was returned. |
| | The FDT to which the DDM refers does not exit in Adabas. |
| Actn. | Change the DBID and/or FNR of the DDM, or load the Ababas FDT. |

NAT4029: Object(s) printed.

| Text | Object(s) printed. |
|-------|--|
| Expl. | The object(s) you selected, have been routed to the printer. |
| Actn. | No action. |

NAT4031: Please enter "ON" or "OFF".

| Text | Please enter "ON" or "OFF". |
|------|---|
| 1 1 | Valid input for this field is "ON" or "OFF" only. Please refer to the documentation for the meaning of the values. |
| | Please insert allowed value. |

NAT4032: Please select either "OFF", "ON" or "VID".

| Text | Please select either "OFF", "ON" or "VID". |
|-------|---|
| | Valid input for this field: ON: Global format IDs are generated for all views (default). OFF: No global format IDs are generated. VID: Global format IDs are generated only for views in local/ global data areas, but not for views defined within programs. |
| Actn. | Please enter valid value. |

NAT4033: Compiler options updated.

| Text | Compiler options updated. |
|-------|---|
| 1 1 | The compiler options have been updated according to the values displayed on the screen. |
| Actn. | No action. |

NAT4035: Invalid value :1: entered.

| | Invalid value entered. |
|-------|------------------------|
| Actn. | Enter a correct value. |

NAT4036: Invalid value :1: passed to parameter :2:.

| Text | Invalid value passed to parameter |
|-------|---|
| | An invalid value has been passed to a parameter of a Natural module. There may be a wrong input by the user, or an internal error has occurred. |
| Actn. | Change input parameter or contact Natural administrator. |

NAT4037: :1: must be less than :2:.

| Text | must be less than |
|-------|--|
| Expl. | A value you entered must be less than another value. |
| Actn. | Enter a smaller value. |

NAT4038: :1: must be greater than :2:.

| Text | must be greater than |
|-------|---|
| Expl. | A value you entered must be greater than another value. |
| Actn. | Enter a greater value. |

NAT4039: :1: must be in range of :2: to :3:.

| Text | must be in range of to |
|-------|---|
| Expl. | An input value may be in a wrong range. |
| Actn. | Change input value. |

NAT4040: :1: does not exist.

| Text | does not exist. |
|-------|------------------------------------|
| Expl. | No detailed explanation available. |

NAT4041: :1: already exists.

| Text | already exists. |
|-------|--|
| Actn. | Change input or set a replace option to "yes". |

NAT4043: :1: is empty.

| Text | is empty. |
|-------|------------------------------------|
| Expl. | No detailed explanation available. |

NAT4044: Function disallowed by Predict definition.

| Text | Function disallowed by Predict definition. |
|-------|--|
| | Due to definitions in Predict, you are not allowed to use this function. |
| Actn. | Contact your Predict administrator. |

NAT4045: Error in Predict master record.

| Text | Error in Predict master record. |
|-------|------------------------------------|
| Expl. | No detailed explanation available. |

NAT4046: Field is defined as LOB field in Adabas.

| Text | Field is defined as LOB field in Adabas. |
|-------|---|
| Expl. | The DDM field is defined as an LOB field in Adabas, but it is not marked with the "LB" field option. |
| | Mark the field with the "LB" field option on the extended field editing map, activated with the .e command. |

NAT4047: Field is defined as a long alpha field in Adabas.

| Text | Field is defined as a long alpha field in Adabas. |
|-------|---|
| | The DDM field is defined as a long alpha field in Adabas, but it is not marked with the "LA" field option. |
| Actn. | Mark the field with the "LA" field option on the extended field editing map, activated with the .e command. |

NAT4048: Extended parameter size too small.

| Text | Extended parameter size too small. |
|-------|---|
| - | A Natural subprogram has been called with a dynamic parameter area (1:V). The size of the parameter area in the calling program is smaller than expected in the subprogram. |
| Actn. | Change the calling program or contact a Natural administrator. |

NAT4049: :1: only allowed for :2:.

| Text | only allowed for |
|-------|------------------------------------|
| Expl. | No detailed explanation available. |

NAT4050: Duplicate file number for physical DDM not allowed.

| | Text | Duplicate file number for physical DDM not allowed. |
|---|-------|--|
| - | Expl. | A file number for a physical VSAM DDM may only be used once. |
| | Actn. | Use another file number or specify "yes" for a replace option. |

76 Natural System Error Messages 4051-4100

NAT4051: File related to user DDM does not exist.

| Text | File related to user DDM does not exist. |
|-------|--|
| | A VSAM user DDM is related to physical VSAM DDM, which does not exist. A logical user DDM must have the same file number than the physical file. |
| Actn. | Correct the file number or create an appropriate physical VSAM DDM. |

NAT4052: There is no physical file with the given number.

| Text | There is no physical file with the given number. |
|-------|--|
| Expl. | A VSAM DDM logical refers to a physical VSAM DDM which does not exist. |
| | Create an appropriate physical VSAM DDM, or logically relate the DDM to another physical VSAM DDM. |

NAT4053: Logical file must be of type KSDS or VRDS.

| | Logical file must be of type KSDS or VRDS. |
|-------|--|
| Actn. | Change the logical file type. |

NAT4054: File number missing for related physical file.

| Text | File number missing for related physical file. |
|-------|--|
| Actn. | Enter a file number. |

NAT4055: DDM too large, not enough size.

| Text | DDM too large, not enough size. |
|------|--|
| | A DDM will be temporarily stored in an internal buffer during a CHECK or CAT operation. There is not enough space available to allocate this buffer. |
| | Reduce other Natural buffer sizes (e.g. ESIZE), reduce the size of the DDM or contact a Natural administrator. |

NAT4056: Primary key invalid for ESDS files.

| | Primary key invalid for ESDS files. |
|-------|-------------------------------------|
| Actn. | Remove the primary-key field. |

NAT4057: RRDS files must not contain any key.

| Text | RRDS files must not contain any key. |
|-------|--------------------------------------|
| Actn. | Remove the key. |

NAT4058: Duplicate long field name :1: not allowed.

| Text | Duplicate long field name not allowed. |
|-------|--|
| Expl. | There are two DDM fields with the same long name. This is not allowed. |
| Actn. | Change the long name of the DDM field. |

NAT4059: :1:

| Text | |
|-------|------------------------------------|
| Expl. | No detailed explanation available. |

NAT4060: KSDS file must contain at least one primary key.

| Text | KSDS file must contain at least one primary key. |
|-------|--|
| Actn. | Insert a primary key in the KSDS DDM. |

NAT4061: Alternate index name valid only for types "A", "X".

| Text | Alternate index name valid only for types "A", "X". |
|-------|--|
| · · | An alternate index is specified for a field, but the descriptor column of the field is not marked with "A" or "X". |
| Actn. | Correct error. |

NAT4062: Value for :1: must be "Y" or "N".

| Text | Value for must be "Y" or "N". |
|-------|--|
| Expl. | The value for an input field must be "Y" or "N". |
| Actn. | Enter "Y" or "N" or contact a Natural administrator. |

NAT4063: :1: must not be blank.

| Text | must not be blank. |
|-------|---|
| Actn. | Enter a value other than blank, or contact a Natural administrator. |

NAT4064: :1: must be :2:.

| Text | must be |
|-------|------------------------------------|
| Expl. | No detailed explanation available. |

NAT4065: Catalog :1: disallowed by security definition.

| Text | Catalog disallowed by security definition. |
|-------|--|
| | The user does not have the privileges in Natural Security to catalog this DDM. |
| Actn. | Contact a Natural Security administrator or change the name of the DDM. |

NAT4066: Catalog DDM disallowed for SYSDDM utility.

| Text | Catalog DDM disallowed for SYSDDM utility. |
|-------|---|
| Expl. | The user does not have the privileges to catalog a DDM with the SYSDDM Utility. |
| Actn. | Contact a Natural Security administrator. |

NAT4067: Code "C" not supported. :1:.

| Text | Code "C" not supported |
|-------|--|
| | An internal error during a call to Natural Security occurred. Natural Security does not know code "C" for the cataloging of DDMs. Natural Security issued a response code. |
| Actn. | Contact a Natural Security administrator. |

NAT4068: Duplicate short name :1: not allowed.

| Text | Duplicate short name not allowed. |
|-------|--|
| Expl. | It is not allowed for this DDM to use a short name more than once. |
| Actn. | Change the short name of a field. |

NAT4069: S-Descriptor :1: must not refer to PE/MU field :2:.

| Text | S-Descriptor must not refer to PE/MU field |
|-------|---|
| · · | The master field of a super- or subdescriptor must not be a periodic-group or multiple-value field. |
| Actn. | Change the super- or subdescriptor. |

NAT4070: Creator not found in DDM name, check against table not possible.

| Text | Creator not found in DDM name, check against table not possible. |
|-------|---|
| Expl. | The DDM name of an SQL DDM is supposed to consist of the creator name and the table name separated by a "-". If the creator and table name cannot be identified, the SQL DDM cannot be checked against a SQL table. Note that there is no check against the SQL table when you catalog the DDM. |
| | Use a DDM name which consists of creator and table name separated by a "-". |

NAT4071: Return code :1: after Adabas LF-command.

| Text | Return code after Adabas LF-command. |
|-------|--|
| | An Adabas LF-command was issued to retrieve the field characteristics of |
| | an FDT. A non-zero return code was received after the call. |
| Actn. | Check the file number of the FDT or contact a Natural administrator. |

NAT4072: This command is disallowed.

| Text | This command is disallowed. |
|-------|---|
| · · | There was an attempt to perform a function which is disallowed by Natural Security. |
| Actn. | Contact a Natural Security administrator. |

NAT4073: Specify table name and creator name.

| Text | Specify table name and creator name. |
|------------|--|
| _ _ | Either the creator name or the table name of an SQL table was missing during an attempt to generate a DDM from an SQL table. |
| Actn. | Issue creator and table name. |

NAT4074: Table :1: created by :2: not found.

| Text | Table created by not found. |
|-------|--|
| Expl. | The SQL table from which you wanted to create a DDM was not found. |
| Actn. | Either create the SQL table or issue the correct creator and table name. |

NAT4075: Too many columns for view (< 750).

| Text | Too many columns for view (< 750). |
|-------|---|
| | The SQL table from which you wanted to generate a DDM has too many columns. The maximum number of columns is 750. |
| Actn. | Reduce the number of columns in the table. |

NAT4076: Error :1: parsing SQL View (NATG0301).

| Text | Error parsing SQL View (NATG0301). |
|------|---|
| | The error occurred during a check of a view for updateable fields. There may be an error in the view definition. |
| | Contact a Natural administrator. |

NAT4077: Table :1: has no columns.

| Text | Table has no columns. |
|-------|---|
| Expl. | An attempt was made to generate a DDM from an SQL table which has no columns. |
| Actn. | Contact a Natural administrator. |

NAT4078: Too many columns - cannot generate short names.

| Text | Too many columns - cannot generate short names. |
|-------|--|
| | There is a limited number of short names for key fields and non-key fields in SQL DDMs. The maximum number of one kind of field has been exceeded. |
| Actn. | Reduce the number of columns in the SQL table. |

NAT4079: Invalid database number.

| Text | Invalid database number. |
|-------|---|
| Expl. | A database number was issued which is not valid in the context. |
| Actn. | Enter another database number. |

NAT4080: DDM already defined on database other than SQL.

| Text | DDM already defined on database other than SQL. |
|-------|--|
| Expl. | You were trying to catalog a DDM whose name already exists; however, the DDM is not for SQL. |
| Actn. | Use another name for the DDM. |

NAT4081: DB2 not active, DDM cannot be tested.

| Text | DB2 not active, DDM cannot be tested. |
|------------|--|
| 1 1 | An attempt was made to check a DB2 DDM against the DB2 database, but Natural found that DB2 is not active. |
| Actn. | Contact a Natural administrator. |

NAT4082: Null indicator must be of type I2.

| Text | Null indicator must be of type I2. |
|-------|--|
| Expl. | A null indicator is not of the required type and length. |
| Actn. | Change format and/or length of the null indicator. |

NAT4083: Invalid format or length in LOB or long alpha field.

| Text | Invalid format or length in LOB or long alpha field. |
|-------|---|
| | LOB fields may have the format "A", "B" or "U". The maximum length for format "A" or "B" is 1073741824. The maximum length for format "U" is 536870912. Long alpha fields may have the format "A" or "U". The maximum length for format "A" is 16381. The maximum length for format "U" is 8190. |
| Actn. | Specify the correct format/length. |

NAT4084: Null indicator is a descriptor.

| Text | Null indicator is a descriptor. |
|------------|---|
| 1 1 | The null indicator is defined as a descriptor, but the null-indicator field in the DDM is not a descriptor. |
| Actn. | Define the null-indicator field of the DDM as a descriptor. |

NAT4085: Null indicator could not be related to a field.

| Text | Null indicator could not be related to a field. |
|-------|--|
| | Possible reasons for this message: - The short name of a field and the short name of the corresponding null indicator must be equal. - A null indicator must be preceded by its related DB field. |
| Actn. | Change short name or position of null indicator. |

NAT4086: Invalid null indicator field name.

| Text | Invalid null indicator field name. |
|-------|--|
| | The long name of a null indicator must be the long name of the corresponding field prefixed by N@. On mainframe platforms, "@" is the character with the hexadecimal value H"7C". |
| Actn. | Change the long name of the null indicator. |

NAT4087: Format must be binary (B).

| Text | Format must be binary (B). |
|-------|--|
| 1 1 | The format of a field was found to be binary during the check of the DDM against the database. |
| Actn. | Set the format of the field to binary. |

NAT4088: Field is not defined as LOB field in Adabas.

| Text | Field is not defined as LOB field in Adabas. |
|------|---|
| | The DDM field is marked with the field option "LB", which indicates that the field is an Adabas LOB field. However, the field is not defined as an LOB field in Adabas. |
| | Regenerate the DDM; or change the field option on the extended field editing map, activated with the .e line command. |

NAT4089: Field is not defined as a long alpha field in Adabas.

| Text | Field is not defined as a long alpha field in Adabas. |
|-------|--|
| Expl. | The DDM field is marked with the field option "LA", which indicates that the field is an Adabas long alpha field. However, the field is not defined as a long alpha field in Adabas. |
| Actn. | Regenerate the DDM; or change the field option on the extended field editing map, activated with the .e line command. |

NAT4090: CMZUL :2: with response code :1:.

| Text | CMZUL with response code |
|-------|---|
| Expl. | There has been an error calling the CMZUL editor. |
| Actn. | Contact a Natural administrator. |

NAT4091: Invalid file number.

| Text | Invalid file number. |
|-------|--|
| Expl. | A file number in the range from 1 to 5000 must be entered. |
| Actn. | Enter a valid file number. |

NAT4092: CICS file name missing.

| Text | CICS file name missing. |
|-------|------------------------------------|
| Expl. | No detailed explanation available. |

NAT4093: Only K,E,R,V (file-org); Y,N (compress); F,C (zone) allowed.

| _ L | | Only K,E,R,V (file-org); Y,N (compress); F,C (zone) allowed. |
|-----|-------|--|
| | Expl. | No detailed explanation available. |

NAT4094: Y (compress) only allowed for KSDS, ESDS and VRDS files.

| | Y (compress) only allowed for KSDS, ESDS and VRDS files. |
|-------|--|
| Expl. | No detailed explanation available. |

NAT4095: Invalid command, please enter valid command.

| Text | Invalid command, please enter valid command. |
|-------|--|
| Expl. | A command has been entered which is not valid. |
| Actn. | Enter a valid command. |

NAT4096: Element length cannot be greater than :1:.

| Text | Element length cannot be greater than |
|------------|---|
| 1 1 | A length for a field has been entered which is longer than the maximum for this field type. |
| Actn. | Check and enter correct length. |

NAT4097: Function cancelled.

| Text | Function cancelled. |
|-------|--|
| Expl. | A function has been cancelled by the user. |
| Actn. | No action required. |

NAT4098: Database ID :1: invalid for SQL tables.

| | Database ID invalid for SQL tables. |
|-------|--------------------------------------|
| Actn. | Enter or select a valid database ID. |

NAT4099: Not allowed to write a Super Natural user file.

| Text | Not allowed to write a Super Natural user file. |
|------|--|
| | A Super Natural user file will be generated by a Super Natural application. You can read or list the file and store or backup it with another file type. But it is not allowed to change it, because the Super Natural application which uses the file may not longer run. |

NAT4100: Please specify a file name.

| Text | Please specify a file name. |
|-------|--|
| Expl. | If the function LIST FILE is selected, |
| | a file name must be specified. |
| Actn. | Enter function and file name. |

77 Natural System Error Messages 4101-4150

NAT4101: Currently no object in source work area.

| Text | Currently no object in source work area. |
|-------|---|
| | If you issue the LIST command without any parameters, the source of the object currently residing in the source work area will be listed. However, the source work area is currently empty. |
| Actn. | With the LIST command, specify the name of the object to be listed. |

NAT4102: Input value(s) for line selection must be numeric.

| Text | Input value(s) for line selection must be numeric. |
|-------|---|
| | Only a numeric value may be specified for selected lines of a program to be listed. |
| Actn. | Enter a numeric value for line selection. |

NAT4103: Scan function for cross-reference requires scan value.

| Text | Scan function for cross-reference requires scan value. |
|-------|--|
| | The cross-reference for a value can only be evaluated if an alphanumeric constant has been specified as value. |
| Actn. | Enter a scan value. |

NAT4104: Invalid LIST subcommand.

| Text | Invalid LIST subcommand. |
|-------|--|
| 1 1 | An invalid subcommand was specified for the LIST function. Use the HELP command to get an overview of valid commands. |
| Actn. | Enter a valid LIST subcommand. |

NAT4105: Cross-reference table overflow.

| Text | Cross-reference table overflow. |
|-------|--|
| | The internal table to hold the cross-reference list can only hold up to 240 references. For the specified value, however, more references exist. |
| Actn. | Use a more specific value for reference. |

NAT4106: Line number out of range; listing will be from 1st line.

| Text | Line number out of range; listing will be from 1st line. |
|-------|--|
| | A line number was specified that does not exist in the program. The LIST function will list the program from the beginning. |
| Actn. | Enter correct line number. |

NAT4107: Program terminated abnormally.

| Text | Program terminated abnormally. |
|-------|---|
| _ | In batch mode, the execution of a program was terminated abnormally. The reason for the error is displayed in the batch output list above this message. |
| Actn. | See reason for error in output list. |

NAT4108: Scan only allowed on selected Object(s) in active Object List.

| Text | Scan only allowed on selected Object(s) in active Object List. |
|-------|--|
| Expl. | Scan works on the marked objects in the active Object List |
| Actn. | Select Object(s) and activate Object List |

NAT4110: Selected number is out of range.

| Text | Selected number is out of range. |
|-------|--|
| | Only file references of file names that are displayed for selection can be referenced. The specified number is out of range. |
| Actn. | Enter correct selection number. |

NAT4115: Line number not numeric; listing will be from first line.

| Text | Line number not numeric; listing will be from first line. |
|-------|--|
| | A specification for a line number selection was not numeric. The program will be listed from the beginning. |
| Actn. | Enter correct number for line selection. |

NAT4116: Starting number greater than highest existing line number.

| Text | Starting number greater than highest existing line number. |
|-------|--|
| | The line number specified for positioning was greater than the highest line number existing in the program. The program will be listed from the beginning. |
| Actn. | Enter a correct line number. |

NAT4119: Selected program does not exist in specified library.

| Text | Selected program does not exist in specified library. |
|-------|---|
| | The program selected by the specified program name does not exist in the specified library. |
| Actn. | Enter correct program name. |

NAT4121: Only one program can be selected for editing.

| Text | Only one program can be selected for editing. |
|-------|--|
| | The selection menu allows only one program to be selected for editing. It is possible to select multiple programs for cataloging, purging, scratching, listing, etc. |
| Actn. | Select only one program for editing. |

NAT4122: Selected number out of range for LIST PROGRAM.

| Text | Selected number out of range for LIST PROGRAM. |
|-------|---|
| Expl. | Only program numbers displayed on the selection menu may be selected. |
| Actn. | Enter valid selection number. |

NAT4123: The current library does not contain any source programs.

| Text | The current library does not contain any source programs. |
|------|---|
| Actr | . Check program and correct error. |

NAT4125: The requested file description is not available.

| Text | The requested file description is not available. |
|-------|---|
| Expl. | The file description which has been specified for listing does not exist. |
| Actn. | Check program and correct error; specify correct file name. |

NAT4126: Requested field name not found in DDM.

| Text | Requested field name not found in DDM. |
|-------|---|
| | The requested field name was not found in the DDM. Only the Natural field long names are recognized. |
| Actn. | Enter "" to position to the top of the DDM. |

NAT4127: Invalid LIST FILE command.

| Text | Invalid LIST FILE command. |
|-------|---|
| Expl. | An invalid LIST FILE command was used in the split-screen editor. |
| Actn. | Enter "?" for help information on valid commands. |

NAT4128: File description listing will be truncated.

| Text | File description listing will be truncated. |
|-------|--|
| Expl. | The size of the DDM to be listed is too large. |
| Actn. | Check program and correct error. |

NAT4129: No scan value specified.

| Text | No scan value specified. |
|-------|---|
| | In split-screen mode, you have to specify a value to be scanned for with the command "S SC value", before you can enter the command "S SC=" to repeat the scan. |
| Actn. | Enter correct command. |

NAT4130: Only local commands allowed.

| Text | Only local commands allowed. |
|-------|--|
| - | In this part of the application only local commands are allowed. |
| Actn. | Use help function on command line. |

NAT4131: The library was empty, no programs were purged.

| Text | The library was empty, no programs were purged. |
|------|--|
| - | The PURGE command was issued for a library which does not contain any source programs. |
| | Check program and correct error. |

NAT4132: No command available for LAST command.

| Text | No command available for LAST command. |
|-------|---|
| Expl. | The LAST command is used to display the command(s) that was/were issued last. However, when you issued the LAST command, there was no command issued before. |
| Actn. | No action required. |

NAT4133: The command requested with LAST is not available.

| Text | The command requested with LAST is not available. |
|------|--|
| | With the command LAST, you have requested a specific command; however, this specific command is not available. |
| | Issue the command "LAST *" for a list of the last 9 commands that have been issued. |

NAT4134: Invalid command selection.

| Text | Invalid command selection. |
|-------|---|
| Expl. | In the window invoked with "LAST *", you can select commands as follows: - To execute a single command again, mark the command with any character and press ENTER; or mark the command with the cursor and press PF5. - To execute several commands, mark them with numbers in the order in which you wish them to be executed again and press ENTER; the commands will then be executed in ascending order of numbers. This error has occurred because you have used the same number twice, or have marked one of the commands with a letter instead of a number. |
| Actn. | Select commands correctly. |

NAT4135: Only "L" or "V" allowed as values for DO parameter.

| Text | Only "L" or "V" allowed as values for DO parameter. |
|-------|---|
| | DO=L - Data to display have logical order (default). DO=V - Data to display have visual order. |
| Actn. | Change value for DO parameter to a valid value. |

78

Natural System Error Messages 4151-4200

NAT4199: Object :1:(:2:/:3:/:4:) disabled by bufferpool :5:/:6: blacklist.

| Text | Object(/) disabled by bufferpool/ blacklist. |
|-------|--|
| | The object <name(library dbid="" fnr)=""> to be executed is contained in the blacklist of the current buffer pool <host-id buffer-pool-name=""> (see the SYSBPM utility documentation).</host-id></name(library> |
| Actn. | Remove the program from the blacklist. |

79

Natural System Error Messages 4201-4250

NAT4201: The file number must be in the range 1 - 5000.

| Text | The file number must be in the range 1 - 5000. |
|-------|---|
| Expl. | The database file number must be in the range from 1 to 5000. |
| Actn. | Enter correct file number. |

NAT4202: First character of file name must be alphabetical.

| Text | First character of file name must be alphabetical. |
|-------|--|
| | A valid file name must begin with an alphabetical character, and may be constructed according to the rules for variable names (as described in the section on user-defined variables in the Natural documentation). |
| Actn. | Enter correct file name. |

NAT4203: A file name must be specified.

| Text | A file name must be specified. |
|-------|---|
| | For the CATALOG function, which requires a file name, no file name was specified. |
| Actn. | Enter a valid file name. |

NAT4204: Level must be higher than previous level.

| Text | Level must be higher than previous level. |
|-------|---|
| Actn. | Check and correct the level. |

NAT4205: Invalid characters in file name.

| Text | Invalid characters in file name. |
|-------|---|
| · · | A file name must be constructed according to the rules for variable names (see the section on user-defined variables in the Natural documentation). |
| Actn. | Enter a correct file name. |

NAT4206: Invalid name for the "default sequence" field.

| Text | Invalid name for the "default sequence" field. |
|-------|--|
| Expl. | An invalid name was specified for the default sequence descriptor. The default descriptor must be specified as the 2-character short name of a field which must exist as a descriptor in the global database file definition. |
| Actn. | Enter correct name for default sequence descriptor. |

NAT4207: Invalid database field name for coupling field.

| Text | Invalid database field name for coupling field. |
|-------|---|
| Expl. | The field name specified for the coupling relation must be specified as a 2-character short name and must begin with an alphabetical character. The field to be used for the coupling relation must exist in the global database file definition. |
| Actn. | Enter correct name for coupling field. |

NAT4208: Invalid field name for coupling field (columns S + D).

| Text | Invalid field name for coupling field (columns S + D). |
|-------|--|
| Expl. | The name for the coupling field must be specified as a 2-character database field name beginning with an alphabetical character and must exist in the global file definition. The value for the coupling field name must be entered in the columns with headings S and D (one character each). |
| Actn. | Enter correct coupling field name. |

NAT4209: Coupled file number not numeric.

| Text | Coupled file number not numeric. |
|-------|---|
| Expl. | The identification of the coupled file must be entered as the |
| | file number in the database. The identification must be a valid |
| | file number in the range from 1 to 255. |
| | It must be entered in the field with heading "LENG". |
| Actn. | Enter correct coupling file number. |

NAT4210: Occurrence value must be 1-999.

| Text | Occurrence value must be 1-999. |
|-------|---|
| | The specified value for the occurrence is not correct. Only values in the range from 1 to 999 are allowed for a periodic group or multiple-value field. |
| Actn. | Enter correct value for occurrence. |

NAT4211: Database short field name must be specified (column DB).

| Text | Database short field name must be specified (column DB). |
|-------|---|
| | The specification of a field requires a database short field name. The short field name must be 2 characters long and begin with an alphabetical character. |
| Actn. | Enter correct field short name. |

NAT4212: Field long name must be specified (column NAME).

| Text | Field long name must be specified (column NAME). |
|-------|--|
| Expl. | The specification of a field requires a long name to be specified for a field. The long name must begin with an alphabetical character and must be constructed according to the rules for variable names (see the section on user-defined variables in the Natural documentation). |
| Actn. | Enter valid long field name. |

NAT4213: First character of field long name must be alphabetical.

| Text | First character of field long name must be alphabetical. |
|-------|--|
| Expl. | The first character of a field"s long name must be alphabetical. |
| Actn. | Enter a valid long name for the field. |

NAT4214: Field format (column F) must be A,B,U,I,N,P,F,D,T or L.

| Text | Field format (column F) must be A,B,U,I,N,P,F,D,T or L. |
|-------|--|
| Expl. | Only one of the following formats may be specified for a database field: |
| | A - alphanumeric |
| | B - binary |
| | U - unicode |
| | I - integer |
| | N - numeric unpacked |
| | P - packed numeric |
| | F - floating point |
| | D - date |
| | T - time |
| | L - logical |
| Actn. | Enter a valid format. |

NAT4215: Alpha field length must be 1-253 or LA/LB option must be set.

| Text | Alpha field length must be 1-253 or LA/LB option must be set. |
|-------|---|
| Expl. | Fixed-length alphanumeric fields can only have a length of up to 253 characters. A variable-length field may be defined as DYNAMIC by setting the format option LA or LB. Use the .E line command to enter a format option. |
| Actn. | Enter a valid field length or set LA/LB format option. |

NAT4216: The length of a numeric field must be 1 - 29.

| Text | The length of a numeric field must be 1 - 29. |
|-------|---|
| | The maximum length for a numeric field is 29 digits. The length for a numeric field is always specified in digits. |
| Actn. | Enter valid numeric length. |

NAT4217: VSAM descriptor can only be "P", "S", "A", "X" or blank.

| Text | VSAM descriptor can only be "P", "S", "A", "X" or blank. |
|-------|--|
| - | A character other than "P", "S", "A", "X" or blank has been specified to mark a field as a descriptor field. |
| Actn. | Enter correct character (P, S, A, X or blank). |

NAT4218: Specification of field length must be numeric.

| Text | Specification of field length must be numeric. |
|-------|--|
| | The specification for the field length must be numeric in the form "nn.m", where "nn" represents the digits before and "m" the digits after the decimal character. |
| Actn. | Enter correct length. |

NAT4219: Field long name must consist of at least 3 characters.

| Text Field long name must consist of at least 3 characters. | |
|---|---|
| Expl. | The long name for a field must consist of 3 or more characters. |
| Actn. | Enter valid field long name. |

NAT4220: Invalid characters in long name.

| Text | Invalid characters in long name. |
|-------|---|
| | Long field names must be constructed according to the rules for variable names and must begin with an alphabetical character (see the section on user-defined variables in the Natural documentation). |
| Actn. | Enter valid field long name. |

NAT4221: Invalid database short name (column DB).

| Text | Invalid database short name (column DB). |
|-------|---|
| | The field short name must have 2 characters and must begin with an alphabetical character. The field short name must not be "E0" to "E9". |
| Actn. | Enter valid database short name. |

NAT4222: Length of a binary field must be 1 - 126.

| Text | Length of a binary field must be 1 - 126. |
|-------|---|
| Expl. | Binary fields can only have a length between 1 and 126. |
| Actn. | Correct the length value of the field. |

NAT4223: Field type (column T) must be "*", "P", "G", "M", blank.

| Text | Field type (column T) must be "*", "P", "G", "M", blank. |
|-------|---|
| | Valid field types to be specified in column T are: * - comment line P - periodic group G - group of fields M - multiple-value field " " - elementary field |
| Actn. | Enter valid field type. |

NAT4224: Special options or descriptor entered for group.

| Text | Special options or descriptor entered for group. |
|-------|--|
| | For a field group, no special options or "D" (for descriptor) can be specified. Special options must be specified for the individual fields. |
| Actn. | Do not enter special options for field groups. |

NAT4225: Invalid level. Level must be 1 - 7.

| Text | Invalid level. Level must be 1 - 7. |
|-------|-------------------------------------|
| Expl. | Field levels can only be 1 - 7. |
| Actn. | Enter valid level number. |

NAT4226: Periodic group within periodic group is not allowed.

| Text | Periodic group within periodic group is not allowed. |
|-------|---|
| | Periodic groups cannot be nested; i.e., a periodic group must not contain another periodic group. |
| Actn. | Check program and correct error. |

NAT4227: Edit mask must not be specified for a group.

| Text | Edit mask must not be specified for a group. |
|-------|--|
| · · | No edit mask specification is allowed for a field (periodic) group. Edit masks can only be specified for individual fields. |
| Actn. | Check program and correct error. |

NAT4228: Format must not be specified for a group.

| Text | Format must not be specified for a group. |
|-------|--|
| | For a group, no format can be specified. Formats can only be specified for individual fields. |
| Actn. | Check program and correct error. |

NAT4229: Length must not be specified for a group.

| Text | Length must not be specified for a group. |
|-------|--|
| | For a field group, no length can be specified. Field lengths may only be specified for individual fields. |
| Actn. | Check program and correct error. |

NAT4230: Special option (column S) must be "N", "F", or blank.

| Text | Special option (column S) must be "N", "F", or blank. |
|-------|--|
| | Valid special options are: N - null-value suppression F - fixed field length " " - normal |
| Actn. | Enter valid special option. |

NAT4231: Coupled file entries must be specified at start of DDM.

| Text | Coupled file entries must be specified at start of DDM. |
|-------|---|
| Expl. | Coupled file entries must be specified at the start of the DDM. |
| Actn. | Enter the coupled file entries at the start of the DDM. |

NAT4232: Alternate index missing for VSAM, ISAM or LEASY.

| Text | Alternate index missing for VSAM, ISAM or LEASY. |
|-------|---|
| Expl. | If the descriptor is "A", an alternate index must be specified. |
| Actn. | Enter the alternate index. |

NAT4233: Occurrence must be greater than "1".

| Text | Occurrence must be greater than "1". |
|-------|---|
| | For a periodic group or a multiple-value field, only an occurrence greater than "1" is permitted. |
| Actn. | Enter correct value for the occurrence. |

NAT4234: Multiple-value field within periodic group not allowed.

| Text | Multiple-value field within periodic group not allowed. |
|-------|---|
| Expl. | In VSAM processing, a periodic group must not contain a multiple-value field. |
| Actn. | Change the field in the DDM. |

NAT4235: Multiple-value field cannot be a descriptor.

| Text | Multiple-value field cannot be a descriptor. |
|-------|---|
| Expl. | For VSAM processing, a multiple-value field cannot be a descriptor. |
| Actn. | Change the field type, or remove the descriptor indication. |

NAT4236: Occurrence missing for periodic group.

| Text | Occurrence missing for periodic group. |
|-------|--|
| · · | In VSAM processing, an occurrence greater than "1" must be specified for a periodic group. |
| Actn. | Enter the correct occurrence. |

NAT4237: Alternate index not allowed for group or periodic group.

| Text | Alternate index not allowed for group or periodic group. |
|-------|---|
| Expl. | In VSAM processing, an alternate index is not allowed for a |
| | group or a periodic group. |
| Actn. | Change type of field, or do not specify an alternate index. |

NAT4238: Coupled file entry not allowed.

| Text | Coupled file entry not allowed. |
|-------|--|
| Expl. | In VSAM processing, coupled file entries in the DDM are not allowed. |
| Actn. | Remove the coupled file entries. |

NAT4239: Illegal characters in alternate index file name.

| Text | Illegal characters in alternate index file name. |
|-------|---|
| | The correct syntax for the alternate index file name requires that the first character be alphanumeric; the following characters may either be alphanumeric or numeric. |
| Actn. | Enter correct file name. |

NAT4240: DBID numbers must exclude one another.

| Text | DBID numbers must exclude one another. |
|-------|---|
| Expl. | When copying files, the database identifications (DBIDs) of the files must be different from one another. |
| Actn. | Enter correct DBID. |

NAT4241: Primary key has been defined twice.

| Text | Primary key has been defined twice. | |
|-------|---|--|
| Expl. | In VSAM processing, only one field may be specified as primary key. | |
| Actn. | Define only one primary key. | |

NAT4242: Type must be blank.

| Text | Type must be blank. | |
|-------|--|--|
| | In VSAM processing, the type of the field where the primary key is specified must be specified with a blank character. | |
| Actn. | Change type to a blank character. | |

NAT4243: Primary key has not been specified.

| Text | Primary key has not been specified. | |
|-------|---|--|
| Expl. | In VSAM processing, one primary key must be specified in the DDM. | |
| Actn. | Enter one primary key field. | |

NAT4244: Duplicate name in DDM not possible.

| Text | Duplicate name in DDM not possible. | |
|-------|--|--|
| Expl. | There is a name in the DDM which is specified twice. | |
| Actn. | Change the name which is specified twice. | |

NAT4245: The CICS file name is missing.

| Text | The CICS file name is missing. | |
|-------|--|--|
| Expl. | The CICS file name in the definition of the file entry is missing. | |
| Actn. | Enter the CICS file name. | |

NAT4246: Only "Y" or "N" may be entered in this field.

| Text | Only "Y" or "N" may be entered in this field. | |
|-------|--|--|
| Expl. | In this field, you may only enter "Y" (for YES) or "N" (for NO | |
| Actn. | . Enter "Y" or "N". | |

NAT4247: Periodic group is not in FDT.

| Text | Periodic group is not in FDT. | |
|-------|--|--|
| | There is a periodic group specified in the DDM which does not appear in the corresponding Field Description Table (FDT). | |
| Actn. | Check DDM for the specified periodic group. | |

NAT4248: Use unique key flag/null flag only for VSAM upgrade.

| Text | Use unique key flag/null flag only for VSAM upgrade. | |
|-------|---|--|
| | The unique key flag and the null flag can only be specified if the upgrade flag has been signed. This is only meaningful if the field has an alternate index. | |
| Actn. | Specify correct combination of flags. | |

NAT4249: Invalid format or length.

| Text | Invalid format or length. | |
|-------|--|--|
| Expl. | Only the following format/length combinations are valid: - INTEGER (I4) - FLOAT (F4/F8) - DATE - TIME - LOGICAL (L1). | |
| Actn. | Check DDM and correct error. | |

NAT4250: Invalid character in descriptor option.

| Text | Invalid character in descriptor option. | |
|-------|---|--|
| Expl. | In column D, only the following values are allowed: | |
| | D - descriptor | |
| | S - subdescriptor or superdescriptor | |
| | P - phonetic descriptor | |
| | " " - not a descriptor | |
| | and for VSAM files: | |
| | P - primary index | |
| | A - alternate index | |
| Actn. | Enter valid descriptor option. | |

80 Natural System Error Messages 4251-4300

NAT4251: Invalid action code specified.

| Text | Invalid action code specified. | |
|-------|---|--|
| Expl. | Only the action codes displayed on the selection menu may be specified. | |
| Actn. | Enter valid action code. | |

NAT4252: LIST function executed.

| Text | LIST function executed. |
|-------|-------------------------|
| Actn. | No action required. |

NAT4253: Invalid file number specified.

| Text | Invalid file number specified. |
|-------|--|
| Expl. | The database file number must be specified as a number between 1 and 5000. |
| Actn. | Enter a valid file number. |

NAT4254: DBID numbers must be different and cannot be "0".

| Text | DBID numbers must be different and cannot be "0". |
|-------|--|
| - | The database number must be specified as a number between 1 and 65535 (DBID=254 indicates a VSAM file; DBID=255 indicates a logical file). |
| Actn. | Enter a valid database number. |

NAT4255: File definition does not exist in data dictionary.

| Text | File definition does not exist in data dictionary. |
|-------|---|
| | The referenced file definition cannot be found in the data dictionary. Either a wrong name was specified or the data dictionary entry has not yet been defined. |
| Actn. | Enter valid file name from data dictionary. |

NAT4256: Invalid type of system file.

| Text | Invalid type of system file. |
|-------|--|
| | The following values are valid for specifying the type of system file: A - Adabas system file V - VSAM system file |
| Actn. | Specify correct value for system file type. |

NAT4257: Invalid name for VSAM system file.

| Text | Invalid name for VSAM system file. |
|------|--|
| | A valid name for the VSAM system file is required. This name is the same as specified in the Natural parameter module with the VSAM parameter (VSAM=name of VSAM system file). |
| | Specify correct name of VSAM system file. |

NAT4258: Source and target destination must be different.

| Text | Source and target destination must be different. |
|-------|---|
| Expl. | When copying programs, modules, or DDMs with the Natural utilities SYSMAIN or SYSDDM, a valid source and target destination must be specified. Target destinations may be DBID, FNR, System File Type, or System File Name (in case of VSAM system file). The source and target destination may not have the same values. |
| Actn. | Specify correct source and target destination. |

NAT4261: View cannot be read/listed; FSIZE is too small.

| Text | View cannot be read/listed; FSIZE is too small. |
|-------|---|
| Expl. | The view that is to be read/listed is too large to fit into the current File Buffer. This error may occur when reading a view with an online utility, listing a view with a command, or incorporating a view into a Natural object with an editor. |
| Actn. | Reduce the specifications in the file definition, or increase the value for the FSIZE parameter. |

NAT4262: File definition already exists in data dictionary.

| Text | File definition already exists in data dictionary. |
|------|---|
| - | A duplicate name for a file definition entry in the data dictionary was specified. |
| | Enter different file name or delete existing entry. If necessary, use the REPLACE option to overwrite the existing file definition. |

NAT4271: Error not directly corrigible. Press ENTER to edit DDM.

| Text | Error not directly corrigible. Press ENTER to edit DDM. |
|-------|---|
| Expl. | The error cannot be corrected interactively while processing the file definition. |
| Actn. | Use the editor to correct the error, and then repeat the desired action. |

NAT4272: Periodic group cannot be descriptor or have special option.

| Text | Periodic group cannot be descriptor or have special option. |
|-------|---|
| Expl. | For a periodic group, a descriptor or a value for the special option must not be specified. |
| Actn. | Check whether the field is a group; if it is and should be, specify no values for descriptor and/or special option. |

NAT4274: Field is not member of this periodic group.

| Text | Field is not member of this periodic group. |
|-------|---|
| Actn. | Correct the field (level). |

NAT4275: Field is member of a periodic group.

| Text | Field is member of a periodic group. |
|-------|--------------------------------------|
| Actn. | Correct field. |

NAT4277: Field is not a multiple-value field.

| Text | Field is not a multiple-value field. |
|-------|--|
| | In the FDT (Field Description Table), the field is not a multiple-value field. |
| Actn. | Specify the correct type of the field. |

NAT4278: Level number must be incremented consecutively.

| Text | Level number must be incremented consecutively. |
|-------|---|
| Expl. | The difference between two level numbers must be "1". |
| Actn. | Correct the level number. |

NAT4279: The field specified in the DDM is not in the FDT.

| Text | The field specified in the DDM is not in the FDT. |
|-------|---|
| 1 1 | The field specified in the DDM does not exist in the corresponding Field Description Table (FDT). |
| Actn. | Check whether the correct field has been specified. |

NAT4280: Format must be alphanumeric (A).

| Text | Format must be alphanumeric (A). |
|-------|---|
| | In the FDT, the format is specified as alphanumeric, and the format in the DDM must be the same as in the FDT. |
| Actn. | Change the format to alphanumeric (A). |

NAT4285: Periodic group must be specified with "P".

| Text | Periodic group must be specified with "P". |
|-------|--|
| Expl. | The indicator for a periodic group is "P". |
| Actn. | Specify the correct type, "P". |

NAT4287: Field is not a descriptor.

| Text | Field is not a descriptor. |
|-------|---|
| Expl. | A wrong character has been specified in the descriptor field. |
| Actn. | Specify correct character for descriptor field: " " or "D". |

NAT4288: A group must contain at least one field.

| Text | A group must contain at least one field. |
|-------|--|
| Expl. | A group must contain at least one field, or another group. |
| Actn. | Check the level or add fields to the group. |

NAT4289: You are not allowed to LIST or CATALOG this DDM.

| Text | You are not allowed to LIST or CATALOG this DDM. |
|-------|---|
| Expl. | You are not linked to the file in the Natural Security System and, therefore, not allowed to LIST or CATALOG the DDM. |
| Actn. | Contact your Natural Security administrator. |

NAT4290: You are not authorized to catalog this DDM.

| Text | You are not authorized to catalog this DDM. |
|-------|---|
| Expl. | Natural SECRITY does not allow you to catalog this DDM. |
| Actn. | Contact your Natural Security administrator. |

NAT4291: Do not specify both, edit command and line command.

| Text | Do not specify both, edit command and line command. |
|-------|--|
| | When editing, only one command may be specified, either in a source line or in the command line. |
| Actn. | Press ENTER to eliminate line command. |

NAT4292: Line subcommand outside source lines.

| Text | Line subcommand outside source lines. |
|-------|--|
| - | A line subcommand may only be entered in one of the source lines that are displayed for editing. |
| Actn. | Enter line command in a source line. |

NAT4293: Invalid positioning number.

| Text | Invalid positioning number. |
|-------|--|
| · · | A positioning action was requested, but the position number was specified incorrectly. |
| Actn. | Enter valid position number. |

NAT4294: No line has been marked with "X".

| Text | No line has been marked with "X". |
|-------|---|
| · · | A MOVE, COPY, SHIFT, or X subcommand was used, but no line was marked with "X". |
| Actn. | Mark a line with "X" before referencing it. |

NAT4295: No line has been marked with "Y".

| Text | No line has been marked with "Y". |
|-------|--|
| - | A MOVE, COPY, or SHIFT command was specified, but no line was marked with "Y". |
| Actn. | Mark a line with "Y" before referencing it. |

NAT4296: "Y" position must be after "X" position.

| Text | "Y" position must be after "X" position. |
|-------|--|
| Expl. | The "Y "position must always be located AFTER the "X" position |
| | in the program. |
| Actn. | Position "X" and "Y" correctly. |

NAT4297: Copied/moved lines overlap target line.

| Text | Copied/moved lines overlap target line. |
|-------|---|
| Expl. | A MOVE/COPY line command can only be executed if the target position to which the lines are to be moved/copied is outside the range marked with the labels "X" and "Y". |
| Actn. | Reposition "X" or "Y", or move/copy to different target position. |

NAT4298: Invalid label in MOVE command.

| Text | Invalid label in MOVE command. |
|-------|--|
| Expl. | Only "X" or "Y" may be used as labels in MOVE command. |
| Actn. | Enter valid label for MOVE command. |

NAT4299: Invalid edit command. Enter "?" for help.

| Text | Invalid edit command. Enter "?" for help. |
|-------|---|
| Expl. | An invalid command was specified in the edit command line. |
| | Enter valid edit command. For information on valid edit commands, enter "?" for help. |

81 Natural System Error Messages 4301-4350

NAT4301: No line number space for insertion, renumbering.

| Text | No line number space for insertion, renumbering. |
|-------|---|
| 1 1 | Line numbering does not allow for insertion of lines between the selected lines. |
| Actn. | Press ENTER to renumber or use specific RENUMBER command. |
| | Renumber the source before inserting. |

NAT4303: Edit field definition.

| Text | Edit field definition. |
|-------|--|
| Expl. | The detail specification for a field definition may be edited. |
| Actn. | Perform desired editing. |

NAT4312: Requested file description not available.

| Text | Requested file description not available. |
|-------|--|
| | The file definition to be read cannot be found in the data dictionary. |
| Actn. | Enter correct input. |

NAT4322: Undefined command.

| Text | Undefined command. |
|-------|---|
| Actn. | Enter valid command; or enter "?" to invoke help information on |
| | valid commands. |

NAT4323: No DDM with specified file number found.

| Text | No DDM with specified file number found. |
|-------|---|
| Expl. | There is no DDM with the given file number stored in the system file. |
| Actn. | Enter a correct file number. |

NAT4324: End of list.

| Text | End of list. |
|-------|--|
| Expl. | The end of the file definition list was reached. |
| Actn. | Check program and correct error. |

NAT4331: Enter "DELETE" or leave blank.

| Text | Enter "DELETE" or leave blank. |
|-------|--|
| | If the DELETE function is requested, you must confirm the desired deletion by entering the word "DELETE". If the deletion is not desired, leave the field blank. |
| Actn. | Enter correct input. |

NAT4332: Uncatalog action of file definition was not confirmed.

| Text | Uncatalog action of file definition was not confirmed. |
|-------|--|
| Actn. | Check program and correct error. |

NAT4333: File definition does not exist in data dictionary.

| Text | File definition does not exist in data dictionary. |
|-------|--|
| Expl. | The specified file definition does not exist in the data dictionary. |
| Actn. | Enter valid name for file definition. |

NAT4341: DDM is linked and will be read from the system file.

| Text | DDM is linked and will be read from the system file. |
|------|--|
| · · | The DDM which is to be read is linked. When you press ENTER, the DDM will be read from the system file into the source area. |
| | Press ENTER to read DDM. If you make any changes to the DDM, link it to the Natural nucleus again. |

NAT4342: Help information has been displayed.

| | | Help information has been displayed. |
|---|-------|--------------------------------------|
| I | Actn. | No action required. |

NAT4343: DDM is linked, but cannot be accessed by SYSDDM.

| Text | DDM is linked, but cannot be accessed by SYSDDM. |
|-------|--|
| | The DDM to be read is linked to the Natural nucleus. However, it does not exist on the system file (FDIC) from which it is to be read, because either you are accessing the wrong system file or the DDM has been deleted from the system file. |
| Actn. | Make sure you use the correct system file. |

82 Natural System Error Messages 4351-4400

NAT4371: A database response code was received.

| | Text | A database response code was received. |
|---|-------|---|
| ſ | Actn. | Note the response code and contact your database administrator. |

NAT4373: Internal non-zero response code was received.

| Text | Internal non-zero response code was received. |
|-------|--|
| Expl. | A non-zero response code was received from an internal subroutine. |
| Actn. | Note the error and contact Software AG Technical Support. |

NAT4380: Correct field entry line directly, or press ENTER for editing.

| Text | Correct field entry line directly, or press ENTER for editing. |
|-------|--|
| Expl. | You can correct the error directly while the file definition is being processed. |
| Actn. | Correct the error in the field entry. |

NAT4390: The file definition has been cataloged.

| Text | The file definition has been cataloged. |
|-------|---|
| Expl. | The file definition has been cataloged and stored in the data dictionary. |
| Actn. | No action required. |

NAT4391: File definition checked successfully against the database.

| Text | File definition checked successfully against the database. |
|-------|--|
| | The file definition has been compared with the definition in the physical database and no inconsistencies between the two have been found. |
| Actn. | No action required. |

NAT4392: The file definition for the file has been generated.

| Text | The file definition for the file has been generated. |
|-------|---|
| | The file definition for the data dictionary has been successfully generated from the physical file definition in the database. The file definition is now available in the work area. |
| Actn. | No action required. |

NAT4393: The file definition has been read into the work area.

| Text | The file definition has been read into the work area. |
|-------|---|
| Expl. | The file definition has been read successfully from the data dictionary into the work area. |
| Actn. | No action required. |

NAT4394: File list selection menu has been displayed.

| | Text | File list selection menu has been displayed. |
|---|-------|--|
| ſ | Actn. | No action required. |

NAT4395: The file definition has been uncataloged.

| Text | The file definition has been uncataloged. |
|-------|--|
| Expl. | The file definition has been uncataloged from the data dictionary. |
| Actn. | No action required. |

83 Natural System Error Messages 4401-4450

NAT4404: Error in internal subroutine.

| Text | Error in internal subroutine. |
|-------|-------------------------------------|
| Actn. | Note error and contact Software AG. |

NAT4405: The selected number is out of range.

| Text | The selected number is out of range. |
|-------|---|
| Expl. | You may only select numbers for global variables that are displayed on the screen. |
| Actn. | Enter correct number for selection. |

NAT4406: Number for selection of global variable is missing.

| Text | Number for selection of global variable is missing. |
|-------|--|
| | A number from the display screen must be entered to select a global variable for processing. |
| Actn. | Enter correct selection number. |

NAT4407: End of global variable list.

| Text | End of global variable list. |
|-------|--|
| Expl. | All global variables have been displayed successfully. |
| Actn. | Check program and correct error. |

NAT4408: Unknown function, enter "?" for help.

| Text | Unknown function, enter "?" for help. |
|-------|--|
| Actn. | Enter valid function, or "?" for help information on valid functions |
| | for global variables. |

NAT4409: Contents of work area will be deleted.

| Text | Contents of work area will be deleted. |
|-------|---|
| Expl. | The requested function will delete the source object which is currently in the source work area. |
| Actn. | If you do not wish the source to be deleted, leave the function with PF12, SAVE the source, and then perform the function. Otherwise press ENTER and continue. |

NAT4410: This file number already exists.

| Text | This file number already exists. |
|-------|--|
| Expl. | Each DDM must have a unique file number. |
| Actn. | Correct the file number. |

NAT4411: File number does not correspond to file name for replace.

| Text | File number does not correspond to file name for replace. |
|-------|---|
| Expl. | When you catalog a VSAM DDM to a VSAM system file using the REPLACE option, the file name (number) must already exist on the VSAM system file, so as to avoid duplicate records. If a new DDM is to be cataloged with the layout of an old one, use an unused file name and file number and catalog without the REPLACE option. |
| Actn. | Catalog the DDM with a file name (number) that does not exist on the VSAM system file. Do not use the REPLACE option in this case. |

NAT4412: Format must be "A", "P", "N", or "B".

| Text | Format must be "A", "P", "N", or "B". |
|-------|---------------------------------------|
| | Possible formats are: |
| | A - alphanumeric |
| | N - numeric unpacked |
| | P - packed numeric |
| | B - binary |
| Actn. | Enter valid field format. |

NAT4413: Length of an alphanumeric variable must not exceed 253.

| Text | Length of an alphanumeric variable must not exceed 253. |
|-------|---|
| Actn. | Enter valid length for variable. |

NAT4414: The length of a binary variable must not exceed 126.

| Text | The length of a binary variable must not exceed 126. |
|-------|--|
| Actn. | Enter valid length for binary variable. |

NAT4415: Overall length of numeric field (nn.m) must not exceed 29.

| Text | Overall length of numeric field (nn.m) must not exceed 29. |
|-------|--|
| | The overall length of a numeric field, i.e. the aggregate number of digits before and after the decimal character, must not exceed 29. |
| Actn. | Enter valid length for numeric variable. |

NAT4416: No more than 7 positions allowed after decimal character.

| Text | No more than 7 positions allowed after decimal character. |
|-------|---|
| | For a numeric variable, the number of digits AFTER the decimal character must not exceed 7. |
| Actn. | Enter valid number of digits after decimal character. |

NAT4417: REPLACE only valid for DDM contained in VSAM system file.

| Text | REPLACE only valid for DDM contained in VSAM system file. |
|-------|--|
| Expl. | A DDM may not be cataloged with the REPLACE option being used, unless the DDM already exists in the VSAM system file. |
| Actn. | Do not use the REPLACE option, unless the DDM already exists in the system file. |

NAT4418: Name for global variable must start with a "+".

| Text | Name for global variable must start with a "+". |
|-------|--|
| Expl. | The name of a global variable must begin with a "+". |
| Actn. | Enter "+" as the first character in the name of the global variable. |

NAT4419: Invalid variable name.

| Text | Invalid variable name. |
|-------|---|
| | The name of a global variable must begin with the character "+" and must be built according to the rules for variable names. The name must not contain a blank character. |
| Actn. | Enter a valid name for the variable. |

NAT4420: Global variable already exists.

| Text | Global variable already exists. |
|-------|--|
| - | While creating a new global variable, or while changing the name of a global variable, another global variable with the same name was found. |
| Actn. | Enter a different name for the global variable. |

NAT4421: Currently there is no DDM in the source area.

| Text | Currently there is no DDM in the source area. |
|-------|---|
| Expl. | The catalog (C) or test (T) function was specified, |
| | but no DDM was found in the Natural source area. |
| Actn. | Read a DDM into the source area, or edit or generate a DDM. |

NAT4422: REDEFINE not permitted for this field.

| Text | REDEFINE not permitted for this field. |
|-------|--|
| Actn. | Check program and correct error. |

NAT4423: Index permitted only for per.group/multiple-value field.

| Text | Index permitted only for per.group/multiple-value field. |
|-------|--|
| 1 1 | An index can only be specified for a periodic group or a multiple-value field. |
| Actn. | Check program and correct error. |

NAT4424: Maximum number of dimensions within a structure is 3.

| Text | Maximum number of dimensions within a structure is 3. |
|-------|---|
| Actn. | Check program and correct error. |

NAT4425: Initial value not permitted for view fields.

| Text | Initial value not permitted for view fields. |
|-------|--|
| Actn. | Check program and correct error. |

NAT4426: Edit mask not allowed for group or periodic-group field.

| | Text | Edit mask not allowed for group or periodic-group field. |
|---|-------|--|
| ľ | Actn. | Check program and correct error. |

NAT4427: Edit mask not permitted for structure.

| Text | Edit mask not permitted for structure. |
|-------|--|
| Actn. | Check program and correct error. |

NAT4428: Struct./view level must be 1-99; no variable in data area.

| Text | Struct./view level must be 1-99; no variable in data area. |
|-------|--|
| | The level number for a structure/view must be 1 - 99. Another reason for this error is that no variable is defined in the data area. |
| Actn. | Check program and correct error. |

NAT4429: Level numbers must be assigned in increments of 1.

| | Level numbers must be assigned in increments of 1. |
|-------|--|
| Actn. | Check program and correct error. |

NAT4430: Invalid level specification.

| Text | Invalid level specification. |
|-------|----------------------------------|
| Actn. | Check program and correct error. |

NAT4431: Invalid character in name field.

| | Invalid character in name field. |
|-------|----------------------------------|
| Actn. | Check program and correct error. |

NAT4432: Blank not permitted in name.

| | Blank not permitted in name. |
|-------|----------------------------------|
| Actn. | Check program and correct error. |

NAT4433: Format/length must not be specified for this field type.

| Text | Format/length must not be specified for this field type. |
|-------|--|
| Actn. | Check program and correct error. |

NAT4434: Invalid format.

| Text | Invalid format. |
|-------|----------------------------------|
| Actn. | Check program and correct error. |

NAT4435: Invalid length or format specification.

| Text | Invalid length or format specification. |
|-------|---|
| Actn. | Check program and correct error. |

NAT4436: Do not specify length with format "C", "D", "L", "T".

| Text | Do not specify length with format "C", "D", "L", "T". |
|-------|--|
| | For fields of the following formats, no length can be specified: D - date T - time L - logical C - attribute control |
| Actn. | Check program and correct error. |

NAT4437: Length specification for format "F" must be 4 or 8.

| Text | Length specification for format "F" must be 4 or 8. |
|-------|---|
| Expl. | Floating-point fields can only have format/length F4 or F8. |
| Actn. | Check program and correct error. |

NAT4438: Invalid length for format "A" or "B" or "I".

| Text | Invalid length for format "A" or "B" or "I". |
|-------|---|
| | Valid length for format A is 1 - 253. Valid length for format B is 1 - 126. Valid length for format I is 1, 2, 4. |
| Actn. | Check program and correct error. |

NAT4439: Invalid object type specified in command.

| Text | Invalid object type specified in command. |
|-------|--|
| | |
| Expl. | The object type specified in the command LIST, EDIT, etc. was incorrect. |
| | Valid object types are: |
| | P - program T - text |
| | S - subroutine Z - recording |
| | N - subprogram K - server |
| | 7 - function R - routines (LIST) |
| | H - helproutine D - data areas (LIST) |
| | C - copycode D - Predict description (EDIT) |
| | G - global data area CL - class |
| | L - local data area DI - dialog |
| | A - parameter data area CP - command processor |
| | M - map |
| Actn. | Enter valid command. |

NAT4440: Length must be specified in form "nn" or "nn.n".

| Text | Length must be specified in form "nn" or "nn.n". |
|-------|--|
| - | Length must be specified as "nn" (no decimal digits) or as "nn.n" (nn digits before and n digits after decimal character) |
| Actn. | Check program and correct error. |

NAT4441: Maximum length for decimal digits is 7.

| Text | Maximum length for decimal digits is 7. |
|-------|--|
| Expl. | There must be no more than 7 digits after the decimal character. |
| Actn. | Check program and correct error. |

NAT4442: Maximum length for numeric value is 29.

| Te | xt | Maximum length for numeric value is 29. |
|----|-----|---|
| Ac | tn. | Check program and correct error. |

NAT4443: Data area was tested successfully.

| Text | Data area was tested successfully. |
|-------|---|
| | The data area was tested successfully using the CHECK command. command. Note that a final syntax check of the generated DEFINE DATA statement is NOT done by the CHECK function but by the CATALOG/STOW command. |
| Actn. | No action required. |

NAT4444: Error in Miscellaneous field.

| Text | Error in Miscellaneous field. |
|-------|---|
| Expl. | The specification in the Miscellaneous field is invalid. See the Natural documentation for valid specifications. |
| Actn. | Supply valid specification for Miscellaneous field. |

NAT4445: Only "B", "V", "R" or blank permitted for type.

| Text | Only "B", "V", "R" or blank permitted for type. |
|-------|---|
| Actn. | Check program and correct error. |

NAT4446: Level for substructure must be = or GT previous level.

| Text | Level for substructure must be = or GT previous level. |
|-------|--|
| | The level for a substructure must be the same as or greater than the previous level. |
| Actn. | Check program and correct error. |

NAT4447: Variable definition required following structure definition.

| Text | Variable definition required following structure definition. |
|-------|--|
| Actn. | Check program and correct error. |

NAT4448: Modification of range/format may delete INIT/EM values.

| Text | Modification of range/format may delete INIT/EM values. |
|-------|---|
| Expl. | A field is defined with initial values or with an edit mask. If the range/format of this field is changed, the initial values will remain if they fit into the changed index range definition; if they do not fit, they will be deleted. |
| Actn. | Make sure you do not lose any initial values or edit masks you wish to keep. |

NAT4449: Initial values not permitted; F/L missing for user field.

| Text | Initial values not permitted; F/L missing for user field. |
|-------|---|
| Actn. | Check program and correct error. |

NAT4450: Periodic group within periodic group is not allowed.

| Text | Periodic group within periodic group is not allowed. |
|-------|---|
| Expl. | A periodic group must not be defined within another periodic group. |
| Actn. | Correct view definition. |

84 Natural System Error Messages 4451-4500

NAT4451: Syntax error in array index specification.

| Text | Syntax error in array index specification. |
|-------|--|
| Actn. | Check program and correct error. |

NAT4452: Upper/lower boundary LT 0; or index = 0 in array definition.

| Text | Upper/lower boundary LT 0; or index = 0 in array definition. |
|-------|---|
| | Either the upper/lower array boundary is less than 0, or the index in an array definition is 0. |
| Actn. | Check program and correct error. |

NAT4453: Invalid delimiter in INDEX clause.

| Text | Invalid delimiter in INDEX clause. |
|-------|------------------------------------|
| Actn. | Check program and correct error. |

NAT4454: Data area cataloged/stowed successfully.

| Text | Data area cataloged/stowed successfully. |
|-------|---|
| | The catalog/stow process is terminated without detecting any error in the data definition. The data definition may now be used in a Natural program with a DEFINE DATA statement. |
| Actn. | No action required. |

NAT4455: Only index or edit mask modifiable in a view field.

| Text | Only index or edit mask modifiable in a view field. |
|-------|---|
| Actn. | Check program and correct error. |

NAT4456: Maximum rank for data structures is 3.

| Text | Maximum rank for data structures is 3. |
|-------|---|
| Expl. | In the data area editor, the command ".E" (extended field definition) has been specified for a field inside a data structure, where the rank (maximum dimension of the field) exceeds 3. All dimensions of the previous substructures until level 1 and the dimension of the current field are added to calculate the rank of the current field. |
| Actn. | Check the data structure, or the field currently being edited, for correct dimensions. |

NAT4458: Variable specified in REDEFINE not available.

| Text | Variable specified in REDEFINE not available. |
|-------|--|
| | A variable used in a REDEFINE definition is not defined in the current block (or data area), or is defined on a different level. |
| Actn. | Check program and correct error. |

NAT4459: Data block not found.

| Text | Data block not found. |
|-------|---|
| Expl. | The data block indicated as the parent block in a child block definition was not found. |
| Actn. | Check program and correct error. |

NAT4460: Predict file is not of type "CONCEPTUAL".

| Text | Predict file is not of type "CONCEPTUAL". |
|-------|---|
| Expl. | The Predict file that is to be included as data definition from |
| | the Predict file into the data area, is not defined as a "CONCEPTUAL" |
| | file in Predict. Its only allowed to incorporate "CONCEPTUAL" files |
| | as data structure. |
| Actn. | Change file definition in Predict or select correct file. |

NAT4461: Mark fields for incorporation into global data area.

| Text | Mark fields for incorporation into global data area. |
|-------|---|
| Actn. | Mark the fields which are to be incorporated into the global data area. |

NAT4462: "n" fields have been incorporated into global data area.

| Text | "n" fields have been incorporated into global data area. |
|-------|--|
| Actn. | No action required. |

NAT4463: No fields have been incorporated into global data area.

Text No fields have been incorporated into global data area.

NAT4464: ".V" must not be used during redefinition or in a view.

| Text | ".V" must not be used during redefinition or in a view. |
|-------|---|
| Actn. | Do not use ".V" during redefinition or in a view. |

NAT4465: View definition must be assigned level 1.

| Text | View definition must be assigned level 1. |
|-------|---|
| Actn. | Assign correct level. |

NAT4466: Structure definition must have previous level + 1.

| | Structure definition must have previous level + 1. |
|-------|--|
| Actn. | Assign correct level. |

NAT4467: Group definition must contain at least 1 field.

| Text | Group definition must contain at least 1 field. |
|-------|---|
| Actn. | Check program and correct error. |

NAT4468: Data definition must not end with a flagged definition.

| Text | Data definition must not end with a flagged definition. |
|-------|---|
| Actn. | Check program and correct error. |

NAT4469: Constant has been defined without an initial value.

| Text | Constant has been defined without an initial value. |
|-------|---|
| Actn. | Check program and correct error. |

NAT4470: Constant not permitted within a redefinition.

| Text | Constant not permitted within a redefinition. |
|------|---|
| Actr | . Check program and correct error. |

NAT4471: Non-numeric value in length field.

| Text | Non-numeric value in length field. |
|-------|------------------------------------|
| Actn. | Check program and correct error. |

NAT4472: User-variable definition found within a view definition.

| Text | User-variable definition found within a view definition. |
|-------|--|
| Actn. | Check program and correct error. |

NAT4473: View contains fields not existent in the new DDM.

| Text | View contains fields not existent in the new DDM. |
|-------|---|
| Expl. | You have tried to modify the name of the DDM in the last column of the data area editor screen. However, one or more of the fields specified in the view are not defined in this DDM. |
| Actn. | Either do not change the DDM name, or specify the name of a DDM which contains all fields in the view. |

NAT4474: Program name missing in GENERATE command.

| Text | Program name missing in GENERATE command. |
|-------|---|
| Actn. | Issue GENERATE command with program name. |

NAT4475: Constant used as index has not been defined.

| Text | Constant used as index has not been defined. |
|-------|---|
| | The constant used as index for the array definition must be defined before the array definition. |
| Actn. | Check program and correct error. |

NAT4476: Non-numeric constant used as index for p.group/mult.field.

| Text | Non-numeric constant used as index for p.group/mult.field. |
|-------|--|
| - | A constant which is not numeric has been used as index for a periodic group or multiple-value field. |
| Actn. | Check program and correct error. |

NAT4477: Undefined constant used as index for per.group/mult.field.

| Text | Undefined constant used as index for per.group/mult.field. |
|-------|---|
| · · | A constant used as index for a periodic group or multiple-value field must have been defined before it can be used for that purpose. |
| Actn. | Check program and correct error. |

NAT4478: CATALOG/PURGE command not available if RECAT=ON.

| Text | CATALOG/PURGE command not available if RECAT=ON. |
|-------|--|
| | The commands CATALOG and PURGE are not available if the parameter RECAT (dynamic recatalog) has been set to RECAT=ON, either dynamically or in the Natural parameter module. Instead of CATALOG and PURGE, the commands STOW and SCRATCH should be used. |
| Actn. | Use valid command or change parameter. |

NAT4479: Natural work area is full; increase ESIZE parameter.

| | Natural work area is full; increase ESIZE parameter. |
|-------|--|
| Actn. | Increase the value for the ESIZE parameter. |

NAT4480: Invalid value for FLAG1.

| | Invalid value for FLAG1. |
|-------|----------------------------------|
| Actn. | Check program and correct error. |

NAT4481: ".*" command only allowed for mul.fields/periodic groups.

| Text | ".*" command only allowed for mul.fields/periodic groups. |
|-------|--|
| Expl. | In the data area editor, C* variables can be generated by using the line command ".*" for a multiple-value field or a periodic group. For all other kinds of lines, this command is not allowed. |
| Actn. | Enter ".*" command in a line of a multiple-value field or periodic group. |

NAT4482: Only 1 "C*" variable allowed for a multiple-value field.

| Text | Only 1 "C*" variable allowed for a multiple-value field. |
|-------|--|
| | You have used the command ".*" to generate a C* variable for a multiple-value field for which a C* has already been defined. Only one C* variable per multiple-value field is possible. |
| Actn. | Do not use this line command on this field. |

NAT4488: Function not available, because Predict is not installed.

| Text | Function not available, because Predict is not installed. |
|------|---|
| | The Predict dictionary must be installed in order to perform the function specified or to process the object specified. |
| | Install Predict, or do not use this function. |

NAT4489: DDM not consistent with Predict definitions.

| Text | DDM not consistent with Predict definitions. |
|-------|---|
| Expl. | You have incorporated fields from a DDM into a data area. However, the Predict definitions related to the DDM were modified after the DDM had been generated. Therefore, the Predict definitions were not incorporated into the data area. |
| Actn. | Either ignore, or generate the DDM again to avoid inconsistencies. |

85 Natural System Error Messages 4501-4550

NAT4501: Do not specify both edit and line command.

| Text | Do not specify both edit and line command. |
|-------|---|
| | The full screen editor can only process one line command or one edit command at a time. |
| Actn. | Use an edit command or a line command, not both. |

NAT4502: Line subcommand outside source lines.

| Text | Line subcommand outside source lines. |
|-------|---|
| Expl. | No line command can be processed when this line is empty. |
| Actn. | Do not enter a line command in an empty line. |

NAT4503: Invalid positioning number.

| Text | Invalid positioning number. |
|-------|--|
| - | The edit command for positioning forward (+) or backward (-) requires a number greater than 0. |
| Actn. | Specify correct positioning number. |

NAT4504: No line marked with "X".

| Text | No line marked with "X". |
|-------|---|
| | A command has been entered which refers to a specific line. The editor cannot process this command, however, because the line to which it refers has not been marked with an "X". |
| Actn. | Mark the appropriate line with an "X". |

NAT4505: No line marked with "Y".

| Text | No line marked with "Y". |
|-------|---|
| | A command has been entered which refers to a specific line. The editor cannot process this command, however, because the line has not been marked with a "Y". |
| Actn. | Mark the appropriate line with a "Y". |

NAT4506: Y-position must be behind X-position.

| Text | Y-position must be behind X-position. |
|-------|--|
| | To process the command that has just been entered, the line marker "Y" has to be placed below the line marker "X", not vice versa. |
| Actn. | Mark lines correctly with "X" and "Y", then issue command again. |

NAT4507: Copied/moved lines overlap target line.

| Text | Copied/moved lines overlap target line. |
|-------|--|
| | The line command ".CX-Y" or ".MX-Y" has been entered BETWEEN the lines marked with "X" and "Y". However, it is not possible to move or copy lines to a position which is WITHIN block of lines to be moved/copied. |
| Actn. | Copy/move lines correctly. |

NAT4508: Invalid target in MOVE command.

| Text | Invalid target in MOVE command. |
|-------|--|
| - | The line command MOVE needs as a parameter a specification like ".MX", ".MY" or ".MX-Y". The line(s) to be moved must be marked with "X" and/or "Y". |
| Actn. | Mark line(s) to be moved before issuing MOVE command. |

NAT4509: Invalid edit command. Enter "?" for help.

| Text | Invalid edit command. Enter "?" for help. |
|-------|---|
| Expl. | The edit command that has just been entered is unknown. |
| | Enter valid edit command; or enter "?" to invoke help information on edit commands available. |

NAT4510: Do not replace with the same data.

| Text | Do not replace with the same data. |
|-------|--|
| 1 1 | You must not replace a source string with the same data that you are scanning for. |
| Actn. | Issue correct scan/replace command. |

NAT4511: "SET TYPE object-type" prohibited by security definition.

| Text | "SET TYPE object-type" prohibited by security definition. |
|-------|--|
| Expl. | Natural Security does not allow you do issue this command. |
| Actn. | Do not use this command, or contact your Natural Security administrator. |

NAT4512: Only "+", "-", or "Q" are valid parameters.

| Text | Only "+", "-", or "Q" are valid parameters. |
|-------|---|
| | The shift subcommand allows only the following to be specified: + shift to right. - shift to left. Q leave shift subcommand. |
| Actn. | Enter valid subcommand. |

NAT4513: Shift value must be 1 - 71.

| Text | Shift value must be 1 - 71. |
|-------|---|
| Expl. | Number of positions for the SHIFT subcommand must be 1 to 71. |
| Actn. | Enter valid number for shift function. |

NAT4514: No line number space available; "RENUMBER" required.

| Text | No line number space available; "RENUMBER" required. |
|-------|--|
| Expl. | The line numbers in Natural programs must be unique and in ascending order, since they are used internally for control program flow. When inserting lines, only 9 lines may be inserted at one time between 2 lines numbered with an increment of 10 (for example, between program lines 1220 and 1230). Use the RENUMBER command or press ENTER to renumber the program. |
| Actn. | Renumber source program before inserting lines. |

NAT4515: ".J entered in the last line on screen.

| Text | ".J entered in the last line on screen. |
|-------|--|
| Expl. | The line command ".J" must be entered on the first line of two lines that are to be joined. Both lines to be joined must be visible on the screen. |
| Actn. | Enter ".J" in correct position. |

NAT4516: Command not implemented.

| Text | Command not implemented. |
|-------|--|
| Expl. | The command which has just been entered, does not exist. |
| Actn. | Enter valid command. |

NAT4517: Position the cursor to the split point.

| Text | Position the cursor to the split point. |
|-------|--|
| · · | When you use the line command SPLIT, you mark with the cursor the position at which the line is to be split. |
| Actn. | Place cursor at correct position. |

NAT4518: No shift parameter specified (+nn, -nn).

| Text | No shift parameter specified (+nn, -nn). |
|-------|--|
| | The command SHIFT requires specification of the number of positions for the shift operation and the shift direction. These are specified in the form "+nn" or "-nn". |
| Actn. | Enter number of shift positions and shift direction. |

NAT4519: No shift value specified (number of positions).

| Text | No shift value specified (number of positions). |
|-------|--|
| · · | The number of positions to be shifted must be specified for the SHIFT command. |
| Actn. | Enter number of shift positions. |

NAT4520: X-line must be on the screen for shift.

| Text | X-line must be on the screen for shift. |
|-------|--|
| Expl. | The X-label must be displayed on the screen for the SHIFT command to function. |
| Actn. | Position current line to display X-label. |

NAT4521: Scan value GT 32, or delimiter for scan value missing.

| Text | Scan value GT 32, or delimiter for scan value missing. |
|-------|---|
| | Either a scan value greater than 32 has been specified, or one of the |
| | delimiters enclosing the value to be scanned for is missing. |
| Actn. | Specify correct command. |

NAT4522: Replace value cannot be specified for REPLACE WITH NULL.

| Text | Replace value cannot be specified for REPLACE WITH NULL. |
|-------|--|
| | REPLACE WITH NULL value has been specified (marked) on the Scan Menu of the program editor. Subsequently, however, a SCAN/CHANGE command with a specific replace value has been entered. - If you want to replace a value by a null value, do not specify a replace value. - If you want to replace a value by a specific value, do not use REPLACE WITH NULL. |
| Actn. | Enter correct command/value combination. |

NAT4523: The specified profile does not exist.

| Text | The specified profile does not exist. |
|-------|---|
| Expl. | See the Natural documentation for information on editor profiles. |
| Actn. | Specify a valid profile name. |

NAT4524: Please enter a profile ID.

| Text | Please enter a profile ID. |
|-------|--|
| Expl. | For profile maintenance, a profile ID must be entered. |
| Actn. | Enter a profile ID. |

NAT4525: Do not change other profile.

| Text | Do not change other profile. |
|-------|--|
| | When Natural Security is installed, you are not allowed to change a profile to which a user ID other than yours is assigned. |
| Actn. | Do not try to change any profile you are not allowed to change. |

NAT4526: Profile has been successfully stored.

| Text | Profile has been successfully stored. |
|-------|---|
| Expl. | The profile has been successfully stored in the database. |
| Actn. | No action required. |

NAT4527: No "RECOVER" possible after more than 999 transactions.

| Text | No "RECOVER" possible after more than 999 transactions. |
|-------|---|
| | The highest value for "RECOVER nnn" is 999. After "nnn" source changes, the source will be automatically saved in the current library with the member name that has been defined in the current profile. |
| Actn. | Check program and correct error. |

NAT4528: Invalid parameter specified in SPLIT command.

| Text | Invalid parameter specified in SPLIT command. |
|-------|---|
| Expl. | An invalid parameter has been specified in the split screen command in an editor. Valid parameters are: P - programming objects D - data areas V - views (DDMs) DESC - Predict description |
| Actn. | Enter valid parameter for split command. |

NAT4529: Invalid parameter specified in SET command.

| Text | Invalid parameter specified in SET command. |
|-------|--|
| - | An invalid parameter has been specified in the SET command of an editor. For a description of the SET command syntax, see the Natural documentation. |
| Actn. | Enter correct SET command. |

NAT4530: EDIT command disallowed by security definition.

| Text | EDIT command disallowed by security definition. |
|-------|--|
| · · | The EDIT command for the invoked editor has been disallowed by Natural Security in the corresponding security profile. |
| Actn. | Contact your Natural Security administrator. |

NAT4531: Profile has been successfully deleted.

| Text | Profile has been successfully deleted. |
|-------|--|
| Expl. | The profile has been successfully deleted from the database. |
| Actn. | No action required. |

NAT4532: Editor profile has not been stored in the database.

| Text | Editor profile has not been stored in the database. |
|-------|--|
| | You have modified an editor profile which is not your own; you can use the modified profile, but the modifications will only be valid until you log on to another library. |
| Actn. | No action required. |

NAT4533: Direction indicator must be "+" or "-".

| Text | Direction indicator must be "+" or "-". |
|-------|---|
| | The only possible values for the direction indicator in the command line of the program editor are "+" and "-". |
| Actn. | Set direction indicator to "+" or "-". |

NAT4534: Cursor must be within source for special PF-key functions.

| Text | Cursor must be within source for special PF-key functions. |
|-------|---|
| | Before you press a PF-key to which one of the commands *CURSOR, *X or *Y is assigned, you must place the cursor at that position within the source to which you wish the command to be applied. |
| Actn. | Place cursor correctly, and press PF-key again. |

NAT4535: Message-line position must be "TOP", "BOT", "nn" or "-nn".

| Text | Message-line position must be "TOP", "BOT", "nn" or "-nn". |
|-------|---|
| Expl. | You can specify one of the following positions for the message line: TOP (or T) - top line of screen. BOT (or B) - bottom line of screen. nn - "nn"th line of screen (counting from top of screen). -nn - "nn"th line of screen (counting from bottom of screen). |
| Actn. | Specify a valid message-line position. |

NAT4536: Object :1: cannot be included.

| Text | Object cannot be included. |
|-------|--|
| Expl. | The object to be included has to be cataloged. |
| Actn. | Catalog the object before including it. |

86 Natural System Error Messages 4551-4600

NAT4599: Value of session parameter PD must not be "0".

| Text | Value of session parameter PD must not be "0". |
|-------|--|
| | This error occurs if you issue one of the terminal commands of the NATPAGE utility, and the PD parameter, which determines the number of screens to be stored with NATPAGE in the Natural system file is set to "0". |
| Actn. | Use the GLOBALS command to set the PD parameter to a value between 1 and 255. |

NAT4600: Multiple commands not allowed.

| Text | Multiple commands not allowed. |
|-------|---|
| _ | Only one command may be entered per screen. If multiple commands are detected, no update and no command interpretation are performed. |
| Actn. | Enter only one command. |

87 Natural System Error Messages 4601-4650

NAT4601: Invalid screen operation in line :1:, column :2:.

| Text | Invalid screen operation in line, column |
|-------|---|
| Expl. | A field variable must not be changed to a text constant. |
| | Delete the field or move it to another position by using the appropriate field command, then insert the text. |

NAT4602: Use ".E" command to edit field.

| Text | Use ".E" command to edit field. |
|-------|---|
| | The modification or definition of an edit mask for a field is only possible by invoking "extended field editing" with the command ".E". |
| Actn. | Use the field command ".E". |

NAT4603: Error in DDM.

| Text | Error in DDM. |
|-------|---|
| Expl. | An error was detected in the currently used Data Definition Module. |
| Actn. | Correct the DDM. |

NAT4604: Use edit mask to change format.

| Text | Use edit mask to change format. |
|-------|---------------------------------|
| Actn. | Use edit mask to change format. |

NAT4605: Use ".A" command to define array.

| | Use ".A" command to define array. |
|-------|--|
| Actn. | Enter the field command ".A" in the field. |

NAT4606: Invalid object name.

| | Invalid object name. |
|-------|------------------------------|
| Actn. | Specify a valid object name. |

NAT4607: No DDM loaded.

| Text | No DDM loaded. |
|-------|--|
| Expl. | An internal error occurred while trying to load a DDM. |
| Actn. | Contact Software AG - Natural support. |

NAT4608: The requested DDM is too large.

| Text | The requested DDM is too large. |
|-------|---|
| Expl. | The requested DDM is too large to be processed by the map editor. |
| Actn. | Reduce the size of the DDM. |

NAT4609: Invalid edit mask.

| Text | Invalid edit mask. |
|-------|---|
| | The edit mask specified is invalid. See the Natural documentation for detailed information on edit masks. |
| Actn. | Correct error. |

NAT4610: Invalid field format.

| Text | Invalid field format. |
|-------|---|
| | The specified field format is invalid. See the Natural documentation for valid format definitions. |
| Actn. | Correct error. |

NAT4611: Field name contains illegal characters.

| Text | Field name contains illegal characters. |
|-------|---|
| Expl. | The field name contains characters which are not allowed within a field |
| | name. |
| Actn. | Correct error. |

NAT4612: Too many digits before and/or after decimal character.

| Text | Too many digits before and/or after decimal character. |
|-------|--|
| | There are too many decimal digits before and/or after the decimal character. See the Natural documentation for additional information. |
| Actn. | Correct error. |

NAT4613: The source area is empty.

| Text | The source area is empty. |
|-------|--|
| Expl. | An attempt was made to edit an empty source area. |
| | Use function "I" (Initialize map) or "R" (Read map) to place a map into the source area. |

NAT4614: Map not found in source area.

| Text | Map not found in source area. |
|-------|---|
| Expl. | The source area does not contain the map with the specified name. Function "L" may be used to determine if a map is currently in the source area; or the map-entry field may be left blank to cause all maps in the source area to be displayed. |
| Actn. | Use function "I" (Initialize map) or "R" (Read map) to place a map into the source area. |

NAT4615: Specified object not found in current or steplib library.

| Text | Specified object not found in current or steplib library. |
|-------|--|
| _ | The Natural object (program, subprogram, data area, etc.) with the specified name could not be found either in the current library or in any concatenated library (steplib). |
| Actn. | Specify the correct name of the object. |

NAT4616: Invalid use of a command.

| Text | Invalid use of a command. |
|-------|--|
| | An attempt was made to use a command incorrectly. (for example, using the command ".A" for a text constant. |
| Actn. | Enter correct command in correct field. |

NAT4617: No delimiter matches attributes.

| Text | No delimiter matches attributes. |
|------------|---|
| 1 1 | The specified attributes are not consistent with the delimiter settings in the map profile. |
| Actn. | Use other attributes or change delimiter settings in the map profile. |

NAT4618: Too many occurrences of field in line :1:, column :2:.

| Text | Too many occurrences of field in line, column |
|-------|---|
| Expl. | An output field was used in more than 98 occurrences. |
| Actn. | Specify a new field. |

NAT4619: Multiple fields not allowed here: line :1:, column :2:.

| Text | Multiple fields not allowed here: line, column |
|-------|---|
| Expl. | An input-only field or a modifiable field must not be used in multiple occurrences. |
| Actn. | Correct error. |

NAT4620: String too long: line :1:, column :2:.

| Text | String too long: line, column |
|------|---|
| Expl | A text constant of over 58 characters was specified. Only text which consists of the repeated concatenation of the same character may be longer than 58 characters. |
| Actn | . Divide the text into 2 constants or use a variable containing the text. |

NAT4621: System variable must be an output field.

| Text | System variable must be an output field. |
|-------|--|
| Expl. | System variables may only used in output mode. |
| Actn. | Use a delimiter which indicates output mode. |

NAT4622: Overlapping detected in line :1:, column :2:.

| Text | Overlapping detected in line, column |
|-------|--|
| Expl. | This error may be caused by any of the following: - overlapping of one variable with another; - overlapping of a variable with the right border of the map; - overlapping of a variable and a text constant; - an invalid command was interpreted as text. |
| Actn. | Correct error. |

NAT4623: Type conflict with DDM definition: line :1:, column:2:.

| Text | Type conflict with DDM definition: line, column |
|-------|---|
| Expl. | The DDM variable attribute is not assigned to the screen variable attribute in the case of incompatible formats. Incompatible: A,B with N,P. A with B. Compatible : N with P. |
| Actn. | Change screen specification and then reassign. |

NAT4624: Reassignment not possible in line :1:, column :2:.

| Text | Reassignment not possible in line, column |
|-------|---|
| Expl. | This error may be caused by the following: - the variable is already assigned; - the variable is a system variable. |
| Actn. | Delete the variable and generate it from the DDM. |

NAT4625: Name of field/variable must be specified.

| Text | Name of field/variable must be specified. |
|-------|---|
| Actn. | Enter a field/variable name. |

NAT4626: Internal format error in map definition.

| Text | Internal format error in map definition. |
|------|--|
| - | The map editor has detected an internal format error in the map definition. A possible cause is the attempt to edit the map source area via another utility or program. |
| | Use function "I" (initialize map) or "R" (read map) to place the original map into the source area. |

NAT4627: AL/NL syntax error.

| Text | AL/NL syntax error. |
|-------|--|
| | The specification of AL or NL is incorrect. See the Natural documentation for detailed information. |
| Actn. | Specify AL/NL correctly. |

NAT4628: You may select only one item from the menu.

| Text | You may select only one item from the menu. |
|-------|---|
| Actn. | Select no more than one item. |

NAT4629: Not enough empty lines available for inserting/splitting.

| Text | Not enough empty lines available for inserting/splitting. |
|-------|---|
| Expl. | When you use the line commands "I" (insert) or "S" (split), all lines below the inserted/split line(s) will be "pushed" downward and the last empty line(s) of the map will be deleted to make room for the insertion/splitting. However, if there are not enough empty lines at the bottom of the map, the insert/split command cannot be executed. |
| Actn. | Make sure that enough empty lines are available before you insert new lines or split lines. |

NAT4630: Invalid rank setting.

| Text | Invalid rank setting. |
|-------|---|
| Expl. | This error message may be caused by any of the following: |
| | - The specified value was not greater than zero. |
| | - The specified value was not smaller than or equal to the rank |
| | of the array. |
| | - The specified value has already been assigned. |
| | Note: The rank of an array is equal to the number of indexes; |
| | for example, $A(3,4)$ is an element of array A with rank 2. |
| Actn. | Correct rank setting. |

NAT4631: Index is out of range.

| Text | Index is out of range. |
|-------|--|
| Expl. | The specified index is outside the array dimensions. |
| Actn. | Correct the index specification. |

NAT4632: Fixed index must be specified.

| Text | Fixed index must be specified. |
|-------|--|
| | If an array with 3 dimensions is used in a map, the index of at least one dimension must be fixed (integer or variable). |
| Actn. | Correct index specification. |

NAT4633: Invalid color.

| Text | Invalid color. |
|-------|--|
| | An invalid color was specified. The valid color codes may be determined by placing the cursor on the field COLOUR and pressing the HELP key. |
| Actn. | Specify a valid color. |

NAT4634: No source/object name specified.

| Text | No source/object name specified. |
|-------|--|
| | The source name is missing for a READ or PURGE function; or the object name is missing for the UNCATALOG function. |
| Actn. | Specify source/object name. |

NAT4635: No profile name specified.

| Text | No profile name specified. |
|-------|--|
| Expl. | A profile name must be specified when using function "I" or "M". |
| Actn. | Specify a profile name. |

NAT4636: Column shift can only be 0 or 1.

| Text | Column shift can only be 0 or 1. |
|-------|--|
| - | The standard column shift is "0" . In order to use the first column position for map fields, a column shift of "1" may be specified. |
| Actn. | Specify "0" or "1" . |

NAT4637: Conflict between helptext size/position and screen size.

| Text | Conflict between helptext size/position and screen size. |
|-------|---|
| Expl. | The currently defined size of the helptext window does not permit its being placed in the position you want it to be placed, because it would not fit onto the screen of the specified device ("Device Check"). You have to make the window smaller, change its position (or not use the Device Check option). |
| Actn. | Either make the helptext smaller (reduce page size and/or line size), or change its position. |

NAT4638: Map transmitted successfully.

| | Map transmitted successfully. |
|-------|-------------------------------|
| Actn. | No action required. |

NAT4639: Field/parameter names in a map must be unique.

| Text | Field/parameter names in a map must be unique. |
|-------|--|
| Expl. | The names of fields and parameters used in a map must be unique. |
| Actn. | Do not use duplicate field/parameter names in a map. |

NAT4640: SAVE command executed.

| Text | SAVE command executed. |
|-------|--|
| Expl. | The source has been stored in the current library. |
| Actn. | No action required. |

NAT4641: Map tested successfully.

| Text | Map tested successfully. | |
|-------|---|--|
| Expl. | A RUN command was executed successfully for the current source. | |
| Actn. | No action required. | |

NAT4642: Variable already used with other format/array dimensions.

| Text | Variable already used with other format/array dimensions. |
|-------|---|
| Expl. | The variable whose name you have specified as help parameter, attribute control variable or starting-from value has already been defined elsewhere with a different format or with other array dimensions. |
| Actn. | Use a different name or check the other variable of the same name. |

NAT4643: Invalid function code.

| Text | Invalid function code. |
|-------|---|
| Expl. | The specified function code is invalid. |
| Actn. | Enter a valid function code, or a "?" for help. |

NAT4644: Delimiter class must be "A", "O", "M" or "T".

| Text | Delimiter class must be "A","O","M" or "T". |
|-------|--|
| | An invalid code for the delimiter class was entered. Possible codes are: A - Input-only field O - Output-only field M - Modifiable field (output and input) T - Text constant |
| Actn. | Enter valid delimiter class. |

NAT4645: Attribute of delimiter is invalid.

| Text | Attribute of delimiter is invalid. |
|-------|-------------------------------------|
| Expl. | Valid attribute codes are: |
| | B Blinking NE Neutral |
| | C Cursive/italic BL Blue |
| | D Default (non-I, B, etc.) GR Green |
| | I Intensified RE Red |
| | N Non-display PI Pink |
| | U Underlined YE Yellow |
| | V Reversed video TU Turquoise |
| | Y Dynamic (attributes to be |
| | assigned dynamically by |
| | user program) |
| Actn. | Enter valid code. |

NAT4646: Delimiter must be a special character.

| Text | Delimiter must be a special character. |
|-------|--|
| Expl. | Only special characters may be used as delimiters. |
| Actn. | Enter a special character as delimiter. |

NAT4647: Page size must be 1 - 250.

| Text | Page size must be 1 - 250. |
|-------|--|
| - | The page size value must be in the range from 1 to 250 lines. The standard page size for 3270-type screens is 23 lines. |
| Actn. | Enter a valid page size. |

NAT4648: Line size must be 5 - 249.

| Text | Line size must be 5 - 249. |
|-------|---|
| | The line size value must be in the range from 5 to 249 characters. The standard line size for a 3270-type screen is 79 characters. |
| Actn. | Enter a valid line size. |

NAT4649: Enter "T" (top) or "B" (bottom).

| Text | Enter "T" (top) or "B" (bottom). |
|-------|---|
| · · | The message line may be located at the top (T) or the bottom (B) of the screen. |
| Actn. | Enter valid code ("T" or "B"). |

NAT4650: Invalid color code.

| Text | Invalid color code. |
|-------|---|
| Expl. | Valid color codes are: NE - Neutral BL - Blue GR - Green RE - Red PI - Pink YE - Yellow TU - Turquoise |
| Actn. | Enter a valid color code. |

88

Natural System Error Messages 4651-4700

NAT4651: Enter "UC" (upper case) or "LC" (lower case).

| Text | Enter "UC" (upper case) or "LC" (lower case). |
|-------|--|
| | "UC" indicates that input will be converted to upper case. "LC" indicates that lower-case input will not be converted to upper case. |
| Actn. | Enter a valid code ("UC" or "LC"). |

NAT4652: Enter "Y" (yes) or "N" (no).

| Text | Enter "Y" (yes) or "N" (no). |
|-------|---|
| Expl. | The only possible values for this field are "Y" (yes) and "N" (no). |
| Actn. | Enter "Y" or "N". |

NAT4653: Array dimension must be 0 to 3.

| Text | Array dimension must be 0 to 3. |
|-------|---------------------------------|
| Actn. | Specify valid array dimension. |

NAT4654: Control character must be a special character.

| Text | Control character must be a special character. |
|-------|--|
| · · | Only special characters may be used as the control character. The default control character is ".". |
| Actn. | Enter a valid control character. |

NAT4655: Enter "R" or "L" for right- or left-justified.

| Text | Enter "R" or "L" for right- or left-justified. |
|-------|---|
| | Only the following codes may be specified: R - Default justification of variable fields is right-justified. L - Default justification of variable fields is left-justified. |
| Actn. | Enter a valid code ("R" or "L"). |

NAT4656: Delimiter settings are ambiguous.

| Text | Delimiter settings are ambiguous. |
|-------|---|
| 1 1 | Either the same delimiter is defined more than once, |
| | or more than one delimiter is defined for the same class/attribute. |
| Actn. | Check the delimiter settings and correct error. |

NAT4657: Variable field has to be named.

| Text | Variable field has to be named. |
|-------|---|
| Expl. | A field which is defined directly on the screen (i.e., not selected from a view) must be subsequently assigned the attributes of a view field (post assignment); or must be assigned a name directly, using the extended field editing function. |
| Actn. | Use either post assignment or extended field editing to assign a name to the field. |

NAT4658: Select either "WRITE" or "INPUT".

| Text | Select either "WRITE" or "INPUT". |
|-------|--|
| | This error message may be caused by the following: - Neither WRITE nor INPUT has been marked. - Both WRITE and INPUT have been marked. |
| Actn. | Correct error. |

NAT4659: Dynamic layout contains user-defined variables.

| Text | Dynamic layout contains user-defined variables. |
|-------|--|
| · · | A map which is used as dynamic layout map must not contain user-defined variables. |
| Actn. | Delete the user-defined variables from the dynamic layout map, or use another map as dynamic layout map. |

NAT4660: Conflict between layout and map settings.

| Text | Conflict between layout and map settings. |
|-------|--|
| Expl. | This error message may be caused by one of the following: The layout contains ATTRIBUTE/CLASS combinations in the delimiter settings which are not defined with the current map. PAGESIZE or LINESIZE of layout and map are different. COMP settings of layout and map are not identical. KEYSTD settings of layout and map are not identical. HELP names of both layout and map are not blank and are not identical. |
| Actn. | Check map and layout settings and correct error. |

NAT4661: Profile already exists.

| Text | Profile already exists. |
|-------|---|
| Expl. | The ADD function was applied to a profile which already exists. |
| Actn. | Use the MODIFY function or use another profile name. |

NAT4662: Profile does not exist.

| Text | Profile does not exist. |
|-------|--|
| - | The MODIFY or DELETE function was applied to a profile which does not exist. |
| Actn. | Use the correct profile name. |

NAT4663: Profile "SYSPROF" must not be changed.

| Text | Profile "SYSPROF" must not be changed. |
|-------|---|
| - | It is not possible to change the default profile "SYSPROF" with the maintenance function. |
| Actn. | Define a user profile by using the ADD function. |

NAT4664: Delimiter must differ from control and decimal character.

| Text | Delimiter must differ from control and decimal character. |
|-------|--|
| | A delimiter must not be the same character as the control character or the decimal character defined in the profile settings. |
| | of the decimal character defined in the prome settings. |
| Actn. | Use another special character as the delimiter. |

NAT4665: "DY" option is invalid.

| Text | "DY" option is invalid. |
|-------|---|
| Expl. | The "DY" option must consist of alternating escape characters and attribute/color codes. |
| | Valid escape characters are all special characters and hexadecimal elements. |
| | Examples: <i> (intensify by "<") <re> (red by "<") <bl:re> (blue by "<", red by ":") "27p"28 (protected by "27)</bl:re></re></i> |
| Actn. | Correct error. |

NAT4666: Warning: Conflict between current profile + map profile.

| Text | Warning: Conflict between current profile + map profile. |
|-------|---|
| Expl. | The map to be edited was initialized with a profile other than the current profile. |
| Actn. | Press PF10 to obtain the correct profile name or ignore. |

NAT4667: Editing completed successfully.

| Text | Editing completed successfully. |
|-------|---|
| | This message indicates: In parameter mode, the prototype INPUT USING MAP statement was generated at the beginning of the map. In non-parameter mode, all variables were checked to determine if they were assigned. The validation rules were sorted by validation rank and by positions of the variables. |
| Actn. | No action required. |

NAT4668: Conflict between layout profile and enforced map profile.

| Text | Conflict between layout profile and enforced map profile. |
|-------|--|
| Expl. | The layout map was initialized with a profile other than the current profile; the current profile is marked with the "ENFORCE" option; and some attributes of the current profile have been changed in the meantime. |
| Actn. | Use another profile or another layout. |

NAT4669: Do not use help-text layout for map, or vice versa.

| Text | Do not use help-text layout for map, or vice versa. |
|-------|---|
| - | This message may be caused by one of the following: - The layout was initialized with "H" and the current map with "I". - The layout was initialized with "I" and the current map with "H". |
| Actn. | Use another layout or the other initialization function. |

NAT4670: Print mode setting is incorrect.

| Text | Print mode setting is incorrect. |
|-------|---|
| Expl. | The following codes may be chosen for print mode: |
| | I - inversion of print direction |
| | C - alternate character set |
| | N - field will not appear in hardcopy |
| | D - double-byte character mode. |
| | Attribute combinations may be used. |
| Actn. | Correct error. |

NAT4671: Invalid modification of map settings.

| Text | Invalid modification of map settings. |
|-------|--|
| | This error message may be caused if a class/attribute combination for delimiters was specified in the old map settings and is not specified in the new settings. |
| Actn. | Check settings and correct error. |

NAT4672: "Move" target is within command working range.

| Text | "Move" target is within command working range. |
|-------|---|
| | A "move" line command was issued for a block of lines and the cursor was positioned to a line within that block. |
| Actn. | Change cursor position or line range. |

NAT4673: An object with the same name already exists.

| Text | An object with the same name already exists. |
|-------|---|
| | During initialization of a map or a helptext, a name was specified which is already used by another object in the library. This error may also occur in the STOW or SAVE function, if a name is explicitly specified. |
| Actn. | Change map name or scratch existing object. |

NAT4674: Specified object does not exist, or is not a map/helptext.

| Text | Specified object does not exist, or is not a map/helptext. |
|-------|--|
| | The specified map name is wrong. A map or a helptext with the specified name does not exist; or the referenced object is neither a map nor a helptext. |
| Actn. | Change map name or use initialize function. |

NAT4675: Device specification is missing.

| Text | Device specification is missing. |
|-------|--|
| | The device specified with the device check field was not defined using the maintenance function; or the MODIFY or DELETE function was used for a non-existing device specification. |
| Actn. | Specify the device attributes using the maintenance function. |

NAT4676: Device specification already exists.

| Text | Device specification already exists. |
|-------|---|
| Expl. | The specification of the device already exists. |
| Actn. | Use the MODIFY function. |

NAT4677: Device name is missing.

| Text | Device name is missing. |
|-------|---|
| - | The name of the device specification to be added, modified or deleted is missing. |
| Actn. | Enter a device name. |

NAT4678: Attribute does not match device characteristics.

| Text | Attribute does not match device characteristics. |
|-------|--|
| | The device check was enabled by entering a device name which does not support the defined attributes. The cursor is positioned to the attribute which is in conflict with the specified device. |
| Actn. | Change attribute or disable device check. |

NAT4679: Layout does not exist.

| Text | Layout does not exist. |
|-------|--|
| - | A layout map or a layout help text was specified in the map settings or the profile, but the layout does not exist as a source map. |
| Actn. | Correct error. |

NAT4680: Only "H" or "V" possible.

| Text | Only "H" or "V" possible. |
|-------|--|
| | The direction of the secondary index can only be horizontal (H) or vertical (V). |
| Actn. | Enter valid direction. |

NAT4681: Only output class possible with "WRITE".

| Text | Only output class possible with "WRITE". |
|-------|--|
| | A delimiter or an AD attribute was specified with a field class equal to input (A) or modify (M). This is not possible if a WRITE statement is to be generated as a result of the map definition process. |
| Actn. | Check program or map settings, and correct error. |

NAT4682: Conflict in array dimensions.

| Text | Conflict in array dimensions. |
|-------|--|
| | A DDM array was post-assigned to an array and one or more dimensions of the DDM array are smaller than the predefined array. |
| | |
| Actn. | Check array dimensions and correct error. |

NAT4683: Attribute control variable is missing.

| Text | Attribute control variable is missing. |
|-------|--|
| | A delimiter with attribute "Y" was used, but no attribute control variable (CV=name) was defined in the map settings. An AD attribute "Y" was defined, but no attribute control variable (CV=name) was defined at the field level or in the map settings. |
| Actn. | Define the attribute control variable. |

NAT4684: Validation rule priority already exists.

| Text | Validation rule priority already exists. |
|-------|---|
| | An attempt was made to change the priority of a validation rule, but a validation rule for this field with the specified priority already exists. |
| Actn. | Use another priority. |

NAT4685: Field is not an array.

| Text | Field is not an array. |
|-------|--|
| | Before applying index parentheses to a field name, the field must be defined as an array by using the command ".A" or "A". |
| Actn. | Remove index parentheses. |

NAT4686: Do not apply ".A" command to a scalar value.

| Text | Do not apply ".A" command to a scalar value. |
|-------|---|
| - | The array field command or the array line command cannot be used with elementary database fields or with system variables. Validation rules are not allowed for system variables. |
| Actn. | Do not use an array, or define a user-defined variable. |

NAT4687: Helproutine for a helptext or WRITE map is not allowed.

| Text | Helproutine for a helptext or WRITE map is not allowed. |
|-------|--|
| | A helproutine name may only be specified with maps, not with helptexts. If the map is to be used in a WRITE USING MAP statement, a helproutine name must not be specified. |
| Actn. | Correct error. |

NAT4688: STOW command executed successfully.

| Text | STOW command executed successfully. |
|-------|---|
| Expl. | The map was successfully saved and cataloged. |
| Actn. | No action required. |

NAT4689: Direct command was executed.

| Text | Direct command was executed. |
|-------|---|
| Expl. | The specified direct command was executed successfully. |
| Actn. | No action required. |

NAT4690: Invalid edit mask.

| Text | Invalid edit mask. |
|-------|---|
| | The specified edit mask is not a valid Natural edit mask. For information on valid edit masks, you may invoke the help facility. |
| Actn. | Use valid edit mask. |

NAT4691: Decimal character conflict.

| Text | Decimal character conflict. |
|-------|---|
| | The map uses a decimal character which is in conflict with the decimal character defined for the current session. |
| Actn. | Change session profile, using GLOBALS command. |

NAT4692: Feature not available.

| Text | Feature not available. |
|-------|--|
| | The desired feature is only available if the Predict dictionary system is installed. |
| Actn. | Do not use this feature. |

NAT4693: Conflict between processing rules.

| Text | Conflict between processing rules. |
|-------|---|
| Expl. | This error occurs if a field was first defined as a user-defined or or undefined field, and processing rules were assigned to that field by the user; if this field is then post-assigned to a database field, and the dictionary contains processing rules for that database field on ranks which are already occupied by the user-defined rules, this conflict occurs. |
| Actn. | Check user rules. |

NAT4694: Consistency error in dictionary.

| Text | Consistency error in dictionary. |
|-------|---|
| - | During definition or retrieval of processing rules, a consistency error within the dictionary"s processing rules was discovered. |
| Actn. | Contact your dictionary administrator. |

NAT4695: Processing rule already exists.

| Text | Processing rule already exists. |
|-------|--|
| - | The name specified for the processing rule which is to be added to the dictionary already exits. |
| Actn. | Use another name for the processing rule. |

NAT4696: Specification of prefix not allowed here.

| Text | Specification of prefix not allowed here. |
|-------|---|
| · · | A new prefix may not be introduced with extended field editing. Existing prefixes may only be changed to correspond with program labels. |
| Actn. | Use the post-assign facility to specify new prefixes. |

NAT4697: Page size must be 3 - 250.

| Text | Page size must be 3 - 250. |
|-------|--|
| Expl. | If Standard Keys are set to Y, the minimum page size is 3. |
| Actn. | Specify correct page size. |

NAT4698: Modification rejected by user exit.

| Text | Modification rejected by user exit. |
|-------|--|
| Expl. | User exit activated in Predict DDA services. |
| Actn. | Please contact your DBA to allow the modification of free rules. |

NAT4699: Number of occurrences has to be greater than zero.

| Text | Number of occurrences has to be greater than zero. |
|-------|--|
| Actn. | Set number of occurrences to a value greater than "0". |

| Text | DDM does not exist, or you are not allowed to access it. |
|------|---|
| | The specified DDM does not exist or is protected by Natural Security. The DDM can also be used in the data area of a program and the program is included in the map editor. |
| | Enter valid DDM name or check program; or contact your Natural Security administrator. |

89

Natural System Error Messages 4701-4750

NAT4701: No data defined in program.

| Text | No data defined in program. |
|-------|---|
| Expl. | The program (or subprogram, subroutine, helproutine) to be displayed in the top half of the editing screen does not contain any explicit field definitions. |
| Actn. | Check program to be displayed, and have the data area used by the program displayed to see the desired variables. |

NAT4702: Field/parameter type is missing.

| Text | Field/parameter type is missing. |
|-------|---|
| Expl. | Field/parameter type must be specified. |
| Actn. | Enter a field/parameter type. |

NAT4703: Do not enter starting value for an index which is "0".

| Text | Do not enter starting value for an index which is "0". |
|-------|--|
| Expl. | For a dimension whose index is "0" you cannot specify a "Starting from" value. |
| Actn. | Either specify an index, or remove starting value. |

NAT4704: Dynamic layout not possible for WRITE statement.

| Text | Dynamic layout not possible for WRITE statement. |
|-------|--|
| - | You cannot use a dynamic layout map for a map that is to be output via a WRITE statement. |
| Actn. | Correct error. |

NAT4705: Verification name already exists, but is not a free rule.

| Text | Verification name already exists, but is not a free rule. |
|------|---|
| | The verification you have specified already exists and is defined in Predict as an automatic rule. |
| | Specify other verification name. |

NAT4706: Rejected by Predict defaults.

| Text | Rejected by Predict defaults. |
|-------|---|
| 1 1 | The switch "Rule in Map Editor" in the Predict Defaults is set to "D" (disallowed). |
| Actn. | Ask your Predict administrator to change the default. |

NAT4707: Do not enter a rule name and source text at same time.

| Text | Do not enter a rule name and source text at same time. |
|------|---|
| | Enter either a free rule name to include the rule source from Predict into the rule editor, or enter source text, press ENTER and then enter a rule name to save the source in Predict. |
| | Remove either the rule name or the source text and press ENTER again. |

NAT4708: Do not apply a processing rule to an output field.

| Text | Do not apply a processing rule to an output field. |
|-------|--|
| 1 1 | A processing rule that is attached to an output field is not executed. |
| Actn. | Remove the processing rule or change the field class. |

NAT4709: An internal error occurred.

Text An internal error occurred.

NAT4710: Memory allocation failed.

| Text | Memory allocation failed. |
|------|--|
| Actn | Save your work and try to free computer resources. |

NAT4711: Bad object handle detected.

| Text | Bad object handle detected. |
|-------|--|
| | Natural received an object handle that does not identify an object. A programming error in an application has assigned an illegal value to an object handle. |
| Actn. | Check and correct program. |

NAT4712: Bad value in Attribute type.

| Text | Bad value in Attribute type. |
|-------|--|
| Expl. | An illegal value has been assigned by an application program to the Attribute. |
| Actn. | Check and correct program. |

NAT4713: Invalid value assignment for a SUPPRESS-XXX-EVENT Attribute.

| Text | Invalid value assignment for a SUPPRESS-XXX-EVENT Attribute. |
|------|--|
| - | A value has been assigned to one of the SUPPRESS-XXX-EVENT Attributes that is not permitted. |
| 1 | Consult the documentation for permitted values and correct program accordingly. |

NAT4714: Bad parent type.

| Text | Bad parent type. |
|-------|---|
| | The object referred to by the PARENT Attribute is of an incompatible type. For example, a List Box Item requires a List Box Control as a parent. |
| Actn. | Check object type in the documentation. |

NAT4715: Bad object handle detected in Attribute SUCCESSOR.

| Text | Bad object handle detected in Attribute SUCCESSOR. |
|-------|--|
| Expl. | The Attribute SUCCESSOR does not refer to an object. |
| Actn. | Check and correct program. |

NAT4716: Natural cannot perform requested action.

| Text | Natural cannot perform requested action. |
|-------|---|
| | A Natural application has tried to perform an operation on an object that does not provide for such an operation. |
| Actn. | Consult your documentation for valid operations and correct your program accordingly. |

NAT4717: Invalid data type.

| Text | Invalid data type. |
|-------|--|
| Expl. | The Natural data type used for the parameter value does not match the type required by Natural. |
| Actn. | Consult your documentation for type compatibility and correct your program accordingly. |

NAT4718: Invalid font description.

| Text | Invalid font description. |
|-------|--|
| Expl. | The font description in the Attribute STRING is invalid. |
| Actn. | Check and correct program. |

NAT4719: Font handle not valid.

| Text | Font handle not valid. |
|-------|---|
| - | The FONT-HANDLE Attribute does not refer to an object of the type Font Control. |
| Actn. | Check and correct program. |

NAT4720: Bad index or position value specified in NGU subprgm parameter.

| Text | Bad index or position value specified in NGU subprgm parameter. |
|-------|---|
| Actn. | Check and correct program. |

NAT4721: Bad start position value specified in NGU subprogram parameter.

| Text | Bad start position value specified in NGU subprogram parameter. |
|-------|---|
| Actn. | Check and correct program. |

NAT4722: Bad end position value specified in NGU subprogram parameter.

| Text | Bad end position value specified in NGU subprogram parameter. |
|-------|---|
| Actn. | Check and correct program. |

NAT4723: Bad value in parameter "text-length".

| Text | Bad value in parameter "text-length". |
|------------|--|
| 1 1 | The value in the parameter "text-length" is smaller than the difference between the values of the parameters "start-position" and "end-position". |
| Actn. | Check and correct program. |

NAT4724: Bad value in parameter "line-from".

| Text | Bad value in parameter "line-from". |
|-------|-------------------------------------|
| Actn. | Check and correct program. |

NAT4725: Bad value in parameter "line-to".

| Text | Bad value in parameter "line-to". |
|-------|-----------------------------------|
| Actn. | Check and correct program. |

NAT4726: Bad value in parameter "column-from".

| Text | Bad value in parameter "column-from". |
|-------|---------------------------------------|
| Actn. | Check and correct program. |

NAT4727: Bad value in parameter "column-to".

| | Bad value in parameter "column-to". |
|-------|-------------------------------------|
| Actn. | Check and correct program. |

NAT4728: Bad value in parameter "colour-name".

| Text | Bad value in parameter "colour-name". |
|-------|---|
| Expl. | This can occur for the Attributes FOREGROUND-COLOUR-NAME or BACKGROUND-COLOUR-NAME. |
| Actn. | Consult your documentation for permitted values and correct program accordingly. |

NAT4729: Attribute cannot be modified.

Text Attribute cannot be modified.

NAT4730: Natural could not create window.

| Text Natural could not create window. | |
|---------------------------------------|--|
| Actn. | Check your program and ensure that you have sufficient system resources. |

NAT4731: Natural could not create Dialog Element.

| Text | Natural could not create Dialog Element. |
|-------|--|
| Actn. | Check your program and ensure that you have sufficient system resources. |

NAT4732: Attempt to create Menu Item failed.

| Text | Attempt to create Menu Item failed. |
|-------|--|
| | There is an internal limit for the number of Menu Items per menu. Try to limit the number of your menu items to a manageable number. Human engineering studies recommend a maximum of 7. |
| Actn. | Check and correct program. |

NAT4733: Keyword OBJECT in the handle definition expected.

| Text | Keyword OBJECT in the handle definition expected. |
|-------|---|
| · · | On non-GUI platforms only object handles (HANDLE OF OBJECT) may be defined. |
| Actn. | Check and correct handle definition. |

NAT4734: Operand2 must be defined as a handle variable.

| Text | Operand2 must be defined as a handle variable. |
|-------|--|
| Actn. | Check and correct program. |

NAT4735: Operand format is not INTEGER or length is invalid.

| Text | Operand format is not INTEGER or length is invalid. |
|-------|--|
| Expl. | An operand of format INTEGER is required for this operand. - The dialog id of the OPEN DIALOG, SEND EVENT or CLOSE DIALOG statement does not have format/length (I4). - The GIVING operand of a CREATE OBJECT or SEND METHOD statement does not have format/length I2 or I4. |
| Actn. | Correct format/length definition of the operand. |

NAT4737: Parameter-name not defined.

| Text | Parameter-name not defined. |
|-------|--|
| Expl. | Parameter-name not defined in DEFINE DATA PARAMETER section. |
| Actn. | Check and correct program. |

NAT4738: Statement/variable/constant not permitted on non-GUI platforms.

| Text | Statement/variable/constant not permitted on non-GUI platforms. |
|-------|--|
| | The program contains elements, such as the OPEN DIALOG statement, that are only applicable to GUI platforms. |
| Actn. | Check and correct program. |

NAT4739: Invalid Attribute value.

| Text | Invalid Attribute value. |
|-------|---|
| 1 1 | The value that has been assigned to the Attribute is illegal in this context. |
| Actn. | Assign a valid Attribute value. |

NAT4740: Incompatible Attribute name specified.

| Text | Incompatible Attribute name specified. |
|-------|---|
| - | Attribute name is not in the set of allowed Attributes for the Dialog Element type. |
| Actn. | Choose an allowed Attribute for this Dialog Element type. |

NAT4741: Invalid Dialog Element type specified.

| Text | Invalid Dialog Element type specified. |
|-------|--|
| Expl. | This Dialog Element type is not available. |
| | Consult your documentation and enter a valid Dialog Element type. |

NAT4742: Invalid Attribute name specified.

| Text | Invalid Attribute name specified. |
|------|--|
| | Consult your documentation and choose an allowed Attribute name. |

NAT4743: Attribute must not be queried.

| Text | Attribute must not be queried. |
|-------|---|
| Expl. | For this Dialog Element type, you must not query the value of this Attribute. |
| Actn. | Correct program. |

NAT4744: Attribute must not be modified.

| Text | Attribute must not be modified. |
|-------|--|
| | For this Dialog Element type, you must not modify the value of this Attribute. |
| Actn. | Correct program. |

NAT4745: Event queue overflow.

| Text | Event queue overflow. |
|-------|---|
| Expl. | During a long user interface operation, too many events have occurred. For example, the user has scrolled in a scrollbar by holding down the mouse button for a long time, which has caused too many timer events to occur in the meantime. |
| Actn. | When interacting with the user interface, interrupt from time to time. |

NAT4746: Format error in dialog definition.

| Text | Format error in dialog definition. |
|-------|---|
| Expl. | The dialog editor has detected a format error in the dialog definition. Possible causes: 1) Source data has been corrupted in the storage medium. 2) Source has been generated incorrectly because the source has been edited with another editor or utility. 3) The dialog object has been created and stored with a version of the dialog editor that is incompatible with the current version of the dialog editor. |
| Actn. | Upgrade your Natural development environment. If a dialog box appears offering you the choice to continue, you may be able to work with the dialog |

NAT4747: Format error in dialog source at line :1:.

| Text | Format error in dialog source at line :1:. |
|-------|---|
| Expl. | The dialog editor has detected a format error |
| | in the dialog source at the line indicated. |
| | Possible causes: |
| | 1) Source data has been corrupted in the storage |
| | medium. |
| | 2) Source has been generated incorrectly because |
| | the source has been edited with another |
| | editor or utility. |
| | 3) The dialog object has been created and stored |
| | with a version of the dialog editor that is |
| | incompatible with the current version of the |
| | dialog editor. |
| Actn. | 1) Upgrade your Natural development environment. |
| | 2) If a dialog box appears offering you the choice to continue, |
| | you may be able to work with the dialog. |

NAT4748: XREF request disallowed by Natural Security definition.

| Text | XREF request disallowed by Natural Security definition. |
|-------|---|
| Expl. | In a Natural Security environment, XREF can only request settings that provide more detailed information than defined by means of the Natural Security profile that applies. The following table shows the possible combinations (valid combinations marked with "+"): Definition I Request by XREF command in Natural I Security I profile I OFF ON FORCE |
| Actn. | Check data and correct error, or contact the DBA to modify the appropriate security profile. |

NAT4749: Function not possible with DBID = 0.

| Text | Function not possible with DBID = 0. |
|------|---|
| | To generate the Natural cross references the DBID of the Natural system file, where the module is to be stored, must not be zero. |
| | Contact the DBA to generate a valid Natural parameter module or invoke Natural and overwrite the value of the data base identification dynamically. |

NAT4750: Invalid input data.

| Text | Invalid input data. |
|---|---------------------------|
| Expl. Invalid data have been specified for the fi | |
| Actn. | Specify valid input data. |

90

Natural System Error Messages 4751-4800

NAT4751: A:1:must be entered.

| Text | Amust be entered. |
|-------|-------------------|
| Actn. | Enter a |

NAT4752: Unrecognized OCX control.

| Text | Unrecognized OCX control. |
|-------|--|
| Expl. | This class is not recognized as an OCX control. |
| | Ensure that the OLE control is entered in the system registry and that the licence file exists in your system. |

NAT4753: Unsupported format.

| Text | Unsupported format. |
|-------|--|
| Expl. | This format is not supported by Natural. |
| Actn. | Correct your program. |

NAT4754: Creation of window/dialog element failed due to low USER memory.

| Toyt | Creation of window/dialog element failed due to low USER memory. |
|------|---|
| Text | Creation of whitdow/dialog element failed due to low USER memory. |

| Expl. | This is a phenomenon which affects Windows 3.x and Windows 9x, but not |
|-------|--|
| | Windows NT. On these first two systems, all or part of the window data |
| | is managed by the 16-bit USER module, which imposes a 64KB restriction |
| | on the amount of window data which can be maintained across the whole |
| | system, independent of how much RAM you have installed in your computer. |
| | This in turn restricts the number and/or complexity of the windows which |
| | can be open at any time, as every open window and dialog element eats up |
| | some of this so-called USER memory. |
| | If the amount of USER memory free drops below a critical level, Windows |
| | may hang or the application may crash. To avoid this, Natural will not |
| | create a window or dialog element if it recognizes that (at the time of |
| | writing) less than 15% of the total USER memory is available. |
| | Note that for Windows NT, the window manager is entirely written in |
| | 32-bit code, and as such is not subject to this 64KB limitation. |
| Actn. | 32-bit code, and as such is not subject to this 64KB limitation. Close some windows (in any application) |
| | and retry the failed operation. |
| | |

NAT4755: Window manager attribute stack overflow.

| Text | Window manager attribute stack overflow. |
|-------|---|
| | An internal stack for storing attribute data is full. The most likely explanation is that too many dialogs of style "dialog box" are open at the same time. |
| Actn. | Rewrite the code to reduce the number of concurrently open dialog boxes. |

NAT4756: ActiveX control method or event parameter :1: not converted.

| Text | ActiveX control method or event parameter not converted. |
|-------|---|
| Expl. | The value passed as parameter to an ActiveX control method could not be converted to the format expected by the ActiveX control. The value received as parameter from an ActiveX control method could not be converted to the format expected in the Natural dialog. The value received as parameter from an ActiveX control event could not be converted to the format expected in the Natural event handler. The value passed as parameter in a Natural event handler back to the ActiveX control could not be converted to the format expected by the ActiveX control. |
| Actn. | The Natural documentation and online help contain tables that indicate which Natural data formats map to which ActiveX control data formats. Please cunsult these tables and choose a matching Natural data format. |

NAT4757: ActiveX control property value or return value not converted.

| Text | ActiveX control property value or return value not converted. | |
|-------|--|--|
| Expl. | The value passed as property value to an ActiveX control could not be converted to the format expected by the ActiveX control. The value received as property value from an ActiveX control could not be converted to the format expected in the Natural dialog. The value received as return value from an ActiveX control method could not be converted to the format expected in the Natural dialog. | |
| Actn. | The Natural documentation and online help contain tables that indicate which Natural data formats map to which ActiveX control data formats. Please consult these tables and choose a matching Natural data format. | |

NAT4758: ActiveX control raised exception :1:: :2:

| Text | ActiveX control raised exception: |
|-------|--|
| Expl. | The ActiveX control raised an exception with the indicated number and text. |
| 1 | Please consult the documentation of the ActiveX control to find out under which conditions this exception is raised. |

NAT4759: ActiveX control returned error code :1:: :2:

| Text | ActiveX control returned error code: |
|-------|--|
| Expl. | The ActiveX control returned an error with the indicated number and text. |
| | Please consult the documentation of the ActiveX control to find out under which conditions this error code is returned. |

NAT4760: Redefinition of handle or dynamic variables not allowed.

| Text | Redefinition of handle or dynamic variables not allowed. |
|-------|--|
| Expl. | A variable of type HANDLE or a DYNAMIC variable must not be redefined; and the result of a redefinition must not be a HANDLE or DYNAMIC variable either. |
| Actn. | Correct the variable definition. |

NAT4761: Requested action not available in current context.

| Text | Requested action not available in current context. |
|-------|--|
| - | The availability of the requested action depends upon the current state of the specified object (if any) and/or the current program state. In the current state, it is not possible to perform the requested action. |
| Actn. | Check program and ensure that request is only made in valid contexts. |

NAT4800: Enter valid function code.

| | Enter valid function code. |
|-------|----------------------------|
| Actn. | Enter valid function code. |

91 Natural System Error Messages 4801-4850

NAT4801: Function only applicable to source programs.

| Text | Function only applicable to source programs. |
|-------|---|
| - | The selected function can only be used with source programs, not object programs. |
| Actn. | Enter valid function. |

NAT4802: Library type must be "S" or "O".

| Text | Library type must be "S" or "O". | |
|-----------------------------------|---|--|
| Expl. | Expl. Valid library types are "S" for source and "O" for obje | |
| Actn. Enter a valid library type. | | |

NAT4803: Invalid object specified.

| Text | Invalid object specified. |
|-------|---|
| | Only the following object codes are valid: A - Programs, maps, and data areas, V - Natural views (DDMs), P - Editor, map, and device profiles, E - User and system error message texts. See the Natural documentation for details. |
| Actn. | Enter a valid code. |

NAT4804: Enter valid library ID.

| Text | Enter valid library ID. | |
|-------|---|--|
| Expl. | A valid library ID must be entered for the functions LIST, COPY, MOVE, or DELETE. | |
| Actn. | Enter valid library ID. | |

NAT4805: Enter valid command code.

| Text | Enter valid command code. |
|-------|--|
| Expl. | Valid command codes are: P Select individual program * Selection menu ? Help information . Terminate " " Return to menu |
| Actn. | Enter valid command code. |

NAT4806: Enter program name.

| Text | Enter program name. |
|-------|--|
| · · | If individual programs are specified with command "P", a valid program name must be entered. |
| Actn. | Enter valid program name. |

NAT4807: Enter a valid database ID.

| Text | Enter a valid database ID. |
|-------|--|
| Expl. | A valid database identification must be specified for the SYSMAIN functions. Database numbers allowed are: 0 for default database. 1-253 for specific database. |
| Actn. | Enter valid database number. |

NAT4808: Invalid "new name" specified.

| Text | Invalid "new name" specified. |
|-------|--|
| | When specifying names for libraries (applications) and/or programs, data areas and maps, the names must conform to Natural naming conventions. |
| Actn. | Check and correct the name(s) of the object or library specified. |

NAT4809: Enter a system file number.

| Text | Enter a system file number. |
|-------|---|
| | A valid system file number in the range from 1 to 255 must be in MOVE and COPY commands. |
| Actn. | Enter a valid system file number. |

NAT4810: All data rejected by these selection criteria.

| Text | All data rejected by these selection criteria. |
|-------|---|
| Expl. | All data initially selected for processing have been rejected. |
| | Rejection can occur for a number of reasons; for example: |
| | 1) Object type did not match the object type specified. |
| | 2) Date was not within the specified date range. |
| | 3) A subroutine could not be processed because the internal |
| | subroutine name already existed for another object. |
| | 4) The object could not be copied/moved/renamed because the |
| | REPLACE option was set to "NO" and the object already |
| | existed in the target library. |
| | 5) The RECAT option is "ON" and a cataloged object may only be |
| | processed if the saved object exists. |
| | 6) The RECAT option is "ON" and a saved object may not be processed |
| | separately from an already existing cataloged object. |
| Actn. | Normal termination, but you should verify the selection criteria |
| | specified. |

NAT4811: "Copy/move" to same environment is not allowed.

| Text | "Copy/move" to same environment is not allowed. |
|-------|---|
| Expl. | The COPY and MOVE functions must always have different source and target environments (i.e. different DBID/FNR specifications and/or different library specifications). For error texts, application, DBID, file number and file name (FCT) may be the same for source and target environment if the language code is different. |
| Actn. | Enter different target library or different system file. |

NAT4812: Internal error.

| Text | Internal error. |
|-------|---|
| Expl. | An internal error has occurred while processing name lists. |
| Actn. | Note error and contact Software AG. |

NAT4813: "Move/copy" operation executed.

| Text | "Move/copy" operation executed. |
|-------|--|
| Expl. | The requested MOVE/COPY function has been successfully executed. |
| Actn. | No action required. |

NAT4814: Invalid object type(s) specified.

| Text | Invalid object type(s) specified. |
|-------|---|
| Expl. | One or more of the object types requested are not valid. The object type varies with the function requested. When processing programs, data areas or maps, valid object type codes are: S, N, P, G, L, A, H, C, M, T, Z When processing profiles, valid object type codes are: E, M, D, P When processing error messages, valid object type codes are: S, L The object type code "*" indicates all types. |
| Actn. | Check the code(s) and correct the error. |

NAT4815: Processing terminated at user"s request.

| Text | Processing terminated at user"s request. |
|-------|---|
| | During processing of a function, you have interrupted the processing (for example, by pressing a PF-key or "Program Interrupt/Test Request" key, or by tying a "." on the previous screen). |
| Actn. | Normal termination has occurred. No action required. |

NAT4816: Invalid date or time specified.

| Text | Invalid date or time specified. |
|-------|--|
| Expl. | The date or time specified is not correct. The date format must coincide with the format specified with the Natural profile parameter DTFORM (as described in the Natural documentation). The month range must be from 1 to 12, and the day must correspond with the month (including leap years). The time format must be HH:II. |

| Actn. | Make sure that you specify date and time in the correct format |
|-------|--|
| | and range. |

NAT4817: Date range is out of sequence. TO DATE must be > FM DATE.

| Text | Date range is out of sequence. TO DATE must be > FM DATE. |
|-------|--|
| Expl. | A FROM date cannot be logically greater than a TO date. |
| Actn. | Check the dates and specify the FROM - TO range correctly. |

NAT4818: Library has been successfully listed.

| Text | Library has been successfully listed. |
|-------|--|
| 1 1 | A request to list a specific library was made. This message will appear at the end of that request if normal termination has occurred. |
| Actn. | No action required. |

NAT4819: Invalid selection code specified.

| Text | Invalid selection code specified. |
|-------|---|
| Expl. | One or more codes specified on the selection screen are not correct. The valid codes are: I - Directory info (cataloged and/or saved objects) L - List source (saved objects only) H - Print source (saved objects only) C - Perform specified function on cataloged object only S - Perform specified function of object source only A - Perform specified function on both cataloged and/or saved objects. This code may also be used if only the saved or cataloged object exists. If the profile parameter RECAT is set to "ON", code "C" is also invalid. |
| Actn. | Check selections and correct the error(s) highlighted. |

NAT4820: Selected program does not exist.

| Text | Selected program does not exist. |
|-------|---|
| Expl. | The selected program does not exist in the library specified. |
| Actn. | Check program name and library name. |

NAT4821: Invalid request with dynamic recatalog.

| Text | Invalid request with dynamic recatalog. |
|-------|--|
| Expl. | A request has been made which is not valid in an environment where the parameter RECAT is set to "ON". In an environment with active dynamic recataloging, cataloged and saved objects must be processed together. The only exception is if the saved object exists without a corresponding cataloged object, for example copycode. |
| Actn. | Check the selected request and correct the error. |

NAT4822: Invalid "rename" request.

| Text | Invalid "rename" request. |
|-------|---|
| Expl. | The requested RENAME function cannot be performed with the selection criteria specified. The Selection List, Object Name and/or New Name are not compatible with one another. In batch mode, this may occur when the range notation is used with the Object Name. |
| Actn. | Check the selection criteria and correct the error. If necessary, contact your Natural administrator. |

NAT4823: Invalid selection code specified for option.

| Text | Invalid selection code specified for option. |
|-------|--|
| Expl. | In SYSMAIN, the Library Selection screen allows you to specify the following additional options during processing: L - List all objects in a library S - List all external subroutine names in a library ? - Help Terminate the current processing. |
| Actn. | Check the selection(s) made and correct the error. |

NAT4824: Requested option(s) processed successfully.

| Text | Requested option(s) processed successfully. |
|-------|---|
| Expl. | During the normal processing of a SYSMAIN function, you may perform several options, for example: - listing directory information; - listing all subroutines, by name, in a library; - listing a specific saved object. The processing of the requested option(s) was finished successfully. |
| Actn. | No action required. |

NAT4825: Input command string too long.

| Text | Input command string too long. |
|------|--|
| | When invoking SYSMAIN with a direct command (either in batch or online), the maximum number of elements that may be passed in a single command string is 36. If SYSMAIN detects a number greater than this, processing is terminated. |
| | Review the command string specified to SYSMAIN and reduce the number of elements in the string. |

NAT4826: Data not numeric.

| Text | Data not numeric. |
|-------|--|
| | While processing the data for the DBID, FNR or SETNO parameters of the SYSMAIN command line, the data were found to be non-numeric. Values for DBID, FNR and SETNO must be in the following format: FNR n DBID n SETNO n where "n" is a 1- to 3-digit numeric value (1 to 2 digits for SETNO). |
| Actn. | Check the command line, and correct the data string specified. |

NAT4827: XREF indicator must be "N", "Y", "F" or "S".

| Text | XREF indicator must be "N", "Y", "F" or "S". |
|-------|---|
| Expl. | With Predict, the cross-reference indicator may be set to one of the following values: N - No (delete XREF information if object is deleted) Y - Yes (maintain all XREF information) F - Force (verify Predict entry for program and maintain all XREF information) S - Special (XREF information is processed if existent, but existence of XREF data is no selection criterion) Under Natural Security, the XREF indicator may be changed only to a "higher" setting: for example, if it is "Y", you may change it to "F", but not to "N". |
| Actn. | Check the field concerned and enter correct value. |

NAT4828: Invalid "copy/move/rename" of a subroutine.

| Text | Invalid "copy/move/rename" of a subroutine. |
|-------|--|
| | The subroutine name being copied/moved/renamed already exists in the target library assigned. The function is illegal, because duplicate subroutine names may not exist in a library for cataloged objects. |
| Actn. | Check the object(s) concerned and correct the error(s). |

NAT4829: Invalid function requested.

| Text | Invalid function requested. |
|-------|---|
| - | The function requested is either invalid or has not yet been implemented. |
| Actn. | Check function requested and correct the error. |

NAT4830: "Scan" and "replace" values must be different.

| Text | "Scan" and "replace" values must be different. |
|-------|---|
| - | The SCAN VALUE and REPLACE VALUE fields contain the same values or character strings. |
| Actn. | Change either the SCAN VALUE or the REPLACE VALUE field so that they do not contain the same value. |

NAT4831: "Replace" must not be used with specified object type.

| Text | "Replace" must not be used with specified object type. |
|-------|---|
| Expl. | Natural uses a number of different object types for various different facilities and functions. Certain object types may not be specified when using the REPLACE option of SCAN, because the impact of doing the REPLACE may have serious implications on the activity of the Natural environment. The object types which may NOT be specified with the REPLACE option are G (Global Data), L (Local Data), A (Parameter Data) and M (Maps). When scanning an entire library. the above object types will be listed only, but not edited; however, you may issue an E or EDT command within SCAN to edit the object. |
| Actn. | Remove any values for the REPLACE VALUE field, set NULL REPLACE to "N", or specify a different object type. |

| Text | A "?" may not be requested for object type (batch only). |
|------|---|
| | A "?" may only be specified for the Object Type field of the SCAN utility in a TP environment, not in a batch environment. |
| 1 | Determine the correct setting of the Object Type parameter before using the SCAN utility in batch mode. |

NAT4832: A "?" may not be requested for object type (batch only).

NAT4833: Enter a valid object type.

| Text | Enter a valid object type. |
|-------|--|
| Expl. | The code specified for the object type was not valid. The valid values |
| | are: |
| | A, C, G, H, L, M, N, P, S, *, ?, blank |
| | A "?" will allow you to select a valid code from a list. |
| | A "*" or " " (blank) will result in all object types being scanned in |
| | a library. |
| | For additional information, see the Natural documentation, |
| | use the help function of SCAN, or ask your Natural administrator. |
| Actn. | Enter a valid object type. |

NAT4834: Enter a valid function code.

| Text | Enter a valid function code. |
|-------|--|
| Expl. | An incorrect function code was entered. Valid function codes are: "S", "." and "?". |
| Actn. | Correct the function code and continue. |

NAT4835: Library may not be blank.

| Text | Library may not be blank. |
|-------|---|
| 1 1 | SCAN will scan only one library at a time. Therefore, a valid library |
| | name - or application name (Natural Security) - must be specified. |
| Actn. | Specify a valid library/application name. |

NAT4836: Internal error with "edit": 0000 - contact DBA.

| Text | Internal error with "edit": 0000 - contact DBA. |
|-------|--|
| | SCAN must edit an object before a SCAN/REPLACE is done. If any error is received while editing an object, SCAN will terminate with an error - ERROR: 0000. |
| Actn. | Contact your database administrator. |

NAT4837: Internal error with "scan": 0000 - contact DBA.

| Text | Internal error with "scan": 0000 - contact DBA. |
|-------|--|
| | While SCAN was scanning an object, an error was detected. SCAN will terminate with an error - ERROR: 0000. |
| Actn. | Contact your database administrator. |

NAT4838: Enter new name for "rename" function.

| Text | Enter new name for "rename" function. |
|-------|--|
| Expl. | The RENAME function requires that a new program name be specified. |
| Actn. | Enter new program name. |

NAT4839: Specified library is protected by security definition.

| Text | Specified library is protected by security definition. |
|-------|---|
| | You have attempted to do a SCAN/REPLACE on a library/application whose Natural Security profile does not allow this function. |
| Actn. | Contact your Natural Security administrator. |

NAT4840: Enter a valid command (? blank E EDT I L LET LIST Q .).

Text Enter a valid command (? blank E EDT I L LET LIST Q .).

| Expl. | Valid commands are: |
|-------|--|
| | Q or . Interrupt SCAN/REPLACE processing and return to the menu. |
| | E Invoke the full screen editor to edit an object. |
| | EDT Invoke the line editor to edit an object. |
| | I Ignore processing of the current object and continue with |
| | the next object. Do not save any modifications made. |
| | L or LIST List the object currently being scanned/replaced. |
| | LET Ignore all editing modifications made after ENTER was last |
| | pressed. |
| | blank Continue with normal processing. |
| | ? or PF1 Invoke SCAN"s help facility. |
| | PF2 Interrupt SCAN/REPLACE processing. Return to the menu. |
| | PF3 Interrupt SCAN/REPLACE processing. Return to last function. |
| Actn. | Enter a valid command or press a valid PF key. |

NAT4841: "Scan/replace" terminated by user action.

| Text | "Scan/replace" terminated by user action. |
|-------|--|
| | You have requested the termination of SCAN and are returned to the menu. The SCAN/REPLACE will not be completed; however, all modifications made before termination was requested, will be saved. |
| Actn. | No action required. |

NAT4842: "Scan/replace" interrupted by user action.

| Text | "Scan/replace" interrupted by user action. |
|-------|--|
| Expl. | You have terminated the SCAN/REPLACE operation. Any modifications performed on the object currently being processed will be lost. You will be returned to the menu. |
| Actn. | No action required, as termination was done at your request. |

NAT4843: "Scan/replace" has successfully terminated.

| Text | "Scan/replace" has successfully terminated. |
|-------|---|
| | The selection criteria specified for the SCAN/REPLACE operation have been processed successfully. Processing terminated normally; you will be returned to the menu. |
| Actn. | No action required. |

NAT4844: Scan value must not be blank.

| Text | Scan value must not be blank. |
|-------|---|
| | The SCAN operation cannot be executed without a value or character string being specified for the SCAN VALUE field. |
| Actn. | Enter a value or character string in the SCAN VALUE field. |

NAT4845: Error NATnnnn received during process of object <object>.

| Text | Error NATnnnn received during process of object <object>.</object> |
|-------|---|
| Expl. | If SCAN receives a Natural error code while scanning or replacing a specific object, this message will be returned with the specific Natural error code and the name of the object being processed when the error occurred. Examples of this type of error are: NAT0082 - The object selected was purged before it could be scanned. NAT3148 - The database was terminated during the scan process. |
| Actn. | Enter "? nnnn" for an explanation of error message NATnnnn. If necessary, contact your database administrator for additional information. |

NAT4846: "Replace" operation protected by security definition.

| Text | "Replace" operation protected by security definition. |
|-------|--|
| Expl. | To execute the REPLACE operation in a Natural Security environment, the following Natural commands must be allowed in the appropriate user/application profile: READ, SAVE (and either EDIT or EDT). |
| Actn. | Contact your Natural Security administrator and review the security profile which is in effect during the execution of SCAN. |

NAT4847: Object type is protected by security definition.

| Text | Object type is protected by security definition. |
|-------|--|
| Expl. | Natural has a number of different object types for use with the various Natural facilities and functions; for example, "P" for programs "N" for subprograms, "G" for global data areas, etc. If a specific object type is entered for the SCAN function, SCAN will verify whether you have access to that object type by checking your security definition. |
| Actn. | Contact your Natural Security administrator to review the Natural Security profile in effect during the SCAN processing. |

NAT4848: Status of programs/modules displayed successfully.

| Text | Status of programs/modules displayed successfully. |
|-------|---|
| - | Status information on programs/modules in the user"s library which meet the specified search criteria, has been successfully displayed. |
| Actn. | No action required. |

NAT4849: Invalid date specification.

| Text | Invalid date specification. |
|-------|---|
| | The date was incorrectly entered. A data must be entered in the form for international date (YY-MM-DD). |
| Actn. | Enter correct date in correct form. |

NAT4850: Invalid range specification.

| Text | Invalid range specification. |
|-------|--|
| | The range for a search criterion was specified incorrectly. The start value must be less than or equal to the end value. |
| Actn. | Correct error. |

92 Natural System Error Messages 4851-4900

NAT4851: No program/module with specified criteria found.

| Text | No program/module with specified criteria found. |
|-------|--|
| Expl. | No program/module in the user"s library meets the specified search criteria. |
| Actn. | Check data and specify search criteria more precisely. |

NAT4852: Function disallowed by security definition.

| Text | Function disallowed by security definition. |
|-------|---|
| | The desired function is disallowed by the Natural Security application profile. |
| Actn. | Contact your Natural Security administrator. |

NAT4853: No module found in library.

| Text | No module found in library. |
|------------|--|
| 1 1 | While executing the SIZE command, no module which meets the search criteria was found. |
| Actn. | Check module name. |

NAT4854: "Size" operation protected by security definition.

| Text | "Size" operation protected by security definition. |
|-------|--|
| 1 1 | To execute the SIZE command in a Natural Security environment, you must be allowed to use the command EXECUTE. |
| Actn. | Contact your Natural Security administrator. |

NAT4855: No objects found for specified "scan" criteria.

| Text | No objects found for specified "scan" criteria. |
|-------|--|
| | SCAN will do processing only according to the criteria specified. Only the objects which satisfy the specifications will be displayed, otherwise SCAN will return to the menu. |
| Actn. | No action required, since SCAN has terminated normally. |

NAT4856: Invalid field combination with "rename" function.

| Text | Invalid field combination with "rename" function. |
|-------|--|
| Expl. | When you use the "rename" function of SYSMAIN and have entered a specific name in the Object Name field, you must also enter a New Name. Alternatively, the range notation using a "?", "<", ">" or "*" may be used; in which case no New Name is to be specified. |
| Actn. | Check values specified and correct error. |

NAT4857: File type is not valid for specified file.

| Text | File type is not valid for specified file. |
|-------|---|
| Expl. | With SYSMAIN, only specific file types are supported. The file type is determined by the DBID and FILE number specified for the source and target files. For valid file types, see the relevant Natural documentation. |
| Actn. | Check the DBID and FILE number specified and correct them. |

NAT4858: Access to library is not allowed.

| Text | Access to library is not allowed. |
|-------|---|
| Expl. | When you use the SYSMAIN utility under Natural Security, you are not allowed to access a "private library" of another user. Only access to your own (private) library is possible. This error occurs: - if you perform the LIST/FIND function and attempt to select a private library; or, - if you perform the COPY/MOVE/DELETE/RENAME function and have specified a private library as source/target library. |

Actn. Use only libraries which you are allowed to use.

NAT4859: New "rename" data must be different.

| Text | New "rename" data must be different. |
|-------|--|
| Expl. | When using the RENAME function of SYSMAIN, the new data of the object (saved or cataloged), profile or view must be different from the old data. |
| Actn. | Correct error. |

NAT4860: Enter either a valid function code or a command.

| Text | Enter either a valid function code or a command. |
|-------|--|
| - | Either a valid function code or a command must be entered in the appropriate fields. |
| Actn. | Enter either a valid function code or a valid command. |

NAT4861: Enter a valid library name.

| Text | Enter a valid library name. |
|-------|---|
| Expl. | A library name must be specified. |
| Actn. | Check the library name specified and correct the error. |

NAT4862: Invalid character in library name.

| Text | Invalid character in library name. |
|-------|---|
| | A valid library name must be specified. An asterisk (*) or a question mark (?) indicating a range of values is not permitted. |
| Actn. | Enter a valid library name. |

NAT4863: Database identification must be 0 - 253.

| Text | Database identification must be 0 - 253. |
|-------|---|
| | A valid database identification (DBID) must be specified. Valid DBIDs are: 0 - default database 1 - 253 - specific database. |
| Actn. | Enter a valid database identification. |

NAT4864: File number must be 1 - 255.

| Text | File number must be 1 - 255. |
|-------|--|
| Expl. | A valid system file number in the range from 1 to 255 must be specified. |
| Actn. | Enter a valid file number. |

NAT4865: Invalid type of Natural system file.

| Text | Invalid type of Natural system file. |
|-------|--|
| | An invalid value for system-file identification was entered. Possible values are: A - Adabas system file, V - VSAM system file. |
| Actn. | Enter "A" or "V" as type of system file. |

NAT4866: Invalid name specified for file.

| Text | Invalid name specified for file. |
|-------|--|
| Expl. | If the Natural system file is not an Adabas file, the name of the system file being accessed must be specified. This applies to the following system file types: V - VSAM 2 - DB2 U - USER D - DL/I S - SESAM |
| Actn. | Enter a value for the "Name" field. |

NAT4867: Nothing found for this request.

| Text | Nothing found for this request. |
|-------|---|
| - | Either no data meet the specified selection criteria, or you did not request any processing to be done from the selection screen. This is a normal termination message. |
| Actn. | No action required. |

NAT4868: Function completed successfully.

| Text | Function completed successfully. |
|-------|---|
| 1 1 | The function has successfully terminated, and all data selected have been processed normally. |
| Actn. | No action required. |

NAT4869: Not all module(s)/program(s) were processed.

| Text | Not all module(s)/program(s) were processed. |
|-------|--|
| | The function was not executed for all specified module(s)/program(s). Either the module specified in the selection menu was deleted in the meantime by another user, or the module(s)/program(s) could not be overwritten because the REPLACE option was set to "NO". |
| Actn. | Correct error. |

NAT4870: Syntax error in command line.

| Text | Syntax error in command line. |
|-------|---|
| Expl. | A syntax error was detected when evaluating the command line during |
| | command processing: the command to be processed was not a valid command |
| | Either you have entered a command which does not exist, or you have |
| | specified a command incorrectly (e.g. wrong sequence of parameters). |
| | The actual command being processed may be indicated in parentheses |
| | at the end of the error message. |
| Actn. | Check the command line and correct the error. |

NAT4871: Invalid object name specified.

| Text | Invalid object name specified. |
|-------|--|
| | A valid name must be entered in the field "Object Name" before processing can continue. |
| Actn. | Check data and correct error. |

NAT4872: No XREF information found for object.

| Text | No XREF information found for object. |
|------|--|
| | The XREF indicator is set to either "Y" or "F", but the specified Predict (FDIC) file contains no XREF information for the object being processed. |
| | Check the FDIC file specified, the XREF indicator, and the status of the XREF information for the object in error. |

NAT4873: Libraries listed successfully.

| Text | Libraries listed successfully. |
|-------|--|
| Expl. | The libraries satisfying the specified search criteria were listed successfully. |
| Actn. | No action required. |

NAT4874: Selected number out of range.

| Text | Selected number out of range. |
|-------|---|
| Expl. | Only numbers displayed on the selection menu may be selected. |
| Actn. | Enter a valid number. |

NAT4875: Program does not exist.

| Text | Program does not exist. |
|-------|--|
| Expl. | No program exists for the selected number. |
| Actn. | Select another number. |

NAT4876: No libraries found.

| Text | No libraries found. |
|------------------|---|
| Expl. No library | No library was found which meets the search criteria. |
| Actn. | Verify search criteria. |

NAT4877: Program listed successfully.

| Text | Program listed successfully. |
|-------|--|
| Expl. | The Natural program was listed successfully. |
| Actn. | No action required. |

NAT4878: Function not allowed by security definition.

| Text | Function not allowed by security definition. |
|-------|--|
| Expl. | To execute the desired function in a Natural Security environment, the library to be processed must be either your "private library", a public library, or a people-protected library of which you are an "owner" (if co-owners exist, the required countersignatures must be obtained). Moreover, the use of the corresponding Natural commands - SAVE, CATALOG, STOW, SCRATCH, PURGE, UNCATALOG - must be allowed in that library. |

| Actn. | Do not use this function; |
|-------|---|
| | or contact your Natural Security administrator. |

NAT4879: Range not permitted in batch processing.

| Text | Range not permitted in batch processing. |
|-------|---|
| - | When using the RENAME function of the utility SYSMAIN via a direct command in batch mode, a range of modules/programs must not be specified with the "*" or "?" notation. |
| Actn. | Do not use "*" or "?" notation in batch mode. |

NAT4880: Enter valid command, or enter "?" for help.

| Text | Enter valid command, or enter "?" for help. |
|-------|--|
| | An invalid command was entered. For a list of valid command, you may enter a "?". |
| Actn. | Enter a valid command, or enter a "?" for help. |

NAT4881: Buffer pool maintenance failed.

| Text | Buffer pool maintenance failed. |
|-------|--|
| | The Natural buffer pool maintenance failed, because the Natural buffer pool is either not installed or has been disabled after an ABEND. |
| Actn. | Contact your Natural administrator. |

NAT4882: Buffer pool maintenance performed.

| Text | Buffer pool maintenance performed. |
|-------|---|
| Expl. | Maintenance of the Natural buffer pool was performed. |
| Actn. | No action required. |

NAT4883: TP user ID required.

| Text | TP user ID required. |
|-------|---------------------------|
| Actn. | Enter a valid TP user ID. |

NAT4884: Invalid database ID.

| Text | Invalid database ID. |
|-------|---|
| Expl. | A database identification in the range 0 - 255 must be entered. |
| Actn. | Enter a valid database identification. |

NAT4885: Invalid file number.

| | Text | Invalid file number. |
|---|-------|---|
| E | Expl. | A file number in the range from 0 to 255 must be entered. |
| | Actn. | Enter a valid file number. |

NAT4886: Please enter a valid library name.

| Text | Please enter a valid library name. |
|-------|---|
| Expl. | A valid name for a Natural library must be entered. |
| Actn. | Enter a valid library name. |

NAT4887: Please enter a valid module name.

| Text | Please enter a valid module name. |
|-------|--|
| Expl. | A valid name for a Natural module must be entered. |
| Actn. | Enter a valid module name. |

NAT4888: Currently no logical files available.

| Text | Currently no logical files available. |
|-------|--|
| | The utility makes use of "logical files" to perform any required processing. If all logical files are in use, processing is terminated abnormally. SYSPROF may be used to display the current file settings. |
| Actn. | Contact your database administrator for additional help. |

NAT4889: Library is not defined to Natural Security.

| Text | Library is not defined to Natural Security. |
|-------|--|
| Expl. | You have requested access to a library which is not defined to Natural Security. In the case of SYSMAIN, this may occur when you are maintaining libraries which are defined to another security environment. If you wish to do maintenance across security environments, you should use the SYSMAIN command "CMD FSEC". For further information, see the Natural documentation. |

Actn. Check the selection criteria and correct the error.

NAT4890: Invalid owner/co-owner confirmation.

| Text | Invalid owner/co-owner confirmation. |
|------|---|
| | The countersignature specified for an owner-protected application must be valid for a co-owner to use an application; or the user is NOT an owner of the application. |
| | Specify the correct countersignature for the security environment being accessed. |

NAT4891: Invalid DBID and/or FNR specified for a library.

| Text | Invalid DBID and/or FNR specified for a library. |
|-------|---|
| Expl. | The DBID and FNR specified for a library protected by Natural Security must correspond to the DBID and FNR specified in the security profile for the library. |
| Actn. | Either correct the DBID/FNR, or change the FSEC definition using the "CMD FSEC" command. |

NAT4892: Invalid Predict file(s) defined.

| Text | Invalid Predict file(s) defined. |
|-------|--|
| Expl. | The FDIC parameter is pointing to a database and/or file which is not a valid file for Predict. This causes an error during the deletion of XREF data. - If the FDIC parameter is correct, you should verify the settings of the SYSMAIN FDIC database(s) and/or file(s), since these will override the session FDIC parameter. Note that with XREF support the Predict version must be 2.3 or above. - If the XREF parameter is set to "N", no check will be done online. In batch, the nucleus should not have the XREF module linked. |
| Actn. | Check the current settings of the Natural parameter FDIC and the SYSMAIN FDIC parameters, and correct the error. |

NAT4893: Normal completion, but some data were rejected.

Text Normal completion, but some data were rejected.

| Expl. | During processing of a function which does not result in the display of |
|-------|---|
| | a selection screen, processing continues even if objects are rejected. |
| | There are numerous reasons why objects are rejected, and these are |
| | listed under error NAT4810. If you wish to monitor the status of each |
| | each object as it is processed, use the selection screen |
| | (using the "?" option). |
| | This is a normal end-of-processing message. |
| Actn. | No action required. |

NAT4894: Invalid error number specified.

| Text | Invalid error number specified. |
|-------|---|
| Expl. | The FROM error number has been specified incorrectly: either no range notation has been specified, the FROM number is greater than the TO number, or the range notation is invalid. In batch, this error may also occur if any of the specified error numbers (ERROR FM, ERROR TO, NEW ERROR FM, NEW ERROR TO) are not numeric. Valid specifications of numeric numbers are: 1 or 01 or 001 or 0001 |
| Actn. | Check the error number specifications, and correct the error. |

NAT4895: Invalid language code specified.

| Text | Invalid language code specified. |
|-------|--|
| | The language code specified is invalid. See the Natural documentation for further information on language codes. |
| Actn. | Enter a valid language code. |

NAT4896: Invalid processing request for extended error message.

| Text | Invalid processing request for extended error message. |
|-------|--|
| Expl. | When moving, copying or renaming an extended error message, there must always be a corresponding short error message. If there is no short error message in the source environment, the extended error message will not be processed. If there is not short message in the target environment, this error message will be output. Processing of both, short and extended messages, together is valid. |
| Actn. | Correct error. |

NAT4897: Invalid error application specified.

| Text | Invalid error application specified. |
|-------|---|
| | The specified error application is invalid for the requested function. It may be a non-existent application, or you have tried to move, copy |
| | or rename a user error message to a system error message. Deletion of a system error message has been disallowed. The message may, however, be moved, copied, or renamed. |
| Actn. | Check the application indicated, and correct the error. |

NAT4898: Invalid error number specified with "rename".

| Text | Invalid error number specified with "rename". |
|-------|---|
| Expl. | When renaming (renumbering) error messages, all error number specifications (ERROR FM, ERROR TO, NEW ERROR FM, NEW ERROR TO) must be numeric and follow the rules listed below: 1) The numbers must be in the correct combination as follows: A) only ERROR FM. B) ERROR FM and ERROR TO. C) ERROR FM and NEW ERROR FM. D) ERROR FM, ERROR TO, NEW ERROR FM and NEW ERROR TO. 2) If the range notation is used, the NEW ERROR FM must be by at least 2 higher than the ERROR FM. 3) If the range notation is used, the difference between ERROR FM and NEW ERROR TO. |
| Actn. | Correct the error. |

NAT4899: This feature is not implemented for VSAM system file.

| Text | This feature is not implemented for VSAM system file. |
|-------|--|
| | To use this feature, a Natural system file is required that is contained within an Adabas database. |
| Actn. | Select another feature. |

NAT4900: Too many names specified.

| Text | Too many names specified. |
|-------|--|
| - | For the commands UNCATALOG, PURGE and SCRATCH, a list of up to 40 names of Natural modules/programs may be entered for deletion. |
| Actn. | Reduce number of names. |

93 Natural System Error Messages 4901-4950

NAT4901: Invalid data for batch environment.

| Text | Invalid data for batch environment. |
|-------|--|
| | In a batch environment, the input for an UNCATALOG/PURGE/SCRATCH command can only consist of a list of names for Natural modules/programs. At least 1 name must be entered. A maximum of 40 names can be entered. Asterisk notation is not permitted. |
| Actn. | Enter one or more valid names. |

NAT4902: Only one generic key permitted.

| Text | Only one generic key permitted. |
|-------|---|
| Expl. | Only one generic key is permitted per invocation of the UNCAT/PURGE/ SCRATCH command. A generic key is a character string, which may be empty, truncated by an asterisk. The use of a generic key results in the display of a menu which contains all modules/programs starting with the character string. These modules/programs may be marked for further processing. |
| Actn. | Enter valid data. |

NAT4903: Do not use both, list of names and asterisk notation.

| Text | Do not use both, list of names and asterisk notation. |
|-------|---|
| | For the UNCATALOG/PURGE/SCRATCH commands, you can either enter a list |
| | of Natural module/program names or use asterisk notation, but not both. |
| Actn. | Correct error. |

NAT4904: No module(s)/program(s) found in current library.

| Text | No module(s)/program(s) found in current library. |
|-------|--|
| Expl. | No module/program was found which meets the search criteria. |
| Actn. | Make sure that the correct search criteria were used. |

NAT4905: New error range may not overlap the current error range.

| Text | New error range may not overlap the current error range. |
|-------|---|
| Expl. | When renumbering (renaming) ranges of errors, overlaps of ranges are not permitted within the same application (for reasons of data integrity). The NEW ERROR FROM must be smaller than the original ERROR FROM or greater than the original ERROR TO. Example: When renumbering errors 10 to 20 as 13 to 23; number 10 would be moved to 13, but 13 would be moved to 17, and 17 would be moved to 20, etc.; thus, error number 10 would be duplicated. If the NEW ERROR FROM were smaller than 10 or greater than 20, this . would not occur. If you cannot avoid overlapping with the ranges of numbers available to you, renumber the errors to a dummy application and then from the dummy application to the original application. |
| Actn. | Check the error numbers and the application, and correct the error. |

NAT4906: User exit was invoked but no longer exists.

| Text | User exit was invoked but no longer exists. |
|-------|--|
| Expl. | At initialization of SYSMAIN, the user exit 1 and/or 2 was active, but during processing the user exit could not be invoked. This may occur if the cataloged object is not cataloged in the SYSMAIN library. |
| Actn. | No action required. SYSMAIN will no longer invoke the user exit which caused the error. |

NAT4907: Predict file invalid for processing of XREF data.

| Text | Predict file invalid for processing of XREF data. |
|-------|--|
| Expl. | When XREF data are processed (XREF parameter set to "Y", "F" or "S"), the Predict (FDIC) file must be a valid file for Predict Version 2.3 or above. (With SYSMAIN, you may use the command "SET FDIC" to override the current Predict file setting.) This error also appears if you are processing sets and the FDIC file is not a valid Predict file. |
| Actn. | Use a valid Predict file, or set the XREF indicator to "N", or set the set number to "0". |

NAT4908: Conflicting or too many types.

| Text | Conflicting or too many types. |
|------|--|
| - | The command DELETE has a TYPE option. The number of types entered in the delete request was too large. This is either because types "X" or "U" where expanded and the resulting list became too large, or because repeated or redundant entries were found. |
| | Repeat the request, either with fewer types or, if the default "*" is suitable, without the TYPE specification. |

NAT4909: Do not enter both, asterisk notation and list of names.

| Text | Do not enter both, asterisk notation and list of names. |
|-------|---|
| Expl. | For the UNCATALOG/PURGE/SCRATCH commands, you can either enter a list |
| | of Natural module/program names or use asterisk notation, but not both. |
| Actn. | Correct error. |

NAT4910: Object is protected by Predict Application Control.

| Text | Object is protected by Predict Application Control. |
|-------|---|
| | You cannot maintain the selected object because it is under the control of Predict Application Control. |
| Actn. | Contact your Predict Application Control administrator. |

NAT4911: Set :1: cannot be found.

| Text | Set cannot be found. |
|-------|--|
| Expl. | The specified set cannot be found. |
| | Make sure that you have specified the correct User, Library, Library DBID/FNR, FDIC DBID/FNR, and Set Number. |

NAT4912: PC Download must be "Y" or "N".

| Text | PC Download must be "Y" or "N". |
|-------|---|
| | When you export/download Natural objects to a PC, this option must be set to either "Y" (export) or "N" (normal processing). |
| Actn. | Specify correct value. |

NAT4913: Work files 6 + 7 must be assigned to PCNEW for download.

| Text | Work files 6 + 7 must be assigned to PCNEW for download. |
|-------|--|
| | When you use the PC Download option, work files 6 and 7 must be assigned to PCNEW. |
| Actn. | Assign work files 6 and 7. |

NAT4914: Library range must not be specified for sets.

| Text | Library range must not be specified for sets. |
|-------|--|
| | When a set is used as source location of objects, you can only specify specific library names, but not a range of libraries. |
| Actn. | Provide correct library specification. |

NAT4915: Unload type must be "A", "C", "S" or "W".

| Text | Unload type must be "A", "C", "S" or "W". |
|-------|---|
| | The unload type must be one of the following: A - all objects (cataloged or saved), C - cataloged objects, S - saved objects, W - stowed objects. |
| Actn. | Specify a correct value. |

NAT4916: Conflicting request.

| Text | Conflicting request. |
|-------|---|
| Expl. | The command DELETE has a TYPE option. If views (DDMs) are to be deleted, you must not specify objects of other types in that (sub-)command. |
| Actn. | Delete DDMs (views) separately. |

NAT4917: When object is specified, library name is also required.

| Text | When object is specified, library name is also required. |
|-------|--|
| Expl. | When you specify an object name for unloading/loading, you must also specify a library name to identify the library in which the specified object is stored. |
| Actn. | Specify library name. |

NAT4919: Compare option must be "S" (short) or "D" (differ).

| Text | Compare option must be "S" (short) or "D" (differ). |
|-------|--|
| Expl. | See the Natural SYSMAIN utility documentation for details. |
| Actn. | Specify correct value. |

NAT4920: Invalid command with a versioned library.

| Text | Invalid command with a versioned library. |
|-------|--|
| - | Once a Natural library or application has been defined as being "versioned", the commands STOW, CATALOG, UNCATALOG, PURGE and SCRATCH must not be used on any programming objects. |
| Actn. | Use the STOWALL or VERSION utility to circumvent the problem. |

NAT4921: Compare only available with Predict Application Control.

| Text | Compare only available with Predict Application Control. |
|-------|--|
| Expl. | SYSMAIN"s Compare option can only be used if Predict Application Control (PAC) is installed. If PAC is installed but Compare still does not work, use the SYSMAIN command "SET FSEC" to specify the FSEC source location where PAC is installed. |
| Actn. | Do not use Compare if PAC is not available; or specify valid FSEC source location before you use Compare. |

94 Natural System Error Messages 4951-5000

NAT4960: Invalid access to Natural system file: return code :1:.

| Text | Invalid access to Natural system file: return code |
|-------|--|
| - | During initialization of the logical file, an error with "return code" occurred. |
| Actn. | Contact your database administrator. |

NAT4961: Logical file initialization failed: return code :1:.

| Text | Logical file initialization failed: return code |
|-------|---|
| | The utility makes use of logical files to perform any required processing. If all the available logical files are in use, processing is abnormally terminated. SYSPROF may be used to analyze the current settings. |
| Actn. | Contact your database administrator for additional help. |

NAT4962: No object to be included specified.

| Text | No object to be included specified. |
|-------|-------------------------------------|
| Actn. | Specify object to be included. |

NAT4963: Invalid "expand-type" specified.

| Text | Invalid "expand-type" specified. |
|-------|--|
| Expl. | Valid "expand-types" are: |
| | P - Programs G - Global data areas |
| | N - Subprograms L - Local data areas |
| | S - External Subroutines A - Parameter data areas |
| | H - Helproutines M - Maps |
| | C - Copycodes E - Error messages |
| | * - All object types |
| | You can either specify a single "expand-type", or several of them in |
| | any sequence without blanks in between. |
| Actn. | Specify correct "expand-type". |

NAT4964: Invalid "include" option specified.

| | Invalid "include" option specified. |
|-------|-------------------------------------|
| Expl. | Specify valid "include" option. |

NAT4965: Object type(s) not correctly specified.

| | Object type(s) not correctly specified. |
|-------|---|
| Actn. | Specify object type(s) correctly. |

NAT4966: Valid map parameters are S, P, I, R.

| | Valid map parameters are S, P, I, R. |
|-------|--------------------------------------|
| Actn. | Specify "S", "P", "I" or "R". |

NAT4967: Specified "expand object" not referenced in listed source.

| Tex | Specified "expand object" not referenced in listed source. |
|-----|---|
| Exp | You have specified an "expand object" to be listed within a listed source; however, the specified expand object is not referenced in the listed source. |
| Act | n. Enter valid command. |

NAT4969: To select object, place cursor over object name.

| Text | To select object, place cursor over object name. |
|-------|--|
| | To display the source of an object that is referenced within the listed source, you must mark the NAME of that object with the cursor. |
| Actn. | Place cursor correctly for object selection. |

NAT4981: Subroutine is internal or not in current library.

| Text | Subroutine is internal or not in current library. |
|-------|--|
| Expl. | The subroutine you have selected to be displayed in ZOOM or EXPAND mode is either an internal subroutine (that is, contained in the source that is being listed) or an external subroutine whose source is not contained in the current library. |
| Actn. | Check if listed source or current library contains desired subroutine. |

NAT4983: Only one object was selected for ZOOM display.

| Text | Only one object was selected for ZOOM display. |
|-------|--|
| Expl. | You have entered "PREV" or "NEXT" (or pressed PF4 or PF5) to move from the object currently displayed in the ZOOM window to the previous or next one. However, you have not used asterisk or wildcard notation for the object name specified with the ZOOM command, which means that only a single object is displayed in the ZOOM window. |
| Actn. | Enter valid command. |

NAT4989: Selected object is not in current library.

| Text | Selected object is not in current library. |
|------|--|
| 1 1 | With the LIST command, you have specified an object whose source is not stored in the current library. |
| | Make sure, you are in the correct library. Or issue LIST command with asterisk/wildcard notation for list of objects in the current library. |

NAT4990: FORMAT command can only be applied to a map/data area.

| Text | FORMAT command can only be applied to a map/data area. |
|-------|--|
| | With the LIST command, you have specified the FORMAT option. This option is only applicable to maps and data areas, but the listed object is not a map or data area. |
| Actn. | Do not use FORMAT for this object. |

NAT4991: Only a stowed data area can be displayed formatted.

| Text | Only a stowed data area can be displayed formatted. |
|-------|--|
| | Only a stowed data area can be displayed formatted as only then is there a guarantee that the data area is syntactically correct - thus permitting formatting. |
| Actn. | Stow data area and retry. |

95 Natural System Error Messages 5201-5250

NAT5234: Invalid ADJUST request.

| | Text | Invalid ADJUST request. |
|---|-------|---|
| ſ | Expl. | The dataset version is not consistent with the Natural version. |

NAT5235: Invalid subroutine name detected during loading.

| Text | Invalid subroutine name detected during loading. |
|------|---|
| | During loading, a subroutine was detected whose external name is already used by another subroutine. |

NAT5236: Load file is empty; there is nothing to be loaded.

Text Load file is empty; there is nothing to be loaded.

NAT5237: Non-zero condition code from user exit at termination.

Text Non-zero condition code from user exit at termination.

NAT5238: Invalid FDIC file for processing of XREF data.

Text Invalid FDIC file for processing of XREF data.

NAT5239: Non-zero error code received during NATLOAD processing.

| Text | Non-zero error code received during NATLOAD processing. |
|-------|--|
| Expl. | This occurs when the NATLOAD error transaction is invoked. |

NAT5240: Error in validation of NATUNLD/NATLOAD command.

| Text | Error in validation of NATUNLD/NATLOAD command. |
|-------|---|
| Expl. | An error occurred during validation of a NATUNLD/NATLOAD command. |
| Actn. | Check and correct command. |

NAT5241: Error while reading PC work file.

| Text | Error while reading PC work file. |
|-------|---|
| Expl. | An error occurred while NATLOAD was reading a load file which was a PC work file. |

NAT5242: Invalid header information or load file format.

| Text | Invalid header information or load file format. |
|-------|--|
| Expl. | Either the header information on the load file is invalid, |
| | or the format of the load file is not consistent with the |
| | NATLOAD version being used. |

NAT5243: Incomplete or inconsistent load file.

| Text | Incomplete or inconsistent load file. |
|------|---|
| | When processing programming objects, either an inconsistency occurred |
| | during the processing of the load file, or the load file is incomplete. |

NAT5244: Load file inconsistency while processing views.

| Text | Load file inconsistency while processing views. |
|-------|---|
| Expl. | While processing views, an inconsistency was detected in the processing of the load file. |

NAT5245: Non-zero condition code; NATLOAD could not continue.

| Text | Non-zero condition code; NATLOAD could not continue. |
|-------|--|
| Expl. | A non-zero condition code was received, and NATLOAD processing could |
| | not continue. |

96 Natural System Error Messages 5251-5300

NAT5251: RECOVER rejected: load file is no Natural Security file.

Text RECOVER rejected: load file is no Natural Security file.

NAT5252: RECOVER rejected; Natural Security is not installed.

Text RECOVER rejected; Natural Security is not installed.

NAT5270: You are not authorized for this load operation.

| Text | You are not authorized for this load operation. |
|-------|---|
| | You are not defined as a member of the group "PAA-AUTH" in Natural Security. This error only occurs with Predict APPLICATION AUDIT. |
| Actn. | Contact your Natural Security administrator. |

NAT5271: Inconsistency when processing File Translation Table.

| Text | Inconsistency when processing File Translation Table. |
|-------|--|
| Expl. | While processing the File Translation Table, an inconsistency occurred |
| | during the processing of the load file. |
| | This error only occurs with Predict Application Control. |

NAT5272: Maximum number of versions reached for an object.

| Text | Maximum number of versions reached for an object. |
|-------|--|
| Expl. | Processing cannot continue, because the maximum number of versions was |
| | reached for a particular object. |
| | This error only occurs with Predict APPLICATION AUDIT. |

97 Natural System Error Messages 5351-5400

NAT5360: Non-zero Adabas response - :1:/:2: (RC=:3:/:4:).

| Text | Non-zero Adabas response/ (RC=/). |
|-------|---|
| Expl. | The Natural/SAP Communication has received a non-zero response from the database. The error may have been caused by one of the following: - A time-out condition has occurred. - An invalid request was made to the database. Additional information about which command received the response code can be obtained by analyzing the contents of the DDM field "ERROR-TEXT". |
| Actn. | Analyze persistent errors using the ERROR-TEXT field. |

NAT5361: Installation error: "ADALNK" is not reentrant.

| Text | Installation error: "ADALNK" is not reentrant. |
|-------|---|
| Expl. | Natural/SAP Communication requires that a reentrant Adabas link module "ADALNK" be used. |
| Actn. | Make the necessary modifications to ADANLK, as described in the source. Assemble and link-edit the module before attempting again. |

NAT5362: Unexpected SDAM response received (RC=:1:).

| Text | Unexpected SDAM response received (RC=). |
|-------|--|
| Expl. | The SDAM interface used by Natural/SAP Communication |
| | has returned a non-zero response. |
| | The response code is located in the DDM field ERROR-TEXT |
| | RC Description |
| | |
| | 01 Error in EXTENT chain. |
| | 02 No RSA provided. |
| | 03 No record found with given RSA. |
| | 07 User area too small. |
| | 08 Compressed field group too long. |
| | 09 Invalid Qmacro. |
| | FE Nothing found for search criterion. |
| Actn. | Check the SAP/Qmacros with which XCOMSAP was compiled. |
| | For further assistance, contact Software AG support. |

NAT5363: No record found with given key or RSA.

| Text | No record found with given key or RSA. |
|-------|--|
| Expl. | No record was found because: 1) a header segment was accessed using the Master-Index field "BMI" with an invalid value, or 2) an internal error occurred when accessing the SAP/Document File with an invalid RSA. |
| Actn. | Check the value of "BMI", when used. Contact Software AG Customer Support for further assistance. |

NAT5364: Logical file ID/segment ID not found in description table.

| Text | Logical file ID/segment ID not found in description table. |
|------|---|
| | An access was made using a logical file number which was not found in the SAP/description tables (XCOMSAP); or the segment ID used internally was not located within the SAP/description tables. |
| | Check for the file number (LFID) in the modules XCOMSAP and XCOMFUNC. Check the version of the SAP Qmacros which were used to assemble XCOMSAP. |

NAT5365: Document-type is invalid for the SAP/table used.

| Text | Document-type is invalid for the SAP/table used. |
|-------|---|
| Expl. | The value used in the FIND/READ statement for the document-type (DDM field "BLTYP") is invalid for this SAP/View. A list of document-types and the associated logical files is provided in the documentation. The document-type is optional and can be omitted. Natural/SAP Communication supplies the document-type when it is not otherwise specified. |
| Actn. | Check the value of the document-type, and where possible avoid using it. |

NAT5366: SAP/document files do not have the same database-ID.

| Text | SAP/document files do not have the same database-ID. |
|-------|--|
| Expl. | The SAP/document files have different database IDs |
| | in the SAP/description table (XCOMSAP). |
| | Natural/SAP requires that the SAP/files: |
| | ABMI - Master Index File |
| | ABIB - Secondary Index File |
| | ABEZ - Document Container File |
| | all have the same database ID. |
| Actn. | Check the SAP/description table for correctness. |

NAT5367: Queuing error: WADS or workarea address not found.

| Text | Queuing error: WADS or workarea address not found. |
|-------|--|
| Expl. | An internal error has occurred. |
| Actn. | Contact Software AG Customer Support for further assistance. |

NAT5368: FB/SB work buffer overflow (:1:/RECAREA).

| Text | FB/SB work buffer overflow (:1:/RECAREA). |
|-------|--|
| Expl. | An internal error has occurred. |
| Actn. | Contact Software AG Customer Support for further assistance. |

NAT5369: GETMAIN storage error - :1:/:2: (RC=:3:)

| Text | GETMAIN storage error/ (RC=) |
|-------|--|
| Expl. | A non-zero response code was received by Natural/SAP Communication when attempting to perform a GETMAIN. This error can only occur when the resources are exhausted. The most common reason for this problem is that the region size is too small for the number of users that are concurrently active. |
| Actn. | Check the region size. Contact Software AG Customer Support for further assistance. |

NAT5370: FREEMAIN storage error - :1:/:2: (RC=:3:)

| Text | FREEMAIN storage error/ (RC=) |
|-------|---|
| | A non-zero response code was received by Natural/SAP Communication while attempting to perform a FREEMAIN. This situation should not occur. Repeated occurrence of this error could lead to a depletion of resources and a GETMAIN error. |
| Actn. | Contact Software AG Customer Support for assistance. |

NAT5371: Invalid value in Master-Index - :1:.

| Text | Invalid value in Master-Index |
|-------|---|
| Expl. | A sub-field of the Master-Index used to access the SAP/Document File contains an invalid value. The range of values for each of the sub-fields is listed below: Sub-Field Field Name Range of Values |
| | Client Number MANDANT 00 to 99 Company Code BUKRS Greater than "00" Document Number BLNR Greater than "00000000" |
| Actn. | Check value of Master-Index used in FIND/READ statement. |

NAT5372: Internal error: Search/value buffer analysis (RC=:1:)

| Text | Internal error: Search/value buffer analysis (RC=:1:) |
|-------|--|
| · · | An internal error occurred when performing the search/value buffer analysis. |
| | This error can occur when insufficient work-area space is available or an invalid numeric value is encountered in the value buffer. |
| Actn. | Consult Software AG Customer Support for further assistance. |

NAT5373: Wildcards and multiple SVB entries are not supported.

| Text | Wildcards or multiple field entries in the Search/Value buffer have been encountered. |
|-------|---|
| · · | The use of wildcards "*" or multiple field entries are not supported by Natural/SAP Communication. |
| Actn. | Check and correct the search criterion used in the FIND statement. |

NAT5374: Invalid OFFSET-Field used in search criterion or overlap.

| | Either an OFFSET field which is not a descriptor has been used a part of the search criterion, or one OFFSET field overlaps another. |
|-------|---|
| | The main data key of the secondary index is often redefined, and thus provides the user with multiple keys with which the data can be accessed. This error occurs when an invalid search criterion has been used; i.e. parts of different keys have been combined in one logical search criterion. The search-buffer analysis determines such errors from the fact that these OFFSET fields overlap. |
| Actn. | Check and correct the search criterion. Consult the SAP/system description for further information. |

NAT5375: Invalid DB-Field used as descriptor.

| Text | A field has been used which is either unknown to the file processor or not inverted. |
|-------|--|
| Expl. | Fields which are not descriptors cannot be used in a search criterion. |
| - | Furthermore, some of the fields in the DDM are file-access dependent. |
| | For example, the field group "MASTER-INDEX" and all fields within |
| | this group can only be used when accessing the SAP/document file. |
| | The use of these fields in a search criterion while accessing the |
| | secondary index (ABIB) will result in such an error. |
| Actn. | Check and correct search criterion. |
| | See the NATSAP Programming Considerations for further information. |

NAT5376: Mandatory field missing.

| Text | Mandatory field missing. |
|-------|---|
| Expl. | The use of some fields in the search criterion |
| | is required. |
| | This is the case for the field CLIENT NUMBER (MANDT). |
| | The section "Programming Considerations" of the Natural/SAP |
| | Communication documentation explains this in more detail. |
| Actn. | Check and correct the search criterion. |
| | See the "Programming Considerations" for further information. |

NAT5377: "Single Value" field used with multiple values.

| Text | "Single Value" field used with multiple values. |
|-------|---|
| Expl. | Some fields cannot be used in the search criterion with multiple values or a range of values. They may only be assigned a "single" value, and, for example, must not be used in the Natural THRU clause. Some examples of such fields are: - CLIENT NUMBER - DOCUMENT TYPE Single-value fields are explained in the "Programming Considerations" in greater detail. |
| Actn. | Check and correct search criterion. See the "Programming Considerations" for further information. |

NAT5378: A composite-key field has been misused.

| Text | A composite-key field has been misused. |
|-------|---|
| Expl. | There are two composite keys in every DDM: "BMI" and "BSI". These fields are used as part of the search criterion or are returned for use in the following FIND/READ loops. The fields, when used, are to be used alone, and cannot be combined with other key fields. These composite fields are file-oriented. - "BMI" can only be used when accessing the document file (ABEZ) - "BSI" can only be used when accessing the secondary index (ABIB) The current master-index value for the record being accessed is always returned in "BMI". |
| Actn. | Check and correct the search criterion See the "Programming Considerations" for further information. |

NAT5379: Internal positioning error has occurred (RC=:1:).

| Text | Internal positioning error has occurred (RC=). |
|-------|---|
| Expl. | An internal error has occurred while attempting to position within a structured document. One of the following errors has occurred: RC Description |
| | x"FB" Mismatching segment ID"s positioning in document. x"FD" Index error while positioning within XCOMSAP. |
| Actn. | Contact Software AG Customer Support for further assistance. |

NAT5380: Dependent segment accessed without reading parent segment

| Text | Dependent segment accessed without reading parent segment |
|-------|---|
| Expl. | The position segments of the documents files AUFK and AUAK are hierarchically structured, e.g. parent-child relationship. Structured documents must be accessed in this parent-child order. You cannot access a lower-level document segment without having first read the next higher-level segment. |
| Actn. | See the SAP documentation for a description of the file structure, and correct the nesting of the FIND/READ statements. |

NAT5381: Order of accessing segments incorrect.

| Text | Order of accessing segments incorrect. |
|-------|---|
| Expl. | The position segments of the document files AUFK and AUAK are hierachically structured, e.g. parent-child relationship. Structured documents must be accessed in this parent-child order. You cannot access a higher-level segment from within a lower-level access loop. The order of access must always be from top to bottom. |
| Actn. | See the SAP documentation for a description of the file structure, and correct the nesting of the FIND/READ statements. |

NAT5382: Invalid length of field group encountered.

| Text | Invalid length of field group encountered. |
|-------|--|
| Expl. | While decompressing a document, a field group with an invalid length attribute was encountered. The length attribute is either zero (0) or greater than 8000. This type of error can occur when the version of the SAP data does not coincide with the version of the QMACROS used for generating the NATSAP description table (XCOMSAP). |
| Actn. | Regenerate XCOMSAP and retry; should the error persist, analyze the document with SAP utilities. |

NAT5399: Recursive entry into error handler.

| Text | The error handler has been entered recursively. |
|-------|--|
| Expl. | This is most likely an internal error |
| | and should be reported to Software AG. |
| Actn. | Consult Software AG Customer Support for further assistance. |

NAT5400: No subclause given in COMPOSE statement.

| Text | No subclause given in COMPOSE statement. |
|-------|--|
| Actn. | Correct error in program. |

98

Natural System Error Messages 5401-5450

NAT5401: Format in MOVING clause must be A, or P/N less or equal 16.

| Text | Format in MOVING clause must be A, or P/N less or equal 16. |
|-------|--|
| Expl. | The format of operand 1 in COMPOSE MOVING clause must either be alphanumeric, packed, or numeric. If the operand is of type alphanumeric with length one, the value should not be "." (period) or "," (comma). If the operand is of type packed or numeric, the total number of digits may not exceed 16. |
| Actn. | Correct error in program. |

NAT5402: TO VARIABLES or TO DATAAREA missing in MOVING clause.

| Text | TO VARIABLES or TO DATAAREA missing in MOVING clause. |
|-------|---|
| Actn. | Correct error in program. |

NAT5403: More than 37 variables/constants in MOVING clause.

| Text | More than 37 variables/constants in MOVING clause. |
|-------|--|
| Actn. | Correct error in program. |

NAT5404: Error in STATUS variable.

| | Error in STATUS variable. |
|-------|---------------------------|
| Actn. | Correct error in program. |

NAT5405: Error in left part of ASSIGNING clause in COMPOSE.

| Text | Error in left part of ASSIGNING clause in COMPOSE. |
|-------|--|
| Actn. | Correct error in program. |

NAT5406: Error in right part of ASSIGNING clause in COMPOSE.

| | TC 1 | Error in right part of ASSIGNING clause in COMPOSE. |
|-----|------|---|
| - 1 | Levt | From in right part of ASSIC-NUNC- clause in COMPUSE |
| | ICAL | |
| - 1 | | 0 1 |

Actn. Correct error in program.

NAT5407: Over 19 variable pairs in ASSIGNING/EXTRACTING clause.

| Text | Over 19 variable pairs in ASSIGNING/EXTRACTING clause. |
|-------|--|
| Actn. | Correct error in program. |

NAT5408: Error in left part of EXTRACTING clause.

| Text | Error in left part of EXTRACTING clause. |
|-------|--|
| Actn. | Correct error in program. |

NAT5409: Error in right part of EXTRACTING clause.

TextError in right part of EXTRACTING clause.Actn.Correct error in program.

NAT5411: No output device for formatted output.

| Text | No output device for formatted output. |
|-------|--|
| Actn. | Correct error in program. |

NAT5412: OUTPUT CALLING variable must be of alphanumeric format.

| Text | OUTPUT CALLING variable must be of alphanumeric format. |
|-------|---|
| Actn. | Correct error in program. |

NAT5413: Subclause in FORMATTING clause may be specified only once.

| Text | Subclause in FORMATTING clause may be specified only once. |
|------------|---|
| 1 1 | All subclauses of the FORMATTING clause may be used in any order, but each subclause may be used only once. |
| Actn. | Correct error in program. |

NAT5414: GIVING operand in OUTPUT subclause must be B4 or B10.

| Text | GIVING operand in OUTPUT subclause must be B4 or B10. |
|-------|---|
| | The format/length of the operand specified after the keyword GIVING in the OUTPUT subclause of a COMPOSE statement must be B4 or B10. See the Natural documentation for details on the COMPOSE statement. |
| Actn. | Correct error in program. |

NAT5415: Error in definition of input destination.

| Text | Error in definition of input destination. |
|-------|---|
| Actn. | Correct error in program. |

NAT5416: Error in definition of input source.

| | Error in definition of input source. |
|-------|--------------------------------------|
| Actn. | Correct error in program. |

NAT5417: The keyword "FROM" is missing.

| Text | The keyword "FROM" is missing. |
|-------|--------------------------------|
| Actn. | Correct error in program. |

NAT5418: Max.number of source definitions in INPUT clause is 9/10.

| Text | Max.number of source definitions in INPUT clause is 9/10. | |
|-------|---|--|
| Actn. | Correct error in program. | |

NAT5419: Error in printer assignment in ERRORS/MESSAGES subclause.

| Text | Error in printer assignment in ERRORS/MESSAGES subclause. |
|-------|---|
| Actn. | Correct error in program. |

NAT5420: Invalid page number in STARTING/ENDING subclause.

| Text | Invalid page number in STARTING/ENDING subclause. |
|-------|---|
| Actn. | Correct error in program. |

NAT5422: Error in PROFILE definition.

| Text | Error in PROFILE definition. |
|-------|--|
| | PROFILE operand must be of type A and the operand length must be greater than one character and less than or equal to 32 characters. |
| Actn. | Correct error in program. |

NAT5423: Error in STATUS definition.

| Text | Error in STATUS definition. |
|-------|-----------------------------|
| Actn. | Correct error in program. |

NAT5424: The INPUT subclause may be specified only once.

| Text | The INPUT subclause may be specified only once. |
|-------|---|
| Actn. | Correct error in program. |

NAT5425: Input error in EXIT or CABINET parameter.

| Text | Input error in EXIT or CABINET parameter. |
|-------|---|
| Actn. | Correct error in program. |

NAT5426: The ERRORS subclause may be specified only once.

| Text | The ERRORS subclause may be specified only once. |
|-------|--|
| Actn. | Correct error in program. |

NAT5427: The MESSAGES subclause may be specified only once.

| Text | The MESSAGES subclause may be specified only once. |
|------|--|
| Actn | Correct error in program. |

NAT5428: The STARTING subclause may be specified only once.

| Text | The STARTING subclause may be specified only once. |
|-------|--|
| Actn. | Correct error in program. |

NAT5429: The ENDING subclause may be specified only once.

| Text | The ENDING subclause may be specified only once. |
|-------|--|
| Actn. | Correct error in program. |

NAT5430: The PROFILE subclause may be specified only once.

| Text | The PROFILE subclause may be specified only once. |
|-------|---|
| Actn. | Correct error in program. |

NAT5431: The STATUS subclause may be specified only once.

| | The STATUS subclause may be specified only once. |
|-------|--|
| Actn. | Correct error in program. |

NAT5432: PASSW operand must be of type A, less than or equal 8 char.

| Text | PASSW operand must be of type A, less than or equal 8 char. |
|-------|---|
| | The format/length of the operand specified after the keyword PASSW in a COMPOSE statement must be A8. |
| Actn. | Correct error in program. |

NAT5433: CONTROL variables must be of format/length A1.

| Text | CONTROL variables must be of format/length A1. |
|-------|--|
| | The two variables specified after the keyword CONTROL in the OUTPUT subclause of a COMPOSE statement must be of format A1. |
| Actn. | Correct error in program. |

NAT5434: Maximum number of variables in OUTPUT TO VARIABLES is 20.

| Text | Maximum number of variables in OUTPUT TO VARIABLES is 20. |
|-------|--|
| | In the OUTPUT TO VARIABLES subclause of a COMPOSE statement, you |
| | must not specify more than 20 variables. |
| Actn. | Correct error in program. |

NAT5435: Error in receiving variable of FORMATTING OUTPUT clause.

| Text | Error in receiving variable of FORMATTING OUTPUT clause. |
|-------|---|
| - | The receiving variable in the OUTPUT subclause must be of type A. |
| | Note, that it is not recommended to use A1 variables. |
| Actn. | Correct error in program. |

NAT5436: MOVING OUTPUT operand must be of format A.

| Text | MOVING OUTPUT operand must be of format A. |
|-------|---|
| Expl. | The operand specified after MOVING OUTPUT in a COMPOSE statement must be of format A. |
| Actn. | Correct error in program. |

NAT5440: Java Error (:1:) occurred. Message: :2:.

| Text | Java Error (:1:) occurred. Message: :2:. |
|-------|---|
| Expl. | A Java exception of class java.lang.Error has been thrown in the called Java code. |
| | Refer to the Java documentation for further information. Check the called Java code and correct the error. |

NAT5441: Java Runtime Exception (:1:) occurred. Message: :2:.

| Text | Java Runtime Exception (:1:) occurred. Message: :2:. |
|------|---|
| | A Java exception of class java.lang.RuntimeException has been thrown in the called Java code. |
| | Refer to the Java documentation for further information. Check the called Java code and correct the error. |

NAT5442: Java Exception (:1:) occurred. Message: :2:.

| Text | Java Exception (:1:) occurred. Message: :2:. |
|-------|---|
| Expl. | A Java exception of class java.lang.Exception has been thrown in the called Java code. |
| | Refer to the Java documentation for further information. Check the called Java code and correct the error. |

NAT5444: Initialization of the JVM failed. Function: :1:. Reason: :2:.

| Text | Initialization of the JVM failed. Function: :1:. Reason: :2:. |
|-------|---|
| Expl. | The initialization of the Java Virtual Machine failed. Either the JVM could not be loaded from the location indicated in the Natural configuration parameter "JVM" or the initialization failed when executing the indicated initialization function. |
| Actn. | Correct the entry in the Natural configuration parameter "JVM". Consult also the documentation of the JVM. |

NAT5445: Natural Java Bridge internal error. Line: :1:(:2:). Reason :3:.

| Text | Natural Java Bridge internal error. Line: :1:(:2:). Reason :3:. |
|-------|--|
| | An internal error occurred in the Natural Java Bridge. The message |
| | indicates the location of the error. |
| Actn. | Report the full error information to Software AG Support. |

NAT5446: Mandatory parameter not specified.

| Text | Mandatory parameter not specified. |
|-------|--|
| 1 1 | When calling a method of the Natural Java Bridge, a mandatory parameter was not specified. |
| Actn. | Check the documentation of the method and correct the error. |

NAT5447: Method or field :1: not found.

| Text | Method or field :1: not found. |
|-------|---|
| · · | The Java class does not contain a public method with the given name and signature or no public field with the given name. |
| Actn. | Check the documentation of the Java class and correct the error. |

NAT5448: Wrong number of parameters specified in SEND METHOD.

| Text | Wrong number of parameters specified in SEND METHOD. |
|-------|--|
| Expl. | The Java class does not contain a public method with the given name and parameter count. |
| Actn. | Check the documentation of the Java class and correct the error. |

NAT5449: Conversion of parameter :1: not possible.

| Text | Conversion of parameter :1: not possible. |
|-------|--|
| - | The indicated parameter could not be converted from a Java type to a Natural type or vice versa. |
| Actn. | Conversion of parameter :1: not possible. |

NAT5450: Conversion of field or return value not possible.

| Text | Conversion of field or return value not possible. |
|-------|---|
| Expl. | A method return value or a field could not be converted from a Java type to a Natural type or vice versa. |
| Actn. | Check the possible data type conversions between Natural and Java in the documentation of the Natural Java Bridge. Correct the error. |

99

Natural System Error Messages 5451-5500

NAT5460: Initialization of socket/SSL communication failed.

| Text | Initialization of socket/SSL communication failed. |
|-------|--|
| | The initialization of the socket/SSL communication for Natural for Ajax failed. A socket error occurred. When using SSL encryption, make sure that the client/server certificates and private keys are set up correctly. |
| Actn. | Contact your system administrator. |

NAT5461: Session disconnected. Error number :1:, error text :2:.

| Text | Session disconnected. Error number, error text |
|-------|--|
| | While the session was waiting to receive data from Natural for |
| | Ajax, it was disconnected abnormally. |
| Actn. | Contact your system administrator. |

NAT5462: Receive data length failed. Error no. :1:, error text :2:.

| Text | Receive data length failed. Error no, error text |
|-------|--|
| | An error occurred while receiving the length of the next packet from Natural for Ajax. |
| Actn. | Contact your system administrator. |

NAT5463: Receive data failed. Error number :1:, error text :2:.

| Text | Receive data failed. Error number, error text |
|-------|--|
| - | An error occurred while receiving the next packet from Natural for Ajax. |
| Actn. | Contact your system administrator. |

NAT5464: Send data length failed. Error number :1:, error text :2:.

| Text | Send data length failed. Error number, error text |
|-------|--|
| 1 1 | An error occurred while sending the length of the next packet to Natural for Ajax. |
| Actn. | Contact your system administrator. |

NAT5465: Send data failed. Error number :1:, error text :2:.

| Text | Send data failed. Error number, error text |
|-------|--|
| 1 1 | An error occurred while sending the next packet to Natural for Ajax. |
| Actn. | Contact your system administrator. |

NAT5466: The time limit expired.

| Text | The time limit expired. |
|-------|---|
| Expl. | While the session was waiting to receive data from Natural for Ajax, the time limit specified in NWO@TIMEOUT has expired. |
| Actn. | Contact your system administrator. |

NAT5470: Page layout :1: is not defined.

| Text | Page layout is not defined. |
|-------|--|
| Expl. | The application requested a page layout that was not defined in Natural for Ajax. |
| Actn. | Create the page layout before using it in an application. |

NAT5471: Identifier :1: is not defined in layout :2:.

| Text | Identifier is not defined in layout |
|-------|---|
| | The application sent data for a field that was not defined in the requested page layout. |
| Actn. | Check the page layout and regenerate the page adapter. |

NAT5472: Event :1: is not supported by Natural for Ajax.

| Text | Event is not supported by Natural for Ajax. |
|-------|---|
| | The application sent an event to Natural for Ajax in the SEND EVENT clause of a PROCESS PAGE statement that is not supported by Natural for Ajax. |
| Actn. | Check the program and correct the error. |

NAT5477: Incorrect NAME syntax :1:.

| Text | Incorrect NAME syntax |
|-------|--|
| | The syntax of the indicated value in the NAME clause of the PROCESS PAGE statement is incorrect. |
| Actn. | Correct the indicated value in the NAME clause of the PROCESS PAGE statement. |

NAT5478: Incompatible NAME :1:.

| Text | Incompatible NAME |
|-------|---|
| Expl. | The indicated value in the NAME clause of the PROCESS PAGE statement is incompatible with the corresponding VALUE variable. NAME and VALUE must be both scalar or array type variables with the same number of dimensions. |
| Actn. | Correct the indicated value in the NAME clause or change the VALUE parameter to a compatible variable. |

NAT5479: Identifier :1: is not defined in PROCESS PAGE statement.

| Text | Identifier is not defined in PROCESS PAGE statement. |
|-------|--|
| Expl. | The client has sent data for a field that is not defined by NAME/VALUE for the current PROCESS PAGE statement. |
| Actn. | Make sure that the page adapter corresponds to the page layout of the page requested by the PROCESS PAGE statement. Regenerate, transfer and recatalog the adapter if necessary. |

NAT5500: VSAM error during job submission.

| Text | ESY5500 VSAM error during job submission. |
|-------|--|
| Expl. | An error occurred during job submission. |
| Actn. | Resubmit job. If error persists, contact the systems programmer. |

100 Natural System Error Messages 5501-5550

NAT5502: SYSQL error.

| Text | ESY5502 SYSQL Error. |
|-------|-----------------------------|
| Expl. | Internal ESY Error. |
| Actn. | Please contact SAG Support. |

NAT5503: RECALL error.

| Text | ESY5503 RECALL error. |
|-------|---|
| | Dataset could not be recalled using ARCHRCAL macro. Check if the dataset has actually been migrated. If it has, contact the systems programmer regarding the installed migration tool. |
| Actn. | Check dataset status and/or migration tool with systems programmer. |

NAT5506: Data set is migrated.

| Text | ESY5506 Data set is migrated. |
|-------|--|
| Expl. | Dataset is archived on external storage media. |
| Actn. | Please use startup parameter RECALL in ESY. |

NAT5507: Too many parallel ESY requests.

| Text | ESY5507 Too many parallel ESY requests. |
|-------|--|
| Expl. | You may only use 5 nested loops in ESY. |
| Actn. | Please check programs and correct error. |

NAT5508: ADABAS response code :1: returned from ESY.

| Text | ESY5508 ADABAS response code :1: returned from ESY. |
|-------|---|
| Expl. | ADABAS Rsp :1: return from ESY. |
| Actn. | Please contact your database administrator. |

NAT5509: Logon failed - check LOGON-ID / PASSWORD.

| Text | ESY5509 Logon failed - check LOGON-ID / PASSWORD. |
|-------|--|
| | The attempted logon failed. Note: A more detailed message is returned by the installed security system when the ERROR-TEXT field is specified. |
| Actn. | Try to logon again, using a valid LOGON-ID and PASSWORD. |

NAT5510: Logon required.

| Text | ESY5510 Logon required. |
|-------|---|
| Actn. | Logon to Entire System Server (view NATPROC-LOGON). |

NAT5511: Function must be LOGON/LOGOFF.

| Text | ESY5511 Function must be LOGON/LOGOFF. |
|-------|---|
| Expl. | An invalid function was given in view NATPROC-LOGON. |
| Actn. | Check source program. Valid functions are LOGON and LOGOFF. |

NAT5520: No core available.

| Text | ESY5520 No core available. |
|-------|---|
| | The amount of core required for each user is: MAXFBL + MAXSBL + MAXCBL + (NUMREQ * BUFLEN) |
| Actn. | Increase the auxiliary buffer size (ASIZE parameter). |

NAT5521: NATPNI/NATPNIP unresolved.

| Text | ESY5521 NATPNI/NATPNIP unresolved. |
|-------|---|
| - | This NATURAL nucleus is unable to perform Entire System Server functions. |
| Actn. | Contact the NATURAL Administrator. |

NAT5530: Access denied by Security facility.

| Text | ESY5530 Access denied by Security facility. |
|-------|---|
| | A security violation has occurred. This return code has been issued by the security system with which Entire System Server interfaces. |
| Actn. | No action is required. |

NAT5531: Password missing or incorrect.

| Text | ESY5531 Password missing or incorrect. |
|-------|--|
| Expl. | The dataset is password protected, i.e. a password must be supplied. |
| Actn. | Enter a valid password. |

NAT5532: :1: limit specified.

| Text | ESY5532 limit specified. |
|-------|--|
| Expl. | Limit reached. Request processing stopped. |
| Actn. | No action is required. |

NAT5533: Requested number of records scanned.

| Text | ESY5533 Requested number of records scanned. |
|-------|--|
| 1 1 | Requested number of records in READ-FILE or READ-SPOOL scanned and no match for search-creteria found. |
| Actn. | No action required. |

NAT5534: File is not a load library.

Text ESY5534 File is not a load library.

NAT5535: File has invalid format.

| Text | ESY5535 File has invalid format. |
|-------|------------------------------------|
| Expl. | File has not supported DSORG. |
| Actn. | Check with the systems programmer. |

NAT5536: CVA error :1: accessing VTOC.

| Text | ESY5536 CVA error :1: accessing VTOC. |
|-------|--|
| Expl. | Macro CVAFDIR caused error. |
| Actn. | Check inline error code with the systems programmer. |

NAT5537: Time limit reached.

| Text | ESY5537 Time limit reached. |
|------|--|
| · · | Time limit reached and no record was found for this search criteria. |

NAT5538: Invalid record-length specified.

Text ESY5538 Invalid record-length specified.

NAT5539: DFHSMREQ failed with RC = :1:.

| Text | ESY5539 DFHSMREQ failed with RC = :1:. |
|-------|--|
| Expl. | A request failed to delete a migrated dataset. |
| Actn. | Contact your storage administrator. |

NAT5544: Invalid File-ID.

| Text | ESY5544 Invalid File-ID. |
|-------|---------------------------------------|
| Expl. | The requested file-id does not exist. |
| Actn. | Specify valid file-id. |

NAT5549: Not a PDSE data set.

| Text | Not a PDSE data set. |
|-------|-------------------------------------|
| Expl. | The data set is not in PDSE format. |
| Actn. | No action is required. |

NAT5550: Not a PDS or LIBRARIAN file or VSAM data set.

| Text | ESY5550 Not a PDS or LIBRARIAN file or VSAM data set. |
|-------|--|
| Expl. | An attempt was made to access the directory of a non-PDS file. |
| Actn. | No action is required. |

101 Natural System Error Messages 5551-5600

NAT5551: Member not specified.

| Text | ESY5551 Member not specified. |
|-------|---|
| Expl. | An attempt was made to access a PDS member without specifying its name. |
| Actn. | Specify member name. |

NAT5552: NEWNAME / ALIAS operand missing.

| Text | ESY5552 NEWNAME / ALIAS operand missing. |
|-------|---|
| | No value for NEWNAME or ALIAS was given. Formats are: NEWNAME (A8) - view PDS-UPDATE ALIAS (A8) - view CATALOG-UPDATE NEWNAME (A44) - view VTOC-UPDATE |
| Actn. | Supply a value for NEWNAME or ALIAS. |

NAT5553: I/O error on directory.

| Text | ESY5553 I/O error on directory. |
|-------|---|
| Expl. | An error occurred while reading a PDS directory. |
| | The directory of the specified dataset is probably invalid. Check with the systems programmer. |

NAT5554: MEMBER not found in directory.

| Text | ESY5554 MEMBER not found in directory. |
|-------|--|
| Expl. | An attempt was made to access a member which does not exist. |
| Actn. | Specify valid member name. |

NAT5555: NEWNAME / ALIAS already exists in directory.

| Text | ESY5555 NEWNAME / ALIAS already exists in directory. |
|-------|--|
| | Values for NEWNAME and ALIAS must be unique within a directory. The value specified already exists. |
| Actn. | Enter a unique value for NEWNAME or ALIAS. |

NAT5556: File is in use.

| Text | ESY5556 File is in use. |
|-------|--|
| Expl. | The file is under exclusive control of another user. |
| Actn. | Retry at a later time. |

NAT5557: File is held by linkage editor.

| Text | ESY5557 File is held by linkage editor. |
|-------|--|
| Expl. | The file is under exclusive control of the linkage editor. |
| Actn. | Retry at a later time. |

NAT5558: No space in Directory.

| Text | ESY5558 No space in Directory. |
|-------|---|
| Expl. | No space is available in the Directory. |
| Actn. | Enlarge the Directory. |

NAT5559: STOW error.

| Text | ESY5559 STOW error. |
|-------|--|
| Expl. | An error occurred during a STOW attempt. |
| Actn. | No action is required. |

NAT5560: Segment length greater than 253.

| Text | ESY5560 Segment length greater than 253. |
|-------|--|
| Expl. | The maximum segment length is 253. |
| Actn. | Specify a valid SEGMENT-LENGTH. |

NAT5561: Required catalog does not exist.

| Text | ESY5561 Required catalog does not exist. |
|-------|--|
| Expl. | The specified catalog does not exist. |
| Actn. | Specify a valid CVOL. |

NAT5562: Catalog entry not found.

| Text | ESY5562 Catalog entry not found. |
|-------|---|
| Expl. | The entry was not found in the catalog. |
| Actn. | No action is required. |

NAT5563: Data set is an index.

| Text | ESY5563 Data set is an index. |
|-------|--|
| Expl. | The dataset to be cataloged is an index. |
| Actn. | Specify a valid dataset name. |

NAT5564: Data set not at lowest index level.

| Text | ESY5564 Data set not at lowest index level. |
|-------|---|
| Expl. | The dataset name entered must be at the lowest index level. |
| Actn. | Enter a valid dataset name. |

NAT5565: Syntax error in data set name.

| Text | ESY5565 Syntax error in data set name. |
|-------|--|
| Expl. | A syntax error was detected in the dataset name. |
| Actn. | Specify a valid dataset name. |

NAT5566: Syntax error in catalog name.

| Text | ESY5566 Syntax error in catalog name. |
|-------|--|
| Expl. | A syntax error was detected in the catalog name. |
| Actn. | Specify a valid catalog name. |

NAT5567: Invalid option, specify LONG or USERCAT.

| Text | ESY5567 Invalid OPTION, specify LONG or USERCAT. |
|-------|--|
| Expl. | An invalid OPTION was specified, valid options are LONG and USERCAT. |
| Actn. | Specify a valid OPTION (LONG or USERCAT). |

NAT5571: DSNAME operand missing.

| Text | ESY5571 DSNAME operand missing. |
|-------|---|
| Expl. | A fully qualified dataset name must be specified. |
| Actn. | Enter a valid DSNAME. |

NAT5572: NEWNAME missing.

| Text | ESY5572 NEWNAME missing. |
|-------|--|
| Expl. | A fully qualified DSNAME must be specified as NEWNAME for the RENAME function. |
| Actn. | Specify a valid DSNAME in the NEWNAME field for the RENAME function. |

NAT5573: SCRATCH invalid.

Text ESY5573 SCRATCH invalid.

NAT5574: RENAME invalid.

| Text | ESY5574 RENAME invalid. |
|-------|---|
| Expl. | The NEW dataset name contains invalid characters. |
| Actn. | Check NEW dataset name for invalid characters. |

NAT5575: Dataset not renamed. CATALOG-UPDATE function failed.

| Text | ESY5575 Dataset not renamed, CATALOG-UPDATE function failed. |
|-------|--|
| | The new dataset name cannot be cataloged. Therefore the old dataset name is still valid, and the dataset can now be accessed only specifying the correct volume. |
| Actn. | Check with your systems programmer why the new dataset name cannot be cataloged. |

NAT5576: SCRATCH returned with RC :1: and status :2:.

| Text | ESY5576 SCRATCH returned with RC and status |
|-------|---|
| • | SCRATCH could not be performed. See the OS/390 DFSMSdfp Advanced Services Manual for a detailed explanation of the return code and status code. |
| Actn. | Check status of dataset. |

NAT5577: RENAME returned with RC :1: and status :2:.

| Text | ESY5577 RENAME returned with RC and status |
|-------|--|
| Expl. | RENAME could not be performed. See the OS/390 DFSMSdfp Advanced Services Manual for a detailed explanation of the return code and status code. |
| Actn. | Check status of dataset. |

NAT5578: RENAME fatal error; VOL :1: DSN :2:.

| Text | ESY5578 RENAME fatal error; VOL DSN |
|------------|---|
| 1 1 | RENAME could not be performed. Check the dataset (see DSN value) on volume (see VOL value). |
| Actn. | Check with your systems programmer. |

NAT5580: Binder API :1: call, rc :2:, rsn :3:.

| Text | ESY5580 Binder API :1: call, rc :2:, rsn :3:. |
|-------|---|
| Expl. | A call to the Binder API failed. |
| Actn. | Contact Software AG technical support. |

NAT5590: End of data reached during inplace-update.

| Text | ESY5590 End of data reached during inplace-update. |
|-------|---|
| Expl. | It is not possible to add records with the UPDATE-INPLACE function. |
| Actn. | Do not use UPDATE-INPLACE for adding records. |

NAT5591: Member not found for inplace-update.

| Text | ESY5591 Member not found for inplace-update. |
|-------|--|
| Actn. | Specify a valid MEMBER. |

NAT5592: Record length error for variable inplace-update.

| Text | ESY5592 Record length error for variable inplace-update. |
|-------|---|
| Actn. | Check the source program. RECORD-LENGTH may not be changed. |

NAT5600: Unknown function.

| Text | ESY5600 Unknown function. |
|-------|---|
| Expl. | An invalid value was specified in the FUNCTION field. |
| Actn. | Specify valid FUNCTION value. |

102 Natural System Error Messages 5601-5650

NAT5601: DSNAME missing.

| Text | DSNAME missing |
|-------|--|
| Expl. | Dataset Name is required, to catalog a Dataset |

NAT5602: Device is invalid.

| Text | ESY5602 Device is invalid. |
|-------|--|
| Expl. | An invalid DEVICE value was specified. |
| Actn. | Specify valid DEVICE value. |

NAT5603: INDEX / ALIAS missing.

| Text ESY5603 INDEX / ALIAS miss | |
|---------------------------------|------------------------|
| Actn. | Specify INDEX / ALIAS. |

NAT5604: No volumes specified.

| Text | ESY5604 No volumes specified. |
|-------|--|
| Expl. | No VOLUMES were specified for CATLG / RECATLG. |
| Actn. | Specify VOLUMES. |

NAT5605: IGWASMS returned with RC :1: and reason :2:.

| Text | ESY5605 IGWASMS returned with RC :1: and reason :2:. |
|-------|--|
| Expl. | A request failed to retrieve attributes for a dataset. |
| Actn. | Contact your systems programmer. |

NAT5606: Managed data sets cannot be uncataloged.

| Text | ESY5606 Managed data sets cannot be uncataloged. |
|-------|---|
| Expl. | A request was issued to uncatalog an SMS-managed dataset. |
| Actn. | Do no request to uncatalog an SMS-managed dataset. |

NAT5610: QNAME is missing.

| Text | ESY5610 QNAME is missing. |
|-------|--|
| Expl. | No value was specified in the QNAME field. |
| Actn. | Specify valid QNAME value. |

NAT5611: QNAME cannot start with SYS.

| Text | ESY5611 QNAME cannot start with SYS. |
|-------|---|
| Expl. | Major names beginning with SYS are not allowed. |
| Actn. | Specify valid QNAME value. |

NAT5612: RNAME is missing.

| Text | ESY5612 RNAME is missing. |
|-------|--|
| Expl. | No value was specified in the RNAME field. |
| Actn. | Specify RNAME value. |

NAT5613: RNAME length is missing or invalid.

| Text | ESY5613 RNAME length is missing or invalid. |
|-------|---|
| Expl. | No value was specified in the RNAME-LENGTH field. |
| Actn. | Specify valid RNAME-LENGTH value. |

NAT5614: Resource is in use.

| Text | ESY5614 Resource is in use. |
|-------|---|
| · · | Resource is already allocated as sharable by another task, and exclusive access was requested. |
| Actn. | Retry at a later time. |

NAT5615: Resource held by another task.

| Text | ESY5615 Resource held by another task. |
|-------|--|
| Expl. | Resource is already allocated exclusively by another task. |
| Actn. | Retry at a later time. |

NAT5616: Error in CQSCAN routine.

| Text | ESY5616 Error in GQSCAN routine. |
|-------|--|
| Expl. | An internal error occurred as a result of the GQSCAN macro request. |
| | Notify systems programmer. (Software AG technical support should be notified as well). |

NAT5621: Identifier missing/duplicate/not found.

| Text | ESY5621 Identifier missing/duplicate/not found. |
|-------|--|
| Expl. | The identifier associated with the area was missing/duplicate/not found. |
| Actn. | Specify correct identifier. |

NAT5622: NUMBER-OF-ENTRIES missing or invalid.

| Text | ESY5622 NUMBER-OF-ENTRIES missing or invalid. |
|-------|---|
| Expl. | The specification of the maximum number of entries was missing/invalid. |
| Actn. | Specify a valid NUMBER-OF-ENTRIES value. |

NAT5623: ENTRY-LENGTH missing or invalid.

| Text | ESY5623 ENTRY-LENGTH missing or invalid. |
|-------|--|
| Expl. | The specification of the entry length was missing/invalid. |
| Actn. | Specify a valid ENTRY-LENGTH value. |

NAT5624: ENTRY-NUMBER missing or invalid.

| Text | ESY5624 ENTRY-NUMBER missing or invalid. |
|-------|--|
| Expl. | The specification of the entry number was missing/invalid. |
| Actn. | Specify correct entry number. |

NAT5625: Cannot allocate area.

| Text | ESY5625 Cannot allocate area. |
|-------|--|
| Expl. | Insufficient storage was available to allocate the area. |
| Actn. | Decrease amount of requested storage or notify systems programmer. |

NAT5626: DATA missing.

| Text | ESY5626 DATA missing. |
|-------|-------------------------|
| Expl. | No data was specified. |
| Actn. | Specify the DATA field. |

NAT5627: Field position + length > 250.

| Text | ESY5627 Field position + length > 250. |
|-------|--|
| Expl. | The field extends the maximum area length (250). |
| Actn. | Specify valid field position/length. |

NAT5628: Error in editor.

| Text | ESY5628 Error in editor. |
|-------|------------------------------------|
| Expl. | An internal editor error occurred. |
| Actn. | Notify system programmer. |

NAT5629: Area is protected.

| Text | ESY5629 Area is protected. |
|-------|----------------------------|
| Expl. | Area is protected. |
| Actn. | No action required. |

NAT5630: Console not defined or not active.

| Text | ESY5630 Console not defined or not active. |
|-------|--|
| Expl. | The specified console ID was not found. |
| Actn. | Specify valid console ID. |

NAT5631: Console table not found.

| Text | ESY5631 Console table not found. |
|-------|-----------------------------------|
| Expl. | Console table could not be found. |
| Actn. | Contact your systems programmer. |

NAT5632: General or Control object not found.

| Text | ESY5632 General or Control object not found. |
|-------|---|
| Expl. | General or Control object returned by Multi Console Support (MCS) could not be found. |
| Actn. | Contact your systems programmer. |

NAT5633: Cannot lock Console table.

| Text | ESY5633 Cannot lock Console table. |
|-------|---|
| Expl. | Console table could not be locked for exclusive use. |
| | Retry operation. If problem persists, please contact your systems programmer. |

NAT5634: Invalid record number.

| Text | ESY5634 Invalid record number. |
|-------|---|
| Expl. | Requested record number is invalid. |
| Actn. | Retry operation. If problem persists, please contact your systems programmer. |

NAT5635: Attempt to alter key in KSDS file.

| Text | ESY5635 Attempt to alter key in KSDS file. |
|-------|--|
| Expl. | It is not allowed to alter keys in KSDS files. |
| Actn. | Check program and correct error. |

NAT5636: Too many active requests on this ACB.

| Text | ESY5636 Too many active requests on this ACB. |
|-------|---|
| | There may be a nested loop while accessing VSAM files or there are too many parallel requests open. |
| Actn. | Check your program and check also with your ESY-DBA. |

NAT5637: VSAM subtask is not active.

| Text | ESY5637 VSAM subtask is not active. |
|-------|--|
| | The ESY subtask for VSAM access may be abended. |
| | Check with your ESY-DBA to restart ESY. |
| Actn. | Contact your ESY-DBA or contact Software AG technical support. |

NAT5638: Key not found.

| Text | ESY5638 Key not found. |
|-------|--|
| Expl. | Key to access the requested record in your file not found. |
| Actn. | Check program and correct error. |

NAT5639: Cannot delete record in ESDS file.

| Text | ESY5639 Cannot delete record in ESDS file. |
|-------|--|
| Expl. | It is not allowed to delete records from ESDS-files. |
| Actn. | Check program and correct error. |

NAT5640: Error generating VSAM control blocks.

| Text | ESY5640 Error generating VSAM control blocks. |
|-------|---|
| Expl. | An error occurred generating VSAM control blocks. |
| Actn. | Notify systems programmer. |

NAT5641: Error :1: while opening SMF or VSAM file.

| Text | ESY5641 Error :1: while opening SMF or VSAM file. |
|-------|---|
| Expl. | A VSAM error occurred while opening an SMF file. |
| Actn. | Notify systems programmer. |

NAT5642: Error :1: while reading SMF or VSAM file.

| Text | ESY5642 Error :1: while reading SMF or VSAM file. |
|-------|---|
| Expl. | A VSAM error occurred while reading an SMF file. |
| Actn. | Notify systems programmer. |

NAT5643: SMF not active / not recording.

| Text | ESY5643 SMF not active / not recording. |
|-------|---|
| Expl. | At time of the request SMF is not active / not recording. |
| Actn. | Notify systems programmer. |

NAT5644: :1:.

| Text | ESY5644 xxxxxxx error in POWER interface aabb. |
|-------|--|
| Expl. | Error aabb returned by POWER interface function xxxxxxx. |
| Actn. | Contact systems programmer. |

NAT5645: Invalid RBA was specified.

| Text | ESY5645 Invalid RBA was specified. |
|-------|------------------------------------|
| Expl. | The requested RBA was not found. |
| Actn. | Specify valid RBA value. |

NAT5646: Write to VSAM only allowed on base cluster.

| Text | ESY5646 Write to VSAM only allowed on base cluster. |
|-------|--|
| Expl. | An attempt was made to write to a none base cluster. |
| Actn. | Check program and correct error. |

NAT5647: VSAM cluster is not defined as reusable.

| Text | ESY5647 VSAM cluster is not defined as reusable. |
|-------|--|
| Expl. | Access to VSAM cluster only allowed if reusable. |
| Actn. | Define your VSAM cluster reusable. |

NAT5648: Record not in ascending key sequence.

| Text | ESY5648 Record not in ascending key sequence. |
|-------|---|
| Expl. | An attempt was made to write a record with a wrong key. |
| Actn. | Check program and correct error. |

NAT5649: ESY User not found or cannot be cancelled.

| Text | ESY5649 ESY User not found or cannot be cancelled. |
|-------|--|
| Expl. | The ESY user could not be found for various functions. |
| Actn. | Correct input data. |

NAT5650: Invalid sequential file.

| Text | ESY5650 Invalid sequential file. |
|-------|---|
| Expl. | The requested sequential file does not exist. |
| Actn. | Check file name, and re-run program. |

103 Natural System Error Messages 5651-5700

NAT5651: Requested catalog does not exist.

| Text | ESY5651 Requested catalog does not exist. |
|-------|---|
| Expl. | The requested CVOL does not exist. |
| Actn. | Specify valid CVOL. |

NAT5652: Catalog structure inconsistent.

| Text | ESY5652 Catalog structure inconsistent. |
|-------|---|
| Expl. | The catalog structure is inconsistent. |
| Actn. | Notify the systems programmer. |

NAT5653: Cannot delete index.

| | ESY5653 Cannot delete index. |
|-------|------------------------------|
| Expl. | The index cannot be deleted. |
| Actn. | No action is required. |

NAT5654: Index structure does not exist.

| Text | ESY5654 Index structure does not exist. |
|-------|---|
| Actn. | No action is required. |

NAT5655: Insufficient space on catalog data set.

| Text | ESY5655 Insufficient space on catalog data set. |
|-------|---|
| Expl. | The catalog dataset is full. |
| Actn. | Notify the systems programmer. |

NAT5656: Error cataloging generation data set.

| Text | ESY5656 Error cataloging generation data set. |
|-------|---|
| Expl. | An error occurred while cataloging a generation dataset. |
| Actn. | Check specified values. If valid, contact the systems programmer. |

NAT5657: I/O error on catalog.

| Text | ESY5657 I/O error on catalog. |
|-------|--|
| Expl. | An I/O error occurred while accessing the catalog. |
| Actn. | This is probably a hardware error. Contact the systems programmer. |

NAT5658: Data set is not catalogued.

| Text | ESY5658 Data set is not catalogued. |
|-------|---|
| Expl. | The specified dataset is not cataloged. |
| Actn. | No action is required. |

NAT5659: Data set is already catalogued.

| Text | ESY5659 Data set is already catalogued. |
|-------|---|
| Expl. | The specified dataset is already cataloged. |
| Actn. | No action is required. |

NAT5660: :1: - :2: module not available.

| Text | ESY5660 module not available. |
|-------|---|
| Expl. | The specified Natural module was not found. |
| Actn. | Specify the name of an existing Natural module. |

NAT5661: :1: - NATURAL sub-task already active.

| Text | ESY5661 :1: - NATURAL sub-task already active. |
|-------|---|
| Expl. | A Natural subtask is already active for this user. |
| Actn. | Make sure that subtask is closed prior restarting it. |

NAT5662: :1: - NATURAL sub-task not allowed.

| Text | ESY5662 :1: - NATURAL sub-task not allowed. |
|-------|--|
| Expl. | The Natural subtask system has not been initialized. |
| Actn. | Notify systems programmer. |

NAT5663: :1: - NATURAL sub-task not active.

| Text | ESY5663 :1: - NATURAL sub-task not active. |
|-------|--|
| Expl. | The Natural subtask does not exist. |
| Actn. | No action is required. |

NAT5664: :1: - NATURAL sub-task table full.

| Text | ESY5664 :1: - NATURAL sub-task table full. |
|-------|--|
| Expl. | The maximum number of Natural subtasks is reached. |
| Actn. | Notify systems programmer. |

NAT5665: :1: - invalid action requested.

| Text | ESY5665 :1: - invalid action requested. |
|-------|---|
| Expl. | An invalid action was requested. |
| Actn. | Specify valid action. |

NAT5666: :1: - NATURAL sub-task must have parameters.

| Text | ESY5666 :1: - NATURAL sub-task must have parameters. |
|-------|--|
| Expl. | An attempt was made to start a Natural subtask without parameters. |
| Actn. | Specify parameter for Natural subtask. |

NAT5669: Invalid specification for keyword.

| Text | ESY5669 Queue or job name invalid. |
|-------|--------------------------------------|
| Expl. | Submit JCL contains error. |
| Actn. | Correct JCL error and rerun program. |

NAT5670: View not supported.

| Te | xt | ESY5670 View not supported. |
|----|-----|---|
| Ex | pl. | This view is not supported on the local operating system. |

NAT5671: Class missing or is invalid.

| Text | ESY5671 Class missing or is invalid. |
|-------|--|
| Expl. | The function CHANGE requires a valid NEW-CLASS, NEW-DESTINATION or NEW-USERID value. |

NAT5672: Segment option requires JOBNAME/JOBNUMBER.

| Text | ESY5672 Segment option requires JOBNAME/JOBNUMBER. |
|------|--|
| - | Specifying the SEGMENT option (SEGMENT-NUMBER > 0) requires that |
| | the job is identified with JOB-NAME and JOB-NUMBER. |

NAT5673: Access error due to FILETABLE=STATIC.

| Text | ESY5673 Access error due to FILETABLE=STATIC. |
|-------|---|
| Expl. | The requested file could not be accessed because the Entire System Server startup parameter FILETABLE was specified as STATIC. Only those files available at ESY initialization time (STD,PARSTD & TEMP labels) can therefore be accessed. |
| Actn. | To allow dynamic access of files NOT specified at ESY initialization time, change the FILETABLE parameter to DYNAMIC and restart Entire System Server. |

NAT5674: VTOC error reading format-3 labels.

| Text | ESY5674 VTOC error reading format-3 labels. |
|-------|--|
| Expl. | VTOC error reading format-3 labels for the requested file. |
| Actn. | Information message only. No action necessary or possible. |

NAT5675: :1: not supported.

| Text | ESY5675 :1: not supported. |
|-------|--|
| Expl. | Entire System Server has detected that the requested file |
| | has attributes which are not supported by this version of ESY e.g. Multi-volume files, Multi-extent output files etc. |

NAT5676: Not first volume of a multi volume file.

| Text | ESY5676 Not first volume of a multi-volume file. |
|-------|--|
| Expl. | Entire System Server has detected that the file on the specified |
| | volume is NOT the first volume/extent of a multi-volume file. |

NAT5677: FAMS ERROR, R15=XXXXXXX, R0=XXXXXXXX

| 1 1 | A FAMS error occurred while COPY-FILE was copying one or more program objects. |
|-----|--|
| | Check the console log for IGW prefixed messages issued by FAMS for further information |

NAT5678: Member already exists.

| Text | ESY5678 Member already exists. |
|-------|--|
| - | In WRITE-FILE or COPY-FILE, REPLACE = "NO" was specified, however the member exists. |
| Actn. | No action required. |

NAT5679: Input and output files are incompatible.

| Text | ESY5679 Input and output files are incompatible. |
|-------|---|
| | COPY-FILE has determined that the record formats of the input and output files are not compatible (RECFM does not match, block size incompatibilities, etc.). |
| Actn. | Verify dataset attributes and reissue request with correct parameters. |

NAT5680: Job/output is protected.

| Text | ESY5680 Job/output is protected. |
|-------|--|
| Expl. | The user is not authorized to access the specified job/output. |
| Actn. | Notify systems programmer. |

NAT5681: Job/output is active.

| Text | ESY5681 Job/output is active. |
|-------|---|
| Expl. | The specified job/output is currently active. |
| Actn. | There is no action required. |

NAT5682: Job/output is not dispatchable.

| Text | ESY5682 Job/output is not dispatchable. |
|-------|---|
| Expl. | The job/output is not dispatchable. |
| Actn. | There is no action required. |

NAT5683: FAMS error, R15=:1:, R0=:2:.

| Text | ESY5683 FAMS error, R15=:1:, R0=:2:. |
|------|---|
| 1 1 | A FAMS error occurred while COPY-FILE was copying one or more program objects. |
| | Check the console log for IGW prefixed messages issued by FAMS for further information. |

NAT5684: Remote program object copy currently unsupported.

| Text | ESY5684 Remote program object copy currently unsupported. |
|-------|--|
| Expl. | In this release of Entire System Server, use of COPY-FILE on OS/390 for copying program objects between different nodes is not supported. This message is also issued if a program object copy request is issued to a VSE/ESA node. |
| Actn. | A workaround is to first copy the program object to a PDS on the local node, then copy to a PDS on the remote node, then copy to the target PDSE. |

NAT5685: FAMS subtask abended.

| Text | FAMS subtask abended. |
|-------|--|
| - | One of the subtasks used by remote program object copy has abnormally terminated. The ERROR-NODE and ERROR-VIEW fields will show which node had the ABEND. Information regarding the ABEND will be in the JES log. |
| Actn. | Contact Software AG support. |

NAT5687: Bad variable record.

| Text | ESY5687 Bad variable record. |
|-------|------------------------------|
| Expl. | Bad variable record. |
| Actn. | No action is required. |

NAT5688: Return code :1: HCF function :2:.

| Text | ESY5688 Return code :1: HCF function :2:. |
|-------|--|
| Expl. | The HCF function failed. The return code is the HCF return code. |
| Actn. | Notify systems programmer. |

NAT5690: :1: error :2: during :3:.

| Text | ESY5690 1: error :2: during :3:. |
|-------|---|
| Expl. | An error occurred accessing PANVALET or LIBRARIAN data. |
| Actn. | Notify systems programmer. |

NAT5691: Error while accessing librarian member.

| Text | ESY5691 Error while accessing librarian member. |
|-------|---|
| Expl. | An error occurred accessing a LIBRARIAN member. |
| Actn. | There is no action required. |

NAT5692: You are not permitted to access member.

| Text | ESY5692 You are not permitted to access member. |
|-------|---|
| Expl. | This user is not authorized to access the specified member. |
| Actn. | Check with systems programmer. |

NAT5693: :1:.

| Text | ESY5693 :1:. |
|-------|----------------------------|
| Expl. | A PANVALET error occurred. |
| Actn. | See message text. |

NAT5694: Strange error opening VTOC.

| Text | ESY5694 Strange error opening VTOC. |
|-------|---|
| Expl. | A strange internal error occurred reading the VTOC. |
| Actn. | Notify systems programmer. |

NAT5695: VTOC is in use.

| Text | ESY5695 VTOC is in use. |
|-------|-------------------------------|
| Expl. | The VTOC is currently in use. |
| Actn. | Retry. |

NAT5696: Cannot assign logical unit.

| Text | ESY5696 Cannot assign logical unit. |
|-------|---------------------------------------|
| Expl. | A logical unit could not be assigned. |
| Actn. | Notify systems programmer. |

NAT5697: Library/sublibrary not found.

| Text | ESY5697 Library/sublibrary not found. |
|-------|---|
| Expl. | The specified library/sublibrary was not found. |
| Actn. | Specify valid library/sublibrary name. |

NAT5698: Internal LIBRARIAN error has occurred.

| Text | ESY5698 Internal LIBRARIAN error has occurred. |
|-------|--|
| Expl. | An internal LIBRARIAN error occurred. |
| Actn. | Notify systems programmer. |

NAT5699: Not enough main storage available.

| Text | ESY5699 Not enough main storage available. |
|-------|---|
| Expl. | Not enough main storage was available to process the request. |
| Actn. | Notify systems programmer. |

NAT5700: Invalid value specified (DSORG / RECFM / TYPE).

| Text | ESY5700 Invalid value specified (DSORG / RECFM / TYPE). |
|-------|--|
| | An invalid value was specified for view FILE-ALLOCATE. Note: A more detailed message is returned when field ERROR-TEXT is specified. |
| Actn. | Specify valid value for DSORG / RECFM / TYPE. |

104 Natural System Error Messages 5701-5750

NAT5701: DSNAME missing.

| Text | ESY5701 DSNAME missing. |
|-------|-------------------------|
| Expl. | The DSNAME was missing. |
| Actn. | Specify a valid DSNAME. |

NAT5702: OUTADD error-code :1: reason-code :2: key :3:.

Text ESY5702 OUTADD error-code :1: reason-code :2: key :3:.

NAT5703: Copying of empty files not permitted.

Text ESY5703 Copying of empty files not permitted.

NAT5710: Allocation failed with code :1:.

| Text | ESY5710 Allocation failed with code :1:. |
|-------|--|
| | The allocation failed. The code is the DYNALLOC return code. Note: A more detailed message is returned when field ERROR-TEXT is specified. |
| Actn. | Check the DYNALLOC return code. |

NAT5711: Logical Error occurred in Common JES Interface.

| Text | ESY5711 Logical Error occurred in Common JES Interface. |
|------|---|
| | A logical error has occurred in the Common JES Interface. Additional messages describing the type of error may have been issued to the console. |
| | Check the system log for additional messages. Contact Software AG technical support. |

NAT5712: Request to Common JES Interface failed.

| Text | ESY5712 Request to Common JES Interface failed. |
|-------|---|
| Expl. | A request failed to access spool data. |
| Actn. | Contact Software AG technical support. |

NAT5713: Jobname and Job ID missing. One of them required.

| Text | ESY5713 Jobname and Job ID missing. One of them required. |
|-------|---|
| Expl. | Neither JOB-NAME nor JOB-ID / JOB-NUMBER have been specified. At least one of them is required to process the request. |
| Actn. | Specify JOB-NAME, JOB-ID or JOB-NUMBER with the request. |

NAT5714: Unable to read :1: type SYSOUT datasets.

| Text | ESY5714 Unable to read :1: type SYSOUT datasets. |
|-------|---|
| Expl. | The specified spool file TYPE is invalid or can not be processed. |
| Actn. | Specify a valid spool file type (CC, JL, SI, SM or SO). |

NAT5715: Duplicate jobnames found. Please specify job id.

| Text | ESY5715 Duplicate jobnames found. Please specify job id. |
|-------|--|
| Expl. | Multiple jobs were found for the specified job name. |
| Actn. | Additionally specify job id / job number. |

NAT5717: GENCB for ACB or RPL failed with RC:1:and RSN:2:

| Text | ESY5717 GENCB for ACB or RPL failed with RC:1:and RSN:2:. |
|-------|---|
| Expl. | An ACB or RPL could not be generated to access a SYSOUT dataset. |
| Actn. | Check with systems programmer. Contact Software AG technical support. |

NAT5719: Unable to :1: SYSOUT dataset.

| Text | ESY5719 Unable to :1: SYSOUT dataset. |
|-------|---|
| Expl. | An error occurred during open or close of a SYSOUT dataset. |
| Actn. | Check with systems programmer. Contact Software AG technical support. |

NAT5720: Invalid TYPE.

| Text | ESY5720 Invalid TYPE. |
|-------|---|
| Expl. | An invalid TYPE was given in the READ-SPOOL view. |
| | Check source program. Valid values for TYPE are: in MVS: JL, SI, SO, SM and CC. in VSE: LS, PU, RD, XM, CC. |

NAT5721: Job found, but not for specified spool ID.

| Text | ESY5721 Job found, but not for specified spool ID. |
|-------|--|
| Expl. | The job was found on a different spool than the one specified. |
| Actn. | No action is required. |

NAT5722: Requested data set not found.

| Text | ESY5722 Requested data set not found. |
|-------|---|
| Expl. | The requested dataset could not be found. |
| Actn. | No action is required. |

NAT5723: Job not in output service.

| Text | ESY5723 Job not in output service. |
|-------|---|
| Expl. | The requested job is not in output service. |
| Actn. | No action is required. |

NAT5724: Requested job not found.

| Text | ESY5724 Requested Job not found. |
|-------|--|
| Expl. | The requested job could not be found on the JES spool. |
| Actn. | No action is required. |

NAT5725: I/O error on JES3 spool.

| Text | ESY5725 I/O error on JES3 spool. |
|-------|--|
| Expl. | A READ request to the JES spool failed. |
| Actn. | Retry. If the error persists, this is probably a hardware error. |

NAT5726: Logical error on JES3 spool.

| Text | ESY5726 Logical error on JES3 spool. |
|-------|--|
| Expl. | A logical error occurred while reading the JES3 spool dataset. |
| | Notify systems programmer. Software AG technical support should be notified as well. |

NAT5727: Spanned record is too large.

| Text | ESY5727 Spanned record is too large. |
|-------|--------------------------------------|
| Expl. | A spanned record is too large. |
| Actn. | No action is required. |

NAT5728: You are not allowed to see this job.

| Text | ESY5728 You are not allowed to see this job. |
|-------|--|
| - | The user attempted to access a job for which he has not been authorized. This error is issued by the security system with which Entire System Server interfaces. |
| Actn. | No action is required. |

NAT5729: Invalid job TYPE, specify JOB, STC or TSU.

| Text | ESY5729 Invalid job TYPE, specify JOB, STC or TSU. |
|-------|--|
| Expl. | The specified job TYPE is invalid. |
| Actn. | Specify a valid job type (JOB, STC, or TSU). |

NAT5730: Unknown error during spool open.

| Text | ESY5730 Unknown error during spool open. |
|-------|--|
| Expl. | An unknown error occurred during spool open. |
| Actn. | Notify systems programmer and Software AG technical support. |

NAT5731: Error occurred during spool GET.

| Text | ESY5731 Error occurred during spool GET. |
|-------|--|
| Expl. | An error occurred during spool GET. |
| Actn. | Notify systems programmer and Software AG technical support. |

NAT5732: Account number missing.

| Text | ESY5732 Account number missing. |
|-------|----------------------------------|
| Expl. | Account number was not supplied. |
| Actn. | Check program and correct error. |

NAT5733: User ID does not exist.

| Text | ESY5733 No JOIN entry found for user. |
|-------|--|
| Expl. | The user is not defined in the system. |
| Actn. | No action is required. |

NAT5734: ARCHIVE run with errors.

| Text | ESY5734 ARCHIVE run with errors. |
|-------|---|
| Expl. | An error occurred during ARCHIVE execution. |
| Actn. | Check with systems programmer. |

NAT5735: Logical error using I-T-C.

| Text | ESY5735 Logical error using I-T-C. |
|-------|--|
| Expl. | The inter-task-communication was not used correctly. |
| Actn. | No action is required. |

NAT5736: MESSAGE-ID missing.

| Text | ESY5736 MESSAGE-ID missing. |
|-------|-------------------------------|
| Expl. | No MESSAGE-ID value supplied. |
| Actn. | Specify a MESSAGE-ID. |

NAT5737: No more index space for inserting record.

| Text | ESY5737 No more index space for inserting record. |
|-------|--|
| Expl. | The number of records exceeds the available index range. |
| Actn. | No action required. |

NAT5738: Error when using memory-pools.

| Text | ESY5738 Error when using memory-pools. |
|-------|---|
| Expl. | Incorrect use of the MAIN-STORAGE view. |
| Actn. | No action is required. |

NAT5739: Error when using Job Variables.

| Text | ESY5739 Error when using Job Variables. |
|-------|---|
| | Incorrect use of JOB-VARIABLES view. More details are available in SYSTEM-MESSAGE-CODE. |
| Actn. | Please analyze the SYSTEM-MESSAGE-CODE. |

NAT5740: Error when using BTAM file.

| Text | ESY5740 Error when using BTAM file. |
|-------|--|
| Expl. | An error occurred while allocating a file. |
| Actn. | No action is required. |

NAT5741: Error when using SAM file.

| Text | ESY5741 Error when using SAM file. |
|-------|--|
| Expl. | An error occurred while allocating a file. |
| Actn. | No action is required. |

NAT5742: Error when using PAM file.

| Text | ESY5742 Error when using PAM file. |
|-------|--|
| Expl. | An error occurred while allocating a file. |
| Actn. | No action is required. |

NAT5743: Error when using ISAM file.

| Text | ESY5743 Error when using ISAM file. |
|-------|--|
| Expl. | An error occurred while allocating a file. |
| Actn. | No action is required. |

NAT5744: Invalid Eventing name given.

| Text | ESY5744 Invalid eventing name given. |
|-------|---|
| Expl. | An invalid eventing name was specified. |
| Actn. | No action is required. |

NAT5745: Error occurred when executing Eventing.

| Text | ESY5745 Error occurred when executing Eventing. |
|-------|---|
| Expl. | Logical error using P1-Eventing. |
| Actn. | Contact your systems programmer. |

NAT5746: Serialisation running in error.

| Text | ESY5746 Serialisation running in error. |
|-------|--|
| - | A serialization request has failed. Detailed information available in SYSTEM-MESSAGE-CODE. |
| Actn. | Repeat the request later. |

NAT5747: LENGTH or SUBSTRING-LENGTH invalid.

| Text | ESY5747 LENGTH or SUBSTRING-LENGTH invalid. |
|-------|---|
| Expl. | Invalid value specification for view JOB-VARIABLES. Possible reasons: - position greater than length of JV - substring length greater than JV length minus position - position greater than JV length |
| Actn. | Correct values and try again. |

NAT5748: Internal LMS error has occured.

| Text | ESY5748 Internal LMS error has occurred. |
|-------|--|
| Expl. | An internal LMS error has been returned from LMS subprogram interface. Check SYSTEM-MESSAGE-CODE for details. |
| Actn. | Please check SYSTEM-MESSAGE-CODE. |

NAT5749: PVS (CATID) not available.

| Text | ESY5749 PVS (CATID) not available. |
|-------|---|
| Expl. | The requested CATID is not available for the User ID of caller. |
| Actn. | No action possible. |

NAT5750: Invalid operand within operand list.

| Text | ESY5750 Invalid operand within operand list. |
|-------|--|
| Expl. | Incorrect usage of an Entire System Server view. |
| Actn. | No action is required. |

105 Natural System Error Messages 5751-5800

NAT5751: Not enough memory to execute the function.

| Text | ESY5751 Not enough memory to execute the function. |
|-------|---|
| Expl. | There is not enough memory to execute the function. |
| Actn. | Check with systems programmer. |

NAT5752: Message/Message length missing.

| Text | ESY5752 Message/Message length missing. |
|-------|--|
| Expl. | Possible reasons: - no message length specified - message length lower than 4 - message length greater than 1250 during use of field MESSAGE-ARRAY - message length greater than 250 during use of field MESSAGE-TEXT - no message specified |
| Actn. | Correct input values and try again. |

NAT5753: I-T-C name missing.

| Text | ESY5753 I-T-C name missing. |
|-------|--|
| Expl. | ITC name must be specified for functions OPEN, RECEIVE and SEND. |
| Actn. | Specify ITC name. |

NAT5754: not done.

Text ESY5754 not done.

NAT5755: Invalid or no SWITCH type specified.

| Text | ESY5755 Invalid or no SWITCH type specified. |
|-------|--|
| Expl. | Neither USER nor PROCESS as switch type specified. |
| Actn. | Correct switch type. |

NAT5756: Job Variable name missing or invalid.

| Text | ESY5756 Job Variable name missing or invalid. |
|-------|---|
| Expl. | Invalid syntax used or no value specified. |
| Actn. | Please correct. |

NAT5757: Error during user management.

Text ESY5757 Error during user management.

NAT5758: User ID is missing.

| Text | ESY5758 User ID is missing. |
|-------|-----------------------------|
| Expl. | No user name specified. |
| Actn. | Please specify name. |

NAT5759: Name is missing.

Text ESY5759 Name is missing.

NAT5760: Processor name is missing.

Text ESY5760 Processor name is missing.

NAT5761: Start operand is missing.

Text ESY5761 Start operand is missing.

NAT5762: Line/Station is missing.

Text ESY5762 Line/Station is missing.

NAT5763: Info type operand is missing.

Text ESY5763 Info type operand is missing.

NAT5764: Virtual call is missing.

Text ESY5764 Virtual call is missing.

NAT5765: Required Catalog ID not accessible.

Text ESY5765 Required Catalog ID not accessible.

NAT5766: User ID or Terminal ID missing.

| Text | ESY5766 User ID or Terminal ID missing. |
|-------|---|
| Expl. | Neither User ID nor processor-/terminal-name specified. |
| Actn. | Please specify requested values. |

NAT5767: No TSN found.

Text ESY5767 No TSN found.

NAT5768: Invalid command in macro list.

Text ESY5768 Invalid command in macro list.

NAT5769: Short name is missing.

Text ESY5769 Short name is missing.

NAT5770: Serialisation name missing.

Text ESY5770 Serialisation name missing.

NAT5771: No information found.

| Text | ESY5771 No information found. |
|-------|---|
| Expl. | No information found for specified request. |
| Actn. | No action required. |

NAT5772: BS2000 Command has returned error.

Text ESY5772 BS2000 Command has returned error.

NAT5773: New version operand missing.

Text ESY5773 New version operand missing.

NAT5774: No core available.

| Text | ESY5774 No core available. |
|-------|--|
| Expl. | Not enough space available to allocate an ESY User Block. |
| | Please contact Software AG. For BS2000/OSD only: The number of ESY User Blocks can be configured with startup parameter NUMUSER. |

NAT5775: Invalid Priority Value specified.

Text ESY5775 Invalid Priority Value specified.

NAT5776: Request was cancelled.

| Text | ESY5776 Request was cancelled. |
|------|---|
| | Request was cancelled internally because user has been timed out. |

NAT5777: Request has abended.

| Text | ESY5777 Request has abended. |
|-------|--|
| · · | An internal error occurred. Condensed abend information is contained in the job-log. |
| Actn. | Check with systems programmer. Contact Software AG technical support. |

NAT5778: Cannot perform command - not APF authorized.

| Text | ESY5778 Cannot perform command - not APF authorized. |
|-------|---|
| Expl. | The Entire System Server nucleus is not running APF authorized. |
| Actn. | Check with systems programmer. |

NAT5779: IDCAMS utility has abended.

| Text | ESY5779 IDCAMS utility has abended. |
|-------|---|
| Expl. | The IDCAMS utility has abended. |
| Actn. | Check job-log for additional information. |

NAT5780: Completion code not ok.

| Text | ESY5780 Completion code not ok. |
|-------|--|
| Expl. | The execution of the request was not successful. |
| Actn. | Check input data of request. |

NAT5781: Unable to obtain storage for work area extension.

| Text | ESY5781 Unable to obtain storage for work area extension. |
|-------|---|
| Expl. | A request failed to obtain storage for the work area extension. |
| Actn. | Increase the region size above 16 MB for Entire System Server. |

NAT5782: Error from :1: for :2:, RC :3:, REASON :4:.

| Text | ESY5782 Error from :1: for :2:, RC :3:, REASON :4:. |
|-------|---|
| Expl. | A request failed while attempting to read the VTOC. |
| Actn. | Contact your systems programmer. |

NAT5783: Unable to allocate :1:, RC :2:, REASON :3:.

| Text | ESY5783 Unable to allocate :1:, RC :2:, REASON :3:. |
|-------|---|
| Expl. | The specified volume could not be allocated. |
| Actn. | Contact your systems programmer. |

NAT5784: Unable to open VTOC on :1:, RC :2:.

| Text | ESY5784 Unable to open VTOC on :1:, RC :2:. |
|-------|--|
| Expl. | An OPEN request failed for the VTOC on the specified volume. |
| Actn. | Try again. If the problem persists, contact your systems programmer. |

NAT5785: CVAF :1: failed with RC :2: and CVSTAT :3:.

| Text | ESY5785 CVAF :1: failed with RC :2: and CVSTAT :3:. |
|-------|--|
| Expl. | A request failed to the Common VTOC Access Facility. |
| Actn. | Contact your systems programmer. |

NAT5786: Unable to obtain storage for CSI work area.

| Text | ESY5786 Unable to obtain storage for CSI work area. |
|-------|--|
| Expl. | A request failed to obtain storage for the CSI work area. |
| Actn. | Increase the region size above 16 MB for Entire System Server. |

NAT5787: CSI request failed, Module :1:, Reason :2:, RC :3:.

| Text | ESY5787 CSI request failed, Module :1:, Reason :2:, RC :3:. |
|-------|---|
| Expl. | A request to the catalog search interface failed. |
| Actn. | Contact your systems programmer. |

NAT5788: Unable to substitute symbol :1:, RC :2:.

| Text | ESY5788 Unable to substitute symbol :1:, RC :2:. |
|-------|--|
| Expl. | A request failed to substitute text for a system symbol. |
| Actn. | Contact your systems programmer. |

NAT5789: Unable to get UCB copy for :1:, RC :2:.

| Text | ESY5789 Unable to get UCB copy for :1:, RC :2:. |
|-------|--|
| Expl. | A request failed to get a UCB copy for the volume specified. |
| Actn. | Contact your systems programmer. |

NAT5790: Abend :1: during IEBCOPY.

| Text | ESY5790 Abend :1: during IEBCOPY. |
|-------|---|
| Expl. | An abend has occurred while processing the IEBCOPY utility. |
| Actn. | Contact your systems programmer. |

NAT5799: ENTIRE SYSTEM SERVER internal error.

| Text | ESY5799 Entire System Server internal error. |
|-------|--|
| Expl. | An internal error has occurred. |
| Actn. | Please contact SAG support. |

NAT5800: Specified level is a data set name.

| Text | ESY5800 Specified level is a data set name. |
|-------|---|
| Expl. | The specified level name is a dataset name. |
| Actn. | No action is required. |

106 Natural System Error Messages 5801-5850

NAT5801: Job not found.

| Text | ESY5801 Job not found. |
|-------|----------------------------------|
| Expl. | The requested job was not found. |
| Actn. | No action is required. |

NAT5802: GETMAIN for CSA area failed.

| Text | ESY5802 GETMAIN for CSA area failed. |
|-------|--|
| - | An attempt was made to access main storage, and GETMAIN for the CSA area failed. |
| Actn. | Notify the systems programmer. |

NAT5803: Cannot access data.

| Text | ESY5803 Cannot access data. |
|-------|--|
| Expl. | An attempt was made to access main storage, and the data specified cannot be accessed. |
| Actn. | No action is required. |

NAT5804: Request to access data has timed out.

| Text | ESY5804 Request to access data has timed out. |
|-------|---|
| - | Main storage was accessed, and SRB was scheduled to run in an address space. SRB must be completed within 10 seconds. |
| Actn. | No action is required. |

NAT5805: Invalid TCB address.

| Text | ESY5805 Invalid TCB address. |
|-------|---------------------------------------|
| Expl. | An invalid TCB-ADDRESS was specified. |
| Actn. | Specify valid TCB-ADDRESS. |

NAT5806: Permanent I/O error on catalog.

| Text | ESY5806 Permanent I/O error on catalog. |
|-------|--|
| Expl. | A permanent I/O error occurred while accessing the catalog. |
| Actn. | This may be a hardware error. Contact data center personell. |

NAT5807: Invalid track address.

| | Text | ESY5807 Invalid track address. |
|--|-------|---|
| | Expl. | An invalid track address was specified. |
| | Actn. | Specify valid track address. |

NAT5809: Subsystem not active.

| Text | ESY5809 Subsystem not active. |
|-------|---|
| Expl. | The related subsystem has not been started properly. Therefore, the requested function is not available in this run of ESY. Following views return this error code on BS2000/OSD: - views SPOOL-QUEUE, SPOOL-FILES, WRITE-SPOOL if SPOOL=NONE is defined; - views SEND-MESSAGE, CONSOLE if CONSOLE task is not running; - views CONSOLE, EVENTING if EVENTING task is not running. |
| Actn. | Contact your administrator to get the subsystem started for the next ESY run. |

NAT5810: Error detected in catalog, processing terminated.

| Text | ESY5810 Error detected in catalog, processing terminated. |
|-------|---|
| Expl. | An error in the catalog structure was detected. |
| Actn. | Notify the systems programmer. |

NAT5811: Specified level is an empty index.

| Text | ESY5811 Specified level is an empty index. |
|-------|--|
| Expl. | The level specified is an empty index. |
| Actn. | No action is required. |

NAT5820: Unknown command.

| Text | ESY5820 Unknown command. |
|-------|---|
| Expl. | A command which is not known to Entire System Server was entered. |
| | Check spelling, syntax of command. Check to see whether command is a Natural command. |

NAT5821: Job no longer active.

| Text | ESY5821 Job no longer active. |
|-------|--|
| Expl. | An attempt was made to access a job which is no longer active. |
| Actn. | No action required. |

NAT5822: Logical error on JES3 spool.

| Text | ESY5822 Logical error on JES3 spool. |
|-------|--|
| Expl. | A logical error occurred while reading the JES3 spool dataset. |
| | Try again. If error persists, it may indicate a bad control block on the JES3 spool (which may be caused by a hardware error). |

NAT5823: Requested job in input queue.

| Text | ESY5823 Requested job in input queue. |
|-------|---|
| Expl. | An attempt was made to access output data of a job which is in the input queue. |
| Actn. | Wait until job is processed. |

NAT5824: I/O error on JES3 spool.

| Text | ESY5824 I/O error on JES3 spool. |
|-------|---|
| Expl. | A READ operation to JES3 spool failed to complete normally. |
| Actn. | Probably a hardware failure. A JES3 warmstart (with analysis) should be considered. |

NAT5825: JES3 command data set is full.

| Text | ESY5825 JES3 command data set is full. |
|-------|---|
| Expl. | A WRITE operation to the JES3 command dataset failed because the dataset is full. |
| Actn. | Wait until space becomes available. |

NAT5826: I/O error on JES3 command data set failed.

| Text | ESY5826 I/O error on JES3 command data set. |
|-------|---|
| Expl. | A WRITE attempt to the JES3 command dataset failed. |
| Actn. | This is probably a hardware error. If error persists, it may be |
| | advisable to relocate the JES3 command dataset. |

NAT5830: JES interface is not active.

| Text | ESY5830 JES interface is not active. |
|-------|---|
| Expl. | The JES interface is not active. |
| Actn. | Check the JES parameter in the Entire System Server parameter file. |

NAT5831: Error during queue initialization.

| Text | ESY5831 Error during queue initialization. |
|-------|---|
| Expl. | An error occurred while reading JES control blocks. |
| Actn. | This is probably a hardware error. Contact data center personell. |

NAT5832: Error during queue open.

| Text | ESY5832 Error during queue open. |
|-------|---|
| Expl. | An error occurred during open of JES spool dataset. |
| Actn. | Check with systems programmer. |

NAT5833: You are not allowed to alter this job.

| Text | ESY5833 You are not allowed to alter this job. |
|-------|--|
| · · | An attempt was made to alter a job. The user is not authorized to alter the specified job. This error message is issued by the security system with which Entire System Server interfaces. |
| Actn. | No action is required. |

NAT5834: Command failed, MGCRE RC = :1:.

| Text | ESY5834 Command failed, MGCRE RC = :1:. |
|-------|---|
| Expl. | A request failed to issue an internal JES or system command. |
| Actn. | Check with systems programmer. Contact Software AG technical support. |

NAT5840: VTAM operator ACB is not open.

| Text | ESY5840 VTAM operator ACB is not open. |
|-------|---|
| Expl. | The VTAM operator ACB was not opened successfully during initialization. |
| Actn. | Either active VTAM support has not been requested by the system |
| | parameters, or an open error occurred during initialization. The job-log contains further information. |

NAT5841: Error in SENDCMD - RTNCD=:1: FDBK2=:2:.

| Text | ESY5841 Error in SENDCMD - RTNCD=:1: FDBK2=:2:. |
|------|--|
| | A VTAM error occurred while sending a command. Note: A more detailed message is returned when field ERROR-TEXT is specified. |
| | Check the command requested. The RTNCD and FDBK2 values are defined in the appropriate VTAM documentation. |

NAT5842: Invalid VTAM command.

| Text | ESY5842 Invalid VTAM command. |
|-------|--|
| Expl. | An invalid VTAM command was requested. |
| Actn. | No action is required. |

NAT5843: Printer is not available.

NAT5844: Buffer is waiting to be printed.

NAT5845: Printer is active for user :1:.

| Text | ESY5845 Printer is active for user :1:. |
|-------|---|
| Expl. | Another user is working with the printer. |
| Actn. | Wait until printer is not busy anymore. |

NAT5846: Use function STATUS to get results.

NAT5847: Print mode ASIS error.

NAT5849: Print failed. Fct=:1: FD=:2: S=:3:.

| Text | ESY5849 Print failed. Fct=:1: FD=:2: S=:3:. |
|-------|---|
| | The print request failed. For further details check the variable data of FUNCTION, FEEDBACK and STATUS. You may find the explanation of these fields in the VTAM documentation. |
| Actn. | Please contact your systems programmer. |

NAT5850: Error :1: when processing VTOC.

107 Natural System Error Messages 5851-5900

NAT5851: File not on volume.

| Text | ESY5851 File not on volume. |
|-------|--|
| Expl. | The requested file does not exist on the specified volume. |
| Actn. | No action is required. |

NAT5852: No password supplied / VSAM data space.

| Text | ESY5852 No password supplied / VSAM data space. |
|-------|---|
| | No password was specified before attempting to access a password protected VSAM file. |
| Actn. | Specify a password. |

NAT5853: Retention cycle unexpired / NEWNAME exists.

| Text | ESY5853 Retention cycle unexpired / NEWNAME exists. |
|------|---|
| | A VTOC-UPDATE RENAME function was attempted; however, the retention cycle is unexpired, and the NEWNAME still exists. |
| | Specify a different NEWNAME, or wait until the retention cycle has expired. |

NAT5854: Permanent I/O error.

| Text | ESY5854 Permanent I/O error. |
|-------|---|
| Expl. | A permanent I/O error was detected. |
| Actn. | This is probably a hardware error. Contact data center personell. |

NAT5855: Volume not mounted.

| Text | ESY5855 Volume not mounted. |
|-------|---|
| Expl. | The requested volume was not mounted. |
| Actn. | Make sure that the volume is mounted before re-issuing the request. |

NAT5856: Operator unable to mount volume.

| Text | ESY5856 Operator unable to mount volume. |
|-------|---|
| Expl. | The operator is not able to mount the volume. |
| Actn. | No action is required. |

NAT5857: File in use.

| Text | ESY5857 File in use. |
|-------|----------------------|
| Expl. | The file is in use. |
| Actn. | Retry later. |

NAT5858: Not authorized.

| Text | ESY5858 Not authorized. |
|-------|------------------------------------|
| Expl. | A security violation was detected. |
| Actn. | No action is required. |

NAT5859: File definition not deleted by RACF.

| Text | ESY5859 File definition not deleted by RACF. |
|-------|---|
| Expl. | The file definition has not been deleted by RACF. |
| Actn. | Execute RACF file deletion. |

NAT5860: Member under MSHP control or changed with MSHP bypass.

| Text | ESY5860 Member under MSHP control or changed with MSHP bypass. |
|-------|---|
| 1 1 | The member to be overwritten is under MSHP control or was changed with MSHP bypass. |
| Actn. | Use MSHP=YES to indicate MSHP bypass required. |

NAT5861: Member contains SYSIPT data.

| Text | ESY5861 Member contains SYSIPT data. |
|-------|--|
| Expl. | Member to be overwritten contains SYSIPT data. |
| 1 | Use INLINE-DATA=YES to confirm SYSIPT data required, or INLINE-DATA=OFF to switch off the SYSIPT indicator. |

NAT5870: RECORD field not in search buffer.

| Text | ESY5870 RECORD field not in search buffer. |
|-------|--|
| Expl. | RECORD must be specified for WRITE-FILE. |
| Actn. | Specify RECORD value. |

NAT5871: MEMBER/MEMBER-TYPE not specified.

| Text | ESY5871 MEMBER/MEMBER-TYPE not specified. |
|-------|--|
| Expl. | The member name and/or type was not specified. |
| Actn. | Specify a member name and/or type. |

NAT5872: Record format not supported.

| Text | ESY5872 Record format not supported. |
|-------|--|
| Expl. | The record format of the desired dataset is not supported. |
| Actn. | No action is required. |

NAT5873: RECORD-LENGTH missing.

| Text | ESY5873 RECORD-LENGTH missing. |
|-------|-------------------------------------|
| Expl. | The RECORD-LENGTH value is missing. |
| Actn. | Specify RECORD-LENGTH value. |

NAT5874: RECORD-LENGTH > LRECL.

| Text | ESY5874 RECORD-LENGTH > LRECL. |
|-------|---|
| | The specified RECORD-LENGTH value is greater than the LRECL of the dataset. |
| Actn. | Specify valid RECORD-LENGTH value. |

NAT5875: Position of data field > RECORD-LENGTH.

| Text | ESY5875 Position of data field > RECORD-LENGTH. |
|-------|---|
| Expl. | Invalid parameter specified. |
| Actn. | Check program and correct error. |

NAT5876: No NEW-field for CHANGE request.

| Text | ESY5876 No "NEW-" field for CHANGE request |
|-------|--|
| - | No NEW-CLASS, NEW-DESTINATION or NEW-USERID field was supplied for the CHANGE request. |
| Actn. | Supply "NEW-" value. |

NAT5877: VSAM (SHOWCAT) processing error.

| Text | ESY5877 VSAM (SHOWCAT) processing error. |
|-------|---|
| Expl. | A SHOWCAT error was detected when processing the requested VSAM |
| | catalog. |

NAT5878: Volume defined as DYNAM/D pool name.

| Text | ESY5878 Volume defined as DYNAM/D pool name. |
|-------|--|
| Expl. | The requested volume is defined to Entire System Server as a DYNAM/D |
| | "virtual" pool name. The requested function cannot be performed. |

NAT5881: Error occurred while opening file.

| Text | ESY5881 Error occurred while opening file. |
|-------|--|
| Expl. | An error occurred during OPEN. |
| Actn. | Check the status of the dataset. |

NAT5882: Error occurred while closing file.

| Text | ESY5882 Error occurred while closing file. |
|-------|--|
| Expl. | An error occurred during CLOSE. |
| Actn. | Check the status of the dataset. |

NAT5883: Data set is full.

| Text | ESY5883 Data set is full. |
|-------|---|
| Expl. | The dataset is full. |
| Actn. | Compress the PDS, or increase the dataset size. |

NAT5886: Event is in use.

| Text | ESY5886 Event is in use. |
|-------|---|
| Expl. | An attempt was made to delete an event someone was waiting for. |
| Actn. | Issue "POST" request prior to delete an event. |

NAT5887: Event is already defined.

| Text | ESY5887 Event is already defined. |
|-------|--|
| Expl. | An attempt was made to define an event which already exists. |
| Actn. | No action is required. |

NAT5888: Event name must be specified.

| Text | ESY5888 Event name must be specified. |
|-------|---|
| Expl. | An eventing request was issued without specifying the EVENT-NAME. |
| Actn. | Specify an EVENT-NAME. |

NAT5889: Permanent I/O error while writing data set.

| Text | ESY5889 Permanent I/O error while writing data set. |
|-------|---|
| Expl. | An I/O error was detected during WRITE access. |
| Actn. | This is probably a hardware error. Contact data center personell. |

NAT5890: Event does not exist.

| Text | ESY5890 Event does not exist. |
|-------|-------------------------------------|
| Expl. | The specified event does not exist. |
| Actn. | No action is required. |

NAT5891: Timeout waiting for event.

| Text | ESY5891 Timeout waiting for event. |
|-------|---|
| Expl. | A timeout happened before the event was posted. |
| Actn. | No action is required. |

NAT5893: Getmain failed.

| Text | ESY5893 Getmain failed. |
|-------|---|
| Expl. | There was not sufficient storage available to proceed with the request. |
| Actn. | Notify systems programmer. |

NAT5894: Enable Eventing failed.

| Text | ESY5894 Enable Eventing failed. |
|-------|--|
| Expl. | Internal eventing error occurred. |
| Actn. | Contact Software AG technical support. |

NAT5895: :1: must be specified.

| Text | ESY5895 :1: must be specified. |
|-------|---------------------------------------|
| Expl. | Required value :1: was not specified. |
| Actn. | Provide required value. |

NAT5896: Error occurred when sending E-Mail.

| Text | ESY5896 Error occurred when sending E-Mail. |
|-------|---|
| - | Severe error occurred during E-MAIL processing. Further information are returned in field SYSTEM-MESSAGE to identify subfunction and response code. |
| Actn. | Please contact Software AG support. |

NAT5897: Mailer response: :1:.

| Text | ESY5897 Mailer response :1:. |
|-------|--|
| Expl. | Error :1: occurred during E-MAIL processing in Mailer function. E-MAIL was not delivered to recipient(s) if serious error occurred. |
| Actn. | Please contact Entire System Server Administrator. Mailer report may contain further error diagnostics. |

NAT5899: Permanent I/O error while reading data set.

| Text | ESY5899 Permanent I/O error while reading data set. |
|-------|---|
| Expl. | An I/O error was detected during READ access. |
| Actn. | This is probably a hardware error. Contact data center personell. |

NAT5900: Cannot allocate SYSOUT data set.

| Text | ESY5900 Cannot allocate SYSOUT data set. |
|-------|--|
| Expl. | Dynamic allocation of SYSOUT dataset failed. |
| Actn. | Contact the systems programmer. |

108 Natural System Error Messages 5901-5950

NAT5901: Cannot allocate internal reader.

| Text | ESY5901 Cannot allocate internal reader. |
|-------|---|
| Expl. | Dynamic allocation of internal reader failed. |
| Actn. | Contact the systems programmer. |

NAT5902: Dynamic allocation failed.

| Text | ESY5902 Dynamic allocation failed. |
|-------|------------------------------------|
| Actn. | Contact the systems programmer. |

NAT5903: Dynamic allocation failed for temporary data set.

| Text | ESY5903 Dynamic allocation failed for temporary data set. |
|-------|---|
| Expl. | Dynamic allocation for a temporary dataset failed. |
| Actn. | Contact the systems programmer. |

NAT5904: Edit not allowed (SCLM protection).

| Text | ESY5904 Edit not allowed (SCLM protection). |
|-------|---|
| | The selected PDS member has been protected by SCLM. Only browsing if this member is allowed, all update actions are denied. |
| Actn. | Use SCLM dialog to free member. |

NAT5906: DESERV :1: error, R15=:2:, R0=:3:.

| Text | ESY5906 DESERV :1: error, R15=:2:, R0=:3:. |
|------|---|
| | A DESERV macro was issued and an unexpected error occurred. The function and values for R15 and R0 are shown. |
| | Check the R15 and R0 values and if necessary contact Software AG technical support. |

NAT5907: DSPSERV :1: error, R15=:2:, R0=:3:.

| Text | ESY5907 DSPSERV :1: error, R15=:2:, R0=:3:. |
|------|--|
| | A DSPSERV macro was issued and an unexpected error occurred. The function and values for R15 and R0 are shown. |
| | Check the R15 and R0 values and if necessary contact Software AG technical support. |

NAT5908: ALESERV :1: failure, R15=:2:, R0=:3:.

| Text | ALESERV :1: error, R15=:2:, R0=:3:. |
|------|---|
| | An ALESERV macro was issued and an unexpected error occurred. The function and values for R15 and R0 are shown. |
| | Check the R15 and R0 values and if necessary contact Software AG technical support. |

NAT5909: Syntax error in JCL command.

| Text | ESY5909 Syntax error in JCL command. |
|-------|--------------------------------------|
| Expl. | A syntax error was detected. |
| Actn. | Check JCL and correct error. |

NAT5912: EPS5912 Destination definition time window overlap.

NAT5913: EPS5913 User already belongs to a group.

NAT5914: EPS5914 Owner Id is not defined.

NAT5915: EPS5915 Printer Id is not defined.

NAT5917: EPS5917 Record already exists.

NAT5918: EPS5918 Owner Id is not defined.

NAT5920: EPS5920 Report status must be A, H, P or L.

NAT5921: ENTIRE SYSTEM SERVER node table not linked.

| Text | ESY5921 Entire System Server node table not linked. |
|-------|---|
| Expl. | Entire System Server node table not linked. |
| Actn. | Contact your systems programmer. |

NAT5922: ENTIRE SYSTEM SERVER node :1: not active.

| Text | ESY5922 Entire System Server node :1: not active. |
|-------|---|
| Actn. | Contact operator or systems programmer. |

NAT5923: Error :1: calling ENTIRE SYSTEM SERVER. NAT5924: Binary descriptors not supported for Incore Database. NAT5925: MU field in PE group not supported for Incore Database. NAT5926: Too many concurrent index searches for one file (max. 2). NAT5931: EPS5931 No suitable destination definition. NAT5932: EPS5932 Report already open. NAT5933: EPS5933 Report number must be specified. NAT5934: EPS5934 Error in control data. NAT5935: EPS5935 Invalid printer Id. NAT5936: EPS5936 Report was not opened. NAT5937: EPS5937 You must specify both group and user Id. NAT5938: EPS5938 You must specify a printer Id. NAT5939: EPS5939 Report has too many lines. NAT5940: EPS5940 Printer command table is full. NAT5941: EPS5941 Report does not exist. NAT5942: EPS5942 Report is not available. NAT5943: EPS5943 Line number is not in reports line range. NAT5944: EPS5944 Please specify a report number. NAT5945: EPS5945 Report is printing, priority was not changed. NAT5946: EPS5946 Report control record is missing. NAT5947: EPS5947 Printer is not active. NAT5948: EPS5948 Source must be O or R. NAT5949: EPS5949 Invalid function. NAT5950: EPS5950 Invalid copylist name.

109 Natural System Error Messages 5951-6000

NAT5951: EPS5951 Print Server not active. NAT5952: EPS5952 No line specified for WRITE report. NAT5953: EPS5953 Invalid object type. NAT5954: EPS5954 "SYSDEF" record missing. NAT5955: EPS5955 Invalid command data. NAT5956: EPS5956 Invalid destination data. NAT5957: EPS5957 Invalid data on system defaults. NAT5958: EPS5958 Error in CLIST record. NAT5959: EPS5959 Error in LOG record. NAT5960: Internal error - invalid function code (NOMPUT-N). NAT5961: Internal error - report not opened. NAT5962: Internal error - error during compression of print line. NAT5963: Internal error - invalid CC type specification. NAT5964: Internal error - invalid source type specification. NAT5965: Internal error - invalid NAF DBID. NAT5966: Internal error - invalid NAF FNR. NAT5967: Internal error - invalid logical printer number (1-31). NAT5968: Internal error - invalid User ID specification. NAT5969: Internal error - invalid PROGRAM specification. NAT5970: Internal error - invalid LIBRARY specification. NAT5971: Internal error - invalid LPF specification. NAT5972: Internal error - invalid function code (NOMPUTQN). NAT5973: NOM control record missing. NAT5974: FSPOOL not defined in the NOM monitor defaults. NAT5975: Internal error - error during CMMPP call. NAT5981: Invalid value specified (BLKCTRL/BLKSIZE/LRECL).

| Text | ESY5981 Invalid value specified (BLKCTRL/BLKSIZE/LRECL). |
|-------|---|
| Expl. | Invalid value for BLOCK CONTROL, BLOCK SIZE or RECORD LENGTH specified. |
| Actn. | Please correct error. |

NAT5982: Error during use of ISAM-key.

| Text | ESY5982 Error during use of ISAM-key. |
|-------|--|
| Expl. | Possible reasons: - duplicate key detected for DUPEKY=NO - key must be generated, but KEYLEN is greater than 8 bytes or no default KEYPOS - key length of file is greater than 253 bytes - key not found in ISAM-file - no key supplied for UPDATE-INPLACE=YES - invalid key sequence detected |
| Actn. | Please check parameters or file attributes. |

NAT5983: :1: not supported by :2:.

| Text | ESY5983 :1: not supported by :2:. |
|-------|---|
| Expl. | Various functions are not supported in special modes. E.g. view EVENTING is only available in MULTI USER MODE for BS2000. Error text "SINGLE USER MODE not supported by EVENTING" occurs. |
| Actn. | No action possible. |

NAT5984: Server is not authorized to access.

| Text | ESY5984 Server is not authorized to access. |
|-------|---|
| Expl. | ESY Server Task is not authorized to access various objects with protection attributes, which not allows access for \$TSOS. |
| Actn. | No action possible. |

NAT5985: Access to tape file not allowed.

| Text | ESY5985 Access to tape file not allowed. |
|-------|---|
| | Access to tape file was requested, but parameter TAPES=NO is specified in ESY startup file. |
| Actn. | Please contact your ESY Administrator. |

NAT5986: No or not enough space for :1:.

| Text | ESY5986 No or not enough space for :1:. |
|-------|--|
| Expl. | Various startup parameter sizes are exceeded. See variable text for details. |
| Actn. | Please contact your ESY Administrator. |

NAT5987: Job Variable already exists.

| Text | ESY5987 Job Variable already exists. |
|-------|---|
| Expl. | An existing job variable cannot be allocated again. |
| Actn. | Please check your input values. |

NAT5988: Invalid task type detected.

| Text | ESY5988 Invalid task type detected. |
|-------|--|
| Expl. | Task type must have a value between 1 and 7. |
| Actn. | Correct program. |

NAT5989: Invalid ELEMENT specification.

| Text | ESY5989 Invalid ELEMENT specification. |
|-------|--|
| Expl. | Element name must be unique. |
| Actn. | Correct element name. |

NAT5990: Field RECORD not found in format buffer.

| Text | ESY5990 Field RECORD not found in format buffer. |
|-------|---|
| Expl. | An attempt was made to read a record without specifying the RECORD field. |
| Actn. | Supply field RECORD in program. |

NAT5991: Unknown product.

| Text | ESY5991 Unknown product. |
|-------|---|
| Expl. | An invalid PRODUCT value was specified. |
| Actn. | Specify valid product code. |

NAT5992: Requested job variable not found.

| Text | ESY5992 Requested job variable not found. |
|-------|--|
| Expl. | The requested job variable is not cataloged. |
| Actn. | No action required. |

NAT5993: Cannot open file.

| Text | ESY5993 Cannot open file. |
|-------|---------------------------|
| Expl. | An open request failed. |
| Actn. | No action required. |

NAT5994: File not on volume.

| Text | ESY5994 File not on volume. |
|-------|---|
| Expl. | The requested dataset is not on the specified volume. |
| Actn. | No action is required. |

NAT5995: File not in catalog.

| Text | ESY5995 File not in catalog. | |
|-------------------------------------|-------------------------------------|--|
| Expl. The dataset is not cataloged. | | |
| Actn. | Specify VOLSER, or catalog dataset. | |

NAT5996: Volume not online.

| Text | ESY5996 Volume not online. |
|-------|--|
| Expl. | The specified volume is currently not available. |
| Actn. | Contact operator or systems programmer. |

NAT5997: Data set is not PDS or sequential.

| Text | ESY5997 Data set is not PDS or sequential. |
|-------|--|
| Actn. | No action is required. |

NAT5998: MEMBER not found.

| Text | ESY5998 MEMBER not found. | |
|-------|-------------------------------------|--|
| Expl. | The requested member was not found. | |
| Actn. | No action is required. | |

NAT5999: ENTIRE SYSTEM SERVER node :1: not active.

| Text | ESY5999 Entire System Server node :1: not active. |
|-------|---|
| Actn. | Contact operator or systems programmer. |

110 Natural System Error Messages 6001-6050

NAT6001: Internal error.

| Text | Internal error. |
|-------|--|
| Expl. | Error in internal routine which converts the format of fields. |
| Actn. | Contact Software AG support. |

NAT6003: Incompatible format types used for conversion.

| Text | Incompatible format types used for conversion. |
|------|--|
| | An attempt was made to convert a value from one format type to another, although conversions between these format types are not permitted. Note that (for the purposes of this error) the format of binary values up to length 4 (which can behave as integers) is considered distinct from the format of those of length 5 or greater (which cannot). |
| | See the Reference documentation for information on format type conversion compatibility. |

NAT6005: The list file is already open.

| Text | The list file is already open. |
|-------|---|
| Expl. | The list file is already open so it cannot be opened again. |
| Actn. | Close the list file. |

NAT6007: A program must have less than 40 DO ... DOEND loops.

| Text | A program must have less than 40 DO DOEND loops. |
|-------|--|
| Expl. | This program has at least 40 DO DOEND loops. |
| Actn. | Reduce the number of DO DOEND loops to less than 40. |

NAT6008: A program must have less than 5 SETTIME statements.

| Text | A program must have less than 5 SETTIME statements. |
|-------|---|
| Expl. | This program has at least 5 SETTIME statements. |
| Actn. | Reduce the number of SETTIME statements to less than 5. |

NAT6009: A program must perform less than 50 different subroutines.

| Text | A program must perform less than 50 different subroutines. |
|-------|---|
| Expl. | This program performs at least 50 different subroutines. |
| Actn. | Reduce the number of different subroutines performed to less than 50. |

NAT6010: Operation could not be completed. Memory allocation failed.

| Text | Operation could not be completed. Memory allocation failed. |
|-------|---|
| Expl. | Either the operating system is not configured correctly or there is not enough space on the disk for the system swap file. Another possibility is that the internal Natural buffer sizes USIZE and SSIZE are too small. Check the configuration settings of the operating system and correct them if necessary. Then check the available disk space for your system swap file. Additionally, check your USIZE and SSIZE settings within NATPARM and increase them if they seem to be too small. |
| Actn. | Contact your system administrator for further help. |

NAT6011: Limit of a GP structure exceeded: :1:

| Text | The limit of a GP structure is exceeded. |
|-------|---|
| | The follwing keywords identify the corresponding GP table structure OVFL©CT: statement block is too large (IF-THEN-ELSE, loop structure etc) OVFL©ADE: array definition structure too large OVFL©ATT: field attribute definitions too large |
| Actn. | Reduce appropiate structure in the Natural program. |

NAT6012: Internal buffer overflow.

| Text | Internal buffer overflow. |
|-------|------------------------------|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. |

NAT6013: Unexpected bufferpool error

| Text | Unexpected bufferpool error |
|-------|--|
| Expl. | Unexpected error when accessing the bufferpool. |
| | Restart Natural. If the error occurs again, ask your Natural system administrator to restart the Natural bufferpool. If this does not help, contact Software AG support. |

NAT6014: Timeout during lock of file

| Text | Timeout during lock of file |
|-------|---|
| Expl. | Locking timeout when trying to open a file. |
| Actn. | Retry the operation causing the error. |

NAT6015: WORK FILE number :1: not allocated/available.

| Text | WORK FILE number not allocated/available. |
|-------|---|
| - | Work files must have been previously defined by the Natural administrator. |
| Actn. | Make sure that the correct work file number has been used. If it has, contact your Natural administrator concerning work file status/usage. |

NAT6016: Batch input error: :1:.

| Text | Batch input error: |
|-------|---|
| Expl. | An INPUT statement in batch mode could not be completed. |
| | Make sure that the batch input file is accessible and contains all needed data. |

NAT6017: PC connection already open for workfile :1:

| Text | PC connection already open for workfile |
|-------|---|
| | A transfer to/from a PC was started, while another transfer is already active. There can be only one transfer active at any time. |
| Actn. | Make sure that a transfer is started only when no other one is active. |

NAT6018: Bad architecture record in the work file :1:, code :2:

| Text | Bad architecture record in the work file, code |
|-------|---|
| Expl. | While opening a portable work file, a bad architecture record was found. This error occurs if the work file is not a portable work file, or it has been modified. |
| Actn. | Make sure that the work file to be read is really a portable work file generated by Natural. If the problem persists, call Software AG support and mention the code which occurred. |

NAT6019: Number of fields wrong, file :1:, record :2:, code :3:.

| | · · · · · · · · · · · · · · · · · · · |
|-------|--|
| Text | Number of fields wrong, file, record, code |
| Expl. | While reading a portable work file, an invalid length was encountered. There are the following reasons for this error: 1 the number of fields doesn"t match with the READ WORK statement 2 the length field is corrupted Make sure that the fields in the READ WORK statement match the fields in the corresponding WRITE WORK statement (including the number of fields, scalar/array, etc.) the work file to be read is really a portable work file generated |
| Actn. | If the problem persists, call Software AG support and mention the code which occurred. |

NAT6020: Field mismatch, file :1:, record :2:, field :3:, code :4:.

Text Field mismatch, file ..., record ..., field ..., code

| While reading a portable work file, a field which was read does not |
|---|
| match the specification in the READ WORK statement. The work file |
| number, the record number, and the field number are shown in the error |
| message. Arrays count as one field here, and must match in the type and |
| the number of occurrences. |
| The code means: |
| 1 the field in the READ WORK stmt. is an array, different from file |
| record |
| 2 the field in the file record is an array, different from READ WORK |
| stmt. |
| 3 data type mismatch (e.g., ALPHA and FLOAT) |
| 4 length mismatch (field length in bytes) |
| 5 occurrences mismatch of an array field |
| Make sure that the programs match (the write and read work file). |
| |

NAT6021: Invalid record type, file :1:, record :2:, code :3:.

| Text | Invalid record type, file, record, code |
|-------|---|
| | While reading a portable work file, an invalid record type was found. If the record number and the code are zero, a file has been accessed, which is not a portable work file generated by Natural. |
| Actn. | Make sure that the work file to be read is really a portable work file generated by Natural. If the problem persists, call Software AG support and mention the code which occurred. |

NAT6022: Unexpected END OF FILE, work file :1:.

| Text | Unexpected END OF FILE, work file |
|-------|---|
| Expl. | There are 2 reasons for this error: While reading an unformatted work file, an end of file was reached. This can happen only if the file is truncated while Natural is reading it. While opening/reading a portable work file, an end of file was reached. |
| Actn. | Make sure that there is no other access to the unformatted work file. Make sure that the work file to be read is really a portable work file generated by Natural. If the problem persists, call SAG support. |

NAT6023: Illegal access of work file using dynamic variables

| Text | Illegal access of work file using dynamic variables |
|-------|---|
| - | Only the work file types UNFORMATTED and PORTABLE can be used with dynamic variables. |
| Actn. | Define the work file with type UNFORMATTED or PORTABLE. |

111 Natural System Error Messages 6051-6100

NAT6098: This statement is not implemented in the current version.

| Text | This statement is not implemented in the current version. |
|-------|--|
| Expl. | This statement is not available in the current version of Natural. |
| Actn. | Remove this statement from the program. |

NAT6099: File-open error :1: occurred for :2:.

| Text | File-open error occurred for |
|-------|---|
| Expl. | DU=ON causes dump-file generation into the directory defined in the Natural TMP directory option in the Natural Configuration utility. The "fopen" call failed with the error indicated. The dump file is either already open or the user has no write permission. |
| Actn. | See the operating-system manual for further information. |

NAT6100: Failed to open XREF dump file.

| Text | Failed to open XREF dump file. |
|-------|--|
| - | The XREF dump file is either already open or the user has no write permission. |
| Actn. | Close XREF dump file or set write permission. |

112 Natural System Error Messages 6101-6150

NAT6101: No name for UNIX shell defined, shell cannot be started.

| Text | No name for UNIX shell definded, shell cannot be started. |
|-------|--|
| Expl. | Shell name must be defined before shell can be started. |
| Actn. | Define shell name; name must be entered in natparm (NATENV). |

NAT6102: External editor specified in NATPARM.SAG could not be started.

| Text | External editor specified in NATPARM.SAG could not be started. |
|-------|--|
| - | You tried to call an external editor as program editor. The string defined in your parameter module is not a valid program name. |
| Actn. | Define editor name which can be found in your PATH. |

NAT6103: Registration of a clipboard format failed.

| Text | Registration of a clipboard format failed. |
|-------|---|
| Expl. | A clipboard format could not be registered. |
| | Retry the action with less programs running. If error occurs again contact Software AG Support. |

NAT6104: Posting a message failed.

| Text | Posting a message failed. |
|-------|---|
| Expl. | A message could not be posted. |
| Actn. | Retry the action with less programs running. If error occurs again contact Software AG Support. |

NAT6105: Registration of a window class failed.

| Text | Registration of a window class failed. |
|-------|---|
| Expl. | A window class could not be registered. |
| | Retry the action with less programs running. If error occurs again contact Software AG Support. |

NAT6106: Creation of a window failed.

| Text | Creation of a window failed. |
|-------|---|
| Expl. | A window could not be created. |
| | Retry the action with less programs running. If error occurs again contact Software AG Support. |

NAT6107: Command cannot be processed while debug mode is active.

| Text | Command cannot be processed while debug mode is active. |
|-------|---|
| | A Natural program or dialog is currently being executed in debug mode. In this situation, the entered command cannot be processed. |
| Actn. | Stop debug mode, and then enter the command again. |

NAT6110: Installation has no message text for the error with this number.

| Text | Installation has no message text for the error with this number. |
|-------|---|
| | Either the current version of the Natural message texts is not available at your installation, or the texts have been edited. |
| Actn. | Load the current version of the message texts. |

NAT6111: Natural cannot assign a table type to your program.

| Text | Natural cannot assign a table type to your program. |
|-------|---|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. |

NAT6112: This library is empty.

| Text | This library is empty. |
|-------|---|
| Expl. | You have logged on to a library which has no members. |
| Actn. | No action is required. |

NAT6113: Please enter source name.

| Text | Please enter source name. |
|-------|---|
| Expl. | It is necessary to supply the object name in the edit command if you do not use the Software AG Editor. |
| Actn. | Please retype the command, specifying the name of the object you wish to edit. |

NAT6120: The object is too big to read or edit in the Natural source area.

| Text | The object is too big to read or edit in the Natural source area. |
|-------|---|
| Expl. | An object must fit into the Natural source area before it can be read or edited. |
| 1 | Either clear the Natural source area, or use the NATPARM program to increase the size of the source area. |

NAT6121: Maximum source line number limit exceeded.

| Text | The generated object contains too many source code lines. |
|-------|---|
| | Natural source objects may only contain up to 9999 lines. The number of source lines needed to represent the current object exceeds this limit. |
| Actn. | Reduce the complexity of the object and retry the operation. |

NAT6130: Invalid version of generated program (object code).

| Text | Invalid version of generated program (object code). |
|-------|---|
| Expl. | The generated Natural program cannot be executed with the current execution environment. Please check the following conditions: - The version of a generated program must not be higher than the version of the execution environment. - Generated programs, which are catalogued with Natural version 4.1.1, and which contain SQL statements, may not be executed with Natural version 4.1.2 or higher |
| Actn. | Recatalog the objects before running the application. |

NAT6131: Error accessing temporary print file.

| Text | Error accessing temporary print file. |
|-------|--|
| | Natural is not able to generate a temporary print file in the directory which is specified by the <tmp@path> entry in Natural.INI</tmp@path> |
| Actn. | Check the path specified in Natural.INI |

NAT6132: Detected end of file while reading from standard input.

| Text | Detected end of file while reading from standard input. |
|-------|---|
| 1 1 | Natural detected an error condition while reading from the standard input terminal. |
| Actn. | Check that standard input stream for Natural delivers all neccessary characters. |

NAT6133: Program :1: is non-portable and cannot be imported.

| Text | Program is non-portable and cannot be imported. |
|-------|--|
| Expl. | The target platform for import was unable to process the format of the generated program. The generated program was created using a Natural version which does not support the generation of portable code; in addition, it may be that the program was created in an environment whose endian mode is incompatible with that of the target environment. |
| Actn. | Recatalog the program with a Natural version which does support portable code. |

NAT6134: Path length exceeds 255 characters.

| Text | Path length exceeds 255 characters. |
|-------|--|
| | A Natural object could not be imported/copied/moved/renamed. The operation was rejected because the resulting path name of the file in the target environment exceeded 255 characters. |
| Actn. | Retry the operation using shorter names. |

NAT6139: The parameter CO=ON is not supported.

| Text | The parameter CO=ON is not supported. |
|-------|--|
| | The parameter CO is turned on. This implemention of Natural does not support this feature. |
| Actn. | Please set CO to OFF. |

NAT6140: Dialog is already active.

| Text | Dialog is already active. |
|-------|---|
| Expl. | The current call to the dialog with given dialog ID cannot be executed because this dialog is already active. |
| Actn. | Check your calling structure to prevent invoking of an active dialog. |

NAT6141: Dialog is not defined.

| Text | Dialog is not defined. |
|-------|---|
| - | The call to the dialog cannot be executed because a dialog with this ID is not defined. |
| Actn. | Check the dialog ID you specified in the call. |

NAT6142: Structure of FILEDIR.SAG is invalid.

| Text | Structure of FILEDIR.SAG is invalid. |
|-------|--|
| Expl. | The structure of FILEDIR.SAG belongs to an earlier version of Natural and is not understood by this version. |
| Actn. | Use the FTOUCH utility with the convert option to convert FILEDIR.SAG to the new format. |

NAT6143: SyncSort error: status :1:, errno :2: occurred.

| Text | SyncSort error: status, errno occurred. |
|-------|---|
| Expl. | SyncSort was called for the Natural SORT statement and terminated with error codes. See your SyncSort documentatioin for the appropriate messages: - status is the return code of the function syncsort() and - errno is the standard "error number" variable"s value. |
| Actn. | See your SyncSort documentation for the appropriate action. |

NAT6144: Repository error: failed to back out transaction.

| Text | Repository error: failed to back out transaction. |
|-------|---|
| | The Natural repository was called by the Natural/C system file driver to back out a transaction and returned an error code. |
| Actn. | Check your environment. |

NAT6145: Repository error: transaction not completed successfully.

| Text | Repository error: transaction not completed successfully. |
|-------|--|
| Expl. | The repository was called by the Natural system file driver to end a transaction and returned an error code. |
| Actn. | Check your environment. |

NAT6146: Repository error: failed to start transaction.

| Text | Repository error: failed to start transaction. |
|-------|--|
| | The Natural repository was called by the Natural/C system file driver to start a transaction and returned an error code. |
| Actn. | Check your environment. |

NAT6147: Repository error: failed to delete object.

| Text | Repository error: failed to delete object. |
|-------|---|
| · · | The Natural repository was called by the Natural/C system file driver to delete an object and returned an error code. |
| Actn. | Check your environment. |

NAT6148: Repository error: failed to copy / move object.

| Text | Repository error: failed to copy or move object. |
|-------|--|
| | The Natural repository was called by the Natural/C system file driver to copy or to move an object and returned an error code. |
| Actn. | Check your environment. |

NAT6149: Locking conflict: failed to lock object.

| Text | Locking conflict: failed to lock object. |
|-------|--|
| | The Natural system file driver was called to lock an object, but the |
| | object to be locked was already locked by another user. |
| Actn. | Ask the other user to unlock the object. |

NAT6150: Locking conflict: object is not locked.

| Text | Locking conflict: object is not locked. |
|-------|--|
| Expl. | Either your networking software has an error or Natural attempted to release an object which it expected to be locked. |
| Actn. | Check your environment. |

113 Natural System Error Messages 6151-6200

NAT6151: Natural program error: Infinite recursion.

| Text | Natural program error: Infinite recursion. |
|-------|--|
| Expl. | The typical program in which this error occurs is a dialog containing the statement CLOSE DIALOG *DIALOG-ID for the CLOSE event. |
| Actn. | Check for recursive calls. |

NAT6152: Error while unlocking the object.

| Text | Error while unlocking the object. |
|-------|---|
| | Either your network software contains an error or Natural detected an internal error while unlocking a locked object. |
| Actn. | Check your environment. |

NAT6153: Error during lock of object.

| Text | Error during lock of object. |
|-------|---|
| | Either your networking software has an error or Natural detected an |
| | internal error while locking an object. |
| Actn. | Check your environment. |

NAT6154: Error closing file.

| Text | Error closing file. |
|-------|---|
| Expl. | Natural tried to close a file it has opened, but an error was returned by the operating system. |
| Actn. | Check your environment. If you cannot find the cause of the problem, contact Software AG support. |

NAT6155: Attempt to modify a read-only system file.

| Text | Attempt to modify a read-only system file. |
|-------|--|
| Expl. | Natural tried to open a file in the system file emulation for writing, but this system file was declared as read-only in the global config file. |
| Actn. | Either do not attempt to modify the system file or remove the read only flag from NATCONV.CFG |

NAT6156: Internal error in the system file emulation.

| Text | Internal error in the system file emulation. |
|-------|---|
| Expl. | Natural encountered an internal error in the system file emulation. |
| Actn. | Contact Software AG support. |

NAT6157: Dialog called from non-gui environment.

| Text | Dialog called from non-gui environment. |
|-------|---|
| Expl. | A gui environment is created when a dialog is started at level 1. Dialogs may then be called. A non-gui environment is active when: - a PROGRAM is started at level 1 or - Natural executes as server. It is not possible to call a dialog in a non-gui environment. |
| Actn. | Check your program and remove the calls to dialogs or start the program via a dialog. |

NAT6158: Failed to send object descriptor to repository.

| Text | Failed to send object descriptor to repository. |
|-------|---|
| | During a Natural / repository synchronize operation, Natural was not able to send a Natural object description to the repository. |
| Actn. | Check your environment |

NAT6159: Repository error: failed to delete library.

| Text | Repository error: failed to delete library. |
|-------|---|
| | The Natural repository was called by the Natural system file driver to delete a whole library and returned an error code. |
| Actn. | Check your environment. |

NAT6160: Repository error: failed to rename library.

| Text | Repository error: failed to rename library. |
|-------|---|
| · · | The Natural repository was called by the Natural system file driver to rename a library and returned an error code. |
| Actn. | Check your environment. |

NAT6161: Repository error: failed to save object.

| Text | Repository error: failed to save object. |
|-------|---|
| - | The Natural repository was called by the Natural system file driver to save an object and returned an error code. |
| Actn. | Check your environment. |

NAT6162: Repository error: failed to lock object

| Text | Repository error: failed to lock object. |
|-------|---|
| | The Natural repository was called by the Natural system file driver to lock an object and returned an error code. |
| Actn. | Check your environment. |

NAT6163: Repository error: failed to unlock object.

| Text | Repository error: failed to unlock object. |
|-------|---|
| | The Natural repository was called by the Natural system file driver to unlock an object and returned an error code. |
| Actn. | Check your environment. |

NAT6164: Object saved successfully. Repository information may be faulty.

| Text | Object saved successfully. Repository information may be faulty. |
|-------|--|
| Expl. | The Natural object was saved and/or cataloged successfully, but the object information stored in the Natural repository may be incorrect as a repository operation failed. |
| Actn. | Retry the operation. If the error reoccurs, contact your system administrator or Software AG support. |

NAT6200: Cannot insert global or application-independent variables.

| Text | Cannot insert global or application-independent variables. |
|-------|--|
| Expl. | This error can have two causes: |
| | a) out of memory |
| | b) table overflow |
| | Either the operating system is not configured correctly or there is not |
| | enough space on the disc for the system swapfile. |
| | All descriptions of application-independent variables are collected |
| | in a table of limited size. The table can overflow if an extremely |
| | large number of application-independent variables is created. The same |
| | situation applies to context variables. |
| | Check the configuration settings of the operating system and correct |
| | them if neccessary. Then check the available disk space for your system |
| | swapfile. |
| | Check the number of application-independent and context variables. |
| Actn. | Check the number of application-independent and context variables. Contact your system |
| | administrator. |

114 Natural System Error Messages 6201-6250

NAT6201: Initializing application-independent variables caused an error.

| Text | Initializing application-independent variables caused an error. |
|-------|--|
| - | Natural has encountered an internal error. It can also occur with context variables" initialization. |
| Actn. | Contact Software AG support. |

NAT6202: Error processing nested database loop in multi-fetch mode.

| Text | Error processing nested database loop in multi-fetch mode. |
|-------|--|
| Expl. | In a nested database-access loop, a database-modification statement attempts to modify a file that is read by an outer loop. |
| Actn. | Make sure that multi-fetch processing is switched off in the outer database loop(s). |

NAT6203: A domain error occurred in an arithmetic function.

| Text | A domain error occurred in an arithmetic function. |
|-------|--|
| | An argument to the function is outside the domain of the function. The function was called with an invalid floating-point operand. |
| Actn. | Correct error in program. |

NAT6204: An argument singularity error occurred in an arithmetic function.

| Text | An argument singularity error occurred in an arithmetic function. |
|-------|--|
| - | An argument to the function has an illegal value (for example, the value zero is passed to a function that requires a non-zero value). |
| Actn. | Correct error in program. |

NAT6205: Overflow occurred in an arithmetic function.

| Text | Overflow occurred in an arithmetic function. |
|-------|--|
| Expl. | The result of the function is too large to be represented. |
| Actn. | Correct error in program. |

NAT6206: A partial loss of significance occurred in arithmetic function.

| Text | A partial loss of significance occurred in arithmetic function. |
|------|---|
| Actn | . Correct error in program. |

NAT6207: A total loss of significance occurred in an arithmetic function.

| Text | A total loss of significance occurred in an arithmetic function. |
|-------|--|
| Expl. | The result of the function will be inaccurate. |
| Actn. | Correct error in program. |

NAT6208: Underflow occurred in an arithmetic function.

| Text | Underflow occurred in an arithmetic function. |
|-------|--|
| Expl. | The result of the function is too small to be represented. |
| Actn. | Correct error in program. |

NAT6209: Calling object no longer available when the call was returned.

| Text | Calling object no longer available when the call was returned. |
|-------|--|
| Expl. | An object has been called and has completed its processing. Processing cannot return to the the object which called it, because that object is available neither in the bufferpool nor in a library. |
| Actn. | Put the calling object, in cataloged form, into the current library, the system-library or the step library. |

NAT6210: Initializing a global data area caused an internal error.

| Text | Initializing a global data-area caused an internal error. |
|-------|---|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. |

NAT6211: Do not use DYNAMIC direction change in multi-fetch mode.

| Text | Do not use DYNAMIC direction change in multi-fetch mode. |
|-------|---|
| Expl. | The dynamic direction change can only be used when the corresponding processing loop is not executed in multi-fetch mode. |
| | Use a VARIABLE direction clause instead of a DYNAMIC direction clause if possible; or switch off multi-fetch mode for this statement with the MULTI-FETCH OFF clause. |

NAT6212: No more memory is available. Stack of subtasks has overflowed.

| Text | No more memory is available. Stack of subtasks has overflowed. |
|-------|---|
| | Either the operating system is not configured correctly or there is not enough space on the disc for the system swap file. |
| Actn. | Please contact your Administrator. |

NAT6213: No more memory available to process request for input or output.

| Text | No more memory available to process request for input or output. |
|-------|--|
| | Either the operating system is not configured correctly or there is not enough space on the disc for the system swapfile. Check the configuration settings of the operating system and correct them if neccessary. Then check the available disk space for your system swapfile. |
| Actn. | Please contact your system administrator for further help. |

NAT6214: No more memory is available to process a CALL statement.

| Text | No more memory is available to process a CALL statement. |
|-------|--|
| Expl. | Either the operating system is not configured correctly or there is not enough space on the disc for the system swapfile. Check the configuration settings of the operating system and correct them if neccessary. Then check the available disk space for your system swapfile. |
| Actn. | Please contact your system administrator for further help. |

NAT6215: The RET function applies only to programs that have been called.

| Text | The RET function applies only to programs that have been called. |
|-------|--|
| Expl. | The RET function was applied to a program that had not been called. |
| | Either insert a CALL to the program before the RET function, or remove the RET function. |

NAT6216: PF keys are set on too many levels of a program.

| Text | PF keys are set on too many levels of a program. |
|-------|--|
| | A structure is allocated to every level of a program where PF keys (program function keys) are set. All the structures for one program must fit in a segment of 64K. The structure for the current level does not fit in the segment for the current program. |
| Actn. | Set PF keys on fewer levels of the program. |

NAT6217: Processing an error at runtime caused an error in the processing.

| Text | Processing an error at runtime caused an error in the processing. |
|-------|---|
| Expl. | An error has occurred at runtime. Attempts to process the error and display an appropriate message have failed. |
| Actn. | Contact Software AG support because Natural could have an internal error. |

NAT6218: Text for months of the year not available in current language.

| Text | Text for months of the year not available in current language. |
|-------|--|
| Actn. | Ask your administrator if the language is available with your installation. If so, the administrator can check whether the appropriate text file is available and reload it, if it is corrupt. |

NAT6219: Text for days of the week not available in the current language.

| Text | Text for days of the week not available in the current language. |
|-------|--|
| Actn. | Ask your administrator if the language is available with your |
| | installation. If so, the administrator can check whether the appropriate |
| | text file is available and, if it is corrupt, can reload it. |

NAT6220: Internal error when reading work file.

| Text | Internal error when reading work file. |
|-------|---|
| Expl. | There is either a logical error in the work file or a physical error on the disc. |
| Actn. | Try to write the work file again. If this has no effect, change the disc. |

NAT6221: Internal error when writing work file.

| Text | Internal error when writing work file. |
|-------|---|
| Expl. | There is either a logical error in the work file or a physical error on the disc. |
| Actn. | Try to write the work file again. If this has no effect, change the disc. |

NAT6222: Fields in a WRITE WORK FILE statement too long.

| Text | Fields in a WRITE WORK FILE statement too long. |
|-------|---|
| | The total length of all the fields in a WRITE WORK FILE statement must be less than about 64K. For portable work files, the limit has been increased to about 2 GB. |
| Actn. | Apply the WRITE WORK FILE statement to fewer fields or shorter fields. |

NAT6223: A numeric field contains a non-numeric digit.

| Text | A numeric field contains a non-numeric digit. |
|------|--|
| | At least one of the digits in a numeric field is not a numeric digit and cannot be processed in a numeric context. |
| | Check if the numeric field in question is redefined as alphanumeric or binary. If so, make sure it contains only numeric digits. Otherwise, input data (from the database) could be erroneous. |

NAT6224: Internal error during loop processing.

| Text | Internal error during loop processing. |
|-------|--|
| Actn. | Contact Software AG support. |

NAT6225: Internal error during AT BREAK processing.

| Text | Internal error during AT BREAK processing. |
|-------|--|
| Actn. | Contact Software AG support. |

NAT6226: Internal error during RETRY processing.

| Text | Internal error during RETRY processing. |
|-------|---|
| Actn. | Contact Software AG support. |

NAT6227: Internal error.

| Text | Internal error. |
|-------|------------------------------|
| Actn. | Contact Software AG support. |

NAT6228: Internal error during processing of program levels.

| Text | Internal error during processing of program levels. |
|-------|---|
| Actn. | Contact Software AG support. |

NAT6229: Internal error during processing of program levels.

| Text | Internal error during processing of program levels. |
|-------|---|
| Actn. | Contact Software AG support. |

NAT6230: Internal error during loop processing.

| | Internal error during loop processing. |
|-------|--|
| Actn. | Contact Software AG support. |

NAT6231: Internal error during loop processing.

| | Internal error during loop processing. |
|-------|--|
| Actn. | Contact Software AG support. |

NAT6232: Internal error during processing of program levels.

| Text | Internal error during processing of program levels. |
|-------|---|
| Actn. | Contact Software AG support. |

NAT6233: Internal error during processing of program levels.

| | | Internal error during processing of program levels. |
|----|-----|---|
| Ac | tn. | Contact Software AG support. |

NAT6234: Internal error during processing of program levels.

| Text | Internal error during processing of program levels. |
|-------|---|
| Actn. | Contact Software AG support. |

NAT6235: Internal error during processing of operation stack.

| Text | Internal error during processing of operation stack. |
|-------|--|
| Actn. | Contact Software AG support. |

NAT6236: Internal error in interface to database server.

| Text | Internal error in interface to database server. |
|-------|---|
| Actn. | Contact Software AG support. |

NAT6237: Attempt to execute a database call to undefined database type.

| Text | Attempt to execute a database call to undefined database type. |
|-------|--|
| | Attempt to execute a database call to undefined database type. The database environment, which was defined when the Natural programs were catalogued, is different from the environment at execution time (e.g., database ID contains a wrong database type). Do one of the following: 1. Change the database assignment in the global CONFIG file and verify that the environment at execution time is the same as it was at catalog time. Use the NATPARM utility. |
| | 2. Recatalog the Natural programs if the database assignment has changed. |
| Actn. | See explanation |

NAT6238: Attempt to execute a database call to undefined database type.

| Text | Attempt to execute a database call to undefined database type. |
|-------|--|
| Expl. | The database environment, which was defined when the |
| | Natural programs were catalogued, is different |
| | from the environment at execution time (e.g., database ID |
| | contains a wrong database type). |
| | Do one of the following: |
| | 1. Change the database assignment in the global |
| | CONFIG file and verify that the environment |
| | at execution time is the same as it was at |
| | catalog time. |
| | Use the NATPARM utility. |
| | 2. Recatalog the Natural programs if the |
| | database assignment has changed. |
| Actn. | see explanation |

NAT6239: Internal error in interface to database server.

| Text | Internal error in interface to database server (replacement table). |
|-------|---|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. |

NAT6240: FETCH not allowed when dialogs are active.

| Text | FETCH not allowed when dialogs are active. |
|-------|--|
| Expl. | FETCH statements cannot be executed when dialogs are active. |
| Actn. | Remove the FETCH statement from the offending routine. |

NAT6241: Parameter access failed (not passed).

| Text | Parameter access failed (not passed). |
|-------|---|
| Expl. | Parameters are optional when they are passed to a dialog or if they are specified with the keyword OPTIONAL in the PDA for a CALLNAT or an external SUBROUTINE. The parameter(s), which have not been passed, cannot be accessed. If an access is tried, this error occurs. This is also true for a redefinition of a parameter. |
| Actn. | Check the parameter before accessing it. The statements "IF parameter SPECIFIED" or "IF parameter NOT SPECIFIED" can be used for this purpose. |

NAT6242: Value too large for index of dimension :1: (help on array field).

| Text | Value too large for index of dimension :1: (help on array field). |
|-------|--|
| Expl. | Environment, where the error occurrs: |
| | Help is requested for an INPUT field, where the field is an element |
| | of an array. |
| | When the parameters for the helproutine are generated, the indexes of |
| | the array element are passed together with the field contents. |
| | In this case, each index value must fit into an I2 variable, because the |
| | helproutines expect it as an I2. |
| | Reason why the error occurs: |
| | The given index does NOT fit into an I2 (overflow). |
| Actn. | Check the value of the index and make sure it will fit into an I2. |

NAT6243: CALLNAT from extern (3GL): too many parameters specified.

| Text | CALLNAT from extern (3GL): too many parameters specified. |
|-------|---|
| Expl. | A CALLNAT from outside of Natural, e.g. from a 3GL program, exceeds the maximum number of supported parameters. Due to performance optimizations, this limit is internally set to 4500. |
| Actn. | Reduce the number of parameters. If not possible, Contact Software AG support. |

NAT6244: Internal memory handling error.

| Text | Internal memory handling error. |
|-------|---|
| Expl. | This error is caused by incorrect system administration: a Natural object was changed or removed while Natural was running. That is why information about an active object could not be re-loaded. As the information is required to free active memory, Natural will run out of memory if this error occurs again and again. |
| Actn. | Shut the Natural session down, restart Natural. Change or remove Natural objects only when no Natural processes are running. |

NAT6245: Internal error: name :1: code :2: subcode :3:

| Text | Internal error: name code subcode |
|-------|---|
| - | Internal error. A name, code, and subcode |
| | are contained in the error message. |
| Actn. | Contact Software AG support and quote the complete error message. |

NAT6246: Invalid usage of ODA (Object Data Area).

| Text | Invalid usage of ODA (Object Data Area). |
|-------|---|
| Expl. | Object Data Areas are defined in methods to use class specific data. The methods must be activated with the Natural statements CREATE OBJECT and SEND METHOD. An attempt was made to activate a method, which uses an ODA, with a statement other than SEND METHOD (e.g., with the CALLNAT statement). |
| Actn. | Activate method using the SEND METHOD statement. |

NAT6247: Inconsistent structure of ODA in CLASS and METHOD.

| Text | Inconsistent structure of ODA in CLASS and METHOD. |
|-------|--|
| - | Object Data Areas (ODA) are defined in methods to use class specific data. Therefore, the structure of the ODA in the CLASS gp must match the structure of the ODA in a called METHOD. |
| Actn. | Ensure that the ODAs in CLASS and METHOD have the same number of parameters, format and length. |

NAT6248: Inconsistent structure of OPS in runtime and compiler

| Text | Inconsistent structure of OPS in runtime and compiler |
|-------|---|
| Expl. | To support the dynamic operands and operands of type ANY, the compiler has to generate the OPS structure into the gp. This generated OPS structure does not match with the OPS structure that is currently used by the runtime system. |
| Actn. | Ensure that the catalogued Natural program is version compatible to your currently used Natural version. Recatalogue the Natural program in case of incompatibility, else contact the Software AG Support. |

NAT6249: Internal Error during *LENGTH evaluation

| Text | Internal Error during *LENGTH evaluation |
|-------|--|
| | The internal structure for the *LENGTH evaluation is not available due to an internal error. |
| Actn. | Contact the Software AG support. |

NAT6250: Tried to apply a wrong value to *LENGTH

| Text | Tried to apply a wrong value to *LENGTH |
|-------|---|
| | The system variable *LENGTH may be modified in order to increase the used size of a dynamic variable. The following conditions must be kept, when *LENGTH is modified: 1. *LENGTH must not be set to a negative value 2. *LENGTH must not be set to a higher value than the allocated data space |
| Actn. | Check the conditions mentioned above. The Natural EXPAND statement may be used to increase the data space of a dynamic variable. |

115 Natural System Error Messages 6251-6300

NAT6251: Unknown OPD format found during dynamic operand processing

| Text | Unknown OPD format found during dynamic operand processing |
|-------|---|
| | Internal Error. An unknown Natural internal operand format was found during the processing of a dynamic variable. |
| Actn. | Contact the Software AG support. |

NAT6252: Resize of a non dynamic variable not possible

| Text | Resize of a non dynamic variable not possible |
|-------|--|
| | Internal Error. An invalid Natural internal operand format was found, when the value space for a dynamic variable was resized. |
| Actn. | Contact the Software AG support. |

NAT6253: Upper limit for dynamic variable exceeded

| Text | Upper limit for dynamic variable exceeded |
|-------|---|
| | During the reallocation of the value space of a dynamic variable, the upper limit of 1 GB was exceeded. |
| Actn. | Ensure that the data space of a dynamic variable stays below 1 GB. |

NAT6254: Invalid size value for REDUCE or EXPAND statement specified: :1:

| Text | Invalid size value for REDUCE or EXPAND statement specified: <size value=""></size> |
|-------|---|
| Expl. | A size value is specified with the REDUCE and the EXPAND statements, in order to reallocate the memory for the given dynamic operand. |
| | The following conditions must be kept for the size value: 1. The size value must not be negative |
| | 2. The size value must not exceed 1 Gigabyte |
| Actn. | The size value, which leads to the error, is displayed in the error message. Check the value against the conditions mentioned above. |

NAT6255: Invalid usage of dynamic variable with *length = 0

| Text | Invalid usage of dynamic variable with *length = 0 |
|-------|--|
| Expl. | An dynamic variable may have no data assigned, which means, the data length is 0. The content of the dynamic variable is then undefined. The usage of a dynamic variable without data leads to an error, when the following conditions are given: 1. The dynamic variable is used as operand in a logical condition criteria 2. The dynamic variable is used as source operand in an assignment. |
| Actn. | Check the usage of the dynamic variable and ensure, that there is data assigned to it. |

NAT6256: X-arrays cannot be specified in this context.

| Text | X-arrays cannot be specified in this context. |
|-------|---|
| Expl. | The specification of X-arrays is not allowed in this context. |
| Actn. | Check program and correct error. |

NAT6269: Natural application terminated abnormally.

| Text | Natural application terminated abnormally. |
|-------|---|
| Expl. | The Natural application was terminated abruptly due to a hardware or software exception (e.g., memory access violation or stack overflow). |
| Actn. | If you are running Natural interactively, it is recommended that you save any changes and restart Natural as soon as possible. For a resolution of the problem, please contact Software AG support. |

NAT6270: Natural Debugger could not be loaded.

| Text | Natural Debugger could not be loaded. |
|-------|---|
| Expl. | Insufficient memory or incorrect PATH setting. |
| Actn. | Check that the PATH environment variable contains the path to the directory where the Natural Debugger is located and check that you have enough memory to load the Natural Debugger. |

NAT6271: Internal error while creating debugger communication.

| | Text | Internal error while creating debugger communication. |
|---|-------|---|
| | Expl. | Internal error. |
| ĺ | Actn. | Contact Software AG support. |

NAT6272: Event not allowed.

| Text | Event not allowed. |
|-------|---|
| | You specified an event which is allowed only internally (e.g., OPEN, AFTER-OPEN). |
| Actn. | Correct the error by using a different event name. |

NAT6273: AIV/GP version compatibility error

| Text | AIV/GP version compatibility error |
|-------|--|
| Expl. | The current application uses new and old catalogued Natural objects. A new object has created an AIV which starts beyond 64kB. An old Natural object tries to access this AIV, but is limited to the 64kB size. |
| Actn. | You have two possibilities: a) Recatalog the object (preferred). b) Rearrange AIV creation. |

NAT6274: Parameter :1: is too long for this interface

| Text | Parameter is too long for this interface |
|-------|--|
| Expl. | The traditional form of the Natural CALL statement supports only lengths up to 65535. This length can be exceeded by LARGE and DYNAMIC variables. Use the INTERFACE4 option for the CALL statement and write a new user exit to use the new interface. Use a new name for the user exit so that a call to the old user exit with traditional syntax doesn"t crash. |
| | If this error occurs for a different statement, call Software AG support. |

NAT6275: The type of parameter :1: is illegal for this interface

| Text | The type of parameter is illegal for this interface |
|-------|---|
| Expl. | The statement CALL INTERFACE4 does not allow operands of type HANDLE. |
| Actn. | Remove the operands of type HANDLE from the CALL statement. |

NAT6276: Info: :1:.

| Text | Info: :1:. |
|------|---|
| - | Additional information concerning the following error message is displayed. |

NAT6296: Fatal error in the communication.

| Text | Fatal error in the communication. |
|-------|---|
| Expl. | Either the communication with the Entire Screen Builder or Web I/O Interface client was interrupted, or a Natural nucleus was started which is not meant to be started from a Unix terminal (e.g. Natural nucleus for Entire Screen Builder was used or the profile parameter WEBIO is ON). |
| Actn. | Either reconnect, or use a Natural nucleus which is intended for starting from a Unix terminal. |

NAT6300: The suppression option for a group must be blank.

| Text | The suppression option for a group must be blank. |
|-------|--|
| Expl. | A group can have only a level and a long-name. |
| Actn. | No action is required. The editor automatically corrects this error. |

116 Natural System Error Messages 6301-6350

NAT6301: A sub- or super-descriptor has an incorrect begin, end or length.

| Text | A sub- or super-descriptor has an incorrect begin, end or length. |
|-------|--|
| | A subdescriptor or superdescriptor must begin at a position greater than zero and less than the position at which it ends. The position at which it ends must not be greater than the length of the field on which it is based. The length of a superdescriptor must not be greater than 253. |
| Actn. | Enter values within the above ranges. |

NAT6302: A periodic group must be on Level 1.

| Text | A periodic group must be on Level 1. |
|-------|--|
| | Periodic groups must not be defined within groups or within other periodic groups; they must always be on Level 1. |
| Actn. | No action is required. The editor automatically corrects this error. |

NAT6303: The suppression option of a numeric field cannot be fixed format.

| Text | The suppression option of a numeric field cannot be fixed format. |
|-------|--|
| | A field with format N (Natural) or U (Adabas) cannot have a fixed length. Its suppression option must be N or blank. |
| Actn. | Enter a valid suppression option. |

NAT6304: Periodic group descriptors cannot have fixed-format suppression.

| Text | Periodic group descriptors cannot have fixed-format suppression. |
|-------|--|
| Expl. | A descriptor in a periodic group cannot have a fixed length. Its |
| | suppression option must be N or blank. |
| Actn. | Enter a valid suppression option. |

NAT6305: A floating-point number must have fixed-format suppression.

| Text | A floating-point number must have fixed-format suppression. |
|-------|--|
| | If the format of a field is G (Adabas) or F (Natural), its suppression option must be F. |
| Actn. | No action is required. The editor automatically corrects this error. |

NAT6306: Two fields of a database file the same Adabas short name.

| Text | Two fields of a database file have the same Adabas short name. |
|-------|---|
| | The short name of a field must have two characters and must begin with an alphabetic character. It must not be in the range from E0 to E9 and it must not be the same as the short name of any other field in the same file. |
| Actn. | Enter a different short name for one of the two fields. |

NAT6307: The level of a field in a database file must not be changed.

| Text | The level of a field in a database file must not be changed. |
|-------|---|
| Expl. | When a file contains data, the database file must not be changed. |
| | No action is required. The editor automatically corrects this error. To change the database file, you must first unload the data from the file. |

NAT6308: The format of a field in a database file must not be changed.

| Text | The format of a field in a database file must not be changed. |
|-------|---|
| Expl. | When a file contains data, the database file must not be changed. |
| Actn. | No action is required. The editor automatically corrects this error. To change the database file, you must first unload the data from the file. |

NAT6309: The type of a field in a database file must not be changed.

| Text | The type of a field in a database file must not be changed. |
|-------|--|
| Expl. | When a file contains data, the database file must not be changed. |
| Actn. | No action is required. The editor automatically corrects this error. |
| | To change the database file, you must first unload the data from the |
| | file. |

NAT6310: The long name of a field in a database file must not be changed.

| Text | The long name of a field in a database file must not be changed. |
|-------|---|
| Expl. | When a file contains data, the database file must not be changed. |
| | No action is required. The editor automatically corrects this error. To change the database file, you must first unload the data from the file. |

NAT6311: Short name of database file field must not be changed or deleted.

| Text | Short name of database file field must not be changed or deleted. |
|-------|--|
| Expl. | When a file contains data, the database file must not be changed. |
| Actn. | No action is required. The editor automatically corrects this error. |
| | To change the database file, you must first unload the data from the |
| | file. |

NAT6312: The length of a field in a database file must not be changed.

| | - |
|-------|---|
| Text | The length of a field in a database file must not be changed. |
| Expl. | When a file contains data, the database file must not be changed. |
| | No action is required. The editor automatically corrects this error. To change the database file, you must first unload the data from the file. |

NAT6313: An area number must be between 1 and 30.

| Text | An area number must be between 1 and 30. |
|-------|--|
| 1 | The area where a database file is created must have a number between 1 and 30. |
| Actn. | Enter an area number between 1 and 30. |

NAT6314: Sub- / super-descriptors must be at the end of the database-file.

| Text | Sub- / super-descriptors must be at the end of the database-file. |
|-------|--|
| Expl. | Fields that have descriptor S must be at the end of the database-file- description. |
| Actn. | Move all subdescriptors and superdescriptors to the end of the database- file. |

NAT6315: A field must have a level between 1 and 7. No level was entered.

| Text | A field must have a level between 1 and 7. No level was entered. |
|-------|--|
| Expl. | You have not entered a level for the field. |
| Actn. | Enter a level between 1 and 7. |

NAT6316: This field must have a format. No format was entered.

| Text | This field must have a format. No format was entered. |
|-------|--|
| - | A format must be entered for every field that is neither a group nor a |
| | periodic group. |
| Actn. | Enter a format for this field. |

NAT6317: You specified an invalid editing mask.

| Text | You specified an invalid editing mask. |
|-------|---|
| | Valid forms of editing mask are described in the Natural Reference documentation. |
| Actn. | Correct the editing mask. |

NAT6318: The length of a field with fixed-format suppression must be 4.

| Text | The length of a field with fixed-format suppression must be 4. |
|-------|--|
| Expl. | A field with the suppression option F has a length other than 4. |
| Actn. | Either change the length of the field to 4 or change the suppression option. |

NAT6319: Size of the internal Adabas buffer must be between 50K and 9999K.

| Text | Size of the internal Adabas buffer must be between 50K and 9999K. |
|-------|---|
| Expl. | A size outside this range was entered in the profile of a database. |
| Actn. | Enter a size between 50K and 9999K. |

NAT6320: A database with the proposed name already exists.

| Text | A database with the proposed name already exists. |
|-------|---|
| Expl. | Two databases cannot have the same name. |
| Actn. | Enter a different name for the new database. |

NAT6321: Subdescriptors and superdescriptors must be on Level 1.

| Text | Subdescriptors and superdescriptors must be on Level 1. |
|-------|--|
| Expl. | Subdescriptors and superdescriptors must not be defined within groups. |
| Actn. | No action is required. The editor automatically corrects this error. |

NAT6322: Level numbers of adjacent fields must not differ by more than 1.

| Text | Level numbers of adjacent fields must not differ by more than 1. |
|-------|--|
| | Adjacent fields should either be on the same level or, if one of them is a group, their levels should differ by one. |
| Actn. | Correct the level of at least one field. |

NAT6323: A group must contain at least one field.

| Text | A group must contain at least one field. |
|-------|---|
| Expl. | Every definition of a group must be followed by the definition of at least one field that belongs to the group. The level of the field or fields must be one greater than the level of the group. |
| | Insert after the group a definition of each field that belongs to the group. |

NAT6324: Two fields of a file have the same long name.

| Text | Two fields of a file have the same long name. |
|-------|--|
| Expl. | All fields of a file must have different long names. |
| Actn. | Enter a different long-name for one of the two fields. |

NAT6325: A field must have a long name. No long name was entered.

| Text | A field must have a long name. No long name was entered. |
|-------|--|
| Expl. | You have not entered a long name for the field. |
| Actn. | Enter a long name for the field. |

NAT6326: The file had one or more blank lines. They have been deleted.

| Text | The file had one or more blank lines. They have been deleted. |
|-------|--|
| Expl. | A file description must not have blank lines. |
| Actn. | No action is required. The editor automatically corrects this error. |

NAT6327: No database file :1: exists.

| Text | No database file exists. |
|-------|---|
| Expl. | Either the database file has never been created or it has been deleted. |
| Actn. | Use the Adabas-utilities to create the database file, then edit it to define your DDM-file. |

NAT6328: No file :1: exists.

| Text | No file exists. |
|-------|---|
| Expl. | The file named in the error message does not exist. |
| | Enter the correct name of the file. |
| | If the file name starts with D00nnn check if the correct DBID is |
| | entered. |
| | Check the directory specified in the environment variable DBENV |
| | or the directory which was specified as Adabas Utility parameter. |
| Actn. | see explanation |

NAT6329: An error occurred while file :1: was being read or written.

| Text | An error occurred while file was being read or written. |
|-------|---|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. |

NAT6330: Adabas short name cannot be generated.

| Text | Adabas short name cannot be generated. |
|-------|--|
| | All possible Adabas short names have been used in this database file so the editor cannot generate another one. |
| Actn. | Delete any fields that are no longer needed. |

NAT6331: Either a PF key has 2 functions, or one function has 2 PF keys.

| Text | Either a PF key has 2 functions, or one function has 2 PF keys. |
|-------|--|
| Expl. | Either two functions are assigned to the same PF key, or the same function is assigned to two PF keys. |
| Actn. | Assign each function to a separate PF key and do not assign more than one function to any PF key. |

NAT6332: A Field used in a sub- or superdescriptor cannot be changed.

| Text | A Field used in a sub- or superdescriptor cannot be changed. |
|-------|---|
| Expl. | A field cannot be changed if it is used in any subdescriptor or super- descriptor. |
| Actn. | Remove the field from every subdescriptor or superdescriptor that uses it. |

NAT6333: Number of field occurrences in a database file must not change.

| Text | Number of field occurrences in a database file must not change. |
|-------|--|
| Expl. | When a file contains data, the database file must not be changed. |
| Actn. | No action is required. The editor automatically corrects this error. |
| | To change the database file, you must first unload the data from the |
| | file. |

NAT6334: A subdescriptor or superdescriptor must use one or more fields.

| Text | A subdescriptor or superdescriptor must use one or more fields. |
|-------|---|
| 1 1 | A subdescriptor must use part of one field and a superdescriptor must use at least part of two or more fields. |
| Actn. | Enter the fields that are used by the subdescriptor or superdescriptor. |

NAT6335: No userviews are defined for this database file.

| Text | No userviews are defined for this database file. |
|-------|--|
| Actn. | No action is required. |

NAT6336: Specified file name does not exist in specified database.

| Text | Specified file name does not exist in specified database. |
|-------|---|
| Actn. | Specify the correct database and file. |

NAT6337: You must specify the database in which files are to be listed.

| Text | You must specify the database in which files are to be listed. |
|-------|--|
| Expl. | You did not specify a database so the files of a database could not be listed. |
| Actn. | Specify a database. |

NAT6338: Internal editor buffer overflow.

| Text | Internal editor buffer overflow. |
|-------|---|
| · · | When there are more than 1000 lines in your edit area, an internal editor buffer overflow occurs. |
| Actn. | Reduce the number of lines in the edit area. |

NAT6339: A DDM with that name exists already for DBID :1: with FNR :2:.

| Text | A DDM with that name exists already for DBID with FNR |
|-------|--|
| Expl. | DDM with the specified file number and database number cannot be |
| | generated, because a DDM with that name already exists. |
| Actn. | Choose a different DDM name. |

NAT6340: Suppression option of a field in a database file must not change.

| Text | Suppression option of a field in a database file must not change. | |
|-------|---|--|
| Expl. | When a file contains data, the database file must not be changed. | |
| Actn. | No action is required. The editor automatically corrects this error. To change the database file, you must first unload the data from the file. | |

NAT6341: No long names in the database file (upgrade active databases).

| Text | No long names in the database file (upgrade active databases). |
|-------|---|
| Expl. | This is the first time that an FDT has been edited since version 1.0.3 of the Adabas utilities was installed. In version 1.0.2, long names were stored in the database file. In version 1.0.3, they are stored in the database. |
| Actn. | Use the upgrade utility for active databases to copy the long names into the database. |

NAT6342: Some fields in the database do not have long-names.

| Text | Some fields in the database do not have long-names. | |
|-------|--|--|
| Expl. | An error occurred when the file was stored. | |
| | Edit the file, add the missing long names and save the file. If this has no effect, contact Software AG support because the DBMS could have an internal error. | |

NAT6343: The format of a DDM field must be numeric or alphanumeric.

| Text | The format of a DDM field must be numeric or alphanumeric. |
|-------|--|
| | An alphanumeric database file format can be changed to numeric, and numeric format can be changed to alphanumeric. No other change of format is allowed. |
| Actn. | No action is required. The editor automatically corrects this error. |

NAT6344: Size of Adabas communication area must be between 3K and 64K.

| Text | Size of Adabas communication area must be between 3K and 64K. |
|-------|--|
| - | The profile of a database has an invalid size for the Adabas communication area. |
| Actn. | Enter a size between 3K and 64K. |

NAT6345: Number of log commands must be: 0 if no log file; >=0 otherwise.

| Text | Number of log commands must be: 0 if no log file; >=0 otherwise. |
|-------|--|
| | The number of commands to be logged must be zero if there is no log file and must greater than or equal to zero if there is a log file. |
| Actn. | Enter a valid number of commands to be logged. |

NAT6346: The page size of an Adabas database must be 1K, 2K, 4K, or 8K.

| Text | The page size of an Adabas database must be 1K, 2K, 4K, or 8K. | |
|-------|--|--|
| Expl. | An invalid page size was entered when creating an Adabas database. | |
| Actn. | Enter a valid page size. | |

NAT6347: The file :1: failed to close.

| Text | The file failed to close. |
|-------|--|
| Expl. | Natural has encountered an internal error. |
| Actn. | Contact Software AG support. |

NAT6348: The file :1: failed to execute.

| Text | The file failed to execute. |
|-------|------------------------------|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. |

NAT6349: You have not specified a library. You must log on to a library.

| Text | You have not specified a library. You must log on to a library. |
|-------|---|
| | Before you can start working, you must log on to the library in which you wish to work. |
| Actn. | Log on to a library. |

NAT6350: A process failed to execute (termination code: :1:).

| Text | A process failed to execute (termination code:). |
|-------|--|
| Expl. | Natural has detected an error in the operating system. |
| | Look at the operating system documentation for the given error number and take the corrective action which is recommended there. |

117 Natural System Error Messages 6351-6400

NAT6351: A library :1: cannot be created.

| Text | A library cannot be created. |
|------|--|
| | Either the name of the library is invalid, or a directory cannot be created for the library because there is no more space for directories. |
| | Check that the name of the library is valid in Natural and, if necessary, correct it. If this has no effect, delete any directories that are no longer needed. |

NAT6352: Either the path is invalid or the directory does not exist.

| Text | Either the path is invalid or the directory does not exist. |
|-------|---|
| | Either you specified a path which is invalid in the operating |
| | system or no directory exists which matches your specification. |
| Actn. | Enter a valid path to a directory that exists. |

NAT6353: The database :1: (:2:) cannot be closed.

| Text | The database () cannot be closed. |
|-------|---|
| | The database whose name and number appear in the error message cannot be closed, because another process is using it. |
| Actn. | End the other process. |

NAT6354: WARNING: A field was truncated when it was loaded.

| Text | WARNING: A field was truncated when it was loaded. |
|-------|--|
| Expl. | Not all information in the field was loaded. |
| | If you do not wish to lose information, choose or create a field in the database which is long enough to hold all the information, and load the information into that field. |

NAT6355: The fields are not compatible with the Natural CONNECTION file.

| Text | The fields are not compatible with the Natural CONNECTION file. |
|-------|--|
| | The formats or lengths of the fields you specified do not match the fields in the Natural CONNECTION file. |
| Actn. | Specify the fields correctly. |

NAT6356: Function is not possible for the contents of the file.

| Text | Function is not possible for the contents of the file. |
|-------|---|
| - | Examples: The format of a file which is to be loaded into a database may be wrong. Or fields were selected to be loaded into a file but their |
| | lengths do not match the contents of the file. |
| Actn. | Check the format of the file and the lengths of the fields. |

NAT6357: Either one parameter or the number of parameters is invalid.

| Text | Either one parameter or the number of parameters is invalid. |
|-------|---|
| - | A valid name of a program has been entered with either an invalid parameter or an invalid number of parameters. |
| Actn. | Enter a valid number of valid parameters. |

NAT6358: A database file or DDM which is empty cannot be stored.

| Text | A database file or DDM which is empty cannot be stored. |
|-------|---|
| · · | An database file or DDM must have at least one field before it can be stored. |
| Actn. | Insert at least one field into the FDT or DDM. |

NAT6359: A file with the proposed name already exists.

| Text | A file with the proposed name already exists. |
|-------|---|
| Expl. | Two files cannot have the same name. |
| Actn. | Enter a different name for the new file. |

NAT6360: The length of a numeric field must be between 1 and 29 (15).

| Text | The length of a numeric field must be between 1 and 29 (15). |
|-------|---|
| | A numeric field has a length outside this range with Natural mode (Adabas mode for packed fields). |
| Actn. | Enter a length within this range. |

NAT6361: No more memory is available.

| Text | No more memory is available. |
|-------|--|
| Expl. | Either the operating system is not configured correctly or there is not enough space on the disc for the system swap file. Another possibility is that the internal Natural buffer sizes USIZE and SSIZE are too small. Check the configuration settings of the operating system and correct them if neccessary. Then check the available disk space for your system swap file. Additionally, check your USIZE and SSIZE settings within NATPARM and enlarge them if they seems to be too small. |
| Actn. | Please contact your system administrator for further help. |

NAT6362: A database with the proposed number already exists.

| Text | A database with the proposed number already exists. |
|-------|---|
| Expl. | Two databases cannot have the same number. |
| Actn. | Enter a different number for the new database. |

NAT6363: Please select all the elements of the group (one level higher).

| Text | Please select all the elements of the group (one level higher). |
|-------|---|
| | Normally, all elements of a group can be selected simply by marking the group. This group either contains a multiple field or is a periodic group. In either case, this group cannot be selected as a whole by marking it. Each element of the group must be marked individually. |
| Actn. | Mark all the elements of the group individually. |

NAT6364: The database must not be active when this function is executed.

| Text | The database must not be active when this function is executed. |
|-------|---|
| Expl. | This function requires that the database is not active. |
| Actn. | Close the database. |

NAT6365: Number of digits after the decimal point must be between 0 and 7.

| Text | Number of digits after the decimal point must be between 0 and 7. |
|-------|---|
| Expl. | For unpacked and packed numeric fields, the number of digits after the decimal point must be between 0 and 7. |
| Actn. | Enter a number within this range. |

NAT6366: The long name of part of a sub- or super- descriptor is invalid.

| Text | The long name of part of a sub- or super- descriptor is invalid. |
|-------|--|
| Expl. | A sub- or super- descriptor can only contain fields that have already been defined. |
| | Either define a field with this long name or remove this long name from the sub- or super- descriptor. |

NAT6367: The format type specified is not yet implemented.

| Text | The format type specified is not yet implemented. |
|-------|--|
| | The following format types are currently not implemented: C, D, I, L, T. |
| Actn. | Specify a format type that is implemented. |

NAT6368: The total field length of a file description must not exceed 64K.

| Text | The total field length of a file description must not exceed 64K. |
|-------|--|
| Expl. | The length of all fields defined in a Adabas file description must not exceed 64K. |
| Actn. | Decrease field length or number of fields in the database file description. |

NAT6369: The short name specified does not exist in the database file.

| Text | The short name specified does not exist in the database file. |
|-------|---|
| 1 1 | The short name for the DDM field does not exist in the corresponding database file. |
| Actn. | Select a new DDM field with the insert command. |

NAT6370: The specified file cannot be printed in this environment.

| Text | The specified file cannot be printed in this environment. |
|-------|--|
| | It is not possible to print the specified file, because you are not logged in a local drive. |
| | |
| Actn. | Logon to a local drive before starting Natural. |

NAT6371: No read/write access to this parameter file.

| Text | No read/write access to this parameter file. |
|------|--|
| | You tried either to read another user"s parameter file or to overwrite the default parameter file NATPARM. |
| | Logon with the correct user ID or contact your Natural administrator if changes in NATPARM are required. |

NAT6372: No descriptor allowed for multiple and periodic group fields.

| Text | No descriptor allowed for multiple and periodic group fields. |
|------|---|
| 1 1 | When a file contains data, it is not possible to define a descriptor for multiple and periodic group fields. |
| | No action is required. The editor automatically corrects this error. To change the database file, you must first unload the data from the file. |

NAT6373: Phonetic descriptors are not yet implemented.

| Text | Phonetic descriptors are not yet implemented. |
|-------|--|
| I | With the current PC-DBMS version, it is not possible to define phonetic descriptors. |
| Actn. | Select a valid descriptor option from the given choice list. |

NAT6374: Multiple field type not possible for normal database field.

| Text | Multiple field type not possible for normal database field. |
|-------|--|
| Expl. | When a database field is defined as a normal field, you cannot define it as a multiple field within the DDM. If you do so, a format buffer error occurs, when you try to read the contents of this field. |
| Actn. | No action is required. The editor automatically corrects this error. |

NAT6375: The DDM cannot be checked against the database file description.

| Text | The DDM cannot be checked against the database file description. |
|-------|---|
| | When you check a DDM, first the syntax of all DDM fields is checked. Then the DDM fields are checked against the corresponding file description (DBID and FNR within the header). The second check can only be performed when the database is of type Adabas and is active. |
| Actn. | Save the DDM, start the corresponding database and edit the DDM again. |

NAT6376: The category ISN must be in the range from 0 to 65535.

| Text | The category ISN must be in the range from 0 to 65535. |
|-------|--|
| | When you edit a DDM for Entire DB, the field name, file number and default sequence are represented by a category ISN, which must be in the range from 0 to 65535. |
| Actn. | Enter a number within this range. |

NAT6377: The DDM has a database type which cannot be processed.

| Text | The DDM has a database type which cannot be processed. |
|-------|--|
| Expl. | When you try to include a DDM as a template of a FDT, the database type of the DDM must be supported within the utility to process this DDM. For example, you try to include a DDM which is defined for Entire DB. This DDM cannot be included in the FDT editor, because the editor only processes Adabas FDTs. |
| Actn. | Specify a DDM with a supported database type. |

NAT6378: No further category ISNs can be generated.

| Text | No further category ISNs can be generated. |
|-------|---|
| Expl. | All category ISNs have been used in this database file. |
| Actn. | Delete fields which are no longer needed. |

NAT6379: One or more fields are missing within the DDM line.

| Text | One or more fields are missing within the DDM line. |
|-------|--|
| Expl. | The editor detected missing fields within the DDM description. |
| Actn. | Complete the information within the DDM line. |

NAT6380: No Adabas files are coupled with this DDM.

| Text | NO Adabas files are coupled with this DDM. |
|-------|--|
| Expl. | When scanning the DDM source no coupled file information was found. |
| Actn. | See Adabas documentation for further information about physical file coupling. |

NAT6381: Generation of DDM failed due to internal SQL error :1:.

| Text | Generation of DDM failed due to internal SQL error |
|-------|--|
| | The generation of a DDM from a SQL table was interrupted because an internal SQL error occurred. |
| Actn. | See your SQL documentation for further information about error codes. |

NAT6382: The DDM cannot be checked against the SQL table.

| Text | The DDM cannot be checked against the SQL table. |
|-------|---|
| | When you check a DDM, all DDM fields are checked for syntactical correctness. However, NO check against the SQL table can be made within the DDM editor, because after the generation of the DDM, the connection to the SQL database is closed. |
| Actn. | See your SQL documentation for further information about possible modifications. |

NAT6383: When editing SQL DDMs, no verification tests are performed.

| Text | When editing SQL DDMs, no verification tests are performed. |
|-------|---|
| Expl. | When you edit a DDM, all DDM fields are read into the edit area. However, NO check against the SQL table can be made within the DDM editor, because NO connection to the SQL database will be established. |
| Actn. | See your SQL documentation for further information about possible modifications. |

NAT6384: SQL table lists are not provided for this database system.

| Text | SQL table lists are not provided for this database system. |
|-------|---|
| | It is not possible to show the SQL table list, because Entire ACCESS |
| | does not provide catalog information for this database system. |
| Actn. | Enter the desired table owner and table name (no wildcards possible). |

NAT6385: No SQL tables found.

| Text | No SQL tables found. |
|------|--|
| | You specified a table owner/name combination, where no SQL tables exist or the SQL tables are not accessible. |
| | Try to show all SQL tables, which you can access by specifying wildcards. |

NAT6386: LOGON to SQL database failed.

| Text | LOGON to SQL database failed. |
|------|--|
| Exp | l. You specified an invalid user name or password. |
| Acti | n. Contact your database administrator. |

NAT6387: Function disallowed according to Predict definition.

| Text | Function disallowed according to Predict definition. |
|-------|---|
| | Within the Predict protection screen, the SYSDDM utility has been set to D (disallowed) or C (connected). |
| Actn. | See Predict Administration documentation for further information. |

NAT6388: The DDM could not be generated. Writing to a SPF session failed.

| Text | The DDM could not be generated. Writing to a SPF session failed. |
|-------|---|
| Expl. | When generating a DDM from a SQL table, the table data are buffered within a SPF data session. The write can fail if the internal editor buffer pool is full. |
| Actn. | Increase the number of logical files and/or buffer pool blocks within the editor profile. To make the settings active, terminate and restart Natural. |

NAT6389: SQL table name was invalid or an internal runtime error occurred.

| Text | SQL table name was invalid or an internal runtime error occurred. |
|------|--|
| | When generating a SQL based DDM, Natural callnats are executed. Within such a callnat, a Natural runtime error occurred. |
| | Try first to get a list of all available SQL tables and select one. If the problem persists, contact Software AG support. |

NAT6390: A work file name must not be longer than 253 characters.

| Text | A work file name must not be longer than than 253 characters. |
|-------|--|
| | The path and the name of a work file must not be longer than 253 characters. This error occurs also if the name contains blanks only. The length of the variable/constant may not exceed 1024 bytes. |
| Actn. | Choose a shorter name, e.g., using environment variables. |

NAT6391: A work file type must not be longer than 253 characters.

| Text | A work file type must not be longer than than 253 characters. |
|-------|--|
| | The type of a work file must not be longer than 253 characters. This error occurs also if the name contains blanks only. All correct types are shorter. The length of the variable/constant may not exceed 1024 bytes. |
| Actn. | Choose a correct type. |

NAT6392: The work file type :1: is unknown.

| Text | The work file type :1: is unknown. |
|-------|--|
| | The specified work file type is unknown. This usually means that it is incorrect. This error occurs also if the name contains blanks only. |
| Actn. | Choose a correct work file type. |

NAT6393: Illegal work file name

| Text | Illegal work file name extension ".NCF" |
|-------|---|
| 1 | The specified work file name is illegal because it conflicts with Entire Connection's format file. The format file has the extension .NCF, and so the specified work file name must not use the extension .NCF. |
| Actn. | Choose a correct work file name. |

NAT6394: The DBMS type in the DDM header is not defined.

| Text | The DBMS type in the DDM header is not defined. |
|------|---|
| - | Before a DDM is loaded into the editor and during CATALOG, it will be checked if the type of the DBID, which is defined in the global config file, matches the DBMS type in the DDM header. |
| | Define the correct DBMS type in the global config file, section "DBMS assignments". |

NAT6395: DDM generation failed due to wrong datatype combination.

| Text | DDM generation failed due to wrong datatype combination. |
|-------|--|
| Expl. | Natural does not support Oracle tables which contain both LONG or LONG RAW and BLOB or CLOB data types. |
| Actn. | Change the definition of the Oracle table so that it contains only column types LONG and LONG RAW, or BLOB and CLOB. |

NAT6396: The DDM source contains invalid field attribute(s).

| Text | The DDM source contains invalid field attribute(s). |
|-------|--|
| Expl. | The DBMS for which the DDM has been defined does not support the extended field attribute(s) found in the DDM source. |
| Actn. | Load the DDM into the editor. The DDM editor skips the unknown field attribute(s) when loading the DDM. Afterwards you can stow the DDM. |

NAT6400: The parameter :1: is not allowed in this context.

| Text | The parameter is not allowed in this context. |
|-------|--|
| Expl. | The parameter named in the error message has no meaning in this context. |
| 1 | Remove the parameter. If the parameters are correct and you are using |
| 1 | Software AG"s DBMS-services, contact Software AG support because Natural |
| | has encountered an internal error. |

118 Natural System Error Messages 6401-6450

NAT6401: The value of parameter :1: has an unpaired quotation mark.

| Text | The value of parameter has an unpaired quotation mark. |
|------|---|
| | The value of the parameter named in the error message has one quotation mark. The value of a parameter must be enclosed by either two quotation marks or none. |
| | Insert or remove a quotation mark. If the syntax is correct and you are using Software AG"s DBMS services, contact Software AG support because Natural has encountered an internal error. |

NAT6402: The value or name of a parameter is missing before a delimiter.

| Text | The value or name of a parameter is missing before a delimiter. |
|-------|---|
| Expl. | A delimiter should be preceded by either the name of a parameter or the value of a parameter. Either remove the delimiter, or insert the name or value of a parameter before it. |
| Actn. | If the syntax is correct and you are using Software AG's DBMS-services, contact Software AG support because Natural has an internal error. |

NAT6403: The parameter :1: is declared twice.

| Text | The parameter is declared twice. |
|-------|---|
| Expl. | The parameter named in the error message is declared twice. Two keywords may have been used which represent the same parameter. Alternatively, two database-numbers may have been used, although only one is allowed. |
| Actn. | Remove one of the parameters. If the parameters are correct and you are using Software AG"s DBMS-services, contact Software AG support because Natural has encountered an internal error. |

NAT6404: The equals sign is missing in the parameter :1:.

| Text | The equals sign is missing in the parameter |
|-------|---|
| Expl. | The parameter named in the error message must have an equals sign. |
| | Insert an equals sign in the parameter. If the equals sign is present and you are using Software AG"s DBMS services, contact Software AG support, because an internal error occurred. |

NAT6405: The value of the parameter :1: is missing.

| Text | The value of the parameter is missing. |
|-------|--|
| Expl. | The parameter named in the error message must have a value. |
| | Insert the value of the parameter. If the value is present and you are using Software AG"s DBMS-services, contact Software AG support because Natural has encountered an internal error. |

NAT6406: The parameter :1: requires a numeric value.

| Text | The parameter requires a numeric value. |
|-------|---|
| Expl. | The value of the parameter named in the error message must be numeric. |
| | Substitute a numeric value. If the value is numeric and you are using Software AG"s DBMS-services, contact Software AG support because Natural has encountered an internal error. |

NAT6407: This function requires the parameter :1:.

| Text | This function requires the parameter |
|-------|--|
| | A parameter required by this function is missing. The missing parameter is named in the error message. |
| Actn. | Add the missing parameter. If the parameters are correct and you are using Software AG"s DBMS-services, contact Software AG support because Natural has encountered an internal error. |

NAT6408: Two parameters are mutually exclusive. One is :1:.

| Text | Two parameters are mutually exclusive. One is |
|-------|---|
| Expl. | Two parameters are present which must not be used together. One of them is named in the error message. |
| Actn. | Remove one of the parameters. If the parameters are correct and you are using Software AG"s DBMS-services, contact Software AG support because Natural has encountered an internal error. |

NAT6409: A parameter, such as :1:, is missing.

| Text | A parameter, such as, is missing. |
|-------|--|
| Expl. | A parameter is missing. It can be the parameter named in the error message. Add either the parameter named in the error message or another appropriate parameter. |
| Actn. | If the parameters are correct and you are using Software AG"s DBMS-services, contact Software AG support because Natural has encountered an internal error. |

NAT6410: The environment variable DBENV for this database is missing.

| Text | The environment variable DBENV for this database is missing. |
|-------|---|
| Expl. | The environment variable DBENV contains the path of the database. Access to the database is not possible without DBENV. |
| Actn. | Add this environment variable to your environment for the database. |

NAT6411: The parameter :1: has an invalid value.

| Text | The parameter has an invalid value. |
|-------|--|
| Expl. | The value of the parameter named in the error message is not valid. |
| | Substitute a valid value. If the value is valid and you are using Software AG"s DBMS services, contact Software AG support because an internal error occurred. |

NAT6412: The database you specified does not have a profile.

| Text | The database you specified does not have a profile. |
|-------|---|
| Expl. | A database must have a profile. |
| Actn. | Create a profile for the database. |

NAT6413: No database exists which has the number you specified.

| Text | No database exists which has the number you specified. |
|-------|---|
| Expl. | No database exists with the given number. |
| Actn. | Correct the number of the database. |
| | If the error occurs during automatic start via Natural check if the |
| | the database(s) specified in the parameter SDB exist(s). |

NAT6414: No database exists which has the name you specified.

| Text | No database exists which has the name you specified. |
|-------|--|
| Expl. | No database exist with the given name. |
| Actn. | Correct the name of the database. |

NAT6415: Left parenthesis missing in value of parameter :1:.

| Text | Left parenthesis missing in value of parameter |
|------|--|
| | The value of the parameter named in the error message should be preceded by a left (opening) parenthesis. |
| | Insert an opening parenthesis. If the syntax is correct and you are using Software AG"s DBMS services, contact Software AG support because an internal error occurred. |

NAT6416: Right parenthesis missing in value of parameter :1:.

| Text | Right parenthesis missing in value of parameter |
|-------|---|
| Expl. | The value of the parameter named in the error message should be followed by a right (closing) parenthesis. |
| | Insert a closing parenthesis. If the syntax is correct and you are using Software AG"s DBMS-services, contact Software AG support because an internal error occurred. |

NAT6417: Right parenthesis or comma missing in value of parameter :1:.

| Text | Right parenthesis or comma missing in value of parameter |
|------|---|
| | The parameter named in the error message is part of a list, so its value should be followed by either a comma or a right (closing) parenthesis. |
| | Insert either a closing parenthesis or a comma, as appropriate. If the syntax is correct and you are using Software AG's DBMS services, contact Software AG support because an internal error occurred. |

NAT6418: This combination of parameters requires parameter :1:.

| Text | This combination of parameters requires parameter |
|-------|--|
| Expl. | The parameter named in the error message is required because another parameter is present. |
| Actn. | Add the required parameter. If the parameter is present and you are using Software AG"s DBMS services, contact Software AG support because an internal error occurred. |

NAT6419: File :1: failed to open.

| Text | File failed to open. |
|-------|--|
| Expl. | The file named in the error message cannot be opened, either because it does not exist, or because it is already open. |
| | Check that the file exists. If it does exist, check that it is closed. If the file is already open, close it. |

NAT6420: Option :1: is not yet implemented.

| Text | Option is not yet implemented. |
|-------|---|
| Expl. | The option named in the error message is not available in the current version of Natural. |
| Actn. | Either remove the option and circumvent the problem, or wait for a later version of the software. |

NAT6421: The format buffer has an error at position :1:.

| Text | The format buffer has an error at position |
|-------|--|
| Expl. | The FORMAT-BUFFER or FB parameter is wrong. |
| | Check the FORMAT-BUFFER parameter and correct the error. If the parameter is correct, and you are using Software AG"s DBMS services, contact Software AG support because an internal error occurred. |

NAT6422: :1: and another parameter have inconsistent values.

| Text | and another parameter have inconsistent values. |
|------|---|
| | The values of two parameters are inconsistent. One of these parameters is named in the error message. |
| | Check the parameters and correct the error. If the values are consistent, and you are using Software AG''s DBMS services, contact Software AG support because an internal error occurred. |

NAT6423: All fields already selected.

| Text | All fields already selected. |
|-------|---|
| Expl. | You cannot select more fields than there are. |
| Actn. | Do not select any more fields. |

NAT6424: Errors occurred during a general database report by Adabas.

| Text | Errors occurred during a general database report by Adabas. |
|-------|--|
| Expl. | One or more errors occurred while a general database report by Adabas was being executed. The next message explains why. |
| Actn. | Press the ENTER key to display the explanation. |

NAT6425: A report on database :1: (:2:) has errors.

| Text | A report on database () has errors. |
|-------|---|
| | One or more errors occurred while an Adabas report was being executed on the database whose name and number appear in the error message. The next message explains why. |
| Actn. | Press the ENTER key to display the explanation. |

NAT6426: A report on file :1: (:2:) has errors.

| Text | A report on file () has errors. |
|-------|---|
| | One or more errors occurred while an Adabas report was being executed on the file whose name and number appear in the error message. The next message explains why. |
| Actn. | Press the ENTER key to display the explanation. |

NAT6427: One or more errors occurred while Adabas was executing a report.

| Text | One or more errors occurred while Adabas was executing a report. |
|-------|--|
| Expl. | The next message explains why. |
| Actn. | Press the ENTER key to display the explanation. |

NAT6428: The paths to the database are inconsistent.

| Text | The paths to the database are inconsistent. |
|-------|--|
| | The path in the profile of the database is different from the path where the database is stored. This can happen if the COPY command of the operating system is used to move a database. |
| Actn. | To copy a database, only use Software AG"s DBMS-services. |

NAT6429: A path must not be longer than 64 characters.

| Text | A path must not be longer than 64 characters. |
|-------|---|
| Expl. | A path was specified with more than 64 characters. |
| Actn. | Do not use more than 64 characters to specify the path. |

NAT6430: One or more database files are missing.

| Text | One or more database files are missing. |
|-------|---|
| | Files may have been deleted inadvertently. Unless the message appears during a backup, each missing file has the extension .DD, .CRI or .PRF. |
| Actn. | Restore the missing files. |

NAT6431: No command files exist.

| Text | No command files exist. |
|-------|--|
| Expl. | Before the menu item "Start DBMS Cmd-File" can be used, command files must exist. Command files are generated after an ADAREP, ADALOAD or ADAUNLOAD command. |
| Actn. | Issue an ADAREP, ADALOAD or ADAUNLOAD command, then specify a command file. |

NAT6432: Subdescriptors and superdescriptors cannot be loaded or unloaded.

| Text | Subdescriptors and superdescriptors cannot be loaded or unloaded. |
|-------|---|
| Expl. | Subdescriptors and superdescriptors cannot be loaded or unloaded. |
| Actn. | Do not try to load or unload subdescriptors or superdescriptors. |

NAT6433: The specified format is incompatible with the existing format.

| Text | The specified format is incompatible with the existing format. |
|-------|---|
| Expl. | Only compatible formats can be specified when data is loaded or unloaded. The following formats are compatible: SPECIFIED FORMAT EXISTING FORMAT A (alphanumeric) with A, B B (binary) with A, B, P, U G (floating point) with A, B, G P (packed decimal) with A, B. P, U U (unpacked decimal) with A, B, P, U |
| Actn. | Specify a format that is compatible with the existing format. |

NAT6434: The number of occurrences is incompatible with the format-buffer.

| Text | The number of occurrences is incompatible with the format-buffer. |
|-------|---|
| | The number of occurrences of the next Natural CONNECTION data file must be less than or equal to the number of occurrences of the selected field. |
| Actn. | Correct the Natural CONNECTION data file. |

NAT6435: The parameter NOT all databases is not allowed with ALL files.

| Text | The parameter NOT all databases is not allowed with ALL files. |
|-------|--|
| | The parameter combination all databases = NO and all files = YES is not allowed by ADAREP. |
| Actn. | Choose another combination of parameters. |

NAT6436: One or more characters of the file name are invalid.

| Text | One or more characters of the file name are invalid. |
|-------|---|
| - | The file name contains one or more characters that are invalid in the operating system. |
| Actn. | Specify a file name that does not contain invalid characters. |

NAT6437: Either the file cannot be opened or the file is empty.

| Text | Either the file cannot be opened or the file is empty. |
|-------|--|
| Expl. | Either the file does not exist or the file is empty. |
| Actn. | Specify another file. |

NAT6438: The number of occurrences is invalid.

| Text | The number of occurrences is invalid. |
|-------|---|
| - | The number of occurrences must be between 1 and 199 for a multiple field and between 1 and 99 for a periodic group. |
| Actn. | Check the number of occurrences and correct the error. |

NAT6439: The database number must be in the range 1 - 254.

| Text | The database number must be in the range 1 - 254. |
|-------|---|
| - | A database must have a ID between 1 and 254. The database ID is outside this range. |
| Actn. | Enter a database number between 1 and 254. |

NAT6440: Database (:1:) already exists.

| Text | Database () already exists. |
|-------|--|
| | A database with the number or name already exists. |
| | Two databases cannot have the same number or name. |
| Actn. | Enter a different name or number for the database. |

NAT6441: No database (:1:) exists.

| Text | No database () exists. |
|-------|--|
| Expl. | No database exists which has the number or name you specified. |
| Actn. | Enter the correct name or number of the database. |

NAT6442: DB-file (:1:) already exists.

| Text | DB-file () already exists. |
|-------|--|
| Expl. | A database file with the number or name already exists. Two database files cannot have the same number or name. |
| Actn. | Enter a different name or number for the database file. |

NAT6443: No DB-file (:1:) exists.

| Text | No DB-file () exists. |
|-------|---|
| Expl. | No database file exists which has the number or name you specified. |
| Actn. | Enter the correct name or number of the database file. |

NAT6444: There is not enough space available on disk.

| Text | There is not enough space available on disk. |
|-------|---|
| I - | The function could not be executed successfully because there is not enough space available on disk / diskette. |
| | |
| Acth. | Increase free space on disk. |

NAT6445: The Natural extension buffer has an error at position :1:.

| Text | The Natural extension buffer has an error at position |
|------|--|
| | The buffer in which additional specifications for the fields in Natural format are made is erroneous. |
| | If the function was called from DBMS Services, contact Software AG, else check the contents of Natural extension buffer. |

NAT6446: Number of digits after a decimal point must be between 0 and :1:.

| Text | Number of digits after a decimal point must be between 0 and :1:. |
|-------|---|
| Expl. | For unpacked and packed numeric fields, the number of digits after the decimal point must be between 0 and the minimum of 7 or the length of the numeric field. |
| Actn. | Check the number of digits after the decimal point and correct the error. |

NAT6447: Overflow of floating point field occurs.

| Text | Overflow of floating point field occurs. |
|-------|---|
| Expl. | Overflow of floating point field occurs. |
| | On the PC, the maximum value for a floating-point field is bigger than on the Mainframe. This error occurs, when such a field is unloaded in Natural-CONNECTION format. |

NAT6448: Startup configuration of database erroneous.

| Text | Startup configuration of database erroneous. |
|-------|---|
| Expl. | The database mode (standalone, fileserver) and location do not match. In order to start a database in fileserver mode, the database must not be on the local PC. Drives equal / lower than "E" are expected to be local. |
| Actn. | Correct the startup configuration via the profile-function or copy the database to a location which belongs to the mode of the database. |

NAT6449: Source path and target path must be different.

| Text | Source path and target path must be different. |
|-------|--|
| 1 1 | In this function it is not allowed to use the same path for source and target. |
| Actn. | Use different source and target paths. |

NAT6450: All fields of the NCD file must be selected.

| Text | All fields of the NCD file must be selected. |
|-------|---|
| Expl. | You must select aso many fields as there are in the NCD file. |
| Actn. | Select all fields. |

119 Natural System Error Messages 6451-6500

NAT6498: Update operation rejected due to concurrent update.

| Text | Update operation rejected due to concurrent update. |
|-------|---|
| Expl. | An update operation could not be carried out for one of the following reasons: 1) A record to be updated is held by another user. 2) A referenced record is held by another user. 3) The "hold" queue is full. |
| Actn. | Try again later. If the "hold" queue is too small, contact your database administrator. |

NAT6500: Error Number :1: has occurred in the operating system.

| Text | Error Number has occurred in the operating system. |
|-------|--|
| Expl. | Natural has detected an error in the operating system. |
| Actn. | Contact Software AG support because there could be an internal error in Natural. |

120 Natural System Error Messages 6501-6550

NAT6501: Database :1: is not active or accessible.

| Text | Database is not active or accessible. |
|-------|---|
| Expl. | The specified database is currently not active, or, if you are working with a remote database, perhaps NET-WORK is not active. If the error occurs during automatic start via Natural, try to start the database in the foreground from the command prompt (use ADAMAIN DBID) to detect the original error. If you receive the message during execution of a Natural program, start the database you require. To determine this database check the DBIDs of the corresponding DDMs. If the error occurs when transaction data is being read or written, the database specified by the parameter UDB is required. |
| Actn. | see explanation |

NAT6502: The database call is too big to fit into the communication area.

| Text | The database call is too big to fit into the communication area. |
|-------|---|
| Expl. | Either the database call is bigger than the communication area or, if you are using either the standalone version or the file-server version of Natural, the communication area contains an earlier database call. This error can occur when an application (such as Natural or an Adabas utility) ends abnormally while waiting for an answer to the earlier database call. If you are using either the standalone version or the file-server version of Natural, restart the database. If this has no effect or you are using a different version of Natural, increase the size of the communication area and then restart the database. |
| Actn. | see explanation |

NAT6504: The database has failed to answer a call within the time allowed.

| Text | The database has failed to answer a call within the time allowed. |
|------|---|
| · · | The time limit for a database call has been reached and the database has not answered. |
| | Increase the size of the parameter that sets the time limit. If this has no effect, contact Software AG support because there could be an internal error in the database. |

NAT6506: There is no connection to the local routing table.

| Text | There is no connection to the local routing table. |
|------------|--|
| _ _ | The routing table contains information about open databases. The lack of a connection to it indicates an internal error. |
| Actn. | Contact Software AG support. |

NAT6507: The application has already accessed max. number of databases.

| Text | The application has already accessed max. number of databases. |
|-------|--|
| | In the current version there is a limit of 10 different databases which can be accessed by an application. |
| Actn. | Try to reduce the access to so many different databases. |

NAT6508: More databases available than can be returned by apcm*dbstate.

| Text | More databases available than can be returned by apcm@dbstate. |
|-------|---|
| | apcm@dbstate could not return all active databases because not enough space was allocated by the calling function. This message is for internal use only. |
| Actn. | Contact Software AG support. |

NAT6509: Database is already active.

| Text | Database is already active. |
|-------|--|
| Expl. | The database to be started is already active. |
| Actn. | Do not start a database which is already active. |

NAT6510: Database number invalid.

| Text | Database number invalid. |
|-------|--|
| Expl. | The database number must be in the range of 1 255. |
| | Check the database number and use only numbers which are within the range specified above. |

NAT6511: Internal error :1: in interface to database server.

| Text | Internal error in interface to database server. |
|-------|---|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. |

NAT6512: Internal error :1: in interface to TP monitor

| Text | Internal error in interface to TP monitor |
|-------|---|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. |

NAT6513: The TX interface is not available.

| Text | The TX interface is not available. |
|-------|---|
| | A database has been configured to use the TX interface for transaction control. However, the TX interface is not available. |
| Actn. | Make the TX interface available. |

NAT6514: Error :1: from call to TX interface.

| Text | Error from call to TX interface. |
|-------|---|
| | Each nonzero response code from the TP monitor is reported with this error message. |
| Actn. | For more information see: Your TP monitor documentation. |

NAT6515: ET data not available.

| Text | ET data not available. |
|-------|---|
| · · | ET data cannot be stored in databases, that are coordinated by a transaction monitor. |
| Actn. | Correct setting of ETDB or XADB parameter. |

NAT6520: No database found.

| Text | No database found. |
|-------|---|
| Expl. | No database found in the DBENV directory. |

NAT6521: Semaphore already exists.

| Text | Semaphore already exists. | |
|-------|---|--|
| Expl. | A semaphore which should be created exists already. Internal erro | |
| Actn. | Contact Software AG support. | |

NAT6523: Mode of a semaphore is invalid.

| Text | Mode of a semaphore is invalid. | |
|-------|--|--|
| Expl. | A semaphore is created with an invalid mode. Internal error. | |
| Actn. | Contact Software AG support. | |

NAT6524: There are too many semaphores open.

| Text | There are too many semaphores open. |
|-------|--|
| Expl. | All semaphores in the system are in use. |
| Actn. | Reduce active programs which use semaphores. |

NAT6525: Semaphore not found.

| Text | Semaphore not found. | |
|-------|---|--|
| Expl. | A semaphore which should be used is not there. Internal error | |
| Actn. | Contact Software AG support. | |

NAT6526: Error at semaphore setting.

| Text | Error at semaphore setting. |
|-------|------------------------------|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. |

NAT6527: Invalid handle of semaphore.

| Text | Invalid handle of semaphore. | |
|-------|---|--|
| Expl. | A semaphore was used with a wrong handle. Internal error. | |
| Actn. | Contact Software AG support. | |

NAT6528: Private semaphore could not be shared.

| Text | Private semaphore could not be shared. |
|-------|--|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. |

NAT6529: Too many semaphore requests.

| Text | Too many semaphore requests. |
|-------|--|
| Expl. | A semaphore is requested too many times. |
| | End the application and the database and try again. When the error occurs again, contact Software AG support. |

NAT6530: Semaphore timed out.

| Text | Semaphore timed out. |
|-------|--------------------------------------|
| Expl. | A semaphore timeout. Internal error. |
| Actn. | Contact Software AG support. |

NAT6531: Semaphore owner died.

| Text | Semaphore owner died. |
|-------|--|
| | A semaphore could not be accessed because the owner (i.e application or database) has died. To use the semaphore again all processes which use this semaphore must stop. |
| Actn. | End the application and the database. If this is not possible, reboot the system and try again. |

NAT6533: Internal semaphore error occurred.

| Text Internal semaphore error occurr | |
|--------------------------------------|------------------------------|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. |

NAT6542: shared memory segment with the specified name does not exist.

| Text | Shared memory segment with the specified name does not exist. |
|-------|---|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. |

NAT6543: Invalid handle of shared memory.

| Text | Invalid handle of shared memory. |
|-------|---|
| Expl. | A handle of a shared memory is invalid. Internal error. |
| Actn. | Contact Software AG support. |

NAT6544: No more memory available.

| Text | No more memory available. |
|-------|--|
| Expl. | Either the operating system is not configured correctly or there is not enough space on the disc for the system swap file. |
| Actn. | Check the configuration settings of the operating system and correct them if neccessary. Then check the available disk space for your system swap file. Please contact your system administrator for further help. |

NAT6545: Access to shared memory denied.

| Text | Access to shared memory denied. |
|-------|---|
| Expl. | A semaphore which should be created exists already. Internal error. |
| Actn. | Contact Software AG support. |

NAT6547: Shared memory already exists.

| Text | Shared memory already exists. |
|-------|---|
| Expl. | A shared memory which should be created exists already. Internal error. |
| Actn. | Contact Software AG support. |

NAT6549: There are too many shared segments open.

| Text | There are too many shared segments open. |
|-------|---|
| Expl. | All shared segments in the system are in use. |
| Actn. | Reduce active programs which use shared segments. |

NAT6550: Disc full.

| Text | Disc full. |
|-------|---|
| Expl. | The device is full. |
| | Increase free space on the hard disc / floppy. Check the disk space where the swap file is located. |

121 Natural System Error Messages 6551-6600

NAT6561: Wrong item name for DDE message used.

| Text | Wrong item name for DDE message used. |
|-------|---|
| Expl. | A DDE message was sent with a wrong item name. |
| | If only Software AG products are involved, contact Software AG support. Otherwise, check which item names are required. Adabas under Windows needs the item name "ADACALL". |

NAT6562: Wrong message format for DDE message used.

| Text | Wrong message format for DDE message used. |
|-------|---|
| Expl. | A DDE message was sent with a wrong message format. |
| | If only Software AG products are involved, contact Software AG support. Otherwise, check which message format is required. Adabas under Windows needs the format "Adabas@CALL". |

NAT6563: DDE message too long.

| Text | DDE message too long. |
|-------|--|
| | The DDE message is bigger than the communication area of the database. |
| Actn. | Increase the size of the communication area and then restart the database. |

NAT6564: Locking client DDE shared memory failed.

| Text | Locking client DDE shared memory failed. |
|-------|---|
| Expl. | Locking the shared memory for DDE which was allocated by the client failed. |
| Actn. | Contact Software AG support. |

NAT6565: Locking server DDE shared memory failed.

| Text | Locking server DDE shared memory failed. |
|-------|---|
| Expl. | Locking the shared memory for DDE which was allocated by the server failed. |
| Actn. | Contact Software AG support. |

NAT6566: The database cannot process more than one call at a time.

| Text | The database cannot process more than one call at a time. |
|-------|--|
| Expl. | The database receives a DDE message when no message is expected. Probably several applications want to send calls to the database. |
| | Assure that only one application sends DDE messages to the database at one point in time. |

NAT6570: Maximum number of conversations reached.

| Text | Maximum number of conversations reached. |
|-------|--|
| Expl. | An application or a database reached the maximum number of DDE conversations. Currently, 20 conversations are allowed. No more conversations can be initiated. |
| Actn. | Close applications or databases which are no longer needed to reduce the number of active conversations. |

NAT6571: Conversation already exists.

| Text | Conversation already exists. |
|-------|--|
| Expl. | The conversation to be added already exists. |
| Actn. | Contact Software AG support. |

NAT6572: Conversation does not exist.

| Text | Conversation does not exist. |
|-------|--|
| Expl. | The conversation to be deleted or used does not exist. |
| Actn. | Contact Software AG support. |

NAT6573: The database is not ready to process the db call.

| Text | The database is not ready to process the db call. |
|-------|---|
| Expl. | A database call cannot be executed because the database is going down or an internal error occurred. |
| 1 | Check if the database is still active. If not, restart the database and execute the application again, otherwise contact Software AG support. |

NAT6574: Shared memory cannot be allocated for DDE.

| Text | Shared memory cannot be allocated for DDE. |
|-------|---|
| Expl. | The allocation of shared memory neccessary for DDE failed. |
| Actn. | Check the configuration of the operating system and, if necessary, correct it. Otherwise, either make room on the hard disc for the swap-file, or move the swap file to another disc. |

NAT6575: Maximum number of applications reached.

| Text | Maximum number of applications reached. |
|-------|---|
| | Under WINDOWS, the maximum number of applications which are allowed to use ADALNK.DLL at the same time is reached. Currently, a maximum of 10 applications are allowed. |
| Actn. | Reduce the number of active applications. |

NAT6576: Application not found.

| Text | Application not found. |
|-------|--|
| Expl. | Internal information about an application was not found. |
| Actn. | Contact Software AG support. |

NAT6580: Creation of NATPAGE file failed.

| Text | Creation of NATPAGE file failed. |
|------|---|
| 1 1 | The file is already open or is protected against reading or writing, or an internal error occurred. |
| | Check whether the file is already open or is protected against reading or writing. If not, contact Software AG support. |

NAT6581: Current screen size differs from the stored size.

| Text | Current screen size differs from the stored size. |
|------|--|
| | The sizes of the screens which are stored in the NATPAGE file differ from the current screen size. It is not possible to display a NATPAGE screen or to add a new screen to the NATPAGE file. |
| | Either change the screen size so that the NATPAGE screens can be displayed or create a new NATPAGE file with %P. |

NAT6582: NATPAGE screen cannot be stored because of memory problems.

| Text | NATPAGE screen cannot be stored because of memory problems. |
|-------|---|
| | Either the operating system is not configured correctly or there is not enough space on the disc for the system swapfile. Check the configuration settings of the operating system and correct them if neccessary. Then check the available disk space for your system swap file. |
| Actn. | Please contact your system administrator for further help. |

NAT6583: NATPAGE internal error.

| Text | NATPAGE internal error. |
|-------|-------------------------------|
| Expl. | NATPAGE internal error found. |
| Actn. | Contact Software AG support. |

NAT6599: NETWORK error :1: occurred.

| Text | NETWORK error occurred. |
|-------|---|
| Expl. | Natural has detected a NETWORK error. |
| Actn. | See the description of the NETWORK error. |

NAT6600: You have pressed a key that has no function in this context.

| Text | You have pressed a key that has no function in this context. |
|-------|---|
| | The following keys are valid in this context: Page Up, Page Down, Cursor Up, Cursor Down, Home, End, function keys F1-F12 and the editing command keys. To display a list of the editing command keys, press the CHOICE key: F2. |
| Actn. | Press one of the keys named above. |

122 Natural System Error Messages 6601-6650

NAT6601: Not enough memory available to build internal editing structure.

| - | |
|-------|---|
| Text | Not enough memory available to build internal editing structure. |
| Expl. | Either the operating system is not configured correctly or there is not enough space on the disc for the system swapfile. Check the configuration settings of the operating system and correct them if neccessary. Then check the available disk space for your system swap file. |
| Actn. | Please contact your system administrator for further help. |

NAT6602: The data area in the source area has an incorrect format.

| Text | The data area in the source area has an incorrect format. |
|-------|---|
| Expl. | A data area is stored in a specific format. A data area with an incorrect format has been read into the source area. The data area has either been edited using a different editor or been imported from another computer without using the downloading utilities or migration utilities that are provided. |
| Actn. | Either recreate the data area or, if it has been imported from another computer, import it using the downloading utilities or migration utilities that are provided. |

NAT6603: No editing function is assigned to the function key you pressed.

| Text | No editing function is assigned to the function key you pressed. |
|-------|--|
| 1 1 | The editing functions that are available and the keys to which they are assigned are shown in the display at the bottom of the screen. |
| Actn. | Press a key to which an editing function is assigned. |

NAT6604: The requested function cannot be applied to this line.

| Text | The requested function cannot be applied to this line. |
|-------|--|
| Expl. | The requested function has no meaning for a line of this type. |
| Actn. | Either choose a function that applies to a line of this type, or use |
| | the function to a type of line to which it applies. |

NAT6605: Parsing a comment block of the data area editor caused an error.

| Text | Parsing a comment block of the data area editor caused an error. |
|-------|---|
| | After each CHECK, STOW or GEN command, the comment block of the data area editor is parsed to generate corresponding Natural code. The comment block in question does not have the format expected. This could be an internal error. |
| Actn. | Contact Software AG support. To continue working, delete the line where the error occurred, and type it in again. |

NAT6606: Invalid level number specified. Valid levels are 1 to 99.

| Text | Invalid level number specified. Valid levels are 1 to 99. |
|-------|---|
| Expl. | Valid level numbers are 1 to 99. |
| Actn. | Enter a valid level number. |

NAT6607: An invalid field type was entered.

| Text | An invalid field type was entered. |
|-------|---|
| Expl. | To display a list of valid field types, press the CHOICE key: F2. |
| Actn. | Enter a valid field type. |

NAT6608: Comment plus Array Definition/Parent Block/DDM too long (max 32).

| Text | Comment plus Array Definition/Parent Block/DDM too long (max 32). |
|-------|--|
| Expl. | 32 characters are available for each comment plus any corresponding Array Definition, Name of Parent Block or Name of DDM. On the current line, more than 32 characters have been entered. |
| Actn. | Shorten the comment so that it fits in the space available. |

NAT6609: The data area is too big to fit in the Natural source area.

| Text | The data area is too big to fit in the Natural source area. |
|-------|--|
| Expl. | There is not enough space in the source area to insert a field, to generate Natural code or to open a new source. Either the data area is bigger than 512K or several source areas are active. All objects currently in the source area must together not be bigger than the source area size which was defined using the NATPARM program. |
| Actn. | If the data area is bigger than 512K, either shorten it or divide it in two. Otherwise, close any other source texts that are open, or use the NATPARM program to increase the size of the source area. |

NAT6610: This line cannot be redefined.

| Text | This line cannot be redefined. |
|-------|---|
| Expl. | Perhaps the line contains a field that has already been redefined. |
| | Either choose a function that applies to a line of this type, or apply the redefinition to a line where it has meaning. |

NAT6611: New level must be greater than the level of the redefined field.

| Text | New level must be greater than the level of the redefined field. |
|-------|---|
| | When a field is redefined, the level of the new (redefining) fields must be greater than the level of the field that is redefined. |
| Actn. | Enter a level that is greater than the level of the redefined field. |

NAT6612: Not enough bytes remain for such a long redefining field.

| Text | Not enough bytes remain for such a long redefining field. |
|-------|---|
| I - | The number of bytes in all redefining fields cannot be greater than the number of bytes in the field that is redefined. |
| Actn. | Enter a number no greater than the number of bytes left. |

NAT6613: The name of the copycode is missing in the GENERATE command.

| Text | The name of the copycode is missing in the GENERATE command. |
|-------|---|
| Expl. | The GENERATE command requires the name of the copycode that is to be generated. |
| Actn. | Enter the name of the copycode. |

NAT6614: The number of parameters in the direct-command line is not valid.

| Text | The number of parameters in the direct-command line is not valid. |
|-------|---|
| Expl. | A valid command has been entered with the wrong number of parameters. |
| Actn. | Substitute correct parameters. |

NAT6615: This form of the SET command is not valid.

| Text | This form of the SET command is not valid. |
|-------|---|
| - | SET TYPE is the only SET command that is available in Natural. It must be followed by one of the following parameters: A, G, GLOBAL, L, LOCAL or PARAMETER. |
| Actn. | Substitute a valid form of the SET command. |

NAT6616: No more memory in the data area editor.

| Text | No more memory in the data area editor. |
|-------|---|
| Expl. | Either the operating system is not configured correctly or there is not enough space on the disc for the system swapfile. Check the configuration settings of the operating system and correct them if neccessary. Then check the available disk space for your system swap file. |
| Actn. | Please contact your system administrator for further help. |

NAT6617: DDM with the specified name does not exist.

| Text | DDM with the specified name does not exist. |
|-------|---|
| Expl. | A view must belong to an existing DDM. |
| Actn. | Enter the name of an existing DDM. |

NAT6618: An error occurred while a DDM was being processed.

| Text | An error occurred while a DDM was being processed. |
|-------|---|
| Expl. | The internal format of the DDM is inconsistent. |
| | Try to edit the DDM again. If this has no effect, contact Software AG support because there could be an internal error. |

NAT6619: The * command applies only to periodic groups or multiple fields.

| Text | The * command applies only to periodic groups or multiple fields. |
|-------|--|
| Expl. | The * command creates a counter field (c*). Only periodic groups and multiple fields can have counter fields. |
| Actn | Either choose a function that applies to a line of this type, or apply the * command to a line where it has meaning. |

NAT6620: WARNING: Changes in an array may cause errors in initialization.

| Text | WARNING: Changes in an array may cause errors in initialization. |
|-------|--|
| | When an array definition is added to a field, deleted or changed, errors may occur if an initial value has been specified for the field. |
| Actn. | Delete initial values or enter new initial values, if appropriate. |

NAT6622: A periodic group must have between 1 and 191 occurrences.

| Text | A periodic group must have between 1 and 191 occurrences. |
|-------|--|
| Expl. | A periodic group has a number of occurrences outside this range. |
| Actn. | Enter a number between 1 and 191. |

NAT6623: A multiple field must have between 1 and 191 occurrences.

| Text | A multiple field must have between 1 and 191 occurrences. |
|-------|--|
| Expl. | A multiple field has a number of occurrences outside this range. |
| Actn. | Enter a number between 1 and 191. |

NAT6624: The upper limit cannot be less than the lower limit.

| Text | The upper limit cannot be less than the lower limit. |
|-------|--|
| Expl. | The upper limit is less than the lower limit. |
| Actn. | Enter an upper limit that is at least as great as the lower limit. |

NAT6625: No editing block is defined in this data area.

| Text | No editing block is defined in this data area. |
|-------|---|
| Expl. | You cannot HIDE (unmark) an editing block until you have defined (marked) an editing block. |
| Actn. | Choose another function. |

NAT6626: The HIDE command is only valid within an editing block.

| Text | The HIDE command is only valid within an editing block. |
|-------|---|
| Expl. | This line is outside the editing block in this data area. |
| Actn. | Enter the HIDE command within the editing block. |

NAT6627: A block can only be defined in a global data area.

| Text | A block can only be defined in a global data area. |
|-------|--|
| 1 1 | A block can be defined in a data area only if the type of the data area is GLOBAL. |
| Actn. | Choose another function. |

NAT6628: Not enough memory to open the clipboard.

| Text | Not enough memory to open the clipboard. |
|-------|--|
| | Either the operating system is not configured correctly or there is not enough space on the disc for the system swap file. |
| Actn. | Check the configuration settings of the operating system and correct them if neccessary. Then check the available disk space for your system swap file. Please contact your system administrator for further help. |

NAT6629: Nothing to paste - clipboard is empty.

| Text | Nothing to paste - clipboard is empty. |
|-------|--|
| | Nothing has yet been copied into the clipboard. The clipboard is empty so nothing can be pasted from it. |
| Actn. | No action is required. |

NAT6630: The beginning of the editing block is not marked with X.

| Text | The beginning of the editing block is not marked with X. |
|-------|--|
| | The end of an editing block cannot be marked with Y until the beginning of the editing block is marked with X. |
| Actn. | Use the line command X to mark the beginning of the editing block. |

NAT6631: No Edit Mask or Initialisation allowed in a parameter data area.

| Text | No edit mask or initialisation allowed in a parameter data area. |
|-------|--|
| Expl. | You cannot specify an edit mask or an initstring in a parameter data area. |
| Actn. | Erase edit mask or initialisation. |

NAT6632: Constants must not be defined in parameter data areas.

| Text | Constants must not be defined in a parameter data areas. |
|-------|--|
| · · | A constant can be defined in a data area only if the type of the data area is GLOBAL or LOCAL. |
| Actn. | Choose another function. |

NAT6633: The generation of a global unique ID failed.

| Text | The generation of a global unique ID failed. |
|-------|---|
| 1 1 | A new global unique ID was definded, but NaturalX failed to provide it. |
| Actn. | Check your NaturalX installation. |

NAT6634: A value clause may only be specified within parameter data areas.

| Text | A value clause may only be specified within parameter data areas. |
|-------|--|
| Expl. | With this option, it is possible to pass parameters to a subprogram or subroutine by value. That means, the actual parameter values (instead of their addresses) are passed to the subprogram or subroutine. Consequently, the fields in the subprogram or subroutine need not have the same format and length as the CALLNAT or PERFORM parameters. |
| Actn. | You may not specify the value clause for local and global data areas. |

NAT6635: An invalid field value clause was entered.

| Text | An invalid field value clause was entered. |
|-------|---|
| | To display a list of valid field value clauses, press the CHOICE key: F2. |
| Actn. | Enter a valid field value clause. |

NAT6636: Length of a large alphanumeric or binary field must be less 1 GB.

| Text | Length of a large alphanumeric or binary field must be less 1 GB. |
|-------|---|
| Actn. | Enter a valid length for variable. |

123 Natural System Error Messages 6651-6700

NAT6700: File with the specified number does not exist.

| Text | File with the specified number does not exist. |
|-------|--|
| Expl. | Internal error. Check the number you specified. If it is correct and you are using Software AG"s DBMS services, contact Software AG support because an internal error occurred. To continue working, restart the DBMS services. If this has no effect, restart the database. |
| Actn. | see explanation |

124 Natural System Error Messages 6701-6750

NAT6701: File number that is required in this database call is missing.

| Text | File number that is required in this database call is missing. |
|-------|---|
| | This database call must specify a file number. Check that you specified a file number. If you did and you are using Software AG"s DBMS services, contact Software AG support because an internal error occurred. To continue working, restart the DBMS services. If this has no effect, restart the database. |
| Actn. | see explanation |

NAT6702: This database call specifies neither file name nor file number.

| Text | This database call specifies neither file name nor file number. |
|-------|--|
| Expl. | This database call must specify either a file name or a file number. Check that you specified either a file name or a file number. If you did and you are using Software AG"s DBMS services, contact Software AG support because an internal error occurred. To continue working, restart the DBMS services. If this has no effect, restart the database. |
| Actn. | see explanation |

NAT6703: Due to an internal error, no file can be created.

| Text | Due to an internal error, no file can be created. |
|-------|---|
| Expl. | Internal error. |
| | Contact Software AG support. To continue working, restart the DBMS services. If this has no effect, restart the database. |

NAT6704: Function cannot be executed because the file contains records.

| Text | Function cannot be executed because the file contains records. |
|-------|---|
| Expl. | The file must be empty to execute this function. |
| Actn. | Delete the records from the file and execute this function again. |

NAT6706: An area (physical file) with the specified number already exists.

| Text | An area (physical file) with the specified number already exists. |
|-------|--|
| | Internal error. Software AG"s DBMS services tried to create a new area (physical file) with a number that is already in use. |
| Actn. | Contact Software AG support. To continue working, restart the DBMS services. If this has no effect, restart the database. |

NAT6707: Due to an internal error, no descriptor can be created.

| Text | Due to an internal error, no descriptor can be created. |
|-------|---|
| Expl. | Internal error. |
| | Contact Software AG support. To continue working, restart the DBMS services. If this has no effect, restart the database. |

NAT6708: Due to an internal error, a descriptor cannot be found.

| Text | Due to an internal error, a descriptor cannot be found. |
|-------|---|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. To continue working, restart the database. |

NAT6709: Due to an internal error, a field cannot be found.

| Text | Due to an internal error, a field cannot be found. |
|-------|---|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. To continue working, restart the database. |

NAT6710: A field with incompatible characteristics already exists.

| Text | A field with incompatible characteristics already exists. |
|-------|--|
| | The FDT is being restored for a file which already contains data. A field already exists whose characteristics are incompatible with those of the corresponding new field. |
| Actn. | Compare the old FDT with the new FDT and correct the error. |

NAT6711: Attempt to build too many descriptor fields of an existing file.

| Text | Attempt to build too many descriptor fields of an existing file. |
|-------|--|
| Expl. | Not more than 14 fields can be used to build descriptors at the same |
| | time. |
| | For example, this error would occur if you tried to create |
| | four superdescriptors at the same time, each made up of four fields. |
| Actn. | Build the descriptors in several steps. |

NAT6712: Looking for the number of records in a file caused an error.

| Text | Looking for the number of records in a file caused an error. |
|-------|---|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. To continue working, restart the database. |

NAT6713: Due to an internal error, the number of fields is incorrect.

| Text | Due to an internal error, the number of fields is incorrect. |
|-------|--|
| Expl. | Internal error when storing an FDT. |
| 1 | Contact Software AG support. To continue working, restart the DBMS services. |

NAT6714: Due to an internal error, the number of the area is missing.

| Text | Due to an internal error, the number of the area is missing. |
|-------|--|
| Expl. | Internal error. |
| | Contact Software AG support. To continue working, restart the DBMS services. |

NAT6715: Due to an internal error, the format of a field is incorrect.

| Text | Due to an internal error, the format of a field is incorrect. |
|-------|---|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. To continue working, restart the DBMSservices. |

NAT6716: Due to an internal error, the length of a field is incorrect.

| Text | Due to an internal error, the length of a field is incorrect. |
|-------|---|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. To continue working, restart the DBMSservices. |

NAT6717: The sequence of existing fields in the file must not be changed.

| Text | The sequence of existing fields in the file must not be changed. |
|-------|---|
| Expl. | If a file contains data, you must not change the sequence of existing fields. |
| Actn. | Compare the old FDT with the new FDT and correct the error. |

NAT6718: The structure of the internal ET data is inconsistent.

| Text | The structure of the internal ET data is inconsistent. |
|-------|--|
| | ET data is either corrupt or missing, perhaps because the database was created using a pre-beta version of the software. |
| Actn. | Contact Software AG support. |

NAT6719: A normal field must not be unique.

| Text | A normal field must not be unique. |
|-------|---|
| | The unique option is only valid for descriptors, not for normal fields. |
| Actn. | Check FDT and correct error. |

NAT6720: A multiple field / field in pe-group must not become descriptor.

| Text | A multiple field / field in pe-group must not become descriptor. |
|-------|---|
| | If a file contains data, it is not possible to turn a multiple value field or a field in a periodic group into a descriptor. This is valid for new fields, too. |
| Actn. | Check FDT and correct error. |

NAT6750: First page of .DD file not available.

| Text | First page of .DD file not available. |
|-------|--|
| Expl. | Internal error when creating a database. |
| Actn. | Internal error. Contact Software AG support. |

125 Natural System Error Messages 6751-6800

NAT6751: Page size lower than 512 bytes.

| Text | Page size lower than 512 bytes. |
|-------|--|
| Expl. | The page size of the database is lower than the minimum limit. |
| | If error occurs using the Database Services, contact Software AG support, else check the parameter PAGE-SIZE of the program ADACREA. |

NAT6752: Due to an internal error an area could not be created.

| Text | Due to an internal error an area could not be created. |
|-------|--|
| Expl. | Internal error when creating an area. |
| Actn. | Contact Software AG support. |

NAT6753: Due to an internal error a file could not be created.

| Text | Due to an internal error a file could not be created. |
|-------|---|
| Expl. | Internal error when storing a FDT. |
| Actn. | Contact Software AG support. |

NAT6754: Due to an internal error a file description could not be fetched.

| Text | Due to an internal error a file description could not be fetched. | |
|-------|---|--|
| Expl. | Internal error when reading a FDT. | |
| Actn. | Contact Software AG support. | |

NAT6755: Due to an internal error a field could not be inserted.

| Text | Due to an internal error a field could not be inserted. |
|-------|---|
| Expl. | Internal error when storing a FDT. |
| Actn. | Contact Software AG support. |

NAT6756: Due to an internal error an area description couldn"t be fetched.

| Text | Due to an internal error an area description couldn"t be fetched. |
|-------|---|
| Expl. | Internal error when reading an area description. |
| Actn. | Contact Software AG support. |

NAT6757: Due to an internal error a descriptor could not be inserted.

| Text | Due to an internal error a descriptor could not be inserted. | |
|-------|--|--|
| Expl. | Internal error when storing a FDT. | |
| Actn. | Contact Software AG support. | |

NAT6758: Due to an internal error a field description couldn"t be fetched.

| Text | Due to an internal error a field description couldn"t be fetched. | |
|-------|---|--|
| Expl. | Internal error when reading a FDT. | |
| Actn. | Contact Software AG support. | |

NAT6759: Due to an internal error a descriptor could not be fetched.

| Text | Due to an internal error a descriptor could not be fetched. |
|-------|---|
| Expl. | Internal error when reading a FDT. |
| Actn. | Contact Software AG support. |

NAT6760: Due to internal error part of a descriptor couldn"t be inserted.

| Text | Due to internal error part of a descriptor couldn"t be inserted. | |
|-------|--|--|
| Expl. | Internal error when storing a FDT. | |
| Actn. | Contact Software AG support. | |

NAT6761: Due to an internal error a field description couldn"t be changed.

| Text | Due to an internal error a field description couldn"t be changed. | |
|-------|---|--|
| Expl. | Internal error when changing a FDT. | |
| Actn. | Contact Software AG support. | |

NAT6782: Invalid handle used. Internal error of backup/restore.

| Text | Invalid handle used. Internal error of backup/restore. | |
|-------|---|--|
| Expl. | An invalid handle was used. Internal error of backup/restore. | |
| Actn. | Contact Software AG support. | |

NAT6783: The file for the backup is in read-only mode.

| Text | The file for the backup is in read-only mode. |
|------------|--|
| _ _ | The file should be written to a read-only medium or the file is write-protected. |
| Actn. | Check the backup medium and the directory for backup and correct error. |

NAT6784: The file for the restore is in read-only mode.

| Text | The file for the restore is in read-only mode. |
|-------|--|
| - | The file should be written to a read only medium or the file is write-protected. |
| Actn. | Check the restore medium and the directory for restore and correct error. |

NAT6785: Internal error of backup/restore.

| Text | Internal error of backup/restore. |
|-------|-----------------------------------|
| Expl. | Internal error. |
| Actn. | Contact Software AG support. |

NAT6786: No R-lock could be set on file for backup / restore.

| Text | No R-lock could be set on file for backup / restore. |
|------------|--|
| 1 1 | Due to an update conflict no R-lock could be set for backup / restore. |
| Actn. | Check that no other application uses the database for update. |

NAT6787: No X-lock could be set on file for backup / restore.

| Text | No X-lock could be set on file for backup / restore. |
|-------|--|
| 1 1 | Due to an update conflict no X-lock could be set for backup / restore. |
| Actn. | Check that no other application uses the database. |

NAT6788: It is not possible to lock all files for backup / restore.

| Text | It is not possible to lock all files for backup / restore. |
|-------|--|
| | Due to an update conflict not locks could be set for backup / restore. |
| Actn. | Check that no other application uses the database. |

NAT6800: The device specified is not valid.

| Text | The device specified is not valid. |
|-------|---|
| - | If the device is a floppy disc, it must be either A or B. If it is a hard disc, it must be either C or another alphabetic character that has been defined for the hard disc or for part of the hard disc. |
| Actn. | Enter a valid character. |

126 Natural System Error Messages 6801-6850

NAT6801: The disc must be formatted and must not be write-protected.

| Text | The disc must be formatted and must not be write-protected. |
|-------|--|
| | The disc in the drive is either unformatted, or formatted but write-protected. |
| Actn. | Use another disc which is formatted and not write-protected. |

NAT6802: The specified path does not exist.

| Text | The specified path does not exist. |
|-------|--|
| Expl. | The path must exist in the environment for correct processing. |
| Actn. | Specify a path that exists. |

NAT6803: Import failed: the object(s) are not known to Natural.

| Text | Import failed: the object(s) are not known to Natural. |
|-------|---|
| Expl. | The import failed due to an internal error in the FTOUCH routine. |
| Actn. | Contact Software AG support. |

NAT6804: Invalid name for object.

| Text | Invalid name for object. |
|-------|--|
| Expl. | This name is not specified for an object or does not exist in a library. |
| Actn. | Check the name of the object. |

NAT6805: A file cannot be created or written because it cannot be opened.

| Text | A file cannot be created or written because it cannot be opened. |
|------|--|
| | The file is already open or is write-protected, or an internal error occurred. |
| | Check whether the file is already open or write-protected. If not, contact Software AG support. |

NAT6806: Due to an error in the write buffer, a file cannot be written.

| Text | Due to an error in the write buffer, a file cannot be written. |
|-------|--|
| Expl. | Error in write buffer. |
| | Try to write the work file again. If this has no effect, contact Software AG support. |

NAT6807: A source file cannot be deleted.

| Text | A source file cannot be deleted. |
|-------|---|
| Expl. | Either the file is write-protected, or an internal error occurred. |
| | Check whether the file is write-protected. If it is not, contact Software AG support. |

NAT6808: A cataloged file cannot be deleted.

| Text | A cataloged file cannot be deleted. |
|-------|---|
| Expl. | Either the file is write-protected or an internal error occurred. |
| | Check whether the file is write-protected. If it is not, contact Software AG support. |

NAT6809: The record of a file cannot be deleted in directory FILEDIR.SAG.

| Text | The record of a file cannot be deleted in directory FILEDIR.SAG. |
|-------|--|
| Expl. | Either the directory FILEDIR.SAG is missing, or its contents is corrupt. Ask your administrator to check if the directory FILEDIR.SAG is missing or its contents is corrupt. A corrupt directory can be deleted and should then be recreated automatically for the first file that is copied or moved into the library. The records of the other files in the library must then be imported into the directory. Until an importing program is available to all users, the administrator uses the program FTOUCH to import these records. If the directory is missing, contact Software AG support because an internal error occurred. |
| Actn. | see explanation |

NAT6810: A file record cannot be inserted in the directory FILEDIR.SAG.

| Text | A file record cannot be inserted in the directory FILEDIR.SAG. |
|-------|---|
| Expl. | The directory FILEDIR.SAG is missing, its contents is corrupt, or it has no space for the new record. Ask your administrator to check if the directory FILEDIR.SAG is missing or its contents is corrupt. A corrupt directory can be deleted and should then be recreated automatically for the first file that is copied or moved into the library. The records of the other files in the library must then be imported into the directory. Until an importing program is available to all users, the administrator uses the program FTOUCH to import these records. If the directory is missing, contact Software AG support because an internal error occurred. |
| Actn. | see explanation |

NAT6811: Rename failed: path is incorrect or file name not in directory.

| Text | Rename failed: path is incorrect or file name not in directory. |
|------|---|
| | A file was not renamed because it was not found. Perhaps the path of the file or the extension of the file name has been changed. Otherwise, an internal error occurred. |
| | Ask your administrator to check the path of the file and the extension of the file name, and to correct any errors. If both are correct, contact Software AG support. |

NAT6812: Rename failed: file with same name already exists in library.

| Text | Rename failed: file with same name already exists in library. |
|-------|--|
| Expl. | The file could not be renamed because a file with the suggested new name already exists in this library. |
| Actn. | Either choose a different new name for the file, or delete the existing file. |

NAT6813: The object has an invalid extension so it cannot be imported.

| Text | The object has an invalid extension so it cannot be imported. |
|-------|--|
| Expl. | An object can be imported only if its extension is valid in Natural. |
| Actn. | Use the operating system to change the extension so that it is valid in Natural. |

NAT6814: Two objects with the same name cannot be imported.

| Text | Two objects with the same name cannot be imported. |
|-------|--|
| | Two objects with the same name (but not necessarily the same extension) have been selected to be imported. Only one of them can be imported. |
| Actn. | Select only one of the two objects. |

NAT6815: This module name already exists in a system or step library.

| Text | This module name already exists in a system or step library. |
|------------|---|
| 1 1 | A module name which is already used in a system library or in a step library cannot be used for a DDM in this library. |
| Actn. | Choose another module name for this DDM. |

NAT6816: The new name must be shorter than the old names.

| Text | The new name must be shorter than the old names. |
|-------|---|
| | Several objects can be selected and then renamed by changing the first character or characters of their names. At least one character must remain unchanged at the end of every name. The new character strings must be shorter than the old ones. |
| Actn. | Specify a new name which is shorter than any of the old names. |

NAT6817: The header of a DDM has an incorrect format.

| Text | The header of a DDM has an incorrect format. |
|-------|--|
| Expl. | The header of a DDM must have a specific format. |
| | Either use the DDM editor to edit the header and correct its format, or ask your administrator to use the editor of your operating system to edit the header and correct its format. |

NAT6818: The module name of a DDM is incorrect.

| Text | The module name of a DDM is incorrect. |
|-------|---|
| Actn. | Either use the DDM editor to edit and correct the module name, or ask |
| | your administrator to use the editor of your operating system to |
| | edit and correct the module name. |

NAT6819: No valid library with this name can be found.

| Text | No valid library with this name can be found. |
|-------|--|
| 1 1 | You either entered the name incorrectly or the library you are looking for is not part of this environment. |
| Actn. | Correct your input or create a new library. |

NAT6820: Invalid DBID/FNR.

| Text | Invalid DBID/FNR. |
|-------|--|
| Expl. | A library with this DBID/FNR does not exist and cannot be created. |
| | You can declare a new DBID/FNR in NATPARM -> global CFG File -> System File Assignment -> Modify System File Assignment |

NAT6821: The file :1: for choice/help menu cannot be found.

| Text | The file for choice/help menu cannot be found. |
|-------|--|
| Expl. | Copy this file to the correct path. |
| Actn. | Check if the file exists and if it is in the correct path. |

NAT6822: The file :1: cannot be written into memory file.

| Text | The file cannot be written into the memory file. |
|-------|--|
| - | Read error when trying to read the file in order to write it to a memory file. |
| Actn. | Check if the file exists and if its contens is correct. |

NAT6823: Identical DDM names in cur. lib, step lib or SYSTEM not allowed.

| Text | Identical DDM names in cur. lib, step lib or SYSTEM not allowed. |
|-------|---|
| Expl. | A DDM cannot be copied to the library System, or Step Lib because of identical names. |
| Actn. | Change the name of the DDM or move the DDM if you want to use the old name. |

NAT6824: Library full.

| Text | Library full. |
|-------|--|
| · · | A library can only contain a certain number of objects (depending on the type). This number has been reached. |
| Actn. | Choose another library. |

NAT6825: :1: cannot be created, logging is switched off.

| Text | Unable to open/create for logging, logging is switched off. |
|-------|---|
| | The file NATSYSM.LOG for logging taces from SYSMAIN cannot be |
| | opened/created, so SYSMAIN continues to work without logging |
| Actn. | Doesn"t matter, go on without logging |

NAT6826: Overwrite not possible if the max. number of objects is reached.

| Text | Overwrite not possible if the max. number of objects is reached. |
|-------|--|
| | When the max.limit of objects in one library has been reached you can no longer use COPY, MOVE, RENAME, or IMPORT. |
| Actn. | Delete one object. |

NAT6827: Not enough space available on disk.

| Text | Not enough space available on disk |
|-------|--|
| | The function could not be executed successfully because there is not enough space available on drive / discette. |
| Actn. | Increase free space on disk. |

NAT6828: DosQFSInfo (check free space) returns error :1:

| Text | DosQFSInfo (check free space) returns error |
|-------|---|
| | Internal error returned by the system function DosQFSInfo when checking whether enough free space is available for the imported file. |
| Actn. | Check the error return code and check your system |

NAT6829: The maximum size permitted for a Natural object is 65k.

| Text | The maximum size permitted for a Natural object is 65k. |
|-------|--|
| 1 1 | A Natural object cannot exceed 65k. If you create an object larger than this externally, you will not be able to import it into Natural. |
| Actn. | Reduce the size of the object to less than 65k. |

NAT6830: Not enough memory to create a file buffer.

| Text | Not enough memory to create a file buffer. |
|-------|---|
| Expl. | Perhaps too many programs have been loaded. |
| | Restart the program SYSMAIN. If this has no effect, contact Software AG support because an internal error occurred. |

NAT6831: Not enough memory to create an array.

| Text | Not enough memory to create an array. |
|-------|---|
| Expl. | Not enough memory to create an array in which to store a selection list. Perhaps too many programs have been loaded. |
| | Restart the program SYSMAIN. If this has no effect, contact Software AG support because an internal error occurred. |

NAT6832: Internal error :1:.

| Text | Internal error |
|-------|--|
| Expl. | A system call has resulted in an internal error. |
| Actn. | Restart Natural. |

NAT6833: Environment variable :1: not found.

| Text | Environment variable not found. |
|-------|--|
| Expl. | An environment variable which can be set with the "Set" command cannot be found. |
| Actn | Set the environment variable you want to use, or type in the full path name. |

NAT6834: No Natural object found, path invalid or no permission.

| Text | No Natural object found, path invalid or no permission. |
|-------|--|
| Expl. | You cannot read any object in this path. Either there is no Natural object in this directory, the directory of this path is not valid or permissions are denied. |
| Actn. | Check directory, path specifications and read permissions. |

NAT6835: :1: returned by stack or nucleus call.

| Text | returned by stack or nucleus call. |
|-------|--|
| Expl. | Nucleus cannot perfom a stack command. |
| Actn. | Retry the action. If error occurs again contact Software AG Support. |

NAT6836: :1: lib(s) found, access denied by Security.

| Text | lib(s) found, access denied by Security. |
|-------|--|
| Expl. | lib(s) found, access denied by Natural Security |
| Actn. | Make sure you have the permission to work within this lib. |

NAT6837: :1: lib(s) found for this file, access denied by Security.

| Text | lib(s) found for this file, access denied by Security. |
|-------|--|
| Expl. | lib(s) found, access denied by Natural Security. |
| Actn. | Make sure you have the permission to work within this lib. |

NAT6838: Invalid USER #ID.

| Text | Invalid USER@ID. |
|-------|--|
| Expl. | Object(s) with this USER®ID do not exist. |
| Actn. | Type in the correct USER⊚ID or "*" for wildcard. |

NAT6839: Invalid DATE/TIME.

| Text | Invalid DATE/TIME. |
|-------|--|
| Expl. | Object(s) with this DATE/TIME or newer do not exist. |
| Actn. | Type in the correct DATE/TIME or "0" for all. |

NAT6840: Invalid MODE.

| Text | Invalid MODE. |
|-------|--|
| Expl. | Object(s) with this mode (source or cataloged) do not exist. |
| Actn. | Select another MODE or both. |

NAT6841: Cannot delete file.

| Text | Cannot delete file. |
|-------|--|
| Expl. | Natural tried to delete a file, but access to the file was denied by the operating system. |
| Actn. | Check permission for the files in question. |

NAT6842: Sharing violation received during file/folder deletion

| Text | Sharing violation received during file/folder deletion |
|-------|---|
| Expl. | Natural cannot access the file because it is being used by another process. |
| Actn. | Release usage of file or folder. |

NAT6843: Too many matches, Please use more specific selection criteria

| Text | Too many matches, Please use more specific selection criteria |
|-------|--|
| Expl. | The List utility can not display all matching objects of a library |
| Actn. | Please use another selection criteria |

127 Natural System Error Messages 6851-6900

NAT6890: The map source cannot be loaded into the editor.

| Text | The map source cannot be loaded into the editor. |
|------|---|
| | This map cannot be read by the map editor, because the map source contains an invalid Natural syntax or the internal definitions used by the map editor cannot be resolved. |
| | In most cases that is an internal error. Contact Software AG Support. |

NAT6899: Internal error :1:

| Text | Internal error |
|-------|--|
| Actn. | In most cases that is an internal error. |
| | Contact Software AG Support. |

NAT6900: Natural Command Processor internal error :1:.

| Text | Natural Command Processor internal error |
|-------|--|
| Expl. | This is a runtime error. |
| | Note the error number Contact Software AG support and quote the error number. |

128 Natural System Error Messages 6901-6950

NAT6901: Error in ACTION clause of PROCESS COMMAND statement.

| Text | Error in ACTION clause of PROCESS COMMAND statement. |
|-------|---|
| | One of the following errors has occurred in a PROCESS COMMAND statement: - The keyword "ACTION" is missing. - No action or an invalid action has been specified after the keyword "ACTION". See the Natural documentation for the correct PROCESS COMMAND syntax. |
| Actn. | Correct error in program. |

NAT6902: Error in USING clause of PROCESS COMMAND statement.

| Text | Error in USING clause of PROCESS COMMAND statement. |
|-------|---|
| Expl. | One of the following errors has occurred in a PROCESS COMMAND statement: - The keyword "USING" is missing. |
| | The USING operand conflicts with the specified action. One of the values specified in the USING clause does not agree with the field to which it is assigned. An equal sign "=" is missing between a field and its value. |
| Actn. | Correct error in program. |

NAT6903: Error in GIVING clause of PROCESS COMMAND statement.

| Text | Error in GIVING clause of PROCESS COMMAND statement. |
|-------|--|
| Expl. | One of the following errors has occurred in a PROCESS COMMAND statement: - The keyword "GIVING" is missing. |
| | - One of the fields specified in the GIVING clause conflicts with the |
| | action specified in the ACTION clause. |
| | - One of the fields required for the specified action has not been |
| | defined (in the DEFINE DATA statement or GIVING clause). |
| | - If a DEFINE DATA statement is used, the GIVING clause is not allowed. |
| Actn. | Correct error in program. |

NAT6910: Processor name is invalid or missing.

| Text | Processor name is invalid or missing. |
|-------|--|
| Expl. | In the USING clause of a PROCESS COMMAND statement, you have specified the name of a Command Processor which is invalid or does not exist. |
| Actn. | Either specify the correct name or specify the name of an existing Command Processor. |

NAT6911: Specified object is not a Command Processor.

| Text | Specified object is not a Command Processor. |
|-------|--|
| | In the USING clause of a PROCESS COMMAND statement, you have specified the name of an object which is not a Command Processor. |
| Actn. | Use a Command Processor name. Check also your ampersand "&" notation. |

NAT6912: Processor :1: not found.

| Text | Processor not found. |
|-------|--|
| | In the USING clause of a PROCESS COMMAND statement, you have specified the name of a Command Processor which does not exist. |
| Actn. | Specify an existing Command Processor. |

NAT6913: Command line not accepted.

| Text | Command not accepted. |
|-------|---|
| | Possible reasons for this error: - the command line is empty - the command line contains special characters (such as underscores). |
| Actn. | Correct the command line input. |

NAT6914: Invalid use of field :1:.

| Text | Invalid use of field |
|-------|--|
| | For valid usage, see the Natural documentation, PROCESS COMMAND statement, ACTION GET/SET and in particular the list of possible values for GETSET-FIELD-NAME. |
| Actn. | Correct values. |

NAT6915: Contents of field :1: not accepted.

| Text | Contents of field not accepted. |
|-------|---|
| | The format/length of the field does not conform to the definitions as listed for the PROCESS COMMAND statement, action SET, in the Natural documentation. |
| Actn. | Check format/length of field. |

NAT6917: Invalid field name :1: for action :2:.

| Text | Invalid field name for action |
|-------|---|
| Expl. | There is a conflict between the GETSET-FIELD-NAME used in the GET and the SET actions, or the value used in the SET action is invalid. In case the GET action refers to the LAST-BUFFER, this error indicates that this buffer is not available. |
| Actn. | Check program syntax. |

NAT6918: Command Data error :1:.

| Text | Command Data error |
|-------|---|
| Expl. | This error occurs at runtime when the command line contains data that are in conflict with the Command Processor definition. This might occur, for example, if a delimiter is missing. The data that cannot be interpreted are indicated in the variable |
| Actn. | Check command line input against the Command Processor definition and correct error. |

NAT6919: Natural Command Processor - security error :1:.

| Text | Natural Command Processor - security error |
|-------|--|
| Expl. | This error is caused by Natural Security. |
| Actn. | Contact your Natural Security administrator. |

NAT6920: Processor :1: not allowed.

| Text | Command Processor not allowed. |
|-------|---|
| Expl. | You are not authorized to use this Command Processor. |
| Actn. | Contact your Natural Security administrator. |

NAT6921: Keyword :1: not allowed.

| Text | Keyword not allowed. |
|-------|--|
| Expl. | You are not authorized to use this keyword. |
| Actn. | Contact your Natural Security administrator. |

NAT6922: This command is not allowed.

| Text | This command is not allowed. |
|-------|--|
| Expl. | You are not authorized to use this command. |
| Actn. | Contact your Natural Security administrator. |

NAT6923: Inconsistent security definition for Command Processor.

| Text | Inconsistent security definition for Command Processor. |
|-------|---|
| Expl. | The command processor was cataloged after the functional security was defined. Therefore the processor and the functional security information don"t match. |
| Actn. | Contact your Natural Security administrator. |

NAT6925: Cannot :1: PRIVATE synonyms.

| Text | Cannot PRIVATE synonyms. |
|-------|--|
| | Either you do not have authorization for this function; or the Command Processor header definition does not permit this function |
| Actn. | Contact your Natural Security administrator. |

NAT6926: PRIVATE synonym :1: not found.

| Text | PRIVATE synonym not found. |
|-------|---|
| Expl. | The PRIVATE synonym you have specified cannot be found. |
| | For details on PRIVATE synonyms, see the PROCESS COMMAND statement, PRIVATE clause, in the Natural documentation. |

NAT6927: Keyword :1: not found.

| Text | Keyword not found. |
|-------|---|
| 1 | This may be because you have not specified the keyword correctly. |
| Actn. | Check that you have entered the keyword name correctly, particularly regarding upper and lower case characters, and the length of an abbreviated keyword. |

NAT6928: Keyword ... is not used in the correct context.

| Text | Keyword is not used in the correct context. |
|-------|---|
| Expl. | This is a semantic error. |
| | For example, it does not make sense to say: UPDATE DELETE |
| Actn. | Check and correct the semantics. |

NAT6929: Keyword of type :1: missing.

| Text | Keyword of type :1: is missing. |
|------|---|
| | The command you issued is missing an essential keyword. Without this keyword the command cannot be interpreted. |
| 1 | Check to see which keywords of the type mentioned can be used together with the keyword(s) entered. Choose the appropriate one. |

NAT6930: Keyword sequence error.

| Text | Keyword sequence error. |
|-------|--|
| Expl. | You have entered keywords in a sequence other than that specified in the Command Processor header. For example, you may have specified keywords in the order: ACTION OBJECT where the order OBJECT ACTION is required. |
| Actn. | Enter keywords in the correct sequence. |

NAT6931: This command is not defined.

| Text | This command is not defined. |
|-------|---|
| | You have specified a command that is not defined. For example, you might have entered DELETE CUSTOMER but no such command exists, even though the keywords DELETE and CUSTOMER do exist. |
| Actn. | Specify a valid command. |

NAT6932: Command Data disallowed.

| Text | Command Data disallowed. |
|-------|---|
| Expl. | No data can be entered with this command. |
| Actn. | Enter the command without data. |

NAT6933: Data element with more than :1: characters found.

| Text | Data element with more than :1: characters found. |
|-------|---|
| Expl. | The data element entered contains more than the legal number of characters. |
| Actn. | Check the legal range of input for the data element and correct your input. |

NAT6934: Data element with non-numeric character :1: found.

| Text | Data element contains non-numeric character :1:. |
|-------|--|
| | A non-numeric character was entered as part of the data |
| | element. A data element can contain only numeric characters. |
| Actn. | Correct the data element input. |

NAT6940: Error :1: in buffer for Natural Command Processor.

| Text | Error in buffer for Natural Command Processor. |
|-------|--|
| Expl. | This is an unexpected error. NCPWORK cannot be accessed. |
| Actn. | Contact Software AG support. |

NAT6942: Invalid GETMAIN request for Natural Command Processor.

| Text | Invalid GETMAIN request for Natural Command Processor. |
|-------|--|
| Expl. | NCPWORK cannot be opened. This may be because the thread is exhausted. |
| | Reduce ESIZE/FSIZE. Use the BUS command to find out how much space you have. |

NAT6943: GETMAIN failed for :1: KB for Command Processor buffer.

| Text | GETMAIN failed for KB for Command Processor buffer. |
|-------|--|
| | There is not enough space in your Natural thread. The value indicates the number of KB you cannot request. |
| Actn. | Ask your Natural administrator to decrease ESIZE or FSIZE. |

NAT6945: Buffer for Natural Command Processor is not allocated.

| Text | Buffer for Natural Command Processor is not allocated. |
|-------|--|
| Expl. | Either: |
| | The NCPWORK buffer has been overwritten so the |
| | GET / SET action cannot be fulfilled. |
| | Or: |
| | The Command Processor has been closed. |
| Actn. | Open the Command Processor using the PROCESS COMMAND |
| | statement ACTION EXEC. |

NAT6950: Library could not be dynamically loaded.

| Text | Library could not be dynamically loaded. |
|-------|---|
| Expl. | A library required at run time could not be found or could not be loaded. Check system search path for dynamically loaded libraries. Has this been changed in any way since Natural was installed? If not, it could be that you are trying to access a component which was not installed. If this is also not the case, contact SAG support. |
| Actn. | see explanation |

129 Natural System Error Messages 6951-7000

NAT6951: Procedure in dynamically loaded library could not be found.

| Text | Procedure in dynamically loaded library could not be found. |
|-------|--|
| | A procedure required at run time could not be found in a dynamically loaded library. |
| Actn. | Check system search path for dynamically loaded libraries. In particular, check that the system is not loading any libraries from a different Natural version to the one which is currently running. |

NAT6952: Natural Reporter function did not complete successfully.

| Text | Natural Reporter function did not complete successfully. |
|-------|--|
| Expl. | The Natural Reporter failed to carry out the requested function successfully. Check the documentation to ensure that the requested function is being used correctly. Can the series of operations being performed by the program be carried out successfully by hand from within the Reporter when used standalone? If so, has OLE been installed correctly? If the cause of the problem still cannot be found, contact Software AG support. |
| Actn. | see explanation |

NAT6953: Natural/Reporter Interface not initialized.

| Tex | xt Natural/Reporter Interface not initialized. |
|-----|---|
| Exp | An attempt was made to call a Natural/Reporter interface function without first initializing the interface. Either no initializing call has been made, or a call to terminate the interface has been performed, in which case the interface needs to be re-initialized. Note that it is only necessary to initialize and terminate the Natural/Reporter interface once per Natural session. |
| Act | tn. Modify program to include a statement to (re-)initialize the Natural/Reporter interface. |

NAT6954: Requested report could not be found.

| Text | Requested report could not be found. |
|-------|---|
| Expl. | If the report is specified by name (i.e., an OPEN request), the specified report could not be located in the file system. Otherwise, the specified report ID is not valid. Check that the report name contains no path or file extension information, is not longer than 8 characters, and exists in the NATGUI®BMP path as specified in the SAG.INI file. Or check that the report ID corresponds to a valid ID, as returned by a previous OPEN (for example, check the response code from the OPEN to verify that the report was opened correctly). Confirm that no CLOSE request has been issued against this report in the meantime! |
| Actn. | see explanation |

NAT6955: Too many active reports.

| Text | Too many active reports. |
|-------|---|
| Expl. | The maximum number of reports concurrently maintainable by the Natural/Reporter Interface has been reached. |
| | Modify program to issue a CLOSE request for each report as soon as it is no longer needed, or if it will probably not be used again for a significant length of time. |

NAT6956: Invalid parameter(s).

| Text | Invalid parameter(s). |
|-------|--|
| | This error can have various causes: - the number of parameters supplied is incorrect - one or more mandatory parameters were not supplied - one or more parameters were specified with an incorrect format and/or length |
| Actn. | Check the parameters used in the program against the documentation. |

NAT6957: Invalid print device

| Text | Invalid print device |
|------|---|
| | Either the specified printer has not been set up in NATPARM, or it is not associated with the TTY print method. |
| | Check the printer settings via the Printer Configuration dialog in NATPARM. |

NAT6958: Invalid work file

| Text | Invalid work file |
|-------|--|
| | Either the specified work file has not been set up (statically in NATPARM or dynamically via DEFINE WORK FILE), or the file does not exist, or it is not a Natural CONNECTION (*.NCD) work file. |
| Actn. | Check work file name against the above criteria |

NAT6959: Failed to save resources to private resource file.

| Text | Failed to save resources to private resource file. |
|-------|---|
| Expl. | Along with the dialog source, resources needed to be saved. This action failed. Possible reasons: - Problems to access the current library - Problems accessing/creating the resource directory in the current library - Problems writing/appending to the private resource file - Problems executing dynamic functions - Memory problems |
| Actn. | Check the subdirectories of the library the dialog was saved in. If you cannot solve the problem there, contact Software AG support. |

NAT6960: Unable to import (private) resource :1: into library :2:.

| Text | Unable to import (private) resource into library |
|-------|--|
| Expl. | The importing of a resource failed. If the resource is a private resource, the corresponding object to which the private resource belongs must be present in the library and its type must be the same as the type of the private resource. |
| Actn. | Resolve the type conflict by either importing the appropriate resource and/or by first replacing the corresponding Natural object in the target library. If in doubt, contact Software AG support. |

NAT6970: Natural RPC initialization failed. RPC not available.

| Text | Natural RPC initialization failed. RPC not available. |
|-------|---|
| Expl. | This error message is preceded by an initialization error message. |
| | On the client side, the following features are not available: |
| | - execution of a remote CALLNAT, |
| | - SYSRPC functions SM, XC and PM, |
| | - local use of conversations and context variables. |
| | On the server side, the termination of the Natural RPC server session |
| | is enforced by an implicit ITERM=ON. |
| Actn. | Check the previous initialization error. |

NAT6971: Connection error on :1:, reason :2: :3:.

| Text | Connection error on, reason |
|-------|--|
| Expl. | Reason: 1: No transport layer. |
| | 2: Connection timed out. |
| | 3: Conversation timed out. |
| | 4: No space for working storage of broker stub. |
| | Increase Natural thread or region size by 35 KB. |
| | 5: Data have been truncated. Increase MAXBUFF on server side. |
| | 6: Node does not match any pattern. |
| | 7: Node not active. |
| | 8: Server not active. |
| | 9: Error from transport layer; issue RPCERR for details. |
| | After the reason, the message displays the server/node in question. |
| | With AUTORPC=ON this error may also occur instead of a local NAT0082 |
| | error on the client side. |
| Actn. | Proceed depending on above reason. |

NAT6972: Directory error on :1:, reason :2: :3:.

| Text | Directory error on, reason |
|-------|--|
| Expl. | A directory error has occurred. Possible reasons are: |
| | 1 - No directory. |
| | 2 - Invalid directory. |
| | 3 - No space to load directory. Increase the RPC size. |
| | 4 - No server found in service directory for the subprogram/library |
| | whose names are indicated in the error message. |
| | 5 - Recursive RPC with the two subprograms whose names are |
| | indicated in the error message. |
| | 6 - A Natural error has occurred during loading of NATCLTGS. |
| | The error number is indicated in the error message. |
| | With AUTORPC=ON this error may also occur instead of a local NAT0082 |
| | error on the client side. |
| Actn. | Proceed depending on above reason. |

NAT6973: Conversation error on :1:, reason :2: :3:.

| Text | Conversation error on, reason |
|-------|---|
| Expl. | Reason: 1: Too many subprograms for OPEN CONVERSATION. |
| | 2: Invalid subprogram name. |
| | 3: RPC size overflow. Increase RPC size. |
| | 4: Mixed local/remote CALLNAT within one conversation (program). |
| | It is not possible to execute subprograms that are members |
| | of one conversation partially remote and local. |
| | 5: Recursive conversation. It is not possible to execute a |
| | subprogram that is a member of a conversation while you |
| | are executing a subprogram within that conversation. |
| | 6: Conversation to be closed not found. |
| | 7: Conversation ID to be closed is not valid. |
| | 8: CLOSE CONVERSATION executed inside a local conversation. |
| | It is not possible to close a conversation while you are |
| | executing a subprogram within that conversation. |
| Actn. | executing a subprogram within that conversation. Proceed depending on above reason. |

NAT6974: Conversion error on :1:, reason :2: :3:.

Text Conversion error on :1:, reason :2: :3:.

| Expl. | Reason: 1: Variables of type CONTROL and HANDLE and extensible lower |
|-------|--|
| | bounds in X-arrays not supported. |
| | 2: Error converting to external format of parameter :3:. |
| | 3: Error converting to internal format of parameter :3:. |
| | 4: No space for conversion to internal format of parameter :3:. |
| | Increase MAXBUFF on :1: side. |
| | 5: No space for conversion to external format of parameter :3:. |
| | Increase MAXBUFF on :1: side. |
| | 6: Format buffer error for parameter :3:. |
| | 7: No space for working storage in RPC size. |
| | Increase RPC size on :1: side. |
| | 8: No MAXBUFF defined on client side, but RPC is used. |
| | 10: AD=M (inout) or AD=A (in) parameter used with reliable RPC. |
| | 11: No stub with group structures used with reliable RPC. |
| Actn. | 11: No stub with group structures used with reliable RPC. Proceed depending on above reason. |

NAT6975: Security error on :1:, reason :2: :3:.

| Text | Security error on, reason |
|-------|--|
| Expl. | Reason: 1: Logon data required by the Natural RPC server. 2: Invalid logon data received by the Natural RPC server. After the reason, diagnostic information is indicated in the message. 3: Invalid offset to the logon data in the RPC meta data. 4: Impersonation failed for the user indicated in the message. The external security system has rejected the logon attempt of the user. The reason is shown in the Natural RPC server trace and in the system log of the server. |
| Actn. | Reason: 1: Pass logon data from the client to the Natural RPC server.2,3: Contact Software AG support.4: Pass logon data that is valid for your security system. |

NAT6976: Context error on :1:, reason :2: :3:.

Text Context error on ..., reason

| Fypl | Reason: 1: Context size overflow. |
|-------|---|
| Expl. | |
| | The storage for the variables of the DEFINE DATA CONTEXT |
| | statement could not be allocated. |
| | On mainframe computers, the CONTEXT buffer could not be |
| | allocated or increased. This is either caused by storage |
| | restrictions of the operating or TP system, or by Natural |
| | environment constraints (Natural profile parameter OVSIZE, |
| | NATCONFG table entry NTBUFID for CONTEXT buffer). |
| | On Windows and UNIX systems, the USIZE buffer was not large |
| | enough to fulfil the storage request. |
| | 2: Conflict in format/length definition of a variable. |
| | The context variable whose name is shown in the error message |
| | was defined in a previous program with a different |
| | format/length. |
| Actn. | format/length. Reason: 1: Decrease number of context variables and/or number of |
| | concurrent conversations, or remove storage contraints. |
| | 2: Correct format/length of context variable. |
| | Č |

NAT6977: EntireX RPC error on :1:, reason :2: :3:.

| Text | EntireX RPC error on, reason |
|-------|--|
| | An EntireX RPC error has occurred. The reason shows the EntireX RPC error number, optionally followed by additional diagnostic information. This error can only occur if a Natural client is communicating with an EntireX RPC server. |
| Actn. | Refer to the EntireX Communicator messages and codes. |

NAT6978: RPC protocol error on :1:, reason :2: :3:.

| Text | RPC protocol error on, reason |
|-------|---|
| Expl. | Reason: 2: Server does not support this RPC protocol version. After the reason, the unsupported version is indicated in the message.3: RPC protocol header is invalid. After the reason, the corresponding EntireX error number is indicated in the message. |
| Actn. | Use the correct RPC protocol version. Refer to the EntireX messages. |

NAT6979: Premature termination of a remote CALLNAT.

| Text | Premature termination of a remote CALLNAT. |
|-------|---|
| Expl. | The remote execution of a CALLNAT was prematurely terminated on the server side and all data of the parameter area were lost. The reason for this may be the use of one of the following Natural statements: - STOP - FETCH - ESCAPE BOTTOM outside of a processing loop - RUN - TERMINATE Note: These statements will be disabled in a remotely executed CALLNAT in one of the next Natural versions. |
| Actn. | Do not use one of the listed statements in a remotely executed CALLNAT. |

NAT6980: Invalid parameter.

| Text | Invalid parameter. |
|-------|--|
| Expl. | One or more invalid parameters were entered with the command. |
| | Check the DDE client program to ensure that all parameters are in the proper order and are of the correct type. Check the command description in the documentation for valid input. |

NAT6981: Member or file already exists.

| Text | Member or file already exists. |
|-------|---|
| Expl. | An operation tried to update or replace an existing member or file. |
| | Check the command description in the documentation and reissue the command using the "Replace" parameter. |

NAT6982: Unable to read DDM transfer file.

| Text | Unable to read DDM transfer file. |
|-------|--|
| Expl. | Error while reading a DDM transfer file. |
| | Ensure that the file is not being accessed by another application and that the file exists. |

NAT6983: Editor is not active.

| Text | Editor is not active. |
|-------|--|
| Expl. | An editor command was issued for an editor which was not active. |
| Actn. | Start the editor and reissue the command. |

NAT6985: Library not found.

| Text | Library not found. |
|-------|---|
| - | A delete or rename command was issued for a library which does not exist. |
| Actn. | Ensure that the name of the library and reissue the command. |

NAT6986: Library already exists.

| Text | Library already exists. |
|-------|--|
| Expl. | The library cannot be renamed because a library by this name already exists. |
| Actn. | Choose another name. |

NAT6987: Unable to change type.

| Text | Unable to change type. |
|-------|---|
| Expl. | The editor was unable to change the type to the new type. |
| | Check to ensure that valid types are being used for the type of editor and reissue the command. |

NAT6989: Shutdown interrupted.

| Text | Shutdown interrupted. |
|-------|---|
| Expl. | The user cancelled the shutdown process by responding "No" or |
| | "Cancel" to the shutdown prompt. |

NAT6990: Invalid DDM type.

| Text | Invalid DDM type. |
|-------|--|
| Expl. | An invalid type or invalid information was found in a DDM transfer file. |
| Actn. | Check the documentation for valid DDM transfer options. |

NAT6991: Editor is empty.

| Text | Editor is empty. |
|-------|---|
| Expl. | An attempt was made to perform a Natural command for an empty editor. |

NAT6992: Editor is active.

| Text | Editor is active. |
|-------|---|
| | An attempt was made to perform a Natural command such as rename or delete for an active editor. |
| Actn. | Close the editing session and reissue the command. |

NAT6993: Editor list is empty.

| Text | Editor list is empty. |
|-------|---|
| Expl. | The list command was issued when no active editors were active. |

NAT6994: Short name conflict.

| Text | Short name conflict. |
|-------|---|
| Expl. | A GenDDM transfer file was entered in which short names are missing. |
| | Ensure that the transfer file - contains a short name for every field or - contains no sort names in any field. |

NAT6999: Internal DDE server error.

| Text | Internal DDE server error. |
|-------|---|
| Expl. | An internal DDE server error occurred. |
| | Write down all information about how the error occurred and contact |
| | technical support. |
| | Please provide the following information: |
| | 1. Command and parameters issued which led to problem. |
| | 2. Member information (type, member, library) for which the command |
| | (above) was issued. |
| | 3. Description of how error occurs (if reproducible). |
| | 4. Topics to which other clients or multiple connections were connected |
| | (if any were active). |
| | 5. If more than one client was active, whether they were performing |
| | operations simultaneously. |
| Actn. | operations simultaneously. See explanation |

NAT7000: Invalid value specified for dynamic parameter :1:.

| Text | Invalid value specified for dynamic parameter |
|-------|--|
| Expl. | You have specified a value for a dynamic parameter incorrectly. For information on valid values for this Natural profile parameter, see the Natural documentation. |
| Actn. | Either ignore, or invoke Natural again with correct specification of dynamic parameters. |

130 Natural System Error Messages 7001-7050

NAT7001: Value for dynamic parameter :1: must be :2:-:3:.

| Text | Value for dynamic parameter must be |
|-------|--|
| | You have specified a value for a dynamic parameter incorrectly. A valid value for this parameter must be in the range as indicated in the error message. |
| Actn. | Either ignore, or invoke Natural again with correct specification of dynamic parameters. |

NAT7002: Value for dynamic parameter :1: must be :2:-:3: or 0.

| Text | Value for dynamic parameter must be or 0. |
|-------|--|
| Expl. | You have specified a value for a dynamic parameter incorrectly. A valid value for this parameter must be either "0" or in the range as indicated in the error message. |
| | Either ignore, or invoke Natural again with correct specification of dynamic parameters. |

NAT7003: Value for dynamic parameter :1: must be 1 special character.

| Text | Value for dynamic parameter must be 1 special character. |
|-------|---|
| Expl. | You have specified a value for a dynamic parameter incorrectly. A valid value for this parameter must be a single special character. For further information on Natural profile parameters, please refer to the Natural documentation. |
| Actn. | Either ignore, or invoke Natural again with correct specification of dynamic parameters. |

NAT7004: Value for dynamic parameter :1: must be numeric.

| Text | Value for dynamic parameter must be numeric. |
|-------|---|
| Expl. | You have specified a value for a dynamic parameter incorrectly. For this parameter, a numeric value must be specified. For further information on Natural profile parameters, please refer to the Natural documentation. |
| Actn. | Either ignore, or invoke Natural again with correct specification of dynamic parameters. |

NAT7005: Value for dynamic parameter :1: must be :2: characters.

| Text | Value for dynamic parameter must be characters. |
|-------|---|
| Expl. | You have specified a value for a dynamic parameter incorrectly. A valid value for this parameter must be a name of 1 to n characters. For further information on Natural profile parameters, please refer to the Natural documentation. |
| Actn. | Either ignore, or invoke Natural again with correct specification of dynamic parameters. |

NAT7006: Value for dynamic parameter :1: must be 1 character.

| Text | Value for dynamic parameter must be 1 character. |
|-------|---|
| Expl. | You have specified a value for a dynamic parameter incorrectly. A valid value for this parameter must be a single character. For further information on Natural profile parameters, please refer to the Natural documentation. |
| Actn. | Either ignore, or invoke Natural again with correct specification of dynamic parameters. |

NAT7007: Value for dynamic parameter :1: must be :2: or :3:.

| Text | Value for dynamic parameter must be or |
|-------|--|
| | You have specified a value for a dynamic parameter incorrectly. For this parameter, you must specify one of the two value as indicated in the error message. |
| Actn. | Either ignore, or invoke Natural again with correct specification of dynamic parameters. |

| Text | Parameter non-existent or not allowed dynamically. |
|-------|--|
| Expl. | You have specified an invalid Natural profile parameter dynamically. The reason may be one of the following: You have misspelt a parameter name. You have specified a parameter which does not exist (or is obsolete and no longer exists). You have specified a parameter which must not be used dynamically. For further information on Natural profile parameters, please refer to the Natural documentation. |
| Actn. | Either ignore, or invoke Natural again with correct specification of dynamic parameters. |

NAT7008: Parameter :1: non-existent or not allowed dynamically.

NAT7009: Element missing in value list for parameter :1:.

| Text | Element missing in value list for parameter |
|-------|---|
| Expl. | You have specified the values for a dynamic parameter incorrectly. For this parameter, you must specify a list of several values; however, one or more of the values were missing. For further information on valid values for this Natural profile parameter, please refer to the Natural documentation. |
| Actn. | Either ignore, or invoke Natural again with correct specification of dynamic parameters. |

NAT7010: Too many elements in value list for parameter :1:.

| Text | Too many elements in value list for parameter |
|-------|---|
| Expl. | You have specified the values for a dynamic parameter incorrectly. For this parameter, you must specify a list of several values; however, you have specified too many values. For further information on valid values for this Natural profile parameter, please refer to the Natural documentation. |
| Actn. | Either ignore, or invoke Natural again with correct specification of dynamic parameters. |

NAT7011: ")" missing after values list for parameter :1:.

| Text | ")" missing after values list for parameter |
|-------|---|
| Expl. | You have specified the values for a dynamic parameter incorrectly. For this parameter, you must specify a list of values which must be enclosed in parentheses; however, the closing parenthesis at the end of the values list is missing. |
| Actn. | Either ignore, or invoke Natural again with correct specification of dynamic parameters. |

NAT7012: Value for parameter :1: must be a list of elements.

| Text | Value for parameter must be a list of elements. |
|-------|---|
| Expl. | You have specified the values for a dynamic parameter incorrectly. For this parameter, you must specify a list of several values. For further information on valid values for this Natural profile parameter, please refer to the Natural documentation. |
| Actn. | Either ignore, or invoke Natural again with correct specification of dynamic parameters. |

NAT7013: The parameter module :1: does not exist.

| Text | The parameter module does not exist. |
|------|---|
| · · | You have specified the name of a parameter module; however, a parameter module of this name does not exist. |
| | Use valid parameter module name; if necessary, contact your Natural administrator. |

NAT7014: The parameter module :1: is invalid.

| Text | The parameter module is invalid. |
|-------|--|
| Expl. | The specified parameter module is invalid for one of the following |
| | reasons: |
| | - It is not a parameter module at all. |
| | - It was assembled against a Natural macro library of an older |
| | version or an older maintenance level. |
| | - It is restricted to certain users by the NTUSER macro. |
| Actn. | Ensure that you have specified a valid parameter module. |
| | If necessary, contact your Natural administrator. |

NAT7015: Value for dynamic parameter :1: must be hexadecimal.

| Text | Value for dynamic parameter must be hexadecimal. |
|-------|--|
| Expl. | You have specified the value for a dynamic parameter incorrectly. A valid value for this parameter must be hexadecimal. For further information on Natural profile parameters, please refer to the Natural documentation. |
| Actn. | Either ignore, or invoke Natural again with correct specification of dynamic parameters. |

NAT7016: Parameter :1: may only be specified up to :2: times.

| Text | Parameter may only be specified up to times. |
|-------|--|
| Expl. | You have invoked Natural with a dynamic parameter which may be specified several times. However, you have specified the parameter too often. For further information on Natural profile parameters, please refer to the Natural documentation. |
| Actn. | Either ignore, or invoke Natural again with correct specification of dynamic parameters. |

NAT7017: User ID :1: not authorized to use this parameter string.

| Text | User ID not authorized to use this parameter string. |
|-------|--|
| | The parameter string used is restricted to certain user IDs. The initial user ID passed from the environment doesn"t match with one of the user IDs specified by the USER profile parameter in the string. |
| Actn. | Add your user ID to the USER parameter list in the desired parameter string or use an authorized user ID. |

NAT7018: Delimiter */ missing at end of profile parameter comment.

| Text | Ending profile parameter comment delimiter */ missing. |
|-------|--|
| | The dynamic profile parameter string contains a start comment delimiter "/*" but no end comment delimiter "*/" was found. All data after the start comment delimiter is ignored. |
| Actn. | Insert an end comment delimiter in the parameter string. |

NAT7019: Code page :1: invalid or not defined.

| Text | Code page invalid or not defined. |
|-------|--|
| Expl. | The code-page name specified by profile parameter CP was not found in the Natural code-page table in the module NATCONFG, or it cannot be used because MULTI=ON in macro NTCPAGE indicates a multiple-byte code page, i.e. one character may be represented by more than one byte. All valid code-page names have to be predefined by macro NTCPAGE in the source module NATCONFG. Only single-byte character code-pages can be used for character translation. |
| Actn. | Correct the value for profile parameter CP, or add the desired code-page name to the Natural code-page table in NATCONFG. |

NAT7020: Value for dynamic parameter :1: already used by :2:.

| Text | Value for dynamic parameter already used by |
|-------|---|
| | The following profile parameters must have four different values: |
| | DC, IA, ID and STACKD. |
| Actn. | Change the profile parameter values accordingly. |

NAT7021: Character translation parameter :1: ignored due to CFICU=ON.

| Text | Character translation parameter ignored due to CFICU=ON. |
|-------|---|
| Expl. | A character translation parameter was specified in the Natural parameter module with one of the following macros: NTTAB, NTUTAB1, NTUTAB2, NTSCTAB, NTTABL, or by the indicated dynamic profile parameter. Unicode support is activated, which performs the character translation instead. Therefore the indicated character translation parameter is ignored. |
| Actn. | To avoid this message, either remove the character translation parameter or deactivate Unicode support (parameter CFICU=OFF). If CFICU=ON is desired, test your applications for correct character translation. |

NAT7022: Code page support requires parameter setting CFICU=ON.

| Text | Code page support requires parameter setting CFICU=ON. |
|-------|--|
| Expl. | The profile parameter CP has been set to a value different to from default (OFF) for code page support, but parameter CFICU=OFF is set. Code page support requires ICU support. Therefore the CFICU setting has been changed to ON and the session continues. |
| Actn. | To avoid this error, set either the parameter CFICU=ON or the parameter CP=OFF, depending on whether you want code page support or not. |

NAT7043: Value for dynamic parameter KEY incorrectly specified.

| Text | Value for dynamic parameter KEY incorrectly specified. |
|-------|---|
| Expl. | Either the specified the function-key name waswrong or not defined, |
| | or the specified function-key value was wrong. |
| | Examples of valid KEY parameter specifications are: |
| | KEY=(OFF) - releases all keys defined in parameter module. |
| | KEY=(ON) - takes all keys defined in parameter module. |
| | KEY=(PF1=OFF) - ignores the PF1 value defined in parameter module. |
| | KEY=(PF1=LOGON) - replaces the PF1 value defined in parameter module. |
| | KEY=(PF1="LOGON SYSTEM",PF2="L PROGRAM") |
| | - replaces PF1 and PF2 values defined in parameter |
| | module. |
| Actn. | Restart Natural with a valid specification of the KEY parameter. |

NAT7050: The product license module is missing or invalid.

| Text | The product license module is missing or invalid. |
|-------|---|
| Expl. | The license module for Natural is not linked to the nucleus or it was incorrectly generated by the license-file conversion utility. The session cannot start without a correct product license. |
| Actn. | Generate and link a correct license module. If you have no correct license file, please contact Software AG. |

131 Natural System Error Messages 7051-7100

NAT7051: The product license key is invalid.

| Text | The product license key is invalid. |
|------|---|
| - | The license key defined in the product license module does not match the other data in the module. Either the data or the key has been modified or generated incorrectly. |
| | Generate and link a correct license module. If you have no correct license file, please contact Software AG. |

NAT7052: The product license is not for :1:.

| Text | The product license is not for |
|-------|--|
| - | The product license is not valid due to which can be one of the following: - product and release "NAT v.r" (Natural Version v Release r); - operating system "zOS", "zVSE", "zVM" or "BS2000". |
| Actn. | Please check the product release and the operating system in your license file. If you do not have a license file that matches your environment, please contact Software AG. |

NAT7053: The product license has expired on :1:.

| Text | The product license has expired on |
|------|---|
| · · | The product license has expired on (YYYY/MM/DD) and is no longer valid. The session cannot start without a valid product license. |
| | Generate and link a correct license module. If you have no correct license file, please contact Software AG. |

NAT7054: The price unit value of your product license is invalid.

| Text | The price unit value of your product license is invalid. |
|------|--|
| | The price unit value in your product license file must be one of the following: MSU, LPAR, SC or MZ9. |
| | Please check the price unit value in your license file. If you have no valid license file, please contact Software AG. |

NAT7055: CPU-ID :1: is not defined in your product license.

| Text | CPU-ID is not defined in your product license. |
|-------|--|
| 1 1 | The serial number of your CPU is not defined in your product license. |
| Actn. | Please contact Software AG and request a valid license file for your CPUs. |

NAT7056: LPAR name :1: is not defined in your product license.

| Text | LPAR name is not defined in your product license. |
|-------|---|
| | The price model in your license is "LPAR", but the current name of your system does not match one of the LPARs defined in your license. |
| Actn. | Please contact Software AG and request a valid license file for your LPARs. |

NAT7057: Machine capacity higher than MSUs in your product license.

| Text | Machine capacity higher than MSUs in your product license. |
|------|--|
| | The current capacity of your machine or partition is higher than the MSUs defined in your product license. |
| | Please contact Software AG and request a license file with MSU values according your requirements. |

NAT7058: The product license will expire on :1:.

| Text | The product license will expire on |
|------|---|
| - | Your product license has the expiration date (YYYY/MM/DD). Warning: After this date, Natural cannot be started with this license. |
| | Please contact Software AG and request a new license file with another or without an expiration date. |

NAT7059: Disaster Recovery situation assumed.

| Text | Disaster Recovery situation assumed. |
|------|---|
| | The serial number of your CPU is not defined in your product license. We assume a Disaster Recovery scenario. This message is issued only with message NAT7055. |
| 1 | Please contact Software AG and request a valid license file for your disaster CPUs. |

132 Natural System Error Messages 7151-7200

NAT7200: NATSPOOL: :1: error :2: accessing spool file.

| Text | NATSPOOL: error accessing spool file. |
|-------|--|
| Expl. | Adabas/VSAM response code upon call to NATSPOOL file at Natural initialization time was not "0". Possible reasons are: - The FSPOOL parameter is missing in NATPARM. - The NATSPOOL file, as defined in FSPOOL, may not be loaded. - The NATSPOOL file, as defined in FSPOOL, may not be open. - DD/DLBL statements of NATSPOOL (VSAM) files missing in CICS startup job. |
| Actn. | Check status of NATSPOOL file and/or CICS startup job. |

133 Natural System Error Messages 7201-7250

NAT7201: NATSPOOL: User profile :1: not found.

| Text | NATSPOOL: User profile not found. |
|-------|--|
| Expl. | The user profile, as defined in the printer parameter, has not been added to the SYSPOOL file. |
| | Define the user profile by using function "U" of the NATSPOOL operator commands. |

NAT7202: NATSPOOL: Logical printer profile :1: not found.

| Text | NATSPOOL: Logical printer profile not found. |
|-------|---|
| Expl. | One of the logical printer profiles, contained in the currently active user profile, is not defined on the NATSPOOL file. |
| | Define the logical printer profile by using function "L" of the NATSPOOL operator commands. |

134 Natural System Error Messages 7251-7300

NAT7300: Dynamic parameter not found.

| Text | Dynamic parameter not found. |
|-------|---|
| | A keyword cannot be recognized by the dynamic parameters facility. Either you have specified a parameter which does not exist, or you have misspelt a parameter name. |
| Actn. | Restart Natural session with correct parameter specifications. |

Natural System Error Messages 7301-7350

NAT7301: Invalid LFILE assignment.

| Text | Invalid LFILE assignment. |
|-------|--|
| | Either you have specified invalid dynamic LFILE values or the assigments in the parameter module are invalid. |
| Actn. | Correct the respective LFILE assigments. |

136 Natural System Error Messages 7351-7400

NAT7386: Invalid :1: level :2: must be at least :3:.

| Text | Invalid .1. level .2. must be at least .3 |
|-------|--|
| Expl. | The SM level of the component in .1. must be at least .3 |
| | Contact your Natural administrator. Install the correct SM level. |

NAT7387: The Natural for DB2 parameter module is not linked.

| Text | The Natural for DB2 parameter module is not linked. |
|------|---|
| | This may also indicate that you are using an old version of the Natural parameter module (must be at least 2.2.4). |
| 1 | Contact your Natural administrator. Link the Natural for DB2 parameter module to your Natural environment. |

NAT7388: Natural SQL interface not active. SQL calls not possible.

| Text | Natural SQL interface not active. No SQL calls can be processed. |
|-------|--|
| Expl. | This error message is preceded by an initialization error message. |
| Actn. | Check for previous initialization error. |

NAT7389: Natural SQL interface active without file server.

| Text | Natural SQL interface active without file server. |
|-------|--|
| Expl. | This error message is preceeded by an initialization error of the file |
| | server. The file server is not available for this Natural session but |
| | SQL statements will be processed as normal. |

NAT7390: :1: not linked / not found.

| Text | not linked / not found. |
|-------|---|
| Expl. | The required module is not linked to your Natural environment. |
| | Contact your Natural administrator. Check your installation. |

NAT7391: DB2SIZE parameter must be set to at least :1:.

| Text | DB2SIZE parameter must be set to at least |
|-------|--|
| Expl. | The area specified with the DB2SIZE parameter is too small to accommodate all buffer areas required by Natural DB2 / Natural SQL/DS. |
| Actn. | Set DB2SIZE to the value as indicated in the error message; then invoke Natural again. |

NAT7392: GETMAIN for DB2SIZE failed.

| Text | GETMAIN for DB2SIZE failed. |
|------|---|
| | During Natural initialization, the GETMAIN for the buffer area specified by the DB2SIZE parameter failed. The probable reason is that not enough free storage is available or that the thread is too small. |
| | Reduce Natural's total area size allocations, or increase the region size. |

NAT7393: File server initialization error :1:.

| Text | File server initialization error |
|------|----------------------------------|
|------|----------------------------------|

| Expl. | The initialization of the file server failed, returning the reason code |
|-------|---|
| | as indicated in the error message. Possible reason codes and their |
| | meanings are: |
| | 01 - Global directory full. |
| | 04 - Dataset open error. |
| | 05 - Dataset read error. |
| | 06 - Dataset write error. |
| | 07 - ENQUEUE failed. |
| | 08 - DEQUEUE failed. |
| | 10 - DB2SIZE too small. |
| | 11 - System GETMAIN failed. |
| | 12 - System FREEMAIN failed. |
| | 13 - WAIT request failed. |
| | 14 - Not enough space in dataset. |
| Actn. | 14 - Not enough space in dataset. Contact your Natural administrator. |

NAT7394: Load of DB2COMRE failed.

| Text | Load of DB2COMRE failed. |
|-------|---|
| | During initialization of the Natural SQL interface under Com-plete, the Com-plete to DB2 interface DB2COMRE could not be loaded. Typically DB2COMRE is not defined as RESIDENTPAGE. |
| Actn. | Contact your Com-plete administrator. |

NAT7395: Natural must be started via NDLSINIB in DSNMTV01.

| Text | Natural must be started via NDLSINIB in DSNMTV01. |
|-------|---|
| Expl. | In the DSNMTV01 environment all ET/BT calls are to be processed by NDLSINIB as requested by the parameter DLISYNC=ON in the NDBPARM but Natural has not been started via the NDLSINIB bootstrap module. |
| | Start Natural via the NDLSINIB bootstrap module or set the parameter DLISYNC in the NDBPARM to OFF. |

NAT7396: User area has been modified.

| Text | User area has been modified. |
|-------|---|
| | Natural checks the contents of the user area at regular intervals. When this area has been overwritten, Natural cannot guarantee correct continuation of the Natural session. |
| Actn. | Restart Natural. |

NAT7397: System file has been modified.

| Text | System file has been modified. |
|-------|---|
| - | Natural checks the integrity of the Natural system file. |
| | If Natural detects a discrepancy, this error message is issued. |
| | The DBA should try to find out who or why data have been modified |
| | in the system file without proper authorization. |
| Actn. | Re-INPL the Natural system file. |

NAT7398: Natural nucleus SM level does not agree with system file.

| Text | Natural nucleus SM level does not agree with system file. |
|-------|---|
| - | During startup, Natural checks whether the system file level agrees with the SM level of the Natural nucleus. If these levels do not agree, it is highly likely that some system program will not work. |
| Actn. | Restart Natural with the correct system file. |

NAT7399: Natural system file information missing.

| Text | Natural system file information missing. |
|-------|--|
| Expl. | During startup, Natural checks the system file information for validity. Natural could not find any system file information. Either the system file specified with the profile parameter FNAT is not a valid system file or the system file has been corrupted by unauthorized access. |
| Actn. | Restart Natural with a correct system file. |

NAT7400: Value for dynamic parameter missing.

| Text | Value for dynamic parameter missing. |
|-------|---|
| | Invalid syntax in dynamic parameters. Probably an equal sign (=) or a keyword value is missing. |
| Actn. | Restart the Natural session with correct specification of dynamic parameters. |

137 Natural System Error Messages 7401-7450

NAT7402: No dynamic parameters allowed.

| Text | No dynamic parameters allowed. |
|-------|--|
| | The Natural admininstrator has specified in the default parameter settings for all Natural sessions that parameters cannot be specified dynamically. All dynamic parameters are ignored. |
| Actn. | Start Natural without parameters. |

NAT7403: Specified profile :1: not found. DB/FNR :2:/:3:.

| Text | Specified profile not found. DB/FNR/ |
|-------|---|
| Expl. | Natural should start with a given parameter profile, but it could not be found in the specified system file. |
| Actn. | Check the profile definition and the system file using the SYSPARM utility. |

NAT7404: Automatic time adjustment (TD=AUTO) failed.

| Text | Automatic time adjustment (TD=AUTO) failed. |
|-------|--|
| | When the parameter TD=AUTO is set, Natural uses the difference between physical machine time and logical machine time to set the value for the TD (time differential) parameter. While trying to do this, however, an inconsistency between the times to be evaluated has been detected. The time differential has been set to TD=0. |
| Actn. | Contact Software AG support. |

NAT7405: Product of LS and PS parameters must not exceed 32760.

| Text | Product of LS and PS parameters must not exceed 32760. |
|-------|--|
| - | The product of the values for the parameter LS and PS must not exceed 32760. |
| Actn. | Specify smaller value for LS and/or PS parameter. |

NAT7407: Time zone :1: not defined.

| Text | Time zone not defined. |
|-------|--|
| | The time zone defined in the Natural parameter module (with the profile parameter TD) or in Natural Security is not predefined in the Natural configuration module NATCONFG. |
| Actn. | Define the time zone in the Natural configuration module NATCONFG. |

138 Natural System Error Messages 7501-7550

NAT7508: Compression table full.

| Text | Compression table full. |
|-------|--|
| Actn. | Increase value of CMPRTSZ parameter in Natural parameter module. |

NAT7509: GETMAIN failed for Entire.

| Text | GETMAIN failed for Entire. |
|-------|---|
| - | The subsystem using the corresponding buffer will not be able to run. |
| Actn. | Restart Natural in a larger environment. |

NAT7510: GETMAIN failed for CON-NECT.

| Text | GETMAIN failed for CON-NECT. |
|-------|---|
| | The subsystem using the corresponding buffer will not be able to run. |
| Actn. | Restart Natural in a larger environment. |

NAT7511: GETMAIN failed for TRS.

| Text | GETMAIN failed for TRS. |
|-------|---|
| 1 1 | The subsystem using the corresponding buffer will not be able to run. |
| Actn. | Restart Natural in a larger environment. |

NAT7512: GETMAIN failed for VSAM.

| Text | GETMAIN failed for VSAM. |
|-------|---|
| - | The subsystem using the corresponding buffer will not be able to run. |
| Actn. | Restart Natural in a larger environment. |

NAT7513: GETMAIN failed for EDITOR.

| Text | GETMAIN failed for EDITOR. |
|-------|---|
| | The subsystem using the corresponding buffer will not be able to run. |
| Actn. | Restart Natural in a larger environment. |

NAT7514: GETMAIN failed for PROCESS (ASIZE).

| Text | GETMAIN failed for PROCESS (ASIZE). |
|-------|--|
| Expl. | The subsystem using the corresponding buffer will not be able to run. |
| Actn. | Restart Natural in a larger environment: Increase your region size or increase the size of your Natural thread when running in a thread environment. |

NAT7515: GETMAIN failed for DEBUG.

| Text | GETMAIN failed for DEBUG. |
|-------|---|
| · · | The subsystem using the corresponding buffer will not be able to run. |
| Actn. | Restart Natural in a larger environment. |

NAT7516: GETMAIN failed for PC-CONNECTION.

| Text | GETMAIN failed for PC-CONNECTION. |
|-------|---|
| · · | The subsystem using the corresponding buffer will not be able to run. |
| Actn. | Restart Natural in a larger environment. |

NAT7540: GETMAIN failed for DB2.

Text GETMAIN failed for DB2.

NAT7543: GETMAIN failed for USERBUF buffer.

Text GETMAIN failed for USERBUF buffer.

NAT7544: GETMAIN request failed for :1:.

| Text | GETMAIN request failed for |
|------|---|
| | The requested buffer size exceeded the available space in the current thread/partition/region/task. |
| | Either decrease the size of the buffer, or start Natural in a larger thread/partition/region/task. |

NAT7545: GETMAIN of :1: for :2: buffer failed (:3:/:4:).

| Text | GETMAIN of for buffer failed (reason/response). |
|-------|---|
| Expl. | The requested buffer size exceeds the available space in the current thread/partition/region/task. Possible reason/response codes: (04/0) Upper thread limit exceeded. (52/n) Non-zero response code n from operating (sub-)system GETMAIN. (56/0) Thread overflow size OVSIZE exceeded. For any other reason code, please refer to the Natural messages and codes documentation. |
| Actn. | Either decrease the size of the buffer, or start Natural in a larger thread/partition/region/task, or if (56/0) increase OVSIZE. |

NAT7546: FREEMAIN for :1: buffer failed (:2:/:3:).

| Text | FREEMAIN for buffer failed (reason/response). |
|-------|---|
| | An internal error has occurred. For an explanation of the |
| | reason/response code, see the Natural messages and codes documentation. |
| Actn. | Please contact Software AG support. |

NAT7548: :1: unavailable, reason/reason code :2:/:3:.

| Text | unavailable, reason/reason code/ |
|-------|--|
| Expl. | The indicated Natural component is not available. |
| | Possible reasons are that a subcomponent or a module required to |
| | execute the component is not available or not accessible. |
| | Possible reason codes are: |
| | 04 - Initialization failed. |
| | 08 - GETMAIN failed. |
| | 12 - Module could not be loaded. |
| | 16 - Module has not been linked to Natural. |
| | 20 - Subcomponent does not run with this Natural version |
| Actn. | Contact your Natural administrator. |

Natural System Error Messages 7551-7600

NAT7600: :1: locked by :2:.

| Text | Object is locked. |
|------|---|
| | The object to be locked is already locked, for example, because another user is editing the object. |
| | Wait until the object is available again. |
| | If the lock is erroneous (e.g. after a system failure), use the Natural system command UNLOCK to unlock the object. |

140 Natural System Error Messages 7601-7650

NAT7601: Error in Application Manager.

| Text | Error in Application Manager. |
|-------|---|
| Expl. | An error has occurred in the Application Manager. |

NAT7602: Locking conflict: object is not locked.

| Text | Locking conflict: object is not locked. |
|------|---|
| · · | Either your networking software has an error, or Natural attempted to release an object which it expected to be locked. |
| | Check your environment. |

141 Natural System Error Messages 7651-7700

NAT7660: Connect to server :1: port :2: failed; socket code :3:.

| Text | Connect to server port failed; socket code |
|-------|---|
| Expl. | A connection to the development server failed due to one of the following reasons: A wrong development server name was specified. The specified port ID does not match the port where the development server is listening. The development server is not active. The server machine hosting the development server is not active. |
| Actn. | Check that the specified name matches the development server name, the development server is active, its port matches the specified port, and the server machine is accessible (e.g. via "ping" command). |

NAT7661: Protocol mismatch of Server Nat :1: (:2:) and Nat Studio (:3:)

| Text | Protocol mismatch of Server Nat () and Nat Studio () |
|-------|---|
| | The protocol versions of the Natural Development Server and the Natural Studio do not match. Although the Natural Studio can run with servers using an older or newer version of the protocol, some functionality might not or only partly be supported. |
| Actn. | Upgrade the Natural Development Server or the Natural Studio. |

NAT7662: Development server file for application :1: not unique.

| Text | Development server file for application not unique. |
|-------|--|
| | The specified development server file differs from the active development server file. All mapped applications have to use one common development server file. |
| Actn. | Change the development server file for the current application. |

NAT7663: Connection to NDV server lost or network failure.

| Text | Connection to NDV server lost or network failure. |
|-------|---|
| Expl. | The remote Natural session or the Natural Development Server (NDV) has terminated abnormally, or a network failure has occurred. |
| | Examine the NDV trace output for information on the connection termination. If NDV trace contains no such information, contact your network administrator. Try to remap the session to the server. |
| | If the problem persists, check in the NDV server trace whether your buffer has arrived: - If data have arrived, check for error information in subsequent trace records. - If no data have arrived, contact your network administrator. |
| Actn. | See explanation above. |

NAT7664: Command not applicable within the current context.

| Text | Command not applicable within the current context. |
|-------|--|
| Expl. | The issued command cannot be executed in the selected remote environment or application context. Possible reasons are: - The command is not available for the selected environment or application; e.g. the command "Connect" is issued for a compound application. - The command is not available for the current state of the selected environment or application; e.g. the command "Activate" is issued for a disconnected environment, although only connected environments can be activated. |
| Actn. | Check whether all conditions for issuing the command are fulfilled. |

NAT7665: Command not supported by Natural Development Server.

| Text | Command not supported by Natural Development Server. |
|-------|--|
| | The issued command is not supported by the protocol version of the Natural Development Server. |
| Actn. | Upgrade the Natural Development Server. |

NAT7666: Invalid value specified.

| Text | Invalid value specified. |
|-------|--|
| · · | The value which has been assigned to a property or was specified as method parameter is not allowed in this context. |
| Actn. | Assign a valid attribute value, or use a valid method parameter. |

NAT7667: Natural :1: cannot be used to access NDV server.

| Text | Natural cannot be used to access NDV server. |
|-------|--|
| 1 1 | This Natural version is not capable of using the requested NDV server. |
| Actn. | Upgrade Natural Studio. |

NAT7668: Environment name :1: already exists.

| Text | Environment name already exists. |
|-------|--|
| | The specified environment name is already used either by another mapped environment or by a mapped application. |
| Actn. | Use a different name for the environment to be mapped. |

NAT7669: Function not available, because :1: is not installed.

| Text | Function not available, because is not installed. |
|-------|---|
| | The required component must be installed in order to perform the function specified or to process the object specified. |
| Actn. | Install component, or do not use this function. |

NAT7670: Remote Debug could not be started: :1:

| Text | Remote Debug could not be started. |
|-------|---|
| | An internal error occurred which prevented the session for Remote Debug from being started. For details see the NDV trace, at least trace-level bit 15 should be activated. |
| Actn. | Contact Software AG support. |

NAT7671: Internal error during Remote Debug, terminating.

| Text | Internal error during Remote Debug, terminating. |
|-------|--|
| | The connection to Remote Debug could not be maintained because of internal errors. For details see the NDV trace, at least trace-level bit 15 should be activated. |
| Actn. | Contact Software AG support. |

NAT7672: Parameter error in MAP/UNMAP command.

| Text | Parameter error in MAP/UNMAP command. |
|-------|--|
| Expl. | The MAP/UNMAP command cannot be performed, because the specified parameters are not correct. Possible errors are, for example: - Mandatory parameters of the MAP command are missing (for APPL= at least the application name has to be specified; for ENV= at least the server name and the port number have to be specified). - No parameters are specified for the UNMAP command, but the local environment is active. |
| | - The application/environment specified in the UNMAP command cannot be found. See the Natural system commands documentation for further information. |
| Actn. | Correct the parameter specification. |

NAT7674: The debugger port is already in use.

| Text | The debugger port is already in use. |
|-------|--|
| Expl. | The debugger port specified via the SPODDEBUGPORT parameter is already used by a different program. Therefore the remote connection to the Natural application could not be established. |
| | Set the SPODDEBUGPORT parameter to a different value. Or set the SPODDEBUGPORT parameter to 0; Natural Studio will then automatically select a free port on the machine for debugging. |

NAT7699: :1: locked by :2:.

| Text | locked by |
|-------|------------------------------------|
| Expl. | No detailed explanation available. |

142 Natural System Error Messages 7701-7750

NAT7720: Command not applicable in remote environment.

| Text | Command not applicable in remote environment. |
|------|---|
| | The issued command cannot be executed in a remote (server) environment. |
| | Use the appropriate Natural Studio command or tool. In case of a file-operation command, use an equivalent "Object Menu" operation or "right mouse button" operation to achieve the desired result. |

NAT7721: Command not applicable within the application context.

| Text | Command not applicable within the application context. |
|------|---|
| - | The issued command cannot be executed within the context of an application. |
| | Use the appropriate command in the library workspace, or use the right mouse button "Unlink" command, if you want to unlink an object from the application. |

NAT7722: Command not applicable in local environment.

| Text | Command not applicable in local environment. |
|------|---|
| - | The issued command cannot be executed in a local (client) environment. |
| | Use the appropriate Natural Studio command or tool. In case of a file operation command, use an equivalent "Object Menu" operation or "right mouse button" operation to achieve the desired result. |

NAT7723: Message from server: :1:.

| Text | Message from server: |
|-------|--|
| Expl. | The server has sent a message to indicate a special situation. E.g., if, when deleting/renaming a library, one or more objects could not be deleted or renamed (primarily caused by locked objects), the server reports this to the client. |

NAT7724: Error during session reconnect.

| Text | Error during session reconnect. |
|-------|---|
| Expl. | The Natural Development Server cannot reconnect your session for remote development. Possible reasons are: - Corrupted session directory of Natural Development Server. - Server address space exceeds specified limit of subtasks. - Region size (memory below 16 MB) is too small. - Natural Studio requests a reconnect with an invalid session identifier. |
| Actn. | Examine Natural Development Server trace file for additional error information. |

NAT7725: Cannot create new session directory entry or subtask.

| Text | Cannot create new session directory entry or subtask. |
|-------|--|
| Expl. | The Natural Development Server cannot create a new entry in its session directory or cannot create a new subtask to process remote development. Possible reasons are: - Server address space exceeds specified limit of subtasks. - Region size (memory below 16 MB) is too small. |
| Actn. | Examine Natural Development Server trace file for additional error information. |

NAT7726: New session cannot be initialized.

| Text | New session cannot be initialized. |
|-------|---|
| Expl. | The Natural Development Server cannot perform the basic initialization of a new subtask. Possible reason is shortage of memory above 16 MB. |
| Actn. | Examine Natural Development Server trace file for additional error information. |

NAT7727: Session execution failed.

| Text | Session execution failed. |
|-------|---|
| Expl. | The Natural Development Server cannot locate the Natural session in its session directory. Possible reasons are: The session was cancelled using the server monitor. The session directory is corrupted. The Natural Studio requests a reconnect with an invalid session identifier. |
| Actn. | Examine Natural Development Server trace file for additional error information. |

NAT7728: I/O execution not allowed.

| Text | I/O execution not allowed. |
|-------|--|
| | The remote Natural session executes an I/O, although I/O execution is not permitted. I/O execution is not permitted during session initialization and Natural Security logon processing. |
| Actn. | Locate the I/O buffer in the Natural Development Server trace file and contact Software AG Support. |

NAT7729: Incompatible versions of Web I/O Interface and Natural.

| Text | Incompatible versions of Web I/O Interface and Natural. |
|-------|--|
| Expl. | The NWO server/daemon/service and Natural operate according the NWO protocol specification. Therefore it is required that both components relate to the same NWO protocol version. To assure this, NWO and Natural have a version dependency. This error occurs if the version dependency is violated or Natural is not started by a daemon/service. Under UNIX, OpenVMS and Windows, the version of the NWO daemon/service must match the version of the Natural process that is started by the daemon/service. |
| Actn. | Ensure that the Natural and NWO versions correspond. |

NAT7730: Error during I/O execution.

| Text | Error during I/O execution. |
|------|---|
| | The Natural Studio returns invalid data for the terminal I/O, or there is not enough memory available above 16 MB. |
| | Examine the Natural Development Server trace file for additional error information and contact Software AG Support. |

NAT7731: Protocol element missing.

| Text | Protocol element missing. |
|------|---|
| | For the processing of Natural Development Server (NDV) requests, the NDV requires protocol data; these were not sent by the Natural Studio. |
| | Examine the Natural Development Server trace file for additional error information and contact Software AG Support. |

NAT7732: NDV not installed on Natural system file.

| Text | NDV not installed on Natural system file. |
|-------|--|
| | The Natural Development Server (NDV) cannot locate the NDV transaction-processor modules on the FNAT system file. The Natural Development Server installation is incomplete. |
| Actn. | Check whether the Natural Development Server INPL has been executed on the specified FNAT system file. |

NAT7733: Library undefined, LOGON required.

| Text | Library undefined, LOGON required. |
|-------|--|
| Expl. | The logon library of the Natural Development Server session is undefined. This usually happens if the system command LOGOFF is executed, of if a Natural program executes a RETURN statement and no SETUP record is found. |
| Actn. | Enter a LOGON command to a valid library of your remote environment; or click any library within your remote tree view to continue. |

NAT7734: System command cannot be executed if WEB I/O is active.

| Text | System command cannot be executed if WEB I/O is active. |
|-------|---|
| Expl. | If WEB I/O is active, the system commands SCAN, LIST, SYSMAIN, CATALL and GLOBALS cannot be executed from the command line. |
| Actn. | Do not enter any of the system commands mentioned above. |

| Text | FDIC system file assignment of the NDV server is invalid. |
|-------|---|
| | The file assignment for the FDIC system file which has been specified for the Natural Development Server (NDV) is invalid. The specified assignment does not access a valid FDIC system file. |
| Actn. | Correct the FDIC assignment in order to access a valid FDIC system file. |

NAT7735: FDIC system file assignment of the NDV server is invalid.

NAT7736: FDIC system file of the NDV server is not accessible.

| Text | FDIC system file of the NDV server is not accessible. |
|-------|--|
| | The Natural Development Server (NDV) cannot access the specified FDIC system file. Either the specified database has not been started, or the specified file does not exist in the database. |
| Actn. | Start the database or correct the file number in order to access a valid FDIC system file |

NAT7738: Natural Studio version not supported.

| Text | Natural Studio version not supported. |
|-------|---|
| | With the configuration parameter MINIMUM®STUDIO®VERSION you can customize the allowed client version. Clients with a version below the configured version are rejected. |
| Actn. | Upgrade you client version to the configured version or above. |

NAT7739: Dynamic screen definition not supported.

| Text | Dynamic screen definition not supported. |
|-------|---|
| | The dynamic screen definition (Natural profile parameter TMODEL) is not supported. TMODEL is restricted to actual teminal model definitions (2, 3, 4 or 5). |
| Actn. | Define a supported value for TMODEL, or upgrade the SPoD components to have dynamic screen support. |

143 Natural System Error Messages 7801-7850

NAT7801: Dialog cannot be used as generic document window. Reason: :1:.

| Text | Dialog cannot be used as generic document window. Reason: |
|-------|--|
| Expl. | This error can occur when a Natural dialog is to be displayed as a generic document window in Natural Studio. Common reasons are: (1) The dialog was not created or has already been closed. (2) The dialog is not of type "MDI plug-in window". (3) The creation of the generic document window failed. |
| Actn. | Make sure that the dialog has been created and that it is of type "MDI plug-in window". |

NAT7802: Natural runtime system is busy.

| Text | Natural runtime system is busy. |
|-------|---|
| | An attempt was made to execute or run a program or dialog through the Natural Studio Automation interface, while the Natural runtime in that session was already executing. This is not possible. |
| Actn. | No action required. |

144 Natural System Error Messages 7951-8000

NAT7998: Initialization of access method :1: failed.

| Text | Initialization of access method :1: failed. |
|------|--|
| | The initialization of a print/work file access method has failed. This access method cannot be used during the current session. Any print or work files defined for this access method cannot be used. |
| | Check for the access method error message previously displayed. It should give more detailed information. Correct the problem and restart the session. |

NAT7999: GETMAIN failed for print / work file buffer.

| Text | GETMAIN failed for print / work file buffer. |
|-------|---|
| Expl. | Natural tried to allocate storage for print/work files which were requested either via JCL or via entries in the parameter module. However, there was not enough space available for these files in the Natural partition/region/thread. |
| Actn. | Enlarge size of partition/region/thread, or delete requests for print/ work files. If the problem remains, contact your Natural administrator for review of printer/work file parameters. |

145 Natural System Error Messages 8251-8300

NAT8300: Wrong protocol type, or protocol not supported.

| Text | Wrong protocol type, or protocol not supported. |
|-------|--|
| Expl. | Request Document needs the type of the used document as first part of the requested URL at operand 1. Either no protocol type or a protocol type that is not supported was specified with operand1. |
| Actn. | Change the protocol type to a valid type, e.g. "http://", and run the program again. |

146 Natural System Error Messages 8301-8350

NAT8301: Wrong URL syntax.

| Text | Wrong URL syntax. |
|-------|---|
| | REQUEST DOCUMENT needs the correct syntax of the requested URL at operand1. The syntax of the specified URL was not correct. No protocol type or an unsupported protocol type was specified with operand1. |
| Actn. | Correct the URL of operand1 and run the program again. |

NAT8302: Request method :1: not supported.

| Text | Request method :1: not supported. |
|-------|---|
| | REQUEST DOCUMENT has been advised by a user-defined header "REQUEST®METHOD" to use a different request method. The REQUEST DOCUMENT statement does not support the specified request method. |
| Actn. | Delete the header value, or change the header "REQUEST®METHOD" to a valid value. |

NAT8303: Internal error with REQUEST DOCUMENT statement.

| Text | Internal error with REQUEST DOCUMENT statement. |
|------------|--|
| 1 1 | An internal error has occurred while executing a REQUEST DOCUMENT and writing back error messages. |
| Actn. | Contact Software AG support. |

NAT8304: HTTP request failed. Reason :1:.

| Text | HTTP request failed. Reason :1:. |
|-------|---|
| - | The REQUEST DOCUMENT statement has received an error from the |
| | transport layer. |
| Actn. | Contact Software AG support. |

NAT8305: Header :1: is longer than the receiving variable.

| Text | Header :1: is longer than the receiving variable. |
|------|---|
| | The REQUEST DOCUMENT statement has returned a header value which is longer than the receiving variable. |
| | Use a GIVING clause to ignore this error, increase the length of the receiving variable, or use a dynamic variable. |

NAT8306: Return value is longer than the receiving variable.

| Text | Return value is longer than the receiving variable. |
|-------|---|
| | The REQUEST DOCUMENT statement has returned a value which is longer than the receiving variable. |
| Actn. | Use a GIVING clause to ignore this error, increase the length of the receiving variable, or use a dynamic variable. |

NAT8307: Cannot convert header :1: to format :2: of receiving variable.

| Text | Cannot convert header :1: to format :2: of receiving variable. |
|------|---|
| | The REQUEST DOCUMENT statement has returned a header value which is no valid alphanumeric representation of the format of the receiving variable. LASTMSG shows additional information about the header value. |
| | Check the program and correct the error. Change the format of the receiving variable. |

NAT8310: Required parts of Internet Explorer missing.

| Text | Required parts of Internet Explorer missing. |
|-------|---|
| Expl. | Request Document relies on technology delivered with Internet Explorer 4 or above. "wininet.dll" is particularly important. Request Document failed because required parts of the Internet Explorer are missing. |
| Actn. | Install at least a minimum installation package for Internet Explorer 4 or above. |

NAT8311: Error parsing XML document, line :1: col. :2:; msg. :3:.

| Text | Error parsing XML document, line col; msg |
|-------|---|
| | The XML parser terminated with an error. The XML input document is syntactically invalid. The line/column at which the error occurred and the message returned by the parser are indicated in the error message. |
| Actn. | Correct the XML input document. |

NAT8312: Error during XML parser processing, reason :1:.

| Text | Error during XML parser processing, reason |
|-------|--|
| Expl. | Possible reasons: |
| | 1: Error in parser access; XML parser not available. |
| | 2: Parser instance request failed; new instance not available. |
| | 3: Parser initialization failed. |
| | 4: XML input document is invalid. |
| | 5: Unsupported encoding is used. |
| | 6: Internal parse save-area stack overflow. |
| | 7: Resizing of parse operand failed. |
| Actn. | Check the XML parser condition or XML document. |

NAT8313: GETMAIN for :1: failed; return code :2:.

| Text | GETMAIN for failed; return code |
|-------|---|
| Expl. | Natural for XML is not able to allocate its internal buffers. Return code = 4 : Not enough storage. Return code > 4 : Internal error. |
| Actn. | If return code = 4, increase the size of thread/region/partition/task; otherwise contact Software AG support. |

NAT8314: No Natural ICU handler available.

| Text | No Natural ICU handler available. |
|-------|---|
| Expl. | The Natural ICU handler is not available. |
| | Possible reason are: |
| | - The ICU handler module is not linked to Natural or cannot be loaded. |
| | - The session profile parameter for ICU is set to OFF. |
| | - An error occurred during the initialization of the Natural ICU. |
| | The Natural ICU handler is a prerequisite for the Natural XML handler. |
| Actn. | Depends on the reason of the error. If an initialization error has occurred, check the session initialization error messages. |

NAT8315: Incompatible versions of Natural and Natural XML.

| Text | Incompatible versions of Natural and Natural XML. |
|-------|--|
| · · | Version 4.2 of Natural XML can only be used with Natural Version 4.2.1 or above. |
| Actn. | Use a compatible Natural version. |

NAT8316: Unsupported operating/TP system.

| Text | Unsupported operating/TP system. |
|-------|--|
| Expl. | Currently, Natural XML does not support BS2/UTM. |
| Actn. | Use a supported environment. |

NAT8317: Natural OS/TP driver is not LE370/CRTE enabled.

| Text | Natural OS/TP driver is not LE370/CRTE enabled. |
|-------|--|
| | To use the REQUEST DOCUMENT statement, the OS/TP driver used must be compiled with the option LE370=ON or CRTE=ON. |
| Actn. | Install a driver with the requested option. |

NAT8318: Module :1: is missing in link-edit.

| Text | Module is missing in link-edit. |
|-------|---|
| Expl. | A module is missing in the link-edit of the Natural front-end stub. |
| Actn. | Include the module in the link-edit. |

NAT8319: Natural statements REQUEST DOCUMENT and PARSE disabled.

| Text | Natural statements REQUEST DOCUMENT and PARSE disabled. |
|-------|---|
| Expl. | The profile parameter XML was set to "OFF". |
| | Set the XML profile parameter or at least one of the subparameters RDOC or PARSE to "ON". |

NAT8320: Natural XML initialization failed.

| Text | Natural XML initialization failed. |
|-------|--|
| - | The reason for this failure is explained by the more detailed error message issued together with this error message. |
| Actn. | See explanation of detailed message. |

NAT8321: Natural statement PARSE is disabled.

| Text | Natural statement PARSE is disabled. |
|-------|--|
| 1 | The subparameter PARSE of the Natural profile parameter XML is set to "OFF". |
| Actn. | Change the PARSE subparameter value to "ON". |

NAT8322: Natural statement REQUEST DOCUMENT is disabled.

| Text | Natural statement REQUEST DOCUMENT is disabled. |
|-------|---|
| Expl. | The subparameter RDOC of the Natural profile parameter XML is set to "OFF". |
| Actn. | Change the RDOC subparameter value to "ON". |

NAT8323: Nested parse loop not allowed.

| Text | Nested parse loops not allowed. |
|-------|--|
| Expl. | Natural detected a recursive call to the XML parser. |
| Actn. | Correct program. |

147 Natural System Error Messages 8351-8400

NAT8400: Tamino error :1: occurred.

| Text | Tamino error occurred. |
|-------|--|
| Expl. | Tamino has encountered an error. |
| Actn. | For more information, see Tamino Messages and Codes. |

148 Natural System Error Messages 8401-8450

NAT8401: Internal error :1: in Tamino database handler.

| Text | Internal error in Tamino database handler. |
|-------|---|
| | An internal error occurred in the Tamino database handler. The error code is contained in the error message. |
| Actn. | Contact Software AG support and quote the complete error message. |

NAT8402: Natural for Tamino runtime error :1:.

| Text | Natural for Tamino runtime error |
|-------|--|
| | The following Natural for Tamino runtime error has occurred: - 1: The value specified for the index of an array is less than 1. |
| Actn. | Check program and correct error. |

NAT8410: Wrong URL for DBID :1:.

| Text | Wrong URL for DBID |
|------|--|
| | The URL used in the request is wrong, or an invalid protocol type is specified in the URL, or the specified server behind this URL could not be contacted. |
| | Check the URL in the Natural configuration file and correct it, or check the existence of the server in the URL. |

NAT8411: HTTP request failed with response code :1:.

| Text | HTTP request failed with response code |
|-------|---|
| | A HTTP request returns a response code not equal to "200". The standardized response code indicates the possible error situation. |
| Actn. | Examine the response code and correct the error or contact Software AG support. |

NAT8412: Internal error in HTTP request.

| Text | Internal error in HTTP request. |
|-------|--|
| Expl. | An error occurred while executing an HTTP request. |
| Actn. | Contact Software AG support. |

NAT8415: Error while mapping XML Schema to DDM with reason :1:.

| Text | Error while mapping XML Schema to DDM with reason |
|-------|--|
| Expl. | Possible reasons: 1: Illegal syntax used in XML Schema. 2: Unresolved element reference. 3: Unresolved type reference. 4: Unresolved group reference. 5: Requested doctype or schema not found. |
| Actn. | Check the validity of the XML Schema. References have to be resolved within the Schema internally. |

NAT8416: Maximum number of nested levels exceeded.

| Text | Maximum number of nested levels exceeded. |
|-------|--|
| | The maximum number of nested levels in a DDM is 99. This number was exceeded while generating a DDM from the given XML Schema. |
| Actn. | Modify the XML Schema so that is has fewer nested structures. |

NAT8417: Internal error in DDM generation for Tamino XML Schema.

| Text | Internal error in DDM generation for Tamino XML Schema. |
|-------|---|
| | An error has occurred while generating a Natural DDM from a Tamino XML Schema definition. |
| Actn. | Contact Software AG support. |

NAT8418: Use of unsupported XML schema element :1:.

| Text | Use of unsupported XML schema element |
|-------|--|
| Expl. | An unsupported XML schema element was used: 1: "mixed=true" (mixed content mode) is not allowed. 2: maxOccurs > 1 not allowed for sequence, choice and all. 3: wildcards (any, anyAttribute) are not allowed. |
| Actn. | Do not use the stated XML schema element when generating a DDM for this schema. |

149 Natural System Error Messages 8951-9000

NAT9000: Natural error text 9nnn cannot be displayed.

| Text | Natural error text 9nnn cannot be displayed. |
|-------|--|
| Expl. | For error NAT9nnn, there is no specific error message available. |

150 Natural System Error Messages 9901-9950

NAT9901: Natural/TSO runtime environment is not TSO.

| Text | Natural/TSO runtime environment is not TSO. |
|-------|--|
| Expl. | Natural/TSO has been started in a non-TSO environment. |
| | Natural/TSO can run in a TSO environment only. Link the appropriate frontend interface for this environment to your nucleus. |

NAT9902: Dataset cannot be opened - :1:.

| Text | Dataset cannot be opened |
|-------|---|
| Expl. | The required dataset cannot be opened. Either it is not or incorrectly defined in the JCL, or it cannot be opened due to other reasons. |
| Actn. | Supply the correct dataset definition in the JCL. Check for operating-system error messages in the job log to ascertain the cause of the error. |

NAT9903: NATSTUB not linked to Natural nucleus :1:.

| Text | NATSTUB not linked to Natural nucleus :1:. |
|-------|---|
| | Either the module NATSTUB is not linked to the Natural nucleus; or the shared nucleus :1: has been loaded; but NATSTUB is not defined as its entry point. |
| Actn. | Link the module NATSTUB to the Natural nucleus. If a shared nucleus is used, specify CMSTUB as its entry point in the link job. |

NAT9904: Invalid Natural nucleus - :1:.

| Text | Invalid Natural nucleus |
|-------|--|
| Expl. | The version of the Natural nucleus module, as indicated in the error message, does not correspond to the front-end interface module. For example, the front-end has loaded a shared nucleus of a different version. |
| Actn. | Link the correct Natural nucleus; or specify a correct shared nucleus name, using the profile parameter NUCNAME. |

NAT9905: Terminal I/O error - :1:: RC=:2:.

| Text | Terminal I/O error - :1:: RC=:2:. |
|-------|---|
| Expl. | A terminal I/O error has occurred. The I/O response code RC=:2: indicates the reason for the failure of request :1:. Under TSO, the response code comes from the failing TSO I/O request macro TPUT or TGET. |
| Actn. | Check the meaning of the response code in the TSO documentation. Contact Software AG Support for further problem analysis. |

NAT9906: Natural server cannot run as LE main routine.

| Text | Natural server cannot run as LE main routine. |
|-------|---|
| Expl. | The Natural front-end (NATOS) received control from a front-end server stub which did not initialize the IBM language environment. NATOS as a server generated with LE370=YES cannot run as an LE main routine. |
| Actn. | Either generate NATOS with option LE370=NO, or generate the front-end server stub with LE support if possible. |

NAT9907: Unsupported operating-system version.

| Text | Unsupported operating-system version. |
|-------|--|
| Expl. | The current operating-system version is not supported by this Natural version. |
| Actn. | See Natural documentation for supported operating systems and versions. |

NAT9908: Nucleus module does not reside below 16 MB line - :1:

| Text | Nucleus module does not reside below 16 MB line |
|-------|---|
| | The nucleus module specified in the message must be executed below the 16 MB line due to operating-system requirements. |
| Actn. | Re-link the specified nucleus module with parameter MODE RMODE(24). |

NAT9909: Unsupported teleprocessing system version.

| Text | Unsupported teleprocessing system version. |
|-------|---|
| Expl. | This version of the teleprocessing system (e.g. Com-plete) is not supported by Natural. It is either an old version which does not contain the facilities required by Natural, or a new version which is not yet supported by your version of Natural. |
| Actn. | Either install a newer version of the teleprocessing system, or install a newer version of Natural. |

NAT9910: Session communication area missing or invalid.

| Text | Session communication area missing or invalid. |
|-------|---|
| | The Natural server session communication area is missing or invalid. The session communication area is internally used by the Natural server and must be supplied by the front-end server stub. |
| Actn. | Contact Software AG Support for further problem analysis. |

NAT9911: Invalid storage thread size specified.

| Text | Invalid storage thread size specified. |
|-------|---|
| | Running Natural as a server requires the acquisition of main-storage threads of a fixed size. The thread size defined by the front-end server stub is invalid. It must be in the range from 256 kilobytes to 16 megabytes. |
| Actn. | Specify a correct thread size in the front-end server stub definitions. |

NAT9912: The number of threads is invalid or too high.

| Text | The number of threads is invalid or too high. |
|-------|---|
| Expl. | Running Natural as a server requires the acquisition of main-storage threads. The number of threads defined by the front-end server stub is invalid or too great. It must be in the range from 0 to 8191, and the total thread storage must be less than 2 gigabytes. |
| Actn. | Reduce the number of threads or the thread size in the front-end server stub definitions. |

NAT9913: Server environment already initialized.

| Text | Server environment already initialized. |
|------|--|
| 1 1 | The front-end server stub requested Natural to initialize the server environment, but the server environment has already been initialized. |
| | Terminate the server environment before restarting it. Contact Software AG Support for further problem analysis. |

NAT9914: GETMAIN for common server table failed.

| Text | GETMAIN for common server table failed. |
|-------|---|
| Expl. | The Natural server environment cannot be initialized because the GETMAIN for its central control block has failed. Sufficient region storage must be available. |
| Actn. | Increase the region size for the Natural server. If the problem cannot be solved, contact SAG technical support for further problem analysis. |

NAT9915: GETMAIN for thread storage failed.

| Text | GETMAIN for thread storage failed. |
|-------|---|
| | The Natural server environment cannot be initialized because a GETMAIN for its storage threads has failed. Sufficient region storage must be available. |
| Actn. | Increase the region size for the Natural server or reduce the number or the size of its storage threads in the frontend stub definitions. |

NAT9916: Error retrieving server name token. RC=:1:.

| Text | Error retrieving server name token. RC= |
|-------|--|
| Expl. | The central anchor for the Natural server is an MVS name token. The retrieve request for the name token has failed with the decimal return code shown in the message. The explanation of the return code can be found in the IBM MVS Authorized Assembler Services Reference under the IEANTRT macro call description. |
| Actn. | If you cannot find the reason for the problem and correct it, contact Software AG technical support for further problem analysis. |

NAT9917: Error creating server name token. RC=:1:.

| Text | Error creating server name token. RC= |
|-------|--|
| Expl. | The central anchor for the Natural server is an MVS name token. The create request for the name token has failed with the decimal return code shown in the message. The explanation of the return code can be found in the IBM MVS Authorized Assembler Services Reference under the IEANTCR macro call description. |
| Actn. | If you cannot find the reason for the problem and correct it, contact Software AG technical support for further problem analysis. |

NAT9918: Error deleting server name token. RC=:1:.

| Text | Error deleting server name token. RC= |
|-------|--|
| Expl. | The central anchor for the Natural server is an MVS name token. The delete request for the name token has failed with the decimal return code shown in the message. The explanation of the return code can be found in the IBM MVS Authorized Assembler Services Reference under the IEANTDL macro call description. |
| Actn. | If you cannot find the reason for the problem and correct it, contact Software AG technical support for further problem analysis. |

NAT9919: Invalid server function code.

| Text | Invalid server function code. |
|-------|--|
| - | The frontend server stub called the Natural server with an invalid server function code. |
| Actn. | Contact SAG technical support for further problem analysis. |

NAT9920: Roll server not active. SUBSID=:1:.

| Text | Roll server not active. SUBSID=:1:. |
|-------|---|
| Expl. | The Natural server environment requires the Natural roll server for running multiple server sessions within a limited number of storage threads. Either there is no roll server started for the specified Natural subsystem ID or the SUBSID profile parameter is incorrectly or dynamically specified in the Natural parameter module. |
| Actn. | Start the Natural roll server for the subsystem ID or set the SUBSID profile parameter correctly or use SUBSID=" " to run without a roll server or specify this in the frontend server stub definitions. |

NAT9921: Server environment not initialized.

| Text | Server environment not initialized. |
|-------|--|
| Expl. | The frontend server stub called Natural with a server function code other than "initialize server" and the Natural server environment is in uninitialized state. |
| | Restart the frontend server stub to reset its state completely. Contact SAG technical support for further problem analysis. |

NAT9922: The initialization session cannot be rolled.

| Text | The initialization session cannot be rolled. |
|-------|---|
| | The frontend server stub requested a session create, roll-out or roll-in server function while the Natural server was initializing. During the server initialization phase these server functions are not allowed. |
| Actn. | Contact SAG technical support for further problem analysis. |

NAT9923: No server clone session available.

| Text | No server clone session available. |
|-------|---|
| | The frontend server stub requested a session create but the clone session had not been saved yet. |
| Actn. | Contact SAG technical support for further problem analysis. |

NAT9924: Session ID missing or invalid.

| Text | Session ID missing or invalid. |
|-------|--|
| | The Natural server session ID is a unique internal ID to identify a Natural session. The frontend server stub passed either no session ID or a hexadecimal null session ID which is not allowed or the session ID hads been modified. |
| Actn. | Contact SAG technical support for further problem analysis. |

NAT9925: Session ID already exists.

| Text | Session ID already exists. |
|-------|---|
| | The front-end server stub requested a "session create" but a session with the same session ID exists already and is ready to run. |
| Actn. | Contact Software AG Support for further problem analysis. |

NAT9926: Session not in rolled-in status.

| Text | Session not in rolled-in status. |
|-------|--|
| | The frontend server stub requested a session roll-out, execute or save clone function, but the session is not in rolled-in state. |
| Actn. | Contact SAG technical support for further problem analysis. |

NAT9927: Session not in rolled-out status.

| Text | Session not in rolled-out status. |
|-------|--|
| | The frontend server stub requested a session roll-in function, but the session is not in rolled-out state. |
| Actn. | Contact SAG technical support for further problem analysis. |

NAT9928: Compression failed during roll-out. RC=:1:.

| ſ | Text | Compression failed during roll-out. RC= |
|---|-------|--|
| E | | The Natural thread storage compression failed. The exact reason is indicated by the decimal return code RC=00nn. It is explained in the Natural documentation. |
| I | Actn. | Contact Software AG support for further problem analysis. |

NAT9929: Decompression failed during roll-in. RC=:1:.

| Text | Decompression failed during roll-in. RC= |
|-------|--|
| | The Natural thread storage decompression failed. The exact reason is indicated by the decimal return code RC=00nn. It is explained in the Natural documentation. |
| Actn. | Contact SAG technical support for further problem analysis. |

NAT9930: GETMAIN failed for roll buffer.

| Text | GETMAIN failed for roll buffer. |
|------|--|
| | During Natural session thread storage roll-out the GETMAIN request for the roll buffer failed. Sufficient region storage must be available to save the compressed session storage. |
| 1 | Increase the region size for the Natural server or use the Natural roll server as roll facility. |

NAT9931: The AUTOTERM facility cannot be initialized.

| Text | The AUTOTERM facility cannot be initialized. |
|-------|--|
| Expl. | In a Natural server environment, the automatic server termination facility helps to avoid problems caused by an unintended DETACH of the server initialization TCB (e.g. MVS abends A03, no server resource cleanup etc.). The AUTOTERM facility cannot be initialized due to storage protection problems. |
| | Disable the AUTOTERM facility in the frontend server stub definitions or contact SAG technical support for further problem analysis. |

NAT9932: Natural runtime error occurred - :1:.

| Text | Natural runtime error occurred - :1:. |
|------|---|
| | During the execution of a Natural server session, the indicated Natural runtime error :1: occurred. |
| | Check the complete runtime error message issued by Natural. It can be found either in the return data on the client side or in the Natural standard output dataset of the server. |

NAT9933: Roll server ALLOCATE request failed. RC=:1:/:2:.

| Text | Roll server ALLOCATE request failed. RC=/ |
|------|--|
| Expl | L. During session creation, the ALLOCATE request for a new roll-file slot failed. Sufficient roll-file storage must be available. The reason for the failure is indicated by the decimal return/reason codes. These are explained in the Natural documentation. |
| Actr | n. If you cannot find the reason for the problem and correct it, contact Software AG support for further problem analysis. |

NAT9934: Roll server WRITE request failed. RC=:1:/:2:.

| Text | Roll server WRITE request failed. RC=/ |
|-------|---|
| | During session roll-out, the WRITE request to the Natural roll server failed. The reason for the failure is indicated by the decimal return/reason codes. These are explained in the Natural documentation. |
| Actn. | If you cannot find the reason for the problem and correct it, contact Software AG support for further problem analysis. |

NAT9935: Roll server READ request failed. RC=:1:/:2:.

| Text | Roll server READ request failed. RC=:1:/:2:. |
|-------|--|
| Expl. | During session roll-in the READ request from the Natural roll server failed. The reason for the failure is indicated by the decimal return/reason codes. These are explained in the Natural Documentation. |
| Actn. | If you cannot find the reason for the problem and correct it, contact SAG technical support for further problem analysis. |

NAT9936: Roll server FREE request failed. RC=:1:/:2:.

| Text | Roll server FREE request failed. RC=/ |
|-------|--|
| Expl. | During session termination, the FREE request to the Natural roll server failed. The reason for the failure is indicated by the decimal return/reason codes. These are explained in the Natural documentation. |
| Actn. | If you cannot find the reason for the problem and correct it, contact Software AG support for further problem analysis. |

NAT9937: Server I/O subtask cannot be started. RC=:1:/:2:.

| Text | Server I/O subtask cannot be started. RC=:1:/:2:. |
|-------|--|
| Expl. | In the Natural server environment, the whole I/O handling is done by a separate MVS subtask, started during server initialization. The ATTACH request for the I/O subtask failed. The reason for the failure is indicated by RC=:1:/:2:, where :1: is the decimal return code of the internal function code :2:. |
| Actn. | Contact Software AG Support for further problem analysis. |

NAT9938: Termination of SMARTS environment failed.

| Text | Termination of SMARTS environment failed. |
|-------|---|
| Expl. | No further explanation available. |
| Actn. | Contact Software AG support. |

NAT9939: :1: RC=:2:

| Text | Remote front-end communication error. RC= |
|-------|--|
| Expl. | A Natural server environment uses the Natural remote front-end to dispatch a Natural session in a remote TP environment (e.g. CICS). This is used, for example, by the NDV CICS Adapter. This error indicates an error in the communication between the Natural server environment and the remote TP environment. The meaning of the RC value depends on the error text. For example: - "Cannot load NCI front-end RC=": RC contains the CICS EIB response code. - "Error at Remote Gateway Obtain/Restore": RC contains the response code from the NDV remote gateway. |
| Actn. | In case of a CICS EIB response code, examine the CICS messages or the remote front-end trace for further error information. In case of a remote gateway RC, contact Software AG technical support. |

NAT9940: Server parameter list(s) missing or invalid.

| Text | Server parameter list(s) missing or invalid. |
|-------|---|
| | A mandatory Natural server parameter list is missing or invalid. A Natural front-end server stub communicates with a Natural server session using internal parameter lists, which are mandatory depending on the internal server function. |
| Actn. | Contact Software AG Support for further problem analysis. |

NAT9941: Wrong Smarts version for use of LE/370.

| Text | Wrong Smarts version for use of LE/370. |
|-------|---|
| - | Smarts version V272 is required to support the CEEPIPI interface for LE/370 programs. |
| Actn. | Install the required Smarts version. |

NAT9942: Server Front-End incompatible with Natural version.

| Text | Server Front-End incompatible with Natural version. |
|-------|---|
| Expl. | The Front-End Server Stub requires a Natural version different from the version of the current Natural environment-dependent nucleus. |
| Actn. | Install and use a compatible Natural version according to the Front-End Server Stub documentation. |

NAT9943: Logic error in Natural program for asynchronous session.

| Text | Logic error in Natural program for asynchronous session. |
|-------|--|
| - | Input data requested, but an asynchronous session runs without any input device. |
| | To avoid this error situation, check the Natural system variable *SCREEN-IO. |
| Actn. | Correct the program logic. |

151 Natural System Error Messages 9951-9999

NAT9965: Natural termination forced by administrator - :1:.

| Text | Natural termination forced by administrator |
|-------|---|
| Expl. | The session has been marked for termination by the Review for Natural command TERMNAT within the Review SYSRNM administrator application. When the session resumes after a terminal I/O, it is terminated. The user ID of the Review SYSRNM administrator is indicated at the end of the message. |
| Actn. | None. |

NAT9966: Session terminated due to license check failure.

| Text | Session terminated due to license check failure. |
|-------|---|
| Expl. | The session terminated due to a problem with your product license. Natural cannot start without a valid license. The license module is either not linked or invalid or insufficient for your environment. |
| Actn. | Check the session initialization error messages for more detailed information about the problem. If you have no correct license file, please contact Software AG. |

NAT9967: Termination forced by unhandled LE condition - :1:.

| Text | Termination forced by unhandled LE condition |
|-------|--|
| Expl. | During the execution of an LE (IBM Language Environment) subprogram, an error condition has occurred. As no condition handler was active in the subprogram to handle the error, control has been passed to the Natural LE condition handler, which calls LE services to write an LE snap dump to CEEDUMP and to issue more detailed LE error messages. Accordung to the DU profile parameter, Natural has been terminated with a dump. |
| | 1 |

| Actn. | Check the LE error condition, the messages and the snap dump to find |
|-------|---|
| | out the reason of the error. If necessary, correct the LE subprogram. |

NAT9968: Natural termination forced by DUE - :1: :2: :3:.

| Text | Natural termination forced by DUE - :1: :2: :3:. |
|-------|---|
| Expl. | Error :3: has occurred, and Natural has been terminated with a dump. The Natural program :1: has caused the error on line number :2:. :3: is the error message ID which was defined by profile parameter parameter DUE to get a dump. If :1: and :2: are missing, there wasn"t any program active when the error occurred. |
| Actn. | Analyse the dump which has been produced, and correct the error. If necessary, contact Software AG Support. |

NAT9969: Natural escaped from error loop - :1: :2: NAT:3:.

| Text | Natural escaped from error loop nnnn NATnnnn. |
|------|--|
| | An error loop has occurred, and Natural has been terminated. "" - is the name of the program which caused the error. "nnnn" - is the number of the source-code line which caused the error. "NATnnnn" - is the number of the last error which occurred before NAT9969 was issued. |

NAT9970: Natural initialization failed due to ITERM=ON.

| Text | Natural initialization failed due to ITERM=ON. |
|------|---|
| | During the initialization of Natural, an error condition occurred. This message is preceded by one or more other Natural error messages. The session is terminated because profile parameter ITERM=ON is set. |
| | Correct the error as indicated by the preceding error messages, or set ITERM=OFF (not possible with STACK=INPL). |

NAT9971: Session terminated by front-end driver - RC=:1:.

| Text | Session terminated by front-end driver - RC=:1:. |
|-------|---|
| - | During session initialization, the environment- dependent driver has detected a crucial error and the session cannot be continued. RC=:1: indicates the driver-error reason code. |
| Actn. | Contact Software AG Support. |

NAT9972: Natural module missing or invalid - :1:.

| Text | Natural module missing or invalid - :1:. |
|-------|---|
| 1 1 | During initialization Natural has detected that the module :1: is missing or its maintenance level does not match. |
| Actn. | Link the correct module to the Natural nucleus and restart Natural. |

NAT9973: Abend :1: :2:.

| Text | Abend :1: :2:. |
|-------|--|
| | An unexpected internal runtime error has occurred. The session was terminated and a dump was produced. :1: is name of the nucleus component which caused the error. :2: contains additional error information (optional). |
| Actn. | Save the dump and contact Software AG Support. |

NAT9974: Natural termination forced by abend :1:.

| Text | Natural termination forced by abend |
|-------|--|
| Expl. | Natural has been abnormally terminated after the abend condition shown in the error message has occurred, and the profile parameter DU=ON was set. The abend condition was set by the operating system and/or TP system in use. For an explanation of the abend condition, see the appropriate operating-system or TP-system documentation. Possible abend conditions are, for example: "S0C7" - data exception, "AICA" - possible loop under CICS, "ATCH" - task cancelled by operator (CICS). If the abend occurred during Adabas call processing, the indicator ADABAS is added after the abend code. |
| Actn. | Analyse the dump which has been produced, and correct the error. If necessary, contact Software AG Support. |

NAT9975: Back-end program not found - :1:.

| Text | Back-end program not found - :1:. |
|------|---|
| | The Natural session was terminated normally, but the program :1:, which should receive control after the session termination (as specified with the profile parameter PROGRAM), could not be found. |
| | Make sure that the correct program name is specified with the PROGRAM parameter and the program is contained in the appropriate library. |

NAT9976: Initialization buffer too small.

| Text | Initialization buffer too small. |
|-------|---|
| Expl. | Natural could not be initialized because there was not enough space in the initialization buffer. The size of this buffer is determined by the profile parameter ISIZE. |
| Actn. | Increase value for ISIZE parameter in the Natural parameter module, then start Natural session again. |

NAT9977: Permanent I/O error during input processing.

| Text | Permanent I/O error during input processing. |
|-------|--|
| Expl. | During batch processing, Natural did not receive any input data. Or: During online processing, this message is issued to the console in case of an I/O error, because in such a case the associated output device is considered to be inoperational. |
| Actn. | Make sure input data are passed correctly to Natural. |

NAT9978: Error occurred during execution/compilation.

| Text | Error occurred during execution/compilation. |
|-------|--|
| Expl. | During Natural batch processing, an error has occurred when a program was being compiled or executed. Batch processing was continued after the error. The session was terminated with return code "4". |
| | Check the output protocol for any error messages. Correct the error, and re-run the batch job if necessary |

NAT9979: Terminal converter module not linked - :1:

| Text | Terminal converter module not linked |
|-------|---|
| Expl. | Natural was invoked with terminal type which cannot be supported because the corresponding converter module for this terminal type has not been linked to the Natural nucleus or is incompatible with the current environment. |
| Actn. | Link the missing module to the Natural nucleus or specify a correct terminal type by means of the profile parameter TTYPE. |

NAT9980: Nucleus module does not reside in residentpage - :1:.

| Text | Nucleus module does not reside in residentpage |
|-------|---|
| Expl. | The called program is not loaded as a Com-plete resident program. |
| Actn. | Load the program as a Com-plete resident program. |

NAT9981: GETMAIN for back-end program data failed.

| Text | GETMAIN for back-end program data failed. |
|-------|---|
| | The size requested for the back-end program data cannot be allocated in the Natural thread. |
| Actn. | Increase the thread size. |

NAT9982: Error occurred during session termination.

| Text | Error occurred during session termination. |
|-------|--|
| 1 1 | An error has occurred during session termination. The corresponding error message has been issued before. |
| Actn. | Check the corresponding error message and correct the error if necessary. |

NAT9983: Conversation I/O requested, nucleus/thread displaced.

| Text | Conversation I/O requested, nucleus/thread displaced. |
|-------|--|
| Expl. | The nucleus and/or the thread has been displaced during the last terminal I/O. |
| Actn. | Place the Natural nucleus in the (E)LPA and/or do not specify RELO=FORCE/ON. |

NAT9984: Natural address relocation failed - RC=:1:.

| Text | Natural address relocation failed - RC= |
|-------|---|
| Expl. | An internal error has occurred. |
| Actn. | Contact Software AG support. |

NAT9985: Thread-locked sessions cannot be recovered.

| Text | Thread-locked sessions cannot be recovered. |
|-------|---|
| Expl. | Com-Plete tries to recover a Natural session, which is not possible as the session runs in RELO=OFF mode. The session must be terminated. |
| Actn. | Restart session with RELO=ON. |

NAT9986: Natural parameter module missing or invalid.

| Text | Natural parameter module missing or invalid. |
|-------|--|
| Expl. | Either no Natural parameter module has been linked to the Natural environment dependant nucleus, or the parameter module is invalid, e.g. it was assembled against a Natural macro library of an older version or an older maintenance level. |
| Actn. | Re-assemble the Natural parameter module using the macro library of the current maintenance level and link it to the Natural nucleus. |

NAT9987: Natural session terminated abnormally - RC=:1:.

| Text | Natural session terminated abnormally - RC=:1:. |
|-------|--|
| | The Natural session was terminated by a TERMINATE statement with return code :1: in a Natural program. |
| Actn. | No action required. |

NAT9988: Invalid system file information.

| Text | Invalid system file information. |
|-------|--|
| | The database ID and/or file number of the Natural system file FNAT have been changed, but the Natural system environment has not been adjusted to this change. |
| Actn. | Use function "A" of the INPL utility to adjust the system environment. |

NAT9989: Natural versions do not agree.

| Text | Natural versions do not agree. |
|-------|---|
| Expl. | During initialization, Natural checks whether the versions of the environment-dependent interface and the Natural shared nucleus are of the same Natural release. |
| Actn. | Re-assemble and re-link the environment-dependent interface with the correct Natural macro and link libraries. |

NAT9990: Natural initialization failed.

| Text | Natural initialization failed. |
|-------|---|
| | During initialization of Natural, an error condition occurred which |
| | does not allow for continuation of the Natural session. |
| | This message is preceded by one or more other Natural error messages. |
| Actn. | Correct error as indicated by preceding error messages. |

NAT9991: Required module not linked - :1:.

| Text | Required module not linked - :1:. |
|-------|--|
| 1 1 | During initialization Natural has detected that module :1: is missing. The module is required to run the Natural nucleus. |
| Actn. | Link the missing module to the Natural nucleus and restart Natural. |

NAT9992: Session terminated due to unrecoverable abend :1:.

| Text | Session terminated due to unrecoverable abend :1:. |
|-------|---|
| Expl. | During the attempt to recover the Natural session from abend :1:, another abend has occurred. To avoid an abend loop, the Natural session was terminated. |
| Actn. | Analyse the dump which has been produced, and correct the error. If necessary, contact Software AG Support. |

NAT9993: Adabas link module missing or invalid - :1:.

| Text | Adabas link module missing or invalid - :1:. |
|-------|--|
| | The Adabas link module :1: specified by profile parameter ADANAME cannot be loaded or is invalid. Either the load library is missing or invalid, or the specified module does not exist or has been linked incorrectly. |
| Actn. | Ensure that the correct load library is attached to the Natural session and that it contains the correct Adabas link module. |

NAT9994: Dynamic parameter string is too long.

| Text | Dynamic parameter string is too long. |
|-------|--|
| | The character string supplied as dynamic parameters at the start of the Natural session is too long. It must not exceed 32767 characters. This includes the dynamic parameters read from the CMPRMIN file. |
| Actn. | Restart the Natural session with fewer dynamic parameters. |

NAT9995: Natural session terminated normally.

| Text | Natural session terminated normally. |
|-------|--|
| Expl. | The Natural session for this terminal/user was terminated without any error conditions. Natural was terminated by one of the following actions: - entering the command FIN in NEXT/MORE mode, - entering the command %% in NEXT mode, - pressing the CLEAR key in NEXT mode, - executing the statement TERMINATE in a Natural program. |
| Actn. | No action required. |

NAT9996: Unable to load Natural nucleus module - :1: :2:.

| Text | Unable to load Natural nucleus module - :1: :2:. |
|-------|--|
| Expl. | Natural could not load its shared or reentrant nucleus module :1:. The front-end part of Natural attempted a TP- or OS-dependent load request and received error condition :2:. |
| Actn. | Check the shared nucleus name specified by the NUCNAME parameter or re-link the reentrant part with a corresponding name. Check whether the correct load library is accessible by Natural. |

NAT9997: Not enough memory to start Natural - :1: :2:K RC=:3:.

| Text | Not enough memory to start Natural - :1: :2:K RC=:3:. |
|-------|--|
| Expl. | Natural was not able to acquire all required storage buffers. |
| | These buffers are used for user area, terminal area, I/O areas, |
| | file buffers, etc. If one of the storage acquisition calls fails, |
| | Natural cannot be initialized. Additional information as follows: |
| | :1: buffer type (as documented in NATCONFG), |
| | :2: buffer size (in KB), |
| | :3: return code from the GETMAIN request: |
| | 04 = Not enough storage. |
| | 08 = Invalid buffer type. |
| | 10 = Duplicate buffer type. |
| | 18 = Invalid buffer length. |
| | 1C = Buffer type not defined in NATCONFG. |
| | 30 = Module NATCONFG not linked. |
| | 34 = Physical GETMAIN failed. |
| Actn. | 34 = Physical GETMAIN failed. RC=04/34: Reduce buffer sizes or assign a larger thread/partition. |
| | The other return codes indicate a product error; contact Software AG |
| | support. |

NAT9998: I/O error on input file - :1:.

| Text | I/O error on input file - :1:. |
|-------|---|
| | An I/O error occurred during batch processing on an input file, e.g. CMSYNIN or CMOBJIN. :1: indicates the name of the input file. |
| Actn. | Check for operating-system error messages in the job log and correct the error. |

NAT9999: I/O error on output file - :1:.

| Text | I/O error on output file - :1:. |
|-------|--|
| | An I/O error occurred during batch processing on an output file, e.g. CMPRINT. :1: indicates the name of the output file. |
| Actn. | Check for operating-system error messages in the job log and correct the error. |