

Entire Operations

Direct Commands

Version 5.4.3

December 2017

This document applies to Entire Operations Version 5.4.3 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 1988-2017 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://softwareag.com/licenses>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://softwareag.com/licenses/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software AG.

Document ID: NOP-ONOPREFERENCE-543-20191101

Table of Contents

Preface	v
1 About this Documentation	1
Document Conventions	2
Online Information and Support	2
Data Protection	3
2 Direct Command Syntax	5
Valid Name Specifications	6
3 Direct Commands in Alphabetical Order	9
ACTIVITY	10
ADD	10
EDIT	11
FIN	12
HELP	12
LIST	13
LOG	14
LOGOFF or LOGOUT	15
LOGON or LOGIN	15
MAIL	16
MENU	17
MODIFY	17
QUIT	18
REPORTS	18
SET	18
STATUS	20
TECH	20
XREF	21

Preface

You can use a direct command to directly perform an Entire Operations function.

You can enter a direct command on any screen or window that contains a **Command** => input field (also referred to as the command line).

This document describes the Entire Operations direct commands:

Direct Command Syntax	Explains the syntax elements used in the descriptions of the Entire Operations direct commands.
Direct Commands in Alphabetical Order	Lists and describes the Entire Operations direct commands in alphabetical order.

1

About this Documentation

■ Document Conventions	2
■ Online Information and Support	2
■ Data Protection	3

Document Conventions

Convention	Description
Bold	Identifies elements on a screen.
Monospace font	Identifies service names and locations in the format <i>folder.subfolder.service</i> , APIs, Java classes, methods, properties.
<i>Italic</i>	Identifies: Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies: Text you must type in. Messages displayed by the system. Program code.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the symbol.
[]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

Online Information and Support

Software AG Documentation Website

You can find documentation on the Software AG Documentation website at <http://documentation.softwareag.com>. The site requires credentials for Software AG's Product Support site Empower. If you do not have Empower credentials, you must use the TECHcommunity website.

Software AG Empower Product Support Website

If you do not yet have an account for Empower, send an email to empower@softwareag.com with your name, company, and company email address and request an account.

Once you have an account, you can open Support Incidents online via the eService section of Empower at <https://empower.softwareag.com/>.

You can find product information on the Software AG Empower Product Support website at <https://empower.softwareag.com>.

To submit feature/enhancement requests, get information about product availability, and download products, go to [Products](#).

To get information about fixes and to read early warnings, technical papers, and knowledge base articles, go to the [Knowledge Center](#).

If you have any questions, you can find a local or toll-free number for your country in our Global Support Contact Directory at https://empower.softwareag.com/public_directory.asp and give us a call.

Software AG TECHcommunity

You can find documentation and other technical information on the Software AG TECHcommunity website at <http://techcommunity.softwareag.com>. You can:

- Access product documentation, if you have TECHcommunity credentials. If you do not, you will need to register and specify "Documentation" as an area of interest.
- Access articles, code samples, demos, and tutorials.
- Use the online discussion forums, moderated by Software AG professionals, to ask questions, discuss best practices, and learn how other customers are using Software AG technology.
- Link to external websites that discuss open standards and web technology.

Data Protection

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.

2

Direct Command Syntax

■ Valid Name Specifications	6
-----------------------------------	---

This section explains the elements used within the syntax descriptions of Entire Operations direct commands.

Syntax Element	Meaning
ABCDEF or AbcDef	All uppercase non-italic letters (input not case-sensitive) or non-italic mixed-case letters (input case-sensitive) must be entered exactly as specified.
<u>ABC</u> DEF	If a word is partially underlined (not a hyperlink!), the underlined portion indicates the shortest possible abbreviations of a term.
<i>abcdef</i>	Letters in italics are used to represent variable information. You must supply a valid value when specifying this term.
[]	Elements contained within square brackets are optional. If the square brackets contain several lines stacked one above the other, each line is an optional alternative. You may choose at most one of the alternatives.
{ }	If the braces contain several lines stacked one above the other, each line is an alternative. You must choose exactly one of the alternatives.
	The vertical bar separates alternatives.
. . .	A term preceding an ellipsis may optionally be repeated. A number after the ellipsis indicates how many times the term may be repeated. If the term preceding the ellipsis is an expression enclosed in square brackets or braces, the ellipsis applies to the entire bracketed expression.
, . . .	A term preceding a comma-ellipsis may optionally be repeated; if it is repeated, the repetitions must be separated by commas. A number after the comma-ellipsis indicates how many times the term may be repeated. If the term preceding the comma-ellipsis is an expression enclosed in square brackets or braces, the comma-ellipsis applies to the entire bracketed expression.

Valid Name Specifications

If indicated in the syntax description of a direct command, you can select an item (such as a network or a job) by specifying either a single name or a range of names as described in the list of input options below where *value* is any combination of one or more alphanumeric characters:

Input	Names Selected
*	All names.
<i>value</i> *	All names that start with <i>value</i> . Example: AB* Selected: AB, AB1, ABC, ABEZ Not selected: AA1, ACB
<i>value</i> >	All names greater than or equal to <i>value</i> . Example: AB> Selected: AB, AB1, BBB, ZZZZZZZ Not selected: AA1, AAB
<i>value</i> <	All names less than or equal to <i>value</i> . Example: AX< Selected: AB, AWW, AX Not selected: AXA, AY
<i>value</i> ?	All names that start with <i>value</i> and end with any single character for each question mark (?) entered. Example: ABC? Selected: ABCA, ABCZ Not selected: AXC, ABCAA
<i>value</i> ? <i>value</i>	All names that match and <i>value</i> combined with a question mark (?) in any order. Example: A?C Selected: ABC, ACC Not selected: ABCA, AC

Input	Names Selected
*	All names.
<i>value</i> *	All names that start with <i>value</i> . Example: AB* Selected: AB, AB1, ABC, ABEZ Not selected: AA1, ACB
<i>value</i> >	All names greater than or equal to <i>value</i> . Example: AB> Selected: AB, AB1, BBB, ZZZZZZZ Not selected: AA1, AAB
<i>value</i> <	All names less than or equal to <i>value</i> . Example: AX< Selected: AB, AWW, AX Not selected: AXA, AY

3

Direct Commands in Alphabetical Order

■ ACTIVITY	10
■ ADD	10
■ EDIT	11
■ FIN	12
■ HELP	12
■ LIST	13
■ LOG	14
■ LOGOFF or LOGOUT	15
■ LOGON or LOGIN	15
■ MAIL	16
■ MENU	17
■ MODIFY	17
■ QUIT	18
■ REPORTS	18
■ SET	18
■ STATUS	20
■ TECH	20
■ XREF	21

ACTIVITY

ACTIVITY

The ACTIVITY direct command allows you to start the permanent activity display of Entire Operations directly.

For detailed information, see *Monitoring Entire Operations Activities* in the *User's Guide*.

ADD

ADD {
 USER
 {
 NETWORK
 JOB [network]
 INCONDITION [job] [network]
 }
 CALENDAR
 TABLE
 RESOURCE
 {
 NODE [network]
 }
 CONDITION

The ADD direct command is used to define a new Entire Operations object.

Syntax Description

Syntax Element	Description
USER	Add a user.
NETWORK	Add a network.
JOB	Add a master job definition to a job network.
INCONDITION	Add a master input condition to a job.
CALENDAR	Define a new calendar.
TABLE	Define a new master symbol table.
RESOURCE	Define a new resource.
NODE	Define a new node.
CONDITION	Add an active condition. See <i>Adding an Active Condition</i> in the section <i>Active Job Networks</i> in the <i>User's Guide</i> .

Syntax Element	Description
<i>job</i>	Name of the job to which the object belongs. You can use an asterisk (*) or asterisk notation to open a selection window with a list of available names: see Valid Name Specifications .
<i>network</i>	Name of the network to which the object belongs. You can use an asterisk (*) or asterisk notation to open a selection window with a list of available names: see Valid Name Specifications .

If you issue the command from a system screen in the Network and Job Maintenance facility and omit the *network* or *job* name parameter, the currently specified network and/or job is selected.

For further information, see *Defining and Managing Jobs* in the section *Job Maintenance* in the *User's Guide*.

EDIT

EDIT	$\left\{ \begin{array}{l} \text{JCL} \\ \text{NPROSE} \\ \text{JPROSE} \end{array} \right\} [name] [network]$
------	---

The **EDIT** direct command provides direct access to the Entire Operations Editor to edit JCL, Natural programs or text descriptions at the network and job level. After editing the specified object, you can press PF3 (End) to return to the screen from which you issued the **EDIT** command.

Syntax Description

Syntax Element	Description
JCL	Edit job JCL. If a job <i>name</i> is not specified, a window prompts you to select a job from a list of jobs available.
NPROSE	Edit the description of the currently selected network or the <i>network</i> specified with the command.
JPROSE	Edit the description of the currently selected job or the job specified with <i>name</i> .
<i>name</i>	Name of the object to be edited. (Not required if the object is NPROSE.) You can use an asterisk (*) or asterisk notation to open a selection window with a list of available names: see Valid Name Specifications .
<i>network</i>	Name of the network to which the object belongs. You can use an asterisk (*) or asterisk notation to open a selection window with a list of available names: see Valid Name Specifications .

If you issue the `EDIT` command from the Network and Job Maintenance facility and omit the *network* or *name* parameter, the editor opens for the currently selected network and/or job.

For further information, see *Editing Master JCL and Natural Sources* in the section *Job Maintenance* and *Editor* in the section *System Overview* in the *User's Guide*.

FIN

FIN

The `FIN` direct command terminates the Entire Operations session. It corresponds to the `QUIT` direct command.

HELP

HELP [MSG *message-id*]

The `HELP` direct command invokes the **Entire Operations Help** facility or displays the long message text of the message code specified with the command.

Syntax Description

Syntax Element	Description
<i>message-id</i>	<p>The 7-character ID of a system message returned by Entire Operations, Natural or BS2000 (if installed).</p> <p>Entire Operations messages begin with EOR, followed by a four-digit number, for example, EOR0930.</p> <p>Natural messages begin with NAT, followed by a four-digit number, for example, NAT0954.</p>

For further information, see the section *Online Help Facility* in the *User's Guide*.

LIST

	<u>U</u> SERS
	<u>N</u> ETWORKS
	<u>J</u> OBS [<i>network</i>]
	<u>I</u> NCONDITIONS [<i>job</i>] [<i>network</i>]
	<u>E</u> OJ [<i>job</i>] [<i>network</i>]
	<u>C</u> ALENDARS
<u>L</u> IST {	<u>T</u> ABLES
	<u>R</u> ESOURCES
	<u>N</u> ODES
	<u>M</u> AILBOX
	<u>A</u> CTIVE [<i>network</i>]
	<u>C</u> ONDITIONS

The **LIST** direct command displays all objects that meet the selection criteria specified with the command. You can perform available functions on the object as normal and press PF3 (End) to return to the screen from which you issued the **LIST** command.

Syntax Description

Syntax Element	Description
USERS	List of users
NETWORKS	List of job networks
JOB	List of jobs that belong to the specified job network
INCONDITIONS	List of input conditions
EOJ	List of events and actions for End-of-Job checking
CALENDARS	List of defined calendars assigned to the specified owner
TABLES	List of master symbol tables
NODES	List of defined nodes
MAILBOX	List of mailbox messages and requests Note: The use of the LIST MAILBOX direct command can be disallowed in the Entire Operations user profile: see the Show Mailbox Requests option described in the section <i>Monitoring Functions</i> in the <i>Administration</i> documentation.
ACTIVE	List of active jobs that belong to the specified job network
CONDITIONS	List of active conditions

Syntax Element	Description
<i>job</i>	Name of the job to which the object list belongs (input conditions, events in End-of-Job handling, dependencies) You can list a range of names by using an asterisk (*) or a greater than (>) or smaller than (<) sign: see Valid Name Specifications .
<i>network</i>	Name of the network to which the object belong (jobs, input conditions, End-of-Job handling, active jobs, dependencies) You can list a range of names by using an asterisk (*) or a greater than (>) or smaller than (<) sign: see Valid Name Specifications .

Examples of LIST

■ LIST ACTIVE NETWORK1

Displays the list of active jobs in the job network NETWORK1.

■ LIST NETWORKS DEMO*

Lists all networks with names starting with DEMO.

If you issue the LIST command from the Network and Job Maintenance facility and omit the *job* or *network* name parameter, the currently specified network and/or job is selected.

For further information, see *Listing Active Jobs for a Network* in the section *Network Maintenance* in the *User's Guide*.

LOG

LOG

The LOG direct command invokes the **Log Selection Display** screen where you can specify the required log. Press PF3 (End) to return to the screen from which you issued the LOG command.

For further information, see the section *Log Information* in the *User's Guide*.

LOGOFF or LOGOUT

```
{ LOGOFF } { NODE } { node-number }
{ LOGOUT } { SERVER } { node-short-name }
           { MONITOR }
```

The LOGOFF (or LOGOUT) direct command logs off an Entire System Server node or prompts the Entire Operations Monitor to log off an Entire System Server node.

For z/OS: The security system access rights (RACF, for example) will be re-read by Entire System Server.

Syntax Description

Syntax Element	Description
LOGOFF or LOGOUT	LOGOUT and LOGOFF can be used synonymously. Logs off the specified Entire System Server node.
NODE or SERVER	Logs off the specified Entire System Server node. NODE and SERVER can be used synonymously.
MONITOR	Forces the Entire Operations Monitor to logoff a node and to perform a new logon on a node (when the node is used again). The logoff task is confirmed by an appropriate log message.
<i>node-number</i>	The node number, for example, 42.
<i>node-short-name</i>	The physical (short) node name, for example, N0042.

LOGON or LOGIN

```
{ LOGON } { NODE } { node-number }
{ LOGIN } { SERVER } { node-short-name }
```

The LOGON (or LOGIN) direct command logs in an Entire System Server node.

Syntax Description

Syntax Element	Description
LOGON or LOGIN	LOGON and LOGIN can be used synonymously.
NODE or SERVER	Logs on the specified Entire System Server node. NODE and SERVER can be used synonymously.
<i>node-number</i>	The node number, for example, 42.
<i>node-short-name</i>	The physical (short) node name, for example, N0042.

After this command has been issued a logon window (see *Logging on to an Operating System Server Node* in the *User's Guide*) appears.

For z/OS: The security system access rights (RACF, for example) will be re-read by Entire System Server.



Note: For each combination of UNIX or Windows node and user ID, at least one successful logon (by LOGON NODE) must have been made, before this combination can be used within the Entire Operations Monitor. These LOGON NODE commands must be repeated after a password modification on a UNIX or Windows system.

See also *Displaying Job Dependencies and Connecting or Disconnecting Jobs* in the section *Job Maintenance* in the *User's Guide*.

MAIL



The MAIL direct command displays the contents of the user's mailbox.

For further information, see *Viewing Mailbox Messages* in the *User's Guide*.



Note: The use of the MAIL direct command can be disallowed in the Entire Operations user profile: see the **Show Mailbox Requests** option described in the section *Monitoring Functions* in the *Administration* documentation.

MENU

MENU

The **MENU** direct command returns directly to the Main Menu from any screen in Entire Operations.

For further information, see *Entire Operations Main Menu* in the section *Logging on to Entire Operations* in the *User's Guide*.

MODIFY

```

MODIFY {
  USER      [userid]
  NETWORK [network] [ version]
  JOB       [job] [network] [version]
}

```

The **MODIFY** direct command provides direct access to Entire Operations definition screens containing current values of the selected object. When you have modified the object, press PF3 (End) to return to the screen from which you issued the **MODIFY** command.

Syntax Description

Syntax Element	Description
<i>job</i>	Name of the job to be modified.
<i>network</i>	Name of the network to be modified.
<i>owner</i>	Name of the network owner.
<i>version</i>	Network version.
<i>userid</i>	Entire Operations user ID.

If you issue the **MODIFY** command from the Network and Job Maintenance facility and omit the *job* or *network* name parameter, the currently specified network and/or job is selected.

For further information, see *Defining and Managing Jobs* in the section *Job Maintenance* in the *User's Guide*.

QUIT

QUIT

The **QUIT** direct command terminates the Entire Operations session. It corresponds to the **FIN** direct command.

REPORTS

REPORTS

The **REPORTS** direct command opens the **Reports** menu with a list of report types provided by the Entire Operations reporting facility.

For information on reporting, see the relevant section in the *User's Guide*.

SET

$$\text{SET} \left\{ \begin{array}{l} \text{LANGUAGE} \left[\begin{array}{l} 1 \\ 2 \end{array} \right] \\ \text{MAILBOX} \left[\begin{array}{l} \text{ON} \\ \text{OFF} \end{array} \right] \\ \text{ACTIVE} \left\{ \begin{array}{l} \text{A} \\ \text{E} \\ \text{I} \\ \text{O} \\ \text{N} \\ \text{S} \\ \text{T} \\ \text{W} \end{array} \right\} \\ \text{OWNER} \left[\begin{array}{l} * \\ \text{owner} \end{array} \right] \end{array} \right\}$$

The **SET** direct command allows you to change Entire Operations system settings directly from any system screen that contains the direct command line.

Syntax Description

Syntax Element	Description	
LANGUAGE	Sets the language of the Entire Operations screens and messages. Possible options:	
	1	English
	2	German
MAILBOX	Specifies automatic notification of pending conditions via mailbox when you wish to display the Entire Operations Main Menu. Possible options:	
	ON	Automatic notification.
	OFF	No notification.
ACTIVE	Sets the active database selection criteria. Possible options:	
	A	Display all active jobs.
	E	Display all currently running jobs.
	I	Display all jobs in JES input queue.
	N	Display all jobs that terminated not OK.
	O	Display all jobs that terminated OK.
	S	Display all submitted jobs.
	T	Display all terminated jobs.
	W	Display all jobs with pending prerequisites.
OWNER	<p>Changes the current owner name. By default, the name of the owner defined as Owner at Logon is used (see <i>Viewing, Adding and Modifying a User</i> in the <i>Administration</i> documentation).</p> <p>You can access all definitions belonging to the <i>owner</i> whose name you specify with the command, provided you are authorized to do so. See <i>Granting Definition: Authorizing Other Users or Owners to Access a Network</i> in the <i>User's Guide</i>.</p> <p>You can enter an asterisk (*) for a list of available owners.</p>	


Example of SET

```
SET MAILBOX OFF
```

Deactivates the automatic notification of pending conditions when you wish to display the Entire Operations Main Menu.

For further information, see the section *Overview of Administration Functions and Options* of the *Administration* documentation.


STATUS



The STATUS direct command allows you to perform certain system functions. When you have issued the command, the Entire Operations Monitor handling window opens. You can now enter the appropriate instruction.

Syntax Description

Syntax Element	Description
MONITOR	Displays the Entire Operations Monitor handling window. You can start and stop the Monitor from this window. Note: Even if under the user's profile settings for Administrator Functions, Monitor Start/Shutdown is set to N, this command allows a check of Monitor status.
NODES	Opens the Node Status screen and displays the status of all defined Entire System Server nodes. For more information, see the section <i>Logging on to an Operating System Server Node</i> in the <i>User's Guide</i> .
ACTIVE	Opens the window for handling Entire Operations activity monitoring (see the section <i>Control of Activity Monitoring</i> in the <i>Administration</i> documentation).

 **Note:** The use of the STATUS direct command can be disallowed in the Entire Operations user profile: see the **Monitor Start/Shutdown** option described in the section *Administration Functions* in the *Administration* documentation.

TECH



The TECH direct command displays technical information on your current Entire Operations session:

- Software AG products and components (for example, the Software AG Editor of Natural) and versions used and their installation dates

Software AG product versions include service packs, cumulative fixes and hot fixes for Entire Operations (NOP) and System Automation Tools (SAT) if installed

- Node (Nd.) on which Entire System Server runs
- Natural program, map and library currently active
- code page used
- user ID/name
- current date and time
- operating system/version installed
- TP monitor and terminal ID/type installed on the server (mainframes only)

XREF



The XREF direct command displays cross-reference information on user exit routines, symbol tables, JCL, nodes, resources and undefined Entire Operations objects.

For further information, refer to *Cross References* in the *User's Guide*.



Note: The use of the XREF direct command can be disallowed in the Entire Operations user profile: see the **Cross References** option described in the section *Reporting Functions* in the *Administration* documentation.

