

Direct Commands

Version 5.5.1

February 2020

This document applies to Version 5.5.1 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 2020 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://softwareag.com/licenses>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://softwareag.com/licenses/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software AG.

Document ID: OGC-ONOPREFERENCE-551-20200211

Table of Contents

Preface	v
1 About this Documentation	1
Document Conventions	2
Online Information and Support	2
Data Protection	3
2 Direct Command Syntax	5
Valid Name Specifications	6
3 Direct Commands in Alphabetical Order	9
EXPORT DIAGRAM	10
FOCUS TO	10
HELP	10
LIST	11
LOG	12
LOGOFF or LOGOUT	12
LOGON or LOGIN	13
MAIL	13
REPORTS	14
SET OWNERLIST	14
STATUS	15
TECH	15
XREF	16

Preface

You can use a direct command to directly perform an Entire Operations function.

You enter a direct command in the **Command** input field (also referred to as the command line) when you select **Command Line** from the **View** menu of the main application window:

A screenshot of a software interface showing a text input field labeled "Command:". The field is empty and has a small downward-pointing arrow on the right side, indicating it is a dropdown menu.

-  **Note:** Make sure that Entire Operations is selected as your current Entire Systems Management application. Otherwise, direct commands specific to Entire Operations may not be recognized.

From the list box you can view and select all direct commands you have previously entered during the current session.

This document describes the Entire Operations direct commands:

Direct Command Syntax	Explains the syntax elements used in the descriptions of the Entire Operations direct commands.
Direct Commands in Alphabetical Order	Lists and describes the Entire Operations direct commands in alphabetical order.

1 About this Documentation

▪ Document Conventions	2
▪ Online Information and Support	2
▪ Data Protection	3

Document Conventions

Convention	Description
Bold	Identifies elements on a screen.
Monospace font	Identifies service names and locations in the format <code>folder.subfolder.service</code> , APIs, Java classes, methods, properties.
<i>Italic</i>	Identifies: Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies: Text you must type in. Messages displayed by the system. Program code.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the symbol.
[]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

Online Information and Support

Software AG Documentation Website

You can find documentation on the Software AG Documentation website at <http://documentation.softwareag.com>. The site requires credentials for Software AG's Product Support site Empower. If you do not have Empower credentials, you must use the TECHcommunity website.

Software AG Empower Product Support Website

If you do not yet have an account for Empower, send an email to empower@softwareag.com with your name, company, and company email address and request an account.

Once you have an account, you can open Support Incidents online via the eService section of Empower at <https://empower.softwareag.com/>.

You can find product information on the Software AG Empower Product Support website at <https://empower.softwareag.com>.

To submit feature/enhancement requests, get information about product availability, and download products, go to [Products](#).

To get information about fixes and to read early warnings, technical papers, and knowledge base articles, go to the [Knowledge Center](#).

If you have any questions, you can find a local or toll-free number for your country in our Global Support Contact Directory at https://empower.softwareag.com/public_directory.asp and give us a call.

Software AG TECHcommunity

You can find documentation and other technical information on the Software AG TECHcommunity website at <http://techcommunity.softwareag.com>. You can:

- Access product documentation, if you have TECHcommunity credentials. If you do not, you will need to register and specify "Documentation" as an area of interest.
- Access articles, code samples, demos, and tutorials.
- Use the online discussion forums, moderated by Software AG professionals, to ask questions, discuss best practices, and learn how other customers are using Software AG technology.
- Link to external websites that discuss open standards and web technology.

Data Protection

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.

2 Direct Command Syntax

- Valid Name Specifications 6

This section explains the elements used within the syntax descriptions of Entire Operations direct commands.

Syntax Element	Meaning
ABCDEF or AbcDef	All uppercase non-italic letters (input not case-sensitive) or non-italic mixed-case letters (input case-sensitive) must be entered exactly as specified.
<u>ABCDEF</u>	If a word is partially underlined (not a hyperlink!), the underlined portion indicates the shortest possible abbreviations of a term.
<i>abcdef</i>	Letters in italics are used to represent variable information. You must supply a valid value when specifying this term.
[]	Elements contained within square brackets are optional. If the square brackets contain several lines stacked one above the other, each line is an optional alternative. You may choose at most one of the alternatives.
{ }	If the braces contain several lines stacked one above the other, each line is an alternative. You must choose exactly one of the alternatives.
	The vertical bar separates alternatives.
. . .	A term preceding an ellipsis may optionally be repeated. A number after the ellipsis indicates how many times the term may be repeated. If the term preceding the ellipsis is an expression enclosed in square brackets or braces, the ellipsis applies to the entire bracketed expression.
, . . .	A term preceding a comma-ellipsis may optionally be repeated; if it is repeated, the repetitions must be separated by commas. A number after the comma-ellipsis indicates how many times the term may be repeated. If the term preceding the comma-ellipsis is an expression enclosed in square brackets or braces, the comma-ellipsis applies to the entire bracketed expression.

Valid Name Specifications

If indicated in the syntax description of a direct command, you can select an item (such as a network or a job) by specifying either a single name or a range of names as described in the list of input options below where *value* is any combination of one or more alphanumeric characters:

Input	Names Selected
*	All names.
<i>value</i> *	<p>All names that start with <i>value</i>.</p> <p>Example: AB*</p> <p>Selected: AB, AB1, ABC, ABEZ</p> <p>Not selected: AA1, ACB</p>
<i>value</i> >	<p>All names greater than or equal to <i>value</i>.</p> <p>Example: AB></p> <p>Selected: AB, AB1, BBB, ZZZZZZZ</p> <p>Not selected: AA1, AAB</p>
<i>value</i> <	<p>All names less than or equal to <i>value</i>.</p> <p>Example: AX<</p> <p>Selected: AB, AWW, AX</p> <p>Not selected: AXA, AY</p>
<i>value</i> ?	<p>All names that start with <i>value</i> and end with any single character for each question mark (?) entered.</p> <p>Example: ABC?</p> <p>Selected: ABCA, ABCZ</p> <p>Not selected: AXC, ABCAA</p>
<i>value</i> ? <i>value</i>	<p>All names that match and <i>value</i> combined with a question mark (?) in any order.</p> <p>Example: A?C</p> <p>Selected: ABC, ACC</p> <p>Not selected: ABCA, AC</p>
???	<p>All names with an exact length of three characters.</p> <p>Example: ???</p> <p>Selected: ABC, DEF</p> <p>Not selected: AC, DEFA</p>

3 Direct Commands in Alphabetical Order

- EXPORT DIAGRAM 10
- FOCUS TO 10
- HELP 10
- LIST 11
- LOG 12
- LOGOFF or LOGOUT 12
- LOGON or LOGIN 13
- MAIL 13
- REPORTS 14
- SET OWNERLIST 14
- STATUS 15
- TECH 15
- XREF 16

EXPORT DIAGRAM

The `EXPORT DIAGRAM` direct command exports a network diagram to a PC file.

Syntax Description

See *EXPORT DIAGRAM Command Syntax* in the section *Using Entire Operations in Batch Mode*.

FOCUS TO

`FOCUS TO application-library`

The `FOCUS TO` direct command selects the main tree view node of the Entire Systems Management application you want to make the current application.

Syntax Description

Syntax Element	Description
<code>application-library</code>	The name of the Natural library associated with the required Entire Systems Management application. For Entire Operations, the library name is <code>SYSOGC</code> .

HELP

`HELP message-id`

The `HELP` direct command invokes displays the long message text of the message code specified with the command.

Syntax Description


Syntax Element	Description
<code>message-id</code>	The 7-character ID of a system message returned by Entire Operations or Natural. Entire Operations messages begin with EOR, followed by a four-digit number, for example, EOR0930. Natural messages begin with NAT, followed by a four-digit number, for example, NAT0954.



Notes:

1. Message text is displayed in the user language set in your environment, with a few exceptions where text can only be provided in English.
2. BS2000-specific message text is only displayed if you are logged on to a BS2000 node.

LIST



The LIST direct command displays all objects that meet the selection criteria specified with the command.

Syntax Description

Syntax Element	Description
USERS	List of users.
NETWORKS	List of job networks. If no owner is selected in the tree, a Selection window prompts you to enter an owner name.
TABLES	List of master symbol tables. If no owner is selected in the tree, a Selection window prompts you to enter an owner name.
NODES	List of defined nodes.
ACTIVE	List of active jobs that belong to the specified job network.
<i>owner</i>	Name of owner to which the objects belong (networks, jobs, job schedules, messages).
or	You can enter an asterisk (*) to open a selection window with a list of available names.
*	

LOG

LOG

The LOG direct command invokes the **Log Display Selection Display** window where you can specify the required log.

For further information, see the section *Log Information* in the *User's Guide*.

LOGOFF or LOGOUT

$\left\{ \begin{array}{l} \text{LOGOFF} \\ \text{LOGOUT} \end{array} \right\} \left\{ \begin{array}{l} \left\{ \begin{array}{l} \text{NODE} \\ \text{SERVER} \end{array} \right\} \left\{ \begin{array}{l} \textit{node-number} \\ \textit{node-short-name} \end{array} \right\} \\ \text{MONITOR } \textit{node-number} \end{array} \right\}$
--

The LOGOFF (or LOGOUT) direct command logs off an Entire System Server node or prompts the Entire Operations Monitor to log off an Entire System Server node.

Syntax Description

Syntax Element	Description
LOGOFF or LOGOUT	LOGOUT and LOGOFF can be used synonymously. Logs off the specified Entire System Server node.
NODE or SERVER	Logs off the specified Entire System Server node. NODE and SERVER can be used synonymously.
MONITOR	Forces the Entire Operations Monitor to logoff a node and to perform a new logon on a node (when the node is used again). The logoff task is confirmed by an appropriate log message.
<i>node-number</i>	The node number, for example, 42.
<i>node-short-name</i>	The physical (short) node name, for example, N0042.

LOGON or LOGIN

```
{ LOGON } { NODE } { node-number }
{ LOGIN } { SERVER } { node-short-name }
```

The LOGON (or LOGIN) direct command logs in an Entire System Server node.

Syntax Description

Syntax Element	Description
LOGON or LOGIN	LOGON and LOGIN can be used synonymously.
NODE or SERVER	Logs on the specified Entire System Server node. NODE and SERVER can be used synonymously.
<i>node-number</i>	The node number, for example, 42.
<i>node-short-name</i>	The physical (short) node name, for example, N0042.

After this command has been issued a logon window (see *Logging on to an Operating System Server Node* in the *User's Guide*) appears.



Note: For each combination of UNIX or Windows node and user ID, at least one successful logon (by LOGON NODE) must have been made, before this combination can be used within the Entire Operations Monitor. These LOGON NODE commands must be repeated after a password modification on a UNIX or Windows system

MAIL

```
MAIL
```

The MAIL direct command displays the contents of the user's mailbox.

For further information, see *Viewing Mailbox Messages* in the *User's Guide*.



Note: The use of the MAIL direct command can be disallowed in the Entire Operations user profile: see the **Show Mailbox Requests** option described in the section *Monitoring Functions* in the *Administration* documentation.

REPORTS

REPORTS

The `REPORTS` direct command opens the **Reporting** window with a list of report types provided by the Entire Operations reporting facility.

For information on reporting, see the relevant section in the *User's Guide*.

SET OWNERLIST

SET OWNERLIST { ALL LINKED }

The `SET OWNERLIST` direct command changes the list of items displayed in the tree view of the **Owner** nodes in the object workspace.

Syntax Description

Option	Description
ALL	This command requires that you are authorized to access the networks of all owners. The Owner node changes to Owner (SYSDBA access) and lists all available owners. The Owner via Granting node does not list items to which owners have explicitly granted access.
LINKED	The Owner node only lists the items that belong to the current user. The Owner via Granting node lists all items to which owners have explicitly granted access.

For information on using owners and maintaining owner links and owners, see the relevant sections in the *User's Guide* and *Administration* documentation, respectively.

STATUS

```
STATUS { MONITOR
        NODES }
```

The `STATUS` direct command allows you to perform certain system functions. When you have issued the command, the Entire Operations Monitor handling window opens. You can now enter the appropriate instruction.

Syntax Description

Syntax Element	Description
MONITOR	<p>Displays the Entire Operations Monitor handling window. You can start and stop the Monitor from this window.</p> <p>Note: Even if the Entire Operations user profile setting for Monitor Start/Shutdown (Administration Functions) is set to <code>N</code>, this command allows a check of the Monitor status.</p> <p>See also <i>Administration Functions</i> in the <i>Administration</i> documentation.</p>
NODES	<p>Opens the Node Connection Status window and displays the status of all defined Entire System Server nodes.</p> <p>For more information, see the section <i>Logging on and off an Operating System Server Node</i> in the <i>User's Guide</i>.</p>

 **Note:** The use of the `STATUS` direct command can be disallowed in the Entire Operations user profile: see the **Monitor Start/Shutdown** option described in the section *Administration Functions* in the *Administration* documentation.

TECH

```
TECH
```

The `TECH` direct command displays technical information on your current Entire Operations session:

- Software AG products and components (for example, the Software AG Editor of Natural) and versions used on the client (OGC) and server and their installation dates

Software AG product versions include service packs, cumulative fixes and hot fixes for Entire Operations (NOP) and System Automation Tools (SAT) if installed

- Node on which Entire System Server runs
- Application ID
- Application name
- Code page used on the client (OGC) and server
- User ID/name
- Current date and time
- Operating system/version installed on the server
- Server type (for example, RPC)

XREF

XREF

The XREF direct command displays cross-reference information on user exit routines, symbol tables, JCL, nodes, resources and undefined Entire Operations objects.

For further information, refer to *Cross-References* in the *User's Guide*.



Note: The use of the XREF direct command can be disallowed in the Entire Operations user profile: see the **Cross-References** option described in the section *Reporting Functions* in the *Administration* documentation.