

Integration Cloud

Version 6.0.0

October 2019

This document applies to webMethods Integration Cloud Version 6.0.0 and to all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 2014-2019 Software AG, Darmstadt, Germany and/or Software AG USA Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://softwareag.com/licenses>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software AG.

Table of Contents

webMethods Integration Cloud	15
Document Conventions	17
Online Information and Support	19
Data Protection	21
What's New	23
Integration Cloud and Cloud Deployment.....	24
Version 6.0.0 (October 2019).....	24
Version 5.6.0 (August 2019).....	26
Version 5.5.0 (April 2019).....	32
Version 5.1.0 (February 2019).....	35
Version 5.0.0 (October 2018).....	39
Create and secure your account	43
Registration.....	44
Creating an Account.....	44
Securing your Account.....	47
Projects and Permissions	49
Projects.....	50
Project Permissions.....	52
Settings	55
Users.....	56
Adding Users.....	56
Updating Users.....	60
Resetting Passwords.....	61
User Profile.....	62
Security Question.....	62
Change Password.....	63
My Certificate.....	63
Capability.....	63
Access Profiles.....	65
Adding or Updating Access Profiles.....	67
Access Control Lists.....	72
Adding or Updating Access Control Lists.....	73
Project Permissions.....	74
Single Sign-On.....	76
Configuring SAML Settings for Single Sign-On.....	78
Company Information.....	83

Updating Company Information.....	83
Password Policy.....	85
Updating Password Policy Settings.....	85
Client Certificate.....	87
Adding Client Certificates.....	88
Executing Integrations using Two-way SSL.....	89
OAuth 2.0.....	94
About OAuth 2.0.....	94
Configuring OAuth 2.0.....	95
Registering Clients.....	96
Managing Scopes.....	100
Generating Tokens.....	101
Refreshing Access Tokens Using Refresh Tokens.....	104
Managing Tokens.....	104
Running Services Using OAuth 2.0.....	105
Audit Log.....	105
Applications.....	107
Overview.....	108
Predefined Applications.....	109
Alfabet.....	109
Apache Solr Search.....	111
Applicability Statement 2 (AS2).....	113
AS2 Predefined Operations.....	117
receive.....	117
send.....	120
Configuring the Auto Detect Option.....	123
Creating an Endpoint URL.....	123
Amazon DynamoDB.....	124
Amazon Kinesis.....	126
Amazon Simple Notification Service(SNS).....	128
Amazon Simple Queue Service (SQS).....	130
Amazon Simple Storage Service (S3).....	131
Atlassian Jira.....	134
Avalara AvaTax.....	136
Cloud Deployment.....	138
Cloud Deployment Operations.....	138
CloudStreams Connector for Anaplan®.....	139
CloudStreams Connector for Microsoft Azure Cosmos DB.....	141
CloudStreams Connector for Microsoft Azure Data Lake Store.....	143
CloudStreams Connector for Microsoft Azure Storage.....	145
CloudStreams Connector for NetSuite™.....	147
Concur.....	150
Coupa.....	151
Cumulocity.....	153

Database.....	155
Database Application Operations.....	157
Advanced Options.....	158
Configuring the Parameter Values.....	159
Custom SQL Operation.....	159
Select Operation.....	160
Update Operation.....	161
Insert Operation.....	161
Delete Operation.....	162
Stored Procedure Operation.....	163
Batch Insert Operation.....	163
Batch Update Operation.....	164
JDBC Data Type to Java Data Type Mappings.....	164
Important Considerations When Using BLOB and CLOB Data Types.....	169
Important Considerations When Using the Array and Struct Database Specific Data Types.....	169
Using the SetAsString Data Type in Database Application.....	170
JDBC Data Type to Java Data Type Mapping Constraints.....	170
Driver Management.....	171
Driver Management Fields.....	172
Certified Databases and JDBC Driver Jars.....	172
Samples Accounts.....	183
Microsoft SQL Server.....	183
Oracle.....	183
PostgreSQL.....	184
MySQL.....	185
MariaDB.....	185
Tibero.....	186
Supported Cloud Databases.....	186
DocuSign.....	187
Electronic Data Interchange.....	188
Predefined Operations.....	189
File Transfer Protocol (FTP/FTPS).....	200
FTP Predefined Operations.....	201
getFile.....	202
listFiles.....	202
deleteFiles.....	203
putFile.....	203
renameFile.....	204
Google Analytics.....	205

Google Apps Admin.....	207
Google BigQuery.....	208
Google Calendar.....	210
Google Contacts.....	212
Google Drive.....	214
Google Cloud Pub/Sub.....	216
Google Cloud Storage.....	218
Google Prediction.....	220
Google Sheets.....	222
IBM Watson Tone Analyzer.....	223
Magento eCommerce Platform.....	225
Marketo.....	227
Microsoft Dynamics CRM.....	229
OData v2.0.....	233
OData v4.0.....	235
Salesforce.....	237
Salesforce® Bulk v2 Data Loader.....	245
Salesforce® CRM REST.....	248
SAP Cloud for Customer(C4C) OData v2.0.....	252
SAP S/4HANA Marketing Cloud.....	254
Secure File Transfer Protocol (SFTP).....	257
SFTP Predefined Operations.....	259
cd.....	259
chgrp.....	260
chmod.....	260
chown.....	261
get.....	261
ls.....	261
mkdir.....	262
put.....	263
pwd.....	264
rename.....	264
rm.....	264
rmdir.....	265
symlink.....	265
ServiceNow Enterprise Service Management.....	266
Shopify.....	268
Siemens MindSphere.....	269
Simple Mail Transfer Protocol (SMTP).....	272
Using the SMTP Application to send emails.....	274
SMTP Predefined Operation.....	280
Slack.....	281
Strikelron Contact Verification.....	283
SuccessFactors HCM.....	285
SugarCRM.....	287

Twilio.....	289
webMethods.io B2B.....	291
webMethods.io B2B account configuration.....	291
Predefined Operations.....	291
Zendesk.....	295
Zuora.....	297
REST Applications.....	300
Creating and updating REST Applications.....	302
REST Applications - Account Configuration Details.....	308
Tweet the status on Twitter using the REST Application.....	313
On-Premises Applications.....	320
Uploading on-premises services to Integration Cloud.....	321
SOAP Applications.....	325
SOAP Applications - Account Configuration Details.....	327
SOAP Signature.....	329
Flat File Applications.....	334
Creating a flat file Application manually.....	335
Creating a flat file Application from a sample file.....	348
Flat File Predefined Operations.....	353
.....	
convertFlatFileToDocument.....	353
convertDocumentToFlatFile.....	356
Accounts, Operations, Listeners.....	359
Accounts.....	360
Adding or Editing Accounts.....	360
Operations.....	362
Adding or Editing Operations.....	363
Listeners.....	370
Creating and updating listeners.....	370
Integrations.....	375
Overview.....	376
Point-to-Point Integrations.....	378
Orchestrated Integrations.....	380
Pipeline and Signatures.....	393
Default Pipeline Rules for Linking to and from Array Variables.....	396
Indexed Mapping.....	399
Integration Details.....	400
Versioning of Integrations.....	406
Preview Integrations.....	407
Debug Integrations.....	409
Export Integrations.....	412
Import Integrations.....	413
Lock and Unlock Integrations.....	414
View the status of a locked Integration.....	414

Recipes	417
How to view and use Recipes.....	418
Built-In Services	421
Overview.....	422
Built-In Services.....	422
Date.....	422
.....	
calculateDateDifference.....	427
compareDates.....	428
currentNanoTime.....	429
dateBuild.....	430
dateTimeBuild.....	431
dateTimeFormat.....	432
elapsedNanoTime.....	433
formatDate.....	434
getCurrentDate.....	435
getCurrentDateString.....	435
incrementDate.....	436
Document.....	438
.....	
findDocuments.....	439
insertDocument.....	440
deleteDocuments.....	440
documentListToDocument.....	441
documentToDocumentList.....	443
groupDocuments.....	444
documentToBytes.....	445
bytesToDocument.....	446
searchDocuments.....	447
sortDocuments.....	448
List.....	449
.....	
addItemToVector.....	450
appendToDocumentList.....	451
appendToStringList.....	452
sizeOfList.....	452
stringListToDocumentList.....	453
vectorToArray.....	454
Math.....	455
.....	
addObjects.....	456
divideObjects.....	457
min.....	458
multiplyObjects.....	458

subtractObjects.....	459
toNumber.....	460
absoluteValue.....	460
addFloatList.....	460
addFloats.....	461
addIntList.....	462
addInts.....	463
divideFloats.....	463
divideInts.....	465
max.....	465
multiplyFloatList.....	466
multiplyFloats.....	467
multiplyIntList.....	468
multiplyInts.....	468
randomDouble.....	469
roundNumber.....	469
subtractFloats.....	470
subtractInts.....	471
Storage.....	471
.....	
add.....	475
deleteStore.....	476
get.....	477
keys.....	478
lock.....	478
put.....	480
remove.....	481
unlock.....	482
String.....	482
.....	
HTMLDecode.....	485
HTMLEncode.....	485
base64Decode.....	486
base64Encode.....	487
bytesToString.....	487
concat.....	488
indexOf.....	488
length.....	489
lookupDictionary.....	489
makeString.....	490
messageFormat.....	490
numericFormat.....	491
objectToString.....	492
padLeft.....	493
padRight.....	494

replace.....	495
stringToBytes.....	495
substring.....	496
tokenize.....	496
toLowerCase.....	497
toUpperCase.....	497
trim.....	498
URLDecode.....	498
URLEncode.....	499
fuzzyMatch.....	499
isNumber.....	500
isAlphanumeric.....	501
isNullOrBlank.....	501
isDate.....	502
substitutePipelineVariables.....	503
compareStrings.....	503
Flow.....	504
.....	
clearPipeline.....	505
getLastError.....	505
getSessionInfo.....	507
getHTTPRequest.....	508
setHTTPResponse.....	508
countProcessedDocuments.....	509
logCustomMessage.....	510
sleep.....	510
Hashtable.....	510
.....	
containsKey.....	511
createHashtable.....	511
get.....	512
listKeys.....	512
put.....	512
remove.....	513
size.....	513
Flat File.....	514
.....	
delimitedDataBytesToDocument.....	514
delimitedDataStreamToDocument.....	517
delimitedDataStringToDocument.....	520
documentToDelimitedDataBytes.....	523
documentToDelimitedDataStream.....	525
documentToDelimitedDataString.....	527
JSON.....	529
.....	

documentToJSONBytes.....	530
documentToJSONStream.....	530
documentToJSONString.....	531
jsonBytesToDocument.....	531
jsonStreamToDocument.....	532
jsonStringToDocument.....	533
Transaction.....	533
.....	
Transaction:commit.....	534
Transaction:rollback.....	534
Transaction:setTimeout.....	535
Transaction:start.....	536
XML.....	536
.....	
documentToXMLBytes.....	537
documentToXMLStream.....	541
documentToXMLString.....	545
xmlBytesToDocument.....	549
xmlNodeToDocument.....	557
xmlStreamToDocument.....	566
xmlStringToDocument.....	573
xmlStringToXMLNode.....	581
getXMLNodeType.....	582
queryXMLNode.....	583
IO.....	585
.....	
bytesToStream.....	586
streamToBytes.....	586
streamToString.....	587
stringToStream.....	587
Utils.....	588
.....	
generateUUID.....	588
Document Types.....	589
Overview.....	590
Creating Document Types from Scratch.....	591
Creating Document Types from an XML Schema Definition.....	593
About Variable Constraints.....	596
Applying Constraints to a Variable.....	596
Content Types.....	597
Customizing a String Content Type.....	607
Upgrade assets.....	609
How to upgrade assets.....	610

Monitor Integrations.....	613
Overview.....	614
Dashboard.....	614
Execution Results.....	616
Alert Rules.....	618
Reports.....	620
Reference Data.....	623
Overview.....	624
Add Reference Data.....	625
Reference Data Signature.....	626
REST APIs.....	629
Overview.....	630
Creating REST APIs from scratch.....	630
Modifying Resource Operations.....	632
Creating REST APIs with Swagger.....	634
Copying REST APIs.....	635
Exporting REST APIs.....	636
Importing REST APIs.....	637
SOAP APIs.....	639
Overview.....	640
Creating SOAP APIs from scratch.....	641
Creating SOAP APIs with WSDL.....	644
Copying SOAP APIs.....	647
Manage stages, Deploy assets.....	649
Manage Stages.....	650
Apply Access Profiles to a Stage.....	651
Deploy Assets.....	652
Change Stage To View.....	652
Keys and Certificates.....	655
Overview.....	656
Add Keystore.....	656
Add Truststore.....	657
Add Partner Certificate.....	658
Containers.....	659
Overview.....	660
Managing Repositories.....	661
Viewing Tag Details.....	662
Managing Services.....	663
Switch to Cloud Deployment.....	665

Overview.....	666
Solutions.....	671
Creating Solutions.....	671
Exploring Solutions.....	678
Assets.....	680
Support for GraphQL Assets.....	683
Asset Repository.....	689
Deploy.....	690
Capability.....	692
Usage.....	693
Copying Solutions.....	694
Managing Solutions.....	695
Landscape.....	695
Service Access Settings.....	696
Administration.....	698
Restart.....	700
Monitoring Solutions.....	700
Dashboard.....	701
Solutions.....	702
Runtimes.....	703
Viewing Adapter KPIs.....	706
Viewing Connector KPIs.....	706
Services.....	707
Uptime.....	708
Alerts.....	708
Alert Types.....	710
Configuring the Alerts.....	710
Logs.....	712
Database.....	713
Creating a Database.....	713
Connecting a Solution to the Database.....	713
Securing the Connection Between a Solution and the Database.....	714
Monitoring the Database.....	715
Cloud Deployment CLI.....	716
Install Cloud Deployment CLI.....	716
Cloud Deployment CLI Reference.....	718
End-to-End Monitoring.....	737
Overview of End-to-End Monitoring.....	738
What is End-to-End Monitoring.....	738
Why End-to-End Monitoring.....	738
Benefits of End-to-End Monitoring.....	738
How do I Access End-to-End Monitoring.....	738
End-to-End Monitoring Architecture.....	739
General Data Protection Regulation (GDPR) Considerations.....	740

Working with End-to-End Monitoring.....	740
Dashboard for End-to-End Monitoring.....	741
Creating a Group of Transactions.....	744
Viewing the Transactions List.....	745
Editing a Transactions Group.....	746
Deleting a Group.....	747
Filtering the Business Transactions.....	747
Alert.....	749
Viewing Alerts.....	750
Creating a Rule.....	750
Default Rules.....	752
Working with Rule Violations.....	753
Working with Rule List.....	754
Business Transaction Details Page.....	755
Viewing the Transaction Details.....	756
User Journey.....	758

webMethods Integration Cloud

Software AG Cloud is the cloud-based Platform-as-a-Service (PaaS) suite from Software AG and addresses today's business needs with unmatched speed, ease-of-use, and full support for social and mobile collaboration.

webMethods Integration Cloud is the Integration Platform as a Service (iPaaS) offering from Software AG and is a part of the Software AG Cloud family of products. Integration Cloud enables you to integrate your cloud-based Software as a Service (SaaS) applications, with other cloud-based applications. It also integrates your SaaS applications with on-premises applications.

Integration Cloud provides service-based Integration for faster development and deployment. It enables cloud-to-any integration and connects cloud-based SaaS applications and on-premises ESB implementations. The multi-tenant environment scales elastically based on demand. Delivered as a service, the solution empowers your subject matter experts and eliminates integration silos. You can integrate applications hosted in public or private clouds, as well as applications hosted on-premises, reduce the dependency on IT and integrate your SaaS applications faster.

Integration Cloud enables:

- Lightweight integration on public and private clouds
- Easy-to-configure cloud-to-cloud integrations
- Secure and reliable hybrid integrations
- Elastic scalability managed automatically based on usage

Integration Cloud also enables cloud deployment of on-premises integrations. You can build integration projects in Software AG Designer, a full-featured Eclipse™-based environment, and deploy new or existing projects directly into the cloud.

With Integration Cloud, you can use the same set of tools to develop, debug and test integrations for the cloud as you do for on-premises integration. When you want to deploy your existing integrations to the cloud, Integration Cloud combines powerful developer tooling with a SaaS platform. You can select from a range of deployment landscapes, from simple to production-ready configurations that include clustered webMethods Integration Servers, Universal Messaging and Terracotta In-Memory Data Management. Your landscape will be provisioned automatically—and your integrations, APIs, and business logic deployed with it.

Develop integrations faster with:

- Rich data mapping, a large collection of built-in services, and data and cloud applications
- Easy conversion of Java® or flow services into APIs

- Familiar debugging, version control and test tools, while deploying to a multi-function iPaaS
- Integration to on-premises resources through VPN for secure data transmission
- Dashboards to monitor solution health and flow service behavior

Integration Cloud is intended for you if you have a requirement to integrate and synchronize data between multiple SaaS applications, as well as integrate your existing on-premises applications with cloud-based SaaS applications. This solution is delivered as a service, offered on a subscription basis, and is available in multiple package and price tiers.

Document Conventions

Convention	Description
Bold	Identifies elements on a screen.
Narrowfont	Identifies service names and locations in the format <i>folder.subfolder.service</i> , APIs, Java classes, methods, properties.
<i>Italic</i>	Identifies: Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies: Text you must type in. Messages displayed by the system. Program code.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the symbol.
[]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

Online Information and Support

Software AG Documentation Website

You can find documentation on the Software AG Documentation website at "<http://documentation.softwareag.com>". The site requires credentials for Software AG's Product Support site Empower. If you do not have Empower credentials, you must use the TECHcommunity website.

Software AG Empower Product Support Website

If you do not yet have an account for Empower, send an email to "empower@softwareag.com" with your name, company, and company email address and request an account.

Once you have an account, you can open Support Incidents online via the eService section of Empower at "<https://empower.softwareag.com/>".

You can find product information on the Software AG Empower Product Support website at "<https://empower.softwareag.com/>".

To submit feature/enhancement requests, get information about product availability, and download products, go to "[Products](#)".

To get information about fixes and to read early warnings, technical papers, and knowledge base articles, go to the "[Knowledge Center](#)".

If you have any questions, you can find a local or toll-free number for your country in our Global Support Contact Directory at "https://empower.softwareag.com/public_directory.asp" and give us a call.

Software AG TECHcommunity

You can find documentation and other technical information on the Software AG TECHcommunity website at "<http://techcommunity.softwareag.com>". You can:

- Access product documentation, if you have TECHcommunity credentials. If you do not, you will need to register and specify "Documentation" as an area of interest.
- Access articles, code samples, demos, and tutorials.
- Use the online discussion forums, moderated by Software AG professionals, to ask questions, discuss best practices, and learn how other customers are using Software AG technology.
- Link to external websites that discuss open standards and web technology.

Data Protection

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.

1 What's New

- Integration Cloud and Cloud Deployment 24

Integration Cloud and Cloud Deployment

Version 6.0.0 (October 2019)

Integration Cloud

Item	Description
“Preview integrations” on page 407	You can now view the pipeline and mapping details for a previous version of an orchestrated integration by clicking the <i>Show History</i> option in the Development stage. Pipeline preview is available in all stages of the Integration. To view the pipeline and mapping details for a previous version of an orchestrated integration in any stage other than the Development stage, change the stage, select the integration from the Integrations page, and then click <i>Preview</i> . You will not be able to make any modifications to the existing pipeline and mapping data.
“Usage Reports” on page 620	You can now view or download the run counts of integration usages for a specific stage and for the specified time frame. The report shows the count for the currently active stage. The data you see on the Reports page depends on when you view the data and when data collection ends, and it displays data collected till the day before yesterday.
“Copy Integrations, REST APIs, and SOAP APIs across projects” on page 376	You can now copy Integrations, SOAP APIs, and REST APIs between projects. Ensure that you create any account or reference data associated with the respective asset in the target project.
“New services” on page 422	<p>Storage</p> <ul style="list-style-type: none"> ■ deleteStore - Deletes a data store and all its contents. <p>XML</p> <ul style="list-style-type: none"> ■ xmlNodeToDocument - Converts an XML node to a document. ■ xmlStringToXMLNode - Converts an XML document (represented as a String, byte[], or InputStream) to an XML node.

Item	Description
	<ul style="list-style-type: none"> ■ <code>getXMLNodeType</code> - Returns information about an XML node. ■ <code>queryXMLNode</code> - Queries an XML node.
“New Applications” on page 109	<ul style="list-style-type: none"> ■ Salesforce® CRM REST - Integration Cloud connects to Salesforce® CRM REST using the REST API and allows you to manage security for inbound requests, log payloads, and specify run-time performance conditions for consumers for outbound requests. It also supports multiple authentication mechanisms. ■ Google Cloud Pub/Sub - Integration Cloud connects to Google Cloud Pub/Sub and allows you to create, get, delete, set policy, and get policy on topics and subscription resources.
“Locale information” on page 56	<p>You can now set the locale information according to the user's preference from the <i>Users > Locale</i> tab. The value set by you here is the locale applicable for your user profile, irrespective of the value set by a tenant administrator in the <i>Default Locale</i> field in <i>Company Information</i>.</p>
“Support for duplicate keys” on page 380	<p>While running or debugging Integrations and testing Operations, if the input has any duplicate keys, or if the service returns an output with duplicate keys, you can now view those keys.</p>
“End to End Monitoring” on page 758	<p>End-to-End Monitoring is a cloud offering by Software AG to monitor a business transaction from its start to end, as it passes through the various cloud platforms which includes webMethods API Gateway, webMethods Integration Cloud, and webMethods.io B2B. End-to-End Monitoring allows you to identify any errors that occur during a business transaction. It identifies the application within the cloud platform where the error has occurred and also provides details of the time at which the error has occurred.</p>
Cloud Deployment	


Item	Description
“Support upgrade to v10.5 from v10.4 and v10.3” on page 671	You can now upgrade runtimes like webMethods Integration Server, Universal Messaging, and Terracotta that are part of a solution from an earlier solution 10.3 or 10.4 version to the latest 10.5 version.
“Support GraphQL in Cloud Deployment” on page 683	Cloud Deployment now allows you to deploy GraphQL assets which are developed using Software AG Designer and on-premises webMethods Integration Server. You can choose from predefined solution landscapes to deploy your GraphQL on-premises assets from Software AG Designer.
“Support for tenant specific image” on page 671	Hot fixes are now created for specific tenants. The <i>Hot Fix</i> list box in the Solution page lists all available fixes that include enhancements to the selected versions.
“Support for creating solutions in non-development stage” on page 671	Cloud Deployment now supports creating solutions in any stage, for example, in the development, test, live, and pre-live stage.
“Support for defining stateless or stateful cluster for a solution in all stages” on page 671	You can now define that a cluster is stateless or stateful for a solution in all stages. A stateless cluster of webMethods Integration Servers does not use a Terracotta Server Array. Select <i>Stateful</i> to add the Terracotta section. The Terracotta icons will be activated.

Version 5.6.0 (August 2019)

Integration Cloud Version 5.6.0

Item	Description
Projects	A project is an independent entity and corresponds to a folder for organizing your assets. A project holds all the assets created as a part of that project by the logged-in user, along with the configurations associated with the assets. Any asset, for example, Integrations, REST APIs, SOAP APIs, Document Types, and Reference Data, is a part of a project.

Item	Description
	<p>If you are an existing tenant, your assets will be available in the <i>Default</i> project. You cannot delete this default project. If you are a new tenant, the <i>Default</i> project is not available and you need to create a new project.</p> <p>Note: Only Administrators can create new projects.</p>
Project Permissions	<p>Project permissions are used to associate permissions with projects. The new <i>Project Permissions</i> page available under the <i>Settings > Project Permissions</i> tab allows you to associate permissions. Permissions for the <i>Default</i> project are assigned on the <i>Administrative Permissions</i> page in Access Profiles.</p>
Assets categorized under Projects	<p>Assets are now categorized under <i>Projects</i> on the <i>Deploy</i> page. If an asset is pulled and if the associated project is not present in the current stage, the project along with the asset will be available in the current stage.</p>
Administrative permissions regrouped	<p>Administrative permissions under Access Profiles have been regrouped under <i>Global Permissions</i>, <i>Functional Controls</i>, and <i>Project Permissions for Default Project</i>.</p> <p>If you are an existing tenant, your user's <i>Access Profile</i> controls global permissions as well as permissions for the <i>Default</i> project. If you are a new tenant, the <i>Default</i> project is not available and your user's <i>Access Profile</i> controls only global permissions.</p>
Multi Authentication Support	<p>You can now select different authentication types for the same Application while creating an Account. Currently, you can select different authentication types, for example, <i>Credentials</i>, <i>OAuth V2.0 (Authorization Code Flow)</i>, or <i>OAuth V2.0 (JWT Flow)</i> only for Salesforce CRM v44.</p>
Flat File enhancements	<p>Integration Cloud now supports Fixed length and Variable length parsers when you use a <i>sample file</i> to define the definition and structure of a Flat File Application.</p>
Lock and unlock Integrations	<p>Integration Cloud allows you to manage an Integration during the development life cycle by auto locking. When you edit an Integration, it is automatically</p>

Item	Description
	<p>locked for you. This restricts multiple users editing that Integration at the same time. To unlock an Integration, from the Integrations page, click the Integration link. The Integration Overview page appears. From the Integration Overview page, click <i>Unlock</i>.</p> <p>Note: Only the user who locked the Integration or an Administrator can unlock the Integration.</p>
Create document type from an XML Schema Definition	You can now create and delete a document type built from an XML Schema Definition (XSD).
Integration Versioning	<p>While editing an Integration, you can now view the version change history of the Integration and also restore an earlier or previous version of the Integration. Click the <i>Show history</i> option available on the tool bar to view the version change history of the Integration.</p>  <p>Click on an earlier version to view that Integration version and click the <i>Restore</i> option to restore the selected previous version of the Integration.</p>  <p>If you have reverted to an earlier version and there is a scheduled execution for the Integration, the reverted version of the Integration will be run as per the defined schedule.</p>
User Interface enhancements	<p>The following user interface enhancements and changes are made in this release:</p> <ul style="list-style-type: none"> ■ When you log in to Integration Cloud, you will now reach the <i>Projects</i> page instead of the home page. ■ The new <i>Notifications</i> icon on the Integration Cloud navigation bar allows you to view update notifications, when was the last login, and the list of enhancements and changes in the current release.  <ul style="list-style-type: none"> ■ The Orchestrated Integration workspace has been enhanced to improve the usability. Icons on the Orchestrated Integration workspace navigation

Item	Description
	<p>bar have been replaced with intuitive icons and the new <i>Show inline comments</i> option allows you to view comments entered for the blocks.</p> 
Database Application enhancements	<p><i>SSL account in the Database Application</i></p> <p>You can now create SSL account to the databases. To create an SSL account, choose the respective certificate from the <i>Truststore Alias</i> option available in the <i>Account</i> screen.</p> <p><i>Pre-loaded driver support</i></p> <p>You can now use driver groups like Microsoft JDBC Driver for Microsoft SQL Server and PostgreSQL JDBC Driver for PostgreSQL to create the connection.</p>
Custom <i>From Email Address</i> for alert emails	<p>Alert emails that come from Integration Cloud have the <i>From Email Address</i> as <i>noreply@webmethodscloud.*</i> by default. You can now request for a custom <i>From email Address</i> for your tenant.</p>
Custom Domain Name	<p>You can now request for a custom domain name for your tenant. For example, if your company name is XYZ, you can have the domain name as <code>https://subdomain.xyz.com</code>.</p>
Support for form encoded parameter	<p>You can now send simple key value parameters embedded in the Request Body for POST or PUT requests. This uses the default web form encoding, which is <code>application/x-www-form-urlencoded</code>.</p>
Server Name Indication (SNI) Support	<p>While configuring an Account for an Application, you can select the <i>Enable SNI</i> option if a SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SaaS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.</p> <p>To explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the</p>

Item	Description
	Server URL field, specify the host name value in the <i>SNI Server Name</i> field.
Modify alert frequency period	You can now set the alert frequency period from the <i>Alert Rules</i> page to send email messages.
New Applications	<p>The following new Applications are available in this release:</p> <ul style="list-style-type: none"> <li data-bbox="760 619 1541 787">■ Simple Mail Transfer Protocol (SMTP) Application: Integration Cloud allows you to connect to an SMTP server using the Simple Mail Transfer Protocol (SMTP) Application. The SendEmail predefined operation sends an email to the specified recipient using SMTP. <li data-bbox="760 808 1541 934">■ Shopify: Integration Cloud connects to Shopify using the Shopify REST API and allows you to organize your products, customize your storefront, accept credit card payments, track, and respond to orders. <li data-bbox="760 955 1541 1228">■ CloudStreams Connector for Microsoft Azure Data Lake Store: Integration Cloud connects to CloudStreams Connector for Microsoft Azure Data Lake Store using the REST API and allows you to manage File System resources through the Hadoop Distributed File System (HDFS) API. You create directories, folders, and files in your Azure Data Lake Store instance that can store and retrieve data. <li data-bbox="760 1249 1541 1417">■ Zuora REST: Integration Cloud connects to Zuora REST using the Zuora REST API. Zuora allows you to manage Zuora objects in the Zuora Business Object Model, process revenue schedules, and perform other financial operations. <li data-bbox="760 1438 1541 1648">■ Salesforce® CRM REST: Integration Cloud connects to Salesforce® CRM REST using the REST API and allows you to manage security for inbound requests, log payloads and specifies run-time performance conditions for consumers for outbound requests. It also supports multiple authentication mechanisms. <li data-bbox="760 1669 1541 1843">■ webMethods.io B2B: The webMethods.io B2B application allows you to: <ul style="list-style-type: none"> <li data-bbox="808 1774 1541 1843">■ Interact, accept requests, and build integrations for the webMethods.io B2B product instance.

Item	Description
	<ul style="list-style-type: none"> ■ Exchange business documents between trading partners. ■ Electronic Data Interchange (EDI): This application provides predefined operations to parse, validate, and transform EDI messages received from the webMethods.io B2B application and use these transformed messages to create orchestrations.

Cloud Deployment Version 5.6.0

Item	Description
Cloud Deployment Command Line Interface (CLI)	You can now manage a solution, monitor the status of all runtimes in a solution, promote assets from one stage to another, and so on using the Cloud Deployment CLI. The CLI supports <i>Interactive</i> and <i>Normal</i> modes.
Database as a Service	You can now add a MySQL database to your cloud deployment subscription. This enables you to configure, store, and monitor your database directly in the cloud instead of using external systems. The database endpoint can be shared by multiple solutions deployed by the tenant.
Self-managed update management	You can now update any product in a solution to the available higher version after you create the solution. The <i>Update Available</i> option appears if a higher version is available for any of the products in the solution. The latest version will appear in the <i>Version</i> drop-down list.
Copying solutions	You can now copy solutions in any stage. Copying solutions allows you to have a back up of your solution before you make any changes. You can choose to make a copy of a solution by either using the same configuration and services in the solution landscape or by modifying the configuration and services in the solution landscape.
End to end monitoring using AppDynamics	If you are currently using AppDynamics to trace end to end business flows, the new tracing list box option available on the Solution creation page allows you to trace logs after creating or updating a solution for a webMethods Integration Server runtime.

Item	Description
Viewing API signature of executable services	<p>After deploying assets, you can go to the Asset explorer page and click the <i>API Details</i> option to view the API details of the service such as the HTTP Method, URL, Input structure, and the parameters that are required to invoke the service from an external system, for example, a REST client.</p> <p>Note: The <i>API Details</i> option appears only for executable services.</p>
Monitoring support for JDBC adapter and CloudStreams connectors	You can now view <i>Connectivity KPIs</i> for both JDBC adapter and CloudStreams connectors in the runtimes of solutions. For connectors, listeners and connections data are displayed.
webMethods Integration Server service execution statistics	webMethods Integration Server service execution for solutions is now displayed by default for all services. There is no need to enable audit logging.

Version 5.5.0 (April 2019)

This section describes the enhancements and changes made in Version 5.5.0 for **Integration Cloud**:

Item	Description
Validate Input and Output	You can now select the Validate input and Validate output options to specify whether you want Integration Cloud to validate the input and output to the Integration, against the service input or output signature.
Streaming support and replaying Salesforce events	<p>Some Integration Cloud Applications, for example, <i>Salesforce CRM version 44</i>, now support connectivity with streaming APIs and processing of streaming API events.</p> <p>You can create a <i>Salesforce CRM</i> listener, select a subscription channel, and specify the Integration to be invoked on the incoming events. Additionally, you can configure the headers and parameters as well as enable and disable the listener. Once enabled, the listener receives the streaming API events and processes the received events.</p> <p>The <i>Salesforce CRM</i> listener can subscribe and listen to Salesforce events. Salesforce stores standard-volume</p>

Item	Description
	<p>events for 24 hours, so for versions of Salesforce later than v37.0, you can retrieve the events if they are within the retention window. You can replay the lost events by selecting the following replay options:</p> <ul style="list-style-type: none"> ■ <i>New</i> - Receive only new events that are broadcast after subscription. ■ <i>All</i> - Receive new events including past events (last 24 hrs) that are within the retention window. <p>The Salesforce CRM listener can now subscribe and listen to all event types, for example, Salesforce Push Topic Event, Salesforce Platform Event, Salesforce Change Data Capture Event, and Salesforce Generic Event.</p>
Support for consuming and producing Flat Files	<p>You can now create a Flat File Application by defining a flat file structure either manually or from a sample file. You can then convert an inbound flat file to a document by invoking the predefined <i>convertFlatFileToDocument</i> operation in an Integration, or convert a document to an outbound flat file by invoking the predefined <i>convertDocumentToFlatFile</i> operation.</p>
Support for creating SOAP APIs	<p>Integration Cloud allows you to write integration logic to integrate different types of applications. This logic can now be exposed to the external world using SOAP APIs. You can create SOAP APIs by using an existing set of Integrations (from scratch) or by using a WSDL file.</p> <p>A SOAP API exposes one or more Integrations as <i>operations</i>, so each operation in a SOAP API corresponds to an Integration.</p> <p>Using a SOAP client, you can invoke the SOAP operation <i>externally</i> by using either Basic Authentication or 2-way SSL. When the SOAP operation is invoked, the associated Integration gets executed.</p>
Connect to a database using the Database Application	<p>You can now connect to a database using the new <i>Database Application</i> and perform database operations with cloud databases.</p>

This section describes the enhancements and changes made in Version 5.5.0 for **Cloud Deployment**:

Item	Description
Upgrade products to a higher fix version in a solution	You can now upgrade any product in a solution to the available higher fix version after you create the solution. The <i>Upgrade</i> option appears if a higher fix version is available for any of the products in the solution. The latest fix version will appear in the <i>Fix</i> version drop-down list.
Enable packages during solution creation	While creating a solution, after you select a fix version, webMethods Integration Server packages such as WmCloudStreams and WmJDBCAdapter will appear in the <i>Packages</i> group box based on the selected fix version. You can select the packages that you want to enable.
Enable cloud deployment capability for all tenants	Cloud Deployment capability is now enabled by default for all tenants. As soon as you register, 3 CPU cores and 6 GB memory are allocated for all tenants. <i>Provisioning</i> happens if you access Cloud Deployment for the first time using the application launcher. Solutions created using a trial account are deactivated daily. After you log in, you need to reactivate the solutions. All assets will be available after a short delay.
Deploy webMethods CloudStreams assets	You can now deploy CloudStreams provider packages, CloudStreams connector services, CloudStreams connection, and CloudStreams connector listeners to a solution in Cloud Deployment and view those assets. This is applicable only if you have selected <i>WmCloudStreams</i> as the package option while creating the solution.
Promote assets from a solution to another solution	Within a tenant, you can now promote assets from a solution to another solution, from a previous stage to the current stage, for the same runtime type. You can promote assets if the source runtime version is lesser than or same as the target runtime version.
Load pipeline data for testing services	When you run a service in Software AG Designer, you can save the pipeline data as an XML document to your local file system. After you deploy the service in Cloud Deployment, you can now click the <i>Load Data</i> option in the service editor in Cloud Deployment to load or update the pipeline data and test the service.

Item	Description
Download user deployed packages and configurations	<p>You can now download user deployed packages and configurations from the <i>Assets</i> page. The assets will be zipped and downloaded to your local storage space.</p> <p>From the <i>Asset Repository</i> page, you can either download individual packages or download the whole repository for each product. The assets including ACDL files will be zipped and downloaded to your local storage.</p>
Enhanced user interface for Monitoring	<ul style="list-style-type: none"> ■ The <i>Alerts</i> page now displays the <i>Resolved On</i> date for all the resolved alerts. ■ On the <i>Runtimes</i> page, you can now click on the <i>Adapter KPI</i> link to display the Adapters details in a pop-up window. ■ On the landing page, a help icon is now added in the <i>Service Executions</i> card. ■ From the <i>Alerts</i> card on the landing page, you can now click <i>Configure</i> and go to the <i>Alerts Configuration</i> page.

Version 5.1.0 (February 2019)

This section describes the enhancements and changes made in Version 5.1.0 for **Integration Cloud**:

Item	Description
Support for multi-part request body	<p>For some Applications and Operations, for example, for the <i>CloudStreams Connector for Salesforce(R) Bulk v2 Data Loader</i> Application and <i>Create Job and Upload Job Data</i> Operation, Integration Cloud supports multipart request body.</p>
User Interface changes due to performance enhancements	<p>The following user interface changes are made to enhance the performance and reduce the wait time for user actions:</p> <ul style="list-style-type: none"> ■ Applications are now listed under different categories such as Predefined Applications, REST Applications, On-Premises Applications, and SOAP Applications. ■ The Integrations list page (Develop > Integrations) now shows a basic view of all the Integrations. To view the references (Uses column), select the <i>Show Advanced View</i> check box available on the Integrations list page.

Item	Description
Mapping enhancement	While doing pipeline mapping, you can now view only the mapped fields by selecting the <i>Show Only Mapped Fields</i> check box.
Support for viewing Integration Cloud Capabilities	The new <i>Capabilities</i> page allows you to view the status of some of the system capabilities, based on your license offering. To access this page, from the Integration Cloud navigation bar, click  and select <i>Licensing > Capability</i> .
Support for invoking deployed services from Integration Cloud	Integration Cloud Integrations can now invoke Cloud Deployment webMethods Integration Server Flow and Java services for the same tenant. A new pre-defined Application, <i>Cloud Deployment</i> , is added in Integration Cloud. Using this Application, you can select the solution webMethods Integration Server services that you want to call from Integration Cloud.
OAuth 2.0 enhancements	<p>The following OAuth 2.0 enhancements have been implemented in this release:</p> <ul style="list-style-type: none"><li data-bbox="732 1045 1541 1182">■ From the <i>Client Registration</i> page, you can now associate scopes with a client as well as create a new scope and associate it with a client by clicking the <i>Associate Scopes</i> option.<li data-bbox="732 1203 1541 1297">■ Support is added for <i>Client Credentials Grant</i> and <i>Resource Owner Password Credential Grant</i> types as part of OAuth spec for OAuth token generation flow.<li data-bbox="732 1318 1541 1591">■ After you select the <i>Enable Integration to be invoked over HTTP</i> option on the <i>Integration Details</i> page, <i>OAuth Scopes containing the exposed Integration URL</i> appears. Clicking the <i>OAuth Scopes</i> option displays the OAuth Scopes which contain the exposed URL of the Integration. You can add the exposed URL of the Integration to an existing scope or add a new Scope which will contain the exposed URL of the Integration.<li data-bbox="732 1612 1541 1848">■ From the REST API Resources page for a REST API which is created from scratch, you can now click the <i>OAuth Scopes</i> option to view the OAuth Scopes which contain the REST Resource path with Method. You can add the REST Resource path with Method to an existing scope or add a new scope which will contain the REST Resource path with Method.

Item	Description
	<ul style="list-style-type: none"> ■ While creating or updating a scope, you can now select the exposed Integrations and REST Resources that you want to add as <i>Service URLs</i> from the <i>Services</i> dialog box. ■ Enhanced the OAuth Approval page generated in the OAuth token generation flow. ■ SSO support for authentication during OAuth token generation flow. ■ Support for auditing OAuth Client, Scope, and Token CRUD operations.

This section describes the enhancements and changes made in Version 5.1.0 for **Cloud Deployment**:

Item	Description
Support for usage based license monitoring of CPU and Memory capacity	<p>You can now view the cumulative usage of CPU and Memory for all the active solutions in all the stages from the <i>Usage</i> page.</p> <p>To access this page, from the Cloud Deployment navigation bar, click  and select <i>Licensing > Usage</i>.</p> <p>Further, on the Cloud Deployment landing page, you can see the current usage (CPU and Memory) for the tenant.</p>
Continuous Integration/ Continuous Deployment (CI/CD)	<p>You can now build user-created assets and configurations using webMethods Asset Build Environment (ABE), retrieve those assets and configurations from a VCS by using ABE or an automated tool like Jenkins, and then deploy those assets and configurations to the Integration <i>CloudDevelopment Stage</i> using ABE.</p> <div style="background-color: #f0f0f0; padding: 10px; margin-top: 10px;"> <p>Note: For information on CI/CD and how to promote assets across stages, see the <i>Deploying to webMethods Integration Cloud</i> document.</p> </div>
Landscape component status	<p>You can now see the status of a solution landscape component whether it is Ready or Not Ready on the landscape page.</p>
Support for stateless cluster of webMethods Integration Servers	<p>In addition to supporting stateful webMethods Integration Server clusters, you can now define that a cluster is <i>stateless</i> from the <i>Landscape</i> page for a solution. The</p>

Item	Description
	deployment of a solution will therefore not need a Terracotta Server Array.
Support for viewing more assets	You can now view more on-premises assets for Cloud Deployment.
Deployment Status Tracking	<p>You can now type a message to describe the rollback. The rollback message appears on the <i>History</i> page.</p> <p>The History page shows the <i>Trace ID</i>, that is, the tracking ID, which is automatically generated on every successful or unsuccessful promotion or rollback, or deletion, the Deployment, Rollback, or Deletion <i>Action</i>, <i>Date</i> when the asset was promoted, rolled back, or deleted, the <i>User</i> who promoted, rolled back, or deleted the asset, and the commit <i>Message</i> for the selected instance. You can click on a Trace ID to see the <i>Track History</i> for the specific action.</p>
Support for deleting assets	You can now delete assets from all stages from the <i>Deploy</i> page for a solution.
Support for viewing Cloud Deployment Capabilities	<p>The new <i>Capabilities</i> page allows you to view the status of some of the Cloud Deployment capabilities, based on your license offering.</p> <p>To access this page, from the Cloud Deployment navigation bar, click  and select <i>Licensing > Capability</i>.</p>
Support for webMethods Adapter KPI monitoring	<p>You can now monitor the following details of all the installed Adapters:</p> <ul style="list-style-type: none"><li data-bbox="732 1381 1513 1413">■ Total number of enabled and disabled connection pools<li data-bbox="732 1434 1513 1465">■ Total number of enabled and disabled listeners<li data-bbox="732 1486 1513 1518">■ Total number of enabled and disabled notifications
Duplicate low severity alerts	In earlier releases, along with critical alerts, redundant alerts of lower severity like warning and info alerts were also displayed. From this release, if there are critical alerts, lower severity alerts will not be displayed.

Version 5.0.0 (October 2018)

This section describes the enhancements and changes made in Version 5.0.0 for Integration Cloud:

Item	Description
Debug Orchestrated Integrations	You can now debug an orchestrated Integration and can inspect the data flow during the debugging session. You can inspect and edit the pipeline data before and after executing the individual blocks. Further, you can step over each block one at a time, or can specify breakpoints where you want to halt the execution.
Support for OAuth 2.0	You can now protect Integration services and REST APIs using the OAuth 2.0 protocol.
Support for enabling dynamic account configuration details at runtime	For REST Application operations, you can now provide account configurations at runtime during integration execution. When you create or edit an operation of a REST application, you can select the fields you want to pass at runtime in the <i>Dynamic Account Configuration Fields</i> dialog box.
Support for configuring two-way SSL for inbound connections	Integration Cloud now supports two-way SSL for inbound connections. You can store client certificates and associate a certificate with a user account.
Support for refreshing OAuth 2.0 Access Tokens	To refresh the access tokens for accounts which use the OAuth 2.0 protocol, you can now specify a call-back Integration which will execute when the access token expires. Select <i>Custom ESB Service</i> in the <i>Refresh URL Request</i> field and provide the Integration name in the <i>Refresh Custom ESB Service</i> field.
New Applications	<p><i>Applicability Statement 2 (AS2)</i> - Applicability Statement 2 (AS2) allows you to transport EDI and other business data securely and reliably using the HTTP transport protocol. The application supports the AS2 protocol versions 1.1 and 1.2.</p> <p><i>Microsoft Dynamics CRM 365</i> - Microsoft Dynamics CRM 365 allows you to manage CRM data and access metadata that defines the specific CRM instance to which you are connecting using the OData API Version 4.0. This Application performs standard CRUD operations on</p>

Item	Description
	business objects by connecting to the OData service endpoint.
Support for configuring Headers and Parameters for REST-based Applications	You can now add and configure the Headers and Parameters for REST-based Applications.
Support for viewing associated ACLs for an Access Profile	You can now view ACLs associated with an Access Profile from the Access Profile details page.
Support for editing the default Access Control List	You can now edit the default Access Control List. Further, the name of the default ACL has been changed from <i>Everybody</i> to <i>Default</i> .
Service changes	<p><i>New services</i></p> <p>sleep: This service has been added under the Flow category.</p> <p><i>Updated Services</i></p> <p>xmlStringToDocument: New input parameters have been added to this service.</p>
Enhancements for Interactions and Business Objects for Operations	You can now edit interactions in a single request and also edit multiple business objects in a single request. Further, you can drag and drop the interactions or business objects to change the order in which they will execute.
This section describes the enhancements and changes made in Version 5.0.0 for Cloud Deployment:	

Item	Description
Cloud Deployment	Cloud Deployment allows you to deploy on-premises assets and configurations, which are developed using Software AG Designer and on-premises webMethods Integration Server, to Integration Cloud. You can choose from predefined solution landscapes to deploy your on-premises assets from Software AG Designer. The assets and configurations can be promoted from one stage to another stage. During promotion, the asset field values can be changed. You can monitor the health and availability of the solutions and run-time instances, alerts, and alert statuses for all the deployed solutions.

Item	Description
New Administrative Permissions for Solutions	Permissions for creating, updating, and deleting solutions have been added under <i>Access Profile > Administrative Permissions > Functional Controls</i> . The permissions allow you to add, modify, and delete solutions available on Integration Cloud.
Solution Permissions	A new <i>Solution Permissions</i> page in Access Profiles is now available which allows you to map webMethods Integration Server user groups to an Access Profile. With this mapping, the Integration Cloud user who has that Access Profile can perform tasks on the solution webMethods Integration Server(s) by being present in that particular user group.
Customized message while promoting assets	You can now type a message while promoting assets. The promotion message appears on the new <i>History</i> page.
Infrastructure provisioning status for Cloud Deployment	You can now see the status when a solution landscape is provisioning or has been successfully provisioned. The user interface pages will be disabled when a solution is being provisioned.


2 Create and secure your account

■ Registration	44
■ Creating an Account	44
■ Securing your Account	47

Registration

Note: The registration page is not applicable if you have created your account using the Software AG Cloud sign-up page.

Note: If you have created your account using the Software AG Cloud sign-up page, you will receive an email which contains the link to log in. After you log in, you can go to the Software AG Cloud portal using the Application Launcher.



Registration is the process of creating a new Integration Cloud user account. You need to register to create your instance of the platform in the cloud.

Your organization may have multiple members, for example, your organization may be an entire company, an internal department, or just yourself. Similarly, your Integration Cloud account can have multiple internal users who interact with the platform. The very first person to open the Integration Cloud account becomes the first System Administrator for the tenant. The Administrator can then create new users (internal users).

Creating an Account

Note: This page is not applicable if you have created your account using the Software AG Cloud sign-up page.

Creating an account is the first step in the Registration Process.

To create a new User Account

1. On the **Registration** page, complete the following fields:

Note: Required fields are marked with an asterisk on the screen.

Field	Description
First Name	Type your first name. You can change the value after the user is created from the Settings  > Users screen.
Last Name	Type your last name. You can change the value after the user is created from the Settings  > Users screen.
Company	Type your company name. You can change that later from the Settings  > Company Information screen.
Country	Select your country from the drop-down list box. You can change that later from the Settings  > Users screen.
State or Province	Type your State or Province. You can change that later from the Settings  > Users screen.
Phone	Type your phone number. You can change that later from the Settings  > Users screen.
Your Role	Select your role in your current organization from the drop-down list box.
Company Size	Select the number of employees range in your current organization from the drop-down list box.
Is your interest based on	Select at what stage is your current project from the drop-down list box.
Sub-Domain	Provide a unique sub-domain, typically your company name. For example, suppose you are at ABC Company and you decide to use “abc” as your unique sub-domain. With that setting, you will access your instance of the platform at https://abc.webmethodscloud.com .


Field	Description
	<p>Note: You must log in with the correct sub-domain. Some functionalities may not work properly if you log in with a generic sub-domain.</p>
Work Email Address	<p>Type your work email address.</p> <p>The email field becomes both the user name and the email address for the initial user. You can change the values after the user is created, from the Settings  > Users screen.</p>
Type the characters shown in the image	<p>Type the twisted alphanumeric characters in the text input area as shown in the image. You can click the refresh icon to view a new set of characters.</p>
I agree to the Terms of Service	<p>Select this option to agree to the webMethods Integration Cloud Terms of Service.</p>
I confirm that I have acknowledged and accepted the terms of the Data Processing Agreement. I further confirm that I have downloaded and validly countersigned the Data Processing Agreement.	<p>Select this option to acknowledge and accept the terms and conditions of processing of personally identifiable information as per the General Data Protection Regulation (GDPR). GDPR sets guidelines on how to collect and process personally identifiable information. You must also download and countersign the agreement.</p>
Promo Code	<p>Enter a valid promotion code if you have one, for availing subscription benefits.</p>
I opt-in to hearing from Software AG	<p>Select this option if you want to receive information about products, services, and events from Software AG. Software AG may also contact you by phone and may process your personally identifiable information for these purposes. You can unsubscribe and withdraw your consent at any time.</p>

- Click **Register** to continue to the next step to activate and secure your account. After you click **Register** and as soon as the registration process is complete, two different

emails will be sent to the email address you provided during registration. One email will contain the user ID and the other email will contain the temporary password. Use the temporary password to log in. You will be asked to change your password.

Note: Your organization is a tenant in the platform. When you log in to the platform, you log into your organization's tenancy.

Note: If you have created your account using the Software AG Cloud sign-up page, you will receive an email which contains the link to log in. After you log in, you can go to the Software AG Cloud portal using the Application Launcher.



Note: If you are not able to login successfully after a few login attempts, Integration Cloud displays twisted alphanumeric characters in the login page. Type the twisted alphanumeric characters that appear in the text box. You can click the refresh icon to view a new set of characters.

If you have already configured SAML based single sign-on (SSO), the **SSO Login** option appears in the login page. If you click the **SSO Login** option, Integration Cloud redirects you to the Identity Provider (IdP) login page. After you provide the IdP login credentials, you will be logged into Integration Cloud.

Securing your Account

Note: This page is not applicable if you have created your account using the Software AG Cloud sign-up page.

Securing your account is the second step in the Registration process. When you login for the first time, you are asked to change your password and also select a security question. The security question and answer is associated with your user name. If you forget your password, this information is used to verify the account ownership.

To secure your account

1. Type your new password, and then select a security question from the drop down list. Optionally, you can select the option **Write my own security question** to compose a personalized security question.

2. Provide an answer to the security question.
3. Click **Submit**.

Note: If you forget your password, in the login page, click the **Forgot Password?** link, enter your user name, type the distorted alphanumeric characters in the text box, and then click **Change Password**. An email is sent that contains a request to answer the **Security Question** you chose when your account was created. When the email arrives, click the link to open the **Password Reset** page. Provide the answer to your Security Question and enter a new password. After you provide the correct answer, you can log in with your changed password.

3 Projects and Permissions


■ Projects	50
■ Project Permissions	52

Projects

A project is an independent entity and corresponds to a folder for organizing your assets. A project holds all the assets created as a part of that project by the logged-in user, along with the configurations associated with the assets. Any asset, for example, Integrations, REST APIs, SOAP APIs, Document Types, and Reference Data, is a part of a project.

If you are an *existing tenant*, your assets will be available in the *Default* project. You cannot delete this default project. If you are a *new tenant*, the *Default* project is not available and you need to create a new project. Once you log in, click **Projects > + New Project** to create a new project.

Note: Only Administrators can create new projects.



In the **New Project** dialog box that appears, enter a suitable name for the project that you want to create and then click **Create**. This will create a new project. You can now start creating Integrations inside this project. You can create as many projects as you want.

Project permissions are used to associate permissions with projects. See [“Project Permissions” on page 52](#) for information on how to assign permissions to projects.

Note: On-premises applications are stored globally when uploaded to Integration Cloud. They can be referenced by any project while creating Integrations. The same global principle applies to predefined applications, predefined operations, and recipes. REST Applications, SOAP Applications, Flat File

Applications and the Accounts and Operations created for the Applications are contained within a project.


The following table lists the asset types and identifies whether the asset type is specific to a project or is shared across all projects.

Asset Type	Location	Remarks
Predefined Applications	Global	Shared across all projects
REST Applications	Project	Project specific
On-Premises Applications	Global	Shared across all projects
SOAP Applications	Project	Project specific
Flat File Applications	Project	Project specific
Accounts	Project	Project specific
Operations - Custom	Project	Project specific
Operations - Predefined	Global	Shared across all projects
Keys & Certificates	Project	Project specific
SFTP Application	Project	Project specific
FTP Application	Project	Project specific
Integrations	Project	Project specific
Document types	Project	Project specific
REST APIs	Project	Project specific
SOAP APIs	Project	Project specific
Reference data	Project	Project specific

Asset Type	Location	Remarks
Recipes	Global	Shared across all projects

Editing and Deleting Projects

To edit a project, locate the project that you want to edit. Then click on the vertical ellipsis icon (or three tiny dots) at the top-right corner of your project and click on **Edit**. You can edit the name of the project from here.



To delete a project, locate the project that you want to delete. Then click on the vertical ellipsis icon (or three tiny dots) at the top-right corner of your project and click **Delete**. Confirm the delete action to permanently delete the project.

Project Permissions

A project is an independent entity and corresponds to a folder for organizing your assets. A project holds all the assets created as a part of that project by the logged-in user, along with the configurations associated with the assets. Project permissions are used to associate permissions with projects.

You associate permissions with projects from the **Settings**  > **Project Permissions** > **Add New Project Permission** page.



Integration Cloud provides a system-generated **Developer** project permission profile in your tenant. Any new project created is automatically associated with the **Developer** project permission profile. This profile has permissions to create, update, delete, and execute all assets. You cannot edit or delete this system-generated project permission profile. If a project permission profile is associated with a user on the user profile page, the user can perform only the permitted tasks in the mapped project.

If you are an existing tenant:

- Your user's **Access Profile** controls global permissions as well as permissions for the **Default** project.
- Your user's Project Permissions profile control permissions for other projects.

- All existing user profiles will be associated with the **Developer** project permission profile.
- All projects created have the **Developer** project permission profile associated with it.
- All existing assets will be available in the *Default* project.
- Manage the permissions for existing assets inside the **Default** project from the **Project Permissions for Default Project** section under **Settings**  > **Access Profiles** > **Administrative Permissions**.
- Manage the permissions for new assets created inside the **Default** project from the **Project Permissions for Default Project** section under **Settings**  > **Access Profiles** > **Administrative Permissions**.
- If you create a new project, you have to assign the project permissions from the **Settings**  > **Project Permissions** > **Add New Project Permission** page.

If you are a new tenant:

- The *Default* project is not available. There are no existing assets. Your user's **Access Profile** controls only global permissions.
- The Administrator will be associated with the **Developer** project permission profile and can assign a project permission profile to a new user.
- All projects created have the **Developer** project permission profile associated with it.
- If you create a new project, you have to assign the project permissions from the **Settings**  > **Project Permissions** > **Add New Project Permission** page.

Once you log in, from the Integration Cloud navigation bar, click **Settings**  > **Project Permissions** > **Add New Project Permission**. Select a project and then click the add icon  to add the project in the panel. Then assign the relevant permissions to the selected project. You can select another project and assign the permissions to the selected project. Click **Add**.

Add project and assign permissions



Note: If you associate the project permission profile to a user on the user profile page, the user can perform only the permitted tasks in each mapped project.

Example 1

A user is assigned to two project permission profiles A and B in the user profile. Project permission profile A has the Execute Integration permission in Project X but Project permission profile B does not have the Execute Integration permission for the same Project X. The user will still be able to execute the Integration.

Example 2

In this example, we will see how you will allow an existing user U1 to create, update, delete, and execute Integrations for the Project P1 but not for Project P2.

1. You must have the **Access Control** permission under **Access Profiles > Administrative Permissions**.
2. Create Project P1 and Project P2.
3. Create a new Project Permission profile PP1 under **Settings > Project Permissions > Add New Project Permission**.
4. On the **Add New Project Permission** page, add Project P1 in the mapped projects list. Assign the create, update, delete, and execute Integration permissions to the mapped Project P1.
5. Do not map Project P2.
6. Go to the **Basic** tab of user U1 and select *only* PP1.

So when U1 logs in, U1 will only be able to create, update, delete, and execute Integrations for the Project P1 but not for Project P2.

4 Settings

■ Users	56
■ Capability	63
■ Access Profiles	65
■ Access Control Lists	72
■ Project Permissions	74
■ Single Sign-On	76
■ Company Information	83
■ Password Policy	85
■ Client Certificate	87
■ OAuth 2.0	94
■ Audit Log	105

Users

You can use the **Users** screen to create and manage administrators and other users. A User has a login identity, password, email address, and other descriptive attributes.

From the main **Users** screen, you can search for users, create a new user, delete an existing user, update existing user information, and reset a user's password. If you have the **User Management** permission under **Settings**  > **Access Profiles** > **Administrative Permissions** > **User and Ownership Controls**, you can either edit or delete users.

Note: You cannot delete your own user profile. If a user is deleted, then the user cannot be recovered and all assets created or modified by the user will appear in the *Created By* and *Modified By* columns as *Unknown User{first two characters of the first name and last name}*.

Click **Reset Password** to reset the user's password. As soon as the password is reset, two different emails will be sent to the email address you provided during registration. One email will contain the user ID and the other email will contain the temporary password. Use the temporary password to log in. You will be asked to change your password.

Users who have the required access privileges under **Settings**  > **Access Profiles** > **Administrative Permissions** > **User and Ownership Controls** can edit user information.

Adding Users

Note: If you have created your account using the Software AG Cloud sign-up page, that is, if you are a Software AG Cloud tenant, you can perform certain user management tasks like adding users, updating users, and resetting passwords only from the Software AG Cloud User Administration page. Further, a new user is created in Integration Cloud when you log in for the first time using the Software AG Cloud login page. The newly created user is associated with the **Regular User** Access Profile if you have selected Integration Cloud-User in the Software AG Cloud User Administration page, or the **Administrator** Access profile if you have selected Cloud-Tenant-Administrator in the Software AG Cloud User Administration page.

You can delete users from the **Users** page in Integration Cloud. If you have created Users U1, U2, and U3 in Software AG Cloud, the first time U1 logs in to Integration Cloud, user U1 will be created in Integration Cloud. Now if U1 is deleted from Software AG Cloud but still exists in Integration Cloud, U1 will not be able to log in to Integration Cloud. If U1 is deleted from Integration Cloud but still exists in Software AG Cloud, U1 will be created in Integration Cloud when you again log in to Integration Cloud.

If you have not created your account using the Software AG Cloud sign-up page, you can add users in Integration Cloud.

To add a user if you have not created your account using the Software AG Cloud sign-up page

1. From the Integration Cloud navigation bar, go to **Settings**  > **Users**.
2. From the upper right part of the Users screen, click **Add New User**.
3. On the **Basic** tab, complete the following fields. Required fields are marked with an asterisk on the screen.

Field	Description
First name	User's first name as it should appear in the platform.
Last name	User's last name as it should appear in the platform.
Title	User's professional title.
Access Profile	<p>The access profile assigned to the User. Each User is assigned an access profile, which can be shared by other users. An Access Profile specifies the network locations (IP addresses) from where it is possible to login and administrative permissions. Select one of the following Access Profiles:</p> <ul style="list-style-type: none"> ■ Administrator - Provides permissions needed by the System Administrator. ■ Regular User - Provides permissions that are more appropriate for normal users. <p>By default, the system administrator can change the Administrative Permissions associated with each Access Profile (except the above mentioned Administrator Access Profile), and can add additional Access Profiles, as needed.</p> <div style="background-color: #f0f0f0; padding: 10px;"> <p>Note: By default, the Administrator and Regular User Access Profiles are associated with the Development Stage. If you have created a new Access Profile, ensure that the Access Profile you have created is associated with the Development Stage. See Adding or Updating Access Profiles for more information and for information on API Management Access Profiles and permissions.</p> </div>
Project Permission	Project permissions are used to associate permissions with projects.

Field	Description
	 <p data-bbox="586 499 1343 911">Any new project created is automatically associated with the <i>Developer</i> project permission profile. If a project permission profile is associated with a user on the user profile page, the user can perform only the permitted tasks in the mapped project. If you are an existing tenant, all existing user profiles will be associated with the <i>Developer</i> project permission profile. If you are a new tenant, the Administrator will be associated with the <i>Developer</i> project permission profile and can assign a project permission profile to a new user. You can add more project permission profiles to the user. See “Project Permissions” on page 52 for more information.</p>
Employee Number	Optional identification number for each employee.
Email	<p data-bbox="586 1031 1343 1100">Email address of the user. User credentials will be sent to the specified email address.</p> <p data-bbox="586 1121 1343 1289">As soon as you add a new user, two different emails will be sent to the email address. One email will contain the user ID and the other email will contain the temporary password. Use the temporary password to log in. You will be asked to change your password.</p>
User Name	<p data-bbox="586 1335 1343 1436">User name is a unique name associated with each user and is required to log in. It can be an email address or an alphanumeric text string.</p> <div data-bbox="586 1457 1343 1549" style="background-color: #f0f0f0; padding: 5px;"> <p data-bbox="586 1457 1343 1549">Note: If you are a Software AG Cloud user, you will not be able to update the User Name.</p> </div>
Federation ID	<p data-bbox="586 1583 1343 1818">Enter the Federation ID if your Identity Provider passes the Federation ID for Single Sign-On. See the "Single Sign-On" Help page for more information. The Federation ID acts as a user's authentication across multiple IT systems or organizations. A federated identity means linking a person's electronic identity and attributes stored across multiple distinct identity management systems.</p>

Field	Description
Partner	Select this option if the user is a Partner user. If Allow User Interface Access permission available under Access Profile > Administrative Permissions > Account Controls is not enabled, a Partner User can still perform on-premises tasks.
Active	Select this option to indicate that the user account is active. You can use this option to reactivate a locked or disabled user account.

4. On the **Locale** tab, complete the following fields:

Field	Description
Time Zone	Choose a Time Zone Code from the drop down list.
Date Format	<p>Choose a Date Format from the drop down list. "mm" is "Month", "dd" is "Day", and "yyyy" is Year.</p> <p>Dates and Times are used throughout the platform, in Appointments, as Start/End Dates in Tasks, Expected Close Date, Estimated Start/End Date, Date Due, and so on. Default formats are specified under the Settings  > Company Information > Advanced Information tab. Administrators and Users can change the default selection in the Users screen.</p>
Locale	<p>This setting determines the language in which you will view the application.</p> <p>The value set by you here is the language applicable for your user profile, irrespective of the value set by the administrator in the Default Locale field of Company Information settings.</p> <p>For example, if you set the value in the Locale field as <i>Chinese</i> and the value set by the administrator in the Default Locale field of Company Information settings is <i>English</i>, then you will view all the application labels in the Chinese language.</p>
Time Format	Select a 12-hour clock (hh:mm a) with AM/PM, or a 24-hour clock (HH:mm).

5. On the **Address and Contact** tab, complete the following fields:

Field	Description
Phone	Primary phone number for the user.
Mobile Phone	Mobile phone number for the user.
Fax	Fax number for the user.
Street Address	Street address for the user.
City	City for the user.
State/Province	State or province for the user.
Postal/Zip Code	Postal or ZIP Code for the user.
Country	Country for the user.

- Click **Add** if you are adding a User or **Apply** if you are editing any User information.

You can fill the **Address and Contact** section later or the Administrator can fill the details by editing the record after the User has been added. The **Address and Contact** screen is also available under  > **My Profile** > **My Information** tab.

Note: A User can log in, and then go to  > **My Profile** > **Edit** to change the user details. The Administrator who created the User can also edit the User details.

Updating Users

To edit or update the user information

Note: If you have created your account using the Software AG Cloud sign-up page, that is, if you are a Software AG Cloud tenant, you can perform certain user management tasks like adding users, updating users, and resetting passwords only from the Software AG Cloud User Administration page.

- From the Integration Cloud navigation bar, click **Settings**  > **Users**.
- Select a user from the list, and then click **Edit**.
- Make necessary modifications. See [“Adding Users” on page 56](#) for information on the relevant fields. You can also enter or update the following information on the **Address and Contact** tab. Required fields are marked with an asterisk on the screen.

Note: If you are a Software AG Cloud user, you will not be able to update the **User Name**.

Field	Description
Phone	Primary phone number for the user.
Mobile Phone	Mobile phone number for the user.
Fax	Fax number for the user.
Street Address	Street address for the user.
City	City for the user.
State/Province	State or province for the user.
Postal/Zip Code	Postal or ZIP Code for the user.
Country	Country for the user.

4. Click **Apply**.

The default initial information comes from the  > **Company Information** page, but you can modify it here.

Note: A user can log in and then go to  > **My Profile** to change the user details. The administrator who created the user can also edit the user details.

Note: If you have the **User Management** permission under **Settings**  > **Access Profiles** > **Administrative Permissions** > **User and Ownership Controls**, you can either update or delete users. You cannot delete your own user profile. If a user is deleted, then the user cannot be recovered and all assets created or modified by the user will appear in the *Created By* and *Modified By* columns as *Unknown User{first two characters of the first name and last name}*.

Resetting Passwords

Note: This page is not applicable if you have created your account using the Software AG Cloud sign-up page.

Note: If you have created your account using the Software AG Cloud sign-up page, that is, if you are a Software AG Cloud tenant, you can perform certain user

management tasks like adding users, updating users, and resetting passwords only from the Software AG Cloud User Administration page.

To reset a user's password if you have not created your account using the Software AG Cloud sign-up page

1. From the Integration Cloud navigation bar, go to **Settings**  > **Users**.
2. For the user whose password is to be reset, select the user and click **Reset Password**.



Integration Cloud sends two different emails to the email address you provided during registration. One email will contain the user ID and the other email will contain the temporary password. Use the temporary password to log in. You will be asked to change your password.

Note: A User can log in, and then go to  > **My Profile** to change the user details. The administrator who created the User can also edit the User details.

User Profile

If you are on the **My Information** page  > **My Profile** > **My Information**, the page provides profile information for the logged in user for the Integration Cloud instance.

If you are on any user profile page, (**Settings**  > **Users** > **Click on the User Name link**), the page provides profile information for the selected user for the Integration Cloud instance.

You can view the **Basic**, **Locale**, and the **Address and Contact** information.

Click **Edit** to update the information.

Security Question

Note: This page is not applicable if you have created your account using the Software AG Cloud sign-up page.

To update the Security Question and Answer

1. From the Integration Cloud navigation bar, go to  > **My Profile** > **Security Question**.
2. Select a **Security Question** and type a **Security Answer**. You can change the **Security Question** associated with your Account Login/Password.

3. Click **Submit**.

Note: The User name and Email address can differ, depending on the settings specified in the  > **My Profile > My Information** page.

Change Password

Note: This page is not applicable if you have created your account using the Software AG Cloud sign-up page.

To change your password

1. From the Integration Cloud navigation bar, go to  > **My Profile > Change Password**.
2. Type your current password in the **Old Password** field, your new password in the **New Password** field, and again retype your new password in the **Retype New Password** field.
3. Click **Submit**. You will receive a confirmation email about your changed password.

My Certificate


Integration Cloud allows you to store client certificates and associate a certificate with a user account. When a client presents one of these certificates, Integration Cloud logs in the client, as the user *mapped* to the certificate. You can view the client certificate for the logged in user on the **My Certificate** page.

To view the certificate

1. From the Integration Cloud navigation bar, click  > **My Profile > My Certificate**.
2. If a certificate is configured for the user, the **View Certificate** panel displays the configured certificate. You can click **Download** to download the user certificate or click **Delete** to delete the user certificate. The downloaded file is named as <username>.crt.
3. In the **Upload New Certificate** field, click **Browse** to upload a new client certificate signed by a trusted Certificate Authority (CA).
4. In the **Generate Private Key and Certificate** field, click **Generate** if you want Integration Cloud to generate a private key and a new Integration Cloud signed client certificate. Integration Cloud validates it against the issuer of the certificate. The generated certificate is named as <username>.txt.

Capability

The **Capability** ( > Licensing) page allows you to view the status of some of the system capabilities, based on your license offering.



You can view the details of the following capabilities in **Integration Cloud**:

Field	Description
Allowed application count	Total number of Applications that can be utilized by the tenant.
On-premises connection	If Yes , then on-premises applications can be uploaded from on-premises systems.
Max allowed users	Maximum number of active users allowed for the tenant.
Allowed number of stages	Maximum number of staging environments allowed for the tenant.
Integration restart and resume	Integrations can be restarted and resumed.
Integration import and export	Integrations can be imported and exported.
Trial account	If Yes , then the account is a trial account.
Trial end date	The trial period end date. This field appears only if the account is a trial account.

You can view the details of the following capabilities in **Cloud Deployment**:

Field	Description
Max allowed cores	Maximum number of CPU cores allowed across all active solutions and all stages for the tenant. You will not be able to create additional solutions if you exceed this capability.
Max allowed memory	Maximum memory capacity allowed across all active solutions and all stages for the tenant. You will not be able to create additional solutions if you exceed this capability.
Allowed number of stages	Maximum number of staging environments allowed for the tenant.
Trial account	If Yes , then the account is a trial account.
Trial end date	The trial period end date. This field appears only if the account is a trial account.

Access Profiles

An **Access Profile** specifies a collection of permissions that can be applied to multiple users. Each user is assigned an Access Profile, which can be shared by other users.

Users who have the required access privileges under **Settings**  **> Access Profiles > Administrative Permissions > User and Ownership Controls** can edit the Access Profiles information.

An Access Profile specifies:

- The network locations (IP addresses) from where it is possible to login.
- Administrative permissions.
- Container user groups
- API Management permissions

The default Access Profiles are:

- Administrator, which provides permissions needed by the System Administrator.
- Regular User, which provides permissions that are more appropriate for normal users.

Note: The Integration Cloud User role in Software AG Cloud maps to the Regular User access profile in Integration Cloud. Users assigned to the

Integration Cloud User role have limited permissions that are more appropriate for normal users.

- API Gateway Administrators - By default, all API Management permissions are assigned to the Administrators access profile and these privileges cannot be modified.
- API Gateway Providers - By default, the following permissions are assigned to the API Gateway Providers access profile and these privileges cannot be modified:
 - Manage APIs
 - Manage Applications
 - Manage policy templates
 - Manage packages and plans
 - Publish to API Portal
 - Export assets
 - Execute service result cache APIs
 - Activate/Deactivate APIs/Packages
 - Manage aliases
 - Import assets
- API Portal Administrators - The API Portal Administrator can perform all the functions in API Portal.
- API Portal Providers - The API Portal Provider can manage APIs and packages in API Portal.

Note: You can create and manage API Management Access Profiles provided you have the required API Gateway Cloud and/or API Portal Cloud licenses.

By default, the system administrator can change the **Administrative Permissions** associated with each Access Profile and can add additional Access Profiles, as needed.

To edit an existing Access Profile, select the profile and click **Edit**. To delete an Access Profile, select the profile and click **Delete**. You will not be able to delete an Access Profile if it is used by a user. To create a new Access Profile, click **Add New Access Profile**.

Note: The Access Profile ID is needed while configuring Single Sign-On (SSO). You have to provide the ID while configuring the Identity Provider (IDP), if you want to create a user if the user is not present. The newly created user will be associated with the Access Profile represented by the ID sent by the IDP in the SAML Response. The name of the SAML attribute that designates the user's access profile must contain the ID of the Access Profile.

Adding or Updating Access Profiles

Use the **Access Profiles** screen to create or edit profiles assigned to users.

To add or update an Access Profile

1. From the Integration Cloud navigation bar, go to **Settings**  > **Access Profiles**.
2. Click **Add New Access Profile** to add a custom access profile or click **Edit** to modify an existing Access Profile.
3. On the **Add New Access Profile** or **Update Access Profile** > **Access Profile Information** tab, complete the following fields. Required fields are marked with an asterisk on the screen.

Field	Description
Name	Provide a name for the Access Profile. You can reference the profile by name when assigning it to a user.
Description	Provide a general description for the Access Profile.

4. On the **Login IP Address Restrictions** page, complete the following fields:

Field	Description
IP Address Ranges	For extra security, enter ranges of IP addresses from which users are allowed to access the platform. If a user attempts to login from a computer on a network outside of the specified range, access to the platform is denied.

Note: A maximum of 25 IP address ranges can be specified. You can add, modify, and delete the entries. Accepted format is xxx.xxx.xxx.xxx - yyy.yyy.yyy.yyy, where xxx and yyy are numbers in the range 0-255 and xxx.xxx.xxx.xxx is less than or equal to yyy.yyy.yyy.yyy. To specify a single IP address, use the same IP address for the start and endpoint of the range: 192.168.1.1 - 192.168.1.1

When a user attempts to log in, the IP address of the system the request originated from is checked against the configured settings. If the address is in the allowed range, the user can continue the login process. Otherwise, login is denied. Access violations are recorded in the audit log, identifying both the user and the IP address from where the login attempt originated. Login restrictions do not apply to Customer Support logins.

5. On the **Administrative Permissions** page, select the operations a user can perform in order to access, view, create, update, upgrade, administer, execute, export, deploy, and delete and to allow the user to customize selected aspects of the platform.

Field	Description
Global Permissions	
User and Ownership Controls	User Management - Select this option if you want to add, update, delete users, or assign users to Access Profiles.
	Access Control - Select this option if you want to allow a user to modify Access Profiles, edit ACLs, specify user application access rights, manage Access Profiles, specify the password policy, create, edit, and delete OAuth 2.0 clients and scopes, and delete OAuth 2.0 tokens.
	Manage Personal Setup - Select this option if you want to allow a user to modify the personal information, and generate or edit the user's own certificate.
Account Controls	Manage Company Capabilities - Select this option if you want to allow users to modify the company information.
	Allow User Interface Access - Select this option if you want to allow users to log in to Integration Cloud and access the user interface. Clear this option if you want to deny users to access the user interface. Further, even if you clear this option, all users can still interact with Integration Cloud using REST interface calls.
<p>Note: If the Allow User Interface Access permission is not enabled for a user but if the user is a Partner user, that user will still be able to perform on-premises tasks.</p>	
Data Management Controls	Manage Audit Log - Select this option if you want to allow users to view the Audit Log. If this option is enabled, the Audit Log page will be displayed. If not selected, the user will not be able to view the Audit log page. To view the Audit Log screen, from the Integration Cloud navigation bar, click Monitor > Audit Log .
Functional Controls	
Select the required options under Assets, Stages, Advanced Security, Application, Solution, and Database . You must select the required permissions to deploy, export, administer, upgrade, create, update, and delete those functions.	

Field	Description
-------	-------------

Project Permissions for Default Project

Here you will manage the permissions for new and existing assets inside the **Default** project. See [“Project Permissions” on page 52](#) for information. Select the required options under **Accounts, Operations, Reference Data, Document Type, Integrations, REST APIs, SOAP APIs, and Listeners.**

Note: If you are a new tenant, the *Default* project is not available, so this section is not applicable. Your user's **Access Profile** controls only global permissions.

- On the **Container** page, enter the names of the webMethods Integration Server Access Control List (ACL) groups separated by a comma, for example, Administrators, Developers, and so on. Users who are assigned to this Access Profile will be now part of the webMethods Integration Server container user group (s) and can perform tasks allowed for those user groups. If you do not map an Access Profile to an webMethods Integration Server group, you will not be able to invoke webMethods Integration Server services. For information about user groups, see the *Managing Users and Groups* section in the *webMethods Integration Server Administrator's Guide*.

Note: The **Container** tab and Container related Administrative permissions are available only if you have the required license for Containers.

Note: Integration Cloud Administrator profiles are *not automatically* assigned to the webMethods Integration Server Administrators ACL group. If you do not enter any user groups in the **Container User Groups** field, but have configured webMethods Integration Server in a way such that it needs to verify the ACL groups you have entered in the **Container User Groups** field while invoking services, you will not be able to run or invoke webMethods Integration Server services from Integration Cloud.

- The **API Management** tab displays the API management permissions.

Note: Integration Cloud provides the user management capability for API Gateway. You can create and manage API Management Access Profiles provided you have the required API Gateway Cloud and/or API Portal Cloud licenses.

Field	Description
-------	-------------

User and Ownership Controls	User Management - Select this option if you want to create and manage users.
------------------------------------	---

Select the following **Functional Controls** based on your requirements:

Field	Description
Manage APIs	To create and manage APIs.
Activate/Deactivate APIs	To activate, deactivate and manage APIs.
Publish to API Portal	To publish assets to API Portal.
Manage Applications	To create and manage applications and register applications with the APIs. You cannot modify or delete an application if you are not the owner of the application.
Manage aliases	To create and manage aliases.
Manage Global Policies	To apply a global policy to all APIs or the selected set of APIs.
Activate/Deactivate Global Policies	To activate and deactivate global policies.
Manage Policy Templates	To apply one or more policy templates to an API.
Manage Threat Protection Policies	To prevent malicious attacks on applications that typically involve large, recursive payloads, and SQL injections.
Manage Packages and Plans	To create packages and plans, associate a plan with a package, and associate APIs with a package. In addition, you can view the list of packages, package details, APIs, and plans associated with the package.
Activate/Deactivate Packages	To activate and deactivate packages.
Import Assets	To import already exported APIs, application, policies, and aliases by selecting <i>Username > Import</i> in API Gateway.
Export Assets	To export assets to your local system.

Field	Description
Manage general administration configurations	To create and manage administration configurations.
View Administration Configurations	To view administration configurations.
Manage General Configurations	To manage general configurations.
Manage Security Configurations	To create and manage security configurations.
Manage Destination Configurations	To publish events and performance metrics data to the configured destinations.
Manage System Settings	To create and manage system settings.
Purge/Restore Runtime Events	To purge and restore events from the API Gateway store by setting the required date or duration in API Gateway.
Manage Service Result Cache	To manage caching of the results of API invocations depending on the caching criteria defined.
Manage Promotions	To add, modify, and delete API Gateway stages, or move API Gateway assets from the source stage to one or more target stages, or to rollback an asset promotion that is already available in the target stage at any time.
API Portal Administrator	To manage all API Portal administrative tasks.
API Portal Provider	To manage all API Portal provider tasks.

- The **Solution Permissions** page displays the webMethods Integration Server User Groups for all the solutions. You can map webMethods Integration Server user groups to an Access Profile. Enter the names of the webMethods Integration Server User Groups separated by a comma, for example, Administrators, Developers, and so on. Integration Cloud users who are assigned to this Access Profile will then be a part of the webMethods Integration Server user group(s) and can perform tasks allowed for those user groups. If you do not map an Access Profile to a webMethods Integration Server user group, you will not be able to view, edit, or run webMethods Integration Server services in a *solution*. For information about user groups, see the

Managing Users and Groups section in the *webMethods Integration Server Administrator's Guide*.

Note: Integration Cloud Administrator profiles are *automatically assigned* to the webMethods Integration Server Administrators User Group.

Note: To view and access webMethods Integration Server packages in Integration Cloud, you must assign any custom user groups created in webMethods Integration Server, which are assigned to Access Profiles in the **Solution Permissions** page, to the following Access Control Lists in webMethods Integration Server:

- Administrators ACL
- Developers ACL
- Replicators ACL

9. Click **Apply**.

The new Access Profile appears in the **Access Profiles** page.

10. Click on the Access Profile link in the **Access Profiles** page. In the **Associated Users** page, you can view the active users associated with the selected Access Profile. In the **Associated ACLs** page, you can view the Access Control Lists associated with the selected Access Profile.

Access Control Lists

You can use Access Control Lists (ACLs) to control the execution permission of an Integration. ACLs provide you with another level of control over who can execute specific Integrations. An ACL can be assigned to an Integration and a user can be associated with the ACL through the Access Profile. Therefore using ACLs, you can control the users who can execute an Integration.

Example 1

You have three users U1, U2, and U3. U1 is assigned to Access Profile AP1, U2 is assigned to Access Profile AP2, and U3 is assigned to Access Profile AP3. Each user has the Integration execution permission. There are also four Integrations IN1, IN2, IN3, and IN4 in your tenancy. Initially, U1, U2, and U3 can run all the four Integrations IN1, IN2, IN3, and IN4. Now you want IN1 to be executed only by U1 and *not* by U2 and U3. To do that, create an Access Control List, ACL1. Associate ACL1 to IN1. Then associate ACL1 to AP1. As U1 has already been assigned to AP1, IN1 can be executed by *only* U1. If you want IN1 to be executed also by U2, then associate ACL1 with AP2.

Integration Cloud provides you with a default ACL, *Default*, and this default ACL is associated with all Integrations. You can change the ACL associated with an Integration in the *Integration Details* page.

Example 2

You have three users U1, U2, and U3. U1 is assigned to Access Profile AP1, U2 is assigned to Access Profile AP2, and U3 is assigned to Access Profile AP3. Each user has the Integration execution permission. There are also four Integrations IN1, IN2, IN3, and IN4 in your tenancy. Initially, U1, U2, and U3 can run all the four Integrations IN1, IN2, IN3, and IN4. Now you want U1 to run only IN1 and *not* IN2, IN3, and IN4. To do that, create an Access Control List, ACL1. Associate ACL1 to IN1. Then associate ACL1 to AP1, AP2, and AP3. Now disassociate AP1 from the default ACL. As AP1 is associated with *only* ACL1, U1 will be able to execute only those Integrations associated with ACL1.

Users who have the **Access Control** permission under **Settings > Access Profiles > Administrative Permissions > User and Ownership Controls** can edit the ACL information.

To edit an existing ACL other than the default ACL, select the ACL and click **Edit**. To delete an existing ACL other than the default ACL, select the ACL and click **Delete**. If you delete an ACL, the ACL will be removed from the associated Integration and the Integration will be associated with the default ACL. To create a new ACL, click **Add New Access Control List**.

Adding or Updating Access Control Lists

Use the **Access Control Lists** page to create, edit, or delete Access Control Lists (ACLs). You can also edit the default ACL, *Default*, but you cannot delete it.

To add or update an ACL

1. From the Integration Cloud navigation bar, go to **Settings  > Access Control Lists**.
2. Click **Add New Access Control List** to add an ACL or click **Edit** to modify an existing ACL.
3. On the **Add New Access Control List** or **Update Access Control List** page, complete the following fields. Required fields are marked with an asterisk on the screen.

Field	Description
Name	Provide a name for the ACL. The name cannot be modified after you save the ACL.

4. On the **Associate with Access Profiles** tab, complete the following fields:

Field	Description
Select Access Profiles	Select the Access Profiles that you want to associate with the ACL. All Access Profiles created in Integration Cloud appear in the panel. The <i>Administrator</i> Access Profile will always be associated with all the ACLs, therefore users associated with

Field	Description
	the Administrator Access Profile will be able to execute all Integrations.

- Click **Apply**.

Project Permissions

A project is an independent entity and corresponds to a folder for organizing your assets. A project holds all the assets created as a part of that project by the logged-in user, along with the configurations associated with the assets. Project permissions are used to associate permissions with projects.

You associate permissions with projects from the **Settings**  > **Project Permissions** > **Add New Project Permission** page.



Integration Cloud provides a system-generated **Developer** project permission profile in your tenant. Any new project created is automatically associated with the **Developer** project permission profile. This profile has permissions to create, update, delete, and execute all assets. You cannot edit or delete this system-generated project permission profile. If a project permission profile is associated with a user on the user profile page, the user can perform only the permitted tasks in the mapped project.

If you are an existing tenant:


- Your user's **Access Profile** controls global permissions as well as permissions for the **Default** project.
- Your user's Project Permissions profile control permissions for other projects.
- All existing user profiles will be associated with the **Developer** project permission profile.
- All projects created have the **Developer** project permission profile associated with it.
- All existing assets will be available in the *Default* project.
- Manage the permissions for existing assets inside the **Default** project from the **Project Permissions for Default Project** section under **Settings**  > **Access Profiles** > **Administrative Permissions**.
- Manage the permissions for new assets created inside the **Default** project from the **Project Permissions for Default Project** section under **Settings**  > **Access Profiles** > **Administrative Permissions**.

- If you create a new project, you have to assign the project permissions from the **Settings**  > **Project Permissions** > **Add New Project Permission** page.

If you are a new tenant:

- The *Default* project is not available. There are no existing assets. Your user's **Access Profile** controls only global permissions.
- The Administrator will be associated with the **Developer** project permission profile and can assign a project permission profile to a new user.
- All projects created have the **Developer** project permission profile associated with it.
- If you create a new project, you have to assign the project permissions from the **Settings**  > **Project Permissions** > **Add New Project Permission** page.

Once you log in, from the Integration Cloud navigation bar, click **Settings**  > **Project Permissions** > **Add New Project Permission**. Select a project and then click the add icon  to add the project in the panel. Then assign the relevant permissions to the selected project. You can select another project and assign the permissions to the selected project. Click **Add**.



Note: If you associate the project permission profile to a user on the user profile page, the user can perform only the permitted tasks in each mapped project.

Example 1

A user is assigned to two project permission profiles A and B in the user profile. Project permission profile A has the Execute Integration permission in Project X but Project permission profile B does not have the Execute Integration permission for the same Project X. The user will still be able to execute the Integration.

Example 2

In this example, we will see how you will allow an existing user U1 to create, update, delete, and execute Integrations for the Project P1 but not for Project P2.

1. You must have the **Access Control** permission under **Access Profiles** > **Administrative Permissions**.
2. Create Project P1 and Project P2.
3. Create a new Project Permission profile PP1 under **Settings** > **Project Permissions** > **Add New Project Permission**.
4. On the **Add New Project Permission** page, add Project P1 in the mapped projects list. Assign the create, update, delete, and execute Integration permissions to the mapped Project P1.

5. Do not map Project P2.
6. Go to the **Basic** tab of user U1 and select *only* PP1.

So when U1 logs in, U1 will only be able to create, update, delete, and execute Integrations for the Project P1 but not for Project P2.

Single Sign-On

Note: This page is not applicable if you have created your account using the Software AG Cloud sign-up page.


Single sign-on is a process that allows users to access all authorized network resources without having to log in separately to each resource.

Security Assertion Markup Language 2.0 (SAML 2.0) is a standard for exchanging authentication and authorization data between security domains. SAML 2.0 is an XML-based standard that uses security tokens containing assertions to pass information about a principal (usually an end user), between a SAML authority, that is, an identity provider (IdP), and a SAML consumer, that is, a service provider. Using SAML, a service provider can contact an identity provider to authenticate users who are trying to access secure content.

Note: Currently, only SAML 2.0 is supported.

Integration Cloud supports single sign-on (SSO) that allows users to authenticate themselves against an Identity Provider (IdP) rather than obtaining and using a separate username and password. Under the SSO setup, Integration Cloud works as a Service Provider through SAML. You can put the IdP you already trust in charge of authentication, while your users can access Integration Cloud without another password to manage.

The following actions take place while logging into Integration Cloud using SAML 2.0:



Service Provider: Integration Cloud

Identity Provider (IdP): Microsoft Azure, Okta, Oracle Access Manager

1. User logs into a web application and clicks on the SAML SSO link to access Integration Cloud.
2. Integration Cloud generates a SAML authentication request and posts the request to the user's browser.
3. The browser sends the SAML request to the Identity Provider for authentication. The SAML request contains user information, Identity Provider URL, and the assertion response URL.
4. The Identity Provider decodes the SAML request, extracts the URL, authenticates the user, generates a SAML response, and posts the SAML response to the browser.
5. The browser sends the SAML response to Integration Cloud.
6. Integration Cloud checks if the Identity Provider authentication was successful, that is, verifies the SAML response, and redirects the user to the appropriate home page or the error message page.

Note: Integration Cloud SSO capability has been tested to work with Microsoft Azure Active Directory (Azure), Oracle Access Manager (OAM), and Okta as Identity Providers.

You can click **Edit** to configure SAML 2.0 settings for single sign-on or click **Export SAML 2.0 Metadata** if you want to export the Integration Cloud SAML metadata.

See [Configuring SAML Settings for Single Sign-On](#) on how to configure SAML settings for single sign-on.

Note: If you have already configured SAML based single sign-on (SSO), the **SSO Login** option appears in the login page. If you click the **SSO Login** option, Integration Cloud redirects you to the Identity Provider (IdP) login page. After you provide the IdP login credentials, you will be logged into Integration Cloud.

Note: You can access or edit the single sign-on configuration page only if you can edit the **Company Information**, that is, have the **Manage Company Capabilities** permission under **Settings**  > **Access Profiles** > **Administrative Permissions** > **Account Controls**.

Configuring SAML Settings for Single Sign-On

Note: This page is not applicable if you have created your account using the Software AG Cloud sign-up page.

The **Single Sign-On Configuration** screen allows you to configure SAML 2.0 settings for single sign-on (SSO). To prevent modifications to the SSO configurations, the SSO settings may not be enabled in your organization.

Note: You can access or edit the single sign-on configuration page only if you can edit the **Company Information**, that is, have the **Manage Company Capabilities** permission under **Settings**  > **Access Profiles** > **Administrative Permissions** > **Account Controls**.

Note: If you have configured SSO, the **SSO Login** option appears in the login page. You can click the **SSO Login** option to log in to Integration Cloud without providing your Username and Password.

To configure SAML 2.0 settings for single sign-on

1. From the Integration Cloud navigation bar, click **Settings**  > **Single Sign-On**.
2. Click **Edit**.
3. On the **Update Single Sign-On Configuration** screen, select **SAML 2.0** in the **Sign-On Using** field and make the necessary modifications. Required fields are marked with an asterisk on the screen.

Field	Description
Choose Single Sign-On Type	
Sign-On Using	<p>Select the sign-on type from the drop-down list. Default is None.</p> <p>Security Assertion Markup Language 2.0 (SAML 2.0) is an XML-based standard for exchanging authentication and authorization data between security domains. Integration Cloud (Service Provider) must enroll with an Identity Provider (IdP) and obtain an Identity Provider URL.</p>
Requestor Details	
Authentication Service URL	<p>This URL is the SAML SSO link and is used to trigger the SAML based single sign-on. Use this link to login to Integration Cloud using your Identity Provider.</p> <p>To login to API Gateway Cloud, add <code>done=apiGatewayUIHome</code> parameter to the Authentication Service URL.</p> <p>To login to API Portal Cloud, add <code>done=apiPortalUIHome</code> parameter to the Authentication Service URL.</p>
Assertion Consumer Service URL	<p>This is the URL which consumes the SAML response from the Identity Provider. You need to apply this URL in the relevant field in the Identity Provider SAML configuration page.</p> <p>For Oracle Access Manager (OAM), apply it in the Assertion Consumer Service URL field.</p> <p>For Microsoft Azure, apply it in the Reply URL field.</p> <p>For Okta, apply it in the Single sign on URL field.</p>
RelayState for Identity Provider initiated SSO	<p>RelayState is a parameter used by SAML protocol implementations to identify the specific resource at the resource provider, in an Identity Provider initiated single sign-on scenario. In an Identity Provider initiated single sign-on scenario, you must set the RelayState value in the Identity Provider. Test the Identity Provider initiated SSO only after configuring the RelayState.</p> <p>For Oracle Access Manager (OAM), apply the RelayState value as the Return URL in the Identity Provider initiated URL.</p>

Field	Description
	<p>For Microsoft Azure, send the RelayState value to Microsoft Azure AD to configure the RelayState for your application instance. See Microsoft Azure website for more information.</p> <p>For Okta, apply it in the Default RelayState field.</p>
Identity Provider Configuration	
SAML Request Issuer URL	<p>This is the Integration Cloud (Service Provider) URL used to access this tenant. This URL acts as the Service Provider ID.</p> <p>For Oracle Access Manager (OAM), apply it in the Provider ID field.</p> <p>For Microsoft Azure, apply it in the Identifier field.</p> <p>For Okta, apply it in the Audience URI (SP Entity ID) field.</p>
Identity Provider Details	<p>Specify how you want to define the Identity Provider details.</p> <p>Select Enter Manually if you want to manually enter the URL that uniquely identifies Integration Cloud in your SAML Identity Provider in the Issuer field.</p> <p>Select Load From Identity Provider Metadata and select the metadata file to upload the IdP details.</p>
Issuer	<p>A URL that uniquely identifies Integration Cloud in your SAML Identity Provider. Integration Cloud (Service Provider) must enroll with an Identity Provider and obtain an Issuer URL.</p> <p>If you have selected Enter Manually for Identity Provider Details, copy the URL provided by the IdP here after setting up Integration Cloud configuration in the IdP.</p> <p>If you have selected Load From Identity Provider Metadata for Identity Provider Details and uploaded the IdP file, the Issuer field will be automatically populated.</p> <p>For Microsoft Azure, copy the URL from the Issuer URL field.</p> <p>For Oracle Access Manager (OAM), copy the URL from the Provider Id field under Federation Settings.</p> <p>For Okta, copy the URL from the Identity Provider Issuer field.</p>

Field	Description
Identity Provider Certificate	<p>This is the authentication certificate (a valid x509 issuer certificate) issued by your Identity Provider and is required to sign and verify SAML messages.</p> <p>If you have selected Enter Manually for Identity Provider Details, select Browse and upload a file that contains the Identity Provider's certificate.</p> <p>If you have selected Load From Identity Provider Metadata for Identity Provider Details and uploaded the IdP file, the IdP certificate will be automatically uploaded.</p>
Identity Provider Login URL	<p>This is the URL used to log in to the Identity Provider.</p> <p>If you have selected Enter Manually for Identity Provider Details, type the URL that will be used to log in to the Identity Provider.</p> <p>If you have selected Load From Identity Provider Metadata for Identity Provider Details and uploaded the IdP file, the IdP login URL will be automatically populated.</p> <p>For Oracle Access Manager (OAM), the URL is <i>http://<oamserverhost name>:14100/oamfed/idp/samlv20</i>.</p> <p>For Microsoft Azure, copy the URL from the Single sign-on service URL field.</p> <p>For Okta, copy the URL from the Identity Provider Single Sign-On URL field.</p>
User ID Type	<p>Determines the type of identifier.</p> <p>Assertion contains user's Integration Cloud username - Select this option if your Identity Provider passes the username  > <i>User Profile</i> > Basic tab) in the SAML assertion to identify the user.</p> <p>Assertion contains the Federation ID from the User Object - The Federation ID acts as a user's authentication across multiple IT systems or organizations. A federated identity means linking a person's electronic identity and attributes stored across multiple distinct identity management systems. Select this option if your Identity Provider passes the Federation ID ( > <i>User Profile</i> > Basic tab), to identify the user. You can add the Federation ID ( > <i>User Profile</i> > Basic tab) to each user's profile after you have configured single sign-on.</p>

Field	Description
User ID Location	<p>Specifies an attribute tag that defines the location of the User ID. This is the location in the assertion where a user should be identified.</p> <p>Select Subject if the User ID is located in the <Subject> statement of the assertion.</p> <p>Select Attribute if the User ID is specified in an <AttributeValue>, located in the <Attribute> of the assertion. If you have selected Attribute, specify the attribute that contains the User ID in the Attribute for User ID field. If the User ID attribute is empty or does not match an existing user, then either login fails or a new user is created, depending on the Create Users setting.</p>
Attribute for User ID	<p>This field appears if you have selected Attribute in the User ID Location field. Specify the attribute that contains the User ID. If the User ID attribute is empty or does not match an existing user, then either login fails or a new user is created, depending on the Create Users setting.</p>
Create Users	<p>Select this option to create a new user when the User ID is not recognized. When selected, additional options appear where you can specify the attribute to use for the First Name, Last Name, Email, and Access Profile.</p> <p>Attribute for First Name - The name of the SAML attribute that designates the user's first name.</p> <p>Attribute for Last Name - The name of the SAML attribute that designates the user's last name.</p> <p>Attribute for Email - The name of the SAML attribute that designates the user's email address.</p> <p>Default Access Profile - This field is used to specify the default Access Profile for the created user.</p> <p>Attribute for Access Profile - The name of the SAML attribute that designates the user's access profile. The attribute must contain the ID of the Access Profile. You can get the ID of the Access Profile from the Access Profiles screen (Settings  > Access Profiles).</p>

Note: You must select Email Address as the NameID Format in the Identity Provider SSO Configuration screen.

Company Information

This screen displays your company information. Users who have the **Manage Company Capabilities** permission under **Settings**  > **Access Profiles** > **Administrative Permissions** > **Account Controls** can edit the company information.

See [“Updating Company Information” on page 83](#) for information on the fields.

Click **Edit** to update the company information.

Updating Company Information

You can view and update the company information and use them across all applications in the platform.

To update the Company Information

1. From the Integration Cloud navigation bar, go to **Settings**  > **Company Information**.
2. Click **Edit**.
3. On the **Basic** tab, complete the following fields. Required fields are marked with an asterisk on the screen.

Field	Description
Tenant ID	This is the unique ID assigned to your organization's tenancy on the platform. Note: This field cannot be edited and appears in view only mode under the Basic tab.
Sub Domain	This is the unique sub domain that you specified during registration. A sub domain is a domain that is part of a main domain. For example, suppose you are at ABC Company and you decide to use “abc” as your unique sub domain. With that setting, you will access your instance of the platform at https://abc.webmethodscloud.com. Note: This field cannot be edited and appears in view only mode under the Basic tab.
Company Name	The name of the company. This field accepts only alphanumeric, spaces, and hyphens (-). The company name is automatically populated from the Registration screen.

Field	Description
Street	The street address of the company.
City	The city where the company is located.
State/Province	The state or Province where the company is located. The state or province name is automatically populated from the Registration screen.
Postal/Zip Code	The postal or zip code for the company.
Country	The country where the company is located. The country name is automatically populated from the Registration screen.
System Notification Email Addresses	Enter an address or comma-separated email addresses to receive system notifications. Such notifications can occur, for example, when a connection to the system mailbox fails after repeated attempts. This field displays the information from the Registration screen but you can change that later using the Edit button.

4. On the **Advanced Information** tab, complete the following fields:

Field	Description
Time Zone	Choose your time zone from the drop down list.
Time Format	Choose a time format from the drop down list. You can choose a 12-hour clock with AM/PM or a 24-hour clock. hh:mm a - 12-hour clock - 3:30 AM, 3:30 PM HH:mm - 24-hour clock - 3:30, 15:30
Date Format	Choose a date format from the drop down list. mm is "Month", dd is "Day", yyyy is Year and the delimiters are:(/) slash or stroke(-) dash or hyphen(.) period, dot, or full stop.
Default Locale	This setting determines the language for the tenant. Note: Users within a tenant can set their preferred language from the Users > Locale tab. For example, if you set the value here as <code>English</code> and the user for this tenant sets the value as <code>Chinese</code> in the Locale

Field	Description
	field, then the user will see all the application labels in the Chinese language. For more information, see “Adding Users” on page 56 .
Last Modified	This field displays the date and time when the company information record was last updated. This field cannot be edited and appears in view only mode .

Password Policy

Note: This page is not applicable if you have created your account using the Software AG Cloud sign-up page. Password policies are defined in the Software AG Cloud User **Administration** page.

A Password Policy defines password requirements and login protections. Users who have the **Access Control** permission under **Settings**  **> Access Profiles > Administrative Permissions > User and Ownership Controls** can edit the Password Policy information.

You can view the password policies for the Integration Cloud instance in this screen. See [“Updating Password Policy Settings” on page 85](#) for information on the fields.

Click **Edit** to modify the password policy information.

Updating Password Policy Settings

Note: This page is not applicable if you have created your account using the Software AG Cloud sign-up page. Password policies have to be defined in the Software AG Cloud User **Administration** page.

You can set password policies for users on the **Update Password Policy** page.

To update the Password Policy

1. From the Integration Cloud navigation bar, click **Settings**  **> Password Policy**.
2. Click **Edit**.
3. On the **Update Password Policy** page, make the necessary modifications.

Field	Description
Minimum Length	Select the minimum number of characters in the password.

Field	Description
Required Character types	This option defines the level of security for passwords, which can be simple and allow any character combination, or very secure, requiring upper and lower case characters, as well as special characters.
Expires in	Select the number of days the password will remain valid before the user will be prompted to change it. By default, no user is exempt from the Password Policy. You can specify a user to be excluded from the password expiration policy by selecting <i>Never</i> .
Password Never Expires for	Select the users for whom the password will never expire. Only active users appear in the list. You can make an user account active by selecting the Settings  > Users > Update User > Basic tab > Active option.
New Password cannot match	The new password cannot match the number of previous passwords.
Minimum Age	Select the number of days that must pass before a user can change passwords.
Session Timeout	Select the length of time the session will remain active without any user activity. The session will end when it reaches the selected timeout. The user will need to log in again.
Account Lockout Threshold	Select the number of login attempts before the account is locked out. The login limit defines the number of failed attempts allowed before a user account is disabled or locked for a specified time. When a user attempts to login and fails (because of an incorrect password), each attempt counts against the login limit. When the login limit is achieved, the account is disabled or locked for a specified time, according to the parameters set in the <i>Account Lockout Duration</i> field. The login limit is defined by the <i>Password Policy</i> .
Account Lockout Duration	Select the length of time that an account is locked out.
Record Information	For audit purposes, the following information is displayed after you save the record:

Field	Description
	<i>Last Modified By <username> on {date} <time> Created by System.</i>

4. Click **Apply**.

Client Certificate

Secure Sockets Layer (SSL) is a means of securing communications over a network so that only the sender and receiver have access to the sensitive data.

In a *one-way* SSL connection, an anonymous client authenticates the credentials of a server in preparation for setting up a secure transaction. In most cases, the server knows nothing about the client's identity because verification of its credentials is not required. When desired, the client can be authenticated using basic authentication by providing a username and password. This type of authentication typifies connections where a browser establishes a connection to a server to perform a secure transaction, for example, viewing a savings account, or buying items with a credit card. The client must authenticate the server's credentials before initiating the transaction, but it is not necessary for the server to authenticate and keep a record of every possible client (browser). This type of connection is typically one where a partner application or resource needs to verify the authenticity of the server without itself needing to be authenticated.

Two-way SSL authentication refers to two parties authenticating each other by verifying the provided digital certificate so that both parties are assured of the others' identity. It refers to a client (web browser or client application) authenticating itself to a server and the server authenticating itself to the client by verifying the public key certificate or digital certificate issued by the Certificate Authorities (CAs).

Integration Cloud supports two-way SSL for inbound connections. The request for an SSL connection originates from a client. During the SSL handshake process, the entity acting as the SSL server responds to the request for a connection by presenting its SSL credentials (an X.509 certificate) to the requesting client. If those credentials are authenticated by the client, either:

- An SSL connection is established and information can be exchanged between the client and server.
- or -
- The next phase of the authentication process occurs, and the server requests the SSL credentials of the client. If the server verifies those credentials, that is, the client's *identity*, an SSL connection is established and information exchange takes place.

Note: When a client or partner application submits a request to Integration Cloud using HTTPS on port 8443, and a two-way SSL connection is established, the client acts as the SSL client and Integration Cloud acts as the SSL server.

The following table provides a high-level roadmap for configuring SSL.

Task	Activities	Notes
Create keys and certificates	<ul style="list-style-type: none"> ■ Generate a public key/private key pair. ■ Generate a certificate signing request (CSR) and send it to the certificate authority (CA) for signing. ■ Receive validated certificate from the CA. 	Two-way SSL connection requires a valid client certificate.
Upload client certificate or generate a certificate	Upload the CA signed client certificate for the user in the Client Certificate page or generate a private key and a new Integration Cloud signed client certificate.	Required for two-way SSL connections.
Connect to Integration Cloud using the client certificate.	Configure the REST client with the private key and certificate. Optionally you can also pass the basic authentication credentials.	Integration Cloud support two-way SSL on port 8443.

Users who have the **User Management** permission under **Settings**  > **Access Profiles** > **Administrative Permissions** > **User and Ownership Controls** can generate or edit any client certificate. Users who have the **Manage Personal Setup** permission under **Settings**  > **Access Profiles** > **Administrative Permissions** > **User and Ownership Controls** can generate or edit the user's own certificate.

See [“Adding Client Certificates” on page 88](#) for information on how to add client certificates.

Adding Client Certificates

Integration Cloud allows you to store client certificates and associate a certificate with a user account. You can add client certificates for users on the **Client Certificate** page. When a client presents one of these certificates, Integration Cloud logs in the client, as the user "mapped" to the certificate.

To add a client certificate

1. From the Integration Cloud navigation bar, click **Settings**  > **Client Certificate**.
2. In the **User** field, select a user. Only active users are listed in the **User** field.

3. In the **Upload New Certificate** field, click **Browse** to upload a new client certificate signed by a trusted certificate authority (CA). If a certificate is configured for a user, the **Certificate Details** panel displays the configured certificate. You can click **Download** to download the user certificate or click **Delete** to delete the user certificate. The downloaded file is named as <username>.crt.
4. In the **Generate Private Key and Certificate** field, click **Generate** if you want Integration Cloud to generate a private key and a new Integration Cloud-signed client certificate. Integration Cloud validates it against the issuer of the certificate. The generated certificate is named as <username>.txt which contains the private key and the client certificate.

Executing Integrations using Two-way SSL

Summary

Two-way SSL authentication, also referred to as client or mutual authentication or certificate-based authentication, refers to two parties authenticating each other by verifying the provided digital certificate, so that both the parties are assured of the other's Identity.

Two-way SSL authentication involves the following steps:

1. Client (Postman, SoapUI) requests access to protected resources of server (webMethods Integration Cloud).
2. Server presents its certificate to the client.
3. Client validates the server's certificate.
4. Client sends its certificate to the server.
5. Server verifies the client's certificate.
6. If successful, the server grants access to the protected resources requested by the client.

In this tutorial, we will create an integration in webMethods Integration Cloud, expose the integration over HTTP (exposing the integration over HTTP allows the integration to be executed from an outside environment), and then execute the integration using two-way SSL authentication by using a REST Client (Postman). You can also use the same technique for SOAP APIs, REST APIs, or any other exposed APIs.

Actors


- Integration developers who develop and expose the integrations over HTTPS in Integration Cloud.
- Integration executors who runs integrations.

Before you begin

- You must have the permissions to create and execute integrations in Integration Cloud under **Settings**  > **Access Profiles** > **Administrative Permissions** > **Functional Controls** > **Integrations**.


Basic Flow

1. Log in to Integration Cloud.
2. Create an Integration (testApp) in Integration Cloud.
3. On the Integrations page, click the integration link, and on the integration **Overview** page, select the **Enable Integration to be invoked over HTTP** option.



4. Click **Settings**  > **Client Certificate**.


To access RESTful APIs using two-way authentication, connect to Integration Cloud on port 8443, and provide a valid client certificate.
For Basic Authentication, pass the user credentials.
If you want to use two-way SSL with X.509 authentication, you need not pass the user credentials.



5. Select the **User**. You can either upload a certificate to the user if there are any available CA-signed certificates, or you can generate and assign a certificate to the user. Click **Browse** to upload a certificate if you want to use the user's own certificate or click **Generate** to generate and download the private and public key for the user.

After downloading the file, copy the private key to a file and name it as {privateKeyFileName}.key and the public key to a file and name it as {publicKeyFileName}.crt.

6. Open the Postman REST client and click **Settings** > **Certificates**. Then click **Add Certificate**.



7. The Add Certificate page appears. Now configure the certificate and private key in Postman.

SETTINGS

General Themes Shortcuts Data Add-ons Certificates Proxy Update About

Client Certificates > Add Certificate

Host :

CRT file X

KEY file X

PFX file

Passphrase

[Learn more about working with certificates at our Learning Center.](#)

- As shown in the above figure, specify the **Host** name and the port number as 8443. Specify the location of the key files, that is, the **CRT file** (certificate) and the **KEY file** (private key). Click **Add** to save the two-way SSL configuration.
- Open a new tab in Postman and add the request details you have obtained from Integration Cloud. The request details are available after you select the **Enable Integration to be invoked over HTTP** option.

Enable Integration to be invoked over HTTP [?](#)

https://[redacted]/integration/rest/external/integration/run/development/test12/testApp

[Hide Advanced Options](#)

Details

Sample usage

HTTP Method: POST

Sample JSON input:

```
{
  "num1": "2",
  "num2": "3"
}
```

URL: https://[redacted]/integration/rest/external/integration/run/development/test12/testApp

Parameters

Accept

Allowed value: application/json

Mandatory: No

Parameter Type: Header

Authorization

Allowed value: Basic Authorization

Mandatory: Yes

Parameter Type: Authorization Header

Content Type

Allowed value: application/json

Mandatory: Yes

Parameter Type: Header

10. To execute the Integration, configure a POST request in Postman as shown below and click **Send**. Change the port to 8443 of your service. URL is `https://mydomain.webmethodscloud.com:8443/<Your service URL>`.

POST ▼ https://mydomain.webmethodscloud.com:8443/integration/rest/external/integration/run/development/test12/testApp Send Save ▼

Params Authorization **Headers (2)** Body ● Pre-request Script Tests Settings Cookies Code

▼ Headers (2)

KEY	VALUE	DESCRIPTION	...	Bulk Edit	Presets
<input checked="" type="checkbox"/> Accept	application/json				
<input checked="" type="checkbox"/> Content-Type	application/json				
Key	Value	Description			


Response

Exceptions

The following errors may occur in the REST Client when there is a certificate mismatch between what is specified in Integration Cloud with what is sent from the REST Client.

- The server could not send a response.
- Self-signed SSL certificates are blocked.

Visual Model




OAuth 2.0

About OAuth 2.0

Note: This page is not applicable if you have created your account using the Software AG Cloud sign-up page.

The OAuth 2.0 Authorization Framework facilitates the sharing of private resources (data or services) with a third-party client application (*client*). In an OAuth session, private resources are stored on a *resource server* and the owner of the resources, or *resource owner*, grants the client application permission to access them. The resource owner is typically a person; however, in some cases it could be an application. When a resource owner grants permission, the OAuth *authorization server* issues an *access token* to the client application. When the client application passes the access token to the resource server, the resource server communicates with the authorization server to validate the token and, if valid, provides access to the resources.

The following example illustrates the roles involved with an OAuth session. In the example, Bob is the resource owner who wants to access and print his photos stored on the PhotoStorage website (the resource server) using the PhotoPrint service (the client application). PhotoPrint supplies Bob with an application that runs on his device (phone or laptop). Bob uses that application to initiate the process. PhotoPrint sends a request to the PhotoStorage authorization server. The authorization server requests authorization from Bob and issues a token to PhotoPrint. PhotoPrint can then access Bob's photos on PhotoStorage.



Integration Cloud services can be accessed through REST APIs from any REST client. In OAuth 2.0, the client obtains an access token issued by an authorization server on approval of the resource owner. The client uses the access token to access the protected resources.

Note: Integration Cloud acts both as a Resource server and as an Authorization server.

An in-depth description of OAuth is beyond the scope of this guide but is available elsewhere. For information about the OAuth protocol, see the OAuth 2.0 Authorization Framework.

Configuring OAuth 2.0

Before you can invoke services using OAuth 2.0 tokens, you must define clients, scopes, associate scopes to clients, and generate OAuth 2.0 tokens. The following table describes how to configure OAuth 2.0.

Steps	Description
"Define Clients" on page 96	Define the clients that are authorized to invoke services in Integration Cloud. Specify the client name, version number of the client, client type, redirection URLs, allowed grants, expiration interval, and the refresh count. See

Steps	Description
	“Registering Clients” on page 96 for more information.
“Define Scopes” on page 100	A scope defines the services the client can access on behalf of the resource owner. A scope consists of a name and one or more services. If access is granted for a scope, then access is granted for all the services in that scope.
“Associate scopes to a client” on page 96	Associate defined scopes with the registered clients. When you associate scopes, you authorize the scopes that each client can access.
“Generate Tokens” on page 101	Generate tokens (Access Token and Refresh Token) by using a REST Client. See “Generating Tokens” on page 101 for more information. Integration Cloud supports the Authorization Code Grant, Implicit Grant, Client Credentials Grant, and the Resource Owner Password Credentials Grant to generate the access tokens. Clients use the tokens to execute REST URLs for running the Integrations. After you generate the tokens, the tokens are available in the Token Management page in Integration Cloud.

Registering Clients

Before a client can request access to a protected resource, it should register with Integration Cloud. When you register a client, you identify the client as a confidential client or a public client, select the grant types the client can use, and specify the token expiration and refresh information. The **Client Registration** page lists the clients registered with Integration Cloud.

See [“About OAuth 2.0” on page 94](#) for information on the high-level steps for configuring OAuth 2.0.

Note: When you delete a client, Integration Cloud also deletes all the access tokens and refresh tokens for the client. When you deactivate a client by clearing the **Active** option while updating the client, all the access tokens and refresh tokens for the client become invalid. You can activate a deactivated client.

Note: Users who have the **Access Control** permission under **Settings**  **> Access Profiles > Administrative Permissions > User and Ownership Controls** can create, edit, and delete clients.

To add a Client

1. From the Integration Cloud navigation bar, go to **Settings**  > **OAuth 2.0** > **Client Registration** > **Add New Client**.
2. On the **Add New Client** page, complete the following fields. Required fields are marked with an asterisk on the screen.

Field	Description
Name	Type the name of the client. You cannot create clients with the same Name and Version combination. You cannot modify the client name after the client is saved. Client names are not case-sensitive.
Description	Type a description of the client.
Client ID	The Client ID field appears only when you update a client. This is a client identifier issued to the client to identify itself to the authorization server, and is used while generating tokens.
Client Secret	The Client Secret field appears only when you update a client. This is a secret matching to the client identifier and is used while generating tokens. It will not be generated if the Client Type is Public .
Authorization Endpoint	View the authorization URL that has to be provided while generating tokens. See the <i>Generating Tokens</i> section for more information.
Token Endpoint	View the Access Token URL that has to be provided while generating tokens. See the <i>Generating Tokens</i> section for more information.
Refresh Token Endpoint	View the Refresh Token URL that has to be provided while refreshing Access Tokens. See the <i>Refreshing Access Tokens Using Refresh Tokens</i> section for more information.

Field	Description
Version	Type the version number of the client. You cannot create clients with the same Name and Version combination.
Type	<p>Select the type of the client according to its ability to communicate with Integration Cloud.</p> <p>Confidential - Select Confidential when the OAuth session uses the following grants:</p> <ul style="list-style-type: none">■ Authorization Code Grant■ Client Credentials Grant■ Resource Owner Password Credentials Grant <p>This client is capable of maintaining secure client authentications. When you select client type as Confidential, Integration Cloud generates a client secret. This client secret will be required by Integration Cloud when the client makes requests to the OAuth services.</p> <p>Public - Select Public when the OAuth session uses the Implicit Grant type. This client is not capable of maintaining secure client authentications.</p>
Redirection URLs	<p>Specify the URLs that Integration Cloud will use to redirect the resource owner's browser during the grant process.</p> <p>You can add more than one redirection URL.</p> <p>If you select the Authorization Code Grant or the Implicit Grant types, you must enter at least one Redirection URL for the client.</p>
Allowed Grants	Select the type of grant flow required by the client.
Expiration Interval	Select the length of time (in seconds) that the access token is valid.

Field	Description
	<p>Never Expires - Indicates that the access token never expires. The Token Management page displays Lifetime for that token.</p> <p>Expires In - Specify the number of seconds the access token is valid.</p>
Refresh Count	<p>Select the number of times the access token can be refreshed.</p> <p>Unlimited - Refresh the access token an unlimited number of times using the refresh token. The Token Management page displays Unlimited for that refresh token.</p> <p>Limited - Specify the number of times to refresh the access token. The Token Management page will display the Refresh Count for that refresh token. If you specify 0 or leave the field empty, a refresh token will not be issued.</p> <div data-bbox="748 1024 1352 1125" style="background-color: #f0f0f0; padding: 5px;"> <p>Note: Tokens can be refreshed only when using the Authorization Code Grant flow.</p> </div>
Active	<p>This option appears only when you update a client. Clear this option to deactivate the client. When you deactivate a client, all the access tokens and refresh tokens for the client become invalid.</p>

3. Click **Add** to add the client in the **Client Registration** page.
4. On the **Client Registration** page, if you want to associate scopes with a client, select a client and then click **Associate Scopes**. The **Associate Scopes with <ClientName(Version)>** page appears. The **Associate Scopes with <ClientName(Version)>** page displays the already associated scopes with the selected client.
 - a. On the **Associate Scopes with <ClientName(Version)>** page, to associate existing scopes with the client, select **Associate Existing Scopes**.
 - b. On the **Select Scopes to Associate** dialog box, select the existing scopes to associate with the client and then select **Associate Scopes**. The newly associated scopes will appear in the **Associate Scopes with <ClientName(Version)>** page.
 - c. To create a new scope and associate it with the selected client, select **Associate New Scope**. Create the new scope as described in the [“Managing Scopes” on page 100](#) section. The new scope will be associated with the selected client.

- d. To disassociate a scope from a client, select the scope on the **Associate Scopes with <ClientName(Version)>** page and then click **Disassociate**.

Managing Scopes

A scope defines the services the client can access on behalf of the resource owner. A scope consists of a name and one or more services. If access is granted for a scope, then access is granted for all the services in that scope. When a request is made, Integration Cloud verifies that the scope is defined for a client. The client is allowed to access only the service URLs that are specified for the scope. If the requested scope is not defined, Integration Cloud returns an error indicating that the scope is invalid.

Note: You cannot delete a scope that is used by a client. Also, a scope cannot be deleted if it is associated with an existing token.

Note: Users who have the **Access Control** permission under **Settings**  **> Access Profiles > Administrative Permissions > User and Ownership Controls** can create, edit, and delete scopes.

See [“About OAuth 2.0” on page 94](#) for information on the high-level steps for configuring OAuth 2.0.

To add a scope

1. From the Integration Cloud navigation bar, go to **Settings**  **> OAuth 2.0 > Scope Management > Add New Scope**.
2. On the **Add New Scope** page, complete the following fields. Required fields are marked with an asterisk on the screen.

Field	Description
Name	Type a unique name for the scope. You cannot modify the scope name after a scope is saved. Scope names are not case-sensitive.
Description	Type a description of the scope.
Services	Specify the list of services that the client can access on behalf of the resource owner for executing the integrations. Click Select Services and in the Services dialog box, select the exposed Integrations or REST Resources that you want to add as Service URLs.

Note: Exposed Integrations and REST APIs available *only* in the [“Default project”](#)

Field	Description
Service URLs	<p data-bbox="821 306 1300 373">on page 50 are currently available for selection in the Services dialog box.</p> <p data-bbox="764 407 1341 716">Note:Service URL is a relative URL and it must start with <i>/integration</i>. For example, if the absolute URL is <code>https://<sub-domain>.webmethodscloud.com/integration/rest/external/integration/run/development/restintegration</code>, then the Service URL is <code>/integration/rest/external/integration/run/development/restintegration</code>.</p> <p data-bbox="748 758 1308 856">This field appears once you have added the exposed Integrations and REST Resources and shows the selected services.</p>

3. See the “[Registering Clients](#)” on page 96 section on how to associate scopes with a client.

Generating Tokens

You can generate tokens (Access Token and Refresh Token) by using a REST Client. Integration Cloud supports the Authorization Code Grant, Implicit Grant, Client Credentials Grant, and Resource Owner Password Credentials Grant to generate the access tokens. Clients use the access tokens to invoke REST URLs for running the Integrations.

See “[About OAuth 2.0](#)” on page 94 for information on the high-level steps for configuring OAuth 2.0.

The following example shows how to generate tokens using Postman

1. Add the Postman extension to your Google Chrome web browser.
2. Open the Postman application.
3. On the Postman **Authorization** page, select the **Type** as **OAuth 2.0**, and then click **Get New Access Token**. The **Get New Access Token** page appears.

GET ▾ Enter request URL

Authorization Headers Body Pre-request Script Tests

Type OAuth 2.0 ▾

Existing Tokens [Get New Access Token](#) Token Details

Get a new access token to add it to this list. Select a token from the list to view details

4. On the **Get New Access Token** page, complete the following fields to request a new access token.

GET NEW ACCESS TOKEN ✕

Request a new access token to add it to your list of tokens
On clicking Request Token, you will be redirected to the Auth URL where you can enter the user's credentials and request for a token

Callback URL `https://www.getpostman.com/oauth2/callback`
Set this as the callback URL in your app settings page.

Token Name

Auth URL

Access Token URL

Client ID

Client Secret

Scope (Optional)

Grant Type ▾

Request access token locally

[Cancel](#) [Request Token](#)

Field	Description
Callback URL	Specify the redirection URL added during client registration.
Token Name	Provide a token name.
Auth URL	Provide the Authorization Endpoint URL available on the Client page in the following format: https://abc.webmethodscloud.com/integration/rest/oAuth/authorize
Access Token URL	Provide the Access Token Endpoint URL available on the Client page in the following format: https://abc.webmethodscloud.com/integration/rest/oAuth/getToken
Client ID	Specify the client ID available on the Client page.
Client Secret	Specify the client secret available on the Client page.
Scope (Optional)	Specify the scope associated with the client.
Grant Type	Select Authorization Code or Implicit .

5. Click **Request Token**.

Integration Cloud login page appears.

6. Login to Integration Cloud with your credentials.

An approval page appears. The approval page is an HTML page Integration Cloud sends to the resource owner, after a client submits a request for access to its private resources. The resource owner uses the page to accept or deny the request.

7. Select the scopes you want to grant access and then click **Approve**.

On approval, an access token will be generated. A refresh token may also be generated depending on the **Refresh Count** configured for your client, and also if your grant type is **Authorization Code Grant**.

Refreshing Access Tokens Using Refresh Tokens

You can refresh Access Tokens using Refresh Tokens.

To refresh access tokens using Postman

1. Add the Postman extension to your Google Chrome web browser.
2. Open the Postman application.
3. Make a HTTP POST call with the following details:

Field	Description
Post URL	Provide the following URL: https://abc.webmethodscloud.com/integration/rest/oauth/getToken
Query Parameters	Provide the following query parameters: <i>grant_type</i> - The Grant Type value will be <i>refresh_token</i> <i>refresh_token</i> is the refresh token obtained while generating the tokens. Example of an HTTP POST request for refreshing an access token: https://abc.webmethodscloud.com/integration/rest/oauth/getToken?grant_type=refresh_token&refresh_token=<refresh_token_id>

Note: In Postman, select **Basic Auth** as the **Authorization** type and specify Client ID and Client Secret as the **Username** and **Password** while refreshing the token.

4. An access token will be generated which can be used to invoke the service URLs. The Refresh Count value will decrease by 1.

Managing Tokens

You can use this page to delete the *active tokens* issued by Integration Cloud. Client applications use these tokens to access the resources on Integration Cloud. When you delete the tokens, the client application can no longer access the resources owned by the resource owners. See the [“Generating Tokens” on page 101](#) section on how to generate tokens (Access Token and Refresh Token) by using a REST Client. See [“About](#)

[OAuth 2.0](#) on page 94 for information on the high-level steps for configuring OAuth 2.0.

Note: Users who have the **Access Control** permission under **Settings**  > **Access Profiles** > **Administrative Permissions** > **User and Ownership Controls** can delete tokens.

For expired Access Tokens, the **Expiry Time** displays **Expired**. If the Refresh Count is also 0, then the row in the Token Management page is removed.

To delete a token

1. From the Integration Cloud navigation bar, go to **Settings**  > **OAuth 2.0** > **Token Management**.
2. Select a token and click **Delete**.

When you delete a token from the list of active tokens, Integration Cloud deletes both the access token and the refresh token. To prevent a client from accessing resources, you can delete the client.

Running Services Using OAuth 2.0

To invoke service URLs using Postman

1. Add the Postman extension to your Google Chrome web browser.
2. Open the Postman application.
3. Type the **Request URL** and change the **HTTP method** to **POST**.



4. On the **Headers** tab, add *Authorization* as the **Key** and *Bearer <token ID>* as the **Value**.
5. Click **Send** to run the Integration.

Audit Log

Audit Log allows you to access logs related to additions, deletions, updates, export, schedule, skip, login, logout, password changes, record access attempts, access violations, deployments, restart Integration executions, resume Integration executions, and so on for a user.

To view the **Audit Log**, from the Integration Cloud navigation bar, click **Settings > Audit Log**.

Note: The Audit Log page can be viewed only by administrators and users who have the **Manage Audit Log** permission under **Settings  > Access Profiles > Administrative Permissions > Data Management Controls**.

By default, the **Audit Log** page displays the current day's log entries, with the most recent entries listed on top. You can sort the log to view the latest log entries. You can also search the **Audit Log** for **User**, **Type**, or **Operation**.

Activity Date refers to the date and time when the event occurred. **User** refers to the name of the logged in user when the event occurred. **Type** refers to the type of log entry, for example, User, Login/Logout, Reference Data, Stage, Account, Application, Integration, License Agreement, Password Policy, Access Profile, Company, and so on. **Operation** refers to the action performed, for example, Export, Execute, Terminate, Add, Delete, Update, Login, Logout, and so on. **Description** refers to a summary of the action performed.

Click **Modify Retention Period** and specify the number of days to retain the Audit Log entries. Logs whose age exceeds the specified retention period are deleted.

Click **Download Audit Log** if you want to download and export log entries for a specified period. You can download Audit logs only up to 30 days.

5 Applications

■ Overview	108
■ Predefined Applications	109
■ REST Applications	300
■ On-Premises Applications	320
■ SOAP Applications	325
■ Flat File Applications	334

Overview

Integration Cloud allows you to create and govern Integrations between Software as a Service (SaaS) or on-premises applications. A set of predefined and configurable Applications are provided, for example, Salesforce, StrikeIron, ServiceNow, and so on. Applications allow you to connect to the particular SaaS providers.

You create SOAP, REST, Flat File, FTP/FTPS, SFTP, and SMTP Applications from this page. To create a REST Application, click **Projects > <Select a Project> > Applications > REST Applications > Add New Application**. To create a SOAP Application, click **Projects > <Select a Project> > Applications > SOAP Applications > Add New Application**. To create a Flat File Application, click **Projects > <Select a Project> > Applications > Flat File Applications > Add New Application**. FTP/FTPS, SFTP, and SMTP Applications are available under Predefined Applications that allow Integration Cloud to connect to FTP/FTPS, SFTP, and SMTP servers.

On-Premises Applications loaded from on-premises systems are also listed in the **Applications > On-Premises Applications** page but you will not be able to create Accounts or Operations for on-premises Applications. Those can be uploaded only from webMethods Integration Server. Further, when you upload services as part of an Application from on-premises webMethods Integration Server to webMethods Integration Cloud, the comments field of the service is uploaded and displayed in the webMethods Integration Cloud Application. This field will be displayed if present and cannot be edited. See the *Configuring On-Premise Integration Servers for webMethods Cloud* document for more information.

From the **Application category** page, you can create Accounts and Operations for an Application and Integrations between different SaaS applications. For an Application, click **Accounts**, **Operations**, or **Integrations** if you want to create or edit them for that Application. For REST Applications, the **Documents Types** link appears and allows you to create new Document Types. Document Types created for a REST Application appear only in the **Document Types** panel for the selected REST Application.

If you have the required access privileges, you can upgrade Application assets (Accounts, Operations, and the associated Integrations) from a lower version to a higher version by clicking the **Upgrade** button.

To use an Application, you are required to agree to the summary of terms. Click **I agree** to use the Application. Click **I do not agree** if you disagree with the summary of terms and do not want to use the Application. Click **Cancel** to go back to the **Applications** page.

Note: Users who have the required access privileges under **Settings  > Access Profiles > Administrative Permissions > Functional Controls** can create, update, administer, execute, deploy, or delete the Accounts, Operations, Integrations, Stages, Advanced Security, Document Types, and Reference Data information.

Predefined Applications

A set of predefined and configurable Applications are provided, for example, Salesforce, StrikeIron, ServiceNow, and so on. These Applications allow you to connect to the particular SaaS providers.

Note: It is recommended to use secured protocols such as HTTPS and FTPS for securing the data transmitted over the network.

Alfabet

Integration Cloud connects to Alfabet using the Interface for RESTful Web Services and supports working with the various object types as defined in Alfabet. You can use it to query, retrieve, create, update, and delete objects of any type, and also manage relations between the objects.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. This is the native provider endpoint target for the Account configuration. The URL depends on where the required instance of Alfabet is installed. It is possible to either include or omit the endpoint suffix <code>"/Alfabet/api/vXX"</code> in the URL. For example, both these options are equivalent: <ul style="list-style-type: none"> ■ <code>https://myalfabet.com</code> ■ <code>https://myalfabet.com/Alfabet/api/v1</code>
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent

Field	Description
	successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Authorization Token	The Alfabet Authorization Token as defined in the <code>web.config</code> file of the Alfabet Web Application on the server side, under the <code><alfaSection></code> element. <p>Note: See the <i>Authorization</i> chapter in the Alfabet Interface for RESTful Web Services reference manual for required configurations in the server side for Alfabet and for details about the different authorization modes.</p>
Use Chunking	Enable this option if you want to send or receive a large binary stream with a chunk size of 8192 bytes. This is applicable only if the back end supports HTTP/1.1 chunking.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host

Field	Description
	name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Apache Solr Search

Solr is an open source enterprise search platform built on Apache Lucene. Solr is a standalone enterprise search server with a REST-like API. You can place documents in it (called "indexing") using JSON, XML, CSV, or binary over HTTP. You can query it using HTTP GET and receive JSON, XML, CSV, or binary results. Integration Cloud connects to Apache Solr using the REST API Version 6.1 and allows you to execute search operations over the indexed data.

Field	Description
Server URL	<p>Provide the login endpoint to initiate communication with the SaaS provider. For example, the end point URL would be of the format: https://<hostName>.</p> <p>Replace <hostName> with your actual back end system server URL hosting Apache Solr as the search engine.</p>
Response Timeout	<p>The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.</p>
Retry Count on Response Failure	<p>The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.</p>
Retry on Response Failure	<p>Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.</p>
Username	<p>Username received from the back end system hosting Apache Solr as the search engine.</p>
Password	<p>This is the password received from the back end system hosting Apache Solr as the search engine.</p>

Field	Description
Authorization Type	Apache Solr REST APIs use Basic Authentication. The Username and Password is passed when you invoke any of the REST API endpoints. This is the type of HTTP authorization scheme to use for the connection. If you select none , no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password, but do not specify a value for the Authorization Type, the user credentials are not inserted into an Authorization header. If you enter the username and password, then set the authorization type as basic . Basic refers to HTTP Basic Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.

Field	Description
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Applicability Statement 2 (AS2)

Applicability Statement 2 (AS2) is a communication protocol developed by the Internet Engineering Task Force (IETF) for the exchange of business-to-business (B2B) transactions over the Internet securely. The AS2 application uses the HTTP transport protocol along with Multipurpose Internet Mail Extensions (MIME). The AS2 application governs the means of connection and exchange of data securely and reliably. Besides the advanced security features, the AS2 application offers the following additional benefits:

- Privacy
- Authentication
- Nonrepudiation of origin and receipt of the message
- Data integrity

The AS2 application provides a medium to exchange business data with partners by configuring an account in Integration Cloud. The application supports the AS2 protocol versions 1.1 and 1.2.

Field	Description
Recipient Endpoint	The endpoint URL of the recipient.
Authorization Type	<p>The type of HTTP authorization scheme to use for the connection. You can choose one of the following options:</p> <ul style="list-style-type: none"> ■ none: No additional authorization scheme will be executed at run time. For example, when you specify a user name and password, but do not specify a value for the authorization type, the user credentials are not inserted into an authorization header. ■ basic: When the application requires or supports HTTP basic authentication for user name and password.

Field	Description
From	The AS2 ID of the sender.
To	The AS2 ID of the recipient.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration from the list. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. Select Add New Truststore to add a new trust store from this list.
Keystore Alias	Select the alias for the Integration Cloud keystore configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. Select Add New Keystore to add a new keystore from this list.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both, Keystore Alias and Client Key Alias fields.

Field	Description
Hostname verifier	Select a hostname verifier implementation for guards against man-in-the-middle (MITM) attacks from the list. The default is org.apache.http.conn.ssl.DefaultHostnameVerifier . This enables hostname verification. Select org.apache.http.conn.ssl.NoopHostnameVerifier from the list to disable hostname verification.
Username	The name of the user account that the AS2 connection will use to connect to the AS2 provider.
Password	The password for the user name provided in the Username field.
Compression	Select this option to compress an outbound AS2 message.
Sign Message	Select this option to sign an outbound AS2 message.
Signing Algorithm	The signing algorithm to use for an outbound AS2 message. The available options are: <ul style="list-style-type: none">■ MD5■ SHA-1■ SHA-256■ SHA-384■ SHA-512
Signing Keystore and Key Aliases	The keystore aliases and the key aliases in the keystore to use for signing an outbound AS2 message.
Receive Signed Message	Select this option to receive a signed inbound AS2 message. If you select this option and the incoming AS2 message is not signed, then an <code>Insufficient message security</code> error is encountered and shared with the sender if MDN is requested by the sender.
Signature Verification Certificate	The certificate to use for verifying an inbound signed AS2 message.

Field	Description
Encrypt Message	Select this option to encrypt an outbound AS2 message.
Encryption Algorithm	<p>The encryption algorithm to use for an outbound AS2 message. The available options are:</p> <ul style="list-style-type: none">■ RC2 40■ RC2 64■ RC2 128■ DES■ TripleDES■ AES 128■ AES 192■ AES 256
Encryption Certificate	The certificate to use for encrypting an outbound AS2 message.
Receive Encrypted Message	Select this option to receive an encrypted inbound AS2 message. If you select this option and the incoming AS2 message is not encrypted, then an <code>Insufficient message security</code> error is encountered and shared with the sender if MDN is requested by the sender.
Decryption Keystore and Key Aliases	The keystore aliases the key aliases in the keystore to use for decrypting an inbound AS2 message.
Request MDN	<p>Whether you want the recipient to return an MDN to the sender.</p> <p>You can select one of the following options:</p> <ul style="list-style-type: none">■ None: The recipient of the AS2 message does not return an MDN to the sender.■ Synchronous: The recipient of the AS2 message returns an MDN to the sender through the same HTTP connection used to send the original AS2 message.■ Asynchronous: The recipient of the AS2 message returns an MDN to the sender through a different

Field	Description
	HTTP connection instead of the one used to send the original AS2 message.
Request Signed MDN	<p>Select this option if you want the recipient to sign an AS2 MDN.</p> <p>Ensure that you also select an option in the Request MDN field if you want the recipient to sign and return an AS2 MDN.</p>
Asynchronous MDN Endpoint	Type your endpoint URL that accepts an inbound AS2 MDN if you selected the Asynchronous option for Request MDN .
AS2 Version	Select the AS2 protocol version to use from the list.
Enable SNI	<p>Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.</p>
SNI Server Name	<p>If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.</p>

AS2 Predefined Operations

The following predefined Applicability Statement 2 (AS2) operations are available:

receive

Receives an AS2 message from a recipient.

You can perform the following configurations in the AS2 application using the receive service.

- [“Configuring the Auto Detect Option” on page 123](#)
- [“Creating an Endpoint URL” on page 123](#)

Input Parameters

<i>contentStream</i>	Object Receives an AS2 message of content type other than <code>application/xml</code> .
<i>node</i>	Object Optional. Receives an AS2 message of content type <code>application/xml</code> only.

Output Parameters

<i>status</i>	String Status of an inbound message.
<i>statusMessage</i>	String Processing status of an inbound message.
<i>request</i>	Document Receives the raw stream, extracted payload, and attachments of an inbound message.
<i>stream</i>	Object Raw output stream received by an application.
<i>headers</i>	Document AS2 message headers.
<i>AS2-To</i>	String AS2 ID of the recipient.
<i>AS2-From</i>	String AS2 ID of the sender.
<i>Message-ID</i>	String Message ID of the inbound message.
<i>AS2-Version</i>	String AS2 protocol version used for the inbound message.
<i>Content-Type</i>	String MIME content type of the inbound message.
<i>EDIINT-Features</i>	String Optional features supported by the application.

	<i>Receipt-Delivery-Option</i>	String Optional. Sender's asynchronous MDN endpoint URL.
	<i>Disposition-Notification-To</i>	String Optional. Acknowledgment request for the inbound message.
	<i>Disposition-Notification-Options</i>	String Optional. Acknowledgment request to be signed for the inbound message.
<i>payload</i>		Document Extracted payload that you receive.
	<i>stream</i>	Object Extracted payload stream.
	<i>contentType</i>	String Content type assigned to the payload.
	<i>headers</i>	Document Headers assigned to the payload.
<i>attachments</i>		Document Array Optional. Attachments you receive with an inbound message, if any.
	<i>stream</i>	Object Output stream of the attachment.
	<i>contentType</i>	String Content type assigned to the attachment.
	<i>headers</i>	Document Headers assigned to the attachment.
<i>response</i>		Document Sent MDN or received asynchronous MDN response.
	<i>status</i>	String Status of the sent or received MDN.
	<i>statusMessage</i>	String Status message of the sent or received MDN.
	<i>receipt</i>	Document Optional. Sent or received MDN.

<i>stream</i>	Object Object stream of the sent or received MDN.
<i>headers</i>	Document Headers of the sent or received MDN.
<i>AS2-To</i>	String AS2 ID of the recipient.
<i>AS2-From</i>	String AS2 ID of the sender.
<i>Message-ID</i>	String Message ID of the inbound or outbound MDN.
<i>AS2-Version</i>	String AS2 protocol version used for the inbound or outbound MDN.
<i>Content-Type</i>	String MIME content type of the inbound or outbound message.

send

Sends an AS2 message to a recipient's defined endpoint.

Input Parameters

data **Document** Payload you want to send.

<i>stream</i>	Object java.io.InputStream object you want map from EDI or XML data.
<i>contentType</i>	<p>String Content type to assign to an outbound message. The following options are available by default:</p> <ul style="list-style-type: none"> ■ application/edi-x12 ■ application/edifact ■ application/xml <p>You can also type a custom value.</p>
<i>otherHeaders</i>	Document Optional. <i>key</i> and <i>value</i> strings of the header for an outbound message.
<i>attachments</i>	Document Array Optional. Attachments for a message, if any.
<i>stream</i>	Object java.io.InputStream object you want add to the attachment.
<i>contentType</i>	String Content type of the attachment. For example, <i>application/zip</i> if the attachment is a <i>.zip</i> file.
<i>otherHeaders</i>	Document Optional. <i>key</i> and <i>value</i> strings of the header you want to add to the attachment.
<i>customHeaders</i>	Document Optional. Custom headers you want to include in an AS2 message.
<i>key</i>	String Key for the custom header.
<i>value</i>	String Value for the customer header.

Output Parameters

<i>status</i>	String Status of an outbound message.
<i>statusMessage</i>	String Processing status of an outbound message.
<i>request</i>	Document AS2 message sent to a recipient.

<i>stream</i>	Object AS2 message stream.
<i>headers</i>	Document Optional. AS2 message headers.
<i>AS2-To</i>	String AS2 ID of the recipient.
<i>AS2-From</i>	String AS2 ID of the sender.
<i>Message-ID</i>	String Message ID of the outbound message.
<i>AS2-Version</i>	String AS2 protocol version used for the outbound message.
<i>Content-Type</i>	String MIME content type of the outbound message.
<i>EDIINT-Features</i>	String Optional features supported by the application.
<i>Receipt-Delivery-Option</i>	String Optional. Recipient's asynchronous MDN endpoint URL.
<i>Disposition-Notification-To</i>	String Optional. Acknowledgment request for the outbound message.
<i>Disposition-Notification-Options</i>	String Optional. Acknowledgment request to be signed for the outbound message.
<i>response</i>	Document Received MDN response.
<i>status</i>	String Status of the received MDN.
<i>statusMessage</i>	String Status message of the received MDN.
<i>receipt</i>	Document Optional. Received MDN.
<i>stream</i>	Object Object stream of the received MDN.
<i>headers</i>	Document Optional. Headers of the received MDN.

<i>AS2-To</i>	String AS2 ID of the recipient.
<i>AS2-From</i>	String AS2 ID of the sender.
<i>Message-ID</i>	String Message ID of the inbound MDN.
<i>AS2-Version</i>	String AS2 protocol version used for the inbound MDN.
<i>Content-Type</i>	String MIME content type of the inbound message.

Configuring the Auto Detect Option

You can select the **Auto Detect** option for the AS2 application to automatically identify an account based on the **AS2-From** and **AS2-To** headers of an inbound message.

This option enables the AS2 application to compare an account configured with **From** and **To** fields with the **AS2-From** and **AS2-To** headers of an inbound message and vice versa. In addition, specifying this option allows the use of an individual endpoint URL with multiple partners.

Note: **Auto Detect** option is supported only for the **receive** operation.

Important: Configuring multiple accounts with identical values for the **From** and **To** fields might generate unpredictable results. This happens when the application uses the account that matches the first **AS2-From** and **AS2-To** headers of an inbound message. Therefore, if you have multiple accounts configured with identical values for the **From** and **To** fields, then do not select the **Auto Detect** option.

Creating an Endpoint URL

A sender requires a recipient's endpoint URL to transfer AS2 messages. You must create an endpoint URL and share it with your partner to send AS2 messages to the endpoint URL.

To create an endpoint URL

1. Create an orchestrated integration. For instructions, see [“Orchestrated Integrations” on page 380](#). Ensure that you specify a signature with *contentStream* and *node* as

input parameters of type **Object**. For instructions, see [“Pipeline and Signatures” on page 393](#). Ensure you specify a name for the integration.

Alternatively, you can define a Document Type as a signature with *contentStream* and *node* as input parameters of type **Object**. For instructions, see [“Creating Document Types from Scratch” on page 591](#).

2. Configure the AS2 application with the **receive** operation to work with a new or existing account, or select the **Auto Detect** option for the application. For information about accounts and configuring an account using the **Auto Detect** option, see [“Adding or Editing Accounts” on page 360](#) and [“Configuring the Auto Detect Option” on page 123](#) respectively.
3. Map the *contentStream* and *node* parameters of the Pipeline Input signature defined in step 1 with the AS2 application's *receiveInput* parameter. For more information, see [“Pipeline and Signatures” on page 393](#).
4. Select the **Enable Integration to be invoked over HTTP** option for the integration. For more information, see [“Integration Details” on page 400](#).

An endpoint URL for this integration is generated. Share this endpoint URL with your partner to enable the partner to send AS2 messages.

Amazon DynamoDB

Integration Cloud connects to Amazon DynamoDB using the REST interface and allows you to create a database table that can store and retrieve any amount of data, and serve any level of request traffic.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: <code>https://dynamodb.<instance>.amazonaws.com</code> .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.

Field	Description
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Access Key	This is a username. It is an alphanumeric text string that uniquely identifies the user who owns the account. No two accounts can have the same Access Key.
Secret Key	This key plays the role of a password. It is called secret because it is assumed to be known only by the owner. When you type the secret key, it is displayed as an asterisk or dots.
Region	An area specific value.
Use Chunking	Enable this option if you want to send or receive a large binary stream with a chunk size of 8192 bytes. This is applicable only if the back end supports HTTP/1.1 chunking.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send

Field	Description
	the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Amazon Kinesis

Amazon Kinesis is a managed service that scales elastically for real-time processing of streaming big data. The most common Amazon Kinesis use case scenario is rapid and continuous data intake and aggregation.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: <code>https://kinesis.<Region>.amazonaws.com</code> .
Access Key	This is a username. It is an alphanumeric text string that uniquely identifies the user who owns the account. No two accounts can have the same Access Key.
Secret Key	This key plays the role of a password. It is called secret because it is assumed to be known only by the owner. When you type the secret key, it is displayed as an asterisk or dots.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent

Field	Description
	successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Use Chunking	Enable this option if you want to send or receive a large binary stream with a chunk size of 8192 bytes. This is applicable only if the back end supports HTTP/1.1 chunking.
Region	An area specific value.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.

Field	Description
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Amazon Simple Notification Service(SNS)

Integration Cloud connects to Amazon Simple Notification Service (Amazon SNS) using the REST interface and allows you to publish messages and deliver them to subscribers and other applications.

Field	Description
Server URL	The endpoint to connect with AWS SNS. Prefix the endpoint with <code>https://</code> , for example, <code>https://sns.(Region).amazonaws.com</code> . This is the native provider endpoint target for the Account configuration.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.

Field	Description
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Access Key	Access Key obtained from AWS Identity and Access Management (IAM) Console. This is a username. It is an alphanumeric text string that uniquely identifies the user who owns the account. No two accounts can have the same Access Key.
Secret Key	Secret key obtained from AWS Identity and Access Management (IAM) Console. This key plays the role of a password. It is called secret because it is assumed to be known only by the owner. When you type the secret key, it is displayed as an asterisk or dots.
Region	An area specific value. The region is different for different users.
Signing Algorithm	Explicitly select the signing algorithm, for example, HMAC-SHA1 Signatures used to sign the message.
Use Chunking	Enable this option if you want to send or receive a large binary stream with a chunk size of 8192 bytes. This is applicable only if the back end supports HTTP/1.1 chunking.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Amazon Simple Queue Service (SQS)

Integration Cloud connects to Amazon Simple Queue Service (SQS) using the REST interface and provides access to the SQS objects within the Amazon instance.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: <code>https://sqs.us-east-1.amazonaws.com/</code> .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's

Field	Description
	identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Access Key	This is a username. It is an alphanumeric text string that uniquely identifies the user who owns the account. No two accounts can have the same Access Key.
Secret Key	This key plays the role of a password. It is called secret because it is assumed to be known only by the owner. When you type the secret key, it is displayed as an asterisk or dots.
Region	An area specific value.
Signing Algorithm	Explicitly select the signing algorithm, for example, HMAC-SHA1 Signatures used to sign the message. Note: This field is not applicable for Amazon SQS Version 4.
Use Chunking	Enable this option if you want to send or receive a large binary stream with a chunk size of 8192 bytes. This is applicable only if the back end supports HTTP/1.1 chunking.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Amazon Simple Storage Service (S3)

Integration Cloud connects to Amazon Simple Storage Service (S3) using the REST interface and provides read, write, and delete access to the Amazon S3 buckets and objects within the Amazon instance.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: https://s3.amazonaws.com/.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Use Stale Checking	If enabled, additional processing is performed to test if the socket is still functional each time the socket is used.
Validate After Inactivity	This field is used in conjunction with the Use Stale Checking field to control the period of inactivity after which persistent connections must be revalidated prior to being leased. This field is considered only if the Use Stale Checking field is enabled, else this field is ignored.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is org.apache.http.conn.ssl.DefaultHostnameVerifier, which will enable hostname verification. Select org.apache.http.conn.ssl.NoopHostnameVerifier to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the

Field	Description
	keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Use Expect Continue	Whether to use the Expect/Continue HTTP/1.1 handshake and send the Expect request header. When the client sends the Expect request header, the client waits for the server to confirm that it will accept the request, before the client sends the request body. Enable this option to use the Expect/Continue handshake.
Use Chunking	Enable this option if you want to send or receive a large binary stream with a chunk size of 8192 bytes. This is applicable only if the back end supports HTTP/1.1 chunking.
Access Key	This is a username. It is an alphanumeric text string that uniquely identifies the user who owns the account. No two accounts can have the same Access Key.
Secret Key	This key plays the role of a password. It is called secret because it is assumed to be known only by the owner. When you type the secret key, it is displayed as an asterisk or dots.
Region	An area specific value.
Signing Algorithm	Explicitly select the signing algorithm, for example, HMAC-SHA1 Signatures used to sign the message.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if

Field	Description
	you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Atlassian Jira

Integration Cloud connects to JIRA using the Interface for RESTful Web Services. You can use it for bug tracking, issue tracking, and project management functions.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. For example, the end point URL would be of the format: <code>http://host:port</code> . Replace <code>< host:port ></code> with your actual JIRA instance.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Username	User name of the JIRA account.

Field	Description
Password	Password of the JIRA account.
Authorization Type	The type of HTTP authorization scheme to use for the connection. If you select none , no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password, but do not specify a value for the Authorization Type, the user credentials are not inserted into an Authorization header. If you enter the username and password, then set the authorization type as basic . Basic refers to HTTP Basic Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password. Select the Authorization Type as basic .
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.

Field	Description
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Avalara AvaTax

Integration Cloud connects to Avalara AvaTax using the Avalara SOAP API and allows you to calculate taxes, modify documents, and validate addresses.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: <code>https://<instance_name>.avalara.net</code> , where <code><instance_name></code> represents the actual instance name.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Username	This is the user account name on the SaaS provider that the Account will use to connect to the SaaS provider.
Password	Provide a password for the user name provided in the Username field to initiate communication with the SaaS provider.
Authorization Type	The type of HTTP authorization scheme to use for the connection. If you select none , no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password, but do not specify a value for the

Field	Description
	Authorization Type, the user credentials are not inserted into an Authorization header. If you enter the username and password, then set the authorization type as basic . Basic refers to HTTP Basic Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password.
clientname	Client application name and version. This should uniquely identify the software client that is calling the AvaTax service.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host

Field	Description
	name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Cloud Deployment

Use this Application to invoke Java and Flow services for any “[Cloud Deployment](#)” on [page 671](#) solution.

Field	Description
Run As	Select the user name you want Integration Cloud to use while running the cloud deployment service. Integration Cloud runs the service as if the user you specify is the authenticated user that invoked the service. If the service is governed by an Access Control List, be sure to specify a user that is allowed to invoke the service.

Note: You must map the selected user's Access Profile to a webMethods Integration Server user group (**Settings**  **> Access Profiles > Select an Access Profile > Solution Permissions**), else you will not be able to view, edit, or run webMethods Integration Server services in a solution.

Stage	Select the stage where the cloud deployment services are available.
--------------	---

Cloud Deployment Operations

Integration Cloud Integrations can invoke Cloud Deployment solution webMethods Integration Server Java and Flow services for the same tenant, by using the “[Cloud Deployment](#)” on [page 138](#) Application. You can use these services along with other Integrations and services, both in Orchestration and Point-to-Point Integrations.

Note: The Cloud Deployment Application appears under the **Predefined Applications** category.

To import Cloud Deployment solution webMethods Integration Server services, do the following:

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > Applications > Predefined Applications > Cloud Deployment**. The **Cloud Deployment** Application details page appears.
2. Select **Accounts > Add New Account** to create a new “[Cloud Deployment account](#)” on [page 138](#).

3. Click **Operations**.
4. Click **Import Operations** if you want to import multiple Java or Flow services. If any of the services have a *Document Reference* in its input/output signature, then those services will not be imported. To import those services, select **Add new Operation** and import those services individually.
5. If you click **Import Operations**, the **Import Operations** window will appear. Select the cloud deployment account, and then select the services that you want to import in Integration Cloud.
6. Click **Import**. The services will appear on the **Operations** list page for the Cloud Deployment Application.

Note: Importing will copy the metadata of the services in Integration Cloud. After import, you can use the operation in an Integration. The operation execution happens on the Cloud Deployment solution webMethods Integration Server.

CloudStreams Connector for Anaplan[®]

Using the REST interface, CloudStreams Connector for Anaplan[®] allows you to interact with data in your models and securely upload files, download files, import and export data, and run actions programmatically.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. For example, the end point URL would be of the format: http://host:port. Replace < host:port > with your actual JIRA instance.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.

Field	Description
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Username	The name of the user account on the SaaS provider that the connection will use to connect to the SaaS provider.
Password	The password for the user name provided in the Username field.
Authorization Type	<p>The type of HTTP authorization scheme to use for the connection. If you select none, no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password, but do not specify a value for the Authorization Type, the user credentials are not inserted into an Authorization header.</p> <p>If you enter the username and password, then set the authorization type as basic . Basic refers to HTTP Basic Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password. Select the Authorization Type as basic.</p>
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's

Field	Description
	identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

CloudStreams Connector for Microsoft Azure Cosmos DB

Integration Cloud connects to Microsoft Azure Cosmos DB and provides access to Microsoft's fully managed NoSQL database. You can use this Application to create, query, and manage resources in a NoSQL database.

Field	Description
Server URL	The login endpoint to initiate communication with the SaaS provider. For example, for the CloudStreams Connector for Microsoft Azure Cosmos DB, the end point URL will be of the format: <code>https://<accountName>.documents.azure.com:443/</code> . Replace <code><accountName></code> with the name of your Microsoft Azure Cosmos DB account.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.

Field	Description
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Access Key	The Access key token that contains the secret of the account required by the SaaS provider.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

CloudStreams Connector for Microsoft Azure Data Lake Store

Integration Cloud connects to CloudStreams Connector for Microsoft Azure Data Lake Store using the REST API and allows you to manage File System resources through the Hadoop Distributed File System (HDFS) API. You can create directories, folders, and files in your Azure Data Lake Store instance that can store and retrieve data.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. For example, the end point URL is of the format: <code>https://<yourstorename>.azuredatalakestore.net/webhdfs/v1</code> . Replace <code><yourstorename></code> with your actual Microsoft Azure Data Lake Store account.
Consumer ID	Also referred to as the Client ID, this is a client identifier issued to the client to identify itself to the authorization server.
Access Token	This token is used for authentication and is issued by the Authorization Server. To get the Access Token, you first need to have an Azure subscription. Then create an Azure Active Directory native application. See “End-user authentication with Data Lake Store using Azure Active Directory” on how to create it. Successful authentication will provide an access token and a refresh token. The access token gets attached to each request made to Data Lake Store and is valid for one hour by default. The refresh token can be used to obtain a new access token and is valid for two weeks by default, if used regularly.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.

Field	Description
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.
Use Chunking	Enable this option if you want to send or receive a large binary stream with a chunk size of 8192 bytes.

Field	Description
	This is applicable only if the back end supports HTTP/1.1 chunking.
Consumer Secret	Also referred to as the Client Secret, this is a secret matching to the client identifier.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token.

CloudStreams Connector for Microsoft Azure Storage

Integration Cloud connects to Microsoft Azure Storage and allows you to store, load, and query data. It includes a set of storage services, such as, Blob storage (object storage) for unstructured data, File storage for SMB-based cloud file shares, Table storage for NoSQL data, and Queue storage to reliably store messages.

Field	Description
Server URL	<p>The login endpoint to initiate communication with the SaaS provider. For example, for the CloudStreams Connector for Microsoft Azure Storage, the end point URL will be of the format: https://<accountName>.</p> <p>Replace <accountName> with the name of your Microsoft Azure Storage account.</p>
Response Timeout	<p>The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.</p>
Retry Count on Response Failure	<p>The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.</p>

Field	Description
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Access Key	Microsoft Azure Storage REST APIs use Shared Key for authentication. Type the Access key that contains the secret of your Microsoft Azure Storage account.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

CloudStreams Connector for NetSuite™

Integration Cloud connects to NetSuite™ SuiteTalk platform using the SuiteTalk web services. It provides programmatic access to NetSuite™ data related to accounting, order management/inventory, CRM, professional services automation (PSA), and eCommerce applications through operations like `addList`, `get`, `updateList`, `upsertList`, and `deleteList`.

The NetSuite SOAP Web Service Application for v2018_2 uses the Token Based authentication mechanism. With each request, Integration Cloud calculates the signature, and the token passport details are sent as part of the request headers.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. This is the native provider endpoint target for the Account configuration. You may need to specify the correct URL for your exact instance, for example, <code>https://webservices.netsuite.com/services/NetSuitePort_2018_2</code> .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Email	The user email account that the connection will use to connect to the SaaS provider.

Field	Description
Password	The password of the user email account.
Authorization Type	This is the type of HTTP authorization scheme to use for the connection. If you select none , no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password, but do not specify a value for the Authorization Type, the user credentials are not inserted into an Authorization header. If you enter the username and password, then set the authorization type as basic . Basic refers to HTTP Basic Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password.
Account Id	The Account ID or Account number received from NetSuite TM .
Consumer Key	Consumer Key received from NetSuite.
Consumer Secret	Consumer Secret received from NetSuite.
Token Id	Token received from NetSuite.
Token Secret	Token Secret received from NetSuite.
Role	Specify the role with which you want to execute the web services, for example, Administrator.
ApplicationID	When you create the NetSuite TM Account, it sends a login request to the back end using email, password, Account, and the Application Id. Application Id is required for requests using end point 2015.2 or later.
Use Chunking	Enable this option if you want to send or receive a large binary stream with a chunk size of 8192 bytes. This is applicable only if the back end supports HTTP/1.1 chunking.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains

<u>Field</u>	<u>Description</u>
	trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is org.apache.http.conn.ssl.DefaultHostnameVerifier , which will enable hostname verification. Select org.apache.http.conn.ssl.NoopHostnameVerifier to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Concur

Integration Cloud connects to Concur using the Concur API and allows you to manage expenses and travel requests. It includes the Expense and Travel Request services.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. For example, the end point URL is of the format: <code>https://<instance>/api</code> . Replace <code><instance></code> with your actual Concur instance.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's

Field	Description
	identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Consumer ID	Also referred to as the Client ID, this is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, this is a secret matching to the client identifier.
Access Token	This token is used for authentication and is issued by the Authorization Server. Concur REST APIs use OAuth 2.0. The Access Token is passed when you invoke any of the REST API endpoints.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Coupa

Integration Cloud connects to Coupa using the Coupa API and allows you to create, update, and query individual entries (records) within Coupa. It manages indirect purchases, invoices, and expenses in real time and provides executive dashboards and expense management.

Field	Description
Server URL	<p>Provide the login endpoint to initiate communication with the SaaS provider. For example, for Coupa, the end point URL would be of the format: https://<instance>.com.</p> <p>Replace <instance> with your actual Coupa instance.</p>
Response Timeout	<p>The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.</p>
Retry Count on Response Failure	<p>The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.</p>
Retry on Response Failure	<p>Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.</p>
Hostname verifier	<p>Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is org.apache.http.conn.ssl.DefaultHostnameVerifier, which will enable hostname verification. Select org.apache.http.conn.ssl.NoopHostnameVerifier to disable hostname verification.</p>
Keystore Alias	<p>Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.</p>
Client Key Alias	<p>Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.</p>
X-COUPA-API-KEY	<p>The API Key received from the user account.</p>

Field	Description
	Coupa REST APIs authentication requests require a unique API key generated in Coupa. All API requests must pass an X-COUPA-API-KEY header with an API key. A key can be created from the API Keys section of the Administration tab by an administrator. The key is a 40-character long case-sensitive alphanumeric code. The API key is associated with an API user who is the equivalent of an administrator in Coupa. Any changes to resources through the API are attributed to the API user.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Cumulocity

Integration Cloud connects to Cumulocity and allows you to manage assets and Internet of Things (IoT) devices.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. For example, for Cumulocity, the end point URL would be of the format: <code>https://<instance></code> . Replace <code><instance></code> with your actual Cumulocity instance.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.

Field	Description
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Username	This is the user account name on the SaaS provider that the Account will use to connect to the SaaS provider.
Password	Provide a password for the user name provided in the Username field to initiate communication with the SaaS provider.
Authorization Type	The type of HTTP authorization scheme to use for the connection. If you select none , no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password, but do not specify a value for the Authorization Type, the user credentials are not inserted into an Authorization header. If you enter the username and password, then set the authorization type as basic . Basic refers to HTTP Basic Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.

Field	Description
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Database

Integration Cloud allows you to connect to a database using the Database Application. The Database Application allows you to perform database operations with cloud databases using a JDBC driver.

Complete the following fields to create a new account:

Field	Description
Database	Select the supported database.
Driver Group	Select the driver group to connect to the database. You can upload a new JDBC driver through the Add Driver option from the drop-down list box. You can upload only certified jars.
Transaction Type	Select the transaction type for transaction support for the account. The following are the supported transaction types: <ul style="list-style-type: none"> ■ NO_TRANSACTION: The connection automatically commits operations. ■ LOCAL_TRANSACTION: The connection uses local transactions. With this transaction type, all of the operations

Field	Description
	on the same account in a single transaction boundary are either committed or rolled back together.
DataSource Class	Select the DataSource class. This field specifies the name of the JDBC driver's DataSource class.
Server Name	Type the name of the server that hosts the database. Note: If the tenant cannot connect to the cloud database, then check the security settings of the cloud database.
User	Type the user name that the connection uses to connect to the database.
Password	Type the password for the user name specified in User .
Database Name	Type the database name to which the connection connects to.
Port Number	Type the port number that the connection uses to connect to the database.
Truststore Alias	Select the alias name of the Integration Cloud truststore configuration. The truststore contains trusted certificates that are used to determine the trust for the remote server peer certificates. You can also add a new Truststore from this field.
Network Protocol	Indicates the name of the network protocol that the connection uses when connecting to the database. Type <code>TCP</code> or <code>TCPS</code> to indicate the network protocol.
Other Properties	Select or type the property name. Also, enter the value for the corresponding property in the input text field. Note: Properties listed for you to select from the drop-down list box are driver-dependent. Example: Use this field to choose a property such as <code>TableFilter</code> . You can either select or type the <code>TableFilter</code> property in the drop-down list box and enter the <code>'<current catalog>'. 'Accounting'</code> in the input text field.

Field	Description
	<p>Use {} to configure a combination of multiple key-value pairs.</p> <p>Example,</p> <pre data-bbox="743 457 1482 541">connectionProperties={oracle.jdbc.V8Compatible=true, includeSynonyms=true }</pre> <p>By default, the <code>loginTimeout</code> is set to 60. This value specifies the login timeout in seconds that a connection waits while attempting to connect to a database.</p>

The `<current catalog>` represents the default catalog associated with an account.

The `<current schema>` represents the default schema associated with an account.

PostgreSQL Database

When you configure an operation to select a table, you must always select the table under `<current catalog>`.

MariaDB

If you configure an operation for MariaDB using the driver versions greater than or equal to 2.4.0, select the table under `<current catalog>`.

Database Application Operations

To use Database Application, you must create operations. Database operations allow you to connect to the database and initiate an operation on the database from Integration Cloud.

You call database operations from **Integration** to perform database operation on tables, views, or synonyms. The database operations are performed by calling JDBC APIs.

Operations are based on templates provided with Database Application. Each template represents an SQL statement for doing an operation on a database. For example, use `Select` operation to retrieve specified information from the database tables.

Creating a new operation from a template is straightforward. You will have to create an account using which you can create a new operation. During this process, select the operation template and configure the operation using the operation wizards.

Database Application provides the following operation templates:

Operation	Description
Batch Insert	Inserts new information into a database table. Use this operation when you insert a large volume of data into a single table.
Batch Update	Updates the existing information in a database table. Use this operation when you update a large volume of data in a single table.
Custom SQL	Executes custom SQL to perform a database operation.
Delete	Deletes rows from a database table.
Insert	Inserts new information into a database table.
Select	Retrieves specified information from the database table.
Stored Procedure	Calls a stored procedure. It obtains the stored procedure's input/output parameters by introspecting when you configure the operation.
Update	Updates the existing information in a database table.

Advanced Options

The following options provide additional capabilities for Database operations:

Parameter	Description
Select DISTINCT	Select the checkbox to suppress the duplicate rows in the query output.
	Note This option is applicable only for Select operation.

Parameter	Description
Convert all to STRING	<p>Select the checkbox to convert the fields with input or output data type to <code>java.lang.String</code>. The fields which are already added to the table gets automatically converted to a String data type. It does not impact the fields which cannot be converted to String data type.</p> <p>Note This option is applicable for Select, Insert, Update, Delete, Batch Insert, and Batch Update operations.</p>
Use SQL Expression (Advanced)	<p>Use the following formats to provide SQL expressions:</p> <ul style="list-style-type: none"> ■ For table columns use <code>tableAlias.columnName</code>. ■ For valid database functions use <code>databaseFunction(tableAlias.columnName)</code>. <p>For example, <code>upper(tableAlias.columnName)</code>.</p> <p>Note This option is applicable for Select, Update, Delete, and Batch Update operations.</p>

Configuring the Parameter Values

Custom SQL Operation

You can configure the following parameters for Custom SQL operation:

Parameter	Description
Query Time Out	<p>Type or Select the query time out value in seconds.</p> <p>This field specifies the number of seconds the database connection will wait for a SQL statement.</p>

Parameter	Description
	<p>NoteSelect No Timeout if you do not want to specify the Query Time Out.</p>
Maximum Row	<p>Type the number of rows to be retrieved from a database table.</p> <p>NoteSelect No Limit to indicate no limit on the number of rows retrieved.</p>
Row Count Field Name	<p>Type the field name of the Row Count Field.</p> <p>This field specifies the name of the output field whose value contains the number of affected rows while executing an SQL query.</p>
Row Count Field Type	<p>Select the data type of the Row Count Field.</p>

Select Operation

You can configure the following parameters for Select operation:

Parameter	Description
Query Time Out	<p>Type or Select the query time out value in seconds.</p> <p>This field specifies the number of seconds the database connection will wait for a Statement to execute.</p> <p>NoteSelect No Timeout if you do not want to specify the Query Time Out.</p>
Maximum Row	<p>Type the number of rows to be retrieved from a database table.</p> <p>NoteSelect No Limit to indicate no limit on the number of rows retrieved.</p>

Parameter	Description
Row Count Field Name	Type the field name of the Row Count Field. This field specifies the name of the output field whose value contains the number of affected rows while executing a Select SQL query.
Row Count Field Type	Select the data type of the Row Count Field.

Update Operation

You can configure the following parameters for Update operation:

Parameter	Description
Query Time Out	Type or Select the query time out value in seconds. This field specifies the number of seconds the database connection will wait for a SQL statement to execute. Note Select No Timeout if you do not want to specify the Query Time Out.
Row Count Field Name	Type the field name of the Row Count Field. This field specifies the name of the output field whose value contains the number of affected rows while executing an Update SQL query.
Row Count Field Type	Select the data type of the Row Count Field.

Insert Operation

You can configure the following parameters for Insert operation:

Parameter	Description
Query Time Out	Type or Select the query time out value in seconds.

Parameter	Description
	<p>This field specifies the number of seconds the database connection will wait for a SQL statement to execute.</p> <p>NoteSelect No Timeout if you do not want to specify the Query Time Out.</p>
Row Count Field Name	<p>Type the field name of the Row Count Field.</p> <p>This field specifies the name of the output field whose value contains the number of affected rows while executing a SQL statement.</p>
Row Count Field Type	Select the data type of the Row Count Field.

Delete Operation

You can configure the following parameters for Delete operation:

Parameter	Description
Query Time Out	<p>Type or Select the query time out value in seconds.</p> <p>This field specifies the number of seconds the database connection will wait for a SQL statement to execute.</p> <p>NoteSelect No Timeout if you do not want to specify the Query Time Out.</p>
Row Count Field Name	<p>Type the field name of the Row Count Field.</p> <p>This field specifies the name of the output field whose value contains the number of affected rows while executing a SQL statement.</p>
Row Count Field Type	Select the data type of the Row Count Field.

Stored Procedure Operation

You can configure the following parameters for Stored Procedure operation:

Parameter	Description
Query Time Out	<p>Type or Select the query time out value in seconds.</p> <p>This field specifies the number of seconds the database connection will wait for a SQL statement to execute.</p> <p>NoteSelect No Timeout if you do not want to specify the Query Time Out.</p>

Batch Insert Operation

You can configure the following parameters for Batch Insert operation:

Parameter	Description
Query Time Out	<p>Type or Select the query time out value in seconds.</p> <p>This field specifies the number of seconds the database connection will wait for a SQL statement to execute.</p> <p>NoteSelect No Timeout if you do not want to specify the Query Time Out.</p>

Batch Result Output Name	<p>Type the output name of the Batch Result Output Name.</p> <p>The output of the batch operation is a string list. Elements in the list appear in the order in which you add the Insert SQL queries for execution in the batch mode. Depending on the JDBC driver you use, the elements in the list contains one of the following values:</p> <ul style="list-style-type: none"> ■ A number greater than or equal to 0. This indicates the insert SQL query is successfully executed and returns the number of rows affected in the database.
---------------------------------	---

Parameter	Description
	<ul style="list-style-type: none"> ■ A value of -2. This indicates that the insert SQL query was executed successfully but the number of rows affected is unknown.

Batch Update Operation

You can configure the following parameters for Batch Update operation:

Parameter	Description
Query Time Out	<p>Type or Select the query time out value in seconds.</p> <p>This field specifies the number of seconds the database connection will wait for a SQL statement to execute.</p> <p>NoteSelect No Timeout if you do not want to specify the Query Time Out.</p>

Batch Result Output Name	<p>Type the output name of the Batch Result Output Name.</p> <p>The output of the batch operation is a string list. Elements in the list appear in the order in which you add the Update SQL queries for execution in the batch mode. Depending on the JDBC driver you use, the elements in the list contains one of the following values:</p> <ul style="list-style-type: none"> ■ A number greater than or equal to 0. This indicates the Update SQL query is successfully executed and returns the rows affected in the database. ■ A value of -2. This indicates that the command was processed successfully but the number of rows affected is unknown.
--------------------------	--

JDBC Data Type to Java Data Type Mappings

Each column in the database table is assigned a SQL type. The JDBC driver maps each SQL data type to a JDBC data type. Database Application then maps each JDBC data

type to one or more Java data types that are used as the input or output of the database operation.

The following table shows the JDBC data type to Java data type mappings. You can map each JDBC data type to a set of Java data types by choosing one from the set. The JDBC data type you select during configuration will then map to the input or output of the database operation.

For a list of data types for which Database Application has some constraints, see [“JDBC Data Type to Java Data Type Mapping Constraints” on page 170](#).

- Note:** Database Application does not support the `TIMESTAMP WITH TIME ZONE` and `TIMESTAMP WITH LOCAL TIME ZONE` data types in Oracle 10g.
- Note:** Database Application does not support user-defined data types, Oracle PL/SQL collections, or Oracle PL/SQL records.
- Note:** `UROWID` data type is not supported for Oracle database.
- Note:** If the `DATE` JDBC type contains String as Java type, then the date format which Database Application accepts is `YYYY-MM-DD`.

JDBC Data Type	Java Data Type
ARRAY	java.sql.Array java.lang.Object
BIT	java.lang.Boolean java.lang.String java.lang.Object
TINYINT	java.lang.Byte java.lang.Integer java.lang.String java.lang.Object SetAsString
SMALLINT	java.lang.Short java.lang.Integer java.lang.String java.lang.Object

JDBC Data Type	Java Data Type
INTEGER	java.lang.Integer java.lang.String java.lang.Object
BIGINT	java.lang.Long java.lang.String java.lang.Object
FLOAT	java.lang.Double java.lang.String java.lang.Object java.math.BigDecimal SetAsString
REAL	java.lang.Float java.lang.String java.lang.Object java.math.BigDecimal
BOOLEAN	java.lang.Boolean java.lang.String java.lang.Object
DOUBLE	java.lang.Double java.lang.String java.lang.Object java.math.BigDecimal SetAsString
NUMERIC	java.math.BigDecimal java.lang.String java.lang.Object

JDBC Data Type	Java Data Type
DECIMAL	java.math.BigDecimal java.lang.String java.lang.Object
CHAR	java.lang.String java.lang.Character java.lang.Object
VARCHAR	java.lang.String java.lang.Object
LONGVARCHAR	java.lang.String java.lang.Object
DATE	java.sql.Date java.util.Date java.lang.String java.lang.Object *SetAsString
TIME	java.sql.Time java.util.Date java.lang.String java.lang.Object SetAsString
TIMESTAMP	java.sql.Timestamp java.util.Date java.lang.String java.lang.Object SetAsString
TIMESTAMP WITH TIME ZONE	

JDBC Data Type	Java Data Type
TIMESTAMP WITH LOCAL TIME ZONE	
BINARY	byte array (byte []) java.lang.Object
VARBINARY	byte array (byte[]) java.lang.Object
LONGVARBINARY	byte array (byte[]) java.lang.Object
LONGNVARCHAR	java.lang.String java.lang.Object
NCHAR	java.lang.String java.lang.Object
NULL	java.lang.String java.lang.Object
NVARCHAR	java.lang.String java.lang.Object
CLOB	java.sql.Clob java.lang.String java.io.Reader java.lang.Object
BLOB	java.sql.Blob byte array java.io.InputStream java.lang.Object
ORACLECURSOR	java.lang.Object

JDBC Data Type	Java Data Type
ORACLEFIXED_CHAR	java.lang.String
STRUCT	java.sql.Struct java.lang.Object
OTHER	java.lang.Object java.lang.String java.sql.Struct java.sql.Array

Important Considerations When Using BLOB and CLOB Data Types

- When passing large CLOB or BLOB data, use the Java data types `java.io.Reader` for CLOB and `java.io.InputStream` for BLOB to prevent Database Application from running out of memory. When using these data types, Database Application streams the data into bytes thus allowing to pass large data. The data types `java.io.Reader` and `java.io.InputStream` are supported only for the Oracle database using the Oracle driver.
- When using the CLOB data with `java.io.Reader` as input data type, it is recommended that you use the `InputStreamReader` implementation of `java.io.Reader` with the correct encoding parameter.
- When Integration Cloud executes a SELECT operation that has its output type set to `java.sql.Blob` for a BLOB data type, Integration Cloud issues a `java.io.NotSerializableException` error. The work around for this issue is to use with **Integration**.

Important Considerations When Using the Array and Struct Database Specific Data Types

- In database operation, when using the `java.lang.Object` as the output field type for a database column of type ARRAY or STRUCT, Database Application returns the data as a `java.lang.Object` array, provided that the ARRAY or STRUCT data in the database table is composed of primitive data types.
- When using the `java.sql.Array` or `java.sql.Struct` as the output field type for a database column of type ARRAY or STRUCT, Database Application returns the `java.sql.Array` and the `java.sql.Struct` objects, respectively, as returned by the driver. However, when serializing the data across the JVMs, this returned data may not be serializable and may result into a `java.io.NotSerializableException`. Therefore, before serializing the data across the JVMs, it is important that you use Integration to process the `java.sql.Struct` and `java.sql.Array` objects as required, and then drop them from the pipeline.

Note: The `java.sql.Struct` and `java.sql.Array` data types are available only for Database Application operations.

Using the SetAsString Data Type in Database Application

The `SetAsString` data type is a dummy string data type. When using this data type, Database Application does not try to convert the input data into the equivalent JDBC data type, but passes the data to the underlying database driver as a string data type. Thus, you have the flexibility to specify the format of the equivalent JDBC data type by using a database specific function.

For example, you can specify the format for date, time, or timestamp using the `to_date` function or a similar database function for Oracle database. Database Application treats the input data as a string data type and does not convert it to the equivalent JDBC data type. The `to_date` function then uses the string data to provide the required format of the date, time or timestamp.

If your database has native database specific functions that can convert string data type to any other data type, you may use the `SetAsString` data type.

Note: The `SetAsString` data type is available only for database operations.

JDBC Data Type to Java Data Type Mapping Constraints

Database Application has some constraints when mapping JDBC data types to Java data types.

If you select one of the following Java data types, the data type will map exactly to the **Input/Output** of operation:

- `java.lang.String`
- `java.lang.Byte`
- `java.lang.Boolean`
- `java.lang.Character`
- `java.lang.Double`
- `java.lang.Float`
- `java.lang.Integer`
- `java.lang.Long`
- `java.lang.Short`
- `java.util.Date`
- `java.math.BigDecimal`
- `java.math.BigInteger`
- `java.lang.Object`

Those data types not included in this list will map to `java.lang.Object`. In these cases, if the JDBC data type you specify is for input, you will need to pass in the object with the selected Java data type. If the JDBC type is for output, you can cast the object to the selected Java data type.

Driver Management

The **Driver Management** screen is available only for Database Application. This screen lists all the available drivers uploaded for Database Application. It also gives you an option to upload a custom driver jar for a particular database. This uploaded driver can be used when you create an account. You can add or delete a driver jar from this screen.

Pre-bundled driver jars are provided to connect to the databases like Microsoft SQL Server, Oracle, PostgreSQL. You cannot delete these pre-bundled driver group. The below table shows the driver groups and supported databases.

Driver Group	Supported Databases	Version
Progress® DataDirect®.	Microsoft SQL Server, Oracle	5.1.4
Microsoft JDBC Driver for SQL Server	Microsoft SQL Server	4.0.0
PostgreSQL JDBC Driver	PostgreSQL	42.2.5

Note: If you use Progress® DataDirect® driver to create a Non-SSL connection for Microsoft SQL Server database, then set the **Other Properties** with `validateservercertificate=false;encryptionmethod=ssl`.

Note: For Oracle database, if you are using Progress® DataDirect® driver group to create a connection for Stored Procedure operation, then the Stored Procedure operation cannot fetch the metadata for `SYS_CURSOR` data type.

To add a new driver

1. From the Integration Cloud navigation bar, click **Connect > Applications** .
2. Select **Database Application** and then click **Driver Management**.
3. From the **Driver Management**, click **Add Driver**.
4. Select the supported **Database**.
5. Type or select the driver from the **Driver Group**. Browse the jar in the **Select the Driver** field for a particular database.

The driver jar gets uploaded for the corresponding database.

Note: You can upload only the certified jars.

Note: The uploaded driver jars can be used across the projects in the tenant.

Driver Management Fields

You can configure the following fields for Driver Management:

Parameter	Description
Database	Select the supported database.
Driver Group	Type a new driver group name or select the existing group name from the drop-down The uploaded JDBC driver jars are referred by the given name when you create an account.
Select the Driver	Browse and select the driver jar for a particular vendor. You must select the driver jars which are certified by Software AG.

Certified Databases and JDBC Driver Jars

You can upload only the following list of certified driver jars:

Database	Driver Version	Driver Jar Name	Java Version	Supported DB Versions	Download Path
Oracle	11.2.0.4	ojdbc5.jar	5	Oracle 11.2.0.4	https://www.oracle.com/technetwork/documentation/jdbc-112010-090769.html
	11.2.0.4	ojdbc6.jar	6,7,8	Oracle 11.2.0.4	https://www.oracle.com/technetwork/documentation/jdbc-112010-090769.html
	11.2.0.4	xdbc.jar	6,7	Oracle 11.2.0.4	https://www.oracle.com/technetwork/

Database	Driver Version	Driver Jar Name	Java Version	Supported DB Versions	Download Path
					documentation/ jdbc-112010-090769.html
	11.2.0.4	xmlparserv2-11.2.0.4.jar	NA	Oracle 11.2.0.4	https:// www.oracle.com/ content/ secure/ maven/ content/ com/ oracle/ jdbc/ xmlparserv2/11.2.0.4/ xmlparserv2-11.2.0.4.jar
	12.1.0.1	ojdbc6.jar	6	Oracle 11.2.0.4, 12.1.0.1	https:// www.oracle.com/ technetwork/ database/ features/ jdbc/ jdbc- drivers-12c- download-1958347.html
	12.1.0.1	ojdbc7.jar	7,8	Oracle 11.2.0.4, 12.1.0.1	https:// www.oracle.com/ technetwork/ database/ features/ jdbc/ jdbc- drivers-12c- download-1958347.html
	12.1.0.1	xdb6.jar	6,7	Oracle 11.2.0.4, 12.1.0.1	https:// www.oracle.com/ technetwork/ database/ features/ jdbc/ jdbc-

Database	Driver Version	Driver Jar Name	Java Version	Supported DB Versions	Download Path
					drivers-12c-download-1958347.html
	12.1.0.1	xmlparserv2-12.1.0.1.jar	NA	Oracle 11.2.0.4, 12.1.0.1	https:// www.oracle.com/ content/ secure/ maven/ content/ com/ oracle/ jdbc/ xmlparserv2/12.1.0.1/ xmlparserv2-12.1.0.1.jar
	12.1.0.2	ojdbc6.jar	6	Oracle 11.2.0.4, 12.1.0.1, 12.1.0.2	https:// www.oracle.com/ technetwork/ database/ features/ jdbc/ default-2280470.html
	12.1.0.2	ojdbc7.jar	7,8	Oracle 11.2.0.4, 12.1.0.1, 12.1.0.2	https:// www.oracle.com/ technetwork/ database/ features/ jdbc/ default-2280470.html
	12.1.0.2	xdb6.jar	6,7	Oracle 11.2.0.4, 12.1.0.1, 12.1.0.2	https:// www.oracle.com/ technetwork/ database/ features/ jdbc/ default-2280470.html
	12.1.0.2	xmlparserv2-12.1.0.2.jar	NA	Oracle 11.2.0.4, 12.1.0.1, 12.1.0.2	https:// www.oracle.com/ content/ secure/

Database	Driver Version	Driver Jar Name	Java Version	Supported DB Versions	Download Path
					maven/ content/ com/ oracle/ jdbc/ xmlparserv2/12.1.0.2/ xmlparserv2-12.1.0.2.jar
	12.2.0.1	ojdbc8.jar	8	Oracle 11.2.0.4, 12.1.0.1, 12.1.0.2, 12.2.0.1	https:// www.oracle.com/ technetwork/ database/ features/ jdbc/ jdbc- ucp-122-3110062.html
	12.2.0.1	xdb6.jar	7,8	Oracle 11.2.0.4, 12.1.0.1, 12.1.0.2, 12.2.0.1	https:// www.oracle.com/ technetwork/ database/ features/ jdbc/ jdbc- ucp-122-3110062.html
	12.2.0.1	xmlparserv2-12.2.0.1.jar	NA	Oracle 11.2.0.4, 12.1.0.1, 12.1.0.2, 12.2.0.1	https:// www.oracle.com/ content/ secure/ maven/ content/ com/ oracle/ jdbc/ xmlparserv2/12.2.0.1/ xmlparserv2-12.2.0.1.jar
MySQL	8.0.16	mysql-connector- java-8.0.16.jar	8	MySQL 8.0, 5.7, 5.6, 5.5	https:// downloads.mysql.com/ archives/ c-j/

Database	Driver Version	Driver Jar Name	Java Version	Supported DB Versions	Download Path
	8.0.17	mysql-connector-java-8.0.17.jar	8	MySQL 8.0, 5.7, 5.6, and 5.5	https://dev.mysql.com/downloads/connector/j/
					<p>Note: If you are unable to find the driver jar for the specified version, then download the driver from the archived version's download link as shown below: https://downloads.mysql.com/archives/c-j/</p>
Microsoft SQL Server	4.1	sqljdbc41.jar	7	Microsoft SQL Server 2008, 2012, 2014, 2016, and Azure SQL Database	https://go.microsoft.com/fwlink/?linkid=841533

Database	Driver Version	Driver Jar Name	Java Version	Supported DB Versions	Download Path
	4.2	sqljdbc41.jar	7	Microsoft SQL Server 2008, 2012, 2014, 2016, and Azure SQL Database	https://go.microsoft.com/fwlink/?linkid=841534
	4.2	sqljdbc42.jar	8	Microsoft SQL Server 2008, 2012, 2014, 2016, and Azure SQL Database	https://go.microsoft.com/fwlink/?linkid=841534
	6.0	sqljdbc41.jar	7	Microsoft SQL Server 2008, 2012, 2014, 2016 and Azure SQL Database	https://go.microsoft.com/fwlink/?LinkId=245496
	6.0	sqljdbc42.jar	8	Microsoft SQL Server 2008, 2012, 2014, 2016,	https://go.microsoft.com/fwlink/?LinkId=245496

Database	Driver Version	Driver Jar Name	Java Version	Supported DB Versions	Download Path
				and Azure SQL Database	
	6.2.2	mssql-jdbc-6.2.2.jre7.jar	7	Microsoft SQL Server 2008, 2012, 2014, 2016, 2017, and Azure SQL Database	https:// go.microsoft.com/ /fwlink/? linkid=852460
	6.2.2	mssql-jdbc-6.2.2.jre8.jar	8	Microsoft SQL Server 2008, 2012, 2014, 2016, 2017 and Azure SQL Database	https:// go.microsoft.com/ /fwlink/? linkid=852460
	6.4.0	mssql-jdbc-6.4.0.jre7.jar	7	Microsoft SQL Server 2008, 2012, 2014, 2016, 2017, and Azure SQL Database	https:// go.microsoft.com/ /fwlink/? linkid=868290

Database	Driver Version	Driver Jar Name	Java Version	Supported DB Versions	Download Path
	6.4.0	mssql-jdbc-6.4.0.jre8.jar	8	Microsoft SQL Server 2008, 2012, 2014, 2016, 2017, and Azure SQL Database	https://go.microsoft.com/fwlink/?linkid=868290
	7.0.0	mssql-jdbc-7.0.0.jre8.jar	8	Microsoft SQL Server 2008, 2012, 2014, 2016, 2017, and Azure SQL Database	https://go.microsoft.com/fwlink/?linkid=2063159
	7.2.2	mssql-jdbc-7.2.1.jre8.jar	8	Microsoft SQL Server 2008, 2012, 2014, 2016, 2017, and Azure SQL Database	https://go.microsoft.com/fwlink/?linkid=2063159
PostgreSQL 42.2.5		postgresql-42.2.5.jre6.jar	6	Aurora PostgreSQL (Compatible with	https://jdbc.postgresql.org/download.html

Database	Driver Version	Driver Jar Name	Java Version	Supported DB Versions	Download Path
				PostgreSQL 9.6.8, 9.6.9, 10.4, 10.5, 10.6)	
	42.2.5	postgresql-42.2.5.jre7.jar	7	Aurora PostgreSQL (Compatible with PostgreSQL 9.6.8, 9.6.9, 10.4, 10.5, 10.6)	https://jdbc.postgresql.org/download.html
	42.2.5	postgresql-42.2.5.jar	8	Aurora PostgreSQL (Compatible with PostgreSQL 9.6.8, 9.6.9, 10.4, 10.5, 10.6)	https://jdbc.postgresql.org/download.html
	42.2.6	postgresql-42.2.6.jre6.jar	6	Aurora PostgreSQL (Compatible with PostgreSQL 9.6.8, 9.6.9, 10.4, 10.5, 10.6)	https://jdbc.postgresql.org/download.html
	42.2.6	postgresql-42.2.6.jre7.jar	7	Aurora PostgreSQL (Compatible with PostgreSQL 9.6.8, 9.6.9, 10.4, 10.5, 10.6)	https://jdbc.postgresql.org/download.html

Database	Driver Version	Driver Jar Name	Java Version	Supported DB Versions	Download Path
				with PostgreSQL 9.6.8, 9.6.9, 10.4, 10.5, 10.6)	
	42.2.6	postgresql-42.2.6.jar	8	Aurora PostgreSQL (Compatible with PostgreSQL 9.6.8, 9.6.9, 10.4, 10.5, 10.6)	https://jdbc.postgresql.org/download.html
	42.2.7	postgresql-42.2.7.jar	8	Aurora PostgreSQL (Compatible with PostgreSQL 9.6.8, 9.6.9, 10.4, 10.5, 10.6)	https://jdbc.postgresql.org/download.html
	42.2.7	postgresql-42.2.7.jre6.jar	6	Aurora PostgreSQL (Compatible with PostgreSQL 9.6.8, 9.6.9, 10.4, 10.5, 10.6)	https://jdbc.postgresql.org/download.html

Database	Driver Version	Driver Jar Name	Java Version	Supported DB Versions	Download Path
	42.2.7	postgresql-42.2.7.jre7.jar	7	Aurora PostgreSQL (Compatible with PostgreSQL 9.6.8, 9.6.9, 10.4, 10.5, 10.6)	https://jdbc.postgresql.org/download.html
	42.2.8	postgresql-42.2.8.jar	8	Aurora PostgreSQL (Compatible with PostgreSQL 9.6.8, 9.6.9, 10.4, 10.5, 10.6)	https://jdbc.postgresql.org/download.html
Tibero	6.0	tibero6-jdbc.jar	NA	Tibero 6	The driver jar is available in the Tibero 6 installation directory, (\$TB_HOME/client/lib/jar).
MariaDB	2.3.0	mariadb-java-client-2.3.0.jar	8	MariaDB 10.3.8	http://downloads.mariadb.com/Connectors/java/

Note: For MySQL driver, ensure that you download the **Platform Independent** variant.

Samples Accounts

The following are the sample accounts created for secured and non secured connection for various databases:

Microsoft SQL Server

The following are the fields to be configured for a non-secure Microsoft SQL Server account:

The screenshot shows the 'New Account' configuration interface. On the left, there is a sidebar with expandable sections: 'Save as', 'Description', 'Account Configuration Fields', and 'Other Properties'. The main area contains the following fields:

- Name:** sample_mssql
- Description:** Account to Microsoft SQL Server
- Database:** Microsoft SQL Server
- Driver Group:** Microsoft JDBC Driver for SQL Server
- Transaction Type:** NO_TRANSACTION
- DataSource Class:** com.microsoft.sqlserver.jdbc.SQLServerDataSource
- Server Name:** sample.com
- User:** sampleUser
- Password:** *****
- Database Name:** sampleDB
- Port Number:** 1433
- Truststore Alias:** Select or Type
- Network Protocol:** (empty)
- Other Properties:** loginTimeout=60;

At the bottom right, there are three buttons: 'Test', 'Cancel', and 'Save'.

Note: For a secured connection using Microsoft SQL database, edit the following fields:

- Select **Truststore Alias** from the drop-down. If this option is not available in the drop-down, then upload your certificate using **Add New Truststore**.
- Set the **Other Properties** to `loginTimeout=60;encrypt=true`.

Oracle

The following are the fields to be configured for a non-secure Oracle account:

New  Account

Save as *

Description

Account Configuration Fields

Database *

Driver Group *

Transaction Type *

DataSource Class *

Server Name *

User *

Password *

Database Name

Port Number

Truststore Alias

Network Protocol

Other Properties

- Note:** For a secured connection using Oracle database, edit the following fields:
- Select **Truststore Alias** from the drop-down. If this option is not available in the drop-down, then upload your certificate using **Add New Truststore**.
 - Type `tcps` for **Network Protocol**

Note: By default, 2484 is the `tcps` port.

PostgreSQL

The following are the fields to be configured for a non-secure PostgreSQL account:

New  Account

Save as *

Description

Account Configuration Fields

Database *

Driver Group *

Transaction Type *

DataSource Class *

Server Name *

User *

Password *

Database Name

Port Number

Truststore Alias

Network Protocol

Other Properties

- Note:** For secured connection using PostgreSQL, you need to select the **Truststore Alias** from the drop-down. If this option is not available in the drop-down, then upload your certificate using **Add New Truststore**.

Note: The **Network Protocol** field is not mandatory for PostgreSQL account.

MySQL

The following are the fields to be configured for a non-secure MySQL account:

The screenshot shows the 'New Account' configuration window for MySQL. The fields are as follows:

- Save as: sample_MySQL
- Description: Account to MySQL Database
- Account Configuration Fields:
 - Database: MySQL
 - Driver Group: Test_MySQL_Driver
 - Transaction Type: NO_TRANSACTION
 - DataSource Class: com.mysql.cj.jdbc.MySQLDataSource
 - Server Name: sample.com
 - User: sampleUser
 - Password: *****
 - Database Name: sampleDB
 - Port Number: 3306
 - Truststore Alias: Select or Type
 - Network Protocol: (empty)
 - Other Properties: loginTimeout:60

Note: For secured connection using MySQL database, you need to select the **Truststore Alias** from the drop-down. If this option is not available in the drop-down, then upload your certificate using **Add New Truststore**.

MariaDB

The following are the fields to be configured for a non-secure MariaDB account:

The screenshot shows the 'New Account' configuration window for MariaDB. The fields are as follows:

- Save as: sample_maria
- Description: Account to MariaDB
- Account Configuration Fields:
 - Database: MariaDB
 - Driver Group: Test_Maria
 - Transaction Type: LOCAL_TRANSACTION
 - DataSource Class: org.mariadb.jdbc.MariaDBDataSource
 - Server Name: SAG-6PNMCM2.eur.ad.sag
 - User: root
 - Password: *****
 - Database Name: maria
 - Port Number: 3306
 - Truststore Alias: top
 - Network Protocol: (empty)
 - Other Properties: loginTimeout:60

Note: For secured connection using MariaDB, select the **Truststore Alias** from the drop-down list. If this option is not available in the drop-down list, then upload your certificate using **Add New Truststore**.

Tibero

The following are the fields to be configured for a non-secure Tibero account:

The screenshot shows the 'New Account' configuration window for Tibero. The left pane lists configuration fields, and the right pane shows the values for these fields. The fields and their values are:

- Save as: Tibero_v6_Connection
- Description: Tibero connection
- Database: Tibero
- Driver Group: TiberoDriver
- Transaction Type: LOCAL_TRANSACTION
- DataSource Class: com.tmax.tibero.jdbc.ext.TbConnectionPoolDataSource
- Server Name: localhost
- User: SYS
- Password: *****
- Database Name: tibero
- Port Number: 8629
- Truststore Alias: (empty)
- Network Protocol: tcp
- Other Properties: (empty)

At the bottom right, there are buttons for 'Test', 'Cancel', and 'Save'.

Supported Cloud Databases

The following table lists the supported cloud databases:

Cloud Database	Database Version
Microsoft Azure	Microsoft SQL Azure (RTM) - 12.0.2000.8
Amazon RDS Oracle	Oracle 12c, Version 12.1.0.2
Amazon RDS MS SQL Server	SQL Server 2016 SP1 CU7 13.00.4466.4, released
AWS Aurora PostgreSQL	Aurora PostgreSQL 10.6
AWS Aurora MySQL	Aurora MySQL 5.7.12
Amazon RDS MariaDB	MariaDB 10.3.8
Tibero on Amazon EC2	Tibero 6

DocuSign

Integration Cloud connects to DocuSign using the DocuSign API. It provides electronic signature technology and digital transaction management services for facilitating electronic exchanges of contracts and signed documents.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. For example, for the DocuSign connector version 2, the end point URL is of the format: <code>https://demo.DocuSign.net/restapi</code> .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to

Field	Description
	send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Consumer ID	Also referred to as the Client ID, this is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, this is a secret matching to the client identifier.
Access Token	This token is used for authentication and is issued by the Authorization Server. DocuSign REST APIs use OAuth 2.0. The Access Token is passed when you invoke any of the REST API endpoints. The Access Token is valid in all future API calls to authenticate the user, until the token is revoked. It is not affected by password changes.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Electronic Data Interchange

Use the predefined operations in the Electronic Data Interchange (EDI) application to parse, validate, and transform EDI messages received from the webMethods.io B2B application. Use these transformed messages to create orchestrations.

This application requires you to have access to the webMethods.io B2B product instance.

Note: Only the documents you add in the webMethods.io B2B product tenant appear on the EDI application page of the corresponding Integration Cloud tenant. And these documents are available across all projects.

Predefined Operations

The following predefined operations are available for EDI application:

addGroupEnvelope

Adds a functional group header to an EDI message according to the UN/EDIFACT, ANSI X12, UCS, or VICS standards.

Input Parameters

<i>ediMessages</i>	String EDI messages to which a group envelope is added.
<i>documentType</i>	Either X12/UCS/VICS or UN/EDIFACT .
<i>functionalIDcode</i>	String Functional ID Code of the EDI document.
<i>senderQual</i>	String EDI ID qualifier for the sender ID. It is used with <i>sender</i> .
<i>sender</i>	String Identifies sender in the group envelope. For example, if you specify 01 for <i>senderQual</i> (indicating a D-U-N-S number), specify the D-U-N-S number for <i>sender</i> .
<i>receiverQual</i>	String EDI ID qualifier for the receiver ID. It is used with <i>receiver</i> .
<i>receiver</i>	String Receiver to be identified in the group envelope. For example, if you specify 01 for <i>receiverQual</i> (indicating a D-U-N-S number), specify the D-U-N-S number for <i>receiver</i> .
<i>grpCtlNumber</i>	String Group control number of the EDI document.
<i>agencyCode</i>	String Responsible agency code as per EDI standard: T (default) or X.
<i>verCode</i>	String EDI standard version and release code. For example, 4010, 3040.
<i>UN/EDIFACT</i>	Document When the document type is UN/EDIFACT , assign values to the following parameters:

Key

Description

<i>syntaxVersion</i>	String Syntax version of the envelope level.
<i>releaseCode</i>	String EDI message standard release code. For example, 96A, 97b.
<i>assignedCode</i>	String EDI message standard assigned code. For example, OD, EN.
<i>password</i>	String The recipient transmission reference password.

delimiters

Document Delimiters used in the EDI document:

<u>Key</u>	<u>Description</u>
<i>segment</i>	String Segment terminator for the EDI document. For example, \u000a. Default New line character
<i>field</i>	String Field separator for each EDI segment. For example, exclamation mark (!). Default *
<i>subfield</i>	String Separator for composite elements. For example, caret (^). Default :
<i>release</i>	String Release character for composite elements. For example, caret (^). Default ?

Output Parameters

<i>ediMessage</i>	String Contains the <i>ediMessage</i> .
<i>statusCode</i>	String Status code based on success or failure.
<i>statusMessage</i>	String Status message after executing the operation.

addInterchangeEnvelope

Adds an interchange control header to an EDI message according to the UN/EDIFACT, ANSI X12, UCS, or VICS standards.

Input Parameters

<i>ediMessages</i>	String EDI messages to which a group envelope is added.
<i>documentType</i>	Either X12/UCS/VICS or UN/EDIFACT .
<i>senderQual</i>	String EDI ID qualifier for the sender ID. It is used with <i>sender</i> .
<i>sender</i>	String The sender to be identified in the group envelope. For example, if you specify 01 for <i>senderQual</i> (indicating a D-U-N-S number), specify the D-U-N-S number for <i>sender</i> .
<i>receiverQual</i>	String EDI ID qualifier for the receiver ID. It is used with <i>receiver</i> .
<i>receiver</i>	String The receiver to be identified in the group envelope. For example, if you specify 01 for <i>receiverQual</i> (indicating a D-U-N-S number), specify the D-U-N-S number for <i>receiver</i> .
<i>ctlNumber</i>	String The interchange control number of the EDI document.
<i>ackRequested</i>	String Indicates whether to request an acknowledgment for this interchange:

<u>Value</u>	<u>Meaning</u>
false	Do not request an acknowledgment. Default False
true	Requests an acknowledgment.

delimiters **Document** Delimiters used in the EDI document.

<u>Key</u>	<u>Description</u>
<i>segment</i>	String Segment terminator for the EDI document. For example, \u000a. Default \

<i>field</i>	String Field separator for each EDI segment. For example, exclamation mark (!). Default *
<i>subfield</i>	String Separator for composite elements. For example, caret (^). Default :
<i>release</i>	String Release character for composite elements. For example, caret (^). Default ?
<i>decimal</i>	String Decimal character for composite elements. For example, caret (^). If <i>UN/EDIFACT > unaSegmentRequired</i> is <code>true</code> , the decimal delimiter is used. Default . If <i>UN/EDIFACT > unaSegmentRequired</i> is <code>false</code> , <i>decimal</i> is ignored.

*X12/UCS/
VICS*

Document When the document type is **X12/UCS/VICS**, assign values to the following parameters:

<u>Key</u>	<u>Description</u>
<i>authQual</i>	String Authorization qualifier for the interchange envelope.
<i>authInfo</i>	String Authorization information for the interchange envelope.
<i>securityQual</i>	String Security qualifier for the interchange envelope.
<i>securityInfo</i>	String Security information for the interchange envelope.
<i>ctlVersion</i>	String Version of the EDI standard used, with a 00 prefix. For example, if version is 4010, specify 004010.

addLeadingZerosToCtlNumber **String** (ANSI X12 only) Adds leading zeros to the interchange control number to make it a nine-digit number.

<u>Value</u>	<u>Meaning</u>
false	Do not add leading zeros to the interchange control number. Default false
true	Add leading zeros to the interchange control number to make it a nine digit number. For example, 12 becomes 00000012.

repSeparator **String** A separator for the repeated occurrences of a simple data element or a composite data structure. Field length: 1

Note:The *repSeparator* must be different from the *record*, *field*, or *subfield* delimiters.

messageAlignment

String Aligns the messages.

<u>Value</u>	<u>Description</u>
left	Left justify.
right	Right justify.
none	No justification.
	Default

UN/EDIFACT **Document** When the document type is **UN/EDIFACT**, assign values to the following parameters:

<u>Key</u>	<u>Description</u>
<i>syntaxID</i>	String Syntax identifier.

<i>syntaxVersion</i>	String Syntax version of the envelope level.						
<i>password</i>	String Recipient transmission reference password.						
<i>passwordQual</i>	String Recipient reference password qualifier.						
<i>applReference</i>	String Application reference.						
<i>priority</i>	String Processing priority code.						
<i>agreementID</i>	String Interchange agreement identifier.						
<i>unaSegmentRequired</i>	String Adds a UNA segment to the resulting final message.						
	<table> <thead> <tr> <th><u>Value</u></th> <th><u>Description</u></th> </tr> </thead> <tbody> <tr> <td>true</td> <td>Create UNA segment.</td> </tr> <tr> <td>false</td> <td>Do not create UNA segment.</td> </tr> </tbody> </table>	<u>Value</u>	<u>Description</u>	true	Create UNA segment.	false	Do not create UNA segment.
<u>Value</u>	<u>Description</u>						
true	Create UNA segment.						
false	Do not create UNA segment.						
<i>directoryVersionNumber</i>	String Type the directory version number in the UNB01/S00103 subfield of the EDIFACT envelope interchange header.						
<i>characterEncoding</i>	String Type the character encoding in the UNB01/S00104 subfield of the EDIFACT envelope interchange header.						
<i>syntaxReleaseNumber</i>	String Type the syntax release number in the UNB01/S00105 subfield of the EDIFACT envelope interchange header.						
<i>senderInternalId</i>	String Type the sender's internal ID in the UNB02/S00203 subfield of the EDIFACT envelope interchange header.						
<i>senderInternalSubId</i>	String Type the sender's internal sub ID in the UNB02/S00204 subfield of the EDIFACT envelope interchange header.						

<i>receiverInternalId</i>	String Type the receiver's internal ID in the UNB03/S00203 subfield of the EDIFACT envelope interchange header.
<i>receiverInternalSubId</i>	String Type the receiver's internal sub ID in the UNB03/S00204 subfield of the EDIFACT envelope interchange header.

Output Parameters

<i>ediMessage</i>	String Contains the <i>ediMessage</i> .
<i>statusCode</i>	String Status code based on success or failure.
<i>statusMessage</i>	String Status message after executing the operation.

convertDocumentToEDIMessage

Converts a document to an EDI message. When creating an orchestration with **ConvertDocumentToEDIMessage**, you must select the appropriate document type. This is for the structure of an *ediDocument* to appear in the pipeline data when you map with another *ediDocument* during orchestration.

Input Parameters

<i>ediDocument</i>	Document The <i>ediDocument</i> you want to convert to an EDI message.
<i>documentType</i>	Either Default or TRADACOMS .
<i>encoding</i>	String The type of encoding used to write a message to the output file. Default UTF-8
<i>delimiters</i>	Document Delimiters used in the outbound EDI document.

<u>Key</u>	<u>Description</u>
<i>segment</i>	String Segment terminator character to be appended at the end of each record in the output string.
<i>field</i>	String Field separator to be inserted between each field for each segment.

<i>subfield</i>	String Separator for composite elements.										
<i>release</i>	String Release character to use as the escape character for composite elements.										
<i>messageAlignment</i>	String Aligns the messages.										
	<table> <thead> <tr> <th><u>Value</u></th> <th><u>Description</u></th> </tr> </thead> <tbody> <tr> <td>left</td> <td>Left justify.</td> </tr> <tr> <td>right</td> <td>Right justify.</td> </tr> <tr> <td>none</td> <td>No justification.</td> </tr> <tr> <td></td> <td>Default</td> </tr> </tbody> </table>	<u>Value</u>	<u>Description</u>	left	Left justify.	right	Right justify.	none	No justification.		Default
<u>Value</u>	<u>Description</u>										
left	Left justify.										
right	Right justify.										
none	No justification.										
	Default										
<i>noEmptyTrailingFields</i>	String Indicates whether to remove empty trailing fields from the output.										
	<table> <thead> <tr> <th><u>Value</u></th> <th><u>Description</u></th> </tr> </thead> <tbody> <tr> <td>true</td> <td>Removes empty trailing fields from the output. For example, AAA*01*02! (where ! is the segment terminator).</td> </tr> <tr> <td>false</td> <td>This does not remove empty trailing fields. Instead it uses the field separator to denote an empty field. For example, AAA*01*02*****!(where * is the field separator and ! is the segment terminator).</td> </tr> </tbody> </table>	<u>Value</u>	<u>Description</u>	true	Removes empty trailing fields from the output. For example, AAA*01*02! (where ! is the segment terminator).	false	This does not remove empty trailing fields. Instead it uses the field separator to denote an empty field. For example, AAA*01*02*****!(where * is the field separator and ! is the segment terminator).				
<u>Value</u>	<u>Description</u>										
true	Removes empty trailing fields from the output. For example, AAA*01*02! (where ! is the segment terminator).										
false	This does not remove empty trailing fields. Instead it uses the field separator to denote an empty field. For example, AAA*01*02*****!(where * is the field separator and ! is the segment terminator).										

Output Parameters

<i>ediMessage</i>	String Contains the EDI message.
<i>errors[]</i>	String List Error messages describing the errors encountered during conversion. If there are no errors, then <i>error[]</i> is null.
<i>segmentCount</i>	String The number of segments in the <i>ediMessage</i> .
<i>statusCode</i>	String Status code based on success or failure.

statusMessage **String** Status message after executing the operation.

convertEDIMessageToDocument

Converts an EDI message that is stream or string into a document. When creating an orchestration with **ConvertEDIMessageToDocument**, you must select the appropriate document type. This is for the structure of an *ediDocument* to appear in the pipeline data when you map with another *ediDocument* during orchestration.

Input Parameters

ediMessage **String** The *ediMessage* you want to convert to a document.

edistream **InputStream** The *ediMessage* stream you want to convert to a document.

documentType Either **Default** or **TRADACOMS**

encoding **String** The encoding of the message passed into an *ediMessage* or *edistream*.

delimiters **Document** Delimiters to parse the input message. If no delimiters are specified, then the parameter uses the default delimiter defined for the flat file schema.

<u>Key</u>	<u>Description</u>
<i>segment</i>	String Segment terminator used in the input message.
<i>field</i>	String Field separator used in the input message.
<i>subfield</i>	String Subfield separator used in the input message.
<i>release</i>	String Release character used in the input message.

validate **String** Validates the *ediMessage*.

<u>Value</u>	<u>Description</u>
true	Return errors describing how the given <i>ediMessage</i> violates the constraints described in the flat file schema.

`false` Do not return error messages describing how the *ediMessage* differs from the specified flat file schema. This is the default value.

processOnlyTopLevelRecord **String** Processes the segments one at a time or process all input data at one time. Specify `true` or `false`.

<u>Value</u>	<u>Meaning</u>
<u><code>true</code></u>	Starts processing segment structures with a top-level record as defined by the flat file schema. The parameter returns to the caller when it encounters another top-level record in the input data.
<code>false</code>	Processes all input data at one time. This is the default value.

ignoreSpaces **String** Ignores white space from the beginning of the segments. Specify `true` or `false`.

<u>Value</u>	<u>Meaning</u>
<code>true</code>	Ignore white spaces. This is the default value.
<code>false</code>	Use the segments as they are. Specify <code>false</code> when the data contains positional data records.

repeatingFieldSeparator **String** Inserts field separator between repeating fields of an EDI document.

Output Parameters

ediDocument **Document** The Document representation of the input *ediMessage* .

isValid **String** Checks the validity of *ediMessage* .

<u>Value</u>	<u>Description</u>
<code>true</code>	<i>validate</i> input parameter was set to <code>true</code> and no errors were found.

	<code>false</code>	<i>validate</i> input parameter was set to <code>true</code> and errors were found, or the <i>validate</i> input parameter was set to <code>false</code> .
<i>errors[]</i>	Document List	The validation errors, if any, that were found in <i>edimessage</i> . Validation errors are returned in <i>errors</i> only if <i>validate</i> is set to <code>true</code> and <i>returnErrors</i> is set to <code>asArray</code> or <code>both</code> . The list includes the path of the errors.
<i>statusCode</i>	String	Status code based on success or failure.
<i>statusMessage</i>	String	Status message after executing the operation.

processEnvelope

Accepts and processes the envelope of an ANSI X12/UN/EDIFACT/UCS/VICS or EANCOM EDI message and converts the envelope header segments to a document. When creating an orchestration with **processEnvelope**, you must select the appropriate document type. This is for the structure of an *ediDocument* to appear in the pipeline data when you map with another *ediDocument* during orchestration.

Input Parameters

<i>ediMessage</i>	String	Processes the input EDI message. Input must not have manual line breaks.
<i>validate</i>	String	Whether to validate the envelopes against a predefined flat file schema.

<u>Value</u>	<u>Description</u>
<code>true</code>	Validate the envelopes against a predefined flat file schema.
<code>false</code>	Do not validate the envelope.

<i>complianceCheck</i>	String	Performs a compliance check against the interchange.
------------------------	---------------	--

<u>Value</u>	<u>Description</u>
<code>true</code>	Perform a compliance check. The parameter stops executing after encountering the first error. This is the default value.

`false` Do not perform the compliance check.

Output Parameters

ediEnvelopeDocument **Document** Resulting EDI envelope document.

standard **String** The standard to which the EDI document adheres. For example, X12 or UNEDIFACT.

hasError **String** Whether the validation or compliance check resulted in error.

Value	Description
<code>false</code>	If the <i>validate</i> is <code>true</code> , validation errors are retrieved from <i>errorArray</i> . Otherwise, it indicates errors from the compliance check.
<code>true</code>	No errors.

errors[] **Document List** Validation errors, if any, that were found in *edimessage*. Validation errors are returned in *errors* only if *validate* is set to `true` -AND- *returnErrors* is set to `asArray` or `both`. The list includes the path of the errors.

statusCode **String** Status code based on success or failure.

statusMessage **String** Status message after executing the operation.

File Transfer Protocol (FTP/FTPS)

Integration Cloud connects to an FTP server using the FTP protocol and provides operations to list, download, upload, and delete files. It also supports FTPS (FTP over SSL).

Note: FTP is not a secure file transfer protocol and it has security vulnerabilities. It does not provide any encryption for data transfer. It is recommended to use secured protocols such as HTTPS and FTPS for securing the data transmitted over the network.

Note: See this [“video”](#) on how to create an Account for an FTP Application and test the connection.

Field	Description
Host	Host name or IP address or the domain name of the FTP server.
Port	FTP port defined on the FTP server.
User	Valid user name on the FTP server.
Password	Password of the FTP user.
SSL Configuration - Select this option for secured FTP connection.	
Secure Data	Select True to secure the data channel. Select False if you do not want to secure the data channel.
Keystore Alias	Alias to the keystore that contains the private key used to connect to the host securely. You can also add a new Keystore from this field. Note: Users who have the Administer permission under Settings  > Access Profiles > Administrative Permissions > Functional Controls > Advanced Security can add, edit, and delete Keystores.
Key Alias	Alias to the key in the keystore that contains the private key used to connect to the host securely. The key must be in the keystore specified in the Keystore Alias field.
Truststore Alias	The alias for the truststore, which contains the trusted root of a certificate or signing authority (CA). You can also add a new Truststore from this field. Note: Users who have the Administer permission under Settings  > Access Profiles > Administrative Permissions > Functional Controls > Advanced Security can add, edit, and delete Truststores.

FTP Predefined Operations

The following predefined FTP operations are available:

getFile

Retrieves a file from a remote FTP server.

Input Parameters

<i>remoteFile</i>	String Name of the remote file.
<i>transferType</i>	String FTP file transfer mode (ASCII or binary). The default is ASCII.

Output Parameters

<i>contentStream</i>	Object A java.io.InputStream object.
<i>statusCode</i>	String Standard FTP protocol status code.
<i>statusMessage</i>	String Standard FTP protocol status message.

listFiles

Returns a list of file names in a specified remote directory. If path is not specified, the operation retrieves the file listing of the current remote directory. The operation also retrieves additional details such as permissions and ownership information.

Input Parameters

<i>remotePath</i>	String Optional. Absolute or relative path of the remote directory. If <i>remotepath</i> is not specified, the listFiles operation retrieves the directory listing of the current remote directory. You can use the wildcard characters asterisk (*) and question mark (?) after the last slash mark (/) to view all remote directories that match the specified path.
<i>listFilter</i>	String Optional. Filter that specifies the names of the files to include in the list (for example, *.txt).

Output Parameters

<i>fileList</i> []	String List List of file names matching <i>listFilter</i> .
<i>statusCode</i>	String Standard FTP protocol status code.
<i>statusMessage</i>	String Standard FTP protocol status message.

deleteFiles

Delete file(s) from a remote FTP server.

Input Parameters

<i>remotePath</i>	String Optional. Absolute or relative path of the remote directory. If <i>remotePath</i> is not specified, the <i>deleteFiles</i> operation deletes the directory listing of the current remote directory. You can use the wildcard characters asterisk (*) and question mark (?) after the last slash mark (/) to view all remote directories that match the specified path.
<i>deleteFilter</i>	String Optional. Filter that specifies the names of the files to be deleted (for example, *.txt).

Output Parameters

<i>filesDeleted</i> []	String List List of deleted files that match the <i>deleteFilter</i> .
<i>filesNotDeleted</i> []	String List List of files not deleted.
<i>statusCode</i>	String Standard FTP protocol status code.
<i>statusmsg</i>	String Standard FTP protocol status message.

putFile

Transfers a file to a remote FTP server.

Input Parameters

<i>remoteFile</i>	String The name of the remote file.
<i>transferType</i>	String FTP file transfer mode (<code>ascii</code> or <code>binary</code>). The default is <code>ascii</code> .
<i>writeOption</i>	String Optional. Indicates whether to send a <code>STOR</code> or a <code>STOU</code> (Store as Unique File) command to the remote FTP server. Set to: <ul style="list-style-type: none">■ <code>true</code> to send a <code>STOU</code> (Store as Unique File) command.■ <code>false</code> to send a <code>STOR</code> command. This is the default.
<i>contentStream</i>	java.io.InputStream, byte[], or String Data to be transferred to the remote file.

Output Parameters

<i>statusCode</i>	String Standard FTP protocol status code.
<i>statusMessage</i>	String Standard FTP protocol status message.

Usage Notes

Some FTP servers do not support “putting” a unique file. When using the `putFile` operation to put a unique file to an FTP server that does not support putting a unique file, you may encounter the following error:

```
com.wm.app.b2b.server.ServiceException: 500 'STOU': command not understood.
```

renameFile

Renames a file on a remote FTP server.

Input Parameters

<i>oldFileName</i>	String Fully qualified name of the file you want to rename (for example, <code>temp/oldfilename.txt</code>).
<i>newFileName</i>	String Fully qualified name of the new file (for example, <code>temp/newfilename.txt</code>).

Output Parameters

StatusCode **String** Standard FTP protocol status code.

StatusMessage **String** Standard FTP protocol status message.

Google Analytics

Integration Cloud connects to Google Analytics using the API for Management services. You can use Management services to retrieve, create, update, and delete analytics configuration data (accounts, metrics, dimensions, and custom data sources).

Integration Cloud also connects to Google Analytics using the API v4 for Core Reporting services. You can use Reporting services to generate customized reports based on dimensions, date range, and metrics.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: https://www.googleapis.com .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.

Field	Description
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Consumer ID	Also referred to as the Client ID, specify the Client ID you obtained from the Google Developer Console. This is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, specify the Client Secret you obtained from the Google Developer Console. This is a secret matching to the client identifier.
Access Token	Specify the access token you obtained from the OAuth Playground. This token is used for authentication and is issued by the Authorization Server.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token. Example: https://www.googleapis.com/oauth2/v4/token .
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Google Apps Admin

Integration Cloud connects to Google Apps Admin and supports the functionality to create and list users.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: <code>https://www.googleapis.com/admin</code> .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's

Field	Description
	identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Consumer ID	Also referred to as the Client ID, specify the Client ID you obtained from the Google Developer Console. This is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, specify the Client Secret you obtained from the Google Developer Console. This is a secret matching to the client identifier.
Access Token	Specify the access token you obtained from the OAuth Playground. This token is used for authentication and is issued by the Authorization Server.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token. Example: https://www.googleapis.com/oauth2/v4/token .
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Google BigQuery

Integration Cloud connects to Google BigQuery using the Google BigQuery API and allows you to create, update, and delete data sets and tables. You can also load, copy, extract, and query data from BigQuery's Bigtable.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: https://www.googleapis.com/admin .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Consumer ID	Also referred to as the Client ID, specify the Client ID you obtained from the Google Developer Console. This is a client identifier issued to the client to identify itself to the authorization server.

Field	Description
Consumer Secret	Also referred to as the Client Secret, specify the Client Secret you obtained from the Google Developer Console. This is a secret matching to the client identifier.
Access Token	Specify the access token you obtained from the OAuth Playground. This token is used for authentication and is issued by the Authorization Server.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token. Example: https://www.googleapis.com/oauth2/v4/token .
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Google Calendar

Integration Cloud connects to Google Calendar using Google Calendar APIs. It enables you to manage calendar data such as Secondary Calendars, Events, and Quick Event Add.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: https://www.googleapis.com/calendar/v3 .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes

Field	Description
	longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Consumer ID	Also referred to as the Client ID, specify the Client ID you obtained from the Google Developer Console. This is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, specify the Client Secret you obtained from the Google Developer Console. This is a secret matching to the client identifier.

Field	Description
Access Token	Specify the access token you obtained from the OAuth Playground. This token is used for authentication and is issued by the Authorization Server.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token. Example: https://www.googleapis.com/oauth2/v4/token
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Google Contacts

Integration Cloud connects to Google Contacts using Google Contacts APIs. It enables you to manage a user's contact list. The contacts are usually stored in the user's Google Account.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: https://www.google.com/m8/feeds .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.

Field	Description
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Consumer ID	Also referred to as the Client ID, specify the Client ID you obtained from the Google Developer Console. This is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, specify the Client Secret you obtained from the Google Developer Console. This is a secret matching to the client identifier.
Access Token	Specify the access token you obtained from the OAuth Playground. This token is used for authentication and is issued by the Authorization Server.

Field	Description
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token. Example: https://www.googleapis.com/oauth2/v4/token .
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Google Drive

Integration Cloud connects to Google Drive using the Google Drive API. It provides functionality of file storage and access to list, upload, and delete files.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: https://www.googleapis.com .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.

Field	Description
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Consumer ID	Also referred to as the Client ID, specify the Client ID you obtained from the Google Developer Console. This is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, specify the Client Secret you obtained from the Google Developer Console. This is a secret matching to the client identifier.
Access Token	Specify the access token you obtained from the OAuth Playground. This token is used for authentication and is issued by the Authorization Server.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token. Example: <code>https://www.googleapis.com/oauth2/v4/token</code> .

Field	Description
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.

SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.
------------------------	--

Google Cloud Pub/Sub

Integration Cloud connects to Google Cloud Pub/Sub and allows you to create, get, delete, set policy, and get policy on topics and subscription resources.

Field	Description
Server URL	Provide the login endpoint to initiate communication with Google Cloud Pub/Sub, for example, <code>https://pubsub.googleapis.com</code> .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> ,

Field	Description
	which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Consumer ID	Also referred to as the Client ID, specify the Client ID you obtained from the Google Developer Console. This is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, specify the Client Secret you obtained from the Google Developer Console. This is a secret matching to the client identifier.
Issuer	Applicable when you select the OAuth 2.0 JWT Token Flow as the Authentication Type. This is the Client ID, or Identifier, or name of the server or system issuing the JWT token.
Subject	Applicable when you select the OAuth 2.0 JWT Token Flow as the Authentication Type. This is the identifier or the name of the user this token represents.
Access Token	Specify the access token you obtained from the OAuth Playground. This token is used for authentication and is issued by the Authorization Server. Google Cloud Pub/Sub REST APIs use OAuth 2.0. The Access Token is passed when you invoke any of the REST API endpoints. The Access Token is valid for 1 hour. It is not affected by password changes. The client application is responsible for storing and protecting this token.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.

Field	Description
Refresh URL	This is the provider specific URL to refresh an Access Token. Example: https://www.googleapis.com/oauth2/v4/token .
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Google Cloud Storage

Integration Cloud connects to Google Cloud Storage using the Google Cloud Storage API and allows you to create and manage Buckets, Objects, and AccessControls.

Field	Description
Server URL	Provide the login endpoint to initiate communication with Google Cloud Storage. Example: https://www.googleapis.com .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.

Field	Description
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Consumer ID	Also referred to as the Client ID, specify the Client ID you obtained from the Google Developer Console. This is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, specify the Client Secret you obtained from the Google Developer Console. This is a secret matching to the client identifier.
Access Token	Specify the access token you obtained from the OAuth Playground. This token is used for authentication and is issued by the Authorization Server.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token. Example: <code>https://www.googleapis.com/oauth2/v4/token</code> .
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send

Field	Description
	the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Google Prediction

Integration Cloud connects to Google Prediction using the Google Prediction API. It includes the Hosted Model and Trained Model services that are used to predict data by using machine learning.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: <code>https://www.googleapis.com/prediction/v1.6</code> .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.

Field	Description
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Consumer ID	Also referred to as the Client ID, specify the Client ID you obtained from the Google Developer Console. This is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, specify the Client Secret you obtained from the Google Developer Console. This is a secret matching to the client identifier.
Access Token	Specify the access token you obtained from the OAuth Playground. This token is used for authentication and is issued by the Authorization Server.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token. Example: https://www.googleapis.com/oauth2/v4/token
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Google Sheets

Integration Cloud connects to Google Sheets and allows you to create, update, and get a spreadsheet, as well as append values to a spreadsheet.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: <code>https://sheets.googleapis.com</code> .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's

Field	Description
	identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Consumer ID	Also referred to as the Client ID, specify the Client ID you obtained from the Google Developer Console. This is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, specify the Client Secret you obtained from the Google Developer Console. This is a secret matching to the client identifier.
Access Token	Specify the access token you obtained from the OAuth Playground. This token is used for authentication and is issued by the Authorization Server.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token. Example: https://www.googleapis.com/oauth2/v4/token .
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

IBM Watson Tone Analyzer

Integration Cloud connects to IBM Watson Tone Analyzer using the REST interface to detect emotional, social, and language tones in written text. You can use the Application to learn the tone of your customer's communications and to respond to each customer appropriately, or to understand and improve customer conversations.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Username	IBM Bluemix Watson username.
Password	IBM Bluemix Watson password.
Authorization Type	The type of HTTP authorization scheme to use for the connection. If you select none , no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password, but do not specify a value for the Authorization Type, the user credentials are not inserted into an Authorization header. If you enter the username and password, then set the authorization type as basic . Basic refers to HTTP Basic Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password. Select the Authorization Type as basic .
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> ,

Field	Description
	which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Magento eCommerce Platform

Integration Cloud connects to Magento using the Magento REST API. You can use it to manage customers, customer addresses, sales orders, inventory, products, and so on, without having to directly work on Magento.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: <code>http://<yourhost>/api/rest</code> .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is

Field	Description
	recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is org.apache.http.conn.ssl.DefaultHostnameVerifier, which will enable hostname verification. Select org.apache.http.conn.ssl.NoopHostnameVerifier to disable hostname verification.
Consumer ID	Also referred to as the Client ID, this is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, this is a secret matching to the client identifier.
Access Token	This token is used for authentication and is issued by the Authorization Server.
Access Token Secret	A secret used by the Consumer to establish ownership of a given Access Token.

Field	Description
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Marketo

Integration Cloud connects to Marketo using the Marketo REST API and allows you to create, retrieve, and remove entities and data stored within Marketo.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. For example, the end point URL is of the format: <code>https://<instance>.mktoreset.com</code> . Replace <code><instance></code> with your actual Marketo instance.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.

Field	Description
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Consumer ID	Also referred to as the Client ID, this is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, this is a secret matching to the client identifier.
Access Token	This token is used for authentication and is issued by the Authorization Server.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host

Field	Description
	name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Microsoft Dynamics CRM

Integration Cloud connects to **Microsoft Dynamics CRM** using the Microsoft Dynamics CRM SOAP API. You can manage CRM data and access metadata that defines the specific CRM instance to which you are connecting.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. For example, the end point URL is of the format: <code>https://<organization>.api.crm.dynamics.com/XRMServices/2011/Organization.svc</code> , where <code><organization></code> must be replaced with your actual Microsoft Dynamics CRM organization.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Username	This is the user account name on the SaaS provider that the Account will use to connect to the SaaS provider. The Account will use this credential to connect to the SaaS provider.

Field	Description
Password	Provide a password for the user name to initiate communication with the SaaS provider.
Authorization Type	This is the type of HTTP authorization scheme to use for the connection. If you select none , no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password, but do not specify a value for the Authorization Type, the user credentials are not inserted into an Authorization header. If you enter the username and password, then set the authorization type as basic . Basic refers to HTTP Basic Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password.
Use Chunking	Enable this option if you want to send or receive a large binary stream with a chunk size of 8192 bytes. This is applicable only if the back end supports HTTP/1.1 chunking.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you

Field	Description
	must specify values in both the Keystore Alias and the Client Key Alias fields.

Microsoft Dynamics CRM 365

Integration Cloud connects to **Microsoft Dynamics CRM 365** using the OData API Version 4.0 and allows you to manage CRM data and access metadata that defines the specific CRM instance to which you are connecting. This Application performs standard CRUD operations on business objects by connecting to the OData service endpoint.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. For example, for Microsoft Dynamics CRM 365, the end point URL is the OData service endpoint.
Consumer ID	Also referred to as the Client ID, this is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, this is a secret matching to the client identifier.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token.
Access Token	This token is used for authentication and is issued by the Authorization Server.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial

Field	Description
	attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Use Chunking	Enable this option if you want to send or receive a large binary stream with a chunk size of 8192 bytes. This is applicable only if the back end supports HTTP/1.1 chunking.
Caching	Select this option if you want the Application to cache the back end metadata. Caching of the metadata significantly increases the performance of a request sent. By default, the cache will be refreshed every 12 hours. It is recommended to enable the cache to increase the performance.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you

Field	Description
	must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

OData v2.0

Integration Cloud connects to any cloud application that exposes its services using the OData Version 2.0 Specification. It supports only those OData providers, which strictly adhere to the OData Version 2.0 Specification and allows you to perform standard CRUD operations on business objects by connecting to the OData service endpoint.

Field	Description
Server URL	This is the OData service endpoint to initiate communication with the OData provider.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.

Field	Description
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Username	This is the user account name on the OData provider that the Account will use to connect to the OData provider.
Password	Provide the password for the user name provided in the Username field.
Authorization Type	The type of HTTP authorization scheme to use for the connection. If you select none , no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password , and also select none , you do not specify a value for the Authorization Type , so the user credentials are not inserted into an Authorization header. If you enter the Username and Password , then set the authorization type as basic . Basic refers to HTTP Basic Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password. If you enter the username and password, then set the authorization type as basic .
Caching	Select this option if you want the OData v2.0 Application to cache the backend metadata. Caching of the metadata significantly increases the performance of a request sent. By default, the cache will be refreshed every 12 hours. It is recommended to enable the cache to increase the performance.
Use Chunking	Enable this option if you want to send or receive a large binary stream with a chunk size of 8192 bytes. This is applicable only if the back end supports HTTP/1.1 chunking.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.

Field	Description
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

OData v4.0

Integration Cloud connects to any cloud application that exposes its services using the OData Version 4.0 Specification. It supports only those OData providers, which strictly adhere to the OData Version 4.0 Specification and allows you to perform standard CRUD operations on business objects by connecting to the OData service endpoint.

Field	Description
Server URL	This is the OData service endpoint to initiate communication with the OData provider.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.

Field	Description
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Caching	Select this option if you want the OData v4.0 Application to cache the back end metadata. Caching of the metadata significantly increases the performance of a request sent. By default, the cache will be refreshed every 12 hours. It is recommended to enable the cache to increase the performance.
Consumer ID	Also referred to as the Client ID, this is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, this is a secret matching to the client identifier.
Access Token	This token is used for authentication and is issued by the Authorization Server.

Field	Description
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token.
Use Chunking	Enable this option if you want to send or receive a large binary stream with a chunk size of 8192 bytes. This is applicable only if the back end supports HTTP/1.1 chunking.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Salesforce

Salesforce Bulk Data Loader

Integration Cloud connects to Salesforce using the Salesforce Bulk API and supports Job and Batch resources. You can use it to create, update, delete, query jobs and batches, and operate on large number of records asynchronously by submitting batches which are processed in the background by Salesforce.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: <code>https://login.salesforce.com/services/Soap/u/31.0</code> .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a

Field	Description
	value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Username	This is the user account name on the SaaS provider that the Account will use to connect to the SaaS provider.
Password	The password for the user name provided in the Username field. When you access Salesforce from outside your company's trusted networks, you must append a security token (provided by Salesforce) to your password. Your security token may have been emailed to you when you had set up your Salesforce account or if you had reset your password. For example, if your password is <i>abc</i> and your security token is <i>xxxx</i> , then you must enter <i>abcxxxx</i> . For more information about logging in to Salesforce, see the Salesforce documentation.
Authorization Type	The type of HTTP authorization scheme to use for the connection. If you select none , no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password, but do not specify a value for the Authorization Type, the user credentials are not inserted into an Authorization header. If you enter the username and password, then set the authorization type as basic . Basic refers to HTTP Basic Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password.
Session Timeout (min)	The number of minutes you want Integration Cloud to wait before terminating an idle session. The session

Field	Description
	timeout value must be within the range of 10 and 60 minutes.
Use Chunking	Enable this option if you want to send or receive a large binary stream with a chunk size of 8192 bytes. This is applicable only if the back end supports HTTP/1.1 chunking.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable Connection Pooling	Select this option if you want to enable connection pooling for a connection. Integration Cloud includes a connection management service that dynamically manages connections and connection pools based on configuration settings that you specify for the connection. A connection pool is a collection of connections with the same set of attributes. Connection pools improve performance by enabling Integrations to reuse open connections

Field	Description
	<p>instead of opening new connections for every service request.</p> <p>When you enable connection pooling, Integration Cloud creates the number of connection instances you specified in the connection's Minimum Pool Size field. Whenever an Integration needs a connection, Integration Cloud provides a connection from the pool. If no connections are available in the pool, and the Maximum Pool Size has not been reached, Integration Cloud creates one or more new connections (according to the number specified in the Pool Increment Size field) and adds them to the connection pool.</p> <p>If the pool is full (as specified in the Maximum Pool Size field), the requesting service will wait for Integration Cloud to obtain a connection till one sec, until a connection becomes available. Periodically, Integration Cloud inspects the pool and removes inactive connections that have exceeded the expiration period of one sec.</p>
Minimum Pool Size	The minimum number of connection objects that remain in the connection pool at all times, if connection pooling is enabled. When the connector creates the pool, it creates this number of connections.
Maximum Pool Size	The maximum number of connection objects that can exist in the connection pool if connection pooling is enabled. When the connection pool has reached its maximum number of connections, the connector will reuse any inactive connections in the pool, or, if all connections are active, it will wait for a connection to become available.
Pool Increment Size	The number of connections by which the pool will be incremented, up to the maximum pool size, if connection pooling is enabled and connections are needed.

Salesforce CRM

Integration Cloud connects to Salesforce using the Partner SOAP API. It supports all business objects (for example, Account) and operations including any customizations done on the Salesforce instance. It also supports Salesforce analytics using wave.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: <code>https://login.salesforce.com/services/Soap/u/44.0</code> .
Username	This is the user account name on the SaaS provider that the Account will use to connect to the SaaS provider.
Password	The password for the user name provided in the Username field. When you access Salesforce from outside your company's trusted networks, you must append a security token (provided by Salesforce) to your password. Your security token may have been emailed to you when you had set up your Salesforce account or if you had reset your password. For example, if your password is <i>abc</i> and your security token is <i>xxxx</i> , then you must enter <i>abcxxxx</i> . For more information about logging in to Salesforce, see the Salesforce documentation.
Authorization Type	The type of HTTP authorization scheme to use for the connection. If you select none , no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password, but do not specify a value for the Authorization Type, the user credentials are not inserted into an Authorization header. If you enter the username and password, then set the authorization type as basic . Basic refers to HTTP Basic Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password.
Session Timeout (min)	The number of minutes you want Integration Cloud to wait before terminating an idle session. The session timeout value must be within the range of 10 and 60 minutes.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you

Field	Description
	specify 0, Integration Cloud will wait indefinitely for a response.
Connection TimeOut	The number of milliseconds a connection waits before canceling its attempt to connect to the resource. If you specify 0, the connection waits indefinitely. It is recommended that you specify a value other than 0 to avoid using a socket with no timeout.
Connection Retry Count	<p>The number of times the system should attempt to initialize the connection at startup if the initial attempt fails.</p> <p>The system retries to establish a connection when an I/O error occurs while sending the request message to the back end. If an I/O exception occurs when the system is reading a response back from the back end, the system will only retry if Retry on Response Failure is enabled.</p>
Issuer	Applicable when you select the Salesforce OAuth 2.0 JWT Token Flow as the Authentication Type. This is the Client ID, or Identifier, or name of the server or system issuing the JWT token.
Subject	Applicable when you select the Salesforce OAuth 2.0 JWT Token Flow as the Authentication Type. This is the identifier or the name of the user this token represents.
Consumer ID	Applicable when you select the Salesforce Web Server Authentication Flow as the Authentication Type. Also referred to as the Client ID, this is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Applicable when you select the Salesforce Web Server Authentication Flow as the Authentication Type. Also referred to as the Client Secret, this is a secret matching to the client identifier.
Access Token	Applicable when you select the Salesforce Web Server Authentication Flow as the Authentication Type. This

<u>Field</u>	<u>Description</u>
	token is used for authentication and is issued by the Authorization Server.
Refresh Token	Applicable when you select the Salesforce Web Server Authentication Flow as the Authentication Type. A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	Applicable when you select the Salesforce Web Server Authentication Flow as the Authentication Type. This is the provider specific URL to refresh an Access Token.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.

Field	Description
Hostname verifier	<p>Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code>, which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.</p>
Use Chunking	<p>Enable this option if you want to send or receive a large binary stream with a chunk size of 8192 bytes. This is applicable only if the back end supports HTTP/1.1 chunking.</p>
Enable SNI	<p>Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.</p>
SNI Server Name	<p>If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.</p>
Enable Connection Pooling	<p>Select this option if you want to enable connection pooling for a connection.</p> <p>Integration Cloud includes a connection management service that dynamically manages connections and connection pools based on configuration settings that you specify for the connection. A connection pool is a collection of connections with the same set of attributes. Connection pools improve performance by enabling Integrations to reuse open connections instead of opening new connections for every service request.</p> <p>When you enable connection pooling, Integration Cloud creates the number of connection instances you specified in the connection's Minimum</p>

Field	Description
	<p>Pool Size field. Whenever an Integration needs a connection, Integration Cloud provides a connection from the pool. If no connections are available in the pool, and the Maximum Pool Size has not been reached, Integration Cloud creates one or more new connections (according to the number specified in the Pool Increment Size field) and adds them to the connection pool.</p> <p>If the pool is full (as specified in the Maximum Pool Size field), the requesting service will wait for Integration Cloud to obtain a connection till one sec, until a connection becomes available. Periodically, Integration Cloud inspects the pool and removes inactive connections that have exceeded the expiration period of one sec.</p>
Minimum Pool Size	<p>The minimum number of connection objects that remain in the connection pool at all times, if connection pooling is enabled. When the connector creates the pool, it creates this number of connections.</p>
Maximum Pool Size	<p>The maximum number of connection objects that can exist in the connection pool if connection pooling is enabled. When the connection pool has reached its maximum number of connections, the connector will reuse any inactive connections in the pool, or, if all connections are active, it will wait for a connection to become available.</p>
Pool Increment Size	<p>The number of connections by which the pool will be incremented, up to the maximum pool size, if connection pooling is enabled and connections are needed.</p>

Salesforce® Bulk v2 Data Loader

Using the Bulk API 2.0, Salesforce supports Job resource, and allows you to create, update, delete, upsert jobs, and operate on large number of records asynchronously by submitting jobs which are processed in the background.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. For example, <code>https://<instance>.salesforce.com</code> . Replace <code><instance></code> with your actual Salesforce instance.
Consumer ID	Also referred to as the Client ID, this is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, this is a secret matching to the client identifier.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token, for example, <code>https://<instance>.salesforce.com/services/oauth2/token</code> .
Access Token	This token is used for authentication and is issued by the Authorization Server.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Session Timeout (min)	The number of minutes you want Integration Cloud to wait before terminating an idle session. The session

Field	Description
	timeout value must be within the range of 10 and 60 minutes.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Salesforce® CRM REST

Integration Cloud connects to Salesforce® CRM REST using the REST API and allows you to manage security for inbound requests, log payloads and specify run-time performance conditions for consumers for outbound requests. It also supports multiple authentication mechanisms.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. For example, <code>https://<instance>.salesforce.com</code> . Replace <code><instance></code> with your actual Salesforce instance.
Consumer ID	Also referred to as the Client ID, this is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, this is a secret matching to the client identifier.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token, for example, <code>https://login.salesforce.com/services/oauth2/token</code> .
Access Token	This token is used for authentication and is issued by the Authorization Server. Salesforce REST APIs use OAuth 2.0. The access token is passed when you invoke any of the REST API endpoints and is valid for one hour. It is not affected by password changes. The client application is responsible for storing and protecting this token. You can manage the Salesforce REST connection by enabling the connection pool and session management.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a

Field	Description
	value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Session Timeout (min)	The number of minutes you want Integration Cloud to wait before terminating an idle session. The session timeout value must be within the range of 10 and 60 minutes.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Enable Connection Pooling	<p>Select this option if you want to enable connection pooling for a connection.</p> <p>Integration Cloud includes a connection management service that dynamically manages connections and connection pools based on configuration settings that you specify for the connection. A connection pool is a collection of connections with the same set of attributes. Connection pools improve performance by enabling Integrations to reuse open connections instead of opening new connections for every service request.</p> <p>When you enable connection pooling, Integration Cloud creates the number of connection instances you specified in the connection's Minimum Pool Size field. Whenever an Integration needs a connection, Integration Cloud provides a connection from the pool. If no connections are available in the pool, and the Maximum Pool Size has not been reached, Integration Cloud creates one or more new connections (according</p>

Field	Description
	<p>to the number specified in the Pool Increment Size field) and adds them to the connection pool.</p> <p>If the pool is full (as specified in the Maximum Pool Size field), the requesting service will wait for Integration Cloud to obtain a connection till one sec, until a connection becomes available. Periodically, Integration Cloud inspects the pool and removes inactive connections that have exceeded the expiration period of one sec.</p>
Minimum Pool Size	The minimum number of connection objects that remain in the connection pool at all times, if connection pooling is enabled. When the connector creates the pool, it creates this number of connections.
Maximum Pool Size	The maximum number of connection objects that can exist in the connection pool if connection pooling is enabled. When the connection pool has reached its maximum number of connections, the connector will reuse any inactive connections in the pool, or, if all connections are active, it will wait for a connection to become available.
Pool Increment Size	The number of connections by which the pool will be incremented, up to the maximum pool size, if connection pooling is enabled and connections are needed.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server.

Field	Description
	To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Connection Timeout	The number of milliseconds a connection waits before canceling its attempt to connect to the resource. If you specify 0, the connection waits indefinitely. It is recommended that you specify a value other than 0 to avoid using a socket with no timeout.
Connection Retry Count	<p>The number of times the system should attempt to initialize the connection at startup if the initial attempt fails.</p> <p>The system retries to establish a connection when an I/O error occurs while sending the request message to the back end. If an I/O exception occurs when the system is reading a response back from the back end, the system will only retry if Retry on Response Failure is enabled.</p>
Issuer	Applicable when you select the Salesforce OAuth 2.0 JWT Token Flow as the Authentication Type. This is the Client ID, or Identifier, or name of the server or system issuing the JWT token.
Subject	Applicable when you select the Salesforce OAuth 2.0 JWT Token Flow as the Authentication Type. This is the identifier or the name of the user this token represents.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

SAP Cloud for Customer(C4C) OData v2.0

Integration Cloud connects to SAP Cloud for Customer (C4C) including SAP Cloud for Sales, SAP Cloud for Service, and SAP Cloud for Social Engagement solutions using the REST interface, and allows you to do standard CRUD operations on business objects by connecting to the OData Service endpoint.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. This is the OData service endpoint to initiate communication with the SAP C4C OData provider.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Username	This is the user account name on the SAP C4C OData provider that the Account will use to connect to the SaaS provider. The Account will use this credential to connect to the SaaS provider.
Password	Provide the password for the user name provided in the Username field to initiate communication with the SaaS provider.
Authorization Type	The type of HTTP authorization scheme to use for the connection. If you select none , no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password , and also select none , you do not specify a value for the Authorization Type , so the user credentials are not inserted into an Authorization header. If you enter the Username and Password , then set the authorization type as basic . Basic refers to HTTP Basic Authentication. This option can be used if the Application requires

Field	Description
	or supports HTTP Basic authentication using a username and password.
Metadata Caching	Select this option if you want the SAP C4C Application to cache the backend metadata. Caching of the metadata significantly increases the performance of a request sent through SAP C4C. If this option is selected, the cache will be refreshed every 12 hours. It is recommended to enable the metadata cache to increase the performance.
Use CSRF Token	To prevent cross site request forgery, SAP C4C protects its resources by using a CSRF token. Select this option if you want Integration Cloud to use the CSRF token key, received in the response from SAP C4C, to perform any state changing requests on SAP C4C. By default, the CSRF token is enabled by the SAP C4C back end. You must enable this option particularly when the entity state changing operation is invoked.
Use Chunking	Enable this option if you want to send or receive a large binary stream with a chunk size of 8192 bytes. This is applicable only if the back end supports HTTP/1.1 chunking.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's

Field	Description
	identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

SAP S/4HANA Marketing Cloud

Integration Cloud connects to SAP S/4HANA Marketing Cloud using the OData based REST interface, which allows you to do only bulk imports. You can create or update Interaction Contacts, Interactions, Interests, Corporate Accounts, Product Categories, Products, and so on.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. This is the OData service endpoint to initiate communication with the SAP S/4HANA Marketing Cloud provider.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.

Field	Description
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Username	This is the user account name on the SAP S/4HANA Marketing Cloud provider that the Account will use to connect to the SaaS provider. The Account will use this credential to connect to the SaaS provider.
Password	Provide the password for the user name provided in the Username field to initiate communication with the SaaS provider.
Authorization Type	The type of HTTP authorization scheme to use for the connection. If you select none , no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password , and also select none , you do not specify a value for the Authorization Type , so the user credentials are not inserted into an Authorization header. If you enter the Username and Password , then set the authorization type as basic . Basic refers to HTTP Basic Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password.
Metadata Caching	Select this option if you want the SAP S/4HANA Marketing Cloud Application to cache the back end metadata. Caching of the metadata significantly increases the performance of a request sent through SAP S/4HANA Marketing Cloud. If this option is selected, the cache will be refreshed every 12 hours. It is recommended to enable the metadata cache to increase the performance.
Validate Metadata	Whether to validate the \$metadata xml during edm object creation. Select this option to enable the metadata validation.
Use CSRF Token	To prevent cross site request forgery, SAP S/4HANA Marketing Cloud protects its resources by using a CSRF token. Select this option if you want Integration Cloud to use the CSRF token key, received in the response from SAP S/4HANA Marketing Cloud, to perform any state changing requests on SAP S/4HANA Marketing Cloud. By default, the CSRF token is enabled by the SAP S/4HANA Marketing Cloud back end. You must enable this option particularly when the entity state changing operation is invoked.

Field	Description
Use Chunking	Enable this option if you want to send or receive a large binary stream with a chunk size of 8192 bytes. This is applicable only if the back end supports HTTP/1.1 chunking.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Secure File Transfer Protocol (SFTP)

The SSH File Transfer Protocol (SFTP) is a network protocol that is based on the Secure Shell protocol (SSH). SFTP facilitates secure file access, file transfer, and file management over any reliable data stream. The Secure File Transfer Protocol (SFTP) Application downloads files from or uploads files to an SFTP-enabled server using the secure file transport channel.

Integration Cloud connects to an SFTP server using the SSH File Transfer Protocol (SFTP) and provides operations to retrieve, transfer, rename, and delete files or directories in the SFTP server. You can also change the permission or ownership of files in the SFTP server.

You can configure Integration Cloud to connect to an SFTP server to perform the following tasks using the SFTP protocol:

- Transfer files between Integration Cloud and the SFTP server. You can get a file from the SFTP server or upload a file to the SFTP server.
- Access files in the SFTP server. You can view the directories and files in the SFTP server and also view their permissions and ownership information.
- Manage directories or files in the SFTP server. You can create, rename, or delete files or directories in the SFTP server. You can also change the permissions or ownership of files in the SFTP server.

For this parameter...	Specify...
Host Name or IP Address	The host name or IP address of the SFTP server.
Port Number	The port number of the SFTP server. The port number must be within the range of 1 and 65535 (inclusive).
Host Public Key	The public key of the SFTP server. Select Auto Retrieve if you want Integration Cloud to automatically retrieve the public key of the SFTP server. Select Upload if you have the public key of the SFTP server. Integration Cloud will use the uploaded public key.
Finger Print	The host public key fingerprint of the SFTP server.
	<p>Note: This field is visible only after you have established a connection to an SFTP server.</p>

Before establishing a connection, the SFTP server sends an encrypted fingerprint of its host public keys to ensure that the SFTP connection will be exchanging data with

<u>For this parameter...</u>	<u>Specify...</u>
	the correct server. Save the fingerprint information locally. This enables you to check the fingerprint information against the data you have saved every time you establish a new connection.
User Name	The user name for the SFTP user account.
Authentication Type	The type of authentication Integration Cloud uses to authenticate itself to the SFTP server. Client authentication can be either by password or by public and private keys. Select Password if you want to use password authentication. If you are using password authentication, enter the password for the specified user to connect to the SFTP server. Select Public Key if you want to authenticate Integration Cloud by using public and private keys. To use this authentication type, the SFTP server and Integration Cloud must each have access to their own private key and each other's public key.
Private Key	If you selected Public Key as the authentication type, select the private key file of the specified SFTP user.
PassPhrase	If you selected Public Key as the authentication type and if the private key you specified requires a passphrase, enter the passphrase for the private key file of the specified user.
Advanced Options	
Maximum Retries	The number of times Integration Cloud attempts to connect to the SFTP server. The maximum allowed value is 6. The minimum allowed value is 1.
Response Timeout	The amount of time (measured in seconds) Integration Cloud waits for a response from the SFTP server before timing out and terminating the request. A value of 0 indicates that the session will never time out. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value.
Session Timeout	The number of minutes you want Integration Cloud to wait before terminating an idle session. The session timeout value must be within the range of 10 and 60 minutes.

For this parameter...	Specify...
Preferred Key Exchange Algorithms	The algorithms that Integration Cloud presents to the SFTP server for key exchange. You can specify the order in which Integration Cloud presents the algorithms to the SFTP server by moving the available algorithms up or down by clicking Move Up or Move Down . The SFTP server has its own set of preferred algorithms configured. At the time of key exchange, one of the algorithms supported by both Integration Cloud and the SFTP server will be chosen.
Compression	Whether or not to compress the data to reduce the amount of data that is transmitted. Integration Cloud supports compression using the compression algorithm zlib . You can use compression only if the SFTP server that you are connecting to supports compression. Select None if you do not want to compress the data. Select zlib if you want to compress the data that is transmitted between the SFTP server and Integration Cloud.
Compression Level	The compression level to use if you selected the compression algorithm zlib in the Compression field. The minimum allowed value is 1 (fast, less compression) and the maximum allowed value is 9 (slow, most compression).

SFTP Predefined Operations

The following predefined SFTP operations are available:

cd

Changes the working directory on the remote SFTP server.

Input Parameters

path **String** Absolute or relative path of the directory that you want as the working directory on the remote SFTP server.

Output Parameters

returnCode **String** Standard SFTP protocol return code.

returnMsg **String** Text message describing the return code.

chgrp

Changes the group ownership of one or more remote files.

Input Parameters

groupId **String** Numeric group identifier of the group to which you want to transfer ownership of the remote files.

path **String** Absolute or relative path of the remote files.

Output Parameters

returnCode **String** Standard SFTP protocol return code.

returnMsg **String** Text message describing the return code.

chmod

Changes permissions of one or more remote files.

Input Parameters

mode **String** The permission mode to apply to the remote file (for example, *777*).

path **String** Absolute or relative path of the remote files.

Output Parameters

returnCode **String** Standard SFTP protocol return code.

returnMsg **String** Text message describing the return code.

chown

Changes the owning user of one or more remote files.

Input Parameters

uid **String** Numeric user ID of the new owning user of the file.

path **String** Absolute or relative path of the remote files.

Output Parameters

returnCode **String** Standard SFTP protocol return code.

returnMsg **String** Text message describing the return code.

get

Retrieves a file from a remote SFTP server.

Input Parameters

remoteFile **String** Absolute or relative path of the remote file.

Output Parameters

returnCode **String** Standard SFTP protocol return code.

returnMsg **String** Text message describing the return code.

contentStream **Object** A java.io.InputStream object.

ls

Retrieves the remote directory listing of the specified path. If path is not specified, the ls service retrieves the file listing of the current remote directory. The ls service also retrieves additional details such as permissions and ownership information.

Input Parameters

path **String** Optional. Absolute or relative path of the remote directory. If no *path* is specified, the *ls* service retrieves the directory listing of the current remote directory.

You can use the wildcard characters asterisk (*) and question mark (?) after the last slash mark (/) to view all remote directories that match the specified path.

Output Parameters

returnCode **String** Standard SFTP protocol return code.

returnMsg **String** Text message describing the return code.

dirList **Document** List of directories matching the pattern specified in the *path* parameter. This document has the following parameters:

fileName: **String** Specifies the name of the remote file. .

fileSize: **String** Specifies the size of the remote file.

permissions: **String** Specifies the access permission of the file (read, write, or execute).

lastAccessTime: **String** Specifies the time when the file was last accessed.

lastModifiedTime: **String** Specifies the time when the file was last modified.

uid: **String** Specifies the user ID of the file owner.

gid: **String** Specifies the group ID associated with the file.

longName: **String** Specifies the long name of the *ls* entry. It contains all the parameters separated by a space.

mkdir

Creates a new remote directory.

Input Parameters

path **String** Absolute or relative path of the remote directory where you want to create a new directory.

Output Parameters

returnCode **String** Standard SFTP protocol return code.

returnMsg **String** Text message describing the return code.

put

Transfers a file to a remote SFTP server.

Input Parameters

contentStream **java.io.InputStream** Data to be transferred to the remote file.

remoteFile **String** Absolute or relative path of the remote file to which the *contentStream* would be written based on the *mode* .

mode **String** Optional. Specifies how the local file is to be transferred to the remote SFTP server. Set to:

- `overwrite` to overwrite the contents of the remote file with the contents of the *contentStream* . This is the default.
- `append` to append the entire contents of the *contentStream* to the remote file.
- `resume` to resume writing the contents of the *contentStream* to the remote file from the point the writing was stopped during previous SFTP sessions.

Output Parameters

returnCode **String** Standard SFTP protocol return code.

returnMsg **String** Text message describing the return code.

pwd

Displays the remote working directory in the SFTP server.

Input Parameters

None.

Output Parameters

<i>returnCode</i>	String Standard SFTP protocol return code.
<i>returnMsg</i>	String Text message describing the return code.
<i>path</i>	String Absolute or relative path of the working directory on the remote SFTP server.

rename

Renames a file or directory on a remote SFTP server.

Input Parameters

<i>oldPath</i>	String Fully qualified name of the file you want to rename (for example, <code>temp/oldname.txt</code>).
<i>newPath</i>	String New fully qualified name for the file (for example, <code>temp/newname.txt</code>).

Output Parameters

<i>returnCode</i>	String Standard SFTP protocol return code.
<i>returnMsg</i>	String Text message describing the return code.

rm

Deletes one or more remote files on the SFTP server.

Input Parameters

path **String** Absolute or relative path of the file you want to delete.

Output Parameters

returnCode **String** Standard SFTP protocol return code.

returnMsg **String** Text message describing the return code.

rmdir

Deletes one or more remote directories on the SFTP server.

Input Parameters

path **String** Absolute or relative path of the directory you want to delete.

Output Parameters

returnCode **String** Standard SFTP protocol return code.

returnMsg **String** Text message describing the return code.

Usage Notes

The remote directories that you want to delete must be empty.

symlink

Creates a symbolic link between the old path and the new path of a file.

Input Parameters

oldPath **String** Old path of the file for which you want to create a symbolic link.

newPath **String** New path of the file to which the symbolic link should point.

Output Parameters

returnCode **String** Standard SFTP protocol return code.

returnMsg **String** Text message describing the return code.

ServiceNow Enterprise Service Management

Integration Cloud connects to different areas (Incident, Problem, and Change management) of ServiceNow using the Geneva version of the ServiceNow API. You can create incidents, get details of created incidents, and update and delete them. Similar operations are available for problem and change management cloud applications.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: <code>https://<instance_name>.service-now.com</code> , where <code><instance_name></code> represents the actual instance name.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Username	This is the user account name on the SaaS provider that the Account will use to connect to the SaaS provider.
Password	Provide a password for the user name provided in the Username field to initiate communication with the SaaS provider.

Field	Description
Authorization Type	The type of HTTP authorization scheme to use for the connection. If you select none , no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password, but do not specify a value for the Authorization Type, the user credentials are not inserted into an Authorization header. If you enter the username and password, then set the authorization type as basic . Basic refers to HTTP Basic Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.

Field	Description
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Shopify

Integration Cloud connects to Shopify using the Shopify REST API and allows you to organize your products, customize your storefront, accept credit card payments, track, and respond to orders.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. For example, the end point URL is of the format: <code>https://<my-store>.myshopify.com</code> . Replace <code><my-store></code> with your actual Shopify store.
Shopify Access Token	This token is used for authentication and is issued by the Authorization Server. The Access Token is passed when you invoke any of the REST API endpoints. Shopify REST APIs authentication requests require a unique API key generated in Shopify. All API requests must pass an <code>X-Shopify-Access-Token</code> header with an API key.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.

Field	Description
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Siemens MindSphere

Integration Cloud connects to Siemens MindSphere using the API version 2.0 and allows you to create aspects and post data into a MindSphere asset.

Note: The fields displayed may vary according to the version of the Application.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the

Field	Description
	SaaS provider. For example, https://mindconnectcom.apps.mindsphere.io/
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is

Field	Description
	org.apache.http.conn.ssl.DefaultHostnameVerifier, which will enable hostname verification. Select org.apache.http.conn.ssl.NoopHostnameVerifier to disable hostname verification.
MSU Limit	MindSphere Unit (MSU) limit for an asset. MSU is the basis for fees invoiced monthly per asset and as per a used application.
Security Profile	The type of security profile/algorithm used for token generation. Default is SHARED_SECRET.
Agent Id	The ID of the agent managing a MindSphere asset.
Schemas	Schemas used by the MindSphere platform. Default is urn:siemens:mindsphere:v1.
IAT	Initial access token for agent onboarding.
Tenant	The tenant ID of the onboarded agent.
Links	Links returned upon successful agent onboarding.
JWT Signing Algorithm	The JSON Web Token (JWT) signing algorithm. Default is HS256 (HMAC with SHA 256).
JWT Token Expiration (msec)	The JWT token expiration time in milliseconds. Default is 600000.
JWT Audience	The JWT Audience. Default is MindSphere AS.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect

Field	Description
	to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Simple Mail Transfer Protocol (SMTP)

Integration Cloud allows you to connect to an SMTP server using the Simple Mail Transfer Protocol (SMTP). This Application provides the [“sendEmail” on page 280](#) predefined operation to send emails to specified recipients. You can attach one or more files to the message.

Field	Description
Host	Host name or IP address or the domain name of the SMTP server.
Port	SMTP port defined on the SMTP server. This is the number of the port on which the SMTP host listens.
User	Valid user name on the SMTP server. This is the user name used to connect with the mail server.
Password	Password of the SMTP user. This is the password to connect with the mail server.
From	The email address of the sender, that is, the person that is going to send the messages.
To	E-mail address of the receiver. If you specify multiple addresses, separate them with commas without any spaces.

Field	Description
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the SMTP server. In case the network is slow or the SMTP server processing takes longer than usual, increase this value.
Read Timeout	The number of milliseconds in which Integration Cloud must read a response message from the SMTP server.
Write Timeout	Socket write timeout value in milliseconds.
SSL configuration details	<p data-bbox="771 875 1333 974">Type of security protocol Integration Cloud uses when communicating with the SMTP server port. Set to:</p> <ul data-bbox="771 1001 1349 1514" style="list-style-type: none"> <li data-bbox="771 1001 1292 1100">■ none to use a non-secure mode when communicating with the port on the SMTP server. This is the default. <li data-bbox="771 1121 1349 1325">■ explicit to use explicit security when communicating with the port on the SMTP server. With explicit security, Integration Cloud establishes an un-encrypted connection to the email server, and then switches to the secure mode. <li data-bbox="771 1346 1349 1514">■ implicit to use implicit security when communicating with the port on the SMTP server. With implicit security, Integration Cloud always establishes an encrypted connection to the email server.
Truststore Alias	This is the alias for the truststore that contains the list of certificates that Integration Cloud uses to validate the trust relationship. Integration Cloud uses the default truststore if you do not specify a truststore alias. You can add a new truststore from this field.

Note Users who have the **Administer** permission under **Settings**  **> Access**

Field	Description
	Profiles > Administrative Permissions > Functional Controls > Advanced Security can add, edit, and delete truststores.

Using the SMTP Application to send emails

Summary


In this tutorial, we will create an integration that queries Salesforce accounts and create opportunities in Marketo, and then sends an email containing the total number of records queried from Salesforce and inserted into Marketo.

Before you begin

- A valid Gmail account as we will use the Gmail SMTP server to send emails.

Using the SMTP Application to send emails

1. Log in to Integration Cloud.
2. Click **Projects > Select a Project > Applications > Predefined Applications > Simple Mail Transfer Protocol (SMTP)**.
3. Click **Add New Account**.



4. Configure the Gmail SMTP settings as shown below. For information on the Account Configuration fields, see “[Simple Mail Transfer Protocol \(SMTP\)](#)” on page 272.

Note: You can specify the **From** and **To** addresses either at the Account level here or while executing the operation. If you provide them at both places, Integration Cloud will use the addresses provided by you when you execute the operation.

Further, as shown below, set the **Transport Layer Security** to **Implicit** to connect to SSL port 465. Integration Cloud internally sets the `mail.smtp.ssl.enable` property to `true`.

The screenshot shows the configuration page for a Simple Mail Transfer Protocol (SMTP) account in the WEBMETHODS Integration Cloud. The interface is divided into several sections:

- Name:** gmailAccount
- Description:** Describe your Account
- Account Configuration Fields:**
 - Host: smtp.gmail.com
 - Port: 465
 - User: ankumar2403@gmail.com
 - Password: *****
 - From: ankumar2403@gmail.com
 - To: anub@softwareag.com
 - Response Timeout: 30000
 - Read Timeout: 30000
 - Write Timeout: 30000
- SSL CONFIGURATION:**
 - Transport Layer Security: implicit
 - Truststore Alias: Select Truststore

If you want to connect to Gmail SMTP server TLS Port (587), specify the mandatory account configuration fields. Also, as shown below, specify the **Transport Layer Security** as **Explicit**.

If **Transport Layer Security** is set as **Explicit**, Integration Cloud adds the `mail.smtp.tls.required` property as `true` by default, while executing the operation. Also, Integration Cloud connects to the SMTP server and issues `STARTTLS` to change the unencrypted connection to an encrypted connection.

The screenshot shows the configuration page for a Simple Mail Transfer Protocol (SMTP) account in the WEBMETHODS Integration Cloud. The interface is divided into several sections:

- Name:** gmail
- Description:** Describe your Account
- Account Configuration Fields:**
 - Host: smtp.gmail.com
 - Port: 587
 - User: ankumar2403@gmail.com
 - Password: *****
 - From:
 - To:
 - Response Timeout: 30000
 - Read Timeout: 30000
 - Write Timeout: 30000
- SSL CONFIGURATION:**
 - Transport Layer Security: **explicit** (highlighted with a red box)
 - Truststore Alias: Select Truststore

- After you have provided the above account configuration values, click **Test** on the **Account Configuration** page as shown below to test the SMTP server configuration.

Simple Mail Transfer Protocol (SMTP) You are using 2 out of unlimited number of Applications allowed

Name *
Description

Account Configuration Fields

Host *
Port *
User *
Password *
From
To
Response Timeout
Read Timeout
Write Timeout

SSL CONFIGURATION

Transport Layer Security
Truststore Alias



Host * smtp.gmail.com

Port * 465

User Name * arnkumar2403@gmail.com

Password * *****

Transport Layer Security implicit

From *

To *

6. Click **Send** to send the test email to the recipient. You can also click **Test** on the **Operations** page to test the SMTP server configuration.



7. After you click **Test** on the **Operations** page, add the input values as shown below, and then click **Run**.

Note: You can add attachments only while creating an Integration.

sendEmail

Account *

Input

from	<input type="text"/>	...
to	<input type="text"/>	...
subject *	sending test email	...
body *	sample body	...
cc	<input type="text"/>	...
bcc	<input type="text"/>	...
subjectCharSet	<input type="text"/>	...
bodyCharSet	<input type="text"/>	...
▼ attachments []		
contenttype *	<input type="text"/>	
content *	<input type="text"/>	
filename *	<input type="text"/>	
encoding	<input type="text"/>	
charset	<input type="text"/>	


Clear Close **Run**

8. Use the SMTP Application to create the Orchestrated Integration as shown below. See [“Orchestrated Integrations” on page 380](#) on how to create an Orchestrated Integration.


Do the following:

- Add the QueryAccounts operation from Salesforce.
- Add the createOpportunities operation from Marketo.
- Map the queried Salesforce accounts to Marketo createOpportunities.


- Add the sizeOfList service from the List category.
- Map the queried Salesforce accounts to the sizeOfList service to get the total number of accounts queried.
- Add the “sendEmail” on page 280 operation from the SMTP Application.




9. Map input and output.



10. Click subject and set a value. Then click body.



- Set a value for the `body`, that is, type the email body. Wrap the dynamic fields which are in the pipeline with `%` and click **Perform pipeline variable substitution**.



- Click **Apply**, save the integration, and then run the Integration.

An email is sent to the recipients specified in the **To** field on the SMTP Account Configuration page.

Exceptions

Timeout errors may occur while executing the “[sendEmail](#)” on [page 280](#) operation. Do the following as remedial actions:

- Check if the host and port details are configured correctly.
- Increase the **Response Timeout** value on the **Account Configuration** page.

SMTP Predefined Operation

sendEmail

Sends emails to specified recipients. You can attach one or more files to the message.

Input Parameters

<i>from</i>	String Optional. E-mail address of the sender.
<i>to</i>	String Optional. E-mail address of the receiver. If you specify multiple addresses, separate them with commas.
<i>subject</i>	String Subject of the message.
<i>body</i>	String The content of the message.
<i>cc :</i>	String Optional. E-mail addresses of additional receivers. If you specify multiple addresses, separate them with commas.
<i>bcc :</i>	String Optional. E-mail addresses of additional receivers. If you specify multiple addresses, separate them with commas.
<i>subjectCharSet :</i>	String Optional. The character set used to encode the subject. Default: UTF-8.
<i>bodyCharSet :</i>	String Optional. The character set used to encode the email message. Default: UTF-8.
<i>attachments</i>	Document List Attachments to the email message.

Key

Description

<i>contenttype</i>	String Content type of the attachment. For example: application/pdf.
<i>content</i>	byte[], String, or java.io.InputStream Content of the attachment.
<i>filename</i>	String Name to assign to the attachment.
<i>encoding</i>	String Encoding of the attachment, for example, base64 or 7bit. If <i>encoding</i> is not specified, 7bit is used.
<i>charset</i>	String Character set encoding of the attachment. If <i>charset</i> is not specified, then UTF-8 encoding is used.

Output Parameters

status **String** Final status of the operation.

Usage Notes

- You must define the *from* and *to* fields either in the **Account Configuration** section or while executing the operation.
- If you are using *filename* to attach a file to the message and the file is not a plain text file, you must set the *contenttype* and *encoding*.

Slack

Integration Cloud connects to Slack using the Slack REST API. You can use it to collaborate in your team within persistent chat rooms, private groups, and direct messaging, where all the content is searchable.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider.

Field	Description
	<p>The URL for Slack REST Application depends on the team name: https://YOURTEAM.slack.com</p> <p>Example: https://exampleteam.slack.com</p>
Response Timeout	<p>The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.</p>
Retry Count on Response Failure	<p>The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.</p>
Retry on Response Failure	<p>Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.</p>
Keystore Alias	<p>Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.</p>
Client Key Alias	<p>Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.</p>
Hostname verifier	<p>Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is org.apache.http.conn.ssl.DefaultHostnameVerifier, which will enable hostname verification. Select org.apache.http.conn.ssl.NoopHostnameVerifier to disable hostname verification.</p>
Access Token	<p>The token used for authentication and issued by the Authorization Server.</p>

Field	Description
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

StrikeIron Contact Verification

Integration Cloud connects to StrikeIron using the StrikeIron Contact Verification APIs, and provides access to email verification and hygiene services, along with the North America address verification service.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: <code>https://ws.strikeiron.com/StrikeIron</code> .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.

Field	Description
Username	This is the user account name on the SaaS provider that the Account will use to connect to the SaaS provider. The Account will use this credential to connect to the SaaS provider.
Password	Provide a password for the user name provided in the Username field to initiate communication with the SaaS provider.
Authorization Type	The type of HTTP authorization scheme to use for the connection. If you select none , no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password, but do not specify a value for the Authorization Type, the user credentials are not inserted into an Authorization header. If you enter the username and password, then set the authorization type as basic . Basic refers to HTTP Basic Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to

Field	Description
	connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

SuccessFactors HCM

Integration Cloud connects to SuccessFactors using the SuccessFactors web service SFAPI, and performs SuccessFactors operations (Create, Read, Update, Delete, Fetch, Insert, Query, queryMore, and Upsert) over HTTP using synchronous SOAP protocols. This Application has been tested with the following business objects: GOAL\$1, GOAL\$2, GOAL\$3, GoalMilestone\$2, GoalMilestone\$3, GoalTask\$2, GoalTask\$3, MatrixManager, and CustomManager.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: <code>https://api.successfactors.com/sfapi/v1/soap</code> <code>https://<instance_name>.successfactors.com</code> , where <code><instance_name></code> represents the actual instance name.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent

Field	Description
	successfully. Select this option if you want to re-establish the connection.
Username	This is the user account name on the SaaS provider that the Account will use to connect to the SaaS provider. The Account will use this credential to connect to the SaaS provider.
Password	Provide a password for the user name to initiate communication with the SaaS provider.
Authorization Type	<p>The type of HTTP authorization scheme to use for the Account. The SuccessFactors Application does not use Authorization headers.</p> <p>If you specify none, no additional authorization scheme will be executed at run time. If you specify a Company ID, Username, and Password, but do not specify a value for Authorization Type, the user credentials are not inserted into an Authorization header. If you enter the username and password, then set the authorization type as basic. Basic refers to HTTP Basic Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password.</p>
Company ID	The company ID that SuccessFactors provided, when your company registered with them.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.

Field	Description
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

SugarCRM

Integration Cloud connects to SugarCRM using the Interface for RESTful Web Services v10 and manages the CRM data. You can use it to retrieve, query, create, update, and delete business objects of any type.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. For example, the end point URL is of the format: <code>https://<instance>/rest/v10</code> . Replace <code><instance></code> with your actual SugarCRM instance.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.

Field	Description
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Consumer ID	Also referred to as the Client ID, this is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, this is a secret matching to the client identifier.
Access Token	This token is used for authentication and is issued by the Authorization Server. SugarCRM REST APIs use OAuth 2.0. The Access Token is passed when you invoke any of the REST API endpoints.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's

Field	Description
	identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Twilio

Using the REST interface, Twilio allows you to programmatically make and receive phone calls and send and receive text messages.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. For example, the end point URL would be of the format: <code>https://api.twilio.com/2010-04-01</code>
Authorization Type	The type of HTTP authorization scheme to use for the connection. If you select none , no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password, but do not specify a value for the Authorization Type, the user credentials are not inserted into an Authorization header. If you enter the username and password, then set the authorization type as basic . Basic refers to HTTP Basic Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password. Select the Authorization Type as basic .
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes

Field	Description
	longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Username	The name of the user account on the SaaS provider that the connection will use to connect to the SaaS provider.
Password	The password for the user name provided in the Username field.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.

Field	Description
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

webMethods.io B2B

The webMethods.io B2B application allows you to:

- Interact, accept requests, and build integrations for the webMethods.io B2B product instance.
- Exchange business documents between trading partners.

webMethods.io B2B account configuration

You must configure an account in the webMethods.io B2B application for you to utilize its predefined operations in Integration Cloud to build orchestrations.

Note: webMethods.io B2B application on Integration Cloud requires you to have access to the webMethods.io B2B product instance.

Field	Description
B2B Environment	Connects to the webMethods.io B2B product instance within your environment.

Note: You can only create one account in the webMethods.io B2B application. To create a new account, you must delete the existing account. If the existing account has integrations, then the integrations must be updated with the new account details.

Predefined Operations

The following predefined operations are available for webMethods.io B2B application:

changeUserStatus

Changes the user status of a specified transaction.

Input Parameters

<i>transactionID</i>	String Transaction ID of the document in exchange.
<i>userStatus</i>	String The user status for a transaction. For example, New, Open, or Fixed. Character length limit is 255.

Output Parameters

<i>isUpdated</i>	String Indicates if the operation changed the user status of a transaction. <ul style="list-style-type: none">■ <code>true</code>. The operation changed the user status of the transaction.■ <code>false</code>. The operation has not changed the status of the transaction.
------------------	--

parseContent

Parses request content passed by the processing rule **Call an integration** action as bytes or string data type. For more information on **Call an integration**, see *webMethods B2B Cloud Help*

Input Parameters

<i>inputContent</i>	String Content passed in the integration request.
<i>loadContentAs</i>	String Data type in which <i>outputContent</i> field value is passed. <ul style="list-style-type: none">■ bytes. <i>outputContent</i> is generated as bytes.■ string. <i>outputContent</i> is generated as a string.
<i>encoding</i>	String Type of character set used for encoding <i>inputContent</i> value. This can be any IANA registered character set. Default UTF-8

Output Parameters

outputContent **Object** Content data corresponds to the data type option set for the *loadContentAs* field.

generateResponse

Generates a response for the processing rule **Call an integration** action.

Input Parameters

inputContent **String** Content data sent as part of integration response after encoding.

readContentAs **String** Data type in which *inputContent* field value is passed.

- **bytes.** *inputContent* is read as bytes.
- **string.** *inputContent* is read as a string.

contentType **String** Content-Type passed corresponds to *inputContent* field. For example, application/EDI, application/x12, text/plain and so on.

errorCode **String** Value of error code passed as part of integration response.

errorMessage **String** Value of error message passed as part of integration response.

encoding **String** Type of character set used for encoding *inputContent* value. This can be any IANA registered character set.

Default UTF-8

Output Parameters

response **Document** Response is a composite object containing the parameters:

Key	Description
-----	-------------

<i>content</i>	String Encoded in <code>Base64</code> . Value is specified in <i>encoding</i> .
<i>type</i>	String Value specified in <i>contentType</i> .
<i>encoding</i>	String Type of encoding used to encode the <i>inputContent</i> . Value is specified in <i>encoding</i> .

error **Document** Error is a composite object containing the fields:

<u>Key</u>	<u>Description</u>
<i>code</i>	String Error code received from the input. Value is specified in <i>errorCode</i> .
<i>message</i>	String Error message associated with the input. Value is specified in <i>errorMessage</i> .

submit

Submits the business documents to webMethods.io B2B product instance.

Input Parameters

<i>inputContent</i>	Object Content to submit to webMethods.io B2B product instance for processing.
<i>readContentAs</i>	<p>String Data type in which <i>inputContent</i> field value is passed.</p> <ul style="list-style-type: none"> ■ bytes. <i>inputContent</i> is read as bytes. ■ string. <i>inputContent</i> is read as string.
<i>contentType</i>	<p>String Specifies the type of content.</p> <ul style="list-style-type: none"> ■ application/EDIStream. Content is read as an EDI InputStream. ■ application/EDI. Content is read as EDI input. ■ application/x12. Content is read as X12 input. ■ application/UNEDIFACT. Content is read as UNEDIFACT input.

encoding **String** Type of character set used for encoding *inputContent* value. This can be any IANA registered character set.
Default: UTF-8

Output Parameters

transaction **Document** Contains the following information about the transaction created in webMethods.io B2B product instance.

Key	Description
<i>transactionID</i>	String Transaction ID of the document created in webMethods.io B2B product instance.
<i>senderID</i>	String Sender ID of the document.
<i>receiverID</i>	String Receiver ID of the document.
<i>documentTypeID</i>	String Internal ID of the document type in the webMethods.io B2B product instance.
<i>userStatus</i>	String User-defined status of the document.
<i>transactionStatus</i>	String Status of the transaction submitted in the webMethods.io B2B product instance.
<i>customAttributes</i>	Document Extracted custom attributes from <i>inputContent</i> . Key is the attribute name and value is the attribute value.

Zendesk

Integration Cloud connects to Zendesk using the Zendesk API v2. It includes ticketing system, self-service options, and customer support features, and allows you to create, update, and solve customer support tickets and also track problems and questions.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. For example, the end point URL is of the format:

Field	Description
	<code>https://<domain>.zendesk.com</code> . Replace <domain> with your actual Zendesk instance.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Consumer ID	Also referred to as the Client ID, this is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, this is a secret matching to the client identifier.

Field	Description
Access Token	This token is used for authentication and is issued by the Authorization Server. Zendesk REST APIs use OAuth 2.0. The Access Token is passed when you invoke any of the REST API endpoints.
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Zuora

Zuora

Integration Cloud connects to Zuora using the Zuora SOAP API. You can use it to connect to Zuora and automate billing, commerce, and financial operations.

Zuora REST

Integration Cloud connects to Zuora REST using the Zuora REST API. Zuora allows you to manage Zuora objects in the Zuora Business Object Model, process revenue schedules, and perform other financial operations.

Field	Description
Server URL	Provide the login endpoint to initiate communication with the SaaS provider. Example: <code>https://api.zuora.com/apps/services/a/76.0</code> . For Zuora REST: <code>https://rest.<your_tenant_name>.zuora.com</code> .

Field	Description
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Username	This is the user account name on the SaaS provider that the Account will use to connect to the SaaS provider. The Account will use this credential to connect to the SaaS provider. When you use a SOAP based Zuora Application, it is not recommended to use more than one Account with the same user name.
Password	Provide a password for the user name provided in the Username field to initiate communication with the SaaS provider. When you access Zuora from outside your company's trusted network, you must add a security token (provided by Zuora) to your password. For more information about logging on Zuora, see the Zuora documentation.
Authorization Type	The type of HTTP authorization scheme to use for the Account. The Zuora Application does not use Authorization headers. If you select none , no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password, but do not specify a value for the Authorization Type, the user credentials are not inserted into an Authorization header. If you enter the username and password, then set the authorization type as basic . Basic refers to HTTP Basic Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used

Field	Description
	to determine trust for the remote server peer certificates. You can also add a new Truststore from this field.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification.
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.
Consumer ID	Also referred to as the Client ID, this is a client identifier issued to the client to identify itself to the authorization server.
Consumer Secret	Also referred to as the Client Secret, this is a secret matching to the client identifier.
Access Token	This token is used for authentication and is issued by the Authorization Server. The Access Token is passed when you invoke any of the REST API endpoints.

Field	Description
Refresh Token	A token used by the client to obtain a new access token without involving the resource owner.
Refresh URL	This is the provider specific URL to refresh an Access Token. Example: https://rest.apisandbox.zuora.com/oauth/token .

REST Applications

REST (Representational State Transfer) is an architectural style that requires web applications to support the HTTP GET, POST, PUT, and DELETE methods and to use a consistent, application-independent interface.

Endpoint URL

The endpoint of an API is a unique URL, which represents an object or collection of objects. The endpoint is a reference to a URI that accepts web requests. It is the login endpoint URL to initiate communication with the SaaS provider. To get the endpoint, go through the SaaS provider documentation available on the internet. For example, <https://api.twitter.com/1.1/> is the Twitter endpoint.

Authentication Type

Every back end provides its own Authentication mechanism to provide authorized access to its APIs. You need to get the authentication details from the SaaS provider documentation. For example, for Twitter, go to <https://apps.twitter.com>, create a new application, and then get the credentials. For Twitter, the authentication is OAuth V1.0a, which you can get from <https://apps.twitter.com>.

Resource

A resource refers to some object or set of objects that are exposed at an API end point. It is a representation of a thing (a noun) on which the REST APIs (verbs) operate. A resource has a type, one or more parameters, and some standard operations that allow you to manipulate or retrieve it from a remote location if you know its endpoint URL. Each resource derives its path from the namespace of the resource. For example, if the REST resource is named `myREST.myRESTResource`, the path is `"/myREST.myRESTResource"`.

Action

Actions are tasks that act on a Resource. You must create at least one Action for a Resource after you have created the Resource. You can add a Method, Request Parameters, Request and Response Headers, and a Request and Response body to an Action.

HTTP Method

The primary or most-commonly-used HTTP verbs (or methods, as they are properly called) are POST, GET, PUT, and DELETE. These correspond to create, read/retrieve, update, and delete (or CRUD) operations, respectively. You use the following HTTP methods to map the CRUD operations to HTTP requests. In a REST request, the resource that you are working with is specified in the URL – Uniform Resource Locator. The URL is a special case of the URI – Uniform Resource Identifier.

- **GET** - Used to read or retrieve a representation of a resource. For example, GET <endpointurl>/addresses/2 will retrieve an address with an ID of 2.
- **POST** - Creates a resource. For example, POST <endpointurl>/addresses will create a new address.
- **PUT** - Updates an existing resource. For example, PUT <endpointurl>/addresses/3 will modify the address with an ID of 3.
- **DELETE** - Used to delete a resource identified by a URI. For example, DELETE <endpointurl>/addresses/4 will delete an address with an ID of 4.

Resource	GET	PUT	POST	DELETE
http://example.com/api/resource/	Lists details and perhaps URIs of the resources in this collection.	Replaces the entire collection.	Creates a new item in the collection.	Deletes a collection.
http://example.com/api/resource/123/	Retrieves a specific item in the collection.	Updates the item in the collection and possibly creates an item if it does not exist.	Creates a new item in the collection.	Deletes an item from the collection.

Headers and Parameters

REST is not a standard in itself but instead makes use of the HTTP standard. HTTP headers allow the client and the server to pass additional information with the request or the response. For example, the *Accept* and *Content-Type* HTTP headers can be used to describe the content being sent or requested within an HTTP request. The client may set *Accept* to *application/json* if it is requesting a response in JSON or *application/xml* if it is requesting a response in XML, that is, when sending data, setting the *Content-Type* to *application/xml* tells the client that the data being sent in the request is XML.

REST calls (requests) and responses are sent over the HTTP protocol, hence REST requests are in the form of URLs that point to the resource(s) on the server. Required parameters are attached to the end of the URL. For example, in the resource URL `http://<name>.com/user/789`, `user` is the resource and `789` is the parameter that is passed to the URL of the resource. You can use any REST client to make REST calls.

REST parameters specify the variable parts of your resources, that is, the data that you are working with. QUERY parameters are the most common type of parameters, which is appended to the path of the URI when submitting a request. For example, `https://api.twitter.com/1.1/users/show.json?screen_name=twitterdev` is an example of a QUERY parameter URI where `screen_name` is the name of the parameter and `twitterdev` is the value of the parameter.

HTTP Status Codes

HTTP Status Codes indicate the status of the HTTP response:

- 1XX - Informational
- 2XX - Success
- 3XX - Redirection
- 4XX - Client error
- 5XX - Server error

Creating and updating REST Applications

These screens allow you to define a REST Application, define Resources and Actions, and then create a REST Application. See [“REST Applications” on page 300](#) for conceptual information on REST Resources, HTTP Methods, HTTP Status Codes, HTTP Headers, and Parameters.

Note: Users who have the required permissions under **Settings**  **> Access Profiles > Administrative Permissions > Functional Controls > REST APIs** can create, update, delete, or execute REST APIs.

To create a REST Application

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > Applications > REST Applications > Add New Application**.
2. In the **Define Application Details** page, complete the following fields. Required fields are marked with an asterisk on the screen.

Field	Description
Name	Type a name for the REST Application.
Description	Type an optional description for the REST Application. The description you enter here will appear in the Applications page.
Default Endpoint URL	Specify the Endpoint for the Application. It is the login endpoint URL to initiate

Field	Description
	communication with the SaaS provider. To get the end point, see the back end documentation available on the internet for the SaaS provider.
Authentication Type	Every back end provides its own authentication mechanism. Get the authentication details from the back end documentation and select the supported Authentication Type from the drop-down list.
Application Icon	Click Browse and select another icon for the REST Application, if necessary.

3. Click **Next**.

The **Define Resources and Actions** page appears.

4. In the **Define Resources and Actions** page, click **Add Resource** to create a new REST Resource.

The **Add Resource** dialog box appears. In the **Add Resource** dialog box, complete the following fields:

Field	Description
Name	Type the Resource name.
Path	Type the path to the Resource. The Resource path is relative to the endpoint specified. Each REST Resource derives its path from the namespace of the REST Resource. For example, if the REST Resource is named myREST.myRESTResource, the path is “/myREST.myRESTResource”. You can define dynamic parameters in the resource path by enclosing each parameter within { } brackets. For example, to get the employee data corresponding to a dynamic parameter called employeeID, specify the resource path as /employee/{employeeID}. To get item information from a particular department in a store, specify the resource path as /store/{departmentID}/{itemID}.

Note: While adding an **Action**, if your Resource path contains { } brackets, for example, /

Field	Description
	user/{userID}, you must add a request parameter having the same name, that is, "userID", and set the Parameter Type to URI_CONTEXT .

- Click **Add** to create the Resource. You can **Edit** or **Delete** the Resource from the **Define Resources and Actions** page.
- In the **Define Resources and Actions** page, select the Resource and click **Add Action**.

Note: Every Resource must have an Action associated with it.

In the **Add Action to Resource** dialog box, complete the following fields:

Field	Description
Method	<p>Select an HTTP Method.</p> <ul style="list-style-type: none"> ■ GET - Reads or retrieves a representation of a resource. For example, GET <endpointurl>/addresses/2 will retrieve an address with an ID of 2. ■ PUT - Updates an existing resource. For example, PUT <endpointurl>/addresses/3 will modify the address with an ID of 3. ■ POST - Creates a resource. For example, POST <endpointurl>/addresses will create a new address. ■ DELETE - Deletes a resource identified by an URI. For example, DELETE <endpointurl>/addresses/4 will delete an address with an ID of 4.
Description	Type an optional description for the Action.
Request Parameter	<p>You can set parameters that become part of the outgoing request. Parameters specify the variable parts of your resources. Click Add Parameter to add a parameter to the request. Complete the following fields:</p> <p>Name - Type the parameter name.</p> <p>Value - Type a value for the parameter.</p> <p>Parameter Type - Select the parameter's type, which determines how the parameter should be used.</p>

Field	Description
	<p>if you select an AWS authentication type, then you must add a <i>mandatory request parameter</i> in all the Actions you create. The parameter name must be <i>aws.service</i> and the parameter type must be <i>CFG_PARAM</i>. Type the service name in the endpoint URL as the parameter value. For example, if the endpoint URL is <code>https://<instance>.s3.com/</code>, type the parameter value as <code>s3</code>.</p> <p>REST services rely on HTTP methods (GET, POST, PUT, and DELETE) to make requests to a SaaS provider. Thus the parameters are closely tied to these HTTP methods, as they are sent as part of these HTTP method requests. The parameters are part of the HTTP URI. <i>CFG_PARAM</i> is an internal configuration parameter.</p> <p><i>URI_CONTEXT</i> parameters are passed as the path component of a REST Resource URI, and the parameter names correspond to the URI path variable names specified in the {} annotation. For example, if the URI is <code>https://api.twitter.com/1.1/users/{id}</code>, the Resource path will be <code>/users/{id}</code>, the parameter type will be <code>uriContext</code>, the parameter name will be <code>id</code>, and the value could be the user id, for example, either 1, or 2, or 3.</p> <p><i>QUERYSTRING_PARAM</i> parameters are passed as the query component of a REST resource invocation request. For example, if the URI is <code>https://api.twitter.com/1.1/users/show.json?screen_name=twitterdev</code>, the resource path will be <code>/users/show.json</code>, <code>screen_name</code> is the name of the parameter, <code>twitterdev</code> is the value of the parameter, and the parameter type is <code>query</code>.</p> <p><i>FORM_ENCODED_PARAM</i> - Define a parameter of type <i>FORM_ENCODED_PARAM</i> if you want to send the parameter as part of the Request body. <i>FORM_ENCODED_PARAM</i> allows you to send simple key value parameters embedded in the Request body for POST or PUT requests. This uses the default web form encoding, which is <code>application/x-www-form-urlencoded</code>.</p>

Note: For passing parameters of *FORM_ENCODED_PARAM* type, you will not be able to define the Request body for a

Field	Description
	<p>Resource, as the generated parameter key value string will be automatically embedded in the Request body.</p> <p>Required - Select this option if you want this parameter to be made mandatory while creating an Integration.</p>
<p>Request Header</p>	<p>HTTP headers allow the client and the server to pass additional information with the request or the response.</p> <p>Note: Do not add an authorization header if you use credentials as the mode of authentication.</p> <p>Click Add Header to add a request HTTP header. In the Add Header dialog box, complete the following fields:</p> <p>Name - Type the Header name.</p> <p>Value - Type a value for the Header.</p> <p>Required - Select this option if you want this Header to be made mandatory while creating an Integration.</p>
<p>Request Body</p>	<p>In the Request Body pane, complete the following fields:</p> <p>Content Type If the documentation of the SaaS provider specifies that the content type of the request body is JSON, select application/json as the content type. If the documentation of the SaaS provider specifies that the content type of the request body is XML, select application/xml as the content type. If the documentation of the SaaS provider specifies that the content type of the request body is binary, select Binary as the content type. These options allow you to control the content in an HTTP request body.</p> <p>Document Type - Select a Document Type for the request body or click Create Document Type to create a new Document Type. See “Creating Document Types from Scratch” on page 591.</p> <p>Note: Document Types created for a REST Application do not appear in the Develop ></p>

Field	Description
	<p data-bbox="696 306 1284 407">Document Types screen but appears only in the Document Types panel for the selected REST Application.</p> <p data-bbox="615 443 1230 575">If the request payload is an array of object, then first create a document type resembling the content of the object, and then select the Array option.</p>
Response Header	<p data-bbox="615 625 1243 688">In the Response Header pane, click Add Header to add a Response HTTP header.</p> <p data-bbox="631 724 1292 787">Note: Do not add an authorization header if you use credentials as the mode of authentication.</p> <p data-bbox="615 823 1008 854">Complete the following fields:</p> <p data-bbox="615 875 1011 907">Name - Type the Header name.</p> <p data-bbox="615 928 1073 959">Value - Type a value for the Header.</p> <p data-bbox="615 980 1243 1081">Required - Select this option if you want this Header to be made mandatory while creating an Integration.</p>
Response Body	<p data-bbox="615 1129 1146 1192">In the Response Body pane, complete the following fields:</p> <p data-bbox="615 1213 1263 1346">HTTP Code - Type a single HTTP status code or a code range to indicate the status of the response. Valid values are 100, 101, 102...599 or a range from 100-599.</p> <p data-bbox="615 1367 1239 1749">Content Type If the documentation of the SaaS provider specifies that the content type of the response body is JSON, select application/json as the content type. If the documentation of the SaaS provider specifies that the content type of the response body is XML, select application/xml as the content type. If the documentation of the SaaS provider specifies that the content type of the response body is binary, select binary as the content type. These options allow you to control the content in an HTTP response body.</p> <p data-bbox="615 1770 1219 1904">Document Type - Select a Document Type for the Response Body or click Create Document Type to create a new Document Type. See “Creating Document Types from Scratch” on page 591.</p>

Field	Description
	<p>Note: Document Types created for a REST Application do not appear in the Develop > Document Types screen but appears only in the Document Types panel for the selected REST Application.</p>

7. Click **Save**.

The Action appears in the **Define Resources and Actions** page. You can **Edit** or **Delete** the Action from the **Define Resources and Actions** page.

Note: Do not edit or delete an Action if it is already used in an Operation. If the Action is edited or deleted, the Operations that are dependent on the Action including the Integrations that are dependent on the affected Operations, will not function properly.

8. Click **Next**.

The **Confirm REST Application** page appears.

9. Click **Finish** to create the REST Application.

The new REST Application appears in the **REST Applications** page.

Note: To edit the REST Application, click the REST Application link and then click **Edit Application**. You can change the **Description** and **Application Icon**. After you click **Finish**, the **Update REST Application** window appears, which provides a summary of the impacted Accounts, Operations, and Integrations. Click **Update** to update the REST Application.

To delete the REST Application, click **Delete Application**

REST Applications - Account Configuration Details

Integration Cloud allows you to create custom REST Applications. REST (Representational State Transfer) is an architectural style that requires web applications to support the HTTP GET, POST, PUT, and DELETE methods and to use a consistent, application-independent interface.

Field	Description
Server URL	This is the login Endpoint URL you have specified in the Define Application Details page while creating the REST Application.
Authorization Type	The type of HTTP authorization scheme to use for the connection. If you enter the username and password, then set the authorization type as basic . Basic refers to HTTP Basic

Field	Description
	Authentication. This option can be used if the Application requires or supports HTTP Basic authentication using a username and password. If you select none , no additional authorization scheme will be executed at run time. For example, when you specify a Username and Password, but do not specify a value for the Authorization Type, the user credentials are not inserted into an Authorization header.
Response Timeout	The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the Response Timeout value. It is recommended to specify a value other than 0. If you specify 0, Integration Cloud will wait indefinitely for a response.
Retry Count on Response Failure	The number of times Integration Cloud attempts to connect to the back end to read a response if the initial attempt fails. If an I/O error occurs, it will retry only if you have selected the Retry on Response Failure option.
Retry on Response Failure	Whether Integration Cloud should attempt to resend the request when the response has failed, even though the request was sent successfully. Select this option if you want to re-establish the connection.
Consumer ID	Also referred to as the Client ID, in OAuth 2.0, this is a client identifier issued to the client to identify itself to the authorization server. For Auth 1.0a, it is the Consumer Key issued by the Service Provider and used by the consumer to identify itself to the Service Provider.
Access Token	This token is used for authentication and is issued by the Authorization Server. For OAuth 1.0a, it is a value used by the Consumer to gain access to the Protected Resources on behalf of the User, instead of using the User's Service Provider credentials.
Access Token Secret	A secret used by the Consumer to establish ownership of a given Access Token. For OAuth 1.0a, it is the secret used by the Consumer to establish ownership of a given Access Token.
Refresh URL	The provider specific URL to refresh an Access Token.

Field	Description
Session Timeout (min)	The maximum number of minutes a session can remain active, in other words, how long you want the server to wait before terminating a session. The value should be equal to the session timeout value specified at the SaaS provider back end.
Username	The username credentials for the current Account configuration.
Password	The password credentials for the current Account configuration.
Trust store Alias	Select the alias name of the Integration Cloud trust store configuration. The trust store contains trusted certificates used to determine trust for the remote server peer certificates. You can also add a new Truststore from this field. This option is available only if Credentials is selected as the Authentication Type while creating the Application.
Hostname verifier	Select a hostname verifier implementation. Guards against man-in-the-middle (MITM) attacks. The default is <code>org.apache.http.conn.ssl.DefaultHostnameVerifier</code> , which will enable hostname verification. Select <code>org.apache.http.conn.ssl.NoopHostnameVerifier</code> to disable hostname verification. This option is available only if Credentials is selected as the Authentication Type while creating the Application.
Enable SNI	Server Name Indication (SNI) is an extension to the TLS protocol by which a client indicates which host name it is attempting to connect to at the start of the handshaking process. Enable this option if the SaaS provider offers SNI-based TLS connectivity, and if you want to connect to an SNI enabled SAAS provider to send the host name specified in the Server URL field, as part of the TLS SNI Extension <code>server_name</code> parameter.
SNI Server Name	If you want to explicitly specify a host name to be included as a part of the SNI extension <code>server_name</code> parameter, in case the host name is other than the host name specified in the Server URL field, specify the host name value in the SNI Server Name field.

Field	Description
Keystore Alias	Select the alias for the Integration Cloud key store configuration. This is a text identifier for the keystore alias. A keystore file contains the credentials (private key/signed certificate) that a client needs for authentication. You can also add a new Keystore from this field. This option is available only if Credentials is selected as the Authentication Type while creating the Application.
Client Key Alias	Alias to the private key in the keystore file specified in the Keystore Alias field. The outbound connections use this key to send client credentials to a remote server. To send the client's identity to a remote server, you must specify values in both the Keystore Alias and the Client Key Alias fields. This option is available only if Credentials is selected as the Authentication Type while creating the Application.
Consumer Secret	Also referred to as the Client Secret, this is a secret matching to the client identifier. For Auth 1.0a, it is the secret used by the Consumer to establish ownership of the Consumer Key.
Refresh Token	Issued with the OAuth v2.0 access token only. A token used by the client to obtain a new access token without having to involve the resource owner.
Refresh URL Request	Options for sending the parameters in the Access Token refresh request. The options are Body Query String , URL Query String , and Custom Integration . Body Query String - The refresh request parameters, for example, refresh_token, grant_type, and so on, and their values are sent as query strings in the body of the POST request. URL Query String - The refresh request parameters, for example, refresh_token, grant_type, and so on, and their values are sent as query strings in the URL of the POST request. Custom ESB Service - Use this option if the back end requires refresh requests in a custom format. If you select this option, you must specify the name of your Integration in the Refresh Custom ESB Service field. You can also create an Integration by clicking the link.

Field	Description
Refresh Custom ESB Service	<p data-bbox="537 321 1299 426">To refresh the access tokens for accounts which use the OAuth 2.0 protocol, you can specify a call-back Integration which will execute when the access token expires.</p> <p data-bbox="537 443 1308 579">This is a user implemented service for refreshing the <i>OAuth 2.0</i> Access Token. This option allows you to create an Integration, which will be executed when the Access Token has expired or is not valid.</p> <p data-bbox="537 598 1320 737">To create this Integration, create a custom REST Application with an Operation that invokes the back end to fetch the refresh token. You can use this custom REST Application along with its Operation to create this Integration.</p> <p data-bbox="537 753 1208 789">Click the <i>Integration link</i> to create a new Integration.</p> <p data-bbox="537 808 1243 877">The Integration must have a specification whose input parameters are:</p> <div data-bbox="537 898 857 1073" style="border: 1px solid black; padding: 5px; margin: 10px 0;">  </div> <p data-bbox="537 1094 941 1129">and the output parameters are:</p> <div data-bbox="537 1150 747 1312" style="border: 1px solid black; padding: 5px; margin: 10px 0;">  </div> <p data-bbox="553 1350 1338 1419">Note: The integration will be pre-populated with the input/output adhering to the above mentioned specification.</p> <p data-bbox="537 1451 1304 1556">The newly created Integration will generate an access token that is mapped to the access token field in the output signature.</p> <p data-bbox="553 1585 1364 1690">Note: While editing the Account, this new Integration appears in the Refresh Custom ESB Service field in the Account Configuration page.</p>

Tweet the status on Twitter using the REST Application

Summary


In this tutorial, we will see how to create a REST Application using the Twitter REST API and use that REST Application to post a tweet on Twitter.

Before you begin


- Permissions to create Operations and Integrations for a project in Integration Cloud.
- An email account ID, for example, `twitapplication@gmail.com`.
- A Twitter account. You can create one using your email ID.

Steps

1. Log in to Twitter, go to <https://developer.twitter.com/en/apps>, and click **Create an app** to create a Twitter app.



2. Create an application by filling the form and click **Create**.



Note: See <https://developer.twitter.com/en/docs/tweets/post-and-engage/api-reference/post-statuses-update> for information on POST statuses/update.

Post, retrieve and engage with Tweets

Overview Guides **API Reference**

API Reference contents

- POST statuses/update**
- POST statuses/destroy/id
- GET statuses/show/id
- GET statuses/oembed
- GET statuses/lookup
- POST statuses/retweet/id
- POST statuses/unretweet/id
- GET statuses/retweets/id
- GET statuses/retweets_of_me
- GET statuses/retweeters/ids
- POST favorites/create
- POST favorites/destroy
- GET favorites/list
- POST statuses/update_with_media (deprecated)

POST statuses/update

Updates the authenticating user's current status, also known as Tweeting.

For each update attempt, the update text is compared with the authenticating user's recent Tweets. Any attempt that would result in duplication will be blocked, resulting in a 403 error. A user cannot submit the same status twice in a row.

While not rate limited by the API, a user is limited in the number of Tweets they can create at a time. If the number of updates posted by the user reaches the current

- Log in to Integration Cloud and go to **Projects > <Select a Project> > Applications > REST Applications > Add New Application**. Fill in the details as shown below in the **Define Application Details** screen and then click **Next**.

Note: Default Endpoint URL should not contain the path of the endpoint. For example, if the complete endpoint URL is `https://api.twitter.com/1.1/statuses/update.json`, then `https://api.twitter.com/1.1` is the Default Endpoint URL. Rest of the path `/statuses/update.json` will be used as the Resource Path while adding a Resource later.

Step 1: Define Application Details

Name *

Description

Default Endpoint URL *

Authentication Type *

Application Icon No file chosen

REST

"Resource URL" section
<https://developer.twitter.com/en/docs/tweets/post-and-engage/api-reference/post-statuses-update>

- On the **Define Resources and Actions** page, click **Add Resource**.

Step 2: Define Resources and Actions

Resources

Name	Path	Actions
No items to be displayed.		

- Let us add the `postTweet` Resource. Click **Add**.

Add Resource

Name *

Path * ⓘ

! If your path contains () brackets, for example, /user/(userID), you must add a request parameter userID while adding an Action, and set the parameter type to URI_CONTEXT.

6. Select the postTweet Resource and click **Add Action**.

Applications Keys & Certificates

1 Define Application
2 Define Resources
3 Confirm Application

Step 2: Define Resources and Actions

Resources

Search for Resources...

A Resource must have an Action.

Name	Path	Actions
postTweet	/statuses/update.json	

7. On the **Add Action to Resource** page, select **POST** as the **Method**. In our example, we are considering a POST request which needs a Request PARAMETER and a Response BODY. Click **Add Parameter** to add the Request PARAMETER.

Add Action to Resource

Method *

Description

An Action must have a Response Body.

PARAMETER HEADER BODY

8. Specify the PARAMETER name exactly as it is in the API documentation (<https://developer.twitter.com/en/docs/tweets/post-and-engage/api-reference/post-statuses-update>).

Add Parameter

Name *

Value

Parameter Type *

Required

Select this option if you want this parameter to be made mandatory while creating an integration.

Parameters

Name	Required	Description	Default Value	Example
status	required	The text of the status update. URL encode as necessary. i.co link wrapping will affect character counts.		
in_reply_to_status_id	optional	The ID of an existing status that the update is in reply to. Note: This parameter will be ignored unless the		

Add Action to Resource

Method *

Description

An Action must have a Response Body.

PARAMETER HEADER BODY

Name	Default value	Parameter Type	Required
status	Hello	QUERYSTRING_PARAM	false

9. Now let us add the Response Body. Click **Response > BODY > Add Response Body**.

Add Action to Resource

Method *

Description

An Action must have a Response Body.

HEADER BODY

Add Response Body

HTTP Code *

Content Type *

Document Type *

None.

10. In the **Document Type** drop-down list, click **Create Document Type** and then click **Load JSON** in the **Add New Document Type** window.

The screenshot shows the 'Add New Document Type' interface. The 'Save as' dropdown is set to 'ResponseBody'. Below it is a text area for 'Describe your Document Type'. At the bottom right, there are two buttons: 'Load XML' and 'Load JSON'. The 'Load JSON' button is highlighted with a red border. A search bar for fields is visible at the bottom left, and a 'Click on + to add a new Field.' prompt is at the bottom center.

11. Copy the *Example Response* from the Twitter API Documentation page (<https://developer.twitter.com/en/docs/tweets/post-and-engage/api-reference/post-statuses-update>), paste it in the text area of the page as shown below, and click **Load**. Note that there is a known issue in the response section of the Twitter API Documentation. As a workaround, while pasting, omit the record starting with the string *source*. After loading, click **Save** and then **Add** to add the Response BODY.

The screenshot shows the 'Add New Document Type' interface with the 'Load' button highlighted in red. A red arrow points from the 'Load' button to the 'source' field in the JSON response, which has been removed from the original example. The JSON response is as follows:

```
{
  "created_at": "Wed Oct 10 20:19:24 +0000 2018",
  "id": "1050118621198921700",
  "id_str": "1050118621198921728",
  "text": "To make room for more expression, we will now count all emojis as equal-including rose with gender and skin: https://t.co/4G5G8t",
  "source": "<a href='\"http://twitter.com\"' rel='\"nofollow\"'>Twitter Web Client</a>",
  "truncated": true,
  "in_reply_to_status_id": null,
  "in_reply_to_status_id_str": null,
  "in_reply_to_user_id": null,
}
```

12. Click **Add** to add the Action.

Add Action to Resource

Method *

Description

Request **Response**

HEADER BODY

HTTP Code	Document Type	Content Type
200	ResponseBody	application/json

13. The **Actions** column displays the **POST** action.

Step 2: Define Resources and Actions

Resources


Name	Path	Actions
postTweet	/statuses/update.json	<input type="button" value="POST"/>

14. Click **Next** and then click **Finish** to create the REST Application **TweetOnTwitter**. Then create a new Account by clicking **Accounts** as shown below.


Default **Applications**

TweetonTwitter
Version 1.0


15. Then click **Add New Account**, fill in the Account configuration details obtained from the Twitter app (Consumer API Keys and Access Tokens) as shown below, and click **Save**.



16. Now click **OPERATIONS > Add New Operation**. Provide all the details and create the **Tweetop** operation.



17. Select the operation, click **Test**, and then **Run** the operation.




18. You will see that running the operation has triggered a tweet on your Twitter account.



On Twitter Account of the User


19. You can also trigger the REST Application from an integration. Click **INTEGRATIONS > Add New Integration**, and select the **Orchestrate two or more applications** option.



20. Setup the Integration as shown below using the REST Application, and then click **Save**.



21. Run and test the Integration. This will tweet as *Hello World Once Again*.



Next Steps

Whenever you execute the Integration, you will see a new tweet on the user's Twitter account with your message.

On-Premises Applications

On-Premises applications uploaded from on-premises systems are listed in the **On-Premises Applications** page, but you will not be able to create Accounts or Operations for on-premises applications. Those can be uploaded only from webMethods Integration Server. Further, when you upload services as part of an application from the on-premises webMethods Integration Server to webMethods Integration Cloud, the comments field of the service is uploaded and displayed in the webMethods Integration Cloud application. This field will be displayed if present and cannot be edited. See

the *Configuring On-Premise Integration Servers for webMethods Cloud* document for more information.

If you select an Account for an on-premises Application and click **Test Connection**, the screen displays the status of the connection. If you have configured the Account details incorrectly in any stage, the state appears in red color in the **Connectivity Status** column. If an Account is configured correctly in a particular stage, the state appears in green color and if an Account is not configured in a particular stage, the state appears in white color. For on-premises Applications, you can use the Account to execute services on the on-premises webMethods Integration Server.

See [“Uploading on-premises services to Integration Cloud” on page 321](#) on how to upload on-premises webMethods Integration Server services to webMethods Integration Cloud.

Uploading on-premises services to Integration Cloud

Summary

In this tutorial, we will see how to upload on-premises services from webMethods Integration Server to Integration Cloud.

Actors

- On-premises webMethods Integration Server user
- Integration Cloud instance to upload the on-premises application
- Integration Cloud user

Before you begin

- Software AG Universal Messaging installed and running on-premises along with webMethods Integration Server. Software AG Universal Messaging is required for communication between on-premises webMethods Integration Server and Integration Cloud.
- Your Access Profile must have the permission to create Accounts, Operations, Applications, and Integrations.
- Your Access Profile must have the administer stages permission.

Basic Flow

Update Settings and create Account and Application in webMethods Integration Server.

1. Log in to the webMethods Integration Server instance, for example, `http://<hostName>:5555/`.

Note: Software AG Universal Messaging should be running.

2. Go to **webMethods Cloud > Settings**.

- Enter your Integration Cloud URL, for example, `https://{instanceName}.webmethodscloud.com`, user name, password, and click **Update Settings**.

webMethods Cloud > Settings

Settings saved successfully.

Settings	
User Name	bugbash
Password	*****
webMethods Cloud URL	https://bugbasha.saglive.com

Update Settings

- Go to **webMethods Cloud > Accounts** and click **Create On-Premise Account**.

WEBMETHODS Integration Server default :: is-03.us-east-1a.wmic.saglive.sag ::

webMethods Cloud > Accounts

- [Create On-Premise Account!](#)

On-Premise Accounts	
Alias	Description
IntegrationLive_Default_Connection	

- Enter the details as shown below on the **Create Account** page and click **Test Account Settings**.

The account is valid.

webMethods Cloud > Accounts > Create Account

- [Return to On-Premise Accounts](#)

General Settings

Enable Yes No

Alias Name

Description

Stage

Account Settings

Maximum Reconnection Attempts

Request Timeout milliseconds

Time to Live seconds

Allowed On-Premise Hosts

Run As User

[Test Account Settings](#)

Note: The **Alias Name** is the name of the account that will appear on Integration Cloud and the **Stage** is the stage where you want to expose the webMethods Integration Server services.

- Click **Save Changes** and check if the account is enabled.

webMethods Cloud > Accounts


- [Create On-Premise Account](#)

On-Premise Accounts


Alias	Description	Stage	Last Uploaded Time	Upload	Test	Enabled	Delete
onPremiseDemoAccount	demo account	Development				Yes	

- Go to **webMethods Cloud > Applications** and click **Define webMethods Cloud Application**.
- Select the webMethods Integration Server services that you want to expose on Integration Cloud, provide a **Display Name** for the service, and **Save** your changes.


Note: Services that have wrapper type fields, for example, fields of type other than String and IData in its Input or Output signature, cannot be exposed to Integration Cloud and they will not be available in the **Package/Services** column.




9. Go to **webMethods Cloud > Applications** and click the upload icon.



10. Select the account and click **Upload**. The Application will be uploaded to Integration Cloud.



11. Log in to your Integration Cloud instance and go to **Projects > <Select a Project> > Applications > On-Premises Applications**. The on-premises Application appears in the list. Use the operations of the on-premises Application to create Integrations.



SOAP Applications

The SOAP Application enables you to access third party Web Services hosted in the cloud. The SOAP Application uses a WSDL to create consumer operations.

The following features are supported for SOAP Applications:

- A SOAP Application implementation follows the WS-I Basic Profile 1.1 specification.
- SOAP Applications can be created by uploading a WSDL file or by using a valid WSDL URL that can be accessed over a network.
- SOAP Applications can be created with WSDLs that are annotated with WS-Security Policy/Policies.
- SOAP Applications with SOAP version 1.1 and 1.2 and Style/Use as Document/Literal and RPC/Literal (RPC/Encoded model is not supported for SOAP version 1.2).
- The following SOAP Binding types are supported:
 - SOAP over HTTP.
 - SOAP over HTTPS.
- Authentication type: HTTP Basic Token.

SOAP Applications have the following restrictions:

- The WSDL and associated schema(s) must be accessible through a publicly or locally accessible URL.
- Only WSDLs with WS-Security policies are supported. Any other policies, for example, WS-Addressing, WS-Reliable Messaging, and so on, are not supported. If you create SOAP Applications with WSDLs having non-WS-Security Policies, exceptions may appear while executing Integrations.
- Manual addition of WS-Security Policies in a SOAP Application is not supported. SOAP Applications with WS-Security can be created with only policy-annotated WSDLs, that is, WSDLs that already have WS-Security Policies annotated in them.
- SOAP over JMS is not supported.
- Only Basic Authentication is supported. Other authentication types such as Digest, NTLM, and Kerberos are not supported.
- You will not be able to attach or upload a file while executing an Integration.

To add a SOAP Application

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > Applications > SOAP Applications > Add New Application.**

2. Provide a name and description of your SOAP Application. The description you enter here will appear in the **SOAP Applications** page. Required fields are marked with an asterisk on the screen.
 3. Click **Browse** next to the **Application Icon** if you want to select a different icon for your SOAP Application. The icon must be a PNG file and the size cannot exceed 50 KB, else the default image is displayed.
 4. Click **Next** and specify the **WSDL Source**.
 - Select **URL** if you want to specify the URL of the WSDL. The URL should begin with `http://` or `https://`. The URL is used to retrieve the WSDL for the SOAP Application.
 - Select **File** and then click **Browse** if you want to select the WSDL from your local file system. The size of the WSDL cannot exceed 5 MB. You can click the  icon beside the **Browse** button if you want to add separate elements of a service definition after import, such as WSDLs or XSDs, to the primary WSDL.
- Note:** Ensure that you add the primary WSDL as the first WSDL, and then add separate elements of the service definition, for example, dependent WSDLs and XSDs to the primary WSDL.
5. Enter the user name and password in the **Authentication** section if authentication is required to access the WSDL URL.
 6. Click **Next** to review the details you have entered.
 7. Click **Finish** to create the SOAP Application.

Editing SOAP Applications

From the **SOAP Applications** page, click the SOAP Application link, and then click **Edit Application**. You can change the **Description** and the **Application Icon**.

In the Application details page, **Update WSDL** section, select **No, keep existing WSDL** if you do not want to modify the WSDL URL or the WSDL file. Select **Yes, override WSDL** if you want to specify a new WSDL URL or upload a new WSDL file in the **WSDL Source** section.

Confirm the updated Application. After you click **Finish**, the **Update SOAP Application** window appears, which provides a summary of the impacted Accounts, Operations, and Integrations. Click **Update** to update the SOAP Application. Updating the WSDL may result in addition or removal of Operations or fields in the Input/Output signature of an Operation. This may lead to incorrect mappings if you have used that Operation in an Integration.

Note: To delete a SOAP Application, click **Delete Application**.

SOAP Applications - Account Configuration Details

Integration Cloud allows you to create Custom SOAP Applications. Custom SOAP Applications enable you to access third party web services hosted in the cloud or on-premises environment. The Custom SOAP Application uses a WSDL that is accessible through publicly or locally accessible URLs.

Field	Description
Port Binding	Select the bind address from the drop-down list, that is, the concrete protocol and data format specification for the web service.
URL	This is the URL for the web service. You can edit the URL to specify a different web service endpoint.
Response Timeout	<p>The number of milliseconds Integration Cloud waits for a response before canceling its attempt to connect to the back end. In case the network is slow or the back end processing takes longer than usual, increase the response timeout value. It is recommended to specify a value other than 0.</p> <p>If you specify 0, Integration Cloud will wait indefinitely for a response.</p> <p>If you do not specify a timeout, Integration Cloud will consider 5 minutes as the response timeout.</p> <p>If the connection to the host provider ends before Integration Cloud receives a response, the web service operation ends with an exception and a status code of 408.</p>
User	User name used to authenticate the consumer at the HTTP or HTTPS transport level on the host server.
Password	The password used to authenticate the consumer on the host server.
Keystore Alias	Alias to the keystore that contains the private key used to connect to the Web Service host securely. You can also add a new Keystore from this field.

Note: Users who have the **Administer** permission under **Settings**  **> Access Profiles > Administrative Permissions > Functional Controls > Advanced Security** can add, edit, and delete Keystores.

Field	Description
Key Alias	Alias to the key in the keystore that contains the private key used to connect to the Web Service host securely. The key must be in the keystore specified in the Keystore Alias field.

Show Advanced Options - WS-Security properties are used by the SOAP processor to provide security information in the WS-Security header of the SOAP message.

Security Credentials

User Name	Name to include with the Username Token, if the Web Service's security policy requires one.
Password	The password to include with the UsernameToken (must be plain text).

Keystore / Truststore

Keystore Alias	The alias for the keystore, which contains private keys and certificates associated with those private keys. You can also add a new Keystore from this field.
-----------------------	---

Note: Users who have the **Administer** permission under **Settings**  > **Access Profiles** > **Administrative Permissions** > **Functional Controls** > **Advanced Security** can add, edit, and delete Keystores.

Key Alias	The text identifier for the private key associated with the Keystore Alias .
------------------	---

Truststore Alias	The alias for the truststore, which contains the trusted root of a certificate or signing authority (CA). You can also add a new Truststore from this field.
-------------------------	--

Note: Users who have the **Administer** permission under **Settings**  > **Access Profiles** > **Administrative Permissions** > **Functional Controls** > **Advanced Security** can add, edit, and delete Truststores.

Partner Certificate Alias	The file that contains the partner's self-signed certificate. You can also add a new Partner Certificate from this field.
----------------------------------	---

Note: Users who have the **Administer** permission under **Settings**  > **Access Profiles** > **Administrative Permissions** > **Functional**

Field	Description
	Controls > Advanced Security can add, edit, and delete Partner Certificates.
Timestamp	
Timestamp Precision	Whether the timestamp placed in the Timestamp element of the security header of an outbound message is precise to seconds or milliseconds. If the precision is set to milliseconds, the timestamp format yyyy-MM-dd'T'HH:mm:ss:SSS'Z' is used. If the precision is set to seconds, the timestamp format yyyy-MM-dd'T'HH:mm:ss'Z' is used.
Timestamp TTL	The time-to-live value for an outbound message in seconds. This value is used to set the expiry time in the Timestamp element of outbound messages. The timestamp precision value is used only when WS-Security is implemented through a WS-Policy.
Timestamp Max Skew	The maximum number of seconds that the Web Services client and host clocks can differ so that the timestamp expiry validation does not fail. The timestamp precision value is used only when WS-Security is implemented through a WS-Policy. The inbound SOAP message is validated only if the creation timestamp of the message is less than the sum of the timestamp maximum skew value and the current system clock time.

SOAP Signature

All SOAP Application operations have an identical input and output signature with the exception of the variables used to represent the input and output messages. For information about how a SOAP Application operation represents the input and output messages in the signature, see *How a SOAP Application Operation represents the Input and Output Messages*.

How a SOAP Application Operation represents the Input and Output Messages

How a SOAP Application operation represents the contents of the input and output message in the signature depends on the style/use of the binder for the SOAP Application operation.

- For a SOAP Application operation that uses a style/use of Document/Literal:
 - The input signature contains an optional document reference to a document type created to represent the operation input message. At run time, if you do not specify any input for the document reference variable or any of its child variables, Integration Cloud sends an empty SOAP body in the SOAP message.

- The output signature contains a document reference to a document type created to represent the operation output message. This document reference is conditional and is only returned by the SOAP Application operation if the SOAP Application operation executes successfully. If returned at run time, this document reference contains the response from a successful invocation of a SOAP Application operation. If the SOAP Application operation receives a SOAP fault, it is converted to an exception that can be caught with the try catch block in an Orchestrated Integration.
- For a SOAP Application operation that uses a style/use of RPC/Encoded or RPC/Literal:
 - The input signature contains variables that represent the top-level elements in the operation input message. All of these variables are optional. At run-time, if you do not specify any input for the variable (or variables) that represent the input message, Integration Cloud sends an empty SOAP body in the SOAP message.
 - The output signature contains variables that represent the top-level elements in the operation output message. All of these variables are conditional and are only returned by the SOAP Application operation if the SOAP Application operation executes successfully. If returned, these variables contain the response from a successful invocation of a SOAP Application operation.

Input Parameters

transportHeaders

Document Optional. Transport-specific header fields that you want to explicitly set in the request. Specify a key in *transportHeaders* for each header field that you want to set, where the key's name represents the name of the header field and the key's value represents the value of that header field.

The names and values supplied to *transportHeaders* must be of type String. For information about using *transportHeaders* with HTTP/S requests including a description of the default behavior, see *Setting Transport Headers for HTTP/S*.

Output Parameters

transportInfo

Document Conditional. Headers from response and request messages.

The contents of the *transportInfo* vary depending on the actual transport (HTTP or HTTPS) used.

transportInfo contains the following keys:

Key	Value
-----	-------

<i>requestHeaders</i>	<p>Document Conditional. Header fields from the request message. The contents of the <i>requestHeaders</i> document are not identical to <i>transportHeaders</i> used as input. The transport can add, remove, or alter specific headers while processing the request.</p> <p>Whether or not the SOAP Application operation returns the <i>requestHeaders</i> parameter depends on the success or failure of the operation. In the case of failure, the point at which the failure occurs determines the presence of the <i>requestHeaders</i> parameter. For more information, see <i>Transport and Exceptions Returned by a SOAP Application Operation</i>.</p> <p>For the HTTP or HTTPS transports, the <i>requestHeaders</i> parameter will not contain any HTTP headers that the transport mechanism added or modified when sending the request.</p>
<i>responseHeaders</i>	<p>Document Conditional. Header fields from the response. Each key in <i>responseHeaders</i> represents a field (line) of the response header. Key names represent the names of header fields. The keys' values are Strings containing the values of the fields.</p> <p>Whether or not the SOAP Application operation returns the <i>responseHeaders</i> parameter depends on the success or failure of the operation. In the case of failure, the point at which the failure occurs determines the presence of the <i>responseHeaders</i> parameter. For more information, see <i>Transport and Exceptions Information Returned by a SOAP Application Operation</i>.</p> <p>For the HTTP or HTTPS transports, the <i>responseHeaders</i> parameter contains any HTTP/HTTPS headers present in the response.</p>
<i>status</i>	<p>String Conditional. Status code from the request, returned by the underlying transport.</p>

For more information about status codes and status messages returned by a SOAP Application operation, see *Transport and Exceptions Information Returned by a SOAP Application Operation*.

statusMessage

String Conditional. Description of the status code returned by the transport.

For more information about status codes and status messages returned by a SOAP Application operation, see *Transport and Exceptions Information Returned by a SOAP Application Operation*.

Setting Transport Headers for HTTP/S

When creating a service that executes a SOAP Application operation, you can pass transport header information directly into the SOAP Application operation by passing name/value pairs in to the *transportHeaders* input parameter. When creating the SOAP request, Integration Cloud adds a transport header for each name/value pair.

Keep the following information in mind when setting *transportHeaders* for an HTTP/S request:

- Specify a key in *transportHeaders* for each header field that you want to set, where the key's name represents the name of the header field and the key's value represents the value of that header field.
- The names and values supplied to *transportHeaders* must be of type String. If a transport header has a name or value that is not of type String, the header will not be included in the message.
- For any header name/value pair supplied in *transportHeaders* for an HTTP/S request, Integration Cloud simply passes through the supplied headers and does not perform any validation for the headers beyond verifying that the name and value are of type String.
- If you do not set *transportHeaders* or do not specify the following header fields in *transportHeaders*, Integration Cloud adds and specifies values for the following standard header fields:
 - Accept
 - Authorization
 - Connection
 - Content-Type
 - SOAPAction (Added when *soapProtocol* is SOAP 1.1 only)
 - User-Agent

Note: Pass in the preceding headers to *transportHeaders* only if you are an experienced SOAP Application developer. Incorrect header values can result in failure of the request.

- For a SOAP Application operation, Integration Cloud sets the value of the `Host` header and overwrites any supplied value.
- If you specify `Authorization` in *transportHeaders*, the values specified for the *auth/transport* document and its children will not be used in the `Authorization` header.
- If you specify `Content-Type` in *transportHeaders* and the SOAP Protocol is SOAP 1.2, Integration Cloud ignores the value of `soapAction` obtained from the WSDL used to create the SOAP Application operation.
- If you specify the `SOAPAction` header in *transportHeaders* and the SOAP Protocol is SOAP 1.1, Integration Cloud ignores the value of `SOAPAction` obtained from the WSDL used to create the SOAP Application operation.
- Integration Cloud sets the value of `Content-Length` automatically and overwrites any value passed in to *transportHeaders*.
- Integration Cloud automatically adds the `Cookie` header to the HTTP header and supplies any cookies established between Integration Cloud and the HTTP server with which it is interacting. If you supply the `Cookie` header to *transportHeaders*, Integration Cloud prepends the values you supply to the already established `Cookie` header value.
- The following headers are considered to be standard and require the specified capitalization: `Accept`, `Authorization`, `Connection`, `Content-Type`, `Cookie`, `Host`, `SOAPAction`, `User-Agent`.

Important: Using capitalization other than that which is specified results in undefined behavior.

Important: Supplying duplicate entries for any standard header results in undefined behavior.

Transport and Exceptions Returned by a SOAP Application Operation

The transport information, such as headers, status codes, and status messages, returned by a SOAP Application operation varies depending on the following:

- The transport used to send and receive the SOAP message
- The success or failure of the SOAP Application operation
- The point at which failure occurs
- The message exchange pattern (MEP) for the operation

Note: Transport information is returned in the *transportInfo* output parameter.

If the SOAP Application operation receives a SOAP fault, it is converted to an exception that can be caught with the try catch block in an Orchestrated Integration.

Flat File Applications

You can use the Flat File Application to translate documents into and from flat file formats. To set up the translation, you create the *definition and structure of the Flat File Application, which is called a flat file schema*. The schema also contains the instructions for parsing or creating the flat file and defines how to identify individual records within a flat file and what data is contained in each of those records.

What is a flat file definition and structure?

The definition and structure of a flat file Application contains the instructions for parsing or creating a flat file. It details the structure of the document, including delimiters, records, and repeated record structures. It also acts as the model against which you can validate an inbound flat file. A flat file structure consists of hierarchical elements that represent each record, field, and subfield in a flat file.

What are the different approaches to create a flat file Application?

You can create a flat file Application using any one of the following approaches:

- [“Create manually” on page 335](#): In this approach, you define the definition and structure of a flat file Application and then manually add the elements or properties.
- [“Use a sample file” on page 348](#): In this approach, you use a sample file to define the definition and structure of a flat file Application. Here, you use the automated wizards to create the structure of the flat file.

What are the high-level steps to create a flat file Application?

- Step 1** **Define the Application details.** In this stage, you define the Application details and the approach. You can create the flat file Application either manually or by using a sample file.
- Step 2** **Define the record parser and specify a record identifier.** In this stage, you associate a record parser with the flat file Application that will process flat files inbound to Integration Cloud. You also specify how you want the record to be identified after it is parsed.
- Step 3** **Define the flat file structure.** If you are creating the flat file Application manually, in this stage, you specify the hierarchical structure of the flat file by creating and nesting the record definitions.

Invoke Operations.

After creating the flat file Application, create an Orchestrated Integration, select the Flat File Application created, and invoke the following predefined operations:

- [“convertFlatFileToDocument” on page 353](#) - Converts the flat file to a document (inbound)
- [“convertDocumentToFlatFile” on page 356](#) - Converts a document to a flat file (outbound)

Creating a flat file Application manually

Integration Cloud can process flat files in which:

- The records in the flat file are defined using one of the following methods:

Property	Description
Delimiter	Each record in the flat file is separated by a delimiter.
Fixed length	Each record is a fixed number of bytes (for example, mainframe punch or print records).
Variable length	Each record is <i>preceded</i> by two bytes that indicate the length of the record. Records in the flat file can have different lengths.

- Each distinct record structure must have a record identifier. If no record identifier is present, the record will not be parsed.
- If the flat file contains record identifiers, the record identifiers must be located in the same location in all records in the file.

Integration Cloud can then identify fields in these records based on:

- **Fixed position** - Each field is defined by 1) the number of bytes from the beginning of the record and 2) the field length. This can be used regardless of whether a field delimiter has been specified.
- **Delimiters** - Each field is separated by a delimiter, and you can specify the *N*th delimited field in a record to represent the record identifier. This can be used only when a field delimiter (and, if necessary, subfield delimiter) has been specified.

To create a flat file Application manually

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > Flat File Applications > Add New Application**.
2. Type a name and description of the flat file Application and select the creation mode as **Create manually**.
3. Click **Next** and in the **Flat File Definition** page, configure the **Record parser** and the **Record identifier**.

4. In the **Record parser** section, to configure a delimited record parser, select **Delimiter** in the **Record parser** area and specify the following fields.

For a record delimiter, you can specify a character (for example, !) or character representation (for example, `\r\n` for carriage return).

Use the **Delimiter** record parser for the Flat File Application when each record is separated by a delimiter.

<u>Delimiter</u>	<u>Record type</u>	<u>Description</u>
Record	Character	Character that separates records in a flat file document.

--OR--

Character Position	Starting from the beginning of the document and counting from zero (0), the character position at which the record delimiter for this document is located.
---------------------------	--

Note For example, if you specify 3 as the character position, you have indicated that the record delimiter appears in the fourth character position from the beginning of the document.

<u>Delimiter</u>	<u>Field or composite type</u>	<u>Description</u>
Field or composite	Character	Character that separates fields in a flat file document.

--OR--

Character position	Starting from the beginning of the document and counting from zero (0), the character position at which the field delimiter for this document is located.
---------------------------	---

<u>Delimiter</u>	<u>Field or composite type</u>	<u>Description</u>
		<p>Note For example, if you specify 4 as the character position, you have indicated that the field delimiter appears in the fifth character position from the beginning of the document.</p>

<u>Delimiter</u>	<u>Subfield type</u>	<u>Description</u>
Subfield	Character	Character that separates subfields in a flat file document. The default is a period ".".
	--OR--	
	Character position	Starting from the beginning of the document and counting from zero (0), the character position at which the subfield delimiter for this document is located.
		<p>Note For example, if you specify 5 as the character position, you have indicated that the subfield delimiter appears in the sixth character position from the beginning of the document.</p>

<u>Delimiter</u>	<u>Quoted release character type</u>	<u>Description</u>
Quoted release character	Character	Character used to enable a section of text within a field to be represented as its literal value. Any delimiter characters that appear within this section will not be treated as delimiters.
		<p>Note For example, your field delimiter is (,) and your release character is ". When you want to use (,) within a field as text, you must prefix it with your quoted release character. When</p>

Delimiter	Quoted release character type	Description
		<p>using the <code>convertFlatFileToDocument</code> operation to create the strings <code>Doe, John</code> and <code>Doe, Jane</code>, the record would appear as <code>"Doe, John"</code>, <code>"Doe, Jane"</code>. When using the <code>convertDocumentToFlatFile</code> operation to create <code>"Doe, John"</code>, <code>"Doe, Jane"</code>, the value of the record would be <code>Doe, John</code> and <code>Doe, Jane</code>. When using the <code>convertDocumentToFlatFile</code> operation, if you have specified both the Release Character and the Quoted Release Character, the Quoted Release Character will be used.</p>
	--OR--	
	Character position	<p>Starting from the beginning of the document and counting from zero (0), the character position at which the quoted release character for this document is located.</p>
		<p>Note For example, if you specify 5 as the character position, you have indicated that the quoted release character appears in the sixth character position from the beginning of the document.</p>

Delimiter	Release character type	Description
Release character	Character	<p>Character used to enable a delimiter to be used for its intended, original meaning. The character following the release character will not be treated as a delimiter.</p>
		<p>Note For example, your field delimiter is <code>+</code> and your release character is <code>\</code>. When using <code>+</code> within a field as text, you must prefix it with your</p>

<u>Delimiter</u>	<u>Release character type</u>	<u>Description</u>
		release character. When using the convertFlatFileToDocument operation to create the strings a+b+c and d+e+f, the record would appear as a\b\+c+d\+e\+f. When using the convertDocumentToFlatFile operation to create a\b\+c+d\+e\+f, the value of the record would be a+b+c and d+e+f.

--OR--

<u>Character position</u>	<u>Description</u>
	Starting from the beginning of the document and counting from zero (0), the character position at which the field delimiter for this document is located.

Note For example, if you specify 5 as the character position, you have indicated that the field delimiter appears in the sixth character position from the beginning of the document.

Next, set the record identifier.

- Use a **Fixed Length** record parser type when each record is of a fixed length (for example, mainframe punch or print records). This parser splits a file into records of the same pre-specified length. To configure a fixed length record parser, in the **Record Parser Type** area, select **Fixed Length**.

Specify the following fields:

<u>Fixed Length</u>	<u>Field or composite type</u>	<u>Description</u>
Field or composite	Character	Character that separates fields or composites in a flat file document.

--OR--

<u>Fixed Length</u>	<u>Field or composite type</u>	<u>Description</u>
	Character position	Starting from the beginning of the document and counting from zero (0), the character position at which the field delimiter for this document is located.
		Note For example, if you specify 4 as the character position, you have indicated that the field delimiter appears in the fifth character position from the beginning of the document.

<u>Fixed Length</u>	<u>Subfield type</u>	<u>Description</u>
Subfield	Character	Character that separates subfields in a flat file document.
	--OR--	
	Character position	Starting from the beginning of the document and counting from zero (0), the character position at which the subfield delimiter for this document is located.
		Note For example, if you specify 5 as the character position, you have indicated that the subfield delimiter appears in the sixth character position from the beginning of the document.

<u>Fixed length</u>	<u>Quoted release character type</u>	<u>Description</u>
Quoted release character	Character	Character used to enable a section of text within a field to be represented as its literal value. Any delimiter characters that appear within

Fixed length	Quoted release character type	Description
		<p>this section will not be treated as delimiters.</p> <p>Note: For example, your field delimiter is (,) and your release character is ". When you want to use (,) within a field as text, you must prefix it with your quoted release character. When using the <code>convertFlatFileToDocument</code> operation to create the strings <code>Doe, John</code> and <code>Doe, Jane</code>, the record would appear as "Doe, John", "Doe, Jane". When using the <code>convertDocumentToFlatFile</code> operation to create "Doe, John", "Doe, Jane", the value of the record would be <code>Doe, John</code> and <code>Doe, Jane</code>. When using the <code>convertDocumentToFlatFile</code> operation, if you have specified both the Release Character and the and the Quoted Release Character, the Quoted Release Character will be used.</p>
	--OR--	
	Character position	<p>Starting from the beginning of the document and counting from zero (0), the character position at which the quoted release character for this document is located.</p> <p>Note: For example, if you specify 5 as the character position, you have indicated that the quoted release character appears in the sixth character position from the beginning of the document.</p>

<u>Fixed length</u>	<u>Release character type</u>	<u>Description</u>
Release character	Character	<p>Character used to enable a delimiter to be used for its intended, original meaning. The character following the release character will not be treated as a delimiter.</p> <p>Note: For example, your field delimiter is + and your release character is \. When using + within a field as text, you must prefix it with your release character. When using the convertFlatFileToDocument operation to create the strings a+b+c and d+e+f, the record would appear as a \+b \+c+d \+e \+f. When using the convertDocumentToFlatFile operation to create a \+b \+c+d \+e \+f, the value of the record would be a+b+c and d+e+f.</p>
--OR--		
	Character position	<p>Starting from the beginning of the document and counting from zero (0), the character position at which the field delimiter for this document is located.</p> <p>Note: For example, if you specify 5 as the character position, you have indicated that the field delimiter appears in the sixth character position from the beginning of the document.</p>
<u>Fixed length</u>	<u>Description</u>	
Record length	<p>In the Record Length field, enter the length, in characters, of each record in the flat file. Record length cannot be empty.</p>	

Next, set the record identifier.

- The **Variable Length** record parser type expects each record to be preceded by two bytes that indicate the length of the record. Each record may be a different length.

To configure a variable length record parser, in the **Record Parse Type** area, select **Variable length**, and specify the following fields:

<u>Variable Length</u>	<u>Field or composite type</u>	<u>Description</u>
Field or composite	Character	Character that separates fields or composites in a flat file document.
	--OR--	
	Character position	Starting from the beginning of the document and counting from zero (0), the character position at which the field delimiter for this document is located.
<p>Note: For example, if you specify 4 as the character position, you have indicated that the field delimiter appears in the fifth character position from the beginning of the document.</p>		

<u>Variable length</u>	<u>Subfield type</u>	<u>Description</u>
Subfield	Character	Character that separates subfields in a flat file document.
	--OR--	
	Character position	Starting from the beginning of the document and counting from zero (0), the character position at which the subfield delimiter for this document is located.
<p>Note: For example, if you specify 5 as the character position, you have indicated that the subfield delimiter appears in the sixth character</p>		

<u>Variable length</u>	<u>Subfield type</u>	<u>Description</u>
		position from the beginning of the document.

<u>Variable length</u>	<u>Quoted release character type</u>	<u>Description</u>
Quoted release character	Character	Character used to enable a section of text within a field to be represented as its literal value. Any delimiter characters that appear within this section will not be treated as delimiters.

NoteFor example, your field delimiter is (,) and your release character is “. When you want to use (,) within a field as text, you must prefix it with your quoted release character. When using the `convertFlatFileToDocument` operation to create the strings `Doe, John` and `Doe, Jane`, the record would appear as “`Doe, John`”, “`Doe, Jane`”. When using the `convertDocumentToFlatFile` operation to create “`Doe, John`”, “`Doe, Jane`”, the value of the record would be `Doe, John` and `Doe, Jane`. When using the `convertDocumentToFlatFile` operation, if you have specified both the Release Character and the and the Quoted Release Character, the Quoted Release Character will be used.

--OR--

Character position	Starting from the beginning of the document and counting from zero (0), the character position at which the quoted release character for this document is located.
---------------------------	--

NoteFor example, if you specify 5 as the character position, you have indicated that the quoted release character

<u>Variable length</u>	<u>Quoted release character type</u>	<u>Description</u>
		appears in the sixth character position from the beginning of the document.

<u>Variable length</u>	<u>Release character type</u>	<u>Description</u>
Release character	Character	<p>Character used to enable a delimiter to be used for its intended, original meaning. The character following the release character will not be treated as a delimiter.</p> <p>Note:For example, your field delimiter is + and your release character is \. When using + within a field as text, you must prefix it with your release character. When using the convertFlatFileToDocument operation to create the strings a+b+c and d+e+f, the record would appear as a\+b\+c+d\+e\+f. When using the convertDocumentToFlatFile operation to create a\+b\+c+d\+e\+f, the value of the record would be a+b+c and d+e+f.</p>
	Character position	<p>Starting from the beginning of the document and counting from zero (0), the character position at which the field delimiter for this document is located.</p> <p>Note:For example, if you specify 5 as the character position, you have indicated that the field delimiter appears in the sixth character position from the beginning of the document.</p>

Next, set the record identifier.

7. Specifying a Record Identifier

When parsing a file, Integration Cloud looks at a record and extracts an identifier out of the data and uses that identifier to connect the record definition with a particular record in the flat file. The name of the record definition must match the value obtained by the record identifier.

To set the record identifier for a definition, in the **Record identifier** area, set the record identifier to one of the following values:

Record identifier	Value	Description
	Start at position	<p>Identifies the character position in the record (counting from zero) where the record identifier is located. Start at position record identifiers compare the value that occurs in the record, at the specified offset, to all the record names defined in the flat file structure. Note that the Start at position identifier cannot distinguish between all types of record names.</p> <p>NoteFor example, if you name records “Rec1” and “Rec,” some instances of “Rec1” may be identified as “Rec,” because “Rec1” begins with “Rec.”</p>
	Nth field	<p>Identifies the field in the record (counting from zero) that contains the identifier. Nth field identifiers use the value of the specified field as the record identifier. These identifiers count from zero (0).</p> <p>NoteFor example, if 2 is specified, the third field is used as the record identifier.</p>

- Click **Next** to define the **Flat File Structure**. Use the **Flat File Structure** page to add records to the flat file structure and define the hierarchical relationships between them.

The application receiving the flat file uses the structure to read the flat file. This structural information identifies the parent-child relationships between different records in the flat file. By nesting record elements in the flat file structure (adding record elements to a record), you can represent the hierarchical structure of the data in the flat file.

To add the first record, click the **Add new element** icon and in the **Element type** field, select **Record Definition**. Specify a name for the record definition and click **Finish**.

- To add a **Composite Definition** after you have added a record definition, specify the following:

Extractor type	Description
Nth field	Field number in the record that contains the composite you want to extract. This pulls the subfield data from the composite. If you leave this property empty, the composite will not be extracted.

To add a **Field Definition** after you have added a record definition, specify the following:

Extractor type	Description				
Fixed Position	Counting from zero (0), indicates a fixed number of bytes to be extracted from a record.				
	<table border="1"> <thead> <tr> <th>Position</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td></td> <td>Type the first byte to extract from the record. Type the first byte that is not included in the extraction. If you enter a negative number (for example, -1), the extractor returns all bytes from the byte specified in Start to the last byte in the record or composite.</td> </tr> </tbody> </table>	Position	Description		Type the first byte to extract from the record. Type the first byte that is not included in the extraction. If you enter a negative number (for example, -1), the extractor returns all bytes from the byte specified in Start to the last byte in the record or composite.
Position	Description				
	Type the first byte to extract from the record. Type the first byte that is not included in the extraction. If you enter a negative number (for example, -1), the extractor returns all bytes from the byte specified in Start to the last byte in the record or composite.				
Nth field	Counting from zero (0), indicates the field that you want to extract from the record.				

Extractor

Type a value to indicate the position of the field that you want to extract from the record. This value cannot be null and must be an integer greater than or equal to zero (0).

Note: For example, if you type 1, the second field will be extracted.

This option is available only if you specified a field delimiter when configuring the definition and structure of the Flat File Application. This extractor returns the field as a key-value pair. The key is the name of the field. The value is the String value of the field.

10. Click **Finish** to create the flat file Application.

After creating the flat file Application, create an Orchestrated Integration, select the Flat File Application created, and invoke the following predefined operations:

- [“convertFlatFileToDocument” on page 353](#) - Converts the flat file to a document (inbound)
- [“convertDocumentToFlatFile” on page 356](#) - Converts a document to a flat file (outbound)

Creating a flat file Application from a sample file

When you create a flat file Application from a sample file, ensure that the format of the sample file is *.txt.

To create a flat file Application from a sample file

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > Flat File Applications > Add New Application**.
2. Type a name and description of the flat file Application and select the creation mode as **Create from a sample file**.
3. Click **Browse** and select the sample file from your computer. The file must have a record identifier. The **Preview** pane displays the sample file.
4. Click **Next** and in the **Record Parser** panel, select one of the following to indicate how the data in the sample file is formatted:

Record Parser	Description
Delimiter	Use this parser when each record is separated by a delimiter.
Fixed length	Use a fixed length record parser when each record is of a fixed length (for example, mainframe punch or print records). This parser splits a file into records of the same pre-specified length.
Variable length	This parser expects each record to be preceded by two bytes that indicate the length of the record. Each record may be of different length.

- If you select **Delimiter** as the parser type, specify the parser properties in the record parser panel. Integration Cloud updates the **Preview** contents based on your selections. Use the following table to specify the delimiters used in the sample file.

Property	Description
Record	Character that separates records in a flat file document. Note: If a new line character (\n) exists at the end of each record and the Record delimiter is not ending with \n, then Integration Cloud cannot render the records properly under the <code>Preview</code> pane.
Field or composite	Character that separates fields in a flat file document.
Subfield	Character that separates subfields in a flat file document.
Quoted release character	Character used to enable a section of text within a field to be represented as its literal value. Any delimiter characters that appear within this section will not be treated as delimiters. Note: For example, your field delimiter is (,) and your quoted release character is ". When you want to use (,) within a field as text, you must prefix it with your quoted release character. When using the <code>convertFlatFileToDocument</code> operation to create the strings <code>Doe, John</code> and <code>Doe, Jane</code> , the record would appear as <code>"Doe, John"</code> , <code>"Doe, Jane"</code> . When using the <code>convertDocumentToFlatFile</code> operation to create <code>"Doe, John"</code> , <code>"Doe, Jane"</code> , the value of the record would be <code>Doe, John</code> and <code>Doe, Jane</code> . When using the <code>convertDocumentToFlatFile</code> operation, if you have specified both the <code>Release Character</code> and the <code>Quoted Release Character</code> , the <code>Quoted Release Character</code> will be used.
Release character	Character used to enable a delimiter to be used for its intended, original meaning. The character following the release character will not be treated as a delimiter. Note: For example, your field delimiter is + and your release character is \. When using + within a field as text, you must prefix it

Property	Description
	with your release character. When using the <code>convertFlatFileToDocument</code> operation to create the strings <code>a+b+c</code> and <code>d+e+f</code> , the record would appear as <code>a\+b\+c+d\+e\+f</code> . When using the <code>convertDocumentToFlatFile</code> operation to create <code>a\+b\+c+d\+e\+f</code> , the value of the record would be <code>a+b+c</code> and <code>d+e+f</code> .

- If you select **Fixed length** as the parser type, specify the parser properties in the record parser panel. Integration Cloud updates the **Preview** contents based on your selections. Specify the position of each field in `Field separators`. The `Field separators` must be comma separated integer values, for example, 5, 10, 15. You can set a value for `Record length` to adjust the record so that it appears correctly under the `Preview` pane. `Record length` supports only positive integer values between one and total number of characters in the file. and cannot be empty.
- If you selected **Variable length** as the parser type, specify the parser properties in the Record Parser panel. Integration Cloud updates the `Preview` contents based on your selections. Use the following table to specify the delimiters used in the sample file.

Property	Description
Field	Character that separates fields in a flat file document.
Subfield	Character that separates subfields in a flat file document.
Quoted release character	<p>Character used to enable a section of text within a field to be represented as its literal value. Any delimiter characters that appear within this section will not be treated as delimiters.</p> <p>For example, your field delimiter is <code>(,)</code> and your quoted release character is <code>"</code>. When you want to use <code>(,)</code> within a field as text, you must prefix it with your quoted release character. When using the <code>convertToValues</code> service to create the strings <code>Doe, John</code> and <code>Doe, Jane</code>, the record would appear as <code>"Doe, John"</code>, <code>"Doe, Jane"</code>. When using the <code>convertToString</code> service to create <code>"Doe, John"</code>, <code>"Doe, Jane"</code>, the value of the record would be <code>Doe, John</code> and <code>Doe, Jane</code>. When using the <code>convertToString</code> service, if you have specified both the Release Character and the</p>

Property	Description
	Quoted Release Character, the Quoted Release Character will be used.
Release character	Character used to enable a delimiter to be used for its intended, original meaning. The character following the release character will not be treated as a delimiter. For example, your field delimiter is + and your release character is \. When using + within a field as text, you must prefix it with your release character. When using the <code>convertToValues</code> service to create the strings <code>a+b+c</code> and <code>d+e+f</code> , the record would appear as <code>a\+b\+c+d\+e\+f</code> . When using the <code>convertToString</code> service to create <code>a\+b\+c+d\+e\+f</code> , the value of the record would be <code>a+b+c</code> and <code>d+e+f</code> .

- Click **Next** to view the **Flat File Structure**. You can add records to the flat file structure and define the hierarchical relationships between them. The application receiving the flat file uses the structure to read the flat file. This structural information identifies the parent-child relationships between different records in the flat file. By nesting record elements in the flat file structure (adding record elements to a record), you can represent the hierarchical structure of the data in the flat file. To add a record, click the **Add new element** icon and select **Record Definition** from the **Element type** field. Specify a name for the record definition and click **Finish**.
- To add a **Composite Definition** after you have added a record definition, click the **Add new element** icon and select **Composite Definition** from the **Element type** field. Specify a name for the record definition and click **Finish**.

Extractor type	Description
Nth field-Extractor	Field number in the record that contains the composite you want to extract. This pulls the subfield data from the composite. If you leave this property empty, the composite will not be extracted.

To add a **Field Definition** after you have added a record definition, click the **Add new element** icon and select **Field Definition** in the **Element type** field.

Extractor Type	Description
Fixed Position	Counting from zero (0), indicates a fixed number of bytes to be extracted from a record.

Extractor	Description
-----------	-------------

Extractor Type	Description
	<p>Position</p> <p>Type the first byte to extract from the record. Type the first byte that is not included in the extraction. If you enter a negative number (for example, -1), the extractor returns all bytes from the byte specified in Start to the last byte in the record or composite.</p>
<p>Nth Field</p>	<p>Counting from zero (0), indicates the field that you want to extract from the record.</p>
	<p>Extractor</p> <p>Type a value to indicate the position of the field that you want to extract from the record. This value cannot be null and must be an integer greater than or equal to zero (0).</p>
	<p>Note For example, if you type 1, the second field will be extracted.</p>
	<p>This option is available only if you specified a field delimiter when configuring the definition and structure of the flat file Application. This extractor returns the field as a key-value pair. The key is the name of the field. The value is the String value of the field.</p>

- Click **Finish** to create the flat file Application.

After creating the flat file Application, create an Orchestrated Integration, select the flat file Application created, and invoke the following predefined operations:

- [“convertFlatFileToDocument” on page 353](#) - Converts the flat file to a document (inbound)
- [“convertDocumentToFlatFile” on page 356](#) - Converts a document to a flat file (outbound)

Flat File Predefined Operations

The following predefined Flat File operations are available:

convertFlatFileToDocument

Converts a flattened flat file data into a structured data, which will conform to the document type associated with the flat file Application.

Input Variables

<i>ffDataString</i>	String The flat file input with type of String.
<i>ffData</i>	Object The flat file input with type of InputStream or ByteArray. If both <i>ffData</i> and <i>ffDataString</i> are parsed, <i>ffDataString</i> takes precedence.
<i>ffIterator</i>	Object Optional. An object that encapsulates and keeps track of the input data during processing. It is used only when the <i>iterate</i> variable has been set to true.
<i>encoding</i>	String Optional. The encoding of the InputStream passed in to <i>ffData</i> . The default encoding is UTF-8.
<i>delimiters</i>	<p>Document Optional. A document object that contains the segment terminator and the field and subfield separators. If the delimiter is <code>null</code>, it will be located using the information defined in the definition and structure of the Flat File Application. To specify a delimiter, you can specify:</p> <ul style="list-style-type: none"> ■ One character or character representation (for example, <code>*</code>, <code>\n</code> for line terminator, <code>\t</code> for tab) ■ The space character

Variable	Description
<i>record</i>	String Character used to separate records. If you want to specify the two-character carriage return line feed (CRLF) characters, specify <code>\r\n</code> .
<i>field</i>	String Character used to separate fields.

<i>subfield</i>	String Character used to separate subfields.
<i>release</i>	String Character used to ignore a <i>record</i> , <i>field</i> , or <i>subfield</i> delimiter in a field. If a release character occurs in a field or subfield before the delimiter, it will be prefixed with the <i>release</i> .
<i>quotedRelease</i>	String Character to use to ignore a <i>record</i> , <i>field</i> , or <i>subfield</i> delimiter in a field. If a quoted release character occurs in a field or subfield before the delimiter, it will be prefixed with <i>quotedRelease</i> before being written to the output <i>string</i> . The string is pre- and appended with the quoted release character. For example, if * is a delimiter, the field value is a*b, and the quoted release character is “”, the string appears as “a*b”.
<i>iterate</i>	String Optional. Whether you want to process the input all at one time.
<i>createIfNull</i>	String Optional. Whether to create the document object if all the fields are null.
<i>skipWhiteSpace</i>	String Optional. Whether white space at the beginning of records will be ignored.
<i>keepResults</i>	String Optional. Whether to return the parsed data.
<i>validate</i>	String Optional. Whether to return error messages that describe how <i>ffData</i> differs from the definition and structure of the Flat File Application.
<i>returnErrors</i>	String Optional. Whether to return the validation errors.
<i>maxErrors</i>	String Optional. The maximum number of errors that can be returned from one record. When the flat file parser encounters more than the maximum number of errors within a record, the parser will stop parsing and return the parsed data and errors processed up until that point.

flags

String Optional. Flags that you can set to govern `convertFlatFileToDocument` options.

Variable	Description
<i>addRecordCount</i>	String Whether you want the operation to add an additional field (<i>@record-count</i>) to each parsed record in the resulting document object.
<i>detailedErrors</i>	String Whether you want detailed conditional validation error information.
<i>skipToFirstRecord</i>	String Whether you want the operation to wait until it finds the first valid record before reporting invalid records as errors.
<i>trimWhitespace</i>	String Whether you want the operation to delete any blank spaces at the beginning of fields, at the end of fields, or both.
<i>resultAsArray</i>	String Whether you want the operation to return the document object that represents the input flat file data as a document reference that can be mapped to the document types generated.

Output Variables

<flatfile_application_name> **Document** The name of the output document will be *flatfile_application_name_dt*, where *flatfile_application_name* is the name of the flat file Application. For example, if the Application name is *test*, then the name of the output document will be *test_dt*. The structure of the output document will be similar to what you have defined in your Flat File Application.

isValid **String** Whether flat file contains validation errors.

errors **String** Optional. An array containing the validation errors, if any, that were found in *ffData* or *ffDataString*.

convertDocumentToFlatFile

Converts a structured data conforming to the given document type structure associated with the Application, to the flattened flat file data.

Input Variables

<i><flatfile_application_name>_dt</i>	Document Structure conforming to the Document type created for the corresponding application of this operation.
<i>spacePad</i>	String Optional. How to position the records in the flat file.
<i>signalError</i>	String Whether to create errors in the output.
<i>noEmptyTrailing Fields</i>	String Whether trailing empty fields are to be removed from the output. Used only with records that have delimited fields.
<i>noEmptyTrailing SubFields</i>	<p>String Whether trailing empty subfields are to be removed from the output. Used only with records that have delimited fields.</p> <p>If no value is specified for the <i>noEmptyTrailingSubFields</i> parameter, Integration Cloud uses the value set for the <i>noEmptyTrailingFields</i> parameter.</p>
<i>delimiters</i>	<p>Document Optional. The separator characters used to construct the output string. To specify a delimiter, you can specify:</p> <ul style="list-style-type: none"> ■ One character or character representation (for example, *, \n for line terminator, \t for tab)

<u>Value</u>	<u>Description</u>
<i>record</i>	String Character to use to separate records. If you want to specify the two-character carriage return line feed (CRLF) characters, specify \r\n.

<i>field</i>	String Character to use to separate fields.
<i>subfield</i>	String Character to use to separate subfields.
<i>release</i>	String Character to use to ignore a <i>record</i> , <i>field</i> , or <i>subfield</i> delimiter in a field. If a release character occurs in a field or subfield before the delimiter, it will be prefixed with <i>release</i> before being written to the output <i>string</i> .
<i>quotedRelease</i>	String Character to use to ignore a <i>record</i> , <i>field</i> , or <i>subfield</i> delimiter in a field. If a quoted release character occurs in a field or subfield before the delimiter, it will be prefixed with <i>quotedRelease</i> before being written to the output <i>string</i> . The string is pre- and appended with the quoted release character. For example, if * is a delimiter, the field value is a*b, and the quoted release character is ", the string appears as "a*b".
<i>FormatInfo</i>	Document Any values mapped to the <i>FormatInfo</i> variable will be passed unmodified to all format operations invoked by <code>convertDocumentToFlatFile</code> and <code>convertFlatFileToDocument</code> .
<i>outputFileName</i>	String Optional. If you want the output returned in a file instead of in the <i>string</i> output variable, provide the name of the file you want created as a result of this operation.
<i>Encoding</i>	String The type of encoding used to write data to the output file. The default encoding is UTF-8.

<i>sortInput</i>	String Optional. Whether you want the operation to sort the input records to match the definition and structure of the Flat File Application.
<i>returnAsBytes</i>	Returns the document as a string or as a byte array instead of a string.

Output Variables

<i>string</i>	String Data that represents the flat file document.
<i>bytes</i>	Object If the input variable <i>returnAsBytes</i> is <code>true</code> , returns the output as a byte array encoded using the specified encoding. The string value is not returned.
<i>errorArray</i>	Object String array containing messages pertaining to errors that occurred during conversion.

Usage Note

When the `convertDocumentToFlatFile` operation executes, the field that is defined to start after the end of the fixed length record will not be included in the output data if the following conditions are met:

- The definition and structure of the Flat File Application uses a fixed length record delimiter.
- The definition and structure of the Flat File Application contains a fixed position field that begins beyond the defined length of the fixed length record.
- The input to the `convertDocumentToFlatFile` operation contains a value for the fixed position field that begins beyond the defined length of the fixed length record.

6 Accounts, Operations, Listeners

■ Accounts	360
■ Operations	362
■ Listeners	370

Accounts

This screen lists all the available Accounts created for an Application.

If you select an Account for an FTP, SFTP, custom SOAP, or on-premises Application and click **Test Connection**, the screen displays the status of the connection. If you have configured the Account details incorrectly in any stage, the status appears in red color in the **Connectivity Status** column. If an Account is configured correctly in a particular stage, the status appears in green color and if an Account is not configured in a particular stage, the status appears in white color.

For on-premise Applications, the Account can be used to execute services on the on-premises webMethods Integration Server. See the *Configuring On-Premise Integration Servers for webMethods Cloud* document for information on how to configure webMethods Integration Server as an on-premise server for use with Integration Cloud.

Note: Only enabled or active Accounts are listed in the drop down list of the Operation wizard, Integration wizard, Look up Transformer, and Manage Stages page.

You can create, edit, or delete an Account for a particular application from this screen.

Note: Users who have the required permissions under **Settings**  **> Access Profiles > Administrative Permissions > Functional Controls > Accounts** can create, update, or delete the Accounts information.

To create or edit an Account

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > Applications > <Application category>**.
2. Select an Application from the Application category page and then click **Accounts**.
To use an Application, you are required to agree to the summary of terms. Click **I agree** to use the Application. Click **I do not agree** if you disagree with the summary of terms and do not want to use the Application. Click **Cancel** to go back to the **Applications** page.
3. From the Accounts screen, click **Add New Account** to add an Account or click **Edit** to update an existing Account.

Adding or Editing Accounts

Use the **Accounts** page to add, edit, or delete Accounts. The options available may vary according to the selected Application.

Note: See the [“Predefined Applications” on page 109](#) section for information on the Account configuration fields for each Application.

To add or edit an Account

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > Applications > <Application category>**.
2. Select an Application from the page, and then click **Accounts**.

To use an Application, you are required to agree to the summary of terms. Click **I agree** to use the Application. Click **I do not agree** if you disagree with the summary of terms and do not want to use the Application. Click **Cancel** to go back to the **Applications** page.

3. From the **Accounts** page, click **Add New Account** to add an Account or click **Edit** to change any field in an existing Account.
4. On the **New Account** or **Edit Account** page, complete the following fields. Required fields are marked with an asterisk on the page.

Note: Based on the Application you had selected, applicable fields are displayed.

Field	Description
Save As	Provide a valid name for the Account. This field is common for all Applications. Names can contain alphanumeric characters, underscores (_), and hyphens (-). The name must not be null and cannot be an empty string.
Description	Provide a description for the Account. This field is common for all Applications.
Authentication Type	Every back end provides its own authentication mechanism. Here you can select different authentication schemes for the same Application. Get the authentication details from the back end documentation for the Application and select the supported Authentication Type from the drop-down list. The Account Configuration Fields may vary according to the selected authentication type.

Note: You cannot change the authentication type while editing the Account. Further, this functionality may not be available for all Applications.

Credentials: Basic authentication credentials.

OAuth V2.0 (Authorization Code Flow): An OAuth 2.0 flow that is used to grant an access token to server-

Field	Description
	hosted applications. In this flow, CloudStreams opens the web page for authorization, and after authorization, redirects the authorization code to CloudStreams.
	OAuth V2.0 (JWT Flow): Authorization by a signed JWT.

The Account configuration section allows you to provide details to connect with the Application. The fields available may vary according to the selected Application. See the [“Predefined Applications” on page 109](#) section for information on the Account configuration fields for each predefined Application. If you have configured the Account details incorrectly in any stage, the stage will appear in red text and the Account will be inactive. If an Account is configured correctly in a particular stage, then the stage appears in green text and is active. Only active or enabled Accounts are listed in the drop down list of the Operation wizard, Integration wizard, Look up Transformer, and Manage Stages page.

See [“Manage Stages” on page 650](#) for more information.

You must have the permission to administer stages (**Settings**  **> Access Profiles > Administrative Permissions > Functional Controls > Stages**) if you want to create or delete stages.

- Click **Save** or **Update** to save your settings.

A new Account will be created.

Operations

Integration Cloud provides pre-configured applications. The Applications contain SaaS provider-specific information that enables you to connect to a particular SaaS provider. Further, each Application uses an Account to connect to the provider's back end and perform Operations.

Note: Users who have the required permissions under **Settings**  **> Access Profiles > Administrative Permissions > Functional Controls > Operations** can create, update, or delete Operations.

Each application comes with a predefined set of Operations. You can also create your own custom Operations and also edit/delete those custom Operations. This page lists all the available Operations for a selected application including predefined Operations.

See [“FTP Predefined Operations” on page 201](#) for information on the FTP operations.

See [“SFTP Predefined Operations” on page 259](#) for information on the SFTP operations.

See “AS2 Predefined Operations” on page 117 for information on the Applicability Statement 2 (AS2) operations.

See “Database Application Operations” on page 157 for information on the Database operations.

See “Cloud Deployment Operations” on page 138 for information on how to import Cloud Deployment services.

To create or edit a custom Operation

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > Applications**.
2. Select an Application category and then click **Operations**.

To use an Application, you are required to agree to the summary of terms. Click **I agree** to use the Application. Click **I do not agree** if you disagree with the summary of terms and do not want to use the Application. Click **Cancel** to go back to the **Applications** page.

3. From the Operations page for the selected Application, click **Add New Operation** to create a new Operation or select an Operation and click **Edit** to update an existing Operation. You can click **Delete** to delete an existing Operation, click **Show Signature** to view the input and output signature of the Operation, or click **Test** to test the Operation. The **Add New Operation** option is not available for some Applications.

Select an Operation and click **Show Signature** to view the input and output signature of the operation. The input and output fields cannot be edited. This option is available for all predefined and custom operations. Click the input and output fields to view the field properties. From the **Input** or **Output** pane, click the  icon to copy a field. Depending on the context, you can either paste the field or the field path.

Click the **Test** option and in the test dialog box, specify the **Account** name and the **Input** data. If an operation does not have an input signature, the input fields are not displayed. The **Test** option is available for all predefined and custom operations.

Click **Run** to test the Operation and view the test results in the test results window.

Click the  icon beside **Result** if you want to go back to the test dialog box and enter another set of values. The last 5 test results are also displayed and are applicable only for the same test operation run, that is, if you close the test results window, you will not be able to view the test results later. Further, a test result appears in red color if the test run is unsuccessful and appears in green color for a successful test run.

Adding or Editing Operations

Use the **Operations** page to add, edit, or delete custom operations.

To add or edit a custom operation

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > Applications**.
2. Select an Application from an Application category and then select **Operations**.
To use an Application, you are required to agree to the summary of terms. Click **I agree** to use the Application. Click **I do not agree** if you disagree with the summary of terms and do not want to use the Application. Click **Cancel** to go back to the **Applications** page.
3. From the Operations page for the selected Application, click **Add New Operation** to add a custom operation or click **Edit** to update an existing custom operation. The **Add New Operation** option is not available for some Applications.
4. On the **Select your <...> account** page, complete the following fields. Required fields are marked with an asterisk on the page.

Field	Description
Save as	Provide a name for the custom operation.
Description	Provide a description for the custom operation.
Select account	Select an Account created for the Application from the drop-down list. Only active or enabled Accounts are listed in the drop-down list. Note: If you select an Account with a different Authentication Type, existing Integrations that are using this Account may not work.
Select functional area	Select the Application service from the drop-down list. Note: This option is available only for certain Applications.
Enable dynamic account configuration at runtime	For REST Application operations, you can now provide account configurations at <i>runtime</i> during integration execution. Select the Enable dynamic account configuration at runtime check box and then click Configure Fields to run the operation by passing authentication details that may be <i>different</i> from the authentication details configured in the Account configuration page. Dynamic authentication overwrites the Account configuration details.

Field	Description
	<p>For example, suppose you have configured authentication details X for Account A. You can use different authentication details Y to run the service, by overwriting the authentication details X of Account A.</p>
	<p>Note: Enable dynamic account configuration at runtime is currently supported only for custom REST Applications. Further, the option is enabled only after you have selected an Account in the Select account field.</p>
	<p>While creating an operation, if you select the Enable dynamic account configuration at runtime check box and click Configure Fields, the Dynamic Account Configuration Fields window appears. Select the fields you want to include in the operation input signature. When you select the fields, the operation input signature will be automatically updated based on your selections. Only the fields that are part of the signature gets mapped as the input request. You can override the field values at run time. Default Account configuration values will be used for other fields while creating the operation.</p>
	<p>Note:</p> <ul style="list-style-type: none">■ You cannot clear encrypted fields like Access Token and Consumer Secret. Further, you cannot enter a value for encrypted fields. You can enter the values for encrypted fields only while running the operation.■ While running the operation, if you have provided details in both the Account configuration page and in the Dynamic Account Configuration Fields dialog box, Integration Cloud reads the data from the Account configuration page and merges the data with the data provided in the Dynamic Account Configuration Fields dialog box. Existing Account configuration details will not be modified.■ Details specified in the Dynamic Account Configuration Fields dialog box take precedence over the details specified in the Account configuration page.■ If you pass incorrect values in the Dynamic Account Configuration Fields dialog box, service execution will fail while running the operation.

5. Click **Next**.

The **Select the Operation** page appears. If you do not want to add **Headers** and **Parameters**, skip to Step 9.

6. For a REST-based Application, select an operation and click **Headers** to add input Headers, if required. Integration Cloud displays the default HTTP transport headers for the operation, along with their default values. At run time, while processing the headers, Integration Cloud substitutes the values as necessary. In order to customize the headers, do the following:
 - a. Click **Add Header** to add a custom Header. Specify the **Header** name. To specify an optional default value for the header variable, click the **Default Value** box and type or paste the new value. If the variable is null in the input pipeline, this value will be used at run time. If the variable already has an existing default value defined, this value will overwrite the existing value at run time.
 - b. If headers appear in the signature, select **Active** to activate the headers in the signature.
 - c. To delete a custom header that you have added, select the header and click **Delete**.

Note: You cannot delete the required headers.

7. For a REST-based Application, select an operation and click **Parameters**. To customize the parameters, do the following:
 - a. Review the operation parameter details. Integration Cloud displays the parameter **Name** and **Description**, the **Data Type** used to represent the kind of information the parameter can hold, the parameterization **Type** of the request, and the default value needed to access the operation.
 - b. To specify a default value for the parameter, click the **Default Value** box and then type or paste the default value. The default value is used at run time.

You cannot add or delete request parameters. You can only modify the default value of a parameter. If parameters appear in the signature, select **Active** to activate the parameters in the signature.

8. For some Applications and Operations, for example, for the *CloudStreams Connector for Salesforce(R) Bulk v2 Data Loader* Application and *Create Job and Upload Job Data* Operation, Integration Cloud supports multipart request body. For example, if you want to create a user as well as upload a photo, the request has to be a multipart request where one part is an image file while the other part is a JSON request body.

Though application/x-www-form-urlencoded is a more natural way of encoding, it becomes inefficient for encoding binary data or text containing non-ASCII characters. The media type *multipart/form-data* is the preferred media type for request payloads that contain files, non-ASCII, and binary data. Integration Cloud supports this media type using which you can embed binary data such as files into the request body.

A multipart/form-data request body contains a series of parts separated by a boundary delimiter, constructed using Carriage Return Line Feed (CRLF), "--", and also the value of the boundary parameters. The boundary delimiter must not appear inside any of the encapsulated parts.

Each part has the Type, Name, Content-Type, and Part ID fields.


Example of a multipart request

```
--BOUNDARY
Content-Type: application/json
Content-Disposition: form-data; name="job"
{
  "object": "Contact",
  "contentType": "CSV",
  "operation": "insert"
}
--BOUNDARY
Content-Type: text/csv
Content-Disposition: form-data; name="content"; filename="content"
(Content of your CSV file)
--BOUNDARY-
```

Part Configuration

The **Part Configuration** window lists all the configured parts to be sent to the service provider. To view the **Part Configuration** window, on the **Select the Operation** page, select **Attachments**.

The configured parts appear in the input signature.



- **Name** - The **Name** field displays the name of the file part as documented in the SaaS provider API documentation.
- **Content Type** - The **Content Type** field displays the content type of the file you are uploading.
- **Type - Document** - Some back ends expect application/json or application/xml content in the part body. This represents a part where the content of the part is of type application/json or application/xml. **File** - Represents a binary part of

a multipart/form-data payload where the content of the part is binary or the content of the file itself. For file upload kind of use cases, this part is the main or mandatory part required by the service provider.

9. On the **Select the Operation** page, select the operation to be performed and then click **Next**. Depending on whether the operation is Complex, Simple, or Dynamic, the **Business Object** or the **Interactions** page appears. Examples of **Business Objects** are Contact, Account, and so on and examples of **Interactions** are Create, Update, Upsert, Delete, and so on.

Note: For some operations, Integration Cloud displays appropriate Business Object pages, for example, for the createMultiple and updateMultiple operations in the Salesforce v42 Application, or Interactions (sub-operations) pages, for example, for the Batch and ChangeSet operations in the OData 4.0 Application, depending on whether the selected operation requires metadata, such as a business object, fields, and data types of fields. You can add or edit multiple business objects in a single request. You can also add or edit interactions and then associate those interactions with business objects in a single request. Interactions or multiple business objects will be executed in the same sequence as they appear in the table. You can drag and drop the interactions or multiple business objects to change the order in which they will be executed.

Different pages appear based on the scenarios mentioned in the following *Single or Multiple Interactions with Single or Multiple Business Objects with dependencies* section.

Single or Multiple Interactions with Single or Multiple Business Objects with dependencies

- **Single operation has a single Business Object** - An operation has only a single business object. The operation has neither multiple interactions nor has records. An example of a single operation and a single object can be a "create" operation that contains only the "contact" business object.
- **Single operation has multiple Business Objects** - A single operation has multiple business objects. An example of a single operation with multiple business objects can be a "create" operation that contains two business objects, "contact" and "account".
- **Single operation has multiple Business Objects with dependencies** - A single operation has multiple business objects and some of the business objects may have dependencies on other business objects.
- **Multiple Interactions have multiple Business Objects** - Multiple Interactions have multiple business objects. For example, the "create" and "update" Interactions can act on the "account" and "contact" business objects respectively.
- **Multiple Interactions have multiple Business Objects with dependencies** - Multiple Interactions have multiple business objects and some of the business objects may have dependencies on other business objects. For example, the "create" and "update" Interactions can act on the "account" and "contact" business objects respectively.

Further, for some operations, for example, for the *Retrieve Contained Or Derived Entity* operation in the OData 4.0 Application, Integration Cloud displays nested, hierarchical, or multi-level business objects if the operation is designed to support nested business objects. You can expand the nested business objects to display the child-level objects.

10. Select the Business Object to be associated with the operation you have selected in the previous step and then click **Next**. For some operations, you must select the Interaction and then the Business Object. Business Objects and Interactions appear only for certain Applications and operations.
11. In the **Data Fields** page, select the data fields for the Business Object you have chosen in the previous step and then click **Next**. Data fields appear only for certain Applications and operations. Mandatory data fields for the Business Object are selected by default and cannot be cleared.

Note: For some operations of certain Applications, for example, Coupa, you can add your own fields. Such fields are called custom fields. Custom fields are marked by *custom* on the page. You can add, edit, or delete only custom fields. Click the  icon to add a custom field. The  icon appears only if you are allowed to add custom fields for the selected operation. After you have added a custom field, you can click on the custom field to edit the field properties.

Simple fields appear with a check box while complex fields appear with a check box followed by an arrow mark. The following states are observed for complex fields:

- **Unchecked** - For unchecked complex fields, only the mandatory child fields are selected but those fields will not be added to the signature, unless you select the parent field.
- **Checked** - If a complex field is selected by default, then only the mandatory child fields are selected. You can select the optional fields, if required. If you select a complex field, then all the child fields are selected.

Note: For some Applications, for example, Microsoft Dynamics CRM, you can choose the way a query can be executed in the **Confirm operation** page. Choose the operation and then click **Finish**.

12. In the **Confirm Operation** page, verify the details. You can click the **Data Fields** link to view the data fields you have added. For some operations, you can click the Business Object link to view the data fields added.
13. Click **Finish** to create the custom operation.

After you click **Finish** or **Save**, if there are any Business Parameters, you will be asked to configure the Business Parameters.

Listeners

Some Integration Cloud Applications now support connectivity with streaming APIs and processing of streaming API events. You can use Integration Cloud Accounts to connect to streaming APIs. While creating an Integration Cloud listener, you select a subscription channel from a list of available channels for an endpoint and select the Integration that will be invoked when the events are received. Additionally, you can configure transport or communication related parameters for an Integration Cloud listener as well as enable and disable the listener. A listener receives the streaming API events and processes the received events.

Note: Currently, only some Integration Cloud Applications support streaming API capability, for example, the Salesforce CRM version 44 Application. Salesforce trial accounts have restrictions on the maximum number of concurrent subscribers. See [“PushTopic Streaming Allocations”](#) for information. So if you create multiple listeners using the same trial account details, due to the high availability nature of Integration Cloud, some active listeners may not work properly.

Creating and updating listeners

To add a listener

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project > Applications > Predefined Applications**.

Note: You must have the required permissions under **Settings  > Access Profiles > Administrative Permissions > Functional Controls > Listeners** to create, update, and delete listeners. Further, to create a Listener and also invoke the associated Integration when events are received, you must have the Listeners **Create** permission and the Integration **Execute** permission.

2. Select a predefined Application and click **Listeners**.

To use an Application, you are required to agree to the summary of terms. Click **I agree** to use the Application. Click **I do not agree** if you disagree with the summary of terms and do not want to use the Application. Click **Cancel** to go back to the **Applications** page.

The **Listeners** page appears for the selected Application.

Note: **Listeners** option appears only for Applications that have streaming API capability.

3. On the **Listeners** page, click **Add New Listener** to add a listener or click **Edit** to update a listener.

4. On the **Configure the Listener** page, complete the following fields. Required fields are marked with an asterisk on the screen.

Field	Description
Save As	Provide a valid name for the listener. Names can contain alphanumeric characters, underscores (_), and hyphens (-). The name must not be null and cannot be an empty string.
Description	Provide a description for the listener.
Streaming API Endpoint URL	Specify the endpoint of the streaming provider. When configuring a Salesforce streaming endpoint, specify the URL in the following format: <code>https://<Salesforce_Instance>/cometd/<Salesforce API version></code> Example: <code>https://ap5.salesforce.com/cometd/44.0</code>
Select replay option	<p>The Integration Cloud listener for Salesforce can subscribe and listen to Salesforce events. This allows the Integration Cloud listener to establish a persistent connection with Salesforce. This connection remains open while transmitting the events until either side closes the connection. Through this established connection, events are streamed to the listener. If the connection is lost due to a network failure or any other reason, you can retrieve the standard-volume events that are within Salesforce's 24-hour retention window. You can retrieve Salesforce events only if you are using Salesforce v37.0 or later versions.</p> <p>Each Salesforce event is assigned an opaque ID which is unique for each event. This ID is contained in the <code>replayId</code> field of the event object. The <code>replayId</code> field value which is populated by Salesforce when the event is delivered to subscribers, refers to the position of the event in the event stream. For consecutive events, <code>replayId</code> values may have a break between them, for example, the event with ID 110 may follow the event with ID 101.</p> <p><i>Example of an event object that Salesforce sends to its subscribed clients</i></p> <pre>{</pre>

Field	Description
	<pre data-bbox="667 304 1497 569"> "clientId": "alps4wpe52qytvcvbsko09tapc", "data": { "event": { "createdDate": "2016-03-29T19:05:28.334Z", "replayId": 55 }, "payload": "This is a message." }, "channel": "/u/TestStreaming" } </pre> <p data-bbox="667 590 1497 793">To replay events, Salesforce provides a way to configure the <code>replayId</code> while subscribing to a particular channel. You can replay the events by specifying the <code>replay</code> option and can use it on a resubscription, to retrieve events that are within the retention window.</p> <ul data-bbox="667 814 1497 1039" style="list-style-type: none"> ■ New - Receive new events that are broadcast after the client subscribes and replay only the new events from the time the listener is enabled. ■ All - Receive all events including past events that are within the retention window including new events. Replay all the events for the last 24 hours.
Select account	<p data-bbox="667 1081 1497 1285">Select an account to connect to the Application. The streaming functionality will leverage the existing authentication, timeouts, truststore, keystore, and host name verification configurations from the referenced Account selected in the Select account drop-down list box.</p>
Select subscription	<p data-bbox="667 1327 1497 1432">Select a channel from the list of available subscription channels, that is, select the subscriber you want the listener to connect.</p>
5. Click Next .	<p data-bbox="667 1474 1497 1558">The Parameters and Headers page appears.</p>
6. In the Parameters section, Integration Cloud displays the pre-configured parameters for the selected subscription.	<ol data-bbox="667 1579 1497 1894" style="list-style-type: none"> a. Review the details about the parameters. Integration Cloud displays the parameter name and description, the data type used to represent the kind of information the parameter can hold, and the parameterization type for the subscription request. b. To specify the default value for the parameter, select the pre-configured parameter and click Edit. In the Parameter Properties dialog box, type the default

- value. For example, for Salesforce, type the Topic Name. The **Active** option includes the parameter as part of the subscription request.
7. In the **Headers** section, Integration Cloud displays the pre-configured HTTP transport headers for the selected subscription.
 - a. To specify a value for a pre-configured header variable, click **Edit** and then in the **Header Properties** dialog box, type the new default value.
 - b. To add a header, click **Add Header**. Type a name for the header, select the **Active** check box to include the header as part of the subscription request, and provide a default value.
 - c. To delete a header that you have added, select the header and click **Delete**.

Note: You cannot delete required headers.

8. Click **Next**.

The **Event** page appears.

9. On the **Event** page, specify the event action configuration for the listener subscriber. You can invoke an Integration based on your configuration.
 - a. In the **Integration Name** field, select the Integration that will be invoked when the events are received. In the **Run As User** field, select the Integration Cloud user you want Integration Cloud to use when running the Integration. Integration Cloud runs the Integration as if the user you specify is the authenticated user that invoked the Integration. If the Integration is governed by an Access Control List (ACL), ensure that you specify a user that is allowed to invoke the Integration.

Note: You must manually run the Integration before you map that Integration to the listener, else the listener will not execute the mapped Integration.

10. Click **Next**, review the **Summary** details, and then click **Finish** to create the listener.

The new listener appears on the **Listeners** page.

11. To enable the new listener, move the slider under the **Status** column.

The listener will be enabled after a short delay. Once the listener is enabled, connection with the streaming API is established, and incoming events will be processed whenever the streaming provider triggers the events.

Note: As an example, for Salesforce CRM version 44, you have created a topic using the following sample query.

Sample Query

```
PushTopic testCvent = new PushTopic();
testCvent.ApiVersion = 42.0;
testCvent.Name = 'TestContact';
testCvent.Description = 'All records for the Contact object';
testCvent.Query = 'SELECT Id, Email, Phone, FirstName, LastName, Title, Salutation
FROM Contact';
insert testCvent;
System.debug('Created new PushTopic: '+ testCvent.Id);
```

After that you have subscribed to that topic by creating a listener in Integration Cloud. Now whenever the Contact object is modified in Salesforce, the Integration Cloud listener is notified.

To use the streaming data as an input to an Integration, ensure that you create a JSON document type that has the same fields inside subject as that of the query parameters of the topic.

Sample Document

```
{
  "data":{
    "event":{
      "createdDate":"","
      "replayId":"","
      "type":""
    },
    "subject":{
      "Email":"","
      "Phone":"","
      "FirstName":"","
      "Title":"","
      "LastName":"","
      "Id":"","
      "Salutation":"","
    }
  },
  "channel":"/topic/TestContact2"
}
```

Note: If a listener L1 is using an Integration IN1 and if IN1 uses an Operation OP1 which triggers L1 through a Salesforce Topic, then whenever OP1 is run, L1 will be triggered. L1 will again execute IN1 and IN1 will again execute OP1, thereby creating Integration execution loops. Therefore ensure that loops are not created in an Integration, which is mapped to a listener.

7 Integrations

■ Overview	376
■ Point-to-Point Integrations	378
■ Orchestrated Integrations	380
■ Pipeline and Signatures	393
■ Default Pipeline Rules for Linking to and from Array Variables	396
■ Indexed Mapping	399
■ Integration Details	400
■ Versioning of Integrations	406
■ Preview Integrations	407
■ Debug Integrations	409
■ Export Integrations	412
■ Import Integrations	413
■ Lock and Unlock Integrations	414

Overview

An Integration is an orchestration of a source and a target Operation with appropriate data mappings and transformations.

Note: Users who have the required permissions under **Settings**  > **Access Profiles** > **Administrative Permissions** > **Functional Controls** > **Integrations** can create, update, delete, execute, or deploy Integrations.

Integrations page

The **Integrations** page lists Point to Point and Orchestrated Integrations created for cloud-based SaaS applications with other cloud-based applications and also SaaS applications with on-premises applications. The **Name** column in the **Integrations** page displays the name of the Integration. If you select an Integration and click the Integration name link under the **Name** column, the Integration details **Overview** page appears for that Integration. To view the last five execution results for an Integration, click **Last 5 Execution Results** available in the Integration details page. The **Type** column shows whether the Integration is an Orchestration or a Point to Point. The **Uses** column displays the Integrations, Accounts, Operations, Applications, Reference Data, Document Types, and so on that are used or utilized to create the Integration. The Integrations list page by default shows a basic view of all the Integrations. To view the references (*Uses* column), select the **Show Advanced View** check box. Click the  icon to view the components used by the Integration. The **Created On** column displays when the Integration was created and the **Created By** column displays who created it.

Create, Edit, Delete, and Copy Integrations

To create an Integration:

- Click **Add New Integration**.
- To create a Point to Point Integration, select **Synchronize two applications**.
- To create an Orchestrated Integration, select **Orchestrate two or more applications**.

To edit an Integration:

- Select the Integration you want to edit.
- Click **Edit**. The Integration opens up for editing in the **Design** panel.

To delete an Integration:

- Select the Integration you want to delete.
- Click **Delete**. The Integration is permanently deleted and you cannot recover it.

To copy an Integration:

- Select the Integration you want to copy. You can make a copy of the Integration within the same project or in another project.
- Click **Copy**.
- In the **Select Project** field, the currently open project is set as the default option. To copy to another project, select the project from the drop-down list as shown in the following example:

Copy Addint1
✕

Select Project *

MapperTest

Copy As *

Addint2

!

Ensure to create any account or reference data associated with this asset in the target project

Cancel

Copy

- Provide a different name in the **Copy As** field
- Click **Copy**. The system creates a copy of this Integration with the new name in the Integrations page of the target project.

Note: Ensure that you create any account or reference data associated with this Integration in the target project.

Export and Import Integrations

To export an Integration, select the Integration, and then click **Export**. See “[Export Integrations](#)” on page 412 for more information.

Note: Users who have the required permissions under **Settings**  > **Access Profiles** > **Administrative Permissions** > **Functional Controls** > **Assets** can export assets.

To import Integrations, select the Integration, and then click **Import Integrations**. See “[Import Integrations](#)” on page 413 for more information.

Note: If assets used by an Integration are deleted, you will not be able to deploy the Integration into subsequent stages or export the Integration. See “[Deploy Assets](#)” on page 652 for information on how to deploy assets.

Point-to-Point Integrations


Integration Cloud enables you to integrate your cloud-based Software as a Service (SaaS) applications with other cloud-based SaaS applications. It also integrates your SaaS applications with on-premises applications.

Integration between two cloud providers includes the following steps:

- Invoking a source Operation on an application, which fetches data from it
- Invoking a target Operation on an application, which uploads data into it
- Filtering the data fetched from an application, before it is passed on to the target application
- Mapping the data fetched from an application, to the structure needed by the target application to which you want to upload the data.

To add or edit an existing Point-to-Point Integration

1. From the Integration Cloud navigation bar, click **Projects**. The **Projects** screen appears.
2. Select a project in which you want to create the Integration. You can also create a new project. See [“Projects” on page 50](#) for more information.
3. To edit an existing Integration, select an Integration from the **Integrations** screen and click **Edit**.
4. To create a new point-to-point Integration, from the **Integrations** screen, click **Add New Integration**, select **Synchronize two applications**, and click **OK**.



Note: See [“Orchestrated Integrations” on page 380](#) for information on how to create an orchestrated Integration.

Note: To use an Application, you are required to agree to the summary of terms. Click **I agree** to use the Application. Click **I do not agree** if you disagree with

the summary of terms and do not want to use the Application. Click **Cancel** to go back to the **Applications** page.

5. Provide a name and description of your Integration. Required fields are marked with an asterisk on the screen.
6. Drag and drop your applications to the **Source** and **Target** sections. You can also double-click an Application to move it to the required section.
7. Select an Account, and then select a custom or a predefined Operation in both the Source and Target sections. Only active or enabled Accounts are listed in the drop down list.

Note: If you had already done the mapping for a source and target Operation, and you want to change any of the source and target Operations, all the mappings you had performed before will be removed.

8. Click **Next** to filter the data fetched by the application selected in the source section, before it is passed on to the application selected in the target section. Click **Load Data** to preview the data as well as view the data filters. The source Operation fetches the data and displays a sample of the data in the preview pane. Out of all the records fetched, you may want to upload only selected records. To do this, you can have a selection or a filter criteria so that you can view only a few records. A **sample preview** of only a few records can be viewed to analyze the kind of data that exists in the system. After you analyze the records, you can set filters, to upload, for example only Accounts that are based out of California to the target application. After you set the filters, whenever you run the Integration, all records will be fetched from the source application, but only the filtered records will be moved to the target application after mapping and transformation.
9. Click **Next** to map the data fetched by the application selected in the source section, to the structure needed by the application selected in the target section.

Select a field from the source section and drag and drop it on to a relevant field in the target section. Select a mapping and then click the **Unmap** icon to unmap only the selected mapping. Click the **Clear All** icon to unmap all the mapped elements, values set for fields, and transformers. To view only the mapped fields, select the **Show Only Mapped Fields** option.

You can select a field in the target Operation table, and then choose to set a new value of the selected field in the target Operation. You can assign a value to a field when the field is not linked or when the field is only implicitly linked to another value in the pipeline. You cannot assign values to fields that are explicitly linked to another value in the pipeline or fields that have been dropped from the pipeline.


You can copy a field from the fields panel by clicking the  icon. Depending on the context, you can either paste the field or the field path. For example, if you copy a field and paste the field in the **Set Value** window in an Integration (double-click a field to set a value), the field path will be pasted. If you copy an array item, the path that is pasted includes the item index. For example, if the item that is copied is A/B/C[10], then the pasted path will also include the item index [10]. But if it is pasted

in the document tree, it will appear as an array, like A[]. If there are multiple fields with the same name in a document, and one of the occurrences of such a field is copied, then the path when pasted will contain the occurrence number in brackets, for example, the path will be A/B/C(5) if the copied element C is the 5th occurrence under field B.

Note: The paste option is not applicable for Point-to-Point Integrations.

Click the **Add Transformer** icon to add a transformer in the **Transform Data** page. This page allows you to transform the source Operation data, for example, concatenate two strings and map it to a single field. Several *built-in services* specifically designed to translate values between formats are provided. You can transform time and date information from one format to another, perform simple arithmetic calculations (add, subtract, multiply, and divide) on integers and decimals contained in String fields, or transform String values in various ways. Reference Data is also available while transforming the data.

The **Transform Data** screen also allows you to look up and use data from another source Operation to transform the data. After adding a transformer, you can click the  icon and select **Edit Transformer** or **Delete Transformer** to either modify the transformer or delete it.



10. Click **Next** to review your Integration.
11. Click **Save** and then click **Finish** to create your Integration.

The new Integration appears in the **Integrations** page.


Orchestrated Integrations

Orchestrated Integration is the process of integrating two or more applications together, to automate a process, or synchronize data in real-time. Orchestrated Integration enables you to integrate applications and provides a way to manage and monitor your integrations.


Integration Cloud supports advanced integration scenarios involving multiple application endpoints, complex routing, and Integrations involving multiple steps. Using a graphical drag and drop tool, you can create complex, orchestrated integrations and run them in the Integration Cloud environment.

To create an orchestrated integration

1. From the Integration Cloud navigation bar, click **Projects**. The **Projects** screen appears.
2. Select a project in which you want to create the Integration. You can also create a new project. See [“Projects” on page 50](#) for more information.
3. To create a new Integration, from the **Integrations** screen, click **Add New Integration**.
4. Select **Orchestrate two or more applications**, and then click **OK**.



The user interface consists of a *tool bar* and a *workspace*. The tool bar holds all the available categories with blocks. You can browse through the menu of blocks and can set up your own Integration by plugging blocks together in the workspace. The menu of blocks comes with a large number of predefined blocks from Applications, Services, Integrations, conditions to looping structures. You can drag relevant blocks from the tool bar and drop them at the anchor point.




The tool bar has a large number of blocks for common instructions and the blocks are divided into the following categories:

- Applications
 - Predefined Applications
 - REST Applications


- SOAP Applications
- On-Premises Applications
- Flat File Applications
- Services
- Integrations
- Control Flow
- Expressions


Block category	Icons	Description
Applications		Displays the Application categories available in Integration Cloud.
Services		Use the <i>Service</i> blocks (date, math, string, and so on) to specify the service that will be invoked at run time. Related services are grouped in blocks. You can sequence services and manage the flow of data among them. <p>Note: For information on the different services, see Built-In Services.</p> <p>The Reference Data block appears only if a Reference Data service is available at the Projects > <Select a Project> > Reference Data page. See Add Reference Data for more information.</p>
Integrations		Displays the list of Integrations created in Integration Cloud. You can invoke an Integration from another Integration. When copying integrations from one stage to another, all the referred Integrations and their dependents will also be copied. <p>Click the  icon if you want to view or modify an Integration after it is dropped at the anchor point. The Integration will open up for editing in a new tab.</p> <p>Click the  icon and select Map Input and Output if you want to map the input of the operation from the Pipeline and also map the output of the operation into the pipeline.</p>

Block category	Icons	Description
----------------	-------	-------------




Click **Comments** to add comments for the block. You can click the **Show comments inline** option to view the comments entered for the block. Click **Duplicate** to repeat a block, click **Collapse** to flatten a block, click **Delete** to remove a block from the workspace, or click **Disable** to disable a block and all blocks within that block. If you disable blocks, those blocks will not be considered for execution, test, or debug operations.

Control Flow		<p>Conditional expressions, looping structures, and transform pipeline.</p> <p>Conditional expressions perform different computations or actions depending on whether a specified boolean condition evaluates to true or false. The if block is used to evaluate a boolean condition and if the condition is true, statements inside the <i>if</i> block are executed. The <i>if</i> statement can be followed by an optional <i>else</i> statement, which executes when the boolean expression is false.</p>  <p>The <i>if</i> statements are executed from the top towards the bottom. You can use one <i>if</i> or else if statement inside another <i>if</i> or <i>else if</i> statement(s). You cannot have multiple else statements.</p> <p>Switch allows a variable to be tested for equality against a list of values. Each value is called a case,</p>
---------------------	--	--

Block category	Icons	Description
		<p>and the variable being switched on is checked for each case, that is, Switch evaluates a variable and skips to the value that matches the case. For example, if the Switch variable evaluates as "A", then case "A" is executed. A switch statement can have an optional default case, which must appear at the end of the switch. The default case can be used for performing a task when none of the cases are true. You cannot insert multiple default statements.</p>



Note: You can include case steps that match null or empty switch values. A switch value is considered to be null if the variable does not exist in the pipeline or is explicitly set to null. A switch value is considered to be an empty string if the variable exists in the pipeline but its value is a zero length string.

Note: Switch executes the first case that matches the value, and *exits the block*.

The **try catch** block is used to handle errors and exceptions. If you have a statement in the try block that has thrown an error, the error will be caught in the catch statement.

Note: If an error is thrown inside the catch section of the try catch block, the error will be ignored and the next statements in the Integration will be executed.

Loops execute a set of steps multiple times based on the block you have chosen. It repeats a sequence of child steps once for each element in an array that you specify. For example, if your pipeline contains an array of purchase-order line items, you could use a Loop to process each line item in the array.

Block category	Icons	Description
		<p>Loop requires you to specify an input array that contains the individual elements that will be used as input to one or more steps in the Loop. At run time, the Loop executes one pass of the loop for each member in the specified array. For example, if you want to execute a Loop for each line item stored in a purchase order, you would use the document list in which the order's line items are stored as the Loop's input array.</p> <p>The while loop is used to iterate a part of the program several times. If the number of iterations are not fixed, it is recommended to use the while loop.</p> <p>The do-until loops are similar except that they repeat their bodies until some condition is true.</p> <p>The for-each block traverses items in a collection. Unlike other for loop constructs, for-each loops usually maintain no explicit counter: they essentially say "do this to everything in this set", rather than "do this x times".</p> <p>The Exit Integration signaling success block allows you to successfully terminate and exit from the currently running Integration. You cannot attach child blocks to the Exit Integration signaling success block.</p> <p>The Exit Integration signaling failure "..." block abnormally terminates the currently running integration with an error message. You can specify the text of the error message that is to be displayed. If you want to use the value of a pipeline variable for this error message, type the variable name between % symbols, for example, <code>%mymessage%</code>. The variable you specify must be a String. You cannot attach child blocks to the Exit Integration signaling failure "..." block.</p> <p>The Throw error "..." block can be attached inside any block <i>except the catch section of the try catch block</i>, and allows you to <i>explicitly</i> throw an exception with a custom error message. If it is used inside the try section of the try catch block, the error will be caught in the catch section. If you want to use the value of a pipeline variable for this custom error message, type the variable name between % symbols, for example, <code>%mymessage%</code>. The variable</p>

Block category	Icons	Description
		<p>you specify must be a String. You cannot attach child blocks to the Throw error "..." block.</p> <div data-bbox="665 394 1367 558" style="background-color: #f0f0f0; padding: 10px;"> <p>Note: If you add a Throw error "..." block inside a try catch block, any changes done to the pipeline variables inside the try block will be reset to the previous values existing in the pipeline.</p> </div> <p>The Break out of loop block should be used only within a loop and allows you to break out of the containing loop, that is, it allows you to break the program execution out of the loop it is placed in. You cannot attach child blocks to the Break out of loop block.</p> <p>A Loop takes as input an array field that is in the pipeline. It loops over the members of an input array, executing its child steps each time through the loop. For example, if you have a Integration that takes a string as input and a string list in the pipeline, use Loops to invoke the Integration one time for each string in the string list. You identify a single array field to use as input when you set the properties for the Loop. You can also designate a single field for the output. Loop collects an output value each time it runs through the loop and creates an output array that contains the collected output values.</p> <p>Use the Transform Pipeline block to make pipeline modifications. See Pipeline and Signatures for more information.</p>
Expressions		<p>Logical operations, comparisons, and values.</p> <p>The six comparison operators are: equal to, not equal to, less than, less than or equal to, greater than, greater than or equal to. Each takes two inputs and returns true or false depending on how the inputs compare with each other.</p> <p>The and block will return true only if both of its two inputs are also true. The or block will return true if either of its two inputs are true. The not block converts its Boolean input into its opposite.</p>

Block category	Icons	Description
		<p>You can also type a text value, select a field on which to build an expression (Select field), or select a block with no inputs.</p> <p>The Field exists block allows you to check if a variable exists or not and can be used with other Control Flow blocks, for example, the <i>if</i> block. The <i>Field exists</i> block validates the existence of a particular field in the pipeline.</p>

Note: It is recommended not to leave an input empty.


5. Provide a valid name and description for the Integration.
6. Click **Applications**. The list of supported Applications appears.
7. Drag and drop an Application to the root block anchor point.
8. To select the Operation and Account for the Application, click 

The following table depicts the block interactions:

Icons	Applicable for...	Action/Description
	Only for the Control Flow block and the Root block.	Comments for the Control Flow block and the Root block. Click the Show comments inline check box to view the comments entered for the blocks.
	Applications, Services, Integrations, and the Root block	<p>Define Input and Output Signature</p> <p>Click the Define Input and Output Signature icon  to define the input and output signature of an Integration. You can declare the input and output parameters for an Integration using the Input and Output tabs. Input and output parameters are the names and types of fields that the Integration requires as input and generates as output. These parameters are also collectively referred to as a signature. For example, an Integration can take two string values, an account number (AcctNum) and a dollar</p>

Icons	Applicable for...	Action/Description
		<p>amount (OrderTotal) as inputs and produces an authorization code (AuthCode) as the output. On the Output tab, specify the fields that you want the Integration to return.</p> <p>You can use a Document Reference to define the input or output parameters for an Integration. If you have multiple Integrations with identical input parameters but different output parameters, you can use a Document Type to define the input parameters rather than manually specifying individual input fields for each Integration. When you assign a Document Type to the Input or Output side, you cannot add, modify, or delete the fields on that part of the tab.</p> <p>You can select a Document Type from the Document Reference drop-down list. To create a Document Type, from the Integration Cloud navigation bar, select Projects > <Select a Project> > Document Types > Add New Document Type. See “Overview” on page 590 for more information.</p> <p>You can create pipeline variables as document references, create document types comprising of document references, and also define the signature of Integrations comprising of document references.</p> <p>You can also copy a field from the fields panel by clicking the  icon. Depending on the context, you can either paste the field or the field path by clicking the  icon. For example, if you copy a field and paste the field in the Set Value window in an Integration, (double-</p>


Icons	Applicable for...	Action/Description
		<p>click a field to set a value), the field path will be pasted.</p> <p>See Creating Document Types from Scratch for more information.</p> <div data-bbox="867 478 1367 613" style="background-color: #f0f0f0; padding: 5px;"> <p>Note You cannot modify or paste the child fields of a Document Reference.</p> </div> <p>Select the Validate input and Validate output options if you want to validate the input and output to the Integration, against the service input or output signature.</p> <p>Select Business Data to Log</p> <p>Integration Cloud allows you to log select business data from the Operation and Integration signatures either always, or only when errors occur. Values of logged fields can be viewed in the Only Business Data section in the Execution Results screen. You can also create aliases for the logged fields.</p> <div data-bbox="867 1268 1367 1470" style="background-color: #f0f0f0; padding: 5px;"> <p>Note User specific data which may be considered as personal data will be stored and retained till the retention period defined in Execution Results.</p> </div> <p>To select input or output fields for logging, click the Select Business Data to Log icon , and in the Select Business Data to Log dialog box, choose whether you want to log business data only when errors occur (On Failure) or choose (Always) to always log business data. The default setting is On Failure. Then expand the Input Fields and Output Fields trees to display the fields</p>

Icons	Applicable for...	Action/Description
		<p>available in the signature, and select the check boxes next to the fields you want to log. If you want to define an alias for a field, type an alias name beside the field. The alias defaults to the name of the selected field, but it can be modified. Click the  icon to clear the selections.</p> <p>When selecting fields for logging, you can create the same alias for more than one field, but this is not recommended. Having the same alias might make monitoring the fields at run time difficult.</p> <p>Map Input and Output</p>  <p>Map the input of the operation from the Pipeline and also map the output of the operation into the pipeline.</p> <p>You can copy a field from the fields panel by clicking the  icon. Depending on the context, you can either paste the field or the field path by clicking the  icon. If you copy an array item, the path that is pasted includes the item index. For example, if the item that is copied is A/B/C[10], then the pasted path will also include the item index [10]. But if it is pasted in the document tree, it will appear as an array, like A[]. If there are multiple fields with the same name in a document, and one of the occurrences of such a field is copied, then the path when pasted will contain the occurrence number in brackets, for example, the path will be A/B/C(5) if the copied</p>

Icons	Applicable for...	Action/Description
		<p>element C is the 5th occurrence under field B.</p> <p>You can select a block, other than the root block, and click Duplicate to repeat a block, click Collapse to flatten a block, click Delete to remove a block from the workspace, or click Disable to disable a block and all blocks within that block. If you disable blocks, those blocks will not be considered for execution, test, or debug operations.</p>
	Control Flow > Transform Pipeline	Make pipeline modifications. Edit data mapping, add Transformer, clear all mappings, add, delete, edit, or discard a field, set a value for a field and perform pipeline variable substitutions.
	Applications	Account and an Operation for the Application is configured.
	Applications	The block is not configured. Select an Account and an Operation for the Application.
	Services	The block is not configured. Select a service.
	Orchestrated Integrations	Click to view or modify an Orchestrated Integration after it is moved to the workspace. The Orchestrated Integration will open up for editing in a new tab.
	Orchestrated Integrations	An Orchestrated Integration has been modified or newly created but not saved.

9. Create the Integration using the available constructs by inserting the blocks, setting properties, declaring the input and output parameters, setting values, performing pipeline variable substitutions (if you want to replace the value of a pipeline field at run time), and mapping the pipeline data.

10. Click the ☰ icon and then select **Map Input and Output** to map the Pipeline Input to the Input Signature.




11. To view only the mapped fields, select the **Show Only Mapped Fields** option. Map the Output Signature to the Pipeline Output in the **Pipeline Data** window, and then click **Finish**.
12. Use the **Transform Pipeline** block under the **Control Flow** category to adjust the pipeline at any point in the Integration and make pipeline modifications. Within this step, you can discard or remove an existing pipeline input field, (once you discard a field from the pipeline, it is no longer available subsequently), restore the discarded field, add a field, set a new value or modify the existing value of a selected field, map selected fields, remove the selected map between the fields, or perform value transformations by inserting transformers.
13. Click **Save** to save your Integration or click **Save All** to save all modified Integrations. The new Integration appears in the **Integrations** page. Click on the Integration link in the **Integrations** page to view the Integration details.

Note: While running or debugging Integrations and testing Operations, if the input has any duplicate keys, or if the service returns an output with duplicate keys, you can view those keys.

14. After saving the Integration, in the edit Integration page, click the ▶ icon to run and test the Integration execution in real time and view the execution results on the **Test Results** panel.

The **Test Results** panel displays up to 25 test entries and the most recent test entry is located at the top of the panel. Click the ⋮ icon on the **Test Results** panel header and click **Remove All** to delete the test results permanently or click **Close** to close the test results panel.



Point to a test result entry, click the  icon, and click **Download Result** to save the entry locally in JSON format. Click **Remove Result** to remove the selected entry. Click **Pin Result** if you want to prevent a previous result from getting deleted as more results fill the test results panel. Click **Unpin Result** to move the result to the **Previous Results** panel.

Pipeline and Signatures

The pipeline is the general term used to refer to the data structure in which input and output values are maintained for an Integration. The pipeline starts with the input to the Integration and collects inputs and outputs from subsequent Applications and services in the Integration. When an operation of an Application or an Integration executes, it has access to all data in the pipeline at that point.

Input and output parameters are the names and types of fields that the Integration requires as input and generates as output. These parameters are also collectively referred to as a *signature*.

For example, an Integration that takes two string values—an account number (*AcctNum*) and a dollar amount (*OrderTotal*)—as input and produces an authorization code (*AuthCode*) as output, has the following input and output parameters:

Input Parameters

Output Parameters

<u>Name</u>	<u>Data Type</u>	<u>Name</u>	<u>Data Type</u>
<i>AcctNum</i>	String	<i>AuthCode</i>	String
<i>OrderTotal</i>	String		

Although you are not required to declare input and output parameters for an Integration, (Integration Cloud will execute an Integration regardless of whether it has a specification or not), there are good reasons to do so:

- Declaring parameters makes the Integration's input and outputs visible in the user interface. Without declared input and output parameters, you cannot:

- Link data to and/or from the Integration using the Pipeline view.
- Assign default input values to the Integration on the Pipeline view.
- Run the Integration and enter initial input values.
- Declaring parameters makes the input and output requirements of your Integration known to other developers who may want to call your Integration from their programs.

For these reasons, it is strongly recommended that you make it a practice to declare a signature for every Integration that you create.

Integration Cloud supports several data types for use in Integrations. Each data type supported by Integration Cloud corresponds to a Java data type and has an associated icon. When working in the editor, you can determine the data type for a field by looking at the icon next to the field name.

The input side describes the initial contents of the pipeline. In other words, it specifies the fields that this Integration expects to find in the pipeline at run time. The output side identifies the fields produced by the Integration and returned to the pipeline.

Guidelines for specifying input parameters

When you define the input parameters for an Integration, keep the following points in mind:

- **Specify all inputs that a calling program must supply to this Integration.** For example, if an Integration invokes two other Integrations, one that takes a field called *AcctNum* and another that takes *OrderNum*, you must define both *AcctNum* and *OrderNum* as input parameters for the Integration.

Note: The purpose of declaring input parameters is to define the inputs that a calling program or client must provide when it invokes this Integration. You do not need to declare inputs that are obtained from within the Integration itself. For example, if the input for one Integration is derived from the output of another Integration, you do not need to declare that field as an input parameter.

- **When possible, use variable names that match the names used by the Integrations.** Variables with the same name are automatically linked to one another in the pipeline. (Remember that variable names are case sensitive.) If you use the same variable names used by Integration's constituent services, you reduce the amount of manual data mapping that needs to be done. When you specify names that do not match the ones used by the constituent Integrations, you must use the Pipeline view to manually link them to one another.
- **Avoid using multiple inputs that have the same name.** Although the user interface permits you to declare multiple input parameters with the same name, the fields may not be processed correctly within the Integrations or by other Integrations that invoke this Integration.

- **Ensure that the variables match the data types of the variables they represent in the Integration.** For example, if an Integration expects a document list called *LineItems*, define that input variable as a document list.
- **Declared input variables appear automatically as inputs in the pipeline.** When you select the Transform Pipeline step in an Integration, the declared inputs appear under **Pipeline Input**.


Guidelines for specifying output parameters

On the output side of the Input/Output tab, you specify the variables that you want the Integration to return to the calling program or client. The guidelines for defining the output parameters are similar to those for defining input parameters:

- **Specify all of the output variables that you want this Integration to return** to the calling program or client.
- **Ensure that the names of output variables match the names used by the Integrations** that produce them. Like input variables, if you do not specify names that match the ones produced by the Integration's constituent services, you must use the Pipeline view to manually link them to one another.
- **Avoid using multiple outputs that have the same name.** Although the user interface permits you to declare multiple output parameters with the same name, the fields may not be processed correctly within the Integration or by other Integrations that invoke this Integration.
- **Ensure that the variables match the data types of the variables they represent in the Integration.** For example, if an Integration produces a String called *AuthorizationCode*, ensure that you define that variable as a String.
- **Declared output variables appear automatically as outputs in the pipeline.** When you select the Transform Pipeline step in an Integration, the declared output variables appear under **Pipeline Output**.

Declaring Input and Output Parameters

Click the **Define Input and Output Signature** icon  to define the input and output parameters. On the **Input** tab, you define the variables that the Integration requires as input. On the **Output** tab, you define the variables the Integration returns to the client or calling program.



The screenshot shows the 'Define Input and Output Signature' window. At the top, there are tabs for 'INPUT' and 'OUTPUT', with 'INPUT' selected. Below the tabs, there is a 'Document Reference' dropdown menu currently set to 'Numbers'. Underneath, there is a checkbox labeled 'Validate input' which is unchecked. A search box with the placeholder text 'Search for Field...' is located above a list of fields. The list contains three items: 'Number1', 'Number2', and 'Sum'. To the right of the field list is a 'Field Properties' panel. This panel has a 'Name' field with the value 'Number1', a 'Type' dropdown menu set to 'String', an unchecked 'Array' checkbox, and an 'XML Namespace' field with the value 'XML Namespace'.

For an Integration, the input side describes the initial contents of the pipeline. In other words, it specifies the variables that this Integration expects to find in the pipeline at run time. The output side identifies the variables produced by the Integration and returned to the pipeline.

Note: You can create pipeline variables as document references, create document types comprising of document references, and also define the signature of Integrations comprising of document references.

You can declare a signature in one of the following ways:

- **Reference a document type.** You can use a document type to define the input or output parameters for an Integration. When you assign a document type to the Input or Output side, you cannot add, modify, or delete the variables on that half of the tab.
- **Manually insert input and output variables.** Click the **+** icon to manually insert variables to the Input or Output sides.


Using a Document Type to specify Integration input or output parameters

You can use a document type as the set of input or output parameters for an Integration. If you have multiple Integrations with identical input parameters but different output parameters, you can use a document type to define the input parameters rather than manually specifying individual input fields for each Integration. When a document type is assigned to the input or output of an Integration, you cannot add, delete, or modify the fields on that tab.


Default Pipeline Rules for Linking to and from Array Variables

When you create links between scalar and array variables, you can specify which element of the array variable you want to link to or from. Scalar variables are those that hold a single value, such as String, Document, and Object. Array variables are those that hold multiple values, such as String List, Document List, and Object List. For example, you can link a String to the second element of a String List. If you do not specify which element in the array variable that you want to link to or from, default rules in the Pipeline view are used to determine the value of the target variable. The following table identifies the default pipeline rules for linking to and from array variables.


If you link...	To...	Then...
A scalar variable	An array variable that is empty (the variable does not have a defined length)	The link defines the length of the array variable; that is, it contains one element and has length of one. The first (and only) element in the array is assigned the value of the scalar variable.

If you link...	To...	Then...
		

If you link...	To...	Then...
A scalar variable	An array variable with a defined length	The length of the array is preserved and each element of the array is assigned the value of the scalar variable.



If you link...	To...	Then...
An array variable	A scalar variable	The scalar variable is assigned the first element in the array.



If you link...	To...	Then...
An array variable	An array variable that does not have a defined length	The link defines the length of the target array variable; that is, it will be the same length as the source array variable. The elements in the target array variable are assigned the values


If you link...	To...	Then...
		of the corresponding elements in the source array variable.



If you link...	To...	Then...
An array variable	An array variable that has a defined length	The length of the source array variable <i>must</i> equal the length of the target array variable. If the lengths do not match, the link will not occur. If the lengths are equal, the elements in the target array variable are assigned the values of the corresponding elements in the source array variable.



A source variable that is the child of a Document List is treated like an array because there is one value of the source variable for each Document in the Document List. For example:


If you link...	To...
	
Where the value of DocumentList1 is...	
	

Indexed Mapping

You can add an indexed item to a String List, Document List, Document Reference List, or Object List and also map the indexed item. You can delete the selected indexed item provided the indexed item or none of its child fields are mapped.

When you link to an array variable or from an array variable (String List, Document List, Document Reference List, or Object List), you can specify which element in the array you want to link to or from. Click on the **Add Array Item** icon to get an index value for the array item. Then map the indexed item to the target. For example, you can link the second element in a String List to a String or link the third Document in a Document List to a Document variable.

For example, suppose that a buyer's address information is initially stored in a String List. However, the information might be easier to work with if it is stored in a Document. To map the information in the String List to a Document, click on the **Add Array Item** icon to get an index value for the String List. Then map each indexed item to the address fields. In the following pipeline, the elements in buyerAddress String List are mapped to the address Document.



Suppose a String List has length 3 and if you link index 4 of the String List, at run time the String List length is increased from 3 to 5.

When you link a Document or Document List variable to another Document or Document List variable, the structure of the source variable determines the structure of the target variable.

Integration Details

This page allows you to view when the Integration was created or last modified, who created or last modified the Integration, when was the last execution, and whether the Integration is scheduled. You can edit, delete, preview, or run the Integration, enable the Integration to be invoked over HTTP and view and add OAuth Scopes containing the exposed Integration URL, enable Integration executions to be restartable or resumable, associate another Access Control List (ACL) with the Integration, and also view the last five execution results.

Default ▾ Integrations Document Types Reference Data REST APIs SOAP APIs Applications Keys & Certificates

addint

OVERVIEW LAST 5 EXECUTION RESULTS

[Edit](#) [Delete](#) [Run Now](#)

Uses	LIP_10743
Created On	2018/23/07 03:41:11 PM IST
Created By	
Last modified	2019/29/05 12:47:09 PM IST
Last modified by	
Scheduled status	Scheduled
Next scheduled execution	2019/21/06 04:50:00 PM IST
Associated Execute Access Control List	Default

OAuth Scopes containing the exposed Integration URL

Enable executions to be restartable

Enable Integration to be invoked over HTTP

[Permissions](#) [OAuth Scopes](#)

[Pause](#) [Modify Schedule](#)

`https://adsi.eur.ad.sag/integration/rest/external/integration/run/development/addint`

Show Advanced Options

Option	Description
Overview	This page allows you to view the components used to create the Integration, when the Integration was created or last modified, who created or last modified the Integration, when was the last execution, and whether the Integration is scheduled. You can edit, delete, or run the Integration, enable the Integration to be invoked over HTTP and view and add OAuth Scopes containing the exposed Integration URL, enable Integration executions to be restartable or resumable, and associate another Access Control List (ACL) with the Integration.
Last 5 Execution Results	Click this tab to view the last five execution results panel. This screen allows you to view the audit trail of the executions that happened in the current stage. See Execution Results for information on the Last 5 Execution Results table columns.

Option	Description
Preview	View the pipeline and mapping details for a previous version of an orchestrated integration in <i>any stage</i> . You will not be able to make any modifications to the existing pipeline and mapping data.
Uses	Displays the components used to create the Integration. This field will appear only if the selected Integration has components.
	<p>Note: If assets used by an Integration are deleted, you will not be able to pull the Integration into subsequent stages or export the Integration.</p>
Created on	Displays the date and time when the Integration was created.
Created by	Displays the user who created the Integration.
Edit	Click this option to modify the Integration.
Delete	Click this option to delete the Integration from the active stage. You can delete an Integration from all stages except from the <i>Development</i> stage.
Run Now	Click this option to submit the Integration for execution. You can provide inputs to the Integration based on the defined input signature.
Last modified/Last modified by	When and by whom was the Integration last modified.
Scheduled status	If the Integration in the active stage is scheduled, the status of the Integration displays Scheduled , else it appears as Not Scheduled . The Status appears as Paused if the Integration has been paused.
Last execution	When was the Integration last executed. A warning message appears if the last execution was not successful.
Next scheduled execution	When is the Integration scheduled to run again.


Option	Description
Schedule	<p>Click this option to define a schedule. Select Run Once if you want to schedule the Integration to run just once immediately or run once at a specified date and time.</p> <p>Select Run Recurrently if you want to define a recurrence pattern. You can define a recurrence pattern daily, weekly, monthly, and in hours. Select the frequency (Hourly, Daily, Weekly, Monthly) with which the pattern recurs, and then select the options for the frequency. Click the  icon to repeat the execution for daily, weekly, and monthly schedules. Click the  icon to delete the selected execution time for daily, weekly, and monthly schedules. Select Prevent concurrent executions to skip the next scheduled execution if the previous scheduled execution is still running except when the previous scheduled execution is running for more than 3 hours. In this case, the next scheduled execution will start even if the previous scheduled execution is still running. If you do not select this option, the next scheduled execution will start, even if the previous scheduled execution has not yet completed.</p> <p>Click Delete if you want to permanently remove the current recurrence schedule.</p> <p>Click Next to provide inputs to the Integration based on the defined input signature.</p>
Modify Schedule	Click this option to change the existing schedule.
Pause	Click this option to pause the Integration that was scheduled.
Resume	Click this option to start the scheduled Integration that was paused.
Associated Execute Access Control List	<p>Displays the Access Control List (ACL) associated with the Integration. Integration Cloud associates the default ACL, <i>Default</i>, to an Integration when the Integration is created. Click Permissions to associate the Integration with another ACL.</p>
	<p>Note: The ACL will be enforced only if an Integration acts as a top-level Integration. For example, if</p>

Option	Description
Enable executions to be restartable	<p data-bbox="730 306 1370 411">Integration A has Integration B and Integration C as sub-Integrations, then the ACL if associated, will be enforced only on Integration A.</p> <p data-bbox="649 453 1328 789">For an orchestrated Integration, select the Enable executions to be restartable option if you want to enable Integration executions to be restartable or resumable. If an operation fails, you can resume the Integration execution from the point where it had failed from the Execution Results page (Resume option). Resuming an execution does not execute the previous successful operations but executes only the failed operations and operations that are not yet executed.</p> <p data-bbox="649 814 1334 949">You can also restart an execution from the Execution Results page (Restart option). When an Integration is restarted, the execution occurs from the beginning of an Integration.</p> <p data-bbox="662 982 1370 1159">Note: The "Restart/Resume" capability is available only if you have the required license for restarting and resuming Integrations. You must also have the Integration execution (Execute) permission if you want to restart or resume an execution.</p> <p data-bbox="662 1188 1370 1528">Note: You cannot resume successful Integrations but can only restart them. If an Integration has referenced Integrations, then those referenced Integrations can also be restarted or resumed. Only top level Integrations are displayed in the Execution Results page and the referenced Integrations are displayed in the Execution Details page of that top level Integration execution. The Audit Log will display the "Restart" and "Resume" entries.</p> <p data-bbox="662 1566 1354 1671">Note: User specific data which may be considered as personal data will be stored and retained till the retention period defined in Execution Results.</p> <p data-bbox="649 1713 1218 1743">See Execution Results for more information.</p> <p data-bbox="662 1776 1354 1856">Note: Enabling this option will increase the execution time of this Integration.</p>

Option	Description
<p>Enable Integration to be invoked over HTTP</p>	<div data-bbox="649 304 1364 598" style="background-color: #f0f0f0; padding: 10px;"> <p>Once the Integration is updated, you cannot restart or resume its executions that have occurred before the update.</p> <p>Integrations using Operations and other Integrations, which have fields of type “Object” in their signature, may not execute properly when restarted or resumed.</p> </div> <p>Select the Enable Integration to be invoked over HTTP option if you want to trigger the execution of an Integration from an external system. This option provides you with one more way to trigger Integration executions from a software application, for example, a REST client, apart from manual and scheduled integrations from the user interface.</p> <p>Once the Integration is enabled to be invoked over HTTP, the HTTP request URL appears. Click the Show Advanced Options link to view the HTTP Method, sample JSON input, and the parameters that are required to invoke this Integration from an external system.</p> <p>You need to provide the HTTP URL, Method, required JSON body, and necessary header parameters in the external program, including the required security credentials (user name and password) for invoking the Integration. After the Integration is executed, the response will contain the pipeline data.</p> <p><i>Request URL format</i></p> <pre>https://<sub-domain>.webmethodscloud.com/ integration/rest/external/integration/run/ <stagename>/<integrationname></pre> <p><i>sub-domain</i> is a domain that is part of the primary domain.</p> <p><i>stagename</i> is the name of the active stage.</p> <p><i>integrationname</i> is the name of the Integration.</p> <p><i>HTTP Status Codes</i></p> <ul style="list-style-type: none"> ■ 200 - OK

Option	Description
OAuth Scopes containing the exposed Integration URL	<ul style="list-style-type: none"> ■ 500 - Internal Server Error ■ 401 - Unauthorized User Error
	<div style="background-color: #f0f0f0; padding: 10px; border: 1px solid #ccc;"> <p>Note: You must provide your user name and password to execute the Integration from the external program, else you may encounter the 401 - Unauthorized User Error.</p> </div> <p>A “scope” on page 100 defines the services the client can access on behalf of the resource owner and consists of one or more services. If access is granted for a scope, then access is granted for all the services in that scope. When a request is made, Integration Cloud verifies that the scope is defined for a client. The client is allowed to access only the service URLs that are specified for the scope.</p> <p>The OAuth Scopes containing the exposed Integration URL option appears when you select the Enable Integration to be invoked over HTTP check box. Click OAuth Scopes to view the OAuth scopes that contain the exposed URL of the selected Integration.</p> <p>In the OAuth Scopes dialog box, click Add URL to Another Scope. In the Add Exposed URL to OAuth Scope dialog box, select Add To Existing Scope to add the exposed Integration URL to an existing scope or select Add New Scope to create a new scope and add the exposed Integration URL to that new scope.</p>

Versioning of Integrations

Integration Cloud allows you to view the version change history of an Integration. Click the **Show history** option  available on the tool bar panel to view the version change history.

Current 4

Date: 07/02/2019 02:55:06 AM PDT
Author: JDBC
Action: Modify
Message: Commit made by:JDBC

3

Date: 07/02/2019 02:53:28 AM PDT
Author: JDBC
Action: Modify
Message: Commit made by:JDBC

2

Date: 07/02/2019 02:43:24 AM PDT
Author: JDBC
Action: Modify
Message: Commit made by:JDBC

While editing the Integration, you can restore an earlier version of the Integration. To restore an earlier version of an Integration, select the earlier version of the Integration, and then click the **Restore** option to restore that previous version of the Integration. If you have reverted to an earlier version and there is a scheduled execution for the Integration, the reverted version of the Integration will be run as per the defined schedule.

I/O | [Play] [Share] [Help] **Restore** [Close]

Restore [Close]

Restored from: Version 3

OK Cancel

Note: If an Integration references any other Integration, then the input/output mapping of the referenced Integration will be restored to that particular version. But if the input/output mapping of the referenced Integration has been modified in a later version, the modifications will break the mappings and the Integration execution may not be successful.

Note: If you delete an Integration and then create another Integration with the same name, the version history of the deleted Integration will be available.

Preview Integrations

Integration Cloud allows you to view the pipeline and mapping details for a previous version of an orchestrated integration.

To view the pipeline and mapping details in the **Development** stage, select the Integration from the **Integrations** page and click **Edit**. Then click the **Show History** option available on the tool bar panel to view the version change history for the integration. On the version change history panel, select a previous version of the integration. When you select an Integration version, you will notice that options to configure accounts and operations are not available. You will not be able to make any modifications to the existing pipeline and mapping data.

The screenshot displays the 'Development' stage of an integration named 'ConcurAttendeeToSalesforceContacts'. On the left, a history panel shows two versions of the integration, both with the message 'Commit made by:sandbox'. The main area shows a pipeline diagram with a 'do' loop containing a 'Concur : getAttendee' block, a 'Salesforce CRM Version 44 : addContact' block, and a 'Flow : countProcessedDocuments' block. A 'Show History' button is located in the top right corner.

Click  on the block for which you want to preview the pipeline. The Pipeline Data window shows all the mappings that are part of this Integration. The pipeline preview is also available for Transform Pipeline. To view the pipeline data for Transform Pipeline, click .

The 'Pipeline Data' window shows the mapping between 'Pipeline Input' and 'addContact Input'. The 'Pipeline Input' section lists various fields, including Custom23, Custom24, Custom25, ExternalID, FirstName, HasExceptionsPrevYear, HasExceptionsYTD, ID, LastName, MiddleInitial, OwnerLoginID, OwnerName, Suffix, and Title. The 'addContact Input' section shows a 'Contact[]' field. Arrows indicate the mapping from the 'Pipeline Input' fields to the 'Contact[]' field. The window includes a 'Map Source to Target Input' step indicator and navigation buttons: 'Cancel', 'Previous', and 'Next'.

Note: In the pipeline preview, none of the action buttons are available. Also, you cannot modify the existing pipeline or the mapped data.

To view the pipeline and mapping details for a previous version of an orchestrated integration in *any stage other than the Development stage*, change the stage, select the integration from the **Integrations** page, and then click **Preview**.

Default ▾ **Integrations** Document Types

Go to the **Deploy** page to pull assets from the **Development** stage.

Delete **Preview**

The **Preview** option is also available on the Integration details **Overview** page if you are in *any stage other than the Development stage*.

Default ▾ **Integrations**

IntegrationName

OVERVIEW LAST 5 EXECUTION RESULTS

Preview Delete Run Now


Debug Integrations

You can debug an orchestrated Integration and can inspect the data flow during the debugging session. You can debug an orchestrated Integration only in the Development stage and after the Integration has been saved.

You can do the following in debug mode:

- Start an Integration in debug mode, specify the input values, and inspect the results.
- Examine and edit the pipeline data before and after executing the individual blocks.
- Monitor the execution path, execute the blocks one at a time, or specify breakpoints where you want to halt the execution.

To start the **Debug** mode, click the **Debug Integration** icon .



The following table describes the options available in the **Debug** panel:

Icons	Applicable for...	Action/Description
	Inserting Breakpoints	<p>A breakpoint is a point in an Integration where you want processing to halt when you debug that Integration. Breakpoints can help you isolate a section of code or examine data values at a particular point in the execution path. For example, you might want to set a pair of breakpoints before and after a particular block so that you can examine the pipeline before and after that block executes.</p> <p>Breakpoints are recognized only when you execute an Integration in debug session. To insert a breakpoint, in debug mode, click the top-left corner of the block. To remove a breakpoint, click on the inserted breakpoint.</p> <p>When you execute an Integration that contains a breakpoint, the Integration is executed up to, but not including the designated breakpoint. At this point, processing stops and the debug session suspends. To resume processing, select Resume. After you resume the debug session, the Integration flow stops at the next breakpoint.</p>
	Ignore All Breakpoints	<p>Ignores all breakpoints inserted in the Integration blocks. You cannot insert</p>

Icons	Applicable for...	Action/Description
		breakpoints for variables in the Expressions category.
	Stepover	Executes the current block. Integration Cloud suspends the debug session immediately before executing the next block in the Integration.
	Resume	The debug session resumes but suspends at the next breakpoint.
	Stop	<p>Terminates the debug session.</p> <p>A debug session may also stop by itself for the following reasons:</p> <ul style="list-style-type: none"> ■ The Integration that you are debugging executes to completion (error or success). ■ You select Stepover for the last step in the Integration. ■ You Exit the Integration.
	Clear All Breakpoints	Removes all breakpoints inserted in the Integration.

Modifying the current pipeline data while debugging

During debugging, you can modify the contents of the pipeline. The changed values will be applied when you perform a **Stepover** or **Resume**.

While modifying the pipeline, keep the following points in mind:

- You can modify the pipeline data only during an active debug session.
- When you modify values in the pipeline, the changes apply only to the current debugging session. The Integration is not permanently changed.
- You can only modify existing variables. You cannot add new variables to the pipeline.

Export Integrations

Integration Cloud allows you to export Integrations from the **Integrations** page. The export capability is available only if you have the required license for exporting Integrations. You can export Integrations from one tenant and import those Integrations to another tenant. Ensure that you have the **Export** Integration permission to export Integrations.

To export Integrations

1. From the Integration Cloud navigation bar, click **Projects** > **<Select a Project>** > **Integrations**. The **Integrations** page appears.
2. Select the Integrations from the **Integrations** page and click **Export**. If the Integrations you are exporting use Reference Data, Document Types, SOAP, or REST Applications, then those Applications including the Reference Data and Document Types will also be exported along with the Integrations.

The **Confirm Export** dialog box appears.

Confirm Export
✕

The table lists the Integrations selected for export.

IMPORTANT: If exported Integrations contain on-premises Applications, same on-premises Applications must be uploaded before the import.

Name
ConcurAttendeeToSalesforceContacts12
add_integration_service

Cancel
Export

3. Click **Export** to export the Integrations. The Integrations will be downloaded as a zip file to your default download folder. The zip file size must not be greater than 50 MB.

Note: Do not modify the contents of the exported zip file. If you modify the contents of the zip file, the Integrations cannot be imported back to Integration Cloud.

Exporting Integrations having on-premises Applications

After exporting an Integration that has an on-premises Application, if you want to import the Integration, then before importing the Integration, ensure that you upload the same on-premises Application to Integration Cloud. Else, you will not be able to import the Integration.

Import Integrations

Integration Cloud allows you to import Integrations from the **Integrations** page. You can import Integrations from a zip file that was earlier exported from Integration Cloud. You can export Integrations from one tenant and import those Integrations to another tenant. You can import Integrations provided you have the **Create** Integration permission.


Note: If you want to import an Integration that has an on-premises Application, before importing the Integration, ensure that you upload the same on-premises Application to Integration Cloud. Else, you will not be able to import the Integration.

To import Integrations

1. From the Integration Cloud navigation bar, click **Projects** > **<Select a Project>** > **Integrations**. The **Integrations** page appears.
2. Click **Import Integrations**.

The **Import Integrations** page appears.

3. Click **Browse** and select the zip file that contains the exported Integrations. The zip file size must not be greater than 50 MB. The Integrations available in the zip file appears in the pane.



4. Click **Preview** to view an Integration or click **Import** to import an Integration.
5. In the **Configure Project and Applications** screen, select the **Account** for each Application or create a new Account, and then click **Next**.

Note: If the Integrations you are importing use SOAP or REST Applications and if those Applications do not exist in your system, you will not be able to create Accounts at this step. Continue importing the Integrations. The Applications will also be imported along with the Integrations. After importing, create the Accounts and then configure them in the imported Integrations.

Note: If an Integration you are importing uses an on-premises Application and if the Application does not exist in your system, you will not be able to select

the Account at this step. The Account will appear only after you have uploaded the on-premises Application. See the *Configuring On-Premise Integration Servers for webMethods Cloud* document for information on how to upload on-premises Applications.

The **Overview and Save Integration** screen appears.

6. In the **Overview and Save Integration** screen, provide a name and description for your Integration. By default, the Integration name and description appears.
7. Click **Finish**. If you have existing references (Reference Data, Document Types, and custom Operations) with the same name in the development stage, the **Copy References** screen appears. Click **Cancel** to go back to the **Overview and Save Integration** screen. By default, all references are selected in the **Copy References** screen.
8. Deselect the references that you do not want to replace and then click **Continue** to replace or overwrite all the selected references from the Integration in the development stage.

The Integration details screen appears for the newly created Integration.

Lock and Unlock Integrations

An Integration is an orchestration of a source and a target Operation with appropriate data mappings and transformations.

Note: Users who have the required permissions under **Settings**  > **Access Profiles** > **Administrative Permissions** > **Functional Controls** > **Integrations** can create, update, delete, execute, or deploy Integrations.

Integration Cloud allows you to manage an Integration during the development life cycle by auto locking. When you edit an Integration, it is automatically locked for you. This restricts multiple users editing that Integration at the same time.

After you edit an Integration and save the changes, you can exit the edit mode to unlock the Integration and make it available for other users. If you have locked the Integration and if another user opens the Integration in the preview mode, then that user gets notified when the lock gets released.

Note: Only the user who locked the Integration or an Administrator can unlock the Integration. To unlock an Integration, from the Integrations page, click the Integration link. The Integration **Overview** page appears. From the Integration **Overview** page, click **Unlock**.

View the status of a locked Integration


If an integration is locked, the lock status messages tells you who owns the lock.

View Integration ✕

 The Integration cannot be edited because **FirstName LastName** is currently editing the integration.

Do you want to view the Integration?

You can view the lock status of an integration in the workspace.



The screenshot shows a workspace interface. At the top, a blue header bar contains the text "Stage in view Development" and three icons: a gear, a question mark, and a user profile. Below the header, a central area displays a lock icon labeled "FL" and an "Exit" button. A tooltip points to the lock icon with the text: "FirstName LastName is currently editing the Integration."

If the integration you need is already locked, and if the current owner of the lock exits the integration, the integration screen notifies that the selected integration is ready for editing.

Edit Integration ✕

 **FirstName LastName** has completed editing the Integration.

Do you want to edit the Integration?

8 Recipes

- How to view and use Recipes 418

How to view and use Recipes

Recipes are pre-built Orchestrated or Point-to-Point Integration templates that can be used to create an Integration. Recipes are based on the most common integration needs and can significantly reduce the effort required to build an Integration. A recipe includes associated assets, for example Applications, Operations, Reference Data, and so on, that are used to create an Integration. A detailed description of the recipe along with its assets are available for preview, which helps you to select the right recipe. All Integrations created from recipes are initially copied to the development stage. The Recipes page is paginated to identify the sequential order of the pages. You can also select the number of recipes to be viewed per page.

To view and use recipes

- From the Integration Cloud navigation bar, click **Recipes**. The **Recipes** page appears. By default, recipes for all Applications and for all Integration types (Orchestrated and Point-to-Point) are displayed. You can search Recipes by Application names and for a specific Integration type. The **Recipes** page also displays the number of times you have used a recipe to create Integrations and the Applications referenced in the recipe. If there are more than two Applications referenced in the recipe, the **Recipes** page also displays the incremental number. The Recipes page is paginated to identify the sequential order of the pages. You can also select the number of recipes to be viewed per page.

ConcurAttendeeToSalesforceContacts



Extracts attendees from Concur and creates or updates the corresponding contacts in Salesforce.



Times used **10**

[Details](#)

[Use](#)

[Preview](#)

- Click **Preview** to see a view-only mode of the Integration details of the recipe.
- Click **Details** to view a detailed description of the recipe and the references in the **Recipe Details** page.
- From the **Recipes** or **Recipe Details** page, click **Use** if you want to apply the recipe to create a new Integration. The **Configure Project and Applications** page appears. Depending on the number of Integrations referenced in your recipe, a message is

displayed at the top of the page. You will be asked to configure all the Integrations in your recipe one after another.

- In the **Configure Project and Applications** page, select the project where you want to use this recipe.

Step 1: Configure Project and Applications

You are creating an Integration based on a recipe

Select Project *

Connect to Applications

Extracts attendees from Concur and creates or updates the corresponding contacts in Salesforce.

Select or Create Application Accounts

Application	Operation	Account
Salesforce CRM	addContact	connectCRM
Concur	getAttendee	ConnectConcur

- Select the **Account** for each Application or create a new Account, and then click **Next**.

The **Overview and Save Integration** page appears.

- In the **Overview and Save Integration** page, provide a name and description for your Integration. By default, the recipe name and recipe description is displayed.

Step 2: Overview and Save Integration

Save as *
Integration with name ConcurAttendeeToSalesforceContacts already exists.

Description

Application	Operation	Account
Salesforce CRM	addContact	connectCRM
Concur	getAttendee	ConnectConcur

- Click **Finish**. If you have existing references (Reference Data, Document Types, and custom Operations) with the same name in the development stage, the **Copy References** page appears. Click **Cancel** to go back to the **Overview and Save Integration** page. By default, all references are selected in the **Copy References** page.

Copy References x

The table displays the list of existing references with the same name in the development stage. Click Continue to replace all the selected references from the recipe in the development stage.

<input checked="" type="checkbox"/>	Name	Type
<input checked="" type="checkbox"/>	addContact	
<input checked="" type="checkbox"/>	getAttendee	

- Deselect the references that you do not want to replace and then click **Continue** to replace or overwrite all the selected references from the recipe in the development stage.

The Integration details page appears for the newly created Integration. The Integration is available in the selected project.

9 Built-In Services

- Overview 422
- Built-In Services 422

Overview

Services are method-like units of logic that clients can invoke. Integration Cloud has an extensive library of built-in services for performing common integration tasks such as transforming data values, performing simple mathematical operations, and so on. Related services are grouped in blocks. Input and output parameters are the names and types of fields that the service requires as input and generates as output and these parameters are collectively referred to as a signature.

Built-In Services

Services will be invoked at run time and related services are grouped together. While creating an Integration, you can sequence services and manage the flow of data among them.

Date

Use **Date** services to generate and format date values.

Pattern String Symbols - Many of the Date services require you to specify pattern strings describing the data's current format and/or the format to which you want it converted. For services that require a pattern string, use the symbols in the following table to describe the format of your data. For example, to describe a date in the January 15, 1999 format, you would use the pattern string `MMMM dd, yyyy`. To describe the format `01/15/99`, you would use the pattern string `MM/dd/yy`.

Symbol	Meaning	Presentation	Example
G	era designator	Text	AD
y	year	Number	1996 or 96
M	month in year	Text or Number	July or Jul or 07
d	day in month	Number	10
h	hour in am/pm (1-12)	Number	12
H	hour in day (0-23)	Number	0
m	minute in hour	Number	30

Symbol	Meaning	Presentation	Example
s	second in minute	Number	55
S	millisecond	Number	978
E	day in week	Text	Tuesday or Tue
D	day in year	Number	189
F	day of week in month	Number	2 (2nd Wed in July)
w	week in year	Number	27
W	week in month	Number	2
a	am/pm marker	Text	PM
k	hour in day (1-24)	Number	24
K	hour in am/pm (0-11)	Number	0
z	time zone	Text	Pacific Standard Time or PST or GMT-08:00
Z	RFC 822 time zone (JVM 1.4 or later)	Number	-0800 (offset from GMT/UT)
'	escape for text	Delimiter	
''	single quote	Literal	'

Time Zones - When working with date services, you can specify time zones. The Earth is divided into 24 standard time zones, one for every 15 degrees of longitude. Using the time zone including Greenwich, England (known as Greenwich Mean Time, or GMT) as the starting point, the time is increased by an hour for each time zone east of Greenwich and decreases by an hour for each time zone west of Greenwich. The time difference between a time zone and the time zone including Greenwich, England (GMT) is referred to as the *raw offset*.

The following table identifies the different time zones for the Earth and the raw offset for each zone from Greenwich, England. The effects of daylight savings time are ignored in this table.

Note: Greenwich Mean Time (GMT) is also known as Universal Time (UT).

ID	Raw Offset	Name
MIT	-11	Midway Islands Time
HST	-10	Hawaii Standard Time
AST	-9	Alaska Standard Time
PST	-8	Pacific Standard Time
PNT	-7	Phoenix Standard Time
MST	-7	Mountain Standard Time
CST	-6	Central Standard Time
EST	-5	Eastern Standard Time
IET	-5	Indiana Eastern Standard Time
PRT	-4	Puerto Rico and U.S. Virgin Islands Time
CNT	-3.5	Canada Newfoundland Time
AGT	-3	Argentina Standard Time
BET	-3	Brazil Eastern Time
GMT	0	Greenwich Mean Time
ECT	+1	European Central Time
CAT	+2	Central Africa Time
EET	+2	Eastern European Time
ART	+2	(Arabic) Egypt Standard Time
EAT	+3	Eastern African Time

ID	Raw Offset	Name
MET	+3.5	Middle East Time
NET	+4	Near East Time
PLT	+5	Pakistan Lahore Time
IST	+5.5	India Standard Time
BST	+6	Bangladesh Standard Time
VST	+7	Vietnam Standard Time
CTT	+8	China Taiwan Time
JST	+9	Japan Standard Time
ACT	+9.5	Australian Central Time
AET	+10	Australian Eastern Time
SST	+11	Solomon Standard Time
NST	+12	New Zealand Standard Time

Examples - You can specify *timezone* input parameters in the following formats:

- As a full name. For example:

```
Asia/Tokyo           America/Los_Angeles
```

You can use the `java.util.TimeZone.getAvailableIDs()` method to obtain a list of the valid full name time zone IDs that your JVM version supports.

- As a custom time zone ID, in the format `GMT[+ | -]hh[[:]mm]`. For example:

```
GMT+2:00           All time zones 2 hours east of Greenwich (that is, Central Africa
                   Time, Eastern European Time, and Egypt Standard Time)

GMT-3:00           All time zones 3 hours west of Greenwich (that is, Argentina
                   Standard Time and Brazil Eastern Time)
```

GMT+9:30 All time zones 9.5 hours east of Greenwich (that is, Australian Central Time)

- As a three-letter abbreviation from the table above. For example:

PST Pacific Standard Time

Note: Because some three-letter abbreviations can represent multiple time zones, for example, "CST" could represent both U.S. "Central Standard Time" and "China Standard Time", all abbreviations are deprecated. Use the full name or custom time zone ID formats instead.

Notes on Invalid Dates - The dates you use with a date service must adhere to the `java.text.SimpleDateFormat` class.

If you use an invalid date with a date service, the date service automatically translates the date to a legal date. For example, if you specify `1999/02/30` as input, the date service interprets the date as `1999/03/02` (two days after `2/28/1999`).

If you use `00` for the month or day, the date service interprets `00` as the last month or day in the Gregorian calendar. For example, if you specify `00` for the month, the date service interprets it as `12`.

If the pattern `yy` is used for the year, the date service uses a 50-year moving window to interpret the value of `yy`. The date service establishes the window by subtracting 49 years from the current year and adding 50 years to the current year. For example, if you are running Integration Cloud in the year 2000, the moving window would be from 1951 to 2050. The date service interprets 2-digit years as falling into this window (for example, `12` would be 2012, `95` would be 1995).

The following **Date** services are available:

Service	Description
calculateDateDifference	Calculates the difference between two dates and returns the result as seconds, minutes, hours, and days.
compareDates	Compares two dates and returns the result as integer.
currentNanoTime	Returns the current time returned by the most precise system timer, in nanoseconds.
dateBuild	Builds a date String using the specified pattern and the specified date services.

Service	Description
<code>dateTimeBuild</code>	Builds a date/time string using the specified pattern and the specified date services.
<code>dateTimeFormat</code>	Converts date/time (represented as a String) string from one format to another.
<code>elapsedNanoTime</code>	Calculates the time elapsed between the current time and the given time, in nanoseconds.
<code>formatDate</code>	Formats a Date object as a string.
<code>getCurrentDate</code>	Returns the current date as a Date object.
<code>getCurrentDateString</code>	Returns the current date as a String in a specified format.
<code>incrementDate</code>	Increments a date by a specified period.

calculateDateDifference

Calculates the difference between two dates and returns the result as seconds, minutes, hours, and days.

Input Parameters

<code>startDate</code>	String Starting date and time.
<code>endDate</code>	String Ending date and time.
<code>startDatePattern</code>	String Format in which the <code>startDate</code> parameter is to be specified (for example, yyyyMMdd HH:mm:ss.SSS). For pattern-string notation, see the “Pattern String Symbols” section.
<code>endDatePattern</code>	String Format in which the <code>endDate</code> parameter is to be specified (for example, yyyyMMdd HH:mm:ss.SSS). For pattern-string notation, see the “Pattern String Symbols” section.

Output Parameters

<i>dateDifferenceSeconds</i>	String The difference between the <i>startingDateTime</i> and <i>endingDateTime</i> , truncated to the nearest whole number of seconds.
<i>dateDifferenceMinutes</i>	String The difference between the <i>startingDateTime</i> and <i>endingDateTime</i> , truncated to the nearest whole number of minutes.
<i>dateDifferenceHours</i>	String The difference between the <i>startingDateTime</i> and <i>endingDateTime</i> , truncated to the nearest whole number of hours.
<i>dateDifferenceDays</i>	String The difference between the <i>startingDateTime</i> and <i>endingDateTime</i> , truncated to the nearest whole number of days.

Usage Notes

Each output value represents the same date difference, but in a different scale. Do not add these values together. Make sure your subsequent Integration steps use the correct output, depending on the scale required.

compareDates

Compares two dates and returns the result as an integer.

Input Parameters

<i>startDate</i>	String Starting date to compare against <i>endDate</i> .
<i>endDate</i>	String Ending date to compare against <i>startDate</i> .
<i>startDatePattern</i>	String Format in which the <i>startDate</i> parameter is specified (for example, yyyyMMdd HH:mm:ss.SSS). For pattern-string notation, see the "Pattern String Symbols" section.
<i>endDatePattern</i>	String Format in which the <i>endDate</i> parameter is specified (for example, yyyyMMdd HH:mm:ss.SSS). For pattern-string notation, see the "Pattern String Symbols" section.

Output Parameters

result **String** Checks whether *startDate* is before, the same, or after the *endDate*.

<u>A value of...</u>	<u>Indicates that...</u>
+1	The <i>startDate</i> is after the <i>endDate</i> .
0	The <i>startDate</i> is the same as the <i>endDate</i> .
-1	The <i>startDate</i> is before the <i>endDate</i> .

Usage Notes

If the formats specified in the *startDatePattern* and *endDatePattern* parameters are different, Integration Cloud takes the units that are not specified in the *startDate* and *endDate* values as 0.

That is, if the *startDatePattern* is `yyyyMMdd HH:mm` and the *startDate* is `20151030 11:11` and if the *endDatePattern* is `yyyyMMdd HH:mm:ss.SSS` and the *endDate* is `20151030 11:11:55:111`, then the `compareDates` service considers start date to be before the end date and will return the result as `-1`.

To calculate the difference between two dates, use the `calculateDateDifference` service.

currentNanoTime

Returns the current time returned by the most precise system timer, in nanoseconds.

Input Parameters

None.

Output Parameters

nanoTime **java.lang.Long** Current time returned by the most precise system timer, in nanoseconds.

dateBuild

Builds a date String using the specified pattern and the specified date services.

Input Parameters

<i>pattern</i>	String Pattern representing the format in which you want the date returned. For pattern-string notation, see the "Pattern String Symbols" section. If you do not specify <i>pattern</i> , <code>dateBuild</code> returns null. If <i>pattern</i> contains a time zone and <i>timezone</i> is not specified, the default time zone is used.
<i>year</i>	String Optional. The year expressed in <i>yyyy</i> or <i>yy</i> format (for example, 01 or 2001). If you do not specify <i>year</i> or you specify an invalid value, <code>dateBuild</code> uses the current year.
<i>month</i>	String Optional. The month expressed as a number (for example, 1 for January, 2 for February). If you do not specify <i>month</i> or you specify an invalid value, <code>dateBuild</code> uses the current month.
<i>dayofmonth</i>	String Optional. The day of the month expressed as a number (for example, 1 for the first day of the month, 2 for the second day of the month). If you do not specify <i>dayofmonth</i> or you specify an invalid value, <code>dateBuild</code> uses the current day.
<i>timezone</i>	String Optional. Time zone in which you want the output date and time expressed. Specify a time zone code as shown in the "Time Zones" section, for example, <code>EST</code> for Eastern Standard Time. If you do not specify <i>timezone</i> , the value of the server's "user timezone" property is used. If this property has not been set, GMT is used.
<i>locale</i>	String Optional. Locale in which the date is to be expressed. For example, if <i>locale</i> is <code>en</code> (for English), the pattern <code>EEE d MMM yyyy</code> will produce <code>Friday 23 August 2002</code> , and the <i>locale</i> of <code>fr</code> (for French) will produce <code>vendredi 23 août 2002</code> .

Output Parameters

<i>value</i>	String The date specified by <i>year</i> , <i>month</i> , and <i>dayofmonth</i> , in the format of <i>pattern</i> .
--------------	--

dateTimeBuild

Builds a date/time string using the specified pattern and the specified date services.

Input Parameters

<i>pattern</i>	String Pattern representing the format in which you want the time returned. For pattern-string notation, see the “Pattern String Symbols” section. If you do not specify <i>pattern</i> , <code>dateTimeBuild</code> returns null. If <i>pattern</i> contains a time zone and the <i>timezone</i> parameter is not set, the default time zone is used.
<i>year</i>	String Optional. The year expressed in <i>yyyy</i> or <i>yy</i> format (for example, 01 or 2001). If you do not specify <i>year</i> or you specify an invalid value, <code>dateTimeBuild</code> uses the current year.
<i>month</i>	String Optional. The month expressed as a number (for example, 1 for January, 2 for February). If you do not specify <i>month</i> or you specify an invalid value, <code>dateTimeBuild</code> uses the current month.
<i>dayofmonth</i>	String Optional. The day of the month expressed as a number (for example, 1 for the first day of the month, 2 for the second day of the month). If you do not specify <i>dayofmonth</i> or you specify an invalid value, <code>dateTimeBuild</code> uses the current day.
<i>hour</i>	String Optional. The hour expressed as a number based on a 24-hour clock. For example, specify 0 for midnight, 2 for 2:00 A.M., and 14 for 2:00 P.M. If you do not specify <i>hour</i> or you specify an invalid value, <code>dateTimeBuild</code> uses 0 as the <i>hour</i> value.
<i>minute</i>	String Optional. Minutes expressed as a number. If you do not specify <i>minute</i> or you specify an invalid value, <code>dateTimeBuild</code> uses 0 as the <i>minute</i> value.
<i>second</i>	String Optional. Seconds expressed as a number. If you do not specify <i>second</i> or you specify an invalid value, <code>dateTimeBuild</code> uses 0 as the <i>second</i> value.
<i>millis</i>	String Optional. Milliseconds expressed as a number. If you do not specify <i>millis</i> or you specify an invalid value, <code>dateTimeBuild</code> uses 0 as the <i>millis</i> value.

<i>timezone</i>	<p>String Optional. Time zone in which you want the output date and time expressed. Specify a time zone code as shown in the “Time Zones” section, for example, <code>EST</code> for Eastern Standard Time.</p> <p>If you do not specify <i>timezone</i>, the value of the server's "user timezone" property is used. If this property has not been set, GMT is used.</p>
<i>locale</i>	<p>String Optional. Locale in which the date is to be expressed. For example, if <i>locale</i> is <code>en</code> (for English), the pattern <code>EEE d MMM yyyy</code> will produce <code>Friday 23 August 2002</code>, and the <i>locale</i> of <code>fr</code> (for French) will produce <code>vendredi 23 août 2002</code>.</p>

Output Parameters

<i>value</i>	String Date and time in format of <i>pattern</i> .
--------------	---

dateTimeFormat

Converts date/time (represented as a String) string from one format to another.

Input Parameters

<i>inString</i>	<p>String Date/time that you want to convert.</p> <div style="background-color: #f0f0f0; padding: 10px; margin-top: 10px;"> <p>Important: If <i>inString</i> contains a character in the last position, that character is interpreted as 0. This can result in an inaccurate date. For information about invalid dates, see the “Notes on Invalid Dates” section.</p> </div>
<i>currentPattern</i>	String Pattern string that describes the format of <i>inString</i> . For pattern-string notation, see the “Pattern String Symbols” section.
<i>newPattern</i>	String Pattern string that describes the format in which you want <i>inString</i> returned. For pattern-string syntax, see the “Pattern String Symbols” section.
<i>locale</i>	<p>String Optional. Locale in which the date is to be expressed. For example, if <i>locale</i> is <code>en</code> (for English), the pattern <code>EEE d MMM yyyy</code> will produce <code>Friday 23 August 2002</code>, and the <i>locale</i> of <code>fr</code> (for French) will produce <code>vendredi 23 août 2002</code>.</p>

<i>lenient</i>	<p>String Optional. A flag indicating whether an exception will appear if the <i>inString</i> value does not adhere to the format specified in <i>currentPattern</i> parameter. Set to:</p> <ul style="list-style-type: none"> ■ <code>true</code> to perform a lenient check. This is the default. <p>In a lenient check, if the format of the date specified in the <i>inString</i> parameter does not match the format specified in the <i>currentPattern</i> parameter, the date in the format specified in the <i>currentPattern</i> parameter will be interpreted and returned. If the interpretation is incorrect, the service will return an invalid date.</p> ■ <code>false</code> to perform a strict check. <p>In a strict check, an exception will appear if the format of the date specified in the <i>inString</i> parameter does not match the format specified in the <i>currentPattern</i> parameter.</p>
----------------	---

Output Parameters

<i>value</i>	<p>String The date/time given by <i>inString</i>, in the format of <i>newPattern</i>.</p>
--------------	--

Usage Notes

As described in the “Notes on Invalid Dates” section, if the pattern *yy* is used for the year, `dateTimeFormat` uses a 50-year moving window to interpret the value of the year.

If *currentPattern* does not contain a time zone, the value is assumed to be in the default time zone.

If *newPattern* contains a time zone, the default time zone is used.

elapsedNanoTime

Calculates the time elapsed between the current time and the given time, in nanoseconds.

Input Parameters

<i>nanoTime</i>	<p>java.lang.Long Time in nanoseconds. If <i>nanoTime</i> is less than zero, then the service treats it as zero.</p>
-----------------	---

Output Parameters

<i>elapsedNanoTime</i>	java.lang.Long The difference between the current time in nanoseconds and <i>nanoTime</i> . If <i>nanoTime</i> is greater than the current nano time, the service returns zero.
<i>elapsedNanoTimeStr</i>	<p>String The difference between the current time in nanoseconds and <i>nanoTime</i> . The difference is expressed as a String, in this format:</p> <p>[years] [days] [hours] [minutes] [seconds] [millisec] [microsec] <nanosec></p> <p>If <i>nanoTime</i> is greater than the current nano time, the service returns zero.</p>

formatDate

Formats a Date object as a string.

Input Parameters

<i>date</i>	java.util.Date Optional. Date/time that you want to convert.
<i>pattern</i>	String Pattern string that describes the format in which you want the date returned. For pattern-string notation, see the <i>Pattern String Symbols</i> section.
<i>timezone</i>	<p>String Optional. Time zone in which you want the output date and time expressed. Specify a time zone code as shown in the <i>Time Zones</i> section, for example, <i>EST</i> for Eastern Standard Time.</p> <p>If you do not specify <i>timezone</i> , the user's time zone is used, else GMT is used.</p>
<i>locale</i>	String Optional. Locale in which the date is to be expressed. For example, if <i>locale</i> is <i>en</i> (for English), the pattern <i>EEE d MMM yyyy</i> will produce <i>Friday 23 August 2002</i> , and the <i>locale</i> of <i>fr</i> (for French) will produce <i>vendredi 23 août 2002</i> .

Output Parameters

<i>value</i>	String The date/time given by <i>date</i> in the format specified by <i>pattern</i> .
--------------	--

getCurrentDate

Returns the current date as a Date object.

Input Parameters

None.

Output Parameters

date **java.util.Date** Current date.

getCurrentDateString

Returns the current date as a String in a specified format.

Input Parameters

pattern **String** Pattern representing the format in which you want the date returned. For pattern-string notation, see the “Pattern String Symbols” section.

timezone **String** Optional. Time zone in which you want the output date and time expressed. Specify a time zone code as shown in the “Time Zones” section, for example, `EST` for Eastern Standard Time.

If you do not specify *timezone*, the value of the server's "user timezone" property is used. If this property has not been set, GMT is used.

locale **String** Optional. Locale in which the date is to be expressed. For example, if *locale* is `en` (for English), the pattern `EEE d MMM yyyy` will produce `Friday 23 August 2002`, and the *locale* of `fr` (for French) will produce `vendredi 23 août 2002`.

Output Parameters

value **String** Current date in the format specified by *pattern*.

incrementDate

Increments a date by a specified amount of time.

Input Parameters

<i>startDate</i>	String Starting date and time.
<i>startDatePattern</i>	String Format in which the <i>startDate</i> parameter is specified (for example, yyyyMMdd HH:mm:ss.SSS). For pattern-string notation, see the "Pattern String Symbols" section.
<i>endDatePattern</i>	String Optional. Pattern representing the format in which you want the <i>endDate</i> to be returned. For pattern-string notation, see the "Pattern String Symbols" section. If no <i>endDatePattern</i> is specified, the <i>endDate</i> will be returned in the format specified in the <i>startDatePattern</i> parameter.
<i>addYears</i>	String Optional. Number of years to add to <i>startDate</i> . The value must be an integer between -2147483648 and 2147483647.
<i>addMonths</i>	String Optional. Number of months to add to <i>startDate</i> . The value must be an integer between -2147483648 and 2147483647.
<i>addDays</i>	String Optional. Number of days to add to <i>startDate</i> . The value must be an integer between -2147483648 and 2147483647.
<i>addHours</i>	String Optional. Number of hours to add to <i>startDate</i> . The value must be an integer between -2147483648 and 2147483647.
<i>addMinutes</i>	String Optional. Number of minutes to add to <i>startDate</i> . The value must be an integer between -2147483648 and 2147483647.

<i>addSeconds</i>	String Optional. Number of seconds to add to <i>startDate</i> . The value must be an integer between -2147483648 and 2147483647.
<i>addMilliseconds</i>	String Optional. Number of milliseconds to add to <i>startDate</i> . The value must be an integer between -2147483648 and 2147483647.
<i>timezone</i>	String Optional. Time zone in which you want the <i>endDate</i> to be expressed. Specify a time zone code, for example, EST for Eastern Standard Time. If you do not specify <i>timezone</i> , the value of the server's "user timezone" property is used. If this property has not been set, GMT is used.
<i>locale</i>	String Optional. Locale in which the <i>endDate</i> is to be expressed. For example, if <i>locale</i> is <i>en</i> (for English), the pattern <i>EEE d MMM yyyy</i> will produce <i>Friday 23 August 2002</i> , and the <i>locale</i> of <i>fr</i> (for French) will produce <i>vendredi 23 août 2002</i> .

Output Parameters

<i>endDate</i>	String The end date and time, calculated by incrementing the <i>startDate</i> with the specified years, months, days, hours, minutes, seconds, and/or milliseconds. The <i>endDate</i> will be in the <i>endDatePattern</i> format, if specified. If no <i>endDatePattern</i> is specified or if blank spaces are specified as the value, the <i>endDate</i> will be returned in the format specified in the <i>startDatePattern</i> parameter.
----------------	--

Usage Notes

The *addYears*, *addMonths*, *addDays*, *addHours*, *addMinutes*, *addSeconds*, and *addMilliseconds* input parameters can take positive or negative values. For example, If *startDate* is 10/10/2001, *startDatePattern* is MM/dd/yyyy, *addYears* is 1, and *addMonths* is -1, *endDate* will be 09/10/2002.

If you specify only the *startDate*, *startDatePattern*, and *endDatePattern* input parameters and do not specify any of the optional input parameters to increment the period,

the `incrementDate` service just converts the format of `startDate` from `startDatePattern` to `endDatePattern` and returns it as `endDate`.

Note: The format of the date specified in the `startDate` parameter must match the format specified in the `startDatePattern` and the format of the date specified in the `endDate` parameter must match the `endDatePattern` format.

Document

Use **Document** services to perform operations on documents.

The following **Document** services are available:

Service	Description
findDocuments	Searches a set of documents for entries matching a set of Criteria.
insertDocument	Inserts a new document in a set of documents at a specified position.
deleteDocuments	Deletes the specified documents from a set of documents.
documentListToDocument	Constructs a document from a document list by generating key/value pairs from the values of two elements that you specify in the document list.
documentToDocumentList	Expands the contents of a document into a list of documents. Each key/value pair in the source document is transformed to a single document containing two keys (whose names you specify). These two keys will contain the key name and value of the original pair.
groupDocuments	Groups a set of documents based on specified criteria.
documentToBytes	Converts a document to an array of bytes.
bytesToDocument	Converts an array of bytes to a document.

Service	Description
searchDocuments	Searches a set of documents for entries matching a set of Criteria.
sortDocuments	Sorts a set of input documents based on the specified sortCriteria.

findDocuments

Searches a set of documents for entries matching a set of criteria.

Input Parameters

- documents* **Document List** Set of documents from which the documents meeting the retrieve criteria are to be returned.
- matchCriteria* **Document** Criteria on which the documents in the `documents` parameter are to be matched. Parameters for `matchCriteria` are:
- path:** Name of the element in `documentList` whose value provides the value for the search text. The value for `key` can be a path expression. For example, "Family/Chidren[0]/ BirthDate" retrieves the birthday of the first child from the input `Family` document list.
- compareValueAs:** Optional. Allowed values are string, numeric, and datetime. The default value is string.
- datePattern:** Optional. Pattern will be considered only if `compareValueAs` is of type datetime. Default value is MM/dd/yyyy hh:mm:ss a.
- joins:** List of join criteria. Each join criteria consists of:
- operator:** Allowed values are equals, doesNotEqual, greaterThan, greaterThanEqual, lessThan, lessThanEqual, equalsIgnoreCase, contains, doesNotContain, beginsWith, doesNotBeginWith, endsWith, doesNotEndWith.
- value:** Optional. Allowed values are string, numeric, and datetime. The default value is string.
- joinType:** Specifies the way two joins can be linked. Values are "and" or "or". Default value is "and".

Output Parameters

result **Document List** List of documents that match the retrieve criteria.
documents

insertDocument

Inserts a new document in a set of documents at a specified position.

Input Parameters

documents **Document List** Set of documents in which a new document is to be inserted.

insertDocument **Document** The new document to be inserted to the set of documents specified in the *documents* parameter.

index **String** Optional. The position in the set which the document is to be inserted.

 The *index* parameter is zero-based. If the value for the *index* parameter is not specified, the document will be inserted at the end of the document list specified in the *documents* parameter.

Output Parameters

documents **Document List** Document list after inserting the new document.

deleteDocuments

Deletes the specified documents from a set of documents.

Input Parameters

documents **Document List** Set of documents that contain the documents you want to delete.

indices **String List** Index values of documents to be deleted from the *documents* parameter document list.

Output Parameters

documents **Document List** List of documents whose indices do *not* match the values in *indices* parameter.

deletedDocuments **Document List** List of deleted documents.

Usage Notes

The deleteDocuments service returns an error if the *indices* parameter value is less than zero or more than the number of documents in the *documents* input parameter.

documentListToDocument

Constructs a document from a document list by generating key/value pairs from the values of two elements that you specify in the document list.

Input Parameters

documentList **Document List** Set of documents that you want to transform into a single document.

Note: If the *documentList* parameter contains a single document instead of a Document List, the *documentListToDocument* service does nothing.

name **String** Name of the element in the *documentList* parameter whose value provides the name of each key in the resulting document.

Important: The data type of the element that you specify in the *name* parameter must be String.

value **String** Name of the element in the *documentList* parameter whose values will be assigned to the keys specified in *name*. This element can be of any data type.

Output Parameters

document **Document** Document containing the key/value pairs generated from the *documentList* parameter.

Usage Notes

The following example illustrates how the `documentListToDocument` service would convert a document list that contains three documents to a single document containing three key/value pairs. When you use the `documentListToDocument` service, you specify which two elements from the source list are to be transformed into the keys and values in the output document. In the following example, the values from the `pName` elements in the source list are transformed into key names, and the values from the `pValue` elements are transformed into the values for these keys.

A `documentList` containing these three documents:

Key	Value
<i>pName</i>	<code>cx_timeout</code>

<i>pValue</i>	1000
---------------	------

Key	Value
<i>pName</i>	<code>cx_max</code>

<i>pValue</i>	2500
---------------	------

Key	Value
<i>pName</i>	<code>cx_min</code>

<i>pValue</i>	10
---------------	----

Would be converted to a document containing these three key:

Key	Value
<i>cx_timeout</i>	1000
<i>cx_max</i>	2500
<i>cx_min</i>	10

documentToDocumentList

Expands the contents of a document into a list of documents.

Each key/value pair in the source document is transformed to a single document containing two keys (whose names you specify). These two keys will contain the key name and value of the original pair.

Input Parameters

<i>document</i>	Document Document to transform.
<i>name</i>	String Name to assign to the key that will receive the key name from the original key/value pair. In the example above, this parameter was set to <code>pName</code> .
<i>value</i>	String Name to assign to the key that will receive the value from the original key/value pair. In the example above, this parameter was set to <code>pValue</code> .

Output Parameters

<i>documentList</i>	Document List List containing a document for each key/value pair in the <i>document</i> parameter. Each document in the list will contain two keys, whose names were specified by the <i>name</i> and <i>value</i> parameters. The values of these two keys will be the name and value (respectively) of the original pair.
---------------------	--

Usage Notes

The following example shows how a document containing three keys would be converted to a document list containing three documents. In this example, the names *pName* and *pValue* are specified as names for the two new keys in the document list.

A document containing these three keys:

Key	Value
<i>cx_timeout</i>	1000
<i>cx_max</i>	2500
<i>cx_min</i>	10

Would be converted to a document list containing these three documents:

Key	Value
<i>pName</i>	<code>cx_timeout</code>
<i>pValue</i>	1000

Key	Value
<i>pName</i>	<code>cx_max</code>
<i>pValue</i>	2500

Key	Value
<i>pName</i>	<code>cx_min</code>
<i>pValue</i>	10

groupDocuments

Groups a set of documents based on specified criteria.

Input Parameters

<i>documents</i>	Document List Set of documents to be grouped based on the specified criteria.
<i>groupCriteria</i>	<p>Document List The criteria on which the input documents are to be grouped. Valid values for the <i>groupCriteria</i> parameter are:</p> <ul style="list-style-type: none"> ■ <i>key</i>. Key in the pipeline. The value for <i>key</i> can be a path expression. For example, "Family/Chidren[0]/BirthDate" retrieves the birthday of the first child from the input Family document list. ■ <i>compareStringsAs</i>. Optional. Valid values for <i>compareStringsAs</i> are <code>string</code>, <code>numeric</code>, and <code>datetime</code>. The default value is <code>string</code>. ■ <i>pattern</i>. Optional. <i>pattern</i> will be considered only if the <i>compareStringsAs</i> parameter is of type <code>datetime</code>.

Note: If *key* is not found in all the input documents, the documents that do not match the *groupCriteria* are grouped together as a single group.

Output Parameters

documentGroups **Document List** List of documents where each element represents a set of documents grouped based on the criteria specified.

Usage Notes

The following example illustrates how to specify the values for the *groupCriteria* parameter:

key	compareStringsAs	pattern
name	string	
age	numeric	
birthdate	datetime	yyyy-MM-dd

The input documents will be grouped based on name, age, and birth date.

documentToBytes

Converts a document to an array of bytes.

Input Parameters

document **Document** Document to convert to bytes.

- If *document* is null, the service does not return an output or an error message.
- If *document* is not a document, the service throws an exception.
- If *document* contains no elements, the service produces a zero-length byte array.

Output Parameters

documentBytes **Object** A serialized representation of the document as an array of bytes (byte[]).

Usage Notes

Use the `documentToBytes` service with the `bytesToDocument` service, which converts the byte array created by this service back into the original document.

The `documentToBytes` service is useful when you want to write a document to a file, an input stream, or a cache.

In order for the document-to-bytes-to-document conversion to work, the entire content of the document must be serializable. Every object in the document must be of a data type known to Integration Cloud, or it must support the `java.io.Serializable` interface. If Integration Cloud encounters an unknown object in the document that does not support the `java.io.Serializable` interface, that object's value will be lost. Integration Cloud will replace it with a string containing the object's class name.

bytesToDocument

Converts an array of bytes to a document. This service can only be used with byte arrays created by executing the `documentToBytes` service.

Input Parameters

documentBytes **Object** An array of bytes (byte[]) to convert to a document.

- If *documentBytes* is null, the service does not return a document or an error message.
- If *documentBytes* is not a byte array, the service throws an exception.
- If *documentBytes* is zero-length, the service produces an empty document.

Output Parameters

document **Document** A document.

Usage Notes

Use this service with the `documentToBytes` service, which converts a document into a byte array. You can pass the resulting byte array to the `bytesToDocument` service to convert it back into the original document.

In order for the document-to-bytes-to-document conversion to work, the entire content of the document must be serializable. Every object in the document must be of a data type known to Integration Cloud, or it must support the `java.io.Serializable` interface.

Note: If Integration Cloud encounters an unknown object in the document that does not support the `java.io.Serializable` interface, that object's value will be lost. It will be replaced with a string containing the object's class name.

searchDocuments

Searches a set of documents for entries matching a set of Criteria.

Input Parameters

<i>documents</i>	Document List Set of documents from which the documents meeting the search criteria are to be returned.
<i>searchCriteria</i>	<p>Document Criteria on which the documents in the <i>documents</i> parameter are to be searched.</p> <p>Valid values for <i>searchCriteria</i> parameters are:</p> <ul style="list-style-type: none"> ■ <i>key</i>. Name of the element in <code>documentList</code> whose value provides the value for the search text. The value for <i>key</i> can be a path expression. For example, "Family/Chidren[0]/BirthDate" retrieves the birthday of the first child from the input Family document list. ■ <i>value</i>. Optional. Any search text. If no value is specified, the service searches for null in the document list. ■ <i>compareStringsAs</i>. Optional. Allowed values are <code>string</code>, <code>numeric</code>, and <code>datetime</code>. The default value is <code>string</code>. ■ <i>pattern</i>. Optional. <i>pattern</i> will be considered only if the <i>compareStringsAs</i> value is of type <code>datetime</code>. For information about using patterns, see the <i>Time Zones</i> section.
<i>sorted</i>	String Optional. The value of the <i>sorted</i> parameter is <code>true</code> if the document list is already sorted based on the search criteria and same search key; otherwise <code>false</code> .

If the value for the *sorted* parameter is set to `true`, the required documents are searched faster.

Output Parameters

<i>resultdocuments</i>	Document List List of documents which are matching the search criteria.
<i>documentListIndices</i>	String List Positions of search documents in the document list.
<i>documents</i>	Document List List of documents that were input.

Usage Note

For example, if you want to search a set of documents for documents where BirthDate is 10th January 2008, the values for the *searchCriteria* parameter would be:

<u>key</u>	<u>value</u>	<u>compareStringsAs</u>	<u>pattern</u>
Birthdate	2008-01-10	datetime	yyyy-MM-dd

sortDocuments

Sorts a set of input documents based on the specified sortCriteria.

Input Parameters

<i>documents</i>	Document List Set of documents that are to be sorted.
<i>sortCriteria</i>	<p>Document List Criteria based on which the documents in the <i>documents</i> parameter are to be sorted.</p> <p>Valid values for <i>sortCriteria</i> parameters are:</p> <ul style="list-style-type: none"> ■ <i>key</i>. Name of the element in documentList whose value provides the value based on which the documents are to be sorted. The value for <i>key</i> can be a path expression. For example, "Family/Children[0]/BirthDate" retrieves the birthday of the first child from the input Family document list. ■ <i>order</i>. Optional. Allowed values are <code>ascending</code> and <code>descending</code>. The default value is <code>ascending</code>.

- *compareStringsAs* . Optional. Allowed values are `string`, `numeric`, and `datetime`. Default value is `string`.
- *pattern* . Optional. The value for *pattern* will be considered only if the *compareStringsAs* value is of type `datetime`.

Note: If *key* is not found in all the input documents, the sorted list of documents appears at the end or start of the list based on the *order* specified. If the order is ascending, then all the documents that do not match the sort criteria appears at the top of the list, followed by the sorted list. If the order is descending, the sorted list will appear at the top, followed by the documents that do not match the sort criteria.

Output Parameters

documents **Document List** The documents sorted based on the sort criteria specified in the *sortCriteria* parameter.

Usage Notes

For example, if you want to sort a set of documents based on name, age, and then on birth date, the values for *sortCriteria* parameter would be:

<u>key</u>	<u>order</u>	<u>compareStringsAs</u>	<u>pattern</u>
Name	ascending	string	
Age	descending	numeric	
Birthdate	ascending	datetime	yyyy-MM-dd

List

Use **List** services to retrieve, replace, or add elements in an Object List, Document List, or String List, including converting String Lists to Document Lists.

The following **List** services are available:

Service	Description
addItemToVector	Adds an item or a list of items to a <code>java.util.Vector</code> object.

Service	Description
appendToDocumentList	Adds documents to a document list.
appendToStringList	Adds Strings to a String list.
sizeOfList	Returns the number of elements in a list.
stringListToDocumentList	Converts a String list to a document list.
vectorToArray	Converts a java.util.Vector object to an array.

addItemToVector

Adds an item or a list of items to a java.util.Vector object.

Input Parameters

<i>vector</i>	java.util.Vector Optional. The vector object to which you want to add an item or list of items. If no value is specified, the service creates a new java.util.Vector object to which the item(s) will be added.
<i>item</i>	Object Optional. Item to be added to the vector object. Note: You can use either <i>item</i> or <i>itemList</i> to specify the input object. If both <i>item</i> and <i>itemList</i> input parameters are specified, the item as well as the list of items will be added to the vector object.
<i>itemList</i>	Object[] Optional. List of items to be added to the vector object.
<i>addNulls</i>	String Optional. Specifies whether a null item can be added to the vector object. Set to: <ul style="list-style-type: none"> ■ <code>false</code> to prevent null values from being added to the vector object. This is the default. ■ <code>true</code> to allow null values to be added to the vector object.

Output Parameters

vector **java.util.Vector** Updated vector object with the list of items added or an empty vector in case no items are added.

Usage Notes

Either of the optional input parameters, *item* or *itemList*, is required.

appendToDocumentList

Adds documents to a document list.

Input Parameters

toList **Document List** Optional. List to which you want to append documents. If you do not specify *toList*, the service creates a new list.

fromList **Document List** Optional. Documents you want to append to the end of *toList*.

fromItem **Document** Optional. Document you want to append to the end of *toList*. If you specify both *fromList* and *fromItem*, the service adds the document specified in *fromItem* after the documents in *fromList*.

Output Parameters

toList **Document List** The *toList* document list with the documents in *fromList* and *fromItem* appended to it.

Usage Notes

The documents contained in *fromList* and *fromItem* are not actually appended as entries to *toList*. Instead, references to the documents in *fromList* and *fromItem* are appended as entries to *toList*. Consequently, any changes made to the documents in *fromList* and *fromItem* also affect the resulting *toList*.

appendToStringList

Adds Strings to a String list.

Input Parameters

<i>toList</i>	String List Optional. List to which you want to append Strings. If the value of <i>toList</i> is null, a null pointer exception error is thrown. If you do not specify <i>toList</i> , the service creates a new list.
<i>fromList</i>	String List Optional. List of Strings to add to <i>toList</i> . Strings are added after the entries of <i>toList</i> .
<i>fromItem</i>	String Optional. String you want to append to the end of <i>toList</i> . If you specify both <i>fromList</i> and <i>fromItem</i> , the service adds the String specified in <i>fromItem</i> after the Strings specified in <i>fromList</i> .

Output Parameters

<i>toList</i>	String List The <i>toList</i> String list with the Strings from <i>fromList</i> and <i>fromItem</i> appended to it.
---------------	--

Usage Notes

The Strings contained in *fromList* and *fromItem* are not actually appended as entries to *toList*. Instead, references to the Strings in *fromList* and *fromItem* are appended as entries to *toList*. Consequently, any changes made to the Strings in *fromList* and *fromItem* also affect the resulting *toList*.

sizeOfList

Returns the number of elements in a list.

Input Parameters

<i>fromList</i>	Document List, String List, or Object List Optional. List whose size you want to discover. If <i>fromList</i> is not specified, the service returns a <i>size</i> of 0.
-----------------	--

Output Parameters

<i>size</i>	String Number of entries in <i>fromList</i> .
<i>fromList</i>	Document List, String List, or Object List Original list.

Usage Notes

For example, if *fromList* consists of:

```
fromList [0] = "a"
```

```
fromList [1] = "b"
```

```
fromList [2] = "c"
```

The result would be:

```
size = "3"
```

stringListToDocumentList

Converts a String list to a document list.

Input Parameters

<i>fromList</i>	String List Optional. List of Strings (a <code>String[]</code>) that you want to convert to a list of documents. If <i>fromList</i> is not specified, the service returns a zero length array for <i>toList</i> .
<i>key</i>	String Optional. Key name to use in the generated document list.

Output Parameters

<i>toList</i>	Document List Resulting document list.
---------------	---

Usage Notes

Creates a document list containing one document for each element in the *fromList* . Each document will contain a single String element named *key* .

For example, if *fromList* consists of:

```
fromList [0] = "a"
```

```

fromList [1] = "b"
fromList [2] = "c"
key = "myKey"

```

The result would be:

▼  toList []	
▼  toList[0]	
 myKey	a
▼  toList[1]	
 myKey	b
▼  toList[2]	
 myKey	c

vectorToArray

Converts a java.util.Vector object to an array.

Input Parameters

<i>vector</i>	java.util.Vector The object to be converted to an array.
<i>stronglyType</i>	<p>String Optional. If this option is specified, the service expects all items in the vector to have the same Java type as the first non-null item in the vector. If the service detects an item of a different type, an error appears.</p> <p>Set to:</p> <ul style="list-style-type: none"> ■ <code>false</code> to convert the vector to an object array. This is the default. ■ <code>true</code> to convert the vector to a strongly typed array holding the same type of objects.

Output Parameters

<i>array</i>	Object[] Converted object array.
--------------	--

Math

Use **Math** services to perform mathematical operations on string-based numeric values. Services that operate on integer values use Java's long data type (64-bit, two's complement). Services that operate on float values use Java's double data type (64-bit IEEE 754). If extremely precise calculations are critical to your application, you should write your own Java services to perform math functions.

The following **Math** services are available:

Service	Description
addObjects	Adds one java.lang.Number object to another and returns the sum.
divideObjects	Divides one java.lang.Number object by another ($num1/num2$) and returns the quotient.
min	Returns the smallest number from a list of numbers.
multiplyObjects	Multiplies one java.lang.Number object by another and returns the product.
subtractObjects	Subtracts one java.lang.Number object from another and returns the difference.
toNumber	Converts a string to numeric data type.
absoluteValue	Returns the absolute value of the input number.
addFloatList	Adds a list of floating point numbers (represented in a string list) and returns the sum.
addFloats	Adds one floating point number (represented as a String) to another and returns the sum.
addIntList	Adds a list of integers (represented in a String list) and returns the sum.
addInts	Adds one integer (represented as a String) to another and returns the sum.

Service	Description
divideFloats	Divides one floating point number (represented as a String) by another (<i>num1/num2</i>) and returns the quotient.
divideInts	Divides one integer (represented as a String) by another (<i>num1/num2</i>) and returns the quotient.
max	Returns the largest number from a list of numbers.
multiplyFloatList	Multiplies a list of floating point numbers (represented in a String list) and returns the product.
multiplyFloats	Multiplies one floating point number (represented as String) by another and returns the product.
multiplyIntList	Multiplies a list of integers (represented in a String list) and returns the product.
multiplyInts	Multiplies one integer (represented as a String) by another and returns the product.
randomDouble	Returns the next pseudorandom, uniformly distributed double between 0.0 and 1.0.
roundNumber	Returns a rounded number.
subtractFloats	Subtracts one floating point number (represented as a String) from another and returns the difference.
subtractInts	Subtracts one integer (represented as a String) from another and returns the difference.

addObjects

Adds one `java.lang.Number` object to another and returns the sum.

Input Parameters

num1 **java.lang.Number** Number to add. See the Usage Notes for supported subclasses.

num2 **java.lang.Number** Number to add. See the Usage Notes for supported sub-classes.

Output Parameters

value **java.lang.Number** Sum of the numeric values of *num1* and *num2*.

Usage Notes

This service accepts the following sub-classes of `java.lang.Number`: `java.lang.Byte`, `java.lang.Double`, `java.lang.Float`, `java.lang.Integer`, `java.lang.Long`, `java.lang.Short`.

This service applies the following rules for binary numeric promotion to the operands in order:

- If either operand is of type `Double`, the other is converted to `Double`.
- Otherwise, if either operand is of type `Float`, the other is converted to `Float`.
- Otherwise, if either operand is of type `Long`, the other is converted to `Long`.
- Otherwise, both operands are converted to type `Integer`.

These promotion rules mirror the Java rules for numeric promotion of numeric types.

divideObjects

Divides one `java.lang.Number` object by another ($num1/num2$) and returns the quotient.

Input Parameters

num1 **java.lang.Number** Number that is the dividend. See the Usage Notes for supported sub-classes.

num2 **java.lang.Number** Number that is the divisor. See the Usage Notes for supported sub-classes.

Output Parameters

value **java.lang.Number** Quotient of $num1 / num2$.

Usage Notes

This service accepts the following sub-classes of `java.lang.Number`: `java.lang.Byte`, `java.lang.Double`, `java.lang.Float`, `java.lang.Integer`, `java.lang.Long`, `java.lang.Short`.

This service applies the following rules for binary numeric promotion to the operands in order:

- If either operand is of type Double, the other is converted to Double.
- Otherwise, if either operand is of type Float, the other is converted to Float.
- Otherwise, if either operand is of type Long, the other is converted to Long.
- Otherwise, both operands are converted to type Integer.

These promotion rules mirror the Java rules for numeric promotion of numeric types.

min

Returns the smallest number from a list of numbers.

Input Parameters

numList **String List** List of numbers from which the smallest number is to be returned.

Output Parameters

minValue **String** Smallest number from the list of numbers.

multiplyObjects

Multiplies one `java.lang.Number` object by another and returns the product.

Input Parameters

num1 **java.lang.Number** Number to multiply. See the Usage Notes for supported sub-classes.

num2 **java.lang.Number** Number to multiply. See the Usage Notes for supported sub-classes.

Output Parameters

value **java.lang.Number** Product of *num1* and *num2* .

Usage Notes

This service accepts the following sub-classes of `java.lang.Number`: `java.lang.Byte`, `java.lang.Double`, `java.lang.Float`, `java.lang.Integer`, `java.lang.Long`, `java.lang.Short`.

This service applies the following rules for binary numeric promotion to the operands in order:

- If either operand is of type `Double`, the other is converted to `Double`.
- Otherwise, if either operand is of type `Float`, the other is converted to `Float`.
- Otherwise, if either operand is of type `Long`, the other is converted to `Long`.
- Otherwise, both operands are converted to type `Integer`.

These promotion rules mirror the Java rules for numeric promotion of numeric types.

subtractObjects

Subtracts one `java.lang.Number` object from another and returns the difference.

Input Parameters

num1 **java.lang.Number** Number. See the Usage Notes for supported sub-classes.

num2 **java.lang.Number** Number to subtract from *num1* . See the Usage Notes for supported sub-classes.

Output Parameters

value **java.lang.Number** Difference of *num1* - *num2* .

Usage Notes

This service accepts the following sub-classes of `java.lang.Number`: `java.lang.Byte`, `java.lang.Double`, `java.lang.Float`, `java.lang.Integer`, `java.lang.Long`, `java.lang.Short`.

This service applies the following rules for binary numeric promotion to the operands. The following rules are applied in order:

- If either operand is of type `Double`, the other is converted to `Double`.
- Otherwise, if either operand is of type `Float`, the other is converted to `Float`.
- Otherwise, if either operand is of type `Long`, the other is converted to `Long`.
- Otherwise, both operands are converted to type `Integer`.

These promotion rules mirror the Java rules for numeric promotion of numeric types.

toNumber

Converts a string to numeric data type.

Input Parameters

<i>num</i>	String Number (represented as a string) to be converted to numeric format.
<i>convertAs</i>	String Optional. Specifies the Java numeric data type to which the <i>num</i> parameter is to be converted. Valid values for the <i>convertAs</i> parameter are <code>java.lang.Double</code> , <code>java.lang.Float</code> , <code>java.lang.Integer</code> , <code>java.math.BigDecimal</code> , <code>java.math.BigInteger</code> , <code>java.lang.Long</code> . The default value is <code>java.lang.Double</code> .

Output Parameters

<i>num</i>	java.lang.Number Converted numeric object.
------------	---

absoluteValue

Returns the absolute value of the input number.

Input Parameters

<i>num</i>	String Number whose absolute value is to be returned.
------------	--

Output Parameters

<i>positiveNumber</i>	String Absolute value of the input number.
-----------------------	---

addFloatList

Adds a list of floating point numbers (represented in a string list) and returns the sum.

Input Parameters

numList **String List** Numbers (floating point numbers represented in a string list) to add.

Output Parameters

value **String** Sum of the numbers in *numList*. If a sum cannot be produced, *value* contains one of the following:

Value	Description
Infinity	The computation produces a positive value that overflows the representable range of a float type.
-Infinity	The computation produces a negative value that overflows the representable range of a float type.
0.0	The computation produces a value that underflows the representable range of a float type (for example, adding a number to infinity).
NaN	The computation produces a value that cannot be represented as a number (for example, any operation that uses NaN as input, such as $10.0 + \text{NaN} = \text{NaN}$).

Usage Notes

Make sure the strings that are passed to the service in *numList* are in a locale-neutral format (that is, using the pattern `-####.##`). Passing locally formatted strings may result in unexpected results. For example, calling `addFloats` in a German locale with the arguments `1,23` and `2,34` will result in the value `357`, not `3.57` or `3,57`.

addFloats

Adds one floating point number (represented as a String) to another and returns the sum.

Input Parameters

num1 **String** Number to add.

<i>num2</i>	String Number to add.
<i>precision</i>	String Optional. Number of decimal places to which the sum will be rounded. The default value is null.

Output Parameters

value **String** Sum of the numbers in *num1* and *num2*. If a sum cannot be produced, *value* contains one of the following:

<u>Value</u>	<u>Description</u>
Infinity	The computation produces a positive value that overflows the representable range of a float type.
- Infinity	The computation produces a negative value that overflows the representable range of a float type.
0.0	The computation produces a value that underflows the representable range of a float type (for example, adding a number to infinity).
NaN	The computation produces a value that cannot be represented as a number (for example, any operation that uses NaN as input, such as $10.0 + \text{NaN} = \text{NaN}$).

Usage Notes

Make sure the strings that are passed to the service in *num1* and *num2* are in a locale-neutral format (that is, using the pattern `-####.##`). Passing locally formatted strings may result in unexpected results. For example, calling `addFloats` in a German locale with the arguments `1,23` and `2,34` will result in the value `357`, not `3.57` or `3,57`.

addIntList

Adds a list of integers (represented in a String list) and returns the sum.

Input Parameters

<i>numList</i>	String List Numbers (integers represented as Strings) to add.
----------------	--

Output Parameters

value **String** Sum of the numbers in *numList* .

Usage Notes

Make sure the strings that are passed to the service in *numList* are in a locale-neutral format (that is, using the pattern -####.##). Passing locally formatted strings may result in unexpected results. For example, calling `addFloats` in a German locale with the arguments 1,23 and 2,34 will result in the value 357, not 3.57 or 3,57.

addInts

Adds one integer (represented as a String) to another and returns the sum.

Input Parameters

num1 **String** Number (integer represented as a String) to add.

num2 **String** Number (integer represented as a String) to add.

Output Parameters

value **String** Sum of *num1* and *num2* .

Usage Notes

Ensure that the result of your calculation is less than 64 bits in width (the maximum width for the long data type). If the result exceeds this limit, it will generate a data overflow.

Ensure that the strings that are passed to the service in *num1* and *num2* are in a locale-neutral format (that is, using the pattern -####.##). Passing locally formatted strings may result in unexpected results. For example, calling `addFloats` in a German locale with the arguments 1,23 and 2,34 will result in the value 357, not 3.57 or 3,57.

divideFloats

Divides one floating point number (represented as a String) by another (*num1/num2*) and returns the quotient.

Input Parameters

- num1* **String** Number (floating point number represented as a String) that is the dividend.
- num2* **String** Number (floating point number represented as a String) that is the divisor.
- precision* **String** Optional. Number of decimal places to which the quotient will be rounded. The default value is null.

Output Parameters

- value* **String** The quotient of *num1* / *num2* . If a quotient cannot be produced, *value* contains one of the following:

Value	Description
Infinity	The computation produces a positive value that overflows the representable range of a float type.
-Infinity	The computation produces a negative value that overflows the representable range of a float type.
0.0	The computation produces a value that underflows the representable range of a float type (for example, dividing a number by infinity).
NaN	The computation produces a value that cannot be represented as a number (for example, the result of an illegal operation such as dividing zero by zero or any operation that uses NaN as input, such as $10.0 + \text{NaN} = \text{NaN}$).

Usage Notes

Make sure the strings that are passed to the service in *num1* and *num2* are in a locale-neutral format (that is, using the pattern `-####.##`). Passing locally formatted strings may result in unexpected results. For example, calling `addFloats` in a German locale with the arguments `1,23` and `2,34` will result in the value `357`, not `3.57` or `3,57`.

divideInts

Divides one integer (represented as a String) by another (*num1/num2*) and returns the quotient.

Input Parameters

num1 **String** Number (integer represented as a String) that is the dividend.

num2 **String** Number (integer represented as a String) that is the divisor.

Output Parameters

value **String** The quotient of *num1 / num2*.

Usage Notes

Make sure the strings that are passed to the service in *num1* and *num2* are in a locale-neutral format (that is, using the pattern -####.##). Passing locally formatted strings may result in unexpected results. For example, calling `addFloats` in a German locale with the arguments `1,23` and `2,34` will result in the value `357`, not `3.57` or `3,57`.

max

Returns the largest number from a list of numbers.

Input Parameters

numList **String List** List of numbers from which the largest number is to be returned.

Output Parameters

maxValue **String** Largest number from the list of numbers.

multiplyFloatList

Multiplies a list of floating point numbers (represented in a String list) and returns the product.

Input Parameters

numList **String List** Numbers (floating point numbers represented as Strings) to multiply.

Output Parameters

value **String** Product of the numbers in *numlist* . If a product cannot be produced, *value* contains one of the following:

Value	Description
Infinity	The computation produces a positive value that overflows the representable range of a float type.
- Infinity	The computation produces a negative value that overflows the representable range of a float type.
0.0	The computation produces a value that underflows the representable range of a float type (for example, multiplying a number by infinity).
NaN	The computation produces a value that cannot be represented as a number (for example, the result of an illegal operation such as multiplying zero by zero or any operation that uses NaN as input, such as $10.0 + \text{NaN} = \text{NaN}$).

Usage Notes

Make sure the strings that are passed to the service in *numList* are in a locale-neutral format (that is, using the pattern `-####.##`). Passing locally formatted strings may result in unexpected results. For example, calling `addFloats` in a German locale with the arguments `1,23` and `2,34` will result in the value `357`, not `3.57` or `3,57`.

multiplyFloats

Multiplies one floating point number (represented as String) by another and returns the product.

Input Parameters

<i>num1</i>	String Number (floating point number represented as a String) to multiply.
<i>num2</i>	String Number (floating point number represented as a String) to multiply.
<i>precision</i>	String Optional. Number of decimal places to which the product will be rounded. The default value is null.

Output Parameters

value **String** Product of the numeric values of *num1* and *num2* . If a product cannot be produced, *value* contains one of the following:

<u>Value</u>	<u>Description</u>
Infinity	The computation produces a positive value that overflows the representable range of a float type.
- Infinity	The computation produces a negative value that overflows the representable range of a float type.
0.0	The computation produces a value that underflows the representable range of a float type (for example, multiplying a number by infinity).
NaN	The computation produces a value that cannot be represented as a number (for example, the result of an illegal operation such as multiplying zero by zero or any operation that uses NaN as input, such as $10.0 + \text{NaN} = \text{NaN}$).

Usage Notes

Make sure the strings that are passed to the service in *num1* and *num2* are in a locale-neutral format (that is, using the pattern -####.##). Passing locally formatted strings may result in unexpected results. For example, calling `addFloats` in a German locale with the arguments `1,23` and `2,34` will result in the value `357`, not `3.57` or `3,57`.

multiplyIntList

Multiplies a list of integers (represented in a String list) and returns the product.

Input Parameters

numList **String List** Numbers (floating point numbers represented as Strings) to multiply.

Output Parameters

value **String** Product of the numbers in *numList*.

Usage Notes

Make sure the result of your calculation is less than 64 bits in width (the maximum width for the long data type). If the result exceeds this limit, it will generate a data overflow.

Make sure the strings that are passed to the service in *numList* are in a locale-neutral format (that is, using the pattern -####.##). Passing locally formatted strings may result in unexpected results. For example, calling `addFloats` in a German locale with the arguments `1,23` and `2,34` will result in the value `357`, not `3.57` or `3,57`.

multiplyInts

Multiplies one integer (represented as a String) by another and returns the product.

Input Parameters

num1 **String** Number (integer represented as a String) to multiply.

num2 **String** Number (integer represented as a String) to multiply.

Output Parameters

value **String** Product of *num1* and *num2*.

Usage Notes

Make sure the result of your calculation is less than 64 bits in width (the maximum width for the long data type). If the result exceeds this limit, it will generate a data overflow.

Make sure the strings that are passed to the service in *num1* and *num2* are in a locale-neutral format (that is, using the pattern -####.##). Passing locally formatted strings may result in unexpected results. For example, calling `addFloats` in a German locale with the arguments `1,23` and `2,34` will result in the value `357`, not `3.57` or `3,57`.

randomDouble

Returns the next pseudorandom, uniformly distributed double between 0.0 and 1.0.

Random number generators are often referred to as pseudorandom number generators because the numbers produced tend to repeat themselves over time.

Input Parameters

None.

Output Parameters

number **String** Generated random number.

roundNumber

Returns a rounded number.

Input Parameters

num **String** Number to be rounded.

numberOfDigits **String** Specifies the number of digits to which you want to round the number.

roundingMode **String** Optional. Specifies the rounding method.

Valid values for the *roundingMode* parameter are `RoundHalfUp`, `RoundUp`, `RoundDown`, `RoundCeiling`, `RoundFloor`, `RoundHalfDown`, and `RoundHalfEven`. The default value is `RoundHalfUp`.

Output Parameters

roundedNumber **String** The rounded number.

subtractFloats

Subtracts one floating point number (represented as a `String`) from another and returns the difference.

Input Parameters

num1 **String** Number (floating point number represented as a `String`).

num2 **String** Number (floating point number represented as a `String`) to subtract from *num1*.

precision **String** Optional. Number of decimal places to which the difference will be rounded. The default value is `null`.

Output Parameters

value **String** Difference of *num1* - *num2*. If a difference cannot be produced, *value* contains one of the following:

<u>Value</u>	<u>Description</u>
<code>Infinity</code>	The computation produces a positive value that overflows the representable range of a float type.
<code>-Infinity</code>	The computation produces a negative value that overflows the representable range of a float type.
<code>0.0</code>	The computation produces a value that underflows the representable range of a float type (for example, subtracting a number from infinity).

NaN The computation produces a value that cannot be represented as a number (for example, the result of an illegal operation such as multiplying zero by zero or any operation that uses NaN as input, such as $10.0 - \text{NaN} = \text{NaN}$).

Usage Notes

Make sure the strings that are passed to the service in *num1* and *num2* are in a locale-neutral format (that is, using the pattern -####.##). Passing locally formatted strings may result in unexpected results. For example, calling `addFloats` in a German locale with the arguments `1,23` and `2,34` will result in the value `357`, not `3.57` or `3,57`.

subtractInts

Subtracts one integer (represented as a String) from another and returns the difference.

Input Parameters

num1 **String** Number (integer represented as a String).

num2 **String** Number (integer represented as a String) to subtract from *num1*.

Output Parameters

value **String** Difference of *num1* - *num2*.

Usage Notes

Make sure the result of your calculation is less than 64 bits in width (the maximum width for the long data type). If the result exceeds this limit, it will generate a data overflow.

Make sure the strings that are passed to the service in *num1* and *num2* are in a locale-neutral format (that is, using the pattern -####.##). Passing locally formatted strings may result in unexpected results. For example, calling `addFloats` in a German locale with the arguments `1,23` and `2,34` will result in the value `357`, not `3.57` or `3,57`.

Storage

Use **Storage** services to insert, retrieve, update, and remove entries from a data store.

When using the storage services, keep in mind that the short-term store is not intended to be used as a general-purpose storage engine. Rather, it is primarily provided to

support shared storage of application resources and transient data in Integration Cloud. It is recommended not to use the short-term store to process high volumes, large data records, or to permanently archive records.

Note: User specific data which may be considered as personal data will be stored and retained till the retention period defined in Execution Results.

Note: These services are a tool for maintaining state information in the short-term store. It is up to the developer of the Integration to make sure that the Integration keeps track of its state and correctly handles restarts.

Locking Considerations

The following sections describe in general how the storage services handle locking requests.

Entry Locking

To maintain data integrity, the short-term store uses locking to ensure that multiple threads do not modify the same entry at the same time. For insertions and removals, the short-term store sets and releases the lock. For updates, the client must set and release the lock. Using locking improperly, that is, creating a lock but not releasing it, can cause deadlocks in the short-term store.

The following guidelines can help you avoid short-term store deadlocks:

- Release locks in the thread through which they were set. In other words, you cannot set a lock in one thread and release it in another. The safest way to do this is to release each lock in the Integration that acquired it.
- Unlock entries before the Integration completes. Entries remain locked until released using a put or an explicit unlock. To accomplish this, always pair a call to get or lock with a call to put or unlock so that every lock is followed by an unlock. In addition, use a try-catch pattern in your Integration so that an exception does not prevent the Integration from continuing and releasing the lock.

Data Store Locking

When a storage service locks an entry, the service also implicitly locks the data store in which the entry resides. This behavior prevents another thread from deleting the entire data store and the entries it contains while your thread is working with the entry. When the locked entry is unlocked, the implicit lock on the data store is also released.

Be careful when explicitly unlocking data stores. Consider the following example:

1. User_A locks an item. This creates two locks: an explicit lock on the entry, and an implicit lock on the data store.
2. User_A later unlocks the data store explicitly while still holding the lock on the entry.
3. User_B locks, then deletes the data store, including the entry locked by User_A in the first step.

When User_A explicitly unlocked the data store in step 2, User_B was able to delete the entry the User_A was working with.

Automatic Promotion to Exclusive Lock


If a storage service tries to acquire an exclusive lock on an object, but finds a shared lock from the same thread already in place on the object, the service will try to promote the lock to an exclusive lock.

If a storage service that requires an exclusive lock encounters a shared or exclusive lock held by another thread, it will wait until the object becomes available. If the object remains locked for the period specified by the *waitlength* parameter passed by the service, the service will fail.

Sample Integration for Checkpoint Restart

The following diagram shows how to create checkpoint restarts into your Integrations. It explains the logic of an Integration and shows where the various storage services are used to achieve checkpoint restarts.

Logic to achieve checkpoint restart



The following **Storage** services are available:

Element	Package and Description
add	Inserts a new entry into a data store.
deleteStore	Deletes a data store and all its contents. Any data in the data store is deleted. If the data store does not exist, the service takes no action.
get	Retrieves a value from a data store and locks the entry and the data store on behalf of the thread that invoked the service.
keys	Obtains a list of all the keys in a data store.
lock	Locks an entry and/or data store on behalf of the thread invoking this service.
put	Inserts or updates an entry in a data store. If the key does not exist in the data store, the entry is inserted.
remove	Removes an entry from a data store.
unlock	Unlocks an entry or a data store.

add

Inserts a new entry into a data store.

If the key already exists in the data store, the service does nothing.

Input Parameters

<i>storeName</i>	String Name of the data store in which to insert the entry.
<i>key</i>	String Key under which the entry is to be inserted.
<i>value</i>	Document Value to be inserted.

Output Parameters

<i>result</i>	String Flag indicating whether the entry was successfully added. A value of: <ul style="list-style-type: none">■ <code>true</code> indicates that the new entry was inserted successfully.■ <code>false</code> indicates that the entry was not inserted (usually because an entry for <i>key</i> already exists).
<i>error</i>	String Error message generated while inserting the new entry into the data store.

deleteStore

Deletes a data store and all its contents. Any data in the data store is deleted. If the data store does not exist, the service takes no action.

Input Parameters

<i>storeName</i>	String Name of the data store to delete.
<i>waitLength</i>	String Optional. Length of time, in milliseconds, that you want to wait for this data store to become available for deletion if it is already locked by another thread.

Output Parameters

<i>count</i>	String Number of data store entries that were deleted. If the store does not exist, this value is 0.
--------------	---

Usage Notes

This service obtains an exclusive lock on the data store, but no locks on the individual entries in the data store. If this service finds a shared lock from the same thread on the data store, the service will automatically promote the lock to an exclusive lock. The exclusive lock prevents other threads from acquiring locks on the data store or entries within the data store during the delete operation.

get

Retrieves a value from a data store and locks the entry and the data store on behalf of the thread that invoked the service.

Important: This service does not automatically release the lock on the data store or entry after performing the get operation, so you need to ensure that the lock is released by calling the put or unlock services. If you do not release the lock, Integration Cloud will release the lock at the end of the Integration execution.

Input Parameters

<i>storeName</i>	String Name of the data store from which you want to retrieve the entry.
<i>key</i>	String Key of the entry whose value you want to retrieve.
<i>waitLength</i>	String Optional. Length of time, in milliseconds, that you want to wait for this entry to become available if it is already locked by another thread.
<i>lockMode</i>	String Optional. Type of lock you want to place on the entry. Set to: <ul style="list-style-type: none">■ Exclusive to prevent other threads from reading or updating the entry while you are using it. The service also obtains a shared lock on the data store. An exclusive lock on an entry allows you to modify the entry.■ Read is obsolete. If this value is specified, the service obtains a shared lock.■ Share to prevent other threads from obtaining an exclusive lock on the entry. The service also obtains a shared lock on the data store. A shared lock on an entry allows you to read, but not modify, the entry. This is the default.

Output Parameters

<i>value</i>	Document Retrieved entry. If the requested entry does not exist, the value of this parameter is null.
--------------	--

Usage Notes

If you request an exclusive lock and the service finds a shared lock from the same thread on the entry, the service will automatically promote the shared lock on the entry to an exclusive lock.

When this service locks an entry, it also acquires a shared lock on the associated data store to prevent another thread from deleting the data store, and the entries it contains, while your thread has the entry locked.

When storing and retrieving the flow state in the short-term store for checkpoint restart purposes, ensure that the value of *key* is unique to the transaction.

keys

Obtains a list of all the keys in a data store.

Input Parameters

storeName **String** Name of the data store from which you want to obtain a list of keys.

Output Parameters

keys **String List** Keys for the data store specified in *storeName* .

lock

Locks an entry and/or data store on behalf of the thread invoking this service.

Important: When you lock an entry or data store using this service, you must release the lock by using a put or an explicit unlock. If you do not release the lock, Integration Cloud will release the lock at the end of the Integration execution.

Important: Be careful when releasing locks with the unlock service. If you release a lock on a data store, another thread can obtain a lock on the data store and delete it, and the entries it contains, even if your thread still has locks on one or more of the entries.

Input Parameters

<i>storeName</i>	String Name of the data store containing the entry.
<i>key</i>	String Optional. Key of the entry that you want to lock. If <i>key</i> is not supplied and you request: <ul style="list-style-type: none">■ A shared lock, the service obtains a shared lock on the data store, allowing other threads to read and modify entries, but not to delete them.■ An exclusive lock, the service obtains an exclusive lock on the data store, preventing other threads from locking the data store and the entries, thereby preventing those threads from reading, modifying, or deleting the entries or the data store. If both <i>storeName</i> and <i>key</i> are specified and you request: <ul style="list-style-type: none">■ A shared lock, the service obtains a shared lock on the data store and the entry.■ An exclusive lock, the service obtains a shared lock on the data store and an exclusive lock on the entry.
<i>waitLength</i>	String Optional. Length of time, in milliseconds, that you want to wait for this entry to become available if it is already locked by another thread.
<i>lockMode</i>	String Optional. Type of lock you want to place on the entry or data store. Set to: <ul style="list-style-type: none">■ Exclusive to prevent other threads from obtaining a lock on the data store or entry. An exclusive lock on an entry allows you to modify the entry, and prevents other threads from reading or modifying the entry. An exclusive lock on a data store also locks the entries in the data store. In addition, an exclusive lock on a data store allows you to delete the data store.■ Read is obsolete. If this value is specified, the service obtains a shared lock.■ Share to prevent other threads from obtaining an exclusive lock on an entry or a data store. A shared lock on an entry allows you to read, but not modify, the entry. A

shared lock on a data store prevents another thread from deleting the data store. This is the default.

Output Parameters

None.

Usage Notes

If you have not specified a *key*, and your Integration does not invoke `put` or `unlock`, or your Integration throws an exception before invoking `put` or `unlock`, the entire data store remains locked.

If the key does not exist in the data store at the time your Integration executes, the lock service inserts the key with an empty value and takes the lock on the entry.

If you request an exclusive lock on an entry, the service obtains an exclusive lock on the entry and a shared lock on the data store. If this service finds a shared lock from the same thread on the entry, the service will automatically promote the shared lock on the entry to an exclusive lock.

If you request a shared lock on an entry, the service obtains a shared lock on the entry and a shared lock on the data store.

If you request a shared lock on an entry or a data store and this service finds an exclusive lock from the same thread, the existing exclusive lock will be reused. The exclusive lock will not be demoted to a shared lock.

If you request an exclusive lock on a data store, and this service finds a shared lock from the same thread on the data store, the service will automatically promote the shared lock on the data store to an exclusive lock.

put

Inserts or updates an entry in a data store. If the key does not exist in the data store, the entry is inserted.

If the requested entry is not currently locked by the thread that invoked this service, the `put` service will automatically attempt to lock the entry for the duration of the `put` operation.

The service obtains an exclusive lock on the entry and a shared lock on the data store. If the service finds a shared lock from the same thread on the entry, the service will automatically promote the shared lock to an exclusive lock.

This service releases the lock when the `put` operation has completed.

Input Parameters

<i>storeName</i>	String Name of the data store into which you want to insert or update the entry.
<i>value</i>	Document Value to be inserted or updated.
<i>waitLength</i>	String Optional. Length of time, in milliseconds, that you want to wait for this entry to become available if it is already locked by another thread. If the wait length expires before a lock is obtained, the service fails and throws an exception. This parameter is used only when your service did not explicitly lock the entry beforehand.
<i>key</i>	String Key where you want to insert or update the entry.

Output Parameters

<i>error</i>	String Error message generated while inserting the new entry into the data store.
--------------	--

Usage Notes

When storing and retrieving the flow state in the short-term store for checkpoint restart purposes, ensure that the value of *key* is unique to the transaction.

remove

Removes an entry from a data store. This service obtains an exclusive lock on the entry and a shared lock on the data store.

Input Parameters

<i>storeName</i>	String Name of the data store from which to remove an entry.
<i>key</i>	String Key of the entry that you want to remove.
<i>waitLength</i>	String Optional. Length of time, in milliseconds, that you want to wait for this entry to become available for deletion if it is already locked by another thread.

Output Parameters

<i>result</i>	String Flag indicating whether the entry was successfully removed. A value of: <ul style="list-style-type: none">■ <code>true</code> indicates that the entry was removed successfully.■ <code>false</code> indicates that the entry was not removed (usually because an entry for key does not exist).
---------------	---

unlock

Unlocks an entry or a data store.

When an Integration retrieves an entry using the get service, the entry is locked to prevent modification by other users before the Integration completes. The entry remains locked until the lock owner invokes a put service. To unlock a service without using the put service, use the unlock service.

In addition, if an Integration uses the lock service to lock an entry or data store, you must use the unlock or put service to release the lock.

Important: Be careful when releasing locks with this service. If you release a lock on a data store, another thread can obtain a lock on the data store and delete it, and the entries it contains, even if the original thread still has locks on one or more of the entries.

Input Parameters

<i>storeName</i>	String Name of the data store in which to unlock an entry.
<i>key</i>	String Optional. Key of the entry that you want to unlock. If <i>key</i> is not supplied, the lock will be removed from the data store specified in <i>storeName</i> , but any locks on entries in the data store will remain.

Output Parameters

None.

String

Use **String** services to perform string manipulation and substitution operations.

The following **String** services are available:

Service	Description
HTMLDecode	Replaces HTML character entities with native characters.
HTMLEncode	Replaces HTML-sensitive characters with equivalent HTML character entities.
base64Decode	Decodes a Base-64 encoded string into a sequence of bytes.
base64Encode	Converts a sequence of bytes into a Base64-encoded String.
bytesToString	Converts a sequence of bytes to a String.
concat	Concatenates two strings.
indexOf	Returns the index of the first occurrence of a sequence of characters in a string.
length	Returns the length of a string.
lookupDictionary	Looks up a given key in a hash table and returns the string to which that key is mapped.
makeString	Builds a single string by concatenating the elements of a String List.
messageFormat	Formats an array of strings into a given message pattern.
numericFormat	Formats a number into a given numeric pattern.
objectToString	Converts an object to string representation using the Java toString() method of the object.
padLeft	Pads a string to a specified length by adding pad characters to the beginning of the string.
padRight	Pads a string to a specified length by adding pad characters to the end of the string.

Service	Description
replace	Replaces all occurrences of a specified substring with a substitute string.
stringToBytes	Converts a string to a byte array.
substring	Returns a substring of a given string.
tokenize	Tokenizes a string using specified delimiter characters and generates a String List from the resulting tokens.
toLowerCase	Converts all characters in a given string to lowercase.
toUpperCase	Converts all characters in a given string to uppercase.
trim	Trims leading and trailing white space from a given string.
URLDecode	Decodes a URL-encoded string.
URLEncode	URL-encodes a string.
fuzzyMatch	A given string is not exactly matched against a set of strings. If the match is above <code>similarityThreshold</code> , it returns the <code>matchedValue</code> . If more than one string has not exactly matched, then the first matched string is returned.
isNumber	Determines whether the contents of a string can be converted to a float value.
isAlphanumeric	Determines whether a string consists entirely of alphanumeric characters (in the ranges A–Z, a–z, or 0–9).
isNullOrBlank	Checks a string for a null or a blank value.
isDate	Determines whether a string follows a specified date pattern.

Service	Description
substitutePipelineVariables	Replaces a pipeline variable with its corresponding value.
compareStrings	Performs a case-sensitive comparison of two strings, and indicates whether the strings are identical.

HTMLDecode

Replaces HTML character entities with native characters.

Specifically, the service:

Replaces this HTML character entity...	With...
>	>
<	<
&	&
"	"

Input Parameters

inString **String** An HTML-encoded String.

Output Parameters

value **String** Result from decoding the contents of *inString*. Any HTML character entities that existed in *inString* will appear as native characters in *value*.

HTMLEncode

Replaces HTML-sensitive characters with equivalent HTML character entities.

Specifically, this service:

<u>Replaces this native language character...</u>	<u>With...</u>
>	>
<	<
&	&
"	"
'	'

These translations are useful when displaying text in an HTML context.

Input Parameters

inString **String** The character you want to encode in HTML.

Output Parameters

value **String** Result from encoding the contents of *inString*. Any HTML-sensitive characters that existed in *inString*, for example, > or &, will appear as the equivalent HTML character entities in *value*.

base64Decode

Decodes a Base-64 encoded string into a sequence of bytes.

Input Parameters

string **String** A Base64-encoded String to decode into bytes.

Output Parameters

value **byte[]** The sequence of bytes decoded from the Base64-encoded String.

encoding **String** Optional. Specifies the encoding method. Default value is ASCII.

base64Encode

Converts a sequence of bytes into a Base64-encoded String.

Input Parameters

bytes **byte[]** Sequence of bytes to encode into a Base64-encoded String.

useNewLine **String** Optional. Flag indicating whether to retain or remove the line breaks. Set to:

- `true` to retain the line breaks. This is the default.
- `false` to remove the line breaks.

encoding **String** Optional. Specifies the encoding method. Default value is ASCII.

Output Parameters

value **String** Base64-encoded String encoded from the sequence of bytes.

Usage Notes

By default, the `base64Encode` service inserts line breaks after 76 characters of data, which is not the canonical lexical form expected by implementations such as MTOM. You can use the `useNewLine` parameter to remove the line breaks.

bytesToString

Converts a sequence of bytes to a String.

Input Parameters

bytes **byte[]** Sequence of bytes to convert to a String.

<i>encoding</i>	String Optional. Name of a registered, IANA character set (for example, <code>ISO-8859-1</code>). If you specify an unsupported encoding, the system throws an exception. To use the default encoding, set <i>encoding</i> to <code>autoDetect</code> .
<i>ignoreBOMChars</i>	String Optional. Flag indicating whether or not the byte order mark (BOM) characters in the input sequence of bytes are removed before converting the byte array to string. Set to: <ul style="list-style-type: none">■ <code>true</code> to remove the byte order mark (BOM) characters before converting the input sequence of bytes to string, if the byte array contains BOM characters.■ <code>false</code> to include the byte order mark (BOM) characters while converting the input sequence of bytes to string. The default is <code>false</code>.

Output Parameters

string **String** String representation of the contents of *bytes* .

concat

Concatenates two strings.

Input Parameters

inString1 **String** String to which you want to concatenate another string.

inString2 **String** String to concatenate to *inString1* .

Output Parameters

value **String** Result of concatenating *inString1* with *inString2* (*inString1* + *inString2*).

indexOf

Returns the index of the first occurrence of a sequence of characters in a string.

Input Parameters

<i>inString</i>	String String in which you want to locate a sequence of characters.
<i>subString</i>	String Sequence of characters to locate.
<i>fromIndex</i>	String Optional. Index of <i>inString</i> from which to start the search. If no value is specified, this parameter contains 0 to indicate the beginning of the string.

Output Parameters

<i>value</i>	String Index of the first occurrence of <i>subString</i> in <i>inString</i> . If no occurrence is found, this parameter contains -1.
--------------	---

length

Returns the length of a string.

Input Parameters

<i>inString</i>	String String whose length you want to discover.
-----------------	---

Output Parameters

<i>value</i>	String The number of characters in <i>inString</i> .
--------------	---

lookupDictionary

Looks up a given key in a hash table and returns the string to which that key is mapped.

Input Parameters

<i>hashtable</i>	java.util.Hashtable Hash table that uses String objects for keys and values.
<i>key</i>	String Key in <i>hashtable</i> whose value you want to retrieve.

Note: The key is case sensitive.

Output Parameters

value **String** Value of the string to which *key* is mapped. If the requested key in *hashtable* is null or if *key* is not mapped to any value in *hashtable*, the service returns null.

makeString

Builds a single string by concatenating the elements of a String List.

Input Parameters

elementList **String List** Strings to concatenate.

separator **String** String to insert between each non-null element in *elementList*.

Output Parameters

value **String** Result from concatenating the strings in *elementList*. Strings are separated by the characters specified in *separator*.

messageFormat

Formats an array of strings into a given message pattern.

Input Parameters

pattern **String** Message that includes "placeholders" where elements from *argumentList* are to be inserted. The message can contain any sequence of characters. Use the {*n*} placeholder to insert elements from *argumentList*, where *n* is the index of the element that you want to insert. For example, the following pattern string inserts elements 0 and 1 into the message:

```
Test results: {0} items passed, {1} items failed.
```

Note: Do not use any characters except digits for *n*.

argumentList **String List** Optional. List of strings to use to populate *pattern*. If *argumentList* is not supplied, the service will not replace placeholders in *pattern* with actual values.

Output Parameters

value **String** Result from substituting *argumentList* into *pattern*. If *pattern* is empty or null, this parameter is null.

numericFormat

Formats a number into a given numeric pattern.

Input Parameters

num **String** The number to format.

pattern **String** A pattern string that describes the way in which *num* is to be formatted:

<u>This symbol...</u>	<u>Indicates...</u>
0	A digit.
#	A digit. Leading zeroes will not be shown.
.	A placeholder for a decimal separator.
,	A placeholder for a grouping separator.
;	A separation in format.
-	The default negative prefix.
%	That <i>num</i> will be multiplied by 100 and shown as a percentage.
x	Any character used as a prefix or suffix (for example, A, \$).

' That special characters are to be used as literals in a prefix or suffix. Enclose the special characters within " (for example, '#').

The following are examples of pattern strings:

Pattern	Description
#,###	Use commas to separate into groups of three digits. The pound sign denotes a digit and the comma is a placeholder for the grouping separator.
#,####	Use commas to separate into groups of four digits.
\$.00	Show digits before the decimal point as needed and exactly two digits after the decimal point. Prefix with the \$ character.
'#'#.0	Show digits before the decimal point as needed and exactly one digit after the decimal point. Prefix with the # character. The first character in a pattern is the dollar sign (\$). The pound sign denotes a digit and the period is a placeholder for decimal separator.

Output Parameters

value **String***num* formatted according to *pattern*. If *pattern* is an empty (not null) string, the default pattern of comma separators is used and the number of digits after the decimal point remains unchanged.

objectToString

Converts an object to string representation using the Java `toString()` method of the object.

Input Parameters

object **Object** The object to be converted to string representation.

Output Parameters

string **String** String representation of the input object converted using the Java `toString()` method of the object.

padLeft

Pads a string to a specified length by adding pad characters to the beginning of the string.

Input Parameters

inString **String** String that you want to pad.

padString **String** Characters to use to pad *inString* .

length **String** Total length of the resulting string, including pad characters.

Output Parameters

value **String** Contents of *inString* preceded by as many pad characters as needed so that the total length of the string equals *length* .

Usage Notes

If *padString* is longer than one character and does not fit exactly into the resulting string, the beginning of *padString* is aligned with the beginning of the resulting string. For example, suppose *inString* equals `shipped` and *padString* equals `x9y`.

If <i>length</i> equals...	Then <i>value</i> will contain...
-----------------------------------	--

7	<code>shipped</code>
---	----------------------

10	<code>x9yshipped</code>
----	-------------------------

If <i>length</i> equals...	Then <i>value</i> will contain...
12	x9x9yshipped

If *inString* is longer than *length* characters, only the last *length* characters from *inString* are returned. For example, if *inString* equals acct1234 and *length* equals 4, *value* will contain 1234.

padRight

Pads a string to a specified length by adding pad characters to the end of the string.

Input Parameters

<i>inString</i>	String String that you want to pad.
<i>padString</i>	String Characters to use to pad <i>inString</i> .
<i>length</i>	String Total length of the resulting string, including pad characters.

Output Parameters

<i>value</i>	String Contents of <i>inString</i> followed by as many pad characters as needed so that the total length of the string equals <i>length</i> .
--------------	--

Usage Notes

If *padString* is longer than one character and does not fit exactly into the resulting string, the end of *padString* is aligned with the end of the resulting string. For example, suppose *inString* equals shipped and *padString* equals x9y.

If <i>length</i> equals...	Then <i>value</i> will contain...
7	shipped
10	shippedx9y
12	shippedx9y9y

If *inString* is longer than *length* characters, only the first *length* characters from *inString* are returned. For example, if *inString* equals `1234acct` and *length* equals `4`, value will contain `1234`.

replace

Replaces all occurrences of a specified substring with a substitute string.

Input Parameters

<i>inString</i>	String String containing the substring to replace.
<i>searchString</i>	String Substring to replace within <i>inString</i> .
<i>replaceString</i>	String Character sequence that will replace <i>searchString</i> . If this parameter is null or empty, the service removes all occurrences of <i>searchString</i> from <i>inString</i> .
<i>useRegex</i>	String Optional. Flag indicating whether <i>searchString</i> is a regular expression. When regular expressions are used to specify a search string, <i>replaceString</i> may also contain interpolation fields (for example, "\$1") that match parenthetical subexpressions in <i>searchString</i> . Set to: <ul style="list-style-type: none">■ <code>true</code> to indicate that <i>searchString</i> is a regular expression.■ <code>false</code> to indicate that <i>searchString</i> is not a regular expression. This is the default.

Output Parameters

<i>value</i>	String Contents of <i>inString</i> with replacements made.
--------------	---

stringToBytes

Converts a string to a byte array.

Input Parameters

<i>string</i>	String String to convert to a <code>byte[]</code> .
---------------	--

encoding **String** Optional. Name of a registered, IANA character set that specifies the encoding to use when converting the String to an array of bytes (for example: ISO-8859-1).

To use the default encoding, set this value to `autoDetect`. If you specify an unsupported encoding, an exception will be thrown.

Output Parameters

bytes **byte[]** Contents of *string* represented as a `byte[]`.

substring

Returns a substring of a given string.

Input Parameters

inString **String** String from which to extract a substring.

beginIndex **String** Beginning index of the substring to extract (inclusive).

endIndex **String** Ending index of the substring to extract (exclusive). If this parameter is null or empty, the substring will extend to the end of *inString*.

Output Parameters

value **String** Substring from *beginIndex* and extending to the character at *endIndex* - 1.

tokenize

Tokenizes a string using specified delimiter characters and generates a String List from the resulting tokens.

This service does not return delimiters as tokens.

Input Parameters

<i>inString</i>	String String you want to tokenize, that is, break into delimited chunks.
<i>delim</i>	String Delimiter characters. If null or empty, the service uses the default delimiters <code>\t\n\r</code> , where t, n, and r represent the white space characters tab, new line, and carriage return.

Output Parameters

<i>valueList</i>	String List Strings containing the tokens extracted from <i>inString</i> .
------------------	---

toLower

Converts all characters in a given string to lowercase.

Input Parameters

<i>inString</i>	String String to convert.
<i>language</i>	String Optional. Lowercase, two-letter ISO-639 code. If this parameter is null, the system default is used.
<i>country</i>	String Optional. Uppercase, two-letter ISO-3166 code. If this parameter is null, the system default is used.
<i>variant</i>	String Optional. Vendor and browser-specific code. If null, this parameter is ignored.

Output Parameters

<i>value</i>	String Contents of <i>inString</i> , with all uppercase characters converted to lowercase.
--------------	---

toUpper

Converts all characters in a given string to uppercase.

Input Parameters

<i>inString</i>	String String to convert.
<i>language</i>	String Optional. Lowercase, two-letter ISO-639 code. If this parameter is null, the system default is used.
<i>country</i>	String Optional. Uppercase, two-letter ISO-3166 code. If this parameter is null, the system default is used.
<i>variant</i>	String Optional. Vendor and browser-specific code. If null, this parameter is ignored.

Output Parameters

<i>value</i>	String Contents of <i>inString</i> , with all lowercase characters converted to uppercase.
--------------	---

trim

Trims leading and trailing white space from a given string.

Input Parameters

<i>inString</i>	String String to trim.
-----------------	-------------------------------

Output Parameters

<i>value</i>	String Contents of <i>inString</i> with white space trimmed from both ends.
--------------	--

URLDecode

Decodes a URL-encoded string.

Input Parameters

<i>inString</i>	String URL-encoded string to decode.
-----------------	---

Output Parameters

value **String** Result from decoding *inString*. If *inString* contains plus (+) signs, they will appear in *value* as spaces. If *inString* contains *%hex* encoded characters, they will appear in *value* as the appropriate native character.

URLEncode

URL-encodes a string.

Encodes characters the same way that data posted from a WWW form is encoded, that is, the `application/x-www-form-urlencoded` MIME type.

Input Parameters

inString **String** String to URL-encode.

Output Parameters

value **String** Result from URL-encoding *inString*. If *inString* contains non-alphanumeric characters (except `[-_.*@]`), they will appear in *value* as their URL-encoded equivalents (`%` followed by a two-digit hex code). If *inString* contains spaces, they will appear in *value* as plus (+) signs.

fuzzyMatch

A given string is not exactly matched against a set of strings. If the match is above *similarityThreshold*, it returns the *matchedValue*. If more than one string has not exactly matched, then the first matched string is returned.

Input Parameters

inString **String (Required)** Text to be matched. Text should not be empty or null.

matchData **String [] (Required)** Array of strings, which are used for matching. If the string array value is either empty or null, it is not used for matching.

<i>similarityThreshold</i>	String (Optional) If the inexact match score is above the given threshold, then service output contains the <code>matchedValue</code> parameter. Default value is 0.65. Valid values should be between 0.0 and 1.0. Value 0.0 represents no match and value 1.0 represents an exact match.
<i>algorithm</i>	String (Optional) The algorithm used for an inexact match. Default value is Levenshtein. Supported algorithms are Levenshtein and JaroWinkler.

Output Parameters

<i>matchedValue</i>	String (Optional) If the inexact match is above <i>similarityThreshold</i> , then the returned value contains the matched string.
<i>similarity</i>	String (Optional) If the inexact match is above <i>similarityThreshold</i> , then it contains a similarity score. It provides the measure of how close the match is. The returned value can be between 0.0 and 1.0. Value 0.0 represents no match and value 1.0 represents an exact match.

Usage Notes

Search the web for more information about Levenshtein and JaroWinkler algorithms.

isNumber

Determines whether the contents of a string can be converted to a float value.

Input Parameters

<i>inString</i>	String Optional. String to be checked for conversion to float.
-----------------	---

Output Parameters

<i>isNumber</i>	String Indicates whether or not <i>inString</i> can be converted to a float value. <ul style="list-style-type: none"> ■ <code>true</code> indicates that <i>inString</i> can be converted to a float value.
-----------------	---

- `false` indicates that *inString* cannot be converted to a float value.

The service returns `false` if *inString* is not specified.

isAlphanumeric

Determines whether a string consists entirely of alphanumeric characters (in the ranges A–Z, a–z, or 0–9).

Input Parameters

inString **String** Optional. String to be checked for alphanumeric characters.

Output Parameters

isAlphanumeric **String** Indicates whether or not all the characters in *inString* are alphanumeric.

- `true` indicates that all the characters in *inString* are alphanumeric.
- `false` indicates that *not all* the characters in *inString* are alphanumeric.

The service returns `false` if *inString* is not specified.

isNullOrBlank

Checks a string for a null or a blank value.

Input Parameters

inString **String** Optional. String to be checked for a null or a blank value.

Output Parameters

isNullOrBlank **String** Indicates whether or not *inString* has a null or a blank value.

- `true` indicates that *inString* has either a null or a blank value.
- `false` indicates that *inString* contains a value that is not null.

Note: If *inString* is not specified, the service considers the string to be blank and returns `true`.

isDate

Determines whether a string follows a specified date pattern.

Input Parameters

<i>inString</i>	String Optional. String to be checked for adherence to the specified date <i>pattern</i> .
<i>pattern</i>	<p>String Date format for specifying the <i>inString</i> parameter (for example, yyyyMMdd HH:mm:ss.SSS).</p> <p>For more information about the pattern strings that can be specified for the date, see the “Pattern String Symbols” section.</p>

Output Parameters

<i>isDate</i>	<p>String Indicates whether or not <i>inString</i> follows the specified date pattern.</p> <ul style="list-style-type: none"> ■ <code>true</code> indicates that <i>inString</i> follows the specified date pattern. ■ <code>false</code> indicates that <i>inString</i> does not follow the specified date pattern. <p>The service returns <code>false</code> if <i>inString</i> is not specified.</p>
---------------	--

Usage Notes

The service returns an error if both *inString* and *pattern* are not specified.

You can specify any random string (for example, 111212) as both *inString* and *pattern*. The service returns `true` if the same user-defined string is specified as both *inString* and *pattern*. This is because the `java.text.SimpleDateFormat` class parses the user-defined input string and pattern to a valid date when the particular input values are identical.

substitutePipelineVariables

Replaces a pipeline variable with its corresponding value.

Input Parameters

inString **String** Optional. String containing the pipeline variable to replace. Specify the name of the pipeline variable between the % symbols (for example, %phone%).

Output Parameters

value **String** Contents of *inString* with the pipeline variable replaced.

Usage Notes

The service returns an error if *inString* is not specified.

If *inString* does not contain any variable between the % symbols, or contains a value other than the pipeline variable between the % symbols, the service does not perform any variable substitution from the pipeline.

If you want to include the % symbol in the output, you can specify it as \% in *inString*. To specify the value of the pipeline variable as a percentage in the output, append \% after the variable name in *inString*. For example, suppose a pipeline variable *revenueIncreasePercent* has a value of 100.

If <i>inString</i> equals...	Then <i>value</i> will contain...
%revenueIncreasePercent%\%	100%

The service cannot be used for substitution of global variables.

compareStrings

Performs a case-sensitive comparison of two strings and indicates whether the strings are identical.

Input Parameters

inString1 **String** Optional. String to compare against *inString2*. This input variable can be null.

inString2 **String** Optional. String to compare against *inString1*. This input variable can be null.

Output Parameters

isEqual **String** Indicates whether or not *inString1* and *inString2* are identical.

- `true` indicates that *inString1* and *inString2* are identical.
- `false` indicates that *inString1* and *inString2* are not identical.

Note: If both *inString1* and *inString2* are null, the service considers the strings to be identical and returns `true`.

Flow

Use **Flow** services to perform utility-type tasks.

The following **Flow** services are available:

Service	Description
clearPipeline	Removes all fields from the pipeline. You may optionally specify fields that should not be cleared by this service.
getLastError	Obtains detailed information about the last error that was trapped within an Integration.
getSessionInfo	Obtains detailed information about the current logged-in user session. Also provides the current Integration name and the execution result reference identifier.
getHTTPRequest	Gets information about the HTTP request, received by Integration Cloud.
setHTTPResponse	Sets the HTTP response information to be returned by Integration Cloud.
countProcessedDocuments	Counts the number of documents processed by an Integration. Details about the processed

Service	Description
	documents can be viewed in the Execution Results screen.
logCustomMessage	Logs a message, which can be viewed in the Execution Results screen.
sleep	Causes the currently executing Integration to pause for the specified number of seconds.

clearPipeline

Removes all fields from the pipeline. You may optionally specify fields that should not be cleared by this service.

Input Parameters

preserve **String List** Optional. Field names that should not be cleared from the pipeline.

Output Parameters

None

getLastError

Obtains detailed information about the last error that was trapped within an Integration.

Input Parameters

None

Output Parameters

lastError **Document**. Information about the last error, which contains details of the time, error, user, block, and call stack information.

<u>Key</u>	<u>Description</u>
time	String. Date and time the event occurred, in the format <i>yyyy/MM/dd HH:mm:ss.SSS</i>
error	String. Optional. Error message of the exception.
localizedError	String. Optional. Error message in the language that corresponds to the server locale.
user	String. User who executed the Integration.
block	Document. Contains the following fields:

<u>Key</u>	<u>Description</u>
name	String. Integration, Operation, or Service name.
type	String. Application, Integration, or Service.
details	String. Optional. Account and Application name if the Block Type is "Application".
callStack	Document List. The call stack information describing where the error occurred including details of the block. Each document represents a block on the call stack. The first document in the list represents the block that threw the error and the last document in the list represents the top level block. It contains the following fields:

<u>Key</u>	<u>Description</u>
name	String. Integration, Operation or Service name.

<code>type</code>	String. Application, Integration, or Service.
<code>details</code>	String. Optional. Account and Application name if the Block Type is "Application".

Usage Notes

You can use this service in the *catch* section of the *try-catch* block. Each execution of an Integration or a service (whether the Integration or the service succeeds or fails) updates the value returned by `getLastError`. Consequently, `getLastError` itself resets the value of `lastError`. Therefore, if the results of `getLastError` will be used as input to subsequent Integrations, map the value of `lastError` to a variable in the pipeline.

If a map has multiple transformers, then a subsequent call to `getLastError` will return the error associated with the last failed transformer in the map, even if it is followed by successful transformers.

getSessionInfo

Obtains detailed information about the current logged-in user session. Also provides the current Integration execution result reference identifier.

Input Parameters

None

Output Parameters

\$session **Document** Returns information about the current logged-in user session. Also provides the current Integration name and the execution result reference identifier.

<u>Key</u>	<u>Description</u>
<i>tenantId</i>	String Tenant Identifier.
<i>stageId</i>	String The stage ID where the current integration resides.
<i>user</i>	Document Returns user details.
<u>Key</u>	<u>Description</u>

<i>name</i>	String Name of the user who is executing the service.
<i>integrationName</i>	String The name of the Integration. Note If Integration A has a referenced Integration B, and if the <code>getSessionInfo</code> service is called in Integration B, then <code>integrationName</code> will be A but if Integration B is executed independently, then <code>integrationName</code> will be B.
<i>executionResultReference</i>	String Returns the current Integration execution result reference identifier. For example, you can pass the identifier to an on-premises operation and trace the Integration execution.

getHTTPRequest

Gets information about the HTTP request, received by Integration Cloud.

Parameters

<i>headers</i>	Document Contains the header fields from the HTTP request.
<i>requestURL</i>	String URL used by the client to invoke the service.
<i>method</i>	String HTTP method used by the client to request the top-level service. Possible values are GET, PUT, POST, PATCH, and DELETE.

setHTTPResponse

Sets the HTTP response information to be returned by Integration Cloud.

Parameters

<i>headers</i>	Document Optional. Contains the header fields to be returned in the HTTP response.
<i>responseCode</i>	String Optional. HTTP status code to be returned to the client. The response codes and phrases are defined in " https://tools.ietf.org/html/rfc7231#section-6 ". If you provide a value for <i>responseCode</i> that is not listed in RFC 7321, Section 6, you must also provide a value for <i>reasonPhrase</i> .
<i>responsePhrase</i>	String Optional. HTTP reason phrase to be returned to the client. If no reason is provided, the default reason phrase associated with <i>responseCode</i> will be used. You must provide a <i>reasonPhrase</i> for any <i>responseCode</i> that is not listed in RFC 7321, Section 6.
<i>responseString</i>	String Optional. Response to be returned to the client, specified as a string.
<i>responseBytes</i>	byte[] Optional. Response to be returned to the client, specified as a byte array.
<i>responseStream</i>	java.io.InputStream Optional. Response to be returned to the client, specified as an InputStream.

countProcessedDocuments

Counts the number of documents processed by an Integration. Details about the processed documents can be viewed in the Execution Results screen.

Input Parameters

<i>status</i>	String Optional valid values are "success" or "fail". Set status to "success" to count the number of successfully processed documents, else set it to "fail". Default value is "success".
<i>incrementBy</i>	String Optional. Increment the number of documents processed by an Integration. Every time the service is used, successful or failed documents are incremented by the given value. Default value is 1.

Output Parameters

None

Usage Notes

To increment the number of documents processed by a list, use the **sizeOfList** service in the **List** service block.

logCustomMessage

Logs a message, which can be viewed in the Execution Results screen.

Input Parameters

message **String** Custom message to be logged, which can be viewed in the Execution Results screen.

Output Parameters

None

sleep

Causes the currently executing Integration to pause for the specified number of seconds.

Input Parameters

seconds **String** The number of seconds to pause the currently executing Integration. The value must be an integer between 1 second and 60 seconds.

Output Parameters

None

Hashtable

Use **Hashtable** services to create, update, and obtain information about the hashtable.

The following **Hashtable** services are available:

Service	Description
<code>containsKey</code>	Checks for the existence of a hashtable element.
<code>createHashtable</code>	Creates a hashtable object.
<code>get</code>	Gets the value for a specified key in the hashtable.
<code>listKeys</code>	Lists all the keys stored in the hashtable.
<code>put</code>	Adds a key/value pair in the hashtable.
<code>remove</code>	Removes a key/value pair from the hashtable.
<code>size</code>	Gets the number of elements in the hashtable.

containsKey

Checks for the existence of a hashtable element.

Input Parameters

hashtable **java.util.Hashtable** Hashtable in which to check for the existence of a hashtable element.

key **String** Hashtable element to be checked for.

Output Parameters

containsKey **String** Indicates whether the specified hashtable element exists. A value of:

- `true` indicates that the element exists.
- `false` indicates that the element does not exist.

createHashtable

Creates a hashtable object.

Input Parameters

None.

Output Parameters

hashtable **java.util.Hashtable** The new hashtable object.

get

Gets the value for a specified key in the hashtable.

Input Parameters

hashtable **java.util.Hashtable** Hashtable from which to retrieve the specified value.

key **String** Key of the hashtable element whose value is to be retrieved.

Output Parameters

value **Object** Value of the input hashtable element.

listKeys

Lists all the keys stored in the hashtable.

Input Parameters

hashtable **java.util.Hashtable** Hashtable from which the keys are to be listed.

Output Parameters

keys **String[]** List of keys stored in the input hashtable.

put

Adds a key/value pair in the hashtable.

Input Parameters

hashtable **java.util.Hashtable** Hashtable to which the key/value pair is to be added.

key **String** Key of the element to be added to the hashtable.

value **Object** Value of the element to be inserted into the hashtable.

Output Parameters

hashtable **java.util.Hashtable** Hashtable object after the insertion of the key/value pair.

remove

Removes a key/value pair from the hashtable.

Input Parameters

hashtable **java.util.Hashtable** Hashtable from which to remove the key/value pair.

key **String** Key of the hashtable element to be removed.

value **Object** Value of the hashtable element to be removed.

Output Parameters

hashtable **java.util.Hashtable** Hashtable object after the key/value pair is removed.

value **Object** Value of the hashtable element that was removed. Returns `null` if the input *key* is not found in the hashtable.

size

Gets the number of elements in the hashtable.

Input Parameters

hashtable **java.util.Hashtable** Hashtable from which the number of elements stored in it is to be retrieved.

Output Parameters

size **String** Number of elements in the hashtable.

Flat File

Use **Flat File** services to convert data bytes, data stream, and data string to a document and vice versa.

The following **Flat File** services are available:

Service	Description
delimitedDataBytesToDocument	Converts delimited data bytes (byte array) to a document.
delimitedDataStreamToDocument	Converts delimited data stream to a document.
delimitedDataStringToDocument	Converts delimited data string to a document.
documentToDelimitedDataBytes	Converts a document to delimited data bytes (byte array object).
documentToDelimitedDataStream	Converts a document to a delimited data stream.
documentToDelimitedDataString	Converts a document to a delimited data string.

delimitedDataBytesToDocument

Converts delimited data bytes (byte array) to a document.

This service will convert the following delimited data from byte array:

"Date","Pupil","Grade"

"25 May","Bloggs, Fred","C"

"25 May","Doe, Jane","B"

"15 July","Bloggs, Fred","A"

Note: Here the fieldQualifier = Comma(,) and textQualifier= double quote(")

to a document that looks like: (useHeaderRowForFieldNames=true)

▼  document	
▼  rows []	
▼  rows[0]	
 Date	25 May
 Grade	C
 Pupil	Bloggs, Fred
▼  rows[1]	
 Date	25 May
 Grade	B
 Pupil	Doe, Jane
▼  rows[2]	
 Date	15 July
 Grade	A
 Pupil	Bloggs, Fred

or to a document that looks like: (useHeaderRowForFieldNames=false)

▼  document	
▼  rows []	
▼  rows[0]	
 column1	Date
 column2	Pupil
 column3	Grade
▼  rows[1]	
 column1	25 May
 column2	Bloggs, Fred
 column3	C
▼  rows[2]	
 column1	25 May
 column2	Doe, Joe
 column3	B
▼  rows[3]	
 column1	15 July
 column2	Bloggs, Fred
 column3	A

Input Parameters

<i>delimitedDataBytes</i>	java.lang.Byte[] . Delimited data in bytes (Byte array) to convert to a document.
<i>fieldQualifier</i>	String Optional. The delimiter to use for separating entries in <i>delimitedDataBytes</i> . Default is comma (,).
<i>textQualifier</i>	String Optional. The character to use for quoted elements. Default is double quote (").

<i>useHeaderRowForFieldNames</i>	String Optional. Consider first line as header row and use the delimited data of this line as property names in the output document. Set to: <ul style="list-style-type: none"> ■ <i>true</i> . The delimited data of first line will be used as the property name in the output document. This is the default. ■ <i>false</i> . column1, column2...columnN will be used as the property name in the output document.
<i>encoding</i>	String Optional. The encoding to use while parsing the delimited data.

Output Parameters

<i>document</i>	Document. Document resulting from the conversion of <i>delimitedDataBytes</i> . This document contains document array rows[] corresponding to the delimited data.
-----------------	--

delimitedDataStreamToDocument

Converts delimited data stream to a document. The permissible size of the content stream is based on your tenancy. The permissible size of the content stream is based on your tenancy.

This service converts the following delimited data in a stream:

"Date","Pupil","Grade"

"25 May","Bloggs, Fred","C"

"25 May","Doe, Jane","B"

"15 July","Bloggs, Fred","A"

Note: Here the fieldQualifier = Comma(,) and textQualifier= double quote(")

to a document that looks like: (useHeaderRowForFieldNames=true)

▼  document

▼  rows []

▼  rows[0]

 Date	25 May
 Grade	C
 Pupil	Bloggs, Fred

▼  rows[1]

 Date	25 May
 Grade	B
 Pupil	Doe, Joe

▼  rows[2]

 Date	15 July
 Grade	A
 Pupil	Bloggs, Fred

or to a document that looks like: (useHeaderRowForFieldNames=false)

▼  document	
▼  rows []	
▼  rows[0]	
 column1	Date
 column2	Pupil
 column3	Grade
▼  rows[1]	
 column1	25 May
 column2	Bloggs, Fred
 column3	C
▼  rows[2]	
 column1	25 May
 column2	Doe, Joe
 column3	B
▼  rows[3]	
 column1	15 July
 column2	Bloggs, Fred
 column3	A

Input Parameters

<i>delimited DataStream</i>	java.io.InputStream . Delimited data in an input stream to convert to a document.
<i>fieldQualifier</i>	String Optional. The delimiter to use for separating entries in <i>delimitedDataStream</i> . Default is comma (,).
<i>textQualifier</i>	String Optional. The character to use for quoted elements. Default is double quote (").

<i>useHeaderRowForFieldNames</i>	String Optional. Consider first line as header row and use the delimited data of this line as property names in the output document. Set to: <ul style="list-style-type: none"> ■ <i>true</i> . The delimited data of first line will be used as the property name in the output document. This is the default. ■ <i>false</i> . column1, column2...columnN will be used as the property name in the output document.
<i>encoding</i>	String Optional. The encoding to use while parsing the delimited data.

Output Parameters

<i>document</i>	Document. Document resulting from the conversion of <i>delimitedDataStream</i> . This document contains document array rows[] corresponding to the delimited data.
-----------------	---

delimitedDataStringToDocument

Converts delimited data string to a document.

This service will convert the following delimited data string:

"Date","Pupil","Grade"

"25 May","Bloggs, Fred","C"

"25 May","Doe, Jane","B"

"15 July","Bloggs, Fred","A"

Note: Here the fieldQualifier = Comma(,) and textQualifier= double quote(")

to a document that looks like: (useHeaderRowForFieldNames=true)

▼  document	
▼  rows []	
▼  rows[0]	
 Date	25 May
 Grade	C
 Pupil	Bloggs, Fred
▼  rows[1]	
 Date	25 May
 Grade	B
 Pupil	Doe, Jane
▼  rows[2]	
 Date	15 July
 Grade	A
 Pupil	Bloggs, Fred

or to a document that looks like: (useHeaderRowForFieldNames=false)

▼  document	
▼  rows []	
▼  rows[0]	
 column1	Date
 column2	Pupil
 column3	Grade
▼  rows[1]	
 column1	25 May
 column2	Bloggs, Fred
 column3	C
▼  rows[2]	
 column1	25 May
 column2	Doe, Joe
 column3	B
▼  rows[3]	
 column1	15 July
 column2	Bloggs, Fred
 column3	A

Input Parameters

<i>delimited DataString</i>	String. Delimited string to convert to a document.
<i>fieldQualifier</i>	String Optional. The delimiter to use for separating entries in <i>delimitedDataString</i> . Default is comma (,).
<i>textQualifier</i>	String Optional. The character to use for quoted elements. Default is double quote (").

- useHeader* **String** Optional. Consider first line as header row and use the delimited data of this line as property names in the output document.
- RowForFieldNames* Set to:
- *true* . The delimited data of first line will be used as the property name in the output document. This is the default.
 - *false* . *column1, column2...columnN* will be used as the property name in the output document.
- encoding* **String** Optional. The encoding to use while parsing the delimited data.

Output Parameters

- document* **Document**. Document resulting from the conversion of *delimitedDataString* . This document contains document array rows[] corresponding to the delimited data.

documentToDelimitedDataBytes

Converts a document to delimited data bytes (byte array object).

This service will convert the following document:

▼  document	
▼  rows []	
▼  rows[0]	
 Date	25 May
 Grade	C
 Pupil	Bloggs, Fred
▼  rows[1]	
 Date	25 May
 Grade	B
 Pupil	Doe, Jane
▼  rows[2]	
 Date	15 July
 Grade	A
 Pupil	Bloggs, Fred

To bytes (byte array object) containing the following delimited data:
(useHeaderRowForFieldNames=true)

"Date","Pupil","Grade"

"25 May","Bloggs, Fred","C"

"25 May","Doe, Jane","B"

"15 July","Bloggs, Fred","A"

Note: Here the fieldQualifier = Comma(,) and textQualifier= double quote(")

To the byte (byte array object) containing the following delimited data:
(useHeaderRowForFieldNames=false)

"column1","column2","column3"

"Date","Pupil","Grade"

"25 May","Bloggs, Fred","C"

"25 May","Doe, Jane","B"

"15 July","Bloggs, Fred","A"

Here the fieldQualifier = Comma(,) and textQualifier= double quote(")

Input Parameters

<i>document</i>	Document. Document to be converted to delimited data bytes (byte array object). This document contains a document array <code>rows[]</code> corresponding to the delimited data.
<i>fieldQualifier</i>	String Optional. The delimiter to use for separating entries in <i>delimitedDataBytes</i> . Default is comma (,).
<i>textQualifier</i>	String Optional. The character to use for quoted elements. Default is double quote (").
<i>useFieldNamesForHeaderRow</i>	String Optional. The first line in the output delimited data <i>delimitedDataBytes</i> will be constructed using the property names in the input document array <code>document \ rows[]</code> . Set to: <ul style="list-style-type: none">■ <i>true</i> . Property names in the input document array <code>document \ rows[]</code> will be used as the first row in the output <i>delimitedDataBytes</i> .■ <i>false</i> . <code>column1, column2...columnN</code> will be used as the first row in the output <i>delimitedDataBytes</i> .
<i>encoding</i>	String Optional. The encoding to use while parsing the delimited data.

Output Parameters

<i>delimitedDataBytes</i>	Object. Delimited data byte array object resulting from the conversion of a document.
---------------------------	--

documentToDelimitedDataStream

Converts a document to a delimited data stream.

This service will convert the following document:

▼  document	
▼  rows []	
▼  rows[0]	
 Date	25 May
 Grade	C
 Pupil	Bloggs, Fred
▼  rows[1]	
 Date	25 May
 Grade	B
 Pupil	Doe, Jane
▼  rows[2]	
 Date	15 July
 Grade	A
 Pupil	Bloggs, Fred

To the stream containing the following delimited data:
(useHeaderRowForFieldNames=true)

```
"Date","Pupil","Grade"
"25 May","Bloggs, Fred","C"
"25 May","Doe, Jane","B"
"15 July","Bloggs, Fred","A"
```

Note: Here the fieldQualifier = Comma(,) and textQualifier= double quote(")

or to the stream containing the following delimited data:
(useHeaderRowForFieldNames=false)

```
"column1","column2","column3"
"Date","Pupil","Grade"
"25 May","Bloggs, Fred","C"
"25 May","Doe, Jane","B"
"15 July","Bloggs, Fred","A"
```

Note: Here the fieldQualifier = Comma(,) and textQualifier= double quote(")

Input Parameters

<i>document</i>	Document. Document to be converted to delimited data stream. This document contains a document array rows[] corresponding to the delimited data.
<i>fieldQualifier</i>	String Optional. The delimiter to use for separating entries in <i>delimitedDataStream</i> . Default is comma (,).
<i>textQualifier</i>	String Optional. The character to use for quoted elements. Default is double quote (").
<i>useFieldNamesForHeaderRow</i>	<p>String Optional. The first line in the output delimited data <i>delimitedDataStream</i> will be constructed using the property names in the input document array document \ rows[]. Set to:</p> <ul style="list-style-type: none"> ■ <i>true</i> . Property names in the input document array document \ rows[] will be used as the first row in the output <i>delimitedDataStream</i> . ■ <i>false</i> . column1, column2...columnN will be used as the first row in the output <i>delimitedDataStream</i> .
<i>encoding</i>	String Optional. The encoding to use while parsing the delimited data.

Output Parameters

<i>delimitedDataStream</i>	java.io.InputStream. Delimited data stream resulting from the conversion of a document.
----------------------------	--

documentToDelimitedDataString

Converts a document to a delimited data string.

This service will convert the following document:

▼  document	
▼  rows []	
▼  rows[0]	
 Date	25 May
 Grade	C
 Pupil	Bloggs, Fred
▼  rows[1]	
 Date	25 May
 Grade	B
 Pupil	Doe, Jane
▼  rows[2]	
 Date	15 July
 Grade	A
 Pupil	Bloggs, Fred

To the string containing the following delimited data:
(useHeaderRowForFieldNames=true)

"Date","Pupil","Grade"

"25 May","Bloggs, Fred","C"

"25 May","Doe, Jane","B"

"15 July","Bloggs, Fred","A"

Here the fieldQualifier = Comma(,) and textQualifier= double quote(")

To the string containing the following delimited data:
(useHeaderRowForFieldNames=false)

"column1","column2","column3"

"Date","Pupil","Grade"

"25 May","Bloggs, Fred","C"

"25 May","Doe, Jane","B"

"15 July","Bloggs, Fred","A"

Here the fieldQualifier = Comma(,) and textQualifier= double quote(")

Input Parameters

<i>document</i>	Document. Document to be converted to delimited data string. This document contains document array rows[] corresponding to the delimited data.
<i>fieldQualifier</i>	String Optional. The delimiter to use for separating entries in <i>delimitedDataString</i> . Default is comma (,).
<i>textQualifier</i>	String Optional. The character to use for quoted elements. Default is double quote (").
<i>useFieldNamesForHeaderRow</i>	<p>String Optional. The first line in the output delimited data <i>delimitedDataString</i> will be constructed using the property names in the input document array document \ rows[]. Set to:</p> <ul style="list-style-type: none"> ■ <i>true</i>. Property names in the input document array document \ rows[] will be used as the first row in the output <i>delimitedDataString</i>. ■ <i>false</i>. column1, column2...columnN will be used as the first row in the output <i>delimitedDataString</i>.
<i>encoding</i>	String Optional. The encoding to use while parsing the delimited data.

Output Parameters

<i>delimitedDataString</i>	String. Delimited data byte string resulting from the conversion of a document.
----------------------------	--

JSON

Use **JSON** services to convert JSON content into a document and to convert a document into JSON content.

The following **JSON** services are available:

Service	Description
documentToJSONBytes	Converts a document to JSON bytes (byte array).
documentToJSONStream	Converts a document to a JSON stream.
documentToJSONString	Converts a document to a JSON string.

Service	Description
jsonBytesToDocument	Converts JSON content in bytes (byte array) to a document.
jsonStreamToDocument	Converts content from the JSON content stream to a document.
jsonStringToDocument	Converts content from the JSON string to a document.

documentToJSONBytes

Converts a document to JSON bytes (byte array).

Input Parameters

document **Document.** The document to be converted to JSON bytes (byte array).

Output Parameters

jsonBytes **Object.** JSON bytes (byte array) resulting from the conversion of a document.

documentToJSONStream

Converts a document to a JSON stream.

Input Parameters

document **Document.** The document to be converted to a JSON stream.

Output Parameters

jsonStream **java.io.InputStream.** JSON stream resulting from the conversion of a document.

documentToJsonString

Converts a document to a JSON string.

Input Parameters

<i>document</i>	Document. The document to be converted to a JSON string.
<i>prettyPrint</i>	String. Formats the <i>jsonString</i> output parameter for human readability by adding carriage returns and indentation to the JSON content. Set to: <ul style="list-style-type: none">■ <i>true</i> to format the <i>jsonString</i> output field for human readability■ <i>false</i> to leave the <i>jsonString</i> output field in its unformed state The service will not add any additional carriage returns or indentation to the JSON content.

Output Parameters

<i>jsonString</i>	Object. JSON string resulting from the conversion of a document.
-------------------	---

jsonBytesToDocument

Converts JSON content in bytes (byte array) to a document.

Input Parameters

<i>jsonBytes</i>	java.lang.Byte[]. JSON content in bytes (byte array) to convert to a document.
<i>decodeRealAsDouble</i>	String. Optional. Converts real numbers from <i>jsonBytes</i> to either a Float or Double Java wrapper type. Set to: <ul style="list-style-type: none">■ <i>true</i> to convert real numbers to Double Java wrapper types■ <i>false</i> to convert real numbers to Float Java wrapper types Default value is <i>true</i> .
<i>decodeIntegerAsLong</i>	String. Optional. Converts integers from <i>jsonBytes</i> to either a Long or Integer Java wrapper type. Set to:

- *true* to convert integers to Long Java wrapper types
- *false* to convert integers to Integer Java wrapper types

Default value is *true* .

Output Parameters

document **Document.** Document resulting from the conversion of *jsonBytes* .

jsonStreamToDocument

Converts content from the JSON content stream to a document. The permissible size of the content stream is based on your tenancy.

Input Parameters

jsonStream **java.io.InputStream.** JSON content in an input stream to convert to a document.

decodeRealAsDouble **String.** Optional. Converts real numbers from *jsonStream* to either a Float or Double Java wrapper type. Set to:

- *true* to convert real numbers to Double Java wrapper types
- *false* to convert real numbers to Float Java wrapper types

Default value is *true* .

decodeIntegerAsLong **String.** Optional. Converts integers from *jsonStream* to either a Long or Integer Java wrapper type. Set to:

- *true* to convert integers to Long Java wrapper types
- *false* to convert integers to Integer Java wrapper types

Default value is *true* .

Output Parameters

document **Document.** Document resulting from the conversion of *jsonStream* .

jsonStringToDocument

Converts content from the JSON content string to a document.

Input Parameters

- jsonString* **String.** JSON content string to convert to a document.
- decodeRealAsDouble* **String.** Optional. Converts real numbers from *jsonString* to either a Float or Double Java wrapper type. Set to:
- *true* to convert real numbers to Double Java wrapper types
 - *false* to convert real numbers to Float Java wrapper types
- Default value is *true* .
- decodeIntegerAsLong* **String.** Optional. Converts integers from *jsonString* to either a Long or Integer Java wrapper type. Set to:
- *true* to convert integers to Long Java wrapper types
 - *false* to convert integers to Integer Java wrapper types
- Default value is *true* .

Output Parameters

- document* **Document.** Document resulting from the conversion of *jsonString* .

Transaction

Use **Transaction** services only in conjunction with Database Application operations. These services are applicable when the Database Application account is of type Transactional.

The following **Transaction** services are available:

Service	Description
Transaction:commit	Commits an explicit transaction.
Transaction:rollback	Rolls back an explicit transaction.

Service	Description
Transaction:setTimeout	Manually sets a transaction timeout interval for implicit and explicit transactions.
Transaction:start	Starts an explicit transaction.

Transaction:commit

Commits an explicit transaction.

Input Parameters

commitTransactionInput **Document** Information for each commit request.

Key	Description
<i>transactionName</i>	<p>String The name of an explicit transaction that you want to commit. The <i>transactionName</i> must have been previously used in a call to Transaction:start.</p> <p>This value must be mapped from the most recent Transaction:start that has not previously been committed or rolled back.</p>

Output Parameters

None.

Usage Notes

This service must be used in conjunction with the [Transaction:start](#) service. If the *transactionName* parameter was not provided in a prior call to [Transaction:start](#), a run-time error will be returned.

Transaction:rollback

Rolls back an explicit transaction.

Input Parameters

rollbackTransactionInput

Document List Information for each rollback request.

<u>Key</u>	<u>Description</u>
<i>transactionName</i>	<p>String The name of an explicit transaction that you want to roll back. The <i>transactionName</i> must have been previously used in a call to Transaction:start.</p> <p>This value must be mapped from the most recent Transaction:start that has not previously been committed or rolled back.</p>

Output Parameters

None.

Usage Notes

This service must be used in conjunction with the [Transaction:start](#) service. If the given *transactionName* parameter was not provided in a prior call to [Transaction:start](#), a run-time error will be returned.

Transaction:setTimeout

Manually sets a transaction timeout interval for implicit and explicit transactions.

Input Parameters

<i>timeoutSeconds</i>	<p>Integer The number of seconds that the implicit or explicit transaction stays open before the transaction manager marks it for rollback.</p>
-----------------------	--

Output Parameters

None.

Usage Notes

You must call this service before you call the [Transaction:start](#) service.

If the execution of a transaction takes longer than the transaction timeout interval, all transacted operations are rolled back.

Transaction:start

Starts an explicit transaction.

Input Parameters

startTransactionInput **Document** Information for each start transaction request.

<u>Key</u>	<u>Description</u>
<i>transactionName</i>	String Optional. Specifies the name of the transaction to be started. If you leave this parameter blank, the Database Application will generate a name for you. In most implementations it is not necessary to provide your own transaction name.

Output Parameters

startTransactionOutput **Document** Information for each start transaction request.

<u>Key</u>	<u>Description</u>
<i>transactionName</i>	String The name of the transaction the service just started.

Usage Notes

This service is intended for use with the [Transaction:commit](#) or [Transaction:rollback](#) service. The *transactionName* value returned by a call to this service can be provided to [Transaction:commit](#) (to commit the transaction) or [Transaction:rollback](#) (to roll back the transaction).

XML

Use **XML** services to convert a document to XML content and XML content to a document.

The following **XML** services are available:

Service	Description
documentToXMLBytes	Converts a document to XML content bytes, as a byte array object.
documentToXMLStream	Converts a document to XML stream, as a <code>java.io.InputStream</code> object.
documentToXMLString	Converts a document to XML content string.
xmlBytesToDocument	Converts XML content bytes (byte array) to a document.
xmlNodeToDocument	Converts an XML node to a document.
xmlStreamToDocument	Converts an XML content stream to a document.
xmlStringToDocument	Converts an XML string to a document.
xmlStringToXMLNode	Converts a String, byte[], or <code>InputStream</code> containing an XML document to an XML node.
getXMLNodeType	Returns information about an XML node.
queryXMLNode	Queries an XML node.

documentToXMLBytes

Converts a document to xml content bytes, as a byte array object. This service will recurse through a given document and build an XML representation from the elements within it. Key names are turned into XML elements, and the key values are turned into the contents of those elements.

This service will convert the following document:

▼ document		
@version		1.0
▼ AcctInfo		
▼ accNum		
*body		G97041A
@type		Platinum
▼ address[0]		
@country		USA
city		closed
postalCode		22130
state		OH
street1		10211 Brook Road
▼ address[1]		
*doctype		DerivedAddress.documentLocation:docTypeRef_tns_DerivedAddress
@country		USA
city		closed
landmark		Ohio River-Bank Square
postalCode		22130
state		OH
street1		10211 Brook Road
name		Midwest Extreme Sports
▼ phoneNum		
*body		216-741-7566
@cc		011
rep		Laura M. Sanchez
▼ serialNum []		
serialNum[0]		19970523A

To XML document bytes (byte array object), whose content looks like:

```
<?xml version="1.0" ?>
<tns:AcctInfo>
  xmlns:tns="http://localhost/DerivedAddress/schema.xsd"
  xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
  <name>Midwest Extreme Sports</name>
  <rep>Laura M. Sanchez</rep>
  <acctNum type=platinum>G97041A</acctNum>
  <phoneNum cc=011>216-741-7566</phoneNum>
  <address country=USA><street1>10211 Brook Road</street1>
  <city>Cleveland</city>
  <state>OH</state>
  <postalCode>22130</postalCode>
  </address>
  <address country=USA xsi:type="tns:DerivedAddress">
  <street1>10211 Brook Road</street1>
```

```

<city>Cleveland</city>
<state>OH</state><postalCode>22130</postalCode>
<landMark>Besides Ohio River-Bank Square</landMark>
<telNo>001222555</telNo>
</address>
<serialNum>19970523A</serialNum>
<serialNum>20001106G</serialNum>
<serialNum>20010404K</serialNum>
</tns:AcctInfo>

```

Input Parameters

document **Document.** Document that is to be converted to XML. Note that if you want to produce a valid XML document (one with a single root node), document must contain only one top-level document that is, a single document. The name of that document will serve as the name of the XML document's root element. If you need to produce an XML fragment, for example, a loose collection of elements that are not encompassed within a single root element, then document can contain multiple top level elements.

nsDecls [] **Document.** Optional. Namespaces associated with any namespace prefixes that are used in the key names in document. Each entry in nsDecls represents a namespace prefix/URI pair, where a key name represents a prefix and the value of the key specifies the namespace URI. For example, to define the URIs associated with two prefixes called GSX and TxMon, you would set nsDecls as follows:

nsDecls []	
nsDecls [0]	
prefix *	GSX ...
uri *	http://www.gsx.com ...
nsDecls [1]	
prefix *	TxMon ...
uri *	http://www.acrtrak/txmonitor ...

For each prefix specified in nsDecls, this service generates an xmlns attribute and inserts it into the top-most element of the resulting XML String. For example, if nsDecls had the two keys shown above, this service would insert the following attribute into the root element of the XML String:

```
xmlns:gsx="http://www.gsx.com"
```

```
xmlns:TxMon="http://www.acrtrak/txmonitor"
```

Alternatively, you can declare a namespace by including an `@xmlns` key in document. If you were not using the `@` character to designate attributes, use the correct attribute prefix in your code.

Parameters for `nsDecls []` are:

prefix: Key name.

uri: Key value.

`addHeader` **String.** Optional.

Flag specifying whether the header element `<?xml version="1.0"?>` is to be included in the resulting XML String.

Set to:

`true` to include the header. This is the default.

`false` to omit the header. Omit the header to generate an XML fragment or to insert a custom header.

Output Parameters

`xmlBytes` **Object.** XML content bytes (byte array) produced from document.

Usage Notes

If you are building a Document that will be converted to an XML String, keep the following points in mind:

If you want to generate a simple element that contains only a character value, represent it with a String element in the document as shown below:

 name Midwest Extreme Sports

If you want to generate an element that contains children, represent with a document in the document as shown below:

 address1

 @country	USA
 street1	10211 Brook Road
 city	closed
 state	OH
 postalCode	22130

If you want to generate a simple element that contains a character value and one or more attributes, you must represent it as a document that has one key for each attribute and a key named `*body` that contains the element's value.

For example, if you want to produce the following element:

`<phoneNum cc=011>216-741-7566</phoneNum>`, you would include the following in document:

▼  phoneNum	
 @cc	011
 *body	216-741-7566

To include namespaces, ensure that you do the following:

Include the appropriate namespace prefix in the key names in document. For example, to produce an element called `acctNum` that belongs to a namespace that is represented by the "GSX" prefix, you would include a key named `GSX:acctNum` in document.

Define the URIs for the prefixes that appear in document. You can do this through `nsDecls` or by including an `@xmlns` key in the element where you want the `xmlns` attribute to be inserted.

documentToXMLStream

Converts a document to xml stream, as a `java.io.InputStream` object. This service will recurse through a given document and build an XML representation from the elements within it. Key names are turned into XML elements and the key values are turned into contents of those elements.

This service will convert the following document:

▼ document		
@version		1.0
▼ AcctInfo		
▼ accNum		
*body		G97041A
@type		Platinum
▼ address[0]		
@country		USA
city		closed
postalCode		22130
state		OH
street1		10211 Brook Road
▼ address[1]		
*doctype		DerivedAddress.documentLocation:docTypeRef_tns_DerivedAddress
@country		USA
city		closed
landmark		Ohio River-Bank Square
postalCode		22130
state		OH
street1		10211 Brook Road
name		Midwest Extreme Sports
▼ phoneNum		
*body		216-741-7566
@cc		011
rep		Laura M. Sanchez
▼ serialNum []		
serialNum[0]		19970523A

To an XML document stream, whose content looks like:

```
<?xml version="1.0" ?>
<tns:AcctInfo>
  xmlns:tns="http://localhost/DerivedAddress/schema.xsd"
  xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
  <name>Midwest Extreme Sports</name>
  <rep>Laura M. Sanchez</rep>
  <acctNum type=platinum>G97041A</acctNum>
  <phoneNum cc=011>216-741-7566</phoneNum>
  <address country=USA>
    <street1>10211 Brook Road</street1>
    <city>Cleveland</city>
    <state>OH</state>
    <postalCode>22130</postalCode>
  </address>
  <address country=USA xsi:type="tns:DerivedAddress">
```

```

<street1>10211 Brook Road</street1>
<city>Cleveland</city>
<state>OH</state>
<postalCode>22130</postalCode>
<landMark>Besides Ohio River-Bank Square</landMark>
<telNo>001222555</telNo>
</address>
<serialNum>19970523A</serialNum>
<serialNum>20001106G</serialNum>
<serialNum>20010404K</serialNum>
</tns:AcctInfo>

```

Input Parameters

document **Document.** Document that is to be converted to XML. Note that if you want to produce a valid XML document (one with a single root node), document must contain only one top-level document that is, a single document. The name of that document will serve as the name of the XML document's root element. If you need to produce an XML fragment, for example, a loose collection of elements that are not encompassed within a single root element, then document can contain multiple top level elements.

nsDecls [] **Document.** Optional. Namespaces associated with any namespace prefixes that are used in the key names in document. Each entry in nsDecls represents a namespace prefix/URI pair, where a key name represents a prefix and the value of the key specifies the namespace URI. For example, to define the URIs associated with two prefixes called GSX and TxMon, you would set nsDecls as follows:

▼ nsDecls []		
▼ nsDecls [0]		
prefix *	GSX	...
uri *	http://www.gsx.com	...
▼ nsDecls [1]		
prefix *	TxMon	...
uri *	http://www.acrtrak/txmonitor	...

For each prefix specified in nsDecls, this service generates an xmlns attribute and inserts it into the top-most element of the resulting XML String. For example, if nsDecls had the two keys shown above, this service would insert the following attribute into the root element of the XML String:

```
xmlns:gsx="http://www.gsx.com"
```

```
xmlns:TxMon="http:www.acrtrak/txMonitor"
```

Alternatively, you can declare a namespace by including an `@xmlns` key in document. If you were not using the `@` character to designate attributes, use the correct attribute prefix in your code.

Parameters for `nsDecls []` are:

prefix: Key name.

uri: Key value.

addHeader **String.** Optional.

Flag specifying whether the header element `<?xml version="1.0"?>` is to be included in the resulting XML String.

Set to:

true to include the header. This is the default.

false to omit the header. Omit the header to generate an XML fragment or to insert a custom header.

Output Parameters

xmlStream **java.io.InputStream.** XML content stream produced from document.

Usage Notes

If you are building a Document that will be converted to an XML String, keep the following points in mind:

If you want to generate a simple element that contains only a character value, represent it with a String element in document as shown below:

```
 name Midwest Extreme Sports
```

If you want to generate an element that contains children, represent with a document in the document as shown below:

▼  address1	
 @country	USA
 street1	10211 Brook Road
 city	closed
 state	OH
 postalCode	22130

If you want to generate a simple element that contains a character value and one or more attributes, you must represent it as a document that has one key for each attribute and a key named `*body` that contains the element's value.

For example, if you want to produce the following element:

```
<phoneNum cc=011>216-741-7566</phoneNum>
```

You would include the following in document:

▼  phoneNum	
 @cc	011
 *body	216-741-7566

To include namespaces, ensure that you do the following:

Include the appropriate namespace prefix in the key names in document. For example, to produce an element called `acctNum` that belongs to a namespace that is represented by the "GSX" prefix, you would include a key named `GSX:acctNum` in document.

Define the URIs for the prefixes that appear in document. You can do this through `nsDecls` or by including an `@xmlns` key in the element where you want the `xmlns` attribute to be inserted.

documentToXMLString

Converts a document to xml content string. This service will recurse through a given document and build an XML representation from the elements within it. Key names are turned into XML elements, and the key values are turned into the contents of those elements.

This service will convert the following document:

▼ document		
@version		1.0
▼ AcctInfo		
▼ accNum		
*body		G97041A
@type		Platinum
▼ address[0]		
@country		USA
city		closed
postalCode		22130
state		OH
street1		10211 Brook Road
▼ address[1]		
*doctype		DerivedAddress.documentLocation:docTypeRef_tns_DerivedAddress
@country		USA
city		closed
landmark		Ohio River-Bank Square
postalCode		22130
state		OH
street1		10211 Brook Road
name		Midwest Extreme Sports
▼ phoneNum		
*body		216-741-7566
@cc		011
rep		Laura M. Sanchez
▼ serialNum []		
serialNum[0]		19970523A

To an XML document string, whose content looks like:

```
<?xml version="1.0" ?>
<tns:AcctInfo>
  xmlns:tns="http://localhost/DerivedAddress/schema.xsd"
  xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
  <name>Midwest Extreme Sports</name>
  <rep>Laura M. Sanchez</rep>
  <acctNum type=platinum>G97041A</acctNum>
  <phoneNum cc=011>216-741-7566</phoneNum>
  <address country=USA>
  <street1>10211 Brook Road</street1>
  <city>Cleveland</city>
  <state>OH</state>
  <postalCode>22130</postalCode>
  </address>
  <address country=USA xsi:type="tns:DerivedAddress">
```

```

<street1>10211 Brook Road</street1>
<city>Cleveland</city>
<state>OH</state>
<postalCode>22130</postalCode>
<landMark>Besides Ohio River-Bank Square</landMark>
<telNo>001222555</telNo>
</address>
<serialNum>19970523A</serialNum>
<serialNum>20001106G</serialNum>
<serialNum>20010404K</serialNum>
</tns:AcctInfo>

```

Input Parameters

document **Document.** Document that is to be converted to XML. If you want to produce a valid XML document (one with a single root node), document must contain only one top-level document that is, a single document. The name of that document will serve as the name of the XML document's root element. If you need to produce an XML fragment, for example, a loose collection of elements that are not encompassed within a single root element, then document can contain multiple top level elements.

nsDecls [] **Document.** Optional. Namespaces associated with any namespace prefixes that are used in the key names in document. Each entry in nsDecls represents a namespace prefix/URI pair, where a key name represents a prefix and the value of the key specifies the namespace URI. For example, to define the URIs associated with two prefixes called GSX and TxMon, you would set nsDecls as follows:

nsDecls []	
▼ nsDecls [0]	
prefix *	GSX ...
uri *	http://www.gsx.com ...
▼ nsDecls [1]	
prefix *	TxMon ...
uri *	http://www.acrtrak/txmonitor ...

For each prefix specified in nsDecls, this service generates an xmlns attribute and inserts it into the top-most element of the resulting XML String. For example, if nsDecls had the two keys shown above, this service would insert the following attribute into the root element of the XML String:

```
xmlns:gsx="http://www.gsx.com"
```

```
xmlns:TxMon="http:www.acrtrak/txMonitor"
```

Alternatively, you can declare a namespace by including an @xmlns key in document. If you were not using the @ character to designate attributes, use the correct attribute prefix in your code.

Parameters for *nsDecls []* are:

prefix: Key name.

uri: Key value.

addHeader **String.** Optional.

Flag specifying whether the header element `<?xml version="1.0"?>` is to be included in the resulting XML String.

Set to:

true to include the header. This is the default.

false to omit the header. Omit the header to generate an XML fragment or to insert a custom header.

Output Parameters

xmlString **Object.** XML document string produced from document.

Usage Notes

If you are building a Document that will be converted to an XML String, keep the following points in mind:

If you want to generate a simple element that contains only a character value, represent it with a String element in document as shown below:

 name Midwest Extreme Sports

If you want to generate an element that contains children, represent with a document in the document as shown below:

▼  address1	
 @country	USA
 street1	10211 Brook Road
 city	closed
 state	OH
 postalCode	22130

If you want to generate a simple element that contains a character value and one or more attributes, you must represent it as a document that has one key for each attribute and a key named `*body` that contains the element's value.

For example, if you want to produce the following element:

```
<phoneNum cc=011>216-741-7566</phoneNum>
```

You would include the following in document:

▼  phoneNum	
 @cc	011
 *body	216-741-7566

To include namespaces, ensure that you do the following:

Include the appropriate namespace prefix in the key names in document. For example, to produce an element called `acctNum` that belongs to a namespace that is represented by the "GSX" prefix, you would include a key named `GSX:acctNum` in document.

Define the URIs for the prefixes that appear in document. You can do this through `nsDecls` or by including an `@xmlns` key in the element where you want the `xmlns` attribute to be inserted.

xmlBytesToDocument

Converts XML content bytes (byte array) to a document. This service transforms each element and attribute in XML content bytes to an element in a Document.

This service will convert XML bytes containing the following XML content:

```
<?xml version="1.0" ?>
<tns:AcctInfo>
xmlns:tns="http://localhost/DerivedAddress/schema.xsd"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
```

```
<name>Midwest Extreme Sports</name>
<rep>Laura M. Sanchez</rep>
<acctNum type=platinum>G97041A</acctNum>
<phoneNum cc=011>216-741-7566</phoneNum>
<address country=USA>
<street1>10211 Brook Road</street1>
<city>Cleveland</city>
<state>OH</state>
<postalCode>22130</postalCode>
</address>
<address country=USA xsi:type="tns:DerivedAddress">
<street1>10211 Brook Road</street1>
<city>Cleveland</city>
<state>OH</state>
<postalCode>22130</postalCode>
<landMark>Besides Ohio River-Bank Square</landMark>
<telNo>001222555</telNo>
</address>
<serialNum>19970523A</serialNum>
<serialNum>20001106G</serialNum>
<serialNum>20010404K</serialNum>
</tns:AcctInfo>
```

To a Document that looks like:

▼  document	
 @version	1.0
▼  AcctInfo	
▼  accNum	
 *body	G97041A
 @type	Platinum
▼  address[0]	
 @country	USA
 city	closed
 postalCode	22130
 state	OH
 street1	10211 Brook Road
▼  address[1]	
 *doctype	DerivedAddress.documentLocation:docTypeRef_tns_DerivedAddress
 @country	USA
 city	closed
 landmark	Ohio River-Bank Square
 postalCode	22130
 state	OH
 street1	10211 Brook Road
 name	Midwest Extreme Sports
▼  phoneNum	
 *body	216-741-7566
 @cc	011
 rep	Laura M. Sanchez
▼  serialNum []	
 serialNum[0]	19970523A

Input Parameters

xmlBytes **Object.** XML content bytes that is to be converted to a document.

nsDecls [] **Document.** Optional. Namespace prefixes to use for the conversion. This parameter specifies the prefixes that will be used when namespace-qualified elements are converted to key names in the resulting document object. For example, if you want elements belonging to a particular namespace to have the prefix GSX in the resulting document, for example, GSX:acctNum, you would associate the prefix GSX with that namespace in nsDecls . This is important because incoming XML documents can use any prefix for a given

namespace, but the key names expected by a target service will have a fixed prefix. Namespace prefixes in `nsDecls` also define the prefixes used by the arrays, documents, `documentTypeName`, and `collect` parameters. Each entry in `nsDecls` represents a namespace prefix/URI pair, where a key name represents a prefix and the value of the key specifies the namespace URI. For example, to define the URIs associated with two prefixes called `GSX` and `TxMon`, you would set `nsDecls` as follows:

▼ nsDecls []

- ▼ nsDecls [0]
 - prefix * GSX ...
 - uri * http://www.gsx.com ...
- ▼ nsDecls [1]
 - prefix * TxMon ...
 - uri * http://www.acrtrak/txmonitor ...

Parameters for `nsDecls []` are:

prefix: Key name.

uri: Key value.

`preserveUndeclaredNS`

String Optional. Flag indicating whether or not Integration Cloud keeps undeclared namespaces in the resulting document. An undeclared namespace is one that is not specified as part of the `nsDecls` input parameter.

Set to:

- `True` to preserve undeclared namespaces in the resulting document. For each namespace declaration in the XML document that is not specified in the `nsDecls` parameter, Integration Cloud adds the `xmlns` attribute as a String variable to the document. Integration Cloud gives the variable a name that begins with "@xmlns" and assigns the variable the namespace value specified in the XML document. Integration Cloud preserves the position of the undeclared namespace in the resulting document.
- `False` to ignore namespace declarations in the XML document that are not specified in the `nsDecls` parameter. This is the default.

`preserveNSPositions`

String Optional. Flag indicating whether or not Integration Cloud maintains the position of namespaces declared in the `nsDecls` parameter in the resulting document.

Set to:

- `True` to preserve the position of namespaces declared in `nsDecls` in the resulting document. For each namespace specified in the `nsDecls` parameter, Integration Cloud adds the `xmlns` attribute to the document as a String variable named `"@xmlns:NSprefix"` where `NSprefix` is the prefix name specified in `nsDecls`. Integration Cloud assigns the variable the namespace value specified in the XML document. This variable maintains the position of the `xmlns` attribute declaration within the XML document.
- `False` to not maintain the position of the namespace declarations specified in `nsDecls` in the resulting document. This is the default.

Output Parameters

`document` **Document.** Document representation of nodes and attributes in node.

Usage Notes

Following are examples of XML documents and the documents that `xmlBytesToDocument` will produce:

XML Document	Document
<pre><myDoc><e1>e1Value</e1> </myDoc></pre>	
<pre><?xml version="1.0" encoding="UTF-8" standalone="no"?><myDoc><e1>e1Value </e1></myDoc></pre>	

```
<?xml version="1.0" encoding="UTF-8"
standalone="no"?><myDoc><e1
e1Attr="attrValue">
e1Value</e1></myDoc>
```

document	
@encoding	UTF-8
@standalone	no
@version	1.0
myDoc	
e1	
*body	e1Value
@e1Attr	attrValue

```
<?xml version="1.0" encoding="UTF-8"
standalone="no"?><myDoc><e1>e1Value
</e1><e2>e2Value</e2></myDoc>
```

document	
@encoding	UTF-8
@standalone	no
@version	1.0
myDoc	
e1	e1Value
e2	e2Value

```
<?xml version="1.0" encoding="UTF-8"
standalone="no"?><myDoc><e1>e1Value1
</e1><e2>e2Value</e2><e1>e1Value2
</e1></myDoc>
```

document	
@encoding	UTF-8
@standalone	no
@version	1.0
myDoc	
e1	e1Value1
e2	e2Value

```
<?xml version="1.0"encoding="UTF-8"?>
<myDoc><e1 e1Attr="attrValue1">e1Value1
</e1><e2>e2Value</e2><e1 e1Attr=
"attrValue2">
e1Value2</e1></myDoc>
```

document		
@encoding	UTF-8	
@version	1.0	
myDoc		
e1 []		
e1[0]		
*body		e1Value1
@e1Attr		attrValue1
e1[1]		
*body		e1Value2
@e1Attr		attrValue2
e2		e2Value

```
<?xml version="1.0"encoding="UTF-8"?>
<myDoc><e1 e1Attr="attrValue1">
e1Value1
</e1><e2>e2Value</e2><e1
e1Attr="attrValue2">
e1Value2</e1></myDoc>
```

document		
@encoding	UTF-8	
@version	1.0	
myDoc		
e1 []		
e1[0]		
*body		e1Value1
@e1Attr		attrValue1
e1[1]		
*body		e1Value2
@e1Attr		attrValue2
e2		e2Value

```
<?xml version="1.0"encoding="UTF-8"?>
<myDoc><e1 e1Attr="attrValue1">e1Value1
</e1><e2>e2Value</e2><e1 e1Attr=
"attrValue2">
e1Value2</e1></myDoc>
```

document		
@encoding	UTF-8	
@version	1.0	
myDoc		
e1		
*body		e1Value1
@e1Attr		attrValue1
e2		e2Value

```
<?xml version="1.0"encoding="UTF-8"?>
<myDoc><e1 e1Attr="attrValue1">e1Value1
</e1><e2><e3>e3Value</e3>
<e4 e4Attr="attrValue4"e4Attrb=
"attrValue4b">
e4Value</e4></e2></myDoc>
```

document		
@encoding	UTF-8	
@version	1.0	
myDoc		
e1		
*body		e1Value1
@e1Attr		attrValue1
e2		
e3		e3Value
e4		
*body		e4Value
@e4Attr		attrValue4
@e4Attrb		attrValue4b

```
<?xml version="1.0" encoding="UTF-8"
standalone="no"?><tns:AcctInfo>
xmlns:tns="http://localhost/
DerivedAddress/schema.xsd"
xmlns:xsi="http://www.w3.org/
2001/XMLSchema-instance">
<myDoc>
<e1>e1Value</e1></myDoc>
<myDoc xsi:type="tns:DerivedDoc">
<e1>e1Value</e1><e2>
e2Value</e2></myDoc>
</tns:AcctInfo>
```

document		
@encoding	UTF-8	
@version	1.0	
myDoc []		
myDoc[0]		
e1		e1Value
myDoc[1]		
*docType		DerivedDoc.documentLocation:docTypeRef
e1		e1Value
e2		e2Value

xmlNodeToDocument


Converts an XML node to a document.

This service transforms each element and attribute in the XML node to an element in a Document. For example:

This service would convert this XML document...

```
<?xml version="1.0" ?>
  <tns:AcctInfo>
    xmlns:tns="http://localhost/DerivedAddress/schema.xsd"
    xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" >
    <name>Midwest Extreme Sports</name>
    <rep>Laura M. Sanchez</rep>
    <acctNum type=platinum>G97041A</acctNum>
    <phoneNum cc=011>216-741-7566</phoneNum>
    <address country=USA>
      <street1>10211 Brook Road</street1>
      <city>Cleveland</city>
      <state>OH</state>
      <postalCode>22130</postalCode>
    </address>
    <address country=USA xsi:type="tns:DerivedAddress">
    <street1>10211 Brook Road</street1>
      <city>Cleveland</city>
      <state>OH</state>
      <postalCode>22130</postalCode>
      <landMark>Besides Ohio River-Bank Square</landMark>
      <telNo>001222555</telNo>
    </address>
    <serialNum>19970523A</serialNum>
    <serialNum>20001106G</serialNum>
    <serialNum>20010404K</serialNum>
  </tns:AcctInfo>
```

To a document that looks like this...



Note that:

- The XML version attribute is converted to an element named `@version`.
- The resulting document is given the same name as the XML document's root element (`AcctInfo` in the example above) and is a child of the `document` variable that this service returns.
- Simple elements (such as `<name>` and `<rep>` in the example above) are converted to String elements.
- Complex elements (that is, elements with children, such as `<address>` in the example above) and simple elements that have attributes (such as `<acctNum>` and `<phoneNum>`) are converted to documents. Note that keys derived from attributes are prefixed with a "@" character to distinguish them from keys derived from elements. Also note that when a simple element has an attribute, its value is placed in an element named `*body`.
- Repeated elements (such as `<serialNum>`) can be collected into arrays using the `makeArrays` and/or `arrays` parameters. See `makeArrays` and `arrays` below for additional information about producing arrays.

- While creating a document, the `xmlNodeToDocument` service assigns a value of `emptyString` to the fields that are empty in the document.

Input Parameters

<i>node</i>	<p>XML node that is to be converted to a document.</p> <p>This parameter supports the following types of input:</p> <ul style="list-style-type: none"> ■ <code>com.wm.lang.xml.Node</code> ■ <code>org.w3c.dom.Node</code>
<i>attrPrefix</i>	<p>String Optional. Prefix that is to be used to designate keys containing attribute values. The default is "@". For example, if you set <i>attrPrefix</i> to <code>ATT_</code> and <i>node</i> contained the following element:</p> <pre><tx currency=dollars> <acct>cash</acct> <amt>120.00</amt> </tx></pre> <p><code>xmlNodeToDocument</code> would convert the <code>currency</code> attribute as follows:</p> 
<i>arrays[]</i>	<p>String List Optional. Names of elements that are to be generated as arrays, regardless of whether they appear multiple times in <i>node</i>. For example, if <i>arrays</i> contained the following values for the XML document shown in the example in the description for this service:</p> <pre>rep address</pre> <p><code>xmlNodeToDocument</code> would generate element <code>rep</code> as a String List and element <code>address</code> as a Document List.</p> <p>Important: you include namespace prefixes in the element names that you specify in <i>arrays</i>, you must define the namespaces associated with those prefixes in <i>nsDecls</i>.</p>
<i>makeArrays</i>	<p>String Optional. Flag indicating whether you want <code>xmlNodeToDocument</code> to automatically create an array for</p>

every element that appears in *node* more than once.
Set to:

- `true` to automatically create arrays for every element that appears more than once in *node*. This is the default.
- `false` to create arrays for only those elements specified in *arrays*.

collect

Document Optional. Elements that are to be placed into a new, named array (that is, a "collection"). Within *collect*, use key names to specify the names of the elements that are to be included in the collection. Then set the value of each key to specify the name of the collection in which you want that element placed. For example, if you wanted to place the `<name>` and `<rep>` elements in an array called *originator*, you would set *collect* as follows:

Key	Value
<i>name</i>	<i>originator</i>
<i>rep</i>	<i>originator</i>

If the set of elements in a collection are all simple elements, a String List is produced. However, if the set is made up of complex elements, or a combination of simple and complex elements, a Document List is produced. When this is the case, each member of the array will include a child element called `*name` that contains the name of the element from which that member was derived.

You may optionally include namespace prefixes in the element names that you specify in *collect*; however, if you do, you must define the namespaces associated with those prefixes in *nsDecls*.

Important You cannot include an element in more than one collection.

nsDecls

Document Optional. Namespace prefixes to use for the conversion. This parameter specifies the prefixes that will be used when namespace-qualified elements are converted to key names in the resulting Document. For example, if you want elements belonging to a particular namespace to have the prefix `GSX` in the

resulting Document (for example, `GSX:acctNum`), you would associate the prefix `GSX` with that namespace in `nsDecls`. (This is important because incoming XML documents can use any prefix for a given namespace, but the key names expected by a target service will have a fixed prefix.)

Namespace prefixes in `nsDecls` also define the prefixes used by the `arrays`, `documents`, and `collect` parameters.

Each entry in `nsDecls` represents a namespace prefix/URI pair, where a key name represents a prefix and the value of the key specifies the namespace URI.

For example, to define the URIs associated with two prefixes called `GSX` and `TxMon`, you would set `nsDecls` as follows:



`documents[]`

String List Optional. Names of any simple elements that are to be generated as documents instead of Strings. The document produced for each element specified in `documents[]` will have the same name as the source element from which it is derived. It will contain a String element named `*body` that holds the element's value.

For example, if `documents[]` contained the Strings `name` and `rep` and the source document contained the following:

```

.
.
.
<name>Midwest Extreme Sports</name>
<rep>Laura M. Sanchez</rep>
.
.
.

```

`xmlNodeToDocument` would produce the following:



Note: If you include namespace prefixes in the element names that you specify, you must define the

namespaces associated with those prefixes in *nsDecls*.


mixedModel

String Optional. Flag specifying how mixed-content elements (elements containing both text values and child elements) are to be converted. The following is an example of a mixed-content element:

```
<comment>
This job is <status>pending</status>. Estimated
completion date is <edc>Feb 14, 2000</edc>.
</comment>
```

Set to:

- **true** to place top-level text in an element named **body*. This setting would produce the following Document for the `<comment>` element shown above:



- **false** to omit top-level text and include only the child elements from mixed-content elements. This setting would produce the following Document for the `<comment>` element shown above:



preserveUndeclaredNS

String Optional. Flag indicating whether or not Integration Cloud keeps undeclared namespaces in the resulting document. An undeclared namespace is one that is not specified as part of the *nsDecls* input parameter.

Set to:

- **True** to preserve undeclared namespaces in the resulting document. For each namespace declaration in the XML document that is not specified in the *nsDecls* parameter, Integration Cloud adds the `xmlns` attribute as a String variable to the document. Integration Cloud gives the variable a name that begins with "`@xmlns`" and assigns the variable the namespace value specified in the XML document. Integration Cloud preserves the position of the undeclared namespace in the resulting document.

- `False` to ignore namespace declarations in the XML document that are not specified in the `nsDecls` parameter. This is the default.

preserveNSPositions

String Optional. Flag indicating whether or not Integration Cloud maintains the position of namespaces declared in the `nsDecls` parameter in the resulting document.

Set to:

- `True` to preserve the position of namespaces declared in `nsDecls` in the resulting document. For each namespace specified in the `nsDecls` parameter, Integration Cloud adds the `xmlns` attribute to the document (IData) as a String variable named `"@xmlns:NSprefix"` where `"NSprefix"` is the prefix name specified in `nsDecls`. Integration Cloud assigns the variable the namespace value specified in the XML document. This variable maintains the position of the `xmlns` attribute declaration within the XML document.
- `False` to not maintain the position of the namespace declarations specified in `nsDecls` in the resulting document. This is the default.

Output Parameters

document

Document Document representation of the nodes and attributes in node.

Examples

Following are examples of XML documents and the documents that `xmlNodeToDocument` would produce.

XML Document

```
<myDoc>
<e1>e1Value</e1>
</myDoc>
```

Output from `xmlNodeToDocument`



XML Document

```
<?xml version="1.0" encoding="UTF-8"
standalone="no"?>
<myDoc>
<e1>e1Value</e1>
</myDoc>
```

Output from xmlNodeToDocument




```
<?xml version="1.0" encoding="UTF-8"
standalone="no"?>
<myDoc>
<e1 e1Attr="attrValue">e1Value</e1>
</myDoc>
```




```
<?xml version="1.0" encoding="UTF-8"
standalone="no"?>
<myDoc>
<e1>e1Value</e1>
<e2>e2Value</e2>
</myDoc>
```



```
<?xml version="1.0" encoding="UTF-8"
standalone="no"?>
<myDoc>
<e1>e1Value1</e1>
<e2>e2Value</e2>
<e1>e1Value2</e1>
</myDoc>
```



```
<?xml version="1.0"
encoding="UTF-8"?>
<myDoc>
<e1 e1Attr="attrValue1">e1Value1</e1>
<e2>e2Value</e2>
<e1 e1Attr="attrValue2">e1Value2</e1>
</myDoc>
```



Note This example assumes that `makeArrays` is set to true. Note that `e1` was created as a document list, which

XML Document

```
<?xml version="1.0"
encoding="UTF-8"?>
<myDoc>
<e1 e1Attr="attrValue1">e1Value1</e1>
<e2>e2Value</e2>
<e1 e1Attr="attrValue2">e1Value2</e1>
</myDoc>
```

```
<?xml version="1.0"
encoding="UTF-8"?>
<myDoc>
<e1 e1Attr="attrValue1">e1Value1</e1>
<e2>e2Value</e2>
<e1 e1Attr="attrValue2">e1Value2</e1>
</myDoc>
```

```
<?xml version="1.0"
encoding="UTF-8"?>
<myDoc>
<e1 e1Attr="attrValue1">e1Value1</e1>
<e2>
<e3>e3Value</e3>
<e4 e4Attr="attrValue4"
e4Attrb="attrValue4b">e4Value
</e4>
</e2>
</myDoc>
```

Output from xmlNodeToDocument

holds both <e1> elements from the XML document.

document	
@version	1.0
@encoding	UTF-8
myDoc	
e1	
@e1Attr	attrValue1
*body	e1Value1
e1	
@e1Attr	attrValue2
*body	e1Value2
e2	e2Value

document	
@version	1.0
@encoding	UTF-8
myDoc	
e1	
@e1Attr	attrValue2
*body	e1Value2
e2	e2Value

document	
@version	1.0
@encoding	UTF-8
myDoc	
e1	
@e1Attr	attrValue1
*body	e1Value1
e2	
e3	e3Value
e4	
@e4Attr	attrValue4
@e4Attrb	attrValue4b
*body	e4Value

XML Document

```
<?xml version="1.0" encoding="UTF-8"
standalone="no"?>
  <tns:AcctInfo>
    xmlns:tns="http://localhost/Derived
Address/schema.xsd"
    xmlns:xsi="http://www.w3.org/2001/
XMLSchema-instance" >
      <myDoc>    <e1>e1Value</e1>
      </myDoc>
      <myDoc xsi:type="tns:DerivedDoc">
        <e1>e1Value</e1>
        <e2>e1Value</e2>
      </myDoc>
    </tns:AcctInfo>
```

Output from xmlNodeToDocument

```
document
├── @version 1.0
├── @encoding UTF-8
├── @standalone no
├── myDoc[0]
│   └── e1 e1Value
├── myDoc[1]
│   ├── e1 e1Value
│   └── e2 e2Value
└── *docType DerivedDoc.documentLocation:
    docTypeRef_tns_DerivedDoc
```

xmlStreamToDocument

Converts an XML content stream to a document. This service transforms each element and attribute in the XML content stream to an element in a Document.

This service will convert the XML stream containing the following XML content:

```
<?xml version="1.0" ?>
<tns:AcctInfo>
  xmlns:tns="http://localhost/DerivedAddress/schema.xsd"
  xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
  <name>Midwest Extreme Sports</name>
  <rep>Laura M. Sanchez</rep>
  <acctNum type=platinum>G97041A</acctNum>
  <phoneNum cc=011>216-741-7566</phoneNum>
  <address country=USA>
  <street1>10211 Brook Road</street1>
  <city>Cleveland</city>
  <state>OH</state>
  <postalCode>22130</postalCode>
  </address>
  <address country=USA xsi:type="tns:DerivedAddress">
  <street1>10211 Brook Road</street1>
  <city>Cleveland</city>
  <state>OH</state>
  <postalCode>22130</postalCode>
  <landMark>Besides Ohio River-Bank Square</landMark>
  <telNo>001222555</telNo>
  </address>
  <serialNum>19970523A</serialNum>
  <serialNum>20001106G</serialNum>
  <serialNum>20010404K</serialNum>
  </tns:AcctInfo>
```

To a Document that looks like:

▼ document		
@version		1.0
▼ AcctInfo		
▼ accNum		
*body		G97041A
@type		Platinum
▼ address[0]		
@country		USA
city		closed
postalCode		22130
state		OH
street1		10211 Brook Road
▼ address[1]		
*doctype		DerivedAddress.documentLocation:docTypeRef_tns_DerivedAddress
@country		USA
city		closed
landmark		Ohio River-Bank Square
postalCode		22130
state		OH
street1		10211 Brook Road
name		Midwest Extreme Sports
▼ phoneNum		
*body		216-741-7566
@cc		011
rep		Laura M. Sanchez
▼ serialNum []		
serialNum[0]		19970523A

Input Parameters

<i>xmlStream</i>	java.io.InputStream. XML content stream that is to be converted to a document.
<i>nsDecls []</i>	Document. Optional. Namespace prefixes to use for the conversion. This parameter specifies the prefixes that will be used when namespace-qualified elements are converted to key names in the resulting document object. For example, if you want elements belonging to a particular namespace to have the prefix GSX in the resulting document, for example, GSX:acctNum, you would associate the prefix GSX with that namespace in nsDecls . This is important

because incoming XML documents can use any prefix for a given namespace, but the key names expected by a target service will have a fixed prefix. Namespace prefixes in `nsDecls` also define the prefixes used by the arrays, documents, `documentTypeName`, and `collect` parameters. Each entry in `nsDecls` represents a namespace prefix/URI pair, where a key name represents a prefix and the value of the key specifies the namespace URI. For example, to define the URIs associated with two prefixes called `GSX` and `TxMon`, you would set `nsDecls` as follows:

The screenshot shows a configuration interface for `nsDecls`. It is organized into a tree structure:

- Root: `nsDecls []` (expanded)
 - Child: `nsDecls [0]` (expanded)
 - Field: `prefix *` (String type) with value `GSX`
 - Field: `uri *` (String type) with value `http://www.gsx.com`
 - Child: `nsDecls [1]` (expanded)
 - Field: `prefix *` (String type) with value `TxMon`
 - Field: `uri *` (String type) with value `http://www.acrtrak/txmonitor`

Parameters for `nsDecls []` are:

prefix: Key name.

uri: Key value.

`preserveUndeclaredNS`

String Optional. Flag indicating whether or not Integration Cloud keeps undeclared namespaces in the resulting document. An undeclared namespace is one that is not specified as part of the `nsDecls` input parameter.

Set to:

- `True` to preserve undeclared namespaces in the resulting document. For each namespace declaration in the XML document that is not specified in the `nsDecls` parameter, Integration Cloud adds the `xmlns` attribute as a String variable to the document. Integration Cloud gives the variable a name that begins with `"@xmlns"` and assigns the variable the namespace value specified in the XML document. Integration Cloud preserves the position of the undeclared namespace in the resulting document.
- `False` to ignore namespace declarations in the XML document that are not specified in the `nsDecls` parameter. This is the default.

`preserveNSPositions` **String** Optional. Flag indicating whether or not Integration Cloud maintains the position of namespaces declared in the `nsDecls` parameter in the resulting document.

Set to:

- `True` to preserve the position of namespaces declared in `nsDecls` in the resulting document. For each namespace specified in the `nsDecls` parameter, Integration Cloud adds the `xmlns` attribute to the document as a String variable named "`@xmlns:NSprefix`" where "`NSprefix`" is the prefix name specified in `nsDecls`. Integration Cloud assigns the variable the namespace value specified in the XML document. This variable maintains the position of the `xmlns` attribute declaration within the XML document.
- `False` to not maintain the position of the namespace declarations specified in `nsDecls` in the resulting document. This is the default.

Output Parameters

`document` **Document.** Document representation of nodes and attributes in node.

Usage Notes

Following are examples of XML documents and the documents that `xmlStreamToDocument` will produce:

XML Document	Document
<pre><myDoc><e1>e1Value</e1> </myDoc></pre>	<pre> document ├── myDoc │ └── e1 e1Value </pre>
<pre><?xml version="1.0" encoding="UTF-8" standalone="no"?><myDoc><e1> e1Value</e1></myDoc></pre>	<pre> document ├── @encoding UTF-8 ├── @standalone no ├── @version 1.0 └── myDoc └── e1 e1Value </pre>

```
<?xml version="1.0" encoding="UTF-8"
standalone="no"?><myDoc>
<e1 e1Attr="attrValue">
e1Value</e1></myDoc>
```

▼ document		
STR @encoding		UTF-8
STR @standalone		no
STR @version		1.0
▼ myDoc		
▼ e1		
STR *body		e1Value
STR @e1Attr		attrValue

```
<?xml version="1.0" encoding="UTF-8"
standalone="no"?><myDoc>
<e1>e1Value</e1><e2>e2Value</e2>
</myDoc>
```

▼ document		
STR @encoding		UTF-8
STR @standalone		no
STR @version		1.0
▼ myDoc		
STR e1		e1Value
STR e2		e2Value

```
<?xml version="1.0" encoding="UTF-8"
standalone="no"?><myDoc><e1>
e1Value1</e1><e2>
e2Value</e2><e1>
e1Value2</e1></myDoc>
```

▼ document		
STR @encoding		UTF-8
STR @standalone		no
STR @version		1.0
▼ myDoc		
STR e1		e1Value1
STR e2		e2Value

```
<?xml version="1.0"encoding="UTF-8"?>
<myDoc><e1 e1Attr="attrValue1">
e1Value1</e1><e2>e2Value</e2>
<e1 e1Attr="attrValue2">e1Value2
</e1></myDoc>
```

document		
@encoding	UTF-8	
@version	1.0	
myDoc		
e1 []		
e1[0]		
*body		e1Value1
@e1Attr		attrValue1
e1[1]		
*body		e1Value2
@e1Attr		attrValue2
e2		e2Value

```
<?xml version="1.0"encoding="UTF-8"?>
<myDoc><e1 e1Attr="attrValue1">
e1Value1</e1><e2>
e2Value</e2><e1 e1Attr="attrValue2">
e1Value2</e1></myDoc>
```

document		
@encoding	UTF-8	
@version	1.0	
myDoc		
e1 []		
e1[0]		
*body		e1Value1
@e1Attr		attrValue1
e1[1]		
*body		e1Value2
@e1Attr		attrValue2
e2		e2Value

```
<?xml version="1.0"encoding="UTF-8"?>
<myDoc><e1 e1Attr="attrValue1">
e1Value1</e1><e2>e2Value</e2>
<e1 e1Attr="attrValue2">
e1Value2</e1>
</myDoc>
```

document		
@encoding	UTF-8	
@version	1.0	
myDoc		
e1		
*body		e1Value2
@e1Attr		attrValue2
e2		e2Value

```
<?xml version="1.0"encoding="UTF-8"?>
<myDoc><e1 e1Attr="attrValue1">
e1Value1
</e1><e2><e3>e3Value</e3>
<e4 e4Attr=
"attrValue4"e4Attrb="attrValue4b">
e4Value
</e4></e2></myDoc>
```

document		
@encoding	UTF-8	
@version	1.0	
myDoc		
e1		
*body		e1Value2
@e1Attr		attrValue2
e2		
e3		e3Value
e4		
*body		e4Value
@e4Attr		attrValue4
@e4Attrb		attrValue4b

```
<?xml version="1.0" encoding="UTF-8"
standalone="no"?><tns:AcctInfo>
xmlns:tns="http://localhost/
DerivedAddress/
schema.xsd"xmlns:xsi="http://www
.w3.org/
2001/XMLSchema-instance"><myDoc>
<e1>e1Value</e1></myDoc>
<myDoc xsi:type="tns:DerivedDoc">
<e1>e1Value</e1><e2>e2Value</e2>
</myDoc>
</tns:AcctInfo>
```

document		
@encoding	UTF-8	
@version	1.0	
myDoc []		
myDoc[0]		
e1		e1Value
myDoc[1]		
*docType		DerivedDoc.documentLocation:docTypeRef_tns_DerivedD
e1		e1Value
e2		e2Value

xmlStringToDocument

Converts an XML string to a document. This service transforms each element and attribute in the XML string to an element in a Document.

This service will convert the following XML string:

```
<?xml version="1.0" ?>
<tns:AcctInfo>
  xmlns:tns="http://localhost/DerivedAddress/schema.xsd"
  xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
  <name>Midwest Extreme Sports</name>
  <rep>Laura M. Sanchez</rep>
  <acctNum type=platinum>G97041A</acctNum>
  <phoneNum cc=011>216-741-7566</phoneNum>
  <address country=USA>
  <street1>10211 Brook Road</street1>
  <city>Cleveland</city>
  <state>OH</state>
  <postalCode>22130</postalCode>
  </address>
  <address country=USA xsi:type="tns:DerivedAddress">
  <street1>10211 Brook Road</street1>
  <city>Cleveland</city>
  <state>OH</state>
  <postalCode>22130</postalCode>
  <landMark>Besides Ohio River-Bank Square</landMark>
  <telNo>001222555</telNo>
  </address>
  <serialNum>19970523A</serialNum>
  <serialNum>20001106G</serialNum>
  <serialNum>20010404K</serialNum>
</tns:AcctInfo>
```

To a Document that looks like:

▼ document		
@version		1.0
▼ AcctInfo		
▼ accNum		
*body		G97041A
@type		Platinum
▼ address[0]		
@country		USA
city		closed
postalCode		22130
state		OH
street1		10211 Brook Road
▼ address[1]		
*doctype		DerivedAddress.documentLocation:docTypeRef_tns_DerivedAddress
@country		USA
city		closed
landmark		Ohio River-Bank Square
postalCode		22130
state		OH
street1		10211 Brook Road
name		Midwest Extreme Sports
▼ phoneNum		
*body		216-741-7566
@cc		011
rep		Laura M. Sanchez
▼ serialNum []		
serialNum[0]		19970523A

Input Parameters

xmlString

String. XML string that is to be converted to a document.

nsDecls []

Document. Optional. Namespace prefixes to use for the conversion. This parameter specifies the prefixes that will be used when namespace-qualified elements are converted to key names in the resulting document object. For example, if you want elements belonging to a particular namespace to have the prefix GSX in the resulting

document, for example, `GSX:acctNum`, you would associate the prefix `GSX` with that namespace in `nsDecls`. This is important because incoming XML documents can use any prefix for a given namespace, but the key names expected by a target service will have a fixed prefix. Namespace prefixes in `nsDecls` also define the prefixes used by the arrays, documents, `documentTypeName`, and collect parameters. Each entry in `nsDecls` represents a namespace prefix/URI pair, where a key name represents a prefix and the value of the key specifies the namespace URI. For example, to define the URIs associated with two prefixes called `GSX` and `TxMon`, you would set `nsDecls` as follows:

▼  nsDecls []	
▼  nsDecls [0]	
 prefix *	GSX
 uri *	http://www.gsx.com
▼  nsDecls [1]	
 prefix *	TxMon
 uri *	http://www.acrtrak/tx

Parameters for `nsDecls []` are:

prefix: Key name.

uri: Key value.

`preserveUndeclaredNS`

String Optional. Flag indicating whether or not Integration Cloud keeps undeclared namespaces in the resulting document. An undeclared namespace is one that is not specified as part of the `nsDecls` input parameter.

Set to:

- `True` to preserve undeclared namespaces in the resulting document. For each namespace declaration in the XML document that is not specified in the `nsDecls` parameter, Integration Cloud adds the `xmlns` attribute as a String variable to the document. Integration Cloud gives the variable a name that begins with

"@xmlns" and assigns the variable the namespace value specified in the XML document. Integration Cloud preserves the position of the undeclared namespace in the resulting document.

- `False` to ignore namespace declarations in the XML document that are not specified in the `nsDecls` parameter. This is the default.

`preserveNSPositions`

String Optional. Flag indicating whether or not Integration Cloud maintains the position of namespaces declared in the `nsDecls` parameter in the resulting document.

Set to:

- `True` to preserve the position of namespaces declared in `nsDecls` in the resulting document. For each namespace specified in the `nsDecls` parameter, Integration Cloud adds the `xmlns` attribute to the document as a String variable named "@xmlns:NSprefix" where "NSprefix" is the prefix name specified in `nsDecls`. Integration Cloud assigns the variable the namespace value specified in the XML document. This variable maintains the position of the `xmlns` attribute declaration within the XML document.
- `False` to not maintain the position of the namespace declarations specified in `nsDecls` in the resulting document. This is the default.

`arrays []`

String List Optional. Names of elements that are to be generated as arrays, regardless of whether they appear multiple times. For example, if `arrays` contained the following values for the XML document shown in the example in the description for this service:

```
rep
address
```

`xmlStringToDocument` would generate element `rep` as a String List and element `address` as a Document List.

Important you include namespace prefixes in the element names that you specify in `arrays`, you must define the namespaces associated with those prefixes in `nsDecls`.

makeArrays

String Optional. Flag indicating whether you want `xmlStringToDocument` to automatically create an array for every element that appears more than once. Set to:

- `true` to automatically create arrays for every element that appears more than once. This is the default.
- `false` to create arrays for only those elements specified in *arrays*.

Output Parameters

document **Document.** Document representation of nodes and attributes in node.

Usage Notes

Following are examples of XML documents and the documents that `xmlStringToDocument` will produce:

XML Document	Document
<pre><myDoc><e1>e1Value</e1> </myDoc></pre>	<pre> document └── myDoc └── e1 └── e1Value </pre>
<pre><?xml version="1.0" encoding="UTF-8" standalone="no"?><myDoc><e1> e1Value</e1></myDoc></pre>	<pre> document ├── @encoding UTF-8 ├── @standalone no ├── @version 1.0 └── myDoc └── e1 └── e1Value </pre>

```
<?xml version="1.0" encoding="UTF-8"
standalone="no"?><myDoc>
<e1 e1Attr="attrValue">
e1Value</e1></myDoc>
```

▼ document		
STR @encoding		UTF-8
STR @standalone		no
STR @version		1.0
▼ myDoc		
▼ e1		
STR *body		e1Value
STR @e1Attr		attrValue

```
<?xml version="1.0" encoding="UTF-8"
standalone="no"?><myDoc><e1>
e1Value</e1><e2>e2Value</e2>
</myDoc>
```

▼ document		
STR @encoding		UTF-8
STR @standalone		no
STR @version		1.0
▼ myDoc		
STR e1		e1Value
STR e2		e2Value

```
<?xml version="1.0" encoding="UTF-8"
standalone="no"?><myDoc><e1>e1Value1
</e1><e2>e2Value</e2><e1>
e1Value2</e1></myDoc>
```

▼ document		
STR @encoding		UTF-8
STR @standalone		no
STR @version		1.0
▼ myDoc		
STR e1		e1Value1
STR e2		e2Value

```
<?xml version="1.0"encoding="UTF-8"?>  
<myDoc><e1 e1Attr="attrValue1">  
e1Value1</e1><e2>e2Value</e2>  
<e1 e1Attr="attrValue2">  
e1Value2</e1></myDoc>
```

document		
@encoding	UTF-8	
@version	1.0	
myDoc		
e1 []		
e1[0]		
*body		e1Value1
@e1Attr		attrValue1
e1[1]		
*body		e1Value2
@e1Attr		attrValue2
e2		e2Value

```
<?xml version="1.0"encoding="UTF-8"?>  
<myDoc><e1 e1Attr="attrValue1">  
e1Value1</e1><e2>e2Value</e2>  
<e1 e1Attr="attrValue2">  
e1Value2</e1></myDoc>
```

document		
@encoding	UTF-8	
@version	1.0	
myDoc		
e1 []		
e1[0]		
*body		e1Value1
@e1Attr		attrValue1
e1[1]		
*body		e1Value2
@e1Attr		attrValue2
e2		e2Value

```
<?xml version="1.0"encoding="UTF-8"?>
<myDoc><e1 e1Attr="attrValue1">
e1Value1</e1><e2>e2Value</e2>
<e1 e1Attr="attrValue2">
e1Value2</e1></myDoc>
```

document		
@encoding	UTF-8	
@version	1.0	
myDoc		
e1		
*body		e1Value2
@e1Attr		attrValue2
e2		e2Value

```
<?xml version="1.0"encoding="UTF-8"?>
<myDoc><e1 e1Attr="attrValue1">
e1Value1</e1><e2><e3>e3Value
</e3><e4 e4Attr="attrValue4"
e4Attrb=
"attrValue4b">e4Value</e4>
</e2></myDoc>
```

document		
@encoding	UTF-8	
@version	1.0	
myDoc		
e1		
*body		e1Value2
@e1Attr		attrValue2
e2		
e3		e3Value
e4		
*body		e4Value
@e4Attr		attrValue4
@e4Attrb		attrValue4b

```
<?xml version="1.0" encoding="UTF-8"
standalone="no"?><tns:AcctInfo>
xmlns:tns="http://localhost/
DerivedAddress/
schema.xsd"xmlns:xsi="http:
//www.w3.org/2001/
XMLSchema-instance"><myDoc>
<e1>e1Value</e1></myDoc>
<myDoc xsi:type="tns:DerivedDoc">
<e1>e1Value</e1><e2>e2Value
</e2></myDoc>
</tns:AcctInfo>
```

document		
@encoding	UTF-8	
@version	1.0	
myDoc []		
myDoc[0]		
e1		e1Value
myDoc[1]		
*docType		DerivedDoc.documentLocation:docTypeRef_tns_DerivedD
e1		e1Value
e2		e2Value

xmlStringToXMLNode

Converts a String, byte[], or InputStream containing an XML document to an XML node. An XML node is a representation of an XML document that can be consumed by Integration Cloud.

Input Parameters

<i>xmldata</i>	<p>String Optional. String containing the XML document to convert to an XML node.</p> <p>Note: If you specify <i>xmldata</i>, do not specify <i>\$filedata</i> or <i>\$filestream</i>.</p>
<i>\$filedata</i>	<p>byte[] Optional. byte[] containing the XML document to convert to an XML node.</p> <p>Note: If you specify <i>\$filedata</i>, do not specify <i>xmldata</i> or <i>\$filestream</i>.</p>
<i>\$filestream</i>	<p>java.io.InputStream Optional. InputStream containing the XML document to convert to an XML node.</p> <p>Note: If you specify <i>\$filestream</i>, do not specify <i>xmldata</i> or <i>\$filedata</i>.</p>
<i>encoding</i>	<p>String Optional. Character encoding in which text is represented. Specify UTF-8 for XML files and ISO-8859-1 for HTML files. To have the parser attempt to detect the type of encoding, specify <i>autoDetect</i> (which is the default, if <i>encoding</i> is not specified).</p>
<i>isXML</i>	<p>String Optional. Flag specifying whether the input document is XML or HTML. (<i>xmlStringToXMLNode</i> must know this so that it can parse the document correctly.) Set to:</p> <ul style="list-style-type: none"> ■ <i>autoDetect</i> to parse the document based on its type. When you use this option, <i>xmlStringToXMLNode</i> detects the document's type based on its document type declaration as indicated by a <code><!DOCTYPE... \></code> or <code><?XML... \></code> tag. If it cannot determine the document type, it parses it as HTML. This is the default. ■ <i>true</i> to parse the document as XML. ■ <i>false</i> to parse the document as HTML.

Output Parameters

node **com.wm.lang.xml.Node** XML node representation of the XML document in *xmlData* . This object can be used as input to webMethods services that consume XML nodes.

Usage Notes

The input parameters *xmlData* , *\$filedata* , and *\$filestream* are mutually exclusive. Specify only one of the preceding parameters. Integration Cloud checks the parameters in the following order: *\$filedata* , *\$filestream* , and *xmlData* , and uses the value of the first parameter with a value.

getXMLNodeType

Returns information about an XML node.

Input Parameters

rootNode **com.wm.lang.xml.Document** XML node about which you want information.

Output Parameters

systemID **String** Conditional. System identifier, as provided by the DTD associated with *rootNode* . If *rootNode* does not have a system identifier, this value is null.

publicID **String** Conditional. Public identifier, as provided by the DTD associated with *rootNode* . If *rootNode* does not have a public identifier, this value is null.

rootNamespace **String** URI of the XML namespace to which *rootNode*'s root element belongs.

rootNSPrefix **String** Conditional. Namespace prefix of root element in *rootNode* , if any.

rootLocalName **String** Conditional. Local name (excluding the namespace prefix) of the root element in *rootNode* , if any.

queryXMLNode

Queries an XML node.

The *fields* parameter specifies how data is extracted from the node to produce an output variable. This output variable is called a "binding," because the *fields* parameter binds a certain part of the document to a particular output variable. At run time, this service must include at least one *fields* entry. The service must include at least one entry in *fields*. The result of each query you specify in *fields* is returned in a variable whose name and type you specify.

Input Parameters

node The XML node that you want to query. This parameter supports the following types of input:

- **com.wm.lang.xml.Node** XML node that you want to query. An XML node can be produced by `xmlStringToXMLNode` or an XML content handler.

nsDecls **Document** Optional. Namespaces associated with any namespace prefixes used element to specify elements in *fields/query*. Each entry in *nsDecls* represents a namespace prefix/URI pair, where a key name represents a prefix and the value of the key specifies the namespace URI.

For example, to define the URIs associated with two prefixes called `GSX` and `TxMon`, you would set *nsDecls* as follows:



fields **Document List** Optional. Parameters describing how data is to be extracted from *node*. Each document in the list contains parameters for a single query, as follows:

Key	Description
<i>name</i>	String Name to assign to resulting value.
<i>resultType</i>	String Object type that the query is to yield. The following shows the allowed values for <i>resultType</i> .

	<u>Underlying Value</u>	<u>Corresponding Data Type</u>
	Object	Object
	Object[]	Object List
	Record	Document
	Record[]	Document List
	String	String
	String[]	String List
	String[][]	String Table
<i>query</i>	String Query identifying the data to be extracted from <i>node</i> .	
<i>queryType</i>	String Query language in which <i>query</i> is expressed. Valid values are <code>WQL</code> and <code>XQL</code> .	
<i>onnull</i>	<p>String Code indicating what you want <code>queryXMLNode</code> to do when the result is null. Set to one of the following:</p> <ul style="list-style-type: none"> ■ <code>continue</code> to indicate that all result values are acceptable for this query (including null). ■ <code>fail</code> to indicate that the service should fail if the result of this query is null and continue in all other cases. ■ <code>succeed</code> to indicate that the service should continue if the result of this query is null and fail in all other cases. 	
<i>fields[]</i>	Document List Parameters that support recursive execution of bindings. Each <i>fields</i> list defines bindings for one level of the output with the top level being the pipeline and the first level down being contents of a document or document list in the pipeline.	

Output Parameters

Document Results from the queries specified in *fields*. This service returns one element for each query specified in *fields*. The specific names and types of the returned elements are determined by the *fields/name* and *field/resultType* parameters of the individual queries.

Usage Notes

If `queryXMLNode` fails, it throws an exception. Common reasons for `queryXMLNode` to fail include:

- A variable that has no query string assigned to it.
- A syntax error in a query string.
- A query fails the “Allows Null” test.
- The node variable does not exist or it is null.

IO

Use **IO** services to convert data between `byte[]`, characters, and `InputStream` representations. These services are used for reading and writing bytes, characters, and streamed data to the file system. These services behave like the corresponding methods in the `java.io.InputStream` class. These services can be invoked only by other services. Streams cannot be passed between clients and the server, so these services will not execute if they are invoked from a client.

The following **IO** services are available:

Service	Description
bytesToStream	Converts a <code>byte[]</code> to <code>java.io.ByteArrayInputStream</code> .
streamToBytes	Creates a <code>byte[]</code> from data that is read from an <code>InputStream</code> .
streamToString	Creates a string from data that is read from an <code>InputStream</code> .
stringToStream	Converts a string to a binary stream.

bytesToStream

Converts a `byte[]` to `java.io.ByteArrayInputStream`.

Input Parameters

<i>bytes</i>	byte[] The byte array to convert.
<i>length</i>	String Optional. The maximum number of bytes to read and convert. If <i>length</i> is not specified, the default value for this parameter is the length of the input byte array.
<i>offset</i>	String Optional. The offset into the input byte array from which to start converting. If no value specified, the default value is zero.

Output Parameters

<i>stream</i>	java.io.ByteArrayInputStream An open <code>InputStream</code> created from the contents of the input <i>bytes</i> parameter.
---------------	---

Usage Notes

This service constructs *stream* from the byte array using the constructor `ByteArrayInputStream(byte[])`. This constructor does not make a copy of the byte array, so any changes to *bytes* will be reflected in the data read from the stream.

streamToBytes

Creates a `byte[]` from data that is read from an `InputStream`.

Input Parameters

<i>stream</i>	java.io.InputStream The <code>InputStream</code> that you want to convert.
---------------	---

Output Parameters

<i>bytes</i>	byte[] The bytes read from <i>stream</i> .
--------------	--

Usage Notes

This service reads all of the bytes from *stream* until the end of file is reached, and then it closes the `InputStream`.

streamToString

Creates a string from data that is read from an `InputStream`.

Input Parameters

<i>inputStream</i>	java.io.InputStream The <code>InputStream</code> to convert to a string.
<i>encoding</i>	String Optional. Name of a registered, IANA character set (for example, ISO-8859-1). If you specify an unsupported encoding, the system throws an exception. If no value is specified the encoding will be UTF-8.

Output Parameters

<i>string</i>	String Data read from <i>inputStream</i> and converted to a string.
---------------	--

stringToStream

Converts a string to a binary stream.

Input Parameters

<i>string</i>	String The string object to be converted.
<i>encoding</i>	String Optional. Name of a registered, IANA character set, for example, ISO-8859-1. If you specify an unsupported encoding, the system throws an exception. If no value is specified, the encoding will be UTF-8.

Output Parameters

<i>inputStream</i>	java.io.ByteArrayInputStream An open <code>InputStream</code> created from the contents of <i>string</i> .
--------------------	---

Utils

Contains utility services.

The following **Utils** services are available:

Service	Description
generateUUID	Generates a random Universally Unique Identifier (UUID).

generateUUID

Generates a random Universally Unique Identifier (UUID).

Input Parameters

None.

Output Parameters

UUID **String** A randomly generated Universally Unique Identifier (UUID).

10 Document Types

■ Overview	590
■ Creating Document Types from Scratch	591
■ Creating Document Types from an XML Schema Definition	593
■ About Variable Constraints	596
■ Applying Constraints to a Variable	596
■ Content Types	597
■ Customizing a String Content Type	607

Overview

A **Document Type** contains a set of fields used to define the structure and type of data in a document. You use a document type to specify the input or output parameters for an Integration.

Integration Cloud also allows you to create document types for already created REST Applications from the **Projects > <Select a Project> > Applications > REST Applications > Document Types** link or from the Request Body and Response Body panels while creating a REST Application. Document types created for a REST Application does not appear in the **Projects > <Select a Project> > Document Types** page but appears in the **Document Types** panel for the selected REST Application. Document types for REST Applications are used in the Request Body and Response Body of an **Action**.

Note: Users who have the required access privileges under **Settings  > Access Profiles > Administrative Permissions > Functional Controls > Document Types** can create, update, and delete a document type.

Document types provide the following benefits:

- Using a document type as the input or output signature for an Integration reduces the effort required to build an Integration.
- Using a document type to build document or document list fields reduces the effort and time needed to declare input or output parameters or build other document fields.
- Document types improve accuracy because there is less possibility to introduce a typing error while typing field names.
- Document types make future changes easier to implement because you make a change in one place (the Document Type) rather than everywhere the document type is used.

You use document types to define the input or output parameters for an Integration. Input and output parameters are the names and types of fields that the Integration requires as input and generates as output. These parameters are also collectively referred to as a signature. For example, an Integration takes two string values, an account number (AcctNum) and a dollar amount (OrderTotal) as inputs and produces an authorization code (AuthCode) as the output. If you have multiple Integrations with identical input parameters but different output parameters, you use a document type to define the input parameters rather than manually specifying individual input fields for each Integration.

Creating a Document Type

You can create a document type in the following ways:

- **Build from scratch:** Create an empty document type and define the structure of the document type yourself by inserting fields to define its contents and structure.

- **Build from XML schema:** Create a Document Type from a source file, such as an XML Schema. The structure and content of the document type will match that of the source file.

Creating Document Types from Scratch

To add or edit a Document Type from scratch

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > Document Types**. The **Document Types** page appears.

Note: You can create document types for already created REST Applications from the **Projects > <Select a Project> > Applications > REST Applications > Document Types** link or from the Request Body and Response Body panels while creating a REST Application.

From the **Document Types** page, you can add, edit, delete, or copy a document type.

2. To edit an existing document type, select a document type from the **Document Types** page and click **Edit**. Select a field to view the **Field Properties** panel.
3. To create a new document type from scratch, from the **Document Types** page, click **Add New Document Type > Build from scratch**.
4. Provide a name and description of your document type. Required fields are marked with an asterisk on the page.
5. Click **Load XML** to generate a document type from the XML structure or click **Load JSON** to generate a document type from the JSON structure.
6. Click the **+** icon to add a new field. You can update the field properties by using the **Field Properties** window.

Provide the **Name** and **Type** of the field in order to define the structure and content of the document type. A field can be a String, Document, Document Reference, Object,

Boolean, Double, Float, Integer, Long, or Short. If you select Document Reference, select the **Document Reference**. Fields are used to declare the expected content and structure of Integration signatures, document contents, and pipeline contents. In addition to specifying the name and type of a field, and whether the type is an **Array**, you can set properties that specify an **XML Namespace** and indicate whether the field is required at runtime by selecting the **Required** option. Select the **Content Type** you can apply to String, String list, or String table variables. See [“About Variable Constraints” on page 596](#) for information.

You can copy a field from the fields panel by clicking the  icon. Depending on the context, you can either paste the field or the field path by clicking the  icon. For example, if you copy a field and paste the field in the **Set Value** window in an Integration, the field path will be pasted. If you copy an array item, the path that is pasted includes the item index. For example, if the item that is copied is A/B/C[10], then the pasted path will also include the item index [10]. But if it is pasted in the document tree, it will appear as an array, like A[]. If there are multiple fields with the same name in a document, and one of the occurrences of such a field is copied, then the path when pasted will contain the occurrence number in brackets, for example, the path will be A/B/C(5) if the copied element C is the 5th occurrence under field B.

Note: You cannot modify or paste the child fields of a Document Reference.

Note: When defining a document type, avoid adding identically named fields to the document. In particular, do not add identically named fields that are of the same data type.

You can assign an **XML namespace** and prefix to a field by specifying a URI for the XML namespace property and by using the *prefix:fieldName* format for the field name. For example, suppose a field is named *eg:account* and the XML namespace property is set to `http://www.example.com`. The prefix is *eg*, the localname is *account*, and the namespace name is `http://www.example.com`.

Keep the following points in mind when assigning XML namespaces and prefixes to a field:

- The field name must be in the format: *prefix:fieldName*
 - You must specify a URI in the XML namespace property.
 - Do not use the same prefix for different namespaces in the same document type, input signature, or output signature.
7. Click **Apply** after you have entered the details and constraints for each field, and then click **Save** to save the **Document Type**.

Note: When you edit a document type, any change is automatically propagated to all Integrations that use or reference the document type.

The new document type appears in the **Document Types** page.

Creating Document Types from an XML Schema Definition

Keep the following point in mind when creating a document type from an XML Schema Definition:

- You can specify whether Integration Cloud enforces strict, lax, or no content model compliance when generating the document type. Content models provide a formal description of the structure and allowed content for a complex type. The type of compliance that you specify can affect whether Integration Cloud generates a document type from a particular XML Schema definition successfully. Currently, Integration Cloud does not support repeating model groups, nested model groups, or the *any* attribute. If you select strict compliance, Integration Cloud does not generate a document type from any XML schema definition that contains those items.

To create a document type from an XML Schema definition

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > Document Types**. The **Document Types** page appears.
From the **Document Types** page, you can add, edit, delete, or copy a document type.
2. To edit an existing document type, select a document type from the **Document Types** page and click **Edit**.
3. To create a new document type from an XML Schema Definition, from the **Document Types** page, click **Add New Document Type > Build from XML schema**.
4. Provide a name of your document type. Required fields are marked with an asterisk on the page.
5. On the **Specify the location of the XML schema file** panel, under **XML schema source**, do one of the following to specify the source file for the document type:
 - To use an XML Schema definition that resides on the Internet as the source, select **URL**. Then, type the URL of the resource. (The URL you specify must begin with `http:` or `https:.`)
 - To use an XML Schema definition that resides on your local file system as the source, select **File**. Then click **Browse** and select the file. The maximum file upload size is 5 MB.
6. Click **Next** and on the **Select schema-related processing options** panel, under **Content model compliance**, select one of the following to indicate how strictly Integration Cloud represents content models from the XML Schema definition in the resulting document type.

Select...	To...
Strict	<p>Generate the document type only if Integration Cloud can represent the content models defined in the XML Schema definition correctly. Document type generation fails if Integration Cloud cannot accurately represent the content models in the source XML Schema definition.</p> <p>Currently, Integration Cloud does not support repeating model groups, nested model groups, or any attribute. If you select strict compliance, Integration Cloud does not generate a document type from any XML schema definition that contains those items.</p>
Lax	<p>When possible, generate a document type that correctly represents the content models for the complex types defined in the XML schema definition. If Integration Cloud cannot correctly represent the content model in the XML Schema definition in the resulting document type, Integration Cloud generates the document type using a compliance mode of None.</p> <p>When you select lax compliance, Integration Cloud will generate the document type even if the content models in the XML schema definition cannot be represented correctly.</p>
None	<p>Generate a document type that does not necessarily represent or maintain the content models in the source XML Schema definition.</p>

7. If you select strict or lax compliance, next to **Preserve text position**, do one of the following to specify whether document types generated will contain multiple **body* fields to preserve the location of text in instance documents.
 - Select the **Preserve text position** check box to indicate that the document type generated preserves the locations for text in instance documents. The resulting document type contains a **body* field after each field and includes a leading **body* field. In instance documents for this document type, Integration Cloud places text that appears after a field in the **body*.
 - Clear the **Preserve text position** check box to indicate that the document type generated does not preserve the locations for text in instance documents. The resulting document type contains a single **body* field at the top of the document type. In instance documents for this document type, text data around fields is all placed in the same **body* field.
8. If you want Integration Cloud to use the Xerces parser to validate the XML Schema definition, select the **Validate schema using Xerces** check box.

Note: Integration Cloud automatically uses an internal schema parser to validate the XML Schema definition. However, the Xerces parser provides stricter validation than the internal schema parser. As a result, some schemas that the internal schema parser considers to be valid might be considered invalid by the Xerces parser.

9. Click **Next** and on the **Select root nodes** panel, under **Select root nodes**, select the elements that you want to use as the root elements for the document type. The resulting document type will contain all of the selected root elements as top-level fields in the generated document type. To select multiple elements, press the CTRL key while selecting elements.
10. Click **Finish**.

Integration Cloud creates the document type.

Notes

- If you have selected strict compliance and Integration Cloud cannot represent the content model in the complex type accurately, Integration Cloud does not generate any document type.
- If you have selected lax compliance and indicated that Integration Cloud should preserve text locations for content types that allow mixed content (you selected the **Preserve text position** check box), Integration Cloud adds *body fields in the document type only if the complex type allows mixed content and Integration Cloud can correctly represent the content model declared in the complex type definition. If Integration Cloud cannot represent the content model in a document type, Integration Cloud adds a single *body field to the document type.
- If the XML schema definition contains an element reference to an element declaration whose type is a named complex type definition (as opposed to an anonymous complex type definition), Integration Cloud creates a document type for the named complex type definition only if it is referred multiple times in the schema.
- Integration Cloud uses the prefixes declared in the XML Schema or the ones you specified as part of the field names. Field names have the format *prefix:elementName* or *prefix:@attributeName*.
- If the XML Schema does not use prefixes, Integration Cloud creates prefixes for each unique namespace and uses those prefixes in the field names. Integration Cloud uses “ns” as the prefix for the first namespace, “ns1” for the second namespace, “ns2”.
- If the XML Schema definition contains a user-specified namespace prefix and a default namespace declaration, both pointing to the same namespace URI, Integration Cloud uses the user-specified namespace prefix and not the default namespace.

- If the namespace prefix in the XML Schema as well as the default namespace point to the same namespace URI, Integration Cloud gives preference to the user-specified namespace prefix over the default namespace.

About Variable Constraints

You apply content constraints to variables in the document types that you want to use as blueprints in data validation. Content constraints describe the data a variable can contain. At validation time, if the variable value does not conform to the content constraints applied to the variable, the validation engine considers the value to be invalid.

When applying content constraints to variables, do the following:

- **Select a content type** - A content type specifies the type of data for the variable value, such as string, integer, boolean, or date. A content type corresponds to a simple type definition in a schema.
- **Set constraining facets** - Constraining facets restrict the content type, which in turn, restrict the value of the variable to which the content type is applied. Each content type has a set of constraining facets. For example, you set a length restriction for a string content type, or a maximum value restriction for an integer content type.

For example, for a String variable named *itemQuantity*, specify a content type that requires the variable value to be an integer. You could then set constraining facets that limit the content of *itemQuantity* to a value between 1 and 100.

The content types and constraining facets described in this appendix correspond to the built-in data types and constraining facets in XML Schema. The World Wide Web Consortium (W3C) defines the built-in data types and constraining facets in the specification *XML Schema Part 2: Datatypes* ("<http://www.w3c.org/TR/xmlschema-2>").

Applying Constraints to a Variable

You apply content constraints to variables in the document types that you want to use as blueprints in data validation.

To apply constraints to a variable

1. Select a document type from the **Document Types** page and click **Edit**. Select a field to view the **Field Properties** panel.

You apply constraints to variables in document types declared on the Input/Output tab. If the selected variable is a String or String list and you want to specify content constraints for the variable, then do the following:

- If you want to use a content type that corresponds to a built-in simple type in XML schema, in the **Content type** list, select the type for the variable contents. To apply the selected type to the variable, click **Save**.

- Repeat this procedure for each variable to which you want to apply the constraints in the document type and click **Save**.

Content Types

The following table identifies the content types you can apply to String or String list variables. Each of these content types corresponds to a built-in simple type defined in the specification *XML Schema Part 2: Datatypes*.

Content Types	Description
anyURI	<p>A Uniform Resource Identifier Reference. The value of anyURI may be absolute or relative.</p> <p>Constraining Facets</p> <p>enumeration, length, maxLength, minLength, pattern</p> <p>Note: The anyURI type indicates that the variable value plays the role of a URI and is defined like a URI. webMethods Integration Server does not validate URI references because it is impractical for applications to check the validity of a URI reference.</p>
base64Binary	<p>Base64-encoded binary data.</p> <p>Constraining Facets</p> <p>enumeration, length, maxLength, minLength, pattern</p>
boolean	<p>True or false.</p> <p>Constraining Facets</p> <p>pattern</p> <p>Example</p> <pre>true, 1, false, 0</pre>
byte	<p>A whole number whose value is greater than or equal to -128 but less than or equal to 127.</p> <p>Constraining Facets</p> <p>enumeration, fractionDigits, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern, totalDigits</p> <p>Example</p> <pre>-128, -26, 0, 15, 125</pre>

Content Types	Description
date	<p>A calendar date from the Gregorian calendar. Values need to match the following pattern:</p> <p>CCYY-MM-DD</p> <p>Where CC represents the century, YY the year, MM the month, DD the day. The pattern can include a Z at the end to indicate Coordinated Universal Time or to indicate the difference between the time zone and coordinated universal time.</p> <p>Constraining Facets</p> <p>enumeration, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern</p> <p>Example</p> <p>1997-08-09 (August 9, 1997)</p>
dateTime	<p>A specific instant of time (a date and time of day). Values need to match the following pattern:</p> <p>CCYY-MM-DDThh:mm:ss.sss</p> <p>Where CC represents the century, YY the year, MM the month, DD the day, T the date/time separator, hh the hour, mm the minutes, and ss the seconds. The pattern can include a Z at the end to indicate Coordinated Universal Time or to indicate the difference between the time zone and coordinated universal time.</p> <p>Constraining Facets</p> <p>enumeration, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern</p> <p>Example</p> <p>2000-06-29T17:30:00-05:00 represents 5:30 pm Eastern Standard time on June 29, 2000. (Eastern Standard Time is 5 hours behind Coordinated Universal Time.)</p>
decimal	<p>A number with an optional decimal point.</p> <p>Constraining Facets</p> <p>enumeration, fractionDigits, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern, totalDigits</p> <p>Example</p> <p>8.01, 290, -47.24</p>

Content Types	Description
double	<p>Double-precision 64-bit floating point type.</p> <p>Constraining Facets</p> <p>enumeration, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern</p> <p>Example</p> <pre>6.02E23, 3.14, -26, 1.25e-2</pre>
duration	<p>A length of time. Values need to match the following pattern:</p> <p><i>Pn Yn Mn DTn Hn MnS</i></p> <p>Where <i>n Y</i> represents the number of years, <i>n M</i> the number of months, <i>n D</i> the number of days, T separates the date and time, <i>n H</i> the number of hours, <i>n M</i> the number of minutes and <i>nS</i> the number of seconds. Precede the duration with a minus (-) sign to indicate a negative duration.</p> <p>Constraining Facets</p> <p>enumeration, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern</p> <p>Example</p> <p>P2Y10M20DT5H50M represents a duration of 2 years, 10 months, 20 days, 5 hours, and 50 minutes</p>
ENTITIES	<p>Sequence of whitespace-separated ENTITY values declared in the DTD. Represents the ENTITIES attribute type from the XML 1.0 Recommendation.</p> <p>Constraining Facets</p> <p>enumeration, length, maxLength, minLength</p>
ENTITY	<p>Name associated with an unparsed entity of the DTD. Represents the ENTITY attribute type from the XML 1.0 Recommendation.</p> <p>Constraining Facets</p> <p>enumeration, length, maxLength, minLength, pattern, whiteSpace</p>
float	<p>A number with a fractional part.</p> <p>Constraining Facets</p>

Content Types	Description
	<p>enumeration, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern</p> <p>Example</p> <p>8.01, 25, 6.02E23, -5.5</p>
gDay	<p>A specific day that recurs every month. Values must match the following pattern:</p> <p>---DD</p> <p>Where DD represents the day. The pattern can include a Z at the end to indicate Coordinated Universal Time or to indicate the difference between the time zone and coordinated universal time.</p> <p>Constraining Facets</p> <p>enumeration, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern</p> <p>Example</p> <p>---24 indicates the 24th of each month</p>
gMonth	<p>A Gregorian month that occurs every year. Values must match the following pattern:</p> <p>--MM</p> <p>Where MM represents the month. The pattern can include a Z at the end to indicate Coordinated Universal Time or to indicate the difference between the time zone and coordinated universal time.</p> <p>Constraining Facets</p> <p>enumeration, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern</p> <p>Example</p> <p>--11 represents November</p>
gMonthDay	<p>A specific day and month that recurs every year in the Gregorian calendar. Values must match the following pattern:</p> <p>--MM-DD</p> <p>Where MM represents the month and DD represents the day. The pattern can include a Z at the end to indicate Coordinated</p>

Content Types	Description
	<p>Universal Time or to indicate the difference between the time zone and coordinated universal time.</p> <p>Constraining Facets</p> <p>enumeration, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern</p> <p>Example</p> <p>--09-24 represents September 24th</p>
gYear	<p>A specific year in the Gregorian calendar. Values must match the following pattern:</p> <p>CCYY</p> <p>Where CC represents the century, and YY the year. The pattern can include a Z at the end to indicate Coordinated Universal Time or to indicate the difference between the time zone and coordinated universal time.</p> <p>Constraining Facets</p> <p>enumeration, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern</p> <p>Example</p> <p>2001 indicates 2001</p>
gYearMonth	<p>A specific month and year in the Gregorian calendar. Values must match the following pattern:</p> <p>CCYY-MM</p> <p>Where CC represents the century, YY the year, and MM the month. The pattern can include a Z at the end to indicate Coordinated Universal Time or to indicate the difference between the time zone and coordinated universal time.</p> <p>Constraining Facets</p> <p>enumeration, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern</p> <p>Example</p> <p>2001-04 indicates April 2001</p>
hexBinary	<p>Hex-encoded binary data.</p> <p>Constraining Facets</p>

Content Types	Description
	enumeration, length, maxLength, minLength, pattern
ID	<p>A name that uniquely identifies an individual element in an instance document. The value for ID needs to be a valid XML name. The ID datatype represents the ID attribute type from the XML 1.0 Recommendation.</p> <p>Constraining Facets</p> <p>enumeration, length, maxLength, minLength, pattern, whiteSpace</p>
IDREF	<p>A reference to an element with a unique ID. The value of IDREF is the same as the ID value. The IDREF datatype represents the IDREF attribute type from the XML 1.0 Recommendation.</p> <p>Constraining Facets</p> <p>enumeration, length, maxLength, minLength, pattern, whiteSpace</p>
IDREFS	<p>Sequence of white space separated IDREFs used in an XML document. The IDREFS datatype represents the IDREFS attribute type from the XML 1.0 Recommendation.</p> <p>Constraining Facets</p> <p>enumeration, length, maxLength, minLength</p>
int	<p>A whole number with a value greater than or equal to -2147483647 but less than or equal to 2147483647.</p> <p>Constraining Facets</p> <p>enumeration, fractionDigits, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern, totalDigits</p> <p>Example</p> <p>-21474836, -55500, 0, 33123, 4271974</p>
integer	<p>A positive or negative whole number.</p> <p>Constraining Facets</p> <p>enumeration, fractionDigits, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern, totalDigits</p> <p>Example</p> <p>-2500, -5, 0, 15, 365</p>

Content Types	Description
language	<p>Language identifiers used to indicate the language in which the content is written. Natural language identifiers are defined in IETF RFC 1766.</p> <p>Constraining Facets</p> <p>enumeration, length, maxLength, minLength, pattern, whiteSpace</p>
long	<p>A whole number with a value greater than or equal to -9223372036854775808 but less than or equal to 9223372036854775807.</p> <p>Constraining Facets</p> <p>enumeration, fractionDigits, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern, totalDigits</p> <p>Example</p> <p><code>-55600, -23, 0, 256, 3211569432</code></p>
Name	<p>XML names that match the Name production of XML 1.0 (Second Edition).</p> <p>Constraining Facets</p> <p>enumeration, length, maxLength, minLength, pattern, whiteSpace</p>
NCName	<p>Non-colonized XML names. Set of all strings that match the NCName production of Namespaces in XML.</p> <p>Constraining Facets</p> <p>enumeration, length, maxLength, minLength, pattern, whiteSpace</p>
negativeInteger	<p>An integer with a value less than or equal to -1.</p> <p>Constraining Facets</p> <p>enumeration, fractionDigits, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern, totalDigits</p> <p>Example</p> <p><code>-255556, -354, -3, -1</code></p>
NMTOKEN	<p>Any mixture of name characters. Represents the NMTOKEN attribute type from the XML 1.0 Recommendation.</p> <p>Constraining Facets</p>

Content Types	Description
	enumeration, length, maxLength, minLength, pattern, whiteSpace
NMTOKENS	<p>Sequences of NMTOKENS. Represents the NMTOKENS attribute type from the XML 1.0 Recommendation.</p> <p>Constraining Facets</p> <p>enumeration, length, maxLength, minLength</p>
nonNegativeInteger	<p>An integer with a value greater than or equal to 0.</p> <p>Constraining Facets</p> <p>enumeration, fractionDigits, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern, totalDigits</p> <p>Example</p> <p>0, 15, 32123</p>
nonPositiveInteger	<p>An integer with a value less than or equal to 0.</p> <p>Constraining Facets</p> <p>enumeration, fractionDigits, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern, totalDigits, whiteSpace</p> <p>Example</p> <p>-256453, -357, -1, 0</p>
normalizedString	<p>Represents white space normalized strings. Set of strings (sequence of UCS characters) that do not contain the carriage return (#xD), line feed (#xA), or tab (#x9) characters.</p> <p>Constraining Facets</p> <p>enumeration, length, maxLength, minLength, pattern, whiteSpace</p> <p>Example</p> <p>MAB-0907</p>
positiveInteger	<p>An integer with a value greater than or equal to 1.</p> <p>Constraining Facets</p> <p>enumeration, fractionDigits, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern, totalDigits</p> <p>Example</p> <p>1, 1500, 23000</p>

Content Types	Description
short	<p>A whole number with a value greater than or equal to -32768 but less than or equal to 32767.</p> <p>Constraining Facets</p> <p>enumeration, fractionDigits, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern, totalDigits</p> <p>Example</p> <pre>-32000, -543, 0, 456, 3265</pre>
string	<p>Character strings in XML. A sequence of UCS characters (ISO 10646 and Unicode). By default, all white space is preserved for variables with a string content constraint.</p> <p>Constraining Facets</p> <p>enumeration, length, maxLength, minLength, pattern, whiteSpace</p> <p>Example</p> <pre>MAB-0907</pre>
time	<p>An instant of time that occurs every day. Values must match the following pattern:</p> <pre>hh:mm:ss.sss</pre> <p>Where hh indicates the hour, mm the minutes, and ss the seconds. The pattern can include a Z at the end to indicate Coordinated Universal Time or to indicate the difference between the time zone and coordinated universal time.</p> <p>Constraining Facets</p> <p>enumeration, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern</p> <p>Example</p> <pre>18:10:00-05:00 (6:10 pm, Eastern Standard Time) Eastern Standard Time is 5 hours behind Coordinated Universal Time.</pre>
token	<p>Represents tokenized strings. Set of strings that do not contain the carriage return (#xD), line feed (#xA), or tab (#x9) characters, leading or trailing spaces (#x20), or sequences of two or more spaces.</p> <p>Constraining Facets</p>

Content Types	Description
	enumeration, length, maxLength, minLength, pattern, whiteSpace
unsignedByte	<p>A whole number greater than or equal to 0, but less than or equal to 255.</p> <p>Constraining Facets</p> <p>enumeration, fractionDigits, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern, totalDigits</p> <p>Example</p> <p>0, 112, 200</p>
unsignedInt	<p>A whole number greater than or equal to 0, but less than or equal to 4294967295.</p> <p>Constraining Facets</p> <p>enumeration, fractionDigits, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern, totalDigits</p> <p>Example</p> <p>0, 22335, 123223333</p>
unsignedLong	<p>A whole number greater than or equal to 0, but less than or equal to 18446744073709551615.</p> <p>Constraining Facets</p> <p>enumeration, fractionDigits, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern, totalDigits</p> <p>Example</p> <p>0, 2001, 3363124</p>
unsignedShort	<p>A whole number greater then or equal to 0, but less than or equal to 65535.</p> <p>Constraining Facets</p> <p>enumeration, fractionDigits, maxExclusive, maxInclusive, minExclusive, minInclusive, pattern, totalDigits</p> <p>Example</p> <p>0, 1000, 65000</p>

Customizing a String Content Type

Instead of applying an existing content type or simple type to a String or String list, you can customize an existing type and apply the new, modified type to a variable. You customize a content type or simple type by changing the constraining facets applied to the type.

When you customize a type, you actually create a new content type. Designer saves the changes as a new content type. The constraining facets you can specify depend on the content type. Note that content types and constraining facets correspond to datatypes and constraining facets defined in XML Schema. For more information about constraining facets for a datatype, see the specification *XML Schema Part 2: Datatypes* ("<http://www.w3.org/TR/xmlschema-2/>").

To customize a content type

1. Select the variable to which you want to apply a customized content type.
2. In the **Constraints** category on the Properties view, click the **Content type** browse button and then do one of the following to select the content type you want to customize:
 - In the **Content type** list, select the content type you want to customize.
 - If you want to customize a simple type from an IS schema, click **Browse**. In the Browse dialog box, select the IS schema containing the simple type. Then, select the simple type you want to customize and apply to the variable. Click **OK**.
3. Click **Customize**. Designer makes the constraining facet fields below the **Content type** list available for data entry (that is, changes the background of the constraining facet fields from grey to white). Designer changes the name of the content type to *contentType_customized*.
4. In the fields below the **Content type** list, specify the constraining facet values you want to apply to the content type.
5. Click **OK**. Designer saves the changes as a new content type named *contentType_customized*.

Note: The constraining facets displayed below the **Content type** list depend on the primitive type from which the simple type is derived. *Primitive types* are the basic data types from which all other data types are derived. For example, if the primitive type is string, Designer displays the constraining facets **enumeration**, **length**, **minLength**, **maxLength**, and **pattern**. For more information about primitive types, refer to *XML Schema Part 2: Datatypes* at "<http://www.w3.org/TR/xmlschema-2/>".

11 Upgrade assets

- How to upgrade assets 610

How to upgrade assets

You can upgrade assets, for example, Accounts, Operations, and the associated Integrations which uses those assets, from a lower version to a higher version. When an upgrade is available for a version, the upgrade notification text *Upgrade available for this version*, appears beside the relevant Application on the **Applications** screen, else the message *This is the latest version* appears.

Note: Users who have the **Upgrade** permission under **Settings**  > **Access Profiles** > **Administrative Permissions** > **Functional Controls** > **Application** can perform the upgrade task.

If an upgrade is available for a version, and if you click the **Add New Account** button on the Application specific Accounts screen, a dialog box appears where you can either select **Upgrade** to start the asset upgrade process or select **Skip** to add a new Account.

If you click the **Upgrade** button, the upgrade confirmation screen appears which displays the number of assets (Accounts, Operations, and the associated Integrations) that will be upgraded. The screen also displays details of all the conflicting assets. Conflicting assets are those assets that exist in the higher version with the same name.

On the upgrade confirmation screen, select **Skip** if you do not want to upgrade the conflicting assets to the higher version. You can also select to **Overwrite** if you want the conflicting assets in the higher version to be replaced with the lower version assets. Here, the higher version assets will be deleted and will be replaced with the lower version assets.

Note: The upgrade process upgrades Accounts from a lower version to a higher version only in the Development stage. If you want to reflect the upgraded Accounts in other stages in the higher version, you must *manually* configure the Accounts in the different stages from the Account configuration screen, and then **Pull** the Integration in the respective stages.

Integration Cloud performs the following tasks if you click **Upgrade** on the upgrade confirmation page:

- Migrates all the Accounts from the lower version to the higher version only in the development stage.
- Migrates all the custom Operations and predefined Operations to the latest version.
- Updates those Integrations which uses the upgraded Accounts and Operations.
- Updates Integrations only in the development stage.
- Displays the upgraded Accounts, Operations, and Integrations in the Integration Cloud **Audit Log**.
- Displays the upgrade results along with a list of all the modified Accounts, Operations, and Integrations.

- Displays a message in case of an upgrade failure and performs rollback of the Accounts, Operations, and Integrations in case of an error in the upgrade process.

12 Monitor Integrations

■ Overview	614
■ Dashboard	614
■ Execution Results	616
■ Alert Rules	618
■ Reports	620

Overview

The **Dashboard** allows you to view and monitor Integration executions and performance details. The **Execution Results** page allows you to view the audit trail of all the executions that happened in a stage for an Integration or for all Integrations for a project or for all projects. You can also create **Alert Rules** and send email messages to selected users for one or more Integrations based on Integration execution results. The **Reports** page provides you information about the number of times an Integration is run for the specified time frame.


Dashboard

The **Dashboard** provides a centralized and intuitive way to view and monitor Integration executions and performance details. To view the **Dashboard**, click **Monitor > Dashboard**.

You can identify and diagnose problems for those Integrations that are available in the active stage. To select another active stage, click **Stages > Change Stage To View**. You can view the **Dashboard** if the Access Profile assigned to you is also specified for that stage in the **Manage Stages (Stages > Manage)** page. Further, you must be able to access the stages to view the dashboard.

The **Dashboard** displays the following details:

- When was the Dashboard last refreshed.
- Options to select Projects and Integrations to view the execution details.
- Total number of documents processed by an Integration or for all Integrations in the active stage. Documents processed appear only if the Integration invokes the **countProcessedDocuments** service to count the number of documents processed by the Integration. See the **countProcessedDocuments** service available in the **Flow** block under the **Services** category for more information.



The screenshot shows a dropdown menu for selecting a service in a flow. The menu is open, and 'countProcessedDocuments' is highlighted. Other visible options include 'clearPipeline', 'getHTTPRequest', 'getLastError', 'getSessionInfo', and 'logCustomMessage'.

countProcessedDocuments

Counts the number of documents processed by an Integration. Details about the processed documents can be viewed in the Execution Results screen.

Input Parameters

<i>status</i>	String Optional valid values are "success" or "fail". Set status to "success" to count the number of successfully processed documents, else set it to "fail". Default value is "success".
---------------	---

- Number of completed and failed Integration executions that happened during the selected time period in the active stage.
- Number of Integration executions that have completed with errors during the selected time period in the active stage.
- Completed Integration executions, failed Integration executions, and Integration executions that completed with errors displayed in a pie chart, along with the **Success Rate**, that is, the percentage of completed Integration executions compared to the total Integration executions, during the selected time period in the active stage.
- Number of in-progress Integration executions in the active stage. You can click on the **In-Progress Executions** number to view the in-progress Integration execution details in a table. You can terminate in-progress Integration executions from the Execution Results details page. The *Terminate* audit log entry is created. You can terminate an in-progress Integration execution if you have the *Execute* Integration permission.

To terminate an in-progress execution, click the **Terminate** option available in the Execution Results details page.



Note: The **Terminate** option is available only if the current logged in user has the *Execute* Integration permission and the Integration status is in-progress.

- Successful Integration executions, failed Integration executions, and Integration executions that completed with errors displayed in a bar chart along with clickable links, for the selected time period in the active stage. You can click the Integration execution links available above the bar charts to display the relevant Integration execution details in the table. You can also point to each bar in the chart to view the date and time when the Integration executed and the result of the Integration execution.
- Name of the Integration, stage name, when the Integration started, the Integration run duration, documents processed details, result of the Integration execution (Completed Successfully, Failed, Completed with errors), and the Integration execution message displayed in a tabular format. The **Documents Processed** column displays the total number of documents processed by an integration, the number of documents processed successfully, and the success percentage. Values in this column appear only if the Integration invokes the `countProcessedDocuments` service to count the number of documents processed by the Integration. For more information, see the `countProcessedDocuments` service available in the **Flow** block under the **Services** category.
- If you click a row on the table, you can view the execution information as well as the operations details for the Integration. See [Execution Results](#) for more information.

Execution Results

The **Execution Results** page allows you to view the audit trail of all the Integration executions that happened in the current stage, during a specified time period, for a selected project or for all projects. You can also restart or resume an Integration execution, specify the number of days to retain the entries, and download the entries.

Note: To view execution results, ensure that the Access Profile of the user is assigned to the current stage.

To view the execution results

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > Integrations**.
The **Integrations** page appears.
2. From the **Integrations** page, select the Integration for which you want to view the execution results.
3. Click the *Integration link* to view the Integration **Overview** page. You can click **Edit** to modify the Integration, click **Delete** to delete the Integration from this page, or click **Run Now** to execute the Integration. You can also see the last five execution results in the **Last 5 Execution Results** tab.

You can also access the **Execution Results** by clicking **Monitor > Execution Results**.

4. On the **Execution Results** page, select a project, an Integration, and the time period for which you want to view the execution results. Select **All Integrations** and **All Projects** if you want to view the execution results for all Integrations in all projects in the active stage, for the specific time period. The **Custom Range** option allows you to set a time period to view the results. The default time period is for the last 24 hours.

Execution results are displayed in a tabular form. You can filter the results in the table by clicking on the status filter circles available on the top-right corner above the table. The numbers inside the status circles indicate the sum of the execution counts for that status.



- **All** - All operations of an Integration, which have **Completed Successfully**, **Failed**, and **Completed with errors** are displayed.
- **Completed Successfully** - All operations of an Integration that completed successfully while executing are displayed.
- **Failed** - Exceptions occurred while executing an operation in an Integration.

- **Completed with errors** - Exceptions occurred while executing an operation in an Integration and caught by the try-catch block in an orchestrated Integration.
5. In the **Execution Results** page, click **Download Results** to download the execution results, or click **Modify Retention Period** and specify the number of days to retain the execution result entries. You can retain entries up to 30 days. Entries whose age exceeds the specified retention period are deleted. Default value of the Retention Period is 30 days.

Note: User specific data which may be considered as personal data will be stored and retained till the retention period defined in Execution Results.

6. On the **Execution Results** page, click an Integration in the table to view more information about the selected Integration execution. The **Execution Details** page appears.

In the **Execution Details** page, the **Documents** row displays the total number of documents processed by the integration, the number of documents processed successfully, the number of documents that did not process successfully, and the success percentage. Values in this row appear only if the Integration invokes the **countProcessedDocuments** service to count the number of documents processed by the Integration. See the **countProcessedDocuments** service in the **Flow** block under the **Services** category for more information. You can also terminate in-progress Integration executions from the Execution Results details page. The **Terminate** option is available only if you have the *Execute* Integration permission and the Integration status is in-progress. The **Execution Information** section displays when the Integration execution was started, when it ended, the duration of the execution, who executed the Integration, through which channel the Integration was executed, for example, Scheduler, User Interface, and REST Interface, the execution result reference, that is, the Integration execution result reference identifier, and the business data details.

7. The **Execution Results** page also provides information about operations for the selected Integration. Click **Show Everything** to view all information about the operation execution including business data and custom messages. Click **Only Business Data** to view only the logged business data information. Click **Only Custom Messages** to view only custom messages. You can filter the results in the table by clicking on the status filter circles on the top-right corner of the Operations table. Click on the **All** (blue) circle to view operation information, business data, and custom messages. Click on the **Successful** (green) circle to view only successful operation information and business data. Click on the **Failed** (red) circle to view only failed operation information and business data. Custom messages appear only if you have set up log messages. See the **logCustomMessage** service in the **Flow** block under the **Services** category for more information on how to set up custom messages in an Integration.
8. In the **Execution Results** page, select a row and click **Restart** to edit the input data and restart the Integration execution from the beginning, even though the previous execution has been successful. When an Integration is restarted, the Audit Log entry displays "Restart".

Click **Resume** to edit the input data for failed operations and execute the failed and not yet executed operations. When an Integration is resumed, the Audit Log entry displays "Resume".

Note: The "Restart/Resume" capability is available only if you have the required license for restarting and resuming Integrations. You must also have the Integration execution (Execute) permission if you want to restart or resume an execution.

Note: You must select the **Enable executions to be restartable** option in the **Integration Details** page in order to enable Integration executions to be restartable or resumable. See [Integration Details](#) for more information.

The following table provides information on when you can restart or resume an Integration execution:

<u>Execution Result Status</u>	<u>Restartable</u>	<u>Resumable</u>
Completed Successfully	Yes	No
Completed with Errors	Yes	No
Failed	Yes	Yes
In-Progress	No	No

Alert Rules

Integration Cloud allows you to create alert rules and send email messages to selected users for one or more Integrations based on Integration execution results (Failed, Completed with Errors, or Completed Successfully) for the current stage. All executions that have occurred within a 15-minute period and have alert rules configured are sent as email messages to specified users.

Note: Email messages are sent only if there are executions that match the alert rules.

Note: Ensure that the Access Profile of the user is assigned to the active stage. To select another active stage, click **Stages > Change Stage To View**.

To create a new alert rule

1. From the Integration Cloud navigation bar, click **Monitor > Alert Rules**. The **Alert Rules** page appears. You can edit, delete, activate, or deactivate an existing alert rule from this page.
2. From the **Alert Rules** page, click **Add New Alert Rule** to create a new alert rule.

The **Add New Alert Rule** page appears.

3. On the **Add New Alert Rule** page, provide a name and description for the alert rule and complete the following fields. Required fields are marked with an asterisk on the page.

Field	Description
Select Project	Select a project from the drop-down list. Choose the Integrations available in the selected project by clicking the  icon in the next section. The alert rule will apply to the selected Integrations. <p>Note: You can also select another project and choose the Integrations available in that project. The alert rule will apply to all the selected Integrations.</p>
For the following Integrations	Click the  icon and select the Integrations you want this alert rule to apply.
when their executions have	Select the Integration execution results. <ul style="list-style-type: none"> ■ Failed - Exceptions occurred while executing an operation in an Integration. ■ Completed with Errors - Exceptions occurred while executing an operation in an Integration and caught by the try-catch block in an orchestrated Integration. ■ Completed Successfully - All operations of an Integration that completed successfully while executing.
send an email message to the following users	Click the  icon and select the active users to whom you want to send email alerts. Alerts will be sent to the email address specified in the Basic tab of the user's profile (Settings  > Users > User Profile > Basic > Email).

4. Click **Save and Activate** to save and enable the new alert rule.

The new alert rule appears in the **Alert Rules** page. You can disable an alert rule by selecting the alert rule and clicking **Mark As > Inactive**. You can also enable the alert rule by selecting the alert rule and clicking **Mark As > Active**.



- Go to the **Alert Rules** page and click **Modify Alert Frequency Period** to specify the alert frequency period to send email messages. If you do not want to receive email alerts for Integration executions, open the Alert Rule for editing, and remove your username from the user's list.

Reports

The Reports page provides you information about the number of times an Integration is run for the specified time frame. The report shows the count for the currently active stage and the reports data is collected daily, at the end of day.

By default, the data shown on the Reports page is for all the Integrations run across all projects. When the reports data is collected initially, it is compiled for the number of days as specified in the retention period on the Execution Results page. Default value of the retention period is 30 days.

A zero count may mean that either the integration is not executed for that month, or the integration execution had occurred earlier than the value specified in the retention period. This is applicable only during the initial period.

Note: The data you see on the Reports page depends mainly on two factors:

- When you view the data
- When data collection ends

The Reports page displays data collected till the day before yesterday. Daily around 9:10 PM, data collection starts. The time when data collection ends depends on the volume of data and for how long Integration Cloud takes to collect the data.

Example

Let us assume that the current date and time is *18th October, 9 PM*. If you view the Reports page now at 9 PM, data collection is yet to start for today (it will start at 9:10 PM), and so the Reports page will show the integration execution counts that have occurred till *16th October 11:59 PM*. If the data collection starts at 9:10 PM today and ends by 11 PM, then after 11 PM, the Reports page will show the integration execution counts till *17th October 11:59 PM*.

You can know when the data collection has completed from the entries in the Audit Log:

- *Type*: IntegrationResults History
- *Operation*: Update

To view the reports

1. From the Integration Cloud navigation bar, click **Monitor > Reports**. The **Reports** page appears.
2. Select the time frame for which you want to view the report. You can set from the following options:
 - **1m** - Show data for 1 month from the current system date.
 - **3m** - Show data for 3 months from the current system date.
 - **6m** - Show data for 6 months from the current system date.
 - **12m** - Show data for 12 months from the current system date.
 - **Custom Range** - In the **Set Custom Range** dialog box, set the **Start date** and **End date** for the time range.
3. To download the report, click **Download Reports**. Currently, you can download reports in the following formats:

Note: The downloaded report also shows the stage for which you have run the report.

- PDF
- CSV
- PDF (detailed) - In addition to the details provided in PDF format, here you can view how many times in each month an Integration has run.
- CSV (detailed) - In addition to the details provided in CSV format, here you can view how many times in each month an Integration has run.

13 Reference Data

■ Overview	624
■ Add Reference Data	625
■ Reference Data Signature	626

Overview

Reference data is data that defines the set of permissible values to be used by other data fields. It is a collection of *key-value pairs*, which can be used to determine the value of a data field based on the value of another data field. For example, the value of a status field in an Application can be “Canceled” and that needs to be interpreted as “CN” in another Application. If you have the required access privileges under **Settings**  > **Access Profiles** > **Administrative Permissions** > **Functional Controls** > **Reference Data**, you can create, update, or delete a Reference Data.

Integration Cloud allows you to upload Reference Data from a text file containing tabular data separated by a character, for example, a comma, semicolon, and so on. The uploaded file should not have an empty column heading or space in the first row, and the first row cannot be empty.

Note: See this [“video”](#) on how to upload Reference Data, access the uploaded Reference Data in an Orchestrated Integration, and view the input and output parameters.

The Reference Data block appears under **Services** in the Orchestrated Integration workspace, only after you have created a Reference Data. See [Reference Data Signature](#) for information on the Input and Output parameters. The Reference Data is also available in Point-to-Point Integrations while transforming data. You can access the uploaded Reference Data in Orchestrated Integrations as a list of documents by using the *Reference Data block* and providing an appropriate name. You can filter the documents returned into the pipeline by the Reference Data block.

You can create a Reference Data only in the **Development** stage but can view, edit, delete, and download the Reference Data *in all stages*. The **Status** column in the Reference Data table displays **Configured** if the Reference Data is available in the current stage (Stage in view) and displays **Not Configured** if the Reference Data is not available in the current stage but available in any other stage. The **Delete** and **Download** options are enabled if the Reference Data is available in the current stage. The **Edit** option is enabled in all stages. The **Download** option allows you to download the previously uploaded Reference Data, edit it, and then upload the modified file. In this way you can upload different sets of data in different stages.



Name	Used In	Modified On	Modified By	Status
ref_data				Not Configured
anotherData	@reference @batch_ref	2018/12/07 02:34:59 PM IST	Unknown User	Configured

You can pull an Integration only if the Integration is consistent in the source stage, that is, all references of the Integration are present in the source stage. While pulling an Integration from the source stage to the target stage, if the same Reference Data is not available in the target stage, then you must configure the Reference Data in the target stage. If the same Reference Data is available in the target stage with a signature

mismatch, for example, the number of columns or the column names are not the same, then you can either reconfigure the Reference Data or skip the reconfiguration. If the Reference Data is already available in the target stage and the signature is same as in the source stage, then it will not be copied from the source stage to the target stage while pulling the Integration.

Note: If a Reference Data is in the Development stage, the Reference data can be deleted even it is referenced or used in an Integration. Integrations using the deleted Reference Data will be in an inconsistent state.

If a Reference Data is in a stage other than the Development stage, the Reference data can be deleted only if it is configured in that stage and not used in any Integration.

Add Reference Data

To add or edit a Reference Data


1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > Reference Data**. The **Reference Data** page appears.
2. To edit an existing Reference Data, select a configured Reference Data from the **Reference Data** page, and click **Edit**.
3. To create a new Reference Data, from the **Reference Data** page, click **Add New Reference Data**. You can create a Reference Data only in the **Development** stage.

The **Upload Reference Data** page appears.

4. Provide a name and description of your Reference Data. Required fields are marked with an asterisk on the page.
5. For **Reference Data File**, click **Browse** and select the file. Only a text file having tabular data is supported. The maximum file size you can upload is 1 MB. Further, the file should not have an empty column heading or space in the first row and the first row cannot be empty. This is because the first row of data is read as column headings.
6. Click **Next** to define and preview the Reference Data. Select the field separator and the text qualifier.
7. Determine the encoding of the Reference Data file and from the **File Encoding** drop down list, select the same encoding. Click **Load Preview** to preview the data. If you select an incorrect encoding, garbage characters will appear in the preview pane.
8. Click **Next** to review the Reference Data and then click **Finish** to create the Reference Data.

The new Reference Data appears in the **Reference Data** page with the status as **Configured**.

Note: The **Reference Data** block appears under **Services** only after you have created a Reference Data and the Reference Data service will be available while creating an Orchestrated Integration.



The Reference Data is also available in Point-to-Point Integrations while transforming data.

Reference Data Signature

Reference Data signature is derived from the column names of the uploaded text file. You can filter the Reference data by providing an appropriate **matchCriteria**. The output of Reference Data is a list of documents that match the specified **matchCriteria**.

Note: The root element in the output of Reference Data created from version 2.1.0 has the same name as the Reference Data.

Input Parameters

matchCriteria **Document** Criteria on which documents from the Reference Data will be matched.

Parameters for *matchCriteria* are:

path: Column names of the Reference Data.

compareValueAs: Optional. Allowed values are string, numeric, and datetime. The default value is string.

datePattern: Optional. Pattern will be considered only if *compareValueAs* is of type datetime. Default value is MM/dd/yyyy hh:mm:ss a.

joins: List of join criteria.

Each join criteria consists of:

operator: Allowed values are equals, doesNotEqual, greaterThan, greaterThanEqual, lessThan, lessThanEqual, equalsIgnoreCase, contains, doesNotContain, beginsWith, doesNotBeginWith, endsWith, doesNotEndWith.

`value`: Optional. Allowed values are string, numeric, and datetime. The default value is string.

`joinType`: Specifies the way two joins can be linked. Values are “and” or “or”. Default value is “and”.

Output Parameters

<Reference Data Name> **Document List** List of documents that match the retrieve criteria.

In the following example, the flat file contains “Type”, “Our Type”, and “Marketer” as headers and has one or more data rows.

Type,Our Type,Marketer

Existing - Growth,Growth,HUNT & SONS INC

The following graphic illustrates the generated Reference Data signature:

fx AccountType Input

▼
📄 matchCriteria [] *

GTR
path *

GTR
compareValueAs

GTR
datePattern

▶
📄
joins [] *

fx AccountType Output

▼
📄 AccountType []

GTR
Type

GTR
Our Type

GTR
Marketer

14 REST APIs

■ Overview	630
■ Creating REST APIs from scratch	630
■ Creating REST APIs with Swagger	634
■ Copying REST APIs	635
■ Exporting REST APIs	636
■ Importing REST APIs	637

Overview

Integration Cloud allows you to write integration logic to integrate different types of applications. This logic can be exposed to the external world using REST APIs.

These REST APIs can be created by using an existing set of Integrations (from scratch) or by using a file containing the Open API specification (formerly known as the Swagger specification) as a template.

A REST API consists of many Resource Operations and each Resource Operation has a Path, one or more HTTP Methods, and an associated Integration.

A REST Resource Operation can be tried out from the **Swagger** screen of a REST API. When the Resource Operation is invoked using the HTTP Method, the associated Integration gets executed.

Note: Users who have the required permissions under **Settings**  **> Access Profiles > Administrative Permissions > Functional Controls > REST APIs** can create, update, delete, and execute REST APIs.

Note: If you have created a REST API by using a file containing the Open API specification (formerly known as the Swagger specification) as a template (**Build with Swagger** approach), and have now uploaded a new file, Integrations and Document Types that are created are now based on the new Swagger file.

Creating REST APIs from scratch

To create a REST API from scratch

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > REST APIs**.

The **REST APIs** page appears.

2. From the **REST APIs** page, click **Add New REST API**, select **Build from scratch**, and then click **OK**.
3. Complete the following fields and click **Save**.

The new REST API appears in the **REST APIs** page.

In this field...

Specify...

Save As

Type a name for the REST resource using any combination of letters, numbers, and/or underscore characters.

<u>In this field...</u>	<u>Specify...</u>
Swagger Title	Provide a title for the REST API.
Description	Type an optional description for the REST API.
Version	A version number. The value is typically 1.0. You need to change the version number if you want to modify and republish the REST API.
Consumes	Select the MIME types that the API consumes.
Produces	Select the MIME types that the API produces. The MIME types you select here will be part of the Swagger definition and will appear in the Responses section of the Swagger editor. While executing the REST API, you can choose the format in which you want to view the response. You must specify an <i>Accept</i> header in the REST client, else the default response will conform to the Content Type <i>text/html</i> .

4. Click **Save**.

The REST API is created and appears in the **REST APIs** page. When you create a REST API, Integration Cloud uses the general information that you supplied to populate the **Overview** page in the REST API. You can click **Edit** to change the information in the **Overview** page. The name cannot be modified.

5. In the **Resources** page, click **Add New Resource** to add a Resource to the REST API. Type a **Path**, select a **Mapped Integration** that you want to invoke with this path, and select the **HTTP Methods** that can be used to invoke this Integration with this path. You can also provide a description for each method in the **Operation Summary** field. You can add more Resource Operations, if needed.
6. Click **Save and Continue** to add parameters and responses and then click **Save and Finish**. See [“Modifying Resource Operations” on page 632](#) for information on how to modify a REST Resource Operation.
7. To run an Integration with a certain path and method, go to the **REST APIs** page, select a REST API, and click the REST API link. The REST API details page appears.
8. Go to the **Swagger** page from the REST API details page. Click **Authorize** and type your Integration Cloud user name and password to authorize access to your APIs. Select the path and method pair and click **Try it out**. If required, pass the parameters and click **Execute**.

Responses will be displayed on the pane.

Modifying Resource Operations

To modify a REST Resource Operation

1. From the Integration Cloud navigation bar, click **Projects** > **<Select a Project>** > **REST APIs**.

The **REST APIs** page appears.

2. Click on the link of a REST API that has been *created from scratch*, go to the **Resources** page, select a resource operation, and then click **Edit**.

1 Define RES

Operation Description

Path *

Mapped Integration *

HTTP Methods

Select one or more HTTP methods to complete the REST Operation definition

Method	Operation Summary
<input checked="" type="checkbox"/> POST	
<input checked="" type="checkbox"/> PUT	
<input checked="" type="checkbox"/> GET	
<input checked="" type="checkbox"/> DELETE	
<input checked="" type="checkbox"/> PATCH	

Modifying the Path

On the **Resources** page, select a resource operation and then click **Edit**. Change the path. If you modify the path, the Integration will run on the new path. To run the Integration, for a given method, go to the **Swagger** page, click **Authorize** and type your Integration Cloud user name and password to authorize access to your APIs, and click **Try it out** that corresponds to the new path and method pair.

Modifying the HTTP Methods

On the **Resources** page, select a resource operation and then click **Edit**. Select new HTTP Methods with respect to which you want to expose the given Integration. To run the integration now, go to the **Swagger** page, click **Authorize** and type your Integration Cloud user name and password to authorize access to your APIs, and click **Try it out** that corresponds to the path and one of the new methods that was selected.

Changing the mapped Integration

On the **Resources** page, select a resource operation and then click **Edit**. Choose a new **Mapped Integration** from the drop-down list. To run the new Integration, go to the **Swagger** page, click **Authorize** and type your Integration Cloud user name and

password to authorize access to your APIs, and click **Try it out** that corresponds to the Integration method and path pair.

Modifying an existing Integration

Select an Integration in the **Integrations (Develop > Integrations)** page that is exposed in a REST API and click **Edit**. Change the input signature and output signature of the Integration. Now go to the **REST APIs (Develop > REST APIs)** page, select a REST API, and click on the REST API link. Go to the **Resources** page. Identify any method and path pair that corresponds to the Integration whose signature was modified. Then go to the **Swagger** page and navigate to the method and path pair that was identified. You can see that the parameters have changed and they now correspond to the new Integration input signature. Note that the responses have also changed and they correspond to the output signature of the Integration. Click **Authorize** and type your Integration Cloud user name and password to authorize access to your APIs, and then click **Try it out**, supply the new parameter values, and run the Integration.

Changing Parameter Types

On the **Resources** page, select a resource operation and then click **Edit**. Click **Save and Continue**. Parameters corresponding to the Integration appears.

- If the parameter type is **body**, you cannot change its type.
- If the parameter type is **formdata**, you can change it to a header or a query parameter.
- If the parameter type is **header**, you can change it to a query or formdata parameter.
- If the parameter type is **query**, you can change it to a form or a header parameter.

Adding Responses

On the **Resources** page, select a resource operation and then click **Edit**. Click **Continue**. You will see the responses corresponding to the output signature of the Integration in the panel. You can add more response codes, if needed.

Note: Click **Back to Definition** to go back to the REST Resource Operation definition page.

3. A “[scope](#)” on page 100 defines the services the client can access on behalf of the resource owner and consists of one or more services. If access is granted for a scope,

then access is granted for all the services in that scope. When a request is made, Integration Cloud verifies that the scope is defined for a client. The client is allowed to access only the service URLs that are specified for the scope.

For a Resource Path with Method, click **OAuth Scopes** to view the OAuth Scopes that contain the REST Resource path with Method.

In the **OAuth Scopes** dialog box, click **Add URL to Another Scope**. In the **Add REST Resource Path to OAuth Scope** dialog box, select **Add To Existing Scope** to add the REST Resource path with Method to an existing scope or select **Add New Scope** to create a new scope and add the REST Resource path with Method to that new scope.

Path	Description	Integration	Permissions	OAuth Scopes
POST	Add a new pet to the store	addPet	Permissions	OAuth Scopes
PUT	Update an existing pet	updatePet	Permissions	OAuth Scopes

Creating REST APIs with Swagger

To create a REST API using a Swagger file

1. From the Integration Cloud navigation bar, click **Projects** > **<Select a Project>** > **REST APIs**.

The **REST APIs** page appears.

2. From the **REST APIs** page, click **Add New REST API**, select **Build with Swagger**, and then click **OK**.

In the **New REST API** page, complete the following fields. Required fields are marked with an asterisk on the screen.

Select...	To...
Save As	Type a name for the REST API using any combination of letters, numbers, and/or the underscore character.
Swagger Source	Select URL and enter the URL for the Swagger document. The URL should begin with https://. OR Select File and click Browse to select a Swagger document on your local file system. Swagger documents must be in either JSON format with a .json file extension or YAML format with a .yaml or .yml file extension.

Click **Save**.

Note the following points after you click **Save**:

- The REST API is created based on the Swagger definition that is uploaded or the Swagger definition that is referred to by the given URL.
 - Integrations are generated based on the Operation IDs in the Swagger file. One Integration is created for each Operation ID in the Swagger file. A Swagger file cannot have two Operation IDs that are similar.
 - Resource Operations are created for a unique path in the Swagger file.
3. To view the Swagger definition, from the **REST APIs** page, click the REST API link. The **Overview** page provides general information on the REST API. The **Resources** page allows you to view the resource operations. The **Swagger** page allows you to view the Swagger definition.

You can use Access Control Lists (ACLs) to control the execution permission of a REST API. Integration Cloud associates the default ACL, *Default*, to a REST API when the REST API is created using a Swagger file. Click **Permissions** to associate the REST API with another ACL.

Note: The ACL will be enforced only if an Integration acts as a top-level Integration. For example, if Integration A has Integration B and Integration C as sub-Integrations, then the ACL if associated, will be enforced only on Integration A.

4. To edit the Integration, go to the **Resource Operations** page, select a Resource Operation, expand its path, and click on the icon next to the Integration. The Integration will be open for editing in the Edit Integrations page. Add necessary blocks and perform mappings.

Note: You will not be able to modify the Input/Output signature of the Integration because the signature is derived from the Swagger definition.

5. To run the Integration with the given path and method, go to the **Swagger** page for the REST API, click **Authorize** and type your Integration Cloud user name and password to authorize access to your APIs, and then click **Try it out**.

Copying REST APIs

Integration Cloud allows you to create a copy of a REST API from the **REST APIs** page. You can copy a REST API if you have the required permissions.

To copy a REST API

1. From the Integration Cloud navigation bar, click **Projects** > **<Select a Project>** > **REST APIs**. The **REST APIs** page appears.
2. Select a REST API and click **Copy**.

The **Copy** dialog box appears.

3. By default, in the **Select Project** field, the current project is selected. To copy the REST API to another project, select a different project from the **Select Project** drop-down list.

Note: Ensure that you create any account or reference data associated with this REST API in the target project.

4. Type a new name in the **Copy As** field.
5. Click **Copy**. The system creates a copy of the REST API with the new name and it appears in the **REST APIs** page of the target project.

Note: If you have created a REST API by using a file containing the Open API specification (formerly known as the Swagger specification) as a template, a copy of the REST API (including its dependencies namely its Integrations, Document Types, and Resources) is created. All resources and document types are renamed as per the new name. When Integrations encapsulated by the copied REST API are modified, the changes are reflected only in the copied REST API and not in the REST API from which it was copied. This is because, if you have created a REST API using the **Build with Swagger** approach, each REST API has its own set of Integrations.

If you create a REST API by using an existing set of Integrations (**Build from scratch**), a copy of the REST API is created. You can type a new name at the time of copying and a REST API with the new name is created. The same REST APIs that are referred to in the original REST API are also referred to in the copied REST API. If the Integration to which it is referred is modified in the copied REST API, then the changes will reflect in the original REST API because both the REST APIs refer or point to the same Integration. However, if another path with a different Integration is added to the copied REST API, this does not show in the original REST API.

Exporting REST APIs

Integration Cloud allows you to export REST APIs from the **REST APIs** page. The export capability is available only if you have the required license for exporting REST APIs. You can export REST APIs from one tenant and import those REST APIs to another tenant. Ensure that you have the **Export** Integration permission to export REST APIs.

When a REST API is exported, all its dependencies (Integrations, Document Types, and Resources) are exported. Integrations referred to by the REST API, their dependencies, and all dependant Document Types of the referred Integrations are also exported.

Note: If assets used by a REST API are deleted, you will not be able to export the REST API.

To export REST APIs

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > REST APIs**. The **REST APIs** page appears.
2. Select the REST APIs from the **REST APIs** page and click **Export**. If the REST APIs you are exporting use Reference Data, Document Types, SOAP, or REST Applications, then those Applications including the Reference Data and Document Types will also be exported along with the REST APIs.

The **Confirm Export** dialog box appears.

3. Click **Export** to export the REST APIs. The REST APIs will be downloaded as a zip file to your default download folder. The zip file size must not be greater than 50 MB.

Note: Do not modify the contents of the exported zip file. If you modify the contents of the zip file, the REST APIs cannot be imported back to Integration Cloud.

Importing REST APIs

Integration Cloud allows you to import REST APIs from the **REST APIs** page. You can import REST APIs from a zip file that was earlier exported from Integration Cloud. You can export REST APIs from one tenant and import those REST APIs to another tenant. You can import REST APIs provided you have the **Create** Integration permission.

Note: If you want to import a REST API that has an on-premises Application, before importing the REST API, ensure that you upload the same on-premises Application to Integration Cloud. Else, you will not be able to import the REST API.

To import REST APIs

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > REST APIs**. The **REST APIs** page appears.
2. Click **Import REST APIs**.
The **Import REST APIs** page appears.
3. Click **Browse** and select the zip file that contains the exported REST APIs. The zip file size must not be greater than 50 MB. The REST APIs available in the zip file will appear in the pane.
4. Select the REST APIs that you want to import and then click **Import**.

The REST APIs appear in the **REST APIs** page.

Note: While importing a REST API, the REST API including its dependencies are imported. If there is a REST API with the same name, you will be

asked to provide a new name. If you have Integrations that have the same name as those referred to by the REST API, you will be asked whether you want to override those integrations. If you choose to override, then the Integrations in your current tenant will be removed. If you want to retain the Integrations, you can cancel importing the REST API. If you want to retain your current Integrations and also import the REST API, create a copy of your Integrations by providing another name and then override your current Integrations at the time of import of the REST API.

15 SOAP APIs

■ Overview	640
■ Creating SOAP APIs from scratch	641
■ Creating SOAP APIs with WSDL	644
■ Copying SOAP APIs	647

Overview

Web services are building blocks for creating open, distributed systems. A web service is a collection of functions that are packaged as a single unit and published to a network for use by other software programs. For example, you could create a web service that checks a customer's credit or tracks delivery of a package. If you want to provide higher-level functionality, such as a complete order management system, you could create a web service that maps to many different Integrations, each performing a separate order management function.

A SOAP API defines a web service and it encapsulates all the information of a web service. The SOAP API contains the message formats, data types, transport protocols, and transport serialization formats that should be used between the consumer (requester) and the provider of the web service. In essence, the SOAP API represents an agreement governing the mechanics of interacting with that service.

Integration Cloud allows you to write integration logic to integrate different types of applications. This logic can be exposed to the external world using SOAP APIs. A SOAP API is a service *provided* to external users.

Note: Users who have the required permissions under **Settings**  **> Access Profiles > Administrative Permissions > Functional Controls > SOAP APIs** can create, update, delete, and execute SOAP APIs.

An *operation* is the WSDL element that exposes some functions of a web service and defines how data is passed back and forth. A SOAP API exposes one or more Integrations as *operations*, so each operation in a SOAP API corresponds to an Integration. The input for the Integration corresponds to the request body for the operation. The output of the Integration is the response body for the operation.

Using a SOAP client, you can invoke the SOAP operation *externally* by using either Basic Authentication or 2-way SSL. When the SOAP operation is invoked, the associated Integration gets executed.

You can create SOAP APIs by using an existing set of Integrations (from scratch) or by using a WSDL file:

- **Build from scratch:** You can create a SOAP API from an existing Integration. In this case, you specify the protocol and the use and style for the operations when creating the SOAP API. The Integration becomes an operation in the SOAP API. Integration Cloud uses the existing service signature as the input and output messages for the operation. You can add operations to a SOAP API or delete operations from a SOAP API that is created from scratch.
- **Build with WSDL:** You can create a SOAP API from an existing WSDL document. In this case, Integration Cloud uses the operation definitions from the WSDL to generate an Integration for each operation in the WSDL. You cannot add operations to a SOAP API created from a WSDL.

Creating SOAP APIs from scratch

When you create a SOAP API from scratch, you select one or more Integrations to use as operations. The operation signature becomes the input and output messages for the operations in the WSDL document. However, Integration Cloud allows constructs within operation signatures that cannot be represented in certain web service use/style combinations. When adding an Integration to or creating a SOAP API from scratch, Integration Cloud verifies that the operation signature can be represented in the use/style specified for the SOAP API. If an operation signature does not meet the use/style signature requirements, Integration Cloud will not add the Integration as an operation. Or, in the case of creating a SOAP API from scratch, Integration Cloud will not create the SOAP API.

Following is a list of operation signature restrictions and requirements for each use/style. Note that this list may not be exhaustive.

Signature Restrictions for Document - Literal

*body fields are not allowed at the top level

@attribute fields (fields starting with the “@” symbol) are not allowed at the top level

String table fields are not allowed

Signature Restrictions for RPC - Literal

*body fields are not allowed at the top level

@attribute fields (fields starting with the “@” symbol) are not allowed at the top level

String table fields are not allowed

List fields (String List, Document List, Document Reference List, and Object List) are not allowed at the top level

Duplicate field names (identically named fields) are not allowed at the top level

Top-level fields cannot be namespace qualified

Top-level field names cannot be in the format *prefix:localName*

Signature Restrictions for RPC - Encoded

* body fields are not allowed

@attribute fields are not allowed (fields starting with the "@" symbol)

Top-level fields cannot be namespace qualified

Top-level field names cannot be in the format *prefix:localName*

To create a SOAP API from scratch

1. From the Integration Cloud navigation bar, click **Projects** > **<Select a Project>** > **SOAP APIs**.

The **SOAP APIs** page appears.

2. From the **SOAP APIs** page, click **Add New SOAP API**, select **Build from scratch**, and then click **OK**.

3. Complete the following fields and click **Save**.

The new SOAP API appears in the **SOAP APIs** page.

Field	Description
Name	Type a name for the SOAP API using any combination of letters, numbers, and/or underscore character.
SOAP Version	Whether SOAP messages for this SOAP API should use SOAP 1.1 or SOAP 1.2 message format.
Select Integration	Select the Integration to use as an operation. The operation signature becomes the input and output messages for the operation in the WSDL document.
Use and style for operations	<p>A WSDL document describes a web service and a WSDL binding describes how the service is bound to a SOAP messaging protocol. A WSDL SOAP binding can be either a document style binding or a Remote Procedure Call (RPC) style binding. A SOAP binding can also have a literal or an encoded use.</p> <p>Select the use/style for operations in the SOAP API:</p> <ul style="list-style-type: none"> ■ Document - Literal

Field	Description
	<ul style="list-style-type: none"> ■ RPC - Literal ■ RPC - Encoded
Enforce WS-I Basic Profile 1.1 compliance	Select this option if you want Integration Cloud to validate all the SOAP API objects and properties against the WS-I requirements before creating the SOAP API.
Validate schema using Xerces	Integration Cloud automatically uses an internal schema parser to validate the schemas associated with the XML Schema definition. Select this option if you want Integration Cloud to also use the Xerces parser to validate the schemas associated with the XML Schema definition. However, the Xerces parser provides stricter validation. As a result, some schemas that the internal schema parser considers to be valid might be considered invalid by the Xerces parser.
Attachment Enabled	The Attachment Enabled option is displayed when you edit the SOAP API. If attachments are enabled for the SOAP API, instances of XML-type base64Binary are transported using MIME attachments, which improves the performance of large binary payload transport. Integration Cloud supports SOAP attachments only for SOAP APIs that specify style/use of RPC-Literal or Document-Literal.

4. Click **Save**.

The Integration becomes an operation in the SOAP API. Integration Cloud uses the existing operation signature as the input and output messages for the operation. You can add operations to a SOAP API created from scratch.

5. To add operations, on the **Operations** page, click **Add New Operation**.

The **Add New Operation** dialog box appears.

6. In the **Add New Operation** dialog box, type a name for the WSDL operation, select an Integration, and then click **Add**.

The new operation appears on the **Operations** page. Using a SOAP client, you can invoke the SOAP operation *externally* by using either Basic Authentication or 2-way SSL. When the SOAP operation is invoked, the associated Integration gets executed.

Creating SOAP APIs with WSDL

You can create a SOAP API from a WSDL document accessed through a URL or by selecting a WSDL file. You can specify whether Integration Cloud enforces strict, lax, or no content model compliance when generating document types from the XML Schema definition contained or referenced in the WSDL document. Content models provide a formal description of the structure and allowed content for a complex type. The type of compliance that you specify can affect whether Integration Cloud generates a document type from a particular XML Schema definition successfully.

Do not create a SOAP API from a WSDL that specifies RPC - Encoded, contains attributes in its operation signature, and/or has complex type definitions with mixed content. Integration Cloud might successfully create a SOAP API from such WSDLs but the SOAP API may exhibit unexpected runtime behavior.

To create a SOAP API with WSDL

1. From the Integration Cloud navigation bar, click **Projects** > **<Select a Project>** > **SOAP APIs**.

The **SOAP APIs** page appears.

2. From the **SOAP APIs** page, click **Add New SOAP API**, select **Build with WSDL**, and then click **OK**.

The **New SOAP API** page appears.

3. Provide a name of your SOAP API and complete the following details. Required fields are marked with an asterisk on the screen.

Select...	To...
SOAP API Source	<p>Specify the SOAP API Source.</p> <p>URL - Select URL if you want to specify the URL of the WSDL. The WSDL URL should begin with http:// or https://. The URL is used to retrieve the WSDL for the SOAP API. Enter the User Name and Password if authentication is required to access the WSDL URL.</p> <p>File - Select File and then click Browse if you want to select the WSDL from your local file system. The size of the WSDL file cannot exceed 5 MB. Click the  icon beside the Browse button if you want to add separate elements of a service definition after import, such as WSDLs or XSDs, to the primary WSDL. Ensure that you add the primary WSDL as the first WSDL, and then add separate elements of the service definition, for example, dependent</p>

Select...	To...
	<p>WSDLs and XSDs to the primary WSDL. If you upload a new file, Integrations and Document Types that are created are now based on the uploaded file.</p>
<p>Content model compliance</p>	<p>In Content model compliance, select one of the following to indicate how strictly Integration Cloud enforces content model compliance when creating document types from the XML Schema definition in the WSDL document.</p> <ul style="list-style-type: none"> ■ Strict - Generate the document type only if Integration Cloud can represent the content models defined in the XML Schema definition correctly. Document type generation fails if Integration Cloud cannot accurately represent the content models in the source XML Schema definition. Currently, Integration Cloud does not support repeating or nested model groups. If you select strict compliance, Integration Cloud does not generate a document type from any XML schema definition that contains those items. If Integration Cloud cannot generate a document type that complies with the content model in the XML schema definition in the WSDL document, Integration Cloud will not generate the SOAP API. ■ Lax - When possible, generate a document type that correctly represents the content models for the complex types defined in the XML schema definition from the WSDL document. If Integration Cloud cannot correctly represent the content model in the XML Schema definition in the resulting document type, Integration Cloud generates the document type using a compliance mode of None. When you select Lax compliance, Integration Cloud will generate the document type even if the content models in the XML schema definition cannot be represented correctly. ■ None - Generate a document type that does not necessarily represent or maintain the content models in the source XML Schema definition.
<p>Enforce WS-I Basic Profile 1.1 compliance</p>	<p>Select this option if you want Integration Cloud to validate the SOAP API objects and properties against the WS-I requirements before creating the SOAP API. The Enforce WS-I Basic Profile 1.1</p>

Select...	To...
	<p>compliance option specifies whether the SOAP API enforces compliance with the <i>WS-I Basic Profile 1.1</i>, a set of guidelines for using web services specifications to maximize interoperability (including guidance for such core web services specifications such as SOAP, WSDL, and UDDI).</p> <p>As an example, using the RPC-Encoded style and use is not supported by the WS-I profile. If a SOAP API makes use of the RPC/Encoded style, and Enforce WS-I Basic Profile 1.1 compliance is enabled, Integration Cloud will indicate that the SOAP API is not compliant.</p> <p>Enforcing WS-I compliance also affects the contents and signature for operations in the SOAP API.</p>
<p>Validate schema using Xerces</p>	<p>Integration Cloud automatically uses an internal schema parser to validate the schemas associated with the XML Schema definition. Select this option if you want Integration Cloud to also use the Xerces parser to validate the schemas associated with the XML Schema definition. However, the Xerces parser provides stricter validation. As a result, some schemas that the internal schema parser considers to be valid might be considered invalid by the Xerces parser.</p>
<p>Attachment Enabled</p>	<p>The Attachment Enabled option is displayed when you edit the SOAP API. If attachments are enabled for the SOAP API, instances of XML-type base64Binary are transported using MIME attachments, which improves the performance of large binary payload transport. Integration Cloud supports SOAP attachments only for SOAP APIs that specify style/use of RPC-Literal or Document-Literal.</p>

4. Click **Save** to create the SOAP API.
The SOAP API details page appears where you can edit the SOAP API.
5. Click the **Operations** tab to go to the **Operations** page. Integration Cloud uses the operation definitions from the WSDL to generate an Integration for each operation in the WSDL. You cannot add operations to a SOAP API created from a WSDL.
6. Click the **WSDL** tab to go to the WSDL page.

On the WSDL page, you can view the WSDL document associated with the SOAP API.

- The displayed WSDL document contains all the information to invoke the operations described in the WSDL.
- For a SOAP API created from a WSDL that contains relative URIs that are anonymously addressable, Integration Cloud replaces any relative URIs with an absolute URI using the base URI of the WSDL file.

Copying SOAP APIs

Integration Cloud allows you to create a copy of a SOAP API from the **SOAP APIs** page. You can copy a SOAP API if you have the required permissions.

To copy a SOAP API

1. From the Integration Cloud navigation bar, click **Projects** > **<Select a Project>** > **SOAP APIs**. The **SOAP APIs** page appears.
2. Select a SOAP API and click **Copy**.
The **Copy** dialog box appears.
3. By default, in the **Select Project** field, the current project is selected. To copy the SOAP API to another project, select a different project from the **Select Project** drop-down list.

Note: Ensure that you create any account or reference data associated with this SOAP API in the target project.

4. Type a new name in the **Copy As** field.
5. Click **Copy**. The system creates a copy of the SOAP API with the new name and it appears in the **SOAP APIs** page of the target project.

Note: If you have created a SOAP API by using a WSDL file, a copy of the SOAP API (including its dependencies namely its Integrations, Document Types, and Operations) is created. When Integrations encapsulated by the copied SOAP API are modified, the changes are reflected only in the copied SOAP API and not in the SOAP API from which it was copied. This is because, if you have created a SOAP API using the **Build with WSDL** approach, each SOAP API has its own set of Integrations.

If you have created a SOAP API by using an existing set of Integrations (**Build from scratch**), a copy of the SOAP API is created. You can type a new name at the time of copying and a SOAP API with the new name is created. The same integrations that are referred to in the original SOAP API are also referred to in the copied SOAP API (provided it is copied in the same project). If the referred Integration is modified in the copied SOAP API, then the changes will reflect in the original SOAP API because

both the SOAP APIs refer or point to the same Integration (This does not happen when the **Build from scratch** SOAP API is copied to a different project as the referenced integrations are also copied to the target project). However, if another operation with a different Integration is added to the copied SOAP API, this does not show in the original SOAP API.

16 Manage stages, Deploy assets

■ Manage Stages	650
■ Deploy Assets	652
■ Change Stage To View	652

Manage Stages

Stages provide safe environments for development and testing that are separated from the production environment. They allow assets to migrate from one environment to another environment. When you set up a stage, an environment is created for testing and executing the Integrations.

Integration Cloud provides ways to manage the Integration development life cycle. The typical life cycle of an Integration development involves creating Integrations, testing them, and making them production worthy. Each of these activities can be termed as different stages of an Integration development life cycle. To aide these activities, Integration Cloud provides you with **Stages**.

A predefined set of stages is allowed, each representing an activity in the Integration life cycle development. They are:

- Development
- Test
- Pre-Live
- Live

By default, every user gets a **Development Stage**. *In the Development Stage, you can create, update, delete, or view Integrations. You will not be able to create new assets in other stages.* In other stages, Integrations can be pulled from a preceding stage or deleted. Further, Integrations can be pulled into a stage only from a preceding stage.

Note: You can access a stage only if your Access Profile is assigned to the stage. See [“Apply Access Profiles to a Stage” on page 651](#) for more information.

Adding and deleting stages

You can add stages only in the following order:

- Live
- Test
- Pre-Live

You can delete stages only in the following order:

- Pre-Live
- Test
- Live

Note: Users who have the **Administer** permission under **Settings**  **> Access Profiles > Administrative Permissions > Functional Controls > Stages** can add or delete stages.

To add a new stage, click **Add New Stage**.

Apply Access Profiles to a Stage

The typical life cycle of an Integration development involves creating Integrations, testing them, and making them production worthy. Each of these activities can be termed as different stages of an Integration development.

Every stage can be assigned a number of Access Profiles and users who are assigned the required Access Profiles can perform activities on that stage. For example, if in an Access Profile, **Execute Integrations** permission is granted, the user assigned with that Access Profile can execute Integrations on the stages to which the Access Profile is assigned. If the Access Profile needs to perform scheduling activity on the Live stage, the Access Profile needs to have access to that stage as well. The Development stage can be accessed by everyone.

Click **Add New Stage** to add the next stage. Multiple boundary arrows indicate that more stages can be added.

Click **Delete** to delete a stage. You cannot delete the **Development** stage.

Note: When a stage is deleted, everything it contains is erased and cannot be recovered.

To apply Access Profiles to a stage

1. From the Integration Cloud navigation bar, click **Stage in view > Manage**. All stages added including the Development stage are displayed. Initially, before any other stages are added, the Development stage is displayed.
2. Click **Access Profiles** and select the Access Profiles you want to apply to the stage.



Note: By default, the **Administrator** and **Regular User** Access Profiles are associated with the Development Stage. If you have created a new Access Profile, ensure that the Access Profile you have created is associated with the Development Stage.

3. Click **Apply**.

The Access Profiles are applied to the selected active stage.


Note: When an Integration is pulled, all its dependents will also be pulled and copied to that stage.

Deploy Assets

This page displays all the assets under the relevant projects that are available in the current stage and the previously selected stage. Click the **Change Stage To View** link to deploy assets to another stage.


Note: Users who have the **Deploy** permission under **Settings**  > **Access Profiles** > **Administrative Permissions** > **Functional Controls** > **Assets** can deploy assets.

After you change the current stage to any other stage other than the Development stage, the **Deploy** page gets populated with the relevant assets selected in the **Select Asset Type** drop-down list.



You can select an asset that was in the earlier stage (left panel) and click **Pull** to pull the asset to the current stage (right panel). The assets are categorized under projects. If an asset is pulled and if the associated project is not present in the current stage, the project along with the asset will be available in the current stage.

You can pull an asset only if the asset is consistent in the source stage (left panel), that is, all references of the asset are present in the source stage. The pulled asset can be deleted from the current stage (right panel).



Note: You can access a stage only if your Access Profile is assigned to that stage.


Change Stage To View

This page allows you to change the current stage. Only active and accessible stages appear in the drop-down list for selection in the **Stage to view** field.

Note: You can access a stage only if your Access Profile is assigned to that stage.

After you change the current stage and click **Submit**, assets and services will be displayed in the user interface pages only for the selected current stage.

The **Stage In View** label on the navigation bar displays the current stage.



17 Keys and Certificates

■ Overview	656
■ Add Keystore	656
■ Add Truststore	657
■ Add Partner Certificate	658

Overview

Keystores and truststores are files that function as repositories for storage of keys and certificates necessary for SSL authentication, encryption/decryption, and digital signing/verification services. Keystores and truststores provide added layers of security and ease of administration, compared to maintaining the keys and certificates in separate files.

Integration Cloud stores its private keys and SSL certificates in keystore files and the trusted roots for the certificates in truststore files. Keystores and truststores are secure files with industry-standard file formats.

If you want to run services that submit HTTPS requests to other resources on the Internet, your server will be acting as a client and will receive certificates from these resources. In order for these transactions to work, your server must have copies of their public keys and signing CA certificates.

To identify a particular keystore or truststore file, or private key within a keystore, aliases are used. The use of aliases simplifies keystore and truststore management, because you do not need to enter path information when specifying a keystore, truststore, or the private key.

Note: You can add, edit, or view keystore and truststore aliases and partner's self-signed certificates from **Projects > <Select a Project> > Keys & Certificates** and can use them to secure your Application Accounts. Some Applications, including custom REST Applications allow two-way SSL authentication by providing keystore and truststore aliases in the Account Configuration section. Users who have the **Administer** permission under **Settings  > Access Profiles > Administrative Permissions > Functional Controls > Advanced Security** can add, edit, and delete Keystores, Truststores, and Partner Certificates.

To add a Keystore, from the Integration Cloud navigation bar, click **Projects > <Select a Project> > Keys & Certificates > Keystores > Add Keystore**.

To add a Truststore, from the Integration Cloud navigation bar, click **Projects > <Select a Project> > Keys & Certificates > Truststores > Add Truststore**.

To add a Partner Certificate, from the Integration Cloud navigation bar, click **Projects > <Select a Project> > Keys & Certificates > Partner Certificates > Add Certificate**.

Add Keystore

Integration Cloud allows you to upload a Keystore file to store SSL certificates and keys. A Keystore file contains one or more pairs of a private key and signed certificate for its corresponding public key. From this screen, you can create aliases for the Keystore, so that they can be referenced while creating an Account for an Application.

To add a Keystore

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > Keys & Certificates > Keystores > Add Keystore**.
2. Provide a name and description for the **Keystore file**.
3. In the **Type** field, select the Keystore file format. The default file format is **JKS**. You can also use **PKCS12**, a commonly used, standardized, certificate file format that provides a high degree of portability.
4. In the **Provider** field, select the provider from the list of available providers. The corresponding provider will be available in the provider list for a selected Keystore type.
5. Click **Browse** to select the Keystore file.
6. In the **Passphrase** field, enter the passphrase for the Keystore file. The passphrase must have been defined at the time the Keystore was created.
7. Click **Next** to protect the Key Aliases with passphrases. A key alias is a label for specific key within a Keystore. Enter a passphrase for each Key Alias found in the Keystore file, and then click "Finish" to upload the Keystore file.

The uploaded Keystore file can be used while creating an Account for an Application.

Add Truststore

Integration Cloud allows you to upload a Truststore file, which contains the trusted root of the certificate or signing authority (CA). From this screen, you can create aliases for the Truststore, so that they can be referenced while creating an Account for an Application.

To add a Truststore

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > Keys & Certificates > Truststores > Add Truststore**.
2. Provide a name and description for the Truststore file.
3. In the **Type** field, select the Truststore file format. The default file format is **JKS**. You can also use **PKCS12**, a commonly used, standardized, certificate file format that provides a high degree of portability.
4. In the **Provider** field, select the provider from the list of available providers. The corresponding provider will be available in the provider list for a selected Truststore type.
5. Click **Browse** to select the Truststore file.
6. In the **Passphrase** field, enter the passphrase for the Truststore file. The passphrase must have been defined at the time the Truststore was created and is used to protect the contents of the Truststore.

7. Click **Save** to upload the Truststore file.

The uploaded Truststore file can be used while creating an Account for an Application.

Add Partner Certificate

Integration Cloud allows you to upload the Partner's certificate which contains its public key. The Partner's certificate with the public key is required to encrypt outbound request messages and verify the signature of inbound messages.

From this screen, you can create aliases for Partner Certificates, so that they can be referenced while creating an Account for an Application.

To add a Partner Certificate

1. From the Integration Cloud navigation bar, click **Projects > <Select a Project> > Keys & Certificates > Partner Certificates > Add Certificate**.
2. Provide a name and description for the Partner Certificate file.
3. Click **Browse** to select the Partner Certificate file.
4. Click **Save** to upload the Partner Certificate file.

The uploaded Partner Certificate can be used while creating an Account for an Application.

18 Containers

■ Overview	660
■ Managing Repositories	661
■ Managing Services	663

Overview

Integration Cloud allows you to package existing webMethods Integration Server services as images or repositories and upload them on Integration Cloud using the Docker CLI. Docker is an open-source technology that allows you to deploy applications to software containers. A Docker container is an instance of a Docker image, where the Docker image is the application, including the file system and runtime parameters. To facilitate running webMethods Integration Server in a Docker container, webMethods Integration Server provides a script to use to build a Docker image and then push the resulting Docker image to a Docker registry hosted in Integration Cloud. You can store Docker images in a registry on Integration Cloud and manage those Docker images from the Integration Cloud user interface. Images or a repository are versioned or labeled using tags, that is, a tag is a label applied to an image or a repository. Tags help you to distinguish various images or repositories.

Note: See this [“video”](#) on how to package your existing integrations and logic and deploy them to the cloud using Docker containers and micro-services architectures.

Note: Integration Cloud documentation assumes that you are familiar with Docker technology. An in-depth discussion of Docker and container technology is beyond the scope of this document. For information on using webMethods Integration Server with Docker, see the *webMethods Integration Server Administrator's Guide*.

Images are read-only templates from which containers are instantiated, that is, a container is a runtime instance of an image. A container also consists of an execution environment and a standard set of instructions. After uploading an image on Integration Cloud, you can create and launch services from the image/tag to the desired active stage, specify the number of containers and the container port for each service, and see details of the running instances. A service can contain one or more containers and is defined as a named group of containers created out of a single image tag.

Note: Universal Messaging (UM) can also be run as a container in Integration Cloud. For creating the UM Docker images supported by Integration Cloud, you must run the Integration Cloud UM script to modify the base image before it is uploaded into Integration Cloud.

You can access containers if you have the **Settings**  > **Access Profiles** > **Administrative Permissions** > **Container** > **Access** permission. You can administer containers if you have the **Settings**  > **Access Profiles** > **Administrative Permissions** > **Container** > **Administer** permission. On the **Settings**  > **Access Profile** > **Container** tab, enter the names of the webMethods Integration Server Access Control List (ACL) groups separated by a comma, for example, Administrators, Developers, and so on. Users who are assigned to this Access Profile will also be now part of the webMethods Integration Server container user group (s) and can perform tasks allowed for those user groups. Note that Integration

Cloud Administrator profiles are not automatically assigned to the webMethods Integration Server Administrators ACL group. If you do not map an Access Profile to an webMethods Integration Server group, you will not be able to invoke webMethods Integration Server services.

Note: Enabling the CSRF security feature will prevent CSRF attacks. Enable **CSRF Guard** and configure the CSRF guard settings in webMethods Integration Server Administrator before you create the Docker image and upload it to Integration Cloud. See the *webMethods Integration Server Administrator's Guide* on the Software AG Documentation website at "<http://documentation.softwareag.com>" for information on how to enable CSRF Guard.

You can use the Docker Command Line Interface (CLI) to perform the following tasks:

Log in to the system: `#docker login -u <username> -p <password> https://<subdomain>.<domain.com>/`, for example, `docker login -u x@x.com -p test123 https://john.wmic1.com/`.

Tag an image or repository: `#docker tag <imagename>:<tagname> <subdoamin.wmis.com>/<subdomain>/<stage name>/<image-name>:<tag-name>`, for example, `#docker tag is_912:withkeystore john.wmic1.com/john/development/is_912:withkeystore2`.

Push or upload an image or repository: `#docker push <subdoamin.wmis.com>/<subdomain>/<stage name>/<image-name>:<tag-name>`, for example, `#docker push john.wmic1.com/john/development/is_912:withkeystore2`.

Pull or download an image or repository: `docker pull <subdoamin.wmis.com>/<subdomain>/<stage name>/<image-name>:<tag-name>`, for example, `#docker pull john.wmic1.com/john/development/is_912:withkeystore2`.

Managing Repositories

Images or repositories are read-only templates from which containers are instantiated. The **Repositories** screen allows you to view, delete, and add repositories for the active stage. You can select a repository and click **Delete** to delete a repository or click **Add New Repository** to add a repository. In the **Add New Repository** screen, select the **Deployment Stage** and enter the **Repository Name**. If a stage is not enabled to access containers, contact Support to enable the stage.

To view the details of a tag from the Repositories screen

1. Select a repository and then click the repository link under the **Name** column.
The **Image Tags** screen is displayed. A list of all image tags is displayed along with their names.
2. From the **Image Tags** screen, you can select an image tag and delete it or add a new service for the tag. See [Viewing Tag Details](#) for more information.

3. Click the **Commands** tab to view and copy the commands on how to log in, tag images, push images, or pull images.

Log in to the system: `#docker login -u <username> -p <password> https://<subdomain>.<domain.com>/`, for example, `docker login -u x@x.com -p test123 https://john.wmic1.com/`.

Tag an image or repository: `#docker tag <imagename>:<tagname> <subdoamin.wmis.com>/<subdomain>/<stage name>/<image-name>:<tag-name>`, for example, `#docker tag is_912:withkeystore john.wmic1.com/john/development/is_912:withkeystore2`.

Push or upload an image or repository: `#docker push <subdoamin.wmis.com>/<subdomain>/<stage name>/<image-name>:<tag-name>`, for example, `#docker push john.wmic1.com/john/development/is_912:withkeystore2`.

Pull or download an image or repository: `docker pull <subdoamin.wmis.com>/<subdomain>/<stage name>/<image-name>:<tag-name>`, for example, `#docker pull john.wmic1.com/john/development/is_912:withkeystore2`.

Viewing Tag Details

This screen displays details of all the tags for a repository. You can delete an image tag or add a new service. You can also click the **Commands** tab to view and copy commands on how to log in, tag images, push images, or pull images.

To view the image tag details

1. From the Integration Cloud navigation bar, click **Containers > Repositories**.
2. Select a repository and then click on the repository link. The **Image Tags** screen appears. A list of all Docker image tags is displayed along with their names.

From the **Image Tags** screen, select a tag and then click **Delete** to delete the image tag if it is not used by any service or click **Add New Service** to create a new service for the image tag. In the **New Service** window, specify the **Service Name**, the **Volume Name**, and the number of **Docker Containers** to instantiate.
3. From the **Image Tags** screen, select an image tag and click on the image tag link to view the Image Tag details screen. The Image Tag details screen displays the deployment stage of the image tag including the image tag label details. The image tag label details are as follows:
 - Image Type - Mandatory field. Indicates the type of image, for example, webMethods Integration Server or Universal Messaging.
 - Description, Build Number, and Version - Optional fields you had defined while creating the image.
 - Pushed At - System generated value. Date and time when the Docker image was pushed to the repository.
 - Size - System generated value. Indicates the size of the Docker image.

- **Exposed Port - Mandatory field.** The port you had defined while creating the image. Ensure that the exposed port is the same as defined on your application, that is, on webMethods Integration Server or Universal Messaging.

The Image Tag details screen also displays when the screen was last refreshed, used and available containers for the displayed active stage, and information on all services created for the tag. You can edit, delete, start, stop, or add a new service from the Image Tag details screen. Click on a service link to view the service details screen. See [Managing Services](#) for more information.

4. The **Commands** screen allows you to view and copy the commands on how to log in, tag images, push images, or pull images:

Log in to the system: `#docker login -u <username> -p <password> https://<subdomain>.<domain.com>/`, for example, `docker login -u x@x.com -p test123 https://john.wmic1.com/`.

Tag an image or repository: `#docker tag <imagename>:<tagname> <subdoamin.wmis.com>/<subdomain>/<stage name>/<image-name>:<tag-name>`, for example, `#docker tag is_912:withkeystore john.wmic1.com/john/development/is_912:withkeystore2`.

Push or upload an image or repository: `#docker push <subdoamin.wmis.com>/<subdomain>/<stage name>/<image-name>:<tag-name>`, for example, `#docker push john.wmic1.com/john/development/is_912:withkeystore2`.

Pull or download an image or repository: `docker pull <subdoamin.wmis.com>/<subdomain>/<stage name>/<image-name>:<tag-name>`, for example, `#docker pull john.wmic1.com/john/development/is_912:withkeystore2`.

Managing Services

The **Services** screen displays details of all services in the active stage, the repository name and tag name, status of the service, and number of Docker containers instantiated for a tag. You can start a service, stop a service, edit a service, delete a service, add a new service, refresh the screen, and view details on when the screen was last refreshed.

Note: You can also add a new service for a specified image tag from the **Containers > Repositories > Click a repository link > Image Tags** screen.

From the **Services** screen, select a service and then click the link to view the **Service details** screen. In the Service details screen, you can add or remove docker containers for the service for the selected repository and image tag.

The Service Details screen provides information on the service status (Stopped, Pending, Running), the repository, Deployment stage, and the image tag. You can start a service if it is in a stopped state. The **Docker Containers** pane in the Service Details screen displays information on the docker containers, their status, and the **Admin URL**, which is the webMethods Integration Server Administrator URL. You can modify Docker containers to instantiate by clicking **Manage Containers**, or click the **Admin URL** link to log

into webMethods Integration Server Administrator. In the **Exposed Services** pane, you can view the **Exposed Docker Services**. The exposed Docker service URL can be used to execute the webMethods Integration Server Administrator service running in the Docker container.

Note: Enabling the CSRF security feature will prevent CSRF attacks. Enable **CSRF Guard** and configure the CSRF guard settings in webMethods Integration Server Administrator before you create the Docker image and upload it to Integration Cloud. See the *webMethods Integration Server Administrator's Guide* on the Software AG Documentation website at "<http://documentation.softwareag.com>" for information on how to enable CSRF Guard.

Note: You can now invoke services exposed by webMethods Integration Servers running in the Docker Containers from Integrations. For more information, see the *On-Premises Applications* section and also the *Configuring On-Premise Integration Servers for webMethods Cloud* document.

To add a new service, from the **Containers > Services** screen, click **Add New Service**. The **New Service** screen appears. In the **New Service** screen, enter the following fields:

- **Repository** - Select a repository.
- **Image Tag** - Select an image tag.
- **Service Name** - Enter a valid service name. The service name can contain only alphanumeric characters and should not be more than 16 characters.
- **Volume Name** - Enter the storage volume name. The Volume name is displayed only for Universal Messaging (UM) docker images and represents the data volume for the docker container to persist the container data.
- **Docker Containers** - Enter the number of containers to instantiate for the service.

Click **Save** to create a new service.

To stop a service, from the **Services** screen, select a service that is in **Running** state and then click **Stop**. Click  and refresh the screen to view the latest service status.

To delete a service, from the **Services** screen, select a service that is not in **Running** state and then click **Delete**.

To start a service that is in **Stopped** state, select a service and then click **Start**. The launch service screen appears. Specify the number of **Docker Containers** to instantiate for the selected service and then click **Start**. Click  and refresh the screen to view the latest service status.

19

Switch to Cloud Deployment

■ Overview	666
■ Solutions	671
■ Monitoring Solutions	700
■ Database	713
■ Cloud Deployment CLI	716


Overview

Cloud deployment is the process of deploying packages and configurations that reside within on-premises runtimes or repositories to webMethods Integration Cloud. Using Software AG Designer or by employing the Continuous Integration (CI) approach, you can seamlessly deploy your on-premises webMethods Integration Server packages, Adapter packages, webMethods CloudStreams packages, configuration assets, and customized configurations to solutions created on Integration Cloud. In the cloud deployment context, configuration assets are limited to webMethods Integration Server and Universal Messaging configurations.

Note: As soon as you register, Cloud Deployment capability is enabled by default for all tenants.

Note: See *Deploying to webMethods Integration Cloud* for information on how to deploy packages and configurations that reside within on-premises runtimes or repositories to webMethods Integration Cloud. See the article on [“Software AG TECHcommunity”](#) website to get started on Cloud Deployment.

The following figure provides a high-level overview of the process involved in deploying on-premises webMethods Integration Server packages and configuration assets to Integration Cloud.



With Software AG Designer, you can deploy the webMethods Integration Server packages or configuration assets that you have created, verified, and tested on on-premises webMethods Integration Server or Universal Messaging to Integration Cloud. When you initiate the deployment from Software AG Designer, webMethods Integration Server packages and configuration assets are built from webMethods Integration Server and Software AG Command Central respectively, and are published to the Asset Repository available in Software AG Designer. After performing variable substitutions to make the on-premises configuration data compatible for cloud deployment, you can publish the packages and configurations to an asset repository provisioned for the tenant on Integration Cloud.


User Interface elements


The following table describes the various user interface elements that appear on the **Cloud Deployment** workspace:

Page Elements	Icon	Description
webMethods Cloud Deployment		Access the home page.
Solutions		View and create solutions, deploy

Page Elements	Icon	Description
Monitoring		<p>solutions to stages, view the Asset Repository, and manage webMethods Integration Server instances.</p> <p>View the overall status of the solutions, landscapes, system and runtime alerts, KPI graphs of the runtimes, service executions of the webMethods Integration Server instances, availability of the run times, alert status of the solutions, and logs.</p>
Runtime availability	<p data-bbox="690 1045 906 1108">Runtime availability of all solutions for the last 24hrs</p> 	<p>View the overall runtime availability for all the solutions in the last 24 hours.</p>
Usage Statistics	<p data-bbox="787 1318 987 1381">License Usage Total usage across all stages</p> 	<p>The usage statistics shows the CPU and Memory usage for all solutions in all stages.</p> <p>The CPU bar shows the maximum CPU that is licensed for the tenant. The colored part of the bar shows how much of the allowed CPU is currently used by the tenant.</p> <p>The Memory bar shows the memory in Gb that is licensed</p>

Page Elements	Icon	Description
Database		<p>for the tenant. The colored part of the bar shows how much of the allowed memory is currently used by the tenant.</p> <p>Add a database to your cloud deployment subscription. This enables you to configure, store, and monitor your database directly in the cloud instead of using external systems.</p>
Solutions section		<p>Total number of solutions created. View the <i>Solution List</i> page by clicking the <i>Details</i> link and the <i>Monitoring Dashboard</i> by clicking the <i>Monitoring</i> link.</p>
Service Executions section		<p>Number of service executions and their status in the last 24 hours for all the solutions that are currently available in the selected <i>Stage in view</i>. To view the <i>Services</i> page under <i>Monitoring</i>, click the <i>service execution</i> link.</p>

Page Elements	Icon	Description
Active Alerts section	 The icon shows a bell with a diamond inside, indicating no alerts. Below the bell, it says "No Open Alerts" and at the bottom, "0 Critical 0 Warning 0 Information".	Number of currently open alerts and their severity. Click on the links to go to the <i>Alerts</i> page.
Change the stage	 The icon is a blue button with the text "Stage in view" and "Development" below it.	Click to change and manage stages.
Application Launcher	 The icon is a blue square with a white grid pattern.	Click to access integration Apps.
Help	 The icon is a blue square with a white question mark inside a circle.	Access Help topics, Software AG TECHcommunity, Licensing capabilities, and the About page. The About page displays the version information, Global Support information, Copyright information, Impressum and Privacy Policy, and the release readme.
Profile	 The icon is a blue square with a white person silhouette inside a circle.	Name of the logged in user, profile information of the logged in user, and Logout option.

Page Elements	Icon	Description
Last Login, Notifications, and Help topics	<p>Last Login 07/20/2019 02:12:13</p> <p>Notifications</p>  <p>What's New</p> <p>Help Topics Cloud Deployment</p>	When was the last login, important and other notifications, what is new in this release, and context-sensitive help topics.

Solutions

A **Solution** consists of packages bundled together into one coherent service. It is a logical combination of webMethods Integration Server packages, Adapter packages, Services, webMethods CloudStreams packages, and webMethods Integration Server and Universal Messaging configuration assets or configurations.

Note: After deploying the configurations, due to webMethods Integration Server restart, the assets will appear after a short delay.

Integration Cloud Integrations can invoke Cloud Deployment webMethods Integration Server services for the same tenant. Using the predefined *Cloud Deployment Application* available in Integration Cloud, you can select the solution webMethods Integration Server services that you want to invoke from Integration Cloud.

Creating Solutions

The **Solution List** page displays the solutions created in Integration Cloud.

Note: You must have the required permissions under **Settings**  **> Access Profiles > Administrative Permissions > Functional Controls > Solution** to create, update, or delete Solutions.


Note: You must first create a solution in Integration Cloud before deploying the on-premises assets and configurations.

All solutions created are initially copied to the Development stage. You can create a new solution in any stage, for example, development, test, live, and prelive. Further, you cannot modify the solution name and clustering details after it is created. You can

configure the solution in subsequent stages but after you configure a solution in a stage, you cannot modify the solution again in that stage. In a stage, you can configure only those solutions that are marked as **Not Configured**.

To create a solution

1. Switch to the **Cloud Deployment** perspective.



As soon as you register, Cloud Deployment capability is enabled by default for all tenants. By default, 3 CPU core and 6 GB memory are allocated for all tenants. When you access Cloud Deployment for the first time using the application launcher, you need to start provisioning.

Start provisioning now

[No, thanks. Take me back to Integration Cloud](#)

After provisioning, your setup will be complete, and you can launch Cloud Deployment.

Setup Complete

Start experiencing Cloud Deployment now


Launch Cloud Deployment

Note: Solutions created using a trial account are deactivated daily. After you log in, you need to reactivate the solutions. All assets will be available after a short delay.

- After you launch Cloud Deployment, from the **Cloud Deployment** navigation bar, click **Solutions > Solution List**.


The **Solution List** page appears.

- From the **Solution List** page, click **Create New Solution** to create a solution. You can create a solution in any stage.
- Select the landscape model that best represents your environment. The available designs are an webMethods Integration Server with a Terracotta server, an webMethods Integration Server with a cluster and a Terracotta server, or webMethods Integration Servers with a Universal Messaging cluster and a Terracotta stripe. Your packages, assets, configurations, and services are deployed automatically onto the selected landscape.



- Click **OK**.
- In the **New Solution** page, fill in the solution **Name**, the solution **Description**, the name of the webMethods Integration Server and Universal Messaging instances, number of CPU **Cores**, and **Memory** characteristics of the hardware to support each service in the solution landscape.

Note: You can also select the webMethods Integration Server and Universal Messaging icons to highlight the sections in the **New Solution** page. Terracotta is available only when webMethods Integration Server runs in a clustered mode. Further, clustering and Terracotta options are not available in the **Development** stage.



The **Version** list box lists all the available major versions. The solution will be created based on the available **Fix** version. webMethods Integration Server packages such as WmCloudStreams and WmJDBCAdapter will appear in the **Packages** group box based on the **Fix** version. Select the **Packages** you want to enable. After you save the solution, you will not be able to change the major **Version**. You can change only the number of CPU Cores, Memory, Fix version if available, and Packages.

You can deploy CloudStreams provider packages, CloudStreams connector services, CloudStreams connection, and CloudStreams connector listeners to a solution in Cloud Deployment only if you have selected WmCloudStreams as the package option while creating the solution.

On the **Landscape** page, select the **Cluster Type** as **Stateless** if the group of webMethods Integration Servers function in a manner similar to a cluster but are not part of a configured cluster. A stateless cluster of webMethods Integration Servers does not use a Terracotta Server Array. Select **Stateful** to add the Terracotta section. The Terracotta icons will be activated.

The **Hot Fix** list box lists all available fixes that include enhancements to versions. **Hot fix** field is optional. Selecting **None** option will remove the hotfixes applied on the solution, and the solution will point to the base fix version. Typically, hotfixes are created for specific tenants.

Note: After creating a solution, if you modify the package list options in the **Packages** group box and save the solution, due to webMethods Integration Server restart, the assets will appear after a short delay.

Updating products to a higher fix version in a solution

You can update any product in a solution to the available higher fix version after you create the solution. The **Update Available** option appears if a higher fix version is available for any of the products in the solution. The latest fix version appears in the **Fix** drop-down list. For example, if you have selected Fix 3 of webMethods

Integration Server while creating a solution, and if Fix 4 is now available, you can select Fix 4 and save the solution.

Note: While configuring a solution in a higher stage, the fix version of the products in the solution will be taken from the lower stage. If a solution is updated in a lower stage, you will be given an option to update the solution in the higher stage, to the fix versions of the products in the lower stage.

For example, if you configure a solution in a higher stage (Test stage) and then go back to a lower stage (Development stage), and if a higher fix version is available for a product in the Development stage, you can click **Update Available**, and in the **Edit Solution** screen, you can select the higher fix version for the product in the solution. Now if you go to the higher stage (Test), the **Update Available** option will appear in the Test stage. You can update products in a solution at every stage, to the fix versions of the products in the solution available in the immediate lower stage. Note that after you update or update the products in the solution, the products in the solution will not be accessible for sometime.

Updating products to a higher version in a solution

You can update any product in a solution to the available higher version after you create the solution. The **Update Available** option appears if a higher version is available for any of the products in the solution. The latest version appears in the **Version** drop-down list. For example, if you have selected 10.3 of webMethods Integration Server while creating a solution, and if 10.5 is now available, you can select version 10.5 and save the solution. Further, if you update to v10.5, the latest available fix for v10.5 will be automatically selected.

Note: While configuring a solution in a higher stage, the version of the products in the solution will be taken from the lower stage.

If a higher version is available for a product in a stage, you can click **Update Available**, and in the **Edit Solution** screen, you can select the higher version for the product in the solution.

The **Schedule** option appears if you select a higher version available for any of the products in the solution. Click **Schedule** to schedule the update process by specifying the date and time on which you want the update process to execute. Once the solution is scheduled for update, you can click **Cancel Schedule** to cancel the schedule or click **Modify Schedule** to modify the schedule. If the update process is scheduled, the status of the solution on the **Solution List** page displays **Update scheduled**. The status of the solution on the **Solution List** page displays **Update in progress** if the scheduled update process is under way.

Note: After a solution is updated successfully, ensure that you click **Confirm Update** within seven days to complete the update process or click **Rollback** to rollback the solution to the previous version. After seven days, except for the **Confirm Update** and **Rollback** options, the solution page will not be available. If you rollback, the status of the solution on the **Solution List** page


displays **Rollback in progress** until the solution is rolled back to the previous version.

7. The **Tracing** list box appears only if you have the App Dynamics capability and if you are currently using AppDynamics to trace end to end business flows. It allows you to trace logs after you create or update a solution for an webMethods Integration Server runtime. Currently, tracing support is provided only for the webMethods Integration Server runtime. Select **AppDynamics** from the drop-down list to provide the AppDynamics tracing support and upload a valid Controller XML and Config XML file containing the Appdynamics details. You can update the controller file for each webMethods Integration Server runtime. You also have the option to download the controller and config files and then upload the files after modifying them.


Note: If you select AppDynamics tracing and provide a valid controller file, the tracing data will appear on the AppDynamics cloud application.

Let us see an example of how the tracing data appears on Appdynamics when you create a solution in Cloud Deployment.


- a. Go to <https://www.appdynamics.com/> and register in AppDynamics.
- b. On the Overview > Applications panel, click **Get Started**.



- c. On the Getting Started wizard, click **Java** under the Applications panel.



- d. Download the Java Agent Installer.



- e. Go to the ver<xxx> > **conf** folder on your local system and view the controller-info.xml and app-agent-config.xml files.
- f. Open the controller-info.xml file and provide the following values:
- ```
<application-name>MyApplication</application-name>
<node-name>AppIS</node-name>
```
- g. Log in to Integration Cloud and switch to Cloud Deployment using the App switcher.
- h. Create a new solution in Cloud Deployment and select **AppDynamics** from the drop-down list to provide the AppDynamics tracing support. Upload the controller-info.xml and app-agent-config.xml files, and save the solution.



- i. Log in to AppDynamics. Your application, that is, **MyApplication** appears on the Applications panel.
- j. Click on MyApplication and view the service execution status and execution logs.

The screenshot shows the AppDynamics interface with the 'Transaction Snapshots' view selected. The table below represents the data shown in the interface:

| Time                | Exe Time (ms) | URL                                      | Business Transaction              | Tier   | Node |
|---------------------|---------------|------------------------------------------|-----------------------------------|--------|------|
| 07/22/19 2:53:22 PM | 2             | invoke/wm.server.query/getPrometheusS... | invoke/wm.server.query            | MyTier | App5 |
| 07/22/19 2:47:51 PM | 3             | invoke/wm.server.monitoring/getMetaM...  | invoke/wm.server.monitoring       | MyTier | App5 |
| 07/22/19 2:47:21 PM | 1             | invoke/wm.server.disconnect              | invoke/wm.server                  | MyTier | App5 |
| 07/22/19 2:47:13 PM | 1             | invoke/wm.server.spm.runtimeStatus/ch... | invoke/wm.server.spm.runtimeSt... | MyTier | App5 |
| 07/22/19 2:43:21 PM | 2             | invoke/wm.server.query/getPrometheusS... | invoke/wm.server.query            | MyTier | App5 |

- Click **Save** to save the solution.

The new solution is created and appears in the **Solution List** page. You cannot modify the solution after the solution is created. You can configure the solution in subsequent stages but once a solution is configured in a stage, you cannot modify the solution again in that stage.

**Note:** You can now deploy the solution to the next stage.

### Deactivate, Activate, and Delete a solution

Click the  icon and select **Deactivate** to deactivate a solution. All packages and assets will be permanently deleted and cannot be recovered. Click the  icon and select **Activate** to activate an inactive solution.



Click the  icon and select **Delete** to permanently delete the solution. If a solution is configured in a subsequent stage, it will be permanently deleted from the current stage and cannot be recovered. Further, if you delete the solution, you will not be able to promote assets from the current stage.

## Exploring Solutions


The solution details page allows you to view the packages, assets, configurations and services for different runtimes in the solution, deploy the solution to another stage, view the Asset Repository, and manage the solution, that is, view the landscape, configure

webMethods Integration Server service access settings, administer the webMethods Integration Server, or restart the webMethods Integration Server instances.

**Note:** You can create a new solution in any stage. You can configure the solution in subsequent stages but after you configure the solution in a stage, you cannot modify it again in that stage.


### To view the Solution Explorer

1. Switch to the **Cloud Deployment** perspective.



2. From the **Cloud Deployment** navigation bar, click **Solutions > Solution List**.  
The **Solution List** page appears listing all the solutions.
3. Click on an existing solution. The Solution Explorer page appears.

### Solution Explorer



The following table provides a high-level overview of the Solution Explorer page:

| Component                                      | Description                                                                                                                                                                                |
|------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">“Assets” on page 680</a>           | View the Packages, Folders, Assets, and Services for webMethods Integration Server, Adapters, webMethods CloudStreams packages, and configurations for the Universal Messaging runtime.    |
| <a href="#">“Deploy” on page 690</a>           | Deploy the solution to another stage.                                                                                                                                                      |
| <a href="#">“Asset Repository” on page 689</a> | View the Asset Repository which displays the contents of the on-premises packages published to Integration Cloud.                                                                          |
| <a href="#">“Manage” on page 695</a>           | View the landscape, configure webMethods Integration Server service access settings, administer the webMethods Integration Server, or restart the webMethods Integration Server instances. |


## Assets

A package is a container that is used to bundle services and related elements, such as specifications, webMethods Integration Server document types, webMethods Integration Server schemas, and triggers. When you create a folder, service, webMethods Integration Server document type, or any element, you save it in a package.

**Note:** To view and access webMethods Integration Server packages in Integration Cloud, you must assign any custom user groups created in webMethods Integration Server, which are assigned to Access Profiles in the **Solution Permissions** page, to the following Access Control Lists in webMethods Integration Server:

- Administrators ACL
- Developers ACL
- Replicators ACL

The following figure depicts the package structure in a solution.



Packages are designed to hold all of the components of a logical unit in an integration solution. For example, you might group all the services and files specific to a particular marketplace in a single package. All the components that belong to a package reside in the package's subdirectory.

**Note:** Click the arrow beside a folder or package to view its contents.


### Downloading assets

You can download user deployed packages and configurations from the **Asset** page. To download assets, point to an asset, click the  icon, and then click **Download**. The assets will be zipped and downloaded to your local storage space.

**Note:** You cannot download default packages such as packages that come with webMethods Integration Server installation, for example, Default, WmART, WmCloud, WmJDBCAdapter, WmPublic, and so on.

### Services

Services are method-like units of logic that operate on documents. You build services to carry out work such as extracting data from documents, interacting with back-end resources (for example, submitting a query to a database or executing a transaction on a mainframe computer), and publishing documents. Adapters and other add-on packages provide additional services that you use to interact with specific resources or applications. The service editor allows you to view and run the services.



## Service Signature

Input and output parameters are the names and types of fields that the service requires as input and generates as output. These parameters are also collectively referred to as a *signature*. You declare a signature for all types of services: flow services, Java services, and services written in other supported programming languages.

For a flow service, the input side describes the initial contents of the pipeline. In other words, it specifies the variables that this flow service expects to find in the pipeline at run time. The output side identifies the variables produced by the flow service and returned to the pipeline. An `webMethods Integration Server` document type can also be used to define the input or output parameters for a service.

Click **Test** to run the service after providing the data to pass into the service.

## Service Editor

Use the service editor to view the services. The source code, properties, inputs, and outputs are read only. The editor has the following tabs:

- **Source** tab contains the code or flow for the service.
- **Input/Output** tab contains the input and output signature of the service.
- **Logged Fields** tab indicates the input and output parameters for which the data is logged. You define the data to pass into the service by defining the input parameters on the lower panel of the editor.

## Load pipeline for testing services

The pipeline is the general term used to refer to the data structure in which input and output values are maintained for a service in Software AG Designer. The pipeline holds the input and output for a service. The pipeline starts with the input to the service and collects inputs and outputs from subsequent services. When a service runs, it has access to all data in the pipeline at that point.

When you run a service in Software AG Designer, you can click **Save** and save the pipeline data as an XML document to your local file system. After you deploy the

service, you can click the **Load Data** option in the service editor to select the XML file, and load or update the pipeline data to test the service.

**Note:** Integration Cloud Integrations can now invoke Cloud Deployment webMethods Integration Server services for the same tenant. A new pre-defined Application, *Cloud Deployment*, is added in Integration Cloud. Using this Application, you can select the solution webMethods Integration Server services that you want to call from Integration Cloud.

**Note:** See the *webMethods Service Development Help*, *webMethods Integration Server Administrator's Guide*, and the *webMethods Adapter for JDBC Installation and User's Guide* for detailed descriptions of all the services and document types including Adapter services.

### Displaying the API details of an executable service

After deploying assets, on the Asset explorer page, click the *API Details* option to view the API details of the service such as the HTTP Method, URL, Input structure, and the parameters that are required to invoke this service from an external system, for example, a REST client. You can copy the required API details to execute the service from the external system.

**Note:** The *API Details* option appears only for executable services. Some examples of executable services are Adapter services, Flow services, Java services, Flat File Schema, and Map services.

**Note:** You will be able to execute a Flat File Schema by using *only* the SoapUI tool. You must specify the following settings in the SoapUI tool:

- Set the following query parameters in the **Request** section:

skipWhiteSpace = true

encoding = UTF8

file = file:file1

- In the **Attachments** section, browse for the source file and update the following column values:

Name = file1

ContentID = file

## Support for GraphQL Assets

### Overview

GraphQL is a query language designed to build client applications by providing a flexible syntax and system for describing their data requirements and interactions. Using GraphQL service, you query a specific data to the server and get the response in a predictable way.

Cloud Deployment allows you to deploy GraphQL assets, which are developed using Software AG Designer and on-premises webMethods Integration Server, to Cloud Deployment. You choose from predefined solution landscapes to deploy your on-premises assets from Software AG Designer.

Let us see an example of how we deploy GraphQL assets which are developed using Software AG Designer and on-premises webMethods Integration Server to Cloud Deployment.

## Preconditions

### Create a GraphQL Schema

Create a GraphQL schema using SDL (Schema Definition Language). A sample schema is shown below:

```

type Query {
 dog: Dog
 findDog(complex: ComplexInput): Dog
 booleanList(booleanListArg: [Boolean!]): Boolean
 arguments: Arguments
 human: Human
 pet: Pet
 name: String!
 Name: String!
 catOrDog: CatOrDog
}
enum DogCommand { SIT, DOWN, HEEL }
type Dog implements Pet {
 name: String!
 nickname: String
 barkVolume: Int
 doesKnowCommand(dogCommand: DogCommand!): Boolean!
 isHousetrained(atOtherHomes: Boolean): Boolean!
 owner: Human
}
interface Sentient {
 name: String!
}

```

### Implementing GraphQL Descriptor in Integration Server and Designer

You use the Service Development perspective to create a new GraphQL descriptor based on the schema.

- In the Designer perspective, select **File > New > GraphQL Descriptor**.
- In the New GraphQL Descriptor dialog box, select the folder in which you want to create the *GraphQL descriptor*.
- In the **Element name** field, type a name for the *GraphQL descriptor* using any combination of letters, numbers, and/or the underscore character.
- Click **Next**.
- In the Select the GraphQL Schema Location wizard, browse and select the schema file.

**Note:** Ensure that the format of the schema file is .txt, .json, .graphql, or .graphqls.


- Click **Finish**.
- Designer creates the *GraphQL descriptor* and displays the details in the *GraphQL descriptor* editor.

### Build Resolver Services for the GraphQL Descriptor

Integration Server creates the following assets when you import a GraphQL schema:


- A GraphQL descriptor with the name as provided by the user.

When you create a GraphQL descriptor using the above GraphQL schema with name *Gq*, then Designer creates folders with name *types* and *resolvers* under *Gq* folder like this:



All the document types are created under the *types* folder and all the resolver services are created under the *resolvers* folder.

If you import the above schema in Integration Server with name *Gq*, then Integration Server creates the resolver services for Query operation under *Gq/resolvers/Query* folder, and the resolver services for Mutation operation under *Gq/resolvers/Mutation* folder.



The resolver will have the input/output signature set.

## Deploy Assets to Cloud Deployment

Using Designer, you deploy your on-premises Integration Server GraphQL packages and assets to Cloud Deployment. Before deploying the packages and assets, you must configure a connection to Integration Cloud.

Before you configure a connection to Integration Cloud, ensure that the following criteria are met:

- A valid URL exists to connect to Integration Cloud.
- A valid user account is created on Integration Cloud.

### To add a connection configuration for Integration Cloud

- In Designer, select **Window > Preferences**.
- In the preferences navigation tree, select **Software AG > Integration Cloud**.
- Click **Add**.
- In the **Add connection configuration** dialog box, enter the following information:

| Field       | Description                                                        |
|-------------|--------------------------------------------------------------------|
| <b>Name</b> | The name to use for the Cloud Deployment connection configuration. |

**Note:** The name cannot contain control characters, special characters, and characters outside of the basic ASCII character set, such as multi-byte characters.

| Field                                                | Description                                                                                                                                                                                                                                                                                              |
|------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>URL</b>                                           | URL of the Cloud Deployment host to which Designer is to connect. For example, <code>https://&lt;sub-domain&gt;.&lt;domain-name&gt;.&lt;domain-suffix&gt;</code> .                                                                                                                                       |
| <b>User</b>                                          | The user name for an account on Cloud Deployment.                                                                                                                                                                                                                                                        |
| <b>Password</b>                                      | The password for the specified <b>User</b> .                                                                                                                                                                                                                                                             |
| <b>Save password (in the Eclipse secure storage)</b> | Indicates whether the password for the specified user account should be saved in Eclipse secure storage. Cloud Deployment uses this password from the Eclipse secure storage whenever user authorization is required. If you want to save the password in Eclipse secure storage, select this check box. |

A connection configuration is now added to the Connections page with the specified details.

#### To deploy assets to Cloud Deployment

1. In Package Navigator view, select the Integration Server package that you want to deploy to Cloud Deployment.
2. Right-click the GraphQL package and click **Deploy to Cloud**.


#### Verify the Deployed Assets in Cloud Deployment

After publishing the GraphQL packages to an asset repository provisioned for the tenant on Cloud Deployment, you can view and access the webMethods Integration Server packages in Cloud Deployment. The solution details page allows you to view the packages, assets, and services for GraphQL runtimes in the solution.

To view the GraphQL packages in the Solution Explorer:


1. Switch to the Cloud Deployment perspective.
2. From the Cloud Deployment navigation bar, click **Solutions > Solution List**.
3. Click on an existing solution. The Solution Explorer page appears.

The Solution List page appears listing GraphQL solutions.



### Displaying the API details of an executable service


After deploying assets, on the Asset explorer page, click the  icon to view the API details of the service such as the HTTP Method and URL that are required to invoke this service from an external system. You copy the required API details to execute the service from the external client.



### Service Execution from External Client

To execute the service from a third party tool, let us use Postman as the GraphQL client. So in this example, when we open the GraphQL client, and invoke the

URL as shown below, we get the output as per the fields passed in the query.



## Asset Repository

The **Asset Repository** page (**Cloud Deployment > Solutions > Asset Repository**) displays the list of all solutions and the user-created assets. You can also view the asset type, version of the assets, and services. Before deploying packages and configurations from Software AG Designer, you must create a solution in Integration Cloud to which you want to deploy the configuration assets. Software AG Designer deploys the assets and configurations to the Asset Repository in Integration Cloud.

### Asset Repository for all solutions

The following figure depicts the Asset Repository structure for all solutions.

| Name    | Type                | Version |
|---------|---------------------|---------|
| bankSol | Solution            |         |
| bankIS1 | Integration Server  |         |
| bankum  | Universal Messaging |         |
| paySol  | Solution            |         |
| payis1  | Integration Server  |         |
| payis2  | Integration Server  |         |
| payum   | Universal Messaging |         |

### Asset Repository for a selected solution

The **Asset Repository** page for a solution (**Cloud Deployment > Solutions > Select a Solution > Asset Repository**) displays the assets for the selected solution, including the asset type and version of the assets.

The following figure depicts the Asset Repository structure for a selected solution.

| Solutions > bankSol |        | Type                | Version |
|---------------------|--------|---------------------|---------|
| Assets              | bankS1 | Integration Server  |         |
| Deploy              | bankum | Universal Messaging |         |

## Downloading packages and assets

You can download user deployed packages and configurations from the **Asset Repository** page. You can either download individual packages or the whole repository for each product. To download assets, point to an asset or product and click the  icon. The assets including ACDL files will be zipped and downloaded to your local storage.

## Deploy

After publishing the assets and configurations that reside within on-premises runtimes or repositories to webMethods Integration Cloud, you can promote them from the previous stage to the current stage. Within a tenant, you can promote assets from a solution to another solution, from a previous stage to the current stage, for the same runtime type. You can promote assets if the source runtime version is lesser than or same as the target runtime version.

If you are in the **Development** stage, click the **Change Stage To View** link to change the stage. Only active and accessible stages appear in the drop-down list for selection in the **Stage to view** field. Select a different stage other than Development and click **Submit**.


In the next stage, select a solution and then click **Deploy**. Select a runtime instance. All *solutions* of the previous stage will be listed on the left panel. The right panel will list all the assets of the selected solution in the current stage for the selected runtime instance.

**Note:** You will *not* be able to promote assets from a higher version solution to a lower version solution. For example, if you have a v10.4 solution in the source stage and a v10.3 solution in the current stage, you will not be able to promote the v10.4 assets to the current stage.

The screenshot shows a deployment interface. At the top, there is a 'Select Instance' dropdown menu set to 'IS104'. Below this, there are two tabs: 'DEPLOY' and 'HISTORY'. The 'DEPLOY' tab is active and shows a 'Development' stage. On the left, there are two solution cards: 'sol103' and 'Sol104', each with an orange cube icon and a '1 Instance(s)' label. On the right, there is a 'Test' stage with a 'Rollback' and 'Delete' button. Below the 'Test' stage, there is a list of packages under a 'Packages' folder: 'CT\_UIMtestPackage', 'FlatFileDemo', and 'CT\_Samplepackage', each with a checkbox and an orange cube icon.

**Note:** You can access a stage only if your Access Profile is assigned to the stage.

Click on a solution and select the runtime package folder. Then click on the runtime instance. The assets of the solution corresponding to the selected runtime instance will appear. Select the assets and then click **Promote** to promote the assets to the current stage (right panel).



After you click **Promote**, the **Promote Assets** dialog box appears for the selected asset.

Select an asset and change the values for the variable substitution properties, if needed. The variable substitution properties appear for the selected asset, only if the asset has properties. If there are any similar type of assets for which you want the same values, then select the **Show similar assets to apply values** option. Then select the assets in the lower panel. Click **Apply** to apply the property values to the selected assets. The changed values will be applied to all the selected similar assets during promotion.

On the **Promote** dialog box, you can type a message to describe the promotion. The promotion message will appear on the **History** page.

Click **Simulate Promote** to check the consistency of the assets and their dependencies. If there are dependencies, then for a successful promotion, you have to select all the dependent assets. Select **Save and Promote** to save the variable substitution and promote the assets to the next stage.


On the **Deploy** page, click **Rollback** to rollback *all* promoted assets to their previous state.

You can type a message to describe the rollback. The rollback message will appear on the **History** page.

### Deleting assets

On the **Deploy** page, you can delete an asset from the current stage (right panel). The asset will be deleted from the asset repository in that stage as well as from the runtime.

**Note:** Currently you can delete only webMethods Integration Server packages and not webMethods Integration Server and Universal Messaging configurations.



### History

The **History** page shows the **Trace ID**, that is, the tracking ID, which is automatically generated on every successful or unsuccessful promotion, rollback, or deletion, the **Deployment, Rollback, or Deletion Action, Date** when the asset was promoted, rolled back, or deleted, the **User** who promoted, rolled back, or deleted the asset, and the

commit **Message** for the selected instance. You can click on a **Trace ID** to see the Track History for the specific action.


The **Track History** window displays the following details:

- **Timestamp** - The date and time when the log was generated.
- **Product** - The product that was promoted or rolled back.
- **Log Level** - Information on whether the log type is an Error, Info, or Debug.
- **Message** - Log or status message.

**Note:** Promotion, rollback, or deletion details appear only for the current stage.

## Capability

The **Capability** ([?](#) > Licensing) page allows you to view the status of some of the system capabilities, based on your license offering.



You can view the details of the following capabilities in **Integration Cloud**:

| Field                            | Description                                                                             |
|----------------------------------|-----------------------------------------------------------------------------------------|
| <b>Allowed application count</b> | Total number of Applications that can be utilized by the tenant.                        |
| <b>On-premises connection</b>    | If <b>Yes</b> , then on-premises applications can be uploaded from on-premises systems. |
| <b>Max allowed users</b>         | Maximum number of active users allowed for the tenant.                                  |
| <b>Allowed number of stages</b>  | Maximum number of staging environments allowed for the tenant.                          |

| Field                                 | Description                                                                           |
|---------------------------------------|---------------------------------------------------------------------------------------|
| <b>Integration restart and resume</b> | Integrations can be restarted and resumed.                                            |
| <b>Integration import and export</b>  | Integrations can be imported and exported.                                            |
| <b>Trial account</b>                  | If <b>Yes</b> , then the account is a trial account.                                  |
| <b>Trial end date</b>                 | The trial period end date. This field appears only if the account is a trial account. |

You can view the details of the following capabilities in **Cloud Deployment**:

| Field                           | Description                                                                                                                                                                       |
|---------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Max allowed cores</b>        | Maximum number of CPU cores allowed across all active solutions and all stages for the tenant. You will not be able to create additional solutions if you exceed this capability. |
| <b>Max allowed memory</b>       | Maximum memory capacity allowed across all active solutions and all stages for the tenant. You will not be able to create additional solutions if you exceed this capability.     |
| <b>Allowed number of stages</b> | Maximum number of staging environments allowed for the tenant.                                                                                                                    |
| <b>Trial account</b>            | If <b>Yes</b> , then the account is a trial account.                                                                                                                              |
| <b>Trial end date</b>           | The trial period end date. This field appears only if the account is a trial account.                                                                                             |

## Usage

The **Usage** page allows you to view the current usage of CPU cores and Memory (GB) for all the active solutions in all the stages.

To access this page, from the Cloud Deployment navigation bar, click  and select *Licensing > Usage*.


## Copying Solutions

The **Solution List** page allows you to copy solutions in any stage. Copying solutions allows you to have a back up of your solution before you make any changes and deploy your solution to production. This reduces the risk of not having a back up in case you want to revert to the original solution.

**Note:** If you have the required permission under **Settings**  > **Access Profiles** > **Administrative Permissions** > **Functional Controls** > **Solution**, you can copy, update, and delete solutions.

### To copy a solution

1. Switch to the **Cloud Deployment** perspective.



2. After you launch Cloud Deployment, from the **Cloud Deployment** navigation bar, click **Solutions** > **Solution List**.


The **Solution List** page appears.

3. On a solution, click  > **Create a copy**.



4. On the **Create a copy** page, fill in the new solution **Name**.

You can choose to copy solutions using the same configuration and services in the solution landscape by clicking the **Create with original configuration** option or modify the configuration and services in the solution landscape by clicking the **Create with modified configuration** option.



5. Select **Create with modified configuration** and specify additional configuration of the solution, if necessary. Then click **Configure** to save the configuration details.

The new solution is created and appears on the **Solution List** page.

**Note:** You can now deploy the new solution to the next stage.

### Deactivate, Activate, and Delete a solution

Click the  icon and select **Deactivate** to deactivate a solution. All packages and assets will be permanently deleted and cannot be recovered. Select **Activate** to activate an inactive solution. Select **Delete** to permanently delete a solution.

## Managing Solutions

The **Manage** options allow you to view the solution landscape, configure webMethods Integration Server service access settings, administer the webMethods Integration Server, or restart the webMethods Integration Server instances.

### Landscape

The **Landscape** page displays the landscape configuration for the selected solution.


**Note:** You cannot modify the solution landscape configuration in the Development stage after the solution is created. You can *configure* the solution in subsequent stages but after a solution is configured, the solution cannot be modified again in that stage. Further, clustering and Terracotta options are not available in the Development stage.

**Note:** In a stage, you can configure only those solutions that are marked as **Not Configured**.

---

### To view the landscape configuration for a solution

1. Switch to the **Cloud Deployment** perspective.



2. From the **Cloud Deployment** navigation bar, click **Solutions > Solution List > Select a solution > Manage > Landscape**.
3. On the **Landscape** page, you can view the landscape configuration design, landscape solution name and description, and the landscape components. For each landscape component, you can view the landscape component name, product type, whether the landscape component is in a ready state, and the number of CPU cores and memory characteristics of the hardware to support each service in the solution.
4. Terracotta is available only when webMethods Integration Server runs in a clustered mode. Further, clustering and Terracotta options are not available in the **Development** stage.

On the **Landscape** page, select the **Cluster Type** as **Stateless** if the group of webMethods Integration Servers function in a manner similar to a cluster but are not part of a configured cluster. A stateless cluster of webMethods Integration Servers does not use a Terracotta Server Array. Select **Stateful** to add the Terracotta section. The Terracotta icons will be activated.


## Service Access Settings

The **Service Access Settings** page allows you to configure the webMethods Integration Server services to be called externally over HTTPS. The services will be available to consumers based on the **Allow All** and **Deny All** access modes.

---

### To configure service access settings

1. Switch to the **Cloud Deployment** perspective.



2. From the **Cloud Deployment** navigation bar, click **Solutions > Solution List > Select a solution > Manage > Service Access Settings**.
3. On the **Service Access Settings** page, configure the webMethods Integration Server services to be called externally over HTTPS. Required fields are marked with an asterisk on the screen.

| Field                            | Description                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|----------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Base URL</b>                  | The base URL is a part of the complete service URL, for example, <code>https://wmic1.saglive.com/integration/clouddeployment/service/development/test/tt54/invoke/pub.*</code>                                                                                                                                                                                                                                                                 |
| <b>Solution Alias</b>            | An alias for the solution in the base URL. The alias name for a solution is unique in that particular stage. For example, if the completed service URL is <code>https://wmic1.saglive.com/integration/clouddeployment/service/development/test/tt54/invoke/pub.*</code> , then the Solution Alias is <code>test</code> , the webMethods Integration Server instance is <code>tt54</code> , and the service URL is <code>/invoke/pub.*</code> . |
| <b>Select Integration Server</b> | Select the solution webMethods Integration Server instance where the services need to be configured.                                                                                                                                                                                                                                                                                                                                           |
| <b>Access Mode</b>               | Ensure that the access mode of the services are properly set.<br><br>Select <b>Deny All</b> if you want to deny most of the services to be invoked and allow a few. Then click <b>ADD</b> to add services to the <b>Allowed Services</b> table. In the <b>Add Service</b> window, the <b>Base URL</b> is a part of the complete service                                                                                                        |

| Field | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|-------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|       | <p>URL. In the <b>Service URL</b> field, type the webMethods Integration Server Service URL. The Base URL and the Service URL together forms the complete service URL.</p> <p>Select <b>Allow All</b> if you want to allow most of the services to be invoked and deny a few. Click <b>ADD</b> to add services to the <b>Denied Services</b> table. In the <b>Add Service</b> window, the <b>Base URL</b> is a part of the complete service URL. In the <b>Service URL</b> field, type the webMethods Integration Server Service URL. The Base URL and the Service URL together forms the complete service URL.</p> <p><b>Note:</b>You can update the service URL by clicking the <b>Edit</b> icon beside the service URL in the services table.</p> <p>The services will be available to be invoked from a software application, for example, a REST client, after you add the services to the table.</p> <p>For example, the Service URL <i>/invoke/pub.math:addInts</i> has the following components:</p> <ul style="list-style-type: none"> <li>■ Directive - <i>Invoke</i></li> <li>■ Namespace of the service - <i>pub.math:addInts</i></li> </ul> <p><b>Note:</b>You can match all services to be allowed or denied by typing <i>*</i> at the end of the Service URL. For example, if you have two services, service url1: <i>/invoke/pub.date:formatDate</i> and service url2: <i>/invoke/pub.date:getCurrentDate /invoke/</i>, then instead of typing two entries, you can provide only one entry, service url: <i>/invoke/pub.date.*</i>. All services matching <i>pub.date</i> will be allowed or denied.</p> |

## Administration

Use this page to manage a solution webMethods Integration Server Administrator instance.




## Restart

Restart the server when you need to stop and reload the server. You should restart the server when:

- You make certain configuration changes. Some configuration changes require the server to be restarted before they take effect.
- If you encounter an operational problem or the server is in an inconsistent state.

### To restart the server

1. Switch to the **Cloud Deployment** perspective.



2. From the **Cloud Deployment** navigation bar, click **Solutions > Solution List > Select a solution > Manage > Restart**.

**Note:** webMethods Integration Servers running in a clustered mode cannot be restarted. Further, restarting servers will terminate all active sessions.

3. Click **Restart**.

## Monitoring Solutions

The Monitoring part of **Cloud Deployment** enables you to monitor the health and availability of the solutions and run-time instances, alerts and alert statuses. You receive an email whenever there is a condition that might affect the solution.

The monitoring of a new solution starts automatically 10 minutes after the creation of the solution. The data of the solution is collected and analyzed every 60 seconds.

You can access the following monitoring pages from the left-side navigation menu of the Monitoring main page:

- [“Dashboard” on page 701](#)
- [“Solutions” on page 702](#)
- [“Runtimes” on page 703](#)
- [“Services ” on page 707](#)

- [“Uptime” on page 708](#)
- [“Alerts” on page 708](#)
- [“Logs” on page 712](#)

You can filter the information on most Monitoring pages based on time. To specify the time-range, select a value in the time-range selector.

The following table describes the options in the time-range selector.

| Option | Description                                              |
|--------|----------------------------------------------------------|
| 12h    | Displays the information for the last 12 hours.          |
| 24h    | Default. Displays the information for the last 24 hours. |
| 2d     | Displays the information for the last 2 days.            |
| 1w     | Displays the information for the last week.              |
| 2w     | Displays the information for the last 2 weeks.           |
| 3w     | Displays the information for the last 3 weeks.           |
| 4w     | Displays the information for the last 4 weeks.           |

To navigate to the Monitoring main page, log in to Integration Cloud, switch to the **Cloud Deployment** perspective, and select **Monitoring** in the Cloud Deployment navigation bar.

## Dashboard

On the Dashboard page, you can view:

- The health of the solutions
- The number of the alerts that have been raised for all the solutions
- The landscape view of the solutions, and the number of alerts for all run-times that are part of the solutions

The following table provides more information about the panes on the Dashboard page.

| Pane               | Description                                                                                    |
|--------------------|------------------------------------------------------------------------------------------------|
| Overall KPI Status | Shows the following information about the health of the solutions for the selected time range: |

| Pane       | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|            | <ul style="list-style-type: none"> <li>■ Total number of solutions</li> <li>■ The number of healthy solutions</li> <li>■ The number of unhealthy solutions</li> <li>■ The health of the solutions, as a percentage value calculated by the formula (Number of healthy solutions / total number of solutions) * 100</li> </ul> <p>A healthy solution is a solution without any open critical alerts.</p> <p>An unhealthy solution is a solution which has at least one open critical alert.</p> <p>To see more information about the KPI status of the solutions, click <b>More Details</b>.</p> |
| Alerts     | <p>Shows the total number of open and resolved alerts that have been raised for all solutions for the selected time-range, and the number of alerts from each type: critical, warning, or information.</p> <p>To see more details about the alerts, click <b>More Details</b>.</p> <p>For more information about the alert types, see <a href="#">“Alert Types” on page 710</a>.</p>                                                                                                                                                                                                            |
| Landscapes | <p>Displays the topology of the solutions and the number of alerts for each run-time type since the solution has been activated.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                            |

By default, the page displays information for the last 24 hours. To view the information for a different time period, use the time-range selector. For more information about the time-range selector, see [“Monitoring Solutions” on page 700](#).

## Solutions

On the Solutions page, you can check the health of the run-time instances from all the solutions. For each run-time instance, you can view the current data, and the data for the last 24 hours.

The health metrics are grouped into three categories:

- Memory - indicate the memory utilization of a run-time.
- Uptime - indicate the availability of a run-time.
- Failures- indicate failures of the run-time


The following table describes the icons on the Solutions page.

| Icon                                                                              | Description                                                                                                                                                         |
|-----------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|  | Normal health of the run-time instance.                                                                                                                             |
|  | The health of the run-time instance is deteriorating. Take preventive measures.                                                                                     |
|  | There are critical issues with the health of the run-time instance. Your urgent attention is needed.                                                                |
|  | The run-time instance is not available.                                                                                                                             |
| <b>Note:</b>                                                                      | If the solution uses an Integration Server cluster, the number of Integration Server instances is indicated in brackets after the Integration Server instance name. |

To view more details about a run-time instance on the Runtime page, click the name of the run-time instance.

## Runtimes

On the Runtimes page, you can view the graphs for monitored KPIs for the selected run-time instances from all the solutions.



The example image shows the graph for the Used Memory KPI. The horizontal lines below the graph represent the severity and duration of the alerts that were raised for the KPI. The information alerts are displayed in blue, the warning alerts are in orange, and the critical alerts are in red.

The following table describes the meaning of the alert lines from the example graph for the Used Memory KPI.

| Time Period | Details                                                                  |
|-------------|--------------------------------------------------------------------------|
| 1           | Until 2:05 h, there had been an open information alert.                  |
| 2           | At 2:05 h, the severity of the information alert was changed to warning. |
| 3           | An information alert existed during that period.                         |
| 4           | A warning alert existed during that period.                              |

You can change the value in the **Solutions** drop-down field to load the information about the run-time instances from a specific solution.

You can use the **INTEGRATION SERVER**, **UNIVERSAL MESSAGING**, and **TERRACOTTA** tabs to view the information related to the selected solution and runtime.

By default, the page displays information for the last 24 hours. To view the information for a different time period, use the time-range selector. For more information about the time-range selector, see [“Monitoring Solutions” on page 700](#).

The following table describes the monitored Integration Server KPIs.

| Name              | Description                                       |
|-------------------|---------------------------------------------------|
| Used Memory       | The total used memory for the Java VM.            |
| Service Threads   | The number of active service threads.             |
| Sessions          | The number of active licensed sessions.           |
| Stateful Sessions | The number of the current stateful HTTP sessions. |

The following table describes the monitored Universal Messaging KPIs.

| Name              | Description                                                                                                                                                                                |
|-------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Free Memory       | The amount of free memory that the Realm Server has within the Java VM. This indicates the difference between what the Java VM has currently allocated and what the Realm Server has used. |
| Published Events  | Total number of events published on this realm from the time it started.                                                                                                                   |
| Subscribed Events | Total number of events that this realm has sent to clients from the time it started.                                                                                                       |

The following table describes the monitored Terracotta KPIs.

| Name                 | Description                                                                                                                                                                                                                                                                                                                                                               |
|----------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Off-Heap Used Memory | Shows the amount of off-heap memory that is currently used.                                                                                                                                                                                                                                                                                                               |
| Live Objects         | Shows the total number of live objects in the cluster, mirror group, server, or clients. If the trend for the total number of live objects goes up continuously, clients in the cluster will eventually run out of memory and applications might fail. Upward trends indicate a problem with application logic, garbage collection, or the tuning of one or more clients. |

## Viewing Adapter KPIs

On the Runtimes page, you can view the KPIs for the adapters that are installed on the Integration Server instances.

1. Navigate to the Runtimes page.
2. Select a solution.
3. On the **INTEGRATION SERVER** tab, select an Integration Server instance.
4. Click **Connectivity KPIs**.
5. On the **ADAPTERS** tab, select an Adapter.

The Adapter KPIs are displayed.

The following table describes the monitored Adapter KPIs.

| Name          | Description                                                                                             |
|---------------|---------------------------------------------------------------------------------------------------------|
| Connections   | The number of connection pools in the adapter and how many of them are currently enabled.               |
| Notifications | The number of adapter notifications (polling notifications) and how many of them are currently enabled. |

**Note:** You can view Adapter KPIs only for the current time.

## Viewing Connector KPIs

On the Runtimes page, you can view the KPIs for the connectors that are installed on the Integration Server instances.

1. Navigate to the Runtimes page.
2. Select a solution.
3. On the **INTEGRATION SERVER** tab, select an Integration Server instance.
4. Click **Connectivity KPIs**.
5. Click the **CONNECTORS** tab.
6. Select a provider.
7. Select a connector.

The Connector KPIs are displayed.

The following table describes the monitored Connector KPIs.

| Name        | Description                                                                                 |
|-------------|---------------------------------------------------------------------------------------------|
| Connections | The number of connection pools in the connector and how many of them are currently enabled. |
| Listeners   | The number of connector listeners and how many of them are currently enabled.               |

**Note:** You can view Connector KPIs only for the current time.

## Services

On the Services page, you can view the number of successful and failed service executions of the Integration Server instances from the solutions.

The Services page consists of two the Service Executions pane and the History pane.

| Pane               | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|--------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Service Executions | <p>Shows the following information about the service executions of the Integration Server instances for the selected time range:</p> <ul style="list-style-type: none"> <li>■ Total number of service executions</li> <li>■ The number of successful service executions</li> <li>■ The number of failed service executions</li> <li>■ The successful service execution, as a percentage value calculated by the formula (Number of successful service executions / total number of service executions) * 100</li> </ul> |
| History            | <p>Shows a chart with the history of successful (green) and failed (red) service executions.</p> <p>Hovering over the green and red bars displays the total number of successful and failed service executions, correspondingly.</p>                                                                                                                                                                                                                                                                                    |

The numbers of service executions on the Services page includes the public and internal services of the Integration Server instance and their child services.

You can change the value in the **Solutions** drop-down field to view the information about a specific solution, or the information for all solutions.

By default, the page displays information for the last 24 hours. To view the information for a different time period, use the time-range selector. For more information about the time-range selector, see [“Monitoring Solutions” on page 700](#).

## Uptime

On the Uptime page, you can view time lines that represent the availability of all run-time instances of the solutions.

The color of the time lines changes based on the status of the run-time instances.

The following table describes the meaning of the different colors.

| Time line color | Indicates that                                                                                                                                                      |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| green           | the run-time instance was available during the indicated time period.                                                                                               |
| red             | the run-time instance was unavailable during the indicated time period.                                                                                             |
| grey            | the run-time instance did not exist during the indicated time period.                                                                                               |
| blue            | at least one node from the cluster is unavailable.                                                                                                                  |
| <b>Note:</b>    | If the solution uses an Integration Server cluster, the number of Integration Server instances is indicated in brackets after the Integration Server instance name. |

By default, the time line displays the availability of the instances during the last 24 hours. To view the information for a different time period, use the time-range selector. For more information about the time-range selector, see [“Monitoring Solutions” on page 700](#).

## Alerts

The alert is a notification that a rule is violated.

On the Alerts page you can:

- View the number of critical, warning, and information alerts for all the solutions for the selected time range
- Filter the alerts by solution, runtime, severity, and status
- Configure the rules by adjusting the alert threshold values

- Configure the summary of the alerts
- Configure the recipient email for the alerts. For more information about configuring the alerts, see [“Configuring the Alerts” on page 710](#).

By default, the Alerts page displays the number of alerts (critical, warning, and information) for all the solutions, and detailed information about the alerts in a tabular format.

**Note:** If the duration of the rule violation is less than the time interval at which the rule is evaluated, the alert does not appear on the Alerts page. For more information about the interval, see [“Configuring the Alerts” on page 710](#).

If you deactivate a solution, the Alerts page will not display the alerts for the solution.

If you activate a solution, the Alerts page will display both the historical alerts for the solutions that had been raised before the deactivation of the solution, and the alerts that were raised after the activation of the solution.

The following table describes the information that is displayed in the table on the Alerts page.

| Column             | Description                                                                                                                                                                                                                                                                                             |
|--------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Solution</b>    | Name of the solution.                                                                                                                                                                                                                                                                                   |
| <b>Runtime</b>     | Run-time type. <ul style="list-style-type: none"> <li>■ Integration Server</li> <li>■ Universal Messaging</li> <li>■ Terracotta</li> </ul>                                                                                                                                                              |
| <b>Instance</b>    | Name of the run-time instance.                                                                                                                                                                                                                                                                          |
| <b>Start Date</b>  | Date and time when the alert was raised.                                                                                                                                                                                                                                                                |
| <b>Resolved On</b> | Date and time when the alert was resolved.<br>The field is empty if the alert is still active.                                                                                                                                                                                                          |
| <b>Message</b>     | Description of the alert.                                                                                                                                                                                                                                                                               |
| <b>Status</b>      | Status of the alert. <ul style="list-style-type: none"> <li>■  The alert is inactive.</li> <li>■  The alert is active.</li> </ul> |

**Note:** The Alerts page might not display the alerts for all nodes from a cluster. For example, if you monitor an Integration Server cluster with two Integration Server instances, and both instances have alerts for the same property with different severity, the Alerts page will show the alert of lower severity only, as explained in the following table.

| <u>Integration Server instance</u> | <u>Alert type</u>                | <u>Visibility on the Alerts page</u> |
|------------------------------------|----------------------------------|--------------------------------------|
| Integration Server instance 1      | Information. Free memory is low. | Yes                                  |
| Integration Server instance 2      | Warning. Free memory is low.     | No                                   |

You can view all alerts for all the nodes from the cluster in the email alerts.

By default, the page displays information for the last 24 hours. To view the information for a different time period, use the time-range selector. For more information about the time-range selector, see [“Monitoring Solutions” on page 700](#).

## Alert Types

The following table provides more information about the alert types.

**Note:** Warning alerts and information alerts are not available for KPIs that monitor the availability of a run-time instance.

| <b>Alert Severity</b> | <b>Description</b>                                                     | <b>Color Coding</b> |
|-----------------------|------------------------------------------------------------------------|---------------------|
| Critical              | A condition exists that is critical for the system performance.        | red                 |
| Warning               | A condition exists that might deteriorate the system performance.      | orange              |
| Information           | A condition exists that might evolve into a warning or critical alert. | blue                |

## Configuring the Alerts

You can change the default threshold values and the recipient email for the system alerts. Threshold values determine when a rule is violated and when the system raises an alert.

---

### To configure the system alerts

1. Navigate to the Alerts page.
2. Select the **CONFIGURATION** tab.

The Configuration page shows information about the alerts for all solutions. The following table describes the columns in the form.

| Column         | Description                                              |
|----------------|----------------------------------------------------------|
| <b>Name</b>    | Alert Name.                                              |
| <b>Runtime</b> | Integration Server, Universal Messaging, or Terracotta.  |
| <b>Action</b>  | The icon activates the configuration view for the alert. |

3. Click the **Edit this rule** icon in the Action column for the alert that you want to configure.

A form with the configuration details for the alert rule is displayed. The following table describes the fields in the form.

| Field            | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Threshold</b> | <p>The KPI's boundary values. When the value of the KPI is outside the range that is specified by these boundary values, the alert is raised.</p> <p>You can configure the threshold values of critical alerts by adjusting the ends of the red line.</p> <p>You can configure the threshold values of warning alerts by adjusting the ends of the orange line.</p> <p>You can configure the threshold values of information alerts by adjusting the ends of the blue line.</p> <p><b>Note:</b> The Threshold field is read-only for KPIs that monitor the availability of a runtime instance.</p> |
| <b>Runtime</b>   | Integration Server, Universal Messaging, or Terracotta.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| <b>Summary</b>   | Summary of the alert.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| <b>Interval</b>  | The scrape interval. The scrape interval is the frequency at which the system collects the data. The scrape interval is 60 seconds for all rules. Read-only.                                                                                                                                                                                                                                                                                                                                                                                                                                       |

| Field                 | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|-----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                       | <p><b>Note:</b> The alert does not appear immediately when the corresponding rule violation occurs.</p> <p>The time delay from the actual time of the rule violation to the system alert is the following:</p> <ul style="list-style-type: none"> <li>■ up to 70 seconds for run-time availability rules of critical severity</li> <li>■ up to 420 seconds for run-time availability rules of information severity</li> <li>■ up to 180 seconds for the rest of the rules</li> </ul> <p>The system will not send an alert if the rule violation condition is resolved during the corresponding delay period.</p> |
| <b>Email on alert</b> | <p>Email of the user who will receive the alerts.</p> <p><b>Note:</b> The email is used for all rules. In case there are alerts, the system sends emails once every 10 minutes.</p> <p>To configure more than one email, use comma-separated values.</p>                                                                                                                                                                                                                                                                                                                                                         |

4. In the **Threshold** field, change the default threshold value(s) for the alert.
5. In the **Email on Alert** field, type the email(s) of the user(s) who will receive the email alerts for all rules.

**Note:** webMethods Integration Cloud stores the email(s) in the local alertManager.yaml file. When you uninstall webMethods Integration Cloud or delete a tenant, the related information is deleted automatically.

6. Click **Apply**.

## Logs

On the Logs page, you can view the logs of the run-time instances in the solutions for a selected time period.

To view the logs for all the instances from a specific solution, select the solution in the solutions drop-down list.

To view the logs for a specific run-time instance in a solution, select the run-time instance in the run-time instance drop-down list.

By default, the page displays the logs for the last 24 hours. To view the logs for a different time period, use the time-range selector. For more information about the time-range selector, see [“Monitoring Solutions” on page 700](#).

You can view logs message statistics and logs details, such as log timestamp and message text. You can change the type of log details that you see by adding or editing filters as described in the Kibana documentation.

## Database

---

For optimal performance, you can add a MySQL database to your cloud deployment subscription. This enables you to configure, store, and monitor your database directly in the cloud instead of using external systems. The database endpoint can be shared by multiple solutions deployed by the tenant.

### Creating a Database

---

To create a database instance in the cloud

1. On the home page in Cloud Deployment, under **Database**, click **Learn more**, and then click **Start database setup**.
2. On the Database setup details screen, do the following:
  - a. In the **Database instance identifier** field, specify a name for the database.

**Important:** Each Software AG Cloud tenant can create only one database instance.

- b. In the **Create DB master username** and **DB master password** fields, specify the username and password that you will use to access the database.

**Note:** The master user has full privileges on the database. For more information on database privileges, see the MySQL documentation.

- c. Select **Encrypt database** if you want to enable the encryption of database data and click **Continue**. Note that you cannot change the encryption settings after the database is created.

When the database configuration is complete, you are redirected to the home page of Cloud Deployment where the **Database** element shows that the database server is running.

### Connecting a Solution to the Database

After you create the database instance in the cloud, you can connect one or more solutions to it.

---

### To connect a solution to the database instance in the cloud

1. Enable the wMJDBCAdapter package for the solution. For more information, see the Solutions chapter in *Cloud Deployment*.
2. In Software AG Designer, deploy to the cloud the on-premises webMethods Integration Server packages that you want to include in the solution.
  - a. In the Package Navigator view, right-click any of the packages that you want to include and select **Deploy to Cloud**.
  - b. In the Publish Assets to Integration Cloud dialog box, select all packages that you want to include in the solution and click **Next**.
  - c. In the Integration Server Packages Variable Substitution dialog box, do the following for each of the packages that have JDBC connections:
    - Enable the **State after Deployment** property.
    - In the **user**, **password**, and **serverName** fields, specify the username, password, and host name of the database instance in the cloud.

**Note:** You can see the host name of the database in the **DB instance endpoint** field on the Database page in Cloud Deployment.
  - d. In the Select the Integration Cloud Solution dialog box, select the solution that you want to connect to the database and click **Finish**.

## Securing the Connection Between a Solution and the Database

---

### To secure the connection between a solution and the database

1. Import the Amazon RDS Root CA certificate as a trusted certificate in a Java keystore. For more details on the certificate, see the Amazon Relational Database Service documentation.
2. Copy the truststore to the config directory of any of the packages you deploy to the solution.
3. In the web administration interface of the on-premise webMethods Integration Server, go to **Adapters > WebMethods Adapter for JDBC > Connections**. In the Other Properties field of the JDBC adapter connection, specify:

```
sslMode=VERIFY_IDENTITY;
trustCertificateKeyStoreUrl=file:packages/<package>/config/<truststore>;
trustCertificateKeyStorePassword=<password>
```

where *package* is the name of the package that contains the truststore, *truststore* is the name of the keystore that contains the trusted certificate, and *password* is the password to the truststore.

4. In Software AG Designer, deploy the updated packages to the cloud.

**Note:** Amazon Relational Database Service currently does not support authentication that uses a client certificate.

## Monitoring the Database

After you create the database instance in the cloud, you can monitor its status on the Database page in Cloud Deployment.

On the **Database** dashboard of the Database page, you can view the following elements:

| Element          | Description                                                                                                                                   |
|------------------|-----------------------------------------------------------------------------------------------------------------------------------------------|
| DB CPU usage     | CPU usage in percentage.                                                                                                                      |
| DB storage size  | The allocated storage space and the storage space used by the database.                                                                       |
| DB server status | Shows if the database server is running. You can start or stop the server at any time by clicking <b>Start server</b> or <b>Stop server</b> . |

In the **Configuration details** section of the Database page, you can view the following fields:

| Field                  | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DB instance            | The size of the database, based on your license offering.                                                                                                                                                                                                                                                                                                                                                                                                       |
| DB instance identifier | The name of the database.                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| DB instance endpoint   | The host and port that you can use to access the database.                                                                                                                                                                                                                                                                                                                                                                                                      |
| Allowed IPs            | <p>The list of external IPs that can access the database.</p> <p>Software AG recommends using the database only from applications in Software AG Cloud. By default, you can access the database only in the cloud. For administrative purposes you can enable access to the database from external IPs.</p> <p>To add external IPs, click <b>Edit</b> and type each IP on a new row. The supported IP format is Classless Inter-Domain Routing (CIDR) block</p> |

| Field | Description                                                                                       |
|-------|---------------------------------------------------------------------------------------------------|
|       | format, xxx.xxx.xxx.xxx/yy. If you specify only xxx.xxx.xxx.xxx, mask /32 is automatically added. |

## Cloud Deployment CLI

The Cloud Deployment CLI interacts with webMethods Cloud Deployment and performs tasks such as managing a solution, monitoring the status of all runtimes in a solution, promoting assets from one stage to another, and so on. The CLI supports the following modes:

- **Interactive Mode:** To start the CLI in interactive mode, run the following command:

```
wmcd-cli --mode interactive
```

```
C:\cli>wmcd-cli --profile default --mode interactive

Reading Credentials from C:\Users\arub\AppData\Roaming\wmcd_cli\config.json
Connecting to https://setup.saglive.com
Signing in as setup
No Commands specified

webMethodsCloud
CLI v1.0.0

Copyright © 2014-2019 Software AG, Darmstadt, Germany and/or Software AG USA Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.
Connected to webMethods Cloud Deployment...
wmcd_cli>$ Commands ...
```

- **Normal Mode:** To start the CLI in normal mode, run the following command:

```
wmcd-cli <commands> [options]
```

## Install Cloud Deployment CLI

### Overview

You install the Cloud Deployment CLI (wmcd-cli) using the NPM registry. This section describes tasks such as installing the Cloud Deployment CLI and specifying credentials to connect to Cloud Deployment.


### Actors

Administrators

### Before you begin

Before you install wmcd-cli from the NPM registry, do the following:

- Install the NodeJS runtime environment version 10.13 or later on your computer along with NPM (Node's package manager).



## Downloads

Latest LTS Version: **10.15.3** (includes npm 6.4.1)

Download the Node.js source code or a pre-built installer for your platform, and start developing today.

| LTS<br>Recommended For Most Users                                                                                                                     | Current<br>Latest Features                                                                                                                      |                                                                                                                                                  |
|-------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------|
| <br><b>Windows Installer</b><br><small>node-v10.15.3-x86.msi</small> | <br><b>macOS Installer</b><br><small>node-v10.15.3.pkg</small> | <br><b>Source Code</b><br><small>node-v10.15.3.tar.gz</small> |

Windows Installer (.msi)  
 Windows Binary (.zip)  
 macOS Installer (.pkg)  
 macOS Binary (.tar.gz)  
 Linux Binaries (x64)  
 Linux Binaries (ARM)  
 Source Code

|                      |        |       |
|----------------------|--------|-------|
| 32-bit               | 64-bit |       |
| 32-bit               | 64-bit |       |
| 64-bit               |        |       |
| 64-bit               |        |       |
| 64-bit               |        |       |
| ARMv6                | ARMv7  | ARMv8 |
| node-v10.15.3.tar.gz |        |       |

**Note:** The Cloud Deployment CLI is available for the following operating system environments:

- Windows
- Linux
- macOS

- Open a command line interface and type the following command to install `wmcd-cli`:

```
npm install -g wmcd-cli
```

### Specify the credentials to connect to Cloud Deployment

To connect to Cloud Deployment, you must configure the credentials in one of the following ways:

- Specify the credentials in `config.json` file.
  - Create a `config.json` file under `%appdata%/wmcd_cli/` location for Windows or `/home/wmcd_cli/` in Linux.
  - Add new profiles in the `config.json` file.

The following is an example of default and referenced profile in the configuration file.

```
{
 "default": {
 "url": "https://{subdomain}.webmethodscloud.com",
 "userName": "userName",
 "password": "password"
 },
 "someotherProfile": {
 "url": "https://{subdomain}.webmethodscloud.com",
 "userName": "userName",
 "password": "password"
 }
}
```

By default, the 'default' settings are read from the configuration file. To enable the referenced profile, run the following command:

```
wmcd-cli -profile someotherProfile
```

- Specify credentials as runtime arguments.
  - When you start the CLI, credentials are passed as a runtime argument. For example:

```
wmcd --mode interactive --url <url> --userName <userName>
--password <password>
```

**Note:** Runtime arguments will have the highest priority. However, If runtime arguments are not passed, then the default profile from %appdata%/wmcdd\_cli/config.json is used.

## Cloud Deployment CLI Reference

The following table describes the commands you use to perform various scenarios in the CLI interface.

### Commands for viewing alerts in Cloud Deployment

Run the following command to view alerts.

```
alert list [options]
```

where the options are:

| --Name                           | Description                                                                                                 |
|----------------------------------|-------------------------------------------------------------------------------------------------------------|
| --solutionName<br><solutionName> | Filter the alerts that belong to a particular solution.                                                     |
| --stageName <stageName>          | Filter the alerts that belong to a particular stage. Supported values are development, test, live, prelive. |

| --Name                  | Description                                                                                                                                                                                                                                                                                                           |
|-------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| --alertName <alertName> | Filter the alerts by name .                                                                                                                                                                                                                                                                                           |
| --runtime <runtime>     | Filter the alerts by Instances / Node name in a solution.                                                                                                                                                                                                                                                             |
| --severity <severity>   | Filter the alerts based on the severity. Default supported values are info, warning, and critical.                                                                                                                                                                                                                    |
| --view <view>           | <p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre>alert list --severity critical</pre>                                                                                                                                           |
| --view <json>           | <p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre>alert list --severity critical --view json</pre> <p><b>Note:</b>JSON output format loads complete information that contains additional field than the table output format.</p> |

### Commands for listing the assets in LAR

Run the following command to list all the assets available in the LAR.

```
asset-repo list-assets <solutionName> <nodeName> <stageName> [options]
```

where the options are:

| --Name        | Description                                                                                                                                                                                 |
|---------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| --view <view> | <p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre>asset-repo list-assets DemoSoln IS development</pre> |

### Commands for creating solutions

Run the following command to create solutions.

```
solution create [options] <stagename>
```

where the options are:

| --Name                 | Description                                                                                                                                              |
|------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------|
| --inputFile <fileName> | <p>Provide the name of the file that contains the input data.</p> <pre>solution create --inputFile /home/etc/createSolution.json &lt;stagename&gt;</pre> |

The file must contain a valid solution name, the name of the webMethods Integration Server and Universal Messaging instances, number of CPU Cores, and Memory characteristics of the hardware to support each service in the solution.

Example 1 : Creating Type 1 solution without cluster.

```
{
 "integration": {
 "landscapeDefinition": {
 "solutionName": "Demo",
 "description": "Demo Solution",
 "solutionType": 1,
 "productDefinitions": {
 "IS": [{
 "name": "IS",
 "resources": {
 "limits": {
 "cpu": "1",
 "memory": "2"
 }
 }
 }],
 "version": "10.4",
 "env": {
 "packages": ["packages.WmCloudStreams.enabled=true",
 "packages.WmJDBCAdapter.enabled=true"]
 }
 }
 }
 }
}
```

Example 2: Creating Type 1 solution with stateful cluster.

```
{
 "integration": {
 "landscapeDefinition": {
 "solutionName": "Demo",
 "description": "Demo Solution",
 "solutionType": 1,
 "productDefinitions": {
 "IS": [{
 "name": "IS",
 "replicaCount": "2",

```

| --Name | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|--------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|        | <pre> "resources": {   "limits": {     "cpu": "1",     "memory": "2"   } }, "dependencies": ["DB","tc"], "clusterType": "stateful", "isClustered": true, "statefulCluster": true, "version": "10.4", "env": {   "packages": ["packages.WmCloudStreams.enabled=true", "packages.WmJDBCAdapter.enabled=true"] } }], "TERRACOTTA": [{   "name": "tc",   "isClustered": true,   "statefulCluster": false,   "replicaCount": "2",   "enabled": true,   "resources": {     "limits": {       "cpu": "1",       "memory": "4"     }   } }, "version": "10.4", "env": {   "packages": [],   "monitoringTools": [] } }]] } } } } </pre> |

### Example 3: Creating Type 1 solution with stateless cluster.

```

{
 "integration": {
 "landscapeDefinition": {
 "solutionName": "Demo",
 "description": "Demo Solution",
 "solutionType": 1,
 "productDefinitions": {
 "IS": [{
 "name": "IS",
 "replicaCount": "2",
 "dependencies": ["DB"],
 "resources": {
 "limits": {
 "cpu": "1",
 "memory": "2"
 }
 }
 },
 "clusterType": "stateless",
 "isClustered": true,

```

| --Name | Description                                                                                                                                                                         |
|--------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|        | <pre> "statefulCluster": false, "version": "10.4", "env": {   "packages": ["packages.WmCloudStreams. enabled=true", "packages.WmJDBCAdapter.enabled=true"] } }]] } } } } } } </pre> |

#### Example 4: Creating Type 2 solution without cluster.

```

{
 "integration": {
 "landscapeDefinition": {
 "solutionName": "Solution2",
 "description": "sample solution",
 "solutionType": 2,
 "productDefinitions": {
 "IS": [{
 "name": "IS",
 "resources": {
 "limits": {
 "cpu": "1",
 "memory": "2"
 }
 },
 "version": "10.4",
 "env": {
 "packages": ["packages.WmCloudStreams
.enabled=true",
"packages.WmJDBCAdapter.enabled=true"]
 }
 }],
 "UNIVERSALMESSAGING": [{
 "name": "UM",
 "resources": {
 "limits": {
 "cpu": "1",
 "memory": "2"
 }
 },
 "version": "10.4"
 }
]
 }
 }
}
}

```

#### Example 5: Creating Type 2 solution with stateful cluster.

```

{
 "integration": {
 "landscapeDefinition": {
 "solutionName": "Solution2",
 "description": "sample solution",
 "solutionType": 2,

```

| --Name | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|--------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|        | <pre> "productDefinitions": {   "IS": [{     "name": "IS",     "clusterType": "stateful",     "replicaCount": "2",     "isClustered": true,     "statefulCluster": true,     "dependencies": ["DB", "UM", "tc"],     "resources": {       "limits": {         "cpu": "1",         "memory": "2"       }     },     "version": "10.4",     "env": {       "packages": ["packages.WmCloudStreams. enabled=true", "packages.WmJDBCAdapter.enabled=true"]     }   }],   "UNIVERSALMESSAGING": [{     "name": "UM",     "clusterType": null,     "isClustered": false,     "resources": {       "limits": {         "cpu": "1",         "memory": "2"       }     },     "version": "10.4"   }],   "TERRACOTTA": [{     "name": "tc",     "isClustered": true,     "resources": {       "limits": {         "cpu": "1",         "memory": "4"       }     },     "version": "10.4",     "env": {       "packages": [],       "monitoringTools": []     }   } ] } } } </pre> |

Example 6: Creating Type 2 solution with stateless cluster.

```

{
 "integration": {
 "landscapeDefinition": {
 "solutionName": "Solution2",
 "description": "sample solution",
 "solutionType": 2,

```

| --Name | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|--------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|        | <pre> "productDefinitions": {   "IS": [{     "name": "IS",     "replicaCount": "2",     "clusterType": "stateless",     "dependencies": ["DB","UM"],     "isClustered": true,     "statefulCluster": false,     "resources": {       "limits": {         "cpu": "1",         "memory": "2"       }     },     "version": "10.4",     "env": {       "packages": ["packages.WmCloudStreams. enabled=true", "packages.WmJDBCAdapter.enabled=true"]     }   }],   "UNIVERSALMESSAGING": [{     "name": "UM",     "clusterType": null,     "isClustered": false,     "resources": {       "limits": {         "cpu": "1",         "memory": "2"       }     },     "version": "10.4"   }] } } } </pre> |

### Example 7: Creating Type 3 solution without cluster.

```

{
 "integration": {
 "landscapeDefinition": {
 "solutionName": "Solution3",
 "description": "Sample Solution",
 "solutionType": 3,
 "productDefinitions": {
 "IS": [{
 "name": "IS1",
 "resources": {
 "limits": {
 "cpu": "1",
 "memory": "2"
 }
 },
 "version": "10.4",
 "env": {
 "packages": ["packages.WmCloudStreams.
enabled=true", "packages.WmJDBCAdapter.
enabled=true"]
 }
 }]
 }
 }
 }
}

```

| --Name | Description                                                                                                                                                                                                                                                                                                                                                                                                          |
|--------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|        | <pre> }, {   "name": "IS2",   "resources": {     "limits": {       "cpu": "1",       "memory": "2"     }   },   "version": "10.4",   "env": {     "packages": ["packages.WmCloudStreams.enabled=true", "packages.WmJDBCAdapter.enabled=true"]   } }], "UNIVERSALMESSAGING": [{   "name": "UM",   "resources": {     "limits": {       "cpu": "1",       "memory": "2"     }   },   "version": "10.4" }] } } } </pre> |

### Example 8: Creating Type 3 solution with stateful cluster.

```

{
 "integration": {
 "landscapeDefinition": {
 "solutionName": "Solution3",
 "description": "Sample Solution",
 "solutionType": 3,
 "productDefinitions": {
 "IS": [{
 "name": "IS1",
 "isClustered": true,
 "replicaCount": "2",
 "statefulCluster": true,
 "dependencies": ["UM", "DB", "tcl"],
 "clusterType": "stateful",
 "resources": {
 "limits": {
 "cpu": "1",
 "memory": "2"
 }
 }
 },
 {
 "name": "IS2",
 "isClustered": true,
 "statefulCluster": true,

```

| --Name | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|--------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|        | <pre> "replicaCount": "2", "dependencies": ["UM", "DB", "tc2"], "clusterType": "stateful", "resources": {   "limits": {     "cpu": "1",     "memory": "2"   } }, "version": "10.4", "env": {   "packages": ["packages.WmCloudStreams. enabled=true", "packages.WmJDBCAdapter.enabled=true"] } }], "UNIVERSALMESSAGING": [{   "name": "UM",   "isClustered": false,   "statefulCluster": false,   "clusterType": null,   "resources": {     "limits": {       "cpu": "1",       "memory": "2"     }   },   "version": "10.4" }], "TERRACOTTA": [{   "name": "tc1",   "isClustered": true,   "resources": {     "limits": {       "cpu": "1",       "memory": "4"     }   },   "version": "10.4",   "env": {     "packages": [],     "monitoringTools": []   } }, {   "name": "tc2",   "isClustered": true,   "resources": {     "limits": {       "cpu": "1",       "memory": "4"     }   },   "version": "10.4",   "env": {     "packages": [],     "monitoringTools": []   } } ] } } } </pre> |

| --Name | Description |
|--------|-------------|
|--------|-------------|

Example 9: Creating Type 3 solution with stateless cluster.

```
{
 "integration": {
 "landscapeDefinition": {
 "solutionName": "Solution3",
 "description": "Sample Solution",
 "solutionType": 3,
 "productDefinitions": {
 "IS": [{
 "name": "IS1",
 "isClustered": true,
 "replicaCount": "2",
 "statefulCluster": false,
 "dependencies": ["UM", "DB"],
 "clusterType": "stateless",
 "resources": {
 "limits": {
 "cpu": "1",
 "memory": "2"
 }
 }
 },
 {
 "name": "IS2",
 "isClustered": true,
 "replicaCount": "2",
 "statefulCluster": false,
 "dependencies": ["UM", "DB"],
 "clusterType": "stateless",
 "resources": {
 "limits": {
 "cpu": "1",
 "memory": "2"
 }
 }
 }
],
 "version": "10.4",
 "env": {
 "packages": ["packages.WmCloudStreams.enabled=true",
"packages.WmJDBCAdapter.enabled=true"]
 }
 },
 "UNIVERSALMESSAGING": [{
 "name": "UM",
 "isClustered": false,
 "statefulCluster": false,
 "clusterType": null,
 "resources": {
 "limits": {
 "cpu": "1",
 "memory": "2"
 }
 }
 }],
 "version": "10.4"
 }
}
```

| --Name | Description                                       |
|--------|---------------------------------------------------|
|        | <pre data-bbox="649 304 1344 424"> } } } } </pre> |

### Commands for listing the solutions for a particular stage

Run the following command to list solutions for a particular stage.

```
solution list <stageName> [options]
```

where the valid stage name value includes development, test, prelive, and live.

Example:

```
solution list development --view json
```

### Commands for getting the solution and runtimes for a particular stage

Run the following command to get the solution and all runtimes for a particular stage.

```
solution get <solutionName><stageName> [options]
```

where the options are:

| --Name            | Description                                                                                                |
|-------------------|------------------------------------------------------------------------------------------------------------|
| --view <viewType> | By default, outputs the response in a table view mode. The CLI supports both table and JSON output format. |
|                   | Example:<br><pre data-bbox="649 1228 1344 1268">solution get DemoSoln development</pre>                    |

### Commands for deleting the solution for a particular stage

Run the following command to delete the solution for a particular stage.

```
solution delete <solutionName> <stageName> [options]
```

where the options are:

| --Name            | Description                                                                                                |
|-------------------|------------------------------------------------------------------------------------------------------------|
| --view <viewType> | By default, outputs the response in a table view mode. The CLI supports both table and JSON output format. |
|                   | Example:<br><pre data-bbox="649 1768 1344 1808">solution delete DemoSoln development</pre>                 |

### Commands for activating or deactivating the solution for a particular stage

Run the following command to activate and deactivate a solution for a particular stage.

```
solution update-status <solutionName> <stageName> <actionName> [options]
```

where the options are:

| --Name            | Description                                                                                                                                                                                                                                                                                                                                                                 |
|-------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| --view <viewType> | <p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre>solution update-stats DemoSoln development deactivate</pre> <ul style="list-style-type: none"> <li>■ Allowed stage names are development, test, live, prelive.</li> <li>■ Allowed action names are activate or deactivate</li> </ul> |

### Commands for getting the status of all pods in a solution

Run the following command to get the status of all pods in a solution.

```
solution get-status <solutionName> <stageName> [options]
```

where the options are:

| --Name            | Description                                                                                                                                                                           |
|-------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| --view <viewType> | <p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre>solution get-status DemoSoln development</pre> |

### Commands for getting the license information for a particular tenant

Run the following command to get the license information for a particular tenant.

```
tenant get-license-info [options]
```

where the options are:

| --Name            | Description                                                                                                                                                          |
|-------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| --view <viewType> | <p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre>tenant get-license-info</pre> |

### Commands for getting the total CPU and memory utilization details for a particular tenant

Run the following command to get the total CPU and memory utilization details for a particular tenant.

```
tenant get-utilization-details [options]
```

where the options are:

| --Name            | Description                                                                                                                                                          |
|-------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| --view <viewType> | <p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre>tenant get-license-info</pre> |

### Commands for listing all the users

Run the following command to list all the users.

```
user list [options]
```

where the options are:

| --Name            | Description                                                                                                                                                          |
|-------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| --view <viewType> | <p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre>tenant get-license-info</pre> |

### Commands to get a particular user

Run the following command to get the user information.

```
user get <userId> [options]
```

where the options are:

| --Name            | Description                                                                                                                                                              |
|-------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| --view <viewType> | <p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre>user get &lt;ID details&gt;</pre> |

### Commands for promoting Integration Server and Universal Messaging configurations from one stage to another

Run the following command to promote Integration Server and Universal Messaging configurations from one stage to another.

```
runtime promote-configuration <fromSolutionName> <fromNodeName>
<fromStageName> [toSolutioName] [toNodeName] [options]
```

**Note:** If toSolutionName and toNodeName are provided as part of your command, then the CLI performs the cross solution promotion. However, if toSolutionName and toNodeName are not available, then the configuration will be promoted to higher stage on the same Integration Server or Universal Messaging node.

where the options are:

| --Name                | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|-----------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| --propFile <fileName> | <p>Properties file to perform variable substitution.</p> <p>Example: Use the following command for promotion across same instance:</p> <pre>runtime promote-configuration DemoSoln IS development</pre> <p>Example: Use the following command for cross solution promotion:</p> <pre>runtime promote-configuration DemoSoln IS development DemoSoln1 IS1</pre> <p>Promotes the configuration from the solution DemoSoln IS node to DemoSoln1 and IS1 node.</p> |

### Commands for promoting Integration Server packages from one stage to another

Run the following command to promote Integration Server packages from one stage to another.

```
runtime promote-packages <fromSolutionName> <fromNodeName> <fromStageName>
[toSolutioName] [toNodeName] [options]
```

**Note:** If toSolutionName and toNodeName are provided then the CLI performs the cross solution promotion. If toSolutionName and toNodeName are not available, then the packages will be promoted to higher stage on the same Integration Server instance.

where the options are:

| --Name                                     | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
|--------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| --include <comma separated packages names> | Promotes only specified packages.<br>Example:<br><pre data-bbox="688 680 1338 709">--include package1,package2,package3</pre>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| --exclude <comma separated packages names> | Promotes all the packages other than the packages specified in the options.<br>Example:<br><pre data-bbox="688 875 1338 905">--exclude package1,package2,package3</pre>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| --propFile <fileName>                      | Provide properties file to perform variable substitution.<br>Examples:<br>Use the following command for promotion across same instance:<br><pre data-bbox="688 1157 1382 1209">runtime promote-packages DemoSoln IS development -- propFile /home/etc/var_sub.properties</pre> Use the following command for cross solution promotion:<br><pre data-bbox="688 1310 1382 1362">runtime promote-packages DemoSoln IS development TestSoln IS2</pre> Use the following command to replace a property in a specific composite asset.<br><pre data-bbox="688 1463 1338 1493">&lt;propertyName&gt;/&lt;compositeAssetName&gt;</pre> <p data-bbox="704 1507 1338 1577"><b>Note:</b>The replacement properties should be in the following format:</p> <pre data-bbox="764 1589 1442 1619">&lt;propertyName&gt;/&lt;compositeAssetName&gt;/&lt;assetName&gt;</pre> <p data-bbox="764 1633 1248 1703">Example for replacing properties of a package:</p> <pre data-bbox="764 1717 1382 1747">activatePkgOnInstall/TestODataService=false</pre> <p data-bbox="764 1761 1317 1864">where TestODataService is the package name whose property activatePkgOnInstall" is assigned with value "false".</p> |

| --Name | Description                                                                                                                                                                                                                                                                                                                      |
|--------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|        | <p>Example for replacing properties of a service of a package:</p> <pre data-bbox="764 409 1383 462">serverName/TestODataService/JDBC_Connection.ODataService=localhost</pre> <p>where JDBC_Connection.ODataService is a service under package TestODataService, whose parameter serverName is assigned with value localhost</p> |

### Commands for printing the list of exposed services

Run the following command to print the list of exposed services.

```
runtime get-exposed-is-services <solutionName> <nodeName> <stageName> [options]
```

where the options are:

| --Name           | Description                                                                                                                                                                                                                         |
|------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| -view <viewType> | <p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre data-bbox="699 1178 1487 1205">runtime get-exposed-is-services DemoSoln IS development</pre> |

### Commands for listing all the queues

Run the following command to list all the queues in the Universal Messaging instance.

```
um list-queues <solutionName> <nodeName> <stageName> [options]
```

where the options are:

| --Name           | Description                                                                                                                                                                                                        |
|------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| -view <viewType> | <p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre data-bbox="699 1719 1336 1747">um list-queues DemoSoln UM development</pre> |

### Commands for getting the queue information

Run the following command to retrieve pushed, popped, and memory usage of the queue.

```
um get-queue <solutionName> <nodeName> <stageName> <queueName> [options]
```

where the options are:

| --Name           | Description                                                                                                                                                                              |
|------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| -view <viewType> | By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.<br><br>Example:<br><pre>um get-queue DemoSoln UM development dummyQueue</pre> |

### Commands for getting the queue details

Run the following command to retrieve the queue details.

```
um get-queue-details <solutionName> <nodeName> <stageName> <queueName> [options]
```

where the options are:

| --Name           | Description                                                                                                                                                                                      |
|------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| -view <viewType> | By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.<br><br>Example:<br><pre>um get-queue-details DemoSoln UM development dummyQueue</pre> |

### Commands for listing all the channels in the Universal Messaging instance

Run the following command to list all the channels in a Universal Messaging instance.

```
um list-channels <solutionName> <nodeName> <stageName> [options]
```

where the options are:

| --Name           | Description                                                                                                                                                                       |
|------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| -view <viewType> | By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.<br><br>Example:<br><pre>um list-channels DemoSoln UM development</pre> |

### Commands for getting the channel information

Run the following command to get the channel information.

```
um get-channel <solutionName> <nodeName> <stageName> <channelName> [options]
```

where the options are:

| --Name           | Description                                                                                                                                                                                  |
|------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| -view <viewType> | By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.<br><br>Example:<br><pre>um get-channel DemoSoln UM development dummyChannel</pre> |

### Commands for getting the channel details

Run the following command to get the channel details.

```
um get-channel-details <solutionName> <nodeName> <stageName> <channelName> [options]
```

where the options are:

| --Name           | Description                                                                                                                                                                                          |
|------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| -view <viewType> | By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.<br><br>Example:<br><pre>um get-channel-details DemoSoln UM development dummyChannel</pre> |



# 20 End-to-End Monitoring

---

- Overview of End-to-End Monitoring ..... 738
- Working with End-to-End Monitoring ..... 740
- User Journey ..... 758

## Overview of End-to-End Monitoring

---

This section covers conceptual information about End-to-End Monitoring.

### What is End-to-End Monitoring

End-to-End Monitoring is a cloud offering by Software AG to monitor a business transaction from its start to end, as it passes through the various cloud platforms which includes webMethods API Gateway, webMethods Integration Cloud, and webMethods.io B2B.

### Why End-to-End Monitoring

Currently, a user can execute multiple business transactions in various cloud platforms. However, there is no option to view the details of the transaction in a unified manner as it moves across these cloud platforms. webmethods.io End-to-End Monitoring provides a solution by means of a monitoring dashboard through which you can view the end to end flow of a business transaction across various systems.

It also allows you to troubleshoot any transaction failures by identifying the component at which the transaction failed.

For more information on the use case for End-to-End Monitoring, see [“User Journey” on page 758](#).

### Benefits of End-to-End Monitoring

End-to-End Monitoring allows you to identify any errors that occur during a business transaction. It identifies the application within the cloud platform where the error has occurred and also provides details of the time at which the error has occurred.


The Business Transaction Details page provides you an end to end view of the transaction along with the time spent by the transaction at each component of the platform.

### How do I Access End-to-End Monitoring

Currently, you can access End-to-End Monitoring only from the app switcher button of webMethods Integration Cloud. The application serves no purpose to a user who has only one Software AG product.

## End-to-End Monitoring Architecture

The following section provides details on how End-to-End Monitoring helps a user to get the details of a business transaction.




Let us consider a use case where a customer is requesting for an address change with his bank using a banking application. Here, the banking application is represented as a Third-party system. Following actions take place when the customer wants to change the address:

1. Customer raises an address change request using the client application. Client application is accessible using any device.
2. The request makes an API call to API gateway where the user is validated. Any policy enforcement required happens here.
3. After successful validation, an Integration service call is made to webMethods Integration Cloud. For example, in this case let us say that the Integration service call made to update the customer record is **updateaddress**.
4. The Integration service call authenticates the user with the bank and updates the record in the database of the bank.

- On successful update of the record, a confirmation message is sent to the client application as a response.

### What is the Role of End-to-End Monitoring here

As explained earlier in this section, End-to-End Monitoring monitors the entire business transaction from start to end and provides details of the transaction. A graphical representation of a business transaction flow is as follows. For more information, see [“Business Transaction Details page”](#) on page 755.



## General Data Protection Regulation (GDPR) Considerations

From a GDPR perspective, the following considerations are to be noted:

- As part of the rule creation and group creation, the application collects and stores the user ID and email address of the user in the Elastic Search database. The user ID and email address may be personal data or personally identifiable information.

**Note:** The user ID is the ID using which the user logs into webMethods Integration Cloud.

- In the current release, the user does not have an option to delete this personal data or personally identifiable information from the Elastic Search database. However, if a tenant is deleted, then the user related data is also deleted.
- In the future release, the user will have an option to purge any personal data.
- The application does not store any log information in the database.


## Working with End-to-End Monitoring

This section provides information about the various features of End-to-End Monitoring.


## Dashboard for End-to-End Monitoring

The dashboard for End-to-End Monitoring gives you a collective view of all the business transactions carried out within your cloud platform. The default **Dashboard** view includes the transaction widgets and the default **All Transactions** group. The **All Transactions** group contains all the transactions within the application and cannot be deleted.

**Note:** When you perform sorting, the **All transactions** group remains on the top of the list.



An example of the dashboard that includes custom groups created by an end user is as follows:




-  - An alert icon to notify you of any new transaction notifications.
-  - User help that includes the help content for this application.
-  - Use the link provided here to log off from the application.
- Time range - Below  is the drop-down list for time range selection. By default, it is set to half an hour prior from the current system time. For example, if current system time is 3:30 PM, then the time range shows as 3 PM to 3 30 PM. Click  next to the time range to select a specific duration.

**Note:** The time zone is set automatically based on the system time.


- Transaction widgets - Following widgets are available on the dashboard:
  - **Overview** - This is a pie chart that provides you a summary of all the transactions processed based on the following parameters:
    - Failed
    - Warning
    - Successful

An example of the **Overview** widget is as follows:



- **Topology** - This is a graphical representation of all the transactions across all the supported nodes. It shows the transactions flowing through each runtime as well as the status of each runtime for the selected time range.

An example of the Topology widget is as follows:




- **Top 5 Groups by Error Rate** - This is a graphical representation which shows the top 5 groups based on the error rate. The values are displayed in percentage. The **All**

**Transactions** group is excluded from this widget. An example of this widget is as follows:

### TOP 5 GROUPS BY ERROR RATE

Values in (%) percentage



- **Help Topics** - This provides you quick access to the help content for some of the commonly used topics.
- **All groups** - This lists all the transaction groups you create using the application and also the default **All Transactions** group. At the group level, you can see the following parameters for the selected time range:

**Note:** You can customize the parameters to view by clicking  next to **Create Group**.

- **Name** - Name of the group.
- **Total transactions** - The total number of transactions for each group.
- **Avg. time (ms)** - Average time of execution for all the transactions within a group.
- **Error rate (%)** - The rate of error in percentage for all the transactions within a group.
- **Success rate (%)** - The rate of success in percentage for all the transactions within a group.
- **Warning rate (%)** - The rate of warning for all the transactions within a group.
- **Create group** - Select this option to create a custom group of transactions. For more information, see [“Creating a Group of Transactions” on page 744](#).
- **Search by name** - Search for a transaction group by typing its name in the search box.

## Creating a Group of Transactions

Creating a group of transactions allows you to categorize the transactions based on your requirements.

### To create a group of transactions

1. On the Dashboard page, click **Create Group**.
2. In the Create group dialog box, provide the following details:

| Parameter     | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|---------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Group Name    | Type a name for this group.<br><br><b>Note:</b> The group name cannot be edited after you save this form.                                                                                                                                                                                                                                                                                                                                                                                       |
| Status        | Group the transactions on the basis of their status. It can be a combination of: <ul style="list-style-type: none"> <li>■ Success</li> <li>■ Failed</li> <li>■ Warning</li> </ul>                                                                                                                                                                                                                                                                                                               |
| Starts with   | Group the transactions on the basis of the application from where the business flow starts. You can choose one or more products when creating the group. For example, you can have a group where you have one transaction starting from webMethods API Gateway and another transaction starting from Integration Cloud. You can select from the following: <ul style="list-style-type: none"> <li>■ webMethods API Gateway</li> <li>■ Integration Cloud</li> <li>■ webMethods.io B2B</li> </ul> |
| Duration (ms) | Group the transactions on the basis of their execution time in milliseconds. You can select from the following: <ul style="list-style-type: none"> <li>■ ≤ - Select this operator to group the transactions that have an execution time which is lesser than or equal to the value specified here.</li> </ul>                                                                                                                                                                                   |

| Parameter           | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
|---------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                     | <ul style="list-style-type: none"> <li>■ <math>\geq</math> - Select this operator to group the transactions that have an execution time which is greater than or equal to the value specified here.</li> <li>■ <math>\leq \geq</math> - Select this operator to group the transactions that have an execution time which is between the values specified here. For example, if you specify 20 and 30 (ms), then both the values 20 and 30 are also taken into consideration.</li> </ul>                                                                                                                                                                                                                                                                                       |
| Product(s) involved | <p>Group the transactions on the basis of the product(s) involved in a business transaction. Use the drop-down list to select one or more products. The group includes all the transactions for the selected product. If you select more than one product, it will list the transactions for the standalone products along with the transactions that involve both the products. For example, if you select webMethods API Gateway and Integration Cloud, the group will include the following:</p> <ul style="list-style-type: none"> <li>■ all transactions that involve only Integration Cloud</li> <li>■ all transactions that involve only webMethods API Gateway</li> <li>■ all transactions that involve both Integration Cloud and webMethods API Gateway.</li> </ul> |
| Transaction name(s) | <p>Group the transactions on the basis of their names. Click <b>+</b> to add more than one entry.</p> <p><b>Note:</b> Click <b>X</b> to remove the added names.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| Error Message(s)    | <p>Group the transactions on the basis of an error message. Click <b>+</b> to add more than one entry.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |

3. Click **Save**.

## Viewing the Transactions List

1. On the Dashboard page, select the group for which you want to view the transactions. On the Transactions list page, you will see all the transactions for the selected time frame and the set filter(s).
2. Click  on the top-right corner of the screen to open the **Show Columns** dialog box.

3. Select the parameters for which you want to view the transaction details and click **Save**. The transactions list shows the following parameters:
4. You can also filter the transactions from this page. For more information, see [“Filtering the Business Transactions” on page 747](#)

| Parameter     | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|---------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Status        | Status of the transaction. Currently, we have the following states: <ul style="list-style-type: none"> <li>■  - Transaction successful.</li> <li>■  - Transaction failed.</li> <li>■  - Transaction completed with errors.</li> </ul> |
| Name          | Name of the transaction. This name is based on the starting point of the transaction. For example, if the transaction starts from webMethods API Gateway, then this name would be the name of the API.                                                                                                                                                                                                                                                                                   |
| Duration (ms) | Total time taken by the transaction to complete.                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| Started from  | The application from which the transaction starts. For example, webMethods Integration Cloud.                                                                                                                                                                                                                                                                                                                                                                                            |
| Started on    | Start time for the transaction. The time zone is set based on the system time.                                                                                                                                                                                                                                                                                                                                                                                                           |
| Error message | Message with which the transaction failed.                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| Trace ID      | This is a unique identifier for the transaction.                                                                                                                                                                                                                                                                                                                                                                                                                                         |

## Editing a Transactions Group

1. On the Dashboard page, select  in the row for the transaction that you want to edit.

**Note:** Editing a transaction group impacts all the rules associated with it.

2. Make the necessary changes and click **Update**.

## Deleting a Group

1. On the Dashboard page, select  in the row for the transaction that you want to delete.

**Note:** Deleting a transaction group deletes all the rules and the rule violations associated with it.

2. Click **Delete**.

On successful deletion, you will see a confirmation message on the screen.

## Filtering the Business Transactions

You can filter the business transactions within any group to view a custom set of transactions.

**Note:** Filters that were set during group creation are already applied when you open the group.

### To filter the transactions

1. On the Transactions list page, click  as shown in the following example:

Filter: 

| Status                                                                              | Name                   |
|-------------------------------------------------------------------------------------|------------------------|
|  | API:orderAPI           |
|  | Business Transaction 1 |
|  | Business Transaction 2 |

2. In the Filter dialog box, you can choose from the following filters:

**Note:** Filters set during group creation are greyed out and not available for selection.

| Value               | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
|---------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Status              | <p>Select the transaction status. You can select from the following and click <b>Save</b>:</p> <ul style="list-style-type: none"> <li>■ <b>Success</b> - Lists all the completed business transactions.</li> <li>■ <b>Warning</b> - Lists all the transactions that have completed, but with an error.</li> <li>■ <b>Failed</b> - Lists all the failed transactions.</li> </ul>                                                                                                                                                                                                                                                                                                                                                                                            |
| Name                | <p>Type the name of the business transaction and click <b>Save</b>. To add more than one transaction name, click <b>+</b></p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| Duration            | <p>Select from the following operators using the drop-down list and provide a valid time in milliseconds:</p> <ul style="list-style-type: none"> <li>■ <math>\leq</math> - Select this operator to filter the transactions that have an execution time which is lesser than or equal to the value specified here.</li> <li>■ <math>\geq</math> - Select this operator to filter the transactions that have an execution time which is greater than or equal to the value specified here.</li> <li>■ <math>\leq \geq</math> Select this operator to group the transactions that have an execution time which is between the values specified here. For example, if you specify 20 and 30 (ms), then both the values 20 and 30 are also taken into consideration.</li> </ul> |
| Starts with         | <p>Filter the transactions on the basis of the application from where the business flow starts. Select the checkbox next to the product. You can select more than one product.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| Error message       | <p>Filter the transactions based on the error message with which it failed. Type the error message and click <b>Save</b>. For example, server not found. You can filter based on more than one error message by clicking <b>+</b> next to the error message box.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| Product(s) involved | <p>Filter the transactions based on the products that are involved with this transaction. Select the checkbox next to the product and click <b>Save</b>. You can select more than one product.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |

| Value    | Description                                                                                                                                                                                                                     |
|----------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trace ID | Filter the transactions based on this unique identifier associated with a transaction. Enter the trace ID and click <b>Save</b> . You can filter based on more than one Trace ID by clicking <b>+</b> next to the trace ID box. |

3. The applied filters show up on the top of the page as shown in the following example:

Filter: Status (2) × Duration(ms): <100 Error Message (3) ▼

| Status                                      | Duration (ms)                        |
|---------------------------------------------|--------------------------------------|
| <input checked="" type="checkbox"/> Failed  |                                      |
| <input checked="" type="checkbox"/> Warning | 411                                  |
| <input type="checkbox"/> Successful         | Transaction 1<br>681                 |
| <input type="checkbox"/> Successful         | <b>Business Transaction 2</b><br>195 |

You can close a particular filter by selecting the filter and clicking **X** adjacent to the filter name.

4. After you apply the filters and retrieve the list of transactions, you can further sort the list by clicking the column headings. Sort in ascending or descending order by toggling the column header.

## Alert

The Alert page lists all the Rule violations and the Rule list. From the Alert page, you can create **Rules**. These rules are a set of conditions. When these conditions are met by a group of transactions, the rule violation occurs. You can configure a rule such that it triggers an alert in the form of an on-screen notification or email or both. The rules that you create are applicable to all the transactions of a group with which it is associated. For information on creating a rule, see [“Creating a Rule” on page 750](#)

### Notification Alerts

Notifications for End-to-End Monitoring are currently shown on the top-right corner of your application screen. For example, when there are two new rule violations, you will

see .

## Email Alerts

When you create a rule, you have an option to be notified through an email. Whenever a group violates the conditions defined in a rule, you will receive system generated emails with the details of the violation.

## Rule Violations

This includes a list of all the rules that are violated by the transactions in a group. For more information, see [“Working with Rule Violations” on page 753](#).

## Rule List

This includes the list of all the rules that you create in the application. It also lists all the pre-defined rules available with the application. For more information on pre-defined rules, see [“Default Rules” on page 752](#).

## Viewing Alerts

### To view the alerts

1. Click  at the top of the screen to open the Rule violations pane. Here, you will see a list of all the new rule violations along with the older ones.

If there are new rule violations, you will see a number with . For example, two new rule violations are indicated by  at the top of the screen.

2. In the Rule violations pane, click **View all** to go to the Rule violations section of the Alert page.
3. In the **Rule violations** tab, you will see all the rules violations listed in a table format.

## Creating a Rule

The application triggers alerts when a group of transactions violates the conditions defined in a rule associated with it.

### To create a rule

1. On the Alert page, click **Rule list**.
2. Select **Create rule**.

**Note:** The application provides you a set of default rules. For more information, see [“Default Rules” on page 752](#)

3. In the Create rule dialog, provide the following details:
  - In the General Information section, provide the details for the following and click **Next**.

| Value       | Description                                                                                                                                                                       |
|-------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Name        | Provide a name for the rule.<br><br><b>Note:</b> You cannot change the rule name once you save the rule.                                                                          |
| Description | Provide a meaningful description for the rule.                                                                                                                                    |
| Group       | Select the group from the drop-down list.<br><br><b>Note:</b> Currently, you can associate a rule only to a single group. However, a group can be associated with multiple rules. |

- In the Rule Expression section, provide the details for the following and click **Next**.

| Value      | Description                                                                                                                                                                                                                                                                    |
|------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| KPI        | This is the key performance index. Select from the following options: <ul style="list-style-type: none"> <li>■ Error count</li> <li>■ Error rate</li> <li>■ Average response time</li> </ul>                                                                                   |
| Time range | The time range on the basis of which this rule should trigger an alert when violated. Select from the following options: <ul style="list-style-type: none"> <li>■ In last 30 mins</li> <li>■ In last 1 hour</li> <li>■ In last 12 hours</li> <li>■ In last 24 hours</li> </ul> |
| Operator   | Select the operator on the basis of which this rule should trigger an alert when violated. Select from the following options: <ul style="list-style-type: none"> <li>■ Less than (&lt;) - lesser than the value specified in the <b>Value</b> field.</li> </ul>                |

| Value | Description                                                                                                                                                                                                          |
|-------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|       | <ul style="list-style-type: none"> <li>Greater than (&gt;) - greater than the value specified in the <b>Value</b> field.</li> <li>Equals to (=) - equal to the value specified in the <b>Value</b> field.</li> </ul> |
|       | <p><b>Note:</b> <b>Value</b> could be a number, percentage, or time and changes on the basis of the KPI you select.</p>                                                                                              |

|       |                                                                                                                                                                                                                                                                                                                                                                                                   |
|-------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Value | <p>This field varies on the basis of your selection in the <b>KPI</b> field. The value field changes on the basis of the KPI you select:</p> <ul style="list-style-type: none"> <li>For <b>Error count</b>, it is set to <b>Value(number)</b>.</li> <li>For <b>Error rate</b>, it is set to <b>Value(%)</b>.</li> <li>For <b>Average response time</b>, it is set to <b>Value(ms)</b>.</li> </ul> |
|-------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

- In the **Action** section, select your notification preference and click **Next**. You can select either or both of the following options:

| Value                 | Description                                                                                                                                                                             |
|-----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Show app notification | Select this option to get on-screen app notifications.                                                                                                                                  |
| Send email            | Select this option to subscribe for email alerts whenever a group violates a rule. Provide the recipient email address. You can enter more than one email address separated by a comma. |

- In the **Summary** section, verify all the details provided by you and click **Save**.

### Default Rules

The application provides you with a set of pre-defined rules. By default, these rules are disabled. These pre-defined rules are as follows:

**Note:** Other than the **Name**, you can modify all the other values as per your requirements.

| Name                                       | Description                                                                            | Group            | KPI                      | Time Range     | Operator | Value    | Show app notification | Send email |
|--------------------------------------------|----------------------------------------------------------------------------------------|------------------|--------------------------|----------------|----------|----------|-----------------------|------------|
| Average response time is out of compliance | The average response time for all transactions in last 1 hour is greater than 1000 ms. | All Transactions | Average In response time | In last 1 hour | >        | 100 (ms) | True                  | False      |
| Error count is out of compliance           | The error count for all transactions in last 1 hour is more than 100.                  | All Transactions | Error count              | In last 1 hour | >        | 10       | True                  | False      |
| Error rate is out of compliance            | The error rate for all transactions in last 1 hour exceeds 10%.                        | All Transactions | Error rate               | In last 1 hour | >        | 10%      | True                  | False      |

## Working with Rule Violations

The Rule violations page provides details of all the violations. Use this page to search for specific violations and to view all the violations within the various groups for a specified duration. The following table provides you details of all the actions possible in the Rule violations page:

| Action   | Description                                                                                                                                                                                                                                                             |
|----------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Show all | <p>Use this drop-down list to filter all the violations on the basis of duration or status. The values include:</p> <ul style="list-style-type: none"> <li>■ All open</li> <li>■ All closed</li> <li>■ Last 1 hour</li> <li>■ Last 12 hours</li> <li>■ Today</li> </ul> |

| Action                                                                            | Description                                                                                                                                                                                                                                                                         |
|-----------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                                                                   | <ul style="list-style-type: none"> <li>■ Yesterday</li> <li>■ Last 7 days</li> </ul>                                                                                                                                                                                                |
|  | This is the refresh button. Click this to refresh the list of rule violations. It shows the time when the list was last refreshed.                                                                                                                                                  |
|  | This is the column view settings button. Click this to customize the columns you want to view for the rule violations.                                                                                                                                                              |
|  | <p>Select this drop-down list to filter the rule violations on the basis of group name. You also get a search box when you click this drop-down list. Use this search box to type a group name that you want to search.</p> <p><b>Note:</b> You can select more than one group.</p> |
| Search by name                                                                    | Type a rule name in this search box to filter all the rule violations on the basis of rule name.                                                                                                                                                                                    |

To sort the rule violations, click on the header row of any column. You can sort in both ascending and descending order.

## Working with Rule List

The application lists all the rules that you create in the Rule list page. The following table provides you details of all the actions possible in the Rule violations page:

| Action                                                                              | Description                                                                                                                                |
|-------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Create rule</b>                                                                  | Use this action button to create a new rule. For more information, see <a href="#">“Creating a Rule” on page 750</a> .                     |
|  | <p>To edit a rule, click this action button on the row of the corresponding rule.</p> <p><b>Note:</b> You cannot modify the rule name.</p> |

| Action                                                                              | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|-------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|    | To delete a rule, click this action button on the row of the corresponding rule.                                                                                                                                                                                                                                                                                                                                                                                                                      |
|    | <p>Select this toggle button in the <b>Status</b> column to enable or disable a rule.  indicates that a rule is enabled and  indicates that a rule is disabled.</p> <p><b>Note:</b> When you use this button, you will see corresponding system messages on screen to indicate if a rule is enabled or disabled successfully.</p> |
|    | This is the column view settings button. Click this to customize the columns you want to view for the listed rules. In the Show Columns dialog, select the columns you want to view and click <b>Save</b> .                                                                                                                                                                                                                                                                                           |
|  | <p>Select this drop-down list to filter the rules on the basis of group name. You also get a search box when you click this drop-down list. Use this search box to type a group name that you want to search.</p> <p><b>Note:</b> You can select more than one group.</p>                                                                                                                                                                                                                             |
| <b>Search by name</b>                                                               | Type a rule name in this search box to filter the rules on the basis of rule name.                                                                                                                                                                                                                                                                                                                                                                                                                    |

To sort the rules, click on the header row of any column. You can sort in both ascending and descending order.

## Business Transaction Details Page

The business transaction details page provides the following information about the transaction:


| Parameter | Description       |
|-----------|-------------------|
| Name      | Transaction name. |

| Parameter               | Description                                                                                                                                                                                                                                                                                               |
|-------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Trace ID                | Distinct identifier for the transaction generated internally by the application.                                                                                                                                                                                                                          |
| Status                  | Status of the transaction.                                                                                                                                                                                                                                                                                |
| Start - End period      | Time at which the transaction started and ended.                                                                                                                                                                                                                                                          |
| Duration (ms)           | Total time taken by the transaction to execute. This includes the <b>Total transit time</b> and the <b>Processing time</b> of the transaction. Total transit time is the time it takes for a client to process a request and return a response, which includes any network latency to or from the client. |
| Total transit time (ms) | This is the total time taken by the transaction from the time a client processes a request and receives a response. This includes any network latency to or from the client.                                                                                                                              |

### Business Flow Map

This provides a logical representation of the business flow showing the path taken by the transaction through the various cloud components. Also, the processing time for the transaction within each component is visible.

A legend ✔ *Successful* ⚠ *Warning* ❌ *Failed* is available to identify the status of a transaction. An example of a business flow is as follows:



### Viewing the Transaction Details

#### To view the transaction details

1. On the Application dashboard, select the transaction group for which you want to view the details.

2. On the Business Transaction Details page, click the component from the business flow map for which you want to view the details.

The details open in a separate pane and includes the following information:

| Field            | Description                                                                                                                                                                                                                                                                                                                                                                                       |
|------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Status           | <p>Provides the status of the transaction. Status can be:</p> <ul style="list-style-type: none"> <li>■ Successful</li> <li>■ Warning</li> <li>■ Failed</li> </ul>                                                                                                                                                                                                                                 |
| Cause of failure | <p>Provides the reason for the error to occur. If a transaction is successful, then this parameter is not visible.</p>                                                                                                                                                                                                                                                                            |
| Processing time  | <p>Time spent by the transaction within this component.</p>                                                                                                                                                                                                                                                                                                                                       |
| Stage            | <p>Phase at which the failure has occurred during the execution of a transaction. Stage represents an activity in the life cycle of the transaction. Possible stages are:</p> <ul style="list-style-type: none"> <li>■ Development</li> <li>■ Live</li> <li>■ Test</li> <li>■ Pre-Live</li> </ul> <p><b>Note:</b> Stage is visible only if you are viewing the details for Integration Cloud.</p> |
| More details...  | <p>Click this URL to open the details of the API or the integration that is associated with the business transaction. For an Integration, you are redirected to the instance of webMethods Integration Cloud in a new tab and for an API, you are redirected to the instance of webMethods API Gateway in a new tab.</p>                                                                          |

---

## User Journey

---

### Summary

This section provides details on the journey of a user who is using End-to-End Monitoring application. The application is used to view the end to end details of a business transaction as it moves through the various Software AG applications.

### Actors

As part of this user journey, we have two actors here who play their respective roles:

- Jim - A Software AG customer who owns an enterprise called **XYSales** and sells many products on his business platform. To run his business better, he uses products like webMethods API Gateway, webMethods Integration Cloud, and webMethods.io B2B. **XYSales** has a large customer base where every day new customers create their accounts on his business platform.
- Hayley - A prospective customer of Jim. She wants to create an account in **XYSales**.

### The Challenge

Jim reviews many business transactions in a day. These transactions move across the various Software AG applications. Reviewing the transactions helps Jim identify areas of improvement and any errors. In this scenario, XYSales uses both webMethods API Gateway and webMethods Integration Cloud. Jim can view the details of the transactions within the individual systems. For example, on an API execution, he can view its details using the logs in API Gateway. In the same manner, when an Integration is run, he can view its details using the logs in webMethods Integration Cloud. However, if an API calls an Integration in webMethods Integration Cloud, the log information does not tell Jim which Integration in webMethods Integration Cloud corresponds to which API execution in webMethods API Gateway.

To summarize, Jim is unable to correlate the information when a business transaction traverses through multiple systems. He is unable to view the end to end details of a business transaction. We are helping Jim solve this problem by introducing End to End Monitoring.

Hayley sends a request to create a user account using a client application. This triggers a business transaction. Jim wants to view the complete flow of this business transaction. He wants to know the details from the time Hayley sent the request to the time she received the response.

### Preconditions

As part of the prerequisites, Jim performs the following actions:

- Creates a connection from **XYSales** to webMethods Integration Cloud by creating an account in webMethods Integration Cloud.

- Creates an Integration called **CreateAccountinXYSales** in webMethods Integration Cloud. He exposes this Integration as a REST endpoint such that any client can access it.
- Creates an API called **APItoCreateAccountinXYSales** in webMethods API Gateway. This allows him to make a connection with the REST endpoint created in the earlier step.


### Basic Flow

When Hayley sends a request to create a user account in XYSales using the client application, following events take place:


1. The client application calls the REST API **APItoCreateAccountinXYSales**. The system applies all the policies defined for this API at this stage of the transaction.
2. After successful authentication of Hayley's account credentials with webMethods API Gateway, the API invokes the Integration **CreateAccountinXYSales** which is the REST endpoint.

The screenshot shows the webMethods Integration Cloud interface for the 'CreateAccountinXYSales' integration. The interface includes a navigation bar with 'Projects', 'Monitor', and 'Recipes' tabs. Below the navigation bar, there are tabs for 'Integrations', 'Document Types', 'Reference Data', 'REST APIs', 'SOAP APIs', 'Applications', and 'Keys & Certificates'. The main content area displays the details for the 'CreateAccountinXYSales' integration, including its name, description, and various configuration options. A red box highlights the 'Enable Integration to be invoked over HTTP' checkbox and the URL field below it.

3. The Integration is run and it creates the user account for Hayley in XYSales. On successful creation of the account, the system sends a confirmation message as a response to Hayley through the client application.
4. Jim can view the details of the API execution through the **Analytics** tab of the webMethods API Gateway cloud instance as shown here:




5. Jim can also view the details of the Integration using the **Monitor** tab of the webMethods Integration Cloud instance as shown here:




### How does Jim Monitor the Transactions?

1. Jim logs into webMethods Integration Cloud.
2. He selects **End-to-End Monitoring** from the App Switcher as shown here:



- Jim opens the Dashboard of webmethods.io End-to-End Monitoring to view all the transaction groups. By default, the duration selected for view is last half an hour from the current system time. Jim can see the following details:



- He selects the group **XYSSales** which lists all the transactions associated with his enterprise.
- He selects the transaction which he wants to view.
- On the business transaction details page, he can view all the information for that business transaction as shown here:

The screenshot shows the WEBMETHODS.io End-to-End Monitoring interface. The top navigation bar includes 'Dashboard' and 'Alert'. The breadcrumb trail is 'All Groups > All Transactions > APItoCreateAccountinXYSales'. The transaction details are as follows:

| Name                                                    | Trace ID                | Status                  |
|---------------------------------------------------------|-------------------------|-------------------------|
| APItoCreateAccountinXYSales                             | 2.627.15699271656390009 | Success                 |
| Start - End period (PDT)                                | Duration (ms)           | Total transit time (ms) |
| 1st Oct, 2019 03:52:45.639 - 1st Oct, 2019 03:52:45.710 | 71                      | 62                      |

Below the details is a 'Business flow map' showing a sequence of three components: Client, webMethods.io API (1 ms), and Integration Cloud (8 ms). A legend indicates Success (green circle), Warning (orange triangle), and Failed (red circle).

7. On the business transaction details page, he can get more details for each component of the transaction by selecting the component on the **Business flow map**. When he selects the component, the details are shown in a new pane. For example, Jim selects the **Integration Cloud** component and he can view the details as shown in the following image:

This screenshot is similar to the previous one but includes an open 'Integration Cloud Details' pane on the right side. The transaction details are identical. The 'Integration Cloud Details' pane shows the following information:

| Integration Cloud Details       |             |
|---------------------------------|-------------|
| Status                          | Success     |
| Processing time                 | 8 ms        |
| Stage                           | DEVELOPMENT |
| <a href="#">More details...</a> |             |

8. If Jim clicks on the **More details..** URL, it opens the webMethods Integration Cloud instance. Here, he finds information about the integration that was executed as part of this business transaction as shown in the following image:

The screenshot displays the 'Monitor' section of the WEBMETHODS Integration Cloud interface. The main heading is 'CreateAccountinXYSales'. Below this, it shows the 'Run at' time as '07/26/2019 12:25:51 PM IST', the 'Deployment Stage' as 'DEVELOPMENT', and the 'Overall Result' as 'Completed Successfully' with a green checkmark icon. A summary table shows 'Total Documents', 'Failed Documents', 'Successful Documents', and 'Success Score', all with dashes indicating zero values. An 'Execution Information' section lists details such as Start Time, End Time, Duration, Executed By (S P), Invocation Channel (HTTP Interface), Execution Result Reference, and Business Data. Below this is an 'Operations' section with filter tabs for 'Show Everything', 'Only Business Data', and 'Only Custom Messages'. A table with columns for Name, Start Time, Duration, Result, and Message is shown, with a note 'No items to display'. The interface includes a navigation bar at the top with 'Projects', 'Monitor', and 'Recipes' tabs, and a user profile 'Durga in user Development'.

9. This completes the user journey for Jim.

# Deploying to webMethods Integration Cloud

Version 6.0.0

October 2019

This document applies to webMethods Integration Cloud and Cloud Deployment Version 6.0.0 and to all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 2014-2019 Software AG, Darmstadt, Germany and/or Software AG USA Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://softwareag.com/licenses>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software AG.

# Table of Contents

|                                                                                    |           |
|------------------------------------------------------------------------------------|-----------|
| <b>webMethods Integration Cloud and Cloud Deployment.....</b>                      | <b>7</b>  |
| Document Conventions.....                                                          | 7         |
| Online Information and Support.....                                                | 8         |
| Data Protection.....                                                               | 9         |
| <b>Deploying on-premises packages and configurations to Integration Cloud.....</b> | <b>11</b> |
| Deploying to Integration Cloud.....                                                | 12        |
| <b>Get started with Cloud Deployment.....</b>                                      | <b>15</b> |
| Get started with Cloud Deployment.....                                             | 16        |
| <b>Installation information.....</b>                                               | <b>19</b> |
| Installation Information.....                                                      | 20        |
| <b>Deployable assets and configurations.....</b>                                   | <b>21</b> |
| Deployable Assets and Configurations.....                                          | 22        |
| <b>Cloud Deployment approaches.....</b>                                            | <b>27</b> |
| Cloud Deployment Approaches.....                                                   | 28        |
| <b>Connecting to Integration Cloud for Cloud Deployment.....</b>                   | <b>29</b> |
| Connecting to Integration Cloud for Cloud Deployment.....                          | 30        |
| Configuring a Connection to Integration Cloud.....                                 | 30        |
| Adding a Connection Configuration for Integration Cloud.....                       | 30        |
| Editing a Connection Configuration for Integration Cloud.....                      | 31        |
| Removing a Connection Configuration for Integration Cloud.....                     | 32        |
| <b>Deploying packages and configuration assets to Integration Cloud.....</b>       | <b>33</b> |
| Deploying Packages and Configuration Assets to Integration Cloud.....              | 34        |
| Checking the Deployment Status.....                                                | 35        |
| <b>Deploying Adapter for JDBC assets.....</b>                                      | <b>37</b> |
| Deploying Adapter for JDBC Assets.....                                             | 38        |
| <b>Asset Repository view.....</b>                                                  | <b>39</b> |
| Asset Repository.....                                                              | 40        |
| Opening the Asset Repository View.....                                             | 40        |
| Building Packages and Assets in Asset Repository View.....                         | 40        |
| Deploying Packages and Assets from Asset Repository View.....                      | 40        |
| Retracting Packages and Assets.....                                                | 41        |
| Deleting Packages and Assets.....                                                  | 41        |
| <b>Deploying Command Central assets to Integration Cloud.....</b>                  | <b>43</b> |
| About Deploying Command Central Assets to Integration Cloud.....                   | 44        |

---

|                                                                           |           |
|---------------------------------------------------------------------------|-----------|
| <b>Using Landscape Navigator View to view runtime configurations.....</b> | <b>45</b> |
| Using Landscape Navigator to View Runtime Configurations.....             | 46        |
| What Does the Landscape Navigator View Contain?.....                      | 46        |
| Creating Command Central Definitions.....                                 | 46        |
| Editing Command Central Definition.....                                   | 47        |
| Deleting a Command Central Definition.....                                | 48        |
| What Does the Configuration Browser View Contain?.....                    | 48        |
| Browsing Runtime Instances and Configurations.....                        | 48        |
| <b>Deploying customized configurations to Integration Cloud.....</b>      | <b>51</b> |
| Deploying Customized Configuration to Integration Cloud.....              | 52        |
| Exporting Deployable Configuration.....                                   | 52        |
| Using Configuration Project.....                                          | 54        |
| Editing Configuration Template.....                                       | 54        |
| Deploying a Configuration Project.....                                    | 55        |
| <b>Continuous Build and Publish.....</b>                                  | <b>57</b> |
| Continuous Build and Publish.....                                         | 58        |
| <b>Best Practices, General Information, and Dependencies.....</b>         | <b>65</b> |
| Best Practices, General Information, and Dependencies.....                | 66        |
| Best Practices.....                                                       | 66        |
| General Information.....                                                  | 66        |
| Dependencies.....                                                         | 66        |
| <b>Switch to Cloud Deployment.....</b>                                    | <b>69</b> |
| Overview.....                                                             | 70        |
| Solutions.....                                                            | 75        |
| Creating Solutions.....                                                   | 75        |
| Exploring Solutions.....                                                  | 82        |
| Assets.....                                                               | 84        |
| Support for GraphQL Assets.....                                           | 87        |
| Asset Repository.....                                                     | 93        |
| Deploy.....                                                               | 94        |
| Capability.....                                                           | 96        |
| Usage.....                                                                | 97        |
| Copying Solutions.....                                                    | 98        |
| Managing Solutions.....                                                   | 99        |
| Landscape.....                                                            | 99        |
| Service Access Settings.....                                              | 100       |
| Administration.....                                                       | 102       |
| Restart.....                                                              | 104       |
| Monitoring Solutions.....                                                 | 104       |
| Dashboard.....                                                            | 105       |
| Solutions.....                                                            | 106       |
| Runtimes.....                                                             | 107       |

---

|                                                                  |     |
|------------------------------------------------------------------|-----|
| Viewing Adapter KPIs.....                                        | 110 |
| Viewing Connector KPIs.....                                      | 110 |
| Services.....                                                    | 111 |
| Uptime.....                                                      | 112 |
| Alerts.....                                                      | 112 |
| Alert Types.....                                                 | 114 |
| Configuring the Alerts.....                                      | 114 |
| Logs.....                                                        | 116 |
| Database.....                                                    | 117 |
| Creating a Database.....                                         | 117 |
| Connecting a Solution to the Database.....                       | 117 |
| Securing the Connection Between a Solution and the Database..... | 118 |
| Monitoring the Database.....                                     | 119 |
| Cloud Deployment CLI.....                                        | 120 |
| Install Cloud Deployment CLI.....                                | 120 |
| Cloud Deployment CLI Reference.....                              | 122 |



---

## webMethods Integration Cloud and Cloud Deployment

---

This document contains information pertaining to webMethods Integration Cloud and Cloud Deployment.

### Document Conventions

---

| Convention     | Description                                                                                                                                                                                                              |
|----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Bold</b>    | Identifies elements on a screen.                                                                                                                                                                                         |
| Narrowfont     | Identifies service names and locations in the format <i>folder.subfolder.service</i> , APIs, Java classes, methods, properties.                                                                                          |
| <i>Italic</i>  | Identifies:<br><br>Variables for which you must supply values specific to your own situation or environment.<br>New terms the first time they occur in the text.<br>References to other documentation sources.           |
| Monospace font | Identifies:<br><br>Text you must type in.<br>Messages displayed by the system.<br>Program code.<br>Service names and locations in the format <i>folder.subfolder.service</i><br>APIs, Java classes, methods, properties. |
| { }            | Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.                                                                               |
|                | Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the   symbol.                                                                                                          |
| [ ]            | Indicates one or more options. Type only the information inside the square brackets. Do not type the [ ] symbols.                                                                                                        |

---

| Convention | Description                                                                                                               |
|------------|---------------------------------------------------------------------------------------------------------------------------|
| ...        | Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...). |

---

## Online Information and Support

---

### Software AG Documentation Website

You can find documentation on the Software AG Documentation website at "<http://documentation.softwareag.com>". The site requires credentials for Software AG's Product Support site Empower. If you do not have Empower credentials, you must use the TECHcommunity website.

### Software AG Empower Product Support Website

If you do not yet have an account for Empower, send an email to "[empower@softwareag.com](mailto:empower@softwareag.com)" with your name, company, and company email address and request an account.

Once you have an account, you can open Support Incidents online via the eService section of Empower at "<https://empower.softwareag.com/>".

You can find product information on the Software AG Empower Product Support website at "<https://empower.softwareag.com/>".

To submit feature/enhancement requests, get information about product availability, and download products, go to "[Products](#)".

To get information about fixes and to read early warnings, technical papers, and knowledge base articles, go to the "[Knowledge Center](#)".

If you have any questions, you can find a local or toll-free number for your country in our Global Support Contact Directory at "[https://empower.softwareag.com/public\\_directory.asp](https://empower.softwareag.com/public_directory.asp)" and give us a call.

### Software AG TECHcommunity

You can find documentation and other technical information on the Software AG TECHcommunity website at "<http://techcommunity.softwareag.com>". You can:

- Access product documentation, if you have TECHcommunity credentials. If you do not, you will need to register and specify "Documentation" as an area of interest.
- Access articles, code samples, demos, and tutorials.
- Use the online discussion forums, moderated by Software AG professionals, to ask questions, discuss best practices, and learn how other customers are using Software AG technology.
- Link to external websites that discuss open standards and web technology.

---

## Data Protection

---

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.



# 1 Deploying on-premises packages and configurations to Integration Cloud

---

|                                        |    |
|----------------------------------------|----|
| ■ Deploying to Integration Cloud ..... | 12 |
|----------------------------------------|----|

## Deploying to Integration Cloud

---

Cloud deployment is the process of deploying user-created packages and configurations that reside within on-premise runtimes or repositories to webMethods Integration Cloud. Using Software AG Designer you can seamlessly deploy your on-premise Integration Server packages and configuration assets to solutions present on Integration Cloud.

**Note:** In the cloud deployment context, configuration assets are limited to Integration Server and Universal Messaging configurations.


Software AG Designer allows you to deploy the Integration Server packages or configuration assets that you have created, verified, and tested on on-premise Integration Server or Universal Messaging to Integration Cloud. When you initiate the deployment from Designer, Integration Server packages and configuration assets are built from Integration Server and Command Central respectively, and are published to an asset repository present in Designer.

After performing variable substitutions to make the on-premise configuration data compatible for cloud deployment, you can publish the packages and configurations from the asset repository to a remote repository provisioned for the tenant on Integration Cloud.

Platform Manager plug-ins for Integration Server and Universal Messaging continuously monitor the remote repository on Integration Cloud. When a fresh deployment is detected, Platform Manager plug-ins deploy the Integration Server packages and configuration assets to respective runtime instances on Integration Cloud.

**Note:** Deploying assets to Integration Cloud using Designer eliminates the previous need to install or invoke webMethods Deployer on cloud for the purpose of cloud deployment.

The following figure provides a high-level basic overview of the process involved in deploying on-premise Integration Server packages and configuration assets to Integration Cloud.






# 2 Get started with Cloud Deployment

---

- Get started with Cloud Deployment ..... 16

## Get started with Cloud Deployment



The following table briefly describes the high-level tasks to get started with Cloud Deployment.

### Tasks

What is Cloud Deployment?

License and installation information.

Assets and configurations that can be deployed to Integration Cloud.

### References

See the *Deploying to Integration Cloud* section.

**Note:** See the article on “[Software AG TECHcommunity](#)” website to get started on Cloud Deployment.

- Install the relevant products as mentioned in the “[Installation Information](#)” on page 20 section.
- Create a tenant in webMethods Integration Cloud.
- Download the latest version of Software AG Designer to use the new features available for Cloud Deployment.

See “[Deployable Assets and Configurations](#)” on page 22.

---

| <b>Tasks</b>                                                                                                                                         | <b>References</b>                                                                                     |
|------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------|
| Create a solution in Integration Cloud.                                                                                                              | See the <i>Cloud Deployment</i> section in this document for information on how to create a solution. |
| Connect to Integration Cloud.                                                                                                                        | See <a href="#">“Connecting to Integration Cloud for Cloud Deployment”</a> on page 30.                |
| View and publish assets and configurations to the solution created in Integration Cloud using any of the Cloud Deployment approaches.                | See <a href="#">“Cloud Deployment Approaches”</a> on page 28.                                         |
| View and test the published assets and configurations in Integration Cloud.                                                                          | See the <i>Cloud Deployment</i> section in this document.                                             |
| Promote the assets and configurations to different stages.                                                                                           | See the <i>Cloud Deployment</i> section in this document.                                             |
| View and run services in Integration Cloud.                                                                                                          | See the <i>Cloud Deployment</i> section in this document.                                             |
| View the solution landscape, configure webMethods Integration Server service access settings, administer, and restart webMethods Integration Server. | See the <i>Cloud Deployment</i> section in this document.                                             |
| Monitor the health and availability of the deployed solutions and run-time instances, alerts, and alert statuses.                                    | See the <i>Cloud Deployment</i> section in this document.                                             |
| Best Practices and General Information.                                                                                                              | See <a href="#">“Best Practices, General Information, and Dependencies”</a> on page 66.               |



# 3 Installation information

---

|                                  |    |
|----------------------------------|----|
| ■ Installation Information ..... | 20 |
|----------------------------------|----|

## Installation Information

---

Install Software AG Command Central using the Command Central bootstrapper or provision a Command Central container from the Docker Store. For instructions, see the Command Central documentation.

Install the following products into a different directory or on a different machine, using the Software AG Installer or Command Central:

- webMethods Asset Build Environment
- Service Development in Software AG Designer with Local Version Control System Integration feature and webMethods Unit Test Framework.
- webMethods Integration Server with webMethods Unit Test Framework.
- Software AG Universal Messaging. All child nodes except Enablement for Cloud Foundry and webMethods Broker to UM Migration Utility.

If you want to use an external RDBMS for webMethods Integration Server, install webMethods Database Component Configurator on any machine on the same network as your database server, create the database components for webMethods Integration Server, and then connect webMethods Integration Server to the database components.

For detailed instructions, see the following documents:

- *Installing Software AG Products* document.
- If you are using Software AG Installer to install, see the *Using Software AG Installer* document.
- If you are using Command Central to install, see the *Software AG Command Central Help*.

# 4 Deployable assets and configurations

---

|                                              |    |
|----------------------------------------------|----|
| ■ Deployable Assets and Configurations ..... | 22 |
|----------------------------------------------|----|

## Deployable Assets and Configurations

The following table provides information on the deployable assets and configurations for webMethods Integration Server.

| Configuration/Asset Type                                                                                        | Asset/Configuration |
|-----------------------------------------------------------------------------------------------------------------|---------------------|
| ACLs                                                                                                            | Configuration       |
| Groups                                                                                                          | Configuration       |
| Consumer Web service endpoint alias                                                                             | Configuration       |
| Extended Settings *<br>(See <a href="#">“Best Practices, General Information, and Dependencies”</a> on page 66) | Configuration       |
| Global Variables                                                                                                | Configuration       |
| JMS aliases                                                                                                     | Configuration       |
| JNDI aliases                                                                                                    | Configuration       |
| Keystores                                                                                                       | Configuration       |
| Provider Web service endpoint alias                                                                             | Configuration       |
| Resources Settings *                                                                                            | Configuration       |
| SMTP settings *                                                                                                 | Configuration       |
| Truststores                                                                                                     | Configuration       |
| Users                                                                                                           | Configuration       |
| webMethods messaging                                                                                            | Configuration       |
| Flow Service                                                                                                    | Asset               |

---

| <u>Configuration/Asset Type</u> | <u>Asset/Configuration</u> |
|---------------------------------|----------------------------|
| Java Service                    | Asset                      |
| Map Service                     | Asset                      |
| OData Service                   | Asset                      |
| Adapter Service                 | Asset                      |
| .NET Service                    | Asset                      |
| C Service                       | Asset                      |
| Adapter Notification            | Asset                      |
| Document Type                   | Asset                      |
| Flat File Dictionary            | Asset                      |
| Flat File Schema                | Asset                      |
| JMS Trigger                     | Asset                      |
| REST API Descriptor             | Asset                      |
| REST Resource                   | Asset                      |
| Schema                          | Asset                      |
| Specification                   | Asset                      |
| Web Service Descriptor          | Asset                      |
| webMethods Messaging<br>Trigger | Asset                      |
| XML Document Type               | Asset                      |
| XSLT Service                    | Asset                      |

**\* - Restart Required**

The following table provides information on the deployable assets and configurations for webMethods CloudStreams.

| <u>Configuration/Asset Type</u>         | <u>Asset/Configuration</u> |
|-----------------------------------------|----------------------------|
| CloudStreams Connector Services         | Asset                      |
| CloudStreams Connection                 | Asset                      |
| CloudStreams Streaming Listener Service | Asset                      |
| CloudStreams OAuth Tokens*              | Configuration              |
| CloudStreams Database*                  | Configuration              |
| CloudStreams Large Data*                | Configuration              |
| CloudStreams Streaming Subscribers*     | Configuration              |
| CloudStreams Streaming Providers*       | Configuration              |

**\* - Restart Required**

The following table provides information on the deployable configurations for Software AG Universal Messaging.

| <u>Configuration Type</u> | <u>Asset/Configuration</u> |
|---------------------------|----------------------------|
| Channels                  | Transient                  |
|                           | Simple                     |
|                           | Reliable                   |
|                           | Persistent                 |
|                           | Mixed                      |
|                           | Off-Heap                   |
|                           | Paged                      |

| <u>Configuration Type</u> | <u>Asset/Configuration</u>                      |
|---------------------------|-------------------------------------------------|
| Cluster                   | UM Cluster                                      |
| JNDI Connection Factories | Connection Factory>Shared Durable Type          |
|                           | Connection Factory> Non Shared Durable Type     |
|                           | TopicConnection Factory>Shared Durable Type     |
|                           | TopicConnection Factory>Non Shared Durable Type |
|                           | Queue Connection Factory                        |
|                           | XA Connection Factory                           |
| JNDI Destinations         | Topic                                           |
|                           | Queue                                           |
| Memory *                  | JAVA_MIN_MEM JAVA_MAX_MEM                       |
| Queues                    | Transient                                       |
|                           | Simple                                          |
|                           | Reliable                                        |
|                           | Persistent                                      |
|                           | Mixed                                           |
|                           | Off-Heap                                        |
|                           | Paged                                           |
| Users                     | All Custom Users                                |
| Zones                     | UM Zone                                         |

\* - Restart Required



# 5 Cloud Deployment approaches

---

|                                     |    |
|-------------------------------------|----|
| ■ Cloud Deployment Approaches ..... | 28 |
|-------------------------------------|----|

## Cloud Deployment Approaches

---

Choose the following approaches to publish user-created packages and configurations to a solution created in webMethods Integration Cloud. See the *Cloud Deployment* section in the *webMethods Integration Cloud Help* for information on how to create a solution in webMethods Integration Cloud.

### Using Software AG Designer

- [“Package Navigator” on page 34](#): Use the **Package Navigator** view in Software AG Designer to deploy webMethods Integration Server packages and configuration assets to webMethods Integration Cloud.
- [“Asset Repository” on page 40](#): Use the **Asset Repository** view in the Service Development perspective of Software AG Designer to deploy webMethods Integration Server packages and configuration assets to webMethods Integration Cloud.
- [“Landscape Navigator” on page 46](#): Use the **Landscape Navigator** view in the Service Development perspective of Software AG Designer to deploy customized configuration templates to webMethods Integration Cloud. [“Export the configurations” on page 52](#) into a Software AG Designer configuration project and then build and deploy this project to webMethods Integration Cloud. For continuous integration purposes, these projects can be stored in a Version Control System (VCS) location, built through webMethods Asset Build Environment, and then deployed to webMethods Integration Cloud.

### Using Continuous Integration and Continuous Deployment (CI/CD)

- [“Continuous Integration and Continuous Deployment” on page 58](#)

# 6 Connecting to Integration Cloud for Cloud Deployment

---

- Connecting to Integration Cloud for Cloud Deployment ..... 30

## Connecting to Integration Cloud for Cloud Deployment

Using Designer you can deploy your on-premises Integration Server packages and configuration assets to Integration Cloud. Before deploying the packages and configuration assets, you must configure a connection to Integration Cloud.

Before you configure a connection to Integration Cloud, ensure that the following criteria are met:

- A valid URL exists to connect to Integration Cloud.
- A valid user account is created on Integration Cloud.

### Configuring a Connection to Integration Cloud

You need to provide specific information in Designer for initiating a connection to Integration Cloud. Designer saves this information in a connection configuration. You can add, edit, and update connection configurations in Designer.

### Adding a Connection Configuration for Integration Cloud

Using Designer you can add connections to different instances of Integration Cloud.

#### To add a connection configuration for Integration Cloud

1. In Designer, select **Window > Preferences**.
2. In the preferences navigation tree, select **Software AG>Integration Cloud**.
3. Click **Add**.
4. In the **Add connection configuration** dialog box, enter the following information:

| Field       | Description                                                                                                                                                                                                                                     |
|-------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Name</b> | The name to use for the Integration Cloud connection configuration.<br><br><b>Note:</b> The name cannot contain control characters, special characters, and characters outside of the basic ASCII character set, such as multi-byte characters. |
| <b>URL</b>  | URL of the Integration Cloud host to which Designer is to connect. For example, <code>https://&lt;sub-domain&gt;.&lt;domain-name&gt;.&lt;domain-suffix&gt;</code> , for example, <code>https://mysubdomain.webmethodscloud.com</code> .         |

| Field                                                | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>User</b>                                          | The user name for an account on Integration Cloud.                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| <b>Password</b>                                      | The password for the specified <b>User</b> .                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| <b>Save password (in the Eclipse secure storage)</b> | Indicates whether the password for the specified user account should be saved in Eclipse secure storage. Integration Cloud uses this password from the Eclipse secure storage whenever user authorization is required. If you want to save the password in Eclipse secure storage, select this check box.<br><br>If you decide not to save the password in Eclipse secure storage, you must specify your password each time your user authorization is required for connecting to Integration Cloud. |

- To verify whether Integration Cloud can be accessed by using the specified information, click **Test**.
- To store the connection configuration details, click **OK**.

A connection configuration is added to the Connections page with the specified details. The first connection configuration that you create is automatically marked as default. This default configuration is indicated with a check mark on the Connections page. Designer always uses the default connection configuration for Integration Cloud. If there are multiple connections configured, you can select the connection that you want to make it as default.

## Editing a Connection Configuration for Integration Cloud

You can edit a connection configuration for Integration Cloud if there are any changes in the configuration values.

### To edit a connection configuration for Integration Cloud

- In Designer, select **Window > Preferences**.
- In the preferences navigation tree, select **Software AG > Integration Cloud**.
- Click **Edit**.
- Enter new values in the connection configuration fields you want to change.
- In the **Edit Connection Configuration** dialog box, click **OK**.
- In the **Connections** page, click **OK**.

## Removing a Connection Configuration for Integration Cloud

You can remove connection configurations for Integration Cloud one at a time from the **Connections** page.

---

### To remove a connection configuration for Integration Cloud

1. In Designer, select **Window > Preferences**
2. In the preferences navigation tree, select **Software AG > Integration Cloud**.
3. Select the Integration Cloud connection configuration you want to remove.
4. Click **Remove**.

Designer prompts you to confirm that you want to remove the selected connection configuration.

5. Click **OK**.

# 7 Deploying packages and configuration assets to Integration Cloud

---

|                                                                          |    |
|--------------------------------------------------------------------------|----|
| ■ Deploying Packages and Configuration Assets to Integration Cloud ..... | 34 |
|--------------------------------------------------------------------------|----|

## Deploying Packages and Configuration Assets to Integration Cloud

Using Designer you can deploy Integration Server packages and configuration assets to Integration Cloud.

Before deploying packages and configuration assets to Integration Cloud, ensure the following:

- Designer is configured to connect to Integration Cloud using the Integration Cloud preference page. For more information on configuring a connection to Integration Cloud, see [Connecting to Integration Cloud for Cloud Deployment](#) chapter.
- Designer is configured to connect to Command Central. Use the Landscape Navigator view to connect to Command Central. For more information on Landscape Navigator view and connecting to Command Central, see [“Using Landscape Navigator to View Runtime Configurations” on page 46](#).
- Command Central is connected to Integration Server and Universal Messaging instances.

**Note:** If you plan to deploy only Integration Server packages and not the Universal Messaging and Integration Server configurations, you do not need to connect to Command Central.

### To deploy assets to Integration Cloud

**Note:** The following procedure explains how to deploy packages and configuration assets only to Integration Cloud. If you want to deploy, refresh, or remove the packages and configuration assets from Integration Cloud, use the Asset Repository view in Designer.

1. In Package Navigator view, select the Integration Server package that you want to deploy to Integration Cloud.
2. Right-click the package and click **Deploy to Cloud**.
3. In the Publish Assets to Cloud dialog box, select the package to deploy. You can select multiple packages.

If you want to publish the configuration assets along with the selected Integration Server package, select **Include runtime configurations**, click **Next**, and go to step 4. Otherwise, click **Next** and go to step 5.

Designer fetches the configuration data from Command Central.

4. In the Confirm selected configurations dialog box, select the configuration that you want to deploy and click **Next**.

5. In the Integration Server package variable substitution dialog box, select the package and edit the value of the property that you want to modify before deploying to cloud. Click **Next**.
6. In the Select Cloud Solution dialog box, select the solution on Integration Cloud to which you want to deploy the assets and click **Finish**.

Designer deploys the assets and configurations to a remote repository provisioned for the tenant on Integration Cloud.

## Checking the Deployment Status

After you deploy the assets to the Integration Cloud, you can check the deployment status.

### To check the deployment status

1. In the Service Development perspective of Designer, select **Window > Show View > Other**.
2. In the Show View dialog box, select **Software AG Service Development > Deployment Status**.
3. Click **Open**.

Designer displays the **Deployment Status** view with the current deployment status of the assets.

- Note:**
- To reload the deployment status, click .
  - To remove a specific deployment status, select the asset under the `Asset Name` and click .



# 8 Deploying Adapter for JDBC assets

---

- Deploying Adapter for JDBC Assets ..... 38

## Deploying Adapter for JDBC Assets

To deploy Adapter for JDBC assets such as driver jars and TypeMapping configurations to Integration Cloud, perform the following steps:

1. Create the below folder structure inside any package which needs to be deployed apart from the core product package:
  - `<package_Name>\adapters\WmJDBCAdapter\config`
2. Copy the database specific driver jar files from on-premises installation, `<webM_Home>\Integration Server\instances\<instance_Name>\packages\WmJDBCAdapter\code\jars` to `<package_Name>\code\jars\static`. Also, copy the Adapter for JDBC configurations (TypeMapping.xml files) from `<webM_Home>\Integration Server\instances\<instance_Name>\packages\WmJDBCAdapter\config` to `<package_Name>\adapters\WmJDBCAdapter\config` folder.
3. To enable the assets (Adapter Connections, Polling Notifications) on cloud, ensure to enable the **State After Deployment** option during deployment from Software AG Designer. The state of the assets (Adapter Connections, Polling Notifications) should be disabled on-premises before deploying to Integration Cloud. To deploy Adapter for JDBC to Integration Cloud, see [“Deploying Packages and Configuration Assets to Integration Cloud” on page 34](#).

- Note:**
- To connect to an on-premises database using VPN, you must variable substitute the serverName to IP address of the server as the hostname of the server cannot be resolved.
  - Segregate the driver jars and solutions such as Adapter for JDBC's services, notifications into separate test packages.
  - Set the proper package dependency between the jar package and the Adapter for JDBC's solutions package.

### Limitations

- You can use only Type 4 JDBC drivers for Integration Cloud deployment.
- Kerberos authentication is not supported.
- Data type configuration file editing is not supported.

# 9 Asset Repository view

---

|                          |    |
|--------------------------|----|
| ■ Asset Repository ..... | 40 |
|--------------------------|----|

---

## Asset Repository

---

Asset Repository is a binary repository that provides components for managing user assets . Asset Repository enables the process of repository-based deployment, in which runtime servers pull assets from a repository. You can build Integration Server packages and configuration assets and add to the repository making the assets available for deployment to Integration Cloud. Asset Repository is installed along with Designer using the Software AG Installer.

The Asset Repository view in Designer allows you to build, deploy, refresh, remove, or retract the assets.

---

### Opening the Asset Repository View

---

#### To open the Asset Repository view

1. In the Service Development perspective of Designer, select **Window > Show View > Other**.
2. In the **Show View** dialog box, select **Software AG Service Development > Asset Repository**.
3. Click **OK**.

---

### Building Packages and Assets in Asset Repository View

If the Asset Repository view does not already display the list of Integration Server packages and configuration assets, you can build them.

---

#### To build packages and configuration assets

1. In Asset Repository view, click the View Menu button ▾.
2. Select **Build**.

The Asset Repository view displays all the newly created Integration Server packages and configuration assets.

---

### Deploying Packages and Assets from Asset Repository View

You can deploy Integration Server package or configuration assets using the Asset Repository view.

---

#### To deploy packages and configuration assets from Asset Repository View

1. In Asset Repository view, select the Integration Server package or configuration assets that you want to deploy to Integration Cloud.
2. Right-click the package and click **Deploy to Cloud**.

3. In the **Publish Assets to Cloud** dialog box, select the package to deploy.  
If you want to publish the configuration assets along with the selected Integration Server package, select **Include runtime configurations**, click **Next**, and go to step 4. Otherwise, click **Next** and go to step 5.
4. In the **Confirm selected configurations** dialog box, select the configuration that you want to deploy and click **Next**.  
Designer fetches the configuration data from Software AG Command Central.
5. In the **Integration Server package variable substitution** dialog box, select the package and edit the value of the property that you want modify before deploying to cloud. Click **Next**.
6. In the **Select Cloud Solution** dialog box, select the solution on Integration Cloud to which you want to deploy the assets and click **Finish**.  
Designer deploys the assets and configurations to a remote repository provisioned for the tenant on Integration Cloud.

## Retracting Packages and Assets

Using Designer you can retract Integration Server packages, configuration assets, or both from Integration Cloud.

---

### To retract packages and configuration assets

1. In Asset Repository view, select the Integration Server package or configuration assets that you want to retract.
2. Right-click and select **Retract**.  
Designer retracts the packages and configuration assets from Integration Cloud.

## Deleting Packages and Assets

You can delete Integration Server packages or configuration assets from the Asset Repository view and from Integration Cloud. You can do this to remove packages and configuration assets with incorrect variable substitution or remove old versions of them from Integration Cloud.

---

### To delete packages and configuration assets

1. In Asset Repository view, select the Integration Server package or configuration assets that you want to delete.
2. Right-click and select **Remove**.  
Designer removes the Integration Server packages or configuration assets from Asset Repository view and Integration Cloud.



# 10 Deploying Command Central assets to Integration Cloud

---

- About Deploying Command Central Assets to Integration Cloud ..... 44

## About Deploying Command Central Assets to Integration Cloud

---

Command Central can export configuration properties for Software AG run-time components as YAML templates. Configuration properties are exported as Command Central composite assets using Software AG Designer, stored in the Landscape Asset Repository, and deployed to product instances, running on webMethods Integration Cloud.

To create Command Central assets and deploy them to Integration Cloud, in Designer:

1. Connect to Command Central.
2. Select and export the configurations to be deployed.
3. Edit the YAML configurations.
4. Deploy the assets to Integration Cloud.

# 11 Using Landscape Navigator View to view runtime configurations

---

|                                                                  |    |
|------------------------------------------------------------------|----|
| ■ Using Landscape Navigator to View Runtime Configurations ..... | 46 |
|------------------------------------------------------------------|----|

## Using Landscape Navigator to View Runtime Configurations

Using Landscape Navigator view you can connect to Command Central and view list of registered installations and runtime instances. For more information about connecting to Command Central see the *Creating Command Central Definitions* section.

### What Does the Landscape Navigator View Contain?

You can use Landscape Navigator view and Configuration Browser views to display the list of installations that are registered in Command Central. The available run-time instances are listed in the view for each installation and these available run-time instances are available for deploy to Integration Cloud.

Landscape Navigator view provides an option to connect to a local or remote Command Central server. To view the contents of installations that are registered in Command Central, you must configure a connection to Command Central and then establish a connection.

You can find Landscape Navigator and Configuration Browser views under the **Windows > Show View > Other > Software AG Command Central**.

### Creating Command Central Definitions

Command Central definitions create the connection between Designer and Command Central. The definition for a server contains the connection information needed to establish a connection with the Command Central server.

#### To create a Command Central definition

1. On the Landscape Navigator toolbar, click .
2. In the New Command Central Connection dialog box, enter the details for connecting to the Command Central server as described in following table:

| Field                           | Description                                                                                                                                                                                                                                                                                                    |
|---------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Connection name</b>          | The connection name.                                                                                                                                                                                                                                                                                           |
| <b>Command Central Location</b> | <p>Choose one of the following options to specify the location:</p> <ul style="list-style-type: none"> <li>■ <b>URL:</b> The URL for Command Central connection. For example,           <br/>https://           <br/>&lt;Command_Central_host&gt;:&lt;Command_Central_port&gt;/           <br/>cce.</li> </ul> |

| Field | Description                                                                                                                                                                 |
|-------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|       | <ul style="list-style-type: none"> <li>■ <b>Installation Directory:</b> The local Software AG product installation directory where Command Central is installed.</li> </ul> |

3. Under **Authentication**, enter the details as described in the following table:

| Field                          | Description                                                           |
|--------------------------------|-----------------------------------------------------------------------|
| <b>Username</b>                | Username to use for authentication on the Command Central.            |
| <b>Password</b>                | The password to use for authentication on the Command Central.        |
| <b>Connection timeout (s):</b> | The maximum seconds Designer waits for response from Command Central. |

4. Click **Save** password.

Designer stores the password in Eclipse secure storage location.

5. Click **Test Connection** to ping the Command Central server and to verify that the connection is working.

6. Click **Finish**.

Designer refreshes the Landscape Navigator view and displays the new connection.

## Editing Command Central Definition

If there are changes in the associated Command Central server that require you to update the server definition, edit the Command Central connection properties. For example, to add or edit the username and password, you must edit the Command Central Connection page to reflect that change.

### To edit a Command Central definition

1. Open the Landscape Navigator view.
2. Select the connection you want to edit.
3. Right-click the connection and select **Edit Command Central Connection**.
4. Edit the connection properties as needed.

## Deleting a Command Central Definition

### To delete a Command Central definition

1. Open the Landscape Navigator view.
2. Select the connection that you want to delete.
3. Right-click the connection and select **Delete Command Central Connection**.
4. Click **Yes** to confirm the deletion from the view.

## What Does the Configuration Browser View Contain?

Designer offers a detailed view of run-time specific configuration in Configuration Browser view. Designer retrieves information about a specific run-time component selected in Landscape Navigator.

The following table describes the runtime component information that is displayed in the Configuration Browser view.

| Name        | Description                                                   |
|-------------|---------------------------------------------------------------|
| Name        | Display name of the configuration instance.                   |
| Id          | Id of the runtime instance.                                   |
| Product     | Product to which the runtime instance belongs.                |
| Category    | Configuration category to which the runtime instance belongs. |
| Deployable  | Whether or not the asset is deployable to Integration Cloud.  |
| Description | Description of the configuration instance.                    |

## Browsing Runtime Instances and Configurations

After you connect to Command Central, you can use the Landscape Navigator view to browse the registered installations, for available runtimes and corresponding configurations.

When you expand an installation node, you can view the list of the runtime instances in that installation. You can also view the name and the runtime status as ONLINE, UNKNOWN, FAILED, OFFLINE, and so on. Upon expanding the runtime instances,

the list of configurations are displayed. You can view the configuration data for each configuration instance in Properties view, under Data tab.



# 12 Deploying customized configurations to Integration Cloud


---

|                                                                 |    |
|-----------------------------------------------------------------|----|
| ■ Deploying Customized Configuration to Integration Cloud ..... | 52 |
| ■ Exporting Deployable Configuration .....                      | 52 |
| ■ Using Configuration Project .....                             | 54 |
| ■ Editing Configuration Template .....                          | 54 |
| ■ Deploying a Configuration Project .....                       | 55 |

## Deploying Customized Configuration to Integration Cloud

Using Designer you can deploy customized configuration templates to Integration Cloud. You can use Landscape Navigator view to export the configuration into a Designer configuration project. Designer can be used to build and deploy this project to Integration Cloud. For continuous integration purpose, these projects can be stored in Version Control System location and built through Asset Build Environment and deployed to Integration Cloud.

The following figure depicts the processes involved in exporting deployable configurations.



## Exporting Deployable Configuration

You can export one or more runtime configurations to a YAML template file or as a deployable asset. You can export only deployable configurations. Deployable configurations are those configurations that can be deployed to Integration Cloud. Configuration Browser view lets you identify these deployable configurations assets in the list with the  icon.

You can export deployable configuration from a runtime instance as YAML template within a configuration project. For more information about configuration projects, see [“Using Configuration Project” on page 54](#). This YAML template can be manually edited and build as deployable asset. Alternatively, you can export configurations as deployable asset, which can be readily deployed to cloud solutions.

---

### To export a configuration

1. On the Landscape Navigator view , select one or more configurations from a runtime to export.
2. Right-click and select **Export Configurations**.
3. Under **Location**, provide the following information for the configuration project:

- Project: The project name for configuration project. You can assign a project in either of the following ways:
  - Browse and select an existing configuration template project.
  - Specify a new configuration project resource. For more information about creating a new project resource, see [“Using Configuration Project” on page 54](#).

4. In the **Name** field, select a template name.

The template contains the data for the selected configurations.

5. Under **Format**, select any one of the following values:
  - YAML source: To export configurations to YAML template. You can manually edit and build YAML template as a deployable asset.
  - Deployable Asset : To export configurations that are readily deployable for cloud solutions.
6. In the **Parameterization** field, type the name of a parameter used to identify parameterization.

An identifier can include lowercase a-z, uppercase A-Z, digits, dollar sign, and underscore. An identifier cannot start with a digit and cannot include any other special characters.

7. Click **Next**.

By default, Designer displays deployable configurations that are included for export.

8. Select the configuration contents to confirm the set of configurations to export.

9. Click **Finish**.

The exported YAML template file will open in an editor. You can view the exported contents using the Project Explorer view.

---

## Using Configuration Project

---

The configuration project is used for adding, editing, and building configuration templates exported from Integration Server and Universal Messaging runtimes. This project is pre-configured to build with Asset Build Environment which is used to prepare a deployable configuration asset from YAML source.

Before you configure a project, specify the build path entries to be used as the default path. For more information on specifying build path entries, see the Build Path Preferences page in Designer.

---

### To create a configuration project

1. In Designer, navigate to **File > New > Project > SoftwareAG**.
2. Under SoftwareAG element, select **Asset Builder** and click **Configuration template**.
3. Click **Next**.

Designer displays New Configuration Project dialog box.

4. In the **Project name** field, type the new name for the project.
5. Clear the **Use default location** check box, to choose a different location.  
By default Designer uses the Workspace root location. For example, (c: \<username> \workspace).
6. Click **Browse** adjacent to the **Location** field. Navigate to and select the location directory.
7. In the **Project Settings**, edit the default project structure preference to use for the source and output of builds.
8. Under **Working sets**, select check box **Add project to working sets** to specify a working sets.
9. Click **Finish**.

Designer creates a configuration project.

**Note:** You can install third-party YAML editors such as YEdit for Syntax highlighting support.

---

## Editing Configuration Template

---

Designer stores each configuration template as a YAML resource. A configuration template may contain multiple configuration types and corresponding instances from either Integration Server or Universal Messaging runtime. You can add or edit configuration types or instances in a configuration template exported from Landscape

Navigator. Designer uses the default YAML editor, or the Eclipse text editor to load the template.

---

#### To add configuration type or instance to a template

1. On the Landscape Navigator view , select an existing configuration from a runtime.
2. In the **Properties** view, select **Template** tab.

The **Template** tab displays the YAML source for the selected configuration.

3. Copy the required configuration data from the YAML source.
4. Append the data in the template.

Designer internally validates the YAML content for syntactical correctness and produces Deployable Configuration Asset upon save.

**Note:** You can install third-party YAML editors such as YEdit for Syntax highlighting support.

---

## Deploying a Configuration Project

---

#### To deploy configuration assets to Integration Cloud

1. In **Project Explorer** view, select the configuration project that you want to deploy to Integration Cloud.
2. Right-click the project and click **Deploy Configurations to Cloud**.
3. In the **Configuration Templates** dialog box, select the templates to deploy. Click **Next**.
4. In the **Configuration Template Variable Substitution** dialog box, select the template and edit the values of the property that you want to modify before deploying to cloud. Click **Next**.
5. In the **Select Cloud Solution** dialog box, select the solution on Integration Cloud to which you want to deploy the assets and click **Finish**.

Designer deploys the configurations assets to a remote repository provisioned for the tenant on Integration Cloud.



# 13 Continuous Build and Publish

---


|                                      |    |
|--------------------------------------|----|
| ■ Continuous Build and Publish ..... | 58 |
|--------------------------------------|----|

## Continuous Build and Publish

You can *build* user-created assets and configurations using webMethods Asset Build Environment (ABE), *retrieve* those assets and configurations from a VCS by using ABE or an automated tool like Jenkins, and then *deploy* those assets and configurations to the Integration Cloud *Development Stage* by using ABE.

**Note:** See “<http://techcommunity.softwareag.com/web/guest/pwiki/-/wiki/Main/CLOUD+DEPLOYMENT+USING+ABE>” for information on how to deploy on-premises assets and configurations using webMethods Asset Build Environment.

The following figure depicts the processes involved in the basic build and publish mechanism:



The following high-level steps describe the continuous integration (CI) and continuous deployment (CD) mechanism:

1. Create source packages and store them in a file system or any version control system (VCS). The source directory must be accessible to the build scripts. If the source directory is a file system on a VCS, ensure that the source directory is checked out in the local file system.
2. **Creating and exporting configurations from Software AG Command Central**

To create Command Central configurations, use the following command: `sagcc exec templates composite generate -i <generate-templatemetadata-file>.xml`

To export the configuration YAML files to a directory that you intend to use as sources for ABE, use the following command: `sagcc get templates composite export <templateAlias> -o <template-file>.yaml -f application/yaml`. Ensure that the exported YAML files are accessible to the build scripts.

3. Install webMethods Asset Build Environment (ABE). ABE installs the build scripts and the build properties file that you use to build the composites and descriptors. See the *Building Composites for Repository-Based Deployment* section in the *webMethods Deployer User's Guide* for more information.
4. Set the properties for the build and run the build script in ABE to create the composites and descriptors. See the *Building Composites for Repository-Based Deployment* section in the *webMethods Deployer User's Guide* for more information.
5. Use ABE to push the composites and descriptors to the Integration Cloud Asset Repository. Apart from providing values to the properties in `build.properties`, specify the following *additional* properties to upload composites and descriptors to the Integration Cloud Asset Repository.

| Property                 | Definition                                                                                                                                                                                                                                                                                                                                                            |
|--------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>localStore</code>  | Represents the local folder where the Git repository is cloned or the local Git repository. <code>localStore</code> must be the same as the <code>build.output.dir</code> .                                                                                                                                                                                           |
| <code>remoteStore</code> | <p>URL of the Integration Cloud Asset Repository. The URL format is:</p> <pre>https://mysubdomain.webmethodscloud.com/ integration/rest/internal/wmic-git/ &lt;stagename&gt;-&lt;solutionname&gt;-&lt;productaliasname&gt;</pre> <p>Example:</p> <pre>https://mysubdomain.webmethodscloud.com/ integration/rest/internal/wmic-git/ development-mysolution-mysis</pre> |
| <code>message</code>     | Required. Message which describes the commits.                                                                                                                                                                                                                                                                                                                        |
| <code>username</code>    | Required. Integration Cloud login user name.                                                                                                                                                                                                                                                                                                                          |
| <code>password</code>    | Required. Integration Cloud login password.                                                                                                                                                                                                                                                                                                                           |

Run one of the following commands from the `<Software AG_directory>\common\AssetBuildEnvironment\bin` directory to build and upload the composites and descriptors to the Integration Cloud Asset Repository:

| For this platform... | Run the following command...             |
|----------------------|------------------------------------------|
| Windows              | <code>build.bat buildUploadAssets</code> |
| UNIX                 | <code>build.sh buildUploadAssets</code>  |

## 6. Promoting assets to the next stage

- Using an automated tool like Jenkins, invoke the following API to promote the assets to the next stage:

**Method:** POST

**URL:** `https://{subdomain}.webmethodscloud.com/integration/rest/external/v1/cdep/binaryAssets/solutions/{solutionName}/nodes/{nodeName}?action=promote`

**URI parameters**

- *solutionName* - Name of the solution in Integration Cloud
- *nodeName* - webMethods Integration Server instance where the assets need to be deployed.

**Note:** Use *basic* as the HTTP authorization scheme.

**Request Body:** The request body should contain the following:

- **fromStageName:** In which stage the assets are available in Integration Cloud
- **toStageName:** To which stage the assets are to be promoted in Integration Cloud
- **commitMessage:** An optional commit message
- **acdlComposite:** List of composites, assets, and their properties, which are available in the previous stage.

**Note:** If you want to retrieve the request body, invoke the *getcomposites* API as provided in *Step b*. The *getcomposites* API will get the composites and asset details from the previous stage.

### Sample Request Body

```
{
 "integration": {
 "cicdBean": {
 "fromStageName": "Development",
 "toStageName": "Test",
 "commitMessage": "Promoting assets from Development stage to
 Test stage.",
 "acdlComposite": {
 "IS": [{
 "name": "mySqlAssets",
 "targetNamespace": "http://namespaces.softwareag.com/
 webMethods/IS",
```

```

"assets": [],
"properties": [{
 "name": "activatePkgOnInstall",
 "values": [
 "true"
]
},
{
 "name": "archivePkgOnInstall",
 "values": [
 "true"
]
},
{
 "name": "compilePackage",
 "values": [
 "true"
]
}
]
},
{
 "name": "JDBCRegression_deployment",
 "targetNamespace": "http://namespaces.softwareag.com/webMethods/IS",
 "assets": [{
 "name": "deploy.notifications.deleteN",
 "properties": [{
 "name": "art.deployment.state",
 "values": [
 "disable"
]
 },
 {
 "name": "notificationImmediate",
 "values": [
 "false"
]
 },
 {
 "name": "notificationInterval",
 "values": [
 "10"
]
 },
 {
 "name": "notificationOverlap",
 "values": [
 "false"
]
 }
]
}],
"properties": [{
 "name": "activatePkgOnInstall",
 "values": [
 "true"
]
}
]]
}
]
}
}

```

```
}
}
```

## b. `getcomposites` API

`getcomposites` retrieves all the composites and its assets which have properties.

**Method:** GET

**URL:** `https://{subdomain}.webmethodscloud.com/integration/rest/external/v1/cdep/binaryAssets/solutions/{solutionName}/nodes/{nodeName}?stageName={stageName}`

### URI parameters

- *solutionName*: Name of the solution in Integration Cloud
- *nodeName*: webMethods Integration Server instance where the assets need to be deployed

### Query parameters

- *stagename*: The stage from where the composites and assets have to be retrieved

*Allowed stage names:* development, test, live, preLive

**Note:** Use *basic* as the HTTP authorization scheme.

### Sample Response

```
{
 "integration": {
 "message": {
 "code": 0,
 "description": "Success"
 }
 },
 "cicdBean": {
 "fromStageName": "Development",
 "toStageName": "Test",
 "commitMessage": null,
 "acdlComposite": {
 "IS": [{
 "name": "mySqlAssets",
 "targetNamespace": "http://namespaces.softwareag.com/webMethods/IS",
 "assets": [],
 "properties": [{
 "name": "activatePkgOnInstall",
 "values": [
 "true"
]
 }
],
 {
 "name": "archivePkgOnInstall",
 "values": [
 "true"
]
 }
],
 {
 "name": "compilePackage",
 "values": [
 "true"
]
 }
]
}
```





# 14 Best Practices, General Information, and Dependencies

---

- Best Practices, General Information, and Dependencies ..... 66

## Best Practices, General Information, and Dependencies

---

This section contains information on best practices and general notes on Cloud Deployment.

### Best Practices

#### Extended Settings deployment

- If you use the **Deploy To Cloud** option in Software AG Designer, you cannot deploy *Extended Settings* parameters of on-premises webMethods Integration Server. For deploying extended settings, use the **Landscape Navigator** to generate *Templates*, which can then be deployed to webMethods Integration Cloud.

### General Information

- For specifying JDBC Jars that can be shared by multiple packages, on-premises users may have placed those files under the `custom/jars` directory in webMethods Integration Server. For cloud deployment, place those files in the `code/jars/static` directory of some common package to make the required JDBC classes available when the package is deployed to webMethods Integration Cloud.
- If keystores and truststores are created in the customer's environment, location of the keystores and truststores may be pointing to some file on a local file system. It is recommended to place these files in the `config` directory of some common package. This package can be deployed to webMethods Integration Cloud and keystores and truststores can use the `packages/CustomPackage/config/myKeystore.jks` path to refer to the keystore location.
- In case of failure to send messages from Software AG Universal Messaging, webMethods Integration Server stores the messages in Client side Queue (CSQ), which is currently an embedded database. As webMethods Integration Server is in a Docker container, any such locally stored messages may be lost.
- Time out errors like *504 Gateway Time-out* may appear, if the processing time is greater than 2 minutes.
- Software AG Designer allows you to deploy assets without the required dependencies as well as delete assets which are referenced by other assets. It is recommended to manually check and manage the dependencies.

### Dependencies

- While deploying packages containing webMethods CloudStreams assets like CloudStreams connector services, CloudStreams connection, and CloudStreams

connector listeners, ensure that you set the dependency on the Provider package that was used to create those assets.



# 15 Switch to Cloud Deployment

---

|                              |     |
|------------------------------|-----|
| ■ Overview .....             | 70  |
| ■ Solutions .....            | 75  |
| ■ Monitoring Solutions ..... | 104 |
| ■ Database .....             | 117 |
| ■ Cloud Deployment CLI ..... | 120 |

## Overview


---

Cloud deployment is the process of deploying packages and configurations that reside within on-premises runtimes or repositories to webMethods Integration Cloud. Using Software AG Designer or by employing the Continuous Integration (CI) approach, you can seamlessly deploy your on-premises webMethods Integration Server packages, Adapter packages, webMethods CloudStreams packages, configuration assets, and customized configurations to solutions created on Integration Cloud. In the cloud deployment context, configuration assets are limited to webMethods Integration Server and Universal Messaging configurations.

**Note:** As soon as you register, Cloud Deployment capability is enabled by default for all tenants.

**Note:** See *Deploying to webMethods Integration Cloud* for information on how to deploy packages and configurations that reside within on-premises runtimes or repositories to webMethods Integration Cloud. See the article on [“Software AG TECHcommunity”](#) website to get started on Cloud Deployment.

The following figure provides a high-level overview of the process involved in deploying on-premises webMethods Integration Server packages and configuration assets to Integration Cloud.





With Software AG Designer, you can deploy the webMethods Integration Server packages or configuration assets that you have created, verified, and tested on on-premises webMethods Integration Server or Universal Messaging to Integration Cloud. When you initiate the deployment from Software AG Designer, webMethods Integration Server packages and configuration assets are built from webMethods Integration Server and Software AG Command Central respectively, and are published to the Asset Repository available in Software AG Designer. After performing variable substitutions to make the on-premises configuration data compatible for cloud deployment, you can publish the packages and configurations to an asset repository provisioned for the tenant on Integration Cloud.


### User Interface elements


The following table describes the various user interface elements that appear on the **Cloud Deployment** workspace:

| Page Elements               | Icon                                                                                | Description                       |
|-----------------------------|-------------------------------------------------------------------------------------|-----------------------------------|
| webMethods Cloud Deployment |  | Access the home page.             |
| Solutions                   |  | View and create solutions, deploy |

| Page Elements        | Icon                                                                                                                                                    | Description                                                                                                                                                                                                                                                                                                                                                               |
|----------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Monitoring           |                                                                        | <p>solutions to stages, view the Asset Repository, and manage webMethods Integration Server instances.</p> <p>View the overall status of the solutions, landscapes, system and runtime alerts, KPI graphs of the runtimes, service executions of the webMethods Integration Server instances, availability of the run times, alert status of the solutions, and logs.</p> |
| Runtime availability | <p>Runtime availability<br/>of all solutions for the last 24hrs</p>  | <p>View the overall runtime availability for all the solutions in the last 24 hours.</p>                                                                                                                                                                                                                                                                                  |
| Usage Statistics     | <p>License Usage<br/>Total usage across all stages</p>               | <p>The usage statistics shows the CPU and Memory usage for all solutions in all stages.</p> <p>The CPU bar shows the maximum CPU that is licensed for the tenant. The colored part of the bar shows how much of the allowed CPU is currently used by the tenant.</p> <p>The Memory bar shows the memory in Gb that is licensed</p>                                        |

| Page Elements              | Icon                                                                                | Description                                                                                                                                                                                                                                                                                                    |
|----------------------------|-------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Database                   |    | <p>for the tenant. The colored part of the bar shows how much of the allowed memory is currently used by the tenant.</p> <p>Add a database to your cloud deployment subscription. This enables you to configure, store, and monitor your database directly in the cloud instead of using external systems.</p> |
| Solutions section          |   | <p>Total number of solutions created. View the <i>Solution List</i> page by clicking the <i>Details</i> link and the <i>Monitoring Dashboard</i> by clicking the <i>Monitoring</i> link.</p>                                                                                                                   |
| Service Executions section |  | <p>Number of service executions and their status in the last 24 hours for all the solutions that are currently available in the selected <i>Stage in view</i>. To view the <i>Services</i> page under <i>Monitoring</i>, click the <i>service execution</i> link.</p>                                          |

| Page Elements         | Icon                                                                                                                                                                                                                                                               | Description                                                                                                                                                                                                                                          |
|-----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Active Alerts section |  The icon shows a bell with a diamond in the center, indicating no alerts. Below the bell, it says "No Open Alerts" and at the bottom, "0 Critical   0 Warning   0 Information". | Number of currently open alerts and their severity. Click on the links to go to the <i>Alerts</i> page.                                                                                                                                              |
| Change the stage      |  The icon is a blue button with the text "Stage in view" and "Development" below it.                                                                                              | Click to change and manage stages.                                                                                                                                                                                                                   |
| Application Launcher  |  The icon is a blue square with a white grid pattern.                                                                                                                             | Click to access integration Apps.                                                                                                                                                                                                                    |
| Help                  |  The icon is a blue square with a white question mark inside a circle.                                                                                                            | Access Help topics, Software AG TECHcommunity, Licensing capabilities, and the About page. The About page displays the version information, Global Support information, Copyright information, Impressum and Privacy Policy, and the release readme. |
| Profile               |  The icon is a blue square with a white person silhouette inside a circle.                                                                                                      | Name of the logged in user, profile information of the logged in user, and Logout option.                                                                                                                                                            |

| Page Elements                              | Icon                                                                                                                                                                                                                                   | Description                                                                                                                 |
|--------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------|
| Last Login, Notifications, and Help topics | <p><b>Last Login</b><br/>07/20/2019 02:12:13</p> <p><b>Notifications</b></p>  <p><b>What's New</b></p> <p><b>Help Topics</b><br/>Cloud Deployment</p> | When was the last login, important and other notifications, what is new in this release, and context-sensitive help topics. |

## Solutions

A **Solution** consists of packages bundled together into one coherent service. It is a logical combination of webMethods Integration Server packages, Adapter packages, Services, webMethods CloudStreams packages, and webMethods Integration Server and Universal Messaging configuration assets or configurations.

**Note:** After deploying the configurations, due to webMethods Integration Server restart, the assets will appear after a short delay.

Integration Cloud Integrations can invoke Cloud Deployment webMethods Integration Server services for the same tenant. Using the predefined *Cloud Deployment Application* available in Integration Cloud, you can select the solution webMethods Integration Server services that you want to invoke from Integration Cloud.

## Creating Solutions

The **Solution List** page displays the solutions created in Integration Cloud.

**Note:** You must have the required permissions under **Settings**  **> Access Profiles > Administrative Permissions > Functional Controls > Solution** to create, update, or delete Solutions.


**Note:** You must first create a solution in Integration Cloud before deploying the on-premises assets and configurations.

All solutions created are initially copied to the Development stage. You can create a new solution in any stage, for example, development, test, live, and prelive. Further, you cannot modify the solution name and clustering details after it is created. You can

configure the solution in subsequent stages but after you configure a solution in a stage, you cannot modify the solution again in that stage. In a stage, you can configure only those solutions that are marked as **Not Configured**.

### To create a solution

1. Switch to the **Cloud Deployment** perspective.



As soon as you register, Cloud Deployment capability is enabled by default for all tenants. By default, 3 CPU core and 6 GB memory are allocated for all tenants. When you access Cloud Deployment for the first time using the application launcher, you need to start provisioning.

Start provisioning now

[No, thanks. Take me back to Integration Cloud](#)

After provisioning, your setup will be complete, and you can launch Cloud Deployment.

## Setup Complete

Start experiencing Cloud Deployment now


Launch Cloud Deployment

**Note:** Solutions created using a trial account are deactivated daily. After you log in, you need to reactivate the solutions. All assets will be available after a short delay.

2. After you launch Cloud Deployment, from the **Cloud Deployment** navigation bar, click **Solutions > Solution List**.


The **Solution List** page appears.

3. From the **Solution List** page, click **Create New Solution** to create a solution. You can create a solution in any stage.
4. Select the landscape model that best represents your environment. The available designs are an webMethods Integration Server with a Terracotta server, an webMethods Integration Server with a cluster and a Terracotta server, or webMethods Integration Servers with a Universal Messaging cluster and a Terracotta stripe. Your packages, assets, configurations, and services are deployed automatically onto the selected landscape.



5. Click **OK**.
6. In the **New Solution** page, fill in the solution **Name**, the solution **Description**, the name of the webMethods Integration Server and Universal Messaging instances, number of CPU **Cores**, and **Memory** characteristics of the hardware to support each service in the solution landscape.

**Note:** You can also select the webMethods Integration Server and Universal Messaging icons to highlight the sections in the **New Solution** page. Terracotta is available only when webMethods Integration Server runs in a clustered mode. Further, clustering and Terracotta options are not available in the **Development** stage.



The **Version** list box lists all the available major versions. The solution will be created based on the available **Fix** version. webMethods Integration Server packages such as WmCloudStreams and WmJDBCAdapter will appear in the **Packages** group box based on the **Fix** version. Select the **Packages** you want to enable. After you save the solution, you will not be able to change the major **Version**. You can change only the number of CPU Cores, Memory, Fix version if available, and Packages.

You can deploy CloudStreams provider packages, CloudStreams connector services, CloudStreams connection, and CloudStreams connector listeners to a solution in Cloud Deployment only if you have selected WmCloudStreams as the package option while creating the solution.

On the **Landscape** page, select the **Cluster Type** as **Stateless** if the group of webMethods Integration Servers function in a manner similar to a cluster but are not part of a configured cluster. A stateless cluster of webMethods Integration Servers does not use a Terracotta Server Array. Select **Stateful** to add the Terracotta section. The Terracotta icons will be activated.

The **Hot Fix** list box lists all available fixes that include enhancements to versions. **Hot fix** field is optional. Selecting **None** option will remove the hotfixes applied on the solution, and the solution will point to the base fix version. Typically, hotfixes are created for specific tenants.

**Note:** After creating a solution, if you modify the package list options in the **Packages** group box and save the solution, due to webMethods Integration Server restart, the assets will appear after a short delay.

### Updating products to a higher fix version in a solution

You can update any product in a solution to the available higher fix version after you create the solution. The **Update Available** option appears if a higher fix version is available for any of the products in the solution. The latest fix version appears in the **Fix** drop-down list. For example, if you have selected Fix 3 of webMethods

Integration Server while creating a solution, and if Fix 4 is now available, you can select Fix 4 and save the solution.

**Note:** While configuring a solution in a higher stage, the fix version of the products in the solution will be taken from the lower stage. If a solution is updated in a lower stage, you will be given an option to update the solution in the higher stage, to the fix versions of the products in the lower stage.

For example, if you configure a solution in a higher stage (Test stage) and then go back to a lower stage (Development stage), and if a higher fix version is available for a product in the Development stage, you can click **Update Available**, and in the **Edit Solution** screen, you can select the higher fix version for the product in the solution. Now if you go to the higher stage (Test), the **Update Available** option will appear in the Test stage. You can update products in a solution at every stage, to the fix versions of the products in the solution available in the immediate lower stage. Note that after you update or update the products in the solution, the products in the solution will not be accessible for sometime.

#### Updating products to a higher version in a solution

You can update any product in a solution to the available higher version after you create the solution. The **Update Available** option appears if a higher version is available for any of the products in the solution. The latest version appears in the **Version** drop-down list. For example, if you have selected 10.3 of webMethods Integration Server while creating a solution, and if 10.5 is now available, you can select version 10.5 and save the solution. Further, if you update to v10.5, the latest available fix for v10.5 will be automatically selected.

**Note:** While configuring a solution in a higher stage, the version of the products in the solution will be taken from the lower stage.

If a higher version is available for a product in a stage, you can click **Update Available**, and in the **Edit Solution** screen, you can select the higher version for the product in the solution.

The **Schedule** option appears if you select a higher version available for any of the products in the solution. Click **Schedule** to schedule the update process by specifying the date and time on which you want the update process to execute. Once the solution is scheduled for update, you can click **Cancel Schedule** to cancel the schedule or click **Modify Schedule** to modify the schedule. If the update process is scheduled, the status of the solution on the **Solution List** page displays **Update scheduled**. The status of the solution on the **Solution List** page displays **Update in progress** if the scheduled update process is under way.

**Note:** After a solution is updated successfully, ensure that you click **Confirm Update** within seven days to complete the update process or click **Rollback** to rollback the solution to the previous version. After seven days, except for the **Confirm Update** and **Rollback** options, the solution page will not be available. If you rollback, the status of the solution on the **Solution List** page


displays **Rollback in progress** until the solution is rolled back to the previous version.

7. The **Tracing** list box appears only if you have the App Dynamics capability and if you are currently using AppDynamics to trace end to end business flows. It allows you to trace logs after you create or update a solution for an webMethods Integration Server runtime. Currently, tracing support is provided only for the webMethods Integration Server runtime. Select **AppDynamics** from the drop-down list to provide the AppDynamics tracing support and upload a valid Controller XML and Config XML file containing the Appdynamics details. You can update the controller file for each webMethods Integration Server runtime. You also have the option to download the controller and config files and then upload the files after modifying them.


**Note:** If you select AppDynamics tracing and provide a valid controller file, the tracing data will appear on the AppDynamics cloud application.

Let us see an example of how the tracing data appears on Appdynamics when you create a solution in Cloud Deployment.


- a. Go to <https://www.appdynamics.com/> and register in AppDynamics.
- b. On the Overview > Applications panel, click **Get Started**.




- c. On the Getting Started wizard, click **Java** under the Applications panel.



- d. Download the Java Agent Installer.



- e. Go to the ver<xxx> > **conf** folder on your local system and view the controller-info.xml and app-agent-config.xml files.
- f. Open the controller-info.xml file and provide the following values:
- ```
<application-name>MyApplication</application-name>
<node-name>AppIS</node-name>
```
- g. Log in to Integration Cloud and switch to Cloud Deployment using the App switcher.
- h. Create a new solution in Cloud Deployment and select **AppDynamics** from the drop-down list to provide the AppDynamics tracing support. Upload the controller-info.xml and app-agent-config.xml files, and save the solution.



- i. Log in to AppDynamics. Your application, that is, **MyApplication** appears on the Applications panel.
- j. Click on MyApplication and view the service execution status and execution logs.

The screenshot shows the Appdynamics interface with the 'Transaction Snapshots' view selected. The table below represents the data shown in the interface:

Time	Exe Time (ms)	URL	Business Transaction	Tier	Node
07/22/19 2:53:22 PM	2	invoke/wm.server.query/getPrometheusS...	invoke/wm.server.query	MyTier	App5
07/22/19 2:47:51 PM	3	invoke/wm.server.monitoring/getMetaM...	invoke/wm.server.monitoring	MyTier	App5
07/22/19 2:47:21 PM	1	invoke/wm.server/disconnect	invoke/wm.server	MyTier	App5
07/22/19 2:47:13 PM	1	invoke/wm.server.spm.runtimeStatus/ch...	invoke/wm.server.spm.runtimeSt...	MyTier	App5
07/22/19 2:43:21 PM	2	invoke/wm.server.query/getPrometheusS...	invoke/wm.server.query	MyTier	App5


- Click **Save** to save the solution.

The new solution is created and appears in the **Solution List** page. You cannot modify the solution after the solution is created. You can configure the solution in subsequent stages but once a solution is configured in a stage, you cannot modify the solution again in that stage.

Note: You can now deploy the solution to the next stage.

Deactivate, Activate, and Delete a solution

Click the  icon and select **Deactivate** to deactivate a solution. All packages and assets will be permanently deleted and cannot be recovered. Click the  icon and select **Activate** to activate an inactive solution.



Click the  icon and select **Delete** to permanently delete the solution. If a solution is configured in a subsequent stage, it will be permanently deleted from the current stage and cannot be recovered. Further, if you delete the solution, you will not be able to promote assets from the current stage.

Exploring Solutions


The solution details page allows you to view the packages, assets, configurations and services for different runtimes in the solution, deploy the solution to another stage, view the Asset Repository, and manage the solution, that is, view the landscape, configure

webMethods Integration Server service access settings, administer the webMethods Integration Server, or restart the webMethods Integration Server instances.

Note: You can create a new solution in any stage. You can configure the solution in subsequent stages but after you configure the solution in a stage, you cannot modify it again in that stage.

To view the Solution Explorer

1. Switch to the **Cloud Deployment** perspective.




2. From the **Cloud Deployment** navigation bar, click **Solutions > Solution List**.

The **Solution List** page appears listing all the solutions.

3. Click on an existing solution. The Solution Explorer page appears.

Solution Explorer



The following table provides a high-level overview of the Solution Explorer page:

Component	Description
“Assets” on page 84	View the Packages, Folders, Assets, and Services for webMethods Integration Server, Adapters, webMethods CloudStreams packages, and configurations for the Universal Messaging runtime.
“Deploy” on page 94	Deploy the solution to another stage.
“Asset Repository” on page 93	View the Asset Repository which displays the contents of the on-premises packages published to Integration Cloud.
“Manage” on page 99	View the landscape, configure webMethods Integration Server service access settings, administer the webMethods Integration Server, or restart the webMethods Integration Server instances.


Assets

A package is a container that is used to bundle services and related elements, such as specifications, webMethods Integration Server document types, webMethods Integration Server schemas, and triggers. When you create a folder, service, webMethods Integration Server document type, or any element, you save it in a package.

Note: To view and access webMethods Integration Server packages in Integration Cloud, you must assign any custom user groups created in webMethods Integration Server, which are assigned to Access Profiles in the **Solution Permissions** page, to the following Access Control Lists in webMethods Integration Server:

- Administrators ACL
- Developers ACL
- Replicators ACL

The following figure depicts the package structure in a solution.



Packages are designed to hold all of the components of a logical unit in an integration solution. For example, you might group all the services and files specific to a particular marketplace in a single package. All the components that belong to a package reside in the package's subdirectory.

Note: Click the arrow beside a folder or package to view its contents.


Downloading assets

You can download user deployed packages and configurations from the **Asset** page. To download assets, point to an asset, click the  icon, and then click **Download**. The assets will be zipped and downloaded to your local storage space.

Note: You cannot download default packages such as packages that come with webMethods Integration Server installation, for example, Default, WmART, WmCloud, WmJDBCAdapter, WmPublic, and so on.

Services

Services are method-like units of logic that operate on documents. You build services to carry out work such as extracting data from documents, interacting with back-end resources (for example, submitting a query to a database or executing a transaction on a mainframe computer), and publishing documents. Adapters and other add-on packages provide additional services that you use to interact with specific resources or applications. The service editor allows you to view and run the services.



Service Signature

Input and output parameters are the names and types of fields that the service requires as input and generates as output. These parameters are also collectively referred to as a *signature*. You declare a signature for all types of services: flow services, Java services, and services written in other supported programming languages.

For a flow service, the input side describes the initial contents of the pipeline. In other words, it specifies the variables that this flow service expects to find in the pipeline at run time. The output side identifies the variables produced by the flow service and returned to the pipeline. An `webMethods Integration Server` document type can also be used to define the input or output parameters for a service.

Click **Test** to run the service after providing the data to pass into the service.

Service Editor

Use the service editor to view the services. The source code, properties, inputs, and outputs are read only. The editor has the following tabs:

- **Source** tab contains the code or flow for the service.
- **Input/Output** tab contains the input and output signature of the service.
- **Logged Fields** tab indicates the input and output parameters for which the data is logged. You define the data to pass into the service by defining the input parameters on the lower panel of the editor.

Load pipeline for testing services

The pipeline is the general term used to refer to the data structure in which input and output values are maintained for a service in Software AG Designer. The pipeline holds the input and output for a service. The pipeline starts with the input to the service and collects inputs and outputs from subsequent services. When a service runs, it has access to all data in the pipeline at that point.

When you run a service in Software AG Designer, you can click **Save** and save the pipeline data as an XML document to your local file system. After you deploy the

service, you can click the **Load Data** option in the service editor to select the XML file, and load or update the pipeline data to test the service.

Note: Integration Cloud Integrations can now invoke Cloud Deployment webMethods Integration Server services for the same tenant. A new pre-defined Application, *Cloud Deployment*, is added in Integration Cloud. Using this Application, you can select the solution webMethods Integration Server services that you want to call from Integration Cloud.

Note: See the *webMethods Service Development Help*, *webMethods Integration Server Administrator's Guide*, and the *webMethods Adapter for JDBC Installation and User's Guide* for detailed descriptions of all the services and document types including Adapter services.

Displaying the API details of an executable service

After deploying assets, on the Asset explorer page, click the *API Details* option to view the API details of the service such as the HTTP Method, URL, Input structure, and the parameters that are required to invoke this service from an external system, for example, a REST client. You can copy the required API details to execute the service from the external system.

Note: The *API Details* option appears only for executable services. Some examples of executable services are Adapter services, Flow services, Java services, Flat File Schema, and Map services.

Note: You will be able to execute a Flat File Schema by using *only* the SoapUI tool. You must specify the following settings in the SoapUI tool:

- Set the following query parameters in the **Request** section:

skipWhiteSpace = true

encoding = UTF8

file = file:file1

- In the **Attachments** section, browse for the source file and update the following column values:

Name = file1

ContentID = file

Support for GraphQL Assets

Overview

GraphQL is a query language designed to build client applications by providing a flexible syntax and system for describing their data requirements and interactions. Using GraphQL service, you query a specific data to the server and get the response in a predictable way.

Cloud Deployment allows you to deploy GraphQL assets, which are developed using Software AG Designer and on-premises webMethods Integration Server, to Cloud Deployment. You choose from predefined solution landscapes to deploy your on-premises assets from Software AG Designer.

Let us see an example of how we deploy GraphQL assets which are developed using Software AG Designer and on-premises webMethods Integration Server to Cloud Deployment.

Preconditions

Create a GraphQL Schema

Create a GraphQL schema using SDL (Schema Definition Language). A sample schema is shown below:

```
type Query {
  dog: Dog
  findDog(complex: ComplexInput): Dog
  booleanList(booleanListArg: [Boolean!]): Boolean
  arguments: Arguments
  human: Human
  pet: Pet
  name: String!
  Name: String!
  catOrDog: CatOrDog
}
enum DogCommand { SIT, DOWN, HEEL }
type Dog implements Pet {
  name: String!
  nickname: String
  barkVolume: Int
  doesKnowCommand(dogCommand: DogCommand!): Boolean!
  isHousetrained(atOtherHomes: Boolean): Boolean!
  owner: Human
}
interface Sentient {
  name: String!
}
```

Implementing GraphQL Descriptor in Integration Server and Designer

You use the Service Development perspective to create a new GraphQL descriptor based on the schema.

- In the Designer perspective, select **File > New > GraphQL Descriptor**.
- In the New GraphQL Descriptor dialog box, select the folder in which you want to create the *GraphQL descriptor*.
- In the **Element name** field, type a name for the *GraphQL descriptor* using any combination of letters, numbers, and/or the underscore character.
- Click **Next**.
- In the Select the GraphQL Schema Location wizard, browse and select the schema file.

Note: Ensure that the format of the schema file is .txt, .json, .graphql, or .graphqls.


- Click **Finish**.
- Designer creates the *GraphQL descriptor* and displays the details in the *GraphQL descriptor* editor.

Build Resolver Services for the GraphQL Descriptor

Integration Server creates the following assets when you import a GraphQL schema:


- A GraphQL descriptor with the name as provided by the user.

When you create a GraphQL descriptor using the above GraphQL schema with name *Gq*, then Designer creates folders with name *types* and *resolvers* under *Gq* folder like this:



All the document types are created under the *types* folder and all the resolver services are created under the *resolvers* folder.

If you import the above schema in Integration Server with name *Gq*, then Integration Server creates the resolver services for Query operation under *Gq/resolvers/Query* folder, and the resolver services for Mutation operation under *Gq/resolvers/Mutation* folder.



The resolver will have the input/output signature set.

Deploy Assets to Cloud Deployment

Using Designer, you deploy your on-premises Integration Server GraphQL packages and assets to Cloud Deployment. Before deploying the packages and assets, you must configure a connection to Integration Cloud.

Before you configure a connection to Integration Cloud, ensure that the following criteria are met:

- A valid URL exists to connect to Integration Cloud.
- A valid user account is created on Integration Cloud.

To add a connection configuration for Integration Cloud

- In Designer, select **Window > Preferences**.
- In the preferences navigation tree, select **Software AG > Integration Cloud**.
- Click **Add**.
- In the **Add connection configuration** dialog box, enter the following information:

Field	Description
Name	The name to use for the Cloud Deployment connection configuration.

Note: The name cannot contain control characters, special characters, and characters outside of the basic ASCII character set, such as multi-byte characters.

Field	Description
URL	URL of the Cloud Deployment host to which Designer is to connect. For example, <code>https://<sub-domain>.<domain-name>.<domain-suffix></code> .
User	The user name for an account on Cloud Deployment.
Password	The password for the specified User .
Save password (in the Eclipse secure storage)	Indicates whether the password for the specified user account should be saved in Eclipse secure storage. Cloud Deployment uses this password from the Eclipse secure storage whenever user authorization is required. If you want to save the password in Eclipse secure storage, select this check box.

A connection configuration is now added to the Connections page with the specified details.

To deploy assets to Cloud Deployment

1. In Package Navigator view, select the Integration Server package that you want to deploy to Cloud Deployment.
2. Right-click the GraphQL package and click **Deploy to Cloud**.


Verify the Deployed Assets in Cloud Deployment

After publishing the GraphQL packages to an asset repository provisioned for the tenant on Cloud Deployment, you can view and access the webMethods Integration Server packages in Cloud Deployment. The solution details page allows you to view the packages, assets, and services for GraphQL runtimes in the solution.

To view the GraphQL packages in the Solution Explorer:


1. Switch to the Cloud Deployment perspective.
2. From the Cloud Deployment navigation bar, click **Solutions > Solution List**.
3. Click on an existing solution. The Solution Explorer page appears.

The Solution List page appears listing GraphQL solutions.



Displaying the API details of an executable service


After deploying assets, on the Asset explorer page, click the  icon to view the API details of the service such as the HTTP Method and URL that are required to invoke this service from an external system. You copy the required API details to execute the service from the external client.



Service Execution from External Client

To execute the service from a third party tool, let us use Postman as the GraphQL client. So in this example, when we open the GraphQL client, and invoke the

URL as shown below, we get the output as per the fields passed in the query.



Asset Repository

The **Asset Repository** page (**Cloud Deployment > Solutions > Asset Repository**) displays the list of all solutions and the user-created assets. You can also view the asset type, version of the assets, and services. Before deploying packages and configurations from Software AG Designer, you must create a solution in Integration Cloud to which you want to deploy the configuration assets. Software AG Designer deploys the assets and configurations to the Asset Repository in Integration Cloud.

Asset Repository for all solutions

The following figure depicts the Asset Repository structure for all solutions.

Name	Type	Version
bankSol	Solution	
bankIS1	Integration Server	
bankum	Universal Messaging	
paySol	Solution	
payis1	Integration Server	
payis2	Integration Server	
payum	Universal Messaging	

Asset Repository for a selected solution

The **Asset Repository** page for a solution (**Cloud Deployment > Solutions > Select a Solution > Asset Repository**) displays the assets for the selected solution, including the asset type and version of the assets.

The following figure depicts the Asset Repository structure for a selected solution.

Solutions > bankSol		Type	Version
bankS1		Integration Server	
bankum		Universal Messaging	

Downloading packages and assets

You can download user deployed packages and configurations from the **Asset Repository** page. You can either download individual packages or the whole repository for each product. To download assets, point to an asset or product and click the  icon. The assets including ACDL files will be zipped and downloaded to your local storage.

Deploy

After publishing the assets and configurations that reside within on-premises runtimes or repositories to webMethods Integration Cloud, you can promote them from the previous stage to the current stage. Within a tenant, you can promote assets from a solution to another solution, from a previous stage to the current stage, for the same runtime type. You can promote assets if the source runtime version is lesser than or same as the target runtime version.


If you are in the **Development** stage, click the **Change Stage To View** link to change the stage. Only active and accessible stages appear in the drop-down list for selection in the **Stage to view** field. Select a different stage other than Development and click **Submit**.

In the next stage, select a solution and then click **Deploy**. Select a runtime instance. All *solutions* of the previous stage will be listed on the left panel. The right panel will list all the assets of the selected solution in the current stage for the selected runtime instance.

Note: You will *not* be able to promote assets from a higher version solution to a lower version solution. For example, if you have a v10.4 solution in the source stage and a v10.3 solution in the current stage, you will not be able to promote the v10.4 assets to the current stage.

Note: You can access a stage only if your Access Profile is assigned to the stage.

Click on a solution and select the runtime package folder. Then click on the runtime instance. The assets of the solution corresponding to the selected runtime instance will appear. Select the assets and then click **Promote** to promote the assets to the current stage (right panel).



After you click **Promote**, the **Promote Assets** dialog box appears for the selected asset.

Select an asset and change the values for the variable substitution properties, if needed. The variable substitution properties appear for the selected asset, only if the asset has properties. If there are any similar type of assets for which you want the same values, then select the **Show similar assets to apply values** option. Then select the assets in the lower panel. Click **Apply** to apply the property values to the selected assets. The changed values will be applied to all the selected similar assets during promotion.

On the **Promote** dialog box, you can type a message to describe the promotion. The promotion message will appear on the **History** page.

Click **Simulate Promote** to check the consistency of the assets and their dependencies. If there are dependencies, then for a successful promotion, you have to select all the dependent assets. Select **Save and Promote** to save the variable substitution and promote the assets to the next stage.


On the **Deploy** page, click **Rollback** to rollback *all* promoted assets to their previous state.

You can type a message to describe the rollback. The rollback message will appear on the **History** page.

Deleting assets

On the **Deploy** page, you can delete an asset from the current stage (right panel). The asset will be deleted from the asset repository in that stage as well as from the runtime.

Note: Currently you can delete only webMethods Integration Server packages and not webMethods Integration Server and Universal Messaging configurations.



History

The **History** page shows the **Trace ID**, that is, the tracking ID, which is automatically generated on every successful or unsuccessful promotion, rollback, or deletion, the **Deployment, Rollback, or Deletion Action, Date** when the asset was promoted, rolled back, or deleted, the **User** who promoted, rolled back, or deleted the asset, and the

commit **Message** for the selected instance. You can click on a **Trace ID** to see the Track History for the specific action.


The **Track History** window displays the following details:

- **Timestamp** - The date and time when the log was generated.
- **Product** - The product that was promoted or rolled back.
- **Log Level** - Information on whether the log type is an Error, Info, or Debug.
- **Message** - Log or status message.

Note: Promotion, rollback, or deletion details appear only for the current stage.

Capability

The **Capability** ([?](#) > Licensing) page allows you to view the status of some of the system capabilities, based on your license offering.



You can view the details of the following capabilities in **Integration Cloud**:

Field	Description
Allowed application count	Total number of Applications that can be utilized by the tenant.
On-premises connection	If Yes , then on-premises applications can be uploaded from on-premises systems.
Max allowed users	Maximum number of active users allowed for the tenant.
Allowed number of stages	Maximum number of staging environments allowed for the tenant.

Field	Description
Integration restart and resume	Integrations can be restarted and resumed.
Integration import and export	Integrations can be imported and exported.
Trial account	If Yes , then the account is a trial account.
Trial end date	The trial period end date. This field appears only if the account is a trial account.

You can view the details of the following capabilities in **Cloud Deployment**:

Field	Description
Max allowed cores	Maximum number of CPU cores allowed across all active solutions and all stages for the tenant. You will not be able to create additional solutions if you exceed this capability.
Max allowed memory	Maximum memory capacity allowed across all active solutions and all stages for the tenant. You will not be able to create additional solutions if you exceed this capability.
Allowed number of stages	Maximum number of staging environments allowed for the tenant.
Trial account	If Yes , then the account is a trial account.
Trial end date	The trial period end date. This field appears only if the account is a trial account.

Usage

The **Usage** page allows you to view the current usage of CPU cores and Memory (GB) for all the active solutions in all the stages.

To access this page, from the Cloud Deployment navigation bar, click  and select *Licensing > Usage*.


Copying Solutions

The **Solution List** page allows you to copy solutions in any stage. Copying solutions allows you to have a back up of your solution before you make any changes and deploy your solution to production. This reduces the risk of not having a back up in case you want to revert to the original solution.

Note: If you have the required permission under **Settings**  > **Access Profiles** > **Administrative Permissions** > **Functional Controls** > **Solution**, you can copy, update, and delete solutions.

To copy a solution


1. Switch to the **Cloud Deployment** perspective.



2. After you launch Cloud Deployment, from the **Cloud Deployment** navigation bar, click **Solutions** > **Solution List**.


The **Solution List** page appears.

3. On a solution, click  > **Create a copy**.



4. On the **Create a copy** page, fill in the new solution **Name**.

You can choose to copy solutions using the same configuration and services in the solution landscape by clicking the **Create with original configuration** option or modify the configuration and services in the solution landscape by clicking the **Create with modified configuration** option.



5. Select **Create with modified configuration** and specify additional configuration of the solution, if necessary. Then click **Configure** to save the configuration details.

The new solution is created and appears on the **Solution List** page.

Note: You can now deploy the new solution to the next stage.

Deactivate, Activate, and Delete a solution

Click the  icon and select **Deactivate** to deactivate a solution. All packages and assets will be permanently deleted and cannot be recovered. Select **Activate** to activate an inactive solution. Select **Delete** to permanently delete a solution.

Managing Solutions

The **Manage** options allow you to view the solution landscape, configure webMethods Integration Server service access settings, administer the webMethods Integration Server, or restart the webMethods Integration Server instances.

Landscape


The **Landscape** page displays the landscape configuration for the selected solution.

Note: You cannot modify the solution landscape configuration in the Development stage after the solution is created. You can *configure* the solution in subsequent stages but after a solution is configured, the solution cannot be modified again in that stage. Further, clustering and Terracotta options are not available in the Development stage.

Note: In a stage, you can configure only those solutions that are marked as **Not Configured**.

To view the landscape configuration for a solution

1. Switch to the **Cloud Deployment** perspective.



2. From the **Cloud Deployment** navigation bar, click **Solutions > Solution List > Select a solution > Manage > Landscape**.
3. On the **Landscape** page, you can view the landscape configuration design, landscape solution name and description, and the landscape components. For each landscape component, you can view the landscape component name, product type, whether the landscape component is in a ready state, and the number of CPU cores and memory characteristics of the hardware to support each service in the solution.
4. Terracotta is available only when webMethods Integration Server runs in a clustered mode. Further, clustering and Terracotta options are not available in the **Development** stage.


On the **Landscape** page, select the **Cluster Type** as **Stateless** if the group of webMethods Integration Servers function in a manner similar to a cluster but are not part of a configured cluster. A stateless cluster of webMethods Integration Servers does not use a Terracotta Server Array. Select **Stateful** to add the Terracotta section. The Terracotta icons will be activated.

Service Access Settings

The **Service Access Settings** page allows you to configure the webMethods Integration Server services to be called externally over HTTPS. The services will be available to consumers based on the **Allow All** and **Deny All** access modes.

To configure service access settings

1. Switch to the **Cloud Deployment** perspective.



2. From the **Cloud Deployment** navigation bar, click **Solutions > Solution List > Select a solution > Manage > Service Access Settings**.
3. On the **Service Access Settings** page, configure the webMethods Integration Server services to be called externally over HTTPS. Required fields are marked with an asterisk on the screen.

Field	Description
Base URL	The base URL is a part of the complete service URL, for example, <code>https://wmic1.saglive.com/integration/clouddeployment/service/development/test/tt54/invoke/pub.*</code>
Solution Alias	An alias for the solution in the base URL. The alias name for a solution is unique in that particular stage. For example, if the completed service URL is <code>https://wmic1.saglive.com/integration/clouddeployment/service/development/test/tt54/invoke/pub.*</code> , then the Solution Alias is <code>test</code> , the webMethods Integration Server instance is <code>tt54</code> , and the service URL is <code>/invoke/pub.*</code> .
Select Integration Server	Select the solution webMethods Integration Server instance where the services need to be configured.
Access Mode	Ensure that the access mode of the services are properly set. Select Deny All if you want to deny most of the services to be invoked and allow a few. Then click ADD to add services to the Allowed Services table. In the Add Service window, the Base URL is a part of the complete service

Field	Description
	<p>URL. In the Service URL field, type the webMethods Integration Server Service URL. The Base URL and the Service URL together forms the complete service URL.</p> <p>Select Allow All if you want to allow most of the services to be invoked and deny a few. Click ADD to add services to the Denied Services table. In the Add Service window, the Base URL is a part of the complete service URL. In the Service URL field, type the webMethods Integration Server Service URL. The Base URL and the Service URL together forms the complete service URL.</p> <p>Note:You can update the service URL by clicking the Edit icon beside the service URL in the services table.</p> <p>The services will be available to be invoked from a software application, for example, a REST client, after you add the services to the table.</p> <p>For example, the Service URL <i>/invoke/pub.math:addInts</i> has the following components:</p> <ul style="list-style-type: none"> ■ Directive - <i>Invoke</i> ■ Namespace of the service - <i>pub.math:addInts</i> <p>Note:You can match all services to be allowed or denied by typing <i>*</i> at the end of the Service URL. For example, if you have two services, service url1: <i>/invoke/pub.date:formatDate</i> and service url2: <i>/invoke/pub.date:getCurrentDate /invoke/</i>, then instead of typing two entries, you can provide only one entry, service url: <i>/invoke/pub.date.*</i>. All services matching <i>pub.date</i> will be allowed or denied.</p>

Administration

Use this page to manage a solution webMethods Integration Server Administrator instance.


Restart

Restart the server when you need to stop and reload the server. You should restart the server when:

- You make certain configuration changes. Some configuration changes require the server to be restarted before they take effect.
- If you encounter an operational problem or the server is in an inconsistent state.

To restart the server

1. Switch to the **Cloud Deployment** perspective.



2. From the **Cloud Deployment** navigation bar, click **Solutions > Solution List > Select a solution > Manage > Restart**.

Note: webMethods Integration Servers running in a clustered mode cannot be restarted. Further, restarting servers will terminate all active sessions.

3. Click **Restart**.

Monitoring Solutions

The Monitoring part of **Cloud Deployment** enables you to monitor the health and availability of the solutions and run-time instances, alerts and alert statuses. You receive an email whenever there is a condition that might affect the solution.

The monitoring of a new solution starts automatically 10 minutes after the creation of the solution. The data of the solution is collected and analyzed every 60 seconds.

You can access the following monitoring pages from the left-side navigation menu of the Monitoring main page:

- [“Dashboard” on page 105](#)
- [“Solutions” on page 106](#)
- [“Runtimes” on page 107](#)
- [“Services ” on page 111](#)

- [“Uptime” on page 112](#)
- [“Alerts” on page 112](#)
- [“Logs” on page 116](#)

You can filter the information on most Monitoring pages based on time. To specify the time-range, select a value in the time-range selector.

The following table describes the options in the time-range selector.

Option	Description
12h	Displays the information for the last 12 hours.
24h	Default. Displays the information for the last 24 hours.
2d	Displays the information for the last 2 days.
1w	Displays the information for the last week.
2w	Displays the information for the last 2 weeks.
3w	Displays the information for the last 3 weeks.
4w	Displays the information for the last 4 weeks.

To navigate to the Monitoring main page, log in to Integration Cloud, switch to the **Cloud Deployment** perspective, and select **Monitoring** in the Cloud Deployment navigation bar.

Dashboard

On the Dashboard page, you can view:

- The health of the solutions
- The number of the alerts that have been raised for all the solutions
- The landscape view of the solutions, and the number of alerts for all run-times that are part of the solutions

The following table provides more information about the panes on the Dashboard page.

Pane	Description
Overall KPI Status	Shows the following information about the health of the solutions for the selected time range:

Pane	Description
	<ul style="list-style-type: none"> ■ Total number of solutions ■ The number of healthy solutions ■ The number of unhealthy solutions ■ The health of the solutions, as a percentage value calculated by the formula (Number of healthy solutions / total number of solutions) * 100 <p>A healthy solution is a solution without any open critical alerts.</p> <p>An unhealthy solution is a solution which has at least one open critical alert.</p> <p>To see more information about the KPI status of the solutions, click More Details.</p>
Alerts	<p>Shows the total number of open and resolved alerts that have been raised for all solutions for the selected time-range, and the number of alerts from each type: critical, warning, or information.</p> <p>To see more details about the alerts, click More Details.</p> <p>For more information about the alert types, see “Alert Types” on page 114.</p>
Landscapes	<p>Displays the topology of the solutions and the number of alerts for each run-time type since the solution has been activated.</p>

By default, the page displays information for the last 24 hours. To view the information for a different time period, use the time-range selector. For more information about the time-range selector, see [“Monitoring Solutions” on page 104](#).

Solutions

On the Solutions page, you can check the health of the run-time instances from all the solutions. For each run-time instance, you can view the current data, and the data for the last 24 hours.

The health metrics are grouped into three categories:

- Memory - indicate the memory utilization of a run-time.
- Uptime - indicate the availability of a run-time.
- Failures- indicate failures of the run-time


The following table describes the icons on the Solutions page.

Icon	Description
	Normal health of the run-time instance.
	The health of the run-time instance is deteriorating. Take preventive measures.
	There are critical issues with the health of the run-time instance. Your urgent attention is needed.
	The run-time instance is not available.
Note:	If the solution uses an Integration Server cluster, the number of Integration Server instances is indicated in brackets after the Integration Server instance name.

To view more details about a run-time instance on the Runtime page, click the name of the run-time instance.

Runtimes

On the Runtimes page, you can view the graphs for monitored KPIs for the selected run-time instances from all the solutions.



The example image shows the graph for the Used Memory KPI. The horizontal lines below the graph represent the severity and duration of the alerts that were raised for the KPI. The information alerts are displayed in blue, the warning alerts are in orange, and the critical alerts are in red.

The following table describes the meaning of the alert lines from the example graph for the Used Memory KPI.

Time Period	Details
1	Until 2:05 h, there had been an open information alert.
2	At 2:05 h, the severity of the information alert was changed to warning.
3	An information alert existed during that period.
4	A warning alert existed during that period.

You can change the value in the **Solutions** drop-down field to load the information about the run-time instances from a specific solution.

You can use the **INTEGRATION SERVER**, **UNIVERSAL MESSAGING**, and **TERRACOTTA** tabs to view the information related to the selected solution and runtime.

By default, the page displays information for the last 24 hours. To view the information for a different time period, use the time-range selector. For more information about the time-range selector, see [“Monitoring Solutions” on page 104](#).

The following table describes the monitored Integration Server KPIs.

Name	Description
Used Memory	The total used memory for the Java VM.
Service Threads	The number of active service threads.
Sessions	The number of active licensed sessions.
Stateful Sessions	The number of the current stateful HTTP sessions.

The following table describes the monitored Universal Messaging KPIs.

Name	Description
Free Memory	The amount of free memory that the Realm Server has within the Java VM. This indicates the difference between what the Java VM has currently allocated and what the Realm Server has used.
Published Events	Total number of events published on this realm from the time it started.
Subscribed Events	Total number of events that this realm has sent to clients from the time it started.

The following table describes the monitored Terracotta KPIs.

Name	Description
Off-Heap Used Memory	Shows the amount of off-heap memory that is currently used.
Live Objects	Shows the total number of live objects in the cluster, mirror group, server, or clients. If the trend for the total number of live objects goes up continuously, clients in the cluster will eventually run out of memory and applications might fail. Upward trends indicate a problem with application logic, garbage collection, or the tuning of one or more clients.

Viewing Adapter KPIs

On the Runtimes page, you can view the KPIs for the adapters that are installed on the Integration Server instances.

1. Navigate to the Runtimes page.
2. Select a solution.
3. On the **INTEGRATION SERVER** tab, select an Integration Server instance.
4. Click **Connectivity KPIs**.
5. On the **ADAPTERS** tab, select an Adapter.

The Adapter KPIs are displayed.

The following table describes the monitored Adapter KPIs.

Name	Description
Connections	The number of connection pools in the adapter and how many of them are currently enabled.
Notifications	The number of adapter notifications (polling notifications) and how many of them are currently enabled.

Note: You can view Adapter KPIs only for the current time.

Viewing Connector KPIs

On the Runtimes page, you can view the KPIs for the connectors that are installed on the Integration Server instances.

1. Navigate to the Runtimes page.
2. Select a solution.
3. On the **INTEGRATION SERVER** tab, select an Integration Server instance.
4. Click **Connectivity KPIs**.
5. Click the **CONNECTORS** tab.
6. Select a provider.
7. Select a connector.

The Connector KPIs are displayed.

The following table describes the monitored Connector KPIs.

Name	Description
Connections	The number of connection pools in the connector and how many of them are currently enabled.
Listeners	The number of connector listeners and how many of them are currently enabled.

Note: You can view Connector KPIs only for the current time.

Services

On the Services page, you can view the number of successful and failed service executions of the Integration Server instances from the solutions.

The Services page consists of two the Service Executions pane and the History pane.

Pane	Description
Service Executions	<p>Shows the following information about the service executions of the Integration Server instances for the selected time range:</p> <ul style="list-style-type: none"> ■ Total number of service executions ■ The number of successful service executions ■ The number of failed service executions ■ The successful service execution, as a percentage value calculated by the formula (Number of successful service executions / total number of service executions) * 100
History	<p>Shows a chart with the history of successful (green) and failed (red) service executions.</p> <p>Hovering over the green and red bars displays the total number of successful and failed service executions, correspondingly.</p>

The numbers of service executions on the Services page includes the public and internal services of the Integration Server instance and their child services.

You can change the value in the **Solutions** drop-down field to view the information about a specific solution, or the information for all solutions.

By default, the page displays information for the last 24 hours. To view the information for a different time period, use the time-range selector. For more information about the time-range selector, see [“Monitoring Solutions” on page 104](#).

Uptime

On the Uptime page, you can view time lines that represent the availability of all run-time instances of the solutions.

The color of the time lines changes based on the status of the run-time instances.

The following table describes the meaning of the different colors.

Time line color	Indicates that
green	the run-time instance was available during the indicated time period.
red	the run-time instance was unavailable during the indicated time period.
grey	the run-time instance did not exist during the indicated time period.
blue	at least one node from the cluster is unavailable.
Note:	If the solution uses an Integration Server cluster, the number of Integration Server instances is indicated in brackets after the Integration Server instance name.

By default, the time line displays the availability of the instances during the last 24 hours. To view the information for a different time period, use the time-range selector. For more information about the time-range selector, see [“Monitoring Solutions” on page 104](#).

Alerts

The alert is a notification that a rule is violated.

On the Alerts page you can:

- View the number of critical, warning, and information alerts for all the solutions for the selected time range
- Filter the alerts by solution, runtime, severity, and status
- Configure the rules by adjusting the alert threshold values

- Configure the summary of the alerts
- Configure the recipient email for the alerts. For more information about configuring the alerts, see [“Configuring the Alerts” on page 114](#).

By default, the Alerts page displays the number of alerts (critical, warning, and information) for all the solutions, and detailed information about the alerts in a tabular format.

Note: If the duration of the rule violation is less than the time interval at which the rule is evaluated, the alert does not appear on the Alerts page. For more information about the interval, see [“Configuring the Alerts” on page 114](#).

If you deactivate a solution, the Alerts page will not display the alerts for the solution.

If you activate a solution, the Alerts page will display both the historical alerts for the solutions that had been raised before the deactivation of the solution, and the alerts that were raised after the activation of the solution.

The following table describes the information that is displayed in the table on the Alerts page.

Column	Description
Solution	Name of the solution.
Runtime	Run-time type. <ul style="list-style-type: none"> ■ Integration Server ■ Universal Messaging ■ Terracotta
Instance	Name of the run-time instance.
Start Date	Date and time when the alert was raised.
Resolved On	Date and time when the alert was resolved. The field is empty if the alert is still active.
Message	Description of the alert.
Status	Status of the alert. <ul style="list-style-type: none"> ■  The alert is inactive. ■  The alert is active.

Note: The Alerts page might not display the alerts for all nodes from a cluster. For example, if you monitor an Integration Server cluster with two Integration Server instances, and both instances have alerts for the same property with different severity, the Alerts page will show the alert of lower severity only, as explained in the following table.

<u>Integration Server instance</u>	<u>Alert type</u>	<u>Visibility on the Alerts page</u>
Integration Server instance 1	Information. Free memory is low.	Yes
Integration Server instance 2	Warning. Free memory is low.	No

You can view all alerts for all the nodes from the cluster in the email alerts.

By default, the page displays information for the last 24 hours. To view the information for a different time period, use the time-range selector. For more information about the time-range selector, see [“Monitoring Solutions” on page 104](#).

Alert Types

The following table provides more information about the alert types.

Note: Warning alerts and information alerts are not available for KPIs that monitor the availability of a run-time instance.

Alert Severity	Description	Color Coding
Critical	A condition exists that is critical for the system performance.	red
Warning	A condition exists that might deteriorate the system performance.	orange
Information	A condition exists that might evolve into a warning or critical alert.	blue

Configuring the Alerts

You can change the default threshold values and the recipient email for the system alerts. Threshold values determine when a rule is violated and when the system raises an alert.

To configure the system alerts

1. Navigate to the Alerts page.
2. Select the **CONFIGURATION** tab.

The Configuration page shows information about the alerts for all solutions. The following table describes the columns in the form.

Column	Description
Name	Alert Name.
Runtime	Integration Server, Universal Messaging, or Terracotta.
Action	The icon activates the configuration view for the alert.

3. Click the **Edit this rule** icon in the Action column for the alert that you want to configure.

A form with the configuration details for the alert rule is displayed. The following table describes the fields in the form.

Field	Description
Threshold	<p>The KPI's boundary values. When the value of the KPI is outside the range that is specified by these boundary values, the alert is raised.</p> <p>You can configure the threshold values of critical alerts by adjusting the ends of the red line.</p> <p>You can configure the threshold values of warning alerts by adjusting the ends of the orange line.</p> <p>You can configure the threshold values of information alerts by adjusting the ends of the blue line.</p> <p>Note: The Threshold field is read-only for KPIs that monitor the availability of a runtime instance.</p>
Runtime	Integration Server, Universal Messaging, or Terracotta.
Summary	Summary of the alert.
Interval	The scrape interval. The scrape interval is the frequency at which the system collects the data. The scrape interval is 60 seconds for all rules. Read-only.

Field	Description
	<p>Note: The alert does not appear immediately when the corresponding rule violation occurs.</p> <p>The time delay from the actual time of the rule violation to the system alert is the following:</p> <ul style="list-style-type: none"> ■ up to 70 seconds for run-time availability rules of critical severity ■ up to 420 seconds for run-time availability rules of information severity ■ up to 180 seconds for the rest of the rules <p>The system will not send an alert if the rule violation condition is resolved during the corresponding delay period.</p>
Email on alert	<p>Email of the user who will receive the alerts.</p> <p>Note: The email is used for all rules. In case there are alerts, the system sends emails once every 10 minutes.</p> <p>To configure more than one email, use comma-separated values.</p>

4. In the **Threshold** field, change the default threshold value(s) for the alert.
5. In the **Email on Alert** field, type the email(s) of the user(s) who will receive the email alerts for all rules.

Note: webMethods Integration Cloud stores the email(s) in the local alertManager.yaml file. When you uninstall webMethods Integration Cloud or delete a tenant, the related information is deleted automatically.

6. Click **Apply**.

Logs

On the Logs page, you can view the logs of the run-time instances in the solutions for a selected time period.

To view the logs for all the instances from a specific solution, select the solution in the solutions drop-down list.

To view the logs for a specific run-time instance in a solution, select the run-time instance in the run-time instance drop-down list.

By default, the page displays the logs for the last 24 hours. To view the logs for a different time period, use the time-range selector. For more information about the time-range selector, see [“Monitoring Solutions” on page 104](#).

You can view logs message statistics and logs details, such as log timestamp and message text. You can change the type of log details that you see by adding or editing filters as described in the Kibana documentation.

Database

For optimal performance, you can add a MySQL database to your cloud deployment subscription. This enables you to configure, store, and monitor your database directly in the cloud instead of using external systems. The database endpoint can be shared by multiple solutions deployed by the tenant.

Creating a Database

To create a database instance in the cloud

1. On the home page in Cloud Deployment, under **Database**, click **Learn more**, and then click **Start database setup**.
2. On the Database setup details screen, do the following:
 - a. In the **Database instance identifier** field, specify a name for the database.

Important: Each Software AG Cloud tenant can create only one database instance.

- b. In the **Create DB master username** and **DB master password** fields, specify the username and password that you will use to access the database.

Note: The master user has full privileges on the database. For more information on database privileges, see the MySQL documentation.

- c. Select **Encrypt database** if you want to enable the encryption of database data and click **Continue**. Note that you cannot change the encryption settings after the database is created.

When the database configuration is complete, you are redirected to the home page of Cloud Deployment where the **Database** element shows that the database server is running.

Connecting a Solution to the Database

After you create the database instance in the cloud, you can connect one or more solutions to it.

To connect a solution to the database instance in the cloud

1. Enable the `wMJDBCAdapter` package for the solution. For more information, see the Solutions chapter in *Cloud Deployment*.
2. In Software AG Designer, deploy to the cloud the on-premises `webMethods Integration Server` packages that you want to include in the solution.
 - a. In the Package Navigator view, right-click any of the packages that you want to include and select **Deploy to Cloud**.
 - b. In the Publish Assets to Integration Cloud dialog box, select all packages that you want to include in the solution and click **Next**.
 - c. In the Integration Server Packages Variable Substitution dialog box, do the following for each of the packages that have JDBC connections:
 - Enable the **State after Deployment** property.
 - In the **user**, **password**, and **serverName** fields, specify the username, password, and host name of the database instance in the cloud.

Note: You can see the host name of the database in the **DB instance endpoint** field on the Database page in Cloud Deployment.

- d. In the Select the Integration Cloud Solution dialog box, select the solution that you want to connect to the database and click **Finish**.

Securing the Connection Between a Solution and the Database

To secure the connection between a solution and the database

1. Import the Amazon RDS Root CA certificate as a trusted certificate in a Java keystore. For more details on the certificate, see the Amazon Relational Database Service documentation.
2. Copy the truststore to the config directory of any of the packages you deploy to the solution.
3. In the web administration interface of the on-premise `webMethods Integration Server`, go to **Adapters > WebMethods Adapter for JDBC > Connections**. In the Other Properties field of the JDBC adapter connection, specify:

```
sslMode=VERIFY_IDENTITY;
trustCertificateKeyStoreUrl=file:packages/<package>/config/<truststore>;
trustCertificateKeyStorePassword=<password>
```

where *package* is the name of the package that contains the truststore, *truststore* is the name of the keystore that contains the trusted certificate, and *password* is the password to the truststore.

4. In Software AG Designer, deploy the updated packages to the cloud.

Note: Amazon Relational Database Service currently does not support authentication that uses a client certificate.

Monitoring the Database

After you create the database instance in the cloud, you can monitor its status on the Database page in Cloud Deployment.

On the **Database** dashboard of the Database page, you can view the following elements:

Element	Description
DB CPU usage	CPU usage in percentage.
DB storage size	The allocated storage space and the storage space used by the database.
DB server status	Shows if the database server is running. You can start or stop the server at any time by clicking Start server or Stop server .

In the **Configuration details** section of the Database page, you can view the following fields:

Field	Description
DB instance	The size of the database, based on your license offering.
DB instance identifier	The name of the database.
DB instance endpoint	The host and port that you can use to access the database.
Allowed IPs	<p>The list of external IPs that can access the database.</p> <p>Software AG recommends using the database only from applications in Software AG Cloud. By default, you can access the database only in the cloud. For administrative purposes you can enable access to the database from external IPs.</p> <p>To add external IPs, click Edit and type each IP on a new row. The supported IP format is Classless Inter-Domain Routing (CIDR) block</p>

Field	Description
	format, xxx.xxx.xxx.xxx/yy. If you specify only xxx.xxx.xxx.xxx, mask /32 is automatically added.

Cloud Deployment CLI

The Cloud Deployment CLI interacts with webMethods Cloud Deployment and performs tasks such as managing a solution, monitoring the status of all runtimes in a solution, promoting assets from one stage to another, and so on. The CLI supports the following modes:

- **Interactive Mode:** To start the CLI in interactive mode, run the following command:

```
wmcd-cli --mode interactive
```

```
C:\cli>wmcd-cli --profile default --mode interactive

Reading Credentials from C:\Users\arub\AppData\Roaming\wmcd_cli\config.json
Connecting to https://setup.saglive.com
Signing in as setup
No Commands specified

webMethodsCloud
CLI v1.0.0

Copyright © 2014-2019 Software AG, Darmstadt, Germany and/or Software AG USA Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.
Connected to webMethods Cloud Deployment...
wmcd_cli>$ Commands ...
```

- **Normal Mode:** To start the CLI in normal mode, run the following command:

```
wmcd-cli <commands> [options]
```

Install Cloud Deployment CLI

Overview

You install the Cloud Deployment CLI (wmcd-cli) using the NPM registry. This section describes tasks such as installing the Cloud Deployment CLI and specifying credentials to connect to Cloud Deployment.


Actors

Administrators

Before you begin

Before you install wmcd-cli from the NPM registry, do the following:

- Install the NodeJS runtime environment version 10.13 or later on your computer along with NPM (Node's package manager).



Downloads

Latest LTS Version: **10.15.3** (includes npm 6.4.1)

Download the Node.js source code or a pre-built installer for your platform, and start developing today.

LTS Recommended For Most Users	Current Latest Features	
 Windows Installer <small>node-v10.15.3-x86.msi</small>	 macOS Installer <small>node-v10.15.3.pkg</small>	 Source Code <small>node-v10.15.3.tar.gz</small>

Windows Installer (.msi)
 Windows Binary (.zip)
 macOS Installer (.pkg)
 macOS Binary (.tar.gz)
 Linux Binaries (x64)
 Linux Binaries (ARM)
 Source Code

32-bit	64-bit	
32-bit	64-bit	
64-bit		
64-bit		
64-bit		
ARMv6	ARMv7	ARMv8
node-v10.15.3.tar.gz		

Note: The Cloud Deployment CLI is available for the following operating system environments:

- Windows
- Linux
- macOS

- Open a command line interface and type the following command to install `wmcd-cli`:

```
npm install -g wmcd-cli
```

Specify the credentials to connect to Cloud Deployment

To connect to Cloud Deployment, you must configure the credentials in one of the following ways:

- Specify the credentials in `config.json` file.
 - Create a `config.json` file under `%appdata%/wmcd_cli/` location for Windows or `/home/wmcd_cli/` in Linux.
 - Add new profiles in the `config.json` file.

The following is an example of default and referenced profile in the configuration file.

```
{
  "default": {
    "url": "https://{subdomain}.webmethodscloud.com",
    "userName": "userName",
    "password": "password"
  },
  "someotherProfile": {
    "url": "https://{subdomain}.webmethodscloud.com",
    "userName": "userName",
    "password": "password"
  }
}
```

By default, the 'default' settings are read from the configuration file. To enable the referenced profile, run the following command:

```
wmcd-cli -profile someotherProfile
```

- Specify credentials as runtime arguments.
 - When you start the CLI, credentials are passed as a runtime argument. For example:

```
wmcd --mode interactive --url <url> --userName <userName>
--password <password>
```

Note: Runtime arguments will have the highest priority. However, If runtime arguments are not passed, then the default profile from %appdata%/wmcd_cli/config.json is used.

Cloud Deployment CLI Reference

The following table describes the commands you use to perform various scenarios in the CLI interface.

Commands for viewing alerts in Cloud Deployment

Run the following command to view alerts.

```
alert list [options]
```

where the options are:

--Name	Description
--solutionName <solutionName>	Filter the alerts that belong to a particular solution.
--stageName <stageName>	Filter the alerts that belong to a particular stage. Supported values are development, test, live, prelive.

--Name	Description
--alertName <alertName>	Filter the alerts by name .
--runtime <runtime>	Filter the alerts by Instances / Node name in a solution.
--severity <severity>	Filter the alerts based on the severity. Default supported values are info, warning, and critical.
--view <view>	<p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre>alert list --severity critical</pre>
--view <json>	<p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre>alert list --severity critical --view json</pre> <p>Note:JSON output format loads complete information that contains additional field than the table output format.</p>

Commands for listing the assets in LAR

Run the following command to list all the assets available in the LAR.

```
asset-repo list-assets <solutionName> <nodeName> <stageName> [options]
```

where the options are:

--Name	Description
--view <view>	<p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre>asset-repo list-assets DemoSoln IS development</pre>

Commands for creating solutions

Run the following command to create solutions.

```
solution create [options] <stagename>
```

where the options are:

--Name	Description
--inputFile <fileName>	<p>Provide the name of the file that contains the input data.</p> <pre>solution create --inputFile /home/etc/createSolution.json <stagename></pre>

The file must contain a valid solution name, the name of the webMethods Integration Server and Universal Messaging instances, number of CPU Cores, and Memory characteristics of the hardware to support each service in the solution.

Example 1 : Creating Type 1 solution without cluster.

```
{
  "integration": {
    "landscapeDefinition": {
      "solutionName": "Demo",
      "description": "Demo Solution",
      "solutionType": 1,
      "productDefinitions": {
        "IS": [{
          "name": "IS",
          "resources": {
            "limits": {
              "cpu": "1",
              "memory": "2"
            }
          }
        }],
        "version": "10.4",
        "env": {
          "packages": ["packages.WmCloudStreams.enabled=true",
            "packages.WmJDBCAdapter.enabled=true"]
        }
      }
    }
  }
}
```

Example 2: Creating Type 1 solution with stateful cluster.

```
{
  "integration": {
    "landscapeDefinition": {
      "solutionName": "Demo",
      "description": "Demo Solution",
      "solutionType": 1,
      "productDefinitions": {
        "IS": [{
          "name": "IS",
          "replicaCount": "2",

```

--Name	Description
	<pre> "resources": { "limits": { "cpu": "1", "memory": "2" } }, "dependencies": ["DB","tc"], "clusterType": "stateful", "isClustered": true, "statefulCluster": true, "version": "10.4", "env": { "packages": ["packages.WmCloudStreams.enabled=true", "packages.WmJDBCAdapter.enabled=true"] } }], "TERRACOTTA": [{ "name": "tc", "isClustered": true, "statefulCluster": false, "replicaCount": "2", "enabled": true, "resources": { "limits": { "cpu": "1", "memory": "4" } } }, "version": "10.4", "env": { "packages": [], "monitoringTools": [] } }]] } } } } </pre>

Example 3: Creating Type 1 solution with stateless cluster.

```

{
  "integration": {
    "landscapeDefinition": {
      "solutionName": "Demo",
      "description": "Demo Solution",
      "solutionType": 1,
      "productDefinitions": {
        "IS": [{
          "name": "IS",
          "replicaCount": "2",
          "dependencies": ["DB"],
          "resources": {
            "limits": {
              "cpu": "1",
              "memory": "2"
            }
          }
        }],
        "clusterType": "stateless",
        "isClustered": true,

```

--Name	Description
	<pre> "statefulCluster": false, "version": "10.4", "env": { "packages": ["packages.WmCloudStreams. enabled=true", "packages.WmJDBCAdapter.enabled=true"] } }]] } } } } } </pre>

Example 4: Creating Type 2 solution without cluster.

```

{
  "integration": {
    "landscapeDefinition": {
      "solutionName": "Solution2",
      "description": "sample solution",
      "solutionType": 2,
      "productDefinitions": {
        "IS": [{
          "name": "IS",
          "resources": {
            "limits": {
              "cpu": "1",
              "memory": "2"
            }
          },
          "version": "10.4",
          "env": {
            "packages": ["packages.WmCloudStreams
.enabled=true",
"packages.WmJDBCAdapter.enabled=true"]
          }
        }],
        "UNIVERSALMESSAGING": [{
          "name": "UM",
          "resources": {
            "limits": {
              "cpu": "1",
              "memory": "2"
            }
          },
          "version": "10.4"
        }
      ]
    }
  }
}
}

```

Example 5: Creating Type 2 solution with stateful cluster.

```

{
  "integration": {
    "landscapeDefinition": {
      "solutionName": "Solution2",
      "description": "sample solution",
      "solutionType": 2,

```

--Name	Description
	<pre> "productDefinitions": { "IS": [{ "name": "IS", "clusterType": "stateful", "replicaCount": "2", "isClustered": true, "statefulCluster": true, "dependencies": ["DB", "UM", "tc"], "resources": { "limits": { "cpu": "1", "memory": "2" } }, "version": "10.4", "env": { "packages": ["packages.WmCloudStreams. enabled=true", "packages.WmJDBCAdapter.enabled=true"] } }], "UNIVERSALMESSAGING": [{ "name": "UM", "clusterType": null, "isClustered": false, "resources": { "limits": { "cpu": "1", "memory": "2" } }, "version": "10.4" }], "TERRACOTTA": [{ "name": "tc", "isClustered": true, "resources": { "limits": { "cpu": "1", "memory": "4" } }, "version": "10.4", "env": { "packages": [], "monitoringTools": [] } }] } } } </pre>

Example 6: Creating Type 2 solution with stateless cluster.

```

{
  "integration": {
    "landscapeDefinition": {
      "solutionName": "Solution2",
      "description": "sample solution",
      "solutionType": 2,

```

--Name	Description
	<pre> "productDefinitions": { "IS": [{ "name": "IS", "replicaCount": "2", "clusterType": "stateless", "dependencies": ["DB","UM"], "isClustered": true, "statefulCluster": false, "resources": { "limits": { "cpu": "1", "memory": "2" } }, "version": "10.4", "env": { "packages": ["packages.WmCloudStreams. enabled=true", "packages.WmJDBCAdapter.enabled=true"] } }], "UNIVERSALMESSAGING": [{ "name": "UM", "clusterType": null, "isClustered": false, "resources": { "limits": { "cpu": "1", "memory": "2" } }, "version": "10.4" }] } } } </pre>

Example 7: Creating Type 3 solution without cluster.

```

{
  "integration": {
    "landscapeDefinition": {
      "solutionName": "Solution3",
      "description": "Sample Solution",
      "solutionType": 3,
      "productDefinitions": {
        "IS": [{
          "name": "IS1",
          "resources": {
            "limits": {
              "cpu": "1",
              "memory": "2"
            }
          }
        }],
        "version": "10.4",
        "env": {
          "packages": ["packages.WmCloudStreams.
enabled=true", "packages.WmJDBCAdapter.
enabled=true"]
        }
      }
    }
  }
}

```

--Name	Description
	<pre> }, { "name": "IS2", "resources": { "limits": { "cpu": "1", "memory": "2" } }, "version": "10.4", "env": { "packages": ["packages.WmCloudStreams.enabled=true", "packages.WmJDBCAdapter.enabled=true"] } }], "UNIVERSALMESSAGING": [{ "name": "UM", "resources": { "limits": { "cpu": "1", "memory": "2" } }, "version": "10.4" }] } } } </pre>

Example 8: Creating Type 3 solution with stateful cluster.

```

{
  "integration": {
    "landscapeDefinition": {
      "solutionName": "Solution3",
      "description": "Sample Solution",
      "solutionType": 3,
      "productDefinitions": {
        "IS": [{
          "name": "IS1",
          "isClustered": true,
          "replicaCount": "2",
          "statefulCluster": true,
          "dependencies": ["UM", "DB", "tc1"],
          "clusterType": "stateful",
          "resources": {
            "limits": {
              "cpu": "1",
              "memory": "2"
            }
          }
        },
        {
          "name": "IS2",
          "isClustered": true,
          "statefulCluster": true,

```

--Name	Description
	<pre> "replicaCount": "2", "dependencies": ["UM", "DB", "tc2"], "clusterType": "stateful", "resources": { "limits": { "cpu": "1", "memory": "2" } }, "version": "10.4", "env": { "packages": ["packages.WmCloudStreams. enabled=true", "packages.WmJDBCAdapter.enabled=true"] } }], "UNIVERSALMESSAGING": [{ "name": "UM", "isClustered": false, "statefulCluster": false, "clusterType": null, "resources": { "limits": { "cpu": "1", "memory": "2" } }, "version": "10.4" }], "TERRACOTTA": [{ "name": "tc1", "isClustered": true, "resources": { "limits": { "cpu": "1", "memory": "4" } }, "version": "10.4", "env": { "packages": [], "monitoringTools": [] } }, { "name": "tc2", "isClustered": true, "resources": { "limits": { "cpu": "1", "memory": "4" } }, "version": "10.4", "env": { "packages": [], "monitoringTools": [] } }] } } } </pre>

--Name	Description
--------	-------------

Example 9: Creating Type 3 solution with stateless cluster.

```
{
  "integration": {
    "landscapeDefinition": {
      "solutionName": "Solution3",
      "description": "Sample Solution",
      "solutionType": 3,
      "productDefinitions": {
        "IS": [{
          "name": "IS1",
          "isClustered": true,
          "replicaCount": "2",
          "statefulCluster": false,
          "dependencies": ["UM", "DB"],
          "clusterType": "stateless",
          "resources": {
            "limits": {
              "cpu": "1",
              "memory": "2"
            }
          }
        },
        {
          "name": "IS2",
          "isClustered": true,
          "replicaCount": "2",
          "statefulCluster": false,
          "dependencies": ["UM", "DB"],
          "clusterType": "stateless",
          "resources": {
            "limits": {
              "cpu": "1",
              "memory": "2"
            }
          }
        }
      ],
      "version": "10.4",
      "env": {
        "packages": ["packages.WmCloudStreams.enabled=true",
"packages.WmJDBCAdapter.enabled=true"]
      }
    },
    "UNIVERSALMESSAGING": [{
      "name": "UM",
      "isClustered": false,
      "statefulCluster": false,
      "clusterType": null,
      "resources": {
        "limits": {
          "cpu": "1",
          "memory": "2"
        }
      }
    }
  ],
  "version": "10.4"
}]
```

--Name	Description
	<pre data-bbox="649 304 1344 424"> } } } } </pre>

Commands for listing the solutions for a particular stage

Run the following command to list solutions for a particular stage.

```
solution list <stageName> [options]
```

where the valid stage name value includes development, test, prelive, and live.

Example:

```
solution list development --view json
```

Commands for getting the solution and runtimes for a particular stage

Run the following command to get the solution and all runtimes for a particular stage.

```
solution get <solutionName><stageName> [options]
```

where the options are:

--Name	Description
--view <viewType>	By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.
	Example: <pre data-bbox="649 1228 1344 1268">solution get DemoSoln development</pre>

Commands for deleting the solution for a particular stage

Run the following command to delete the solution for a particular stage.

```
solution delete <solutionName> <stageName> [options]
```

where the options are:

--Name	Description
--view <viewType>	By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.
	Example: <pre data-bbox="649 1768 1344 1808">solution delete DemoSoln development</pre>

Commands for activating or deactivating the solution for a particular stage

Run the following command to activate and deactivate a solution for a particular stage.

```
solution update-status <solutionName> <stageName> <actionName> [options]
```

where the options are:

--Name	Description
--view <viewType>	<p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre>solution update-stats DemoSoln development deactivate</pre> <ul style="list-style-type: none"> ■ Allowed stage names are development, test, live, prelive. ■ Allowed action names are activate or deactivate

Commands for getting the status of all pods in a solution

Run the following command to get the status of all pods in a solution.

```
solution get-status <solutionName> <stageName> [options]
```

where the options are:

--Name	Description
--view <viewType>	<p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre>solution get-status DemoSoln development</pre>

Commands for getting the license information for a particular tenant

Run the following command to get the license information for a particular tenant.

```
tenant get-license-info [options]
```

where the options are:

--Name	Description
--view <viewType>	By default, outputs the response in a table view mode. The CLI supports both table and JSON output format. Example: <pre>tenant get-license-info</pre>

Commands for getting the total CPU and memory utilization details for a particular tenant

Run the following command to get the total CPU and memory utilization details for a particular tenant.

```
tenant get-utilization-details [options]
```

where the options are:

--Name	Description
--view <viewType>	By default, outputs the response in a table view mode. The CLI supports both table and JSON output format. Example: <pre>tenant get-license-info</pre>

Commands for listing all the users

Run the following command to list all the users.

```
user list [options]
```

where the options are:

--Name	Description
--view <viewType>	By default, outputs the response in a table view mode. The CLI supports both table and JSON output format. Example: <pre>tenant get-license-info</pre>

Commands to get a particular user

Run the following command to get the user information.

```
user get <userId> [options]
```

where the options are:

--Name	Description
--view <viewType>	<p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre>user get <ID details></pre>

Commands for promoting Integration Server and Universal Messaging configurations from one stage to another

Run the following command to promote Integration Server and Universal Messaging configurations from one stage to another.

```
runtime promote-configuration <fromSolutionName> <fromNodeName>
<fromStageName> [toSolutioName] [toNodeName] [options]
```

Note: If toSolutionName and toNodeName are provided as part of your command, then the CLI performs the cross solution promotion. However, if toSolutionName and toNodeName are not available, then the configuration will be promoted to higher stage on the same Integration Server or Universal Messaging node.

where the options are:

--Name	Description
--propFile <fileName>	<p>Properties file to perform variable substitution.</p> <p>Example: Use the following command for promotion across same instance:</p> <pre>runtime promote-configuration DemoSoln IS development</pre> <p>Example: Use the following command for cross solution promotion:</p> <pre>runtime promote-configuration DemoSoln IS development DemoSoln1 IS1</pre> <p>Promotes the configuration from the solution DemoSoln IS node to DemoSoln1 and IS1 node.</p>

Commands for promoting Integration Server packages from one stage to another

Run the following command to promote Integration Server packages from one stage to another.

```
runtime promote-packages <fromSolutionName> <fromNodeName> <fromStageName>
[toSolutioName] [toNodeName] [options]
```

Note: If toSolutionName and toNodeName are provided then the CLI performs the cross solution promotion. If toSolutionName and toNodeName are not available, then the packages will be promoted to higher stage on the same Integration Server instance.

where the options are:

--Name	Description
--include <comma separated packages names>	Promotes only specified packages. Example: <pre data-bbox="688 680 1338 709">--include package1,package2,package3</pre>
--exclude <comma separated packages names>	Promotes all the packages other than the packages specified in the options. Example: <pre data-bbox="688 875 1338 905">--exclude package1,package2,package3</pre>
--propFile <fileName>	Provide properties file to perform variable substitution. Examples: Use the following command for promotion across same instance: <pre data-bbox="688 1157 1382 1209">runtime promote-packages DemoSoln IS development -- propFile /home/etc/var_sub.properties</pre> Use the following command for cross solution promotion: <pre data-bbox="688 1310 1382 1362">runtime promote-packages DemoSoln IS development TestSoln IS2</pre> Use the following command to replace a property in a specific composite asset. <pre data-bbox="688 1463 1338 1493"><propertyName>/<compositeAssetName></pre> <p>Note:The replacement properties should be in the following format:</p> <pre data-bbox="764 1589 1442 1619"><propertyName>/<compositeAssetName>/<assetName></pre> <p>Example for replacing properties of a package:</p> <pre data-bbox="764 1715 1386 1745">activatePkgOnInstall/TestODataService=false</pre> <p>where TestODataService is the package name whose property activatePkgOnInstall" is assigned with value "false".</p>

--Name	Description
	<p>Example for replacing properties of a service of a package:</p> <pre>serverName/TestODataService/JDBC_Connection.ODataService=localhost</pre> <p>where JDBC_Connection.ODataService is a service under package TestODataService, whose parameter serverName is assigned with value localhost</p>

Commands for printing the list of exposed services

Run the following command to print the list of exposed services.

```
runtime get-exposed-is-services <solutionName> <nodeName> <stageName> [options]
```

where the options are:

--Name	Description
-view <viewType>	<p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre>runtime get-exposed-is-services DemoSoln IS development</pre>

Commands for listing all the queues

Run the following command to list all the queues in the Universal Messaging instance.

```
um list-queues <solutionName> <nodeName> <stageName> [options]
```

where the options are:

--Name	Description
-view <viewType>	<p>By default, outputs the response in a table view mode. The CLI supports both table and JSON output format.</p> <p>Example:</p> <pre>um list-queues DemoSoln UM development</pre>

Commands for getting the queue information

Run the following command to retrieve pushed, popped, and memory usage of the queue.

```
um get-queue <solutionName> <nodeName> <stageName> <queueName> [options]
```

where the options are:

--Name	Description
-view <viewType>	By default, outputs the response in a table view mode. The CLI supports both table and JSON output format. Example: <pre>um get-queue DemoSoln UM development dummyQueue</pre>

Commands for getting the queue details

Run the following command to retrieve the queue details.

```
um get-queue-details <solutionName> <nodeName> <stageName> <queueName> [options]
```

where the options are:

--Name	Description
-view <viewType>	By default, outputs the response in a table view mode. The CLI supports both table and JSON output format. Example: <pre>um get-queue-details DemoSoln UM development dummyQueue</pre>

Commands for listing all the channels in the Universal Messaging instance

Run the following command to list all the channels in a Universal Messaging instance.

```
um list-channels <solutionName> <nodeName> <stageName> [options]
```

where the options are:

--Name	Description
-view <viewType>	By default, outputs the response in a table view mode. The CLI supports both table and JSON output format. Example: <pre>um list-channels DemoSoln UM development</pre>

Commands for getting the channel information

Run the following command to get the channel information.

```
um get-channel <solutionName> <nodeName> <stageName> <channelName> [options]
```

where the options are:

--Name	Description
-view <viewType>	By default, outputs the response in a table view mode. The CLI supports both table and JSON output format. Example: <pre>um get-channel DemoSoln UM development dummyChannel</pre>

Commands for getting the channel details

Run the following command to get the channel details.

```
um get-channel-details <solutionName> <nodeName> <stageName> <channelName> [options]
```

where the options are:

--Name	Description
-view <viewType>	By default, outputs the response in a table view mode. The CLI supports both table and JSON output format. Example: <pre>um get-channel-details DemoSoln UM development dummyChannel</pre>