

# Universal Messaging Administration Guide

Version 10.1

October 2017

---

This document applies to Software AG Universal Messaging 10.1 and to all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 2013-2021 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <https://softwareag.com/licenses/>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <https://softwareag.com/licenses/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at <https://softwareag.com/licenses/> and/or in the root installation directory of the licensed product(s).

**Document ID: NUM-AG-101-20211124**

# Table of Contents

<b>About this Documentation.....</b>	<b>5</b>
Online Information.....	6
<b>1 About this Documentation.....</b>	<b>7</b>
<b>2 Universal Messaging Enterprise Manager.....</b>	<b>9</b>
Introduction.....	10
Administration Using Enterprise Manager.....	14
Management and Monitoring Sections.....	306
Using the Enterprise Viewer.....	380
<b>3 Using Command Central to Manage Universal Messaging.....</b>	<b>383</b>
Managing Universal Messaging using Command Central.....	384
Securing Access to Command Central.....	384
Instance Management.....	386
Authentication Configuration.....	387
Universal Messaging Configuration Types.....	388
Universal Messaging Logs.....	412
Universal Messaging Administration Types.....	412
Universal Messaging Inventory.....	416
Universal Messaging Lifecycle Actions.....	416
Universal Messaging KPIs.....	416
Universal Messaging Run-time Monitoring Statuses.....	417
Universal Messaging and the Command Line Interface.....	418
Universal Messaging Commands.....	419
<b>4 Command Line Administration Tools.....</b>	<b>451</b>
Introduction to the Administration Tools.....	452
Starting the Tools using the Tools Runner Application.....	452
Performing Standard Administration Tasks on Realms and Clusters.....	454
Running a Configuration Health Check.....	454
Collecting Realm Information.....	464
<b>5 Universal Messaging Administration API.....</b>	<b>471</b>
Introduction.....	472
Administration API Package Documentation.....	475
Namespace Objects.....	475
Realm Server Management.....	481
Security.....	489
Management Information.....	493
<b>6 Thread Pool Monitoring.....</b>	<b>501</b>



# About this Documentation

■ Online Information .....	6
----------------------------	---

---

## Online Information

---

### Software AG Documentation Website

You can find documentation on the Software AG Documentation website at <http://documentation.softwareag.com>. The site requires Empower credentials. If you do not have Empower credentials, you must use the TECHcommunity website.

### Software AG Empower Product Support Website

You can find product information on the Software AG Empower Product Support website at <https://empower.softwareag.com>.

To submit feature/enhancement requests, get information about product availability, and download products, go to [Products](#).

To get information about fixes and to read early warnings, technical papers, and knowledge base articles, go to the [Knowledge Center](#).

### Software AG TECHcommunity

You can find documentation and other technical information on the Software AG TECHcommunity website at <http://techcommunity.softwareag.com>. You can:

- Access product documentation, if you have TECHcommunity credentials. If you do not, you will need to register and specify "Documentation" as an area of interest.
- Access articles, code samples, demos, and tutorials.
- Use the online discussion forums, moderated by Software AG professionals, to ask questions, discuss best practices, and learn how other customers are using Software AG technology.
- Link to external websites that discuss open standards and web technology.

# 1 About this Documentation

---



## 2 Universal Messaging Enterprise Manager

---

■ Introduction .....	10
■ Administration Using Enterprise Manager .....	14
■ Management and Monitoring Sections .....	306
■ Using the Enterprise Viewer .....	380

Universal Messaging provides a powerful management tool that enables the capture of extremely granular metrics, management and audit information from multiple Universal Messaging realms. The enterprise realm manager also allows you to control, configure and administer all aspects of any Universal Messaging realm or clusters of realms.

Universal Messaging's Enterprise Manager has been completely written using the Universal Messaging management API and so any of its functionality can be easily integrated into bespoke or 3rd party systems management services.

The Universal Messaging Enterprise Manager and administration API use in-band management. This ensures that the flexibility of Universal Messaging connections is also made available from a management / monitoring perspective. Universal Messaging realms can be managed remotely over TCP/IP sockets, SSL enabled sockets, HTTP and HTTPS as well as through normal and user-authenticated HTTP/S proxies.

This guide contains information on all aspects of using the Universal Messaging enterprise manager GUI.

## Introduction

---

### Getting Started

In order to start administering and monitoring your Universal Messaging Realm servers you need to launch the Universal Messaging Enterprise Manager. The Enterprise Manager is capable of connecting to multiple Universal Messaging realms at the same time, whether these are part of a cluster / federated namespace or simple standalone realms. A configuration file called `realms.cfg` is created in your home directory which stores the Enterprise Manager's connection info, however the very first time you launch it a bootstrap `RNAME` environment variable can be used to override the default connection information. Subsequent launches will not depend on the environment variable as long as you save your connection information (see [“Realm Profiles” on page 23](#)).

Launching on Windows platforms can be done by selecting the Enterprise Manager shortcut in the start menu.

You can also open a client command prompt and type a command of the following form:

```
<UM_install_dir>\java\<UM_server_name>\bin\nenterprisemgr.exe
```

where `<UM_install_dir>` is the installation root location and `<UM_server_name>` is the name of the Universal Messaging server.

Launching on Unix platforms can be done by executing the `nenterprisemgr` executable, which you can find under the installation directory at the following location:

```
java/umserver/bin/nenterprisemgr
```

### Logging In

When you start the Enterprise Manager, there is a login dialog in which you can enter a user ID and password. The user ID and password are only required for logging in if you have activated

basic authentication. If you have not activated basic authentication, the password is ignored, but the user ID is still subject to the usual ACL checks in the Enterprise Manager.

See the section *Basic Authentication* in the Developer Guide for information about setting up basic authentication.

## The read-only Enterprise Viewer

The Enterprise Viewer is a read-only version of the Enterprise Manager. It allows unprivileged users to view the same information as with the Enterprise Manager, but does not allow you to change the Universal Messaging environment in any way. For further information, see the section [“Using the Enterprise Viewer” on page 380](#).

## Tab-by-Tab Overview

This document provides a high level overview of Enterprise Manager functionality on a tab by tab basis, for each of the following node types (as displayed in Enterprise Manager's left hand pane).

- [“Universal Messaging Enterprise” on page 11](#)
- [“Realm Nodes” on page 11](#)
- [“Container \(Folder\) Nodes” on page 13](#)
- [“Channel Nodes” on page 13](#)
- [“Queue Nodes” on page 14](#)

## Universal Messaging Enterprise View

Highlighting the **Universal Messaging Enterprise** node in the tree provides an **Enterprise Summary** view of all realms to which Enterprise Manager is connected, and includes information such the total number of realms, clusters, channels, queues, events published and received, and more.

### Realm Nodes

Highlighting a Realm Node in the navigation tree in the left hand panel will bring up a context-sensitive set of tabs in the right hand panel:

- **Status Tab**

Provides a snapshot and historical view of statistics such as the number of events published or consumed, numbers of connections, and memory usage.

- **Monitoring Tab**

A container for multiple panels that enable you to view live information on the selected realm:

- **Logs**

Provides a rolling view of Universal Messaging Logs and Plugin Logs including Access and Error logs.

■ **Connections**

Provides a list of all current connections to the realm, along with details such as protocol, user, and host. Allows connections to be "bounced" (forcing them to reconnect).

■ **Threads**

Provides details such as the number of idle and active threads per thread pool, task queue size per thread pool and a total number of executed tasks for the respective thread pool. It also provides details of scheduled operations each task has within the system.

■ **Top**

A "Unix top"-like view of realm memory usage, JVM GC stats, channel and connection usage.

■ **Audit**

Displays the contents of the remote audit file and receives real time updates as and when audit events are generated.

■ **Metrics**

Provides metrics on current memory usage, such as on-heap event memory usage.

■ **ACL Tab**

Displays the realm ACL and the list of subjects and their associated permissions for the realm. Permits editing of ACLs.

■ **Comms Tab**

Provides access to management tools for TCP interfaces, IP Multicast and Shared Memory communication methods:

■ **Interfaces**

Management of TCP Interfaces (creation, deletion, starting/stopping) as well as configuration of advanced interface properties.

■ **Multicast**

Management of IP Multicast Configurations (creation/deletion) and advanced configuration tuning.

■ **Shared Memory**

■ **Realms Tab**

Provides a summary of memory, event and interface information for each realm to which Enterprise Manager is connected.

■ **Config Tab**

Manage the settings for many groups of advanced realm configuration parameters.

- **Scheduler Tab**

Permits the user to view, add, delete and edit scheduler scripts.

- **JNDI Tab**

Enables the creation of references to JMS TopicConnectionFactory and QueueConnectionFactory, as well as references to Topics and Queues.

## **Container (Folder) Nodes**

- **Totals Tab**

Provides status information for resources and services contained within the selected container branch of the namespace tree.

- **Monitor Tab**

A "Unix top"-like view of the usage of Channels or Queues found within the container node.

## **Channel Nodes**

Highlighting a Channel Node in the navigation tree in the left hand panel will bring up a context-sensitive set of tabs in the right hand panel:

- **Status Tab**

Provides a snapshot and historical view of statistics such as the number of events published or consumed, rates, and event storage usage.

- **Joins Tab**

Permits the user to view, add, delete and edit joins between Channels.

- **ACL Tab**

Permits the user to add, remove or modify entries within the Channel ACL.

- **Named Objects**

Enables the viewing and deletion of named objects (which provide state information for durable consumers for the channel).

- **Snoop Tab**

Permits snooping of events on the Channel

- **Connections**

Enables the creation of references to JMS TopicConnectionFactory and QueueConnectionFactory, as well as references to Topics and Queues.

## Queue Nodes

Highlighting a Queue Node in the navigation tree in the left hand panel will bring up a context-sensitive set of tabs in the right hand panel:

- **Status Tab**

Provides a snapshot and historical view of statistics such as the number of events published or consumed, rates, and event storage usage.

- **Joins Tab**

Permits the user to view, add, delete and edit joins from any Channels to this Queue.

- **ACL Tab**

Permits the user to add, remove or modify entries within the Queue ACL.

- **Snoop Tab**

Permits snooping (a non-destructive read) of events on the Queue.

## Administration Using Enterprise Manager

---

### Enterprise View

The enterprise view is the first screen you see whenever the Universal Messaging enterprise manager is launched. The screen is designed to provide an overview of the characteristics as well as current status of the set of Universal Messaging realms that enterprise manager is currently connected with, your Universal Messaging enterprise. This summary view will include any type of Universal Messaging realm you have added to your connection information whether they are standalone development realms or production clustered realms. Adding or removing Universal Messaging realms to the enterprise manager's connection info will result in those realm's data to be also included in this view (see [“Connecting to Multiple Realms” on page 16](#) and [“Disconnecting from Realms” on page 18](#)).

As you navigate through more specific parts of the Universal Messaging enterprise, you can always return to this screen by selecting the root node of the navigation tree called **Universal Messaging Enterprise**.

The top of the screen displays a large real time graph illustrating the total number of events published (yellow) and consumed (red) across all Universal Messaging realms. The bottom of the screen displays 3 panels named **Totals**, **Event Status** and **Connection Status** respectively. The **Totals** panel displays the total number of clusters, realms and resources across all Universal Messaging realms. The **Event Status** panel displays the total number of events consumed, published as well as the current consume and publish rates. Finally the **Connection Status** panel displays the total number, the current number as well as the rate of connections (sessions), whether application or administrative, across all Universal Messaging realms.

The screenshot displays the Nirvana Enterprise Manager interface. The left pane shows a tree view under 'Nirvana Enterprise' with the following structure:

- Clusters
  - test
- Realms
  - realm1(host1:11010)
    - ClusterRates
    - Data Groups
    - GlobalOrders
  - realm2(host2:11030)
    - ClusterRates
    - Data Groups
    - GlobalOrders
  - realm3(host3:11070)
    - ClusterRates
    - Data Groups
    - GlobalOrders

The right pane shows the 'Enterprise Summary' tab with an 'Event History' graph. The graph displays a series of peaks and troughs, with the most recent data points colored in red and yellow, indicating high activity. Below the graph is a summary table:

Totals		Event Status	
Clusters	1	Consumed	12769400
Realms	3	Published	38068304
Channels	3	Consumed/Sec	112951.9
Queues	3	Published/Sec	112952.5
Data Groups	0		

## Realm Administration

### Creating and Starting a Realm Server

Universal Messaging provides the following tools for performing general administrative tasks on realms, such as creating a realm, checking the status of a realm, and deleting a realm.

- **The Universal Messaging Instance Manager:**

For related information, see the section *Universal Messaging Instance Manager* in the *Installation Guide*.

- **Command Central:** If your installation of Universal Messaging includes the optional Command Central component, you can use the command line tool of Command Central to perform administrative tasks on realms.

For related information, see the section “[Universal Messaging Commands](#)” on page 419 in the *Command Central* part of the documentation.

## Creating a Realm Server

You can use either the Universal Messaging Instance Manager or Command Central to create the realm server. See the examples in the corresponding documentation pages at the locations mentioned above.

## Starting a Realm Server

After you have created the realm server, start the realm server as follows:

On Windows systems:

1. From the Windows Start menu, navigate to the node **Start Servers** that is located under the **Universal Messaging** node.
2. Navigate in the hierarchy to find the node labelled **Start <RealmName>**, and click it. Here, <RealmName> is the name you assigned to the realm server when you created it.

On Linux:

1. Start the script `nserver.sh` that is located in `UniversalMessaging/server/<RealmName>/bin/` under the product installation directory.

## Connecting to Multiple Realms


An Enterprise Manager has the ability to connect to multiple Universal Messaging realms at the same time. These realms can be standalone or clustered so developers and administrators can now manage and monitor the whole Universal Messaging enterprise infrastructure from a single instance of Enterprise Manager. Once connected to a set of Universal Messaging realms, it is possible to save (see “[Realm Profiles](#)” on page 23) the connection information so that Enterprise Manager automatically connects to all those realms each time it starts.

A bootstrap `RNAME` environment variable is needed the very first time you run Enterprise Manager or if your connection info file is empty. If you use the shortcut / link created by the installation process this will be automatically set to point to the locally installed realm's bootstrap interface so you don't need to take additional action. If however you open a client command prompt and you wish to initially connect to a realm other than the local one, then you need to change your `RNAME` environment variable.


For more information on how to set the `RNAME` variable, see the section *Communication Protocols and RNAMEs* in the Developer Guide.

Please also note that once your realm connection information is saved, the RNAME environment variable will be ignored.

Once your Enterprise manager is up and running, you have to select the Connect to Realm menu option from the Connections menu, as shown in the figure below:



The menu option will open the Connect To Realm dialog as shown in the figure below:




Simply fill in the RNAME that points to the interface of the Universal Messaging realm you wish to connect to and click on the OK button. The Enterprise Manager status bar will display a message informing you where it is trying to connect to. If the connection is successful, a new realm node will be rendered on the tree with the unique name of that realm. You can manage and monitor the new realm by selecting that newly rendered tree node.

The name displayed for the realm uses the syntax: `realmname(host:port)`, for example `realm1(MyHost:11010)`.

When you connect to a realm server that is part of a cluster or zone, the Enterprise Manager automatically connects to and displays the other realms in the cluster or zone.

If you enter an incorrect RNAME, if that realm is not running or if it is running but the particular interface is not up the connection will fail. In that case a retry dialog will appear like this one below:




If you had typed the correct RNAME this gives you the opportunity to start the Universal Messaging realm or interface needed and click yes to retry the connection without entering the information again. If however the RNAME entered was wrong or you do not wish to retry then clicking no will close the dialog. Finally don't forget that to make this connection get attempted each time you start Enterprise Manager you need to save your connection information.


## Disconnecting from Realms

Using the multiple realm connection functionality, the startup time of the Enterprise manager is slightly increased each time you add a Universal Messaging realm to your connection list. If you connect from a different location or network, if the development phase of a Universal Messaging application completes or if you simply wish to have faster startup times for Enterprise Manager, you may want to stop connecting to one or more of your Universal Messaging realms.

This section explains how it is possible to disconnect from one of multiple realms that your Universal Messaging Enterprise manager may be connected to. To do so, simply select the Disconnect from Realm menu option in the Connections menu as shown in the figure below:



This causes a disconnection dialog to appear like the one shown below:




The dialog lists the names of the currently connected Universal Messaging realms. Select the realm you wish to disconnect from and click OK. The disconnected realm node and any other realm nodes that were added by it when the node was created disappear from the namespace tree.

Disconnecting from a realm is not necessarily a permanent operation. If you disconnect from a realm that was listed in your connection information, then the disconnect is applicable for this Enterprise Manager session only, next time you start up the connection will be attempted again. In order to make the disconnect permanent, please save (see [“Realm Profiles” on page 23](#)) your connection information after you disconnect.

## Editing Connection Information


As mentioned in previous sections, Universal Messaging Enterprise manager can connect to multiple Universal Messaging realms at the same time and allows saving connection information in a configuration file. This configuration file can change in one of 3 ways:

1. By selecting the Save Connection Info menu option (see [“Realm Profiles” on page 23](#)) which replaces the configuration file contents with the list of current connections.
2. When running the Enterprise manager, if a connection to a configured realm fails and the user chooses not to retry, a second dialog appears that looks like the example in the figure below:




If the user clicks Yes, then the configuration file remains the same. However if the user chooses no, the failed connection is removed from the configuration file without any further action required. The Enterprise manager will never try to connect to that Universal Messaging realm again during startup.

3. By using the Edit Connection Info menu option, located under the File menu as shown in the figure below:




This causes the following dialog to appear:




The Realm name combo box contains the complete list of configured Universal Messaging realms that had been connected during the last Save Connection Info operation. If you have connected to additional realms that had not been saved, these will not be included in this list. By selecting a particular Realm name, you can also see the connection RNAME value containing the RNAME that Enterprise manager uses to connect to it. Clicking on the delete button will remove the currently selected realm from the connection info file and this can be repeated many times until only the desired realms are present in the list. When this is done, click on the Save button to recreate the connection info file.

## Realm Profiles

The Universal Messaging Enterprise Manager enables administrators to group realms and their respective connections into profiles for easy management and accessibility. Any number of realms can be saved as part of a profile.



When profiles are reloaded the Universal Messaging Enterprise Manager automatically connects to all realms defined within the loaded profile.



## Realm Federation

As well as clustering technology, Universal Messaging supports the concept of a federated namespace which enables realm servers that are in different physical locations to be viewed within one logical namespace.

### Note:

Clustering and Realm Federation are mutually exclusive. If a realm is a member of a cluster, you cannot use the realm for federation. Similarly, if a realm is part of a federation, the realm cannot be used for clustering.

If you consider that a Universal Messaging namespace consists of a logical representation of the objects contained within the realm, such as resources and services: a federated namespace is an extension to the namespace that allows remote realms to be visible within the namespace of other realms.

For example, if we had a realm located in the UK (United Kingdom), and 2 other realms located in the US (United States) and DE (Germany), we can view the realms located in DE and US within the namespace of the UK realm. Federation allows us to access the objects within the DE and US realms from within the namespace of the UK realm.

It is possible to add realms to a Universal Messaging namespace using the Universal Messaging Administration API or by using the Enterprise Manager as described below.

### Adding Realms

The first step in order to provide federation is to add the realms. Adding a realm to another realm can be achieved in 2 ways. The first way simply makes a communication connection from one realm to another, so the realms are aware of each other and can communicate. This allows you to create a channel join between these realms.

**Note:**

For a description of the general principles involved in creating channel joins, see the section *Creating Channel Joins*. The description details the usage based on the Enterprise Manager, but the same general principles apply if you are using the API.

The second option also makes a new communication connection, but if you specify a *'mount point'*, the realm you add will also be visible within the namespace of the realm you added it to.

### Mount Points


Providing a mount point for added realms is similar to the mount point used by file systems when you mount a remote file system into another. It specifies a logical name that can be used to access the resources within the mounted realm. The mount point is therefore the entry point (or reference) within the namespace for the realm's resources and services.

For example, if I have a realm in the UK, and wish to add to it a realm in the US, I could provide a mount point of *'/us'* when adding the US realm to the UK realm. Using the mount point of *'/us'*, I can then access the channels within the US realm from my session with the UK realm. For example, if I wanted to find a channel from my session with the UK realm, and provided the channel name *'/us/customer/sales'*, I would be able to get a local channel reference to the *'/customer/sales'* channel within the US realm.

### Using the Enterprise Manager to add realms


In order to add a realm to another realm, first of all you need to select the realm node from the namespace that you wish to add the realm to. Then, right-click on the realm node to display the

menu options available for a realm node. One of the menu options is labelled 'Add Realm to Namespace', clicking on this menu option will display a dialog that allows you to enter the RNAME of the realm you wish to add and an optional mountpoint. This dialog is shown in the image below.



The RNAME value in the dialog corresponds to the realm interface you wish the 2 realms to communicate using. The mount point corresponds to the point within the namespace that the realm will be referenceable.

The image below shows the namespace for a realm that has had 2 realms mounted within its namespace, called 'eur' and 'us' respectively. As you can see the resources within both the mounted realms are also displayed as part of the namespace of the 'node1' realm.



Sessions connected to the 'node1' realm now have access to three channels. These are :

- '/global/orders' which is a local channel

- '/eur/orders' which is actually a channel on another Universal Messaging Realm which has been added to this namespace under the mountpoint '/eur'
- '/us/orders' which is actually a channel on another Universal Messaging Realm which has been added to this namespace under the mountpoint '/us'

### Example Use of Federation : Remote Joins

Once you have added the realms to one another, it is possible to create remote joins between the channels of the realms. This is very useful when considering the physical distance and communications available between the different realms. For example, if you wish all events published to the /customer/sales channel in the UK realm to be available on the /customer/sales channel in the US realm, one would create a join from the /customer/sales channel in the UK to the /customer/sales channel on the US realm, so all events published onto the uk channel would be sent to the us channel.

Federation and remote joins provide a huge benefit for your organization. Firstly, any consumers wishing to consume events from the uk channel would not need to do so over a WAN link, but simply subscribe to their local sales channel in the us. This reduces the required bandwidth between the us and uk for your organization, since the data is only sent by the source realm once to the joined channel in the us, as opposed to 1...n times where n is the number of consumers in the us. Remote joins are much more efficient in this respect, and ensure the data is available as close (physically) to the consumers as possible.

**Note:**

For a description of the general principles involved in creating channel joins, see the section *Creating Channel Joins*. The description details the usage based on the Enterprise Manager, but the same general principles apply if you are using the API.

### Realm Configuration


Universal Messaging Realms can be configured based on a number of properties that are accessible both through the Universal Messaging Administration API as well as the Universal Messaging Enterprise Manager. Any changes made to the configuration properties for a Universal Messaging realm are automatically sent to the realm and implemented. This functionality offers major benefits to Administrators, since realms can be configured remotely, without the need to be anywhere near the actual realm itself. More importantly, multiple realms and clustered realms can also be automatically configured remotely.

This section describes the different configuration properties that are available using the Universal Messaging Enterprise Manager.


When you select a realm from the namespace, one of the available panels in the Enterprise Manager is labelled 'Config'. Selecting this panel displays various groups of configuration properties, with each group of properties relating to a specific area within the Universal Messaging Realm. Each group of properties contains different values for specific items.

## Basic and Advanced Properties

There are currently a large number of configuration properties, and they are divided into two categories, namely Basic and Advanced. The properties in the Basic category are the most commonly used ones. The properties in the Advanced category will probably be less frequently used, and are intended for special cases or expert users.



When the Basic and Advanced categories are expanded, you will see a display of the configuration properties. Properties that have a similar effect are arranged into groups; for example, properties that determine when a client times out are contained in the group "Client Timeout Values":



Note that in the example shown, the group "Client Timeout Values" appears in both the Basic and the Advanced category. However, the properties "EventTimeout", "HighWaterMark" etc. belonging to this group appear only under the Basic category, whereas the properties "QueueAccessWaitLimit" etc. belonging to the same group appear only under the Advanced category. The properties in the Basic category are the ones which you will probably find most useful for your day-to-day work.

## Configuration Groups

The configuration groups are :

1. **Audit Settings** - Values relating to what information is stored by the audit process
2. **Client Timeout Values** - Values relating to client / server interaction

3. **Cluster Config** - Values specific to the clustering engine
4. **Comet Config** - Values relating to the configuration of Comet
5. **Connection Config** - Values relating to the client server connection
6. **Data Stream Config** - Values relating to the configuration of Data Streams
7. **DurableConfig** - Values relating to usage of durables
8. **Environment Config** - Read only configuration values that relate to the system environment. These cannot be changed.
9. **Event Storage** - Values specific to how events are stored and retrieved on the server
10. **Fanout Values** - Values specific to the delivery of events to clients
11. **Global Values** - Values specific to the realm process itself
12. **Inter-Realm Comms Config** - Values relating to Inter-Realm communication
13. **JVM Management** - Values relating to the JVM the Realm Server is using
14. **Join Config** - Values specific to channel join management
15. **Logging Config** - Values specific to logging
16. **Metric Config** - Values relating to metric management
17. **MQTT Config** - Values relating to MQTT
18. **Plugin Config** - Values relating to Realm Plugins
19. **Protobuf Config** - Values relating to Protocol Buffers
20. **Protocol AMQP Config** - Values relating to the use of AMQP connections
21. **Protocol MQTT Config** - Values relating to the use of MQTT connections
22. **Proxy Forward Config** - Values relating to Proxy/Forwarding
23. **RecoveryDaemon** - Values relating to clients that are in recovery (i.e. replaying large numbers of events)
24. **Server Protection** - Values specific to server protection
25. **Thread Pool Config** - Values specific to the servers thread pools.
26. **TransactionManager** - Values specific to the transaction engine of the RealmServer

The table below describes the properties that are available within each configuration group. It also shows valid ranges of values for the properties and a description of what each value represents. The "Adv." column shows "Y" if the property is in the Advanced category, whereas no entry indicates that the property is in the Basic category.

Configuration Group/Property	Valid values	Description	Adv.
<b>Audit Settings</b>			
ChannelACL	True or False	Log to the audit file any unsuccessful channel ACL interactions. Default is true.	
ChannelFailure	True or False	Log to the audit file any unsuccessful realm interactions. Default is true.	
ChannelMaintenance	True or False	Log to the audit file any channel maintenance activity. Default is false.	
ChannelSuccess	True or False	Log to the audit file any successful channel interactions. Default is false.	
DataGroup	True or False	Log to the audit file any changes to DataGroup structure	
DataGroupFailure	True or False	Log to the audit file any failed attempts to DataGroup structure	
DataStream	True or False	Log to the audit file DataStream add and removes	
Group	True or False	Log to the audit file any added or removed security groups	
GroupMembers	True or False	Log to the audit file any changes in group membership	
InterfaceManagement	True or False	Log to the audit file any interface management activity. Default is true.	
JoinFailure	True or False	Log to the audit file any unsuccessful join interactions. Default is true.	
JoinMaintenance	True or False	Log to the audit file any join maintenance activity. Default is true.	
JoinSuccess	True or False	Log to the audit file any successful join interactions. Default is false.	
QueueACL	True or False	Log to the audit file any unsuccessful queue ACL interactions. Default is true.	
QueueFailure	True or False	Log to the audit file any unsuccessful queue interactions. Default is true.	
QueueMaintenance	True or False	Log to the audit file any queue maintenance activity. Default is false.	

Configuration Group/Property	Valid values	Description	Adv.
QueueSuccess	True or False	Log to the audit file any successful queue interactions. Default is false.	
RealmACL	True or False	Log to the audit file any unsuccessful realm ACL interactions. Default is true.	
RealmFailure	True or False	Log to the audit file any unsuccessful realm interactions. Default is true.	
RealmMaintenance	True or False	Log to the audit file any realm maintenance activity. Default is true.	
RealmSuccess	True or False	Log to the audit file any successful realm interactions. Default is false.	
SnoopStream	True or False	Log to the audit file Snoop stream add and removes	
<b>Client Timeout Values</b>			
EventTimeout	5000 to No Max	The amount of ms the client will wait for a response from the server. Small values may cause clients to abandon waiting for responses and disconnect prematurely. Large values may cause clients to take an unusually long amount of time waiting for a response before disconnecting. Default is 60000.	
HighWaterMark	2 to No Max	The high water mark for the connection internal queue. When this value is reached the internal queue is temporarily suspended and unable to send events to the server. This provides flow control between publisher and server. Default is 200.	
LowWaterMark	1 to No Max	The low water mark for the connection internal queue. When this value is reached the outbound internal queue will again be ready to push event to the server. Default is 50.	
QueueAccessWaitLimit	200 to No Max	The maximum number of milliseconds it should take to gain access to an internal connection queue to push events. Once this time has elapsed the	Y

Configuration Group/Property	Valid values	Description	Adv.
		client session will inform any listeners registered on the session which monitor these connection queues. Small values may result in an excessive number of notifications. Default is 200.	
QueueBlockLimit	500 to No Max	The maximum number of milliseconds an internal connection queue will wait before notifying listeners after it has reached the HighWaterMark. Small values may result in excessive notifications. Default is 500.	Y
QueuePushWaitLimit	200 to No Max	The maximum number of milliseconds it should take to gain access to an internal connection queue and to push events before notifying listeners. Small values may result in excessive notifications. Default is 200.	Y
TransactionLifeTime	1000 to No Max	The default amount of time a transaction is valid before being removed from the tx store. Default is 20000.	
<b>Cluster Config</b>			
BufferSize	1400 to 1048576	Size in bytes of the inter-realm buffer to use. If the nodes are connected using a high-speed network connection, we suggest using 8192.	Y
ClientQueueSize	10 to 10000	Size of the client request queue.  If this queue is small then the clients will wait longer and performance may drop.  If too large then client requests are queued but not processed.	
ClientQueueWindow	1 to 1000	The value used when an async consumer of type queue or durables of types shared queue, shared, and serial do not set an explicit value for the window size.	

Configuration Group/Property	Valid values	Description	Adv.
		Default is 100. <b>Important:</b> A small number will reduce performance.	
ClientStateDelay	0 to 120000	The number of seconds to delay the cluster processing client requests when a cluster state change occurs. A large number will delay client requests longer than required.	
DisableHTTPConnections	True or False	Disable HTTP(s) connections between cluster nodes. If <code>true</code> then the server will only use <code>nsp(s)</code> connections between realm nodes, and any <code>nhp(s)</code> <code>rnames</code> will be switched to using <code>nsp(s)</code> .	
DisconnectWait	1000 to 120000	Time to wait for the node to form in the cluster. Once this time has expired the behavior is defined by the <code>DisconnectWhenNotReady</code> flag.	
DisconnectWhenNotReady	True or False	If the node has not formed in the cluster then disconnect the client. If <code>true</code> then the client will receive a disconnect, else the request will be queued.	
EnableMulticast	True or False	Enables cluster requests broadcast to realms to be send through the reliable multicast mechanism within Universal Messaging. This setting only takes effect if a multicast interface is configured for all nodes within the cluster.	
EnableSites	True or False	If enabled then the master selection takes into account the Prime Site. <b>Warning:</b> if used incorrectly a split brain scenario may occur, so please use with caution.	Y
EnableStoreRecoveryRetry	True or False	Enables/Disables the ability for the slave to re-attempt a recovery of a store	Y

Configuration Group/Property	Valid values	Description	Adv.
		if it detects changes to the store during recovery. If <code>true</code> the slave will continue to attempt a cluster recovery of a store which may be changing due to TTL or capacity on the store attributes.	
EnginePipelineSize	1 to 32	Number of concurrent pipeline threads running within the cluster engine. If set to 1, then all requests are pipelined through one thread, else topics/queues are bound to specific pipelines.	Y
FilterEventsDuringRecovery	True or False	Only Applicable to JMS Engine Channels. Defines if we recover events that have already been consumed. If <code>false</code> then extra events may be sent to recovering realms for no real reason.	Y
FormationTimeout	60000 to 300000	The time to wait for the state to move from recovery to slave or master. If this value is too small then recovering a large number of events will result in the realms dropping out of the cluster.	
HeartBeatInterval	1000 to 120000	Heart Beat interval in milliseconds. Default is 120000. A small value here will cause excessive messages being generated between realms.	
InitialConnectionTimeout	5000 to 240000	The number of milliseconds that the server will wait while trying to establish a connection to a peer. A small value may reduce the chance of a connection in busy networks, while a large number may delay cluster formation.	
IsCommittedDelay	1000 to 30000	When a slave processes an <code>IsCommitted</code> request and it is still recovering the Transaction store, it will block the clients request for this timeout period. If this is set to a large value, clients may experience a substantial delay in response.	Y
MasterRequestTimeout	1000 to 900000	Specifies the amount of time in milliseconds that the master is going to	

Configuration Group/Property	Valid values	Description	Adv.
		wait for a slave to respond to a single request before disconnecting it. This timeout will prevent a slave from being reconnected if it fails to respond to a master request.	
MasterVoteDelay	1000 to 60000	When a node has requested to be master it will wait this timeout period in milliseconds for the peers to agree. If this number is too high the cluster formation may take some time.	
MasterWaitTimeout	1000 to 600000	When the master is lost from the cluster and the remaining peers detect that the master has the latest state they will wait for this time period for the master to reconnect. If the master fails to reconnect in this time period a new master is elected.	
PublishQueueEnabled	True or False	If enabled the slaves will queue publish requests prior to committing them to the cluster. If enabled and a slave is killed, any outstanding publish events will be lost.	Y
QueueSize	100 to 1000	Number of events outstanding to be processed by the clusters internal queue before sending flow control requests back. Increased size increases the memory usage.	
SecureHandshake	True or False	If <code>true</code> , when peers connect they will perform a secure handshake to ensure the connection is valid. This is the preferred and secure option. Disabling this would only be recommended in debug mode. This handshake requires an RSA provider to work.	
SeparateLog	True or False	Create a separate log file for cluster events. Default is <code>false</code> .	
StateChangeScan	10000 to No Max	When a realm loses master or slave state then after this timeout all cluster based connections will be disconnected. If the realm reenters the cluster then	

Configuration Group/Property	Valid values	Description	Adv.
		the disconnect timeout is aborted. If this value is too low, all clients will be bounced while the cluster is forming.	
SyncPingSize	100 to 10000	Number of events sent before a cluster sync occurs. A small number will effect overall performance, a large number may result in a cluster being to far out of sync.	Y
TransactionSync	True or False	Make all transactional based events sync across the cluster. If <code>true</code> , transactional events may run slow but cluster state is guaranteed.	Y
<b>Comet Config</b>			
BufferSize	1024 to 102400	The buffer size for Comet requests. Large sizes will cause the realm to consume more memory when reading data from Comet clients. Small sizes may introduce delays in the time taken to read requests.	Y
EnableLogging	True or False	Enables logging of all comet queries, will impact server performance	
Timeout	10000 to No Max	The timeout for a Comet connection. Small sizes may cause Comet-based connections to time out prematurely. Large sizes may increase the time a server holds a disconnected Comet connection open.	
<b>Connection Config</b>			
AllowBufferReuse	True or False	If set to <code>true</code> then buffers will be allocated from the buffer pool and once finished with returned to the pool. If set to <code>false</code> then buffers are allocated on the fly and then left for the system to free them. It is best to leave this set to <code>true</code> . For object creation limitation it is best to set this to <code>true</code> .	Y

Configuration Group/Property	Valid values	Description	Adv.
BufferManagerCount	1 to 256	The number of Buffer Managers that the server will allocate. This is used during startup to size and manage the network buffers. This does not need to be large, but a rule of thumb is 1 per core.	Y
BufferPoolSize	100 to 10000	The underlying Universal Messaging IO utilizes buffers from a pool. By default we pre-load the pool with this number of buffers. As the reads/writes require buffers they are allocated from this pool, then once used are cleared and returned. If the size is too small we end up creating and destroying buffers, and the server may spend time creating them when needed. If the size is too large we have a pool of buffers which are not used taking up memory.	Y
BufferQueueSize	10 to 1000	Number of buffers to queue before we stop reading from the socket. If this is small we would block the connection, and performance may drop. The larger it is the more memory we use.	Y
BufferSize	1024 to 1048576	<p>This specifies the default size of the network buffers that Universal Messaging uses for its NIO. If small, then Universal Messaging will require more buffers (up to the maximum specified by <code>BufferPoolSize</code>) to send an event. If too large, then memory may be wasted on large, unused buffers.</p> <p>These buffers are reused automatically by the server, and are used to transfer data from the upper application layer to the network. So, for example, the server might use all <code>BufferPoolSize</code> buffers to stream from 1 application level buffer (depending on the relative sizes of the buffers).</p> <p>An efficient size would be about 40% more than the average client event, or</p>	

Configuration Group/Property	Valid values	Description	Adv.
		5K (whichever is largest). If too small, the server will send many small buffers.	
CometReadTimeout	1000 to 120000	Specifies the time the server will wait for a client to complete sending the data	
ConnectionDelay	10 to 60000	When the server has exceeded the connection count, how long to hold on to the connection before disconnecting. If this is too low, the server will be busy with reconnection attempts. Default is 60000.	Y
EnablePriorityMessaging	True or False	Enables server side prioritization of messages sent to clients. Select true to enable priority messaging.	Y
HandshakeTimeout	1000 to No Max	The number of milliseconds that the server will wait for the session to be established. A small number will impact slow connections. Default is 1000, i.e. 1 second.	
IdleDriverTimeout	120000 to No Max	Specifies the time in milliseconds that a communications driver can be idle before being deemed as inactive. When this happens the server will automatically close and remove the driver. This must be greater than the keep alive timeout else all connections will be closed due to inactivity.	
IdleSessionTimeout	10000 to No Max	If there has been no communication from a client for the configured number of milliseconds, the client is deemed idle and is disconnected. This typically occurs when there are network issues between a client and the server. If the value is too low, the chance of disconnecting a valid session is high.	
KeepAlive	5000 to No Max	The number of milliseconds the server will wait before sending a heartbeat. A small number will cause undue network traffic. Default is 60000.	

Configuration Group/Property	Valid values	Description	Adv.
MaxBufferSize	1024 to No Max	<p>The maximum buffer size in bytes that the server will accept. Default is 20971520 (20MB).</p> <p>Rather than using larger buffers, it is recommended that you compress if possible to save bandwidth and memory on the server.</p> <p>This value exists to stop a user from accidentally or maliciously overloading the server and causing excessive memory consumption.</p>	
MaxBufferSizeClientSideCheck	True or False	If set to <code>true</code> , this enables client-side checks of the size of the events being sent against the connection's <code>MaxBufferSize</code> . This allows for better exception handling and less wasted bandwidth on the client side. Default is <code>true</code> .	
MaxNoOfConnections	-1 to No Max	Sets the maximum concurrent connections to the server, -1 indicates no restriction, default is -1. Reducing this to a small number may cause client connections to be rejected.	
MaxWriteCount	5 to 100	When writing many events to a client the write pool thread may continue to send the events before returning to the pool to process other clients requests. So, for example if it is set to 5, then the thread will send 5 events from the clients queue to the client before returning to the pool to process another request. If this number is small it creates additional CPU overhead.	
NIOSelectArray	True or False	Specifies that the selector thread will use an array-based structure instead of an iterator-based structure to determine if underlying NIO channels are ready.	Y
NetworkMonitorThreads	2 to 100	The number of threads to allocate to flushing client data, Please note this will only take effect after a restart.	

Configuration Group/Property	Valid values	Description	Adv.
		Depending on the number of concurrent clients the latencies during load may be higher than expected	
PriorityQueueCount	2 to 10	Sets the number of queues to divide priority levels between, up to a maximum of 10 queues. It needs EnablePriorityMessaging to be enabled.	
PriorityReadSpinLockMaxConnections	0 to 8	Maximum number of clients allowed to allocate high priority spin locks. It needs EnablePriorityMessaging to be enabled.	
PriorityReadSpinLockTime	1 to 10000	Maximum number of clients allowed to allocate high priority spin locks. It needs EnablePriorityMessaging to be enabled.	Y
PriorityReadType	0 to 2	If enabled then high priority sessions will be enabled to run spin locks waiting to read. It needs EnablePriorityMessaging to be enabled.	
QueueHighWaterMark	100 to No Max	The number of events in a client output queue before the server stops sending events. A small number will cause undue work on the server. Default is 100.	
QueueLowWaterMark	50 to No Max	The number of events in the clients queue before the server resumes sending events. Must be less than the high water mark. Default is 50.	
ReadCount	1 to 20	Number of times the thread will loop around waiting for an event to be delivered before returning. Large values may cause read threads to be held for long periods of time, but avoid context switching for delivering events.	
UseDirectBuffering	True or False	If true the server will allocate DirectByteBuffer to use for network I/O, else the server will use HeapByteBuffer. The main difference is where the JVM will allocate memory	Y

Configuration Group/Property	Valid values	Description	Adv.
		for the buffers the <code>DirectByteBuffer</code> s perform better. For the best performance the <code>DirectByteBuffer</code> s are generally better.	
<code>WriteHandlerType</code>	1 to 5	Specifies the type of write handler to use	
<code>whEventThresholdCount</code>	1 to 2000	Number of events to exceed in the <code>whEventThresholdTime</code> to detect a peak. This number should be small enough to trigger peaks.	
<code>whEventThresholdTime</code>	1 to 2000	Number of milliseconds to sample the event rate to detect peaks	
<code>whMaxEventsBeforeFlush</code>	1 to 10000	Total number of events that can be sent before a flush must be done. If this number is too small then too many flushes will result.	
<code>whMaxEventsPerSecond</code>	No Min to No Max	Specifies the total number of events per second that a realm will send to clients before switching modes into peak mode. If this number is small then the server will go into peak mode too soon and latencies will start to increase.	
<code>whMaxTimeBetweenFlush</code>	1 to 1000	Total number of milliseconds to wait before a flush is done. If this number is too large then latencies will increase.	
<code>whPeakTrailDelay</code>	100 to 5000	When a peak is detected how long to stay in this state before returning to normal. If this is too large then latencies may be larger than expected.	
<b>Data Stream Config</b>			
<code>FanoutTaskQueueSize</code>	32 to 1024	Sets the number of tasks that the <code>FanOut Executor</code> will have outstanding. Large values will consume more memory on the server, as events are cached in the fanout task queue waiting to be written. Large values allow	

Configuration Group/Property	Valid values	Description	Adv.
		batching to occur, potentially increasing publish/subscriber performance.	
FanoutTraversalType	(Values as listed in next column)	<p>The method to use when traversing connections to write events:</p> <ul style="list-style-type: none"> <li>■ In Order. This will traverse connections in the order that they connected to the server (oldest first).</li> <li>■ Round Robin. This will determine the order of delivery in a pseudo-fair fashion (the first connection to be delivered to will become the last, the second will become the first etc.) .</li> <li>■ Reverse Order. This will traverse connections in reverse order (oldest last).</li> </ul> <p>The default is In Order.</p>	
MaxSessionIdSize	5 to 30	Maximum size of the session ID used to uniquely identify the clients. This is currently unused.	Y
MonitorTimer	1000 to 120000	Time interval in milliseconds to scan the data group configuration looking for idle / completed streams. Large values may cause idle and inactive datastreams to remain on datagroups for long periods of time. Small values may cause transient disconnections to trigger datagroup removals for datastreams - requiring them to be added back into the datagroup.	Y
OffloadMulticastWrite	True or False	If true then all multicast writes will be performed by the parallel fanout engine.	Y
ParallelFanoutThreshold	10 to 10000	Number of streams when the server will use parallel fanout. Small values reduce the amount of context switching of the fanout executor. Large values	Y

Configuration Group/Property	Valid values	Description	Adv.
		may result in less optimal fanout throughput.	
SendInitialMapping	True or False	When any stream registered client connect sends the entire DataGroup Name to ID mapping	Y
<b>DurableConfig</b>			
QueuedExtendedException	True or False	If <code>true</code> , then if the selector on a queued durable changes, the selector is added to the exception string.	Y
<b>Environment Config</b>			
AvailableProcessors	READ ONLY	Number of CPUs available	
Embedded	READ ONLY	If <code>true</code> , this specifies that the server is running as an embedded server	
InterRealmProtocolVersion	READ ONLY	Universal Messaging Server Inter-Realm Protocol Version	
JavaVendor	READ ONLY	Vendor of Java Virtual Machine	
JavaVersion	READ ONLY	Virtual Machine Version	
NanosecondSupport	READ ONLY	Nanosecond support available through JVM on Native OS	
OSArchitecture	READ ONLY	Operating System Architecture	
OSName	READ ONLY	Operating System Name	
OSVersion	READ ONLY	Operating System Version	
ProcessId	READ ONLY	Process ID	
ServerBuildDate	READ ONLY	Universal Messaging Server Build Date	

Configuration Group/Property	Valid values	Description	Adv.
ServerBuildNumber	READ ONLY	Universal Messaging Server Build Number	
ServerReleaseDetails	READ ONLY	Universal Messaging Release Details	
ServerVersion	READ ONLY	Universal Messaging Server Build Version	
TimerAdjustment	READ ONLY	The size of the Operating System's time quantum.	
<b>Event Storage</b>			
ActiveDelay	100 to No Max	The time in milliseconds that an active channel will delay between scans. The smaller the number, the more active the server. Default is 1000.	Y
AutoDeleteScan	1000 to 500000	Specifies the number of milliseconds between scans on AutoDelete stores to see if they should be deleted. The larger this time frame, the more AutoDelete stores will potentially not be deleted on the server.	
AutoMaintainOnFileLimit	True or False	Specifies whether the server will automatically perform maintenance on topic or queue stores when the MaintenanceFileSizeThreshold is reached. If false then the MaxFileSize will be ignored.	
AutoMaintainSystemStores	True or False	Specifies whether the server will automatically perform maintenance on internal system file stores	
AutoMaintenanceThreshold	0 to 100	Sets the percentage free before the server should run maintenance on the internal stores. It is by default 50. This means maintenance will be performed when 50% of the number of the events in the file are marked as dead – already consumed and acknowledged so they can be deleted. This is not applicable	

Configuration Group/Property	Valid values	Description	Adv.
		when <code>AutoMaintainOnFileLimit</code> is set to <code>true</code> .	
CacheAge	1000 to No Max	The length of time in ms that cached events will be kept in memory. The larger the value, the more memory will be utilized. Default is 86400000 ms, which is 24 hours.	Y
EnableBufferingKey	True or False	If set to <code>true</code> , the server will use memory mapped files for last EID buffering. This will improve performance for all event stores.	Y
EnableStoreCaching	True or False	If <code>true</code> the server will try to cache events in memory after they have been written/read. Please note the server will need to be rebooted for this to take effect.	
EnableStoreReadBuffering	True or False	If <code>true</code> the server will buffer the reads from the store. This will increase replay performance greatly. Please note the server will need to be rebooted for this to take effect.	Y
IdleDelay	5000 to No Max	The time in milliseconds that an idle channel will delay between scans. The smaller the number, the more active the server. Default is 60000.	Y
JMSEngineAutoPurgeTime	5000 to 600000	Defines the interval between clean up of events on a JMS Engine Resource. A large interval may result in topics with large numbers of events waiting to be purged.	Y
MaintenanceFileSizeThreshold	1024000	Sets the percentage free before the server should run maintenance on the internal stores. The smaller the file size - maintenance will be run more often. The bigger it is – maintenance may take longer time. There are no performance issues with a big file except on startup when the stores need to be reloaded. <code>AutoMaintainOnFileLimit</code> has to be set to <code>true</code> .	

Configuration Group/Property	Valid values	Description	Adv.
MaintenanceMemoryThreshold	1048576	Maximum size in memory for any topic or queue to reach before maintenance of the in-memory cache is run.	
PageSize	10 to 100000	The page size to use for the event store. This value sets the number of events/page.	
QueueDeliveryPersistencePolicy	(Values as listed in next column)	<p>Sets the Queue Delivery Persistence Policy. The policy is a combination of (a) making the disk storage location persistent, i.e. recoverable after a server restart, or non-persistent, i.e. erased at a server restart, and (b) writing events to the disk storage location synchronously or asynchronously.</p> <p>If you choose a policy that uses a non-persistent storage location, unacknowledged but delivered queue events will be stored elsewhere until they are acknowledged or rolled back.</p> <p>The available policies are:</p> <ul style="list-style-type: none"> <li>■ No persistent/No sync: The storage location is not persistent, and writing events to disk is asynchronous.</li> <li>■ Persistent/No sync: The storage location is persistent, and writing events to disk is asynchronous.</li> <li>■ Persistent/Sync: The storage location is persistent, and writing events to disk is synchronous.</li> </ul> <p>The default is Persistent/No sync. This is also the recommended value for production environments.</p>	Y
StoreReadBufferSize	1024 to 3000000	Size of the buffer to use during reads from the store. Note that the server will need to be restarted for this to take effect.	Y

Configuration Group/Property	Valid values	Description	Adv.
SyncBatchSize	1 to 1000	Specifies the maximum size before the sync call is made. The lower this value, the more sync calls made and the more overhead incurred.	Y
SyncServerFiles	True or False	If <code>true</code> the server will sync each file operation for its internal files. If <code>true</code> , this adds additional overhead to the server machines and can reduce overall performance.	
SyncTimeLimit	1 to 1000	Specifies the maximum time in milliseconds that will be allowed before the sync is called. The lower this value, the more file sync calls and the more overhead incurred.	Y
ThreadPoolSize	1 to 4	The number of threads allocated to perform the management task on the channels. The more channels a server has, the larger this number should be. Default is 1.	
<b>Fanout Values</b>			
ConnectionGrouping	true or False	If <code>true</code> allows the server to group connections with the same selector providing improved performance. This allows the server to optimize the way it processes events being delivered to the clients.  This requires a server restart to take effect.	Y
DelayPublishOnCapacity	True or False	Delays the publisher thread when the store capacity is exceeded. If this is not set, an exception is passed back to the client.	
HonourSharedDurableCapacity	True or False	If <code>true</code> , the channel will check any shared durables for capacity before accepting a published event. If any of these durables are over capacity, the server will respond as if the parent channel is over capacity. If <code>false</code> , the	Y

Configuration Group/Property	Valid values	Description	Adv.
		event will be published regardless of the number of events on its shared durables.	
IteratorWindowSize	1 to No Max	Specifies the number of events delivered to each Channel Iterator in a pre fetch. This allows the client to perform much faster by pre fetching events on fast moving topics requiring less client to server communication.  The default is 100.	
JMSQueueMaxMultiplier	1 to 10	The multiplier used on the High Water mark when processing events from a JMS Engine Queue/Topic. If this value is too high the server will consume vast amounts of memory.	Y
MaximumDelayInWrite	1 to 5000	The number of milliseconds an event will wait in a queue before it will be processed. If this number is too high then the first published event may take time to be delivered to the client.	Y
ParallelBatchSize	50 to 10000	Specifies the number of connections to process in one batch per parallel thread. If this number is small then there may be adverse overheads.	
ParallelThreadPoolSize	2 to 64	Specifies the number of threads to use within the thread pool. If this number is small then there may be adverse overheads. This value required a restart to take effect.	
ParallelThreshold	1 to 10000	Specifies the number of connections to a channel before the server will use the parallel fanout engine. If this number is small then there may be adverse overheads.	
ParallelUseGlobalPool	True or False	If <code>true</code> all channels use a common pool else all channel have there own pool. If this number is small then there may be adverse overheads. This value required a restart to take effect.	

Configuration Group/Property	Valid values	Description	Adv.
PeakPublishDelay	0 to No Max	When clients start to hit high water mark, this specifies how long to delay the publisher to allow the client time to catch up. If this is too small the publisher can overwhelm the server.	Y
PublishDelay	0 to No Max	How long to delay the publisher when the subscriber's queue start to fill, in milliseconds. If this number is 0 then no delay. Default is 10.	Y
PublishExpiredEvents	True or False	Specifies whether to publish expired events at server startup. Default is true.	
RoundRobinDelivery	True or False	Specifies whether to use a round robin approach for event delivery to the set of available event consumers. Default is false.	
SendEndOfChannelAlways	True or False	Specifies whether to always send an End Of Channel, even if we find no matches within the topic. If set, the subscriber will always be informed that the subscription request has completed the recovery of the topic.	
SendPubEventsImmediately	True or False	Specify whether to send publish events immediately. If true, then the server will send all publish events to clients immediately, if false the server is allowed to collect events before publishing.	
SyncQueueDelay	10 to 3600000	Maximum number of milliseconds the queue publisher will be delayed. This can be used to slow down the queue publishers.	
SyncQueuePublisher	True or False	If true then the queue publisher will be synchronized with the queue consumers. This allows flow control of queue publishers. If false then the value of SyncQueueDelay is not used.	
<b>Global Values</b>			

Configuration Group/Property	Valid values	Description	Adv.
AllowRealmAdminFullAccess	True or False	If true then any user with the full realm access will have access to all channels and queues.	Y
CacheJoinInfoKeys	True or False	If enabled we cache join key information between events passed over joins. This reduces the number of objects created. If this parameter is set to false then the server will create a new byte[] and string for each joined event.	Y
DisableExplicitGC	True or False	If enabled the server will call the Garbage Collector at regular intervals to keep memory usage down. If this is disabled then the garbage collection will be done solely by the JVM.	
EnableCaching	True or False	<p>If EnableCaching is set to true, the channel storage properties Cache On Reload and Enable Caching are set to the values specified by the client.</p> <p>If EnableCaching is set to false, then the channel storage properties Cache On Reload and Enable Caching are set to false, regardless of the values set by the client for these storage properties.</p> <p>The default for the global value EnableCaching is false.</p>	
EnableDNSLookups	True or False	If enabled the server will attempt to perform a DNS lookup when a client connects to resolve the IP address to a hostname. In some instances this may slow down the initial client connections.	
EnableWeakReferenceCleanup	True or False	If enabled then the server will hook into the JVM's garbage collection and release cached items when the JVM needs memory. By enabling this, the number of cached events stored will be reduced but memory will be maintained.	Y

Configuration Group/Property	Valid values	Description	Adv.
ExtendedMessageSelector	True or False	If <code>true</code> , allows the server to use the extended message selector syntax (enabling string to numeric conversions within the message selector). Default is <code>false</code> .	
HTTPCookieSize	14 to 100	The size in bytes to be used by nhp(s) cookies	Y
NHPScanTime	5000 to No Max	The number of milliseconds that the server will wait before scanning for client timeouts. Default is 5000, i.e. 5 seconds.	Y
NHPTimeout	2000 to No Max	The number of milliseconds the server will wait for client authentication. If this number is too large, the server may have unwanted connections. Default is 120000, i.e. 2 minutes.	Y
NanoDelayBase	10000 to 1000000	This number represents the number of nanoseconds in a millisecond. This is by definition 1000000, but changing the value can be used to increase or decrease the internal delays used by Universal Messaging. If too large, the response will slow down, and if too small, CPU usage increases.	Y
OverrideEveryoneUser	True or False	Override the <code>*@*</code> permission for channels / queues with explicit ACL entry permissions. Default is <code>false</code> .	
PauseServerPublishing	True or False	If <code>true</code> , the Pause Publishing feature is activated. Default is <code>false</code> .  This feature causes the server to block all attempts by clients to publish events, and such clients will receive an <code>nPublishPausedException</code> . However, events that already exist in the publishing client queues on the server continue to be consumed by the subscribing clients until the queues are emptied.	Y

Configuration Group/Property	Valid values	Description	Adv.
		You can use the Pause Publishing feature when it is necessary to clear the client event queues on the realm server. This could be, for example, before performing maintenance tasks such as increasing buffer storage or performing a backup, or before changing the server configuration.	
SendRealmSummaryStats	True or False	If <code>true</code> sends the realm's status summary updates every second. Default is <code>false</code> .	
ServerStateFlush	50 to 1000	Specifies the time in milliseconds between scans to save the server's state files. If this parameter is too large then data may be lost if power to the machine is lost.	Y
ServerTime	True or False	Allow the server to send the current time to the clients. Default is <code>true</code> .	
StampDictionary	True or False	Place Universal Messaging details into the dictionary, default is <code>false</code> . If <code>true</code> , adds additional overhead to the server/client.	
StampHost	True or False	Stamps the header with the publishing host ( <code>true/false</code> ). If <code>true</code> adds additional overhead to the server/client.	
StampTime	True or False	Stamps the header with the current time ( <code>true/false</code> ). If <code>true</code> , adds additional overhead to the server/client.	
StampTimeUseHPT	True or False	If this is set to <code>true</code> , then the server will use an accurate millisecond clock, if available, to stamp the dictionary. This may impact overall performance when delivering events when latency is important.	
StampTimeUseHPTScale	0 to 2	This has 3 values, <code>milli</code> , <code>micro</code> or <code>nano</code> accuracy	
StampUser	True or False	Stamps the header with the publishing user ( <code>true/false</code> ). If <code>true</code> , adds additional overhead to the server/client.	

Configuration Group/Property	Valid values	Description	Adv.
StatusBroadcast	2000 to No Max	<p>This property has two purposes:</p> <ul style="list-style-type: none"> <li>■ The number of milliseconds between status events being published to any clients using Admin API or Enterprise Manager. A small value increases the server load.</li> <li>■ The number of milliseconds between status messages being written to the server log, when periodic status logging has been activated via the <code>EnableStatusLog</code> property.</li> </ul> <p>Remember that if you change the value of this property, it will affect the time interval for both status events and status log intervals.</p> <p>The default is 5000, i.e. every 5 seconds.</p>	
StatusUpdateTime	2000 to No Max	<p>The number of milliseconds between status events being written to disk. Status events provide a history of the realm's state. A small value increases the server load. The default for this is <code>Long.MAX_VALUE</code>, i.e. never written to disk.</p>	
<b>Inter-Realm Comms Config</b>			
EstablishmentTime	10000 to 120000	Time for an inter-realm link to be initially established. This value should reflect the latency between nodes.	Y
KeepAliveInterval	1000 to 120000	Time interval where if nothing is sent a Keep Alive event is sent. This can be used to detect if remote members are still up and functioning.	Y
KeepAliveResetTime	10000 to 180000	If nothing has been received for this time the connection is deemed closed. This value must be larger than the <code>KeepAliveInterval</code> .	Y

Configuration Group/Property	Valid values	Description	Adv.
MaximumReconnectTime	1000 to 50000	The maximum number of milliseconds to wait before trying to re-establish a connection. If this value is too large, cluster formation will be delayed. The reconnect will be attempted at a random amount of time between <code>MinimumReconnectTime</code> and <code>MaximumReconnectTime</code> .	Y
MinimumReconnectTime	100 to 10000	The minimum time to wait before trying to re-establish a connection. If this number is too high then it may impact the network during outages. The reconnect will be attempted at a random amount of time between <code>MinimumReconnectTime</code> and <code>MaximumReconnectTime</code> .	Y
Timeout	60000 to 180000	If no events are received within this time limit, the link is assumed dead and will be closed. If this limit is less than the keep alive time then the link will be closed.	Y
WriteDelayOnFail	True or False	If true then all writes will be delayed until the link is reconnected or the timeout is reached.	Y
WriteDelayTimeout	1000 to 60000	The maximum time to wait on a write if the link has dropped. If a realm disconnects when we are able to write to it, we wait for a set amount of time for the link to come back before abandoning the write and resetting altogether. This insulates the cluster against some transitive network conditions.	Y
ZoneDefaultCanRecv	True or False	The default value that the interest manager will assign to <code>canRecv</code> when a new channel is created	Y
ZoneDefaultCanSend	True or False	The default value that the interest manager will assign to <code>canSend</code> when a new channel is created	Y

Configuration Group/Property	Valid values	Description	Adv.
<b>JVM Management</b>			
AutoThreadDumpOnExit	True or False	Defines if a thread dump is produced when the server exits.	
EmergencyThreshold	50 to 99	The memory threshold when the server starts to aggressively scan for objects to release. If this value is too large the server may run out of memory. Default is 94, i.e. 94%	
EnableJMX	True or False	Enable JMX beans within the server. If enabled the server will present JMX MBeans so it can be monitored by any JMX client.	
ExitOnDiskIOError	True or False	If <code>true</code> , the server will exit if it gets an I/O Exception. Setting this to <code>false</code> may result in lost events if the server runs out of disk space. Default is <code>true</code>	Y
ExitOnInterfaceFailure	True or False	If <code>true</code> and for any reason an interface cannot be started when the realm initializes, the realm will shut down.	Y
ExitOnMemoryError	True or False	If <code>true</code> , the server will exit if it gets an out of memory exception. Setting this to <code>false</code> may result in unstable behavior if the server runs out of memory. Default is <code>true</code> .	Y
IORetryCount	2 to 100	Number of times a file I/O operation will be attempted before aborting	Y
IOSleepTime	100 to 60000	Time between disk I/O operations if an I/O operation fails. If this time is large then the server may become unresponsive for this time.	Y
JMXRMIServerURLString	String	JNDI Lookup URL for the JMX Server to use.	
MemoryMonitoring	60 to 30000	Number of milliseconds between monitoring memory usage on the realm. If this value is too large then the realm will be slow to handle memory usage. Default is 2000.	

Configuration Group/Property	Valid values	Description	Adv.
ThrottleAllPublishersAtThreshold	True or False	Defines if publishers will be throttled back when the memory emergency threshold is reached.	Y
WarningThreshold	40 to 95	The memory threshold when the server starts to scan for objects to release. If this value is small then the server will release objects too soon, resulting in a lower performing realm. Default is 85, i.e. 85%.	
<b>Join Config</b>			
ActiveThreadPoolSize	1 to No Max	The number of threads to be assigned for the join recovery. Default is 2.	
IdleThreadPoolSize	1 to No Max	The number of threads to manage the idle and reconnection to remote servers. This number should be kept small. Default is 1.	
MaxEventsPerSchedule	1 to No Max	Number of events that will be sent to the remote server in one run. A low number will increase the time to recover the remote server, a large number will impact other joins which are also in recovery. Default is 50.	Y
MaxQueueSizeToUse	1 to No Max	The maximum events that will be queued on behalf of the remote server. A low number increases the time for the remote server to recover, a large number increases the memory used for this server. Default is 100.	Y
RemoteJoinAckBatchSize		Events received through remote joins are acknowledged in batches. This property configures the batch size.	Y
RemoteJoinAckInterval		In addition to the batch acknowledgment, remote join events get acknowledged every n milliseconds. This property configures this interval	Y
UseQueuedLocalJoinHandler	True or False	Specifies whether to use a queued join event handler. True will enable source	Y

Configuration Group/Property	Valid values	Description	Adv.
		channels and destination channels to be process events independently	
<b>Logging Config</b>			
DefaultLogSize	100 to No Max	The default size of the log in bytes	
DisplayCurrentThread	True or False	If enabled will display the current thread in the log message.	
DisplayPackageName	True or False	If enabled will display the package name of the logger this message originates from in the log message.	
EnableLog4J	True or False	If enabled will intercept log messages and pass to Log4J as well. This requires a restart before it will take effect.	
EmbedTag	True or False	Used to control if the message tag is displayed in log messages.	
EnableStatusLog	True or False	If <code>true</code> , periodic logging of the Universal Messaging server status is activated. The messages will be logged at time intervals given by the <code>StatusBroadcast</code> configuration property described in the <i>Global Values</i> section.  The default is <code>true</code> .	
LogManager	0 to 2	The Log manager to use.  0 = ROLLING_OLD, 1 = ROLLING_DATE, 2 = ROLLING_NUMBER	
RolledLogFileDepth	No Min to No Max	The number of log files to keep on disk when using log rolling. Oldest log files will be deleted when new files are created.	
customDebugTag	String	The tag to mark Debug log entries with.	
customErrorTag	String	The tag to mark Error log entries with.	
customFatalTag	String	The tag to mark Fatal log entries with.	

Configuration Group/Property	Valid values	Description	Adv.
customInfoTag	String	The tag to mark Info log entries with.	
customLogTag	String	The tag to mark Log entries with.	
customTraceTag	String	The tag to mark Trace log entries with.	
customWarnTag	String	The tag to mark Warn log entries with.	
fLoggerLevel	0 to 6	The server logging level, between 0 and 6, with 0 indicating very verbose, and 6 indicating very quiet. The more logging requested, the more overhead on the server. Default is 4.	
<b>Metric Config</b>			
EnableEventMemoryMonitoring	True or False	If this is set to <code>true</code> , the server will make available memory usage.	
EnableMetrics	True or False	If this is set to <code>true</code> , the server will make available system metrics (e.g. memory usage).	
<b>MQTT Config</b>			
Enable	True or False	If <code>true</code> the server will accept incoming MQTT connections. The default is <code>true</code> if this feature is enabled in the product licence.	
EnableAutoCreateTopics	True or False	If <code>true</code> the server will auto-generate Topics for MQTT clients for subscriptions and publishing. The default is <code>true</code> .	
EnforceAlphaNumericClientID	True or False	If <code>true</code> then the Client ID must consist solely of alphanumeric characters. The default is <code>false</code> .	
DisconnectOnSecurityException	True or False	If <code>true</code> and if a Publish request fails then the client will be disconnected. The default is <code>true</code> .	
IgnoreClientIDLength	True or False	If <code>true</code> then ignore the standard Client ID maximum length check of 23 characters. The default is <code>true</code> .	

Configuration Group/Property	Valid values	Description	Adv.
SessionStateTTL	0 to No Max	The number of milliseconds the state of a Client ID is kept between connections. The default value is set to 3 days. Setting this value to 0 will store the Client ID state until a clean session is received.	
Timeout	1000 to 60000	The number of milliseconds over the timeout value before the server will close the connection.	
SupportZeroLength	True or False	MQTT 3.1.1 allows the server to auto-generate the Client ID if it has zero length. The default is true.	
QoS0AsTransient	True or False	MQTT 3.1.1 allows the server to recover publish events with QoS greater than 0. By default Universal Messaging will recover all publish events. The default is false.	
Strict	True or False	To be compliant with MQTT, stores must use the JMS Engine. This flag enforces this check. The default is true.	
MaxOutstanding	100 to 64000	Sets the maximum number of events that the server will send before waiting for the client to acknowledge them (QoS:1 and above). The default is 64000.	
DisconnectClientsOnPublishFailure	True or False	Defines whether the server should disconnect clients to inform them that publishing has failed. The default is true.	
<b>Plugin Config</b>			
EnableAccessLog	True or False	Defines if plugin access log is produced	
EnableErrorLog	True or False	Defines if plugin error log is produced	
EnablePluginLog	True or False	Defines if plugin status log is produced	

Configuration Group/Property	Valid values	Description	Adv.
MaxNumberOfPluginThreads	10 to 10000	Maximum number of threads to allocate to the plugin manager	Y
PluginTimeout	1000 to 30000	Time in milliseconds that the plugin will read from a client. If too small, the plugin may not load all of the clients requests	Y
<b>Protobuf Config</b>			
CacheEventFilter	True or False	Hold the Protocol Buffer filter cache in memory. Default true	Y
FilterProtobufEvents	True or False	Allows the server to filter on Protocol Buffers. Default is true	
MaximumProtobufBuilders	1 to No Max	The maximum number of builders per descriptor file when using the global (non-channel) caches. Default 4	Y
MinimumProtobufBuilders	1 to 99	The minimum number of builders per descriptor file when using the global (non-channel) caches. Default 2	Y
ProtobufDescriptorsInputDir	String	The folder to search for Protocol Buffer descriptor files to parse incoming messages.	Y
ProtobufDescriptorsOutputDir	String	The folder for the server to put the combined Protocol Buffer descriptor file for serving out to clients.	Y
UpdateDescriptorsInterval	1000 to No Max	The time in milliseconds between checking the Protocol Buffer directory for updates. Default is 60000	Y
useChannelLevelProtobufCache	True or False	Setting this will alter how protobuf descriptors are cached. If set to true, use the channel-level protobuf cache. If set to false, the global-level cache will be used. The server must be restarted for this to take effect.	
<b>Protocol AMQP Config</b>			

Configuration Group/Property	Valid values	Description	Adv.
AllowUserTransformation	No Min to No Max	Will load a user class for event transformation.	Y
AnonymousUser	String	The user name to use for anonymous users	
BufferSize	1000 to 60000	The size of the buffer that will be used to read/write on the AMQP connection	
DefaultNodeMode	0 to 1	The type of node if it is not able to detect it. 0=Queue, 1=Topic	
Enable	0 to No Max	If true the server will accept incoming AMQP connections	
EnableWriteThread	True or False	Enables the off loading of the physical write to a thread pool	Y
EngineLoopCount	4 to 100	How many times the AMQP state engine will cycle per thread pool allocation	Y
MaxFrameSize	10000 to No Max	Maximum size of an AMQP frame	Y
MaxThreadPoolSize	2 to 100	Largest number of threads the pool can have.	
MinThreadPoolSize	1 to 10	Smallest number of threads for the dedicated AMQP thread pool	
QueuePrefix	String	The address prefix for specifying topic nodes as required by some clients	
SASL_Anonymous	True or False	Enable Anonymous SASL	
SASL_CRAM-MD5	True or False	Enable CRAM-MD5 SASL	
SASL_DIGEST-MD5	True or False	Enable DIGEST-MD5 SASL	
SASL_Plain	True or False	Enable Plain SASL	

Configuration Group/Property	Valid values	Description	Adv.
SubscriberCredit	100 to No Max	Sets the subscriber (receiver) credit	
Timeout	10000 to 300000	Sets the network timeout	Y
TopicPrefix	String	The address prefix for specifying topic nodes as required by some clients	
TransformToUse	0 to 4	Selects the type of transformation to use from AMQP style events to native UM events.  0 - No transformation, 1 - Basic Transformation, 2 - Complete Transformation, 3 - User Configurable	
<b>Protocol MQTT Config</b>			
Enable	True or False	If true the server will accept incoming MQTT connections	
EnableAutoCreateTopics	True or False	If true the server will auto generate Topics for MQTT clients for subscriptions and publishing	
IgnoreClientIDLength	True or False	If set to true ignore the standard clientID maximum length check of 24 characters	
MaxBufferSize	10000 to 100 000 000	Sets the maximum buffer size that the MQTT client can send	Y
SessionStateTTL	0 to No Max	The number of milliseconds the state of a clientID is kept between connections. The default value is 3 days. Setting this value to 0 will store the clientID state until a clean session is received.	Y
Timeout	1000 to 60000	The number of milliseconds over the timeout value before the server will close the connection	Y
<b>Proxy Forward Config</b>			

Configuration Group/Property	Valid values	Description	Adv.
BufferSize	1024 to 20480	The size of the buffer to use for the proxied events. If this value is small then there will be additional network traffic dealing with small packets.	Y
FlushTimeout	10000 to 120000	Time to wait for a flush to complete. If this value is too large it may delay other clients from flushing the data.	Y
<b>RecoveryDaemon</b>			
EventsPerBlock	1 to No Max	The number of events to send in one block to a recovering connection. Small values may slow down the overall speed of recovery, however large values may saturate the recovery thread and keep it busy from performing recovery tasks for other stores and connections.	Y
ThreadPool	1 to No Max	Number of threads to use for client recovery	
<b>Server Protection</b>			
EnableFlowControl	True or False	Enables flow control of producer connections. Default is false.	
FlowControlWaitTimeOne	0 to 120000	The time in milliseconds to hold a producing connection before processing its events. This is the longest level of waiting.	Y
FlowControlWaitTimeTwo	0 to 120000	The time in milliseconds to hold a producing connection before processing its events. This is the second level of waiting.	Y
FlowControlWaitTimeThree	0 to 120000	The time in milliseconds to hold a producing connection before processing its events. This is the first level of waiting and the shortest wait time.	Y
<b>Thread Pool Config</b>			

Configuration Group/Property	Valid values	Description	Adv.
CommonPoolThreadSize	5 to 1000	Maximum number of threads to allocate to the common thread pool	
ConnectionThreadPoolMaxSize	10 to No Max	The maximum number of threads allocated to establish client connections. If this number is too small then connections may be left waiting for a thread to process it.	
ConnectionThreadPoolMinSize	4 to 100	The minimum number of threads allocated to establish client connections. If too large then the server will have many idle threads.	
ConnectionThreadWaitTime	10000 to 300000	The time for the thread to wait for the client to finalize the connection. If too low then slow linked clients may not be able to establish a connection.	Y
EnableConnectionThreadPooling	True or False	If true then if NIO is available it will be available for interfaces to use it and then all reads/writes will be done via the Read/Write thread pools. If NIO is not available then a limited used write thread pool is used. This requires a realm restart before it takes effect.	Y
MultiplexReadThreadPoolMaxSize	4 to No Max	The maximum number of threads to allocate to the multiplex thread pool to read multiplex sessions. Default is 100.	
MultiplexReadThreadPoolMinSize	4 to No Max	The minimum number of threads to allocate to the multiplex thread pool to read multiplex sessions. Default is 4.	
MaxUnauthorisedCount	10 to 10000	The maximum outstanding unauthorized connections per hostname (or IP address if host name is unavailable)	Y
PendingTaskWarningThreshold	100 to 100000	The threshold at which the server starts to warn about the number of pending tasks. When the number of pending tasks is below the threshold, but over 100, the server logs a WARNING message. When the number is above the threshold, the server logs an	Y

Configuration Group/Property	Valid values	Description	Adv.
		ERROR message. When the server does not find available threads, it logs a message that the thread pool is exhausted. Default is 1000.	
ReadThreadPoolMaxSize	4 to No Max	The maximum number of threads that will be allocated to the read pool. If NIO is not available this should be set to the maximum number of clients that are expected to connect. If NIO is available then it's best to keep this number under 20.	
ReadThreadPoolMinSize	4 to No Max	This is the number of threads that will always be present in the read thread pool. If this is too small then the thread pool will be requesting new threads from the idle queue more often. If too large then the server will have many idle threads.	
SchedulerPoolSize	10 to 100	The number of threads assigned to the scheduler, default is 10.	
SlowTaskWarningTime	1000 to 30000	The time in milliseconds before reporting a slow-running task. The server logs the information at the WARNING log level and generates a thread dump. Default is 5000.	Y
StalledTaskWarningTime	10000 to 60000	The time in milliseconds before reporting a stalled task. The system writes the information at the WARNING log level and generates a thread dump. When you change this configuration, the thread pool monitor interval is updated to monitor at the same time interval as the value you specify for this property. Default is 60000.	Y
ThreadDumpInterval	1000 to 600000	The interval in milliseconds at which a thread dump is generated when the system reports slow or stalled tasks, or when the number of pending tasks exceeds the value of PendingTaskWarningThreshold. The	Y

Configuration Group/Property	Valid values	Description	Adv.
		thread dump interval applies across all thread pools in the JVM instance. Default is 60000.	
ThreadDumpOnSlowTask	True or False	Whether to generate a thread dump when the system reports a slow task. Default is false.	Y
ThreadIdleQueueSize	5 to 50	When threads are released from various pools since they no longer need them they end up in the idle queue. If this idle queue exceeds this number the threads are destroyed. Specify this number to be large enough to accommodate enough idle threads, so that if any thread pool requires to expand then it can be reused. If the number is too large then the server may have many idle threads.	
WriteThreadPoolMaxSize	5 to No Max	The maximum number of threads that will be allocated to the write pool. If NIO is not available this should be set to the maximum number of clients that are expected to connect. If NIO is available then it's best to keep this number under 20.	
WriteThreadPoolMinSize	5 to No Max	This is the number of threads that will always be present in the write thread pool. If this is too small then the thread pool will be requesting new threads from the idle queue more often. If too large then the server may have many idle threads.	
<b>TransactionManager</b>			
MaxEventsPerTransaction	0 to No Max	The maximum number of events per transaction, a 0 indicates no limit.	
MaxTransactionTime	1000 to No Max	Time in milliseconds that a transaction will be kept active. A large number will cause the server to retain these transactions in memory.	

Configuration Group/Property	Valid values	Description	Adv.
TTLThreshold	1000 to 60000	The minimum time in milliseconds, below which the server will not store the Transaction ID.	Y

Double-clicking on the property you wish to modify in the configuration group will provide you with a dialog window where the new value can be entered. The values of configuration properties will be validated to check whether they are within the correct range of values. If you enter an incorrect value you will be notified.

## Zone Administration

### Overview of Zone Administration


The Enterprise Manager provides menu items for performing the administrative functions on zones. In a zone, messages that are published to a channel on one realm are automatically forwarded to a channel of the same name on other realms in the zone.

**Note:**

Messages on queues are not forwarded between realms in a zone; the zone functionality applies only to channels.

For general information about using zones, refer to the *Architecture* section of the *Universal Messaging Concepts* guide.

Zone administrative functionality is offered in the Enterprise Manager menu bar and in the navigation tree:



The **Zone** tab in the menu bar allows you to perform operations on zones, such as creating and deleting zones.

The **Zones** node in the navigation tree is the parent node of any zones you create.

The zone administration operations that you can perform are described in the following sections.

## Creating a Zone

To create a zone and define it with an initial set of realms or clusters, proceed as follows:

1. Open the dialog for creating a zone.

You can do this in one of the following ways:

- In the Menu bar, select **Zone > Create Zone**, or
- In the navigation tree, select the Zones node, and from the context menu choose **Create Zone**.

2. In the dialog, specify a name that will be assigned to the zone.
3. Add realms or clusters to the zone.

If you select the radio button for realms, you see all of the realms that you can add to the zone. If you select the radio button for clusters, you see all of the clusters that you can add to the zone.

Specify the realms or clusters you want to add to the zone, then click **Add**.

4. Click **OK** to create the zone and close the dialog.

The newly created zone is now displayed under the **Zones** node in the navigation tree.

If you expand the node of the new zone, you will see the realms that belong to the zone.

**Note:**

1. A zone can contain either realms or clusters, but not a mixture of realms and clusters.
2. A zone cannot be empty; it must contain at least one realm or cluster.

### **Modifying the set of realms or clusters in a zone**

To modify the set of realms or clusters in a zone, proceed as follows:

1. Under the **Zones** node in the navigation tree, select the node representing the required zone. In the context menu, select **Modify Zone Members**.

This displays the realms/clusters that are currently members of the zone, and also the realms/clusters that are currently not members but which are available to become members.

2. As required, add realms/clusters to the zone's existing members, or remove existing members.
3. Click **OK** to save the modified zone and close the dialog.

### **Deleting a zone**

To delete a zone, proceed as follows:

1. Select the **Zones** node in the navigation tree, then in the context menu, select **Delete Zone**.  
Alternatively, select **Zone > Delete Zone** from the menu bar.
2. Select the required zone from the displayed list and click **OK** to delete the zone.

### **Creating a channel in a zone**

You can create a channel for a zone, and the channel will be automatically created on all realms/clusters in the zone.

To create a channel in a zone, proceed as follows:

1. Select the node for the zone in the navigation pane. Then, in the context menu of the node, select **Create Channel**.
2. In the **Add Channel** dialog, specify the attributes of the channel that you wish to create.
3. Click **OK** to complete the dialog and create the channel.

The Enterprise Manager now creates the channel on all realms or channels in the zone.

## Modifying a channel in a zone

If you wish to modify the attributes of a channel that was created in a zone via **Create Channel**, you must modify the attributes for the channel in each of the zone members (realms, clusters) individually.

### Note:

Any changes you make to the channel definition for a realm/cluster in a zone are NOT propagated automatically to the other zone members. If you wish to keep all zone members in sync, you have to update the other zone members individually.

To modify a channel on one realm/cluster in a zone, proceed as follows:

1. Select the node for the channel under the node for the realm/cluster on which the channel is defined.
2. In the context menu of the channel, select **Edit Channel**.
3. In the **Modify Channel** dialog, make your changes and click **OK** to complete the dialog.

## General notes on using zones

This section summarizes some operational aspects of using zones.

- If a zone member (a realm or cluster) is not active (e.g. the server is down), no Enterprise Manager operations will be allowed on the zone until all zone members are available again.
- Any given realm or cluster cannot be a member of more than one zone at the same time.

## Cluster Administration

This section describes the process of creating a Universal Messaging cluster. Universal Messaging Clusters enables the replication of resources across the cluster. The state of a clustered resource is maintained across all realms within the cluster. For example if an event is popped from a clustered queue it is popped from all nodes within the cluster.

Creating a cluster of Universal Messaging realms ensures that applications either publishing / subscribing to channels, or pushing / popping events from queues can connect to any of the realms and view the same state. If one of the realms in the cluster is unavailable client applications can automatically reconnect to any of the other cluster realms and carry on from where they were.

For more information on how to use the Enterprise Manager to manage Universal Messaging Clusters please see:

- [“Creating Realm Clusters” on page 74](#)
- [“Deleting Realm Clusters” on page 78](#)
- [“Modifying Cluster Members” on page 80](#)
- [“Creating Cluster Channels” on page 82](#)

- [“Creating Cluster Queues” on page 87](#)
- [“Viewing and Monitoring Cluster Information” on page 91](#)
- [“Manage Inter-Cluster Connections” on page 93](#)

For more information on how to use the Enterprise Manager to manage Universal Messaging Clusters with Sites please see:

- [“Creating and Managing Clusters with Sites” on page 96](#)

## Creating a Cluster

This section describes the process of creating a Universal Messaging Cluster. Clusters allow a group of Universal Messaging Realm Servers to replicate resources between them, and to maintain the state for those objects across all realms within the cluster.

Creating a cluster of Universal Messaging realms ensures that applications which publish/subscribe to channels, or which push/pop events from queues, can connect to *any* of the realms and view the same state. If one of the realms in the cluster is unavailable, client applications can automatically reconnect to any of the other cluster realms and carry on from where they were.

*Universal Messaging’s clustering technology provides an unsurpassed level of reliability.* Client applications can seamlessly switch between any cluster realm if any problems - such as network or hardware failures - occur with the realm to which they are connected. This also provides an exceptional ability to load balance clients between realm servers.

### Tip:

Since the underlying purpose of a cluster is to provide resilience and high availability, we advise against running all the servers in a cluster on a single physical or virtual machine in a production environment.

### Important:

The Enterprise Manager does not support working with two clusters that have the same name.

## Viewing Clusters in Enterprise Manager

The Enterprise Manager's top level view shows a tree node labelled "Universal Messaging Enterprise" (see [“Enterprise Summary” on page 310](#)). One level below this is a tree node labelled "Clusters", which contains any known clusters.

If you use the Enterprise Manager to connect to a realm which is a member of an existing cluster, then the cluster will automatically be displayed under the above-mentioned "Clusters" tree node. When a cluster node is found, the Enterprise Manager will also automatically connect to all of the cluster member realms (if not already connected by default as a result of having loaded realm connection information in a custom Enterprise Manager Connection Profile). See [“Connecting to Multiple Realms” on page 16](#) for related information.

## Preparing to Create a Cluster

Firstly, before a cluster can be created, the Enterprise Manager needs to connect to those realms (see [“Connecting to Multiple Realms” on page 16](#)) that will form the cluster. If any realms cannot be connected to, or you receive a 'Security Alert' message when you click on the realm node, you may want to check that the realm is running, and check the permissions (see [“Realm Entitlements” on page 161](#)) on the realm. If the realms you are connecting to are running on different machines, you need to ensure that all realm machines are given full permissions to connect to the other realms in the cluster. Each realm communicates with the other cluster realms via its own connection. The subject of each connection is as follows:

```
realm-realmname@ip_address
```


For example, in the following example, there are 3 realms that will form part of a cluster, each realm subject needs to exist in the ACLs of the other realms. The following realm subjects need to be added to the ACL for each realm in our example:

```
realm-realm1@10.140.1.1 realm-realm2@10.140.1.2 realm-realm3@10.140.1.3
```


The permissions given for each realm need to be 'Access Realm'. As well as this, each realm must have a valid entry for the user@host that corresponds to the user that will create the cluster using the Enterprise Manager. The permissions for this user must be sufficient in order to create the cluster object. Temporarily it is often better to provide the `*@*` default subject 'Full' privileges to facilitate setting up a realm and clusters.

## Creating a cluster

If you select the 'Clusters' node under the 'Universal Messaging Enterprise' node, you will be shown a pop up menu with a number of options. One of the options is to create a cluster. The image below shows this menu option as described.



When you select the 'Create Cluster' menu option, you are presented with the cluster dialog. The cluster dialog allows you to select which of the realms that the Enterprise Manager is connected to will become members of the cluster. One of the selected realms will become the master during the cluster creation. The master realm will control synchronizing the state between the other realms, and acts as the authoritative source for this information.



The cluster dialog contains a text box for you to input the name of the cluster. Below the name are the details of the cluster members. The available realms are shown on the left hand side of the dialog. The right hand side shows those realms that are members. When you double-click on a realm name in the **Available Realms** list, or click on a realm name and click on the **Add** button, the realm will be added to the **Cluster Members** list. You can remove any realm from the **Cluster Members** list by either double clicking on the realm from the list or by selecting the realm name, and clicking on the **Remove** Button.


When you have finished selecting your cluster members, clicking on the 'OK' button presents you with the local store migration dialog. This dialog allows you to select whether to migrate local stores to cluster-wide stores. Selecting the **Yes** button will convert any local stores (channels, queues, etc.) on the realms being added to the cluster into cluster-wide stores. These stores will then be present on all realms in the cluster when cluster creation completes. If the name of a local store is the same as the name of an existing cluster store, clicking the **Yes** button will cause the cluster creation to fail due to a name clash. Clicking the **No** button will keep these stores local to the realms, and they will not be present on other realms in the cluster when creation is completed.

If the cluster creation is successful, a new cluster node will appear under the **Clusters** node, and the realms that have been selected as members will be shown beneath the cluster.

### Checking the cluster state

When a cluster has been created, you can monitor its state by selecting the cluster node. The 'Cluster Summary' tab will show the state of all cluster members, and which realm is current cluster master.

The image below shows the state of a cluster when it has been created and all realms within the cluster are fully online.




Name	State	Master	realm1	realm3	realm2
realm1	Master	realm1	Local	OnLine	OnLine
realm2	Slave	realm1	OnLine	OnLine	Local
realm3	Slave	realm1	OnLine	Local	OnLine

Creating cluster channels (see [“Cluster Channel Administration” on page 82](#)) and cluster queues (see [“Cluster Queue Administration” on page 87](#)) is not permitted if any of the cluster realms are offline.


## Deleting Clusters

When a Universal Messaging cluster needs to be deleted, all cluster resources that exist in all cluster member realms will also be deleted. Removal of a cluster is a simple operation that can be achieved using the Enterprise Manager. This section will describe the process of removing a cluster.

In order to remove a Universal Messaging Realm cluster, you must first of all select the 'Clusters' node from the Enterprise Manager. Right-clicking on this node will present a pop up menu, as shown in the image below.



Selecting the menu option 'Delete Cluster' will prompt you with a dialog that asks you to select a cluster node from a list. This list will contain all known clusters within the realms you have connected to. This dialog is shown in the image below.




Clicking on the 'OK' button once you have selected the cluster you wish to delete will prompt you to answer a question. This question gives you 2 choices with regard to the cluster resources that may exist within the cluster. These are:

- Delete all cluster wide resources from each cluster realm
- Convert all cluster wide resources to local within each realm

Choosing to delete all cluster resources will not remove any locally created channels, only those created for the cluster.

Choosing to convert each one to local, will keep any data that may be contained with the resources .

This dialog is shown in the image below. Choosing 'Yes' will remove the cluster objects, 'No' will make them all local, 'Cancel' will take no action at all.



## Modifying Clusters

The Universal Messaging Enterprise Manager enables you to modify clusters. By 'Modify' we mean adding new realms to the cluster or removing existing cluster members.


To add a new realm to a cluster, you must first of all ensure that you have connected to (see [“Connecting to Multiple Realms” on page 16](#)) the realm you wish to add. Removing realms is accomplished by selecting the realm you wish to remove from the cluster. This will be discussed in more detail further on.

If for example, you have a cluster with two realms, and wish to add a third realm to the cluster, it is possible to do so. Similarly, if you have a cluster with three (or any number of realms) and wish to remove a realm from the cluster, this is also possible.

## Adding Cluster Members

In order to add a realm to a cluster, you must first ensure that you have created a cluster (see [“Creating a Cluster” on page 74](#)). Once you have a cluster, then also ensure you have connected to (see [“Connecting to Multiple Realms” on page 16](#)) the realm you wish to add to your cluster. Select the cluster node from the namespace and right-click on the node. This will present you with a pop-up menu. Select the menu item labelled 'Modify Cluster Members'.

The dialog this presents you displays the current members of your cluster as well as any realms you are not connected to that are not cluster members. This dialog is shown below:



The dialog shows the name of the cluster, a list of realms which are not currently members of the cluster (shown as a list on the left hand side), and a list of current cluster members (on the right hand side).

As you can see from the above example, currently there are three realms within the cluster 'TestCluster'.

Double-clicking on any non-member realm, or selecting it from the list and clicking the 'Add' button will enable you to add the realm as a member.

### Note:

If the realm has local stores with names matching any store on the cluster, the realm will not be added to the cluster. This is to prevent naming clashes on the cluster.

When you have added the realms you wish to add as cluster members, click on the button labelled 'OK'. This will add all realms in the right-hand list to the cluster. All cluster resources will also be created on the newly added realms once the realms have successfully been added to the cluster.

## Removing Cluster Members

Removing cluster realms is achieved by again selecting the cluster node, right-clicking on the node and choosing the 'Modify Cluster Members' menu item. This presents the same dialog as shown above.

To remove a realm, double-click on the realm from the 'Cluster Members' list or select the realm and click the 'Remove' button. This will remove the realm from the list and add it back into the non-members list.

Clicking on the button labelled 'OK' will then prompt you to answer a question. This question allows you to select one of 2 options:

- Delete all cluster wide resources from each the removed realm members
- Convert all cluster wide resources to local within the removed realm members

Choosing to delete all cluster resources will not remove any locally created channels, only those created for the cluster within the realms you are removing.

Choosing to convert each one to local, will keep any data that may be contained within the cluster resources for the realms you wish to remove.

## Adding and Removing Cluster Members

Cluster members can be added and removed in the same operation. For example, if you have a cluster with 'realm1' and 'realm2' but want to remove 'realm2' and add 'realm3', you would simply remove 'realm2' and add 'realm3' from the 'Cluster Members' list in the 'Modify Cluster' dialog. The Enterprise Manager will work out which realms to add and which to remove for you and perform the necessary channel conversion and deletions you choose.

## Cluster Channel Administration

This section describes the process of creating channels on a Universal Messaging Realm cluster. Channels are the logical rendezvous point for data that is published and subscribed. Each channel that is created consists of a physical object within each Universal Messaging realm within the cluster as well as its logical reference within each realm's namespace.

### Note:

Simple and Transient channels are not supported across realms in a cluster.

Creating channels using the Enterprise Manager creates the physical object within each cluster realm. Once created, references to the cluster channels can be obtained using the Universal


Messaging Client and Admin APIs, as you would with normal channels that are not cluster wide channels. Clustered channels can also be monitored and managed using the Enterprise Manager.

When you connect to a Universal Messaging realm in the Enterprise Manager, all resources and services found within each realm's namespace are displayed in a tree structure under each realm node. Each cluster node also displays the member realms that make up the cluster.

## **Creating Cluster Channels**

To create new cluster channels, you must first create a cluster if one does not already exist.

Secondly, in order to create a cluster channel, you must select the cluster node from the namespace tree where the channel will be created. For example, if there is a cluster called 'TestCluster', which contains 3 realms called 'realm1', 'realm2' and 'realm3' and you want to create a channel called '/eur/gbp' within that cluster of realms, you would need to first of all click on the cluster node called 'TestCluster'. Then, by right-clicking on cluster node a pop-up menu will be displayed that shows a number of menu items (as shown in the image below).



By clicking on the menu item 'Create Cluster Channel', you will be prompted with a dialog box that allows you to enter the details of the cluster channel you wish to create. Cluster channels have exactly the same set of attributes assigned to them as normal channels when they are created.

The create channel dialog for cluster channels allows you to input values for each of these attributes. The only difference is that the channel will be created across all of the realms within the cluster

and the same state will be maintained between all instances of that channel by the cluster realms. This means, for example, that if an event is published to a clustered channel it becomes available on all clusters simultaneously.

In order to create a Mixed cluster channel called '/eur/gbp' the following settings would be configured:

The screenshot shows a dialog box titled "Add channel to cluster TestCluster". It is divided into two main sections: "Channel Attributes" and "Channel Keys".

**Channel Attributes:**


- Channel Name: /eur/gbp
- Channel Type: Mixed
- Channel TTL: (empty)
- Channel Capacity: (empty)
- Parent Realm: realm1
- Dead Event Store: (empty)
- Use JMS Engine:
- Use Merge Engine:
- Storage Properties: (empty) with an "Edit..." button.

**Channel Keys:**

- Select Key To Edit: (empty) with a "New" button.
- Key Properties:**
  - Key Name: (empty)
  - Depth: 1 (with a spinner control) with "Save" and "Delete" buttons.

At the bottom of the dialog are "OK" and "Cancel" buttons.

Clicking on the 'OK' button will create the channel '/eur/gbp' across all realms within the cluster 'TestCluster' and render the channel object in the namespace tree of the Enterprise Manager. The image below shows how the namespace tree looks after the cluster channel has been created, fully expanded.



As you can see from the image above, each realm node now contains the the channel node in its namespace tree under a folder (which we call a container node) called '/eur'. The icon used for a cluster channel is different to that of normal channel and is denoted by the small letter 'c' in the icon, whereas the normal channel icon does not contain the 'c'.

## Cluster Queue Administration

This section describes the process of creating queues on a cluster of Universal Messaging realm servers. Each cluster queue that is created consists of a physical object within each Universal Messaging realm within the cluster as well as its logical reference within each realm's namespace.

### Note:

Simple and Transient queues are not supported across realms in a cluster.


Creating queues using the Enterprise Manager creates the physical object within each cluster realm. Once created, references to the cluster queues can be obtained using the Universal Messaging Client and Admin APIs, as you would with normal queues that are not cluster wide queues. Clustered queues can also be monitored and managed using the Enterprise Manager.

When you connect to a Universal Messaging realm in the Enterprise Manager, all resources and services found within each realm's namespace are displayed in a tree structure under each realm node. Each cluster node also displays the member realms that make up the cluster.

## Creating Cluster Queues

To create new cluster queues, you must first create a cluster (see [“Creating a Cluster” on page 74](#)) if you have not already done so.

Secondly, in order to create a cluster queue, you must select the cluster node from the namespace tree where the queue will be created. For example, if i have a cluster called 'TestCluster', which contains 3 realms called 'realm1', 'realm2' and 'realm3' and i want to create a queue called /eur/orders within that cluster of realms, i would need to first of all click on the cluster node called 'TestCluster'. Then, by right-clicking on cluster node a pop-up menu will be displayed that shows a number of menu items (as shown in the image below).




By clicking on the menu item 'Create Cluster Queue', you will be prompted with a dialog box that allows you to enter the details of the cluster queue you wish to create.


Cluster queues have exactly the same set of attributes assigned to them as normal queues when they are created. The create queue dialog for cluster queues allows you to input values for each of these attributes. The only difference will be that the queue will be created across all of the realms

within the cluster and the same state will be maintained between all instances of that queue by the cluster realms.

In order to create a cluster queue called '/eur/orders' attributes you would add the attributes as shown below:



Clicking on the 'OK' button will create the queue '/eur/orders' across all realms within the cluster 'TestCluster' and render the queue object in the namespace tree of the Enterprise Manager, both under each realm under each realm in the cluster as well as each realm underneath the realms container node. The image below shows how the namespace tree looks after the cluster queue has been created, fully expanded.



As you can see from the image above, each realm node now contains the the queue node in its namespace tree under a folder (which we call a container node) called '/eur'. The icon used for a cluster queue is different to that of normal queue and is denoted by a 'c' in the icon, whereas the normal queue icon does not have a 'c'. queue.


## Viewing Cluster Information

The Enterprise Manager provides Cluster information through the following four tabs:

- Cluster Summary
- Connections
- Logfile
- Sites

### Cluster Summary

The Cluster Summary tab provides an overview of all realms in the Cluster. It identifies the current Master realm, and also shows each realm's perception of the state of all other realms.




Name	State	Master	realm1	realm3	realm2
realm1	Master	realm1	Local	OnLine	OnLine
realm2	Slave	realm1	OnLine	OnLine	Local
realm3	Slave	realm1	OnLine	Local	OnLine

The Cluster Summary Tab.

### Connections

The Connections tab shows all connections to realms in the Cluster. In this example, it shows a single user connected to three realms in the Cluster:




realm	protocol	user	host	connection
realm1	nsp	administrator	127.0.0.1	127.0.0.1:50471
realm2	nsp	administrator	127.0.0.1	127.0.0.1:50474
realm3	nsp	administrator	127.0.0.1	127.0.0.1:50535

## The Cluster Connections Tab.

### Remote Cluster Connections


The Remote Cluster Connections tab shows all remote cluster connections for this Cluster. Clusters can be remotely connected together providing the ability to create joins between channels in different clusters:



## The Remote Cluster Connections Tab.

### Logfile


The Logfile tab shows a real-time Cluster-specific log, and provides the option to stream the log output to a file:



## The Cluster Logfile Tab.

### Sites

The Sites tab shows any site configurations (see [“Creating and Managing Clusters with Sites”](#) on [page 96](#)) for the current cluster. Clusters that have Site configurations are known as *Universal Messaging Clusters with Sites*. (Those without are known as *Universal Messaging Clusters*):




**The Cluster Sites Tab.**


## **Manage Inter-Cluster Connections**

### **Creating Inter-Cluster Connections**

Inter cluster connections can be created through the Enterprise Manager. To do this, firstly connect to a realm in each cluster. Then, once both clusters are displayed in the Enterprise Manager, click on the "Inter-Cluster Connections" tab under one of the cluster panels.



Next, select "Add" and choose the remote cluster from the dropdown list in the popup dialog which will now appear:




The inter-cluster connections should now be established, and inter-cluster joins can now be formed through the Enterprise Manager or programmatically.

**Note:**

For a description of the general principles involved in creating channel joins, see the section *Creating Channel Joins*. The description details the usage based on the Enterprise Manager, but the same general principles apply if you are using the API.

## Deleting Inter-Cluster Connections

To delete an inter-cluster connection, simply select the connection from the list and click "Delete".




## Creating and Managing Clusters with Sites

This section describes the process of modifying a Universal Messaging Cluster into a *Universal Messaging Cluster with Sites*. Clusters with Sites allow a standard Universal Messaging cluster to operate with as little as 50% of the active cluster members (as opposed to the standard 51% quorum in effect for clusters without sites), and provides administrators with a mechanism to prevent the split brain scenario that would otherwise be introduced when using exactly half of a cluster's realms.

## Viewing Site Information in Enterprise Manager

The Enterprise Manager's top level view shows a tree node labelled "Universal Messaging Enterprise" (see "[Enterprise Summary](#)" on page 310). One level below this is a tree node labelled "Clusters", which contains any known clusters.


After creating your cluster (see "[Creating a Cluster](#)" on page 74) and selecting the cluster's icon in the Enterprise Manager, click the *Sites* tab:




*Sites Tab in Cluster View. No Sites have yet been created for the above cluster.*

## Creating a Primary Site for a Cluster

Click the *New* button to create the first site. We'll assume the site is named *Production*. Follow the prompts and pick a Realm to include in the site, for example realm1:




**Creation of a "Production" Site.**



### Addition of an Initial Member to "Production" Site.

At this point, the new site will appear in the Sites tab:




*The "Production" Site with its initial member realm is shown.*


Note that the table will contain a column for all realms in the cluster. In this example we have only added one realm to the Production site. Checking and unchecking the appropriate checkboxes will add or remove clustered realms from the corresponding sites.

### Creating a Backup Site for a Cluster

Next, follow the same steps to create the second site, which in this example we shall assume is named : **Disaster Recovery**




Creation of a "Disaster Recovery" Site and addition of an initial site member realm.



Addition of an Initial Member to "Disaster Recovery" Site.

The new Disaster Recovery site will now also appear in the Sites tab:




Sites Tab in Cluster View. The "Production" and "Disaster Recovery" Sites are both shown.

## Setting a Site's IsPrime Flag

Administrators use a site's *isPrime* flag to determine the site that will contain a cluster's master realm.

We recommend you to make the production site the prime site. For a discussion on the pros and cons of whether to make the production site or the disaster recovery site the prime site, refer to the section *Clusters with Sites* in the *Concepts* guide..



Setting the Production Site to be Prime by checking its *isPrime* checkbox.

## Channel Administration

The links below describe the Channel management features available within Universal Messaging's Enterprise Manager

- [“Creating Channels” on page 101](#)
- [“Editing Channels” on page 107](#)
- [“Copying Channels” on page 111](#)
- [“Channel Joins” on page 480](#)
- [“Channel Snoop” on page 118](#)
- [“Publishing Events Onto Channels” on page 120](#)
- [“Named Object Administration” on page 122](#)

## Creating Channels

This section describes the process of creating a Universal Messaging channel on Universal Messaging realm servers. Channels are the logical rendezvous point for data that is published and subscribed. If you are using Universal Messaging Provider for JMS then channels are the equivalent of JMS topics.


Each channel that is created consists of a physical channel within the Universal Messaging realm as well as its logical reference within a namespace that may be made up of resources that exist across multiple Universal Messaging realm servers. Creating channels using the Enterprise Manager creates the physical object within the realm. Once created, references to channels can be obtained using the Universal Messaging Client and Admin APIs. Channels can also be monitored and managed using the Enterprise Manager.

When you connect to a Universal Messaging realm in the Enterprise Manager, all resources and services found within the realm namespace are displayed in a tree structure under the realm node itself. It is possible to view multiple Universal Messaging realm servers from a single enterprise manager instance.

### Creating Channels on a Universal Messaging Realm

To create new Universal Messaging channels, the Enterprise Manager provides a number of options. Firstly, in order to create a channel, the branch where the channel will exist needs to be selected within the namespace tree.

For example, to create a channel called '/eur/rates' on a Universal Messaging realm called 'nirvana7' simply right-click on the realm node to display a pop-up menu which contains a 'Create Channel' option.



After selecting 'Create Channel', an Add Channel dialog box appears. Channels have a set of attributes assigned to them when they are created. The Add Channel dialog allows you to input values for each of these attributes.

For information about the available channel attributes, such as Channel Type and Channel TTL (time-to-live), see the summary of Channel Attributes in the Commonly Used Features section of the Universal Messaging Concepts guide.

In the example below, the channel '/eur/rates' will be created with a channel type of Simple and a TTL of 7 seconds.

**Add channel to realm nirvana7**

**Channel Attributes**

Channel Name:

Channel Type:

Channel TTL:

Channel Capacity:

Parent Realm:

Dead Event Store:

Use JMS Engine:  Use Merge Engine:

Storage Properties:

**Channel Keys**


Select Key To Edit:

**Key Properties**

Key Name:


Depth:

There are also a number of Storage Properties associated with the channel which can be configured by clicking the "Edit..." button to the right of "Storage Properties".




For information about the available channel attributes, see the summary of Storage Properties in the Commonly Used Features section of the Universal Messaging Concepts guide.

Clicking on the 'OK' button in the Add Channel dialog will create the channel '/eur/rates' on the Universal Messaging realm 'nirvana7' and render the channel object in the namespace tree of the Enterprise Manager underneath the realm node. This is shown in the image below.



As you can see from the image above, the channel node in the tree has been created under a folder (which we call a container node) called '/eur' under the realm 'nirvana7'.

It is also possible to create channels directly underneath container nodes. For example, if we wished to create another channel called '/eur/trades', we could repeat the process described above using the full absolute name of the channel. This would again create a channel called trades under the container node /eur. Alternatively, we can select the /eur node and create the new channel using its relative name /trades. Selecting the container node and right-clicking on the node, shows another pop-up menu of options for container nodes. One of the options is 'Create Channel'. The image below shows this menu as it appears when the container is right-clicked.



By selecting the menu item, 'Create Channel' from the container node, you are once again presented with the create channel dialog. This dialog looks like the dialog used previously, except the dialog shows that the channel will be created under the container /eur.

### Valid Channel and Queue Names

The channel and queue names can contain any of the following characters:

- All letters and digits
- Slash "/"
- Hyphen "-"
- Underscore "\_"

- Hash symbol "#"

Certain character strings are replaced:

- Backslash "\" is replaced by slash "/"
- Two colons "::" are replaced by slash "/"
- Two slashes "//" are replaced by one slash "/"

Valid names have the following length restrictions:

- Channel and queue names have a maximum limit of 235 characters.
- Namespace names have a maximum limit of 255 characters.
- The full path containing the data directory folder path with a channel or queue path appended to it has a maximum limit of 4096 characters.

If your channel or queue name contains slash characters, for example "a/b/c", this is represented in the Enterprise Manager view as a hierarchy, with "a" being the top node, "b" being the child node of "a", and "c" being the child node of "b". This virtual hierarchy is just a visual aid to help you to keep track of your channels and queues, but the store itself is not divided internally into hierarchical parts and can only be referenced by the full name, which in this example is "a/b/c".

**Note:**

There is a restriction that a channel or queue name cannot be the same as an existing folder name. So if you have named a channel "a/b/c", you cannot name a different channel "a" or "a/b". This would lead to a display conflict in Enterprise Manager, since we would have a folder "a" as the root of the path "a/b/c", as well as a channel "a" at the same position in the display. Similarly, trying to assign the name "a/b" to a new channel would conflict in the display with the folder named "a/b". You can however name a different channel "a/c", since "a" is used here again as a virtual folder. Similarly, you can name another channel "a/b/d", since both "a" and "a/b" are used here as virtual folders.

## Editing Channels

This section describes the process of editing the attributes of a Universal Messaging channel.

Editing channels using the Enterprise Manager enables you to change specific attributes of a channel, such as name, event time to live (TTL), capacity, channel keys or even the realm on which the channel exists.

**Note:**

When a channel is edited, its attributes and any events found on the channel will be copied into a temporary channel, the old channel is then removed and then the new channel is created. The original events are then copied from the temporary channel onto the new channel.


As far as possible, channel events are held in memory for performance reasons. The temporary channel is also held in memory, and requires the same amount of memory as the channel being edited. The realm server must be able to allocate sufficient memory to store the temporary copy,

otherwise the channel edit operation will be aborted and an error will be logged. If such a situation occurs, you can resolve it by allocating additional heap size, so that the temporary copy can exist in memory at the same time as the channel being edited.

Since editing a channel involves removing the existing channel, this will end all active subscriptions to the channel. It will also end all shared durables attached to the channel, along with the associated messages. Such subscriptions or shared durables need to be recreated after you have finished editing the channel.

Editing a channel which serves as a dead event store for another channel will cause that reference to be removed, therefore the user should re-create the reference.

In order to edit a channel, select it in the namespace, and then after right-clicking on the node, a menu will be displayed with the various options for a channel node. The image below shows this menu.



By selecting the 'Edit Channel' option, you will be presented with a dialog that allows you to modify the details of the channel. These details not only include the channel attributes, but also the realm to which the channel belongs. The image below shows the edit channel dialog.

The screenshot shows a dialog box titled "Modify channel ClusterRates". It contains two main sections: "Channel Attributes" and "Channel Keys".

**Channel Attributes:**

- Channel Name: ClusterRates
- Channel Type: Mixed
- Channel TTL: 0
- Channel Capacity: 0
- Parent Realm: nirvana7
- Dead Event Store: (empty)
- Use JMS Engine:
- Use Merge Engine:
- Storage Properties: Edit...


**Channel Keys:**

- Select Key To Edit: CCY:1
- New
- Key Properties:**
- Key Name: (empty)
- Depth: 1
- Save
- Delete

At the bottom of the dialog are OK and Cancel buttons.

The Parent Realm field shows a drop down list containing all the names of the realms that the enterprise manager is currently connected to. By selecting a realm name from the list, it is possible to move the selected channel to any of the available realms. Clicking on the 'OK' button will perform the edit operation on the channel.

There are also a number of Storage Properties associated with the channel which can be configured by clicking the "Edit..." button to the right of "Storage Properties".




## Copying Channels

This section describes the process of copying channels in Universal Messaging realms.

Copying channels using the Enterprise Manager enables you to duplicate channels automatically across realms. When a channel is copied, its attributes and any events found on the channel will be copied over onto the new channel copy.

Firstly, by selecting the channel in the namespace that you wish to copy and right-clicking on the node, you will be presented with a menu that shows you the various options for a channel node. The image below shows this menu.



By selecting the 'Copy Channel' option, you will be presented with a dialog that allows you to input the details of the new channel copy. These details not only include the channel attributes, but also the realm to which the channel will be copied. The image below shows the copy channel dialog.

The Parent Realm field shows a drop down list containing all the names of the realms that the Enterprise Manager is currently connected to. By selecting a realm name from the list, it is possible to create a copy of the selected channel in that realm. Clicking on the 'OK' button will create the channel on the selected realm and the channel will then appear in the namespace tree.

## Creating Channel Joins

This section describes the process of joining channels on Universal Messaging realms. Channels are the logical rendezvous point for data that is published and subscribed.

Channels can be joined programmatically or by using the Universal Messaging Enterprise Manager as described below.

Joining channels using the Enterprise Manager creates a physical link between a source channel and a destination channel. Once created, any events published to the source channel will be republished onto the destination channel.

Joins can be created using filters, so that only specific events published to the source channel that match certain search criteria will be routed to the destination channel.

Joins can also be created in several configurations:

- A join may be created between a channel on a realm and a store on another realm federated with the source realm (see [“Realm Federation”](#) on page 25 for details of setting up federation between two realms);
- A join can be created from a channel on a clustered realm to a store within the same cluster. A non-clusterwide channel can be joined to a cluster-wide store, but not vice versa;
- A channel can be joined from a channel on one cluster to a channel on another cluster by using an inter-cluster join (see [“Inter-Cluster Joins”](#) on page 116).
- Universal Messaging also supports joins where the destination (incoming) is a queue. Universal Messaging does not support joins where the source of the join is a queue.


The image below shows a realm that contains the cluster channels `/eur/rates` and `/local/rates`.

The screenshot displays the Nirvana Enterprise Manager interface. The left-hand pane shows a tree view of the 'nirvana' realm, including folders for 'Data Groups', 'channel 1', 'channel 2', 'newtest', 'queue 1', 'showcase', 'eur', 'local', and 'ClusterRates'. Under the 'eur' folder, there is a 'rates' channel. Under the 'local' folder, there is a 'rates' channel. The right-hand pane shows the 'Storage Properties' tab for the selected 'rates' channel. The 'Attributes' section lists: Name (rates), Type (Reliable), Age (0), Capacity (0), and Engine (Default). Below this are tabs for 'Status', 'Joins', 'ACL', 'Named Objects', 'Snoop', and 'Connections'. There are two empty grid sections for 'Consumed Event History' and 'Published Event History'. At the bottom, there are three summary tables:

Totals		Rates		Event Store	
Published	0	Published	0.0	Used Space	
Consumed	0	Consumed	0.0	Events	
Event ID	-1	Connections	0.0	% Free	
Current Connections	0	Fanout (ms)	0.0	Cache Hit	
Total Connections	0				

By selecting any of the cluster channels, then right-clicking, you can select the 'Join Channel' menu option. You will be presented with the join dialog for the selected cluster channel. This allows you to create a join from the channel to any other channel in any realm.


We can, for example, select `/local/rates` as the channel we wish to join to `/eur/rates`, as shown in the join dialog below, with a filter of `CCY='EUR'`. This will ensure that only those events with the event property `CCY` equal to `'EUR'` occurring on `/local/rates` will be published to the `/eur/rates` channel.



The **From Channel** field represents the source channel and the **To Store** field represents the destination channel. By default, the **From Channel** field contains the name of the currently selected channel from which the join dialog was opened.

Clicking on the **OK** button will create the join.

By selecting the **Joins** tab panel for either the `/local/rates` channel or the `/eur/rates` channel, you will be presented with a panel that shows the join just created. The image below shows the display for the `/eur/rates` channel, which in this example is the destination channel. Selecting the newly created join will also show you any relevant filtering criteria that the join has been created with.



The table that shows the joins for a channel will indicate in the **Type** column whether the join is 'Outgoing' or 'Incoming'. An outgoing join indicates that the selected channel is the source for the join, whereas 'Incoming' indicates that the selected channel is the destination channel.

## Deleting Joins

You can delete a join by selecting the join from the joins table, and clicking the **Delete Join** button. Joins can only be deleted in the Enterprise Manager from the source (outgoing) channel. If the destination channel (incoming) is selected, the **Delete Join** button will be disabled.

## Inter-Cluster Joins

To add a join between channels on different clusters, first create an inter-cluster connection between the two clusters. Next, simply select a realm in the desired destination cluster as the join destination in the dropdown menu, as below:

The screenshot displays the Nirvana Enterprise Manager interface. On the left, a tree view shows the hierarchy: Nirvana Enterprise > Clusters > Cluster 1 > realm1 > Data Groups > Cluster1Chan 1. A 'Create Channel Join' dialog box is open, showing the following configuration:

- From Channel: /Cluster1Chan 1
- To Realm: realm3
- To Store: /Cluster2Chan 1
- Filter: (empty)
- Hop Count: (empty)
- Allow Purge:
- Archival:

Below the dialog, the 'Consumed Event History' and 'Published Event History' sections are visible, both showing empty grid tables. At the bottom of the interface, there are two summary tables:

Totals		Rates	
Published	0	Published	0.0
Consumed	0	Consumed	0.0
Event ID	-1	Connections	0.0
Curent Connections	0	Fanout (ms)	0.0
Total Connections	0		

As with non-inter-cluster joins, these joins can be specified with filters and hop-counts. If realms in the destination cluster go down, the join will failover and will continue to deliver events so long as the destination cluster is formed.

Inter-cluster joins can also be formed programmatically .

## Allowing Purge

When a channel is purged, the events in the channel can also be purged. To activate this feature, mark the checkbox **Allow Purge**.

## Archival Joins

An archival join is a specific type of join made between a channel and a queue, where events will not be checked for duplication. Events that are published to the source channel will appear in the destination queue. This may result in duplicate events in the queue if the queue has multiple sources.

If you use the optional **Filter** field, only the events matching the filter criteria will appear in the destination queue.

The channel join dialog contains a checkbox labelled **Archival**. This checkbox is available when you create a join from a channel to a queue. When you mark the checkbox, the join is defined as an archival join.

A typical scenario for using this feature is if you have multiple routes that messages can take to reach the same destination, and you want to retain all duplicates at the destination. For example:

- if an event is duplicated at the source.
- if an event is copied from channel A -> B -> C and from channel A -> D -> C.
- if you define multiple paths over different network protocols between the same source and destination.

Without this feature, the duplicate detection would ensure that only one copy of the message is delivered to the destination queue.

## Channel Snoop

This section will describe how to snoop a Universal Messaging channel. Channels are the logical rendezvous point for data that is published and subscribed.

Snooping a channel using the Universal Messaging enterprise manager allows the display of the contents of events contained within that channel. Each channel node in the namespace tree of a Universal Messaging realm, when selected, displays a snoop panel that provides you with a means of subscribing to the channel so that the events' contents can be displayed in a graphical panel.

You can select where on the channel you wish to subscribe from and to, based on the event id, and you can also provide a filter that enables you to select specific events that match a certain criteria.

First of all, by selecting the channel you wish to snoop in the namespace tree, the Enterprise Manager will display a number of panels in a tabbed pane. One of these tabs is labeled 'Snoop'. Selecting the snoop tab will display a panel like the one shown in the image below.

The snoop panel is split up into a number of different sections. Firstly, the 3 text fields at the top of the panel allow you enter an event id range to and from, and a selector string that will be used

to filter events being snooped on the channel. Clicking the 'Start' button will begin the channel snoop, and start displaying any events that are published onto the channel using whatever values you have input into the text fields.

The screenshot shows the Nirvana Enterprise Manager interface. On the left is a tree view of the hierarchy: Nirvana Enterprise > Clusters > Test > node0, node1, node2; and Realms > node0, ClusterRates (selected), Data Groups, GlobalOrders, eur > rates, local, node1, node2. The main panel has tabs for Summary and Storage Properties. The Summary tab shows attributes: Name, Type, Age, Capacity, Engine, ClusterRates, Reliable, and Default. Below this are buttons for Status, Joins, ACL, Named Objects, Snoop (active), and Connections. The Snoop panel has input fields for From, To, and Filter. Below these is a table of events:

Event Id	Tag	TTL
99		0
98		0
97		0
96		0
95		0
94		0

Below the table are two panels: a Hexadecimal view showing '0: 54 58 49 44 20 2D 20 30' and an ASCII view showing 'T X I D -'. At the bottom are buttons for Start, Stop, and Pause.

When events are published, they are added to the main table below the text field input. This main table shows 4 columns of summary information about each event: the event id, event tag, time to live, and whether the event is persistent. By clicking on any event shown as a row in the main table, more information on the event is shown in the bottom 3 panels. As shown in the image below.

The Top 2 remaining panels show a Hexadecimal view of the event data and an ASCII representation of the same event data. The panel below that shows the contents of the event properties (if one exists for the event) listed within a table. Each property is displayed as a row in the table. The table columns show the name of the property, the type, and the value.

The button labeled 'Pause' will temporarily suspend receipt of any new message being received into the snoop panel for the selected channel. The 'Stop' button will stop snooping events and clear all the panels and tables.

In order to snoop the contents of a Universal Messaging queue (see [“Queue Snoop” on page 153](#)) please see that section of the enterprise .

## Channel Publishing

This section will describe how to publish events to a Universal Messaging channel from the Enterprise Manager.

Events can be published either from scratch, or by duplicating events already published onto a channel from within the snoop (see [“Channel Snoop” on page 118](#)) panel view. Both options allow you to add and remove event properties, set the event TTL, the event persistence, the event tag and the number of times the event will be published to the channel.

The event data can be either manually input, obtained from an xml Document file or any other binary file.

Firstly, to publish a new event from scratch, select the desired channel you wish to publish an event onto, and then right-click on the same node and choose the 'Publish' menu option. This will display a dialog as shown below where you can construct the event.

**Publish event to Channel rates**

Publish Location  
 Realm: nirvana  
 Channel: ClusterRates

Event Data  
 Corporate Sale  
 File  
 Clear

Event Details  
 Event Tag: CSale  
 Event TTL: 0  
 Num Of Publishes: 1  
 Is Persistent:   
 Is Transient:

Property Input  
 Key: discount  
 Value: 0.05  
 Type: Float  
 Add

Property Display

Key	Value	Type
SalesPerson_ID	1024	Integer
quantity	2.0	Float
price	30.05	Float
discount	0.05	Float

Purge Original Event:  OK Cancel

In the image above, the data for the event is simply a string. The properties are added by entering a property key, a value and a type and then clicking on the 'Add Property'. Once added, the

properties are displayed in the table at the bottom of the panel. To remove a property entry, click on the property within the table view and select the 'Remove Property' menu option. Properties can also be edited by clicking on the property from the table and double-clicking in the cell you wish to change. Once you hit return, the value will be updated in the table.

To add an XML document as the event data, click on the 'Open' button in the top right hand corner of the dialog, and choose your xml file from the file chooser. Once opened, the contents of the file will be displayed within the event data section of the dialog and will be non-editable. An example of this is shown in the image below.

**Publish event to Channel ClusterRates**

Publish Location

Realm: nirvana

Channel: ClusterRates

Event Data

```
<?xml version="1.0"
encoding="UTF-8"?><Nirvan
aRealm comment="Realm
configuration from nirvana"
exportDate="2012-07-02+01
:00" name="nirvana">
  <RealmConfiguration>
  <ConfigGroup
```

File

Clear

Event Details

Event Tag: XML-0

Event TTL: 0

Num Of Publishes: 1

Is Persistent:

Is Transient:

Property Input

Key: discount

Value: 0.05

Type: Float

Add

Property Display

Key	Value	Type
price	30.05	Float
quantity	2.0	Float

Purge Original Event:

OK Cancel

To publish the contents of any other file within the event data, repeat the above steps for XML and select a non-xml file. The contents of the file will not be displayed, however the file will be read in binary format when the 'Publish' button is clicked and published to the channel. Once again, when a file is selected for publishing the event data section is non-editable.

Clicking on the 'Clear' button will cancel any file that has previously been selected and allow you to once again select a file or manually enter the event data.

In order to duplicate or modify and republish an event that has already been published to a channel, you must first of all select the snoop panel (see ["Channel Snoop" on page 118](#)) for the channel in question, and snoop the channel. Once events are displayed in the snoop panel, select the event you wish to duplicate or modify and republish from the table of events. Right-clicking on the event

will display a menu with 2 options. The first option allows you to purge an individual event from a channel. The second menu option will open the event publish dialog with the details of the event already filled in, including the event properties, TTL and persistence.

Properties can be added / removed from the duplicate event as well as modified. To modify a property, double-click in the cell of the property you wish to change and then modifying its contents. With the republish option, you can also choose to purge the original event from the channel by checking the 'Purge Original Event' checkbox. Once the 'Publish' button is clicked, the duplicate event will be published onto the channel. The number of publishes depends on the amount entered in the 'Num Of Publishes' field. The image below shows the publish dialog for a JMS Message published onto a Universal Messaging channel.

**Publish event to Channel ClusterRates**

Publish Location  
 Realm:   
 Channel:

Event Data  
 Object  Test  bytesd  
 angela  bytes1d  emily  pi

Event Details  
 Event Tag:   
 Event TTL:   
 Num Of Publishes:   
 Is Persistent:   
 Is Transient:

Property Input  
 Key:   
 Value:   
 Type:

Property Display

Key	Value	Type
JMSDeliveryMode	PERSISTENT	String
JMSDestination	/local/rates	String
JMSExpiration	0	Long
JMSMessageID	ID: 127.0.0.1:3...	String
JMSMsgType	2	Integer

Purge Original Event:

The publish option is also available for queues. The republish option is also available from the snoop panel for queues.

## Channel Named Objects

This section describes how to manage named objects stored by a realm server against a Universal Messaging channel. Named objects provide state information for durable consumers mapped to specific names on channels. Every time a consumer uses a named object, it begins consuming from where the previous consumer finished.

The Universal Messaging APIs provide methods for managing named objects programmatically, in Java and C#.

To retrieve and remove any named objects present on a channel in Enterprise Manager, select the channel and click the **Named Objects** tab. When you first select the **Named Objects** tab, the named object table is empty. To populate the table with any named objects found for the channel, click **Get Names**.

The following image shows that the named object table for the /eur/rates channel has a named object for the name 'administrator'.

The screenshot shows the Nirvana Enterprise Manager interface. The left pane displays a tree view of the system structure, including Clusters (Test) and Realms (node0, ClusterRates, Data Groups, GlobalOrders, eur, local, node1, node2). The 'eur' realm is expanded to show the 'rates' channel. The right pane shows the 'Named Objects' tab for the 'rates' channel. The 'Attributes' section lists: Name (rates), Type (Reliable), Age (0), Capacity (0), and Engine (Default). Below this is a toolbar with buttons for Status, Joins, ACL, Named Objects, Snoop, and Connections. The main area contains a table with the following data:

Named Object	Event Id	Cluster Wide	Persistent
Subscriber1	-1	<input type="checkbox"/>	<input type="checkbox"/>

At the bottom right of the interface are buttons for 'Get Names' and 'Delete Name'.

The named object table shows each named object as a row in the table. The columns of the table show the attributes of a named object, such as the name, current event ID (as known by the server), whether the named object is cluster-wide and whether it is persistent (When a realm is restarted the named object state is read from disk as opposed to being held in memory where it would be lost after a restart).

**Note:**

When changes to the event ID and outstanding events attributes of a named object occur, Enterprise Manager refreshes the values of these attributes at an interval of several seconds. For this reason, if you click **Get Names** too often, the event ID and outstanding events for a named object might not be updated immediately.

To delete a named object, select the named object in the table and click **Delete Name**. This action removes the named object from the server.

## DataGroup Administration

The links below describe the DataGroup management features available within Universal Messaging's Enterprise Manager

- [“Creating DataGroups” on page 124](#)
- [“Adding Existing DataGroups to DataGroups” on page 131](#)
- [“Removing DataGroups from DataGroups” on page 136](#)
- [“Deleting DataGroups” on page 139](#)

### Creating DataGroups


Universal Messaging DataGroups provide a very lightweight grouping structure that allows developers to manage user subscriptions remotely and transparently.

Each DataGroup is a resource that exists within the Universal Messaging realm server, or within a cluster of multiple realm servers. Creating a DataGroup - in this case using the Enterprise Manager - creates the physical object within the realm. Once created, references to the DataGroup can be obtained using the Universal Messaging Client and Admin APIs. DataGroups can also be monitored and managed using the Enterprise Manager.


When you connect to a Universal Messaging realm in the Enterprise Manager, all resources and services found within the realm namespace are displayed in a tree structure under the realm node itself. It is possible to view multiple Universal Messaging realm servers from a single enterprise manager instance.

### Creating a DataGroup

In Enterprise Manager, the **Data Groups** node exists within the realm node. Locate the Data Group Node, and right click on it to bring up a context menu:



Create the DataGroup - in this example, we'll call it EURUSD\_Gold :



The new DataGroup can now be seen in Enterprise Manager:

The screenshot displays the Nirvana Enterprise Manager interface. The main window title is "Software AG - webMethods / Nirvana Enterprise Manager". The menu bar includes "File", "Connections", "Cluster", and "Help".

The left-hand tree view shows the following structure:

- Nirvana Enterprise
  - Clusters
  - Realms
    - nirvana7
      - Data Groups
        - EURUSD\_Gold (highlighted)

The right-hand pane shows the configuration for the selected Data Group:


- Conflation Attributes**
  - Name
  - Multicast Enabled
  - Conflation Action
  - Interval (ms)
- Status** (selected), Streams, Snoop
- Consumed Event History**: A grid area for viewing consumed events.
- Published Event History**: A grid area for viewing published events.
- Totals**
  - Published
  - Consumed
  - Event ID
  - Current Streams
  - Total Streams

Publishers with the *Publish to DataGroups* ACL permission can now publish messages to the new DataGroup programmatically.


## Creating a Nested DataGroup

Choose the DataGroup that is going to contain a new DataGroup. In this example, we'll choose the EURUSD\_Gold DataGroup we created earlier.

Right-click its icon, and the following context menu appears:



Add the nested DataGroup:



The nested DataGroup can now be seen in the tree:

The screenshot displays the Nirvana Enterprise Manager interface. The main window title is "Software AG - webMethods / Nirvana Enterprise Manager". The menu bar includes "File", "Connections", "Cluster", and "Help".

The left-hand pane shows a hierarchical tree view:

- Nirvana Enterprise
  - Clusters
  - Realms
    - nirvana7
      - Data Groups
        - EURUSD\_Gold
        - Customer\_Desk\_A (highlighted)

The right-hand pane contains several sections:

- Conflation Attributes:**
  - Name
  - Multicast Enabled
  - Conflation Action
  - Interval (ms)
- Buttons:** Status (info icon), Streams (arrow icon), Snoop (magnifying glass icon)
- Consumed Event History:** A large empty grid area.
- Published Event History:** A large empty grid area.
- Totals:**
  - Published
  - Consumed
  - Event ID
  - Current Streams
  - Total Streams


## Adding Existing DataGroups to DataGroups

We've already seen how to use Enterprise Manager to create a new DataGroup and add it to an existing DataGroup (see [“Creating DataGroups” on page 124](#)). In this section, we will add an existing DataGroup to a DataGroup.


Assume that in the following example structure of DataGroups, we would like to add the existing **Customer\_Desk\_A** DataGroup, which itself already a member of the **EURUSD\_Gold** DataGroup, to the **GBPUSD\_Gold** DataGroup too.

First, choose the DataGroup that is going to contain a new DataGroup. In this case, it's the **GBPUSD\_Gold** DataGroup we created earlier.

Right-click its icon, and the following context menu appears:



Click the "Add A DataGroup to GBPUSD\_Gold" context menu option, then type in the name of the DataGroup we wish to add as a member - in this case, **Customer\_Desk\_A**:



Because this DataGroup already exists (and was a member of **EURUSD\_Gold**), it now appears as a member of two DataGroups (and thus appears twice in the tree of DataGroup nodes):

The screenshot displays the Nirvana Enterprise Manager interface. The main window title is "Software AG - webMethods / Nirvana Enterprise Manager". The menu bar includes "File", "Connections", "Cluster", and "Help".

The left pane shows a hierarchical tree view:

- Nirvana Enterprise
  - Clusters
  - Realms
    - nirvana7
      - Data Groups
        - EURUSD\_Gold
          - Customer\_Desk\_A
          - Customer\_Desk\_B
          - Customer\_Desk\_C
        - EURUSD\_Silver
          - Customer\_Desk\_D
        - EURUSD\_Bronze
        - GBPUSD\_Gold
          - Customer\_Desk\_A

The right-hand panel contains several sections:

- Conflation Attributes**:
  - Name
  - Multicast Enabled
  - Conflation Action
  - Interval (ms)
- Status** (selected), **Streams**, **Snoop**
- Consumed Event History**: A grid area for displaying consumed events.
- Published Event History**: A grid area for displaying published events.
- Totals**:
  - Published
  - Consumed
  - Event ID
  - Current Streams
  - Total Streams

Now, any events published to the DataGroups **EURUSD\_Gold** or **GBPUSD\_Gold**, or directly to the DataGroup **Customer\_Desk\_A**, will be delivered to any DataStreams which are members of the **Customer\_Desk\_A** DataGroup.


## Removing DataGroups from DataGroups

In this section, we will remove an existing DataGroup from a DataGroup.

Assume that in the following example structure of DataGroups, we would like to remove the existing **Customer\_Desk\_C** DataGroup from the **EURUSD\_Silver** DataGroup.

First, choose the DataGroup that is going to be removed from its "parent" DataGroup. In this case, it's the **Customer\_Desk\_C** DataGroup we created earlier.


Right-click its icon, and the following context menu appears:



Click the "Remove Customer\_Desk\_C from EURUSD\_Silver" context menu option, then click OK on the confirmation dialog.

The DataGroup, having been removed, will either:

- Be moved to the top level DataGroups node if it has no other parent DataGroups, or
- Appear in other nodes in the tree if it has at least one other parent DataGroup.



In this example, the **Customer\_Desk\_C** DataGroup was not a member of any other DataGroups, so having been removed from the **EURUSD\_Silver** DataGroup, it now appears in the top level DataGroups node.

## Deleting DataGroups


There are two ways of deleting a DataGroup using the Enterprise Manager:

1. by navigating the DataGroups tree
2. by typing in its name

Note that if a deleted DataGroup is a member of more than one parent DataGroup, then it will be deleted from all of them, and will no longer be defined for use elsewhere.

### Deleting by Navigating the DataGroups Tree


In Enterprise Manager, locate the Data Group Node (in this example, **EURUSD\_Gold**), and right click on it to bring up a context menu:




Click OK on the confirmation dialog, and the DataGroup will be deleted.

## Deleting by Typing in the DataGroup Name

In Enterprise Manager, right-click the DataGroups node and select the "Delete A DataGroup" context menu option:



In the resulting dialog box, type in the name of the DataGroup to be deleted:



Click OK on the confirmation dialog, and the DataGroup will be deleted.

## Queue Administration

The links below describe the queue management features available within Universal Messaging's Enterprise Manager

- [“Creating Queues” on page 142](#)
- [“Editing Queues” on page 148](#)
- [“Copying Queues” on page 151](#)
- [“Queue Snoop” on page 153](#)

### Creating Queues

This section describes how to create queues on Universal Messaging realms. Each queue that is created consists of a physical object within the Universal Messaging realm as well as its logical reference within the namespace.


Creating queues using the Enterprise Manager creates the physical object within the realm. Once created, references to queues can be obtained using the Universal Messaging Client and Admin APIs. Queues can also be monitored and managed using the Enterprise Manager.

When you connect to a Universal Messaging realm in the Enterprise Manager, all resources and services found within the realm namespace are displayed in a tree structure under the realm node itself.

### Creating Realm Queues


To create new realm queues, the Enterprise Manager provides you with a number of options.

In order to create a queue called '/eur/requests' on a realm called 'nirvana' simply right-click on the realm node called 'nirvana' to display a pop-up menu containing an option called 'Create queue' (as shown in the image below).



By clicking on the menu item 'Create Queue', you will be prompted with a dialog box that allows you to enter the queue attributes. Queues have a set of attributes assigned to them when they are created. The create queue dialog allows you to input values for each of these attributes.

The set of valid characters that you can use for queue names is the same as the valid character set for channel names. For more information, see [“Valid Channel and Queue Names”](#) on page 106.



Clicking on the 'OK' button will create the queue '/eur/requests' on the Universal Messaging realm 'nirvana' and render the queue object in the namespace tree of the Enterprise Manager underneath the realm node. This is shown in the image below.

The screenshot shows the Nirvana Enterprise Manager interface. On the left, a tree view displays the hierarchy: Nirvana Enterprise > Clusters > Realms > realm1 > channel1, channel2, eur (folder) > rates, requests (queue). The main area is divided into several sections:

- Realm Details:** Name, Threads, Realm UpTime, Last Update.
- Navigation:** Status, Monitoring, ACL, Comms, Nirvana Realms, Config, Sched.
- Event History:** A grid chart showing event history.
- Memory Usage History:** A grid chart showing memory usage history.
- Event Status:**

Consumed	0
Published	2
Consumed/Sec	0.0
Published/Sec	0.0
- Totals:**


Realms	0
Channels	2
Queues	0
Data Groups	0
Data Streams	0
Services	0
- Connection Status:**

Total	1
Current	1
Rate	0.0
Allowed	Unlimited
- Memory Usage (M):**

Total	0
Free	0
Used	0
Change	0


As you can see from the image above, the queue node in the tree has been created under a folder (container node) called '/eur' under the realm 'nirvana'.

There are also a number of Storage Properties associated with the queue which can be configured by clicking the "Edit..." button to the right of "Storage Properties".




Queues can also be created from the context of a container nodes by specifying a relative queue name.

For example, to create another queue called '/eur/orders', you can select the '/eur' node and create the new queue using its relative name '/orders'. Selecting the container node and right-clicking on the node, shows another pop-up menu of options for container nodes. One of the menu is 'Create Queue'. The image below shows this menu as it appears when the container is right-clicked.



By selecting the menu item, 'Create Queue' from the container node, you are once again presented with the create queue dialog. This dialog looks like the dialog used previously, except the title of the dialog shows that the queue will be created under the container '/eur', as shown in the image below.



## Editing Queues

This section describes the process of editing queues in Universal Messaging realms. Each queue that is created consists of a physical object within the Universal Messaging realm as well as its logical reference within the namespace.

Editing queues using the Enterprise Manager enables you to change specific attributes for a queue, such as name, TTL, capacity or even the realm on which the queue exists.


### Note:

When a queue is edited, its attributes and any events found on the queue will be copied into a temporary queue, the old queue is then removed and then the new queue is created and the events are then copied from the temporary queue onto the new queue.


As far as possible, queue events are held in memory for performance reasons. The temporary queue is also held in memory, and requires the same amount of memory as the queue being edited. The realm server must be able to allocate sufficient memory to store the temporary copy, otherwise the queue edit operation will be aborted and an error will be logged. If such a situation occurs, you can resolve it by allocating additional heap size, so that the temporary copy can exist in memory at the same time as the queue being edited.

Editing a queue which serves as a dead event store for another queue will cause that reference to be removed, therefore the user should re-create the reference.

In order to edit a queue, select it in the namespace, and then after right-clicking on the node, a menu will be displayed with the various options for a queue node. The image below shows this menu.




By selecting the 'Edit Queue' option, you will be presented with a dialog that allows you to modify the details of the queue. These details not only include the queue attributes, but also the realm to which the queue exists. The image below shows the edit queue dialog.



The image shows a drop down list containing all the names of the realms that the enterprise manager is currently connected to. By selecting a realm name from the list, it is possible to move the selected queue to any of the available realms. Clicking on the 'OK' button will perform the edit operation on the queue.

There are also a number of Storage Properties associated with the queue which can be configured by clicking the "Edit..." button to the right of "Storage Properties".




## Copying Queues


This section will describe the process of copying queues in Universal Messaging realms. Each queue that is created consists of a physical object within the Universal Messaging realm as well as its logical reference within the namespace.

Copying queues using the Enterprise Manager enables you to duplicate queues automatically across realms. When a queue is copied, its attributes and any events found on the queue will be copied over onto the new queue copy.

Firstly, by selecting the queue in the namespace that you wish to copy and right-clicking on the node, you will be presented with a menu that shows you the various options for a queue node. The image below shows this menu.



By selecting the 'Copy Queue' option, you will be presented with a dialog that allows you to input the details of the new queue copy. These details not only include the queue attributes, but also the realm to which the queue will be copied to. The image below shows the copy queue dialog.



The image shows a drop down list containing all the names of the realms that the enterprise manager is currently connected to. By selecting a realm name from the list, it is possible to create a copy of the selected queue in that realm. Clicking on the 'OK' button will create the queue on the selected realm and the queue will then appear in the namespace tree.

## Queue Snoop

This section will describe how to snoop a Universal Messaging queue. Each queue that is created consists of a physical object within the Universal Messaging realm as well as its logical reference within the namespace.

Snooping a queue allows you to view the events contained on a queue. Each queue node in the namespace tree of a Universal Messaging realm, when selected, displays a snoop panel that provides you with a means of browsing the queue and present the events on the queue in a graphical panel.

You can also provide a filter that enables you to select specific events that match a certain criteria.

First of all, by selecting the queue you wish to snoop in the namespace tree, the Enterprise Manager will display a number of panels in a tabbed pane. One of these tabs is labelled 'Snoop'. Selecting the snoop tab will display a panel like the one shown in the image below.

The snoop panel is split up into a number of different sections. Firstly, the 3 text fields at the top of the panel allow you enter an event id range to and from, and a selector string that will be used to filter events being snooped on the queue. For queues, the event id ranges are disabled. Clicking the 'Start' button will begin the queue snoop, and start displaying any events that are published onto the queue using whatever values you have input into the text fields.

When events are published, they are added to the main table below the text field input. This main table shows 4 columns of basic information about each event: the event id, event tag, time to live,

and whether the event is persistent. By clicking on any event shown as a row in the main table, more information on the event is shown in the bottom 3 panels. As shown in the image below.

The top 2 remaining panels show a Hexidecimal view of the event data and an ASCII representation of the same event data. The panel below that shows the contents of the event properties (if one exists for the event) listed within a table. Each property is displayed as a row in the table. The table columns show the name of the property, the type, and the value.

The screenshot shows the Nirvana Enterprise Manager interface. On the left is a tree view of the system structure:

- Nirvana Enterprise
  - Clusters
  - Realms
    - realm1
      - channel1
      - channel2
      - eur
        - rates
        - requests (selected)

The main panel is titled "Summary" and "Storage Properties". It contains the following sections:

- Attributes:** Name, Type, Age, Capacity, Engine.
- Buttons:** Status, Joins, ACL, Snoop.
- From/To/Filter:** Fields for message source and destination.
- Event Table:**

Event Id	Tag	TTL
9		
8		
7		
6		
5		
4		
- Message Content:**

```

0: 54 68 69 73 20 69 73 20 61 20 74 65 78 74 20 6D
16: 65 73 73 61 67 65
  
```

T h i s i  
e s s a g e
- Properties Table:**

Key	Value	Type
nrvpub.host	127.0.0.1	String
nrvpub.name	administrator	String
nrvpub.time	Tue Jul 3 16:32:05, 2012	long
- Control Buttons:** Start, Stop, Pause.


The button labelled 'Pause' will temporarily suspend receipt of any new message being received into the snoop panel for the selected queue. The 'Stop' button will stop snooping events and clear all the panels and tables.

Channels can also be snooped using the snoop panel (see [“Channel Snoop”](#) on page 118).

## Using ACLs for role-based Security


### Adding ACLs

The Enterprise Manager allows Access Control Lists (ACLs) to be controlled via the ACL panel which is displayed for each object within the namespace. These panel allows users to add entries to the ACL, as well as remove the selected entry. The image below shows the dialog for adding an ACL entry.



Clicking on the 'OK' button will add the subject to the selected objects ACL list.

Similarly, once they have been defined, Security Groups (see [“Nirvana Admin API - Nirvana Security Groups” on page 489](#)) may be added into ACL Lists by clicking the "Add Group" button and selecting the desired group as shown:



When an entry is selected from the ACL panel, and the 'Delete' button is selected, you will be prompted to confirm the deletion.

After any changes made to the ACLs, only when the 'Apply' button is clicked will those changes be sent to the realm server for processing. Clicking the 'Cancel' button will discard any changes made and revert back to the state the Realm server has for the ACL.

To read more about the entitlements for each object, follow the links below:


- [“Security Groups” on page 489](#)
- [“Realm ACL” on page 161](#)
- [“Channel ACL” on page 163](#)
- [“Queue ACL” on page 166](#)

- [“Interface VIA ACL” on page 168](#)


## **Security Groups**

Security groups contain a list of subjects (username & host pairs) and, in addition, may contain other Security Groups. Once a Security group is defined, the group can be added to ACL lists like normal subject(user@host) entries are added and permissioned. This allows for "sets" of users to be defined and granted permissions through a single entry in an ACL list, rather than each user having an entry.


Before adding a Security Group to an ACL, it must first be created. This can be done programmatically or via the Enterprise Manager, as shown below.



Once the group has been created, user@host subjects can be added to the group using the "Add Member" button:



Alternatively, groups can be added as members of other groups by using the "Add Group" button. This will present you with a dropdown list of existing groups to choose from:



Membership of Security Groups can be altered dynamically, and the changes will be reflected in the permissions for all ACL lists where the security group is an entry in the ACL list.

As with all ACLs in Universal Messaging, privileges are cumulative. This means that, for example, if a user is in a group which has publish permissions on a channel, but not subscribe permissions,

the user will no be able to subscribe on the channel. Then, if an ACL entry is added on the channel for his specific username/host pair, with subscribe but no publish permissions, the user will then be able to both subscribe(from the non-group ACL permission), and publish (from the group ACL permission).

## **Realm Entitlements**

### **Realm ACLs**


As mentioned in the security introduction (see [“Using ACLs for role-based Security” on page 156](#)), in order to perform operations within a Realm clients connecting to the realm must be given the correct entitlements.

In order for a client to connect to a Universal Messaging Realm server there must be a Realm ACL which allows them to do so. A Realm ACL contains a list of subjects and their entitlements (i.e. what operations they can perform within the realm).

Using the Enterprise manager, one can add to, remove or modify entries within a realm ACL.

ACLs can also be managed via the Universal Messaging administration API.

To view a Realm ACL, click on a realm node within the namespace of the Enterprise Manager, and select the 'ACL' tab. This will display the realm ACL and the list of subjects and their associated permissions for the realm. The following image displays and example of a realm ACL.



As you can see above, the realm ACL has a number of subject entries and operations that each subject is able to perform on the realm. The operations that can be performed on a realm are described below in the order in which they appear in the ACL panel above:

- Manage ACL - Allows the subject to get and manage the list of ACL entries.

**Note:**

This permission is a combination of two permissions at the Administration API level. The boolean `setModify()` API function allows/denies permission to change an ACL value, and the boolean `setList()` API function allows/denies permission to access the current list of ACLs. If both of these functions return the value true, Manage ACL is allowed, otherwise Manage ACL is not allowed.

If the green check icon is displayed in the Manage ACL field, the corresponding two API functions for this field are set to true.

The value of this permission cannot be changed in the Enterprise Manager.

- Full - Has complete access to the secured object
- Access - Can actually connect to this realm
- Configure - Can set run time parameters on the realm
- Channels - Can add/delete channels on this realm
- Realm - Can add / remove realms from this realm
- Admin API - Can use the nAdminAPI package
- Manage DataGroups - Can add / remove data groups from this realm
- Pub DataGroups - Can publish to data groups (including default) on this realm
- Own DataGroups - Can add / delete publish to data groups even when they were not created by the user

The green check icon shows that a subject is permitted to perform the operation. For example, the subject `*@*` is shown as having no permissions for this realm. The minimum requirement for a client to use a realm is the 'Access' privilege. Without this privilege for the `*@*` subject, any Universal Messaging client attempting to connect, whose subject does not appear in the ACL list, will not be able to establish a session with the Realm Server.

In order to modify the permissions for a subject, you simply need to click on the cell in the ACL table for the subject and the operation you wish to modify permissions for. For example, if you want to grant the `*@*` user the 'Access' realm privilege, you would simply click on the `*@*` row at the column labelled 'access'. This would turn the cell from blank to a green check icon.

After making any changes, you then need to click on the 'Apply' button which will notify the Realm Server of the ACL change.

Any ACL changes that are made by other Enterprise Manager users, or from any programs using the Universal Messaging Admin API to modify ACLs will be received by all other Enterprise Managers. This is because ACL changes are automatically sent to all Universal Messaging Admin API clients, the Enterprise Manager being one of those clients.

Any changes made to a realm ACL where the realm is part of a cluster will be replicated to all other cluster realms.

## Channel Entitlements

## Channel ACLs

Once clients have established a session with a Universal Messaging Realm server, and they have successfully been authenticated and the subject has the correct user entitlements, in order to perform operations on channel objects, the correct entitlements must be granted to the subject on the required channels. Each channel has an associated ACL that contains a list of subjects and a set of privileges the subject is given for operations on the channel.

Using the Enterprise Manager, one can add to, remove or modify entries within the channel ACL.

To view a channel ACL, click on a channel node within the namespace of the Enterprise Manager, and select the 'ACL' tab. This will display the channel ACL and the list of subjects and their associated permissions for the channel. The following image displays an example of a channel ACL.

The screenshot shows the Nirvana Enterprise Manager interface. The left pane displays a tree view of the hierarchy: Nirvana Enterprise > Clusters > test > Realms > realm1 > ClusterRates. The right pane is divided into a 'Summary' tab and a 'Storage Properties' tab. The 'Summary' tab shows attributes for the selected object: Name (ClusterRates), Type (Transient), Age (0), Capacity (0), and Engine (Default). Below this is a 'Publish Keys' section. A toolbar contains icons for Status, Joins, ACL, Named Objects, Snoop, and Connections. The ACL panel is active, showing a table with the following data:

Name	Host	Manage ACL	This panel shows and manages		
*	*	✓	✓	✓	✓
pweiss	127.0.0.1	✓	✓	✓	✓

At the bottom of the interface, there are buttons for 'Add', 'Delete', and 'Apply'.

As you can see above, the channel ACL has a number of subject entries and operations that each subject is able to perform on the channel. The operations that can be performed on a channel are described below in the order in which they appear in the ACL panel above:

- Manage ACL - Allows the subject to get and manage the list of ACL entries.

**Note:**

This permission is a combination of two permissions at the Administration API level. The boolean `setModify()` API function allows/denies permission to change an ACL value, and the boolean `setList()` API function allows/denies permission to access the current list of ACLs. If both of these functions return the value true, Manage ACL is allowed, otherwise Manage ACL is not allowed.

If the green check icon is displayed in the Manage ACL field, the corresponding two API functions for this field are set to true. If you remove the green check icon, this sets the corresponding two API functions for this field to false.

- Full - Has complete access to the secured object
- Purge - Can delete events on this channel
- Subscribe - Can subscribe for events on this channel
- Publish - Can publish events to this channel
- Named - Can the user connect using a named (durable) subscriber

The green check icon shows that a subject is permitted to perform the operation. For example, if there is a subject `*@*` with only subscribe permissions for this channel, this means that any client who has successfully established a session and has obtained a reference to this channel within their application code can only subscribe to the channel and read events.

In order to modify the permissions for a subject, you simply need to click on the cell in the ACL table for the subject and the operation you wish to modify permissions for. For example, if you want to remove the subscribe permission for the `*@*` subject you would simply click on the `*@*` row at the column labelled 'subscribe'. This would turn the cell from blank to a green check icon. This would also ensure that only those subjects listed in the ACL and with sufficient privileges, would be able to perform any operations on the channel.

After making any changes, you then need to click on the 'Apply' button which will notify the Realm Server of the ACL change for that channel.

Any ACL changes that are made by other Enterprise Manager users, or from any programs using the Universal Messaging Admin API to modify ACLs will be received by all other Enterprise Managers. This is because ACL changes are automatically sent to all Universal Messaging Admin API clients, the Enterprise Manager being one of those clients.

Any changes made to a channel ACL where the channel is a cluster channel will be replicated to all other instances of the cluster channel in all other cluster realms.

## Queue Entitlements

### Queue ACLs

Once clients have established a session with a Universal Messaging Realm server, and they have successfully been authenticated and the subject has the correct user entitlements, in order to perform operations on queue objects, the correct entitlements must be granted to the subject on

the required queue. Each queue has an associated ACL that contains a list of subjects and a set of privileges the subject is given for operations on the queue.

Using the Enterprise Manager, one can add to, remove or modify entries within the queue ACL.

To view a queue ACL, click on a queue node within the namespace of the Enterprise Manager, and select the 'ACL' tab. This will display the queue ACL and the list of subjects and their associated permissions for the queue. The following image displays an example of a queue ACL.

The screenshot shows the Nirvana Enterprise Manager interface. The left pane displays a tree view of the hierarchy: Nirvana Enterprise > Clusters > test > Realms > realm1 > GlobalOrders. The right pane shows the 'ACL' tab for the selected 'GlobalOrders' queue. The 'Attributes' section lists Name, Type, Age, Capacity, and Engine. Below this, there are buttons for Status, Joins, ACL, and Snoop. The main area displays a table with the following data:

Name	Host	Manage ACL	Full	Purge
*	*	✓	✓	✓
administrator	127.0.0.1	✓	✓	✓

At the bottom of the interface, there are buttons for Add, Delete, and Apply.

As you can see above, the queue ACL has a number of subject entries and operations that each subject is able to perform on the queue. The operations that can be performed on a queue are described below in the order in which they appear in the acl panel above:

- Manage ACL - Allows the subject to get and manage the list of ACL entries.

**Note:**

This permission is a combination of two permissions at the Administration API level. The boolean `setModify()` API function allows/denies permission to change an ACL value, and the boolean `setList()` API function allows/denies permission to access the current list of ACLs. If both of these functions return the value true, Manage ACL is allowed, otherwise Manage ACL is not allowed.

If the green check icon is displayed in the Manage ACL field, the corresponding two API functions for this field are set to true. If you remove the green check icon, this sets the corresponding two API functions for this field to false.

- Full - Has complete access to the secured object
- Purge - Can delete events on this channel
- Peak - Can snoop this queue (non destructive read)
- Push - Can publish events to this queue
- Pop - Can Consume events on this queue (destructive read)

The green check icon shows that a subject is permitted to perform the operation. For example, the subject `*@*` is shown as having only peek permissions for this queue. This means that any client who has successfully established a session and has obtained a reference to this queue within their application code can only subscribe to the queue and read events.

In order to modify the permissions for a subject, you simply need to click on the cell in the ACL table for the subject and the operation you wish to modify permissions for. For example, if I wanted remove the peek permission for the `*@*` subject I would simply click on the `*@*` row at the column labelled 'peek'. This would turn the cell from blank to a green check icon. This would also ensure that only those subjects listed in the ACL and with sufficient privileges, would be able to perform any operations on the queue.

After making any changes, you then need to click on the 'Apply' button which will notify the Realm Server of the ACL change for that queue.

Any ACL changes that are made by other Enterprise Manager users, or from any programs using the Universal Messaging Admin API to modify ACLs will be received by all other Enterprise Managers. This is because ACL changes are automatically sent to all Universal Messaging Admin API clients, the Enterprise Manager being one of those clients.

Any changes made to a channel ACL where the queue is a cluster queue will be replicated to all other instances of the cluster queue in all other cluster realms.

## Interface VIA Rules

Each interface defined within a Universal Messaging Realm server can have an associated ACL list, known as a VIA list.

The VIA list enables list of users to be defined who are entitled to connect to the Universal Messaging realm using a specific protocol 'via' a specific interface.

If for example, a realm has an HTTP (nhp) interface running on port 10000, and we also want a sockets (nsp) interface running on port 15000, and you want all external clients to connect using the nhp interface, and all internal clients to connect using the nsp interface, this can be achieved by providing the nhp and nsp interfaces with a list of subjects that are able to connect via the different interfaces.

This ensures that any user that tries to connect via the nsp interface who is not part of the nsp interface VIA list but exists in the nhp via list will be rejected and will not be able to establish a connection via nsp. The same will apply for the nhp interface. Alternatively, by simply adding a list of via entries to the nhp interface (and leaving the nsp via list empty), any user trying to connect via nsp interface who is found in any other interface via list will be rejected. This allows you to tie specific users to specific interfaces.


The default behaviour for all interfaces is that when no VIA lists exist on any defined interfaces, all users can connect on any interface (Realm ACLs permitting, see [“Realm Entitlements” on page 161](#)). When a user subject exists on an interface, that subject cannot use any other interface other than the one they are listed in.

This is an extra level of security that allows administrators of Realm Servers to define a strict approach to who can connect to the realm via specific protocols. This is particularly useful if for example you run many services on a single Universal Messaging realm server and wish to ensure that specific clients / groups of clients are using completely separate interfaces.

### Interface ACL (VIA List)

In order to view the VIA list for an interface, select the realm where the interface is running, and then select the 'Interfaces' tab in the Enterprise Manager. From the interface list for the realm, select the interface from the table of interfaces, and choose the tab labelled 'VIA' from the bottom of the interface panel. The image below shows the result of an acl entry being added to the default socket interface running on port 9000. By adding this entry, the user johnsmith@192.168.1.2 can only use the nsp0 interface which is using the sockets protocol on port 9000.

As with all Universal Messaging ACLs wildcards are fully supported so that for example, \*@192.168.1.2 or johnsmith@\* are both relevant enforceable VIA rules.



Interface VIA entries can be added to by clicking on the 'Add' button from the VIA panel and entering the subject. Entries can be removed by selecting the entry and clicking the 'Delete' button.

Any changes to the interface VIA list will not take effect at the server until the 'Apply' button has been clicked on the VIA panel. Changes can also be disregarded without updating the server by clicking on the 'Cancel' button on the VIA list panel.

## Scheduling

Universal Messaging provides a sophisticated scheduling engine that enables tasks to be executed on a Realm Server at specific times or when certain conditions occur within the realm. This enables realm servers to automate important tasks, enabling them to self-manage without the need for intervention by administrators or externally scheduled tasks.

Administrators of Universal Messaging Realm servers can provide scripts that outline the conditions and tasks to be performed which are then interpreted by the server. The server converts the scripts into the actual tasks to be completed, and executes them under the correct conditions.

This section will guide you through the basics of Universal Messaging Scheduling. From the links found below you can learn the basic tasks that can be executed by a Realm Server, time based scheduling and conditional triggers, as well as how to write, modify and deploy scheduling scripts.

- [“Writing Scripts” on page 171](#)
- [“Time Based Scheduling” on page 175](#)
- [“Conditional Triggers” on page 177](#)
- [“Tasks” on page 189](#)
- [“The Universal Messaging Enterprise Manager Schedule Editor” on page 201](#)
- [“Example Scheduling Scripts” on page 209](#)

### **Universal Messaging Scheduling : Writing Schedule Scripts**

Universal Messaging scheduling works by interpreting scripts written using a simple grammar. Administrators of realms can deploy as many scheduling scripts as they wish to each Realm Server.

This section will cover the basic structure of a Universal Messaging scheduling script, and then show how to write a script and deploy it to the Realm Server.

Follow the links below to view the guide for each of these:

- [“Scheduling Grammar” on page 172](#)
- [“Declarations” on page 174](#)
- [“Initial Tasks” on page 174](#)
- [“Every Clause” on page 174](#)
- [“When Clause” on page 175](#)
- [“Else Clause” on page 175](#)

## Scheduling Grammar

The grammar for scheduling scripts is extremely simple to understand. The script must conform to a predefined structure and include elements that map to the grammar expected by the Realm Server Scheduler Engine.

In its simplest form the Universal Messaging scheduler syntax starts with the command `'scheduler'`. This tells the parser that a new scheduler task is being defined. This is followed by the name of the scheduler being defined, this is a user defined name. For example:

```
scheduler myScheduler {  
}
```

Within this structure, triggers and tasks are defined. A task is the actual operation the server will perform, and it can be executed at a certain time or frequency, or when a condition occurs. Within the scheduler context the following verbs can be used to define tasks to be executed.

- **declare** : Used to define the name of a trigger for later user
- **initialise** : Is the first thing run when a scheduler is started (also run when the realm server starts up)
- **every** : Used to define a time/calendar based event
- **when** : Used to define a conditional trigger and the list of tasks to execute when it fires
- **else** : Used after a conditional trigger that will fire if the condition evaluates to false

The following shows the basic grammar and structure of a scheduling script.

```
/*  
Comment block  
*/  
scheduler <User defined Name> {  
declare <TRIGGER_DECLARATION>+  
initialise {  
<TASK_DECLARATION>+  
}  
/*  
Time based tasks  
*/  
every <TIME_EXPRESSION> {  
<TASK_DECLARATION>+  
}  
when ( <TRIGGER_EXPRESSION> ) {  
<TASK_DECLARATION>+  
} else {  
<TASK_DECLARATION>+  
}  
}
```

where :

- **TRIGGER\_DECLARATION ::= <TRIGGER> <NAME> (<TRIGGER\_ARGUMENT\_LIST>)**
- **TRIGGER ::= Valid trigger. Learn more about triggers at ["Universal Messaging Scheduling : Conditional Triggers"](#) on page 177.**

- TRIGGER\_ARGUMENT\_LIST ::= Valid comma separated list of arguments for the trigger
- TASK\_DECLARATION ::= Valid task. Learn more about tasks at [“Universal Messaging Scheduling : Tasks” on page 189](#).
- TRIGGER\_EXPRESSION ::=  
 <TRIGGER\_EXPRESSION><LOGICAL\_OPERATOR><TRIGGER\_EXPRESSION> | <TRIGGER>  
 | <NAME><COMPARISON\_OPERATOR><VALUE>
- TIME\_EXPRESSION ::=  
 <HOURLY\_EXPRESSION> | <DAILY\_EXPRESSION> | <WEEKLY\_EXPRESSION> |  
 <MONTHLY\_EXPRESSION> | <YEARLY\_EXPRESSION>
- HOURLY\_EXPRESSION ::= <MINUTES>
- DAILY\_EXPRESSION ::= <HOUR> <COLON> <MINUTES>
- WEEKLY\_EXPRESSION ::= <DAYS\_OF\_WEEK> <SPACE> <HOUR> <COLON> <MINUTES>
- MONTHLY\_EXPRESSION ::= <DAY\_OF\_MONTH> <SPACE> <HOUR> <COLON> <MINUTES>
- YEARLY\_EXPRESSION ::= <DAY\_OF\_MONTH> <HYPHEN> <MONTH> <SPACE> <HOUR>  
 <COLON> <MINUTES>
- MINUTES ::= Minutes past the hour, i.e. a value between 00 and 59
- HOUR ::= Hour of the day, i.e. a value between 00 and 23
- DAYS\_OF\_WEEK ::=  
 <DAY\_OF\_WEEK> | <DAY\_OF\_WEEK> <SPACE> <DAY\_OF\_WEEK>
- DAY\_OF\_WEEK ::= Mo | Tu | We | Th | Fr | Sa | Su
- DAY\_OF\_MONTH ::= Specific day of the month to perform a task, i.e. a value between 01 and 28
- MONTH ::= The month of the year, JAN, FEB, MAR etc.
- NAME ::= The variable name for a trigger
- COMPARISON\_OPERATOR ::= > | => | < | <= | == | !=
- LOGICAL\_OPERATOR ::= AND | OR
- COLON ::= The ":" character
- SPACE ::= The space character
- HYPHEN ::= The "-" character
- + ::= indicates that this can occur multiple times
- VALUE ::= Any valid string or numeric value.

## Declarations

The declarations section of the script defines any triggers and assigns them to local variable names. The grammar notation defined above specifies that the declaration section of a schedule script can contain multiple declarations of triggers. For example, the following declarations section would be valid based on the defined grammar:

```
declare Config myGlobalConfig ("GlobalValues");
declare Config myAuditConfig ( "AuditSettings");
declare Config myTransConfig ( "TransactionManager");
```

The above declarations define 3 variables that refer to the the Config trigger. The declared objects can be used in a time based trigger declaration, conditional triggers and to perform tasks on.

## Initialise

The initialise section of the schedule script defines what tasks are executed straight away by the server when the script is deployed. These initial tasks are also executed every time the Realm Server is started. An example of a valid initialise section of a schedule script is shown below:

```
initialise {
Logger.report("Realm optimisation script and monitor startup initialising");
myAuditConfig.ChannelACL("false");
myAuditConfig.ChannelFailure("false");
myGlobalConfig.MaxBufferSize(2000000);
myGlobalConfig.StatusBroadcast(2000);
myGlobalConfig.StatusUpdateTime(86400000);
myTransConfig.MaxTransactionTime(3600000);
Logger.setLevel(4);
}
```

The example above ensures that each time a server starts, the tasks declared are executed. Using the variables defined in the declarations section, as well as the Logger task, the server will always ensure that the correct configuration values are set on the server whenever it starts.

## Every Clause

The every clause defines those tasks that are executed at specific times and frequencies as defined in the grammar above. Tasks can be executed every hour at a specific time pas the hour, every day at a certain time, every week on one or more days at specific times or day, every month on a specific day of the month and a specific day of the year.

The grammar above defines how to declare an every clause. Based on this grammar the following examples demonstrate how to declare when to perform tasks :

```
Hourly Example (Every half past the hour, log a message to the realm server log)
every 30 {
Logger.report("Hourly - Executing Tasks");
}
Daily Example (Every day at 18:00, perform maintenance on the customerSales channel
)
every 18:00 {
Logger.report("Daily - performing maintenance");
Store.maintain("/customer/sales");
```

```

}
Weekly Example (Every week, on sunday at 17:30, purge the customer sales channel)
every Su 17:30 {
Logger.report("Weekly - Performing Purge");
Store.purge("/customer/sales");
}
Monthly Example (Every 1st of the month, at 21:00, stop all interfaces and start them
again)
every 01 21:00 {
Logger.report("Monthly - Stopping interfaces and restarting");
Interface.stopAll();
Interface.startAll();
}
Yearly Example (Every 1st of the January, at 00:00, stop all interfaces and start them
again)
every 01-Jan 00:00 {
Logger.report("Yearly - Stopping interfaces and restarting");
Interface.stopAll();
Interface.startAll();
}

```

## When Clause

The when clause defines a trigger that evaluates a specific value and executes a task if the evaluation result is 'true'. The grammar for the when clause is defined above. The following example shows a valid when clause :

```

when (MemoryManager.FreeMemory < 30000000) {
Logger.report("Memory below 30M, performing some clean up");
FlushMemory(true);
}

```

The above example will trigger the Realm Server JVM to call garbage collection when the amount of free memory drops to below 30MB.

## Else Clause

The else clause defines an alternative action to the when clause if the when clause evaluates to 'false'. The grammar for the else clause is defined above. The following example shows a valid when clause :

```

when (MemoryManager.FreeMemory < 30000000) {
Logger.report("Memory below 30M, performing some clean up");
FlushMemory(true);
} else {
Logger.report("Memory not below 30M, no clean up required");
}

```

The above example will trigger the Realm Server JVM to call garbage collection when the amount of free memory drops to below 30MB.

To view a sample scheduling script, see the section [“Scheduler Examples” on page 209](#).

## Universal Messaging Scheduling : Calendar Triggers Schedules

Calendar schedules are triggered at specific times, either hourly, daily, weekly, monthly or yearly. Each calendar trigger is declared using the 'every' keyword. For basic information on the grammar for calendar schedules, please read the section on time based triggers in the writing scripts help file (see [“Universal Messaging Scheduling : Writing Schedule Scripts” on page 171](#)). The calendar, or time based triggers are signified by using the 'every' keyword. The values entered after the keyword represent hourly, daily, weekly, monthly or yearly frequency that the defined tasks will be executed. See [“Hourly Triggers” on page 176](#), [“Daily Triggers” on page 176](#), [“Weekly Triggers” on page 176](#), [“Monthly Triggers” on page 177](#), [“Yearly Triggers” on page 177](#).

This section will describe in more detail the variations of the calendar trigger grammar.

## Hourly Triggers

Hourly triggers have the simplest grammar. The value after the 'every' keyword represents the minutes past the hour that the tasks will be executed. For example, specifying '00' means that the tasks are executed on the hour, every hour. If you specify '30' the tasks will be executed at half past the hour every hour:

```
/*
  Execute every hour on the hour
*/
every 00 {
}
```

```
/*
  Execute every hour at half past the hour
*/
every 30 {
}
```

## Daily Triggers

Daily triggers are executed every day at a specific time. The time of day is written as 'HH:MM', in a 24 hour clock format and represents the exact time of day that the tasks are executed. For example, specifying '18:00' means the tasks are executed every day at 6pm. If you specify '08:30' the tasks will be executed at 8.30am every morning.

```
/*
  Execute day at 6pm
*/
every 18:00 {
}
```

```
/*
  Execute day at 8.30am
*/
every 08:30 {
}
```

## Weekly Triggers

Weekly triggers are executed on specific days of the week at a specific time, in the format 'DD HH:MM'. The days are represented as a 2 character string being one of : Su; Mo; Tu; We; Th; Fr;

Sa, and you can specify more than one day. The time of day is written as 'HH:MM', in a 24 hour clock format and represents the exact time on each given day that the tasks are executed. For example, specifying 'Fr 18:00' means the tasks are executed every friday at 6pm. If you specify 'Mo Tu We Th Fr 18:30' the tasks will be executed every week day at 6.30pm.

```
/*
  Execute every friday at 6pm
*/
every Fr 18:00 {
}
```

```
/*
  Execute every week day at 6.30pm
*/
every Mo Tu We Th Fr 18:30 {
}
```

## Monthly Triggers

Monthly triggers are executed on a specific day of the month at a specific time, in the format 'DD HH:MM'. The day is represented as a 2 digit number between 1 and 28. The time of day is written as 'HH:MM', in a 24 hour clock format and represents the exact time on the given day of the month that the tasks are executed. For example, specifying '01 18:00' means the tasks are executed on the 1st of every month at 6pm.

```
/*
  Execute on the first of every month at 6pm
*/
every 01 18:00 {
}
```

## Yearly Triggers

Yearly triggers are executed on a specific day and month of the year at a specific time, in the format 'DD-MMM HH:MM'. The day of the month is represented as a 2 digit number between 1 and 31, and the month is represented as a 3 character string being one of : Jan; Feb; Mar; Apr; May; Jun; Jul; Aug; Sep; Oct; Nov; Dec. The time of day is written as 'HH:MM', in a 24 hour clock format and represents the exact time on the given day and month of the year that the tasks are executed. For example, specifying '01-Jan 18:00' means the tasks are executed on the 1st of January every year at 6pm.

```
/*
  Execute on the first of january every year at 6pm
*/
every 01-Jan 18:00 {
}
```

## Universal Messaging Scheduling : Conditional Triggers

Conditional triggers execute tasks when specific conditions occur. Each defined trigger has a number of attributes that can be used as part of the trigger expression and evaluated to determine whether the tasks are executed. For basic information on the grammar for conditional triggers, please read the section on conditional triggers in the writing scripts help file (see [“Universal](#)

[Messaging Scheduling : Writing Schedule Scripts” on page 171](#)). The conditional triggers are signified by using the 'when' keyword. The expression entered after the keyword represent the trigger object(s) and the values to be checked against.

This section describes in detail the triggers that are available and how to use them within a trigger expression :

- [“Trigger Expressions” on page 178](#)
- [“Store Triggers” on page 179](#)
- [“Interface Triggers” on page 179](#)
- [“Memory Triggers” on page 180](#)
- [“Realm Triggers” on page 181](#)
- [“Cluster Triggers” on page 181](#)
- [“Counter Triggers” on page 182](#)
- [“Timer Triggers” on page 182](#)
- [“Config Triggers” on page 182](#)

To view examples of scheduling scripts, see [“Scheduler Examples” on page 209](#).

## Trigger Expressions

A trigger expression is constructed from the definition of the trigger object(s) to be evaluated and the values that will be used in the comparison. The trigger used in the expression can be either the actual trigger object, or the declared name of the trigger from the declarations section of the script (see [“Universal Messaging Scheduling : Writing Schedule Scripts” on page 171](#)). Multiple triggers can be used in the expression using conditional operators (AND | OR).

For example, the following expression can be used to evaluate when a Realm's Interface accept threads are exhausted 5 times. When this happens, the accept threads will be increased by 10. This schedule will continually monitor the state of the interface and self-manage the accept threads so the realm server is always able to accept connections from clients.

```
scheduler realmInterfaceSchedule {
declare Interface myNHP ("nhp0");
declare Counter myCounter("myExhaustedThreads");
when (myNHP.idleThreads == 0) {
Logger.report("NHP0 Interface has no idles Threads");
myCounter.inc();
}
when (myCounter >= 5) {
Logger.report("Increasing the accept thread count on NHP0");
myNHP.threads("+10");
myCounter.reset();
}
}
```

The above schedule will monitor the number of times the accept threads are exhausted and when the counter trigger hits 5 times, the number of threads will be increased by 10.

The next section will describe the available trigger objects and the available triggers on those objects that can be used within

### Store Triggers - Channel / Queue based triggers

Store triggers are declared using the following syntax as an example:

```
declare Store myChannel("/customer/sales");
```

The table below lists those triggers that can be evaluated on a Store object, such that the trigger expression will look like :

```
when (myChannel.connections > 100) {
}
```

Trigger Object	Parameters	Description
connections	None	Trigger on the number of connections for the channel or queue
freeSpace	None	Trigger on the amount of free space available in the store (used space - size of all purged events)
usedSpace		Trigger on the amount of used space available in the store (size of all event on disk or memory)
numOfEvents	None	Trigger on the number of events on the channel / queue
filter	Valid filter String	Trigger when an event that matches the filter is published to the channel / queue

### Interface Triggers - Universal Messaging Interface based triggers

Interface triggers are declared using the following syntax as an example:

```
declare Interface myNHP("nhp0");
```

The table below lists those triggers that can be evaluated on an Interface object, such that the trigger expression will look like :

```
when (myNHP.connections > 100) {
}
```

Trigger Object	Parameters	Description
connections	None	Trigger on the number of connections for the interface
authentication	None	Trigger on the average authentication time for clients on an interface
failedConnections	None	Trigger on the number of failed authentication attempts
exhaustedTime	None	Trigger on the average amount of time the interface accept thread pool has been exhausted
idleThreads	None	Trigger on the number of idle interface accept pool threads
exhaustedCount	None	Trigger on the number of times an interface accept thread pool is exhausted (i.e. idle == 0)
state	None	Trigger when an interface is in a certain state

### MemoryManager Triggers - Universal Messaging JVM Memory Management based triggers

MemoryManager triggers are declared using the following syntax as an example:

```
declare MemoryManager mem;
```

The table below lists those triggers that can be evaluated on the memory management object, such that the trigger expression will look like :

```
when (mem.freeMemory < 1000000) {
}
```

Trigger Object	Parameters	Description
freeMemory	None	Trigger when the realm server's JVM has a certain amount of free memory
totalMemory	None	Trigger when the realm server's JVM has a certain amount of total memory
outOfMemory	None	Trigger when the realm server JVM runs out of memory

## Realm Triggers - Universal Messaging Realm based triggers

Realm triggers are declared using the following syntax as an example:

```
declare Realm myRealm("productionmaster");
```

The table below lists those triggers that can be evaluated on the realm object, such that the trigger expression will look like :

```
when (realm.connections > 1000) {  
}
```

Trigger Object	Parameters	Description
connections	None	Trigger when the realm server current connections reaches a certain number
eventsSentPerSecond	None	Trigger when the realm server's events per second sent rate reaches a certain value
eventsReceivedPerSecond	None	Trigger when the realm server's events per second sent received reaches a certain value

## Cluster Triggers - Universal Messaging Cluster based triggers

Cluster triggers are declared using the following syntax as an example, assuming a cluster is made up of 4 realms:

```
declare Cluster myNode1("realm1");  
declare Cluster myNode2("realm2");  
declare Cluster myNode3("realm3");  
declare Cluster myNode4("realm4");
```

The table below lists those triggers that can be evaluated on the cluster object, such that the trigger expression will look like :

```
when ( Cluster.nodeOnline("realm1") == true ){  
}
```

Trigger Object	Parameters	Description
hasQuorum	None	Trigger when cluster has quorum == true or false
isMaster	None	Trigger when a cluster realm is voted master

Trigger Object	Parameters	Description
nodeOnline	None	Trigger when a cluster realm is online or offline

## Counter Triggers - Counter value based triggers

Counter triggers allow you to keep a local count of events occurring with the Universal Messaging scheduler engine. The values of the Counters can be incremented / decremented and reset within the tasks section of a trigger declaration. Counter triggers are declared using the following syntax as an example:

```
declare Counter counter1 ("myCounter");
```

The counter trigger can be evaluated by referencing the Counter object itself, such that the trigger expression will look like :

```
when ( counter1 > 5) {  
}
```

## Timer Triggers - Timer based triggers

Timer triggers allow you to start a timer that will keep track of how long (in seconds) it has been running and then evaluate the running time within a trigger expression. Time triggers are declared using the following syntax as an example:

```
declare Timer reportTimer ("myTimer");
```

The timer trigger can be evaluated by referencing the timer object itself, such that the trigger expression will look like :

```
when ( reportTimer == 60 ) {  
}
```

## Config Triggers - Universal Messaging configuration triggers

Config triggers refer to any of the configuration values available in the Config panel for a realm. Any configuration value can be used as part of a trigger expression. Config triggers are declared using the following syntax as an example (the example refers to the 'Global Values' configuration group):

```
declare Config myGlobal ("Global Values");
```

The table below lists the triggers that can be evaluated on a Config object, such that the task expression will look like :

```
when (myGlobal.MaxNoOfConnections == -1) {  
}
```

Trigger Object	Parameters	Description
<b>Global Values</b>		
SchedulerPoolSize	None	The number of threads assigned to the scheduler
MaxNoOfConnections	None	Sets the maximum concurrent connections to the server, -1 indicates no restriction
StatusUpdateTime	None	The number of ms between status events being written to disk
StatusBroadcast	None	The number of ms between status events being published
NHPTimeout	None	The number of milliseconds the server will wait for client authentication
NHPScanTime	None	The number of milliseconds that the server will wait before scanning for client timeouts
HandshakeTimeout	None	The number of milliseconds that the server will wait for the session to be established
StampDictionary	None	Place Universal Messaging details into the dictionary (true/false)
ExtendedMessageSelector	None	If true, allows the server to use the extended message selector syntax (true/false)
ServerTime	None	Allow the server to send the current time to the clients (true/false)
SecureHandshake	None	Performs a security handshake when connecting into a cluster
ConnectionDelay	None	When the server has exceeded the connection count, how long to hold on to the connection before disconnecting
SupportVersion2Clients	None	Allow the server to support older clients (true/false)

Trigger Object	Parameters	Description
SendRealmSummaryStats	None	If true sends the realms status summary updates (true/false)
<b>Audit Settings</b>		
RealmMaintenance	None	Log to the audit file any realm maintenance activity
InterfaceManagement	None	Log to the audit file any interface management activity
ChannelMaintenance	None	Log to the audit file any channel maintenance activity
QueueMaintenance	None	Log to the audit file any queue maintenance activity
ServiceMaintenance	None	Log to the audit file any service maintenance activity
JoinMaintenance	None	Log to the audit file any join maintenance activity
RealmSuccess	None	Log to the audit file any successful realm interactions
ChannelSuccess	None	Log to the audit file any successful channel interactions
QueueSuccess	None	Log to the audit file any successful queue interactions
ServiceSuccess	None	Log to the audit file any successful realm interactions
JoinSuccess	None	Log to the audit file any successful join interactions
RealmFailure	None	Log to the audit file any unsuccessful realm interactions
ChannelFailure	None	Log to the audit file any unsuccessful channel interactions
QueueFailure	None	Log to the audit file any unsuccessful queue interactions

Trigger Object	Parameters	Description
ServiceFailure	None	Log to the audit file any unsuccessful service interactions
JoinFailure	None	Log to the audit file any unsuccessful join interactions
RealmACL	None	Log to the audit file any unsuccessful realm acl interactions
ChannelACL	None	Log to the audit file any unsuccessful channel acl interactions
QueueACL	None	Log to the audit file any unsuccessful queue acl interactions
ServiceACL	None	Log to the audit file any unsuccessful service acl interactions
<b>Client Timeout Values</b>		
EventTimeout	None	The amount of ms the client will wait for a response from the server
DisconnectWait	None	The maximum amount of time to wait when performing an operation when disconnected before throwing session not connected exception
TransactionLifeTime	None	The default amount of time a transaction is valid before being removed from the tx store
KaWait	None	The amount of time the client will wait for keep alive interactions between server before acknowledging disconnected state
LowWaterMark	None	The low water mark for the connection internal queue. When this value is reached the outbound internal queue will

Trigger Object	Parameters	Description
		again be ready to push event to the server
HighWaterMark	None	The high water mark for the connection internal queue. When this value is reached the internal queue is temporarily suspended and unable to send events to the server. This provides flow control between publisher and server.
QueueBlockLimit	None	The maximum number of milliseconds a queue will have reached HWM before notifying listeners
QueueAccessWaitLimit	None	The maximum number of milliseconds it should take to gain access to a queue to push events before notifying listeners
QueuePushWaitLimit	None	The maximum number of milliseconds it should take to gain access to a queue and to push events before notifying listeners
<b>Cluster Config</b>		
HeartBeatInterval	None	Heart Beat interval in milliseconds
SeparateLog	None	Create a separate log file for cluster events
EventsOutStanding	None	Number of events outstanding
<b>Event Storage</b>		
CacheAge	None	The time in ms that cached events will be kept in memory for
ThreadPoolSize	None	The number of threads allocated to perform the management task on the channels

Trigger Object	Parameters	Description
ActiveDelay	None	The time in milliseconds that an active channel will delay between scans
IdleDelay	None	The time in milliseconds that an idle channel will delay between scans
<b>Fanout Values</b>		
ConcurrentUser	None	The number of client threads allowed to execute concurrently in the server
KeepAlive	None	The number of milliseconds between the server will wait before sending a heartbeat
QueueHighWaterMark	None	The number of events in a client output queue before the server stops sending events
QueueLowWaterMark	None	The number of events in the clients queue before the server resumes sending events
MaxBufferSize	None	The maximum buffer size that the server will accept
PublishDelay	None	How long to delay the publisher when subscribers queue start to fill, in milliseconds
RoundRobinDelivery	None	Use a round robin approach to event delivery (true/false)
PublishExpiredEvents	None	Publish expired events at server startup (true/false)
<b>JVM Management</b>		
MemoryMonitoring	None	Number of milliseconds between monitoring memory usage on the realm

Trigger Object	Parameters	Description
WarningThreshold	None	The memory threshold when the server starts to scan for objects to release
EmergencyThreshold	None	The memory threshold when the server starts to aggressively scan for objects to release
ExitOnMemoryError	None	If true, the server will exit if it gets an out of memory exception
ExitOnDiskIOError	None	If true, the server will exit if it gets a I/O Exception
<b>Join Config</b>		
MaxEventsPerSchedule	None	Number of events that will be sent to the remote server in one run
MaxQueueSizeToUse	None	The maximum events that will be queued on behalf of the remote server
ActiveThreadPoolSize	None	The number of threads to be assigned for the join recovery
IdleThreadPoolSize	None	The number of threads to manage the idle and reconnection to remote servers
<b>Logging Config</b>		
fLoggerLevel	None	The server logging level
<b>RecoveryDaemon</b>		
ThreadPool	None	Number of threads to use for client recovery
EventsPerBlock	None	The number of events to send in one block
<b>TransactionManager</b>		

Trigger Object	Parameters	Description
MaxTransactionTime	None	Time in milliseconds that a transaction will be kept active
MaxEventsPerTransaction	None	The maximum number of events per transaction, a 0 indicates no limit
TTLThreshold	None	The minimum time in milliseconds, below which the server will not store the Transaction ID

## Universal Messaging Scheduling : Tasks

Tasks are executed by either time based (calendar, see [“Universal Messaging Scheduling : Calendar Triggers Schedules”](#) on page 175) or conditional triggers (see [“Universal Messaging Scheduling : Conditional Triggers”](#) on page 177). There are a number of tasks that can be executed by the Universal Messaging Scheduling engine. Each task corresponds to a unit of work that performs an operation on the desired object within a Universal Messaging realm.

This section will discuss the available tasks that can be declared within a Universal Messaging scheduling script :

- [“Task Expressions”](#) on page 189
- [“Store Tasks”](#) on page 190
- [“Interface Tasks”](#) on page 191
- [“Memory Tasks”](#) on page 192
- [“Counter Tasks”](#) on page 192
- [“Timer Tasks”](#) on page 193
- [“Config Tasks”](#) on page 193

To view examples of scheduling scripts, see [“Scheduler Examples”](#) on page 209.

## Task Expressions

Task expressions are comprised of the object on which you wish to perform the operation, and the required parameters. For more information on the grammar for task expressions, please see the writing scripts help file (see [“Universal Messaging Scheduling : Writing Schedule Scripts”](#) on page 171). The following sections will describe the task objects and the parameters required to perform them. The example below demonstrates both Interface, Logger and Counter tasks.

```
scheduler realmInterfaceSchedule {
declare Interface myNHP ("nhp0");
declare Counter myCounter("myExhaustedThreads");
```

```

when (myNHP.idleThreads == 0) {
  Logger.report("NHP0 Interface has no idles Threads");
  myCounter.inc();
}
when (myCounter >= 5) {
  Logger.report("Increasing the accept thread count on NHP0");
  myNHP.threads("+10");
  myCounter.reset();
}
}

```

## Store Tasks - Channel / Queue operations

Store tasks can be used by first of all declaring the desired object as in the following syntax:

```
declare Store myChannel("/customer/sales");
```

The table below lists those tasks available on a Store object, such that the task expression will look like :

```

when (myChannel.numOfEvents < 100) {
  myChannel.maintain();
}

```

Task Object	Syntax	Description
maintain	<pre>Store.maintain("*"); Store.maintain("/customer/sales"); myChannel.maintain();</pre>	Perform maintenance on a channel so that any purged events are removed from the channel or queue event store.
publish	<pre>myChannel.publish("Byte array data", "tag", "key1=value1:key2=value2" );</pre>	Publish an event to the channel / queue, using the given byte array, event tag and event dictionary values.
purge	<pre>myChannel.purge(); myChannel.purge(0, 100000); myChannel.purge(0, 10000, "key1 = 'value1'");</pre>	Purge all events on a channel, or events between a start and end eid, or using a purge filter.
createChannel	<pre>myChannel.createChannel(0, 0, "P");</pre>	Create the channel using the name it was declared as, and the ttl, capacity and type specified in the parameters
createQueue	<pre>myChannel.createQueue(0, 0, "P");</pre>	Create the queue using the name it was declared as, and the ttl, capacity and type specified in the parameters

## Interface Tasks - Universal Messaging Interface operations

Interface tasks are operations that can be performed on all interfaces or individually declared interfaces. To declare an interface use the following syntax as an example:

```
declare Interface myNHP("nhp0");
```

The table below lists those tasks that can be executed on an Interface object, such that the task expression will look like :

```
when (myNHP.connections > 1000) {
myNHP.threads("+10");
}
```

Task Object	Syntax	Description
stop	myNHP.stop(); Interface.stop("nhp0");	Stop the interface
start	myNHP.start(); Interface.start("nhp0");	Start The interface
stopAll	Interface.stopAll();	Stop all interfaces on the realm
startAll	Interface.startAll();	Start all interfaces on the realm
authTime	myNHP.authTime(20000); myNHP.authTime("+10000");	Set the interface authentication time to a value, or increase / decrease it by a value.
backlog	myNHP.backlog(200); myNHP.backlog("+100");	Set the interface backlog time to a value, or increase / decrease it by a value.
autoStart	myNHP.autoStart("true"); myNHP.autoStart("false");	Set whether an interface is automatically started when the realm is started.
advertise	myNHP.advertise("true"); myNHP.advertise("false");	Set whether an interface is available to clients using the admin API.
certificateValidation	myNHP.certificateValidation("true"); myNHP.certificateValidation("false");	Set whether an interface (SSL) requires clients to provide a

Task Object	Syntax	Description
		certificate to authenticate.
threads	myNHP.threads(10); myNHP.threads("+10");	Set the interface accept threads to a value or increase / decrease it by a value.

## MemoryManager Triggers - Universal Messaging JVM Memory Management operations

MemoryManager triggers are declared using the following syntax as an example:

```
declare MemoryManager mem;
```

The table below lists those triggers that can be evaluated on the memory management object, such that the task expression will look like :

```
when (mem.freeMemory < 1000000) {  
}
```

Task Object	Syntax	Description
flush	mem.flush(true); mem.flush(false);	Cause the JVM to call garbage collection, and optionally release used memory

## Counter Tasks - Counter tasks

Counter tasks allow you to increment, decrement, set and reset a local counter within the Universal Messaging scheduling engine. Counter tasks are declared using the following syntax as an example:

```
declare Counter counter1 ("myCounter");
```

The counter task can be executing by referencing the Counter object itself, and calling one of a number of available tasks. The basic counter task expression will look like :

```
when ( counter1 > 5) {  
counter1.reset();  
}
```

The table below shows the tasks that can be executed on the Counter task.

Task Object	Syntax	Description
dec	counter1.dec()	Decrement the counter by 1
inc	counter1.inc()	Increment the counter by 1

Task Object	Syntax	Description
set	counter1.set(5)	Set the counter to a value
reset	counter1.reset()	Reset the counter to 0

## Timer Tasks - Timer operations

Timer tasks allow you to start, stop and reset the timer. Time tasks are declared using the following syntax as an example:

```
declare Timer reportTimer ("myTimer");
```

The timer task can be executed by referencing the timer object itself, such that the task expression will look like :

```
when ( reportTimer == 60 ) {
  reportTimer.reset();
}
```

The table below shows the tasks that can be executed on the Counter task.

Task Object	Syntax	Description
start	reportTimer.start()	Start the timer
inc	reportTimer.stop()	Stop the timer
reset	reportTimer.reset()	Reset the timer

## Config Tasks - Channel / Queue based triggers

Config tasks can be used to set any configuration value available in the Config panel for a realm. Any configuration value can be used as part of a trigger task expression. Config tasks are declared using the following syntax as an example (below example refers to the 'Global Values' configuration group):

```
declare Config myGlobal ("Global Values");
declare Config myAudit ("Audit Settings");
declare Config myClientTimeout ("Client Timeout Values");
declare Config myCluster ("Cluster Config");
declare Config myEventStorage ("Event Storage");
declare Config myFanout ("Fanout Values");
declare Config myJVM ("JVM Management");
declare Config myJoinConfig ("Join Config");
declare Config myLoggingConfig ("Logging Config");
declare Config myRecovery ("RecoveryDaemon");
declare Config myTXMgr ("TransactionManager");
```

The table below lists those tasks that can be evaluated on a config object, such that the task expression will look like :

```
when (myGlobal.MaxNoOfConnections == -1) {
```

```
myGlobal.MaxNoOfConnections(1000);
}
```

Trigger Object	Syntax	Description
<b>Global Values</b>		
SchedulerPoolSize	myGlobal.SchedulerPoolSize(10);	The number of threads assigned to the scheduler
MaxNoOfConnections	myGlobal.MaxNoOfConnections(-1);	Sets the maximum concurrent connections to the server, -1 indicates no restriction
StatusUpdateTime	myGlobal.StatusUpdateTime(60000);	The number of ms between status events being written to disk
StatusBroadcast	myGlobal.StatusBroadcast(2000);	The number of ms between status events being published
NHPTimeout	myGlobal.NHPTimeout(2000);	The number of milliseconds the server will wait for client authentication
NHPScanTime	myGlobal.NHPScanTime(10000);	The number of milliseconds that the server will wait before scanning for client timeouts
HandshakeTimeout	myGlobal.HandshakeTimeout(12000);	The number of milliseconds that the server will wait for the session to be established
StampDictionary	myGlobal.StampDictionary(true);	Place Universal Messaging details into the dictionary (true/false)
ExtendedMessageSelector	myGlobal.ExtendedMessageSelector (true);	If true, allows the server to use the extended message selector syntax (true/false)

Trigger Object	Syntax	Description
ServerTime	myGlobal.ServerTime(true);	Allow the server to send the current time to the clients (true/false)
SecureHandshake	myGlobal.SecureHandshake(true);	Performs a security handshake when connecting into a cluster
ConnectionDelay	myGlobal.ConnectionDelay(2000);	When the server has exceeded the connection count, how long to hold on to the connection before disconnecting
SupportVersion2Clients	myGlobal.SupportVersion2Clients (true);	Allow the server to support older clients (true/false)
SendRealmSummaryStats	myGlobal.SendRealmSummaryStats (true);	If true sends the realms status summary updates (true/false)
<b>Audit Settings</b>		
RealmMaintenance	myAudit.RealmMaintenance (false);	Log to the audit file any realm maintenance activity
InterfaceManagement	myAudit.InterfaceManagement (false);	Log to the audit file any interface management activity
ChannelMaintenance	myAudit.ChannelMaintenance (false);	Log to the audit file any channel maintenance activity
QueueMaintenance	myAudit.QueueMaintenance (false);	Log to the audit file any queue maintenance activity
ServiceMaintenance	myAudit.ServiceMaintenance (false);	Log to the audit file any service maintenance activity
JoinMaintenance	myAudit.JoinMaintenance(false);	Log to the audit file any join maintenance activity

Trigger Object	Syntax	Description
RealmSuccess	myAudit.RealmSuccess(false);	Log to the audit file any successful realm interactions
ChannelSuccess	myAudit.ChannelSuccess(false);	Log to the audit file any successful channel interactions
QueueSuccess	myAudit.QueueSuccess(false);	Log to the audit file any successful queue interactions
ServiceSuccess	myAudit.ServiceSuccess(false);	Log to the audit file any successful realm interactions
JoinSuccess	myAudit.JoinSuccess(false);	Log to the audit file any successful join interactions
RealmFailure	myAudit.RealmFailure(false);	Log to the audit file any unsuccessful realm interactions
ChannelFailure	myAudit.ChannelFailure(false);	Log to the audit file any unsuccessful channel interactions
QueueFailure	myAudit.QueueFailure(false);	Log to the audit file any unsuccessful queue interactions
ServiceFailure	myAudit.ServiceFailure(false);	Log to the audit file any unsuccessful service interactions
JoinFailure	myAudit.JoinFailure(false);	Log to the audit file any unsuccessful join interactions
RealmACL	myAudit.RealmACL(false);	Log to the audit file any unsuccessful realm acl interactions
ChannelACL	myAudit.ChannelACL(false);	Log to the audit file any unsuccessful channel acl interactions

Trigger Object	Syntax	Description
QueueACL	myAudit.QueueACL(false);	Log to the audit file any unsuccessful queue acl interactions
ServiceACL	myAudit.ServiceACL(false);	Log to the audit file any unsuccessful service acl interactions
<b>Client Timeout Values</b>		
EventTimeout	myClientTimeout.EventTimeout (10000);	The amount of ms the client will wait for a response from the server
DisconnectWait	myClientTimeout.DisconnectWait (30000);	The maximum amount of time to wait when performing an operation when disconnected before throwing session not connected exception
TransactionLifeTime	myClientTimeout.TransactionLifeTime (10000);	The default amount of time a transaction is valid before being removed from the tx store
KaWait	myClientTimeout.KaWait(10000);	The amount of time the client will wait for keep alive interactions between server before acknowledging disconnected state
LowWaterMark	myClientTimeout.LowWaterMark (200);	The low water mark for the connection internal queue. When this value is reached the outbound internal queue will again be ready to push event to the server
HighWaterMark	myClientTimeout.HighWaterMark (500);	The high water mark for the connection internal queue. When this value is reached the internal

Trigger Object	Syntax	Description
		queue is temporarily suspended and unable to send events to the server. This provides flow control between publisher and server.
QueueBlockLimit	myClientTimeout.QueueBlockLimit (5000);	The maximum number of milliseconds a queue will have reached HWM before notifying listeners
QueueAccessWaitLimit	myClientTimeout.QueueAccessWaitLimit (10000);	The maximum number of milliseconds it should take to gain access to a queue to push events before notifying listeners
QueuePushWaitLimit	myClientTimeout.QueuePushWaitLimit (12000);	The maximum number of milliseconds it should take to gain access to a queue and to push events before notifying listeners
<b>Cluster Config</b>		
HeartBeatInterval	myCluster.HeartBeatInterval (60000);	Heart Beat interval in milliseconds
SeparateLog	myCluster.SeparateLog(true);	Create a separate log file for cluster events
EventsOutStanding	myCluster.EventsOutStanding (10);	Number of events outstanding
<b>Event Storage</b>		
CacheAge	myEventStorage.CacheAge(360000);	The time in ms that cached events will be kept in memory for
ThreadPoolSize	myEventStorage.ThreadPoolSize(2);	The number of threads allocated to perform the

Trigger Object	Syntax	Description
		management task on the channels
ActiveDelay	myEventStorage.ActiveDelay(1000);	The time in milliseconds that an active channel will delay between scans
IdleDelay	myEventStorage.IdleDelay(60000);	The time in milliseconds that an idle channel will delay between scans
<b>Fanout Values</b>		
ConcurrentUser	myFanout.ConcurrentUser(5);	The number of client threads allowed to execute concurrently in the server
KeepAlive	myFanout.KeepAlive(60000);	The number of milliseconds between the server will wait before sending a heartbeat
QueueHighWaterMark	myFanout.QueueHighWaterMark(500);	The number of events in a client output queue before the server stops sending events
QueueLowWaterMark	myFanout.QueueLowWaterMark(200);	The number of events in the clients queue before the server resumes sending events
MaxBufferSize	myFanout.MaxBufferSize(1024000);	The maximum buffer size that the server will accept
PublishDelay	myFanout.PublishDelay(100);	How long to delay the publisher when subscribers queue start to fill, in milliseconds
RoundRobinDelivery	myFanout.RoundRobinDelivery(true);	Use a round robin approach to event delivery (true/false)

Trigger Object	Syntax	Description
PublishExpiredEvents	myFanout.PublishExpiredEvents(true);	Publish expired events at server startup (true/false)
<b>Join Config</b>		
MaxEventsPerSchedule	myJoinConfig.MaxEventsPerSchedule (200);	Number of events that will be sent to the remote server in one run
MaxQueueSizeToUse	myJoinConfig.MaxQueueSizeToUse (50);	The maximum events that will be queued on behalf of the remote server
ActiveThreadPoolSize	myJoinConfig.ActiveThreadPoolSize (4);	The number of threads to be assigned for the join recovery
IdleThreadPoolSize	myJoinConfig.IdleThreadPoolSize (2);	The number of threads to manage the idle and reconnection to remote servers
<b>Logging Config</b>		
fLoggerLevel	myLoggingConfig.fLoggerLevel(4);	The server logging level
<b>RecoveryDaemon</b>		
ThreadPool	myRecovery.ThreadPool(5);	Number of threads to use for client recovery
EventsPerBlock	myRecovery.EventsPerBlock(300);	The number of events to send in one block
<b>TransactionManager</b>		
MaxTransactionTime	myTXMgr.MaxTransactionTime (1000);	Time in milliseconds that a transaction will be kept active
MaxEventsPerTransaction	myTXMgr.MaxEventsPerTransaction (1000);	The maximum number of events per


Trigger Object	Syntax	Description
		transaction, a 0 indicates no limit
TTLThreshold	myTXMgr.TTLThreshold(1000);	The minimum time in milliseconds, below which the server will not store the Transaction ID

### Universal Messaging Scheduling: Editor


The Universal Messaging Enterprise Manager provides a scheduler panel that enables the user to view, add, delete and edit scheduler scripts. To view the scheduler panel, select the realm from the namespace and click on the 'Scheduler' tab.

The scheduler panel displays all scripts that have been deployed to the server within a table. This table shows the name of the schedule, as defined within the script, the user name of the person the script will be executed using (i.e. the user name of the Enterprise Manager user who deployed the script, as well as whether the script is to be deployed cluster wide (i.e. to all realms within the cluster node).


The image below shows the scheduler panel with no scheduling entries.



The button labelled 'Add New' when clicked will display a dialog containing a script editing panel that has been designed to assist with the creation of scheduling scripts. The scheduling grammar is discussed in more detail in the writing scripts section (see [“Universal Messaging Scheduling : Writing Schedule Scripts”](#) on page 171), as well as the calendar, triggers and tasks sections (see [“Universal Messaging Scheduling : Calendar Triggers Schedules”](#) on page 175, [“Universal Messaging Scheduling : Conditional Triggers”](#) on page 177 and [“Universal Messaging Scheduling : Tasks”](#) on page 189). The image below shows the script editor panel.



Once your script is complete, in order to deploy the schedule to the server, you need to click on the 'OK' button. Once clicked, if there are any errors or problems with the script, you will be presented with a dialog similar to the image below.



If the script does not contain any errors, the script editor panel will close and the new scheduler script will then appear within the scheduler table. Clicking on the newly created scheduler within the table will enable you to delete, view and edit the schedule. The image below shows the newly created scheduler script once selected. There are 4 scheduler panels available for each scheduler

selected from the table. Each panel is represented by a tab on the bottom half of the main scheduler panel. Each of these panels is discussed below.

### **Script Editor Panel**

The script editor panel is denoted by the tab labelled 'Script Editor' and provides the same editor view found when you first add a new script. This panel is a simple editor pane that enables you to modify the scheduler triggers and tasks. The image below shows this panel selected from the available tabs.

The screenshot shows the Nirvana Enterprise Manager interface. The left pane displays a tree view of the realm hierarchy, including Clusters, Realms (realm1, realm2, realm3), and various sub-entities like ClusterRates, Data Groups, GlobalOrders, naming, uk, GlobalOrderStatus, defaultContext, and GlobalOrderStatus. The right pane shows the Scheduler script editor, which is currently displaying the 'Initial Tasks' tab. The script editor contains a scheduler script for 'realmSchedule' with the following code:

```

/*
This is an example scheduler script
*/
scheduler realmSchedule {

    declare Config myGlobalConfig ("GlobalValues");
    declare Config myAuditConfig ("AuditSettings");
    declare Config myTransConfig ("TransactionManager");

    initialise {

        Logger.report("Realm optimisation script and monitor startup initialising");
        myAuditConfig.ChannelACL("false");
        myAuditConfig.ChannelFailure("false");
        myGlobalConfig.MaxBufferSize(2000000);
        myGlobalConfig.StatusBroadcast(2000);
        myGlobalConfig.StatusUpdateTime(86400000);
        myTransConfig.MaxTransactionTime(3600000);
        Logger.setLevel(4);
    }
}

```


Below the script editor, there are buttons for 'Apply Changes' and 'Undo'. Above the script editor, there are tabs for 'Script Editor', 'Initial Tasks', 'Triggered Tasks', and 'Calendar Tasks'. Above the table, there are buttons for 'Add New' and 'Delete'.

Name	Runtime Subject
s	administrator@*

## Initial Tasks Panel

The initial tasks panel is denoted by the tab labelled 'Initial Tasks' and represents those tasks defined within the initialisation section of the scheduler script. Each initial task is represented as a row in a table with 3 columns. Column 1 labelled 'Task' is the task object (see [“Universal Messaging Scheduling : Tasks”](#) on page 189). Column 2 labelled 'Function / Object' represents the details of the task, for example, if the task was to purge a channel, column 2 would show 'purge'.

Column 3 labelled 'Parameter' shows any parameters listed in the scheduler script for the given task. The image below shows an example of the Initial Tasks tab being selected.



## Triggered Tasks

The triggered tasks panel is denoted by the 'Triggered Tasks' tab. This panel displays those tasks that are triggered based on some conditional triggers. Each conditional trigger is shown as a row in the table within this panel. Selecting a trigger from this table will then display the tasks to be

executed when this trigger is fired. Each task is shown in a table similar to that found in the Initial Tasks panel. The image below shows the triggered tasks panel being selected.

The screenshot shows the 'Nirvana Enterprise Manager' interface. The left sidebar displays a tree view of the system hierarchy, including Clusters, Realms, and various configuration objects. The main panel displays the 'Triggered Tasks' tab, which shows a table of triggered tasks for 'realm1'.

The 'Triggered Tasks' table has the following columns: Trigger Object, Trigger Cor, Task, Function / Object, and a fourth column (partially visible).

Trigger Object	Trigger Cor	Task	Function / Object	
MemoryManager	< 30000000	Logger	report	Memory bel
		MemoryManager	FlushMemory	true
		Logger	report	Memory not

At the bottom of the panel, there are buttons for 'Apply Changes' and 'Undo'.

## Calendar Tasks

The final panel is the calendar tasks panel and is denoted by the 'Calendar Tasks' tab. This panel shows the tasks that are scheduled to run at specific times. Each calendar task is shown as a row within a table. This table has a total of 11 columns. The first 2 columns show the frequency and

time. The frequency is either 'Hourly', 'Daily', 'Weekly', 'Monthly' or 'Yearly' and the time is specified as HH:MM. For hourly schedules, the HH (hours) will be displayed as XX which denotes every hour.

Columns 3 to 9 represent which days of the week the task will run, starting from Monday ('Mo'). A green circle means the task will run on that day. The last 2 columns represent the Day and Month the task will run.

Selecting one of the rows in the table will display the actual tasks that will be executed in a similar table to that found in the triggered tasks panel. The image below shows the calendar tasks panel with a task selected.

The screenshot shows the Nirvana Enterprise Manager interface. The left pane displays a tree view of the configuration hierarchy, including Clusters, Realms, and various sub-objects like ClusterRates, Data Groups, GlobalOrders, naming, uk, GlobalOrderStatus, and defaultContext. The right pane shows the configuration details for a selected realm, including a table for the scheduler configuration.

The Scheduler configuration table is as follows:

Occu...	Time	Mo	Tu	We	Th	Fr	Sa	S
Hourly	xx:30	✓	✓	✓	✓	✓	✓	✓
Daily	18:00	✓	✓	✓	✓	✓	✓	✓
Weekly	17:30			✓				
Monthly	21:00							
Yearly	00:00							

Below the table, there is a section for 'Task' and 'Function / Object' with the following entries:

Task	Function / Object
Logger	report

The interface also includes buttons for 'Apply Changes' and 'Undo Changes' at the bottom.

Any changes made to the schedule within the script editor panel can either be deployed to the realm server by clicking on the 'Apply Changes' button or discarded by clicking on the 'Undo Changes' button.

Schedule entries can be deleted from the server by selecting them from the main scheduler table and clicking on the 'Delete' button.

## Scheduler Examples

Below is a list of example scheduling scripts that can help you become accustomed to writing Universal Messaging Scheduling scripts.

- “Generic Example” on page 210
- “Store Triggers” on page 211
- “Interface Triggers” on page 212
- “Memory Triggers” on page 212
- “Realm Triggers” on page 213
- “Cluster Triggers” on page 213
- “Counter Triggers” on page 214
- “Timer Triggers” on page 214
- “Config Triggers” on page 215

### Universal Messaging Scheduling : Example Realm Script

```
/*
Comments must be enclosed in /* and */ sections
This is an example scheduler script
*/
scheduler realmSchedule {
  declare Config myGlobalConfig ("GlobalValues");
  declare Config myAuditConfig ( "AuditSettings");
  declare Config myTransConfig ( "TransactionManager");
  initialise {
    Logger.report("Realm optimisation script and monitor startup initialising");
    myAuditConfig.ChannelACL("false");
    myAuditConfig.ChannelFailure("false");
    myGlobalConfig.MaxBufferSize(2000000);
    myGlobalConfig.StatusBroadcast(2000);
    myGlobalConfig.StatusUpdateTime(86400000);
    myTransConfig.MaxTransactionTime(3600000);
    Logger.setlevel(4);
  }
  every 30 {
    Logger.report("Hourly - Executing Tasks");
  }
  every 18:00 {
    Logger.report("Daily - performing maintenance");
    Store.maintain("/customer/sales");
  }
  every We 17:30 {
    Logger.report("Weekly - Performing Purge");
    Store.purge("/customer/sales");
  }
  every 01 21:00 {
    Logger.report("Monthly - Stopping interfaces and restarting");
    Interface.stopAll();
    Interface.startAll();
  }
  every 01-Jan 00:00 {
```

```

Logger.report("Yearly - Stopping interfaces and restarting");
Interface.stopAll();
Interface.startAll();
}
when (MemoryManager.FreeMemory <30000000) {
Logger.report("Memory below 30M, performing some clean up");
MemoryManager.FlushMemory("true");
} else {
Logger.report("Memory not below 30M, no clean up required");
}
}
}

```

## Universal Messaging Scheduling : Store Triggers Example

```

scheduler myStore {
  declare Store myPubChannel("myChannel");
  declare Store myPubQueue("myQueue");
  /*
  Create the channels if they do not exist on the server
  */
  initialise{
    myPubChannel.createChannel( 0, 0, "P");
    myPubQueue.createQueue( 0, 0, "M");
    myPubChannel.publish("Data to store in the byte array", "tag info",
      "key1=value1:key2=value2" );
    myPubQueue.publish("Data to store in the byte array", "tag info",
      "key1=value1:key2=value2" );
  }
  /*
  At 4:30 each morning perform maintenance on the stores to release unused space
  */
  every 04:30 {
    myPubQueue.maintain();
    myPubChannel.maintain();
  }
  /*
  Every hour publish an event to the Channel
  */
  every 0 {
    myPubChannel.publish("Data to store in the byte array", "tag info",
      "key1=value1:key2=value2" );
    myPubQueue.publish("Data to store in the byte array", "tag info",
      "key1=value1:key2=value2" );
  }
  /*
  Every 1/2 hour purge the channels/queue
  The purge takes 3 optional parameters
  StartEID
  EndEID
  Filter string
  So it could be
  myPubChannel.purge(0, 100000);
  or
  myPubChannel.purge(0, 10000, "key1 = 'value1'");
  */
  every 0 {
    myPubChannel.purge();
    myPubQueue.purge();
  }
}

```

```

/*
When the number of events == 10 we purge the channel
*/
when(myPubChannel.numOfEvents == 10){
myPubChannel.purge();
}
/*
When the free space is greater then 60% perform maintenance
*/
when(myPubChannel.freeSpace > 60){
myPubChannel.maintain();
}
/*
When the number of connections on a channel reach 20 log an entry
*/
when(myPubChannel.connections == 20){
Logger.report("Reached 20 connections on the channel");
}
/*
Maintain all channels and queues at midnight every night
*/
every 00:00 {
Store.maintain("*");
}
}

```

## Universal Messaging Scheduling : Interface Triggers Example

```

scheduler realmInterfaceSchedule {
declare Interface myNHP ("nhp0");
declare Counter myCounter("myExhaustedThreads");
when (myNHP.idleThreads == 0) {
Logger.report("NHP0 Interface has no idles Threads");
myCounter.inc();
}
when (myCounter >= 5) {
Logger.report("Increasing the accept thread count on NHP0");
myNHP.threads("+10");
myCounter.reset();
}
}
}

```

## Universal Messaging Scheduling : Memory Triggers Example

```

scheduler myMemory {
/*
Declare the MemoryManager task/trigger. Not really required to do
*/
declare MemoryManager mem;
/*
Just using the MemoryManager task / trigger and not the declared mem as an example.
*/
when (MemoryManager.freeMemory < 100000000){
MemoryManager.flush(false);
}
/*
Now when the Free Memory on the realm drops below 1000000 bytes force the

```

```

realm to release ALL available memory
*/
when ( mem.freeMemory <1000000){
  mem.flush(true);
}
/*
This is the same as the one above, except not using the declared name.
*/
when ( MemoryManager.freeMemory <1000000){
  MemoryManager.flush(true);
}
/*
totalMemory available on the realm
*/
when ( MemoryManager.totalMemory <20000000 ){
  Logger.report("Declared Memory too small for realm");
}
/*
Out Of Memory counter, increments whenever the realm handles an out of memory exception
*/
when ( MemoryManager.outOfMemory> 2){
  Logger.report("Realm has run out of memory more then the threshold allowed");
}
}

```

## Universal Messaging Scheduling : Realm Triggers Example

```

scheduler realmSchedule {
  declare Realm myRealm ("productionmaster");
  declare Config myGlobalConfig ( "GlobalValues");
  when (Realm.connections> 1000) {
    Logger.report("Reached 1000 connections, setting max connections");
    myGlobalConfig.MaxNoOfConnections(1000);
  }
  when (Realm.eventsSentPerSecond> 10000) {
    Logger.report("Reached 10000 events per second, reducing max connection count by 100");
    myGlobalConfig.MaxNoOfConnections("-100");
  }
}

```

## Universal Messaging Scheduling : Cluster Triggers Example

```

/*
This script tests the cluster triggers. It is assumed the cluster is created with 4
realms
named realm1, realm2, realm3, realm4
*/
scheduler myCluster{
  declare Cluster myNode1("realm1");
  declare Cluster myNode2("realm2");
  declare Cluster myNode3("realm3");
  declare Cluster myNode4("realm4");
}
/*
This will trigger when realm1 is online to the cluster
*/
when ( myNode1.nodeOnline == true ){
  Logger.report("Realm1 online");
}

```

```

}
/*
This can also be written as
*/
when ( Cluster.nodeOnline("realm1") == true ){
  Logger.report("Realm1 online");
}
when ( myNode2.nodeOnline == true ){
  Logger.report("Realm2 online");
}
when ( myNode3.nodeOnline ==true ){
  Logger.report("Realm3 online");
}
when ( myNode4.nodeOnline == true ){
  Logger.report("Realm4 online");
}
when ( Cluster.hasQuorum == true ){
  Logger.report("Cluster now has quorum and is running" );
}
when ( Cluster.isMaster("realm1") == true){
  Logger.report("This local realm is the master realm of the cluster");
}
}

```

## Universal Messaging Scheduling : Counter Trigger Example

```

scheduler myCounter{
/*
Define some new counters
*/
declare Counter counter1 ("myCounter");
declare Counter counter2 ("myAdditional");
/*
When the counter reaches 5 reset it to 0;
*/
when(counter2> 5 ){
  counter2.reset();
}
/*
If counter1 is less then 3 then increment the value
*/
when(counter1 <3){
  counter1.inc();
  counter2.dec();
}
/*
if Counter2 equals 0 then set counter1 to 5
*/
when(counter2 == 0 ){
  counter1.set(5);
}
}

```

## Universal Messaging Scheduling : Time Triggers Example

```

scheduler myTimers{
/*
Define some new timers

```

```

*/
declare Timer reportTimer ("myTimer");
declare Timer testTimer ("myDelay");
initialise{
  testTimer.stop();
}
/*
In 60 seconds log a report and start the second timer
*/
when(timer == 60){
  Logger.report("Timer has fired!");
  testTimer.start();
}
/*
When the second timer hits 30 seconds, log it and reset all timers to do it again
*/
when(testTimer == 30){
  Logger.report("Test dela fired, resetting timers");
  testTimer.reset();
  testTimer.stop();
  timer.reset();
}
}

```

## Universal Messaging Scheduling : Configuration Example

```

scheduler myConfig {
  /*
  Declare local names for the Connection Config and the Logging Config configuration
  groups.
  Can be used for both triggers and tasks
  */
  declare Config myConnectionConfig ("Connection Config");
  declare Config myLoggingConfig ("Logging Config");
  /*
  When this scheduler task is initialised, set the Realms log level to 2
  */
  initialise{
    myLoggingConfig.fLoggerLevel(2);
  }
  /*
  Then if the log level is ever set to 0, automatically reset it to 2.
  */
  when(myLoggingConfig.fLoggerLevel == 0){
    myLoggingConfig.fLoggerLevel(2);
  }
  /*
  If the maximum number of connections on the realm is less than 0,
  implying no limit, then set it to 100.
  */
  when(myConnectionConfig.MaxNoOfConnections <0){
    myConnectionConfig.MaxNoOfConnections(100);
  }
}

```

## Integration with JNDI

Universal Messaging supports integration with JNDI through its own provider for JNDI. Universal Messaging's provider for JNDI enables clients using *Universal Messaging Provider for JMS* to locate references to JMS administered objects.


As with all Java APIs that interface with host systems, JNDI is independent of the system's underlying implementation. In the case of the Universal Messaging product, the JNDI provider stores object references in the Universal Messaging channel `/naming/defaultContext`, which is the channel representing the Universal Messaging Initial Context for JNDI, and locates the references to the objects using a channel iterator. Note that if a realm is part of a cluster, the channel will be created on all cluster realm servers. This ensures that any object references bound into the context are available on each realm server in the cluster. See the section "Creating The Initial Context" for information about how and when the channel for the Initial Context is created.

### Setting Up the Context and Connection Factories for JNDI

The provider for JNDI can be managed using the Enterprise Manager tool, by selecting any realm node from the namespace tree, and then clicking on the JNDI tab in the right hand panel. The JNDI panel enables the creation of the provider and Initial Context for JNDI, and of TopicConnectionFactory and QueueConnectionFactory references for JMS, as well as references to Topics and Queues.

### Creating The Initial Context

When you select a realm node from the namespace tree, one of the tabs on the right hand side of the Enterprise Manager will be labelled **JNDI**.



Selecting this tab will display the default JNDI panel for a realm.

If the Universal Messaging channel `/naming/defaultContext` has not been created yet, you will be prompted to create it.

The Initial Context uses the (potentially clustered) Universal Messaging context channel to store all JNDI references. This channel is called `/naming/defaultContext`. When the channel is initially created, full permissions are assigned to the first client who creates it and to all other users and clients who wish to use the channel.

Removing/destroying the Initial Context is as simple as deleting the `/naming/defaultContext` channel. This will of course result in the loss of all existing JNDI references (so make sure you don't accidentally delete this channel).

If the Initial Context no longer exists, then clicking the **Create JNDI context** button at the bottom of the screen will recreate it (though it will not contain any of its previous JNDI entries/references).

## Viewing the JNDI Namespace

Whenever you open the JNDI Panel, Enterprise Manager will enable display of the JNDI Namespace. The JNDI Namespace is displayed as a tree structure within the **Namespace** section of the panel. The root of this tree will be the JNDI Provider URL.


In the case of a cluster, the comma-separated list of RNAME values for each server in the cluster.

If you are using a round-robin connection factory, the URL syntax allows you to specify multiple connection URLs, where each connection URL can specify either a standalone realm or a cluster.

The JNDI namespace tree will render 6 "folders":

- Connection Factories
- Queue Connection Factories
- Queues
- Topic Connection Factories
- Topics
- XA Connection Factories

The image below shows this view after the JNDI panel has been loaded with the JNDI namespace tree expanded:



You can also use the **Refresh** button to update the contents of the JNDI namespace tree with any changes done outside the current instance of the Enterprise Manager.

## Creating Connection Factories

By using a *connection factory* you can connect to both topics and queues. With a *topic connection factory* (see description below) you connect only to topics, and with a *queue connection factory* (also described below) you connect to queues. Normally connection factories can be used as a more generic replacement for both topic connection factories and queue connection factories.

### How to create a connection factory

To create a connection factory, proceed as follows:

1. Select the node **Connection Factories** and open the context menu of this node.
2. In the dialog, supply a name to be displayed for the new connection factory, for example "connectionFactory2". Also provide a connection URL, for example "nsp://localhost:9000".

You can specify a cluster of realms by specifying a comma-separated list of connection URLs, for example "nsp://localhost:9000,nsp://localhost:9010".

If you want to use a round-robin connection factory, you can specify several connection URLs, where each connection URL can point to a standalone realm or a cluster. In this case, each connection URL is bounded by a set of round brackets - "(" and ")".

Examples:

- (UM1)(UM2)(UM3)(UM4) - Indicates 4 standalone realms, namely UM1, UM2, UM3 and UM4, so 4 connections will be constructed here.
- (UM1,UM2)(UM3,UM4) - Indicates 2 clusters, one consisting of UM1 and UM2 and the other consisting of UM3 and UM4, so only 2 connections will be constructed here.
- (UM1)(UM2,UM3)(UM4) - Indicates one cluster consisting of UM2 and UM3, and two standalone realms, namely UM1 and UM4. A total of 3 connections will be constructed here

For the round-robin URL syntax, the following rules apply:

- Each set of brackets must contain at least one valid connection URL.
- There is no limit on the number of sets of brackets in the URL.
- Each set of bracket indicates a unique connection, and the realm names within each sets of brackets will be supplied unchanged to the underlying implementation.

For more information on round-robin connection factories, see the section "Provider for JMS" in the Developer Guide.

3. Use the dropdown list to select the appropriate durable type for durable consumers for topics that can be created using this connection factory.

The following durable types are supported:

- **Named:** There can be only one active consumer at a time.
- **Shared:** Multiple durable consumers can connect to the same durable subscription and can consume messages in a round-robin manner.
- **Shared-Queued:** Multiple durable consumers can connect to the same durable subscription and can consumer messages in a round-robin manner using a queue-based durable.
- **Serial:** Multiple durable consumers can connect to the same durable subscription and can consume messages in a serial manner.
- **Priority:** Multiple consumers can connect to the same durable subscription but there can be only one active consumer at any one time.

Durable subscribers can be defined only for topics; they are not available for queues.

4. Click **OK** to save your changes and close the dialog.

## Editing Connection Factories

To edit an existing connection factory, proceed as follows:

1. Expand the node **Connection Factories** to display the available connection factories. Then double-click the required connection factory to open the edit dialog.
2. Make your changes in the dialog.

3. Click **OK** to save your changes and close the dialog.


## Creating Topic and Queue Connection Factories

In order to allow JMS clients to use the Universal Messaging Context Factory to reference objects via JNDI, we first of all need to create Topic and Queue connection factories.

To create a topic connection factory, proceed as follows:

1. Select the tree node labelled **Topic Connection Factories** and select the menu option **New Topic Connection Factory**.
2. In the dialog, supply a name for the connection factory. Enter any name (in this example, we will use the name **TopicConnectionFactory**). Also provide a connection URL, for example "nsp://localhost:9000".
3. Select the desired durable type from the dropdown list.
4. Click **OK** to save your changes and close the dialog.

You will see that a new node has been created under the **Topic Connection Factories** folder with the name that you entered. The image below shows the JNDI namespace with a newly created topic connection factory:



The Topic Connection Factory object you just created is actually stored as an event, published onto the `/naming/defaultContext` channel. This event is what will be referenced by JMS clients when they attempt to find the details for the connection factory.

To create a queue connection factory, proceed as follows:

1. Select the tree node labelled **Queue Connection Factories** and select the menu option **New Queue Connection Factory**.
2. In the dialog, supply a name for the connection factory. Also provide a connection URL, for example `"nsp://localhost:9000"`.
3. Click **OK** to save your changes and close the dialog.

You will see that a new node has been created under the **Queue Connection Factories** folder with the name that you entered.


**Note:**

Durable types are only applicable to topics or normal connection factories.

## Creating References to Topics and Queues

When JMS clients use the Universal Messaging Initial Context for JNDI, they also reference the topics and queues from the same Initial Context. In order for these clients to access these objects we need to create references to each topic and queue. Creating such references will also create the underlying channel or queue if it does not already exist; note that channels or queues created in this way will have the same default permissions as channels or queues created manually.

In this example, we will add a new topic into the JNDI namespace that corresponds to a Universal Messaging channel that already exists as a cluster channel. To do this, first, right-click on the folder called **Topics** within the JNDI namespace, and select the menu option **New Topic**. If we enter the name **GlobalOrderStatus**, then a new object will be created under the **Topics** folder called **GlobalOrderStatus**. This is because, under the covers, a corresponding event was published to the `/naming/defaultContext` channel. JMS clients can thus look up the reference to this topic (channel) and begin using it within their application. The following image shows the newly created Topic within the JNDI namespace for the existing topic **GlobalOrderStatus**:



Once we have created both the topic connection factory and the topic, we can snoop (see [“Channel Snoop” on page 118](#)) the `/naming/defaultContext` channel to view the individual events that represent these references. If you click the `/naming/defaultContext` channel within the Enterprise Manager namespace, then the **Snoop** panel, and click **Start**, you will see the events representing the JNDI entries that have been created. By selecting any of the events you will see the content of each event on the channel and the corresponding JNDI context information given to the JMS applications that will require it.

The image below shows an example of the Topic Connection Factory created earlier using the JNDI panel:

Software AG - webMethods / Nirvana Enterprise Manager

File Connections Cluster Help

Nirvana Enterprise

- Clusters
  - test
    - Realms
      - realm1
        - ClusterRates
        - Data Groups
        - GlobalOrders
        - naming
        - uk
        - GlobalOrderStatus
      - realm2
        - ClusterRates
        - Data Groups
        - GlobalOrders
        - naming
          - defaultContext
        - GlobalOrderStatus
      - realm3
        - ClusterRates
        - Data Groups
        - GlobalOrders
        - naming
        - GlobalOrderStatus

Summary Storage Properties

Attributes

Name	defaultContext
Type	Mixed
Age	0
Capacity	0
Engine	Default

Publish Keys

KEY
alias

Status Joins ACL Named Objects Snoop Connections

From

To

Filter

Event Id	Tag	TTL
4		0
3		0

0: 54 6F 70 69 63 43 6F 6E 6E 65 63 74 69 6F 6E 46 T o p i c C o n  
16: 61 63 74 6F 72 79 a c t o r y

Key	Value	
alias.type	1	int
alias	TopicConnectionFactory	String
alias.reference.classname	javax.jms.TopicConnectionFactory	String
alias.reference.factoryclass	com.pcbsys.nirvana.nJMS.TopicConnect...	String
alias.reference.url		String
alias.stringRefAddr.type	TopicConnectionFactory	String

Start Stop Pause

## TCP Interfaces, IP Multicast and Shared Memory

### Overview of Working with Interfaces

Using Enterprise Manager, you can configure communication mechanisms including TCP Interfaces, IP Multicast and Shared Memory (SHM):

## TCP Interfaces

Interfaces within a Universal Messaging Realm Server define a protocol, a network interface and a port number. When a Universal Messaging client connects to a realm using an RNAME, they are actually connecting to an Interface that has been created on the Universal Messaging Realm.

If a machine that is running a Universal Messaging Realm has multiple physical network interfaces, with different IP addresses, it is possible to bind specific protocols to specific ports. This way you are able to segment incoming network traffic to specific clients.

For example, if a realm is running on a machine that has an external internet facing network interface, as well as an internal interface, you can create a Universal Messaging interface that uses nhp or nhps on port 80 or 443 respectively using the external facing interface.

If on the other hand when there are multiple network interfaces, and you do not wish to segment network traffic for specific protocols, you can specify to bind to all known network interfaces to the specified protocol and port.

The default realm setting when you first install Universal Messaging creates a Universal Messaging Socket Protocol Interface that binds to port 9000, on all known network interfaces.

Once this basic understanding of Universal Messaging interfaces is understood, you can then set about performing a number of operations using the Universal Messaging Enterprise Manager:

- [“Creating Interfaces” on page 225](#)
- [“Deleting Interfaces” on page 229](#)
- [“Creating SSL Interfaces” on page 229](#)
- [“Stopping Interfaces” on page 229](#)
- [“Starting Interfaces” on page 228](#)
- [“Interface Configuration” on page 229](#)
- [“JavaScript Interface Panel” on page 232](#)
- [“Modify Interfaces” on page 228](#)
- [“Interface Plugins” on page 235](#)
- [“Interface VIA rules” on page 168](#)

## IP Multicast

- [“IP Multicast Configuration” on page 487](#)

## Shared Memory (SHM)

- [“Shared Memory Configuration” on page 241](#)

## Creating Interfaces

This section describes how to create interfaces for a realm. For general information about interfaces, see [“TCP Interfaces, IP Multicast and Shared Memory” on page 223](#).

To reach the dialog for defining and managing interfaces for a realm, proceed as follows:

1. In the namespace tree in the navigation frame, select the realm for which you want to create an interface.
2. Select the **Comms** tab in the **Realm Details** frame.
3. Select the **Interfaces** tab.

You now see a table containing all of the available interfaces on a the selected realm.

The default interface is nsp (Universal Messaging Socket Protocol) and it binds to 0.0.0.0 (i.e. all known interfaces) on port 9000.

Please note that adding an SSL enabled interface (see [“Creating an SSL network interface to a Universal Messaging Realm Server” on page 244](#)) for either SSL enabled sockets or HTTPS requires some additional steps.

The image below shows the **Interfaces** tab containing the default realm interface.

Realm Details

Name: node1  
 Threads: 158  
 Realm UpTime: 04:51:06.385  
 Last Update: Fri Jun 29 16:44:54 BST 2012

Status Monitoring ACL Comms Nirvana Realms Config Scheduler JNDI

Interfaces Multicast Shared Memory

Name	Status	Adapter	Port	Threads
nhp0	Running	0.0.0.0	9000	<div style="width: 100%; height: 10px; background-color: green;"></div>

Status Basic VIA Plugins Javascript

Details

Idle Threads	4
Total Connections	6
Total Failed	0
Ave Authorisation	33ms
Pool Exhausted Count	0
Ave Pool Wait	0
Mb Written / Second	0
Mb Read / Second	0
Total MB Written	0
Total MB Read	0

Connections Authentication


+ Add Interface - Delete Interface Apply Cancel

The interfaces table consists of 5 columns:

- **Name** : Defined as protocol + n, where n is a unique sequence number for the interfaces for that protocol.
- **Status** : Shows whether the interface is 'Running', 'Stopped' or 'Error'. The error status is shown if the interface has not been started due to an error.
- **Adapter** : The physical network interface to bind to, expressed either as an IP address or a hostname. The IP address 0.0.0.0 defines all known interfaces. You can use the hostname if you want the interface to be independent of the underlying IP address.

- **Port** : The port to bind to.
- **Threads** : An indicator for the number of accept threads the interface has free to accept connections. A full green bar denotes all are free.

To add a new interface, click on the **Add Interface** button, which will show a dialog that allows you to choose the protocol, the adapter, the port as well as whether the interface should be started automatically when it is created and also when the server restarts. This dialog is shown below:



In the example above, we have chosen to add a Universal Messaging HTTP Interface (nhp) that will be bound to all known network interfaces (0.0.0.0) on port 80. If you select the Auto Start option (by ticking the **Auto Start** checkbox), then click the **OK** button, this means that when the interface is created in the realm server, it will automatically be started. **Auto Start** will also cause that interface to be started whenever the realm is restarted. Once the interface has been created it will appear in the interfaces table as shown in the image below.

Name	Status	Adapter	Port	Threads
nhp1	Running	0.0.0.0	80	
nhp0	Running	0.0.0.0	9000	

Further instructions on configuring Universal Messaging interfaces are also available in the section [“Interface Configuration”](#) on page 229.

In addition a VIA rule (see [“Interface VIA Rules”](#) on page 168) can be added to interfaces as a security enhancement.

## HTTP / HTTPS Interface

The Javascript tab allows configuration of Comet delivery and is available for HTTP / HTTPS (nhp / nhps) interfaces.

The screenshot displays the 'Interfaces' configuration page in the Universal Messaging Enterprise Manager. At the top, there is a navigation bar with tabs for Status, Monitoring, ACL, Comms, Nirvana Realms, Config, Scheduler, and JNDI. Below this, there are sub-tabs for Interfaces, Multicast, and Shared Memory. The main content area is divided into two sections. The top section is a table of configured interfaces:

Name	Status	Adapter	Port	Threads
nhp0	Running	0.0.0.0	9000	
nhps0	Running	0.0.0.0	9443	

The bottom section is the 'Javascript' configuration tab, which includes several settings:

- Enable Javascript:
- Enable WebSockets:
- CORS Allow Credentials:
- Enable GZIP for longpoll:
- CORS Allowed origins:
- GZIP Minimum Threshold: 1000
- Long Poll Active Delay: 100
- Long Poll Idle Delay: 60000

At the bottom of the configuration area, there is a button labeled 'Custom Header Config'.

## Starting Interfaces

Interfaces can be started by selecting the realm node where the interface you want to start is running, and selecting the **Interfaces** tab. From the table of configured interfaces, select the interface you want to start and double-click on the row. Alternatively, you can click on the **Status** column for the interface. Both will present you with a dialog for starting the selected interface.

Clicking on the **Start** button will start the interface on the realm server.

## Modifying Interfaces

Each interface within a Universal Messaging realm has a number of configuration attributes (see [“Interface Configuration” on page 229](#)) that can be modified using the Enterprise Manager. Once modified, these can be applied to the interface on the fly. Modifying an interface will cause it to restart, closing all connections to the interface. However, since Universal Messaging clients will automatically reconnect to the realm server, the service disruption should be minimal.

When you have modified the configuration attributes for the selected interface, the Interfaces panel contains a button labelled **Apply**. Clicking on this button will send the modified attributes to the realm server and apply them to the interface, causing it to restart. If there are any clients connected to the interface they will automatically reconnect after restart.

## Stopping Interfaces

Interfaces can be stopped by selecting the realm node where the interface you want to stopped is running, and selecting the **Interfaces** tab. From the table of configured interfaces, select the interface you want to stop and double-click on the row. Alternatively, you can click on the **Status** column for the interface. Both will have the same effect, and will present you with a dialog for stopping the selected interface.

Clicking on the **Stop** button will stop the interface on the realm server.

## Deleting Interfaces

Interfaces can be deleted by simply selecting the realm node where the interface you want to delete is running, and selecting the **Interfaces** tab. From the table of configured interfaces, you can simply select the interface you want to delete and click the **Delete Interface** button.

When you delete an interface, Universal Messaging first stops the interface, then closes all clients connected to the interface, then removes the interface from the realm.

## SSL Interfaces

Universal Messaging supports SSL encryption by providing two SSL-enabled protocols. These protocols enable clients to connect to a Universal Messaging realm server running a specific protocol on a port using all or specific physical network interfaces.

Defining an SSL-enabled interface ensures that clients wishing to connect to a realm server can do so only after presenting the correct SSL credentials and authenticating with the server.

SSL authentication occurs within the Universal Messaging handshake which uses the JVM's JSSE provider. This ensures that any unauthorized connections are SSL authenticated before any Universal Messaging specific operations can be performed.

Creating an SSL enabled interface is the same as creating a non-SSL interface (see [“Creating Interfaces” on page 225](#)) except where there are a number of SSL-related attributes in addition to the basic attributes (see [“Interface Configuration” on page 229](#)).

For information on how to create an SSL interface using the Universal Messaging Enterprise Manager, see [“Creating an SSL network interface to a Universal Messaging Realm Server” on page 244](#).

## Interface Configuration


Each interface on a Universal Messaging Realm has a number of configurable attributes that determine the interface behaviour. Some of these attributes are standard across all types of interface protocols, and some are specific to a particular protocol.

This section will describe the attributes that are common to interfaces of all types.

For additional information on specific interfaces types, see [“TCP Interfaces, IP Multicast and Shared Memory” on page 223](#).

## Basic Interface Attributes

When an interface is selected from the table of interfaces on the **Interfaces** tab, there are a number of attributes that are configurable for the interface. Below the interfaces table, there is a set of tabs, one of which is labelled **Basic**, as shown in the image below.



The basic interface configuration panel shows configurable attributes. These are explained in the following section:

### Autostart Interface

The **Autostart** attribute specifies whether the interface is started automatically when the Universal Messaging realm server is started. When this option is not selected, the interface must be started manually in order for it to be used by connecting clients. Please note that if **Autostart** is not set it must be started either manually or using the Universal Messaging Administration API whenever after the realm is started.

If **Autostart** is selected then the interface will be started once the **Apply** button is pressed.

## Auth Time

The **Auth Time** attribute corresponds to the amount of time a client connection using this interface can take to perform the correct handshake with the realm server. For example, the default is 10000 milliseconds, but for some clients connecting on slow modems, and who are using the nhps (https) protocol, this default **Auth Time** may need to be increased. If any client connection fails to perform the handshake in the correct timeframe, the connection is closed by the realm server.

## Accept Threads

Each Universal Messaging realm interface contains a server socket. The **Accept Threads** attribute corresponds to the number of threads that are able to perform the `accept()` for a client connection. The `accept()` operation on a Universal Messaging interface performs the handshake and authentication for the client connection. For more heavily utilised interfaces, the accept threads will need to be increased. For example, on an nhp (http) or nhps (https) interface, each client request corresponds to a socket `accept()` on the interface, and so the more requests being made, the busier the interface will be, so the accept threads needs to be much higher than that of say an nsp (socket) interface. Socket interfaces maintain a permanent socket connection, and so the `accept()` is only performed once when the connection is first authenticated.

## Send Buffer Size

This specifies the size of the send buffer on the socket.

## Receive Buffer Size

This specifies the size of the receive buffer on the socket

## Select Threads

The **Select Threads** option specifies the number of threads allocated to monitor socket reads/writes on the interface if NIO is enabled. When a socket needs to be read, these threads will fire and pass on the request to the read thread pool. If the socket is blocked during a write, then when the socket is available to be written to, these threads will fire and the request will be passed on to the write thread pool. The number of select threads should not typically exceed the number of cores available.

## Enable NIO

Specify whether NIO should be used for this interface.

## Advertise Interface

All interfaces that are advertised by a realm server are available to users (with the correct permissions) of the Universal Messaging Admin API. This property specifies whether the interface is indeed advertised to such users.

## Backlog

The **Backlog** attribute specifies the maximum size of the incoming IP socket request queue. The operating system that the realm server is running on may specify a maximum value for this property. When the maximum queue size is reached the operating system will refuse incoming connections until the request queue reduces in size and more requests can be serviced. For more information on this value, please see the system administration documentation for your Operating System.

## Alias

Each interface on a Universal Messaging Realm Server can have an associated alias in the form of host:port. This alias can be specified here.

For information on interface plugins please see [“Interface plugins” on page 235](#).

For information on adding VIA rules for an interface please see [“Interface VIA Rules” on page 168](#).

When you change any of these attributes, the changes need to be applied by clicking the **Apply** button. For more information, refer to the modifying interfaces documentation (see [“Modifying Interfaces” on page 228](#)).

## JavaScript Interface Panel

Universal Messaging HTTP and HTTPS (nhp and nhps) interfaces have configuration options specific to their communication with web clients using JavaScript. These options are accessible through the **JavaScript** panel when viewing an nhp or nhps interface.

## The Interface Panel

The screenshot shows the 'Interfaces' panel in the Universal Messaging Enterprise Manager. At the top, there are navigation tabs: Status, Monitoring, ACL, Comms, Nirvana Realms, Config, Scheduler, and JNDI. Below these are sub-tabs: Interfaces, Multicast, and Shared Memory. The main content area shows a table of interfaces:

Name	Status	Adapter	Port	Threads
nhp0	Running	0.0.0.0	9000	
nhps0	Running	0.0.0.0	9443	

Below the table, there are tabs for 'Status', 'Basic', 'VIA', 'Plugins', and 'Javascript'. The 'Javascript' tab is selected, showing the following configuration options:

- Enable Javascript:
- Enable WebSockets:
- CORS Allow Credentials:
- Enable GZIP for longpoll:
- CORS Allowed origins:
- GZIP Minimum Threshold: 1000
- Long Poll Active Delay: 100
- Long Poll Idle Delay: 60000

At the bottom, there is a 'Custom Header Config' button.

## JavaScript Interface Properties

Option Name	Description
Enable JavaScript	Recommended Setting: Enabled Allows JavaScript clients to connect on this interface.
Enable WebSockets	Recommended Setting: Enabled Toggles the ability for clients to communicate with the server using the HTML WebSocket Protocol on this interface.
CORS Allow Credentials	Recommended Setting: Enabled

Option Name	Description
	<p>Toggles the server sending an "Access-Control-Allow-Credentials: true" header in response to XHR-with-CORS requests from the client. This is required if the application, or website hosting the application, or intermediate infrastructure such as reverse proxy servers or load balancers, uses cookies.</p> <p>Leave this enabled unless recommended otherwise by support. Disabling this will in most environments prevent all CORS-based drivers from working correctly.</p>
CORS Allowed Origins	<p>Recommended Setting: *</p> <p>A comma separated list of the host names (and IP addresses, if they appear in URLs) of the server/s which host your JavaScript application's HTML. Use an * (asterisk) as a wildcard value if you do not wish to limit the hosts that can serve applications to clients. This server will accept and respond with the required Access-Control-Allow-Origin header when requests originate from a hostname in this list. This header allows CORS enabled transport mechanism to bypass cross site security restrictions in modern browsers.</p> <p>It is important that this is set appropriately, or approximately half of the communication drivers available to JavaScript clients will fail.</p>
Enable GZIP for LongPoll	<p>Recommended Setting: Enabled</p> <p>This will allow the server to gzip responses sent to LongPoll clients. This can reduce network utilization on servers with many LongPoll clients. It increases CPU resource utilization.</p>
GZIP Minimum Threshold	<p>Recommended Setting: 1000</p> <p>The minimum message size in bytes required for the server to begin compressing data sent to LongPoll clients.</p>
Long Poll Active Delay	<p>Recommended Setting: 100</p> <p>The time between clients sending long poll requests to the server in milliseconds. Reducing this may reduce latency up to a certain threshold but will increase both client and server memory, CPU and network usage.</p>
Long Poll Idle Delay	<p>Recommended Setting: 25000</p> <p>The time between clients sending long poll when the client is in idle mode. A client is put in idle mode when no communication takes place between client and server for a period of time. Reducing this may be necessary if a client is timing out owing to local TCP/IP settings, proxy settings, or other infrastructure settings, but will result in higher memory, CPU and network usage on both the client and the server. It is however vital that this value is lower than the timeouts used in any intermediate proxy server, reverse</p>

Option Name	Description
	proxy server, load balancer or firewall. Since many such infrastructure components have default timeouts of as little as 30 seconds, a value of less than 30000 would be prudent. If long polling client sessions continually disconnect and reconnect, then lower this value.
Custom Header Config	Header Key/Value pairs which are sent in the HTTP packets to the client.

## Interface plugins

Universal Messaging supports the concept of plugins that actively process client requests made to nhp and nhps interfaces. There are currently 4 plugins:

- File (Provides behavior similar to a web server)
- XML (Browse resources and events in XML)
- SOAP (Browse channels, queues and events using SOAP protocol)
- Proxy Passthrough (Enable http/s requests for specific URLs to be forwarded to another host:port)

The plugins are discussed in more detail in the section [“Plugins” on page 252](#).

## Multicast Configuration

Universal Messaging delivers 'ultra-low latency' to a large number of connected clients by including IP Multicast functionality for both the delivery of events to Data Group consumers as well as between inter-connected realms within a Universal Messaging cluster.

This section assumes the reader has some knowledge of IP Multicast.

## Universal Messaging Multicast Architecture

Each Universal Messaging interface that you configure on a Universal Messaging Realm binds to one or all of the available physical Network adapters present on the host machine. In order to successfully configure Multicast on a Universal Messaging Realm you must ensure that you know the IP addresses of each of these network adapters (including virtual addresses if running on a virtual host), and which physical network adapter and it's address is capable of supporting IP Multicast. This information allows the correct network adapter to be selected and bound to by the Multicast configuration. Once this information is known, you then need to ensure that the physical network infrastructure including switches and routers can support Multicast. Once validated, the next step is to select an available Multicast address which can be used.


Universal Messaging servers can use IP Multicast either to deliver Data Group events to its consumers or between Universal Messaging realms within a cluster. If you wish to enable IP Multicast delivery to Data Group consumers, you can create a Multicast configuration and select it for use with Data Groups. Once you have configured a Multicast adapter, when you create a

Data Group with the enable Multicast flag set, the Universal Messaging realm will automatically begin delivering the events via Multicast when published to that Data Group. The client application requires no extra setup to begin receiving Multicast. When a client Data Stream is added to a Multicast enabled Data Group, the client will transparently receive the information it needs to begin consuming Multicast for that Data Group. The client will at first both consume the Unicast Data Group events, and if Multicast is possible, also consume the Multicast events. When both Unicast and Multicast are in sync after a period of time, the Universal Messaging Server will stop sending Unicast events for that Data Stream to the client. The Universal Messaging server will track whether each client is in fact able to process the Multicast packets and if any client does not successfully acknowledge safe receipt of the Multicast events, it will simply continue to consume the Unicast events.


With this model, the client is able to seamlessly interact with the Universal Messaging server and begin consuming Multicast events with no changes to the Client application required.

### **Setting Up Multicast for Data Group Delivery**


The first step in configuring a Universal Messaging Realm for Multicast Data Group delivery is to create the Multicast adapter configuration. Once you have the information described in the previous section, and your Universal Messaging realm is running, start the Enterprise Manager and connect to your realm. Once connected, select the realm node from the tree, and choose the Multicast tab in the right hand panel, as shown below.




Clicking on the "Add Multicast Config" button opens a dialog that enables you to enter the Multicast IP Address, as well as the Network Adapter Address of your multicast configuration, as shown below.



When you click on ok in the dialog, the new Multicast configuration will appear in the table. You then need to select that the multicast configuration is to be used for Data Groups by clicking on the "Use for DataGroups" check box. Then click the "Apply" button and the configuration will be sent to the server. The completed multicast Configuration is shown in the table as seen in the image below.



Now you have created the Multicast configuration, you need to create your Multicast enabled Data Groups. To do this, simply click on the Data Groups node in the tree, and right click "Create Data Group". This will open up the standard create Data Group dialog but with an additional check box for enabling Multicast. This is shown in the image below.




Now your data group is ready to be used for Multicast Delivery. If you are familiar with Universal Messaging Data Groups, you will be familiar with our example Data Group programs which you can use to test this out, or you may have your own Data Group setup that you can use. If your Data Groups are created programmatically, then the key thing to remember is that when you call the `nSession.createDataGroup`, you now need to also pass in an additional boolean that marks the Data Group as Multicast enabled.

## Setting Up Multicast for Cluster Inter Realm Communication

If you have a clustered setup, and you wish to setup Multicast between your realms for the inter realm communication, the setup is the same, however on each realm that you create a Multicast Configuration, the configuration itself needs to set the "Use for Clusters" checkbox. The Multicast address can be the same for all realms, or you can choose a different Multicast Address per realm. With this feature enabled, each realm will know the Multicast address for each of the other realms in the cluster and will listen on these addresses for inter realm cluster communication.


## Advanced Multicast Settings

The default settings for the Multicast configurations you create are aimed at providing the lowest possible latency. With this in mind, the configuration is such that the multicast client will ack every 1 second, and the server will maintain a list of un-acked events (default 9000). Should the publish rate exceed 9000 per second, you may notice that the delivery rates might be quite irregular. This is down to the fact that the client will only acknowledge every 1 second, and so the server will automatically back off the delivery until it receives an acknowledgement from the client and can therefore clear its unacknowledged queue. If this happens, you can change both the Unacked Window Size to be > 9000 and the Keep Alive Interval (ack interval) to be less than 1 second (see image of the Advanced Settings tab below).




## Shared Memory Configuration

In order to create a Shared Memory (SHM) interface you will need to select the realm node from the namespace tree to which you wish to add the interface, then in the right hand tabbed area there will be a tab labeled "Comms". Select it, and you will be presented with the "Shared Memory" tab:




Now select "Add SHM Config" and you be presented with the below configuration box, it contains three parameters



1. Path: This is the directory within which the files needed for SHM communication will be created. (Please note that when choosing a path, ensure that the local user id of the server can access this directory, for example, /dev/shm will require root / super user access, or shm communication will not work)
2. Buffer Size: This is the size of the allocated memory in bytes a connection will use, it will also create a file of the same size which is used for mapping.
3. Timeout: This is the idle timeout for a connection, if no activity is detected on the connection it is closed.

Once you press okay the driver is created and ready to go. If you wish to edit any of those values you can edit them by double clicking any on the field you wish to change and then applying them with the apply button or resetting them by pressing cancel.



## Creating an SSL network interface to a Universal Messaging Realm Server

Network Interfaces can be added to a Universal Messaging realm using the Universal Messaging Administration API or by using the Universal Messaging Enterprise Manager.


To add an SSL interface using the Enterprise Manager GUI, follow the steps below:

Step 1: Click on the interfaces panel for a realm. In the example below an interface is being added to the realm "node1". An interface could also be added however to any other realm shown in the Enterprise Manager. This ability makes centralized remote administration very easy using Universal Messaging.

The screenshot displays the Nirvana Enterprise Manager web interface. The left-hand navigation pane shows a tree structure under 'Nirvana Enterprise' with 'Clusters' and 'Realms'. Under 'Realms', there are three nodes: 'node1', 'node2', and 'node3'. Each node contains sub-items for 'Data Groups', 'ClusterRates', and 'GlobalOrders'. The main content area is titled 'Realm Details' and shows fields for 'Name:', 'Threads:', 'Realm UpTime:', and 'Last Update:'. Below these fields is a toolbar with buttons for 'Status', 'Monitoring', 'ACL', 'Comms', 'Nirvana Realms', 'Config', and 'Scheduler'. A secondary toolbar contains 'Interfaces', 'Multicast', and 'Shared Memory'. A table below the toolbar lists network interfaces with columns for 'Name', 'Status', 'Adapter', and 'Port'. The table contains one entry: 'nhp0' with status 'Running', adapter '0.0.0.0', and port '9000'. Below the table are tabs for 'Status', 'Basic', 'VIA', and 'Javascript'. The 'Status' tab is active, showing a 'Details' section with various performance metrics and a 'Connections' grid. The 'Details' section includes: Idle Threads (1), Total Connections (2), Total Failed (0), Ave Authorisation (20ms), Pool Exhausted Count (0), Ave Pool Wait (0), Mb Written / Second (0), Mb Read / Second (0), Total MB Written (0), and Total MB Read (0). The 'Connections' grid is currently empty. At the bottom of the interface are three buttons: 'Add Interface', 'Delete Interface', and 'Apply'.

Step 2: Click on the Add Interface button in order to bring up the Add Interface dialog box. In the dialog choose the network protocol you would like to use for this interface. The choices are Sockets, Secure Sockets, HTTP and HTTPS. Choose either Secure Sockets or Secure HTTPS to add an SSL interface.

In this example HTTPS is chosen as the protocol and the interface is added to the network adapter 192.168.1.5. This will run the network interface on that IP Address. Alternatively, you could add a hostname that will resolve to the IP address of the chosen interface, or you can also specify 127.0.0.1 for localhost or 0.0.0.0 for all network interfaces on this machine.



Step 3: When a new interface is added, if the Auto Start option is not selected the realm interface will not start automatically when a realm starts, and it will have to be started manually.

After the interface has been added you should see the following in your interfaces panel:

The screenshot shows the Nirvana Enterprise Manager interface. On the left is a tree view of the hierarchy: Nirvana Enterprise > Clusters > Test > Realms > node1. Under node1, there are sub-items for ClusterRates, Data Groups, and GlobalOrders. The main pane on the right is titled 'Realm Details' and shows configuration for the selected realm. It includes a table of network interfaces and a configuration form for the selected interface.

**Realm Details**

Name:  
Threads:  
Realm UpTime:  
Last Update:

Buttons: Status, Monitoring, ACL, Comms, Nirvana Realms, Config, Scheduler

Sub-tabs: Interfaces, Multicast, Shared Memory

Name	Status	Adapter	Port
nhps0	Running	0.0.0.0	944
nhp0	Running	0.0.0.0	900

Sub-tabs: Status, Basic, VIA, Certificates, Algorithms, Plugins, Javascript

Enable Client Cert Validation  JSSE Provider

Key store path: C:\Nirvana 7.0.11226\server\nirv Trust store path

Certificate Alias Private Key Passwd

Key Store Passwd: \*\*\*\*\* CA Store Passwd

CRL file name Random Algorithm

Random Provider

Buttons: + Add Interface, - Delete Interface, Apply

In this example you can see that this realm now has 2 network interfaces and that the one just added ("nhps0") has been started.

If you did not choose to start the interface automatically, then in order to start the interface you need to click on the line containing the stopped traffic light. This will populate the tabs at the bottom with details for this interface.

Click on the Certificates tab. You will see that the first 2 text boxes have been automatically filled in. In the Universal Messaging download, we provide a utility called Certificate Generator (see [“How to generate certificates for use” on page 248](#)) that can generate sample .jks files containing certificates bound to localhost, for the server, the client and the truststore used by jsse. In this example we are going to use the sample jks files in order to demonstrate creating an SSL interface.

If you would like instructions on generating your own certificates (see [“How to generate certificates for use” on page 248](#)) for use with Universal Messaging please see our FAQ.

The text field titled 'Key store path' should contain something similar to:

```
c:\Universal Messaging\server\umserver\bin\server.jks
```

which should be the path to the sample Java keystore for the server, bound to localhost. The text field 'Trust store path' should contain something similar to the following:

```
c:\Universal Messaging\server\umserver\bin\nirvanacacerts.jks
```

Next, fill in the entries for the 'Key Store Passwd' and 'CA Store Passwd' with 'password'. This is the password for both the server keystore and the CA (truststore) keystore.

Next select the 'Basic' tab and click on the autostart interface checkbox. Clicking on this box means that the interface will be started automatically when the Universal Messaging realm server is started.

Then click on apply and the Interface will be started. It will also start it now.

Alternatively if you do not wish to autostart then double click on the line with the stopped traffic light. This will bring up a dialog which allows you to start that network interface.

If the network interface fails to start then please inspect the Universal Messaging log file via the messages tab. Please contact your software supplier if any other issues arise.

Similarly, if you wish to stop an interface, simply double-click on the interface you want to stop from the interface table, and click on the 'stop' button.

There is no limit to the number of network interfaces that can be added to a realm and each can have its own configuration such SSL chains etc applied. This allows you to isolate customers from each other while still using only one Universal Messaging realm server.

In this example we have used our own sample Java keystores which will only work when using the loopback interface of your realm server host. If you wish to provide SSL capabilities for remote connections, you must ensure you have your own keystores and valid certificate chains. For related information on topics such as creating your own certificate chains and using the Java keytool, you can visit external links such as the following:

<http://docs.oracle.com/javase/7/docs/technotes/tools/windows/keytool.html>

## How to generate certificates for use

## Generating Demo / Development certificates

In order to generate a demo SSL certificate you can use the Java keytool utility or the Universal Messaging Certificate Generator utility.

The Java keytool utility can be used to create and handle certificates. Keytool stores all keys and certificates in a keystore. For a detailed description of Java's keytool please see its documentation at <http://docs.oracle.com/javase/7/docs/technotes/tools/windows/keytool.html>.

The Universal Messaging Certificate Generator utility can be used to generate a self signed server certificate, a self signed client certificate and a trust store for the above two.

You can run the Certificate Generator from the Start Menu on Windows by selecting the server/<realm name>/Create Demo SSL Certificates

Alternatively you can open a server Command Prompt and run the utility as required for your platform:

- Win32:

```
CertificateGenerator.exe
```

- Linux/Solaris/Generic Unix:

```
./CertificateGenerator
```

- OSX:

```
./CertificateGenerator.command
```

This will generate 3 files:

- client.jks : Self signed certificate you could use if you have client certificate authentication enabled.
- server.jks : Self signed certificate with a CN=localhost . Please note: You can only connect to interfaces using this by specifying a localhost RNAME due to the HTTPS protocol restrictions.
- nirvanacacerts.jks: Keystore that contains the public certificate part of the 2 key pairs above. This should be used as a trust store by servers and clients.

It is also possible to customize some elements of these certificates stores such as the password, the host bound to the server CN attribute and they key size. This can be done by passing the following optional command line arguments to the Certificate Generator:

- Win32:

```
CertificateGenerator.exe <password> <host> <key size>
```

- Linux/Solaris/Generic Unix:

```
./CertificateGenerator <password> <host> <key size>
```

- OSX:

```
./CertificateGenerator.command <password> <host> <key size>
```

## Generating Production certificates

In order to obtain a real SSL Certificate, you must first generate a CSR (Certificate Signing Request). A CSR is a body of text that contains information specific to your company and domain name. This is a public key for your server.

The Java keytool utility can be used to create and handle certificates. Keytool stores all keys and certificates in a keystore. For a detailed description of keytool please see its documentation.

### *Step 1: Create a keystore*

Use the keytool to create a keystore with a private/public keypair.

```
keytool -genkey -keyalg "RSA" -keystore keystore -storepass password -validity 360
```

You will be prompted for information about your organisation. Please note that when it asks for "User first and last name", please specify the hostname that Universal Messaging will be running on ( e.g. www.yoursite.com ).

### *Step 2: Create a certificate request*

Use the keytool to create a certificate request.

```
keytool -certreq -keyalg "RSA" -file your.host.com.csr -keystore keystore
```

This will generate a file containing a certificate request in text format. The request itself will look something like this :

```
-----BEGIN NEW CERTIFICATE REQUEST-----
MIIBtTCCAR4CAQAwdTElMAkGA1UEBhMCVVMxDzANBgNVBAgTBmxxvbmRvbjEPMA0GA1UEBxMGbG9u
ZG9uMRQwEgYDVQQKEwtteS1jaGFubmVsczEMMAoGA1UECxMDYm16MSAwHgYDVQQDExdub2RlMjQ5
Lm15LWNoYW5uZWxzLmNvbTCBnzANBeddiegkqhkiG9w0BAQEFAAOBjQAwgYkCgYEAycg0MJ7PXkQM9sLj
1vWa8+7Ce0FDU4tpcMXLL647dwok3uUGXuaz72DmFtb80ninjawingsjxrMBDK9fXG9hqfDvxWGyU0DEgbn+Bg
03XqmUbyI6eMzGdf0vTyBFSeQIinigomontoyaU9Ahq1T7C6zLryJ9n6XZTW79E5UcbSGjoNAP0gV0CPKbs7/CR
hZECaWEEAAaAMA0GCSqGSIb3DQEBAUAA4GBAB7TkFzQr+KvsZCV/pP5IT0c9tM58vMXkds2J77Y
Op3AueMVixRo14ruLq1obbTudhc385pPgHLz07QHEKI9gJnM5pR9yLL72zpVKPQ9X0ImShv005Tw
0os69BjZeW8LTV60v4w3md47IeGE9typGGxBWscVbXzB4sgVlv0JtE7b
-----END NEW CERTIFICATE REQUEST-----
```

### *Step 3: Submit your certificate request to a certificate supplier*

Certificate vendors will typically ask you to paste the certificate request into a weborder form. This will be used as a public key to generate you private key. Please include the (BEGIN and END) tags when you paste the certificate request.

Please note that a cert of PKCS #7 format is required so that it can be imported back into keytool. (step 4)

The certificate vendor will then provide you with a certificate which that will look something like this:

Please paste this certificate into a file called `your.host.com.cer` [Note. please include the (BEGIN and END) tags]

```
-----BEGIN PKCS #7 SIGNED DATA-----
MIIFpAYJKoZIhvcNAQcCoIIFlTCCBZECAQEADALBgkqhkiG9w0BBwGgggV5MIIC
2DCCAKGgAwIBAgICERyYwDQYJKoZIhvcNAQEEBQAwwGcCzAJBgNVBAYTAlpBMSIw
IAYDVQQIEwltGT1IgeVETVElORyBQVJQT1NFUyBPTkxZMR0wGwYDVQQKEwRUaGF3
dGUgQ2VydGlnaWVhdGlvbGJEXMBUGA1UECXMOMOVEVTVCBURVNUIFRFRU1QxHDAaBgNV
BAMTE1RoYXk0ZSBUZXR0IENBIFJvb3QwHhcNMDQwOTA2MTYwOTIwWhcNMDQwOTI3
MTYwOTIwWjB1MQswCQYDVQQGEwJVUzEPMA0GA1UECBMGbG9uZG9uMUM8wDQYDVQQH
EwZsb25kb24xZDASBgNVBAoTC215LWNoYW5uZWxzMQwwCgYDVQQLEwNiaXoxIDAe
BgNVBAMTF25vZGUyNDkubXktY2hhbm5lbHMUy29tMIGfMA0GCSqGSIb3DQEBAQUA
A4GNADCBiQKBgQDJyDQwns9eRAZ2wuPW9Zrz7sJ7QUNTi2lwxeUvrjt3CiTe5QZe
5rPvYOYw1vw6PGswEMr19cb2Gp80/FYbJtQMSBuf4GA7deqZrVljp4zMZ1/S9PIE
VJ5AhT0CGRVPsLrOwvIn2fpdlNbv0TLRxtIa0g0CkE6BU4I80Gzv8JGFkQIDAQAB
o2QwYjAMBgNVHRMBAf8EAjAAMDMA1UdHwQsMCowKKAmoCSGImh0dHA6Ly93d3cu
dGhhd3RlLmNvbS90ZXN0Y2VydC5jcmwwHQYDVROlBBYwFAYIKwYBBQUHAWEGCCsG
AQUFBwMCA0GCSqGSIb3DQEBAUAA4GBAHGPR6jxU/h1U4yZGt1BQoydQSaWW48e
r7slod/2ff66LwC4d/fymiOTZpWvbiYFH1ZG98XjAvoF/V9iNpF5ALfIkeyJjNj4
ZryYjxGnbBa77GFis4wvUk1sngnoKpaxkQh24t3QwQJ8BRHwnwR3JraNMwDWHM1H
GaUbdBI7WYwQMIICmTCCAgKgAwIBAgIBADANBgkqhkiG9w0BAQQFADCBhzELMAK6
A1UEBhMCWkExIjAgBgNVBAGTGUZPUiBURVNU5U5HIFBVUlBPu0VTIE90TFkxHTAb
BgNVBAoTFFRoYXk0ZSBDZXJ0aWZpY2F0aW9uMRcwFQYDVQQLEw5URVNUIFRFRU1Qg
VEVTVDEcMBoGA1UEAxMTVGhhd3RlIFRlc3QgQ0EgUm9vdDAeFw05NjA4MDEwMDAw
MDBaFw0yMDEyMzE5MTU5NTlaMIGHMQswCQYDVQQGEwJaQTEiMCA0GA1UECBMZk9S
IFRFRU1RJTkcGUUVSUE9TRVMgT05MWTEDMBsGA1UEChMUUVGhhd3RlIENlcnRpZmlj
YXRpb24xZzAVBgNVBAsTDlRFU1QgVEVTVCBURVNUMRwwGgYDVQQDEwNUaGF3dGUg
VGZzdCBDQSB3Sb290MIGfMA0GCSqGSIb3DQEBAQUAA4GNADCBiQKBgQC1fZBvjr0s
fwzoZvrSLEH81TFHoRpebBZhlZDDE19mYuJ+ougb86EXieZ487dSxXKruBFJPSYt
tHoCin5qkc5kBSz+/tZ4knXyRFB03CmONEKCPfdu9D06y4yXmjHApfgGJfpA/kS+
QbbiilNz7q2HLArK3umk74zHKqUyThnkjwIDAQABoxMwETAPBgNVHRMBAf8EBTAD
AQH/MA0GCSqGSIb3DQEBAUAA4GBAIAKM4+wZA/TvLIItldL/hGf7exH8/ywvMupg+
yAVM4h8uf+d8phgBi7coVx71/lCB0lFmx66NyKlZK5m0bgvd2dlnsAP+nnStyhVH
FIpKy3nsD04JqrIgeHcSdpikSpbtDo18jUubV6z1kQ71CrRQtbi/WtdqxQEEtgZC
JO2lPoIWMQA=
-----END PKCS #7 SIGNED DATA-----
```

*Step 4: Store the certificate in your keystore*

Use the keytool to store the generated certificate :

```
keytool -keystore keystore -keyalg "RSA" -import -trustcacerts -file your.host.com.cer
```

Once step 4 is completed you now have a Universal Messaging server keystore and can add an SSL interface (see [“Creating an SSL network interface to a Universal Messaging Realm Server” on page 244](#)).

Please note that if you completed steps 1 to 4 for test certificates then you will also need to create a store for the CA root certificate as Universal Messaging will not be able to start the interface until it validates where it came from. Certificate vendors typically provide test root certificates which are not recognised by browsers etc. In this case you will need to add that cert to another store and use that as your cacert. When specifying certificates for a Universal Messaging SSL interface this would be specified as the Trust Store Path in the certificates tab.

If you are using anonymous SSL then you will have to provide this cacert to clients also as this will not be able to validate the Universal Messaging certificate without it. Please see the Security

section of our Concepts guide for more information on configuring Universal Messaging clients to use certificates.

## Plugins

The Universal Messaging Realm Server supports the concept of Plugins within the context of the NHP or NHPS protocols. The plugins are initiated when the underlying Universal Messaging driver receives an HTTP/S packet which is not part of the standard Universal Messaging protocol. At this point it passes the request over to the Plugin Manager to see if there is any registered plugin interested in the packet's URL. If there is, then the request is forwarded to this plugin for processing. There are several plugins supported by Universal Messaging. Please see below for available documentation:

- [“File Plugin” on page 253](#)
- [“XML Plugin” on page 257](#)
- [“Proxy passthrough Plugin” on page 261](#)
- [“REST Plugin” on page 263](#)
- [“SOAP Plugin” on page 282](#)
- [“Servlet Plugin” on page 285](#)

## Configuration


Configuration of a plugin can be done programmatically with the Administration API supplied with Universal Messaging or it can be done with the Enterprise Manager application. For the rest of this document the Enterprise Manager will be used to describe how to set up and use the plugins.

In order to add a plugin, first of all you need to have created the nhp or nhps interface (see [“Creating Interfaces” on page 225](#)) that will use the plugin within the realm where you wish to run the plugin.

Once the interface is created, proceed as follows to access the plugin configuration dialog:

1. In the navigation frame, select the realm where you want to add the plugin.
2. In the **Realm Details** frame, navigate to the list of defined interfaces for the realm, using **Comms > Interfaces**.
3. Select the interface from the table of configured interfaces.
4. Select the tab **Plugins** from the interface configuration panel.
5. Click **Add Plugin**. This displays the plugin configuration dialog, which enables you to choose which plugin you wish to add.

The diagram below shows a new file plugin about to be added to the known interface nhp0.



## URL Path

When you configure a plugin, you are required to add a URL Path. The URL Path is what the realm server uses to determine if the request is destined for a plugin. If the server name and path within the URL supplied in the plugin configuration dialog match the server name and path within the request to a configured plugin, then this request is passed to the correct configured plugin for processing.

For example:

If a request with a URL of `http://realmServer/pluginpath/index.html` is made to the server, the file path will be extracted, i.e. `pluginpath/index.html`, and the configured plugins will be scanned for a match. If there is a file plugin configured with a URL Path `pluginpath`, then this plugin will get a request for `index.html`.

Similarly:

If a request with a URL of `http://realmServer/pluginpath/pictures/pic1.jpg` is received, then the same file plugin would get a request for `pictures/pic1.jpg`.

## File Plugin

The file plugin enables the Universal Messaging realm server to serve static web pages. This can be used for example to have the realm server serve applets and supported files without the need for a dedicated web server. For example, if you are running a file plugin on your realm server host

called `webhost`, on an `nhp` interface running on port 80, you could type in a URL within a web browser `http://webhost:80/index.html` which will return the index page defined within the file plugin's base path directory.

This enables the realm server to act as a web server and can even be used to serve applets to client browsers that may directly communicate with the realm server and publish and consume events from channels.

**Important:**

The root file directory that the file plugin points to using the `BasePath` parameter can be any disk location. All files under that location are potentially visible to any HTTP client that can connect to the Universal Messaging realm server. We would recommend that you do not point the file plugin to a directory that contains any sensitive data, without also configuring suitable access controls. These could be at the network level (restricting network access to the server), in the file plugin configuration (it supports HTTP basic authentication with a username/password file) or by using file permissions at the Operating System level (so that sensitive data cannot be read by the realm server process). Or of course a combination of these.

## Configuration


Once you have created the file plugin on the interface you require it on, you can then select it from the **Plugins** panel for the selected interface and enter values as you wish for the configuration parameters.

The file plugin requires configuration information defining its behavior as well as the location of the files it is required to serve to the clients. Below is a table that shows each configuration parameter and describes what it is used for.


Parameter Name	Description	Default Value
BufferSize	Size of the internal buffer to use to send the data.	1024
BasePath	Path used to locate the files.	The <code>UniversalMessaging/doc</code> directory under the product installation directory.
DefaultName	If no file name is specified which file should be returned.	<code>index.html</code>
FileNotFoundPage	Name of the file to send when file cannot be located	None.
UserFile	Name of the file containing the usernames and passwords.	None.
Security Realm	Name of the authentication realm	None.
MimeType	Name of the file to load the mime type information from. The format of	Built in types used.

Parameter Name	Description	Default Value
	this file is : <mimetype> <fileExtension>	
CachedObjects	Number of objects to store in the cache	100
CacheObjectSize	Size in bytes that can be stored in the cache	20K
SeparateAccessandErrorLogs	Choose true to have separate log files for the access and error logs.	FALSE

The image below shows the Enterprise Manager **Interfaces** panel with an nhp interface running on port 9000. This interface has a file plugin configured with the default settings and its URL path is /. The default BasePath setting is the `UniversalMessaging/doc` directory in the file hierarchy for your local product installation, which is where the default product installation places the Universal Messaging API docs. Once the plugin is created, you can click the **Apply** button which will restart the interface and enable the new file plugin.



From a browser, it is now possible to enter the URL `http://localhost:9000/` which will then render the default `index.html` page from the `UniversalMessaging/doc` directory for the API docs. The image below demonstrates the browser view from a realm that has a file plugin on an `nhp` interface on port 9000, and displaying the default API docs found in the `UniversalMessaging/doc` directory.



The screenshot shows a web browser window with the address bar displaying `http://localhost:9000/`. The page title is "Universal Messaging (Versi...". The main content area features the Universal Messaging logo (a blue circle with a stylized 'U' and 'M') and the text "Universal Messaging". Below this is the heading "Universal Messaging 10.0 Documentation Index". A paragraph of text reads: "If you are new to Universal Messaging, please see [Universal Messaging for Developers](#), which describes general concepts, installation and administration." The page is organized into three sections: "Java APIs", "C++ APIs", and "C# .NET APIs". Each section is followed by the text "The following packages are available:" and a bulleted list of API packages. The Java section lists: Java Client API, Java Administration API, and Java Transport API. The C++ section lists: C++ Client API, C++ Administration API, and C++ Transport API. The C# .NET section lists: C# .NET Client API, C# .NET Administration API, and C# .NET Transport API. The page has a light blue and white color scheme with a vertical scrollbar on the right side.

# Universal Messaging

## Universal Messaging 10.0 Documentation Index

If you are new to Universal Messaging, please see [Universal Messaging for Developers](#), which describes general concepts, installation and administration.

### Java APIs

The following packages are available:

- [Java Client API](#)
- [Java Administration API](#)
- [Java Transport API](#)

### C++ APIs

The following packages are available:

- [C++ Client API](#)
- [C++ Administration API](#)
- [C++ Transport API](#)

### C# .NET APIs

The following packages are available:

- [C# .NET Client API](#)
- [C# .NET Administration API](#)
- [C# .NET Transport API](#)

## XML Plugin

The XML Plugin can be used to query the realm server, its queues and channels. It returns the data in XML format. This plugin also supports style sheets, so the XML can be transformed into HTML or any format required. For example, a client can publish XML data onto a Universal

Messaging realm's channel, then using a standard web browser, get the server to transform the XML into HTML via a stylesheet, thereby enabling the web browser to view events on the realm.

This functionality enables realm data to be viewed from a channel without any requirement for a Java client. All that is required is for the client to have a browser.

**Important:**

Never include XSL code from untrusted sources into the plugin's XSL code, as this can lead to a security risk for the client browser (or other client application) accessing the plugin. The Universal Messaging realm server itself is not at risk, since it does not execute the plugin's XSL code.

## Configuration

Once you have created the XML plugin on the interface you require it on, you can then select it from the **Plugins** panel for the selected interface and enter values as you wish for the configuration parameters.


The XML plugin requires configuration information relating to its behavior as well as the entry point in the namespace for the channels you wish to make available to serve to the clients. Below is a table that shows each configuration parameter and describes what it is used for.

Parameter Name	Description	Default Value
ChannelRoot	Name of the channel or folder to render.	/
Security Realm	Name of the authentication realm	None.
StyleSheet	Name of the style sheet file to use to process the resulting XML.	None. If you specify a filename without a path, the default path is <code>UniversalMessaging/server/&lt;RealmName&gt;/bin</code> under the product installation root location.
UserFile	Name of the file containing the usernames and passwords	None.

**Note:**

As a starting point for creating your own stylesheet, you can use the stylesheet `xml2html.xsl` that is supplied in the `UniversalMessaging/doc/style` directory in the file hierarchy for your local product installation.

The image below shows the Enterprise Manager **Interface** panel with an nhp interface running on port 9005. This interface has an XML plugin configured to use the `xml2html.xsl` stylesheet and its URL path as `/xml`. The default ChannelRoot setting is `/`, which is the root of the namespace, i.e. all channels. Once the plugin is created, you can click the **Apply** button which will restart the interface and enable the new XML plugin.



From a browser, you can now enter the URL `http://localhost:9005/xml/` which will render the realm information page using the stylesheet. The image below demonstrates the browser view from a realm that has an XML plugin on an nhp interface on port 9005.

If you use the stylesheet `xml2html.xsl` delivered with the product, the result will be similar to the display below. The realm information is displayed at the top of the page, and the information on resources is shown beneath.

my-channels.com - Technologies Working Together - Microsoft Internet Explorer

Address <http://localhost/xml/>

my-channels technologies working together

### Realm Status for nodel


Total Memory	266469376
Free Memory	258004264
Current Threads	83
Total Connections	4
Events Published	6
Events Consumed	0

### Channel Listing

Channel Name	Number of Events	Last Event Id
<a href="#">ClusterRates</a>	2	1
<a href="#">GlobalOrders</a>	4	3
<a href="#">-p2p/serviceinfo</a>	0	-1

2001-2008 my-channels.com. ([Terms of use](#))

As you can see above, each resource is shown as a link within a table showing the information obtainable from the XML plugin. Clicking on a channel link will then take you to another page that has been rendered by the XML plugin which will show you the list of events on a channel. The image below shows the event list for the JNDI naming channel.



The XML plugin will determine whether the events on the channel contain byte data, dictionaries or XML documents and return the relevant elements within the XML document. The stylesheet applied to the XML document then examines each element to find out how to render it within the browser. Each event on the channel or queue is shown in the table with event ID, its size in bytes and links to either the byte data, the dictionary or the XML data. These links are generated by the stylesheet. Clicking on the data or dictionary links will again return an XML document from the XML plugin that will be rendered to show either the base64 encoded event data or the event dictionary.

If any events contain XML documents, these will be returned directly from the XML plugin. The stylesheet provided will not render event XML documents, since the structure of these is unknown. You will need to provide your own stylesheet to render your own XML event documents.

## Proxy Passthrough Plugin

The Proxy Passthrough Plugin can be used to forward http(s) requests from specific URLs to another host. For example, if you want to forward requests from one realm to another realm, or to another web server, you can use the proxy passthrough plugin.

This functionality enables realms to act as a proxy to forward URL requests to any host that accepts http(s) connections.


## Configuration

Once you have created the proxy passthrough plugin on the interface you require it on, you can then select it from the plugins panel for the selected interface and enter values as you wish for the configuration parameters.

The proxy passthrough plugin requires configuration information relating to the host and port that requests will be forwarded to. Below is a table that shows each configuration parameter and describes what it is used for.

Parameter Name	Description	Default Value
HostName	Host name of the process that requests for the URL will be forwarded to	
Port	Port on which the requests will be sent to the host	80

The image below shows the Enterprise Manager **Interface** panel with an nhp interface running on port 9000. This interface has a proxy passthrough plugin configured to redirect requests from this interface using the URL path of /proxy and will forward these requests to any File Plugins and XML Plugins located on the productionmaster realm's nhp interface running on port 9005.



From a browser, it is now possible to enter the URL `http://localhost:9000/proxy/` which will redirect this request to the interface on the `productionmaster` realm interface running on port 9005. This will display the details of the `productionmaster` realm as if you had specified the URL `http://productionmaster:9005/` in your browser.

## REST Plugin

The REST plugin allows access to the Universal Messaging REST API, and can be enabled on any HTTP or HTTPS (NHP or NHPS) interface. The Universal Messaging REST API is designed for publishing, purging and representing events published on channels and queues in 2 initial representations: JSON and XML.

The Universal Messaging REST API supports three different HTTP commands. GET is used for representations of events, POST for publishing and PUT for purging. Both XML and JSON support byte arrays, XML and Dictionary events for publishing, which map to native Universal Messaging event types. There are two MIME types available: text and application.

## Configuration

Once you have created the REST plugin on the interface you require it on, you can then select it from the plugins panel for that interface and enter values as desired for the configuration parameters.

Parameter Name	Description	Default Value
AddUserAsCookie	Add the username to the session's cookies.	Blank
AuthParameters	A list of key=value strings, which are passed to the Authenticator's init() function.	Blank
Authenticator	Classname of Authenticator to use. If blank, no authentication is used.	Blank
EnableStatus	Enables Realm status details. Default is disabled, for security reasons.	False
GroupNames	A comma separated list of groups. The user must be a member of at least one in order to be granted access.	Blank
IncludeTypeInfo	Includes type information for event dictionaries.	False
NamespaceRoot	Name of the namespace folder to be used as root.	Blank
ReloadUserFileDynamically	If set to true and authentication is enabled, fAuthenticator.reload() is called on each request.	True
RoleNames	A comma-separated list of names. The user must have at least one to gain access.	Blank
Security Realm	Name of the authentication realm.	Blank
SessionTimeout	Time in seconds to time-out inactive http sessions.	300

The REST plugin supports WADL documentation which is accessible through the HTTP OPTIONS command. Once you have completed setting up your REST plugin, you can verify it works by opening a browser to the NHP interface in the mount URL path, and appending the query string `?method=options`. For example, for an NHP interface running on port 9000 on localhost, and having the plugin mounted on `/rest`, open a browser to `http://localhost:9000/rest/API?method=options`.

Following this will display an HTML version of the full Universal Messaging REST API documentation which is generated by applying an XSL processor to the WADL XML document. The XML document itself can be obtained by accessing the plugin URL without the `?method=options` query string. For example, the curl command line tool can be used as follows:

```
curl -XOPTIONS http://localhost:9000/rest/API
```

What follows is a summary of the three HTTP commands for both XML and JSON, and what functionality each provides, as well as detailed examples of requests and responses for each command.

## XML: GET

Provides XML representations of channels/queues or events in a channel or queue as specified by the ChannelOrQueue parameter. The parameter is represented by the URI Path following the REST Plugin mount.

If the value supplied corresponds to a Universal Messaging namespace container, the representation returned is a list of channels and queues present in the container. If the value supplied corresponds to a channel or queue then the representation returned is a list of events. Finally if the value supplied does not correspond to either a container or a channel / queue a 404 response will be returned with no body.

Available response representations:

- [“text/xml” on page 266](#)
- [“application/xml” on page 266](#)

## XML: POST

Allows publishing of an event to a channel or queue specified by the ChannelOrQueue parameter, which is represented by the URI Path following the REST Plugin mount. For example `http://localhost:9000/rest/API/xml/testchannel` expects an XML byte, XML or dictionary event to be published to channel **testchannel**.

Acceptable request representations:

- [“text/xml” on page 271](#)
- [“application/xml” on page 271](#)

Available response representations:

- [“text/xml” on page 275](#)
- [“application/xml” on page 275](#)

## XML: PUT

Allows purging of 1 or more events already published on a channel or queue specified by the ChannelOrQueue parameter, which is represented by the URI Path following the REST Plugin mount. For example `http://localhost:9000/rest/API/xml/testchannel` expects a request to purge events to be published to channel **testchannel**. Purging can be specified by EID and selector.

Acceptable request representations:

- [“text/xml” on page 275](#)
- [“application/xml” on page 275](#)

Available response representations:

- [“text/xml” on page 275](#)
- [“application/xml” on page 275](#)

## JSON: GET

Provides JSON representations of channels/queues or events in a channel or queue as specified by the ChannelOrQueue parameter. The parameter is represented by the URI Path following the REST Plugin mount.

If the value supplied corresponds to a Universal Messaging namespace container, the representation returned is a list of channels and queues present in the container. If the value supplied corresponds to a channel or queue then the representation returned is a list of events. Finally if the value supplied does not correspond to either a container or a channel / queue a 404 response will be returned with no body.

Available response representations:

- [“application/json” on page 276](#)

## JSON: POST

Allows publishing of an event to a channel or queue specified by the ChannelOrQueue parameter, which is represented by the URI Path following the REST Plugin mount. For example `http://localhost:9000/rest/API/json/testchannel` expects a JSON byte, XML or dictionary event to be published to channel **testchannel**.

Acceptable request representations:

- [“application/json” on page 279](#)

Available response representations:

- [“application/json” on page 280](#)

## JSON: PUT

Allows purging of 1 or more events already published on a channel or queue specified by the ChannelOrQueue parameter, which is represented by the URI Path following the REST Plugin mount. For example `http://localhost:9000/rest/API/json/testchannel` expects a request to purge events to be published to channel **testchannel**. Purging can be specified by EID and selector.

Acceptable request representations:

- [“application/json” on page 281](#)

Available response representations:

- [“application/json” on page 281](#)

## Representation: XML

**XML REPRESENTATION** : An XML representation of channels/queues or events in a channel or queue as specified by the ChannelOrQueue parameter.

Should the parameter point to an existing container, the response code is 200 and the response looks like this:

```
<Nirvana-RealmServer-ChannelList NumberOfChannels="2">
  <!--Constructed by my-channels Nirvana REST-Plugin :
    Wed Mar 02 16:07:28 EET 2011-->
  <Channel EventsConsumed="0" EventsPublished="0" LastEventID="-1"
    Name="testqueue" NumberEvents="0"
    fq="http://localhost:8080/rest/API/xml/testqueue"/>
  <Channel EventsConsumed="0" EventsPublished="2" LastEventID="223"
    Name="testchannel" NumberEvents="2"
    fq="http://shogun:8080/rest/API/xml/testchannel"/>
</Nirvana-RealmServer-ChannelList>
```

If the REST plugin is configured to include realm status, some additional information about the realm is presented:

```
<Nirvana-RealmServer-ChannelList NumberOfChannels="2">
  <!--Constructed by my-channels Nirvana REST-Plugin :
    Wed Mar 02 16:07:28 EET 2011-->
  <Channel EventsConsumed="0" EventsPublished="0" LastEventID="-1"
    Name="testqueue" NumberEvents="0"
    fq="http://localhost:8080/rest/API/xml/testqueue"/>
  <Channel EventsConsumed="0" EventsPublished="2" LastEventID="223"
    Name="testchannel" NumberEvents="2"
    fq="http://shogun:8080/rest/API/xml/testchannel"/>
  <RealmStatus FreeMemory="498101048" RealmName="nirvana6" Threads="87"
    TotalConnections="0" TotalConsumed="0"
    TotalMemory="530186240" TotalPublished="2"/>
</Nirvana-RealmServer-ChannelList>
```

Should the parameter point to an existing channel or queue, the response code is 200 and the response looks like this:

```
<Nirvana-RealmServer-EventList>
  <!--Constructed by my-channels Nirvana REST-Plugin :
    Wed Mar 02 16:10:57 EET 2011-->
  <Details ChannelName="http://localhost:8080/rest/API/xml/testsrc"
    FirstEvent=
      "http://localhost:8080/rest/API/xml/testsrc?Data=Dictionary&EID=first"

    LastEID="223"
    LastEvent=
      "http://localhost:8080/rest/API/xml/testsrc?Data=Dictionary&EID=last"
    NextLink="http://localhost:8080/rest/API/xml/testsrc?EID=224" StartEID="222"/>
  <Event ByteLink="http://localhost:8080/rest/API/xml/testsrc?Data=Byte&EID=222"

    DataSize="9" EID="222" Tag="Test Tag" hasByte="true"/>
  <Event
    DictionaryLink=
      "http://localhost:8080/rest/API/xml/testsrc?Data=Dictionary&EID=223"
    EID="223" hasDictionary="true"/>
</Nirvana-RealmServer-EventList>
```

You can follow the provided links to view individual events. If you choose to look at an individual byte event, the response code is 200 and the response looks like this:

```
<Nirvana-RealmServer-RawData>
  <!--Constructed by my-channels Nirvana REST-Plugin :
```

```
Wed Mar 02 16:13:17 EET 2011-->
<EventData ChannelName="http://localhost:8080/rest/API/xml/testsrc" EID="222">
  <Data>
    <![CDATA[VGVzdCBCb2R5]]>
  </Data>
  <Tag>
    <![CDATA[Test Tag]]>
  </Tag>
</EventData>
</Nirvana-RealmServer-RawData>
```

If you choose to look at an individual XML event, the response code is 200 and the response looks like this:

```
<Nirvana-RealmServer-XMLData>
  <!--Constructed by my-channels Nirvana REST-Plugin :
    Wed Mar 02 16:13:17 EET 2011-->
  <EventData ChannelName="http://localhost:8080/rest/API/xml/testsrc" EID="222"
    isDOM="true">
    <Data>
      <myUserDataTag>
        Some User Data
      </myUserDataTag>
    </Data>
    <Tag>
      <![CDATA[Test Tag]]>
    </Tag>
  </EventData>
</Nirvana-RealmServer-XMLData>
```

If you choose to look at an individual Dictionary event, the response code is 200 and the response looks like this:

```
<DictionaryData isPersistent="true" TTL="0">
  <Data Key="testdouble">
    <![CDATA[1.0]]>
  </Data>
  <Data Key="testinteger">
    <![CDATA[1]]>
  </Data>
  <Data Key="teststring">
    <![CDATA[teststringvalue]]>
  </Data>
  <Dictionary Key="testdictionary">
    <Data Key="testdouble">
      <![CDATA[1.0]]>
    </Data>
    <Data Key="testinteger">
      <![CDATA[1]]>
    </Data>
    <Data Key="teststring">
      <![CDATA[teststringvalue]]>
    </Data>
    <Data Key="testlong">
      <![CDATA[1]]>
    </Data>
    <Data Key="testfloat">
      <![CDATA[1.0]]>
    </Data>
  </Dictionary>
</DictionaryData>
```

```

    <Data Key="testcharacter">
      <![CDATA[a]]>
    </Data>
    <Data Key="testboolean">
      <![CDATA[true]]>
    </Data>
  </Dictionary>
  <Data Key="testlong">
    <![CDATA[1]]>
  </Data>
  <Data Key="testfloat">
    <![CDATA[1.0]]>
  </Data>
  <Data Key="testcharacter">
    <![CDATA[a]]>
  </Data>
  <Data Key="testboolean">
    <![CDATA[true]]>
  </Data>
  <DataArray Key="teststringarray">
    <ArrayItem Index="0">
      <![CDATA[one]]>
    </ArrayItem>
    <ArrayItem Index="1">
      <![CDATA[two]]>
    </ArrayItem>
    <ArrayItem Index="2">
      <![CDATA[three]]>
    </ArrayItem>
  </DataArray>
  <DataArray Key="testbytearray">
    <ArrayItem Index="0">
      <![CDATA[YSBib2R5]]>
    </ArrayItem>
  </DataArray>
  <DataArray Key="testdictionaryarray">
    <ArrayItem Index="0">
      <Data Key="testdouble">
        <![CDATA[1.0]]>
      </Data>
      <Data Key="testinteger">
        <![CDATA[1]]>
      </Data>
      <Data Key="teststring">
        <![CDATA[teststringvalue]]>
      </Data>
    </ArrayItem>
    <ArrayItem Index="1">
      <Data Key="testdouble">
        <![CDATA[1.0]]>
      </Data>
      <Data Key="testinteger">
        <![CDATA[1]]>
      </Data>
      <Data Key="teststring">
        <![CDATA[teststringvalue]]>
      </Data>
    </ArrayItem>
  </DataArray>
</DictionaryData>

```

If the rest plugin is configured to include type information in representations, dictionary event representations will include them. In this case, responses looks like this:

```
<DictionaryData isPersistent="true" TTL="0">
  <Data Key="testdouble" Type="2">
    <![CDATA[1.0]]>
  </Data>
  <Data Key="testinteger" Type="4">
    <![CDATA[1]]>
  </Data>
  <Data Key="teststring" Type="0">
    <![CDATA[teststringvalue]]>
  </Data>
  <Dictionary Key="testdictionary">
    <Data Key="testdouble" Type="2">
      <![CDATA[1.0]]>
    </Data>
    <Data Key="testinteger" Type="4">
      <![CDATA[1]]>
    </Data>
    <Data Key="teststring" Type="0">
      <![CDATA[teststringvalue]]>
    </Data>
    <Data Key="testlong" Type="1">
      <![CDATA[1]]>
    </Data>
    <Data Key="testfloat" Type="5">
      <![CDATA[1.0]]>
    </Data>
    <Data Key="testcharacter" Type="6">
      <![CDATA[a]]>
    </Data>
    <Data Key="testboolean" Type="3">
      <![CDATA[true]]>
    </Data>
  </Dictionary>
  <Data Key="testlong" Type="1">
    <![CDATA[1]]>
  </Data>
  <Data Key="testfloat" Type="5">
    <![CDATA[1.0]]>
  </Data>
  <Data Key="testcharacter" Type="6">
    <![CDATA[a]]>
  </Data>
  <Data Key="testboolean" Type="3">
    <![CDATA[true]]>
  </Data>
  <DataArray ArrayType="0" Key="teststringarray">
    <ArrayItem Index="0">
      <![CDATA[one]]>
    </ArrayItem>
    <ArrayItem Index="1">
      <![CDATA[two]]>
    </ArrayItem>
    <ArrayItem Index="2">
      <![CDATA[three]]>
    </ArrayItem>
  </DataArray>
```

```

<DataArray ArrayType="7" Key="testbytearray">
  <ArrayItem Index="0">
    <![CDATA[YSBib2R5]]>
  </ArrayItem>
</DataArray>
<DataArray ArrayType="9" Key="testdictionaryarray">
  <ArrayItem Index="0">
    <Data Key="testdouble" Type="2">
      <![CDATA[1.0]]>
    </Data>
    <Data Key="testinteger" Type="4">
      <![CDATA[1]]>
    </Data>
    <Data Key="teststring" Type="0">
      <![CDATA[teststringvalue]]>
    </Data>
  </ArrayItem>
  <ArrayItem Index="1">
    <Data Key="testdouble" Type="2">
      <![CDATA[1.0]]>
    </Data>
    <Data Key="testinteger" Type="4">
      <![CDATA[1]]>
    </Data>
    <Data Key="teststring" Type="0">
      <![CDATA[teststringvalue]]>
    </Data>
  </ArrayItem>
</DataArray>
</DictionaryData>

```

Finally, should the parameter point to a non existing container or channel / queue, the response code is 404 without a response body

## XML PUBLISH REQUEST

XML Byte events can be represented as follows:

```

<EventData isDom="false" isPersistent="true" TTL="0">
  <Data>
    <![CDATA[YSBib2R5]]>
  </Data>
  <Tag>
    <![CDATA[YSB0Ywc=]]>
  </Tag>
</EventData>

```

### **Important:**

data and tag should always be submitted in base64 encoded form.

XML DOM events can be represented as follows:

```

<EventData isDom="true" isPersistent="true" TTL="0">
  <Data>
    <![CDATA[YSBib2R5]]>
  </Data>
  <Tag>
    <![CDATA[YSB0Ywc=]]>
  </Tag>

```

```
</EventData>
```

**Important:**

data and tag should always be submitted in base64 encoded form.

XML Dictionary events can be represented as follows:

```
<DictionaryData isPersistent="true" TTL="0">
  <Data Key="testdouble">
    <![CDATA[1.0]]>
  </Data>
  <Data Key="testinteger">
    <![CDATA[1]]>
  </Data>
  <Data Key="teststring">
    <![CDATA[teststringvalue]]>
  </Data>
  <Dictionary Key="testdictionary">
    <Data Key="testdouble">
      <![CDATA[1.0]]>
    </Data>
    <Data Key="testinteger">
      <![CDATA[1]]>
    </Data>
    <Data Key="teststring">
      <![CDATA[teststringvalue]]>
    </Data>
    <Data Key="testlong">
      <![CDATA[1]]>
    </Data>
    <Data Key="testfloat">
      <![CDATA[1.0]]>
    </Data>
    <Data Key="testcharacter">
      <![CDATA[a]]>
    </Data>
    <Data Key="testboolean">
      <![CDATA[true]]>
    </Data>
  </Dictionary>
  <Data Key="testlong">
    <![CDATA[1]]>
  </Data>
  <Data Key="testfloat">
    <![CDATA[1.0]]>
  </Data>
  <Data Key="testcharacter">
    <![CDATA[a]]>
  </Data>
  <Data Key="testboolean">
    <![CDATA[true]]>
  </Data>
  <DataArray Key="teststringarray">
    <ArrayItem Index="0">
      <![CDATA[one]]>
    </ArrayItem>
    <ArrayItem Index="1">
      <![CDATA[two]]>
    </ArrayItem>
  </DataArray>
```

```

    <ArrayItem Index="2">
      <![CDATA[three]]>
    </ArrayItem>
  </DataArray>
  <DataArray Key="testbytearray">
    <ArrayItem Index="0">
      <![CDATA[YSBib2R5]]>
    </ArrayItem>
  </DataArray>
  <DataArray Key="testdictionaryarray">
    <ArrayItem Index="0">
      <Data Key="testdouble">
        <![CDATA[1.0]]>
      </Data>
      <Data Key="testinteger">
        <![CDATA[1]]>
      </Data>
      <Data Key="teststring">
        <![CDATA[teststringvalue]]>
      </Data>
    </ArrayItem>
    <ArrayItem Index="1">
      <Data Key="testdouble">
        <![CDATA[1.0]]>
      </Data>
      <Data Key="testinteger">
        <![CDATA[1]]>
      </Data>
      <Data Key="teststring">
        <![CDATA[teststringvalue]]>
      </Data>
    </ArrayItem>
  </DataArray>
</DictionaryData>

```

Optionally, dictionary events can include type information (see [“Types” on page 281](#)). This allows the Universal Messaging REST API to preserve these types when publishing the event. The types are defined as byte constants to keep typed dictionary events compact in size.

XML Dictionary events (with type information) can be represented as follows:

```

<DictionaryData isPersistent="true" TTL="0">
  <Data Key="testdouble" Type="2">
    <![CDATA[1.0]]>
  </Data>
  <Data Key="testinteger" Type="4">
    <![CDATA[1]]>
  </Data>
  <Data Key="teststring" Type="0">
    <![CDATA[teststringvalue]]>
  </Data>
  <Dictionary Key="testdictionary">
    <Data Key="testdouble" Type="2">
      <![CDATA[1.0]]>
    </Data>
    <Data Key="testinteger" Type="4">
      <![CDATA[1]]>
    </Data>
    <Data Key="teststring" Type="0">

```

```

        <![CDATA[teststringvalue]]>
    </Data>
    <Data Key="testlong" Type="1">
        <![CDATA[1]]>
    </Data>
    <Data Key="testfloat" Type="5">
        <![CDATA[1.0]]>
    </Data>
    <Data Key="testcharacter" Type="6">
        <![CDATA[a]]>
    </Data>
    <Data Key="testboolean" Type="3">
        <![CDATA[true]]>
    </Data>
</Dictionary>
<Data Key="testlong" Type="1">
    <![CDATA[1]]>
</Data>
<Data Key="testfloat" Type="5">
    <![CDATA[1.0]]>
</Data>
<Data Key="testcharacter" Type="6">
    <![CDATA[a]]>
</Data>
<Data Key="testboolean" Type="3">
    <![CDATA[true]]>
</Data>
<DataArray ArrayType="0" Key="teststringarray">
    <ArrayItem Index="0">
        <![CDATA[one]]>
    </ArrayItem>
    <ArrayItem Index="1">
        <![CDATA[two]]>
    </ArrayItem>
    <ArrayItem Index="2">
        <![CDATA[three]]>
    </ArrayItem>
</DataArray>
<DataArray ArrayType="7" Key="testbytearray">
    <ArrayItem Index="0">
        <![CDATA[YSBib2R5]]>
    </ArrayItem>
</DataArray>
<DataArray ArrayType="9" Key="testdictionaryarray">
    <ArrayItem Index="0">
        <Data Key="testdouble" Type="2">
            <![CDATA[1.0]]>
        </Data>
        <Data Key="testinteger" Type="4">
            <![CDATA[1]]>
        </Data>
        <Data Key="teststring" Type="0">
            <![CDATA[teststringvalue]]>
        </Data>
    </ArrayItem>
    <ArrayItem Index="1">
        <Data Key="testdouble" Type="2">
            <![CDATA[1.0]]>
        </Data>
        <Data Key="testinteger" Type="4">

```

```

        <![CDATA[1]]>
    </Data>
    <Data Key="teststring" Type="0">
        <![CDATA[teststringvalue]]>
    </Data>
</ArrayItem>
</DataArray>
</DictionaryData>

```

**Important:**

byte[ ] types should always be submitted in base64 encoded form.

**XML PUBLISH RESPONSE** : A XML representation to indicate the status of attempting to publish an event to the channel or queue specified by the ChannelOrQueue parameter.

Should the publish call be successful, the response code is 201 and the response looks like this:

```

<Nirvana-RealmServer-PublishRequest>
  <response value="ok"/>
</Nirvana-RealmServer-PublishRequest>

```

Should the publish call fail for any reason, the response code is 400 and the response looks like this:

```

<Nirvana-RealmServer-Error>
  <response value="failInput"/>
  <errorcode value="ErrorCode"/>
  <errormessage value="Error Message"/>
</Nirvana-RealmServer-Error>

```

**XML PURGE REQUEST** : A XML representation of a Purge Request that indicates the event(s) to purge.

A XML purge request looks as follows:

```

<Nirvana-RealmServer-PurgeRequest startEID="10" endEID="20" purgeJoins="false">
  <selector>
    <![CDATA[]]>
  </selector>
</Nirvana-RealmServer-PurgeRequest>

```

**XML PURGE RESPONSE** : A XML representation to indicate the status of attempting to purge an event to the channel or queue specified by the ChannelOrQueue parameter.

Should the purge call be successful, the response code is 200 and the response looks like this:

```

<Nirvana-RealmServer-PurgeRequest>
  <response value="ok"/>
</Nirvana-RealmServer-PurgeRequest>

```

Should the purge call fail for any reason, the response code is 400 and the response looks like this:

```

<Nirvana-RealmServer-Error>
  <response value="failInput"/>
  <errorcode value="ErrorCode"/>
  <errormessage value="Error Message"/>
</Nirvana-RealmServer-Error>

```

## Representation: JSON

**JSON REPRESENTATION** : A JSON representation of channels/queues or events in a channel or queue as specified by the ChannelOrQueue parameter.

Should the parameter point to an existing container, the response code is 200 and the response looks like this:

```
{
  "Channels":
  [ {
    "EventsConsumed": "0",
    "EventsPublished": "0",
    "LastEventID": "-1",
    "Name": "testqueue",
    "NumberEvents": "0",
    "fqdn": "http://localhost:8080/rest/API/json/testqueue"
  }, {
    "EventsConsumed": "0",
    "EventsPublished": "0",
    "LastEventID": "212",
    "Name": "testchannel",
    "NumberEvents": "0",
    "fqdn": "http://localhost:8080/rest/API/json/testchannel"
  } ],
  "Comment": "Constructed by my-channels Nirvana REST-Plugin :
              Wed Mar 02 11:38:30 EET 2011",
  "Name":
  "Nirvana-RealmServer-ChannelList",
  "NumberOfChannels": "2",
}
```

If the REST plugin is configured to include realm status, some additional information about the realm is presented:

```
{
  "Channels":
  [ {
    "EventsConsumed": "0",
    "EventsPublished": "0",
    "LastEventID": "-1",
    "Name": "testqueue",
    "NumberEvents": "0",
    "fqdn": "http://localhost:8080/rest/API/json/testqueue"
  }, {
    "EventsConsumed": "0",
    "EventsPublished": "0",
    "LastEventID": "212",
    "Name": "testchannel",
    "NumberEvents": "0",
    "fqdn": "http://localhost:8080/rest/API/json/testchannel"
  } ],
  "Comment": "Constructed by my-channels Nirvana REST-Plugin :
              Wed Mar 02 11:38:30 EET 2011",
  "Name": "Nirvana-RealmServer-ChannelList",
  "NumberOfChannels": "2",
  "Realm": {
```

```

    "FreeMemory": "503291048",
    "RealmName": "nirvana6",
    "Threads": "104",
    "TotalConnections": "1",
    "TotalConsumed": "0",
    "TotalMemory": "530186240",
    "TotalPublished": "0"
  }
}

```

Should the parameter point to an existing channel or queue, the response code is 200 and the response looks like this:

```

{
  "ChannelName": "http://localhost:8080/rest/API/json/testsrc",
  "Comment": "Constructed by my-channels Nirvana REST-Plugin : Wed
Mar 02 12:19:22 EET 2011",
  "Events":
  [ {
    "ByteLink": "http://localhost:8080/rest/API/json/testsrc?Data=Byte&EID=213",
    "DataSize": "9",
    "EID": "213",
    "Tag": "Test Tag",
    "hasByte": "true"
  }, {
    "DictionaryLink":
      "http://localhost:8080/rest/API/json/testsrc?Data=Dictionary&EID=214",
    "EID": "214",
    "hasDictionary": "true"
  } ],
  "FirstEvent":
"http://localhost:8080/rest/API/json/testsrc?Data=Dictionary&EID=first",
  "LastEID": "214",
  "LastEvent": "http://localhost:8080/rest/API/json/testsrc?Data=Dictionary&EID=last",
  "Name": "Nirvana-RealmServer-EventList",
  "NextLink": "http://localhost:8080/rest/API/json/testsrc?EID=215",
  "StartEID": "213"
}

```

You can follow the provided links to view individual events. If you choose to look at an individual byte event, the response code is 200 and the response looks like this:

```

{
  "ChannelName": "http://localhost:8080/rest/API/json/testsrc",
  "Comment": "Constructed by my-channels Nirvana REST-Plugin :
Wed Mar 02 12:21:46 EET 2011",
  "Data": "VGVzdCBCb2R5",
  "EID": "213",
  "Name": "Nirvana-RealmServer-RawData",
  "Tag": "Test Tag"
}

```

If you choose to look at an individual XML event, the response code is 200 and the response looks like this:

```

{
  "ChannelName": "http://localhost:8080/rest/API/json/testsrc",
  "Comment": "Constructed by my-channels Nirvana REST-Plugin :
Wed Mar 02 12:21:46 EET 2011",

```

```

    "Data": "VGVzdCBCb2R5",
    "EID": "213",
    "Name": "Nirvana-RealmServer-XMLData",
    "Tag": "Test Tag"
  }

```

If you choose to look at an individual Dictionary event, the response code is 200 and the response looks like this:

```

{
  "dictionary":
  {
    "testboolean": [true],
    "testcharacter": ["a"],
    "testdictionary": [
      {
        "testboolean": [true],
        "testcharacter": ["a"],
        "testdouble": [1],
        "testfloat": [1],
        "testinteger": [1],
        "testlong": [1],
        "teststring": ["teststringvalue"]
      }
    ],
    "testdouble": [1],
    "testfloat": [1],
    "testinteger": [1],
    "testlong": [1],
    "teststring": ["teststringvalue"],
    "teststringarray": [
      "one",
      "two",
      "three"
    ]
  ],
  "isPersistent": true
}

```

If the rest plugin is configured to include type information in representations, dictionary event representations will include them. In this case, responses look like this:

```

{
  "dictionary":
  {
    "testboolean": [ true, 3 ],
    "testcharacter": [ "a", 6 ],
    "testdictionary":
    [ {
      "testboolean": [ true, 3 ],
      "testcharacter": [ "a", 6 ],
      "testdouble": [ 1, 2 ],
      "testfloat": [ 1, 5 ],
      "testinteger": [ 1, 4 ],
      "testlong": [ 1, 1 ],
      "teststring": [ "teststringvalue", 0 ]
    }, 9 ],
    "testdouble": [ 1, 2 ],
    "testfloat": [ 1, 5 ],
    "testinteger": [ 1, 4 ],
  }
}

```

```

    "testlong": [ 1, 1 ],
    "teststring": [ "teststringvalue", 0 ],
    "teststringarray":
      [[
        "one",
        "two",
        "three"
      ], 100, 0 ]
  },
  "isPersistent": true
}

```

Finally, should the parameter point to a non existing container or channel / queue, the response code is 404 without a response body

## JSON PUBLISH REQUEST

JSON Byte events can be represented as follows:

```

{
  "data": "VGZzdCBCb2R5",
  "isPersistent": true,
  "tag": "VGZzdCBUYWc="
}

```

### **Important:**

data and tag should always be submitted in base64 encoded form.

JSON DOM events can be represented as follows:

```

{
  "data": "VGZzdCBCb2R5",
  "isDOM": true,
  "isPersistent": true,
  "tag": "VGZzdCBUYWc="
}

```

### **Important:**

data and tag should always be submitted in base64 encoded form.

JSON Dictionary events can be represented as follows:

```

{
  "dictionary":
  {
    "testboolean": [true],
    "testcharacter": ["a"],
    "testdictionary":
    [{
      "testboolean": [true],
      "testcharacter": ["a"],
      "testdouble": [1],
      "testfloat": [1],
      "testinteger": [1],
      "testlong": [1],
      "teststring": ["teststringvalue"]
    }],
    "testdouble": [1],

```

```

    "testfloat": [1],
    "testinteger": [1],
    "testlong": [1],
    "teststring": ["teststringvalue"],
    "teststringarray":
    [[
        "one",
        "two",
        "three"
    ]]
  },
  "isPersistent": true
}

```

Optionally, dictionary events can include type information (see [“Types” on page 281](#)). This allows the Universal Messaging REST API to preserve these types when publishing the event. The types are defined as byte constants to keep typed dictionary events compact in size.

Dictionary events (with type information) can be represented as follows:

```

{
  "dictionary":
  {
    "testboolean": [ true, 3 ],
    "testcharacter": [ "a", 6 ],
    "testdictionary":
    [ {
      "testboolean": [ true, 3 ],
      "testcharacter": [ "a", 6 ],
      "testdouble": [ 1, 2 ],
      "testfloat": [ 1, 5 ],
      "testinteger": [ 1, 4 ],
      "testlong": [ 1, 1 ],
      "teststring": [ "teststringvalue", 0 ]
    }, 9 ],
    "testdouble": [ 1, 2 ],
    "testfloat": [ 1, 5 ],
    "testinteger": [ 1, 4 ],
    "testlong": [ 1, 1 ],
    "teststring": [ "teststringvalue", 0 ],
    "teststringarray":
    [ [
      "one",
      "two",
      "three"
    ], 100, 0 ]
  },
  "isPersistent": true
}

```

**Important:**

byte[] types should always be submitted in base64 encoded form.

**JSON PUBLISH RESPONSE :** A JSON representation to indicate the status of attempting to publish an event to the channel or queue specified by the ChannelOrQueue parameter.

Should the publish call be successful, the response code is 201 and the response looks like this:

```
{
  "Response": "OK"
}
```

Should the publish call fail for any reason, the response code is 400 and the response looks like this:

```
{
  "errorcode": "ErrorCode",
  "errormessage": "Error Message",
  "response": "failInput"
}
```

**JSON PURGE REQUEST** : A JSON representation of a Purge Request that indicates the event(s) to purge.

A JSON purge request looks as follows:

```
{
  "endEID": 20,
  "purgeJoins": false,
  "selector": "",
  "startEID": 10
}
```

**JSON PURGE RESPONSE** : A JSON representation to indicate the status of attempting to purge an event to the channel or queue specified by the ChannelOrQueue parameter

Should the purge call be successful, the response code is 200 and the response looks like this:

```
{
  "Response": "OK"
}
```

Should the purge call fail for any reason, the response code is 400 and the response looks like this:

```
{
  "errorcode": "ErrorCode",
  "errormessage": "Error Message",
  "response": "failInput"
}
```

## Types

Type	ID
String	0
Long	1
Double	2
Boolean	3
Integer	4

Type	ID
Float	5
Character	6
Byte	7
Short	8
Dictionary	9
Array	100

## SOAP Plugin

The Universal Messaging SOAP Plugin utilises the advanced HTTP/HTTPS stack capabilities of the Universal Messaging server to provide an implementation of a SOAP 1.2 based client API. Any SOAP toolkit can use the provided WSDL to generate client stubs for any SOAP compliant language. This way Universal Messaging functionality is offered to programming languages that were previously unsupported and all this without the need for any additional infrastructure component (SOAP server, web server etc).

The plugin can be configured to expose complete Universal Messaging namespaces or subsets, support username/password authentication, control web service listing and other options further explained in the section below.

## Configuration

Once you have created the SOAP plugin on the interface you require it on, you can then select it from the plugins panel for the selected interface and enter values as you wish for the configuration parameters.


The SOAP plugin requires configuration details regarding the entry point in the namespace for the channels you wish to make available to vend to the clients, as well as web-services specific configuration. Below is a table that shows each configuration parameter and describes what it is used for.

Parameter Name	Description	Default Value
URL File Path	The mount URL path for the SOAP plugin to be invoked.	None (/soap needed for samples)
ChannelRoot	Universal Messaging namespace node (channel or folder) to expose through soap	/
UserFile	Name of the file containing the usernames and passwords	None.


Parameter Name	Description	Default Value
Security Realm	Name of the authentication realm	None.
AttachmentDir	Name of the directory to find the AXIS attachments	<ServerPath>/plugins/attachments/
EnableList	Enable or disable the listing of web services WSDL files. This is necessary if you want to generate client stubs.	false.
WebRootDir	Name of the directory containing the WEB-INF directory	<ServerPath>/plugins/
WSDLEncoding	Type of encoding to be used for WSDL, valid values are document, rpc, wrapped	rpc

In the table above, <ServerPath> is the location `UniversalMessaging/server/<RealmName>` under the product installation root location.

The image below shows the Enterprise Manager interface panel with an nhp interface running on port 9000. This interface has a SOAP Plugin configured with its URL path as `/soap`. The default **ChannelRoot** setting is `/`, which is the root of the namespace, i.e. all channels. Once the plugin is created, you can click the **Apply** button which will restart the interface and enable the new SOAP plugin.



From a browser, you can now enter the URL 'http://localhost:9000/soap/' which shows the available services exposed via SOAP as well as links to the WSDL documents required to generate client stubs:



### Samples

The Universal Messaging installation includes a few samples for Perl in the `UniversalMessaging/extras/soap/perl` directory. The applications use the `SOAP::Lite` Perl module and were tested under Cygwin for Windows. Please note that all the samples included assume that you have an NHP interface running on port 80 on the local machine, and that there is a SOAP plugin configured under `/soap`. Furthermore the `getEvent.pl` sample requires you to have a channel called `test` with at least 1 event inside.

For example to execute `getChannelDetails.pl`, open a cygwin (or other) shell and type:

```
$ perl getChannelDetails.pl
-----
firstEid=-1
ttl=0
name=Universal Messaging-p2p/serviceinfo
eventCount=0
type=Simple
capacity=0
lastEid=-1
-----
firstEid=0
ttl=0
name=test
eventCount=10
type=Reliable
capacity=0
lastEid=9
```

### Servlet Plugin

The servlet plugin enables the Universal Messaging realm server to serve Java servlets.

## Configuration

Once you have created the servlet plugin on an interface, you can then select it from the **Plugins** panel for the interface and configure the plugin parameters.

The servlet plugin requires configuration information relating to its behavior, as well as the location of the servlets it is required to serve to the clients. Below is a table that shows each configuration parameter and describes what each is used for.

To ensure security, the `EnforceConfigFile` option can be set to `true`; this allows only those classes specified in the configuration file to be loaded. Alternatively, the `EnforceStrictClassLoader` option can be set; this prevents classes being loaded from different class loaders to that of the servlet, and thereby also prevents arbitrary classes from being loaded.

Parameter Name	Description	Default Value
AddUserAsPlugin	Add the username to the session cookies.	false
AuthParameters	List of key=value string which is passed to authenticators init function.	
AddUserAsPlugin	Classname of authenticator to use, leave blank for default	(default)
EnableClassReload	Automatically reload servlet class if it changes	true
EnforceConfigFile	If true, only servlets within the ServletConfigFile will be executed.	true
EnforceStrictClassLoader	If true, only servlets loaded by the initial class loader will be executed. Any classes loaded by parent loader will be ignored.	true
GroupNames	A comma separated list of groups to which a user must be a member of to be granted access.	
MimeType	Name of the file to load the mime type information from. The format of the file is same as the apache mime types.	
Properties	File containing the servlet properties. The file should be a java properties file that contains one property per line prefixed with the full class name. For example for a servlet class <code>com.example.Servlet</code> defining a property called <code>RNAME</code> you should have a line as follows: <code>com.example.Servlet.RNAME=nsp://localhost:9000</code>	
ReloadUserFileDynamically	If true, the user file will get reloaded on each auth request.	true
RoleNames	A comma separated list of groups to which a user must have one to be granted access.	
Security Realm	Name of the authentication realm.	

Parameter Name	Description	Default Value
Servlet Config File	File which contains all the valid servlets which will run. The file should be a text file containing one full servlet class name per line, indicating only these should be allowed to run. For example having a single line com.example.Servlet would mean that only that servlet will be allowed to run irrespective of how many exist in the server classpath.	
Servlet Path	Directory in which to locate servlet classes	
SessionTimeout	Time in seconds before timeout of servlet session not in use.	

## XML Configuration: Overview

The Universal Messaging Enterprise Manager allows you to export specific elements of the realm or the entire realm structure into an XML representation. The exported XML can contain all clusters, realm ACLs, channels, queues and their ACLs, configuration parameters, JNDI assets, interfaces, plugins and scheduling information. Once exported, the XML can then be imported into any other realm, which is useful when you wish to clone realms and their internal structures. Importing the xml will automatically create and configure those objects selected for the import from the XML file.

The export and import marshals the realm objects from their Administration API representation into XML and back again. This provides a very powerful way of automatically configuring a realm based on a standard structure.


See the links below to view more about the import and export mechanism available in the Universal Messaging Enterprise Manager:

- [“XML Configuration: Exporting To XML” on page 287](#)
- [“XML Configuration: Importing From XML” on page 288](#)

### XML Configuration: Exporting To XML

The ability to export an entire realm or specific elements of a realm's structure is a powerful enabler for managing the configuration of multiple realms within your enterprise. This section will discuss how to export realm elements to their xml representation.

Firstly, to export a realm to xml, you need to select the realm you wish to export from the Enterprise Manager namespace. Right-clicking on the realm node will present a menu for the options available on a realm node. One of those menu options is labelled 'Export Realm to XML'. Selecting this menu option will present a dialog as shown in the image below.



The dialog above shows the list of export options available for the realm, and the name and location of the file that will be exported. The 'Export to' field is the name and location of the file to export which can either be typed manually, or chosen by selecting the button with the folder icon that shows a file chooser dialog.

There are a large number of options for what can be exported from a realm. The check boxes indicated on the dialog can all be selected individually for specific elements of a realm to be exported, or by clicking on the 'Export All' button all options will be selected.

Clicking on the 'OK' button will export the realm to xml into the file and location specified.

To view an example of the XML produced from the export, see [“XML Configuration: Sample XML File for EXPORT” on page 289](#).

## XML Configuration: Importing From XML

The ability to import realm elements from XML is a powerful enabler for managing the configuration of multiple realms within your enterprise. This section describes how to import realm elements from the XML representation.

Firstly, to import a realm to XML, you need to have first made sure you have the desired elements you wish to import within an XML file. For help on export, see [“XML Configuration: Exporting To XML” on page 287](#). To import XML, select the realm you wish to import the realm data to from the Enterprise Manager namespace. Right-clicking on the realm node will present a menu for the

options available on a realm node. One of those menu options is labelled **Import Realm from XML**.

The Import realm from XML dialog box shows the list of import options available for the realm, and the name and location of the file that will be used for the import. The **Import from** field is the name and location of the file to import from which can either be typed manually, or chosen by selecting the button with the folder icon that shows a file chooser dialog.

There are a large number of options for what can be imported from XML into a realm. The check boxes in the dialog can all be selected individually for specific elements of a realm to be imported, or by clicking **Import All** all options will be selected.

**Important:**

Importing a configuration that contains clustered transient channels and queues will fail because transient channels and queues are not supported in a cluster. To resolve this situation, you can use the **Convert cluster-wide transient channels and queues to mixed** option to automatically convert all clustered transient channels and queues to mixed. However, be aware that converting clustered transient channels and queues to mixed might cause additional disk and memory consumption for events published to these channels and queues. If you are importing into a realm that is part of a cluster, the **Convert cluster-wide transient channels and queues to mixed** option is selected by default.

Clicking on the **OK** button will import the XML into the realm from file and location specified, and then attempt to create the objects and set the configuration elements defined within the XML.

To view an example of the XML produced from the export, see [“XML Configuration: Sample XML File for EXPORT” on page 289](#).

To view an example of the XML produced from the import, see [“XML Configuration: Sample XML File for IMPORT” on page 293](#).

## Setting to make Channels and Queues clustered or non-clustered while importing

When you export channels or queues to an XML file, each channel or queue in the XML file has an attribute `clusterWide`. If you export a clustered channel or queue, this attribute is set to "true", and if you export a non-clustered channel or queue, this attribute is set to "false".

Before you import the XML file into a realm, you can manually edit the XML file and modify the `clusterWide` attribute of each channel/queue, depending on how you want to import the channel/queue. If you want a channel or queue to be imported as clustered while doing an import on a clustered realm, set `clusterWide` to "true", and if you want a channel or queue to be imported as non-clustered, set `clusterWide` to "false".

### XML Configuration: Sample XML File for EXPORT

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<Universal MessagingRealm comment="Realm configuration from productionmaster"
  exportDate="2005-01-06+00:00" name="productionmaster">
  <RealmConfiguration>
    <ConfigGroup name="AuditSettings">
      <ConfigItem name="ChannelACL" value="true"/>
    </ConfigGroup>
  </RealmConfiguration>
</Universal MessagingRealm>
```

```

<ConfigItem name="ChannelFailure" value="true"/>
<ConfigItem name="ChannelMaintenance" value="false"/>
<ConfigItem name="ChannelSuccess" value="false"/>
<ConfigItem name="InterfaceManagement" value="true"/>
<ConfigItem name="JoinFailure" value="true"/>
<ConfigItem name="JoinMaintenance" value="true"/>
<ConfigItem name="JoinSuccess" value="false"/>
<ConfigItem name="QueueACL" value="true"/>
<ConfigItem name="QueueFailure" value="true"/>
<ConfigItem name="QueueMaintenance" value="false"/>
<ConfigItem name="QueueSuccess" value="false"/>
<ConfigItem name="RealmACL" value="true"/>
<ConfigItem name="RealmFailure" value="true"/>
<ConfigItem name="RealmMaintenance" value="true"/>
<ConfigItem name="RealmSuccess" value="false"/>
<ConfigItem name="ServiceACL" value="true"/>
<ConfigItem name="ServiceFailure" value="true"/>
<ConfigItem name="ServiceMaintenance" value="true"/>
<ConfigItem name="ServiceSuccess" value="false"/>
</ConfigGroup>
<ConfigGroup name="ClientTimeoutValues">
<ConfigItem name="DisconnectWait" value="120000"/>
<ConfigItem name="EventTimeout" value="60000"/>
<ConfigItem name="HighWaterMark" value="200"/>
<ConfigItem name="KaWait" value="60000"/>
<ConfigItem name="LowWaterMark" value="50"/>
<ConfigItem name="QueueAccessWaitLimit" value="200"/>
<ConfigItem name="QueueBlockLimit" value="500"/>
<ConfigItem name="QueuePushWaitLimit" value="200"/>
<ConfigItem name="TransactionLifeTime" value="20000"/>
</ConfigGroup>
<ConfigGroup name="ClusterConfig">
<ConfigItem name="EventsOutStanding" value="10"/>
<ConfigItem name="HeartBeatInterval" value="120000"/>
<ConfigItem name="SeperateLog" value="false"/>
</ConfigGroup>
<ConfigGroup name="EnvironmentConfig">
<ConfigItem name="JavaVendor" value="Sun Microsystems Inc."/>
<ConfigItem name="JavaVersion" value="1.4.1_02"/>
<ConfigItem name="OSArchitecture" value="x86"/>
<ConfigItem name="OSName" value="Windows XP"/>
<ConfigItem name="OSVersion" value="5.1"/>
<ConfigItem name="ServerBuildDate" value="01-Jan-2005"/>
<ConfigItem name="ServerBuildNumber" value="4000"/>
<ConfigItem name="ServerVersion" value="$Name: $ - $Revision: 1.1 $"/>
</ConfigGroup>
<ConfigGroup name="EventStorage">
<ConfigItem name="ActiveDelay" value="1000"/>
<ConfigItem name="CacheAge" value="86400000"/>
<ConfigItem name="IdleDelay" value="60000"/>
<ConfigItem name="ThreadPoolSize" value="1"/>
</ConfigGroup>
<ConfigGroup name="FanoutValues">
<ConfigItem name="ConcurrentUser" value="5"/>
<ConfigItem name="KeepAlive" value="60000"/>
<ConfigItem name="MaxBufferSize" value="1048576"/>
<ConfigItem name="PublishDelay" value="10"/>
<ConfigItem name="PublishExpiredEvents" value="true"/>
<ConfigItem name="QueueHighWaterMark" value="100"/>
<ConfigItem name="QueueLowWaterMark" value="50"/>

```

```

<ConfigItem name="RoundRobinDelivery" value="false"/>
</ConfigGroup>
<ConfigGroup name="GlobalValues">
<ConfigItem name="ConnectionDelay" value="60000"/>
<ConfigItem name="ExtendedMessageSelector" value="false"/>
<ConfigItem name="HandshakeTimeout" value="5000"/>
<ConfigItem name="MaxNoOfConnections" value="-1"/>
<ConfigItem name="NHPScanTime" value="5000"/>
<ConfigItem name="NHPTimeout" value="120000"/>
<ConfigItem name="SchedulerPoolSize" value="10"/>
<ConfigItem name="SecureHandshake" value="true"/>
<ConfigItem name="SendRealmSummaryStats" value="false"/>
<ConfigItem name="ServerTime" value="true"/>
<ConfigItem name="StampDictionary" value="false"/>
<ConfigItem name="StatusBroadcast" value="5000"/>
<ConfigItem name="StatusUpdateTime" value="9223372036854775807"/>
<ConfigItem name="SupportVersion2Clients" value="true"/>
<ConfigItem name="fLoggerLevel" value="1"/>
</ConfigGroup>
<ConfigGroup name="JVMMangement">
<ConfigItem name="EmergencyThreshold" value="94"/>
<ConfigItem name="ExitOnDiskIOError" value="true"/>
<ConfigItem name="ExitOnMemoryError" value="true"/>
<ConfigItem name="MemoryMonitoring" value="100"/>
<ConfigItem name="WarningThreashold" value="85"/>
</ConfigGroup>
<ConfigGroup name="JoinConfig">
<ConfigItem name="ActiveThreadPoolSize" value="2"/>
<ConfigItem name="IdleThreadPoolSize" value="1"/>
<ConfigItem name="MaxEventsPerSchedule" value="50"/>
<ConfigItem name="MaxQueueSizeToUse" value="100"/>
</ConfigGroup>
<ConfigGroup name="RecoveryDaemon">
<ConfigItem name="EventsPerBlock" value="500"/>
<ConfigItem name="ThreadPool" value="4"/>
</ConfigGroup>
<ConfigGroup name="TransactionManager">
<ConfigItem name="MaxEventsPerTransaction" value="0"/>
<ConfigItem name="MaxTransactionTime" value="86400000"/>
<ConfigItem name="TTLThreshold" value="1000"/>
</ConfigGroup>
</RealmConfiguration>
<RealmPermissionSet>
<RealmACLEntry addremoveChannels="false" addremoveJoins="false"
  addremoveRealms="false" changeRealmConfig="false" connectToRealm="true"
  createP2PService="false" fullControl="false" host="*"
  listACLEntries="false" modifyACLEntries="false" name="*"
  overrideConnectionCount="false" useAdminAPI="false"/>
<RealmACLEntry addremoveChannels="true" addremoveJoins="true"
  addremoveRealms="true" changeRealmConfig="true" connectToRealm="true"
  createP2PService="true" fullControl="true" host="192.168.1.2"
  listACLEntries="true" modifyACLEntries="true" name="johnsmith"
  overrideConnectionCount="true" useAdminAPI="true"/>
<RealmACLEntry addremoveChannels="false" addremoveJoins="false"
  addremoveRealms="false" changeRealmConfig="false" connectToRealm="false"
  createP2PService="false" fullControl="true" host="localhost"
  listACLEntries="false" modifyACLEntries="false" name="johnsmith"
  overrideConnectionCount="false" useAdminAPI="false"/>
<RealmACLEntry addremoveChannels="false" addremoveJoins="false"
  addremoveRealms="false" changeRealmConfig="false" connectToRealm="true"

```

```

createP2PService="false" fullControl="false" host="192.168.1.2"
listACLEntries="false" modifyACLEntries="false"
name="realm-productionmaster" overrideConnectionCount="false"
useAdminAPI="false"/>
<RealmACLEntry addremoveChannels="false" addremoveJoins="false"
addremoveRealms="false" changeRealmConfig="false" connectToRealm="true"
createP2PService="false" fullControl="false" host="192.168.1.2"
listACLEntries="false" modifyACLEntries="false"
name="realm-productionslave1" overrideConnectionCount="false"
useAdminAPI="false"/>
<RealmACLEntry addremoveChannels="false" addremoveJoins="false"
addremoveRealms="false" changeRealmConfig="false" connectToRealm="true"
createP2PService="false" fullControl="false" host="192.168.1.2"
listACLEntries="false" modifyACLEntries="false"
name="realm-productionslave2" overrideConnectionCount="false"
useAdminAPI="false"/>
</RealmPermissionSet>
<ClusterSet>
<ClusterEntry name="productioncluster">
<ClusterMember name="productionmaster" rname="nsp://192.168.1.1:9000/">
<ClusterMember name="productionslave1" rname="nsp://192.168.1.2:9000/">
<ClusterMember name="productionslave2" rname="nsp://192.168.1.3:9000/">
</ClusterEntry>
</ClusterSet>
<ChannelSet>
<ChannelEntry>
<ChannelAttributesEntry EID="0" TTL="0" capacity="0" clusterWide="true"
name="/customer/sales" type="MIXED_TYPE"/>
<ChannelPermissionSet>
<ChannelACLEntry fullControl="false" getLastEID="false" host="*"
listACLEntries="false" modifyACLEntries="false" name="*" publish="false"
purgeEvents="false" subscribe="true" useNamedSubscription="false"/>
<ChannelACLEntry fullControl="true" getLastEID="true" host="192.168.1.2"
listACLEntries="true" modifyACLEntries="true" name="johnsmith"
publish="true" purgeEvents="true" subscribe="true"
useNamedSubscription="false"/>
</ChannelPermissionSet>
</ChannelEntry>
<ChannelEntry>
<ChannelAttributesEntry EID="0" TTL="0" capacity="0" clusterWide="true"
name="/naming/defaultContext" type="MIXED_TYPE"/>
<ChannelPermissionSet>
<ChannelACLEntry fullControl="false" getLastEID="true" host="*"
listACLEntries="false" modifyACLEntries="false" name="*" publish="false"
purgeEvents="false" subscribe="true" useNamedSubscription="true"/>
<ChannelACLEntry fullControl="true" getLastEID="true" host="192.168.1.2"
listACLEntries="true" modifyACLEntries="true" name="johnsmith"
publish="true" purgeEvents="true" subscribe="true"
useNamedSubscription="false"/>
</ChannelPermissionSet>
<ChannelKeySet>
<ChannelKeyEntry keyDepth="1" keyName="alias"/>
</ChannelKeySet>
</ChannelEntry>
<ChannelEntry>
<ChannelAttributesEntry EID="0" TTL="0" capacity="0" clusterWide="true"
name="/partner/sales"
type="MIXED_TYPE"/>
<ChannelPermissionSet>
<ChannelACLEntry fullControl="false" getLastEID="true" host="*"

```

```

    listACLEntries="false" modifyACLEntries="false" name="*" publish="false"
    purgeEvents="false" subscribe="true" useNamedSubscription="true"/>
<ChannelACLEntry fullControl="true" getLastEID="true" host="192.168.1.2"
    listACLEntries="true" modifyACLEntries="true" name="johnsmith"
    publish="true" purgeEvents="true" subscribe="true"
    useNamedSubscription="false"/>
</ChannelPermissionSet>
</ChannelEntry>
</ChannelSet>
<QueueSet>
<QueueEntry>
<ChannelAttributesEntry EID="0" TTL="0" capacity="0" clusterWide="true"
    name="/customer/queries" type="MIXED_TYPE"/>
<QueuePermissionSet>
<QueueACLEntry fullControl="false" host="*" listACLEntries="false"
    modifyACLEntries="false" name="*" peek="true" pop="false" purge="false"
    push="false"/>
<QueueACLEntry fullControl="true" host="192.168.1.2" listACLEntries="true"
    modifyACLEntries="true" name="johnsmith" peek="true" pop="true"
    purge="true" push="true"/>
</QueuePermissionSet>
</QueueEntry>
<QueueEntry>
<ChannelAttributesEntry EID="0" TTL="0" capacity="0" clusterWide="true"
    name="/partner/queries" type="MIXED_TYPE"/>
<QueuePermissionSet>
<QueueACLEntry fullControl="false" host="*" listACLEntries="false"
    modifyACLEntries="false" name="*" peek="true" pop="false" purge="false"
    push="false"/>
<QueueACLEntry fullControl="true" host="192.168.1.2" listACLEntries="true"
    modifyACLEntries="true" name="johnsmith" peek="true" pop="true" purge="true"
    push="true"/>
</QueuePermissionSet>
</QueueEntry>
</QueueSet>
<RealmInterfaces>
<RealmNSPInterface>
<RealmInterface acceptThreads="2" adapter="0.0.0.0" advertise="true"
    authtime="10000" autostart="true" backlog="100" name="nsp0" port="9000"/>
<InterfacePermissionSet>
<InterfaceACLEntry host="192.168.1.2" name="johnsmith"/>
</InterfacePermissionSet>
</RealmNSPInterface>
<RealmNHPInterface>
<RealmInterface acceptThreads="2" adapter="0.0.0.0" advertise="true"
    authtime="10000" autostart="true" backlog="100" name="nhp0" port="80"/>
</RealmNHPInterface>
</RealmInterfaces>
</Universal MessagingRealm>

```

## XML Configuration: Sample XML File for IMPORT

```

<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<NirvanaRealm name="realm0" exportDate="2021-01-12+02:00" comment="Realm configuration
    from realm0"
    version="BuildIdentifier" buildInfo="BuildIdentifier">
    <RealmConfiguration>
        <ConfigGroup name="Audit Settings">
            <ConfigItem name="ChannelACL" value="true"/>

```

```

<ConfigItem name="ChannelFailure" value="true"/>
<ConfigItem name="ChannelMaintenance" value="false"/>
<ConfigItem name="ChannelSuccess" value="false"/>
<ConfigItem name="DataGroup" value="false"/>
<ConfigItem name="DataGroupFailure" value="false"/>
<ConfigItem name="DataStream" value="false"/>
<ConfigItem name="Group" value="true"/>
<ConfigItem name="GroupMembers" value="false"/>
<ConfigItem name="InterfaceManagement" value="true"/>
<ConfigItem name="JoinFailure" value="true"/>
<ConfigItem name="JoinMaintenance" value="true"/>
<ConfigItem name="JoinSuccess" value="false"/>
<ConfigItem name="QueueACL" value="true"/>
<ConfigItem name="QueueFailure" value="true"/>
<ConfigItem name="QueueMaintenance" value="false"/>
<ConfigItem name="QueueSuccess" value="false"/>
<ConfigItem name="RealmACL" value="true"/>
<ConfigItem name="RealmFailure" value="true"/>
<ConfigItem name="RealmMaintenance" value="true"/>
<ConfigItem name="RealmSuccess" value="false"/>
<ConfigItem name="SnoopStream" value="false"/>
</ConfigGroup>
<ConfigGroup name="Client Timeout Values">
  <ConfigItem name="EventTimeout" value="60000"/>
  <ConfigItem name="HighWaterMark" value="3000"/>
  <ConfigItem name="LowWaterMark" value="1000"/>
  <ConfigItem name="QueueAccessWaitLimit" value="200"/>
  <ConfigItem name="QueueBlockLimit" value="500"/>
  <ConfigItem name="QueuePushWaitLimit" value="200"/>
  <ConfigItem name="TransactionLifeTime" value="20000"/>
</ConfigGroup>
<ConfigGroup name="Cluster Config">
  <ConfigItem name="BufferSize" value="8192"/>
  <ConfigItem name="ClientQueueSize" value="1000"/>
  <ConfigItem name="ClientQueueWindow" value="10"/>
  <ConfigItem name="ClientStateDelay" value="5000"/>
  <ConfigItem name="DisableHTTPConnections" value="true"/>
  <ConfigItem name="DisconnectWait" value="30000"/>
  <ConfigItem name="DisconnectWhenNotReady" value="false"/>
  <ConfigItem name="EnableMulticast" value="true"/>
  <ConfigItem name="EnableSites" value="true"/>
  <ConfigItem name="EnableStoreRecoveryRetry" value="true"/>
  <ConfigItem name="EnginePipelineSize" value="2"/>
  <ConfigItem name="FilterEventsDuringRecovery" value="true"/>
  <ConfigItem name="FormationTimeout" value="300000"/>
  <ConfigItem name="HeartBeatInterval" value="120000"/>
  <ConfigItem name="InitialConnectionTimeout" value="30000"/>
  <ConfigItem name="IsCommittedDelay" value="5000"/>
  <ConfigItem name="MasterRequestTimeout" value="60000"/>
  <ConfigItem name="MasterVoteDelay" value="10000"/>
  <ConfigItem name="MasterWaitTimeout" value="60000"/>
  <ConfigItem name="PublishQueueEnabled" value="true"/>
  <ConfigItem name="QueueConsistencyCheck" value="false"/>
  <ConfigItem name="QueueSize" value="1000"/>
  <ConfigItem name="SecureHandshake" value="true"/>
  <ConfigItem name="SeperateLog" value="false"/>
  <ConfigItem name="StateChangeScan" value="60000"/>
  <ConfigItem name="SyncPingSize" value="1000"/>
  <ConfigItem name="TransactionSync" value="true"/>
</ConfigGroup>

```

```

<ConfigGroup name="Comet Config">
  <ConfigItem name="BufferSize" value="5120"/>
  <ConfigItem name="EnableLogging" value="false"/>
  <ConfigItem name="Timeout" value="60000"/>
</ConfigGroup>
<ConfigGroup name="Connection Config">
  <ConfigItem name="AllowBufferReuse" value="true"/>
  <ConfigItem name="BufferManagerCount" value="16"/>
  <ConfigItem name="BufferPoolSize" value="100"/>
  <ConfigItem name="BufferQueueSize" value="100"/>
  <ConfigItem name="BufferSize" value="10240"/>
  <ConfigItem name="CometReadTimeout" value="20000"/>
  <ConfigItem name="ConnectionDelay" value="60000"/>
  <ConfigItem name="EnablePriorityMessaging" value="false"/>
  <ConfigItem name="HandshakeTimeout" value="5000"/>
  <ConfigItem name="IdleDriverTimeout" value="300000"/>
  <ConfigItem name="IdleSessionTimeout" value="300000"/>
  <ConfigItem name="KeepAlive" value="60000"/>
  <ConfigItem name="MaxBufferSize" value="1048576"/>
  <ConfigItem name="MaxBufferSizeClientSideCheck" value="true"/>
  <ConfigItem name="MaxNoOfConnections" value="-1"/>
  <ConfigItem name="MaxWriteCount" value="30"/>
  <ConfigItem name="NIOSelectArray" value="false"/>
  <ConfigItem name="NetworkMonitorThreads" value="4"/>
  <ConfigItem name="PriorityQueueCount" value="10"/>
  <ConfigItem name="PriorityReadSpinLockMaxConnections" value="2"/>
  <ConfigItem name="PriorityReadSpinLockTime" value="500"/>
  <ConfigItem name="PriorityReadType" value="1"/>
  <ConfigItem name="QueueHighWaterMark" value="3000"/>
  <ConfigItem name="QueueLowWaterMark" value="1000"/>
  <ConfigItem name="ReadCount" value="10"/>
  <ConfigItem name="UseDirectBuffering" value="true"/>
  <ConfigItem name="WriteHandlerType" value="3"/>
  <ConfigItem name="whEventThresholdCount" value="350"/>
  <ConfigItem name="whEventThresholdTime" value="500"/>
  <ConfigItem name="whMaxEventsBeforeFlush" value="100"/>
  <ConfigItem name="whMaxEventsPerSecond" value="100000"/>
  <ConfigItem name="whMaxTimeBetweenFlush" value="2"/>
  <ConfigItem name="whPeakTrailDelay" value="1000"/>
</ConfigGroup>
<ConfigGroup name="Data Stream Config">
  <ConfigItem name="FanoutTaskQueueSize" value="32"/>
  <ConfigItem name="FanoutTraversalType" value="0"/>
  <ConfigItem name="MaxSessionIdSize" value="14"/>
  <ConfigItem name="MonitorTimer" value="10000"/>
  <ConfigItem name="OffloadMulticastWrite" value="false"/>
  <ConfigItem name="ParallelFanoutThreshold" value="50"/>
  <ConfigItem name="SendInitialMapping" value="true"/>
</ConfigGroup>
<ConfigGroup name="DurableConfig">
  <ConfigItem name="DurableNameFiltering" value="false"/>
  <ConfigItem name="QueuedExtendedException" value="false"/>
</ConfigGroup>
<ConfigGroup name="Environment Config">
  <ConfigItem name="AvailableProcessors" value="4"/>
  <ConfigItem name="Embedded" value="false"/>
  <ConfigItem name="InterRealmProtocolVersion" value="1"/>
  <ConfigItem name="JavaVendor" value="Oracle Corporation"/>
  <ConfigItem name="JavaVersion" value="1.8.0_271"/>
  <ConfigItem name="NanosecondSupport" value="true"/>

```

```

    <ConfigItem name="OSArchitecture" value="amd64"/>
    <ConfigItem name="OSName" value="Windows 10"/>
    <ConfigItem name="OSVersion" value="10.0"/>
    <ConfigItem name="ProcessId" value="43948"/>
    <ConfigItem name="ServerBuildDate" value="12-Feb-1964"/>
    <ConfigItem name="ServerBuildNumber" value="BuildNumberHere"/>
    <ConfigItem name="ServerReleaseDetails" value="BuildIdentifier"/>
    <ConfigItem name="ServerVersion" value="RealmServerVersion"/>
    <ConfigItem name="TimerAdjustment" value="0"/>
  </ConfigGroup>
  <ConfigGroup name="Event Storage">
    <ConfigItem name="ActiveDelay" value="1000"/>
    <ConfigItem name="AutoDeleteScan" value="5000"/>
    <ConfigItem name="AutoMaintainOnFileLimit" value="false"/>
    <ConfigItem name="AutoMaintainSystemStores" value="true"/>
    <ConfigItem name="AutoMaintenanceThreshold" value="50"/>
    <ConfigItem name="CacheAge" value="60000"/>
    <ConfigItem name="EnableBufferingKey" value="true"/>
    <ConfigItem name="EnableStoreCaching" value="true"/>
    <ConfigItem name="EnableStoreReadBuffering" value="true"/>
    <ConfigItem name="IdleDelay" value="30000"/>
    <ConfigItem name="JMSEngineAutoPurgeTime" value="5000"/>
    <ConfigItem name="JMSEngineIndividualPurgeEnabled" value="false"/>
    <ConfigItem name="MaintenanceFileSizeThreshold" value="1073741824"/>
    <ConfigItem name="MaintenanceMemoryThreshold" value="104857600"/>
    <ConfigItem name="PageSize" value="5000"/>
    <ConfigItem name="QueueDeliveryPersistencePolicy" value="1"/>
    <ConfigItem name="StoreReadBufferSize" value="16384"/>
    <ConfigItem name="SyncBatchSize" value="50"/>
    <ConfigItem name="SyncServerFiles" value="false"/>
    <ConfigItem name="SyncTimeLimit" value="20"/>
    <ConfigItem name="ThreadPoolSize" value="4"/>
  </ConfigGroup>
  <ConfigGroup name="Fanout Values">
    <ConfigItem name="ConnectionGrouping" value="true"/>
    <ConfigItem name="DelayPublishOnCapacity" value="false"/>
    <ConfigItem name="HonourSharedDurableCapacity" value="true"/>
    <ConfigItem name="IteratorWindowSize" value="100"/>
    <ConfigItem name="JMSQueueMaxMultiplier" value="10"/>
    <ConfigItem name="MaximumDelayInWrite" value="1"/>
    <ConfigItem name="ParallelBatchSize" value="50"/>
    <ConfigItem name="ParallelThreadPoolSize" value="2"/>
    <ConfigItem name="ParallelThreshold" value="1"/>
    <ConfigItem name="ParallelUseGlobalPool" value="true"/>
    <ConfigItem name="PeakPublishDelay" value="1"/>
    <ConfigItem name="PublishDelay" value="1"/>
    <ConfigItem name="PublishExpiredEvents" value="true"/>
    <ConfigItem name="RoundRobinDelivery" value="false"/>
    <ConfigItem name="SendEndOfChannelAlways" value="false"/>
    <ConfigItem name="SendPubEventsImmediately" value="true"/>
    <ConfigItem name="SyncQueueDelay" value="1000"/>
    <ConfigItem name="SyncQueuePublisher" value="true"/>
  </ConfigGroup>
  <ConfigGroup name="Global Values">
    <ConfigItem name="AllowRealmAdminFullAccess" value="false"/>
    <ConfigItem name="CacheJoinInfoKeys" value="true"/>
    <ConfigItem name="DisableExplicitGC" value="true"/>
    <ConfigItem name="EnableCaching" value="true"/>
    <ConfigItem name="EnableDNSLookups" value="true"/>
    <ConfigItem name="EnableWeakReferenceCleanup" value="true"/>
  </ConfigGroup>

```

```

    <ConfigItem name="ExtendedMessageSelector" value="true"/>
    <ConfigItem name="HTTPCookieSize" value="14"/>
    <ConfigItem name="NHPScanTime" value="5000"/>
    <ConfigItem name="NHPTimeout" value="120000"/>
    <ConfigItem name="NanoDelayBase" value="1000000"/>
    <ConfigItem name="OverrideEveryoneUser" value="false"/>
    <ConfigItem name="PauseServerPublishing" value="false"/>
    <ConfigItem name="SendRealmSummaryStats" value="false"/>
    <ConfigItem name="ServerStateFlush" value="500"/>
    <ConfigItem name="ServerTime" value="true"/>
    <ConfigItem name="StampDictionary" value="true"/>
    <ConfigItem name="StampHost" value="true"/>
    <ConfigItem name="StampTime" value="true"/>
    <ConfigItem name="StampTimeUseHPT" value="false"/>
    <ConfigItem name="StampTimeUseHPTScale" value="0"/>
    <ConfigItem name="StampUser" value="true"/>
    <ConfigItem name="StatusBroadcast" value="5000"/>
    <ConfigItem name="StatusUpdateTime" value="9223372036854775807"/>
  </ConfigGroup>
  <ConfigGroup name="Inter-Realm Comms Config">
    <ConfigItem name="EstablishmentTime" value="30000"/>
    <ConfigItem name="KeepAliveInterval" value="10000"/>
    <ConfigItem name="KeepAliveResetTime" value="35000"/>
    <ConfigItem name="MaximumReconnectTime" value="20000"/>
    <ConfigItem name="MinimumReconnectTime" value="1000"/>
    <ConfigItem name="Timeout" value="120000"/>
    <ConfigItem name="WriteDelayOnFail" value="false"/>
    <ConfigItem name="WriteDelayTimeout" value="30000"/>
    <ConfigItem name="ZoneDefaultCanRecv" value="true"/>
    <ConfigItem name="ZoneDefaultCanSend" value="true"/>
  </ConfigGroup>
  <ConfigGroup name="JVM Management">
    <ConfigItem name="AutoThreadDumpOnExit" value="true"/>
    <ConfigItem name="EmergencyThreshold" value="94"/>
    <ConfigItem name="EnableJMX" value="false"/>
    <ConfigItem name="ExitOnDiskIOError" value="true"/>
    <ConfigItem name="ExitOnInterfaceFailure" value="false"/>
    <ConfigItem name="ExitOnMemoryError" value="true"/>
    <ConfigItem name="IORetryCount" value="10"/>
    <ConfigItem name="IOSleepTime" value="500"/>
    <ConfigItem name="JMXRMIServerURLString"
value="service:jmx:rmi:///jndi/rmi://localhost:9997/server"/>
    <ConfigItem name="MemoryMonitoring" value="2000"/>
    <ConfigItem name="ThrottleAllPublishersAtThreshold" value="false"/>
    <ConfigItem name="WarningThreshold" value="85"/>
  </ConfigGroup>
  <ConfigGroup name="Join Config">
    <ConfigItem name="ActiveThreadPoolSize" value="2"/>
    <ConfigItem name="IdleThreadPoolSize" value="0"/>
    <ConfigItem name="MaxEventsPerSchedule" value="1000"/>
    <ConfigItem name="MaxQueueSizeToUse" value="0"/>
    <ConfigItem name="RemoteJoinAckBatchSize" value="100"/>
    <ConfigItem name="RemoteJoinAckInterval" value="1000"/>
    <ConfigItem name="UseQueuedLocalJoinHandler" value="false"/>
  </ConfigGroup>
  <ConfigGroup name="Logging Config">
    <ConfigItem name="DefaultLogSize" value="100000000"/>
    <ConfigItem name="DiagnosticsEnabledStores" value="!"/>
    <ConfigItem name="DisplayCurrentThread" value="false"/>
    <ConfigItem name="DisplayPackageName" value="false"/>
  </ConfigGroup>

```

```

    <ConfigItem name="EmbedTag" value="false"/>
    <ConfigItem name="EnableLog4J" value="false"/>
    <ConfigItem name="EnableStatusLog" value="true"/>
    <ConfigItem name="LogManager" value="1"/>
    <ConfigItem name="RolledLogFileDepth" value="10"/>
    <ConfigItem name="customDebugTag" value="DEBUG"/>
    <ConfigItem name="customErrorTag" value="ERROR"/>
    <ConfigItem name="customFatalTag" value="FATAL"/>
    <ConfigItem name="customInfoTag" value="INFO"/>
    <ConfigItem name="customLogTag" value="LOG"/>
    <ConfigItem name="customTraceTag" value="TRACE"/>
    <ConfigItem name="customWarnTag" value="WARN"/>
    <ConfigItem name="fLoggerLevel" value="0"/>
  </ConfigGroup>
  <ConfigGroup name="Metric Config">
    <ConfigItem name="EnableEventMemoryMonitoring" value="true"/>
    <ConfigItem name="EnableMetrics" value="true"/>
  </ConfigGroup>
  <ConfigGroup name="Plugin Config">
    <ConfigItem name="EnableAccessLog" value="true"/>
    <ConfigItem name="EnableErrorLog" value="true"/>
    <ConfigItem name="EnablePluginLog" value="true"/>
    <ConfigItem name="MaxNumberOfPluginThreads" value="200"/>
    <ConfigItem name="PluginTimeout" value="30000"/>
  </ConfigGroup>
  <ConfigGroup name="Protobuf Config">
    <ConfigItem name="CacheEventFilter" value="true"/>
    <ConfigItem name="FilterProtobufEvents" value="true"/>
    <ConfigItem name="MaximumProtobufBuilders" value="4"/>
    <ConfigItem name="MinimumProtobufBuilders" value="2"/>
    <ConfigItem name="ProtobufDescriptorsInputDir"
value="realmDirectories\realm0/plugins/ProtobufDescriptors"/>
    <ConfigItem name="ProtobufDescriptorsOutputDir"
value="realmDirectories\realm0/plugins/htdocs"/>
    <ConfigItem name="UpdateDescriptorsInterval" value="60000"/>
    <ConfigItem name="useChannelLevelProtobufCache" value="true"/>
  </ConfigGroup>
  <ConfigGroup name="Protocol AMQP Config">
    <ConfigItem name="AllowUserTransformation" value="false"/>
    <ConfigItem name="AnonymousUser" value="anonymous_amqp"/>
    <ConfigItem name="BufferSize" value="10240"/>
    <ConfigItem name="DefaultNodeMode" value="0"/>
    <ConfigItem name="Enable" value="true"/>
    <ConfigItem name="EnableWriteThread" value="false"/>
    <ConfigItem name="EngineLoopCount" value="50"/>
    <ConfigItem name="MaxFrameSize" value="10000000"/>
    <ConfigItem name="MaxThreadPoolSize" value="10"/>
    <ConfigItem name="MinThreadPoolSize" value="1"/>
    <ConfigItem name="QueuePrefix" value="queue://"/>
    <ConfigItem name="SASL_Anonymous" value="true"/>
    <ConfigItem name="SASL_CRAM-MD5" value="false"/>
    <ConfigItem name="SASL_DIGEST-MD5" value="false"/>
    <ConfigItem name="SASL_Plain" value="false"/>
    <ConfigItem name="SubscriberCredit" value="1000"/>
    <ConfigItem name="Timeout" value="60000"/>
    <ConfigItem name="TopicPrefix" value="topic://"/>
    <ConfigItem name="TransformToUse" value="2"/>
  </ConfigGroup>
  <ConfigGroup name="Protocol MQTT Config">
    <ConfigItem name="DisconnectClientsOnPublishFailure" value="true"/>

```

```

    <ConfigItem name="DisconnectOnSecurityException" value="true"/>
    <ConfigItem name="Enable" value="true"/>
    <ConfigItem name="EnableAutoCreateTopics" value="true"/>
    <ConfigItem name="EnforceAlphaNumericClientID" value="false"/>
    <ConfigItem name="IgnoreClientIDLength" value="true"/>
    <ConfigItem name="MaxOutstanding" value="64000"/>
    <ConfigItem name="QoS0AsTransient" value="false"/>
    <ConfigItem name="SessionStateTTL" value="259200000"/>
    <ConfigItem name="Strict" value="true"/>
    <ConfigItem name="SupportZeroLength" value="true"/>
    <ConfigItem name="Timeout" value="5000"/>
  </ConfigGroup>
  <ConfigGroup name="Proxy Forward Config">
    <ConfigItem name="BufferSize" value="10240"/>
    <ConfigItem name="FlushTimeout" value="120000"/>
  </ConfigGroup>
  <ConfigGroup name="RecoveryDaemon">
    <ConfigItem name="EventsPerBlock" value="500"/>
    <ConfigItem name="ThreadPool" value="4"/>
  </ConfigGroup>
  <ConfigGroup name="Server Protection">
    <ConfigItem name="EnableFlowControl" value="false"/>
    <ConfigItem name="FlowControlWaitTimeOne" value="16000"/>
    <ConfigItem name="FlowControlWaitTimeThree" value="10000"/>
    <ConfigItem name="FlowControlWaitTimeTwo" value="13332"/>
  </ConfigGroup>
  <ConfigGroup name="Thread Pool Config">
    <ConfigItem name="CommonPoolThreadSize" value="5"/>
    <ConfigItem name="ConnectionThreadPoolMaxSize" value="10"/>
    <ConfigItem name="ConnectionThreadPoolMinSize" value="1"/>
    <ConfigItem name="ConnectionThreadWaitTime" value="120000"/>
    <ConfigItem name="EnableConnectionThreadPooling" value="true"/>
    <ConfigItem name="MaxUnauthorisedCount" value="1000"/>
    <ConfigItem name="PendingTaskWarningThreshold" value="1000"/>
    <ConfigItem name="ReadThreadPoolMaxSize" value="100"/>
    <ConfigItem name="ReadThreadPoolMinSize" value="4"/>
    <ConfigItem name="SchedulerPoolSize" value="10"/>
    <ConfigItem name="SlowTaskWarningTime" value="5000"/>
    <ConfigItem name="StalledTasksWarningTime" value="60000"/>
    <ConfigItem name="ThreadDumpInterval" value="60000"/>
    <ConfigItem name="ThreadDumpOnSlowTask" value="false"/>
    <ConfigItem name="ThreadIdleQueueSize" value="10"/>
    <ConfigItem name="WriteThreadPoolMaxSize" value="1000"/>
    <ConfigItem name="WriteThreadPoolMinSize" value="5"/>
  </ConfigGroup>
  <ConfigGroup name="TransactionManager">
    <ConfigItem name="MaxEventsPerTransaction" value="0"/>
    <ConfigItem name="MaxTransactionTime" value="300000"/>
    <ConfigItem name="TTLThreshold" value="1000"/>
  </ConfigGroup>
</RealmConfiguration>
<ClusterSet>
  <ClusterEntry name="cluster_1">
    <ClusterMember name="realm0" rname="nsp://localhost:11000"
canBeMaster="true"/>
    <ClusterMember name="realm1" rname="nsp://localhost:11010"
canBeMaster="true"/>
    <ClusterMember name="realm2" rname="nsp://localhost:11020"
canBeMaster="true"/>
  </ClusterEntry>

```

```

</ClusterSet>
<RealmSet>
  <RealmEntry name="realm1" rname="nhp://10.248.27.186:11010"/>
  <RealmEntry name="realm2" rname="nhp://10.248.27.186:11020"/>
</RealmSet>
<ChannelSet>
  <ChannelEntry>
    <ChannelAttributesEntry name="/customer/sales/JMSTopic" TTL="0" capacity="0"
EID="0"
clusterWide="true" jmsEngine="true" mergeEngine="false" type="MIXED_TYPE"/>
    <StorePropertiesEntry HonorCapacityWhenFull="true" SyncOnEachWrite="false"

SyncMaxBatchSize="0" SyncBatchTime="0" PerformAutomaticMaintenance="true"
EnableCaching="true"
CacheOnReload="true" EnableReadBuffering="true" ReadBufferSize="10240" Priority="4"
EnableMulticast="false" MultiFileEventsPerSpindle="50000" StampDictionary="0"/>
    <ChannelPermissionSet>
      <ChannelACLEntry listACLEntries="false" modifyACLEntries="false"
fullControl="false"
getLastEID="true" purgeEvents="false" subscribe="true" publish="true"
useNamedSubscription="false"
host="*" name="user"/>
      <ChannelACLEntry listACLEntries="true" modifyACLEntries="true"
fullControl="true"
getLastEID="true" purgeEvents="true" subscribe="true" publish="true"
useNamedSubscription="true"
host="192.168.1.2" name="user"/>
      <ChannelGroupACLEntry listACLEntries="false" modifyACLEntries="false"

fullControl="false" getLastEID="true" purgeEvents="false" subscribe="true"
publish="false"
useNamedSubscription="true" groupname="Everyone"/>
    </ChannelPermissionSet>
  </ChannelEntry>
  <ChannelEntry>
    <ChannelAttributesEntry name="/naming/defaultContext" TTL="0" capacity="0"
EID="2"
clusterWide="true" jmsEngine="false" mergeEngine="false" type="MIXED_TYPE"/>
    <StorePropertiesEntry HonorCapacityWhenFull="true" SyncOnEachWrite="false"

SyncMaxBatchSize="0" SyncBatchTime="0" PerformAutomaticMaintenance="true"
EnableCaching="true"
CacheOnReload="true" EnableReadBuffering="true" ReadBufferSize="10240" Priority="4"
EnableMulticast="false" MultiFileEventsPerSpindle="50000" StampDictionary="0"/>
    <ChannelPermissionSet>
      <ChannelACLEntry listACLEntries="true" modifyACLEntries="true"
fullControl="true"
getLastEID="true" purgeEvents="true" subscribe="true" publish="true"
useNamedSubscription="true"
host="10.248.27.186" name="rgav"/>
      <ChannelGroupACLEntry listACLEntries="true" modifyACLEntries="true"
fullControl="true" getLastEID="true" purgeEvents="true" subscribe="true" publish="true"

useNamedSubscription="true" groupname="Everyone"/>
    </ChannelPermissionSet>
    <ChannelKeySet>
      <ChannelKeyEntry keyName="alias" keyDepth="1"/>
    </ChannelKeySet>
  </ChannelEntry>
  <EventsSet>
    <Event id="0">

```

```

        <EventAttribSet>
          <EventAttrib name="nrtpub.time" type="Long"
value="1610454161489"/>
          <EventAttrib name="nrtpub.host" type="String"
value="10.248.27.186"/>
          <EventAttrib name="nrtpub.name" type="String" value="rgav"/>
          <EventAttrib name="JMSDeliveryMode" type="String"
value="PERSISTENT"/>
          <EventAttrib name="JMSPriority" type="Byte" value="4"/>
        </EventAttribSet>
        <EventPropSet>
          <EventProp name="JMS_my-channels_EnableMultiplexedConnections"
type="Boolean" value="true"/>
          <EventProp name="JMS_my-channels_RandomRNames" type="Boolean"
value="false"/>
          <EventProp name="JMS_my-channels_RetryCommit" type="Boolean"
value="false"/>
          <EventProp name="JMS_my-channels_ConxExceptionOnRetryFailure"
type="Boolean"
value="false"/>
          <EventProp name="JMS_my-channels_MaxReconnectAttempts"
type="Integer"
value="-1"/>
          <EventProp name="JMS_my-channels_EnableSharedDurable"
type="Boolean"
value="true"/>
          <EventProp name="JMS_my-channels_EnableSerialDurable"
type="Boolean"
value="false"/>
          <EventProp name="JMS_my-channels_EnableSingleSharedDurableAck"
type="Boolean" value="false"/>
          <EventProp name="JMS_my-channels_EnableSingleQueueAck"
type="Boolean"
value="false"/>
          <EventProp name="JMS_my-channels_SyncWritesToDisc"
type="Boolean"
value="false"/>
          <EventProp name="JMS_my-channels_SyncSendPersistent"
type="Boolean"
value="true"/>
          <EventProp name="JMS_my-channels_InitialConnectionRetryCount"
type="Integer"
value="2"/>
          <EventProp name="JMS_my-channels_SyncBatchSize" type="Integer"
value="50"/>
          <EventProp name="JMS_my-channels_SyncTime" type="Integer"
value="20"/>
          <EventProp name="JMS_my-channels_GlobalStoreCapacity"
type="Integer"
value="0"/>
          <EventProp name="JMS_my-channels_AutoAckCount" type="Integer"
value="50"/>
          <EventProp name="JMS_my-channels_WindowSize" type="Integer"
value="100"/>
          <EventProp name="JMS_my-channels_useInfiniteWindowSize"
type="Boolean"

```

```

value="false"/>
value="100"/>
value="100"/>
value="30"/>
type="Boolean"
value="false"/>
type="Boolean"
value="true"/>
value="2000"/>
value="true"/>
type="Boolean"
value="true"/>
value="10000"/>
type="Integer"
value="2"/>
type="Boolean"
value="true"/>
value="1310720"/>
value="3"/>
value="true"/>
value="true"/>
type="Boolean"
value="true"/>
value="false"/>
value="ExampleConnectionFactory"/>
value="javax.jms.ConnectionFactory"/>
value="com.pcbsys.nirvana.nJMS.ConnectionFactoryFactory"/>
value="{&quot;JMS_my-channels_EnableMultiplexedConnections&quot;:[3,true],&quot;
JMS_my-channels_RandomRNames&quot;:[3,false],&quot;JMS_my-channels_RetryCommit&quot;
:[3,false],&quot;JMS_my-channels_ConxExceptionOnRetryFailure&quot;:[3,false],&quot;
JMS_my-channels_MaxReconnectAttempts&quot;:[4,-1],&quot;JMS_my-channels_EnableSharedDurable&quot;
:[3,true],&quot;JMS_my-channels_EnableSerialDurable&quot;:[3,false],&quot;
JMS_my-channels_EnableSingleSharedDurableAck&quot;:[3,false],&quot;
JMS_my-channels_EnableSingleQueueAck&quot;:[3,false],&quot;JMS_my-channels_SyncWritesToDisc&quot;
:[3,false],&quot;JMS_my-channels_SyncSendPersistent&quot;:[3,true],&quot;
JMS_my-channels_InitialConnectionRetryCount&quot;:[4,2],&quot;

```

```

JMS_my-channels_SyncBatchSize":[4,50],&quot;;
JMS_my-channels_SyncTime":[4,20],&quot;;JMS_my-channels_GlobalStoreCapacity"
:[4,0],&quot;;JMS_my-channels_AutoAckCount":[4,50],&quot;;JMS_my-channels_WindowSize"
:[4,100],&quot;;JMS_my-channels_useInfiniteWindowSize":[3,false],&quot;;
JMS_my-channels_UnAckedSize":[4,100],&quot;;JMS_my-channels_RedliveredSize":[4,100],&quot;;
JMS_my-channels_ThreadPoolSize":[4,30],&quot;;JMS_my-channels_AutoReconnectAfterACL"
:[3,false],&quot;;JMS_my-channels_ImmediateReconnect":[3,true],&quot;;
JMS_my-channels_ReconnectInterval":[1,2000],&quot;;JMS_my-channels_UseJMSEngine"
:[3,true],&quot;;JMS_my-channels_DisconnectAfterClusterFailure":[3,true],&quot;;
JMS_my-channels_ConnectionTimeout":[1,10000],&quot;;JMS_my-channels_PermittedKeepAlivesMissed"
:[4,2],&quot;;JMS_my-channels_SyncNamedTopicAcks":[3,true],&quot;;JMS_my-channels_AdapterBuffer"
:[4,1310720],&quot;;JMS_my-channels_WriteHandler":[4,3],&quot;;JMS_my-channels_SyncQueueAcks"
:[3,true],&quot;;JMS_my-channels_SyncTopicAcks":[3,true],&quot;;JMS_my-channels_AutoCreateResource"
:[3,true],&quot;;JMS_my-channels_FollowMaster":[3,false]}"/>
    <EventProp name="alias.stringRefAddr.type" type="String"
value="ConnectionFactory"/>
    <EventProp name="alias.stringRefAddr.addr" type="String"
value="nsp://localhost:11000,nsp://localhost:11010,nsp://localhost:11020"/>
    </EventPropSet>
    <EventData>RXhbbXBsZUNvbm5lY3Rpb25GYWN0b3J5</EventData>
  </Event>
  <Event id="1">
    <EventAttribSet>
      <EventAttrib name="nrtpub.time" type="Long"
value="1610454171673"/>
      <EventAttrib name="nrtpub.host" type="String"
value="10.248.27.186"/>
      <EventAttrib name="nrtpub.name" type="String" value="rgav"/>
      <EventAttrib name="JMSDeliveryMode" type="String"
value="PERSISTENT"/>
      <EventAttrib name="JMSPriority" type="Byte" value="4"/>
    </EventAttribSet>
    <EventPropSet>
      <EventProp name="alias.type" type="Integer" value="1"/>
      <EventProp name="alias" type="String"
value="/customer/sales/JMSTopic"/>
      <EventProp name="alias.reference.classname" type="String"
value="javax.jms.Topic"/>
      <EventProp name="alias.reference.factoryclass" type="String"
value="com.pcbSYS.nirvana.nJMS.TopicFactory"/>
      <EventProp name="alias.reference.url" type="String" value=""/>
      <EventProp name="alias.stringRefAddr.type" type="String"
value="Topic"/>
      <EventProp name="alias.stringRefAddr.addr" type="String"
value="/customer/sales/JMSTopic"/>
    </EventPropSet>
    <EventData>L2N1c3RvbWVyL3NhbgVzL0pNU1RvcGlj</EventData>
  </Event>
  <Event id="2">
    <EventAttribSet>
      <EventAttrib name="nrtpub.time" type="Long"
value="1610454193768"/>
      <EventAttrib name="nrtpub.host" type="String"
value="10.248.27.186"/>
      <EventAttrib name="nrtpub.name" type="String" value="rgav"/>
      <EventAttrib name="JMSDeliveryMode" type="String"
value="PERSISTENT"/>
      <EventAttrib name="JMSPriority" type="Byte" value="4"/>
    </EventAttribSet>

```

```

        <EventPropSet>
            <EventProp name="alias.type" type="Integer" value="1"/>
            <EventProp name="alias" type="String"
value="/customer/sales/JMSQueue"/>
            <EventProp name="alias.reference.classname" type="String"
value="javax.jms.Queue"/>
            <EventProp name="alias.reference.factoryclass" type="String"
value="com.pcbsys.nirvana.nJMS.QueueFactory"/>
            <EventProp name="alias.reference.url" type="String" value=""/>
            <EventProp name="alias.stringRefAddr.type" type="String"
value="Queue"/>
            <EventProp name="alias.stringRefAddr.addr" type="String"
value="/customer/sales/JMSQueue"/>
        </EventPropSet>
        <EventData>L2N1c3RvbWVyL3NhbGVzL0pNU1F1ZXVl</EventData>
    </Event>
</EventsSet>
</ChannelEntry>
<ChannelEntry>
    <ChannelAttributesEntry name="/partner/sales" TTL="0" capacity="0" EID="0"
clusterWide="true" jmsEngine="false" mergeEngine="false" type="MIXED_TYPE"/>
    <StorePropertiesEntry HonorCapacityWhenFull="true" SyncOnEachWrite="false"
SyncMaxBatchSize="0" SyncBatchTime="0" PerformAutomaticMaintenance="true"
EnableCaching="true"
CacheOnReload="true" EnableReadBuffering="true" ReadBufferSize="10240" Priority="4"
EnableMulticast="false" MultiFileEventsPerSpindle="50000" StampDictionary="0"/>
    <ChannelPermissionSet>
        <ChannelACLEntry listACLEntries="false" modifyACLEntries="false"
fullControl="false" getLastEID="true" purgeEvents="false" subscribe="true"
publish="true"
useNamedSubscription="false" host="*" name="user"/>
        <ChannelACLEntry listACLEntries="true" modifyACLEntries="true"
fullControl="true"
getLastEID="true" purgeEvents="true" subscribe="true" publish="true"
useNamedSubscription="true"
host="192.168.1.2" name="user"/>
        <ChannelGroupACLEntry listACLEntries="false" modifyACLEntries="false"
fullControl="false" getLastEID="true" purgeEvents="false" subscribe="true"
publish="false"
useNamedSubscription="true" groupname="Everyone"/>
    </ChannelPermissionSet>
    <DurableSet>
        <durableEntry name="serial_durable" EID="-1" outstandingEvents="0"
clusterWide="true" persistent="true" shared="false" serial="true"/>
        <durableEntry name="shared_durable" EID="-1" outstandingEvents="0"
clusterWide="true" persistent="true" shared="true" serial="false"/>
    </DurableSet>
</ChannelEntry>
</ChannelSet>
<QueueSet>
    <QueueEntry>
        <ChannelAttributesEntry name="/customer/sales/JMSQueue" TTL="0" capacity="0"
EID="0"
clusterWide="true" jmsEngine="false" mergeEngine="false" type="MIXED_TYPE"/>
        <StorePropertiesEntry HonorCapacityWhenFull="true" SyncOnEachWrite="false"

```

```

SyncMaxBatchSize="0" SyncBatchTime="0" PerformAutomaticMaintenance="true"
EnableCaching="true"
CacheOnReload="true" EnableReadBuffering="true" ReadBufferSize="10240" Priority="4"
EnableMulticast="false" MultiFileEventsPerSpindle="50000" StampDictionary="0"/>
  <QueuePermissionSet>
    <QueueACLEntry listACLEntries="false" modifyACLEntries="false"
fullControl="false"
purge="false" peek="true" push="true" pop="true" host="*" name="user"/>
    <QueueACLEntry listACLEntries="true" modifyACLEntries="true"
fullControl="true"
purge="true" peek="true" push="true" pop="true" host="192.168.1.2" name="user"/>
    <QueueGroupACLEntry listACLEntries="false" modifyACLEntries="false"
fullControl="false" purge="false" peek="true" push="false" pop="false"
groupname="Everyone"/>
  </QueuePermissionSet>
</QueueEntry>
<QueueEntry>
  <ChannelAttributesEntry name="/partner/queries" TTL="0" capacity="0"
EID="0"
clusterWide="true" jmsEngine="false" mergeEngine="false" type="MIXED_TYPE"/>
  <StorePropertiesEntry HonorCapacityWhenFull="true" SyncOnEachWrite="false"

SyncMaxBatchSize="0" SyncBatchTime="0" PerformAutomaticMaintenance="true"
EnableCaching="true"
CacheOnReload="true" EnableReadBuffering="true" ReadBufferSize="10240" Priority="4"
EnableMulticast="false" MultiFileEventsPerSpindle="50000" StampDictionary="0"/>
  <QueuePermissionSet>
    <QueueACLEntry listACLEntries="false" modifyACLEntries="false"
fullControl="false"
purge="false" peek="true" push="true" pop="true" host="*" name="user"/>
    <QueueACLEntry listACLEntries="true" modifyACLEntries="true"
fullControl="true"
purge="true" peek="true" push="true" pop="true" host="192.168.1.2" name="user"/>
    <QueueGroupACLEntry listACLEntries="false" modifyACLEntries="false"
fullControl="false" purge="false" peek="true" push="false" pop="false"
groupname="Everyone"/>
  </QueuePermissionSet>
</QueueEntry>
</QueueSet>
<DataGroupSet/>
<RealmInterfaces>
  <RealmNHPInterface>
    <RealmInterface name="nhp0" port="11000" adapter="0.0.0.0" autostart="true"
advertise="true" authtime="10000" backlog="100" acceptThreads="10" selectThreads="2"

sendbuffersize="1310720" receivebuffersize="1310720" allowforinterrealm="true"
allowclientconnections="true" EnableNIO="true"/>
  <RealmInterfacePlugin mountPoint="/" name="File Plugin">
    <NirvanaFilePlugin>
      <PluginConfigEntry name="AddUserAsCookie" value=""
description="Add the username to the sessions cookies"/>
      <PluginConfigEntry name="AuthParameters" value=""
description="List of key=value string which is passed to the authenticators init
function"/>
      <PluginConfigEntry name="Authenticator" value=""
description="Name of authenticator to use, leave to use default, else classname to
use"/>
      <PluginConfigEntry name="BasePath"
value="C:\Users\RGAV\dev\NUM-15094\ide\realmDirectories\realm0\plugins\htdocs"

```

```

description="Path used to locate the files"/>
    <PluginConfigEntry name="BufferSize" value=""
description="Size of the internal buffer to use to send the data"/>
    <PluginConfigEntry name="Cache-Control" value=""
description="Specifies the cache control for the plugin"/>
    <PluginConfigEntry name="CacheObjectSize" value=""
description="Size in bytes that can be stored in the cache"/>
    <PluginConfigEntry name="CachedObjects" value=""
description="Number of objects to store in the cache"/>
    <PluginConfigEntry name="DefaultName" value="index.html"
description="If no file name is specified which file should be returned"/>
    <PluginConfigEntry name="EnableURLRewrite" value=""
description="If the plugin will scan the source and rewrite the urls"/>
    <PluginConfigEntry name="FileNotFoundPage" value=""
description="name of the file to send when file can not be located"/>
    <PluginConfigEntry name="GroupNames" value=""
description="A comma seperated list of groups which the user must be a member of at
least one to
be granted access"/>
    <PluginConfigEntry name="MimeType" value=""
description="Name of the file to load the mime type information from"/>
    <PluginConfigEntry name="ReloadUserFileDynamically"
value="" description="Choose true to have the user file get reloaded on each auth
request"/>
    <PluginConfigEntry name="RoleNames" value="" description="A comma
seperated
list of roles which the user must have at least one of to be granted access"/>
    <PluginConfigEntry name="Security Realm" value="" description="Name
of the
authentication realm"/>
    <PluginConfigEntry name="SeparateAccessandErrorLogs" value=""
description="Choose true to have separate log files"/>
    <NirvanaFilePlugin>
    </RealmInterfacePlugin>
    <JavascriptConfigEntry CORSAllowedOrigins="*" EnableJavaScript="true"
EnableWebSockets="true" CORSAllowCredentials="true" EnableGZipLP="true"
MinimumBytesBeforeGZIP="1000" AjaxLPIdleDelay="60000" AjaxLPActiveDelay="100"/>
    </RealmNHPInterface>
    </RealmInterfaces>
    <RealmSecurityGroupSet/>
    <RealmSchedulerSet>
    <Scheduler
source="c2NoZWR1bGVyIHJlYWxtTG9nU2NoZWR1bGUgewoJaW5pdGhhbGZzZSB7CgogCQlMb2dnZXI
ucmVwb3J0KCJEZWZhdWx0IHJlYWxtIGxvZyBmaWxlIGF1dG8gcm9sbCBpbml0aWFsaXNlZCIpOwoKCSB9CgoJZXZlcnkgMDow
MCB7CgoJCUxvZ2dlci5yb2xsKCK7CgkJTG9nZ2VyLnJlcG9ydCgiTG9nIGF1dG9tYXRpY2FsbHkgcm9sbGVkIGJ5IGRlZmF1b
HQgc2NoZWR1bGVkIHJlcnlwdC4gSWYgdGhpcyBpcyBub3QgcmlwZmlyZWQgcGxlyXNlIHJlbW92ZSB0aGUgc2NyaXB0IGZyb2
0gdGhliHNlcnZlciIpOwoKCX0KfQ==" subject="[rgav@0:0:0:0:0:0:1, rgav@127.0.0.1]"
clusterWide="false"/>
    </RealmSchedulerSet>
    </NirvanaRealm>

```

## Management and Monitoring Sections

### Enterprise view

Universal Messaging Enterprise Manager facilitates centralised summary view for a set of Universal Messaging realm servers whether standalone or defined in a cluster setup.

- [“Enterprise Summary” on page 307](#)
- [“Cluster Summary” on page 308](#)

## **Enterprise Summary**

The Universal Messaging Enterprise Manager provides a summary view of all Universal Messaging realms whether clustered or standalone, publish and consume event / connection totals and rates across the entire set of Realms that the instance of the Enterprise Manager is connected to.

For more information on these screens please see the Management Information section.

The screenshot displays the Nirvana Enterprise Manager interface. On the left, a tree view shows the hierarchy: Nirvana Enterprise > Clusters > test > Realms > realm1 (host1:11010), realm2 (host2:11030), and realm3 (host3:11070). Each realm contains ClusterRates, Data Groups, and GlobalOrders. The main area shows an 'Enterprise Summary' tab with an 'Event History' graph. The graph displays a fluctuating line chart with a red-to-yellow color gradient, indicating event activity over time. Below the graph is a summary table.

Totals		Event Status		Connection S
Clusters	1	Consumed	12769400	Total
Realms	3	Published	38068304	Current
Channels	3	Consumed/Sec	112951.9	Rate
Queues	3	Published/Sec	112952.5	
Data Groups	0			

### Cluster Summary

The Universal Messaging Enterprise Manager tool provides a summary view for each cluster defined, showing a real-time cluster status as well as publish and consume event / connections totals and rates.

The screenshot displays the Nirvana Enterprise Manager interface. The left pane shows a tree view of the configuration:

- Nirvana Enterprise
  - Clusters
    - test
  - Realms
    - realm1(host1:11010)
      - ClusterRates
      - Data Groups
      - GlobalOrders
    - realm2(host2:11030)
      - ClusterRates
      - Data Groups
      - GlobalOrders
    - realm3(host3:11070)
      - ClusterRates
      - Data Groups
      - GlobalOrders

The right pane shows the 'Cluster Summary' tab with the following 'Cluster Members' table:

Name	State	Master	realm1	
realm1	Master	realm1	Local	OnLin
realm2	Slave	realm1	OnLine	Local
realm3	Slave	realm1	OnLine	OnLin

Below the table is an 'Event History' graph showing a fluctuating line chart with red and yellow data points on a green grid.

At the bottom, there are two summary tables:

Totals		Event Status		
Realms	3	Consumed	15980469	Total
Channels	3	Published	47864694	Current
Queues	3	Consumed/Sec	111474.1	Rate
Services	0	Published/Sec	225065.8	

## Management Information

Each Universal Messaging Administration API client, (the Enterprise Manager is an admin API client) connects to one or more realms and asynchronously consumes status events on all of the objects within each realm.

Status events are sent periodically (between configurable intervals, see [“Realm Configuration” on page 29](#)) and contain information pertaining to those objects where activity has occurred.

As each status event is received, the Enterprise Manager is updated with the relevant values and these are displayed on the status panels for each object within the namespace.

Selecting an object from the namespace automatically renders a set of panels to the right of the selected node, one of which is the 'Status' panel. The status panels and their contents are described in the links below.

The Universal Messaging enterprise manager has been written entirely with the Universal Messaging admin API and so the functionality seen in these screens can easily be added to any bespoke administration or monitoring tools.

- [“Enterprise Summary” on page 310](#)
- [“Clusters Summary” on page 312](#)
- [“Cluster Status” on page 314](#)
- [“Realms Summary” on page 316](#)
- [“Realm Status” on page 318](#)
- [“Realm Monitoring” on page 321](#)
- [“Container Status” on page 342](#)
- [“Container Monitor Panel” on page 344](#)
- [“Channel Status Information” on page 348](#)
- [“Data Group Status Information” on page 350](#)
- [“Channel Connections” on page 354](#)
- [“Queue Status Information” on page 359](#)
- [“Interface Status Information” on page 361](#)

For more information on other functionality provided in the enterprise manager please refer to the Enterprise Manager guide.


### Enterprise Summary

The enterprise view is the first screen you see whenever the Universal Messaging enterprise manager is launched. The screen is designed to provide an overview of the characteristics as well as current status of the set of Universal Messaging realms that enterprise manager is currently connected with

This section describes the type of status information that can be observed from the Enterprise level view.

The top of the screen displays a large real time graph illustrating the total number of events published (yellow) and consumed (red) across all Universal Messaging realms.

The bottom of the screen displays 3 panels named **Totals**, **Event Status** and **Connection Status**. These panels and the information displayed are described below.



## Totals

The Totals section describes 5 values :

- **Clusters**- The number of clusters defined within the enterprise manager and its realm nodes
- **Realms**- The number of realms known by the enterprise manager
- **Channels**- The number of channels that exist across all known realms

- **Queues**- The number of queues that exist across all known realms
- **Data Groups**- The number of Data Groups that exist across all known realms
- **Services**- Total number of services that exist across all known realms

## Event Status

The Event Status section describes 4 values:

- **Published** - The total number of events being published to all channels, queues and services across all realms
- **Consumed** - The total number of events being consumed from all channels, queues and services across all realms
- **Published/Sec** - The number of events being published to all channels, queues and services, per second across all realms
- **Consumed/Sec** - The number of events being consumed from all channels, queues and services, per second across all realms

## Connection Status

The Connection Status section describes 3 values :

- **Total** - The total number of connections made to all realms
- **Current** - The current number of events across all realms
- **Rate** - The number of connections being made per second across all realms at this point in time

## Clusters Summary

The clusters view is designed to provide an overview of the characteristics as well as current status of the set of Universal Messaging clustered realms that enterprise manager is aware of.

This section describes the type of status information that you can observe from the Clusters Summary view.

The top of the screen displays a large real time graph illustrating the total number of events published (yellow) and consumed (red) across all Universal Messaging clusters.

The bottom of the screen displays 3 panels named **Totals**, **Event Status** and **Connection Status**. These panels and the information displayed are described below.

### Totals

The Totals section describes the following :

- **Clusters**- The number of clusters defined within the enterprise manager and its realm nodes
- **Realms**- The number of realms known by the enterprise manager

- **Channels**- The number of channels that exist across all known realms
- **Queues**- The number of queues that exist across all known realms
- **Data Groups**- The number of Data Groups that exist across all known realms
- **Services**- Total number of services that exist across all known realms

### **Event Status**


The Event Status section describes the following :

- **Published** - The total number of events published to all channels, queues and services across all realms within known clusters
- **Consumed** - The total number of events consumed from all channels, queues and services across all realms within known clusters
- **Published/Sec** - The number of events published to all channels, queues and services, per second across all realms within known clusters
- **Consumed/Sec** - The number of events consumed from all channels, queues and services, per second across all realms within known clusters

### **Connection Status**

The Connection Status section describes the following :

- **Total** - The total number of connections made to all realms within known clusters
- **Current** - The current number of events across all realms within known clusters
- **Rate** - The number of connections being made per second across all realms within known clusters



### Clusters Status

The cluster status view provides an overview of the characteristics as well as current status of a selected Universal Messaging cluster.

This section will describe the type of status information that you can observe from the Cluster Status view.

The top of the screen displays a large real time graph illustrating the total number of events published (yellow) and consumed (red) across all Universal Messaging clusters.

The bottom of the screen displays 3 panels named **Totals**, **Event Status** and **Connection Status**. These panels and the information displayed are described below.

## Totals

The Totals section describes the following :

- **Realms**- The number of realms within the cluster
- **Channels**- The number of channels that exist across all realms within the cluster
- **Queues**- The number of queues that exist across all realms within the cluster
- **Services**- Total number of services that exist across all realms within the cluster

## Event Status


The Event Status section describes the following :

- **Published** - The total number of events published to all channels, queues and services across all realms within the cluster
- **Consumed** - The total number of events consumed from all channels, queues and services across all realms within the cluster
- **Published/Sec** - The number of events published to all channels, queues and services, per second across all realms within the cluster
- **Consumed/Sec** - The number of events consumed from all channels, queues and services, per second across all realms within the cluster

## Connection Status

The Connection Status section describes the following :

- **Total** - The total number of connections made to all realms within the cluster
- **Current** - The current number of events across all realms within the cluster
- **Rate** - The number of connections being made per second across all realms within the cluster



## Realms Summary

The realms view is designed to provide an overview of the characteristics as well as current status of the set of Universal Messaging realms that enterprise manager is aware of.

This section will describe the type of status information that you can observe from the Realms Summary view.

The top of the screen displays a large real time graph illustrating the total number of events published (yellow) and consumed (red) across all Universal Messaging realms.

The bottom of the screen displays 3 panels named **Totals**, **Event Status** and **Connection Status** respectively. These panels and the information displayed are described below.

### **Totals**

The Totals section contains the following values :

- **Realms**- The number of realms known by the enterprise manager
- **Channels**- The number of channels that exist across all known realms
- **Queues**- The number of queues that exist across all known realms
- **Data Groups**- The number of Data Groups that exist across all known realms
- **Services**- Total number of services that exist across all known realms

### **Event Status**


The Event Status section contains the following :

- **Published** - The total number of events published to all channels, queues and services across all known realms
- **Consumed** - The total number of events consumed from all channels, queues and services across all known realms
- **Published/Sec** - The number of events published to all channels, queues and services, per second across all known realms
- **Consumed/Sec** - The number of events consumed from all channels, queues and services, per second across all known realms

### **Connection Status**

The Connection Status section contains the following :

- **Total** - The total number of connections made to all known realms
- **Current** - The current number of events across all known realms
- **Rate** - The number of connections being made per second across all known realms



### Realm Status

The realm status view provides an overview of the characteristics as well as current status of a selected Universal Messaging realm. When you select a Realm node from the namespace, the status panel is displayed by default for the realm.

This section will describe the type of status information that you can observe from the Realm Status view.

The top of the screen displays a panel containing 4 values. These values are :

- **Name** - The name of the selected realm
- **Threads** - Number of threads within the Realm Server's JVM
- **Realm Up Time** - How long the realm has been running for
- **Last Update** - The time that the last status update was sent by the realm

The top of the Status panel contains 2 large real time graphs illustrating the total number of events published (yellow) and consumed (red) across the Universal Messaging Realm, as well as the JVM memory status for the selected realm.

The bottom of the screen displays 4 panels named **Event Status**, **Totals**, **Connection Status** and **Memory Usage**. These panels and the information displayed are described below.

### Event Status

The Event Status section describes 4 values :

- **Published** - The total number of events published to all channels, queues and services within the realm
- **Consumed** - The total number of events consumed from all channels, queues and services within the realm
- **Published/Sec** - The number of events published to all channels, queues and services, per second within the realm
- **Consumed/Sec** - The number of events consumed from all channels, queues and services, per second within the realm

### Totals

The Totals section describes the following values :

- **Realms**- The number of realms mounted within this realm's namespace
- **Channels**- The number of channels that exist within this realm
- **Queues**- The number of queues that exist within this realm
- **Data Groups**- The number of Data Groups that exist within this realm
- **Services**- Total number of services that exist within this realm

### Connection Status

The Connection Status section contains the following values :

- **Total** - The total number of connections made to this realm
- **Current** - The current number of connections to this realm
- **Rate** - The number of connections being made per second to this realm

- **Allowed** - The permitted number of concurrent connections

### **Memory Usage(MB)**

The Memory Usage section contains the following values :

- **Total** - The total amount of MB allocated to the Realm JVM, specified by the -Xmx value for the JVM
- **Free** - The amount of JVM memory available for the Realm
- **Used** - The amount of JVM memory used by the Realm
- **Used/sec** - The amount of memory used per second by the Realm between newest update and previous update

The screenshot displays the Nirvana Enterprise Manager interface. The left sidebar shows a tree view with 'Nirvana Enterprise' at the top, followed by 'Clusters' (containing 'test') and 'Realms' (containing 'realm1', 'realm2', and 'realm3'). Under each realm, there are sub-items: 'ClusterRates', 'Data Groups', and 'GlobalOrders'. The main area is titled 'Monitoring' and contains several panels:

- Realm Details:** Fields for Name, Threads, Realm UpTime, and Last Update.
- Event History:** A line graph showing a red line fluctuating over time on a green grid.
- Memory Usage History:** A line graph showing a yellow line fluctuating over time on a green grid.
- Event Status:** A table showing metrics for Consumed, Published, Consumed/Sec, and Published/Sec.
- Totals:** A list of counts for Realms, Channels, Queues, Data Groups, Data Streams, and Services.
- Connection Status:** A table showing Total (13), Current (3), Rate (0.0), and Allowed (Unlimited).
- Memory Usage (M):** A table showing Total, Free, Used, and Change.


## Realm Monitoring

When you select a Universal Messaging realm node from the namespace, one of the available panels to select is labeled 'Monitoring'. This panel is a container for multiple panels that enable you to view live information on the selected realm.

There are 5 tabs available under the Monitoring section, as shown in the image below.

- [“Logs” on page 322](#)

- “Realm Connections” on page 326
- “Threads Panel” on page 331
- “Top” on page 333
- “Audit” on page 338




## Universal Messaging Enterprise Manager : Logs Panel

Each Universal Messaging Realm Server has a log file within the data directory called `nirvana.log`. The Enterprise Manager provides a panel that displays real time log messages as they are written to the log file. This enables you to remotely view the activity on a realm as it is happening. The Universal Messaging Administration API also provides the ability to consume the log file entries from an `nRealmNode`. See the code example "Monitor the Remote Realm Log and Audit File" for an illustration of usage.

The Universal Messaging log file will contain useful information about various activities, such as connection attempts, channels being located and subscribed to as well as status and warning information.

## The Logs Panel

The Enterprise Manager provides a panel for each realm where the log files can be viewed. To view the log files, click on the realm node from the namespace and select the panel labeled 'Monitor' and then select the 'Logs' tab. This will show the live log messages for the selected realm. The log panel will automatically replay the last 20 log entries from the Realm Server and then each entry thereafter. The image below shows an example of the log panel for a selected realm:



The log panel also provides the ability to stream the log messages to a local file. Clicking on the button labeled 'Start Stream' from the log panel will prompt you to enter the name of the file you wish to stream the log messages to. The stream can be stopped by clicking the same button again.

## Understanding the log file

When a server is started, the initial entries in the log file contain useful information about the server's configuration. The following text is an excerpt from a Realm Server log during startup:

```
[Wed Jun 20 09:37:39 BST 2012],=====
[Wed Jun 20 09:37:39 BST 2012], Copyright . All rights reserved
[Wed Jun 20 09:37:39 BST 2012],Start date           = Wed Jun 20 09:37:39 BST 2012
[Wed Jun 20 09:37:39 BST 2012],Process ID             = 3216
[Wed Jun 20 09:37:39 BST 2012],
[Wed Jun 20 09:37:39 BST 2012],Realm Server Details :
[Wed Jun 20 09:37:39 BST 2012], Realm Server name     = realm1
[Wed Jun 20 09:37:39 BST 2012], Realm Server version = $Name: $ - $Revision: 1.7 $
[Wed Jun 20 09:37:39 BST 2012], Build Number         = Build 11248
[Wed Jun 20 09:37:39 BST 2012], Build Date           = June 19 2012
[Wed Jun 20 09:37:39 BST 2012], Data Directory       =
    C:\\Universal Messaging\\server\\realm1\\data
[Wed Jun 20 09:37:39 BST 2012], Extension Directory =
    C:\\Universal Messaging\\server\\realm1\\plugins\\ext
[Wed Jun 20 09:37:39 BST 2012], Low Latency Executor = false
[Wed Jun 20 09:37:39 BST 2012], Realm(s) Reloaded   = 1
[Wed Jun 20 09:37:39 BST 2012], Channels Reloaded   = 8
[Wed Jun 20 09:37:39 BST 2012], Queues Reloaded     = 0
[Wed Jun 20 09:37:39 BST 2012], Interfaces Reloaded = 1
[Wed Jun 20 09:37:39 BST 2012],
[Wed Jun 20 09:37:39 BST 2012],Operating System Environment :
[Wed Jun 20 09:37:39 BST 2012], OS Name              = Windows 7
[Wed Jun 20 09:37:39 BST 2012], OS Version           = 6.1
[Wed Jun 20 09:37:39 BST 2012], OS Architecture     = x86
[Wed Jun 20 09:37:39 BST 2012], Available Processors = 4
[Wed Jun 20 09:37:39 BST 2012],
[Wed Jun 20 09:37:39 BST 2012],Java Environment :
[Wed Jun 20 09:37:39 BST 2012], Java Vendor          = Sun Microsystems Inc.
[Wed Jun 20 09:37:39 BST 2012], Java Vendor URL      = http://java.sun.com/
[Wed Jun 20 09:37:39 BST 2012], Java Version         = 1.6.0_30
[Wed Jun 20 09:37:39 BST 2012], Memory Allocation    = 494 MB
[Wed Jun 20 09:37:39 BST 2012], Memory Warning       = 420 MB
[Wed Jun 20 09:37:39 BST 2012], Memory Emergency     = 465 MB
[Wed Jun 20 09:37:39 BST 2012], Clock Adjustment     = 0ms
[Wed Jun 20 09:37:39 BST 2012],Startup: Starting Realm status monitoring
[Wed Jun 20 09:37:39 BST 2012], Nanosecond delay    = Supported
[Wed Jun 20 09:37:39 BST 2012], Time Zone           = Greenwich Mean Time
[Wed Jun 20 09:37:39 BST 2012],Startup: Stored Certificate and private key
    in servers keystore
[Wed Jun 20 09:37:39 BST 2012],Startup: Completed Realm Public and Private RSA Key
[Wed Jun 20 09:37:39 BST 2012], Security Provider 0 = SUN version 1.6
[Wed Jun 20 09:37:39 BST 2012],Startup: Reloading Realm Public for realm1
[Wed Jun 20 09:37:39 BST 2012],Startup: Cluster cryptographic initialisation, complete
[Wed Jun 20 09:37:39 BST 2012], Security Provider 1 = SunRsaSign version 1.5
[Wed Jun 20 09:37:39 BST 2012], Security Provider 2 = SunJSSE version 1.6
[Wed Jun 20 09:37:39 BST 2012], Security Provider 3 = SunJCE version 1.6
[Wed Jun 20 09:37:39 BST 2012], Security Provider 4 = SunJGSS version 1.0
[Wed Jun 20 09:37:39 BST 2012], Security Provider 5 = SunSASL version 1.5
[Wed Jun 20 09:37:39 BST 2012], Security Provider 6 = XMLDSig version 1.0
[Wed Jun 20 09:37:39 BST 2012], Security Provider 7 = SunPCSC version 1.6
[Wed Jun 20 09:37:39 BST 2012], Security Provider 8 = SunMSCAPI version 1.6
[Wed Jun 20 09:37:39 BST 2012],=====
```

The above sequence of log entries can be found at the beginning of the Universal Messaging log file, and shows information such as when the realm was started, the build number and build date of the Universal Messaging Server, as well as environmental information like, OS, Java version, timezone.

Each log entry contains a date, the log level as well as the log message itself, in the format:

```
[DATE_TIME] , LOG_LEVEL , Message
```

It is also possible to configure the name of the Java package that the message originates from and the name of the thread the message is being logged from. See the section [“Realm Configuration” on page 29](#) for related information.

The Universal Messaging log level is a level from 0 to 6 that determines what information is written to the log. Log level 0 is the most verbose level of logging and on a heavily utilised server will produce a lot of log output. Log level 6 is the least verbose level, and will produce low levels of log output. The log level of each log message corresponds to a value from 0 to 6. The following list explains the log file messages levels and how they correspond to the values:

- 0 - TRACE (Log level 0 will output any log entries with a level in the range 0-6; this is the most verbose level)
- 1 - DEBUG (Log level 1 will output any log entries with a level in the range 1-6)
- 2 - INFO (Log level 2 will output any log entries with a level in the range 2-6)
- 3 - WARN (Log level 3 will output any log entries with a level in the range 3-6)
- 4 - ERROR (Log level 4 will output any log entries with a level in the range 4-6)
- 5 - FATAL (Log level 5 will output any log entries with a level in the range 5-6)
- 6 - LOG (Log level 6 will output any log entries with a level of 6; this is the least verbose level)

Log levels can be changed dynamically on the server by using the Config Panel (see [“Realm Configuration” on page 29](#)). The log file has a maximum size associated with it. When the maximum file size is reached, the log file will automatically roll, and rename the old log file to `_old` and create a new log file. The maximum size for a log file is set to 10000000 bytes (approximately 10MB). This value can be changed within the `nserver.conf` or `Server_Common.conf` file in the `server/<realm>/bin` directory of your installation, where `<realm>` is the name of the Universal Messaging realm. You need to modify the `-DLOGSIZE` property within this file to change the size.

**Note:**

`nserver.conf` is used if you start the realm server manually, e.g. from the command line. `Server_Common.conf` is used if you start the realm server as a Windows service or as a UNIX daemon.

## Other Logging Frameworks

By default, Universal Messaging uses a built in logging framework, but there is also the capability to use third party open source frameworks. Currently, we support the Logback (<http://logback.qos.ch/>) and Log4J2 (<http://logging.apache.org/log4j/2.x/>) frameworks.

To configure Universal Messaging to use one of these frameworks, you can pass a `-DLOG_FRAMEWORK` parameter with the values `LOGBACK` or `LOG4J2`. See the section *Server Parameters* in the Concepts guide for further information.

These frameworks are configured using XML configuration files loaded from the classpath. The Universal Messaging installation provides default versions of these configuration files in the `lib` directory. These files can be modified in order to produce the desired logging output. For more information on configuration see the official documentation of the relevant framework.

**Note:**

When Universal Messaging is configured to use Logback as the logging framework, the majority of the server startup messages in the server's `nirvana.log` file will be written with status `ERROR`. This happens due to a limitation in Logback that does not provide usage of custom log levels. Therefore, Universal Messaging messages logged with `LOG` level are translated to `ERROR` level when Logback is used.

## The Log Manager

Universal Messaging has 3 different log managers for archiving old log files. When a log file reaches its maximum size, the log manager will attempt to archive it, and a new log file will become active. Options such as the number of log files to keep, and the maximum size of a log file are configurable through the logging section of the Config Panel (see [“Realm Configuration” on page 29](#)). When a log file is archived and a new log file created, realm specific information such as Universal Messaging version number will be printed to the start of the new log in a similar way to when a realm is started. Each log manager uses a different method to store log files once they are not the active logs for the realm.

- `ROLLING_OLD` : This log manager uses 2 log files. The active log file is stored with the default log name, and the most recently rolled log file is stored with `_old` appended to the log name. e.g. `nirvana.log` and `nirvana.log_old`
- `ROLLING_DATE` : The rolling date manager stores a configurable number of log files (`RolledLogFileDepth`). Rolled log files are stored with the date they were rolled appended to the active log file name. e.g. `nirvana.logWed-Sep-14-02-31-40-117-BST-2011`.
- `ROLLING_NUMBER` : The numbered log manager stores a configurable number of log files (`RolledLogFileDepth`). Rolled log files are stored with a numbered index appended to the file name e.g. `nirvana.log3` is the 3rd oldest log file

## Realm Connections

When a Universal Messaging client connects to a Realm Server, the server maintains information on the connection (see [“Connection Information” on page 499](#)) that is available through the Universal Messaging Administration API. The API also provides mechanisms for receiving notification when connections are added and deleted (see the code example "Connection Watch" for an illustration of using this in the Administration API).

The Universal Messaging Enterprise Manager allows you to view the connections on a realm as well as drilldown and view specific information about each connection, such as the last event sent or received, and the rate of events sent and received from each connection.

To view the current realm connections, simply select a realm node from the namespace, and select the 'Connections' tab from within the 'Monitoring' tab of the selected realm node. This will display a panel containing a table of connections, as shown in the image below.

The screenshot shows the Nirvana Enterprise Manager interface. The left pane displays a tree view with 'Nirvana Enterprise' at the root, followed by 'Clusters' (containing 'test') and 'Realms' (containing 'realm1', 'realm2', and 'realm3'). Each realm has sub-nodes for 'ClusterRates', 'Data Groups', and 'GlobalOrders'. The 'Connections' tab is selected in the 'Monitoring' section. The 'Connection Summary' table is displayed below the tabs.

protocol	user	host	conn
nsp	administrator	127.0.0.1	127.0.0.1:
nsp	subscriber	127.0.0.1	127.0.0.1:
nsp	publisher	127.0.0.1	127.0.0.1:

The connections table has 4 columns:

- **Protocol** - The protocol used in the connection

- **User** - The name of the user connected
- **Host** - The host machine that the user is connecting from
- **Connection** - The local connection id, defined as hostname:local\_port

The highlighted connection above shows that the user has connection using the nhp protocol, to localhost. In this example, the nhp interface is running on port 80, so the RNAME of this connection was nhp://localhost:80/

When a connection is highlighted, there a number of things that can be shown for a the connection.

Firstly, connections can be disconnected by clicking on the 'Disconnect' button.

Secondly, by double-clicking on a connection from the table, or by clicking on the 'Show Details' button, you are presented with a panel that contains a more detailed look at the activity for the selected connection. The connection details panel is shown in the image below.

The screenshot displays the Nirvana Enterprise Manager interface. The left sidebar shows a tree view of the system structure: Nirvana Enterprise > Clusters > test > Realms > realm1. The main pane is titled 'Realm Details' and shows the following information:

Realm Details  
 Name:  
 Threads:  
 Realm UpTime:  
 Last Update:

Navigation tabs include: Status, Monitoring, ACL, Comms, Nirvana Realms, Config, Scheduler, Logs, Connections, Threads, Top, Audit.

The 'Connections' tab is active, showing 'Connection Details' and 'Client Environment'.

**Connection Details:**

User:	subscriber
Host:	127.0.0.1
Protocol:	nsp
Connection:	realm1
Connection ID:	127.0.0.1:49487
Multicast Enabled:	true
Requested Priority Connection:	false

**Client Environment:**

Language / Version:	
OS:	
OS Version:	
Build Number:	
Build Date:	

Below the connection details are two empty grid areas for 'Tx Event History' and 'Rx Event History'.

At the bottom, there are two summary tables:

Events Sent		Events Received		Status
Total	16358511	Total	7	Conne
Rate	35894.6	Rate	0.0	Queu
Max	37431.2	Max	0.0	Last T
Last Evt Type	Publish Event	Last Evt Type	HeartBeat	Last R
Bytes	2.7 GB	Bytes	134.0	

Buttons at the bottom include: Show Details, Show List, and Bounce.

## Connection Details

You will see that there are 2 separate information panels above the graphs once you have drilled down into a connection. The first of which is labelled Connection Details. This information contains information about the user connection, such as user name, host protocol.

## Client Environment

Next to this you will see a panel that shows details regarding the client environment for this user. These includes API language / Platform, Host OS and Universal Messaging build number

The two graphs, labeled 'Tx Event History' and 'Rx Event History' show the total (yellow) and rates (red) for events received from the server (TX) and sent to the server (RX) for the selected connection.

The bottom of the connection details panel shows 3 sections of information for the selected connection, 'Events Sent', 'Events Received' and 'Status'. Each of these are described below.

## Events Sent

The Events Sent section contains the values:

- **Total** - The total number of events sent by the realm server to this connection
- **Rate** - The rate at which events are being sent by the realm server to this connection
- **Max** - The maximum rate at which events have been sent by the realm server to this connection
- **Last Event Type** - The type of the last event sent from the realm server
- **Bytes** - Total bytes sent by the realm server to this connection

## Events Received

The Events Received section contains the following values:

- **Total** - The total number of events sent by this connection to the realm server
- **Rate** - The rate at which events are being sent by connection to the realm server
- **Max** - The maximum rate at which events have been sent by this connection to the realm server
- **Last Event Type** - The type of the last event sent from the connection to the realm server
- **Bytes** - Total bytes sent by this connection to the realm server

## Status

The Events Sent section contains the following values:

- **Connect Time** - The amount of time this connection has been connected to the realm server
- **Queue Size** - The number of events in the outbound queue of this connection (i.e. events waiting to be sent to the realm server)
- **Last Tx** - The time since the last event was received by this connection from the realm server
- **Last Rx** - The time since the last event was sent to the server from this connection

Clicking on the 'Show List' button will take you back to the connections table.

### **Threads Status**

The threads tab found within the Enterprise Manager offers 2 statistical views, thread pools and scheduler tasks.

The thread pool display shows the number of idle and active threads per thread pool as well as the task queue size per thread pool and a total number of executed tasks for the respective thread pool

The Scheduler provides information pertaining to the number of scheduled operations each task has within the system.

Software AG - webMethods / Nirvana Enterprise Manager

File Connections Cluster Help

Nirvana Enterprise

- Clusters
  - test
- Realms
  - realm1
    - ClusterRates
    - Data Groups
    - GlobalOrders
  - realm2
    - ClusterRates
    - Data Groups
    - GlobalOrders
  - realm3
    - ClusterRates
    - Data Groups
    - GlobalOrders

Realm Details

Name:

Threads:

Realm UpTime:

Last Update:

Status Monitoring ACL Comms Nirvana Realms Config Scheduler JNDI

Logs Connections Threads Top Audit

Pools Scheduler

Thread Monitor

Scheduled Tasks

Reused Threads

Vended Threads

Queued Threads

Buffers Created

Buffers Reused

Fanout backlog

Thread Pools

Name	Idle Threads	Allocated Threads	Queued Tasks
Scheduler Worker Pool	6	6	0
CommonPool	3	3	0
Client Setup	4	4	0
PersistentStore	4	4	0
Client session closer	1	1	0
Orphaned session closer	1	1	0
Cluster KeepAlive	4	4	0
Inter Realm Connection ...	3	3	0
Flush-Monitor	0	4	5
WritePool	5	5	0
Recovery Pool	4	4	0
ClusterRecovery	5	5	0
KeepAlive	2	2	0
nhp0	0	1	0
HTTP-Plugins	2	2	0
Join Daemon	2	2	0
ReadPool	5	6	0
ClosePool	2	2	0

The screenshot displays the Nirvana Enterprise Manager interface. The left sidebar shows a tree view with 'Nirvana Enterprise' at the top, followed by 'Clusters' (containing 'test') and 'Realms' (containing 'realm1', 'realm2', and 'realm3'). Each realm has sub-nodes for 'ClusterRates', 'Data Groups', and 'GlobalOrders'. The main window is titled 'Software AG - webMethods / Nirvana Enterprise Manager' and has a menu bar with 'File', 'Connections', 'Cluster', and 'Help'. Below the menu bar is a 'Realm Details' section with fields for 'Name:', 'Threads:', 'Realm UpTime:', and 'Last Update:'. A toolbar contains icons for 'Status', 'Monitoring', 'ACL', 'Comms', 'Nirvana Realms', 'Config', and 'Scheduler'. Below the toolbar is another set of icons for 'Logs', 'Connections', 'Threads', 'Top', and 'Audit'. The 'Top' icon is selected, and a 'Scheduler' panel is visible below it. This panel has a 'Pools' tab and a 'Scheduler' tab. The 'Scheduler' tab contains a table with two columns: 'Name' and 'Scheduled'.

Name	Scheduled
com.pcbsys.nirvana.server.nb	
com.pcbsys.nirvana.server.nb	
Server state manager	
Connection Security Monitor	
I/O Interface Integrity monitor	
Connection Security Monitor	
Connection Security Monitor	
Cluster State monitor	
System I/O Throughput monitor	
Channel Delete Agent	
I/O HTTP session timeout manager	
Channel Maintenance Monitor task for C:\Nirvana 7.0.11248\server\...	
Channel Maintenance Monitor task for C:\Nirvana 7.0.11248\server\...	
Channel Maintenance Monitor task for C:\Nirvana 7.0.11248\server\...	
Channel Maintenance Monitor task for C:\Nirvana 7.0.11248\server\...	
Channel Maintenance Monitor task for C:\Nirvana 7.0.11248\server\...	
com.pcbsys.foundation.drivers.ag	
Channel Maintenance Monitor task for C:\Nirvana 7.0.11248\server\...	
Channel Maintenance Monitor task for C:\Nirvana 7.0.11248\server\...	
Channel Maintenance Monitor task for C:\Nirvana 7.0.11248\server\...	
I/O Session establishment time out manager	
nDataGroupReconnectTimeout	
Channel Maintenance Monitor task for C:\Nirvana 7.0.11248\server\...	
Cluster heart beat	
ProtoBuf file descriptor monitor	

## Top

Within the 'Monitoring' panel of a selected Realm node you will find a panel called 'Top'. This provides a view not unlike 'top' for unix systems or task manager for windows based systems. Its main purpose is to present the user with a high level view of realm usage, both from a connection perspective and also from a channel perspective.

The Top panel comprises 2 sections. The top most section contains 2 real time graphs illustrating the realm memory usage in the same way the Realm Status panel (see [“Realm Status” on page 318](#)) displays memory usage, as well as displaying JVM GC stats. This section also contains a summary showing the number of mounted realms, the number of resources and the number of services.

The bottom section of the Monitor panel displays a series of tabs, showing channel and connection usage throughout the realm.

## Channel Usage

The middle section of the Monitor panel displays a table showing multiple columns and rows. This table represents channel usage throughout the realm. Each row in the table represents a channel. Channel usage can be measured a number of ways. Each measurement corresponds to a column within the table. By clicking on one of the column headers, all known channels will be sorted according to their value for the selected column. For example, one of the columns is 'Connections', i.e. the number of current consumers on the channel. By clicking on the column header labelled 'Connections', the table will be sorted according to the number of consumers each channel has. The channel with the most number of consumers will appear at the top of the table.

Channel usage measurements are described below:

- **Connections** - The number of consumers the channel has
- **Published** - The rate of events published per status interval
- **Consumed** - The rate of events consumed per status interval
- **Memory (bytes)** - The number of bytes the channel uses from the JVM memory
- **% Memory** - The percentage of overall JVM memory used by this channel
- **Disk** - The amount of disk space used by this channel, only relevant for persistent / mixed channels

The screenshot displays the Nirvana Enterprise Manager interface. On the left is a tree view showing the hierarchy: Nirvana Enterprise > Clusters (test) > Realms (realm1, realm2, realm3). Under each realm, there are sub-items for ClusterRates, Data Groups, and GlobalOrders. The main panel on the right is titled 'Realm Details' and includes fields for Name, Threads, Realm UpTime, and Last Update. Below these are several tabs: Status, Monitoring, ACL, Comms, Nirvana Realms, Config, Scheduler, Logs, Connections, Threads, Top, and Audit. Two line graphs are visible: 'Memory Usage History' and 'JVM GC Stats'. At the bottom right, there are two tabs: 'Top Channel Usage' and 'Top Connection Usage'. The 'Top Connection Usage' tab is active, showing a table with the following data:

Name	Connections	Published	Consumed	Memory (...)
/ClusterRates	1	36,413.316	36,413.316	
/GlobalOrders	0	0	0	

A 'Bar Graph' button is located at the bottom right of the interface.

## Connection Usage

The bottom section of the monitor panel shows a similar table to that of the channel usage table described above, except that this table represents connection usage. Each row represents a connection. A connection corresponds to the physical aspect of a Universal Messaging Session. Connection usage, like channel usage can be measured in a number of different ways. Each column in the table represents a type of measurement for a realm connection. Clicking on one of the column

headers will cause the table of connections to be sorted according to the value of the selected column. For example, one of the columns is 'Events In', i.e. the number of events sent to the server by the connection. By clicking on the column header labeled 'Events In', the table will be sorted according to the number of events each connection has sent to the server. The connection with the most 'Events In' count will appear at the top of the table.

Connection usage measurements are described below:

- **Queued**- The number of event in the connections outbound queue
- **Events In** - The rate of events sent by the connection to the realm server
- **Bytes In** - The rate of bytes sent by the connection to the realm server
- **Events Out** - The rate of events consumed by the connection from the realm server
- **Bytes Out** - The rate of bytes consumed by the connection from the realm server
- **Latency** - The measured time it takes the connection to consume events from the server, i.e. time taken between leaving the realm server and being consumed by the connection.

The screenshot displays the Nirvana Enterprise Manager interface. On the left is a tree view showing the hierarchy: Nirvana Enterprise > Clusters > test > Realms > realm1 > ClusterRates, Data Groups, GlobalOrders; realm2 > ClusterRates, Data Groups, GlobalOrders; realm3 > ClusterRates, Data Groups, GlobalOrders. The main panel is titled 'Realm Details' and shows fields for Name, Threads, Realm UpTime, and Last Update. Below this are several tabs: Status, Monitoring, ACL, Comms, Nirvana Realms, Config, Scheduler, Logs, Connections, Threads, Top, and Audit. Two line graphs are visible: 'Memory Usage History' and 'JVM GC Stats'. Below the graphs are two buttons: 'Top Channel Usage' and 'Top Connection Usage'. A table is displayed below these buttons, showing channel usage statistics.


ID	Queued	Events In	Bytes In	Events Out
publisher@127.0.0.1:49498	0	19,887,534	3,062,679,880	
administrator@127.0.0.1:49493	0	161	1,282	1,...
subscriber@127.0.0.1:49487	0	23	242	49,987,6...

At the bottom right of the interface, there is a button labeled 'Bar Graph' with a small bar chart icon.

## Monitor Graphs

The monitor panel provides a method of graphing both channel and connection usage. It uses a 3D graph package from [sourceforge](http://sourceforge.net/projects/jfreechart/) (<http://sourceforge.net/projects/jfreechart/>) to display the items in each table as columns in a 3D vertical bar chart. The bar charts can be updated live as the values in the tables are updated. Once a column is selected, simply click on the button labeled 'Bar

Graph' under either the channel or connections table and a graph panel will appear, as shown in the image below showing a graph of the number of events published for channels within a realm..



Right-clicking anywhere within the graph will show a pop-up menu of options. One of the options is labeled 'Start Live Update', which will ensure the graph consumes updates as and when they occur to the table. Once the live update is started, you can also stop the live update by once again right clicking on the graph and selecting 'Stop Live Update'.

You can also print the graph, and save the graph image as a '.png' file, as well as alter the properties of the graph and its axis.

## Audit Panel

Universal Messaging Realm Servers log administration operations performed on the realm to a file. These events are called Audit Events and are stored in a local file called Universal MessagingAudit.mem. These audit events are useful for tracking historical information about the realm and who performed what operation and when. The Universal Messaging Administration API provides the ability to consume the audit file entries from an nRealmNodeM. See the code example "Monitor the Remote Realm Log and Audit File" for an illustration of usage.

The Universal Messaging Enterprise Manager provides an Audit Panel that displays the contents of the remote audit file and receives real time updates as and when audit events are generated. The audit events that are written to the audit file are determined by the configuration specified in the Config Panel (see "[Realm Configuration](#)" on page 29) of the Universal Messaging Enterprise Manager.

## Audit Events

Each audit event corresponds to an operation performed on an object within a realm. The audit event contains the date on which it occurred, the object and the operation that was performed on the object.

The list below shows the objects that audit events correspond to as well as the operations performed on them which are logged to the audit file:

- **Realm** - CREATE, DELETE, ACCESS
- **Interfaces** - CREATE, DELETE, MODIFY, START, STOP
- **Channels** - CREATE, DELETE, MODIFY
- **Queues** - CREATE, DELETE, MODIFY
- **Services** - CREATE, DELETE
- **Joins** - CREATE, DELETE
- **Realm**
- **ACL** - CREATE, DELETE, MODIFY
- **Channel ACL** - CREATE, DELETE, MODIFY
- **Queue ACL** - CREATE, DELETE, MODIFY
- **Service ACL** - CREATE, DELETE, MODIFY

## Audit Panel

The audit panel displays audit events for a realm server. You can view the audit panel by clicking on the realm you wish to view the audit file for within the namespace and selecting the panel labeled 'Audit' from within the 'Monitoring' panel of the selected realm. The image below shows an example of the audit panel for a Universal Messaging Realm.




- **Type** - What type of object was the action performed on
- **Action** - What action was performed
- **Object** - The name of the object

If the object type is an ACL for either realm, resource or service, selecting the entry from the table will also display the ACL changes in the bottom section of the audit panel. For modified ACLs, each acl permission that has been granted or removed will be displayed as a green '+', or a red '-' respectively.

## Audit Stream

The audit panel provides a button that enables you to stream the remote audit events from the realm to a local file. This also provides you with the option of replaying the entire audit file.

Clicking on the 'Start Stream' button will prompt you with a file chooser dialog to select the location and name of the file that the audit events will be streamed to. Once you have selected this file, you will be prompted whether you wish to replay the entire audit file into the stream or just the last 20 audit entries. The image below shows this dialog:



The text below is an excerpt from a sample audit file that has been streamed from a server. Each entry that relates to a modified ACL shows the permissions that have been changed, and the permissions that are granted by either a + or -. For permissions that have remained the same, the letter 'N' for not change will be placed after the permission.

```
Fri Jan 21 15:43:40 GMT 2005,CHANACL,/customer/sales:*@*,MODIFY,paul weiss@localhost,
  Full(-), Last Eid(N),Purge(-),Subscribe(N),Publish(-),Named Sub(N),Modify Acls(-),
  List Acls(-),
Fri Jan 21 15:43:40 GMT 2005,QUEUEACL,/partner/queries:*@*,MODIFY,
  paul weiss@localhost,Full(-),Purge(-), Peek(N),Push(-),Pop(-),Modify Acls(-),
  List Acls(-),
Fri Jan 21 15:43:40 GMT 2005,QUEUEACL,/partner/queries:paul weiss@localhost,MODIFY,
  paul weiss@localhost, Full(N),Purge(N),Peek(N),Push(N),Pop(N),Modify Acls(N),
  List Acls(N),
Fri Jan 21 16:13:10 GMT 2005,INTERFACE,nhp0,CREATE,paul weiss@localhost,
Fri Jan 21 16:15:31 GMT 2005,INTERFACE,nhp0,MODIFY,paul weiss@localhost,
```

## Archive Audit

The audit panel provides a button that enables you to archive the audit file. As mentioned before, depending on what is being logged to the audit file, the file can grow quite large. As it's an audit and provides historical data, there is no automatic maintenance of the file it is down to the realm

administrators when the file is archived. The 'Archive Audit' button when clicked will simply rename the existing audit file to a name with the current date, and start a new audit file.

## Container Status

When you select a container (folder) from the namespace, one of the available panels to select is labeled 'Totals'.

The Totals panel for a container provides status information for resources and services contained within the selected container branch of the namespace tree.

The status information shown within this panel is explained below.

The Totals panel is split into 2 main sections. The top most section of this panel shows 2 graphs, one demonstrates **Event History**, and the other **Storage Usage History**.

The event history graph shows the rates that events are published (red) and consumed (yellow) across all channels, queues and services found within the selected container.

The storage usage history graph shows the total amount of storage space used by each channel, queue and service found within the selected container.

Both graphs are updated every time a status event is received from the realm in which the container exists. The image below demonstrates the Container status graphs as described.

The screenshot displays the Nirvana Enterprise Manager interface. On the left is a tree view of the system structure. On the right, there are several monitoring panels. The top right panel shows 'Event History' and 'Storage Usage History'. Below these are four summary tables: 'Event Status', 'Totals', 'Connection Status', and 'Storage Usage (K)'.

Event Status	
Consumed	1733402
Published	1733403
Consumed/Sec	32146.1
Published/Sec	32146.3

Totals	
Realms	
Channels	
Queues	
Services	

Connection Status	
Total	1
Current	1
Rate	0.0

Storage Usage (K)	
Total	
Free	
Used	
Used/Sec	

The bottom section of the panel displays 4 sections of information, **Event Status**, **Totals**, **Connection Status** and **Storage Usage**. These panels and the information displayed are described below.

### Event Status

The Event Status section describes the following :

- **Published** - The total number of events published to all channels, queues and services within the container
- **Consumed** - The total number of events consumed from all channels, queues and services within the container
- **Published/Sec** - The number of events published to all channels, queues and services, per second within the container
- **Consumed/Sec** - The number of events consumed from all channels, queues and services, per second within the container

## Totals

The Totals section describes the following :

- **Realms**- The number of realms mounted within this container
- **Channels**- The number of channels that exist within this container
- **Queues**- The number of queues that exist within this container
- **Services**- Total number of services that exist within this container

## Connection Status

The Connection Status section describes the following :

- **Total** - The total number of connections made to channels, queues and services within this container
- **Current** - The current number of connections made to channels, queues and services within this container
- **Rate** - The number of connections being made per second to channels, queues and services within this container

## Storage Usage (KB)

The Memory Usage section describes 4 values :

- **Total** - The total amount of KB used by channels, queues and services found within this container
- **Free** - The free memory available in the Realm JVM
- **Used** - The amount of memory available in the Realm JVM
- **Change** - The amount of change in Realm JVM memory between newest update and previous update

## Container Monitor Panel

When you select a container (folder) from the namespace, one of the available panels to select is labeled 'Monitor'.

The Monitor panel provides a view not unlike 'top' for unix systems or task manager for windows based systems. Its main purpose is to present the user with a high level view of usage. The usage is based on channels found within the container node.

The Monitor panel comprises 2 sections. The top most section contains a real time graph illustrating the realm memory usage in the same way the Realm Status panel (see [“Realm Status” on page 318](#)) displays memory usage. This section also contains a summary showing the number of mounted realms, the number of channels, the number of queues and the number of services.

The image below demonstrates the Monitor panel for a container within a clustered realm.

The screenshot shows the Nirvana Enterprise Manager interface. On the left is a tree view of the system structure. On the right is the 'Monitor' panel, which contains two graphs and a table.

**Tree View Structure:**

- Nirvana Enterprise
  - Clusters
    - test
  - Realms
    - realm1
      - ClusterRates
      - Data Groups
        - GlobalOrders
          - uk
            - rates
      - realm2
        - ClusterRates
        - Data Groups
          - GlobalOrders
      - realm3
        - ClusterRates
        - Data Groups
          - GlobalOrders

**Monitor Panel:**

- Totals Monitor
- Memory Usage History (Graph)
- JVM GC Stats (Graph)
- Table:

Name	Connections	Published	Consumed	Memory (b...	%
/uk/rates	1	32,355.922	32,355.723		0

At the bottom right of the monitor panel is a 'Bar Graph' button.

## Channel Usage

The next section of the Monitor panel displays a table showing multiple columns and rows. This table represents channel usage throughout the realm. Each row in the table represents a channel. Channel usage can be measured a number of ways. Each measurement corresponds to a column within the table. By clicking on one of the column headers, all known channels found within the container will be sorted according to their value for the selected column. For example, one of the


columns is 'Connections', i.e. the number of current consumers on the channel. By clicking on the column header labeled 'Connections', the table will be sorted according to the number of consumers each channel has. The channel with the most number of consumers will appear at the top of the table.

Each column used for channel usage measurements is described below:

- **Connections** - The number of consumers the channel has
- **Published** - The rate of events published per status interval
- **Consumed** - The rate of events consumed per status interval
- **Memory (bytes)** - The number of bytes the channel uses from the JVM memory
- **% Memory** - The percentage of overall JVM memory used by this channel
- **Disk** - The amount of disk space used by this channel, only relevant for persistent / mixed channels

## Monitor Graphs

The monitor panel provides a method of graphing channel usage. It uses a 3D graph package from sourceforge (<http://sourceforge.net/projects/jfreechart/>) to display the items in each table as columns in a 3D vertical bar chart. The bar charts can be update live as the values in the tables are updated. Once a column is selected, simply click on the button labeled 'Bar Graph' under either the channel or connections table and a graph panel will appear, as shown in the image below showing a graph of the number of events published for channels within the container..



Right-clicking anywhere within the graph will show a pop-up menu of options. One of the options is labeled 'Start Live Update', which will ensure the graph consumes updates as and when they occur to the table. Once the live update is started, you can also stop the live update by once again right clicking on the graph and selecting 'Stop Live Update'.

You can also print the graph, and save the graph image as a '.png' file, as well as alter the properties of the graph and its axis.

## Channel Status

### Introduction

Every time a channel object is selected from the namespace, the first panel to be displayed on the right hand side of the Enterprise Manager panel is the 'Status' panel. Configuration information is always displayed at the top section of the Enterprise Manager when a channel is selected. This configuration information shows channel type, ttl (age), capacity as well as any channel key information available. The channel 'Status' tab shows real-time management information for the selected channel.

The status panel is split into 2 main sections. The top section shows real time graphs representing the events published and consumed on the channel, both in terms of rates (i.e. per status interval) as well as the totals.

The bottom section shows the actual values plotted in the graphs for events published and consumed, as well as information about the actual channel store at the server.

The image below shows the status panel for an active cluster channel.

The screenshot shows the Nirvana Enterprise Manager interface. The left pane displays a tree view of the hierarchy: Nirvana Enterprise > Clusters > test > Realms > realm1 > ClusterRates. The main panel is titled 'Summary' and 'Storage Properties'. It contains an 'Attributes' table, a 'Consumed Event History' graph, a 'Published Event History' graph, and a 'Totals' table.

Attributes		ClusterRates	Publish Keys
Name		Transient	
Type		0	
Age		0	
Capacity		0	
Engine		Default	

Totals		Rates		Event
Published	223463508	Published	39606.0	Used
Consumed	223463508	Consumed	39606.0	Events
Event ID	223463507	Connections	0.0	% Fre
Curent Connections	1	Fanout (ms)	0.0	Cache
Total Connections	4			

The top most graph in the panel shows the event history for events consumed from the channel. The red line graphs the rates at which events are being consumed while the yellow line graphs the total events consumed from the channel.

The bottom graph shows the event history for events published to the channel. The red line graphs the rates at which events are being published while the yellow line graphs the total events published

to the channel. As the status events are consumed, and the channel (nLeafNode) is updated with the new values for events consumed and published, the status panel and its graphs will be updated.

The bottom section of the status panel shows 3 types of information: Totals, Rates and Event Store. These are discussed below.

## Totals

The totals section shows 5 values:

- **Published** - The total number of events published to the channel when the last status events was consumed
- **Consumed** - The total number of events consumed from the channel when the last status event was consumed
- **Event ID** - The event id of the last event published to the channel
- **Current Connections** - The current number of consumers on the channel
- **Total Connections** - Total number of subscribers that have subscribed to the channel

## Rates

The rates section shows 3 values:

- **Published** - The current rate of events published to the channel, calculated as  $(\text{total} - \text{previous total}) / (\text{interval } 1000 \text{ milliseconds})$
- **Consumed** - The current rate of events consumed from the channel, calculated as  $(\text{total} - \text{previous total}) / (\text{interval } 1000 \text{ milliseconds})$
- **Connections** - The current rate of subscriptions being made to the channel

## Event Store

The event store section shows 4 values:

- **Used Space** - The amount of space in KB used by the channel on the server (either memory, or disk for persistent / mixed channels)
- **Events** - The current number of events on the channel
- **% Free** - The amount of free space in the channel store (calculated as  $(\text{used space} - (\text{total space used by all purged or aged events}))$ )
- **Cache Hit** - The %age of events consumed from the channel event cache as opposed form the actual physical store if persistent or mixed

## Data Group Status

When you select the 'Data Groups' node from the tree, one of the available panels to select is labeled 'Status' panel.

The Status panel for The 'Data Groups' node contains information regarding the publish and consumed events on Data Groups as well as the number of Data Groups and Data Streams currently connected

The status information shown within this panel is explained below.

The Status panel is split into 2 main sections. The top most section of this panel shows a graph that demonstrates **Event History**

The event history graph shows the rates that events are published (red) and consumed (yellow) across all data groups in the current realm.

This graph is updated every time a status event is received from the realm in which data groups are actively being used. The image below demonstrates the status graphs as described.

The screenshot displays the Nirvana Enterprise Manager interface. On the left, a tree view shows the hierarchy: Nirvana Enterprise > Clusters > test > Realms > realm1 > Data Groups. The 'Data Groups' item is selected. Below the tree, three realms (realm1, realm2, realm3) are listed with their respective components: ClusterRates, Data Groups, GlobalOrders, naming, and uk (with rates under uk).

On the right, the 'Event History' panel is active, showing a real-time graph of event data on a green grid. The graph shows a red line representing the event history, which exhibits a sharp dip followed by a recovery and subsequent fluctuations.

Below the graph, the 'Event Status' section displays the following metrics:

- Total Consumed
- Total Published
- Consumed/Sec
- Published/Sec

The 'Totals' section displays the following metrics:

- Current Groups
- Current Streams
- Total Streams

The bottom section of the panel displays 4 sections of information, **Event Status**, **Totals**, **Connection Status** and **Storage Usage** respectively. These panels and the information displayed are described below.

## Event Status

The Event Status section describes the following :

- **Published** - The total number of events published to all channels, queues and services within the container
- **Consumed** - The total number of events consumed from all channels, queues and services within the container
- **Published/Sec** - The number of events published to all channels, queues and services, per second within the container
- **Consumed/Sec** - The number of events consumed from all channels, queues and services, per second within the container

## Totals

The Totals section describes the following :

- **Realms**- The number of realms mounted within this container
- **Channels**- The number of channels that exist within this container
- **Queues**- The number of queues that exist within this container
- **Services**- Total number of services that exist within this container

## Connection Status

The Connection Status section describes the following :

- **Total** - The total number of connections made to channels, queues and services within this container
- **Current** - The current number of connections made to channels, queues and services within this container
- **Rate** - The number of connections being made per second to channels, queues and services within this container

## Storage Usage (KB)

The Memory Usage section describes 4 values :

- **Total** - The total amount of KB used by channels, queues and services found within this container
- **Free** - The free memory available in the Realm JVM
- **Used** - The amount of memory available in the Realm JVM

- **Change** - The amount of change in Realm JVM memory between newest update and previous update

## Channel Connections

When a Universal Messaging client connects to a Realm Server, the server maintains information on the connection (see [“Connection Information” on page 499](#)) that is available through the Universal Messaging Administration API. The API also provides mechanisms for receiving notification when connections are added and deleted (see the code example "Connection Watch" using the Administration API).

Connection information is also maintained when Universal Messaging clients subscribe to channels. This section guides you through channel connection information.

The Universal Messaging Enterprise Manager allows you to view the connections (channel subscriptions) on a realm and drilldown to view more detailed information about each connection, such as the last event sent or received, and the rate of events sent and received from each connection.

To view connections for a channel, select a channel node from the namespace, and select the 'Connections' tab. This will display a panel containing a table of connections, as shown in the image below.

The screenshot shows the Nirvana Enterprise Manager interface. The left pane displays a tree view of the hierarchy: Nirvana Enterprise > Clusters > test > Realms > realm1 > ClusterRates. The main pane is titled 'Summary' and 'Storage Properties'. The 'Attributes' section shows: Name: ClusterRates, Type: Transient, Age: 0, Capacity: 0, Engine: Default. Below this is a toolbar with buttons for Status, Joins, ACL, Named Objects, Snoop, and Connections. The 'Connections Summary' section contains a table with the following data:

protocol	user	host	connection	su
nsp	subscriber	127.0.0.1	127.0.0.1:49502	
nsp	subscriber	127.0.0.1	127.0.0.1:49518	
nsp	durablesubscriber	127.0.0.1	127.0.0.1:49519	johnsmi

At the bottom of the main pane are buttons for 'Show Details', 'Show List', and 'Bounce'.

Connections have the following attributes:

- **Protocol** - The protocol used in the connection
- **User** - The name of the user connected
- **Host** - The host machine that the user is connecting from
- **Connection** - The local connection id, defined as hostname:local\_port

- **Sub-Name**- The named object (see [“Channel Named Objects” on page 122](#)) reference if one has been provided
- **Filter** - The filter string for the subscription if one has been provided

The highlighted connection above shows that the user has subscribed to the 'ClusterRates' channel using the nsp protocol, to localhost. The user has also provided a named object called 'johnsmith' and a filter of "region='UK'" which will ensure the user only consumes events with the value 'UK' in the 'region' property of the event properties.

When a connection is highlighted, there a number of things that can be shown for a the connection.

Firstly, connections can be disconnected by clicking on the 'Disconnect' button.

Secondly, by double-clicking on a connection from the table, or by clicking on the 'Show Details' button, you are presented with a panel that contains a more detailed look at the activity for the selected connection. The connection details panel is shown in the image below.

The screenshot displays the Nirvana Enterprise Manager interface. On the left is a tree view showing the hierarchy: Nirvana Enterprise > Clusters > test > Realms > realm1 > ClusterRates. The main pane is divided into several sections:

- Attributes:**

Name	ClusterRates
Type	Transient
Age	0
Capacity	0
Engine	Default
- Client Environment:**

Language / Version:	
OS:	
OS Version:	
Build Number:	
Build Date:	
- Connection Details:**

User:	subscriber
Host:	127.0.0.1
Protocol:	nsp
Connection:	realm1
Connection ID:	127.0.0.1:49879
Multicast Enabled:	true
Requested Priority Connection:	false
- Events Sent:**

Total	2014934
Rate	39948.4
Max	45460.2
Last Evt Type	Publish Event
Bytes	350.6 MB
- Events Received:**

Total	3
Rate	0.0
Max	0.0
Last Evt Type	Subscribe
Bytes	110.0

At the bottom, there are buttons for 'Show Details', 'Show List', and 'Bounce'.

## Connection Details

You will see that there are 2 separate information panels above the graphs once you have drilled down into a connection. The first of which is labelled Connection Details. This information contains information about the user connection, such as user name, host protocol.

## Client Environment

Next to this you will see a panel that shows details regarding the client environment for this user. These includes API language / Platform, Host OS and Universal Messaging build number

The two graphs, labeled 'Tx Event History' and 'Rx Event History' show the total (yellow) and rates (red) for events received from the server (TX) and sent to the server (RX) for the selected connection.

The bottom of the connection details panel shows 3 sections of information for the selected connection, 'Events Sent', 'Events Received' and 'Status'. Each of these are described below.

## Events Sent

The Events Sent section shows the following values:

- **Total** - The total number of events sent by the realm server to this connection
- **Rate** - The rate at which events are being sent by the realm server to this connection
- **Max** - The maximum rate at which events have been sent by the realm server to this connection
- **Last Event Type** - The type of the last event sent from the realm server
- **Bytes** - Total bytes sent by the realm server to this connection

## Events Received

The Events Received section shows the following values:

- **Total** - The total number of events sent by this connection to the realm server
- **Rate** - The rate at which events are being sent by connection to the realm server
- **Max** - The maximum rate at which events have been sent by this connection to the realm server
- **Last Event Type** - The type of the last event sent from the connection to the realm server
- **Bytes** - Total bytes sent by this connection to the realm server

## Status

The Events Sent section shows the following values:

- **Connect Time** - The amount of time this connection has been connected to the realm server
- **Queue Size** - The number of events in the outbound queue of this connection (i.e. events waiting to be sent to the realm server)
- **Last Tx** - The time since the last event was received by this connection from the realm server
- **Last Rx** - The time since the last event was sent to the server from this connection

Clicking on the 'Show List' button will take you back to the connections table.

## **Queue Status**

Every time a queue object is selected from the namespace, the first panel to be displayed on the right hand side of the Enterprise Manager panel is the 'Status' panel. Configuration information is always displayed at the top section of the Enterprise Manager when a queue is selected. This configuration information shows queue type, ttl (age) and capacity. The queue 'Status' tab shows real-time management information for the selected queue.

The status panel is split into 2 main sections. The top section shows real time graphs representing the events pushed and popped from the queue, both in terms of rates (i.e. per status interval) as well as the totals.

The bottom section shows the actual values plotted in the graphs for events pushed and popped, as well as information about the actual queue store at the server.

The image below shows the status panel for an active cluster queue.

The screenshot shows the Nirvana Enterprise Manager interface. On the left is a tree view of the system structure:

- Nirvana Enterprise
  - Clusters
    - test
  - Realms
    - realm1
      - ClusterRates
      - Data Groups
      - uk
      - GlobalOrders
      - naming
    - realm2
      - ClusterRates
      - Data Groups
      - GlobalOrders
      - naming
    - realm3
      - ClusterRates
      - Data Groups
      - GlobalOrders
      - naming

The right-hand panel is titled "Summary" and "Storage Properties". It contains the following sections:

- Attributes:** Name, Type, Age, Capacity, Engine.
- Navigation:** Status, Joins, ACL, Snoop.
- Consumed Event History:** A line graph showing event history for events popped from the queue. It features a red line for rates and a yellow line for total events.
- Published Event History:** A line graph showing event history for events pushed onto the queue. It features a red line for rates and a yellow line for total events.
- Totals and Rates Summary Table:**

Totals		Rates		Event
Pushed	1040480	Pushed	4965.9	Used
Popped	966487	Popped	4980.3	Event
Event ID	1040479	Connections	4.1	% Fr
Curent Connections	0	Fanout (ms)	0.0	Cach
Total Connections	763			

The top most graph in the panel shows the event history for events popped from the queue. The red line graphs the rates at which events are being popped while the yellow line graphs the total events popped from the queue.

The bottom graph shows the event history for events pushed onto the queue. The red line graphs the rates at which events are being pushed while the yellow line graphs the total events pushed

to the queue. As the status events are consumed, and the queue `nLeafNode ()` is updated with the new values for events popped and pushed, the status panel and its graphs will be updated.

The bottom section of the status panel shows 3 types of information : Totals, Rates and Event Store. These are discussed below.

## Totals

The totals section contains the following values:

- **Published** - The total number of events pushed to the queue when the last status event was consumed
- **Consumed** - The total number of events popped from the queue when the last status event was consumed
- **Event ID** - The event id of the last event pushed to the queue
- **Current Connections** - The current number of asynchronous consumers on the queue
- **Total Connections** - Total number of asynchronous consumers that have subscribed to the queue

## Rates

The rates section contains the following values:

- **Published** - The current rate of events pushed to the queue, calculated as  $(\text{total} - \text{previous total}) / (\text{interval } 1000 \text{ milliseconds})$
- **Consumed** - The current rate of events popped from the queue, calculated as  $(\text{total} - \text{previous total}) / (\text{interval } 1000 \text{ milliseconds})$
- **Connections** - The current rate of asynchronous subscriptions being made to the queue

## Event Store

The event store section contains the following values:

- **Used Space** - The amount of space in KB used by the queue on the server (either memory, or disk for persistent / mixed queues)
- **Events** - The current number of events on the queue
- **% Free** - The amount of free space in the queue store (calculated as  $(\text{used space} - (\text{total space used by all purged or aged events}))$ )
- **Cache Hit** - The %age of events popped from the queue event cache as opposed form the actual physical store if persistent or mixed

## Interface Status

Universal Messaging interfaces (see [“TCP Interfaces, IP Multicast and Shared Memory”](#) on page 223) allow users to connect to a Realm using various protocols and ports on specific physical Network interfaces on the host machine. Interfaces are also available to users through the Universal Messaging Administration API and can provide useful status information regarding user connections.

The Enterprise manager provides a summary of this status information for each interface. This section will describe the status information available for each interface.

To view status information for an interface, you must first select the 'Comms' tab for the Realm you want to view. This tab contains the interface configurations as well as Multicast and Shared Memory configurations. Select the interface you wish to view from the list of interfaces in the 'Interfaces'. By selecting the desired interface, you will be presented with a number of panels, one of which is labeled 'Status'. This panel is shown in the image below.

The screenshot shows the Nirvana Enterprise Manager interface. The left sidebar displays a tree view of the configuration, including Clusters (test) and Realms (realm1, realm2, realm3). The main panel is titled 'Interfaces' and shows the status of the 'nhp0' interface. The interface is currently 'Running' on adapter '0.0.0.0'. Below the interface status, there is a 'Details' section with the following metrics:

Metric	Value
Idle Threads	1
Total Connections	36
Total Failed	0
Ave Authorisation	0ms
Pool Exhausted Count	0
Ave Pool Wait	0
Mb Written / Second	0
Mb Read / Second	0
Total MB Written	0
Total MB Read	0

To the right of the details is a 'Connections' grid, which is currently empty. At the bottom of the interface status panel, there are buttons for 'Add Interface', 'Delete Interface', and 'Apply'.

The interface status panel has a section that describes the details of the interface status information. The status information contains 6 values, each of which is described below.

## Details Panel

- **Idle Threads**- The number of idle threads, calculated as the total threads from the interface accept threads pool - the number of threads from the pool currently accepting connections. Corresponds to available threads
- **Total Connections** - The total number of successful connections made to this interface
- **Total Failed** - The total number of failed connection attempts made to this interface
- **Ave Authorisation** - The average time it takes a connection to authenticate with the realm server
- **Pool Exhausted Count** - The number of times that the interface thread pool has had no threads left to service incoming connection requests. When this count increases, you should increase the number of accept threads (see [“Interface Configuration” on page 229](#)) for the interface
- **Ave Pool Wait** - The average time that a client connection has to wait for the accept thread pool to provide an available thread. Like the Pool Exhausted count, this is a good indicator that the number of accept threads for an interface is too low and needs to be increased

The status panel also shows 2 graphs that depict connection attempts (successful connections are shown in yellow, failed connection attempts are shown in red) and authentication times (average authentication times are shown in yellow, and the last authentication time is shown in red).


## Scheduler view

Universal Messaging Enterprise Manager allows managing, deploying and editing server side scripts for execution in the Universal Messaging scheduler. The scripts consist of initial tasks, triggered tasks and / or calendar tasks as illustrated in the following sections.

- [“Adding Scheduler Scripts” on page 364](#)
- [“Editing Scheduler Scripts” on page 365](#)
- [“Scheduler Script Initial Tasks” on page 366](#)
- [“Scheduler Script Triggered Tasks” on page 367](#)
- [“Scheduler Scripts Calendar Tasks” on page 368](#)

## Adding Scheduler Scripts

The Universal Messaging Enterprise Manager allows deployment of scheduler scripts that execute on the Universal Messaging realm's scheduler. The editor features syntax highlighting to facilitate script editing.



## Editing Scheduler Scripts

The Universal Messaging Enterprise Manager allows viewing and editing of scripts that are already deployed on the realm from any location.

Software AG - webMethods / Nirvana Enterprise Manager

File Connections Cluster Help

Nirvana Enterprise

- Clusters
  - test
- Realms
  - realm1
    - ClusterRates
    - Data Groups
    - GlobalOrders
    - naming
    - uk
    - GlobalOrderStatus
  - realm2
    - ClusterRates
    - Data Groups
    - GlobalOrders
    - naming
      - defaultContext
    - GlobalOrderStatus
  - realm3
    - ClusterRates
    - Data Groups
    - GlobalOrders
    - naming
    - GlobalOrderStatus

Realm Details

Name:  
Threads:  
Realm UpTime:  
Last Update: Tue Jul

Status Monitoring ACL Comms Nirvana Realms Config Scheduler

Name	Runtime Subject	Cluster
s	administrator@*	

Add New Delete

Script Editor Initial Tasks Triggered Tasks Calendar Tasks

```

/*
This is an example scheduler script
*/
scheduler realmSchedule {

    declare Config myGlobalConfig ("GlobalValues");
    declare Config myAuditConfig ("AuditSettings");
    declare Config myTransConfig ("TransactionManager");

    initialise {

        Logger.report("Realm optimisation script and monitor startup initialising");
        myAuditConfig.ChannelACL("false");
        myAuditConfig.ChannelFailure("false");
        myGlobalConfig.MaxBufferSize(2000000);
        myGlobalConfig.StatusBroadcast(2000);
        myGlobalConfig.StatusUpdateTime(86400000);
        myTransConfig.MaxTransactionTime(3600000);
        Logger.setLevel(4);
    }
}

```

Apply Changes Undo Changes

## Scheduler Script Initial Tasks

Each scheduler script has an initialisation section that allows variable definition as well as execution of tasks such as realm configuration changes, custom log messages, interface configuration etc. These can be viewed after they are parsed and validated from the Enterprise Manager.

The screenshot shows the Nirvana Enterprise Manager interface. On the left, a tree view shows the hierarchy: Nirvana Enterprise > Clusters > test > Realms > realm1. The right pane displays the configuration for 'realm1'.

**Realm Details:**

- Name:
- Threads:
- Realm UpTime:
- Last Update:

**Navigation:** Status, Monitoring, ACL, Comms, Nirvana Realms, Config, Scheduler

**Table 1: Runtime Subject**

Name	Runtime Subject
s	administrator@*

**Buttons:** Add New

**Navigation:** Script Editor, Initial Tasks, Triggered Tasks, Calendar Tasks


**Table 2: Triggered Tasks**

Task	Function / Object	
Logger	report	Realm optim
Config	AuditSettings.ChannelACL	false
Config	AuditSettings.ChannelFailure	false
Config	GlobalValues.MaxBufferSize	2000000
Config	GlobalValues.StatusBroadcast	2000
Config	GlobalValues.StatusUpdateTime	86400000
Config	TransactionManager.MaxTransactionTime	3600000
Logger	setlevel	4

**Buttons:** Apply Changes, Undo

## Scheduler Scripts Triggered Tasks

Each scheduler script can optionally contain a triggered tasks section. Triggered tasks are tasks that are executed when certain conditions are met during the operation of the Universal Messaging realm. For example the image below shows a triggered tasks that is executed if the realm log level is set to 0 (very verbose) which results to a custom log message as well as setting the log level to 1.



### Scheduler Scripts Calendar Tasks

Each scheduler script can optionally have a calendar tasks section. Calendar tasks are triggered by calendar events as defined in the scheduler script. The Enterprise Manager image below shows a calendar tasks that writes a custom log message every 30 minutes of every hour, of every day or month.

Software AG - webMethods / Nirvana Enterprise Manager

File Connections Cluster Help

Nirvana Enterprise

- Clusters
  - test
    - Realms
      - realm1
        - ClusterRates
        - Data Groups
        - GlobalOrders
        - naming
        - uk
        - GlobalOrderStatus
      - realm2
        - ClusterRates
        - Data Groups
        - GlobalOrders
        - naming
          - defaultContext
        - GlobalOrderStatus
      - realm3
        - ClusterRates
        - Data Groups
        - GlobalOrders
        - naming
        - GlobalOrderStatus

Realm Details

Name:

Threads:

Realm UpTime:

Last Update:

Status Monitoring ACL Comms Nirvana Realms Config Schedule

Name	Runtime Subject
s	administrator@*

Add New

Script Editor Initial Tasks Triggered Tasks Calendar Tasks

Occu...	Time	Mo	Tu	We	Th	Fr	Sa	Su
Hourly	xx:30	✓	✓	✓	✓	✓	✓	
Daily	18:00	✓	✓	✓	✓	✓	✓	
Weekly	17:30			✓				
Monthly	21:00							
Yearly	00:00							

Scheduled for wednesdays

Task	Function / Object
Logger	report

Apply Changes Undo

## Channel view

Universal Messaging Enterprise Manager allows monitoring, administration and configuration of every aspect of a Universal Messaging channel, as illustrated in the following sections.

- [“Channel Status” on page 370](#)
- [“Channel Access Control List \(ACL\)” on page 371](#)

- [“Channel Joins” on page 372](#)
- [“Channel Connections” on page 373](#)
- [“Channel Named Objects” on page 374](#)
- [“Channel Event Snooping” on page 375](#)

For more information on these screens please see the Management Information section.

## **Channel Status**

The Universal Messaging Enterprise Manager allows monitoring of a channel's status in terms of publish & consume event totals / rates as well as connection total / rates and persistent store / memory.

Software AG - webMethods / Nirvana Enterprise Manager

File Connections Cluster Help

Nirvana Enterprise

- Clusters
  - test
- Realms
  - realm1
    - ClusterRates
    - Data Groups
    - GlobalOrders
    - uk
      - rates
  - realm2
    - ClusterRates
    - Data Groups
    - GlobalOrders
  - realm3
    - ClusterRates
    - Data Groups
    - GlobalOrders

Summary Storage Properties

Attributes

Name	ClusterRates	Publish Keys
Type	Transient	
Age	0	
Capacity	0	
Engine	Default	

Status Joins ACL Named Objects Snoop Connections


Consumed Event History

Published Event History

Totals		Rates		Event
Published	223463508	Published	39606.0	Used
Consumed	223463508	Consumed	39606.0	Events
Event ID	223463507	Connections	0.0	% Fre
Curent Connections	1	Fanout (ms)	0.0	Cache
Total Connections	4			

## Channel Access Control List (ACL)

Universal Messaging offers complete control over security policies. Universal Messaging stores security policies locally or can be driven by any external entitlements service. Universal Messaging's rich set of entitlements ensure that everything from a network connection through to a channel/queue creation can be controlled on a per user and/or host basis. For more information please see the Universal Messaging ACL's FAQ.



## Channel Joins

Universal Messaging allows channels to be joined to other channels or queues creating server side routing tables with the possibility to apply filters based on message content on the local or a remote Universal Messaging realm.


The screenshot shows the Nirvana Enterprise Manager interface. The left pane displays a tree view of the hierarchy: Nirvana Enterprise > Realms > nirvana > Data Groups > channel1. The right pane shows the 'Join Routing Table' for the selected 'rates' object. The table has the following data:

Type	Remote Node	Filtered	Hop Count	Event Id
Incoming	/local/rates	True	4	0

Below the table is an 'Add Join' button.


## Channel Connections

Channel subscribers are reported as channel connections and can be monitored / managed through the Universal Messaging Enterprise Manager.




### Channel Named Objects

Channel subscribers can manage their subscription's event id manually or they can become a named subscriber and let that be managed by the Universal Messaging realm. The Universal Messaging Enterprise Manager allows complete management of channel named objects.



## Channel Event Snooping

The Universal Messaging Enterprise Manager provides the ability to inspect the contents of messages remotely using the Snoop panel.



## Queue view

Universal Messaging Enterprise Manager allows monitoring, administration and configuration of every aspect of a Universal Messaging queue, as illustrated in the following sections.

- [“Queue Status” on page 377](#)
- [“Queue Access Control List \(ACL\)” on page 378](#)
- [“Queue Joins” on page 379](#)
- [“Queue Event Snooping” on page 379](#)

For more information on these screens please see the Management Information section.

## Queue Status


The Universal Messaging Enterprise Manager allows monitoring of a queue's status in terms of publish & consume event totals / rates as well as connection total / rates and persistent store / memory.

The screenshot shows the Universal Messaging Enterprise Manager interface. The left pane displays a tree view of the hierarchy: Nirvana Enterprise > Clusters > test > Realms > realm1 > GlobalOrders. The right pane shows the 'Summary' tab for the selected queue. The 'Attributes' section lists Name, Type, Age, Capacity, and Engine. Below this are tabs for Status, Joins, ACL, and Snoop. The 'Consumed Event History' and 'Published Event History' sections are currently empty. At the bottom, a table displays statistics for 'Totals' and 'Rates'.

Totals		Rates	
Pushed	1040480	Pushed	4965
Popped	966487	Popped	4980
Event ID	1040479	Connections	4
Current Connections	0	Fanout (ms)	0
Total Connections	763		

## Queue Access Control List (ACL)

Universal Messaging offers complete control over security policies. Universal Messaging stores security policies locally or be driven by any external entitlements service. Universal Messaging's rich set of entitlements ensure that everything from a network connection through to a channel/queue creation can be controlled on a per user and/or host basis. For more information please see the Universal Messaging ACL's FAQ.



## Queue Joins

Universal Messaging allows channels to be joined to other channels or queues creating server side routing tables with the possibility to apply filters based on message content on the local or a remote Universal Messaging realm.

The screenshot displays the Nirvana Enterprise Manager interface. The left pane shows a tree view of the system hierarchy under 'Nirvana Enterprise' > 'Realms' > 'nirvana'. The right pane shows the configuration for a 'Join'.


**Join Routing Table**

Type	Remote Node	Filtered	Hop Count	Event Id	Allow Purge
Incoming	/ClusterRates	False	9	0	False

At the bottom of the interface, there are buttons for 'Add New Join' and 'Delete Join'.

## Queue Event Snooping

The Universal Messaging Enterprise Manager provides the ability to inspect the contents of messages remotely using the Snoop panel.



## Using the Enterprise Viewer

The Enterprise Viewer is a read-only version of the Enterprise Manager. Its purpose is to allow clients to view the Universal Messaging environment without the need for special administration rights.

Basically, it offers the same views as the Enterprise Manager, but you cannot use it to modify your Universal Messaging environment in any way. This means, for example, that you cannot create or delete channels and queues, and you cannot publish any events.

## Starting the Enterprise Viewer

### Windows platforms

Windows users can start the Enterprise Viewer by selecting the appropriate component from the Universal Messaging group in the Windows Start menu.

You can also type a command of the following form on the command line:

```
<UM_install_dir>\java\<UM_server_name>\bin\nterpriseview.exe
```

where *<UM\_install\_dir>* is the installation root location and *<UM\_server\_name>* is the name of the Universal Messaging server.

### UNIX / Linux platforms

You can launch the Enterprise Viewer on Unix / Linux platforms by starting the `nterpriseview` executable, which you can find at the following location:

```
<UM_install_dir>/java/umserver/bin/nterpriseview
```



# 3 Using Command Central to Manage Universal Messaging

---

■ Managing Universal Messaging using Command Central .....	384
■ Securing Access to Command Central .....	384
■ Instance Management .....	386
■ Authentication Configuration .....	387
■ Universal Messaging Configuration Types .....	388
■ Universal Messaging Logs .....	412
■ Universal Messaging Administration Types .....	412
■ Universal Messaging Inventory .....	416
■ Universal Messaging Lifecycle Actions .....	416
■ Universal Messaging KPIs .....	416
■ Universal Messaging Run-time Monitoring Statuses .....	417
■ Universal Messaging and the Command Line Interface .....	418
■ Universal Messaging Commands .....	419

## Managing Universal Messaging using Command Central

---

You can configure and administer Universal Messaging server instances using the Command Central web or command-line interface.

Command Central uses one of the Universal Messaging ports (interfaces) for configuration and administration. Command Central checks the ports (interfaces) of a Universal Messaging server instance in the following order and chooses the first available port (interface) to connect to the server:

1. Interfaces that use HTTP protocol (nhp)
2. Interfaces that use socket protocol (nsp)
3. Interfaces that use HTTPS protocol (nhps)
4. Interfaces that use SSL protocol (nsp)

**Note:**

Command Central will use a secured port (nhps and nsp) to connect with a Universal Messaging server instance only if the client-side certificates are not required for establishing the connection. Command Central does not use ports that use shared memory protocol (shm).

If there is a disconnection between Command Central and the Universal Messaging server, Command Central will connect to a new port using the same order used to check the next available port for communicating with the Universal Messaging server.

## Securing Access to Command Central

---

Secure access to Command Central by performing one or more of the following tasks:

### Changing the Authentication Mode

1. Click the Instances tab to view all the available Universal Messaging server instances.
2. Click an Universal Messaging instance name to access the Dashboard.

The Dashboard contains information about the specific Universal Messaging server instance such as status, alerts, and KPIs.

3. In the Details section of the Dashboard, click  in the **Authentication** field to change the authentication mode.

The **Authentication Mode** dialog box appears.

4. Select one of the following authentication modes:
  - **System default:** Use default authentication method.

- **None:** No authentication method is used.
- **Trusted:** Password-less authentication for predefined administrative user account.
- **Delegated:** SAML-based authentication and authorization for the currently logged in user.
- **Fixed user:** Authenticate the specified administrative user credentials. Provide a user name and password for the user.

**Note:**

To use basic authentication, you must change the authentication mode for a run-time component to **Fixed User**. Command Central uses basic authentication with a fixed user to communicate with Platform Manager. With **Fixed User** authentication, the authentication credentials for the Platform Manager will be fixed.

## Verifying the Outbound Authentication Settings

Use the following steps to verify that Command Central is configured with the correct outbound authentication settings.

### ➤ To verify that Command Central is configured with the correct user credentials

1. In Command Central, on the Overview tab for the product component, click . Check that the product status is **Online** and the JVM KPIs are updated.
2. On the Logs tab, check the product log for authentication errors.

## Using Unix Shell Scripts to Change Connection Credentials for Managed Products

You can use the following sample Unix shell script to configure basic authentication credentials for product components managed by Command Central.

```

NODE_ALIAS=local
USERNAME=Administrator
PASSWORD=secret
RCID=integrationServer-default
# RCID=MwsProgramFiles-default
# RCID=Universal-Messaging-nirvana
# RCID=OSGI-CTP
# RCID=OSGI-InfraDC

sagcc get configuration data $NODE_ALIAS $RCID COMMON-LOCAL-USERS-Administrator

-o administrator.xml
sed "s,/>, ><Password>${PASSWORD}</Password></User>,g" administrator.xml >
  administrator_new.xml
sagcc update configuration data $NODE_ALIAS $RCID COMMON-LOCAL-USERS
-Administrator -o administrator_new.xml

```

```
# verify connection
sagcc get monitoring runtimestatus $NODE_ALIAS $RCID -e ONLINE
```

## Instance Management

You can create and delete Universal Messaging server instances using Command Central web or command-line interface.

### Creating an Instance

#### > To create an instance

1. In the **Environments** pane, select the environment in which you want to create the new product instance.
2. Click the **Installations** tab.
3. Select the installation by clicking the installation name in the table.
4. Click the **Instances** tab.
5. Click , and select **Universal Messaging Server**.
6. Specify the following instance properties:

Property	Description
<b>Instance name</b>	Required. Name of the new Universal Messaging server instance. Case-insensitive and can include upper and lower case alphabetic characters, digits (0-9), underscores (_), and non-leading hyphens (-).
<b>NHP interface binding</b>	Specific host or IP address to bind. The instance will bind to all available interfaces if this field is left blank.
<b>NHP interface port</b>	Port number for the Universal Messaging server instance.
<b>Data directory</b>	Absolute path to the data directory of the Universal Messaging server instance. Default path " <i>install directory/UniversalMessaging/server/instance name</i> " is used if this field is left blank.

Property	Description
<b>License file</b>	The registered Universal Messaging license file. Select one of the registered license files from the list.
<b>Configuration profile</b>	Initial configuration settings for the Universal Messaging server instance. Options: <b>webMethods suite use cases</b> , <b>Standalone use cases</b> , and <b>Custom</b> .
<b>Custom configuration file</b>	Required if the <b>Custom</b> option is chosen as the configuration profile. Click <b>Browse</b> , and select the custom profile XML file.

- Click **Next**, and then click **Finish**.

## Deleting an Instance

### > To delete an instance

- In the **Environments** pane, select the environment in which you want to create the new product instance.
- Click the **Instances** tab.
- Select the Universal Messaging instance to be deleted and then click .
- Click **Ok** to confirm deletion and then click **Finish**.

## Authentication Configuration

Perform the following steps to enable basic authentication for Universal Messaging server instance users.

- Enable basic authentication in the Universal Messaging server instance. For information about security and authentication in Universal Messaging, see the Universal Messaging Concepts guide.
- Use the user management feature of Command Central to add users to the user.txt file of the Universal Messaging server instance.
- Use Universal Messaging Enterprise Manager to set the required ACLs for the Universal Messaging server instance users.
- Restart the Universal Messaging server instance, if required.

5. Change the default Authentication Mode from **None** to **Fixed User** and provide a new user name and password.

## Universal Messaging Configuration Types

---

You can configure the following configuration types for a Universal Messaging server instance:

- Internal Users
- Licenses
- Ports
- Memory
- Realm ACL
- Groups
- Properties
- JNDI Connection Factories
- JNDI Destinations
- Channels
- Queues
- Zone
- Java System Properties
- Clustering

## Working with Universal Messaging Configuration Types

Perform the following steps to add, edit, or delete Universal Messaging configuration type items in the Command Central web user interface.

**Note:**

The Universal Messaging server instance must be running during configuration.

➤ **To add, edit, or delete an item for an Universal Messaging configuration type**

1. Select the Universal Messaging environment from the **Environment** pane, then click the instance from the **Instances** tab.
2. Click the **Configuration** tab.
3. Select the configuration type from the drop-down list.

Universal Messaging displays the available or default values for the selected Universal Messaging configuration type.

4. To add an item for the Universal Messaging configuration type, click . Enter the required values, and click **Save**.
5. To edit an item for a configuration type, click on the item that you want to update and then click **Edit**. Make the necessary changes and click one of the following:
  - **Test** to test the configuration type item.
  - **Save** to save your changes.
  - **Cancel** to cancel the edits to the configuration type item.
6. To delete an item for a configuration instance, click .

## User Management

You can add new users, list existing users, change the password of an user, or delete a user from the user repository.

Information to authenticate the users of a Universal Messaging server instance is stored in the user repository (users.txt file) of the Universal Messaging server instance. The users.txt file is generated only after you create a new internal user. The default path to the user repository (users.txt file) of a Universal Messaging server instance is *Software AG\_directory \UniversalMessaging\server\umserver\_instance*, where *umserver\_instance* is the name of the Universal Messaging server instance.

The path to the users.txt file is specified in the Server\_Common.conf file of the server instance irrespective of whether you are running the Universal Messaging server instance as a service or as an application. If you specify a relative path, the users.txt file will be created in a directory relative to the bin directory of the Universal Messaging server instance.

You can also use the command line interface commands or internaluserrepo.bat/sh script to configure users of a Universal Messaging server instance. For more information, see *Software AG Command Central and Software AG Platform Manager Command Reference*.

## License Management

For a Universal Messaging server, you can configure the license, view the details of the license that is configured, and retrieve the location of the license file.

### Note:

You cannot change the location of a Universal Messaging license file.

## Ports Configuration

You can view, create, enable, disable, or edit the following Universal Messaging server ports (interfaces):

- NSP
- NHP
- NHPS
- NSPS

Command Central web user interface displays a table containing a list of ports for a Universal Messaging server instance. The following basic attributes of a port are displayed in the table:

Column	Description
Enabled	Displays if a port is enabled or disabled.
Alias	Each interface is associated with an alias that is used to recognize the port. Each port (interface) on a Universal Messaging server instance will have an associated alias.
Port	Port number. The port number is unique.
Protocol	Type of the port (interface). The port uses one of the following protocols: <ul style="list-style-type: none"> <li>■ NSP (Socket protocol)</li> <li>■ NHP (HTTP protocol)</li> <li>■ NHPS (HTTPS protocol)</li> <li>■ NSPS (SSL protocol)</li> </ul>
Type	Type of port. For example, STANDARD, DIAGNOSTIC.

### Note:

Command Central does not use or report the Universal Messaging server ports that use the shared memory protocol (shm).

### Configure NSP

1. Click , and select **NSP**.
2. Configure the following properties:

Configure this...	To...
Enabled	Enable or disable this NSP port (interface).
Adapter alias	Provide an alias for the port. Each Universal Messaging server instance can have an associated alias in the form of <i>host:port</i> . This alias is used to inform other servers how to contact this server, if this server is behind a NAT or a Proxy Server. This alias is not the same as the Universal Messaging assigned interface alias.
Number	Required. Provide a unique port number. The port number should be unique and cannot be used again in a Universal Messaging server instance.
Backlog	Provide the size of the Internet Protocol (IP) socket queue.
Bind address	The IP address to which to bind this port, if your machine has multiple IP addresses and you want the port to use this specific address.  You cannot change this attribute after you create the port.
Autostart interface	Automatically start this port when starting the Universal Messaging server instance.
Advertise interface	Allow the Universal Messaging server instance to send information about this port to the client.
Allow for inter-realm	Allow port communication between two or more Universal Messaging server instances. For example, allow communication between clusters, or joins.
Allow client connections	Allow clients to connect to this port.
Enable NIO	Enable NIO (Network Input/Output) on this port.
Enable policy server	Allow the ports to respond to policy requests. You can run a policy file server on a socket interface that will automatically handle these requests. Once this is set up, you will also need to set up a client access policy in the <code>clientaccesspolicy.xml</code> file in the <code>/install/server/name/plugins/htdocs</code> directory of the server.
Auth time	Provide the time in milliseconds (ms) that the Universal Messaging server instance waits for the client to complete the authentication process. Default is 10000 milliseconds.
Accept threads	Provide the number of threads processing the accepted sockets.
Select threads	Provide the number of threads allocated for selection.
Send buffer size	Provide the size of the socket send buffer.
Receive buffer size	Provide the size of the socket receive buffer.

For more information about the basic port properties, see [“Interface Configuration” on page 229](#).

3. Click **Test** to validate the entered information or click **Save** to save changes to the port.

## Configure NHP

1. Click , and select **NHP**.
2. Configure the following properties:

### Connection Basics

Configure this...	To...
Enabled	Enable or disable this NHP port (interface).
Adapter alias	Specify an alias for the port. Each interface on a Universal Messaging server instance can have an associated alias in the format <i>host:port</i> . This alias is used to tell other servers how to contact this server, if this server is behind a NAT or a Proxy Server. This alias is not the same as the Universal Messaging assigned interface alias.
Number	Required. Set port number. The port number should be unique and cannot be used again in a Universal Messaging server instance.
Backlog	Provide the size of the Internet Protocol (IP) socket queue.
Bind address	The IP address to which to bind this port, if your machine has multiple IP addresses and you want the port to use this specific address.  You cannot change this attribute after you create the port.
Autostart interface	Automatically start this port when starting the Universal Messaging server instance.
Advertise interface	Allow the Universal Messaging server instance to send information about this port to the client.
Allow for inter-realm	Allow port communication between two or more Universal Messaging server instances. For example, allow communication between clusters, or joins.
Allow client connections	Allow clients to connect to this port.
Enable NIO	Enable NIO (Network Input/Output) on this port.
Enable HTTP 1.1	Enable the usage of HTTP 1.1 protocol on this port.

Configure this...	To...
Auth time	Provide the time in milliseconds (ms) that the Universal Messaging server instance waits for the client to complete the authentication process. Default is 10000 milliseconds.
Accept threads	Provide the number of threads processing the accepted sockets.
Select threads	Provide the number of threads allocated for selection.
Send buffer size	Provide the size of the socket send buffer.
Receive buffer size	Provide the size of the socket receive buffer.

For more information about the basic port properties, see [“Interface Configuration” on page 229](#).

### JavaScript Interface Properties

Set these properties to configure communication with web clients using JavaScript. For more information and description about the JavaScript interface properties, see [“JavaScript Interface Panel” on page 232](#).

Configure this...	To...
Enable JavaScript	Allow JavaScript client connections using this port (interface).
Enable WebSockets	Toggle the ability for clients to communicate with the server using the HTML WebSocket Protocol on this interface.
Enable GZIP for long poll	Enable GZIP compression on HTTP long poll connections.
CORS allow credentials	Allow Cross-Origin Resource Sharing (CORS) credentials.
CORS allowed origins	A comma separated list of the host names (and IP addresses, if they appear in URLs) of the servers that host your JavaScript application's HTML files.
	<p><b>Important:</b> If this property is not set correctly, many communication drivers available to JavaScript clients may fail.</p>
Long poll active delay	The time between clients sending long poll requests to the server in milliseconds. Reducing this may reduce latency but will increase both client and server memory, CPU, and network usage.
GZIP minimum threshold	Set the minimum message size in bytes required for the server to begin compressing data sent to long poll clients.
Long poll idle delay	The time between clients sending long poll when the client is in idle mode.

### Custom Headers

Custom headers are paired with Header Key/Value pairs which are sent in the HTTP packets to the client.

3. Click **Test** to validate the entered information or click **Save** to save changes to the port.

## Configure NHPS

1. Click , and select **NHPS**.
2. Configure the following properties:

### Connection Basics

Configure this...	To...
Enabled	Enable or disable this NHPS port (interface).
Adapter alias	Provide an alias for the port. Each Universal Messaging server instance can have an associated alias in the form of <i>host:port</i> . This alias is used to tell other servers how to contact this server, if this server is behind a NAT or a Proxy Server. This alias is not the same as the Universal Messaging assigned interface alias.
Number	Required. Set port number. The port number should be unique and cannot be used again in a Universal Messaging server instance.
Backlog	Set the size of the Internet Protocol (IP) socket queue.
Bind address	The IP address to which to bind this port, if your machine has multiple IP addresses and you want the port to use this specific address.  You cannot change this attribute after you create the port.
Autostart interface	Automatically start this port when starting the Universal Messaging server instance.
Advertise interface	Allow the Universal Messaging server instance to send information about this port to the client.
Allow for inter-realm	Allow port communication between two or more Universal Messaging server instances. For example, allow communication between clusters, or joins.
Allow client connections	Allow clients to connect to this port.
Enable NIO	Enable NIO (Network Input/Output) on this port.
Enable HTTP 1.1	Enable the usage of HTTP 1.1 protocol on this port.

Configure this...	To...
Auth time	Provide the time in milliseconds (ms) that the Universal Messaging server instance waits for the client to complete the authentication process. Default is 10000 milliseconds.
Accept threads	Provide the number of threads processing the accepted sockets.
Select threads	Provide the number of threads allocated for selection.
Send buffer size	Provide the size of the socket send buffer.
Receive buffer size	Provide the size of the socket receive buffer.

For more information about the basic port properties, see [“Interface Configuration” on page 229](#).

### JavaScript Interface Properties

Set these properties to configure communication with web clients using JavaScript. For more information and description about the JavaScript interface properties, see [“JavaScript Interface Panel” on page 232](#).

Configure this...	To...
Enable JavaScript	Allow JavaScript client connections using this port (interface).
Enable WebSockets	Toggle the ability for clients to communicate with the server using the HTML WebSocket Protocol on this interface.
Enable GZIP for long poll	Enable GZIP compression on HTTP long poll connections.
CORS allow credentials	Allow Cross-Origin Resource Sharing (CORS) credentials.
CORS allowed origins	A comma separated list of the host names (and IP addresses, if they appear in URLs) of the servers that host your JavaScript application's HTML files.
	<p><b>Important:</b> If this property is not set correctly, many communication drivers available to JavaScript clients may fail.</p>
Long poll active delay	The time between clients sending long poll requests to the server in milliseconds. Reducing this may reduce latency but will increase both client and server memory, CPU, and network usage.
GZIP minimum threshold	Set the minimum message size in bytes required for the server to begin compressing data sent to long poll clients.
Long poll idle delay	The time between clients sending long poll when the client is in idle mode.

### Custom Headers

Custom headers are paired with Header Key/Value pairs which are sent in the HTTP packets to the client.

### Security Configuration

Configure this...	To specify...
Client authentication	Whether or not Universal Messaging requires client certificates for all requests. Select: <ul style="list-style-type: none"><li>■ <b>None</b> if Universal Messaging does not require client certificates for all requests.</li><li>■ <b>REQUIRE_CERTIFICATE</b> if you want Universal Messaging to require client certificates for all requests.</li></ul>
SSL enabled	Whether the port is SSL enabled or not. This attribute is always set to true for nhps and nsps port.
Keystore type	File type of the keystore file. Universal Messaging supports only the JKS file type.
Keystore server location	Location of the keystore file.
Keystore password	Password required to access the SSL certificate in the keystore file.
Keystore key password	Password required to access a specific private key in the keystore file.
Truststore type	File type of the truststore file. Universal Messaging supports only the JKS file type.
Truststore server location	Location of the truststore file.
Truststore password	Password required to access the SSL certificate in the truststore file.

3. Click **Test** to validate the entered information or click **Save** to save changes to the port.

### Configure NSPS

1. Click , and select **NSPS**.
2. Configure the following properties:

#### Connection Basics

Configure this...	To...
Enabled	Enable or disable this NSPS port (interface).
Adapter alias	Provide an alias for the port. Each Universal Messaging server instance can have an associated alias in the form of <i>host:port</i> . This alias is used to tell other servers how to contact this server if this server is behind a NAT or a Proxy Server. This alias is not the same as the Universal Messaging assigned interface alias.
Number	Required. Set port number. The port number should be unique and cannot be used again in a Universal Messaging server instance.
Backlog	Set the size of the Internet Protocol (IP) socket queue.
Bind address	The IP address to which to bind this port, if your machine has multiple IP addresses and you want the port to use this specific address.  You cannot change this attribute after you create the port.
Autostart interface	Automatically start this port when starting the Universal Messaging server instance.
Advertise interface	Allow the Universal Messaging server instance to send information about this port to the client.
Allow for inter-realm	Allow port communication between two or more Universal Messaging server instances. For example, allow communication between clusters, or joins.
Allow client connections	Allow clients to connect to this port.
Enable NIO	Enable NIO (Network Input/Output) on this port.
Enable policy server	Allow the ports to respond to policy requests. You can run a policy file server on a socket interface that will automatically handle these requests. Once this is set up, you will also need to set up a client access policy in the <code>clientaccesspolicy.xml</code> file in the <code>/install/server/name/plugins/htdocs</code> directory of the server.
Auth time	Provide the time in milliseconds (ms) that the Universal Messaging server instance waits for the client to complete the authentication process. Default is 10000 milliseconds.
Accept threads	Provide the number of threads processing the accepted sockets.
Select threads	Provide the number of threads allocated for selection.
Send buffer size	Provide the size of the socket send buffer.
Receive buffer size	Provide the size of the socket receive buffer.

For more information about the basic port properties, see [“Interface Configuration” on page 229](#).

## Security Configuration

Configure this...	To specify...
Client authentication	Whether or not Universal Messaging requires client certificates for all requests. Select: <ul style="list-style-type: none"><li>■ <b>None</b> if Universal Messaging does not require client certificates for all requests.</li><li>■ <b>REQUIRE_CERTIFICATE</b> if you want Universal Messaging to require client certificates for all requests.</li></ul>
SSL enabled	Whether the port is SSL enabled or not. This attribute is always set to true for nhps and nsps port.
Keystore type	File type of the keystore file. Universal Messaging supports only the JKS file type.
Keystore server location	Location of the keystore file.
Keystore password	Password required to access the SSL certificate in the keystore file.
Keystore key password	Password required to access a specific private key in the keystore file.
Truststore type	File type of the truststore file. Universal Messaging supports only the JKS file type.
Truststore server location	Location of the truststore file.
Truststore password	Password required to access the SSL certificate in the truststore file.

3. Click **Test** to validate the entered information or click **Save** to save changes to the port.

## Memory Configuration

You can view and update the initial memory size, maximum memory size, and the extended property (MaxDirectMemorySize) of a Universal Messaging server instance. When you add or edit an extended property, ensure that you prefix `-xx:` to the extended property name.

## Realm Access Control Lists (ACLs)

You can configure the permissions for a Universal Messaging server instance by editing one or more of the following parameters:

Configure...	Specify...
Subject	User name in the format <i>user@host</i> , or name of an existing group in the format <i>groupname</i> .
Manage ACL	Allow ACL management.
Full	Grant full privileges to the user or group.
Access	Allow access to the realm.
Configure	Allow realm configuration.
Channels	Allow channel configuration and administration.
Realm	Allow realm configuration and management.
Admin API	Allow use of Universal Messaging Admin API.
Manage data groups	Allow data groups' management.
Own data groups	Allow ownership of data groups.
Publish to data groups	Allow publishing to global data groups.

## Group Management

You can add, edit, or delete a new security group using the Command Central web user interface. You can define subjects for a specific group, the subjects can be an existing group or an individual user in the format *user@host*. For more information about Universal Messaging security groups, see [“Security Groups” on page 157](#).

## General Properties

You can configure a Universal Messaging server instance by editing the configuration parameters. The large number of Universal Messaging configuration parameters are organized into groups. The parameters in each group are organized into two categories: Basic and Advanced. The properties in the Basic category are commonly used. The properties in the Advanced category is less frequently used, and are intended for special cases or expert users.

### Note:

You can view and configure properties only when the Universal Messaging server instance is Online.

Configure this group...	To modify...
Audit Settings	Parameters to configure what gets logged in the audit file.
Client Timeout Values	Parameters to configure client-server communication timeout settings.

<b>Configure this group...</b>	<b>To modify...</b>
Cluster Config	Parameters to configure clustering.
Comet Config	Parameters to configure Comet communication protocol connection.
Connection Config	Parameters to configure client-server connection.
Data Stream Config	Parameters to configure data streams.
Environment Config	System environment configuration parameters.
	<b>Note:</b> You cannot modify the environment configuration parameters, the parameters are read-only.
Event Storage	Parameters to configure how events are stored, and retrieved from the server.
Fanout Values	Parameters to configure delivery of events to the clients.
Global Values	Parameters to configure various global Universal Messaging server instance properties. For example, <code>AllowRealmAdminFullAccess</code> .
Inter-Realm Comms Config	Parameters to configure communication across Universal Messaging server instances.
JVM Management	Parameters to configure the JVM used by the Universal Messaging server.
Join Config	Parameters to modify join properties.
Logging Config	Parameters to modify logging configuration.
Metric Config	Parameters to enable or disable system metrics such as memory usage.
MQTT Config	Parameters to configure MQTT.
Plugin Config	Parameters for Universal Messaging server plugin configuration.
Protobuf Config	Parameters to configure Google protocol buffers.
Protocol AMQP Config	Parameters to configure AMQP connections.
Protocol MQTT Config	Timeout value for MQTT connections.
Proxy Forward Config	Parameters to configure proxy settings.
RecoveryDaemon	Parameters to configure clients that are in recovery and replaying large number of events.

Configure this group...	To modify...
Server Protection	Parameters to configure server protection such as flow control of producer connections.
Thread Pool Config	Parameters for server thread pools.
TransactionManager	Parameters for Universal Messaging transaction engine.

For information about configuration group parameters and their values, see [“Realm Configuration” on page 29](#).

## JNDI Management

You can configure connection factories and destinations in a JNDI namespace using the Command Central web user interface or the command line. You can perform the following operations on JNDI entries:

- Create
- Get
- Update
- Delete

### JNDI Connection Factories

You can perform create, get, update, and delete operations on the following connection factory types:

- Connection Factory
- Topic Connection Factory
- Queue Connection Factory
- XA Connection Factory

The table describes the connection factory configuration parameters:

Configure...	Specify...
Name	Required and unique. Name of the new connection factory. Once created, you cannot edit the JNDI connection factory name. For example, connectionfactory1.
Type	Required. Type of connection factory selected when creating the connection factory. For example, XA Connection Factory.

**Note:**

Configure...	Specify...
Connection URL	<p data-bbox="552 262 1385 315">This field cannot be edited.</p> <p data-bbox="552 325 1385 777">Required. Universal Messaging server URL for binding the connection factory. For example, <code>nsp://umhostname:9000</code>. A cluster of server instances is specified using a comma-separated list of connection URLs, for example, <code>nsp://localhost:9000,nsp://localhost:9010</code>. You can use a round-robin connection factory to specify several connection URLs, where each connection URL can point to a standalone realm or a cluster. Round-robin connection factories allow clients to publish messages so that one message or transaction gets published to the first realm node or cluster, the next message to the next realm node or cluster, and so on. For a round-robin connection factory, each connection URL is bounded by a set of brackets: <code>(nsp://{hostname}:{port})</code>. Examples:</p> <ul data-bbox="552 798 1385 1165" style="list-style-type: none"> <li>■ <code>(UM1)(UM2)(UM3)(UM4)</code> - Indicates four standalone server instances: UM1, UM2, UM3 and UM4, four connections are created.</li> <li>■ <code>(UM1,UM2)(UM3,UM4)</code> - Indicates two clusters, one consisting of UM1 and UM2 and the other consisting of UM3 and UM4, only two connections are created.</li> <li>■ <code>(UM1)(UM2,UM3)(UM4)</code> - Indicates one cluster consisting of UM2 and UM3, and two standalone realms, namely UM1 and UM4. A total of three connections are created.</li> </ul> <p data-bbox="552 1186 1385 1312"><b>Note:</b> Round-robin delivery is not supported for XA Connection Factory.</p>
Durable type	<p data-bbox="552 1333 1385 1396">Select the durable type. The durable type <b>Named</b> is selected by default.</p> <p data-bbox="552 1417 1385 1543"><b>Note:</b> You can configure the durable type property only for Connection Factory and Topic Connection Factory.</p>

## JNDI Destinations

You can perform create, get, and delete operations on the following destination types:

**Note:**  
Update operation for JNDI destinations is not supported.

- Topics

## ■ Queues

The table describes the destination configuration parameters:

Configure...	Specify...
Lookup Name	Required and unique. Name of the JNDI destination. Once created, you cannot edit the JNDI destination name. Name can include upper and lower case alphabetic characters, digits (0-9), double colon (::), slash (/), and periods (.), for example, destination1. Use the double colon (::) for specifying nested name space, for example, destination1::destination2.
Destination Type	Required. Type of destination.  <b>Note:</b> This field cannot be edited.
Store Name	Required and unique. Name of the JMS channel or queue. Once created, you cannot edit the store name. Store name can include upper and lower case alphabetic characters, digits (0-9), double colon (::), and slash (/).
Auto-Create JMS Channel	Select to enable auto-creation of JMS channel.

### Note:

- Creating a connection factory and destination with the same name is not allowed for a Universal Messaging server instance.
- Deleting a JNDI destination will not delete the channel or queue that exists in the Universal Messaging server instance.

## Channels Configuration

You can view, create, update, and delete a channel using the Command Central web or command-line interface.

You can configure the following properties:

### Channel Properties

Property...	Description..
Name	Required. Name of the channel to be created.  <b>Note:</b> Once a channel is created, you cannot edit the channel name.
Type	Type of channel. Universal Messaging channel types: <ul style="list-style-type: none"> <li>■ Transient</li> </ul>

Property...	Description..
	<ul style="list-style-type: none"><li>■ Simple</li><li>■ Reliable</li><li>■ Persistent</li><li>■ Mixed (default)</li><li>■ Off-heap</li><li>■ Paged</li></ul>
TTL (ms)	Specifies how long (in milliseconds) each event is retained on the channel after being published. For example, if you specify a TTL of 10000, the events on the channel will be automatically removed by the server after 10000 milliseconds. Specify 0 for events to remain on the channel indefinitely.
Capacity	Event capacity of the channel. Specifies the maximum number of events that can be on a channel, once published. Specify 0 to store unlimited events. The maximum channel capacity is 2147483646.
Dead event store	Channel or queue to be used to store events that are purged before being consumed.
Engine	Type of engine to be used for the channel. By default, Universal Messaging retains all events on the channel for a specified TTL, modify the retention behavior by selecting <b>JMS</b> engine or <b>Merge</b> engine.
Cluster-wide	Selected automatically if the Universal Messaging server instance is part of a cluster.
Protobuf descriptor	Absolute path to the Protocol Buffer (protobuf) descriptor file that is stored on the machine where Software AG Platform Manager is installed.

### Storage Properties

Property...	Description..
Auto-maintenance	Select to retain events till they reach their TTL. Cancel the selection to purge events from the channel storage file.
Honor capacity	Select to prevent publishing of data when the channel is full. Cancel the selection to purge the oldest published event.
Enable caching	Select for the events to be stored in the cache memory and reused. Cancel the selection to read and stored in the file store.

Property...	Description..
Cache on reload	Select to enable caching during reload.
Enable read buffering	Select to enable read buffering for the store on the Universal Messaging server.
Enable multicast	Select to enable multicast client to receive events over multitask connections.
Read buffer size	Read buffer size in bytes.
Sync each write	Select to sync each write to the file system.
Sync batch size	Configurable only when <b>Sync each write</b> is selected. Number of events that is to be synced with the file system at once.
Sync batch time	Configurable only when <b>Sync each write</b> is selected. Time in milliseconds (ms) between syncs with the file system.
Fanout archive target	Target number of events that are written to an archive after fanout.
Priority	Priority range. 0 (lowest) to 9 (highest).
Events per spindle	Maximum number of events allowed per file.
Stamp dictionary	Select to stamp events on the channel by the server.

### Channel Keys

Column...	Description...
Key name	Name of the channel publish key.
Depth	Depth of the channel publish key. Depth is the maximum number of events that can exist on a channel for a specific key name.

### Channel ACL

Column...	Description...
Subject	User name in the format <code>user@host</code> or the name of an existing group.
Manage ACL	Select to allow the user or group to manage ACLs.
Full	Select to grant full privileges to the user or group.
Purge	Select to allow the user or group to purge events.
Subscribe	Select to allow the user or group to subscribe to events.

Column...	Description...
Publish	Select to allow the user or group to publish events.
Named	Select to allow the user or group to subscribe to named objects.

## Joins

You can add and delete joins, but cannot edit channel join properties.

Column...	Description...
Type	Type of join. Outgoing: channel is source. Incoming: channel is destination.
Destination name	Destination channel or queue.
Target instance name	Name of the target instance. Required only if the channel or queue is in a remote Universal Messaging server instance.
Target instance URL	URL of the target Universal Messaging server instance that has the destination channel or queue for the join.
Filter	Type the filtering criteria, a string or a regular expression. Events will be routed to the destination channel based on the filtering criteria.
Hop count	Type the maximum number of subsequent joins.
Event ID	Last retrieved event ID.
Allow purge	Select to allow purging of events on the channel.
Archival	Select to enable archival join. Archival join is a join between a channel and a queue where events will not be checked for duplication.

## Queues Configuration

You can view, create, update, and delete a queue using the Command Central web or command-line interface.

You can configure the following properties:

### Queue Properties

Property...	Description..
Name	Required. Name of the queue to be created. You cannot edit the queue name.

Property...	Description..
Type	Type of queue. Universal Messaging queue types: <ul style="list-style-type: none"> <li>■ Transient</li> <li>■ Simple</li> <li>■ Reliable</li> <li>■ Persistent</li> <li>■ Mixed (default)</li> <li>■ Off-heap</li> <li>■ Paged</li> </ul>
TTL (ms)	Specifies how long (in milliseconds) each event is retained in the queue after being published. For example, if you specify a TTL of 10000, the events on the queue will be automatically removed by the server after 10000 milliseconds. Specify 0 for events to remain on the queue indefinitely.
Capacity	Event capacity of the queue. Specifies the maximum number of events that can be on a queue once published. Specify 0 to store unlimited events. The maximum queue capacity is 2147483646.
Dead event store	Channel or queue to be used to store events that are purged before being consumed.
Cluster-wide	Selected automatically if the Universal Messaging server instance is part of a cluster.
Protobuf descriptor	Absolute path to the Protocol Buffer descriptor file that is stored on the machine where Software AG Platform Manager is installed.

### Storage Properties

Property...	Description..
Auto-maintenance	Select to retain events till they reach their TTL. Cancel the selection to purge events from the queue storage file.
Honor capacity	Select to prevent publishing of data when the queue is full. Cancel the selection to purge the oldest published event.
Enable caching	Select for the events to be stored in the cache memory and reused. Cancel the selection to read and stored in the file store.
Cache on reload	Select to enable caching during reload.

Property...	Description..
Enable read buffering	Select to enable read buffering for the store on the Universal Messaging server.
Enable multicast	Select to enable multicast client to receive events over multitask connections.
Read buffer size	Read buffer size in bytes.
Sync each write	Select to sync each write to the file system.
Sync batch size	Configurable only when <b>Sync each write</b> is selected. Number of events that is to be synced with the file system at once.
Sync batch time	Configurable only when <b>Sync each write</b> is selected. Time in milliseconds (ms) between syncs with the file system.
Fanout archive target	Target number of events that are written to an archive after fanout.
Priority	Priority range. 0 (lowest) to 9 (highest).
Events per spindle	Maximum number of events allowed per file.
Stamp dictionary	Select to stamp events on the channel by the server.

### Queue ACL

Column...	Description...
Name	User name in the format <code>user@host</code> or the name of an existing group.
Manage ACL	Select to allow the user or group to manage ACLs.
Full	Select to grant full privileges to the user or group.
Purge	Select to allow the user or group to purge events.
Peek	Select to allow the user or group to peek events.
Push	Select to allow the user or group to push events.
Pop	Select to allow the user or group to pop events.

### Joins

You can view the following join properties:

Column...	Description...
Type	Type of join.

Column...	Description...
Destination name	Destination channel.
Target instance name	Name of the target instance. Required only if the target channel is in a remote Universal Messaging server instance.
Target instance URL	URL of the target Universal Messaging server instance that has the destination channel for the join.
Remote node	Destination channel.
Hop count	Maximum number of subsequent joins.
Event ID	Last retrieved event ID.
Allow purge	Allow purging of events in the queue.
Archival	Archival join is a join between a channel and a queue where events will not be checked for duplication.

## Zones

Zones are a logical grouping of one or more Universal Messaging server instances (realms) that maintain active connections to each other. Each Universal Messaging server instance can be a member of zero or one zone, but a server instance cannot be a member of more than one zone. For more information about zones, see the Zones section in the Universal Messaging Concepts guide.

You can create, edit, or delete a zone using the Command Central web user interface. You can create **Zone with Realms** consisting one or more realms, or create **Zone with Clusters** consisting one or more Universal Messaging clusters. You can export the zone configuration using the **Export** option.

The table describes the zone parameters required to create a zone:

Configure...	Specify...
Zone name	Required. Name of the zone, it is used to uniquely identify this zone.
Servers (for Zone with Realms) or	Required. Provide server URL and name if you are creating a <b>Zone with Realms</b> or provide all or one of the cluster nodes if you are creating a <b>Zone with Clusters</b> .
Clustered servers (for Zone with Clusters)	<ul style="list-style-type: none"> <li>■ Server URL: Universal Messaging server URL.</li> <li>■ Server name: Name of the Universal Messaging server.</li> <li>■ Cluster configuration: Automatically populated with the cluster name.</li> </ul>

**Configure...****Specify...****Note:**

You can provide any one cluster node and all the running nodes of the cluster will be added to the zone.

## Java System Properties

You can view, edit, and delete a few Java system properties from the Command Central web user interface. Restart the Universal Messaging instance for the changes to take effect.

You can edit the following Java system properties:

Property	Description
LICENCE_FILE	Name of the license file.
LICENCE_DIR	Absolute path to the location of the license file.
DATADIR	Absolute path to the location of the data directory.

**Note:**

Modifying the DATADIR property does not copy the existing data directory to the new location.

You can delete a property value by passing an empty value for the property, this will revert the property to its default value.

## Cluster Management

### Before You Create a Universal Messaging Cluster

Before you create or update a Universal Messaging cluster:

- Ensure that the server instances that you want to add to the cluster are running.
- Verify that the permissions on the server machines allow connections to the other servers in the cluster.
- Ensure that the `/naming/defaultContext` channel exists only on one or none of the nodes that will form the cluster. The Universal Messaging server instance used as a JNDI provider uses the `/naming/defaultContext` channel to store JMS references and JNDI objects. If channels exists on multiple nodes, you cannot create the cluster.

### Cluster Configuration Fields

Field	Specify...
<b>Cluster Name</b>	Unique cluster name.
<b>Server URL</b>	Server instances URL (for example, nsp://127.0.0.1:9002) of each server node.  When you save the cluster details, the <b>Server Name</b> field is populated with the name of the server corresponding to the specified server URL.
<b>Cluster Site</b>	Name of the site (Optional) to which the server node belongs.
<b>Prime Site</b>	Name of the primary site (Optional), if you have configured sites in the cluster.

## Cluster Configuration Tasks Supported

Cluster configuration tasks that you can perform:

- Create a cluster of two or more server instances
- Add one or more server instances to the existing cluster
- Remove one or more server instances from the existing cluster
- Upgrade a cluster
- Create sites and assign server instances to the sites
- Assign a site as the prime site of a cluster
- Remove one or more server instances from a cluster site
- Remove sites from a cluster
- Delete a cluster
- Migrate a cluster

## Cluster Migration

You can now automatically migrate Universal Messaging clusters using Command Central composite templates. Use Command Central composite templates to migrate all the Universal Messaging server instances that are part of the cluster, and add the following property to resolve the cluster node connections successfully after migration:

- Add the following property to the `um-cluster` section of the composite template YAML file present in the following directory: *Software AG\_directory*  
`\profiles\CCE\data\templates\composite :`

```
<ClusterSettings>
  ...
  <ExtendedProperties>
    <Property name="migrationType">SAME_HOST or CROSS_HOST</Property>
  </ExtendedProperties>
```

```
</ClusterSettings>
```

**Note:**

A Universal Messaging server instance mapping file called `remote_realms_bootstrap.conf` containing information about the new Universal Messaging hosts is automatically generated in each of the Universal Messaging server instances. The mapping file is used to identify the new hosts, and to form the new cluster.

## Universal Messaging Logs

---

You can view, download, and search all the Universal Messaging logs at one place in the Command Central web user interface. You can access the logs for a Universal Messaging server instance by selecting a Universal Messaging instance name and clicking the **Logs** tab.

## Universal Messaging Administration Types

---

Command Central lets you administer and monitor the following on a Universal Messaging server instance:

- Durable Subscribers
- Channels
- Queues

### Durable Subscribers

You can search, monitor, and delete durable subscribers for a Universal Messaging server instance. You can browse and purge events on a specific durable subscriber.

Types of durable subscribers:

- Shared
- Shared - Queued
- Priority
- Serial
- Durable

**Note:**

You can purge events only for shared durable subscribers.

The table displays the following durable subscriber attributes:

Attribute	Description
Name	Name of the durable subscriber.

Attribute	Description
Channel	Name of the channel to which the durable subscriber belongs.
Durable type	Type of the durable subscriber (Shared, Shared - Queued, Priority, Serial, or Durable).
Last event ID	Event ID of the last successfully consumed event.
Outstanding events	The number of events outstanding for a particular durable subscriber.
	<p><b>Note:</b> The outstanding event count displayed for a non-shared durable is only an estimate.</p>
Last read time	The last date and time when the durable subscriber read, committed, or rolled back an event.

Select a durable subscriber to view:

- Durable details
- Browse events
- Bulk purge

The **Durable details** page contains the following information about a durable subscriber:

#### Details

Attribute	Description
Name	Name of the durable subscriber.
Channel	Name of the channel to which the durable subscriber belongs.
Durable type	Type of the durable subscriber (Shared, Shared - Queued, Priority, Serial, or Durable).
Cluster-wide	Whether the durable subscriber is on a channel that is part of a Universal Messaging cluster.
Persistent	Whether the durable subscriber is persistent. Persistent durable subscribers retrieve the last event ID consumed before the Universal Messaging server instance was restarted.
Selector	Events are filtered based on the defined selector.

#### Status

Attribute	Description
Last event ID	Event ID of the last successfully consumed event.
Store size (KB)	The size of the store available for the Shared - Queued durable.
Total events	The number of outstanding events for the durable subscriber.
Pending events	The number of outstanding events waiting for a commit or a rollback.
Last read time	The last date and time when the durable subscriber read, committed, or rolled back an event.
Last write time	The last time the durable was written to. Typically, this is the last time an event was added to the durable subscriber.

### Connections

Attribute	Description
ID	Connection ID.
Mode	Client subscription mode (subscription based or getNext).
Max pending	Window size specified by the client.
Acknowledged	Total acknowledged events.
Rolled back	Total rolled back events.
Pending	Event queues waiting to be acknowledged or rolled back.
Last read time	Last time the session acknowledged, rolled back, or read an event from the durable subscriber.

The **Browse events** page displays the event list and lets you to browse events for a durable subscriber. Events are displayed in the order of old to new. A maximum of 1000 events are displayed in the table with a maximum combined size of 10 MB. For example, if two events of size 10 MB and 100 MB are present for the durable subscriber, only the event of size 10 MB is displayed, and no other events are displayed. Click **Browse events** to refresh the events displayed in the table.

Attribute	Description
Event ID	Unique ID to identify the event.
TTL (ms)	Specifies how long (in milliseconds) each event is retained.
Tag	Shows the tag information of the event if an event tag exists.
Event data	Content of the event.

Attribute	Description
	<p><b>Note:</b> If the payload is Protocol Buffers (Protobuf), the event data will contain the message "Protobuf payload" and not the decoded payload.</p>
Event size (bytes)	Size of the event in bytes.
	<p><b>Note:</b> Event size is the total size of the event that is the sum of event data and event properties.</p>
Event properties	Event properties represented as key-value pairs.
Persistent	Shows whether the event is persistent or not.

You can select an event ID to view the event data and event properties.

The **Bulk purge** option allows you to purge events in bulk for a durable subscriber. You can purge events by providing an event range, event filter, or purge all the events.

## Channels

You can search and monitor the following channel attributes:

Attribute	Description
Name	Name of the channel.
Event ID	Event ID of the last event that was consumed from the channel. Event ID is -1 if the channel is empty.
Events	Number of events in the channel that are yet to be consumed.
Current Connections	Number of current connections to the channel.
% Free	Percentage of free storage available in the channel.

Select a channel to view detailed information about the status of the channel and the durable subscribers (named objects) subscribed to the channel. You can also delete a durable subscriber subscribed to the channel.

## Queues

You can search and monitor the following queue attributes:

Attribute	Description
Name	Name of the queue.
Event ID	Event ID of the last event that was popped from the queue. Event ID is -1 if the queue is empty.
Events	Number of events in the queue that are yet to be consumed.
Current Connections	Number of current connections to the queue.
% Free	Percentage of free storage available in the queue.

Select a queue to view detailed information about the status of the queue.

## Universal Messaging Inventory

---

When you view installations in an environment, Command Central displays the Universal Messaging server instances listed in the *UniversalMessaging\_installationDirectory\UniversalMessaging\server* directory of an installation. Command Central lists all the folders (except the templates) in the server directory.

## Universal Messaging Lifecycle Actions

---

You can start, stop, and restart a Universal Messaging server instance from the Command Central web user interface. The following legend describes what each one of the lifecycle operations.

- **Start.** Start a server instance that has stopped.
- **Stop.** Stop a running server instance.
- **Restart.** Restart a running server instance.

## Universal Messaging KPIs

---

You can view the following key performance indicators (KPIs) to monitor the performance of the Universal Messaging servers:

KPI	Description
JVM Memory	<p>Indicates the utilization of JVM memory.</p> <p>The marginal, critical, and maximum values for this KPI depend on the maximum memory size of the JVM.</p> <ul style="list-style-type: none"><li>■ Marginal is 80% of the maximum JVM memory.</li><li>■ Critical is 95% of the maximum JVM memory.</li><li>■ Maximum is 100% of the maximum JVM memory.</li></ul>

KPI	Description
Fanout Backlog	<p data-bbox="649 252 1461 399">Indicates the total number of events currently waiting to be processed by the fanout engine. If the fanout backlog is more than the critical value, there is a possibility that the subscribers receive the published events after some delay.</p> <p data-bbox="649 420 1429 493">The KPI uses the following marginal, critical, and maximum values:</p> <ul data-bbox="649 514 1461 703" style="list-style-type: none"> <li data-bbox="649 514 1218 556">■ Marginal is 80% of the maximum value.</li> <li data-bbox="649 567 1185 609">■ Critical is 95% of the maximum value.</li> <li data-bbox="649 619 1461 703">■ Maximum is 100% of the peak value (high-water mark) of fanout backlog. Default is 100.</li> </ul>
Queued Tasks	<p data-bbox="649 724 1477 903">Indicates the total number of tasks in the read, write, and common read/write pools. If the number of read and write tasks queued is more than the critical value, it indicates that the Universal Messaging server is unable to match the speed of the publishers and subscribers.</p> <p data-bbox="649 924 1429 997">The KPI uses the following marginal, critical, and maximum values:</p> <ul data-bbox="649 1018 1461 1207" style="list-style-type: none"> <li data-bbox="649 1018 1218 1060">■ Marginal is 80% of the maximum value.</li> <li data-bbox="649 1071 1185 1113">■ Critical is 95% of the maximum value.</li> <li data-bbox="649 1123 1461 1207">■ Maximum is 100% of the peak value (high-water mark) of read and write tasks queued. Default is 100.</li> </ul>

## Universal Messaging Run-time Monitoring Statuses

The Command Central instances page displays the run-time status of a Universal Messaging server instance in the status column. The Universal Messaging can have one of the following run-time status:

- Online  : Server instance is online.
- Failed  : Server instance failed. For example, the Universal Messaging server instance stopped unexpectedly due an error or system failure.
- Stopped  : Server instance is not running.
- Stopping  : Server instance is stopping.

- Unresponsive  : Server instance is running, but it is unresponsive. When none of the server interfaces are connected to the server.
- Unknown  : Server instance status cannot be determined.

When you have set up a Universal Messaging cluster, the run-time status indicates if a server instance is:

- Online Master  : Server instance is online and it is the master node in the cluster.
- Online Slave  : Server instance is online and it is the slave node in the cluster.
- Error  : Server instance is part of a cluster that does not satisfy the requisite quorum.

## Universal Messaging and the Command Line Interface

---

Universal Messaging supports the Platform Manager commands listed below. For information about the commands, see *Software AG Command Central Help*. For Universal Messaging-specific information about using this command, see [“Universal Messaging Commands” on page 419](#).

### **Important:**

When a Universal Messaging server instance is running as a service, you cannot perform administrative tasks such as check the status or start or stop the server instance.

Supported commands:

- `sagcc create configuration data`
- `sagcc delete configuration data`
- `sagcc get configuration data`
- `sagcc update configuration data`
- `sagcc get configuration instances`
- `sagcc list configuration instances`
- `sagcc get configuration types`
- `sagcc list configuration types`
- `sagcc exec configuration validation create`
- `sagcc exec configuration validation delete`
- `sagcc exec configuration validation update`
- `sagcc create instances`
- `sagcc delete instances`

- `sagcc list instances`
- `sagcc list instances supportedproducts`
- `sagcc get inventory components`
- `sagcc exec lifecycle`
- `sagcc get diagnostics logs`
- `sagcc get diagnostic logs export file`
- `sagcc list diagnostics logs`
- `sagcc get monitoring`
- `sagcc exec administration product`

For information about these commands, see *Software AG Command Central Help*.

## Universal Messaging Commands

---

### Instance Management

The following table lists the required parameters that you must include when managing the Universal Messaging instances using the Universal Messaging instance management commands:

Command	Parameter	Description
<code>sagcc create instances</code>	NumRealmServer, NumEnterpriseManager, and NumTemplateApplications	The product ID for the Universal Messaging instance.
	instance.name	Required. A name for the new Universal Messaging instance.
	instance.ip	Optional. An IP address for the Universal Messaging server interface. If you do not specify a value, 0.0.0.0 is the default value.
	instance.port	Optional. A port number for the Universal Messaging server. If you do not specify a value, 9000 is the default port number.
	instance.dataDir	Optional. Absolute path to Universal Messaging server data directory. If you do not specify a path, the default directory location is used for creating the data directory. Location of the default directory is:

Command	Parameter	Description
		<i>Universal Messaging_directory</i> <i>\server\umserver</i>
	license.file	Optional. Absolute path to the Universal Messaging license file. If you do not specify a path, the default license is used. Location of the default directory is: <i>Universal Messaging_directory</i> <i>\server\umserver</i>
	instance.config.profile	Optional. Initial configuration settings for the Universal Messaging server instance. Options for the parameter value: <ul style="list-style-type: none"> <li>■ wm: webmethods suite use cases.</li> <li>■ TC: Standalone use cases.</li> <li>■ CUSTOM: Custom profile.</li> </ul>
	instance.config.file	Required if the <code>instance.config.profile</code> parameter value is CUSTOM. Absolute path to the custom profile XML file.

**Important:**

Universal Messaging does not support `sagcc update instances`. You cannot rename a Universal Messaging instance.

## Examples:

- To check if Universal Messaging supports instance management operations through Command Central for a node with alias “messagingNode”:

```
sagcc list instances messagingNode supportedproducts
```

- To create an instance of Universal Messaging server named “umserver” on port number “9000” of the node with alias “messagingNode”:

```
sagcc create instances messagingNode NUMRealmServer instance.name=umserver
instance.ip=0.0.0.0 instance.port=9000
```

- To create an instance of Universal Messaging server named “umserver” on port number “9000” of the node with alias “messagingNode” and having a custom data directory path and license file:

```
sagcc create instances messagingNode NUMRealmServer instance.name=umserver
instance.ip=0.0.0.0 instance.port=9000
instance.dataDir=Data_Directory_Absolute_Pathlicense.file=
absolute path to the license file
```

- To create an instance of Universal Messaging server named "umserver" on port number "9000" of the node with alias "messagingNode", and provide an initial configuration settings:

```
sagcc create instances messagingNode NUMRealmServer instance.name=umserver
instance.ip=0.0.0.0 instance.port=9000 instance.config.profile=wM or TC
```

- To create an instance of Universal Messaging server named "umserver" on port number "9000" of the node with alias "messagingNode", and provide custom initial configuration settings:

```
sagcc create instances messagingNode NUMRealmServer instance.name=umserver
instance.ip=0.0.0.0 instance.port=9000 instance.config.profile=CUSTOM
instance.config.file=absolute path to the custom profile XML file
```

- To read the following properties of Universal Messaging server named "umserver":

- Port number
- Interface IP address
- Server data directory path
- License path

```
sagcc list instances messagingNode Universal-Messaging-umserver
```

- To remove the "umserver" Universal Messaging server instance existing on the node with alias "messagingNode" node:

```
sagcc delete instances messagingNode Universal-Messaging-umserver
```

- To create an Enterprise Manager instance named "EM1":

```
sagcc create instances messagingNode instance.name=em1
instance.ip=0.0.0.0 instance.port=9000
```

Use the Universal Messaging Instance Manager tool to delete the Enterprise Manager and Template Applications instances. You cannot use Command Central commands for deleting these instances as they are not listed in the product inventory.

**Note:**

You can create a Template Applications instance using the same command used to create an Enterprise Manager instance.

## Universal Messaging Configuration Types

The following table lists the configuration types that Universal Messaging server instance supports.

Configuration Type	Use to...
COMMON-LOCAL-USERS	Configure and manage users of a Universal Messaging server instance. COMMON-LOCAL-USERS- <i>userId</i> supports configuring the user ID and password of each

Configuration Type	Use to...
	user. By default, the users have administrator privileges for the Universal Messaging server instance.
COMMON-LICENSE	Configure the Universal Messaging-specific SagLic license file.
COMMON-LICLOC	View the location of a Universal Messaging server instance's license file.  You cannot change the location of the license file.
COMMON-JAVASYSPROPS	Extended JVM options.
UM-JNDI-CF	Configure the following JNDI connection factories: <ul style="list-style-type: none"> <li>■ Connection Factory</li> <li>■ Topic Connection Factory</li> <li>■ Queue Connection Factory</li> <li>■ XA Connection Factory</li> </ul>
UM-JNDI-DEST	Configure the following JNDI destinations: <ul style="list-style-type: none"> <li>■ Topics</li> <li>■ Queues</li> </ul>
COMMON-CLUSTER	Configure an active/active Universal Messaging cluster.
COMMON-MEMORY	Configure the initial memory size, maximum memory size, and direct memory as an extended property of a Universal Messaging server instance.
COMMON-PORTS	Configure the Universal Messaging server interfaces. <div style="background-color: #f0f0f0; padding: 5px; margin-top: 10px;"> <p><b>Note:</b></p> <ul style="list-style-type: none"> <li>■ You cannot change the protocol, bind address, port number, or alias of a port of an existing server interface.</li> <li>■ If you change the SSL certificates of a secured interface, you must restart the interface.</li> </ul> </div>
UM-ZONE	Create and manage Universal Messaging zones.
UM-CHANNELS	Create and manage Universal Messaging channels.
UM-QUEUES	Create and manage Universal Messaging queues.
UM-REALM-ACL	Manage Universal Messaging Access Control List (ACL).

Configuration Type	Use to...
UM-GROUPS	Manage Universal Messaging security groups.
COMMON-SYSPROPS	DEPRECATED. Use COMMON-JAVASYSPROPS.

## User Configuration

You can use the command line interface commands, web user interface, or `internaluserrepo.bat/sh` script to configure users of a Universal Messaging server instance.

You can perform the following user configuration tasks on a Universal Messaging server instance from the command line interface:

- List the path and the users existing in the user repository using the `sagcc get configuration instances node_alias Universal-Messaging-umserver` command.
- Retrieve information about a specific user using the `sagcc get configuration instances node_alias Universal-Messaging-umserver COMMON-LOCAL-USERS-user name` command.
- Add new users to the user repository using the `sagcc create configuration data node_alias Universal-Messaging-umserver COMMON-LOCAL-USERS --input absolute path to the XML file containing the user ID and password` command.
- Update or change the password of an existing user using the `sagcc update configuration data node_alias Universal-Messaging-umserver COMMON-LOCAL-USERS-user name --input absolute path to the XML file containing new password` command.
- Delete existing users from the user repository using the `sagcc delete configuration data node_alias Universal-Messaging-umserver COMMON-LOCAL-USERS-user name` command.

Information to authenticate the users of a Universal Messaging server instance is stored in the user repository (`users.txt` file). The path of the user repository `users.txt` file is specified in the `Server_Common.conf` file of the Universal Messaging server instance irrespective of whether you are running Universal Messaging as a service or as an application. The `users.txt` file is generated only after you create a new internal user. The default path for the Universal Messaging user repository (`users.txt` file) is `Universal Messaging directory\server\umserver instance`. While creating the user repository, if you specify a relative path, the `users.txt` file will be created in a directory relative to the `bin` directory of the Universal Messaging server instance.

Examples:

- To list the path of the user repository and the users of a Universal Messaging server instance:

```
sagcc get configuration instances sag01 Universal-Messaging-umserver
```

where `umserver` is the name of the Universal Messaging server instance, and `sag01` is the alias name of the installation where `umserver` is running.

- To retrieve information of a Universal Messaging server instance user:

```
sagcc get configuration instances sag01 Universal-Messaging-umserver  
COMMON-LOCAL-USERS-user1
```

where `umserver` is the name of the Universal Messaging server instance, `sag01` is the alias name of the installation where `umserver` is running, and `user1` is the user ID of the user.

- To add a user to a Universal Messaging server instance:

```
sagcc create configuration data sag01 Universal-Messaging-umserver  
COMMON-LOCAL-USERS --input c:\inputxmls\user2.xml
```

where `umserver` is the name of the Universal Messaging server instance, `sag01` is the alias name of the installation where `umserver` is running, and `user2.xml` is file that contains the user ID and the password of the new user.

Format of the `user2.xml` file:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>  
<User id="user2">  
<Password>test</Password>  
</User>
```

- To update the password of a Universal Messaging server instance user:

```
sagcc update configuration data sag01 Universal-Messaging-umserver  
COMMON-LOCAL-USERS-user2 --input c:\inputxmls\user2.xml
```

where `umserver` is the name of the Universal Messaging server instance, `sag01` is the alias name of the installation where `umserver` is running, and `user2.xml` is the file that contains the new password of the specified user.

- To delete a Universal Messaging server instance user:

```
sagcc delete configuration data sag01 Universal-Messaging-umserver  
COMMON-LOCAL-USERS-user2
```

where `umserver` is the name of the Universal Messaging server instance, `sag01` is the alias name of the installation where `umserver` is running.

## License Configuration

You can view the content and the location of the license file, and change the license file of a Universal Messaging server instance.

- View the license details of a Universal Messaging server instance using the `sagcc get configuration data node_alias Universal-Messaging-umserver COMMON-LICENSE-Universal-Messaging` command.
- View the license location of a Universal Messaging server instance using the `sagcc get configuration data node_alias Universal-Messaging-umserver COMMON-LICLOC-Universal-Messaging` command.

- Add a Universal Messaging license key file with the specified alias to the Command Central license key manager using the `sagcc add license-tools keys license key alias -i absolute path to the license file` command.
- Update a license key file assigned to the specified license key alias using `sagcc update configuration license node_alias Universal-Messaging-umserver COMMON-LICENSE-Universal-Messaging license key alias`.

#### Examples:

- To view the license details of a Universal Messaging server instance with "Universal-Messaging-umserver" component ID that runs in the installation with alias name "sag01":

```
sagcc get configuration data sag01 Universal-Messaging-umserver
COMMON-LICENSE-Universal-Messaging
```

- To view the license file location of a Universal Messaging server instance with "Universal-Messaging-umserver" component ID that runs in the installation with alias name "sag01":

```
sagcc get configuration data sag01 Universal-Messaging-umserver
COMMON-LICLOC-Universal-Messaging
```

- To add a Universal Messaging license key file with the license key alias "um\_lic" to the Command Central license key manager:

```
sagcc add license-tools keys um_lic -i C:\umlicense\new_license.xml
```

- To update a license key file assigned to the license key alias "um\_lic" with "Universal-Messaging-umserver" component ID that runs in the installation with alias name "sag01":

```
sagcc update configuration license sag01 Universal-Messaging-umserver
COMMON-LICENSE-Universal-Messaging um_lic
```

## Port Configuration

You can create, update, and delete a port for a Universal Messaging server instance.

- Create a port using the `sagcc get configuration data node_alias Universal-Messaging-umserver COMMON-PORTS --input_port_configuration.xml --password Command Central password` command.

The input port configuration XML file should be of the following format:

```
<PortSettings>
  <Port alias="nhp1">
    <Enabled>true</Enabled>
    <Type>STANDARD</Type>
    <Number>9001</Number>
    <Protocol>NHP</Protocol>
    <Backlog>100</Backlog>
    <ExtendedProperties>
      <Property name="autostart">true</Property>
      <Property name="allowforinterrealm">true</Property>
    </ExtendedProperties>
  </Port>
</PortSettings>
```

```

    <Property name="authtime">1000</Property>
    <Property name="EnableNIO">true</Property>
    <Property name="acceptThreads">2</Property>
    <Property name="receivebuffersize">1310721</Property>
    <Property name="SelectThreads">4</Property>
    <Property name="advertise">true</Property>
    <Property name="allowclientconnections">true</Property>
    <Property name="Backlog">100</Property>
    <Property name="Alias"/>
    <Property name="keyAlias"/>
    <Property name="sendbuffersize">1310721</Property>
    <Property name="EnableHTTP11">true</Property>
    <Property name="EnableJavaScript">true</Property>
    <Property name="CORSAAllowCredentials">true</Property>
    <Property name="CORSAAllowedOrigins">*</Property>
    <Property name="AjaxLPActiveDelay">100</Property>
    <Property name="EnableWebSockets">true</Property>
    <Property name="EnableGZipLP">true</Property>
    <Property name="MinimumBytesBeforeGZIP">1000</Property>
    <Property name="AjaxLPIdleDelay">60000</Property>
    <Property name="header1Name">foo</Property>
    <Property name="header1Value">bar</Property>
    <Property name="header1UserAgent">mozilla</Property>
  </ExtendedProperties>
</Port>
</PortSettings>

```

- Update or modify a port's configuration using the `sagcc get` configuration data `node_alias Universal-Messaging-umserver COMMON-PORTS-port name --input_port_configuration.xml --password Command Central password` command.
- Delete a port configuration using the `sagcc get` configuration data `node_alias Universal-Messaging-umserver COMMON-PORTS-port name --input_port_configuration.xml --password Command Central password` command.

#### Examples:

- To create a port for a Universal Messaging server instance with "Universal-Messaging-umserver" component ID that runs in the installation with alias name "sag01", where `input_port.xml` is an XML file containing port configuration information:

```
sagcc create configuration data sag01 Universal-Messaging-umserver
COMMON-PORTS --input_port.xml --password myccpassword
```

- To update or modify port configuration for a Universal Messaging server instance with "Universal-Messaging-umserver" component ID that runs in the installation with alias name "sag01", where `input_port.xml` is an XML file containing the updated port configuration information, and `nhp1` is the name of the port to be updated:

```
sagcc update configuration data sag01 Universal-Messaging-umserver
COMMON-PORTS-nhp1 --input_port.xml --password myccpassword
```

- To delete a port for a Universal Messaging server instance with "Universal-Messaging-umserver" component ID that runs in the installation with alias name "sag01", where `input_port.xml` is an XML file containing the updated port configuration information, and `nhp1` is the name of the port to be deleted:

```
sagcc delete configuration data sag01 Universal-Messaging-umserver
COMMON-PORTS-nhp1 --input_port.xml --password myccpassword
```

### Realm ACL Configuration

You can view the realm ACL configuration information in XML format using the `sagcc get configuration data node_alias Universal-Messaging-umserver UM-REALM-ACL` command.

Examples:

- To view the realm ACL configuration information for a Universal Messaging server instance with "Universal-Messaging-umserver" component ID that runs in the installation with alias name "sag01":

```
sagcc get configuration data sag01 Universal-Messaging-umserver
UM-REALM-ACL
```

### Security Groups

You can retrieve the security group configuration data for a Universal Messaging server instance using `sagcc get configuration data node_alias Universal-Messaging-umserver UM-GROUPS-group name` command.

Example:

- To retrieve the security group configuration information for a Universal Messaging server instance with "Universal-Messaging-umserver" component ID that runs in the installation with alias name "sag01":

```
sagcc get configuration data sag01 Universal-Messaging-umserver
UM-GROUPS-Everyone
```

### General Properties Configuration

- You can view configuration properties for a specific configuration group by using the `sagcc get configuration data` command.
- You can update the configuration properties by using the `sagcc update configuration data` command.

For information about configuration properties, see [“General Properties” on page 399](#).

Examples:

- To view the cluster configuration properties for the Universal-Messaging-umserver server instance:

```
sagcc get configuration data sag01 Universal-Messaging-umserver
COMMON-SYSPROPS-Data_Stream_Config
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. Data\_Stream\_Config is the name of the configuration group.

- To update cluster configuration properties for Universal-Messaging-umserver server instance:

```
sagcc update configuration data sag01 Universal-Messaging-umserver
COMMON-SYSPROPS-Data_Stream_Config --input c:\datastreamconfig.properties
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running.

COMMON-SYSPROPS-Cluster\_Config is the configuration instance ID where COMMON-SYSPROPS is the configuration type and Data\_Stream\_Config is the name of the configuration group.

datastreamconfig.properties is the properties file containing the modified configuration parameters.

The properties file should contain parameter values in the following format:

```
FanoutTaskQueueSize=66
FanoutTraversalType=2
MaxSessionIdSize=14
MonitorTimer=10000
OffloadMulticastWrite=false
ParallelFanoutThreshold=50
SendInitialMapping=true
```

#### **Important:**

Parameter names are case sensitive. For parameter values of enumeration type, set values ranging from 0 to n to map to the corresponding enumeration values in the Command Central user interface. For example, in the above properties file, FanoutTraversalType=2 will be mapped to the value Reversed Order.

#### **Note:**

The sagcc update configuration data command exits and displays an error at the first instance of a wrong parameter definition. For example, in the above example, the command will exit displaying an error if MonitorTimer is assigned a string value.

### JNDI Configuration

You can create, view, update, and delete a JNDI asset. Ensure that the Universal Messaging server instance is running before running the following commands.

- View all the configuration types for a Universal Messaging server instance using the sagcc get configuration types *node\_alias* Universal-Messaging-umserver command.
- View all the configuration instances for a Universal Messaging server instance using the sagcc get configuration instances *node\_alias* Universal-Messaging-umserver command.
- Create a new JNDI connection factory by passing parameters defined in an XML file using the sagcc create configuration data *node\_alias* Universal-Messaging-umserver UM-JNDI-CF -i *absolute path to the XML file* command. You can create the following connection factory types: ConnectionFactory, TopicConnectionFactory, QueueConnectionFactory, and XAConnectionFactory.

The XML file should contain the parameters in the following format:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<connectionFactory>
  <name>connection_factory_name</name>
  <type>connection_factory_type</type>
  <url>connection_factory_binding_url</url>
  <durableType>type of durable</durableType>
```

```
</connectionFactory>
```

**Note:**

The parameters `name`, `type`, and `url` are required, and the `durableType` parameter is optional.

- Create a new JNDI destination by passing parameters defined in an XML file using the `sagcc create configuration data node_alias Universal-Messaging-umserver UM-JNDI-DEST -i absolute path to the XML file` command. You can create the following destination types: Topic and Queue.

The XML file should contain the parameters in the following format:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<destination>
  <name>destination_name</name>
  <type>destination_type</type>
  <storeName>jms_channel_or_queue_name</storeName>
  <autoCreateDest>true/false</autoCreateDest>
</destination>
```

`name` parameter can include upper and lower case alphabetic characters, digits (0-9), double colon (::), slash (/), and periods (.), for example, `destination1`. Use the double colon (::) for specifying nested name space, for example, `destination1::destination2`. A combination of special characters in a name is not allowed, for example, `destination1::destination2/destination3`. `storeName` parameter can include upper and lower case alphabetic characters, digits (0-9), double colon (::), slash (/), and underscores (\_) but cannot include periods (.).

- Retrieve information about a specific JNDI connection factory using the `sagcc get configuration data node_alias Universal-Messaging-umserver UM-JNDI-CF-connection_factory_name` command.
- Retrieve information about a specific JNDI destination using the `sagcc get configuration data node_alias Universal-Messaging-umserver UM-JNDI-DEST-destination_name` command.
- Update a JNDI connection factory by passing the new parameters defined in an XML file using the `sagcc update configuration data node_alias Universal-Messaging-umserver UM-JNDI-CF-connection_factory_name -i absolute path to the XML file` command.

**Important:**

You can update the URL and the `durableType` property, you cannot update the name of the connection factory.

- Delete a JNDI connection factory using the `sagcc delete configuration data node_alias Universal-Messaging-umserver UM-JNDI-CF-connection_factory_name` command.
- Delete a JNDI destination using the `sagcc delete configuration data node_alias Universal-Messaging-umserver UM-JNDI-DEST-destination_name` command.

**Note:**

Deleting a JNDI destination will not delete the channel or queue that exists on the Universal Messaging server instance.

Examples:

- To view all the configuration types for a Universal Messaging server instance:

```
sagcc get configuration types sag01 Universal-Messaging-umserver
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running.

- To view all the configuration instances for a Universal Messaging server instance:

```
sagcc get configuration instances sag01 Universal-Messaging-umserver
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running.

- To create a new JNDI connection factory by passing parameters defined in an XML file:

```
sagcc create configuration data sag01 Universal-Messaging-umserver
UM-JNDI-CF -i C:\jndi\connecton_factory.xml
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. UM-JNDI-CF is the configuration type and C:\jndi\connecton\_factory.xml is the absolute path to the XML file in which the parameters are defined. Example of properties defined in the XML file:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<connectionFactory>
  <name>connectionfactory1</name>
  <type>ConnectionFactory</type>
  <url>nhp://124.597.890:9100</url>
  <durableType>Shared</durableType>
</connectionFactory>
```

- To create a new JNDI destination by passing parameters defined in an XML file:

```
sagcc create configuration data sag01 Universal-Messaging-umserver
UM-JNDI-DEST -i C:\jndi\destination.xml
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. UM-JNDI-DEST is the configuration type and C:\jndi\destination.xml is the absolute path to the XML file in which the parameters are defined. Example of properties defined in the XML file:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<destination>
  <name>topicLookup</name>
  <type>destination1</type>
  <storeName>topic1</storeName>
  <autoCreateDest>true</autoCreateDest>
</destination>
```

- To retrieve information about a specific JNDI connection factory:

```
sagcc get configuration data sag01 Universal-Messaging-umserver
UM-JNDI-CF-connectionfactory1
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. UM-JNDI-CF is the configuration type and connectionfactory1 is the name of the JNDI connection factory from which information is to be retrieved.

- To retrieve information about a specific JNDI destination:

```
sagcc get configuration data sag01 Universal-Messaging-umserver
UM-JNDI-DEST-destination1
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. UM-JNDI-DEST is the configuration type and destination1 is the name of the JNDI destination from which information is to be retrieved.

- To update a JNDI connection factory by passing the new parameters defined in an XML file:

```
sagcc update configuration data sag01 Universal-Messaging-umserver
UM-JNDI-CF-connectionfactory1 -i C:\jndi\update.xml
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. UM-JNDI-CF is the configuration type, onnectionfactory1 is the name of the connection factory to be updated, and C:\jndi\update.xml is the absolute path to the XML file in which the updated parameters are defined. Example of properties defined in the XML file:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<connectionFactory>
  <name>connectionfactoryupdated</name>
  <type>ConnectionFactory</type>
  <url>nhp://124.597.890:9100</url>
  <durableType>Serial</durableType>
</connectionFactory>
```

- To delete a JNDI connection factory:

```
sagcc delete configuration data sag01 Universal-Messaging-umserver
UM-JNDI-CF-connectionfactory1
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. UM-JNDI-CF is the configuration type and connectionfactory1 is the name of the JNDI connection factory.

- To delete a JNDI destination:

```
sagcc delete configuration data sag01 Universal-Messaging-umserver
UM-JNDI-DEST-destination1
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. UM-JNDI-DEST is the configuration type and destination1 is the name of the JNDI destination.

### Usage Notes

- Updating JNDI destinations is not supported.
- Creating a connection factory and destination with the same name is not allowed for a Universal Messaging server instance.

## Channel and Queue Configuration

Ensure that the Universal Messaging server instance is running before running the following commands.

- View all the configuration instances for a Universal Messaging server instance using the `sagcc get configuration instances node_alias Universal-Messaging-umserver` command.
- Create a channel on a Universal Messaging server instance using the `sagcc create configuration data node_alias Universal-Messaging-umserver UM-CHANNELS -i absolute path to the XML file containing channel properties` command.
- Update a channel on a Universal Messaging server instance using the `sagcc update configuration data node_alias Universal-Messaging-umserver UM-CHANNELS-channel_name -f xml -i absolute path to the XML file containing channel properties` command.
- Create a queue on a Universal Messaging server instance using the `sagcc create configuration data node_alias Universal-Messaging-umserver UM-QUEUES -i absolute path to the XML file containing queue properties` command.
- Update a queue on a Universal Messaging server instance using the `sagcc update configuration data node_alias Universal-Messaging-umserver UM-QUEUES-queue_name -f xml -i absolute path to the XML file containing channel properties` command.
- Retrieve the configuration information of a specific channel using the `sagcc get configuration data node_alias Universal-Messaging-umserver UM-CHANNELS-channel_name` command.
- Retrieve the configuration information of a specific queue using the `sagcc get configuration data node_alias Universal-Messaging-umserver UM-QUEUES-queue_name` command.

Examples:

- To view all the configuration instances for a Universal Messaging server instance:

```
sagcc get configuration instances sag01 Universal-Messaging-umserver
```

sag01 is the alias name of the installation where the Universal-Messaging-umserver server instance is running.

- To create a channel on a Universal Messaging server instance:

```
sagcc create configuration data sag01 Universal-Messaging-umserver
UM-CHANNELS -i C:\Channels\channel_create.xml
```

sag01 is the alias name of the installation where the Universal-Messaging-umserver server instance is running. UM-CHANNELS is the configuration type and channel\_create.xml is an XML file containing the channel attributes of the new channel that is created.

Format of the channel\_create.xml file:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<Channel>
  <name>channel1</name>
  <type>Persistent</type>
  <ttl>0</ttl>
  <capacity>0</capacity>
```

```
.....
</Channel>
```

- To update a channel on a Universal Messaging server instance:

```
sagcc update configuration data sag01 Universal-Messaging-umserver
UM-CHANNELS-channel1 -f xml -i C:\Channels\channel_edited.xml
```

sag01 is the alias name of the installation where the Universal-Messaging-umserver server instance is running. UM-CHANNELS-channel1 is the configuration type, in which channel1 is the name of the channel. channel\_edited.xml is an XML file containing the channel attributes to be updated.

Format of the channel\_edited.xml file:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<Channel>
  <name>channel1</name>
  <type>Persistent</type>
  <ttl>50000</ttl>
  <capacity>50000</capacity>
  <deadEventStore/>
  <engine>JMS Engine</engine>
  .....
</Channel>
```

- To create a queue on a Universal Messaging server instance:

```
sagcc create configuration data sag01 Universal-Messaging-umserver
UM-QUEUES -i C:\queues\queue_create.xml
```

sag01 is the alias name of the installation where the Universal-Messaging-umserver server instance is running. UM-QUEUES is the configuration type and queue\_create.xml is an XML file containing the attributes of the new queue.

Format of the queue\_create.xml file:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<Queue>
  <name>queue1</name>
  <type>Persistent</type>
  <ttl>78</ttl>
  <capacity>99</capacity>
  <parent>umserver</parent>
  .....
</Queue>
```

- To update a queue on a Universal Messaging server instance:

```
sagcc update configuration data sag01 Universal-Messaging-umserver
UM-QUEUES-queue1 -f xml -i C:\queues\queue_edited.xml
```

sag01 is the alias name of the installation where the Universal-Messaging-umserver server instance is running. UM-QUEUES-queue1 is the configuration type, in which queue1 is the name of the queue. queue\_edited.xml is an XML file containing the queue attributes to be updated.

Format of the queue\_edited.xml file:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<Queue>
  <name>queue1</name>
  <type>Persistent</type>
  <ttl>50000</ttl>
  <capacity>50000</capacity>
  <parent>umserver</parent>
  <deadEventStore/>
  .....
</Queue>
```

- To retrieve configuration information about a specific channel:

```
sagcc get configuration data sag01 Universal-Messaging-umserver
UM-CHANNELS-channel1
```

sag01 is the alias name of the installation where the Universal-Messaging-umserver server instance is running. UM-CHANNELS-channel1 is the configuration type, in which channel1 is the name of the channel.

- To retrieve configuration information about a specific queue:

```
sagcc get configuration data sag01 Universal-Messaging-umserver
UM-QUEUES-queue1
```

sag01 is the alias name of the installation where the Universal-Messaging-umserver server instance is running. UM-QUEUES-queue1 is the configuration type, in which queue1 is the name of the queue.

## Zones Configuration

Ensure that the Universal Messaging server instances are running before running the following commands.

- Retrieve zone configuration information for a Universal Messaging server instance using the `sagcc get configuration data node_alias Universal-Messaging-umserver UM-ZONE` command.
- Create a zone using the `sagcc create configuration data node_alias Universal-Messaging-umserver UM-ZONE -i=path to the XML file containing the zone configuration` command.

### Note:

Provide the absolute path to the XML file if the XML file is not in the same directory from which the command is run.

- Update a zone using the `sagcc update configuration data node_alias Universal-Messaging-umserver UM-ZONE -i=path to the XML file containing the updated zone configuration` command.

### Note:

Provide the absolute path to the XML file if the XML file is not in the same directory from which the command is run.

- Delete a zone using the `sagcc delete configuration data node_alias Universal-Messaging-umserver UM-ZONE` command. The delete command deletes the zone in

which *umserver* belongs. You can remove specific server instances from a zone by removing the server instances in the updated zone configuration XML file, and then using the update zone command.

Examples:

- To retrieve zone configuration information for a Universal Messaging server instance:

```
sagcc get configuration data sag01 Universal-Messaging-umserver UM-ZONE
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. UM-ZONE is the configuration type for zones.

- To create a zone:

```
sagcc create configuration data sag01 Universal-Messaging-umserver UM-ZONE
-i=C:\zones\zone_create.xml
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. UM-ZONE is the configuration type for zones. And, c:\zones\zones\_create.xml is the absolute path to the location where the zone configuration XML file is located.

Format of the zone\_create.xml file for zone with realms:

```
<?xml version="1.0" encoding="UTF-8"?>
<Zone>
  <name>RealmZone</name>
  <type>Realm</type>
  <realms>
    <server name="um_realm1">
      <url>nsp://localhost:9701</url>
    </server>
    <server name="um_realm2">
      <url>nsp://localhost:9702</url>
    </server>
  </realms>
  <clusters/>
</Zone>
```

Format of the zone\_create.xml file for a zone with clusters:

```
<?xml version="1.0" encoding="UTF-8"?>
<Zone>
  <name>ClusterZone</name>
  <type>Cluster</type>
  <realms />
  <clusters>
    <server name="um_cluster1">
      <url>nsp://localhost:9704</url>
      <clusterName />
      <status />
    </server>
    <server name="um_cluster2">
      <url>nsp://localhost:9705</url>
      <clusterName />
      <status />
    </server>
  </clusters>
```

```
</Zone>
```

- To update a zone:

```
sagcc update configuration data sag01 Universal-Messaging-umserver UM-ZONE
-i=C:\zones\zone_update.xml
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. UM-ZONE is the configuration type for zones. And, c:\zones\zone\_update.xml is the absolute path to the location where the zone configuration XML file is located.

**Note:**

zone\_update.xml file should be in the same format as the XML file used to create zones. You can substitute the updated configuration values in place of the old values.

- To delete a zone:

```
sagcc delete configuration data local Universal-Messaging-umserver UM-ZONE
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. UM-ZONE is the configuration type for zones.

## Cluster Configuration

### Before you create or update a Universal Messaging cluster:

- Make sure the server instances that you want to add to the cluster are running.
- Verify that the permissions on the server machines allow connections to the other servers in the cluster.
- Make sure the /naming/defaultContext channel exists only on one or none of the nodes that will form the cluster. The Universal Messaging server instance used as a JNDI provider uses the /naming/defaultContext channel to store JMS references and JNDI objects. If channels exists on multiple nodes, you cannot create the cluster.
- If you have created custom composite templates for Command Central 9.9 or earlier, ensure that you remove the Universal Messaging server instance name suffix from COMMON-CLUSTER configuration type in the composite template when applying the composite template in Command Central 9.10 or later. For example,

In Command Central 9.9 and earlier:

```
um-cluster:
  description: Cluster configuration for two UM instances
  products:
    NUMRealmServer:
      ${node.host}:
        instance.port: ${um.instance.port}
        instance.ip:  ${um.host}
        runtimeComponentId: Universal-Messaging-${instance.name}
        configuration:
          Universal-Messaging-${instance.name}:
            COMMON-CLUSTER:
              COMMON-CLUSTER-${instance.name}: &umClusterConfig
              Name: ${um.cluster}
```

```

Servers:                                     # two UM instances cluster
  Server:
  -
    "@name": ${um.host}
    URL: "nsp://${um.host}:${um.instance.port}"
  -
    "@name": ${um.host2}
    URL: "nsp://${um.host2}:${um.instance.port2}"

```

### In Command Central 9.10 and later:

```

um-cluster:
  description: Cluster configuration for two UM instances
  products:
    NUMRealmServer:
      ${node.host}:
        instance.port: ${um.instance.port}
        instance.ip:   ${um.host}
        runtimeComponentId: Universal-Messaging-${instance.name}
        configuration:
          Universal-Messaging-${instance.name}:
            COMMON-CLUSTER:
              COMMON-CLUSTER: &umClusterConfig
              Name: ${um.cluster}
              Servers:
                Server:
                -
                  "@name": ${um.host}
                  URL: "nsp://${um.host}:${um.instance.port}"
                -
                  "@name": ${um.host2}
                  URL: "nsp://${um.host2}:${um.instance.port2}"

```

### Create a Universal Messaging cluster:

To create an active/active cluster of Universal Messaging server instances, input the cluster configuration details in an XML file to the `sagcc create configuration data` command.

Configure...	By specifying...
Cluster name	Cluster name that is unique to an installation.
Server instances	Name, URL, and port of each server node.
Sites (Optional)	Name of the site to which each server node belongs.  <code>siteName</code> is a server level property.
Primary site (Optional)	Name of the primary site, if you have configured sites in the cluster.  <code>primeSite</code> is a cluster level property that holds the name of the site, which is flagged as <code>isPrime</code> .

To create a new cluster with the following configurations specified in the `umSalesClusterConfig.xml` file:

- Cluster name: `umSales`

- Cluster sites: site1 and site2
- Primary site: site1
- Server instances in site1: um9000, um9001
- Server instances in site2: um9002, um9003

```
sagcc create configuration data sag01 Universal-Messaging-um9001  
COMMON-CLUSTER --input C:\inputxmls\umSalesClusterConfig.xml
```

where `sag01` is the alias name of the installation where `Universal-Messaging-um9001` server instance is running. The cluster configurations are specified in the `umSalesClusterConfig.xml` file as shown:

```
<?xml version="1.0" encoding="UTF-8"?>  
<ClusterSettings>  
  <Name>umSales</Name>  
  <Servers>  
    <Server name="um9000">  
      <URL>nsp://127.0.0.1:9000</URL>  
      <ExtendedProperties>  
        <Property name="siteName">site1</Property>  
      </ExtendedProperties>  
    </Server>  
    <Server name="um9001">  
      <URL>nsp://127.0.0.1:9001</URL>  
      <ExtendedProperties>  
        <Property name="siteName">site1</Property>  
      </ExtendedProperties>  
    </Server>  
    <Server name="um9002">  
      <URL>nsp://127.0.0.1:9002</URL>  
      <ExtendedProperties>  
        <Property name="siteName">site2</Property>  
      </ExtendedProperties>  
    </Server>  
    <Server name="um9003">  
      <URL>nsp://127.0.0.1:9003</URL>  
      <ExtendedProperties>  
        <Property name="siteName">site2</Property>  
      </ExtendedProperties>  
    </Server>  
  </Servers>  
  <ExtendedProperties>  
    <Property name="primeSite">site1</Property>  
  </ExtendedProperties>  
</ClusterSettings>
```

To retrieve the following details of the Universal Messaging cluster in an XML file, specify one of the server instances of the cluster in the `sagcc get configuration data` command.

- Name of the cluster
- Name, URL, and port of each Universal Messaging server instance in the cluster
- Site information, if sites are configured

Examples:

To view the details of the cluster configuration of the um9001 Universal Messaging server instance:

```
sagcc get configuration data sag01 Universal-Messaging-um9001 COMMON-CLUSTER
```

where sag01 is the alias name of the installation where Universal-Messaging-um9001 server instance is running.

To update a Universal Messaging cluster:

The XML file used for configuring a cluster must contain all the specifications for the cluster. When you update a cluster, you only edit the parameters that specify the change; other specifications in the cluster configuration file should not be changed. You can make these Universal Messaging cluster configurations changes:

To...	Edit the cluster configuration XML file to...
Add one or more server instances to the existing cluster	Include the name, URL, and port of the server instances that you want to add to the cluster.
Remove one or more server instances from the existing cluster	Remove the specifications of the server instances that you want to remove from the existing cluster.
Create sites and assign server instances to sites	Set the siteName extended property of the corresponding server instances.
Assign a site as the prime site of a cluster	Assign the name of the prime site to the primeSite cluster level property.
Remove one or more server instances from a cluster site	Remove the siteName extended property of the corresponding server instances.
Remove sites from a cluster	Remove the site definitions of all the server instances in the cluster.

Usage notes:

A Universal Messaging server instance can be part of only one cluster.

If you remove all the server instances from a site, the site will be deleted. Server instance deletion is not allowed if the deletion operation leaves less than two server instances in the cluster

Example when running on Command Central

To update the configuration of the cluster that contains the um9001 server instance:

```
sagcc update configuration data sag01 Universal-Messaging-um9001  
COMMON-CLUSTER --input C:\inputxmls\umSalesClusterConfig.xml
```

where sag01 is the alias name of the installation where Universal-Messaging-um9001 server instance is running.

To delete Universal Messaging cluster:

Delete the cluster by specifying one of the server instances of the cluster using the `sagcc delete configuration data` command.

Example:

To delete the cluster that contains the `um9001` server instance:

```
sagcc delete configuration data sag01 Universal-Messaging-um9001  
COMMON-CLUSTER
```

where `sag01` is the alias name of the installation where `Universal-Messaging-um9001` server instance is running.

#### Migrate a Universal Messaging cluster:

You can migrate a Universal Messaging cluster automatically even if the nodes are installed on multiple hosts.

To automatically migrate a Universal Messaging cluster:

1. Add the following extended property to the source Universal Messaging cluster configuration XML file:

```
<ExtendedProperties>  
  <Property name="crossHostMigration">true</Property>  
</ExtendedProperties>
```

2. Run the `sagcc update configuration data` command.

A remote realms bootstrap configuration file is created in the *Universal Messaging\_directory/bin*.

#### Monitoring Channels and Queues

You can retrieve information about channels and queues using the following commands:

- View the list of administration namespaces using the `sagcc get administration component node_alias Universal-Messaging-umserver` command.
- Retrieve all the configuration information about a channel in XML format using the `sagcc get configuration data node_alias Universal-Messaging-umserver UM-CHANNELS-channel name` command.
- Retrieve information about the options available for monitoring channels using the `sagcc get administration component node_alias Universal-Messaging-umserver channels` command.
- List the channels on a Universal Messaging server instance using the `sagcc get administration component node_alias Universal-Messaging-umserver channels list` command.
- Retrieve the status of a specific channel in TSV format using `sagcc get administration component node_alias Universal-Messaging-umserver channels status name=channel name` command.

- Retrieve a list of durable subscribers on a specific channel in TSV format using the `sagcc get administration component node_alias Universal-Messaging-umserver channels durablesubscribers name=channel name` command.
- Delete a durable subscriber subscribed to a channel using `sagcc exec administration component node_alias Universal-Messaging-umserver channels deletedurablesubscriber name=channel_name durablesubscriber=durable subscriber name`

#### Examples:

- To view the list of administration namespaces:

```
sagcc get administration component sag01 Universal-Messaging-umserver
```

`sag01` is the alias name of the installation where `Universal-Messaging-umserver` server instance is running.

- To retrieve all the configuration information about a channel:

```
sagcc get configuration data sag01 Universal-Messaging-umserver
UM-CHANNELS-channelname
```

`sag01` is the alias name of the installation where `Universal-Messaging-umserver` server instance is running. `UM-CHANNELS` is the configuration type and `channelname` is the name of the channel from which the information is to be retrieved.

- To retrieve information about the options available for monitoring channels:

```
sagcc get administration component sag01 Universal-Messaging-umserver channels
```

`sag01` is the alias name of the installation where `Universal-Messaging-umserver` server instance is running.

- To retrieve the list of channels on a Universal Messaging server instance:

```
sagcc get administration component sag01 Universal-Messaging-umserver channels
list
```

`sag01` is the alias name of the installation where `Universal-Messaging-umserver` server instance is running. `list` is the command to list all the channels in a server instance.

- To retrieve the status of a specific channel in TSV format:

```
sagcc get administration component sag01 Universal-Messaging-umserver channels
status name=channel_name
```

`sag01` is the alias name of the installation where `Universal-Messaging-umserver` server instance is running. `channel_name` is the channel name for which the status is to be retrieved.

- To retrieve a list of durable subscribers on a specific channel in TSV format:

```
sagcc get administration component sag01 Universal-Messaging-umserver channels
durablesubscribers name=channel_name
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. channel\_name is the name of the channel from which the durable subscribers list is to be retrieved.

- To delete a durable subscriber subscribed to a channel:

```
sagcc exec administration component sag01 Universal_Messaging-umserver channels
deletedurablessubscriber name=channel_name durablessubscriber=durable_subscriber_name
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. channel\_name is the name of the channel, and durable\_subscriber\_name is the name of the durable subscriber that has to be deleted from this channel.

## Monitoring Durable Subscribers

You can monitor durable subscribers using the following commands:

- View the list of administration namespaces using the `cc get administration component node_alias Universal-Messaging-umserver` command.
- Retrieve information about the options available for monitoring durable subscribers using the `cc get administration component node_alias Universal-Messaging-umserver durablesubscribers` command.

- Retrieve the list of durable subscribers of an Universal Messaging server instance using:

```
sagcc get administration component node_alias Universal-Messaging-umserver
durablesubscribers list -f xml command for XML format.
```

```
sagcc get administration component node_alias Universal-Messaging-umserver
durablesubscribers list -f tsv command for TSV format.
```

```
sagcc get administration component node_alias Universal-Messaging-umserver
durablesubscribers list -f csv command for CSV format.
```

- Retrieve the attributes of a specific durable subscriber using:

```
sagcc get administration component node_alias Universal-Messaging-umserver
durablesubscribers details channel=channel_name name=durable subscriber name -f xml
command for XML format.
```

```
sagcc get administration component node_alias Universal-Messaging-umserver
durablesubscribers details channel=channel_name name=durable subscriber name -f TSV
command for TSV format.
```

```
sagcc get administration component node_alias Universal-Messaging-umserver
durablesubscribers details channel=channel_name name=durable subscriber name -f CSV
command for CSV format.
```

- Retrieve specific attributes of the durable subscribers using the `cc get administration component node_alias Universal-Messaging-umserver durablesubscribers list -f tsv or csv properties=comma separated attribute list` command.

- Retrieve the list of events for a durable subscriber using the `cc get administration` component `node_alias Universal-Messaging-umserver durablesubscribers getDurableEvents durableName=durable name chanName=channel name`
- Purge a specified range of events using the `cc get administration` component `node_alias Universal-Messaging-umserver durablesubscribers purgeStartEndID startEID=start event ID endEID=end event ID durableName=durable subscriber name chanName=channel_name`
- Purge all events using the `cc get administration` component `node_alias Universal-Messaging-umserver durablesubscribers purgeAll durableName=durable subscriber name chanName=channel_name` command.
- Purge events by filtering events using the `cc get administration` component `node_alias Universal-Messaging-umserver durablesubscribers purgeFilter durableName=durable subscriber name chanName=channel_name filter=the filter expression` command.
- Delete a durable subscriber using the `sagcc exec administration` component `node_alias Universal-Messaging-umserver durablesubscribers delete channel=channel_name name=durable subscriber name`

#### Examples:

- To list all the administration namespaces:

```
sagcc get administration component sag01 Universal-Messaging-umserver
```

`sag01` is the alias name of the installation where `Universal-Messaging-umserver` server instance is running.

- To retrieve information about the options available for monitoring durable subscribers:

```
sagcc get administration component sag01 Universal-Messaging-umserver durablesubscribers
```

`sag01` is the alias name of the installation where `Universal-Messaging-umserver` server instance is running.

- To retrieve the list of durable subscribers in a Universal Messaging server instance:

#### XML format

```
sagcc get administration component sag01 Universal-Messaging-umserver durablesubscribers list -f xml
```

#### TSV format

```
sagcc get administration component sag01 Universal-Messaging-umserver durablesubscribers list -f tsv
```

#### CSV format

```
sagcc get administration component sag01 Universal-Messaging-umserver durablesubscribers list -f csv
```

- To retrieve attributes of the durable subscribers:

#### XML format

```
sagcc get administration component sag01 Universal-Messaging-umserver
durableSubscribers details channel=channelname name=durable_subscriber_name
-f xml
```

#### TSV format

```
sagcc get administration component sag01 Universal-Messaging-umserver
durableSubscribers details channel=channelname name=durable_subscriber_name
-f tsv
```

#### CSV format

```
sagcc get administration component sag01 Universal-Messaging-umserver
durableSubscribers details channel=channelname name=durable_subscriber_name
-f csv
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. channelname is the name of the channel, and durable\_subscriber\_name is the name of the durable subscriber from which the attributes are to be retrieved.

- To retrieve the attributes specific attributes of a durable subscriber:

```
sagcc get administration component sag01 Universal-Messaging-umserver
durableSubscribers list -f tsv properties=name,channel,lastEventID,
outStandingEvents
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. name, channel, lastEventID, and outStandingEvents are attribute values to be retrieved.

- To retrieve the list of events for a durable subscriber:

```
sagcc exec administration component sag01 Universal-Messaging-umserver
durableSubscribers getDurableEvents durableName=durablename
chanName=channelname
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. durablename is the name of the durable subscriber, and channelname is the name of the channel on which the durable subscriber exists.

- To purge a specified range of events:

```
sagcc exec administration component sag01 Universal-Messaging-umserver
durableSubscribers purgeStartEndID startEID=10 endEID=20
durableName=durablename chanName=channelname
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. startEID is the the start event ID for the range, endEID is the end event ID of the range, durablename is the name of the durable subscriber, and channelname is the name of the channel on which the durable subscriber exists.

- To purge all the events for a durable subscriber:

```
sagcc exec administration component sag01 Universal-Messaging-umserver
durableSubscribers purgeAll durableName=durablename chanName=channelname
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. durableName is the name of the durable subscriber, and channelName is the name of the channel on which the durable subscriber exists.

- To purge events by filtering events:

```
sagcc exec administration component sag01 Universal-Messaging-umserver
durableSubscribers purgeFilter durableName=durableName chanName=channelName
filter=size BETWEEN 10.0 AND 12.0
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. durableName is the name of the durable subscriber, and channelName is the name of the channel on which the durable subscriber exists.

- To delete a durable subscriber:

```
sagcc exec administration component sag01 Universal-Messaging-umserver
durableSubscribers delete channel=channelName name=DS3
```

sag01 is the alias name of the installation where Universal-Messaging-umserver server instance is running. channelName is the name of the channel on which the durable subscriber exists, and durableName is the name of the durable subscriber.

## Inventory

sagcc get inventory components and sagcc list inventory components gets and lists Universal Messaging inventory:

The commands retrieve information about the Universal Messaging server instances configured in the *Universal Messaging\_directory* \server directory in an installation. Information from all the folders under the server directory, except templates, is displayed.

Property	Value
Display name	Universal-Messaging-ServerInstanceName
Run-time component ID	Universal-Messaging-ServerInstanceName
Product ID	NUMRealmServer
Run-time component category	PROCESS

### Note:

*ServerInstanceName* can include upper and lower case alphabetic characters, digits (0-9), and underscores (\_) but cannot include hyphens (-), periods (.), and colons (:).

## Lifecycle Actions

The following table lists the actions that Universal Messaging supports with the sagcc exec lifecycle command and the operation taken against a Universal Messaging server when an action is executed.

Action	Description
start	Starts the Universal Messaging server instance. When successful, the Universal Messaging server instance run-time status is set to ONLINE.
stop	Stops the Universal Messaging server instance. The Universal Messaging server run-time status is STOPPED.
restart	Stops, then restarts the Universal Messaging server instance. The Universal Messaging server run-time status is set to ONLINE.

## Key Performance Indicators

`sagcc get monitoring runtimestate` and `sagcc get monitoring state` commands provide information about the following key performance indicators (KPIs) for a Universal Messaging server instance:

KPI	Description
JVM memory usage	<p>Indicates the utilization of JVM memory.</p> <p>The KPI uses the following marginal, critical, and maximum values:</p> <ul style="list-style-type: none"> <li>■ Marginal is 80% of the maximum JVM memory.</li> <li>■ Critical is 95% of the maximum JVM memory.</li> <li>■ Maximum is 100% of the maximum JVM memory.</li> </ul>
Fanout backlog	<p>Indicates the total number of events currently waiting to be processed by the fanout engine. If the fanout backlog is more than the critical value, there is a possibility that the subscribers receive the published events after some delay.</p> <p>The KPI uses the following marginal, critical, and maximum values:</p> <ul style="list-style-type: none"> <li>■ Marginal is 80% of the maximum value.</li> <li>■ Critical is 95% of the maximum value.</li> <li>■ Maximum is 100% of the peak value (high-water mark) of fanout backlog. Default is 100.</li> </ul>
Tasks queued for read and write	<p>Indicates the total number of tasks in the read, write, and common read/write pools. If the number of read and write tasks queued is more than the critical value, it indicates that the Universal Messaging server instance is unable to match the speed of the publishers and subscribers.</p> <p>The KPI uses the following marginal, critical, and maximum values:</p> <ul style="list-style-type: none"> <li>■ Marginal is 80% of the maximum value.</li> </ul>

KPI	Description
	<ul style="list-style-type: none"> <li>■ Critical is 95% of the maximum value.</li> <li>■ Maximum is 100% of the peak value (high-water mark) of read and write tasks queued. Default is 100.</li> </ul>

For more information about the Universal Messaging server instance KPIs, see information about monitoring Universal Messaging server instance in [“Universal Messaging Run-time Monitoring Statuses”](#) on page 417.

## Run-time Monitoring Statuses

`sagcc get monitoring runtimestatus` command lists the run-time statuses for a Universal Messaging server instance, the following table lists the run-time statuses.

### Note:

Universal Messaging server instance does not return the STARTING and STOPPING statuses.

Run-time Status	Meaning
ONLINE	Universal Messaging server instance is running.
FAILED	Universal Messaging server instance is not running due to some failure. LOCK file exists.
STOPPING	Universal Messaging instance is being stopped. LOCK file exists.
STOPPED	Universal Messaging server instance is not running because it was shut down normally. LOCK file does not exist.
UNRESPONSIVE	Universal Messaging server instance does not respond to a ping operation. LOCK file exists and the Universal Messaging server instance is running.
UNKNOWN	The status of Universal Messaging server instance cannot be determined.
ONLINE_MASTER	Server instance is online and it is the master node in the cluster.
ONLINE_SLAVE	Server instance is online and it is the slave node in the cluster.
ERROR	Server instance is part of a cluster that does not satisfy the requisite quorum.

## Migrating a Universal Messaging Server Instance

Ensure that the target Universal Messaging has the migration utility installed.

For information about the migration utility, see *Upgrading Software AG Products*.

**Note:**

These commands must be run in the context and order documented in *Upgrading Software AG Products*. Otherwise, you may experience unpredictable results, possibly including corruption of your installation and data.

- View the command line help for the migration utility using the `sagcc list administration product node_alias NUMRealmServer migration help` command.
- Migrate all Universal Messaging server instances present in a source installation using `sagcc exec administration product node_alias NUMRealmServer migration migrate srcDir=SAG_Installation_directory` command.

**Note:**

Use this command when migrating from Universal Messaging server version 9.8 and later.

- Start migration by providing the source Universal Messaging instance name using the `sagcc exec administration product node_alias NUMRealmServer migration migrate srcDir=SAG_Installation_directory instanceName=instance_name[,instance_name,instance_name...]` command.

**Note:**

Use this command when migrating from Universal Messaging server version 9.8 and later.

- Start migration by passing arguments and using the `migrate.dat` file using the `sagcc exec administration product node_alias NUMRealmServer migration migrate srcDir=SAG_Installation_directory importFile=migrate.dat` command.

**Note:**

Use this command when migrating from Universal Messaging server 9.0 through 9.7. The arguments `silent` is set to `true` and `continueOnError` is set to `false` by default.

- Start migration using the Zip file from the old product installation using the `sagcc exec administration product node_alias NUMRealmServer migration migrate srcFile=old_installation.zip importFile=migrate.dat` command.
- Start migration using the Zip file from the old product installation and specifying the source Universal Messaging instance name using `sagcc exec administration product node_alias NUMRealmServer migration migrate srcFile=old_installation.zip instanceName=instance_name[,instance_name,instance_name...]` command.
- View APIs under the migration namespace using the `sagcc list administration product node_alias NUMRealmServer migration` command.
- View if Universal Messaging supports migration as a custom API using the `sagcc list administration product node_alias NUMRealmServer` command.

## Examples:

- To view command line help:

```
sagcc list administration product sag01 NUMRealmServer migration help
```

sag01 is the alias name of the installation where NUMRealmServer server instance is running. migration is the namespace for the custom Command Central API. help is the command to view the migration tool's command line help.

- To migrate all Universal Messaging server instances present in a source installation:

```
sagcc exec administration product sag01 NUMRealmServer
migration migrate srcDir=C:\SoftwareAG
```

sag01 is the alias name of the installation where NUMRealmServer server instance is running. migration is the namespace for the custom Command Central API. migrate is the command to access the migration tool. srcDir is the source Software AG installation directory.

- To start migrating an older server instance to a new NUMRealmServer server instance by providing the source instance name:

```
sagcc exec administration product sag01 NUMRealmServer
migration migrate srcDir=C:\SoftwareAG
instanceName=umserver1,umserver2
```

sag01 is the alias name of the installation where NUMRealmServer server instance is running. migration is the namespace for the custom Command Central API. migrate is the command to access the migration tool. srcDir is the source Software AG installation directory. instanceName is the comma separated names of the Universal Messaging instances that are to be migrated.

- To start migrating an older server instance to a new NUMRealmServer server instance using the migrate.dat file:

```
sagcc exec administration product sag01 NUMRealmServer
migration migrate srcDir=C:\SoftwareAG
silent=true importFile=migrate.dat
```

sag01 is the alias name of the installation where NUMRealmServer server instance is running. migration is the namespace for the custom Command Central API. migrate is the command to access the migration tool. srcDir is the source Software AG installation directory. importFile specifies the data file containing the migration settings.

- To start migration using the Zip file from the old product installation:

```
sagcc exec administration product sag01 NUMRealmServer
migration migrate srcFile=99Src.zip importFile=migrate.dat
```

sag01 is the alias name of the installation where NUMRealmServer server instance is running. migration is the namespace for the custom Command Central API. migrate is the command to access the migration tool. srcFile argument is used to provide the name of the Zip file from the source Universal Messaging instance. importFile specifies the archive file path containing migration settings.

- To view APIs under the migration namespace for the NUMRealmServer server instance:

```
sagcc list administration product sag01 NUMRealmServer migration
```

sag01 is the alias name of the installation where NUMRealmServer server instance is running.

- To view if Universal Messaging supports migration as a custom API:

```
sagcc list administration product sag01 NUMRealmServer
```

sag01 is the alias name of the installation where NUMRealmServer server instance is running.

# 4 Command Line Administration Tools

---

■ Introduction to the Administration Tools .....	452
■ Starting the Tools using the Tools Runner Application .....	452
■ Performing Standard Administration Tasks on Realms and Clusters .....	454
■ Running a Configuration Health Check .....	454
■ Collecting Realm Information .....	464

## Introduction to the Administration Tools

Universal Messaging provides a set of command line tools that allow you to perform many of the common actions available through Universal Messaging. Examples of how to use the tools are also provided.

The tools can in general be grouped into the following categories:

Category	Description
General administration tasks	<p>This is a set of tools for performing many of the common administration actions available through Universal Messaging.</p> <p>For example, the <code>CreateChannel</code> tool allows you to create a channel on a specified realm, with a number of optional arguments - including TTL, ACLs, and many more - available through the parameters passed to the tool.</p>
Configuration health checker	<p>This tool allows you to check your configuration setup for either a single realm or for a cluster. The tool notifies you of any errors or inconsistencies in your setup.</p> <p>You can run the health check on a running system (realm or cluster). You can also run the health check offline on the basis of XML files containing the configuration of a realm or cluster (one XML configuration file per realm).</p>

These tools are described in the following sections.

## Starting the Tools using the Tools Runner Application

To run a tool, you start the `Tools Runner` application and pass the name of the required tool as a parameter to this application, as well as any additional parameters required by the tool.

The `Tools Runner` application is located in `<Software_AG_directory>/UniversalMessaging/tools/runner`.

To start the `Tools Runner` application, use the appropriate command for Windows or Linux:


### Windows:

```
runUMTool.bat
```

### Linux:

```
runUMTool.sh
```

If you run `Tools Runner` with no arguments, this displays a list of installed tools, as well as instructions for using the `Tools Runner`, as shown in the following image.



```

C:\SoftwareAG\UniversalMessaging\tools\runner>runUMTool.bat
UM Tools Runner

This application can be used to launch different UM tools.
You must pass the tool name as a subcommand followed by the tool arguments.

Usage:
runUMTool <subcommand> [args]

Example:
runUMTool CreateChannel -rname=nsp://localhost:9000 -channelname=newchannel

Available subcommands:
1. Store tools
    <CreateChannel>
    <CreateDurable>
    <CreateJoin>
    <CreateQueue>
    <DeleteChannel>
    <DeleteDurable>
    <DeleteJoin>
    <DeleteQueue>
    <GetChannelInfo>
    <GetDurableInfo>
    <GetDurableStatus>
    <IdentifyLargeDurableOutstandingEvents>
    <ListChannels>
    <ListJoins>
    <MonitorChannels>
    <PurgeEvents>
2. Cluster tools
    <ClusterState>
    <CreateCluster>
    <DumpClusterNamedObjectsState>
3. Interface tools
    <AddHTTPInterface>
    <AddHTTPSInterface>
    <AddSHMInterface>
    <AddSSLInterface>
    <AddSocketInterface>
    <DeleteInterface>
    <ModifyInterface>

```

## Running a Tool

To run a specific tool, you pass the name of the tool as the first argument to the `Tools Runner` application. Doing so without any additional arguments will print the usage for the specific tool. For example, running

```
runUMTool.bat CreateChannel
```

will print the usage for the `CreateChannel` tool. The usage contains a description of the tool, and a list of the required and optional arguments that you can supply. Arguments which have a specific set of legal values will have these values displayed here. Also included in the usage are command line examples of running the tool.

To run a tool with additional arguments, each of the required arguments must be specified in the command. For example, the `CreateChannel` tool requires both a realm name and channel name to be specified:

```
runUMTool.bat CreateChannel -rname=nsp://localhost:9000 -channelname=channel
```

Additional optional arguments can be appended to the command in the same way; adding a channel type to the `CreateChannel` tool command would then be:

```
runUMTool.bat CreateChannel -rname=nsp://localhost:9000 -channelname=channel  
-type=R
```

## Performing Standard Administration Tasks on Realms and Clusters

---

Using the Tools Runner application, you can launch command line tools for performing standard administration tasks on realms and clusters.

Tools are available to perform the following tasks:

- Creating, deleting and monitoring channels and queues
- Creating clusters
- Adding, modifying and deleting interfaces (HTTP, HTTPS, SSL, Sockets)
- Adding and deleting ACL entries for channels, queues and realms

For example, the `CreateChannel` tool allows you to create a channel on a specified realm, with a number of optional arguments - including TTL, ACLs, and many more - available through the parameters passed to the tool.

To see the complete set of administration tools available, start the `Tools Runner` application without any parameters, as described in the section [“Starting the Tools using the Tools Runner Application” on page 452](#).

The names of the administration tools are self-explanatory, for example:

- `CreateChannel`
- `DeleteChannel`
- `GetChannelInfo`
- `ListChannels`
- `MonitorChannels`

## Running a Configuration Health Check

---

### Overview

The `HealthChecker` is a tool for checking the correctness of a realm or cluster configuration.

The tool is primarily intended for use by Software AG support staff for analyzing possible problems in customer configurations, but you might also find it useful for checking your configuration.

The tool can be used in the following ways:

- To check the configuration of a live realm (which can be a single entity or a node of a cluster) or a cluster. If the realm is a node of the cluster, the checks will also be automatically executed against all the other cluster members.
- To do an offline check of the configuration of a realm or cluster, based on configuration information that has been exported to XML files. Each such XML file contains the configuration data of a realm, regarding channels, queues, durables, datagroups, etc. The tool will only run the checks against all the cluster members if their XML paths are given explicitly in the call of the tool.

Typical configuration aspects that can be checked in a clustered realm are:

- **Datagroups:**

Datagroups belonging to a cluster must be present on all nodes of the cluster and their attributes must be the same.

- **Durables:**

Durables belonging to clusterwide channels should also be clusterwide. They must be present on all nodes of the cluster and their attributes must be the same.

- **Joins:**

Joins between clusterwide channels must be present on all nodes of the cluster and their attributes have to be the same.

- **Stores:**

Stores belonging to a cluster must be present on all nodes of the cluster and their attributes and properties must be the same.

Typical configuration aspects that can be checked in a non-clustered realm are:

- **Durables:**

Durables belonging to a non-clustered realm must be non-clusterwide and must be attached to a non-clusterwide channel.

- **Stores:**

Some store configurations may impact the performance of the system and they need to be highlighted.

## Checks against a live realm

The checks that can be run against a live realm are the following:

Name of Check	Description	Default check?
DataGroupMismatchCheck	Check if datagroups are coherent across all nodes of the cluster.	Y

Name of Check	Description	Default check?
DurableMismatchCheck	Check if durables are coherent across all nodes of the cluster.	Y
DurableSubscriberLargeStoreCheck	<p>Check the number of remaining events to be consumed in a shared durable. If the number is greater than the threshold a warning will be displayed. The default value for the threshold is 1000.</p> <p>This check takes an additional parameter <code>-threshold</code> that allows you to specify a custom value for the threshold.</p>	Y
EnvironmentStateCheck	<p>Check and display the status of a running environment.</p> <p>The HealthChecker first checks if the server configuration property <code>Enable Flow Control</code> in the configuration group <code>Server Protection</code> (see the note after this table) is set to true. If it is set to true then the HealthChecker will check what percentage of memory is taken by events from the whole heap memory. If the percentage is between 70 and 80, or between 80 and 90, or above 90, an appropriate warning will be displayed.</p> <p>The general idea is that Server Protection mechanism gradually slows the consumption of events from clients when a certain threshold is reached, and 70-80, 80-90 and &gt;90 are these thresholds.</p> <p>The degree of slowing down is marked by these three server configuration properties: <code>FlowControlWaitTimeOne</code>, <code>FlowControlWaitTimeTwo</code> and <code>FlowControlWaitTimeThree</code>. These represent a period of time, measured in milliseconds, by which client publishing requests will be delayed when the corresponding threshold has been reached.</p> <p>Threshold 70%-80%: A warning message is displayed that client publishing requests will be delayed by <code>FlowControlWaitTimeOne</code> milliseconds.</p> <p>Threshold 80%-90%: A warning message is displayed that client publishing requests will be delayed by <code>FlowControlWaitTimeTwo</code> milliseconds.</p>	Y

Name of Check	Description	Default check?
	Threshold 90%-100%: An error message is displayed that client publishing requests will be delayed by <code>FlowControlWaitTimeThree</code> milliseconds.	
<code>FixLevelCheck</code>	Check if the nodes of a given cluster have matching fix levels.	Y
<code>JNDIStatusCheck</code>	Check JNDI status and mismatches for stores.	Y
<code>JoinMismatchCheck</code>	Check if joins are coherent across all nodes of the cluster.	Y
<code>ResourcesSafetyLimitsCheck</code>	Check that channel/queue resources have either TTL or Capacity configured to a non-zero value. If both of these values are zero, this means that the channel/queue is not configured with any safety limits.	
<code>ServerProtectionConsistencyCheck</code>	Check if the server configuration properties in the configuration group <code>Server Protection</code> group (see the note after this table) are coherent across the nodes of a cluster against a running environment.	Y
<code>StoreMemoryCheck</code>	Check the memory usage of stores.	Y
<code>StoreMismatchCheck</code>	Check if stores are coherent across all nodes of the cluster.	Y
<code>StoreWarningsCheck</code>	Check store warnings on the specified realm.	

A "Y" in the column "Default check?" indicates that the check is included in the `-mode=default` setting (see the topic *The -mode parameter* below).

**Important:**

When the tool checks for outstanding durable events or event ID mismatches in a **live** environment, there is a chance of getting warning messages, even though the cluster is working correctly. This is because the check is not atomic for the live cluster, so a small synchronization discrepancy can be expected.

**Note:**

For further information about the server configuration parameters and the configuration group `Server Protection` mentioned in the table above, see the section [“Realm Configuration” on page 29](#).

### Checks against a realm's stored XML configuration

The checks that can be run against a stored XML configuration are the following:

Name of Check	Description	Default check?
XMLDataGroupMismatchCheck	Check if datagroups are coherent across all nodes of the cluster.	Y
XMLDurableMismatchCheck	Check if durables are coherent across all nodes of the cluster.	Y
XMLFixLevelCheck	Check if the nodes of a given cluster have matching fix levels.	Y
XMLJNDIStatusCheck	Check JNDI status and mismatches for stores.	Y
XMLJoinMismatchCheck	Check if joins are coherent across all nodes of the cluster.	Y
XMLResourcesSafetyLimitsCheck	Check that channel/queue resources have either TTL or Capacity configured to a non-zero value. If both of these values are zero, this means that the channel/queue is not configured with any safety limits.	
XMLServerProtectionConsistencyCheck	Check if the server configuration properties in the configuration group <code>Server Protection</code> are coherent across the nodes of a cluster against the exported configurations from the nodes.	Y
XMLStoreMismatchCheck	Check if stores are coherent across all nodes of the cluster.	Y
XMLStoreWarningsCheck	Check store warnings on the specified realm.	

## Command Usage

The syntax is as follows:

```
runUMTool HealthChecker [-rname=<rname> | -xml=/path/to/xml1,...]
  [-check=<checktype>[,<checktype> ...] ]
  [-mode=<modetype>]
  [-include=<checktype>[,<checktype> ...] ]
  [-exclude=<checktype>[,<checktype> ...] ]
  [-<additionalParameter1>=<value>] [-<additionalParameter2>=<value>] ...
```

### Displaying help text

To display a help text showing a summary of the command usage, call the HealthChecker without parameters:

```
runUMTool HealthChecker
```

### Running a health check of a running realm

```
runUMTool HealthChecker -rname=nsp://localhost:11000
```

This will run the HealthChecker tool against the given running realm.

### Running a health check of a stored realm configuration

```
runUMTool HealthChecker -xml=/path/to/xml1.xml, /path/to/xml2.xml
```

This will run the HealthChecker tool against the realm configurations stored in the given XML files.

### The `-check` parameter

This parameter allows you to explicitly specify the check or checks that you want to be executed. No other checks will be included. This parameter can only be used together with the `-rname` or `-xml` parameter; the other additional parameters have no meaning in the context of `-check` so they can't be used.

Example - Execute only the `Store Warnings Check` check against the running realm:

```
runUMTool HealthChecker -rname=nsp://localhost:11000
                        -check=StoreWarningsCheck
```

Example - Execute only the `Store Warnings Check` and `Fix Level Check` checks against the running realm:

```
runUMTool HealthChecker -rname=nsp://localhost:11000
                        -check=StoreWarningsCheck, FixLevelCheck
```

### The `-mode` parameter

This parameter allows you to select a predefined set of checks without having to name the checks explicitly. The `-mode` and `-check` parameters are mutually exclusive.

The mode parameter can take one of the following values:

- **default** - this value selects the recommended minimal subset of checks. This is the default option.
- **all** - this mode selects all checks.

If neither `-mode` nor `-check` is specified, the default set of checks will be executed.

### The `-include` and `-exclude` parameters

You can use the `-include` and `-exclude` parameters to further refine the set of checks that have been selected by the `-mode` parameter. You can use `-include` and `-exclude` in the same call of the health checker, as long as they do not specify the same check.

- **include** - Run all checks from the set defined by the `-mode` parameter, and additionally include the check or checks specified by this parameter. The parameter may contain a single check or a comma-separated list of checks.
- **exclude** - Run all checks from the set defined by the `-mode` parameter, except the specified check or checks. The parameter may contain a single check or a comma-separated list of checks.

## The `-<additionalParameter>` parameters

Some of the health checks allow you to specify one or more additional parameters when calling the HealthChecker. The name and purpose of each additional parameter is specific to the individual health check being run.

For example, the `DurableSubscriberLargeStoreCheck` check allows you to specify the additional parameter `-threshold=<value>`, which defines a threshold for the number of remaining events to be consumed in a shared durable.

The following general rules apply:

- Each additional parameter has a default value, so if you do not specify the additional parameters explicitly, the default values will be taken.
- If multiple additional parameters and multiple checks are specified, each individual check uses only its own additional parameters.
- The additional parameters can be given in any order.
- Checks that do not require additional parameters will ignore the additional parameters.

## Syntax Examples

Example - Execute all available checks for live realm check:

```
runUMTool HealthChecker -rname=nsp://localhost:11000 -mode=all
```

Example - Execute all the available checks except the ones mentioned.

```
runUMTool HealthChecker -rname=nsp://localhost:11000  
-mode=all -exclude=JNDIStatusCheck, FixLevelCheck, JoinMismatchCheck
```

Example - Execute the default set of checks, adding the `StoreWarningsCheck` which is not part of the default set.

```
runUMTool HealthChecker -rname=nsp://localhost:11000  
-mode=default -include= StoreWarningsCheck
```

Example - Execute the default set of checks but excluding the `JNDIStatusCheck`, `FixLevelCheck` and adding the `StoreWarningsCheck`.

```
runUMTool HealthChecker -rname=nsp://localhost:11000  
-mode=default -include= StoreWarningsCheck  
-exclude=JNDIStatusCheck, FixLevelCheck
```

### Note:

The previous examples are based on live checks using the `-realm` parameter. The same logic applies if you use the `-xml` parameter instead, but the names of the checks need to be adapted to the appropriate XML checks.

## Full Example

The following example compares the XML configuration files of two realms in a cluster. The realms are named `realm0` and `realm1`, and their configuration files are named `clustered_realm0.xml` and `clustered_realm1.xml`.

XML configuration file `clustered_realm0.xml` for `realm0`:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<NirvanaRealm name="realm0" exportDate="2016-11-08Z"
  comment="Realm configuration from realm0" version="BuildIdentifier"
  buildInfo="BuildIdentifier">
  <ClusterSet>
    <ClusterEntry name="cluster1">
      <ClusterMember name="realm1" rname="nsp://localhost:11010/"
        canBeMaster="true"/>
      <ClusterMember name="realm0" rname="nsp://localhost:11000/"
        canBeMaster="true"/>
    </ClusterEntry>
  </ClusterSet>
  <ChannelSet>
    <ChannelEntry>
      <ChannelAttributesEntry name="channel1" TTL="0" capacity="5" EID="0"
        clusterWide="true" jmsEngine="false" mergeEngine="false"
        type="PERSISTENT_TYPE"/>
      <StorePropertiesEntry HonorCapacityWhenFull="false"
        SyncOnEachWrite="false" SyncMaxBatchSize="0" SyncBatchTime="0"
        PerformAutomaticMaintenance="false" EnableCaching="true"
        CacheOnReload="true" EnableReadBuffering="true"
        ReadBufferSize="10240" Priority="4" EnableMulticast="false"
        StampDictionary="0" MultiFileEventsPerSpindle="50000"/>
      <ChannelJoinSet>
        <ChannelJoinEntry filter="" hopcount="50" to="channel2"
          from="channel1" allowPurge="false" archival="false"/>
      </ChannelJoinSet>
    </ChannelEntry>
    <ChannelEntry>
      <ChannelAttributesEntry name="channel2" TTL="0" capacity="0" EID="0"
        clusterWide="true" jmsEngine="false" mergeEngine="false"
        type="RELIABLE_TYPE"/>
      <StorePropertiesEntry HonorCapacityWhenFull="false"
        SyncOnEachWrite="false"
        SyncMaxBatchSize="0" SyncBatchTime="0"
        PerformAutomaticMaintenance="false"
        EnableCaching="true" CacheOnReload="true"
        EnableReadBuffering="true"
        ReadBufferSize="10240" Priority="4" EnableMulticast="false"
        StampDictionary="0" MultiFileEventsPerSpindle="50000"/>
      <DurableSet>
        <durableEntry name="durable1" EID="-1" outstandingEvents="0"
          clusterWide="true" persistent="true"
          priorityEnabled="false" shared="true"/>
      </DurableSet>
    </ChannelEntry>
  </ChannelSet>
  <QueueSet>
    <QueueEntry>
```

```

    <ChannelAttributesEntry name="queue1" TTL="0" capacity="0" EID="0"
      clusterWide="true" jmsEngine="false" mergeEngine="false"
      type="RELIABLE_TYPE"/>
    <StorePropertiesEntry HonorCapacityWhenFull="false"
      SyncOnEachWrite="false" SyncMaxBatchSize="0" SyncBatchTime="0"
      PerformAutomaticMaintenance="true" EnableCaching="true"
      CacheOnReload="true" EnableReadBuffering="true"
      ReadBufferSize="10240" Priority="4" EnableMulticast="false"
      StampDictionary="0" MultiFileEventsPerSpindle="50000"/>
  </QueueEntry>
</QueueSet>
</NirvanaRealm>

```

### XML configuration file clustered\_realm1.xml for realm1:

```

<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<NirvanaRealm name="realm1" exportDate="2016-11-16Z"
  comment="Realm configuration from realm1"
  version="BuildIdentifier" buildInfo="BuildIdentifier">
  <ClusterSet>
    <ClusterEntry name="cluster1">
      <ClusterMember name="realm1" rname="nsp://localhost:11010/"
        canBeMaster="true"/>
      <ClusterMember name="realm0" rname="nsp://localhost:11000/"
        canBeMaster="true"/>
    </ClusterEntry>
  </ClusterSet>
  <ChannelSet>
    <ChannelEntry>
      <ChannelAttributesEntry name="channel1" TTL="0" capacity="5" EID="0"
        clusterWide="true" jmsEngine="false" mergeEngine="false"
        type="RELIABLE_TYPE"/>
      <StorePropertiesEntry HonorCapacityWhenFull="false"
        SyncOnEachWrite="false" SyncMaxBatchSize="0" SyncBatchTime="0"
        PerformAutomaticMaintenance="false" EnableCaching="true"
        CacheOnReload="true" EnableReadBuffering="true"
        ReadBufferSize="10240" Priority="4" EnableMulticast="false"
        StampDictionary="0" MultiFileEventsPerSpindle="50000"/>
      <ChannelJoinSet>
        <ChannelJoinEntry filter="" hopcount="10" to="channel2"
          from="channel1" allowPurge="false" archival="false"/>
      </ChannelJoinSet>
    </ChannelEntry>
    <ChannelEntry>
      <ChannelAttributesEntry name="channel2" TTL="0" capacity="0" EID="0"
        clusterWide="true" jmsEngine="false" mergeEngine="false"
        type="RELIABLE_TYPE"/>
      <StorePropertiesEntry HonorCapacityWhenFull="false"
        SyncOnEachWrite="false" SyncMaxBatchSize="0" SyncBatchTime="0"
        PerformAutomaticMaintenance="false" EnableCaching="true"
        CacheOnReload="true" EnableReadBuffering="true"
        ReadBufferSize="10240" Priority="4" EnableMulticast="false"
        StampDictionary="0" MultiFileEventsPerSpindle="50000"/>
    </ChannelEntry>
  </ChannelSet>
  <DataGroupSet>
    <DataGroupEntry>
      <DataGroupAttributesEntry name="dg1" id="3422373812" priority="1"
        multicastenabled="false"/>
    </DataGroupEntry>
  </DataGroupSet>
</NirvanaRealm>

```

```

    </DataGroupEntry>
  </DataGroupSet>
</NirvanaRealm>

```

From a first analysis we can say that these two realms belong to the same cluster (cluster1) and that they both contain various stores, joins and data groups. But let's see what happens when we run the HealthChecker tool specifying both XML files and running all the checks. Note that we need to exclude the XMLServerProtectionConsistencyCheck since the specified XML files do not contain the RealmConfiguration section.

Here is the call of the tool (using Windows syntax) and the result:

```

runUMTool.bat HealthChecker -xml=clustered_realm0.xml,clustered_realm1.xml
                        -exclude=XMLServerProtectionConsistencyCheck
HealthChecker Tool - Version: 1.0

XML JOIN MISMATCHES CHECK
ERROR: Join from (channel1) to (channel2) HopCount mismatch [realm1] does not
      equal [realm0]

XML JNDI PROPERTIES CHECK
WARN: Realm realm0: No JNDI entry for store channel1
WARN: Realm realm0: No JNDI entry for store channel2
WARN: Realm realm0: No JNDI entry for store queue1
WARN: Realm realm1: No JNDI entry for store channel1
WARN: Realm realm1: No JNDI entry for store channel2

XML DURABLE STATUS CHECK
ERROR: Could not find durable (durable1) on realm [realm1] but it is present
      on [realm0]

XML FIX LEVEL CHECK

XML STORE MISMATCHES CHECK
WARN: Store (channel1) Type mismatch [realm1] does not equal [realm0]
ERROR: Could not find store (queue1) on realm [realm1] but it is present
      on realm [realm0]

XML DATAGROUP MISMATCHES CHECK
ERROR: Could not find Data Group (dg1) on realm [realm0] but it is present
      on realm [realm1]

```

These errors and warnings tell us:

- Joins: a join between two clusterwide channels has to be the same on all the nodes - in our case there is a mismatch in the HopCount;
- JNDIs: these simple warnings are saying: "Are you sure that you don't need any JNDI for these stores?";
- Durables: if a durable is clusterwide, then it has to be present on all the other nodes (and it has to be the same);
- Stores: if a store is clusterwide, then it has to be the same on all the other nodes.

- **Datagroups:** the same rule applies for datagroups, which are always clusterwide and have to be present on all the other nodes.

## Collecting Realm Information

### Overview

`RealmInformationCollector` is a command-line tool that gathers files and live data from one or more Universal Messaging realm servers. The tool can be executed in live and offline mode:

- **Live mode:** In live mode, the specified Universal Messaging realm server(s) must be running. The tool will collect files that contain operational data for each running realm server, but will also attempt to connect to and gather information directly from each running server process.
- **Offline mode:** In offline mode, the specified Universal Messaging realm server(s) must be offline.

In this mode, the tool will only collect files that contain operational data for each realm server.

The mode of operation (either offline or live) is a mandatory argument and must be specified when running the tool. You must ensure that the specified Universal Messaging realm servers are stopped when `-mode=offline`, or running when `-mode=live`.

Depending on the mode, the tool will collect different files. For example, in live mode, it will not collect the content of realm server's "data" directory, because this might cause failures on the server.

The tool collects information by executing a list of *collectors*. Each collector is responsible for gathering a specific subset of the realm's information.

### Collectors for a live realm server

The collectors that can be run against a live realm server are shown in the following table. Path names of files and directories given in the table are the installation defaults.

Name of Collector	Description	Default collector?
env	Collects environment information from a running realm server. This includes all JVM system properties and the list of Universal Messaging interfaces.	Y
healthchecker	Acquires health information from a running realm server using the HealthChecker tool. See the section <a href="#">“Running a Configuration Health Check”</a> on page 454 for details.	Y
heapdump	Acquires a heap dump from a running realm server using the <code>jmap</code> tool that is available in the Oracle-based JDK included in the Universal Messaging distribution kit.	

Name of Collector	Description	Default collector?
installlogs	Collects the product's installation log files. These files are located in <code>&lt;InstallDir&gt;/install/logs</code> .	Y
instancemgr	Collects the realm server's manager log. This file is located in <code>&lt;InstallDir&gt;/UniversalMessaging/tools/InstanceManager/instanceLog.txt</code> .	Y
jaas	Collects the JAAS configuration of a realm server. This file is located in <code>&lt;InstallDir&gt;/UniversalMessaging/server/&lt;realmname&gt;/bin/jaas.conf</code> .	Y
license	Collects the license file of a realm server. This file is located in <code>&lt;InstallDir&gt;/UniversalMessaging/server/&lt;realmname&gt;/licence.xml</code> .	Y
logs	Collects logs of a realm server. The location of the file is <code>&lt;InstallDir&gt;/UniversalMessaging/server/&lt;realmname&gt;/data/nirvana.log</code> If there are any rolled log files in addition to the current log file, for example <code>nirvana.log_&lt;timestamp1&gt;</code> and <code>nirvana.log_&lt;timestamp2&gt;</code> , these are collected also.	Y
plugins	Collects the plugins directory of a realm server. This directory is located at <code>&lt;InstallDir&gt;/UniversalMessaging/server/&lt;realmname&gt;/plugins</code> .	Y
realmconfig	Collects the realm configuration properties of a realm server. The properties are listed in the section <a href="#">“Realm Configuration” on page 29</a> . The collector delivers the configuration properties as a serialized XML file.	Y
secfile	Collects the security file of a realm server. This file is located at <code>&lt;InstallDir&gt;/UniversalMessaging/server/&lt;realmname&gt;/bin/secfile.conf</code> .	Y
tanukiconf	Collects the Tanuki service wrapper configuration of a realm server. This includes the files <code>nserver.conf</code> , <code>nserverdaemon.conf</code> , <code>Server_Common.conf</code> and <code>Custom_Server_Common.conf</code> , located at <code>&lt;InstallDir&gt;/UniversalMessaging/server/&lt;realmname&gt;/bin</code> .	Y
tanukilogs	Collects Tanuki service wrapper logs of a realm server.	Y

Name of Collector	Description	Default collector?
	This file is located at <InstallDir>/UniversalMessaging/server/<realmname>/bin/UMRealmService.log. If there are any rolled log files in addition to the current log file, for example UMRealmService.log.1 and UMRealmService.log.2, these are collected also.	
threaddump	Generates three thread dumps of a realm server. The dumps are taken at 15-second intervals. Having three dumps instead of one can make it easier to analyze time-related thread issues.	Y
version	Collects the realm server version. The version will be stored in the file UniversalMessaging/lib/nServer.jar_version.txt in the generated archive.	Y

A "Y" in the column "Default collector?" indicates that the collector is included by default when you run the RealmInformationCollector tool.

### Collectors for an offline realm server

The collectors that can be run against an offline realm server are the following (collectors that can be used also against a live realm server are indicated). Path names of files and directories given in the table are the installation defaults.

Name of Collector	Description	Default collector?
data	Collects the data directory of a realm server.  The location of this directory is <InstallDir>/UniversalMessaging/server/<realmname>/data.	
installlogs	(Same as the live collector)	Y
instancemgr	(Same as the live collector)	Y
jaas	(Same as the live collector)	Y
license	(Same as the live collector)	Y
logs	(Same as the live collector)	Y
plugins	(Same as the live collector)	Y
secfile	(Same as the live collector)	Y
tanukiconf	(Same as the live collector)	Y
tanukilogs	(Same as the live collector)	Y

Name of Collector	Description	Default collector?
version	(Same as the live collector)	Y

## Command Usage

The syntax is as follows:

```
runUMTool RealmInformationCollector
  -mode=live|offline [-username=<username> -password=<password>]
  -instance=*|<instanceName>[,<instanceName> ...]
  [-include=<collectorName>[,<collectorName> ...] ]
  [-exclude=<collectorName>[,<collectorName> ...] ]
  [-outputfile=<dir_or_file>]
```

### Displaying help text

To display a help text showing a summary of the command usage, call the `RealmInformationCollector` tool without parameters:

```
runUMTool RealmInformationCollector
```

### The `-mode` parameter

This parameter allows you to select the execution mode of the tool. The mode parameter is mandatory and can take one of the following values:

- **live** - the `RealmInformationCollector` tool will collect operational data files for each running realm server and also attempt to connect and gather information directly from each running realm server
- **offline** - the tool will collect operational data files only

In live mode, all specified realm servers (see the `-instance` parameter) must be running, whereas in offline mode, all specified realm servers must be stopped.

Also in live mode, the following collectors will connect to each specified running realm server to gather information, and will store the information in the following files under `UniversalMessaging/server/<InstanceName>/generated` in the generated archive:

Collector name	Generated file
env	envinfo.txt
realmconfig	RealmConfig.xml
healthchecker	healthchecker.txt
threaddump	Three thread dump files, generated at 15-second intervals, named <code>threaddump_&lt;timestamp&gt;.txt</code>

### The `-username` and `-password` parameters

When establishing the connection to a live realm server, the `RealmInformationCollector` tool will authenticate using the current operating system user. It is therefore recommended to run the `RealmInformationCollector` tool using the same user as the one used to run the realm server.

You can specify a different user using the `-username` and `-password` arguments.

### The `-instance` parameter

This parameter allows you to select the set of realm servers to collect information from. The parameter is mandatory and must contain either a single realm server name or a comma-separated list of realm server names. The specified realm servers must be available in the installation where the `RealmInformationCollector` tool is run from. You can specify `-instance=*` to select all installed realm servers.

### The `-include` and `-exclude` parameters

You can use the `-include` and `-exclude` parameters to further refine the set of collectors that have been selected by the `-mode` parameter. You can use `-include` and `-exclude` in the same call of the `RealmInformationCollector` tool as long as they do not specify the same collector name.

- **include** - Run all default collectors available with the specified `-mode` parameter, and additionally include the collector or collectors specified by this parameter. The parameter may contain a single collector name or a comma-separated list of collector names.
- **exclude** - Run all default collectors available with the specified `-mode` parameter, except the specified collector or collectors. The parameter may contain a single collector name or a comma-separated list of collector names.

### The `-output` parameter

Specifies the path where the generated zip archive will be stored.

If the path specifies a directory without a filename, the directory must already exist. The archive file will be generated in the specified directory using the following naming convention:

```
<InstallDir>_<mode>_<timestamp>.zip
```

For example, if the product installation directory is `C:\SoftwareAG` and the `RealmInformationCollector` tool is executed with `-mode=live`, the generated archive will be named for example `SoftwareAG_live_20171120100757940.zip`

If the path specifies a directory with a filename, the directory must already exist but the file must not already exist, and the tool will use the filename you specify.

If the parameter is not specified, the tool will generate an archive with a name corresponding to the naming convention mentioned above, and store the archive under the directory `<InstallDir>/UniversalMessaging/tools/runner`.

## Syntax Examples

Example: Execute default collectors in offline mode against the `umserver` instance:

```
runUMTool RealmInformationCollector -mode=offline -instance=umserver
```

Example: Execute default collectors and also the optional collector data in offline mode against the `umserver` instance:

```
runUMTool RealmInformationCollector
  -mode=offline -instance=umserver -include=data
```

Example: Execute default collectors and the optional collector data, excluding the `jaas` collector, in offline mode against all realm server instances:

```
runUMTool RealmInformationCollector
  -mode=offline -instance=* -include=data -exclude=jaas
```

Example: Execute default collectors in live mode against the `umserver` instance:

```
runUMTool RealmInformationCollector -mode=live -instance=umserver
```

Example: Execute the default collectors and the optional collector `heapdump` in live mode against the `umserver` instance:

```
runUMTool RealmInformationCollector
  -mode=live -instance=umserver -include=heapdump
```

Example: Execute the default collectors and the optional collector `heapdump`, excluding the `jaas` collector, in live mode against the `umserver` and `umserver2` instances:

```
runUMTool RealmInformationCollector
  -mode=live -instance=umserver,umserver2 -include=heapdump -exclude=jaas
```

Example: Execute the default collectors and the optional collector `heapdump` in live mode against the `umserver` instance and specify a custom location of the generated zip archive:

```
runUMTool RealmInformationCollector
  -mode=live -instance=umserver -include=heapdump
  -outputfile=C:/SoftwareAG_umserver_live.zip
```

## Operational Issues

- On Windows, if the product installation directory path is too long, acquiring a live heap dump may fail with the error "CreateProcess error=267, The directory name is invalid". You can work around this error by configuring the `-outputFile` parameter to use a shorter directory/file path, for example `C:/SoftwareAG_live.zip`.
- The `RealmInformationCollector` tool does not support connecting via SSL-secured network interfaces to the realm server. If all realm server network interfaces are secured using SSL, live collectors which need to connect to the server (`env`, `realmconfig`, `healthchecker`, `threaddump`) will fail to connect to the server. You can work around this by configuring a temporary non-SSL secured network interface.
- Live heap dump generation is available with the Oracle-based JVM only.
- The `RealmInformationCollector` tool might fail to acquire a live heap dump if the tool run with a different operating system user than the one used for running the realm server. It is recommended to run the tool with the same operating system user that was used to run the realm server.



# 5 Universal Messaging Administration API

---

■ Introduction .....	472
■ Administration API Package Documentation .....	475
■ Namespace Objects .....	475
■ Realm Server Management .....	481
■ Security .....	489
■ Management Information .....	493

Universal Messaging provides a feature rich Administration API capable of capturing all metrics, management and audit information from Universal Messaging realms. The API allows you to control and administer all aspects of any Universal Messaging realm or clusters of realms.

Universal Messaging's Enterprise Manager GUI has been written entirely using the Universal Messaging Administration API as a means of demonstrating how useful the API can be for the management of your messaging infrastructure.

Some example code showing how to use the Universal Messaging management API can be found in the examples section.

The Administration API is available in the following languages:

- Java
- C#.NET
- C++

**Note:**

The Administration APIs for C# and C++ are deprecated and will be removed from the product distribution in the next official release.

## Introduction

---

### Getting Started

The Universal Messaging Admin API (see the Package Documentation) allows management, configuration, audit and monitoring of all aspects of a Universal Messaging realm server.

The starting point for the Admin API is connecting to a realm. In order to connect to a realm using the Admin API, you need to ensure you are familiar with the concept of an RNAME. Once you have the RNAME that corresponds to your realm, you can then connect to the realm.

The way you connect to a realm is by constructing an `nRealmNode` object. The `nRealmNode` object is the main object you need to access all of the objects you wish to configure, monitor and manage:

```
String[] RNAME={"nsp://127.0.0.1:9000"};
nSessionAttributes nsa=new nSessionAttributes(RNAME);
nRealmNode realm = new nRealmNode(nsa);
```

### Universal Messaging namespace

Access to resources on a Universal Messaging realms, or indeed objects in a multi Universal Messaging realm server namespace, is based on a simple tree structure, where the `nRealmNode` is the root of the tree. All nodes within the tree are subclasses of a base class `nNode`. From the root, it is possible to obtain references to all child nodes. Child nodes may be other realm nodes, containers (folders containing other realms, channels etc), channels and queues.

For example, to obtain an enumeration of all child nodes within a realm node, simply call the following:

Java:

```
Enumeration children = realm.getNodes();
```

C#:

```
System.Collections.IEnumerator children = realm.getNodes();
```

C++:

```
fSortedList nodes = pNode->getNodes();
```

From this enumeration you can then perform operations on the child nodes. For example, if you have a realm with 1 channel and 1 queue, and wanted to find the number of events currently on each, the following code would do that:

Example: Finding out how many events are on a channel / queue

Java:

```
while (children.hasMoreElements()) {
    nNode child = (nNode)children.nextElement();
    if (child instanceof nLeafNode) {
        nLeafNode leaf = (nLeafNode)child;
        System.out.println("Leaf node contains "+leaf.getCurrentNumberOfEvents());
    }
}
```

C#:

```
while (children.MoveNext()){
    nNode child = (nNode)children.Current;
    if (child is nLeafNode) {
        nLeafNode leaf = (nLeafNode)child;
        Console.WriteLine("Leaf node contains "+leaf.getCurrentNumberOfEvents());
    }
}
```

C++:

```
void searchNodes(fSortedList nodes)
    for (fSortedList::iterator iterator = nodes.begin(); iterator != nodes.end();
        iterator++)
    {
        nNode *pNode = iterator->second;
        int type = pNode->getType ();
        if (type == fBase::LEAFNODE)
        {
            printf("Leaf node contains %ll events",pNode->getCurrentNumberOfEvents());
        }
    }
}
```

The namespace structure is dynamic and is managed asynchronously for you, so as and when objects are created, deleted modified, stopped or started, the namespace will manage those state changes and keep the structure up to date automatically.

## Management / Configuration / Security

As well as the namespace nodes, there are also other objects that can be obtained from the nodes but which are not part of the namespace tree structure.

For example, from an `nRealmNode` it is possible to obtain the following objects:

- **nClusterNode** - The cluster node that this realm may be part of, allowing the administration of Universal Messaging realm clusters
- **nACL** - The realm acl object (see [“Realm Entitlements” on page 161](#)), allowing control of the ACL permissions (see [“Access Control Lists” on page 489](#))
- **nInterfaceManager** - The realm interface manager, allows me to add, remove, stop, start interfaces on a realm (see [“Interfaces” on page 481](#))
- **nSchedulerManager** - the scheduler manager allows me to control scheduled tasks (see [“Scheduling” on page 483](#)) on the realm
- **nConfigGroup** - an enumeration of these corresponds to all configuration (see [“Config” on page 484](#)) and tuning parameters for a given realm.

From an `nLeafNode` which could be a channel or a queue, the following objects are available:

- **nACL** - The leaf node acl object, allows me to control acl permissions (see [“Channel Entitlements” on page 163](#)) for resources
- **nJoinInfo** - All join information associated with a channel or queue

## Monitoring

As well access to the channel resources as described above, there are also many monitoring tools available to developers that provide information asynchronously as and when events occur on a realm. This can be extremely useful in ongoing real time management of one or more Universal Messaging Realm servers.

For example, for a realm node you can provide listeners for the following :

- **Connections** - get notified as new connections (see [“Connection Information” on page 499](#)) to the realm occur, showing connection information
- **Creation / Deletions / Stop / Start** - get notified when new objects are created, deleted, modified, stopped or started (see [“nRealmNode” on page 493](#)) (for example new channels being created, acls being changed etc)
- **State Changes** - get notified when changes occur to any of the objects in the namespace (see [“nLeafNode” on page 497](#)), such as events being published / consumed. All updates are asynchronously received from the realm server and the API manages those changes for you.
- **Audit / Logging** - when security or state changes occur, get notified of audit events, as well as remotely receiving log file information from the server.

The following sections in this guide will work through in more detail, each of what has been discussed above.

## Administration API Package Documentation

The Administration API is provided in the package `com.pcbssystem.nirvana.nAdminAPI`

The API documentation is available in the *Universal Messaging Reference Guide* section of the documentation.

## Namespace Objects

### nRealmNode

Universal Messaging's namespace contains objects that can be administered, monitored and configured. The `nRealmNode` object in the `nAdminAPI`, corresponds to a Universal Messaging Realm server process. The `nRealmNode` is used to make an admin connection to a realm.

In order to connect to a realm you need to ensure you are familiar with the concept of an RNAME. Once you have the RNAME that corresponds to your realm, you can then construct the `nRealmNode` and connect to the corresponding realm. This is achieved by the following calls:

Java:

```
String[] RNAME={"nsp://127.0.0.1:9000"};
nSessionAttributes nsa=new nSessionAttributes(RNAME);
nRealmNode realm = new nRealmNode(nsa);
```

C++:

```
std::string rName = "nsp://127.0.0.1:9000";
nSessionAttributes* nsa=new nSessionAttributes(rName);
nRealmNode* realm = new nRealmNode(nsa);
```

By constructing an `nRealmNode`, and connecting to a realm, the realm node will automatically begin receiving status information from the realm periodically, as well as when things occur.

### nRealmNode

The `nRealmNode` is the root of a Universal Messaging Realm's namespace, which is a tree like structure that contains child nodes. The tree nodes are all subclasses of a base class `nNode`. Each node corresponds to one of the following node subclasses:

- **nRealmNode** - other realm nodes that have been added to this realm's namespace
- **nContainer** - folders, if there was a channel called `/eur/uk/rates`, there would be a child `nContainer` node called, 'eur' which would have a child called 'uk' etc.
- **nLeafNode** - these correspond to channels and queues

The `nRealmNode` itself is a subclass of the `nContainer` class. To obtain an enumeration of all child nodes within a realm node, simply call the following:

Java:

```
Enumeration children = realm.getNodes();
```

C#:

```
System.Collections.IEnumerator children = realm.getNodes();
```

C++:

```
fSortedList nodes = pNode->getNodes();
```

Once you have this enumeration of nodes, you can then perform the various operations on those nodes available through the `nAdminAPI`.

If you know the name of the child node you wish to obtain a reference to, you can use the following method:

Java:

```
nNode found = realm.findNode("/eur/uk/rates");
```

C++:

```
nNode* found = realm->findNode("/eur/uk/rates");
```

Which should return you an `nLeafNode` that corresponds to the channel called `'/eur/uk/rates'`.

As well as obtaining references to existing nodes, it is also possible to create and delete channels and queues using the `nRealmNode`. For example, to create a channel called `'/eur/fr/rates'`, we would write the following code:

```
nChannelAttributes cattrib = new nChannelAttributes();
cattrib.setMaxEvents(0);
cattrib.setTTL(0);
cattrib.setType(nChannelAttributes.SIMPLE_TYPE);
cattrib.setName("/eur/fr/rates");
nLeafNode channel = realm.createChannel(cattrib);
```

C++:

```
nChannelAttributes* cattrib = new nChannelAttributes();
cattrib->setMaxEvents(0);
cattrib->setTTL(0);
cattrib->setType(nChannelAttributes.SIMPLE_TYPE);
cattrib->setName("/eur/fr/rates");
nLeafNode* channel = realm->createChannel(cattrib);
```

To remove channel or a queue, you can simply call the following method on your realm node (using the channel created above):

```
realm.delLeafNode(channel);
```

C++:

```
realm->delLeafNode(channel);
```

For more information on Universal Messaging Administration, please see the API documentation, and the [“Enterprise Manager Guide” on page 9](#).

## nLeafNode (Channels and Queues)

Once you are familiar with the concept of the Universal Messaging Namespace, as discussed in the nRealmNode guide (see [“nRealmNode” on page 475](#)), you can then begin to use the other administration objects associated with a realm's Namespace.

In this section the nLeafNode is discussed. It is assumed you are aware of how to create an nRealmNode for this section, and have a general understanding of Universal Messaging's publish / subscribe and message queue technologies

### nLeafNode

The nLeafNode is either a channel or a queue, and is, as it's name suggests, an end point of a branch of the namespace tree. An nLeafNode's parent is always an instance of nContainer. Since nRealmNode is a subclass of nContainer, sometimes an nLeafNode's parent is also an instance of an nRealmNode. For example, consider the following 2 channels within the namespace:

```
/eur/uk/rates
/rates
```

The nLeafNode that corresponds to the channel '/eur/uk/rates' will have a parent which is an instance of nContainer, and is called 'uk', whereas the nLeafNode that corresponds to the channel '/rates' has a parent which is also an instance of nContainer, however is is also an instance of an nRealmNode (i.e. the namespace root), since it does not contain any folder information in it's name.

As channels and queues are created, they are added to the nRealmNode's tree structure as nLeafNodes. This is all managed for you and does not require you to modify the structure. However it is possible to be notified when changes to the namespace occur so that your application can handle it as you see fit. This is discussed in more detail in the Management Information section of this guide.

To determine if an nLeafNode is a channel or a queue, there are 2 simple methods you can use. The following code snippet search the namespace and print out whether each leaf node it finds is a channel or a queue.

Example : Find channels and queues in the namespace

Java:

```
public void searchNodes(nContainer container)
    Enumeration children = container.getNodes();
    while (children.hasMoreElements()) {
        nNode child = (nNode)children.nextElement();
        if (child instanceof nContainer) {
            searchNodes((nContainer)child);
        } else if (child instanceof nLeafNode) {
            nLeafNode leaf = (nLeafNode)child;
            if (leaf.isChannel) {
```

```
        System.out.println("Leaf Node "+leaf.getName()+" is a channel");
    } else if (leaf.isQueue()) {
        System.out.println("Leaf Node "+leaf.getName()+" is a queue");
    }
}
}
```

C#:

```
public void searchNodes(nContainer container)
System.Collections.IEnumerator children = realm.getNodes();
while (children.MoveNext()){
    nNode child = (nNode)children.Current;
    if (child is nContainer) {
        searchNodes((nContainer)child);
    } else if (child is nLeafNode) {
        nLeafNode leaf = (nLeafNode)child;
        if (leaf.isChannel) {
            Console.WriteLine("Leaf Node "+leaf.getName()+" is a channel");
        } else if (leaf.isQueue()) {
            Console.WriteLine("Leaf Node "+leaf.getName()+" is a queue");
        }
    }
}
}
```

C++:

```
void searchNodes(fSortedList nodes)
    for (fSortedList::iterator iterator = nodes.begin(); iterator != nodes.end();
        iterator++)
    {
        nNode *pNode = iterator->second;
        int type = pNode->getType ();
        if (type == fBase::LEAFNODE)
        {
            if(iterator->second->isChannel()){
                printf("Leaf Node %s is a Channel");
            } else if(iterator->second->isQueue()){
                printf("Leaf Node %s is a Queue");
            }
        }
        else if (type == fBase::CONTAINER)
        {
            searchNodes(((nContainer*)pNode)->getNodes());
        }
    }
}
```

In the above code example, by the `searchNodes(realm)` method searches the namespace from the realm node, and this `isChannel()` and `isQueue()` methods are used to determine whether each leaf node is a queue or a channel.

Associated with each leaf node, is the `nChannelAttributes` for the queue or channel, this is obtained by using the `getAttributes()` method, so it is possible to determine the characteristics of each leaf node.

Each leaf node also has an associated `nACL` object that can be modified to change security permissions for users. This is discussed in more detail in the security section of this guide.

For more information on Universal Messaging Administration, please see the API documentation, and the Enterprise Manager Guide.

## Realm Federation

A Universal Messaging Realm is an instance of the server and a container for resources. Each Universal Messaging Realm defines a namespace of its own but it is possible to merge the namespaces of multiple Realms into one large one. This is known as *realm federation*.

### Note:

Clustering and Realm Federation are mutually exclusive. If a realm is a member of a cluster, you cannot use the realm for federation. Similarly, if a realm is part of a federation, the realm cannot be used for clustering.

While adding a Universal Messaging Realm into the namespace of another, there is one compulsory options and two optional. The compulsory option is the RNAME of that Realm. The optional parameter is the mount point that the Realm should be added in the existing Realm.

If you are specifying the name of the Realm you are adding it should be specified exactly as it appears in the Enterprise Manager. It appears adjacent to the globe icon specifying the realm to which this realm is being added.

A Universal Messaging Realm can also be added to another Realm's namespace using the Enterprise Manager (see [“Realm Federation” on page 479](#)).

A Realm is added into the namespace of another programmatically as follows.

Java, C#:

```
//Create an instance of the Universal Messaging Realm object to be added
String rname = "nsp://remoteHost:9002";
nRealm nr = new nRealm( realmName, rname);
//Set the mountpoint in the local realm's Namespace
nr.setMountPoint( mountPnt );
//Add the remote realm to the local one.
//assuming mySession has already been connected to your local realm
mySession.addRealm( nr );
```

C++

```
//Create an instance of the Universal Messaging Realm object to be added
string rname = "nsp://remoteHost:9002";
nRealm* nr = new nRealm( realmName, rname);
//Set the mountpoint in the local realm's Namespace
nr->setMountPoint( mountPnt );
//Add the remote realm to the local one.
//assuming mySession has already been connected to your local realm
mySession->addRealm( nr );
```

## Example Usage of a Federated Universal Messaging Namespace

You can then provide filters for channel joins across the multiple realms you have added to the namespace. This allows you to ensure that events are routed to the correct channel based on the content of the event.

**Note:**

For a description of the general principles involved in creating channel joins, see the section *Creating Channel Joins*. The description details the usage based on the Enterprise Manager, but the same general principles apply if you are using the API.

For example, if channel1 on Realm1 is joined to channels channel2, channel3, channel4, channel5 on realms Realm2, Realm3, Realm4, Realm5, and each event is published using an `nEventProperties` dictionary that contains a key called 'DESTINATION'.

If each channel join from channel1 is created with a filter, for example for the join from channel1 to channel2 on Realm2 the filter would be:

```
DESTINATION='realm2'
```

This guarantees only those events that are published to channel1 and that contain 'realm2' in the 'DESTINATION' key will be published to channel2 on Realm2.

For further example code demonstrating adding Universal Messaging Realms to a names space please see the `addRealm` example.

## Channel Join

Joining a channel to another allows you to set up content routing such that events on the source channel will be passed on to the destination channel also. Joins also support the use of filters thus enabling dynamic content routing.

Channels can be joined using the Universal Messaging Enterprise Manager GUI or programmatically.

In joining two Universal Messaging channels there is one compulsory option and two optional ones. The compulsory option is the destination channel. The optional parameters are the maximum join hops and a JMS message selector to be applied to the join.

**Note:**

For a description of the general principles involved in creating channel joins, see the section *Creating Channel Joins* in the *Administration Guide*. The description details the usage based on the Enterprise Manager, but the same general principles apply if you are using the API.

Channel joins can be created using the `nmakechanjoin` join sample application which is provided in the bin directory of the Universal Messaging installation. For further information on using this example please see the `nmakechanjoin` example page.

Universal Messaging joins are created as follows:

Java, C#:

```
//Obtain a reference to the source channel
nChannel mySrcChannel = mySession.findChannel( nca );
//Obtain a reference to the destination channel
nChannel myDstChannel = mySession.findChannel( dest );
//create the join
mySrcChannel.joinChannel( myDstChannel, true, jhc, SELECTOR );
```

C++:

```
//Obtain a reference to the source channel
nChannel* mySrcChannel = mySession->findChannel( nca );
//Obtain a reference to the destination channel
nChannel* myDstChannel = mySession->findChannel( dest );
//create the join
mySrcChannel->joinChannel( myDstChannel, true, jhc, SELECTOR );
```

## Realm Server Management

### Interfaces

Universal Messaging Realm servers provide the ability for connections to be made using any available physical network interface on the server machine. For example, if a machine has 4 physical network interfaces, Universal Messaging provides the ability to bind specific network interface addresses to specific ports and different protocols. This provides the ability to run segment the communication between client and server. There is no limit to the number of separate interfaces that can be run on a Universal Messaging realm server.

For example, a Realm Server that is visible to Internet users may have 4 Network cards, each one having its own physical IP address and hostname. Two of the network interfaces may be externally visible, while the other 2 may be only visible on internal sub-nets.

The 2 external interfaces may be specified as using `nhp`, and `nhps` on ports 80 and 443 respectively, since for firewall purposes, these ports are the most commonly accessible ports to external clients connecting to the realm. The remaining internal interfaces, visible to internal client connections do not have the same restrictions, and so could be defined as using `nsp` and `nsps` protocols on other ports, say 9000 and 9002 respectively.

What this guarantees is separation of internal and external connections based on network interface and protocol.

### nInterfaceManager

When you have connected to a realm, and have a reference to an `nRealmNode` object (see [“nRealmNode” on page 475](#)), you can access an object called `nInterfaceManager`, which provides the ability to add, modify, delete, stop and start interfaces on the Universal Messaging realm. To get access to this object, you can call the following method from a realm node:

Java, C#:

```
nInterfaceManager iMgr = realm.getInterfaceManager();
```

C++:

```
nInterfaceManager* iMgr = realm->getInterfaceManager();
```

Using the `nInterfaceManager` object you can then obtain a list of known interfaces for that realm:

Java:

```
Vector ifaces = iMgr.getInterfaces();
```

C#:

```
List ifaces = iMgr.getInterfaces();
```

C++:

```
int numInterfaces; nInterfaceStatus** pTemp = iMgr->getInterfaces(numInterfaces);
```

All interfaces extend a base class called `nInterface`. There are 4 types of interface object that correspond to the different types of protocols that an interface can use. These are:

- `nSocketInterface` - standard socket interface, Universal Messaging protocol is `nsp`
- `nHTTPInterface` - http interface, Universal Messaging protocol is `nhp`
- `nSSLInterface` - ssl socket interface, Universal Messaging protocol is `nspS`
- `nHTTPSInterface` - https interface, Universal Messaging protocol is `nhps`

Each of these interface objects contain standard configuration information and allows the same operations to be performed on them. For example, if there is an interface called 'nsp1', and you wanted to change the 'autostart' property to true (i.e. make the interface start automatically when the realm is started) this can be achieved with the following code:

Java, C#:

```
nInterface iface = iMgr.findInterface("nsp0");  
iface.setAutostart(true);  
iMgr.modInterface(iface);
```

C++:

```
nInterface* iface = iMgr->findInterface("nsp0");  
iface->setAutostart(true);  
iMgr->modInterface(iface);
```

Which will modify the interface configuration at the server, stop and restart the interface. When performing a `modInterface` operation, if you are modifying the interface that your `nRealmNode` is connected to, you will be disconnected and reconnected when the interface restarts. This is important to remember when using the stop method of an interface too, since if you stop the interface you are connected to, you cannot start it again, since your connection needs to be active, and the stop operation will close your connection. If you wish to restart an interface you should therefore do it from a connection which has been made via another interface.

### Example: creating an NHPS interface

You can create an NHPS interface using code such as the following:

```
nRealmNode rnode = ...;
nHTTPSInterface nhps = new nHTTPSInterface("0.0.0.0", 9443,
autoStart);
nhps.setKeyStore(keystore);
nhps.setKeyStorePassword(kpass);
nhps.setPrivateKeyPassword(kpass);
nhps.setTrustStore(tstore);
nhps.setTrustStorePassword(tpass);
rnode.getInterfaceManager().addInterface(nhps);
```

## Scheduling

Universal Messaging Realm servers provide the ability for scheduling tasks. Tasks can be scheduled to execute based on certain conditions being met.

These conditions can be either time based (scheduling) or event based (triggers).

Universal Messaging scheduling is achieved through the creation of numerous scheduling scripts. Each script can contain multiple definitions of triggers and tasks.

The Universal Messaging server parses these scripts and sets up the triggers and tasks accordingly. For more information on the script grammar, there is a section in the enterprise manager guide which deals with writing scheduling scripts.

### nSchedulerManager

When you have connected to a realm, and have a reference to an nRealmNode object (see [“nRealmNode” on page 475](#)), you can access an object called nSchedulerManager, which provides you with the ability to add, modify, delete scheduling scripts. To get access to this object, you can call the following method from a realm node:

Java, C#:

```
nSchedulerManager sMgr = realm.getSchedulerManager();
```

C++:

```
nSchedulerManager* sMgr = realm->getSchedulerManager();
```

Using the nSchedulerManager object you can then obtain a list of scheduler objects for the realm:

Java:

```
Enumeration schedulers = sMgr.getNodes();
```

C#:

```
System.Collections.IEnumerator schedulers = sMgr.getNodes();
```

C++:

```
fSortedList nodes = pNode->getNodes();
```

This method returns an enumeration of nScheduler objects. The nScheduler objects each correspond to a particular scheduling script.

The following code shows you how to construct a new scheduler object using a sample script that will log a message to the realm server log every hour, signified by the 'every 60' condition: {Please Note: typically this script would be read from a script file or it could be entered directly into the realm enterprise manager GUI.}

Java, C#:

```
String source = "scheduler myScheduler {\n";
String logString = "Sample script : ";
source += "\n";
source += "\n";
source += " initialise{\n";
source += " Logger.setLevel(0);\n";
source += " }\n";
source += " every 60"{\n";
source += " Logger.report(\""+logString+"\");\n";
source += " }\n";
source += "}\n";
sMgr.add(source, "user@localhost", false);
```

C++:

```
stringstream s;
s<<"scheduler myScheduler {\n";
string logString = "Sample script : ";
s<<"\n";
s<<"\n";
s<<"initialise{\n";
s<<"Logger.setLevel(0);\n";
s<<"}\n";
s<<"every 60"{\n";
s<<"fLogger::report(\""+logString+"\");\n";
s<<"}\n";
s<<"}\n";
sMgr->add(source, "user@localhost", false);
```

For more information on Universal Messaging Administration, please see the API documentation, and the Enterprise Manager Guide.

## Config

Universal Messaging Realm servers contain a large number of configurable parameters. These parameters can be modified using the nAdminAPI.

The Universal Messaging Realm config can also be managed via the Realm enterprise manager (see [“Realm Configuration” on page 29](#)). This also provides a useful guide to the configuration groups and their specific config entities.

### nConfigGroup

When connected to a realm, and using a reference to an nRealmNode object (see [“nRealmNode” on page 475](#)), you can access configuration objects that correspond to a group of configuration entries. To get access to the config groups, call the following method from a realm node:

Java, C#

```
Enumeration children = realm.getNodes();
```

C++

```
fSortedList nodes = pNode->getNodes();
```

The enumeration will contain a number of `nConfigGroup` objects. Each `nConfigGroup` contains a number of `nConfigEntry` objects, each one corresponds to a specific configurable parameter in the realm server.

For example, to change the log level of the realm server, we need to obtain the config group called 'Logging Config' and set the 'fLoggerLevel' property:

Java, C#:

```
nConfigGroup grp = realm.getConfigGroup("Logging Config");
nConfigEntry entry = grp.find("fLoggerLevel");
entry.setValue("0");
```

C++

```
nConfigGroup* grp = realm->getConfigGroup("Logging Config");
nConfigEntry* entry = grp->find("fLoggerLevel");
entry->setValue("0");
```

For a definitive list of available configuration groups and their specific properties please see [“Realm Configuration” on page 29](#) in the enterprise manager guide.

For more information on Universal Messaging Administration, please see the API documentation, and the Enterprise Manager Guide.

## Clustering

Universal Messaging provides the ability to group Realm servers together to form a cluster. A cluster is a logical group of realm servers that share common resources. The resources and any operations performed on them are replicated across all cluster members. Clients connecting to 'Realm A' in cluster 1, are able to access the same logical objects as clients connecting to Realms B or C in cluster1.

The state of these objects is fully replicated by each realm in the cluster. For example, if you create a queue (queue1) within cluster 1, it is physically created in realms A, B and C. If there are 3 consumers on queue1, say one on each of realms A, B and C respectively, each realm in the cluster will be aware as each message is consumed and removed from the different physical queue1 objects in the 3 realms.

If one of the realms within cluster1 stops, due to a hardware or network problems, then clients can automatically reconnect to any of the other realms and start from the same point in time on any of the other realms in the cluster.

This ensures a number of things:

- **Transparency** - Any client can connect to any Universal Messaging realm server within a cluster and see the same cluster objects with the same state. Clients disconnected from one realm will automatically be reconnected to another cluster realm.
- **24 x 7 Availability** - If one server stops, the other realms within the cluster will take over the work, providing an always on service
- **Scalability** - Large number of client connections can be managed across multiple servers within a cluster

## nClusterNode

Using the nAdmin API, if you wish to create a cluster that contains 3 realms, and you know the RNAME values for all 3, then the following call will create the cluster.

Java, C#, C++:

```
String[] RNAME= {"nsp://127.0.0.1:9000",  
"nsp://127.0.0.1:10000","nsp://127.0.0.1:11000"};  
nRealmNode realms[] = new nRealmNode[RNAME.length];  
nClusterMemberConfiguration[] config = new nClusterMemberConfiguration[RNAME.length];  
for (int x = 0; x < RNAME.length; x++) {  
    // you don't have to create the realm nodes  
    // here, since the member configuration will create  
    // them for you from the RNAME values  
    realms[x] = new nRealmNode(new nSessionAttributes(RNAME[x]));  
    config[x]=new nClusterMemberConfiguration(realms[x], true);  
}  
nClusterNode cluster = nClusterNode.create("cluster1", config);
```

Once the cluster node is created, each realm node within the cluster will know of the other realms within the cluster, and be aware of the cluster they are part of. For example, calling the following method:

Java, C#, C++:

```
nClusterNode cluster = realms[0].getCluster();
```

will return the cluster node just created with the realm with nsp://127.0.0.1:9000 for an RNAME.

Cluster nodes contain information about the member realms (nRealmNode objects) as well as the current state of the cluster members. This information can be found by calling the `getClusterConnectionStatus()` method on the cluster node, which returns a vector of nClusterStatus objects, each of which corresponds to a realm.

## nRealmNode

Once a realm becomes part of a cluster, channels and queues can be created that are part of the cluster, as well as standard local resources within the realms. For example, if you were to use the following calls:

Java, C#, C++:

```
nChannelAttributes cattrib = new nChannelAttributes();
```

```

cattrib.setMaxEvents(0);
cattrib.setTTL(0);
cattrib.setType(nChannelAttributes.PERSISTENT_TYPE);
cattrib.setClusterWide(true);
cattrib.setName("clusterchannel");
nLeafNode=.createChannel(cattrib);
realms[0].createChannel(cattrib);

```

This would create a channel that is visible to all realms within a cluster. Any administrative changes made to this channel such as ACL modifications will also be propagated to all cluster members in order for the channel to be kept in sync across all realms.

## Inter-Cluster Connections

Inter-cluster connections can be created programmatically through the Administration API. To do this, connect to a realmNode in each cluster and then do the following:

Java, C#, C++:

```

cluster1realm1.getCluster().registerRemoteCluster(cluster2realms1.getCluster());

```

Similarly, the inter-cluster connection can be removed programmatically:

Java, C#, C++:

```

cluster1realm1.getCluster().deregisterRemoteCluster(cluster2realm1.getCluster());

```

For more information on Universal Messaging Administration, please see the API documentation, and the Enterprise Manager Guide.

## Multicast

A common way to add a multicast configuration is via the Enterprise Manager (see [“Multicast Configuration” on page 235](#)) but you can also do this programmatically.

### Creating the nMulticastConfiguration

In order to create an nMulticastConfiguration object you need to specify two parameters:

- multicastAddress - Multicast IP address to use
- adapter - Network adapter address of your multicast configuration

Java, C#:

```

String multicastAddress = "227.0.0.98";
String adapter = "10.150.12.1";
nMulticastConfiguration mConf = new nMulticastConfiguration(multicastAddress,
adapter);

```

C++:

```

std::string multicastAddress = "227.0.0.98";

```

```
std::string adapter = "10.150.12.1";
nMulticastConfiguration* mConf = new nMulticastConfiguration(multicastAddress,
adapter);
```

## Enabling multicast for cluster communication

In order to use multicast for intra-cluster communication you need to set a flag on the `nMulticastConfiguration`:

Java, C#:

```
mConf.setUseForCluster(true);
```

C++:

```
mConf->setUseForCluster(true);
```

## Enabling multicast on DataGroups

When you create a `DataGroup` you have the option to enable multicast delivery. However you also need to enable multicast for `DataGroups` on the multicast configuration:

Java, C#:

```
mConf.setUseForDataGroups(true);
```

C++:

```
mConf->setUseForDataGroups(true);
```

Then (after the configuration has been applied) when you create a `DataGroup` you need to set the `enableMulticast` flag to true:

Java, C#:

```
boolean enableMulticast = true;
String name = "newGroup";
mySession.createDataGroup(name,enableMulticast);
```

C++:

```
bool enableMulticast = true;
std::string name = "newGroup";
mySession->createDataGroup(name,enableMulticast);
```

## Applying the multicast configuration

In order to register the new configuration on the server you will need to connect to a Universal Messaging Realm and establish an `nRealmNode` (see [“nRealmNode” on page 475](#)). You can then get a reference to the `nMulticastManager`:

Java, C#:

```
nMulticastManager mMgr = realm.getMulticastManager();
```

C++:

```
nMulticastManager* mMgr = realm->getMulticastManager();
```

You can now use the nMulticastManager to send the new configuration to the server:

Java, C#:

```
mMgr.addMulticastConfiguration(mConf);
```

C++:

```
mMgr->addMulticastConfiguration(mConf);
```

## Security

### Access Control Lists

The Universal Messaging Administration API allows Access Control Lists (ACLs) to be set using the nACL object defines a set of nACLEntry objects that consist of a user subject and a value that corresponds to the operations permitted for that subject. With an nACL object, it is possible to added, delete and modify acl entries for specific subjects.

#### The nACL Object

There are subclasses of the base nACLEntry object. These are :

- nRealmACLEntry - defines permissions for a specific subject on the Universal Messaging Realm server itself
- nChannelACLEntry - defines permissions for a subject on a channel or queue

ACL Lists can contain any combination and number of user@host entries, along with Security Groups (see [“Nirvana Admin API - Nirvana Security Groups” on page 489](#)).

### Nirvana Admin API - Nirvana Security Groups

The Administration API allows groups of users to be defined. These groups can then be used in ACL lists in-place of individual ACL entries for each user.

Security Groups can contain any number of users (user@host pairs), and may also include other Security Groups.

A new security group can be registered as follows:

Java, C#, C++:

```
nSecurityGroup grp = new nSecurityGroup("mySecurityGroup");
grp.add(add(new nSubject("user@host"));
realmNode.getSecurityGroupManager.registerSecurityGroup(grp);
```

The `SecurityGroupManager` can be used to edit memberships of multiple groups at the same time, for example:

Java, C#, C++:

```
nSecurityGroupManager mgr = realmNode.getSecurityGroupManager();
mgr.registerGroupMembers(group,members);
//Members can be a single subject(user@host), a group, or a collection
//containing many subjects, groups or a combination of these.
```

Once a security group has been registered, it can be added into ACL lists as you would normally add a `user@host` entry. Subsequent changes to the membership of the group will be reflected in which users have permissions for the corresponding resources.

Java, C#, C++:

```
nSecurityGroup grp = securityGroupManager.getGroup("myGroupName");
nChannelACLEntry aclEntry = new nChannelACLEntry(grp);
aclEntry.setFullPrivileges(true);
leafNode.addACLEntry(aclEntry);
```

Groups can also be deregistered from the realm. This will remove the group and will remove the group reference from all ACL lists where the group currently appears. As with the other examples, this can be done via the `nSecurityGroupManager`:

Java, C#, C++:

```
mgr.deregisterSecurityGroup(grp);
```

As with all ACLs in Universal Messaging, privileges are cumulative. This means that, for example, if a user is in a group which has publish permissions on a channel, but not subscribe permissions, the user will not be able to subscribe on the channel. Then, if an ACL entry is added on the channel for his specific username/host pair, with subscribe but no publish permissions, the user will then be able to both subscribe (from the non-group ACL permission), and publish (from the group ACL permission).

Deeply nested Security Groups hierarchies are generally discouraged, since this type of configuration can negatively impact the speed of checking ACLs, and may result in worse performance than a shallow hierarchy.

## Realm Access Control List (nACL)

When you have connected to a realm, and have a reference to an `nRealmNode` object (see [“nRealmNode” on page 475](#)), you can access the realm's acl object. This object contains a list of `nRealmACLEntry` objects that represent a subject and a set permissions for various operations on a realm.

You can also, add, delete and modify acl entry objects. To obtain the realm acl object, simply call the following method from a realm node:

Java, C#:

```
nACL acl = realm.getACLs();
```

C++:

```
nACL* acl = realm->getACLs();
```

## nRealmACLEntry

Once you have the acl object, you can then add, remove or modify acl entries:

To find a specific acl entry from the realm acl, you can search the acl using the subject. For example, if I wished to change the default permissions for the `*@*` subject (i.e. the default permission for a realm), I could use the following code:

```
nRealmACLEntry entry = acl.find("Everyone");
entry.setFullPrivileges(false);
acl.replace(entry);
realm.setACLs(acl);
```

C++:

```
nRealmACLEntry* entry = acl->find("Everyone");
entry->setFullPrivileges(false);
acl->replace(entry);
realm->setACLs(acl);
```

which would set the full privileges flag to false for the default subject.

For more information on Universal Messaging Administration, please see the API documentation, and the Enterprise Manager Guide.

## Channel Access Control List (nACL)

When connected to a Universal Messaging realm server, with a reference to an `nRealmNode` object (see [“nRealmNode” on page 475](#)) it is possible to get a reference to an `nLeafNode` (see [“nLeafNode \(Channels and Queues\)” on page 477](#)) that corresponds to a channel. This can then be used to get access the node's nACL. This object contains a list of `nChannelACLEntry` objects that represent a subject and a set permissions for various operations on a channel. There is a separate `nChannelACLEntry` object for each subject that has been permissioned on the `nLeafNode`.

You can also, add, delete and modify ACL entry objects.

In order to obtain a reference to the correct channel ACL object for a channel called `/products/prices`, simply call the following method from a realm node:

Java, C#, C++:

```
nLeafNode chan = realm.findNode("/products/prices");
nACL acl = chan.getACLs();
```

C++:

```
nLeafNode* chan = realm->findNode("/products/prices");
nACL* acl = chan->getACLs();
```

## nChannelACLEntry

Once you have the ACL object, you can then add, remove or modify acl entries:

To find a specific ACL entry from the channel ACL, the ACL object can be searched using the subject.

For example, to change the default permissions for the `*@*` subject (i.e. the default permission for the channel), the following code can be used:

Java, C#:

```
nChannelACLEntry entry = acl.find("Everyone");
entry.setFullPrivileges(false);
acl.replace(entry);
chan.setACLs(acl);
```

C++:

```
nChannelACLEntry* entry = acl->find("Everyone");
entry->setFullPrivileges(false);
acl->replace(entry);
chan->setACLs(acl);
```

which would set the full privileges flag to false for the default subject.

[Click here](#) to see example of how to modify channel ACLs programmatically or to see example of modifying ACLs using the enterprise manager.

For more information on Universal Messaging Administration, please see the API documentation, and the Enterprise Manager Guide.

## Queue Access Control List

When you have connected to a realm, and have a reference to an `nRealmNode` object (see [“nRealmNode” on page 475](#)), and an `nLeafNode` (see [“nLeafNode \(Channels and Queues\)” on page 477](#)) that corresponds to a queue, you can access the node's ACL object. This object contains a list of `nChannelACLEntry` objects that represent a subject and a set permissions for various operations on a queue.

You can also, add, delete and modify acl entry objects. To obtain the queue ACL object, simply call the following method from a realm node:

Java, C#:

```
nLeafNode queue = realm.findNode("/eur/uk/orders");
nACL acl = queue.getACLs();
```

C++:

```
nLeafNode* queue = realm->findNode("/eur/uk/orders");
nACL* acl = queue->getACLs();
```

Once you have the acl object, you can then add, remove or modify acl entries:

## nChannelACLEntry

To find a specific ACL entry from the queue ACL, you can search the ACL using the subject. For example, if I wished to change the default permissions for the `*@*` subject (i.e. the default permission for the queue), I could use the following code:

Java, C#:

```
nChannelACLEntry entry = acl.find("Everyone");
entry.setFullPrivileges(false);
acl.replace(entry);
queue.setACLs(acl);
```

C++:

```
nChannelACLEntry* entry = acl.find("Everyone");
entry->setFullPrivileges(false);
acl->replace(entry);
queue->setACLs(acl);
```

which would set the full privileges flag to false for the default subject.

[Click here](#) to see example of how to add queue ACLs programmatically or to see example of modifying ACLs using the enterprise manager.

For more information on Universal Messaging Administration, please see the API documentation, and the Enterprise Manager Guide.

## Management Information

---

### nRealmNode

The Universal Messaging admin API provides real time asynchronous management information on all objects within a realm server. By creating an `nRealmNode` (see [“nRealmNode” on page 475](#)), and connecting to a realm, information is automatically delivered to the `nRealmNode` object from the realm. This information is delivered periodically in summary form, and also as and when the state changes for one or all of the objects managed within a realm.

Before reading this section it may be useful to look at the management information available via the Universal Messaging enterprise manager. A full description of all Realm management screens is available in the enterprise manager guide. All functionality seen in the enterprise manager can be easily added to bespoke admin and monitoring processes as it is written entirely using the Universal Messaging Admin API.

This section discusses the following different types of information that can be obtained through the `nAdmin` API for the `nRealmNode` object:

#### Status Information

The `nRealmNode` extends `nContainer`, that extends `nNode` which is a subclass of `Observable`, so when the status information is received for a realm node, (by default this is every 5 seconds

although it is configurable (see [“Realm Configuration” on page 29](#)) by setting the StatusBroadcast property under the Global Values config group) the nRealmNode will trigger the update callback on any known Observers. For example, if you write a class that implements the Observer interface, it can be added as an observer as follows:

Java, C#, C++:

```
realm.addObserver(this);
```

Assuming 'this' is the instance of the class implementing Observer, then the implementation of the update(Observable obs, Object obj) will be notified that the realm node has changed.

When regular status events are sent, the Observable object referenced in the update method will be the realm node that you added your observer to, and the Object will be null.

## State Change Events

When events occur on a realm node that you have added an observer to, the Observable/Observer mechanism will notify you of the details of that event. For example, the following implementation of the update method of the Observer interface demonstrates how to detect that a new channel or queue has been created or deleted :

Java, C#:

```
public void update(Observable obs, Object obj){
    if (obs instanceof nContainer) {
        if (obj instanceof nLeafNode) {
            nLeafNode leaf = (nLeafNode)obj;
            nContainer cont = (nContainer)obs;
            if (cont.findNode(leaf) == null) {
                // node has been deleted
                System.out.println("Node "+leaf.getName()+" removed");
            } else {
                // node has been added
                System.out.println("Node "+leaf.getName()+" added");
            }
        }
    }
}
```

C++:

```
void ObservableMapping::update(Observable *pObs, void *pObj)
{
    if (obs->getType() == fBase::CONTAINER) {
        if (obj->getType() == fBase::LEAFNODE) {
            nLeafNode leaf = (nLeafNode*)obj;
            nContainer cont = (nContainer*)obs;
            if (cont->findNode(leaf)) {
                // node has been deleted
                printf("Node %s removed", leaf->getName());
                System.out.println("Node "+leaf.getName()+" removed");
            } else {
                // node has been added
                printf("Node %s added", leaf->getName());
            }
        }
    }
}
```

```
}
}
```

Any changes to the realm ACL will also use the same notification mechanism. For example, if an ACL entry was changed for a realm, the update method would be fired calling with the realm node object and the nACLEntry that had been modified.

## Logging and Audit

An nRealmNode allows you to asynchronously receive realm log file entries as well as audit file entries as they occur.

Firstly, for receiving asynchronous log file entries, there is an interface called nLogListener which your class must implement. This interface defines a callback method called report(String) that will deliver each new log entry as a string. Once implemented, the following call will add your log listener to the realm node:

Java, C#, C++:

```
realm.addLogListener(this);
```

Assuming 'this' is the instance of the class implementing the nLogListener interface.

The following is an example of the report(String) method implementation:

Java, C#:

```
public void report(String msg) {
    System.out.println("LOG "+msg);
}
```

C++:

```
printf("Log : %s\n", msg);
```

Secondly, realm servers provide an audit file that tracks object creations and deletions, acl changes, connection attempts and failures. This information can be very useful for tracking who has created ACL entries for example and when they were done.

This information, as with log file entries can be asynchronously received by implementing an interface called nAuditListener. This interface defines a callback method called audit(nAuditEvent) that delivers contains the details of the audit entry. Once implemented, the following call will add your log listener to the realm node:

Java, C#, C++:

```
realm.addAuditListener(this);
```

Assuming 'this' is the instance of the class implementing the nAuditListener.

For more information on Universal Messaging Administration, please see the API documentation, and the Enterprise Manager Guide.

## nClusterNode

Universal Messaging's admin API provides real time asynchronous information on all objects within a realm server. By creating an `nRealmNode` (see [“nRealmNode” on page 475](#)), and connecting to a realm, information is automatically delivered to the realm node from the realm. This information is delivered periodically in summary form, and also as and when the state changes for one or all of the objects managed within a realm.

Before reading this section it may be useful to look at the management information available via the Universal Messaging enterprise manager. A full description of all Realm management screens is available in the enterprise manager guide. All functionality seen in the enterprise manager can be easily added to bespoke admin and monitoring processes as it is written entirely using the Universal Messaging Admin API.

This section discusses the following different types of information that can be obtained through the `nAdmin` API for the `nClusterNode` object. The `nClusterNode` corresponds to a cluster that 2 or more realms are members of. Each `nRealmNode` will have access to its cluster node object once it has been added to a new or existing cluster:

### Status Information

Firstly, in order to detect that a cluster node has been created, one has to observe the realm to which you are connected. When the realm is added to a cluster, the Observer/Observable mechanism will notify you of the cluster creation.

As well as implementing the Observer interface to detect new clusters, there is an interface that can be used to be notified of specific cluster events when clusters already exist. This interface is the `nClusterEventListener`. The interface defines various methods that enable your program to receive callbacks for specific cluster events. When the status changes for a cluster node, this will trigger an callback on any known listeners of the `nClusterNode`. For example, when you have constructed your `nRealmNode`, if your class implements the `nClusterEventListener` interface, then we can do the following:

Java, C#:

```
realm.addObserver(this);
nClusterNode cluster = realm.getCluster();
if (cluster != null) {
    cluster.addListener(this);
}
```

C++:

```
pRealm->addObserver(this);
nClusterNode *pCluster = pRealm->getCluster();
pCluster->addListener(this);
```

If the realm is not part of a cluster, then the `getCluster()` method will return null. However, by adding an observer to the realm, if a cluster is created that contains the realm you are connected to, the `update()` method of the Observer implementation will notify you that a cluster has been created. For example, the following code demonstrates how to detect if a cluster has been created with the realm you are connected to as a member:

Java, C#:

```
public void update(Observable o, Object arg) {
    if (arg instanceof nClusterNode) {
        System.out.println("New cluster formed, name = "+(nClusterNode)arg).getName());
        ((nClusterNode)arg).addListener(this);
    }
}
```

C++:

```
nNode *pNode = iterator->second;
int type = pNode->getType ();
if (type == fBase::LEAFNODE)
{
    ((nLeafNode*)pNode)->addListener(new nChannelWatch((nLeafNode*)pNode, this));
}
```

For more information on how to monitor cluster nodes programmatically please see the appropriate code example.

For more information on how to monitor cluster nodes using the enterprise manager please see the enterprise manager guide.

For more information on Universal Messaging Administration, please see the API documentation and the Enterprise Manager Guide.

## nLeafNode

Universal Messaging's admin API provides real time asynchronous information on all objects within a realm server. By creating an [nRealmNode](#) (see [“nRealmNode” on page 475](#)), and connecting to a realm, information is automatically delivered to the realm node from the realm. This information is delivered periodically in summary form, and also as and when the state changes for one or all of the objects managed within a realm.

Before reading this section it may be useful to look at the management information available via the Universal Messaging enterprise manager. A full description of all Realm management screens is available in the enterprise manager guide. All functionality seen in the enterprise manager can be easily added to bespoke admin and monitoring processes as it is written entirely using the Universal Messaging Admin API.

This section will discuss the basic information that can be obtained through the nAdmin API for the nLeafNode object:

### Status Events

The nLeafNode extends nNode which is a subclass of Observable, so when the status information is received for a leaf node, (this occurs only when things change on the channel or queue, i.e. acl, connections, events published / consumed etc) the nLeafNode will trigger the update callback on any known Observers. For example, if you write a class that implements the Observer interface, then we can do the following:

Java, C#:

```

Enumeration children = realm.getNodes();
while (children.hasMoreElements());
    nNode child = (nNode)children.nextElement();
    if (child instanceof nLeafNode) {
        child.addObserver(this);
    }
}

```

C++:

```

pNode->addObserver(this);
pNode->addConnectionListener(new nRealmWatch(this));
fSortedList nodes = registerNodes(pNode->getNodes());
for (fSortedList::iterator iterator = nodes.begin(); iterator != nodes.end();
iterator++)
    {
        if (type == fBase::LEAFNODE)
            {
                ((nLeafNode*)pNode)->addListener(new nChannelWatch((nLeafNode*)pNode,
this));
            }
    }
}

```

Assuming 'this' is the instance of the class implementing Observer, then the implementation of the update(Observable obs, Object obj) will be notified that the leaf node has changed.

When events occur on a leaf node that you have added an observer to, the Observable/Observer mechanism will notify you of the details of that event. For example, the following implementation of the update method of the Observer interface demonstrates how to detect that a channel or queue acl has been added or deleted:

Java, C#:

```

public void update(Observable obs, Object obj){
    if (obs instanceof nLeafNode) {
        if (obj instanceof nACLEntry) {
            nLeafNode leaf = (nLeafNode)obs;
            nACLEntry entry = (nACLEntry)obj;
            if (leaf.isChannel()) {
                // acl modified / added / deleted
                System.out.println("Channel "+leaf.getName()+" acl event for
"+entry.getSubject());
            } else {
                // acl modified / added / deleted
                System.out.println("Queue "+leaf.getName()+" acl event for
"+entry.getSubject());
            }
        }
    }
}
}

```

C++:

```

void ObservableMapping::update(Observable *pObs, void *pObj)
{
    if (obs->getType() == fBase::LEAFNODE) {
        if (obj->getType() == fBase::ACLENTY) {
            nLeafNode leaf = (nLeafNode*)obs;
            nACLEntry entry = (nACLEntry*)obj;

```

```

    if (leaf->isChannel()) {
        // acl modified / added / deleted
        printf("Channel %s acl event for %s",leaf->getName(),+entry->getSubject());
    } else {
        // acl modified / added / deleted
        printf("Queue %s acl event for %s",leaf->getName(),+entry->getSubject());
    }
}
}
}

```

For more information on Universal Messaging Administration, please see the API documentation, and the Enterprise Manager Guide.

## Connection Information

Universal Messaging's admin API provides real time asynchronous information on all objects within a realm server. By creating an `nRealmNode` (see [“nRealmNode” on page 475](#)), and connecting to a realm, information is automatically delivered to the realm node from the realm. This information is delivered periodically in summary form, and also as and when the state changes for one or all of the objects managed within a realm.

Before reading this section it may be useful to look at the management information available via the Universal Messaging enterprise manager. A full description of all Realm management screens is available in the enterprise manager guide. All functionality seen in the enterprise manager can be easily added to bespoke admin and monitoring processes as it is written entirely using the Universal Messaging Admin API.

This section will discuss the connection information that is available through the `nAdmin` API for the `nRealmNode` and the `nLeafNode` objects:

### nRealmNode Connections

The `nRealmNode` provides the ability to be notified of connections to the realm, and when connections are closed. When a client attempts a connection, a callback will be made that gives the details of the connection, such as the user name, hostname, protocol and connection id. When a user connection is closed, again, you will receive notification. This information can be useful for monitoring activity on a realm.

In order to receive this kind of information, you need to implement the `nConnectionListener` class. This class defines 2 methods, `newConnection` and `delConnection`. To receive notifications, you can use the following method:

Java, C#, C++:

```
realm.addConnectionListener(this);
```

Assuming 'this' is the instance of the class implementing `nConnectionListener`, then the implementation of the `newConnection` and `delConnection` methods will be notified when connections are made or closed with the realm.

## nLeafNode Connections

Universal Messaging provides the ability to issue notifications of connections to leaf nodes. Connections to leaf nodes correspond to subscriptions on a channel, so when a user subscribes to a channel or removes the subscription, you can be notified. Notification is via a callback that contains the details of the connection, such as the user name, hostname, protocol, connection id, durable name and subscription filter.

In order to receive this kind of information, you need to implement the `nConnectionListener` class. This class defines 2 methods, `newConnection` and `delConnection`. To receive notifications, you can use the following method:

Java, C#:

```
leafaddListener(this);
```

C++:

```
leaf->addListener(this);
```

Assuming 'this' is the instance of the class implementing `nConnectionListener`, then the implementation of the `newConnection` and `delConnection` methods will be notified when channel subscriptions are made or removed.

# 6 Thread Pool Monitoring

---

In addition to the thread dump generation provided by the Java Service Wrapper, you can configure the Universal Messaging realm servers to monitor the thread pool for slow-running threads and generate thread dumps when certain events occur. The thread dumps and messages generated from the user-defined monitoring of the thread pool are logged into *Software AG\_directory \UniversalMessaging\server\InstanceName\data\nirvana.log*.

The thread pool monitoring generates thread dumps for stalled or slow-moving tasks, and reports reduced thread availability. Stalled tasks are tasks that run longer than the specified time. Slow-moving tasks are tasks that run slower than the timeout for the task execution. You can also set a threshold for pending tasks to monitor thread availability. You can then use the thread dump entries in the log to troubleshoot the task execution.

To ensure that the logs are not too big, you can configure the interval at which the server generates a thread dump.

## Thread-Pool Monitoring Configuration Properties

You configure the thread-pool monitoring properties for a realm in the **Thread Pool Config** group on the Config tab in the Enterprise Manager.

For information about working with Universal Messaging configuration properties in the Enterprise Manager, see .

### **StalledTaskWarningTime**

The time in milliseconds before reporting a stalled task. The system writes the information at the WARNING log level and generates a thread dump. When you change this configuration, the thread pool monitor interval is updated to monitor at the same time interval as the value you specify for this property. Valid values range from 10000 to 60000. Default is 60000.

### **SlowTaskWarningTime**

The time in milliseconds before reporting a slow-running task. The server logs the information at the WARNING log level and generates a thread dump. Valid values range from 1000 to 30000. Default is 5000.

### **PendingTaskWarningThreshold**

The threshold at which the server starts to warn about the number of pending tasks. When the number of pending tasks is below the threshold, but over 100, the server logs a WARNING message. When the number is above the threshold, the server logs an ERROR message. When

the server does not find available threads, it logs a message that the thread pool is exhausted. Valid values range from 100 to 100000. Default is 1000.

### ThreadDumpOnSlowTask

Whether to generate a thread dump when the server reports a slow task. Valid values are true - generate a thread dump, or false - do not generate a thread dump. Default is false.

### ThreadDumpInterval

The interval in milliseconds at which a thread dump is generated when the system reports slow or stalled tasks, or when the number of pending tasks exceeds the value of PendingTaskWarningThreshold. The thread dump interval applies across all thread pools in the JVM instance. Valid values range from 1000 to 600000. Default is 60000.

## Examples

In the following example, the slow-moving task warning timeout is set to 1000ms and the server is configured to generate a thread dump for a slow task. The task completed in 1060ms and the server reports that the task execution time exceeds 1000ms and generates a thread dump. The following entries will show in the log:

```
[Wed Feb 17 07:39:32.790 IST 2021] [ThreadPoolTest-Slow:9] ThreadPool:
<ThreadPool-SlowTasksTest> Slow moving task detected. ThreadPool-SlowTasksTest:9 has
been active
for over 1060(ms) running task class
com.pcbsys.foundation.threads.fThreadPoolTaskReportTest$TestTask, Idle Threads 7,
Allocated
Threads 10, Queued Tasks 0, Task Executed 10
[Wed Feb 17 07:39:32.790 IST 2021] [ThreadPoolTest-Slow:0] ThreadPool:
<ThreadPool-SlowTasksTest>
Slow moving task detected. ThreadPool-SlowTasksTest:0 has been active for over 1060(ms)
running
task class com.pcbsys.foundation.threads.fThreadPoolTaskReportTest$TestTask, Idle
Threads 7,
Allocated Threads 10, Queued Tasks 0, Task Executed 10
```

```
[Wed Feb 17 07:39:41.000 IST 2021] [ThreadPoolTest-Slow:7] ThreadPool:
<ThreadPool-SlowTasksTest> Slow moving task detected. ThreadPool-SlowTasksTest:7 has
been active
for over 1020(ms) running task class
com.pcbsys.foundation.threads.fThreadPoolTaskReportTest$TestTask, Idle Threads 7,
Allocated
Threads 10, Queued Tasks 0, Task Executed 10
[Wed Feb 17 07:39:41.000 IST 2021] [ThreadPoolTest-Slow:7] Producing thread dump.
Reason : Slow
moving task detected on thread pool: ThreadPool-SlowTasksTest
```

In the following example, the threshold for pending tasks is set to 200. Because the number of pending tasks in the thread pool is 209, the server logs an error message and generates a thread dump. The following entries will show in the log:

```
[Wed Feb 17 07:39:39.949 IST 2021] [Time-limited test] ThreadPool:
<ThreadPoolTest-Pending> Pending tasks are above the threshold 200 pending tasks 209,
Idle Threads
0, Allocated Threads 1, Queued Tasks 209, Task Executed 210
[Wed Feb 17 07:39:39.949 IST 2021] [Time-limited test] Producing thread dump. Reason
: Pending
```

---

```
tasks are above the threshold: 200 pending tasks: 209
```

## Troubleshooting Task Execution

To correct or improve the task execution, you can take the following actions:

- In the thread pool configuration, check whether you have allocated enough threads. If the logs report a large number of queued tasks, allocate more threads to the pool.
- Check for overall system slowdown, such as disk speed, network speed, CPU speed and allocation, and JVM garbage collection.
- Check for product behavior that might cause a slow performance.

