

ORACLE®

JD EDWARDS ENTERPRISEONE

Oracle JD Edwards EnterpriseOne

Tools Release 8.97

Web Services Gateway

Installation and Setup Guide

(Microsoft Windows and UNIX Systems)

November 2007

ORACLE®

Copyright © 2007, Oracle. All rights reserved.

The Programs (which include both the software and documentation) contain proprietary information; they are provided under a license agreement containing restrictions on use and disclosure and are also protected by copyright, patent, and other intellectual and industrial property laws. Reverse engineering, disassembly, or decompilation of the Programs, except to the extent required to obtain interoperability with other independently created software or as specified by law, is prohibited.

The information contained in this document is subject to change without notice. If you find any problems in the documentation, please report them to us in writing. This document is not warranted to be error-free. Except as may be expressly permitted in your license agreement for these Programs, no part of these Programs may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose.

If the Programs are delivered to the United States Government or anyone licensing or using the Programs on behalf of the United States Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS

Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are “commercial computer software” or “commercial technical data” pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the Programs, including documentation and technical data, shall be subject to the licensing restrictions set forth in the applicable Oracle license agreement, and, to the extent applicable, the additional rights set forth in FAR 52.227-19, Commercial Computer Software--Restricted Rights (June 1987). Oracle Corporation, 500 Oracle Parkway, Redwood City, CA 94065.

The Programs are not intended for use in any nuclear, aviation, mass transit, medical, or other inherently dangerous applications. It shall be the licensee's responsibility to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of such applications if the Programs are used for such purposes, and we disclaim liability for any damages caused by such use of the Programs.

The Programs may provide links to Web sites and access to content, products, and services from third parties. Oracle is not responsible for the availability of, or any content provided on, third-party Web sites. You bear all risks associated with the use of such content. If you choose to purchase any products or services from a third party, the relationship is directly between you and the third party. Oracle is not responsible for: (a) the quality of third-party products or services; or (b) fulfilling any of the terms of the agreement with the third party, including delivery of products or services and warranty obligations related to purchased products or services. Oracle is not responsible for any loss or damage of any sort that you may incur from dealing with any third party.

Oracle, JD Edwards, and PeopleSoft are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

Open Source Disclosure

Oracle takes no responsibility for its use or distribution of any open source or shareware software or documentation and disclaims any and all liability or damages resulting from use of said software or documentation. The following open source software may be used in Oracle's PeopleSoft products and the following disclaimers are provided.

This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>). Copyright (c) 1999-2000 The Apache Software Foundation. All rights reserved. THIS SOFTWARE IS PROVIDED “AS IS” AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Table of Contents

Table of Contents	iii
Preface	1
Oracle JD Edwards EnterpriseOne 8.97 Web Services Gateway	1
Additional Resources	1
Part 1: Installing Web Services Gateway Foundation.....	2
Understanding Web Services Gateway Foundation.....	3
Installation Overview.....	3
Web Services Gateway <i>Server</i>	3
Web Services Gateway <i>Developer</i>	4
Prerequisites	5
Architecture.....	5
Overview.....	5
Integration Server and Developer.....	5
Administrator	6
EnterpriseOne Adapter	6
Installing Web Services Gateway Foundation	7
Web Services Gateway Foundation Installation Flow	7
Installing Web Services Gateway (Server Installation)	7
Launching the Installer on Microsoft Windows	8
Launching the Installer on UNIX-Based Systems.....	8
Running the Installer.....	8
Completing Post-Installation Tasks	18
Starting Integration Server.....	18
Preparing the Database.....	18
Set Up User IDs, Passwords, and Permissions	19
Configure JDBC Drivers	19
Configure the JDBC Connection for Configuration Editor	25
Configure the JDBC Connection for Integrations	25
Set Up Platform Logging and Document History	27
Configuring Security	27
Disable Well-Known User Accounts	27
Secure EnterpriseOne Table Access.....	28
Secure Integration Server Access	28
Verify and Configure Integration Server Installation.....	28
Setting Up Integration Server to Use a Non-Default Java Development Kit.....	28
Increase File Descriptors on UNIX Systems	29
Change Permissions on UNIX Systems.....	29
Prepare Clients for Communication with Integration Server	29
Streamlining Integration Server.....	30

Uninstalling Web Services Gateway Foundation	32
Launching the Uninstaller	32
Running the Uninstaller	32
Migrating XPI Integration Points to Web Services Gateway	37
Upgrading Web Services Gateway.....	38
Applying Patch Updates to Web Services Gateway.....	39
Troubleshooting the Foundation Installation.....	40
Part 2: Configuring the EnterpriseOne Adapter	43
Understanding the EnterpriseOne Adapter.....	44
Prerequisites	44
Architecture.....	44
Configuring the EnterpriseOne Adapter: <i>Step 1</i>	46
Verifying a Connection to the Oracle JD Edwards EnterpriseOne Server.....	46
Configuring Connections.....	47
Configuring an Oracle EnterpriseOne Connection	53
Configuring an Oracle EnterpriseOne Guaranteed Event Connection.....	61
Configuring an Oracle EnterpriseOne Reliable Event Connection	67
Enabling the EnterpriseOne Adapter Connection: <i>Step 2</i>	77
Creating a Listener: <i>Step 3</i>	79
Enabling EnterpriseOne Adapter Listener: <i>Step 4</i>	83
Disabling the EnterpriseOne Adapter Connection	86
Troubleshooting the EnterpriseOne Adapter.....	89
Part 3: Configuring the Order Promising Adapter	100
Understanding the Order Promising Adapter	101
Prerequisites	101
Architecture.....	101
Configuring the Order Promising Adapter: <i>Step 1</i>	103
Configuring a New Order Promising Server Connection.....	103
Configuring a New Listener for the Order Promising Server	109
Enabling the Order Promising Adapter Connection: <i>Step 2</i>	116
Enabling a Listener: <i>Step 3</i>	119
Troubleshooting the Order Promising Adapter.....	127
Appendix A: Listing of Installable Components.....	133
Appendix B: Building a Web Services Gateway Developer Package	135
Configuring the Web Services Gateway install file.....	135
Creating a feature	135
Creating a Package	137
Appendix C: Determining the version of Integration Server components	149

Preface

Oracle JD Edwards EnterpriseOne 8.97 Web Services Gateway

This Oracle JD Edwards EnterpriseOne 8.97 Web Services Gateway (WSG) guide consists of three parts:

- Part 1 provides instructions for installing Oracle JD Edwards EnterpriseOne WSG foundation.
- Part 2 describes how to configure the EnterpriseOne Adapter.
- Part 3 describes how to configure the Order Promising adapter.

Each part consists of an overview, prerequisites, and system architecture followed by tasks for installing or configuring the software. In addition, a troubleshooting section is included in each part.

Additional Resources

This following table lists related documentation available on the Customer Connection website:

Guide	Description
<i>webMethods Developer User's Guide</i>	This guide provides an overview of the WSG Integration Developer architecture and components.
<i>JD Edwards EnterpriseOne 8.97 Web Services Gateway Integration Development Methodology Guide</i>	This guide provides a development methodology for creating integrations using WSG Integration Developer.
<i>JD Edwards EnterpriseOne Tools 8.97 Web Services Gateway Order Promising Adapter Programmer Guide</i>	This guide provides an overview of how to create and configure inbound service invocation and notification templates for the Order Promising adapter.
<i>JD Edwards EnterpriseOne Tools 8.97 Web Services Gateway EnterpriseOne Adapter Programmer Guide</i>	This guide provides an overview of how to create and configure inbound service invocation and notification templates for the EnterpriseOne Adapter.

Part 1: Installing Web Services Gateway Foundation

Understanding Web Services Gateway Foundation Installation

Web Services Gateway (WSG) is designed only for point-to-point scenarios, where Oracle JD Edwards EnterpriseOne must be one of the points. It is not to be used as an integration hub.

WSG provides for interoperability with Oracle Business Process Execution Language Process Manager (BPEL-PM). Interoperability consists of web services that are created in Oracle JD Edwards EnterpriseOne WSG and consumed by Oracle BPEL PM as well as web services that are provided by Oracle BPEL PM and consumed by Oracle JD Edwards EnterpriseOne WSG.

Installation Overview

The WSG foundation Installer offers two installation options: *WSG Server* and *WSG Developer*.

Web Services Gateway *Server*

WSG Server is the primary runtime engine for executing logic, enabling hosting, and executing the Integration processes. It provides the infrastructure and the tools that model and automate business processes, integrate resources, and manage the environment.

WSG Server 8.97 includes these features:

- WSG Server install contains only the WSG Server components, including Integration Server and foundation packages.

No development components are included.

- WSG Server is a standalone installer.
- WSG Server installer is available for Microsoft Windows, AIX, Solaris, HP-UX, HP-Itanium and Linux platforms.
- WSG Server components are installed in the root folder as /EnterpriseOne/wsg.
- WSG Server can be installed without any Oracle JD Edwards EnterpriseOne components; no Oracle JD Edwards EnterpriseOne Server or Oracle JD Edwards EnterpriseOne Microsoft Windows client is required to install WSG Server.
- WSG installation logs enable you to track the progress of the installation.
- WSG Server installer supports an overwrite feature.

This feature overwrites existing components that have been installed during the WSG installation process (multiple installations on the same box). If you plan to select “yes” to overwrite, make sure you have backed up the adapter configurations.

Note.

If you are familiar with previous versions of this product, note that:

- WSG installs typical server components with no option for other installation types.
 - Classic and Optional components are not available with the WSG Developer install.
-

Web Services Gateway *Developer*

WSG Developer is a graphical development tool for building, editing, and testing integration logic. It provides an Integrated Development Environment for developing the logic and Integration objects that perform the work of an integration solution.

WSG Developer 8.97 includes these features:

- WSG Developer install includes WSG Development components as well as WSG Server components.
- WSG Developer is a part of Oracle JD Edwards EnterpriseOne fat client, not a standalone installer.
- WSG Developer install is only available on Microsoft Windows platforms.
- WSG Developer components are installed in the Oracle JD Edwards EnterpriseOne Microsoft Windows client folder.
- WSG Developer is delivered as part of the Oracle JD Edwards EnterpriseOne package (Full/Update)
- WSG Developer includes GUI silent Install (No user interaction required during install).
- WSG Developer configurations can be saved and restored with Oracle JD Edwards EnterpriseOne Snapshot.
- WSG Installation logs are created to enable you to track the progress of installation.
- WSG Developer installer supports an overwrite feature.

This feature overwrites the existing components that have been installed during the WSG installation. If you plan to select “yes” to overwrite, make sure you have backed up the adapter configuration.

All Developer components are installed automatically during the Oracle JD Edwards EnterpriseOne package install. No selection panels, including install type, License and License agreement, are available.

For a detailed list of components delivered with Server installs and Developer installs, refer to “Appendix A: Listing of Installable Components” in this guide.

For instructions on building customized packages with selected Development components, refer to “Appendix B: Building a Web Services Gateway Developer Package” in this guide.

For instructions on how to determine the version of Integration Server components, refer to “Appendix C: Determining the version of Integration Server components” in this guide.

Selecting Where to Install Oracle JD Edwards EnterpriseOne Web Services Gateway

In designing the Oracle JD Edwards EnterpriseOne WSG architecture, the location of WSG components is flexible. The various components can all be placed on a single server, or they can be split among servers. As performance needs dictate, individual components can be moved off the server to increase scalability.

Prerequisites

Ensure that you meet these requirements before you install:

- Check that this document is the most current version.

Go to the Customer Connection website for the latest documentation.

- Read the release notes.

These notes contain information about features in this release.

- Visit Oracle | PeopleSoft Customer Connection to verify that the system meets the Minimum Technical Requirements (MTRs) for the hardware and software required to install Oracle JD Edwards EnterpriseOne WSG foundation.

Architecture

Overview

This chapter describes dependencies among Oracle JD Edwards EnterpriseOne WSG Integration Platform components and provides basic information on component implementation. To determine the best implementation of JD Edwards WSG components for your organization, contact Oracle Consulting Services.

Integration Server and Developer

If Integration Server and Developer are the only components of the Integration Platform you install, you can install the two components on the same machine. You can also install Integration Server and Developer on different machines on the same network. The Integration Server installation includes Integration Server Administrator, an HTML interface used to administer Integration Server.

This diagram shows the components of the Integration Platform:



Integration Platform components

This table lists data that Integration Server stores for JD Edwards WSG components:

Table or File	Data
IS Core Audit Log	<ul style="list-style-type: none"> Integration Server session, error, guaranteed delivery, and service logging data. 4.x Enterprise adapter activation logging data. In doubt, failed, and retries exceeded documents.
Process Audit Log	Modeler process logging data and Workflow logging data.
Cross-Reference	Cross-reference keys and process integrity status information required for synchronizing updates among various applications and the databases they reference.
Document History	History of documents processed by triggers.

Data stored for WSG components

By default, Integration Server stores most IS Core Audit Log, Process Audit Log, and Cross-Reference data in flat files, but you can store the data in databases as well. Document History must be stored in a database.

See *webMethods Integration Platform Logging and Monitoring Guide*

Administrator

This diagram shows the components of the Administrator application:



Administrator components

Install Administrator on the same machine as the Integration Server you want to use for platform administration.

EnterpriseOne Adapter

The EnterpriseOne Adapter provides a flexible, easy-to-use mechanism for WSG-enabled applications to interface with Oracle JD Edwards EnterpriseOne. The WSG install for a given tools release will install an EnterpriseOne Adapter that enables communication to an EnterpriseOne server having the same tools release level, For example, WSG 8.97A1 can connect to EnterpriseOne Tools Release 8.97A1.

Installing Web Services Gateway Foundation

This chapter discusses:


- The flow of Server and Developer installations.
- Installing Web Services Gateway (WSG) Server on UNIX and Microsoft Windows-based systems.
- Installing WSG Developer on Microsoft Windows-based systems.

Important!


The EnterpriseOne Adapter and Order Promising adapter are installed along with Web Services Gateway Foundation. You do *not* need to manually install these adapters.

Web Services Gateway Foundation Installation Flow

This diagram illustrates the flow of the WSG *Server* installation (see note):



This diagram illustrates the flow of the WSG *Developer* installation (see note):



Note.

You are required to input information on the forms during the *Server* installation.

You do *not* input information on the forms during the *Developer* installation. This is a silent install.

Installing Web Services Gateway (Server Installation)

This section discusses:

- Launching the installer on Microsoft Windows.
- Launching the installer on UNIX-based systems.
- Running the installer (Microsoft Windows and UNIX).

Launching the Installer on Microsoft Windows

► To launch the installer on Microsoft Windows systems

1. Download WSG Server from the Update Center

Locate and run the wininstall.bat or wininstall_console.bat program.

When the installer is launched, the Oracle WSG Installer – WSG 8.97 “welcome” form appears.

2. Skip to the section “Running the Installer” and follow the steps in the task “To run the installer (Microsoft Windows and UNIX-based systems).”

Launching the Installer on UNIX-Based Systems

WSG Server provides the installer for AIX, HP-UX, HP-ITANIUM, Linux, and Solaris platforms.

► To launch the installer on UNIX-based systems

1. Log on to the UNIX machine under the root account.
2. Download the platform specific WSG Server Install from Update Center
3. Run the UNIX installation script by entering one of these commands:

```
./gui.sh
```

or

```
./console.sh
```

Note.

On UNIX systems, there are two scripts to start the installer—one for the GUI mode (gui.sh) and one for the console mode (console.sh). Choose the script for the mode you want the installer to run.


For AIX systems, it is recommended that the console mode be used.

When the installer is started, the Oracle WSG Installer – 8.97 “Welcome” form appears.

Running the Installer


► **To run the installer (Microsoft Windows and UNIX-based systems)**

1. On the Welcome form, click **Next**.



Oracle WSG Installer 8.97 - Welcome Form

2. Enter the directory location for the installation, and then click **Next**.



Root directory for the WSG installation


Note.

For Microsoft Windows, the default installation location is C:\EnterpriseOne\wsg.

For UNIX, the default installation location is `opt/EnterpriseOne/wsg`.

For Microsoft Windows, the installer prompts you for the Start Menu group name. Accept the defaults or change the values.


3. If this pop-up message appears, click **Yes** to overwrite an existing WSG installation or click **No** to exit the installer.



Overwrite or exit message


All the WSG components are auto selected and can not be modified. This is the listing of all installable components.

4. Click Next



Components selected for installation

5. Select the check box to consent to the terms of the license agreement and click **Next**.



License agreement for WSG Integration Platform installation

6. On the “License key/Application type” form, specify:

- The license key (enter here or from IS Admin console).

Enter the Integration Server License key. Contact the Global Support Center to obtain this key. Keys are issued based on customer profiles according to the licensed software.

- One of these application types (Microsoft Windows only).

a. “Install as a normal Windows application” (Recommended).

Integration Server has to be manually started and stopped from the Startup menu or by running the server.bat file in directory `<wsg_home>\IntegrationServer\bin`.

b. “Install as a Windows NT/2000/XP Service”.

Integration Server automatically starts when you restart the machine. It can also be started and stopped from the Control Panel by selecting Administrative Tools, Services.

Oracle WSG Installer 8.97

ORACLE®

Integration Server

License key:

Application type:


Install as a normal Windows application

Install as a Windows NT/2000/XP Service

< Back Next > Cancel

Integration Server license key and application type

7. The next screen will show the list of components to be installed. Click **Next**. The installation process will commence.



List of components to be installed

8. When the installation is finished, review the list of installed components and click **Close**.



Listing of components successfully installed


9. Installing Web Services Gateway (Developer Installation)

WSG Developer can only be installed on a Microsoft Windows client.

► **To install the Developer**

Before performing the steps below, follow the instructions in "Appendix B: Building a Web Services Gateway Developer Package."

1. Run the Oracle JD Edwards EnterpriseOne InstallManager.
2. From the Client Install form, select the Oracle JD Edwards EnterpriseOne package containing WSG Developer and click **Next**.



Package selection form

Note.

This is a silent install. No input is required from the user.

Completing Post-Installation Tasks

After finishing the installation of the Oracle JD Edwards EnterpriseOne Web Services Gateway (WSG) Integration Platform, some components require you to perform post-installation tasks. This section discusses how to:

- Start Integration Server
- Prepare the database.
- Configure security
- Verify and configure the Integration Server installation.

Note.

For information on configuring the EnterpriseOne and Order Promising Adapters, see chapters “Configuring the EnterpriseOne Adapter” and “Configuring the Order Promising Adapter” in this guide.

Starting Integration Server

Perform these steps to start Integration Server on Microsoft Windows or UNIX platforms:

► To start Integration Server on Microsoft Windows

1. On the machine where you installed WSG Integration platform, select Start, Programs, EnterpriseOne, Servers, Web Services Gateway Integration Server.
2. Optionally, you can start Integration Server by running the server.exe file located in this directory:

```
<WSG_Install_Directory>\IntegrationServer\bin\server.exe
```

Where *<WSG_Install_Directory>* is the WSG installation directory. The default installation directory is `\EnterpriseOne\wsg`.

► To start Integration Server on UNIX-based systems

1. On the UNIX server, go to the Integration Server bin directory by entering this command:

```
cd EnterpriseOne/wsg/IntegrationServer/bin
```

2. Enter this command to start Integration Server:

```
./server.sh
```

Preparing the Database

WSG does not require a database at the time of installation. However, during configuration the Configuration Editor tool will require access to a database to create the cross-reference

data and integration options. The database administrator can choose to use an existing EnterpriseOne database or create a new database.

Note.

The Configuration Editor has built-in logic to modify existing cross-reference and integration options table structures when it is first accessed. If upgrading WSG the administrator can use the same database that was being used for the earlier version.

Set Up User IDs, Passwords, and Permissions

Ask the database administrator to set up the user IDs, passwords, and database permissions required for Integration Server to connect to the database. Integration Server requires create, update, and delete permissions. If you are storing different data types in the same database, Integration Server can use the same user ID and password.

The first time Configuration Editor is accessed, it creates new tables or modifies existing tables. Initially, the database user needs admin privileges, however you are advised to limit these privileges once Configuration Editor has created the tables.

Configure JDBC Drivers

Several components of WSG use JDBC drivers to access databases. This table lists the components and the databases accessed:

Integration Server Component	Database
JDBC Adapter connection for Configuration Editor	Database for Cross-Reference and Integration Option tables
JDBC Adapter connection for Integrations	Database for Cross-Reference and Integration Option tables
EnterpriseOne Adapter connection	Databases for EnterpriseOne tables

Configuring JDBC Drivers for Oracle Database (prior to 10g releases)

Complete these tasks when connecting to an Oracle database:

- Obtain the JDBC driver.
- Install the JDBC driver.
- Configure the tnsnames.ora file.

► **To obtain the JDBC driver**

The JDBC driver for Oracle is automatically downloaded when you install the Oracle client or server.

Verify that the file classes12.zip is present in directory `/jdbc/lib`, located in the Oracle install directory. If this file is not present, download it to directory `/jdbc/lib` from the Oracle website. At the time of this writing, the URL is:

http://otn.oracle.com/software/tech/java/sqlj_jdbc/index.html

► **To install the JDBC driver**

1. Copy the file classes12.zip from <oracle_home>\jdbc\lib to <WSG_Install_Directory>\IntegrationServer\lib\jars, Where <WSG_Install_Directory> is the directory where WSG is installed.
2. Rename the copied file from classes12.zip to classes12.jar.

Note.

You must restart the WSG Integration Server after copying the files.

► **To configure the tnsnames.ora file**

For the JD Edwards EnterpriseOne Adapter connection, you must supply or configure the tnsnames.ora file if you are using an Oracle database. This file defines the connection between the Oracle database and the WSG Integration Server. You can copy the tnsnames.ora file from the Oracle JD Edwards EnterpriseOne client to a directory on the WSG Integration Server.

See the JDBC Drivers table in the “Configuring an EnterpriseOne Connection” section of this guide for information on how to specify the location of the tnsnames.ora file.

Configuring JDBC Drivers for Oracle 10g Database

Complete these tasks when connecting to an Oracle 10g database:

- Obtain the JDBC driver.
- Install the JDBC driver.
- Configure the tnsnames.ora file.

► **To obtain the JDBC driver**

The JDBC driver for Oracle 10g is automatically downloaded when you install the Oracle client or server.

Verify that the file ojdbc14.jar is present in directory /jdbc/lib, located in the Oracle install directory. If this file is not present, download it to directory /jdbc/lib from the Oracle website. At the time of this writing, the URL is:

http://otn.oracle.com/software/tech/java/sqlj_jdbc/index.html

► **To install the JDBC driver**

1. Copy the file ojdbc14.jar from <oracle_home>\jdbc\lib to <WSG_Install_Directory>\IntegrationServer\lib\jars, Where <WSG_Install_Directory> is the directory where WSG is installed.

Note.

You must restart the WSG Integration Server after copying the file.

► **To configure the tnsnames.ora file**

For the Oracle JD Edwards EnterpriseOne Adapter connection, you must supply or configure the tnsnames.ora file if you are using an Oracle database. This file defines the connection between the Oracle 10g database and the WSG Integration Server. You can copy the tnsnames.ora file from the Oracle JD Edwards EnterpriseOne client to a directory on the WSG Integration Server.

See the JDBC Drivers table in the “Configuring an EnterpriseOne Connection” section of this guide for information on how to specify the location of the tnsnames.ora file.

Configuring JDBC Drivers for Microsoft SQL Server 2000 Database

Complete these tasks when connecting to a Microsoft SQL Server 2000 database:

- Obtain the JDBC driver.
- Install the JDBC driver.
- Configure the JDBC driver for the EnterpriseOne Adapter for WSG Integration Server.

► **To obtain the JDBC Driver**

Microsoft provides a Type 4 JDBC driver for SQL Server 2000, with full support and no additional charge to licensed customers.

1. Download the driver from Microsoft at this location:
<http://www.microsoft.com/downloads/Search.aspx>
2. From this location, search microsoft.com for “JDBC Driver for SQL Server 2000”
3. Ensure that you download the correct file for the platform where WSG Integration Server is running:

Integration Server Machine	Driver File Name
Microsoft Windows-based	setup.exe
UNIX-based	mssqlserver.tar

► **To install the JDBC driver**

1. Follow the instructions accompanying the downloaded drivers.
2. Verify that the lib folder in the install directory contains these files:
 - mssqlserver.jar
 - msbase.jar
 - msutil.jar

► **To configure the JDBC driver**

To configure the JDBC driver for the EnterpriseOne Adapter for WSG Integration Server, copy the jar files mssqlserver.jar, msbase.jar, and msutil.jar into this directory:

`<WSG_Install_Directory>\IntegrationServer\lib\jars`

Where `<WSG_Install_Directory>` is the directory where WSG is installed.

Note.

You must restart the WSG Integration Server after copying the files into this location.

Configuring JDBC Drivers for Microsoft SQL Server 2005 Database

Complete these tasks when connecting to a Microsoft SQL Server 2005 database:

- Obtain the JDBC driver.
- Install the JDBC driver.
- Configure the JDBC driver for EnterpriseOne Adapter for WSG Integration Server.

► **To obtain the JDBC Driver**

Microsoft provides a Type 4 JDBC driver for SQL Server 2005, with full support and no additional charge to licensed customers.

1. Download the driver from Microsoft at this location:
`http://www.microsoft.com/downloads/Search.aspx`
2. From this location, search microsoft.com for “JDBC Driver for SQL Server 2005”
3. Ensure that you download the correct file for the platform where WSG Integration Server is running:

Integration Server Machine	Driver File Name
Microsoft Windows-based	sqljdbc_1.1.1501.101_enu.exe
UNIX-based	sqljdbc_1.1.1501.101_enu.tar.gz

► **To install the JDBC driver**

1. Follow the instructions accompanying the downloaded drivers.
2. Verify that the lib folder in the install directory contains the file:
 - sqljdbc.jar

► **To configure the JDBC driver**

To configure the JDBC driver for the EnterpriseOne Adapter for WSG Integration Server, copy the sqljdbc.jar into this directory:

`<WSG_Install_Directory>\IntegrationServer\lib\jars`

Where *<WSG_Install_Directory>* is the directory where WSG is installed. The default installation directory is C:\EnterpriseOne\wsg.

Note.

You must restart the WSG Integration Server after copying the files into this location.

Configuring JDBC Drivers for DB2 UDB Databases

Complete these sections when connecting to a DB2 UDB database:

- Obtain the JDBC driver.
- Install the JDBC driver.
- Catalog the DB2 UDB database.

Note.

If you have not yet installed a DB2 UDB client or server on the Integration Server machine, obtain the installation instructions from this IBM website:

<http://www-3.ibm.com/software/data/db2/>

► To obtain the JDBC driver

The JDBC driver for DB2 UDB is delivered with the DB2 VUDB server or client installation. After installing the DB2 UDB server or client, follow the instructions to set up the JDBC 2.0 driver:

1. Ensure these services are stopped:
 - DB2 JDBC Applet Server
 - DB2 JDBC Applet Control Center (if applicable)
2. From a Microsoft Windows command line, change to java12 directory inside the DB2 directory. For example:

```
cd <DB2_UDB_Home_Directory>\java12
```

3. Run batch file `usejdbc2.bat`.

This batch file creates the IBM JDBC 2.0 driver `db2java.zip` in directory `sqllib\java`.

4. Restart the services that you stopped in the first step.

► To install the JDBC driver

1. Copy the file `db2java.zip` from `<DB_Home>\sqllib\java12` to `<WSG_Install_Directory>\IntegrationServer\lib\jars`

Where `<DB_Home>` is the base directory for DB2 UDB and `<WSG_Install_Directory>` is the directory where WSG is installed.

The default installation directory is C:\EnterpriseOne\wsg.

2. Rename the copied file from db2java.zip to db2java.jar.

Note.

You must restart the WSG Integration Server after copying the files to this location.

► **To catalog the DB2 UDB database**

On the WSG Integration Server machine, run the DB2 UDB Client Configuration Assistant to access the file on the Deployment Server that catalogs the DB2 UDB databases.

For instructions on cataloging DB2 UDB databases, refer to the applicable guide:

- *Oracle JD Edwards EnterpriseOne 8.12 Installation Guide for UDB DB2 on Windows-Based Systems*
- *Oracle JD Edwards EnterpriseOne 8.12 Installation Guide for UDB DB2 on UNIX-based Systems*

Assuming the oneworld.spf file is created and available, complete these steps:

1. From the Desktop, select Start, Programs, IBM DB2, Client Configuration Assistant.
2. If the Add Database form appears, close it.
3. Click **Import** at the bottom of the form.
4. Click **Network** and browse to the directory on the Deployment Server that contains the oneworld.spf file.
5. Open the oneworld.spf file.
6. On the Integration Server machine, open file db2cli.ini, located in directory DB2/UDB. For example:

```
c:\sql1lib\
```
7. Comment out or remove the LOBCachSize parameters under the database aliases associated with Oracle JD Edwards EnterpriseOne and save the changes.

Configuring JDBC Drivers for DB2 for iSeries Databases

Complete these tasks when connecting to a DB2 for iSeries (AS/400) database:

- Obtain the JDBC driver.
- Install the JDBC driver.

► **To obtain the JDBC driver**

Obtain the AS/400 Toolbox for Java from IBM at this website:

<http://www.as400.ibm.com/toolbox>

► **To install the JDBC driver**

1. Locate the file jt400.zip that is delivered by the AS/400 Toolbox.
2. Copy the jt400.zip file into this directory:

<WSG_Install_Dir>\IntegrationServer\lib\jars

3. Rename the file from jt400.zip to jt400.jar.

Configure the JDBC Connection for Configuration Editor

Refer to *Oracle JD Edwards EnterpriseOne Tools 8.97 Web Services Gateway: Configuration Editor Guide* for details on how to configure and access this tool.

Configure the JDBC Connection for Integrations

The JDBC Connection is used by integrations to access cross-reference data and integration options.

The cross-reference and integration options tables are created by Configuration Editor.

► To create the JDBC connection

1. Open Integration Server Administrative Console by entering this URL in your internet browser:

`http://<Host_Name>:5555`

Where <Host_Name> is the name, or IP address, of the Integration Server and 5555 is the default port for the Integration Server.

2. Select Adapters, JDBC Adapter.
3. In the right pane on JDBC Adapter Connections, click the link in the Edit column for the PSFT_JDBCAdapterServices.

On the JDBC Adapter menu in the left pane, ensure that Connections is selected. You might need to scroll to see the Edit column.

4. Complete the parameters on the Connection window, and then click **Save Changes**.

For detailed information about each parameter, select the help link located in the upper-right corner of the JDBC Adapter Connections form.

Examples of the form for Oracle and Microsoft SQL Server databases are shown here.

Completing Post-Installation Tasks

This example shows all the parameters on the Connection form for an Oracle database:

Connection Properties	
Transaction Type	NO_TRANSACTION
DataSource Class	oracle.jdbc.pool.OracleDataSource
serverName	DBServer1
user	WSGUser
password	*****
Retype password	*****
databaseName	ora9201
portNumber	1521
networkProtocol	
Other Properties	driverType=thin
Connection Management Properties	
Enable Connection Pooling	true
Minimum Pool Size	1
Maximum Pool Size	10
Pool Increment Size	1
Block Timeout (msec)	1000
Expire Timeout (msec)	1000
Startup Retry Count	1
Startup Backoff Timeout (sec)	10

Connection properties form – Oracle database server

This example shows all the parameters on the Connection form for Microsoft SQL Server:

Transaction Type	NO_TRANSACTION
DataSource Class	com.microsoft.jdbcx.sqlserver.SQLServerDataSource
serverName	DBServer1
user	WSGUser
password	*****
Retype password	*****
databaseName	XRef
portNumber	1433
networkProtocol	
Other Properties	
Connection Management Properties	
Enable Connection Pooling	true
Minimum Pool Size	1
Maximum Pool Size	10
Pool Increment Size	1
Block Timeout (msec)	1000
Expire Timeout (msec)	1000
Startup Retry Count	1
Startup Backoff Timeout (sec)	10

Connection properties form – Microsoft SQL Server

- To make the JDBC adapter connection available, ensure that the link in the Enabled column for the PSFT_JDBCAdapterServices is set to Yes.

If the link is set to No, click the link to toggle it to Yes.

- Close the Connection form.

Set Up Platform Logging and Document History

By default, Integration Server writes IS Core Audit Logs and Process Audit Logs to flat files, but you can configure Integration Server to write to a database. Integration Server stores document history in database tables. SQL scripts in directory `<Web Services GatewayInstallDirectory>\common\db\scripts` are provided to create the required tables.

For complete instructions on this topic and platform logging in general, see the *webMethods Integration Platform Logging and Monitoring Guide*.

Configuring Security

This section contains instructions for securing access to WSG and EnterpriseOne

Disable Well-Known User Accounts

WSG Integration Server uses the default passwords for privileged user accounts such as Administrator and Developer. It is recommended that you change these passwords or disable

these accounts immediately after installation. See *webMethods Integration Server Administrator's Guide*, "Managing Users and Groups."

Secure EnterpriseOne Table Access

An EnterpriseOne user/role is used in the configuration of the EnterpriseOne Adapter. The adapter has read access to the same tables as this EnterpriseOne user/role. It is recommended that you set up EnterpriseOne row security for tables that contain secure data and EnterpriseOne system information. See *EnterpriseOne Security Administration Guide* for more information.

Secure Integration Server Access

It is recommended that you set up who has administrative access to the server, who can develop and update packages, and who can secure Integration Server ports. See *webMethods Integration Server Administrator's Guide*, "Managing Server Security."

Verify and Configure Integration Server Installation

This section contains instructions for verifying and configuring Integration Server installation.

Setting Up Integration Server to Use a Non-Default Java Development Kit

You can configure Integration Server to use a Java Development Kit (JDK) other than the default JDK to compile Java services created using Developer.

► To configure a different JDK for Integration Server

1. Start Integration Server and open Integration Server Administrator.
2. Select the Settings, Extended form, and then click **Show and Hide Keys**.

Integration Server Administrator displays a list of Integration Server configuration properties you can change.

3. Select the check box for the `watt.server.compile` and `watt.server.compile.unicode` properties.
4. Click **Save Changes**.

Integration Server Administrator displays the selected properties in the Extended Settings box.

5. Click **Edit Extended Settings**.

In the Extended Settings box, set these properties:

- `watt.server.compile=<JDK_directory>/bin/javac -classpath {0} -d {1}{2}`
 - `watt.server.compile.unicode=<JDK_directory>/bin/javac -encoding Unicode -classpath {0} -d {1}{2}`
6. Click **Save Changes**.

7. Restart Integration Server.

Increase File Descriptors on UNIX Systems

On UNIX systems, Integration Server's ability to handle traffic is constrained by the number of file descriptors available to the Integration Server process. On most UNIX systems, 64 file descriptors are available to each process by default. It is recommended that you increase the number of file descriptors available to the Integration Server process to at least 1024.

Change Permissions on UNIX Systems

If you installed Integration Server on a UNIX system and non-root users will be running Integration Server, you might want to change the ownership of the installed files to non-root user, change the permissions for the installed files so that they can be accessed by non-root users, or both.

Note.

You might have to increase this number depending on the number of files Integration Server needs to have open at one time. You should not set the `rlim_fd_max` value higher than 1024 because of limitations with the select function "If Integration Server" requires more file descriptors, set the `setrlimit` value directly.

Prepare Clients for Communication with Integration Server

If you have applications (for example, Java or Visual Basic or C/C++ programs) that you want to be Integration Server clients, you must prepare the clients for communication with Integration Server.

► To prepare clients for communication with Integration Server

Integration Server `client.jar` file contains classes that Integration Server clients need to communicate with Integration Server

1. If you have Integration Server clients on the same machine as Integration Server or Developer, set the classpath on the machine to include the `client.jar` file.

The `client.jar` file is located in the `\lib` directory. Set the classpath as appropriate:

```
%CLASSPATH%; <Integration Server Directory>\lib\client.jar
```

or

```
%CLASSPATH%; <Developer Directory>\lib\client.jar
```

2. If you have Integration Server clients on machines that do not contain either Integration Server or Developer, perform these steps for each client:
 - a. Navigate to the `<Integration Server Directory>\lib` or `<Developer_Directory>\lib` directory and copy the `client.jar` file to any directory on the client machine.
 - b. In the directory with the copied `client.jar` file (step a), create a directory named `entrust`.

- c. From the *<Integration Server Directory>\lib* or *<Developer_directory>\lib* directory, copy these files to the *entrust* directory:

- *entbase.jar*
- *entcertlist.jar*
- *entmisc.jar*
- *entnsext.jar*
- *entssl.jar*

For example, if you put the *client.jar* file in directory *c:\myapp*, create the *entrust* directory in that directory, and put the *entrust* files in directory *c:\myapp\entrust*.

The Integration Server *entrust* ".jar" files provide security for client communications.

- d. Set the classpath on the client machine to include the *client.jar* file.

For example, if you put the *client.jar* file in directory *c:\myapp*, you would set the classpath to *%CLASSPATH%;c:\myapp\client.jar*.

Streamlining Integration Server

Integration Server is delivered with several packages that provide different functionality. If you want to streamline Integration Server (for example, you are using it only to run adapters), you can disable many of these packages.

► To disable Integration Server packages

1. Review this table and determine which packages you can safely disable.

Package	Contents
WmART	Services that Integration Server uses to run adapters that are version 6.0 or later.
WmAdminResource	Services that Administrator uses to retrieve resource information about Integration Server.
WmFlatFile	Services that enable you to process flat files and use file polling ports.
WmOmiAgent	Services that Manager Server uses to connect to and manage Integration Server. Note. If you are going to use the WmART package, you cannot disable the WmOmiAgent package.
WmOmils	Services that Manager Server uses to manage adapters installed on Integration Server. Note. If you are going to use the WmART package, you cannot disable the WmOmils package.
WmPRT	Runtime for business process models.
WmWin32	Services you can use to call methods on COM objects. Also contains Microsoft Windows-specific samples, such as sample Visual Basic services.

2. Start Integration Server:

- For **Microsoft Windows**

On the Start menu, select Programs, JD Edwards, Servers, and then double-click JD Edwards Web Services Gateway Integration Server.

- For **UNIX**

Navigate to the *<Integration Server Directory>/bin* directory and run the script `server.sh`.

3. The WmOmiAgent package is dependent on the WmOmiS package. If you want to disable the WmOmiS package, but you want to use the WmOmiAgent package, you must first remove the dependency or the WmOmiAgent package will not load. Perform these steps:

Note.

If you are going to use the WmART package, you cannot disable the WmOmiAgent package or the WmOmiS package.

- a. Start Developer:

- For **Microsoft Windows**

On the Start menu, select Programs, EnterpriseOne, and then double-click WSG Developer.

- For **UNIX**

Navigate to the *<Integration Server Directory>/bin* directory and run the script `server.sh`.

- b. In the Navigation panel, on the left side of the form, right-click the WmOmiS package, and then click **Open**.
- c. On the Settings tab, in the Package dependencies area, select the WmOmiAgent row.
- d. Click **Developer** to remove the WmOmiAgent package's dependency on the WmOmiS package.

4. Open Integration Server Administrator by entering this URL in your internet browser:

`http://<Host_Name>:5555`.

Where *<Host_Name>* is the name, or IP address, of the Integration Server and 5555 is the default port for the Integration Server.

5. Sign in with the default username and password, Administrator and manage.
6. In the navigation area, under the Packages menu, click **Management**.

Integration Server Administrator displays the Packages > Management form.

7. Disable each package you do not need.

To do so, locate the row for the package in the grid on the Packages > Management form, then click **Yes** in the Enabled column for that row.

Note.

Do not disable the WmRoot or WmPublic packages.

Uninstalling Web Services Gateway Foundation

This chapter provides instructions for uninstalling Oracle JD Edwards EnterpriseOne Web Services Gateway (WSG) foundation components.

Launching the Uninstaller

Follow the appropriate set of instructions based on the platform you are using.

► To start the Oracle WSG Uninstaller - 8.97 on Microsoft Windows

1. Using Integration Server Administrator, stop Integration Server.
2. Shut down all other components you want to uninstall.
For adapters, make sure that you disable the adapter connections.
3. Disable any packages containing EnterpriseOne Adapter listeners or listener notifications.
4. Run the uninstaller from Control Panel, Add/Remove Programs, Oracle WSG 8.97.
See “Running the Installer” in the section below.”

► To start the Oracle WSG Uninstaller - 8.97 on UNIX systems

1. Using Integration Server Administrator, stop Integration Server.
2. Shut down all other components you want to uninstall.
For adapters, make sure that you disable the adapter connections.
3. Disable any packages containing EnterpriseOne Adapter listeners or listener notifications.
4. Execute the “uninstall” script, which is found in the bin subdirectory of the Web Services Gateway installation directory

The default location is `opt/EnterpriseOne/wsg/bin`.

Note.


You can also run the uninstall in console mode by entering this command:

```
uninstall -console.
```

Running the Uninstaller


► To run the Oracle WSG Uninstaller

1. When the uninstaller is launched, the “welcome” form appears.
Click **Next**.



Welcome form of the uninstaller

2. On the uninstall component selection form, select the components you want to uninstall, and then click **Next**.



Select components to uninstall

3. On the “ready to uninstall” form, click **Next**.



Oracle WSG Uninstaller ready to uninstall form

4. Verify that the list of uninstalled components is correct, and then click **Close**.



Oracle WSG Uninstall complete form

Uninstalling WSG Developer Installation

WSG Developer is uninstalled through the Oracle JD Edwards EnterpriseOne client uninstall program or the "Add/Remote programs" application of control panel.

► **To uninstall through the Client Uninstall**

1. Using Integration Server Administrator, stop Integration Server.

2. Shut down all other components you want to uninstall.

For adapters, make sure that you disable the adapter connections.

3. Disable any packages containing EnterpriseOne Adapter listeners or listener notifications.

4. Invoke EOne Client Uninstall

5. Select WSG Developer component to be uninstalled

Uninstalling through Add/Remove programs of Control Panel

► **To start the Oracle WSG Uninstaller - 8.97**

1. Using Integration Server Administrator, stop Integration Server.

2. Shut down all other components you want to uninstall.

For adapters, make sure that you disable the adapter connections.

3. Disable any packages containing EnterpriseOne Adapter listeners or listener notifications.

4. Run the uninstaller from Control Panel, Add/Remove Programs, Oracle WSG 8.97.

See "Running the Installer" in the Uninstall WSG Server Installation section." Modifying Web Services Gateway

Migrating XPI Integration Points to Web Services Gateway

Web Services Gateway (WSG) is a new product and upgrade is not supported from versions of eXtended Process Integration (XPI). However, WSG does support integration points defined in versions of XPI.

Considerations for migrating XPI integration points to WSG:

- Integration points need to be exported from earlier XPI Integration Server versions and imported to WSG Integration Server.
- The Integration Server-Based Configuration Editor has a built-in mechanism to update the table structure when CE is accessed the first time.
- Integration Options can be migrated from an old format to a new format through Data Slimmer, which is a built-in tool in Integration Server-based Configuration Editor.
- All the adapters need to be newly configured.
- WSG Developer can only be installed on Oracle JD Edwards EnterpriseOne Microsoft Windows client machines.

Upgrading Web Services Gateway

Upgrading from EnterpriseOne Tools 8.95 and 8.96 WSG to EnterpriseOne Tools 8.97 WSG is supported. The current integration points deployed on Integration Server will continue to function. However, the adapter configurations need to be backed up and then manually restored.

Note.

If applying patch updates to WSG, first complete the steps in “Applying Patch Updates to Web Services Gateway” in this chapter. Then complete these steps.

► To upgrade to EnterpriseOne Tools 8.97 Web Services Gateway

1. Stop the adapter connections.
2. Back up the adapter connections by saving file `node.ndf` to a temporary directory.
For example, to back up the E1 Adapter EnterpriseOne connection, copy file `<WSG_Install_Folder>\IntegrationServer\packages\PSFT_E1_Adapter\ins\connection\EnterpriseOne\node.ndf` to the temporary directory.

Also keep back up of entries for all the connection parameters for the EnterpriseOne connection.

3. If you are installing the new version of *WSG Server*, perform this step. If you are installing the new version of *WSG Developer*, skip to step 4.
 - a. Start the installer by running `wininstall.bat` (on Microsoft Windows) or `gui.sh` (on UNIX platforms).
 - b. For the install location, specify the same location as the existing WSG.
 - c. Change the Start Menu group name to EnterpriseOne.
 - d. Click **Yes** to update the confirmation message.
 - e. Skip to Step 5.
4. Install the new version of WSG Developer:
 - a. Create a new WSG package.

An EnterpriseOne admin user needs to:

 - i. Follow the instructions in “Appendix B: Building a Web Services Gateway Developer Package” in this guide to copy the new WSG install image to the Deployment Server.
 - ii. Edit the setting in file `wsg.ini` to specify the same Start Menu Folder as in the previous install:

```
StartMenuFolder=EnterpriseOne
```
 - iii. Follow the remainder of the instructions in “Appendix B: Building a Web Services Gateway Developer Package” in this guide to complete the package build and deploy process.

- b. Upgrade WSG.

An EnterpriseOne development user needs to:

- i. Use EnterpriseOne InstallManager to install the new update package for WSG.
 - ii. Click **Yes** to update the confirmation message.
5. Restore the adapter connection:
 - a. Configure the connections with the same entries as the previous connection when saved.
 - b. Restart Integration Server.
6. Start the adapter connection.

Applying Patch Updates to Web Services Gateway

Updates for Web Services Gateway will be posted on the Customer Connection Update Center.

Use these search criteria to find and download the latest WSG updates:

Search Type = EnterpriseOne Tools Releases

Release = All EOne 8.9x Releases

Platform = All Platforms

Search For Text = 8.97*_W*

Note:

Refer to Appendix C to learn how to determine the version of WSG Integration Components.

► To apply an update for WSG

1. Download the update package from the Update Center
2. Use Change Assistant to extract the downloaded files (<http://maintenance.peoplesoft.com/softwaredownloads/home/content/documents/changeassistant.html>)
3. Complete the steps in “Upgrading Web Services Gateway” in this chapter.

Troubleshooting the Foundation Installation

This chapter provides information on how to troubleshoot issues in Oracle JD Edwards EnterpriseOne WSG products for version 8.97. In addition, it provides recommendations for configuring certain Oracle JD Edwards EnterpriseOne WSG components.

Installation Issues

Problem: When run in GUI mode, the installer might freeze after clicking the first **Next** button.

Resolution: Cancel and restart the installer. If you cannot cancel the installer, terminate the installer process.

Problem: Installer forms might be combined, resulting in overlapping or missing text.

Resolution: Wait until the text appears on the first form of the installer before proceeding to the next form.

Problem: At the end of a console-mode uninstall on HP-UX, this message might appear:

```
./uninstall[93]: test: ] missing
```

Resolution: None. The message can be ignored.

Integration Server

You should start Integration Server in an environment where there are an adequate number of file descriptors. By default, a user has 64 file descriptors on most UNIX systems. Since the number of file descriptors available limit the Server's scalability, it is recommended that you increase the number of file descriptors available in the Server's environment to at least 1024.

To provide tighter security on the server, all new ports are added in Deny by Default mode. This means only those built-in services with their Execute ACL set to Anonymous ACL are accessible through the port. You add the services you want to make available through the Allow List. You can also change the port to Allow by Default mode, which enables all services to be accessed through the port. Upon installation, only one port (http@5555) is started in Allow by Default mode. If you are installing packages that have listeners defined, after installing and activating the package, populate the Allow/Deny list for the services available through that listener. On the Ports form in the Server Administrator, select the listeners defined in the newly installed package, and click Access Mode. To reset the listener to the default state, click "Reset to default access settings." This invokes the listener Deny by Default for service and populates the Allow list with a predefined list of services. You can now add or remove services to the Allow/Deny list.

You might want to install Integration Server as a Microsoft Windows application. Integration Server has startup issues when it is installed as a service. If Integration Server performance degrades as time passes and you cannot restart it, there is insufficient memory for the JVM.

To increase the memory for the JVM, follow these steps:

1. Navigate to the bin directory of the Integration Server and open file server.bat in a text editor (or server.sh for Unix/Linux platforms).

2. Locate these lines:

```
set JAVA_MIN_MEM=128M
```

```
set JAVA_MAX_MEM=256M
```

3. Edit these lines to increase the heap size:

```
set JAVA_MIN_MEM=256M
```

```
set JAVA_MAX_MEM=512M
```

4. Restart Integration Server.

Problem: On UNIX/Linux, Integration Server will not start, displaying this error message:

```
at com.wm.util.BasisRuntimeException.<init>(BasisRuntimeException.java:173)
at com.wm.util.data.TxnData$TData.getSharedCursor(TxnData.java:521)
at com.wm.util.data.TxnData$TData.getSharedCursor(TxnData.java:471)
at com.wm.app.repov4.server.RepoServerCommon.isRepoDirectory(Repo
ServerCommon.java:46)
at com.wm.app.repov4.server.RepoServerDirectory.getValueAsDirectory(Repo
-----
at
com.wm.distman.install.DistManInstallMain.main(DistManInstallMain.java:24)
```

Resolution: This occurs when the repository files are corrupted during the server startup process. To fix the problem, delete all the files in these directories then restart Integration Server:

- IntegrationServer/WmRepository2
- IntegrationServer/WmRepository4
- IntegrationServer/audit/data
- IntegrationServer/document

Developer

If you are running on Solaris and using Netscape 6.0 as your browser, the navigation panel for Online Help might not display correctly.

Integration Server JDBC Adapter

JDBC adapter Connection Pooling / Firewall Settings: If the database is shut down or restarted, adapter services might not work properly with non-default connection management properties.

Command Line Tools

On HP-UX, use of the at-sign (@) for command line tools requires you to quote the string. Apparently, this is a special character to the default shell.

Language Library: Java Edition

Client programs can hang when running on Solaris using native threads instead of green threads. This problem is due to a bug in the Solaris kernel. The workaround is to switch to green threads by setting the environment variable `THREADS_FLAG` to green.

Client programs can hang when running on HP-UX 11.0 using native threads instead of green threads. This problem is due to a bug in the HP-UX kernel. The workaround is to switch to green threads by setting the environment variable `THREADS_FLAG` to green.

On HP-UX, a Java program containing “destroy” will hang. To make the program execute, use this runtime option:

```
java -XdoCloseWithReadPending <class_name>
```

Part 2: Configuring the EnterpriseOne Adapter

Understanding the EnterpriseOne Adapter

The EnterpriseOne Adapter for WSG Integration Server enables the exchange of information between Oracle JD Edwards EnterpriseOne and other heterogeneous systems, including Clarify, PeopleSoft, SAP, and Oracle Financials. The EnterpriseOne Adapter provides a flexible, easy-to-use mechanism for WSG-enabled applications to interface with Oracle JD Edwards EnterpriseOne.

The procedures in this chapter support these systems:

- Oracle JD Edwards EnterpriseOne 8.9 (Tools Release 8.97)
- Oracle JD Edwards EnterpriseOne 8.10 (Tools Release 8.97)
- Oracle JD Edwards EnterpriseOne 8.11 (Tools Release 8.97)
- Oracle JD Edwards EnterpriseOne 8.12 (Tools Release 8.97)

Prerequisites

Ensure that these prerequisites are met prior to installing and configuring the EnterpriseOne Adapter:


- Obtain the latest version of the applicable installation guides.
- Visit Customer Connection and verify that the system meets the Minimum Technical Requirements (MTRs) for the hardware and software required to install Oracle JD Edwards EnterpriseOne WSG foundation.
- Install 8.97 WSG foundation before you configure the EnterpriseOne Adapter.
- Make sure the package PSFT_E1_Adapter is installed in the WSG Integration Server if you want to use the sample services shipped with the EnterpriseOne Adapter.

Architecture

The EnterpriseOne Adapter connects to Oracle JD Edwards EnterpriseOne using the standard interoperability technologies built into Oracle JD Edwards EnterpriseOne. This adapter has been updated to run on the new adapter framework, which resides on Integration Server. This provides a more scalable and reliable runtime framework for the adapter and exposes the Oracle JD Edwards EnterpriseOne services directly to the WSG Integration Server process flow.

This graphic illustrates the adapter architecture:

Understanding the EnterpriseOne Adapter



JD Edwards EnterpriseOne Adapter for WSG Integration Server architecture

Configuring the EnterpriseOne Adapter: *Step 1*

To configure the EnterpriseOne Adapter, perform these tasks:

- Verify the connection to the Oracle JD Edwards EnterpriseOne server.
- Configure a new connection or update a default connection.

Note.

After you complete the steps in this section, perform these additional tasks to make the adapter available for use:

- Install and configure the JDBC drivers.

Refer to “Configuring JDBC Drivers” in this chapter.

- Before working with the EnterpriseOne Adapter JDBj templates, ensure that the serialized objects for tables and views have been generated in the Oracle JD Edwards EnterpriseOne database.

See the *EnterpriseOne Tools 8.97 HTML Server Installation*.

Verifying a Connection to the Oracle JD Edwards EnterpriseOne Server

Before using the EnterpriseOne Adapter, access the EnterpriseOne Adapter Configuration form and verify the connection to the Oracle JD Edwards EnterpriseOne server.

► **To access the adapter configuration form**

1. Open Integration Server Administrator by entering this URL in your internet browser:

`http://<Host_Name>:5555.`

Where *<Host_Name>* is the name, or IP address, of the Integration Server and 5555 is the default port for Integration Server.

2. Sign in with the default username and password, Administrator and manage.

Configuring the EnterpriseOne Adapter: Step 1

3. In the left pane of the Integration Server Administrator console, click **Adapters**, and then click **EnterpriseOne Adapter**.

This example shows the Integration Server Administrator console:

The screenshot shows the Integration Server Administrator console in a Microsoft Internet Explorer browser window. The browser address bar shows <http://den-ur6864969:5555/>. The page title is "DEN-UR6864969.jdedwards.com :: Integration Server". The left navigation pane is expanded to the "Adapters" section, where the "EnterpriseOne Adapter..." link is highlighted with a pink circle. The main content area displays "Server > Statistics" with several tables and a chart.

Usage			
	Current	Peak	Limit
Total Sessions	1	3	-
Licensed Sessions	0	1	10000
Service Threads	1	4	-
System Threads	284	284	-
Uptime	20h:48m:11s		

Requests	
	Current
Completed Req's	2145
Average Time	0 ms
Service Errors	3
Started	Started
Req's per minute	6/min

Memory	
Total	246462 KB
Used	159402 KB 65%
Free	87060 KB 35%

Memory Usage (average per hour) chart showing usage over time from -24h to -1h. The y-axis represents memory usage in KB, ranging from 0 to 246462 KB.

Server > Statistics form

Note.

If the EnterpriseOne Adapter link does not appear, then the adapter is not installed correctly. See "Troubleshooting the EnterpriseOne Adapter for Web Services Gateway Integration Server" in this guide.

Configuring Connections

JD Edwards includes three default connections with the EnterpriseOne Adapter installation. These connections are used for the adapter samples and for all the pre-built integrations. To use these default connections, you must configure them for the Oracle JD Edwards EnterpriseOne server.

For other services, you can use the default connections or create new connections. Note that adapter services are tied to a connection name when they are created.

Note.

Once created, you cannot change the connection that a particular service uses.

After you update a default connection or create a new one, configure the connection based on the connection type.

This section discusses:


- Configuring a new connection.
- Updating a default connection.
- Configuring an Oracle EnterpriseOne Connection.
- Configuring an Oracle EnterpriseOne Guaranteed Event Connection
- Configuring an Oracle EnterpriseOne Reliable Event Connection

► **To configure a new connection (Optional)**

Note.

It is recommended that you use the default connections. Continue with this section only if you need a separate connection. Otherwise, skip to the task “To update a default connection” in this chapter.

1. From the Integration Server Administrative console, select Adapters > EnterpriseOne Adapter > Connections.
2. On Adapters > EnterpriseOne Adapter > Connections form, click **Configure New Connection**.



Connections form

This form shows where to select connection types:

Configuring the EnterpriseOne Adapter: Step 1

3. On Adapters > EnterpriseOne Adapter > Connection Types, select one of these available types:

- Oracle EnterpriseOne Connection


Connects to Oracle JD Edwards EnterpriseOne servers.

- Oracle EnterpriseOne Reliable Event Connection (8.9 and 8.10 only)

Connects to Oracle JD Edwards EnterpriseOne Tools 8.97 servers (8.9 & 8.10 only) to receive outbound events such as RealTime, XAPI, ZTable, and so on.


- Oracle EnterpriseOne Guaranteed Event Connection

Connects to Oracle JD Edwards EnterpriseOne Tools 8.97 web servers to receive outbound events.



Connection Types form

- On Adapters > EnterpriseOne Adapter > Configure Connection Type, enter values for the Package, Folder Name, and Connection Name (see table for field definitions).



Configure Connection Type form

Field	Definition
Package	Determines the storage location for connection information. It is not recommended to put the connection in the PSFT_E1_Adapter package. The adapter installer upgrades the default connections but is not guaranteed to upgrade any custom connections stored in the PSFT_E1_Adapter package.
Folder Name	With the Package defined above, defines the name of the folder inside the package where the connection is stored. Note that the name of the folder might not contain a space character.
Connection Name	Defines the actual name of the connection. Ensure the name is sufficiently descriptive to allow developers to reference the connection. For example: <code>EnterpriseOne_PROD</code> Note that the name of the connection might not contain a space character.


Note.

To attach the connection to the Oracle JD Edwards EnterpriseOne system, you must configure additional values that are based on the connection type. Refer to the appropriate section in this chapter:

- “Configuring a Oracle EnterpriseOne Connection”
- “Configuring a Oracle EnterpriseOne Guaranteed Event Connection”
- “Configuring a Oracle EnterpriseOne Reliable Event Connection”

► **To update a default connection**

1. On Adapters, EnterpriseOne Adapter, Connections, click an Edit button to update one of these default connections (see table for descriptions).



Adapters > EnterpriseOne Adapter > Connections form

Connection Name	Package Name	Description
Connection: E1_Reliable Events	PSFT_E1_Adapter	Connects to an Oracle JD Edwards EnterpriseOne server to receive outbound events only.
Connection:EnterpriseOne	PSFT_E1_Adapter	Connects to Oracle JD Edwards EnterpriseOne server.
Connection: E1_Guaranteed Events	PSFT_E1_Adapter	Connects to an Oracle JD Edwards EnterpriseOne Tools 8.97 Transaction server to receive outbound events only.

2. The system automatically sets the connection information in the default connections.



Adapters > EnterpriseOne Adapter > Edit Connection form

The remainder of the configuration enables the connection to attach to the Oracle JD Edwards EnterpriseOne system.

Note.

To attach the connection to the Oracle JD Edwards EnterpriseOne system, you must configure additional values that are based on the connection type. Refer to these topics:

- “Configuring a Oracle EnterpriseOne Connection”
 - “Configuring a Oracle EnterpriseOne Guaranteed Event Connection”
 - “Configuring a Oracle EnterpriseOne Reliable Event Connection”
-

Configuring an Oracle EnterpriseOne Connection

An Oracle EnterpriseOne Connection enables a user to execute services on an Oracle JD Edwards EnterpriseOne server. The system displays all configuration settings on the Edit Connection form along with the recommended or default settings.

Important!

The Edit Connection form has several entries for passwords. On Integration Server, if one password is changed, all other passwords are set to "*****." Whenever one password is changed, all passwords must be re-entered.

Note.

In order to use WSG, the version of WSG must match the version of Oracle JD Edwards EnterpriseOne Tools. That is, you must have EnterpriseOne Release 8.97 to use WSG 8.97.

Also note that the 8.97 version of Connector jar files are shipped with the 8.97 EnterpriseOne Adapter.

► To configure a Oracle EnterpriseOne Connection

Note.

The 8.97 version of Connector jar files are shipped with the EnterpriseOne Adapter.

1. To determine which settings to use, refer to these tables:
 - Oracle JD Edwards EnterpriseOne Properties
 - Logging Properties
 - JDBj Bootstrap Properties
 - JDBj Spec Properties
 - JDBC Drivers
 - XAPI Event Introspection Settings
 - JDEInterop INI File Settings
 - Connection Management Properties

Each table contains a major section of the jdeinterop.ini and lists the configuration properties, typical settings, and a brief description of each property.

2. After you enter the configuration values, click **Save Changes** at the bottom of the form.

This table describes the typical settings for Oracle JD Edwards EnterpriseOne properties:

Configuring the EnterpriseOne Adapter: Step 1

Oracle JD Edwards EnterpriseOne Properties		
Parameter	Typical Setting	Description
Unique name for ERP connection	Site-dependent variable	Each connection <i>must</i> be given a unique name to distinguish it from the other connections. This name is used to create a directory name for the required "ini" files to connect to Oracle JD Edwards EnterpriseOne and is used to distinguish this connection in log output.
ERP Username	Site-dependent variable	Username to sign in to Oracle JD Edwards EnterpriseOne.
ERP Password	Site-dependent variable	Password for the specified Oracle JD Edwards EnterpriseOne username.
ERP Role	*ALL	Role for the Oracle JD Edwards EnterpriseOne username.
ERP Environment Name	Site-dependent variable	Oracle JD Edwards EnterpriseOne environment that the adapter connects to and executes business functions on.
ERP Enterprise Server Host Name	Site-dependent variable	Host name or IP address for the enterprise server to which the adapter connects. Always verify that the adapter can access this host by running a ping from a command prompt (such as "ping <hostname>").
ERP Enterprise Server Port	6025	The TCP/IP port for the Oracle JD Edwards EnterpriseOne server. The default port is 6025.
ERP Security Server Host Name	Site-dependent variable	Host name or IP address of the Oracle JD Edwards EnterpriseOne security server, which authenticates the given username. This might or might not be the same value as supplied for the Oracle JD Edwards EnterpriseOne enterprise server host name.
ERP Security Server Port	Site-dependent variable	The TCP/IP port for the Oracle JD Edwards EnterpriseOne Security server.
User Session Timeout	0	Maximum idle time, in milliseconds, before the user session is timed out. If a user session is timed out, the adapter needs to be restarted before a BSFN can be called again. A value of 0 is infinite timeout.
Maximum time in milliseconds to keep specs cached	30000000	This is the maximum time that the Dynamic Connector keeps specs cached. After this time, the internal cache dumps the business function specifications and retrieves them again from Oracle JD Edwards EnterpriseOne. The retrieval of business function specifications is very expensive. It is recommended to keep this value high enough so that the specs are not retrieved too often, but not too high to prevent updated specifications from being retrieved in a timely

Configuring the EnterpriseOne Adapter: Step 1

Oracle JD Edwards EnterpriseOne Properties		
Parameter	Typical Setting	Description
		manner.
Timeout value, in milliseconds, for a request to the enterprise server	90000	Timeout value, in milliseconds, for a request to the enterprise server.
Number of milliseconds before a manual transaction timeouts	600000	Timeout value, in milliseconds, for a manual transaction. The adapter is set to use manual transactions, which are specified in a Flow using the pub.art.transaction:startTransaction and either pub.art.transaction:commitTransaction or pub.art.transaction:rollbackTransaction. This value must be large enough to ensure that any Flow executing on Integration Server has enough time to complete given a realistic load on the enterprise server.
Size of JDENET socket connection pool	30	Maximum number of connections to Oracle JD Edwards EnterpriseOne. This value must be larger than the Maximum Pool size specified for the connection. The recommended value for this setting is 30.
Enable OCM for BSFN execution location	True	When set to True, business functions execute according to the OCM settings.

This table describes the logging properties:

Logging Properties		
Parameter	Typical Setting	Description
Location to place log files.	./logs/EnterpriseOneAdapter	<p>Directory where log files are created. A path relative to the Integration Server directory (such as ./logs/EnterpriseOneAdapter) needs to be preceded with “./”</p> <p>If the specified directory does not exist, it is created when the connection is enabled.</p> <p>If multiple connections are configured for one Integration Server, you must ensure that each connection has a unique directory specified.</p>
EnterpriseOne Log File Name	jderoot.log	Name of EnterpriseOne log file. It is not recommended to change this setting.
EnterpriseOne Log Level	WARNING	<p>Level of logging for the EnterpriseOne log file.</p> <p>Options: SEVERE, WARN, APP, DEBUG</p> <ul style="list-style-type: none"> SEVERE: to log only error messages. WARNING: to log warning and error messages. APP: to log application specific messages and warning/error messages.

Configuring the EnterpriseOne Adapter: Step 1

Logging Properties		
Parameter	Typical Setting	Description
		<ul style="list-style-type: none"> DEBUG: to log debug messages as well as the above types of messages.
EnterpriseOne Log Format	TOOLS	<p>The Logging format. For WSG, TOOLS format is recommended.</p> <p>Options: APPS, TOOLS, TOOLS_THREAD</p>
EnterpriseOne Log Components	ALL	<p>Specify which components will log messages to the EnterpriseOne log. Separate the components with ' ' character.</p> <p>Components: LIB, NET, JDBC, RUNTIME, JAS, JASBASE, XML, INTEROP, JDBJ, METADATA, PSFT, BASE</p> <p>Default selection (ALL) will make all components write log messages to this file.</p>
Connector Log File Name	connector.log	Name of Connector log file. It is not recommended to change this setting.
Connector Log Level	DEBUG	<p>Level of logging for the Connector log file.</p> <p>Options: SEVERE, WARN, APP, DEBUG</p> <ul style="list-style-type: none"> SEVERE: to log only error messages. WARNING: to log warning and error messages. APP: to log application specific messages and warning/error messages. DEBUG: to log debug messages as well as the above types of messages.
Connector Log Format	TOOLS	<p>The Logging format. For WSG, TOOLS format is recommended.</p> <p>Options: APPS, TOOLS, TOOLS_THREAD</p>
Connector Log Components	INTEROP JDBJ JDB C BASE	<p>Specify which components will log messages to this log. Separate the components with ' ' character.</p> <p>Components: LIB, NET, JDBC, RUNTIME, JAS, JASBASE, XML, INTEROP, JDBJ, METADATA, PSFT, BASE</p>
Runtime Log File Name	rt.log	Name of Runtime log file. It is not recommended to change this setting.
Runtime Log Level	DEBUG	<p>Level of logging for the Runtime log file.</p> <p>Options: SEVERE, WARN, APP, DEBUG</p> <ul style="list-style-type: none"> SEVERE: to log only error messages. WARNING: to log warning and error messages. APP: to log application specific messages. Warning and Error messages will also be

Logging Properties		
Parameter	Typical Setting	Description
		logged. <ul style="list-style-type: none"> DEBUG: to get most descriptive log messages.
Runtime Log Format	TOOLS	The Logging format. For WSG, TOOLS format is recommended. Options: APPS, TOOLS, TOOLS_THREAD.
Runtime Log Components	JAS RUNTIME	Specify which components will log messages to this log. Separate the components with ' ' character. Components: LIB, NET, JDBC, RUNTIME, JAS, JASBASE, XML, INTEROP, JDBJ, METADATA, PSFT, BASE

This table describes the JDBj Bootstrap properties:

JDBj Bootstrap Properties		
<p>This section defines the data source where OCM and other system tables reside. The connection uses this at bootstrap time and later to look up OCM entries on demand. If it is not valid, then no Oracle JD Edwards EnterpriseOne database access is possible.</p> <p>Note. The easiest way to configure this section is to locate the jdbj.ini file on the JAS server, and copy the relevant settings. If you cannot find this file, you can match the corresponding information specified in the [DB SYSTEM SETTINGS] section in an Oracle JD Edwards EnterpriseOne client's JDE.INI file.</p>		
Parameter	Typical Setting	Description
BootStrap Data Source Username	Site-dependent variable	Username for logging into the Oracle JD Edwards EnterpriseOne Security Server.
BootStrap Data Source Password	Site-dependent variable	Password for the specified username.
JDBj BootStrap Data Source Name	Site-dependent variable	The name of the data source being connected to. This is not critical for bootstrap connections, but shows up in error messages and in the log file.
BootStrap Data Source Database type	I = AS/400 O = Oracle S = SQL Server W = UDB	Type of database being connected to.
BootStrap Data Source Database name	Site-dependent variable	The name of the database. Only required for Oracle and UDB database types.
BootStrap Data Source Server Name	Site-dependent variable	Host name or IP Address of the server where the database is running. Only required for iSeries and SQL Server database types.

JDBj Bootstrap Properties		
BootStrap Data Source Database Server Port	Site-dependent variable	TCP/IP port the database server is listening on. Only required for SQL Server database types.
Boot Strap Data Source Physical Database	Site-dependent variable	The physical database (used as the library qualifier for the iSeries). Only required for iSeries and SQL Server database types.
Boot Strap Data Source Database Owner	Site-dependent variable	The database owner. Only required for Oracle, SQL Server and UDB database types.

This table describes the JDBj Spec properties:

JDBj Spec Properties		
<p>This section defines the data source where the serialized spec tables reside. JDBj uses these parameters at bootstrap time and after to look up serialized spec objects on demand. If this section is not specified, JDBj uses OCM to find the serialized spec table. If it is not valid, or if OCM is not enabled, then no Oracle JD Edwards EnterpriseOne database access is possible.</p> <p>Note. The easiest way to configure this section is to locate the jdbj.ini file on the JAS server and copy the relevant settings.</p>		
Parameter	Typical Setting	Description
Spec Data Source Username	Site-dependent variable	Username for logging in to the Oracle JD Edwards EnterpriseOne Security Server.
Spec Data Source Password	Site-dependent variable	Password for the specified username.
JDBj Spec Data Source Name	Site-dependent variable	The name of the data source being connected to. This is not critical for bootstrap connections, but shows up in error messages and in the log file.
Spec Data Source Database type	I = AS/400 O = Oracle S = SQL Server W = UDB	The type of database being connected to.
Spec Data Source Database Name	Site-dependent variable	The name of the database. Only required for Oracle and UDB database types.
Spec Data Source Database Server Port	Site-dependent variable	The host name or IP address of the server where the database is running. Only required for iSeries and SQL Server database types.
Spec Data Source Physical Database	Site-dependent variable	The physical database (used as the library qualifier for the iSeries). Only required for iSeries and SQL Server database

JDBj Spec Properties		
		types.
Spec Data Source Database Owner	Site-dependent variable	The database owner. Only required for Oracle, SQL Server and UDB database types.

JDBC Tracing Properties		
Parameter	Typical Setting	Description
Enable JDBC Tracing	False	Specifies whether to log the database logging information. This is used for a DB2/400 database only.

This table describes the JDBC Drivers:

JDBC Drivers		
This section defines the JDBC drivers to be used for different database systems. See "Working with JDBC Drivers" in this guide for instructions on how to install the JDBC drivers. For any database type not being used, make sure to set the value as blank.		
Parameter	Typical Setting	Description
Full path to Oracle's 'tnsnames' file	Site-dependent variable	Specifies the full path, including the file name, of Oracle's tnsnames.ora file. This entry can be left blank if Oracle is not being used as a database.
JDBj JDBC Driver Class for Oracle	oracle.jdbc.driver.OracleDriver	The driver used for Oracle databases. Can be set to blank if Oracle is not being used.
JDBj JDBC Driver Class for Oracle 10g	Oracle.jdbc.OracleDriver	The driver used for Oracle 10g databases. Can be set to blank if Oracle 10g is not being used.
JDBj JDBC Driver Class for AS400	com.ibm.as400.access.AS400JDBCDriver	The driver used for DB2 UDB for the iSeries. Can be set to blank if UDB for iSeries is not being used.
JDBj JDBC Driver Class for SQL Server	com.microsoft.jdbc.sqlserver.SQLServerDriver	The driver used for Microsoft SQL Server databases. Can be set to blank if SQL Server is not being used.
JDBj JDBC Driver Class for SQL Server 2005	com.microsoft.sqlserver.jdbc.SQLServerDriver	The driver used for Microsoft SQL Server 2005 databases. Can be set to blank if SQL Server is not being used.
JDBj JDBC Driver Class for UDB	COM.ibm.db2.jdbc.app.DB2Driver	The driver used for DB2 UDB databases (non-iSeries). Can be set to blank if UDB is not being used.

Note.

Please ensure that you are selecting appropriate driver class for the corresponding database type as mentioned above from the drop down menu.

For example, select “oracle.jdbc.OracleDriver“ for an Oracle10g database, and “com.microsoft.sqlserver.jdbc.SQLServerDriver” for an SQL2005 database.

This table describes the XAPI Event Introspection settings:

XAPI Event Introspection Settings		
Parameter	Typical Setting	Description
Use Guaranteed Event System	true	Specifies whether to use the Guranteed Event System to retrieve the Specs for the XAPI Response Events.
Transaction Host Name	<blank>	Host Name where the Transaction Server is installed. Required only if using Guaranteed Event System.
Transaction Host Port	<blank>	Transaction Server HTTP port. Required only if using Guaranteed Event System.

This table describes the JDEInterop INI file settings:

JDEInterop INI File Settings		
Parameter	Typical Setting	Description
Dynamic connector jar file directory	<blank>	This optional setting enables the user to override the location where the connection picks up the dynamic connector jar files. This can enable a single adapter instance to have different connections pointing to different Oracle JD Edwards EnterpriseOne releases. It is recommended that only advanced users take advantage of this field. Most users should continue to use the default location of the dynamic connector files.
jdeinterop.ini file path	<blank>	This optional setting enables a user to configure a connection using an existing jdeinterop.ini file instead of entering all the values on the form. The existing jdeinterop.ini file must contain all the values not entered on the form. If this field is left blank, the system uses the fields on the form to configure the connection. These properties must still be entered even if a jdeinterop.ini file is specified: <ul style="list-style-type: none"> • Unique connection name. • Oracle JD Edwards EnterpriseOne username,

JDEInterop INI File Settings		
Parameter	Typical Setting	Description
		password, role, and environment. <ul style="list-style-type: none"> All logging properties. It is recommended that only advanced users take advantage of this field. All other users should configure the connection using the GUI.

This table describes the Connection Management Properties:

Connection Management Properties		
Parameter	Typical Setting	Description
Enable Connection Pooling	True	Enables the connection to use pooling. It is highly recommended to leave this value as True.
Minimum Pool	0	The minimum number of connections in the pool. This is also the number of connections created when the pool is first created. At a minimum, this number should be 1 greater than the number of listeners created for this connection.
Maximum Pool Size	10	The maximum number of connections that can exist in the pool.
Pool Increment Size	5	The number of connections created if the numbers of connections in the pool are not great enough to handle incoming requests.
Block Timeout (msec)	20000	The amount of time, in milliseconds, that Integration Server waits while creating a connection before it times out and returns an error.
Expire Timeout (msec)	20000	The amount of time, in milliseconds, before inactive connections can remain in the pool before they are removed.
Startup Retry Count	1	If connection startup fails, the number of times the system will try to start the connection.
Startup Backoff Timeout (sec)	10	The time interval between startup attempts.

Configuring an Oracle EnterpriseOne Guaranteed Event Connection

An Outbound Event connection enables you to receive outbound events from the Guaranteed Event System. Examples of outbound events are RealTime, XAPI, Z-Table, and so on.

► To configure a Tools Release 8.97 event connection

- To determine which settings to use, refer to these tables in this section:

Configuring the EnterpriseOne Adapter: Step 1

- Oracle JD Edwards EnterpriseOne Properties
- Logging Properties
- Transaction Server Settings
- JDEInterop INI File Settings
- Connection Management Properties

Each table contains a major section of the jdeinterop.ini and lists the configuration properties, typical settings, and a brief description of each property.

Note.

- The 8.97 version of Connector jar files is shipped with the adapter.
- You must enter your username.

With the new event system subscriptions, events are username specific. You can no longer share usernames with others.

2. After you enter the configuration values, click **Save Changes** at the bottom of the form.

Note.

You might receive an error on startup that indicates that you do not have a subscription for a specific event. The adapter can no longer dynamically generate subscriptions with the event system. You must enter all subscriptions through an Oracle JD Edwards EnterpriseOne application.

3. When using the Oracle JD Edwards EnterpriseOne application to create Subscriptions, you need to set these properties:
 - Event Name
 - Username
 - Environment

Remember, subscriptions are user-name specific. You must enter a subscription for every event for which you have a Notification. Otherwise, the system will not start the Listener.

This table describes the Oracle JD Edwards EnterpriseOne properties:

Oracle JD Edwards EnterpriseOne Properties		
Parameter	Typical Setting	Description
Unique name for ERP connection	E1_GuaranteedEvents	Each connection must be given a unique name to distinguish it from the other connections. This name is used to create a directory name for the required "ini" files to connect to Oracle JD Edwards EnterpriseOne and is used to distinguish this connection in log output.
ERP Username	Site-dependent variable	The username to sign in to Oracle JD Edwards EnterpriseOne.

Configuring the EnterpriseOne Adapter: Step 1

Oracle JD Edwards EnterpriseOne Properties		
Parameter	Typical Setting	Description
ERP Password	Site-dependent variable	The password for the specified Oracle JD Edwards EnterpriseOne username.
ERP Role	*ALL	The role for the Oracle JD Edwards EnterpriseOne username.
ERP Environment Name	Site-dependent variable	The Oracle JD Edwards EnterpriseOne environment to which the adapter connects and executes business functions.
ERP Enterprise Server Host Name	Site-dependent variable	Host name or IP address of the enterprise server that the adapter connects to. Always verify that the adapter can access this host by running a ping from a command prompt (such as "ping <hostname>").
ERP Enterprise Server Port	Site-dependent variable	The TCP/IP port for the Oracle JD Edwards EnterpriseOne server. The default port is 6009.
ERP Security Server Host Name	Site-dependent variable	The host name or IP address of the Oracle JD Edwards EnterpriseOne security server which authenticates the given username. This might or might not be the same value as supplied for the Oracle JD Edwards EnterpriseOne enterprise server host name.
ERP Security Server Port	Site-dependent variable	The TCP/IP port for the Oracle JD Edwards EnterpriseOne security server.
User Session Timeout	0	The maximum idle time, in milliseconds, before the user session is timed out. If a user session is timed out, you must restart the adapter before a BSFN can be called again. A value of 0 is infinite timeout.
Timeout value, in milliseconds, for a request to the enterprise server	90000	Timeout value, in milliseconds, for a request to the enterprise server.
Number of milliseconds before a manual transaction timeouts	600000	Timeout value, in milliseconds, for a manual transaction. The adapter is set to use manual transactions, which are specified in a Flow using the pub.art.transaction:startTransaction and either pub.art.transaction:commitTransaction or pub.art.transaction:rollbackTransaction. This value must be large enough to ensure that any Flow that executes on Integration Server has enough time to complete given a realistic load on the enterprise server.
Size of JDENET socket connection pool	30	The maximum number of connections to Oracle JD Edwards EnterpriseOne. This value must be larger than the Maximum Pool size specified for the connection. The recommended value for this setting

Configuring the EnterpriseOne Adapter: Step 1

Oracle JD Edwards EnterpriseOne Properties		
Parameter	Typical Setting	Description
		is 30.

This table describes logging properties:

Logging Properties		
Parameter	Typical Setting	Description
Location to place log files.	<code>./logs/E1_GuaranteedEvents</code>	<p>Directory where log files are created. A path relative to the Integration Server directory (such as <code>./logs/E1_GuaranteedEvents</code>) needs to be preceded with <code>./</code></p> <p>If the specified directory does not exist, it is created when the connection is enabled.</p> <p>If multiple connections are configured for one Integration Server, you must ensure that each connection has a unique directory specified.</p>
EnterpriseOne Log File Name	<code>jderoot.log</code>	Name of EnterpriseOne log file. It is not recommended to change this setting.
EnterpriseOne Log Level	WARNING	<p>Level of logging for the EnterpriseOne log file.</p> <p>Options: SEVERE, WARN, APP, DEBUG</p> <ul style="list-style-type: none"> SEVERE: to log only error messages. WARNING: to log warning and error messages. APP: to log application specific messages and warning/error messages. DEBUG: to log debug messages as well as the above types of messages.
EnterpriseOne Log Format	TOOLS	<p>The Logging format. For WSG, TOOLS format is recommended.</p> <p>Options: APPS, TOOLS, TOOLS_THREAD</p>
EnterpriseOne Log Components	ALL	<p>Specify which components will log messages to the EnterpriseOne log. Separate the components with <code>' '</code> character.</p> <p>Components: LIB, NET, JDBC, RUNTIME, JAS, JASBASE, XML, INTEROP, JDBJ, METADATA, PSFT, BASE</p> <p>Default selection (ALL) will make all components write log messages to this file.</p>
Connector Log File Name	<code>connector.log</code>	Name of Connector log file. It is not recommended to change this setting.
Connector Log Level	DEBUG	Level of logging for the Connector log file.

Logging Properties		
Parameter	Typical Setting	Description
		Options: SEVERE, WARN, APP, DEBUG <ul style="list-style-type: none"> SEVERE: to log only error messages. WARNING: to log warning and error messages. APP: to log application specific messages and warning/error messages. DEBUG: to log debug messages as well as the above types of messages.
Connector Log Format	TOOLS	The Logging format. For WSG, TOOLS format is recommended. Options: APPS, TOOLS, TOOLS_THREAD
Connector Log Components	INTEROP JDBJ JDBC BASE	Specify which components will log messages to this log. Separate the components with ' ' character. Components: LIB, NET, JDBC, RUNTIME, JAS, JASBASE, XML, INTEROP, JDBJ, METADATA, PSFT, BASE
Runtime Log File Name	rt.log	Name of Runtime log file. It is not recommended to change this setting.
Runtime Log Level	DEBUG	Level of logging for the Runtime log file. Options: SEVERE, WARN, APP, DEBUG <ul style="list-style-type: none"> SEVERE: to log only error messages. WARNING: to log warning and error messages. APP: to log application specific messages. Warning and Error messages will also be logged. DEBUG: to get most descriptive log messages.
Runtime Log Format	TOOLS	The Logging format. For WSG, TOOLS format is recommended. Options: APPS, TOOLS, TOOLS_THREAD.
Runtime Log Components	JAS RUNTIME	Specify which components will log messages to this log. Separate the components with ' ' character. Components: LIB, NET, JDBC, RUNTIME, JAS, JASBASE, XML, INTEROP, JDBJ, METADATA, PSFT, BASE

This table lists Transaction Server settings:

Configuring the EnterpriseOne Adapter: Step 1

Transaction Server Settings		
Parameter	Typical Setting	Description
Transaction server name or IP	Site-dependent variable	The name of the transaction server host to establish a connection to.
Transaction server port	Site-dependent variable	The HTTP port number for the transaction server connection.

This table describes JDEInterop INI file settings:

JDEInterop INI File Setting		
Parameter	Typical Setting	Description
Directory of dynamic connector jar files	<blank>	<p>This optional setting enables the user to override the location where the connection picks up the dynamic connector jar files. This can enable a single adapter instance to have different connections pointing to different Oracle JD Edwards EnterpriseOne releases.</p> <p>It is recommended that only advanced users take advantage of this field. Most users should continue to use the default location of the dynamic connector files.</p>
jdeinterop.ini file path	<blank>	<p>This optional setting enables a user to configure a connection using an existing jdeinterop.ini file instead of entering all the values on the form. The existing jdeinterop.ini file must contain all the required values. If this field is left blank, the system uses the fields on the form to configure the connection.</p> <p>You must still enter these properties even if a jdeinterop.ini file is specified:</p> <ul style="list-style-type: none"> • Integration Server username and password. • Unique connection name. • Oracle JD Edwards EnterpriseOne username, password, and environment. <p>It is recommended that only advanced users take advantage of this field. All others should configure the connection using the GUI.</p>

This table describes Connection Management properties:

Connection Management Properties		
Parameter	Typical Setting	Description
Enable Connection Pooling	True	Enables the connection to use pooling. It is highly recommended to leave this value as True.
Minimum Pool	0	The minimum number of connections in the pool. This is also the number of connections created when the pool is first created. At a minimum, this number should be 1 greater than the number of Listeners created for this connection.
Maximum Pool Size	10	The maximum number of connections that can exist in the pool.
Pool Increment Size	3	The number of connections created if the number of connections in the pool is not great enough to handle incoming requests.
Block Timeout (msec)	20000	The amount of time, in milliseconds, that Integration Server waits while creating a connection before it times out and returns an error.
Expire Timeout (msec)	20000	The amount of time, in milliseconds, before inactive connections can remain in the pool before they are removed.
Startup Retry Count	1	If connection startup fails, the number of times the system will try to restart the connection.
Startup Backoff Timeout (sec)	10	The time interval between startup attempts.

Configuring an Oracle EnterpriseOne Reliable Event Connection

An Oracle JD Edwards EnterpriseOne event connection enables a user to receive outbound events from an Oracle JD Edwards EnterpriseOne (8.9 and later version) server. Examples of outbound events are RealTime, XAPI, Z-Table, and so on. The system displays all of the configuration settings on the Edit Connection form along with recommended or default settings.

► To configure a Oracle JD Edwards EnterpriseOne Event connection

1. To determine which settings to use, refer to these tables in this section:
 - Integration Server Properties
 - Oracle JD Edwards EnterpriseOne Properties
 - Logging Properties
 - Outbound Event Properties
 - JDBj Bootstrap Properties

Configuring the EnterpriseOne Adapter: Step 1

- JDBj Spec Properties
- JDBC Drivers
- JDEInterop INI File Settings
- Connection Management Properties

Each table contains a major section of the jdeinterop.ini and lists the configuration properties, typical settings, and a brief description of each property.

Important!

Multiple password entries exist on this page. A known issue with Integration Server is that when one password is changed, all other passwords are set to "*****". Whenever one password is changed, all passwords must be re-entered.

Note.

For the Event connection, the JDBj property sections are required.

2. After you enter the configuration values, click **Save Changes** at the bottom of the form.

This table describes Integration Server properties:

Integration Server Properties		
Parameter	Typical Setting	Description
Integration Server username	Site-dependent variable	<p>When processing RealTime and Z-Table events from Oracle JD Edwards EnterpriseOne, the adapter leverages internal services of Integration Server for higher scalability and redundancy. To access these internal services, an Integration Server username must be given which has execute rights to these services:</p> <ul style="list-style-type: none"> • pub.storage:add • pub.storage:put • pub.storage:registerStore • pub.storage:unlock <p>The default value for this property is Developer. It is highly recommended that you change this value to a new user who has minimal rights to execute the above services.</p>
Password for Integration Server username	Site-dependent variable	The password for the specified Integration Server username.

This table describes the Oracle JD Edwards EnterpriseOne properties:

Oracle JD Edwards EnterpriseOne Properties		
Parameter	Typical Setting	Description

Configuring the EnterpriseOne Adapter: Step 1

Oracle JD Edwards EnterpriseOne Properties		
Parameter	Typical Setting	Description
Unique name for ERP connection	Site-dependent variable	Each connection must be given a unique name to distinguish it from the other connections. This name is used to create a directory name for the required ini files to connect to Oracle JD Edwards EnterpriseOne and is used to distinguish this connection in log output.
ERP Username	Site-dependent variable	The username to sign in to Oracle JD Edwards EnterpriseOne.
ERP Password	Site-dependent variable	The password for the specified Oracle JD Edwards EnterpriseOne username.
ERP Role	*ALL	The role for the Oracle JD Edwards EnterpriseOne username.
ERP Environment Name	Site-dependent variable	The Oracle JD Edwards EnterpriseOne environment to which the adapter connects and executes business functions.
ERP Enterprise Server Host Name	Site-dependent variable	The host name or IP address for the enterprise server to which the adapter connects. Always verify that the adapter can access this host by running a ping from a command prompt (such as "ping <hostname>").
ERP Enterprise Server Port	6025	The TCP/IP port for the Oracle JD Edwards EnterpriseOne server. The default port is 6025.
ERP Security Server Host Name	Site-dependent variable	The host name or IP address of the Oracle JD Edwards EnterpriseOne security server which authenticates the given username. This might or might not be the same value as supplied for the Oracle JD Edwards EnterpriseOne enterprise server host name.
ERP Security Server Port	Site-dependent variable	The TCP/IP port for the Oracle JD Edwards EnterpriseOne Security server.
User Session Timeout	0	The maximum idle time, in milliseconds, before the user session is timed out. If a user session is timed out, the adapter needs to be restarted before a BSFN can be called again. A value of 0 is infinite timeout.
Timeout value, in milliseconds, for a request to the enterprise server	90000	The timeout value, in milliseconds, for a request to the enterprise server.

Configuring the EnterpriseOne Adapter: Step 1

Oracle JD Edwards EnterpriseOne Properties		
Parameter	Typical Setting	Description
Number of milliseconds before a manual transaction timeouts	600000	The timeout value, in milliseconds, for a manual transaction. The adapter is set to use manual transactions, which are specified in a Flow using the <code>pub.art.transaction:startTransaction</code> and either <code>pub.art.transaction:commitTransaction</code> or <code>pub.art.transaction:rollbackTransaction</code> . This value must be large enough to ensure that any Flow executing on Integration Server has enough time to complete given a realistic load on the enterprise server.
Size of JDENET socket connection pool	30	The maximum number of connections to Oracle JD Edwards EnterpriseOne. This value must be larger than the Maximum Pool size specified for the connection. The recommended value for this setting is 30.

This table describes logging properties:

Logging Properties		
Parameter	Typical Setting	Description
Location to place log files.	<code>./logs/E1_ReliableEvents</code>	<p>Directory where log files are created. A path relative to the Integration Server directory (such as <code>./logs/E1_ReliableEvents</code>) needs to be preceded with <code>./</code></p> <p>If the specified directory does not exist, it is created when the connection is enabled.</p> <p>If multiple connections are configured for one Integration Server, you must ensure that each connection has a unique directory specified.</p>
EnterpriseOne Log File Name	<code>jderoot.log</code>	Name of EnterpriseOne log file. It is not recommended to change this setting.
EnterpriseOne Log Level	WARNING	<p>Level of logging for the EnterpriseOne log file.</p> <p>Options: SEVERE, WARN, APP, DEBUG</p> <ul style="list-style-type: none"> SEVERE: to log only error messages. WARNING: to log warning and error messages. APP: to log application specific messages and warning/error messages. DEBUG: to log debug messages as well as the above types of messages.
EnterpriseOne Log Format	TOOLS	<p>The Logging format. For WSG, TOOLS format is recommended.</p> <p>Options: APPS, TOOLS, TOOLS_THREAD</p>
EnterpriseOne Log	ALL	Specify which components will log messages to the

Logging Properties		
Parameter	Typical Setting	Description
Components		EnterpriseOne log. Separate the components with ' ' character. Components: LIB, NET, JDBC, RUNTIME, JAS, JASBASE, XML, INTEROP, JDBJ, METADATA, PSFT, BASE Default selection (ALL) will make all components write log messages to this file.
Connector Log File Name	connector.log	Name of Connector log file. It is not recommended to change this setting.
Connector Log Level	DEBUG	Level of logging for the Connector log file. Options: SEVERE, WARN, APP, DEBUG <ul style="list-style-type: none"> • SEVERE: to log only error messages. • WARNING: to log warning and error messages. • APP: to log application specific messages and warning/error messages. • DEBUG: to log debug messages as well as the above types of messages.
Connector Log Format	TOOLS	The Logging format. For WSG, TOOLS format is recommended. Options: APPS, TOOLS, TOOLS_THREAD
Connector Log Components	INTEROP JDBJ JDBC BASE	Specify which components will log messages to this log. Separate the components with ' ' character. Components: LIB, NET, JDBC, RUNTIME, JAS, JASBASE, XML, INTEROP, JDBJ, METADATA, PSFT, BASE
Runtime Log File Name	rt.log	Name of Runtime log file. It is not recommended to change this setting.
Runtime Log Level	DEBUG	Level of logging for the Runtime log file. Options: SEVERE, WARN, APP, DEBUG <ul style="list-style-type: none"> • SEVERE: to log only error messages. • WARNING: to log warning and error messages. • APP: to log application specific messages. Warning and Error messages will also be logged. • DEBUG: to get most descriptive log messages.
Runtime Log Format	TOOLS	The Logging format. For WSG, TOOLS format is recommended. Options: APPS, TOOLS, TOOLS_THREAD.

Logging Properties		
Parameter	Typical Setting	Description
Runtime Log Components	JAS RUNTIME	Specify which components will log messages to this log. Separate the components with ' ' character. Components: LIB, NET, JDBC, RUNTIME, JAS, JASBASE, XML, INTEROP, JDBJ, METADATA, PSFT, BASE

This table describes Outbound Event Properties:

Outbound Event Properties		
Parameter	Typical Setting	Description
Port which will receive outbound events from ERP	6010	The TCP/IP Port where the connection listens for events sent by Oracle JD Edwards EnterpriseOne. This port should not be used by any other resource on the Integration Server machine. If multiple connections are configured, each connection must have a unique port.
Maximum number of connections	10	The maximum number of connections enabled by the connection. The maximum value for this setting is 64.
Maximum number of events	10	The maximum number of events the connection can hold before they are processed. The maximum value for this setting is 100.
Milliseconds before event Listener unsubscribes from transient events	0	The maximum time, in milliseconds, before the connection unsubscribes from transient events. A value of 0 is infinite.

This table describes JDBj Bootstrap properties:

JDBj Bootstrap Properties		
<p>This section defines the data source where OCM and some other system tables reside. The connection uses this at bootstrap time and later to look up OCM entries on demand. If it is not valid, then no Oracle JD Edwards EnterpriseOne database access is possible.</p> <p>Note. The easiest way to configure this section is to locate the jdbj.ini file on the JAS server and copy the relevant settings. If you cannot find this file, you can match the corresponding information specified in the [DB SYSTEM SETTINGS] section in an Oracle JD Edwards EnterpriseOne client's jde.ini file.</p>		
Parameter	Typical Setting	Description
BootStrap Data Source Username	Site-dependent variable	Username for logging into the Oracle JD Edwards EnterpriseOne Security Server.
BootStrap Data Source Password	Site-dependent variable	Password for the specified username.
JDBj BootStrap Data Source Name	System – B9	The name of the data source being connected to. This is not critical for bootstrap connections, but shows up in error messages and in the log file.
BootStrap Data Source	I = AS/400	Type of database being connected to.

JDBj Bootstrap Properties		
Database type	O = Oracle S = SQL Server W = UDB	
BootStrap Data Source Database name	Site-dependent variable	The name of the database. Only required for Oracle and UDB database types.
BootStrap Data Source Server Name	Site-dependent variable	Host name or IP Address of the server where the database is running. Only required for iSeries and SQL Server database types.
BootStrap Data Source Database Server Port	Site-dependent variable	TCP/IP port the database server is listening on. Only required for SQL Server database types.
Boot Strap Data Source Physical Database	Site-dependent variable	The physical database (used as the library qualifier for the iSeries). Only required for iSeries and SQL Server database types.
Boot Strap Data Source Database Owner	Site-dependent variable	The database owner. Only required for Oracle, SQL Server and UDB database types.

This table describes JDBj Spec properties:

JDBj Spec Properties		
<p>This section defines the data source where the serialized spec tables reside. JDBj uses these parameters at bootstrap time and after to look up serialized spec objects on demand. If this section is not specified, JDBj uses OCM to find the serialized spec table. If it is not valid, or if OCM is not enabled, then no Oracle JD Edwards EnterpriseOne database access is possible.</p> <p>Note. The easiest way to configure this section is to locate the jdbj.ini file found on the JAS server and copy the relevant settings.</p>		
Parameter	Typical Setting	Description
Spec Data Source Username	Site-dependent variable	Username for logging in to the Oracle JD Edwards EnterpriseOne Security Server.
Spec Data Source Password	Site-dependent variable	Password for the specified username.
JDBj Spec Data Source Name	Site-dependent variable	The name of the data source being connected to. This is not critical for bootstrap connections, but shows up in error messages and in the log file.
Spec Data Source Database type	I = AS/400 O = Oracle S = SQL Server	The type of database being connected to.

JDBj Spec Properties		
	W = UDB	
Spec Data Source Database Name	Site-dependent variable	The name of the database. Only required for Oracle and UDB database types.
Spec Data Source Database Server Port	Site-dependent variable	The host name or IP address of the server where the database is running. Only required for iSeries and SQL Server database types.
Spec Data Source Physical Database	Site-dependent variable	The physical database (used as the library qualifier for the iSeries). Only required for iSeries and SQL Server database types.
Spec Data Source Database Owner	Site-dependent variable	The database owner. Only required for Oracle, SQL Server and UDB database types.

This table describes JDBC drivers:

JDBC Drivers		
This section defines the JDBC drivers to be used for different database systems. Refer to the <i>Working with JDBC Drivers</i> section in this guide for instructions on how to install the different JDBC drivers. For any database type not being used, make sure to set the value as blank.		
Parameter	Typical Setting	Description
Full path to Oracle's 'tnsnames' file	Site-dependent variable	Specifies the full path, including the file name, of Oracle's tnsnames.ora file. This entry can be left blank if Oracle is not being used as a database.
JDBj JDBC Driver Class for Oracle	oracle.jdbc.driver.OracleDriver	The driver used for Oracle databases. Can be set to blank if Oracle is not being used.
JDBj JDBC Driver Class for Oracle 10g	oracle.jdbc.OracleDriver	The driver used for Oracle 10g databases. Can be set to blank if Oracle 10g is not being used.
JDBj JDBC Driver Class for AS400	com.ibm.as400.access.AS400JDBCDriver	The driver used for DB2 UDB for the iSeries. Can be set to blank if UDB for iSeries is not being used.
JDBj JDBC Driver Class for SQL Server	com.microsoft.jdbc.sqlserver.SQLServerDriver	The driver used for Microsoft SQL Server databases. Can be set to blank if SQL Server is not being used.
JDBj JDBC Driver Class for SQL Server 2005	com.microsoft.sqlserver.jdbc.SQLServerDriver	The driver used for Microsoft SQL Server 2005 databases. Can be set to blank if SQL Server 2005 is not being used.
JDBj JDBC Driver Class for	COM.ibm.db2.jdbc.a	The driver used for DB2 UDB databases (non-

Configuring the EnterpriseOne Adapter: Step 1

JDBC Drivers		
UDB	pp.DB2Driver	iSeries). Can be set to blank if UDB is not being used.

This table describes JDEInterop INI file settings:

JDEInterop INI File Settings		
Parameter	Typical Setting	Description
Dynamic connector jar file directory	<blank>	This optional setting enables the user to override the location where the connection picks up the dynamic connector jar files. This can enable a single adapter instance to have different connections pointing to different Oracle JD Edwards EnterpriseOne releases. It is recommended that only advanced users take advantage of this field. Most users should continue to use the default location of the dynamic connector files.
jdeinterop.ini file path	<blank>	This optional setting enables a user to configure a connection using an existing jdeinterop.ini file instead of entering all the values on the form. The existing jdeinterop.ini file must contain all the values not entered on the form. If this field is left blank, the system uses the fields on the form to configure the connection. These properties must still be entered even if a jdeinterop.ini file is specified: <ul style="list-style-type: none"> • Unique connection name. • Oracle JD Edwards EnterpriseOne username, password, role, and environment. • All logging properties. It is recommended that only advanced users take advantage of this field. All other users should configure the connection using the GUI.

This table describes Connection Management properties:

Connection Management Properties		
Parameter	Typical Setting	Description
Enable Connection Pooling	True	Enables the connection to use pooling. It is highly recommended to leave this value as True.
Minimum Pool	0	The minimum number of connections in the pool. This is also the number of connections created when the pool is first created. At a minimum, this number should be 1 greater than the number of Listeners created for this connection.
Maximum Pool Size	10	The maximum number of connections that can exist

Connection Management Properties		
Parameter	Typical Setting	Description
		in the pool.
Pool Increment Size	3	The number of connections created if the number of connections in the pool is not great enough to handle incoming requests.
Block Timeout (msec)	20000	The amount of time, in milliseconds, that Integration Server waits while creating a connection before it times out and returns an error.
Expire Timeout (msec)	20000	The amount of time, in milliseconds, before inactive connections can remain in the pool before they are removed.
Startup Retry Count	1	If connection startup fails, the number of times the system will try to restart the connection.
Startup Backoff Timeout (sec)	10	The time interval between startup attempts.

Enabling the EnterpriseOne Adapter Connection: *Step 2*

After you configure and save a connection, you must enable the connection before the adapter can use it.

► To enable an EnterpriseOne Adapter connection

1. Open Integration Server Administrator by entering this URL in your internet browser:

`http://<Host_Name>:5555.`

Where `<Host_Name>` is the name, or IP address, of the Integration Server and 5555 is the default port for Integration Server.

2. Sign in with the default username and password, Administrator and manage.
3. In the left pane, click **Adapters**, and then select **EnterpriseOne Adapter**.

The screenshot shows a Microsoft Internet Explorer browser window displaying the Integration Server Administrator interface. The address bar shows `http://den-ur6864969:5555/`. The page title is "DEN-UR6864969.jdedwards.com :: Integration Server". The left navigation pane is expanded to "Adapters", and "EnterpriseOne Adapter..." is selected. The main content area displays the "Server > Statistics" form, which includes several tables and a chart.

Usage			
	Current	Peak	Limit
Total Sessions	1	3	-
Licensed Sessions	0	1	10000
Service Threads	1	4	-
System Threads	284	284	-
Uptime	20h:48m:11s		

Requests	
	Current
Completed Req's	2145
Average Time	0 ms
Service Errors	3
Started	Started
Req's per minute	6/min


Memory	
Total	246462 KB
Used	159402 KB 65%
Free	87060 KB 35%

Memory Usage (average per hour) chart showing usage over time from -24h to -1h. The y-axis represents memory usage in KB, ranging from 0 to 246462 KB.

Server > Statistics form

4. On the Adapters > EnterpriseOne Adapter > Connections form, locate the connection you want to enable.
5. In the Enabled column, click **No** to toggle the value to "Yes."

Enabling the EnterpriseOne Adapter Connection: Step 2



Connection Name	Package Name	Connection Type	Enabled	Edit	View	Copy	Delete
connection:EnterpriseOne	PSFT_E1_Adapter	Oracle EnterpriseOne Connection	No				
connection:E1_GuaranteedEvents	PSFT_E1_Adapter	Oracle EnterpriseOne Guaranteed Event Connection	No				
connection:E1_ReliableEvents	PSFT_E1_Adapter	Oracle EnterpriseOne Reliable Event Connection	No				

Adapters > EnterpriseOne Adapter > Connections


6. On the dialog box, click **OK** to enable the connection.



Enable connection dialog box

You must wait for the connection to be enabled. Do not refresh the form or click another link until the connection is enabled, or returns an error.

If an error message is returned, fix the error and attempt to re-enable the connection. If the connection is correctly enabled, the link in the Enabled column is checked, as shown in this example:



Connection Name	Package Name	Connection Type	Enabled	Edit	View	Copy	Delete
connection:EnterpriseOne	PSFT_E1_Adapter	Oracle EnterpriseOne Connection	<input checked="" type="checkbox"/> Yes				
connection:E1_GuaranteedEvents	PSFT_E1_Adapter	Oracle EnterpriseOne Guaranteed Event Connection	<input checked="" type="checkbox"/> Yes				
connection:E1_ReliableEvents	PSFT_E1_Adapter	Oracle EnterpriseOne Reliable Event Connection	No				

Adapters > EnterpriseOne Adapter > Connections

Creating a Listener: *Step 3*

To receive Real Time or Z-Table events from Oracle JD Edwards EnterpriseOne, you must create at least one Listener. If you intend to use a configured connection only to make *inbound* calls to Oracle JD Edwards EnterpriseOne (for example, business function calls), you can skip this entire step.


Important!

All Oracle JD Edwards EnterpriseOne integrations shipped by Oracle already have a default Listener. You *do not* need to create a new Listener if you intend to use only JD Edwards integrations.

Remember that a Listener can only be connected to an event connection. While you can configure a Listener against a non-event connection, doing so will prevent the Listener from starting.


► To create a Listener for an Event Connection

1. On Adapters > EnterpriseOne Adapter > Connections, verify that the connection is enabled. If the connection is enabled, the adapter is ready to receive events.



Adapters > EnterpriseOne Adapter > Connections form


2. On Adapters > EnterpriseOne Adapter > Connections, in the left pane in the EnterpriseOne Adapter section, click the Listeners link.



Adapters > EnterpriseOne Adapter > Connections form

Creating a Listener: Step 3

- On Adapters > EnterpriseOne Adapter > Listeners, click the Configure New Listener link at the top of the form.



Adapters > EnterpriseOne Adapter > Listeners form

If you have not previously configured any Listeners, the display indicates that no Listeners are found.

- On Adapters > EnterpriseOne Adapter > Listener Types, click the **ERP Event Listener** link.



Adapters > EnterpriseOne Adapter > Listener Types form

- On Adapters > EnterpriseOne Adapter > Configure Listener Type, complete the required fields as described in the accompanying table.



Adapters > EnterpriseOne Adapter > Configure Listener Type form

This table describes the fields on the Configure Listener Type form:

Configure Listener Type		
Parameter	Typical Setting	Description
Package	Site dependent variable	<p>This is the package where the Listener itself is stored. It is not recommended to store the Listener in the PSFT_E1_Adapter package, as the Listener will be removed whenever an adapter update is taken.</p> <p>It is recommended that you use the WSG Developer tool to create a new package to store the Listener in. This can be the same package created to store the Connection.</p>
Folder Name	Site dependent variable	<p>The folder where the Listener is stored. If the folder does not exist under the specified Package, it will be created.</p> <p>You must specify a name and the name should not include any path information. For example, Listener.</p> <p>Note that the name of the folder cannot contain a space character.</p>
Listener Name	Site dependent variable	<p>The name of the Listener. This should be descriptive enough to know the purpose of the Listener and to what resource the Connection is attached. For example, EnterpriseOne Event Listener.</p> <p>Note that the name of the Listener cannot contain a space character.</p>
Connection Name	Site dependent variable	The connection to attach the Listener to. This must be an Event Connection for the Listener to function.
Retry Limit	5	The number of attempts to try and start the Listener.
Retry Backoff Timeout	10	The amount of time, in seconds, to wait between retries attempts.
Environment(s) to subscribe to events on	Site dependent variable	<p>A Listener can subscribe to events on one or more Oracle JD Edwards EnterpriseOne environments. Multiple environments must exist in the same Oracle JD Edwards EnterpriseOne path code, and the username/password configured for the Connection must be valid for all environments.</p> <p>Separate multiple environments with a comma or space.</p> <p>Use this only for Reliable Events. For Guaranteed Events, this information is updated by E1 applications.</p>
Remove these subscriptions when the Listener shuts down	FALSE	By default, a Listener uses persistent subscriptions when subscribing to Oracle JD Edwards EnterpriseOne. If the connection is disabled, any events subscribed to are stored on the Oracle JD Edwards EnterpriseOne side until the Connection restarts and is ready to receive events.

Creating a Listener: Step 3

Configure Listener Type		
Parameter	Typical Setting	Description
		Setting this parameter to TRUE removes the persistent subscriptions on shutdown of the Listener.

- On Adapters > EnterpriseOne Adapter > Configure Listener Type, after you complete all required fields for configuration properties, click **Save Listener**.

The screenshot shows the 'Configure Listener Type' configuration window for the EnterpriseOne Adapter. The breadcrumb navigation is 'Adapters > EnterpriseOne Adapter > Configure Listener Type'. The form contains the following fields and values:

- Package: Default
- Folder Name: Listener
- Listener Name: DevEnv
- Connection name: connection:E1_GuaranteedEvents
- Retry Limit: 5
- Retry Backoff Timeout: 10
- Environment(s) to subscribe to events on: DV811
- ***** Note *****: Environment value is not used to create subscribed environments in Guaranteed Events System
- Remove these subscriptions when listener shuts down: FALSE

The 'Save Listener' button is highlighted with a red box.

Adapters > EnterpriseOne Adapter > Configure Listener Type form

Enabling EnterpriseOne Adapter Listener: *Step 4*


To receive Real Time or Z-Table events from Oracle JD Edwards EnterpriseOne, you must enable the Listener Notifications and Listeners.

Note.

Integrations shipped by Oracle have default Listener and Listener Notifications. Install these integrations before proceeding with the following tasks.

► To enable Listener Notifications

1. Navigate to Adapters > EnterpriseOne Adapter and enable the notification by selecting the Listener Notifications, as shown in this example:




The screenshot shows the 'EnterpriseOne Adapter' interface with the 'Listener Notifications' tab selected. The main area displays a table titled 'EnterpriseOne Adapter Listener Notifications' with the following data:

Name	Package Name	Enabled
EnterpriseOne_AdapterSamples.AdapterServices:notifySalesOrder	PSFT_EnterpriseOne_AdapterSamples	No
Services.Notification.LearningManagement:notifyCompetencyEvent	PSFT_EnterpriseOne_AdapterServices	No
Services.Notification.Procurement:notifyPurchaseOrderReceipt	PSFT_EnterpriseOne_AdapterServices	No
Services.Notification.LearningManagement:notifyCurrencyRateEvent	PSFT_EnterpriseOne_AdapterServices	No
Services.Notification.LearningManagement:notifyJobInBusinessUnitEvent	PSFT_EnterpriseOne_AdapterServices	No
Services.Notification.Financials:notifyDeduction	PSFT_EnterpriseOne_AdapterServices	No
Services.Notification.Sales:notifySalesOrderPromise	PSFT_EnterpriseOne_AdapterServices	No
Services.Notification.Procurement:notifyPurchaseOrderEvent	PSFT_EnterpriseOne_AdapterServices	No
Services.Notification.LearningManagement:notifyUserPreference	PSFT_EnterpriseOne_AdapterServices	No
Services.Notification.Financials:notifyPersonInformationEvent	PSFT_EnterpriseOne_AdapterServices	No

Adapters > EnterpriseOne Adapter > Listener Notifications form


2. On Adapters > EnterpriseOne Adapter > Listener Notifications, locate the notification you like to enable. In the Enabled column, click **No** to toggle the value for the Notification you want to enable.



This screenshot is identical to the previous one, but the 'Enabled' column is highlighted with a pink box to illustrate the toggle action.

Adapters > EnterpriseOne Adapter > Listener Notifications form

- On the dialog, click **OK** to enable the Notification.



Dialog box

- In the Enabled column, verify that the display is refreshed to indicate Yes. This confirms that the Notification is started.



Adapters > EnterpriseOne Adapter > Listener Notifications form

► To enable Listener


- On the Adapters > EnterpriseOne Adapter > Listeners form, locate the listener you want to enable.

In the Enabled column, click **No** to toggle the value to "Yes."



Adapters > EnterpriseOne Adapter > Listeners form

- On the dialog box, click **OK** to enable the listener.



Dialog box

Note.

A Listener can only be connected to an event connection. While you can configure a Listener against a non-event connection, doing so will prevent the Listener from starting.

3. The Adapters > EnterpriseOne Adapter > Listeners form refreshes.



Adapters > EnterpriseOne Adapter > Listeners form

Note.


Integrations shipped by Oracle have default Listener and Listener Notifications. You if need to create new Listener Notifications, follow the instructions in the *Oracle JD Edwards EnterpriseOne Web Services Gateway EnterpriseOne Adapter Programmers Guide*.

Disabling the EnterpriseOne Adapter Connection

To terminate a connection, you must first disable all Listeners.

► To stop a connection that is enabled

1. On Adapters > EnterpriseOne Adapter, verify that the connection is enabled.



EnterpriseOne Adapter > Adapters > EnterpriseOne Adapter > Connections

- [Configure New Connection](#)

Connection Name	Package Name	Connection Type	Enabled	Edit	View	Copy	Delete
connection:EnterpriseOne	PSFT_E1_Adapter	Oracle EnterpriseOne Connection	Yes				
connection:E1_GuaranteedEvents	PSFT_E1_Adapter	Oracle EnterpriseOne Guaranteed Event Connection	Yes				
connection:E1_ReliableEvents	PSFT_E1_Adapter	Oracle EnterpriseOne Reliable Event Connection	No				

Adapters > EnterpriseOne Adapter > Connections form

2. On Adapters > EnterpriseOne Adapter > Connections, in the left pane in the EnterpriseOne Adapter section, click the Listeners link.



EnterpriseOne Adapter > Adapters > EnterpriseOne Adapter > Listeners

- [Configure New Listener](#)

Listener Name	Package Name	Enabled	Status	Edit	View	Copy	Delete
Listeners:NotificationEnterpriseOne	PSFT_EnterpriseOne_AdapterSamples	Yes	Succeeded				
Listener:DevEnv	Default	Yes	Succeeded				

Adapters > EnterpriseOne Adapter > Connections form

3. In the Enabled column, click **Yes** to toggle the setting.



EnterpriseOne Adapter > Adapters > EnterpriseOne Adapter > Listeners

- [Configure New Listener](#)

Listener Name	Package Name	Enabled	Status	Edit	View	Copy	Delete
Listeners:NotificationEnterpriseOne	PSFT_EnterpriseOne_AdapterSamples	Yes	Succeeded				
Listener:DevEnv	Default	Yes	Succeeded				

Adapters > EnterpriseOne Adapter > Listeners form

This disables the selected listener.

Disabling the EnterpriseOne Adapter Connection

- In the dialog box, click **OK** to disable the Listener.



Dialog box

- The system takes a few seconds to completely disable the Listener. While the Enabled column displays “Pending disable” and while the Status column indicates “Pending,” the Listener is not yet disabled. You can click the Listeners link in the left pane to refresh the form until the status changes.

The screenshot shows the 'EnterpriseOne Adapter Listeners' form. The left pane has 'Listeners' selected. The main area shows a table with the following data:

Listener Name	Package Name	Enabled	Status	Edit	View	Copy	Delete
Listeners:NotificationEnterpriseOne	PSFT_EnterpriseOne_AdapterSamples	Yes	Succeeded	[Icon]	[Icon]	[Icon]	[Icon]
Listener:DevEnv	Default	Pending disable	Pending	[Icon]	[Icon]	[Icon]	[Icon]

Adapters > EnterpriseOne Adapter > Listeners form

The Listener is successfully disabled when the Enabled column displays “No” and the Status displays “Succeeded,” as shown in this example:

The screenshot shows the 'EnterpriseOne Adapter Listeners' form. The left pane has 'Listeners' selected. The main area shows a table with the following data:

Listener Name	Package Name	Enabled	Status	Edit	View	Copy	Delete
Listeners:NotificationEnterpriseOne	PSFT_EnterpriseOne_AdapterSamples	No	Succeeded	[Icon]	[Icon]	[Icon]	[Icon]
Listener:DevEnv	Default	No	Succeeded	[Icon]	[Icon]	[Icon]	[Icon]

Adapters > EnterpriseOne Adapter > Listeners form

Note.

Be sure to perform these steps for *all* Listeners of a connection.

- Once all Listeners are disabled, click the Connections link in the left pane.

The screenshot shows the 'EnterpriseOne Adapter Connections' form. The left pane has 'Connections' selected. The main area shows a table with the following data:


Connection Name	Package Name	Connection Type	Enabled	Edit	View	Copy	Delete
connection:EnterpriseOne	PSFT_E1_Adapter	Oracle EnterpriseOne Connection	Yes	[Icon]	[Icon]	[Icon]	[Icon]
connection:E1_GuaranteedEvents	PSFT_E1_Adapter	Oracle EnterpriseOne Guaranteed Event Connection	Yes	[Icon]	[Icon]	[Icon]	[Icon]
connection:E1_ReliableEvents	PSFT_E1_Adapter	Oracle EnterpriseOne Reliable Event Connection	No	[Icon]	[Icon]	[Icon]	[Icon]

Adapters > EnterpriseOne Adapter > Connections form

Disabling the EnterpriseOne Adapter Connection

7. Disable each connection by clicking **Yes** in the Enabled column.

This toggles the Enabled values to “No.”




Adapters > EnterpriseOne Adapter > Connections form

8. On the dialog, click **OK**.



Dialog box

9. Verify that the Enabled status of the connection is changed to No. You can now change connection settings and restart the connection so the changes take effect.



Adapters > EnterpriseOne Adapter > Connections form

Troubleshooting the EnterpriseOne Adapter


Problem: The EnterpriseOne Adapter does not show up under the Adapters section.

Resolution: There are several possible solutions:

Some web browsers cache the information. Press Control + F5 in Internet Explorer to refresh the screen.


If this does not work, open Integration Server's Error log and check for Order Promising adapter startup service errors. If you see this type of error, make sure that the WmART package is installed, loaded, and activated. To verify this, perform these steps:

1. At the main Integration Server page, click the Management link under the Packages section in the left pane:



Packages > Management page

2. Locate the WmART record in the Package List:




Package List on Packages > Management page

Troubleshooting the EnterpriseOne Adapter

If the WmART package is not loaded and enabled, then click the corresponding “No” links under each of the headings to load and enable the package. If the package does not load, then contact the Global Support Center for assistance.

If the WmART package is already loaded and enabled, then try reloading the package by clicking the icon in the Reload column. If the package does not load, then contact the Global Support Center.

3. After successfully loading and enabling the package, click the WmART link in the Package List column.



The screenshot shows the webMethods Integration Server interface in Microsoft Internet Explorer. The browser address bar shows <http://localhost:5555>. The page title is "den-hb7106609.peoplesoft.com :: Integration Server". The main content area is titled "Packages > Management > WmART".

On the left, there is a navigation menu with sections: Server, Logs, Packages, Adapters, Security, and Settings. The "Packages" section is expanded to show "Management", "Publishing", and "Subscribing".

The main content area displays the following information:

- [Return to Packages Management](#)
- [Browse services in WmART](#)

Package Information

Package Name	WmART
Version	6.1
Build	
Minimum Version of JVM	1.3.1
Package List ACL	Developers
Patches Included	
Description	Adapter Runtime
Publisher	webMethods, Inc.
Created on	
Elements Loaded	133
Elements Not Loaded	0
Startup Services	omi.wm.art.ARTMbeanInit:init, wm.art.admin:startup
Shutdown Services	omi.wm.art.ARTMbeanInit:shutdown, wm.art.admin:shutdown
Replication Services	None
Packages on which this package depends	WmRoot;6.1, WmOmits;6.1
Packages that depend on this package	PSFT_World_Adapter, WmSampleAdapter, WmJDBCAdapter
Subscribers	None

Load Errors
No errors

Load Warnings
No Warnings


Patch History
No Patches

Packages > Management > WmART page

Ensure that the Elements Loaded property displays 133 and that there are no Load Errors and Load Warnings.

If everything on this page is correct and the adapter still does not load, then contact the Global Support Center.


Problem: All the fields in the Default connection are not populated.



Resolution: Create and configure a new connection as described in the section “Configuring Connection : To configure New Connection.” Make sure the default values for the highlighted fields are populated.

Problem: I get an Error dialog while configuring a Listener.

Resolution: The system might display this error when you are trying to configure a Listener:



Dialog box

This error is probably related to some hot fixes installed on the version of Internet Explorer you are using to configure the Listener. No other side affects, with the exception of this error dialog, are caused by these hot fixes. You can safely click No and continue.

Problem: I made some configuration changes to a connection and they do not take affect when I enable the connection.

Resolution: Typically, when you make configuration changes and they do not take affect, it is because the connection was not completely shut down before making the changes. You should ensure all Listeners are disabled before disabling and modifying the connection.

Problem: I have replaced the connector files with the version of my enterprise server and now I get a “port in use” error when I restart the Reliable Event Connection.

Resolution: There are two possible resolutions:

After stopping a Connection, you must change the Port that receives outbound events before restarting the Connection. A side effect of this workaround is that ERP creates a new subscription based on this port number, so any queued real-time events will not be received.

After stopping a Connection, you must stop and then start (you cannot restart) the WSG Integration Server. This forces the JVM to close and the port to close. After Integration Server is started, the Connection can be enabled.

Note.


Ensure the enterprise server meets the Minimum Technical Requirements (MTRs) for the EnterpriseOne Adapter for Integration Server.

Problem: While running a business function service, an exception is thrown indicating that the business function returned an error, but I do not get any error messages.

Resolution: The business function is returning a value of 2 – indicating an error – but it is not correctly populating the error list with the reason for the error. If this is a custom business function, verify the error list is being populated. If it is a shipped JD Edwards business function, you might need to enter an ICE incident to have the problem corrected.

Problem: The adapter connection starts correctly but when I attempt to execute a business function service it fails.

Resolution: You might be seeing this error in Developer when running a Business Function Service:



webMethods Developer dialog box

An OCM setup issue causes this problem. To correct the error:

- Verify there is a DEFAULT entry for *PUBLIC for object type BSFN on your specific environment.

- ▶ After making the change, restart both the Oracle JD Edwards EnterpriseOne Server and the adapter connection.

Problem: When I try to start a listener, it fails and gives me this exception message:
"javax.resource.ResourceException, stack=javax.resource.ResourceException:
ConnectionType is not an ERPCCommonConnection. Cannot continue."

Resolution: This error typically occurs after a new adapter package is installed. To clear the error, stop Integration Server and then restart Integration Server. Simply restarting the server does not always clear the problem. Also, make sure the listener is pointing to an outbound event connection (Guaranteed or Reliable).

Problem: I received this warning message: "****WARNING ** Connection is NOT available for the listener. This might be because the connection is disabled before the listener."

Resolution: This happens if the connection is disabled when the listener associated with this connection is still running. This will not cause events to be lost; however, it could cause problems such as NullPointerException in the listener. To avoid this error, disable the listener before disabling the connection.

Problem: When I changed the connection for the listener, I received this error:
"ConnectionType MUST be an EnterpriseOne Event Reliable connection, EnterpriseOne Guaranteed Event Connection. Cannot continue."


Resolution: Restart Integration Server.

Problem: When starting the connection, this exception is thrown:

```
STGAWSC1 Invalid Environment, Please use a valid Environment
[SECURITY_ERROR] A security error occurred.
com.jdedwards.system.security.SecurityServerException: FAILURE: null
```

Troubleshooting the EnterpriseOne Adapter

This form indicates a possible error message:




Adapters > EnterpriseOne Adapter > Connections form

Resolution:

1. In the connection, make sure the environment name, Oracle JD Edwards EnterpriseOne server name, and port number are correct.
2. Verify that the Oracle JD Edwards EnterpriseOne server is running.

This example form shows connection properties:


Troubleshooting the EnterpriseOne Adapter



Connection Properties form

Problem: The Event Listener does not start and fails with following error:


This form indicates a possible error:



Adapters > EnterpriseOne Adapter > Listeners form

Resolution: The environment specified in the listener configuration is wrong. Enter a valid environment.

Problem: Event Listener does not start and fails with this error:




Adapters > EnterpriseOne Adapter > Listeners form

Resolution:

There is a communication issue with EnterpriseOne Transaction Server. Verify that:

- The Transaction Server is running.
- The Transaction Server name and port specified in the connection is accurate.


Problem: The Event Listener does not start and fails with this error:



Adapters > EnterpriseOne Adapter > View Listener form

Resolution: The event subscription is missing in Oracle JD Edwards EnterpriseOne. Use application P90702A and create an event subscription. Refer to the Oracle JD Edwards EnterpriseOne documentation on how to create subscriptions.

Problem: Event Listener does not start and fails with this error:



Adapters > EnterpriseOne Adapter > Listeners Last Error form

Resolution:

The security server referenced in event connection is not the same security server as the one to which Transaction Server is connected. Configure the event connection to use the same security server. Look at the jas.ini file in Transaction server configuration to determine the correct security server.

Problem: When creating the adapter Notifications, required event does not show up in the retrieved event list.

Resolution (Option 1):

Event is not defined or added to the environment. Create event definition and add event to environment using App P90701A. (Refer to the Oracle JD Edwards EnterpriseOne documents for how to create event definitions and add events to environments)

Resolution (Option 2):

A subscription to the event is missing in Oracle JD Edwards EnterpriseOne. Use App P90702A and create an event subscription. (Refer to the Oracle JD Edwards EnterpriseOne documentation for how to create subscriptions)

Problem:

This exception is received from Oracle JD Edwards EnterpriseOne when executing business function Adapter Services:

```
SystemException: Fatal exception thrown when executing BSFN Method.  
Fail to execute BSFNMethod  
com.jdedwards.system.kernel.CallObjectSystemException: Server  
problem. The server may still be available, but because of state  
information, the entire unit-of-work must be resubmitted
```

This error in Integration Server logs before the above exception

```
*ERROR* CallObject@1761119e: COSE#1000 Request timeout: timeout  
after 90000ms host DENMLPS11:6082(4030) SocID:4515 PID:9172  
BSFN:F4311EndDoc user:WSG5 Env:STBAWSI2
```

Resolution:

This exception is thrown when a timeout occurred in executing a business function on the Oracle JD Edwards EnterpriseOne Server. Increase the “Timeout value, in milliseconds, for a request to the enterprise server” in the EnterpriseOne connection of the EnterpriseOne Adapter.

Part 3: Configuring the Order Promising Adapter

Understanding the Order Promising Adapter

JD Edwards provides an Order Promising adapter for Web Services Gateway (WSG) Integration Server that enables the exchange of information between the JD Edwards Order Promising application and other systems such as Oracle JD Edwards EnterpriseOne, PeopleSoft Enterprise, and so on. The Order Promising adapter for Integration Server provides a flexible, easy-to-use mechanism for WSG-enabled applications to interface with the Order Promising application.

The instructions in this chapter support JD Edwards Order Promising Server, version 8.12.

Prerequisites


Ensure that these prerequisites are met prior to installing and configuring the Order Promising adapter for WSG Integration Server:

- Make sure that you obtain the latest version of the applicable installation guides.
- Verify that the system meets the Minimum Technical Requirements (MTRs) for the hardware and software required to install Oracle JD Edwards EnterpriseOne WSG foundation. Check the MTRs on Customer Connection.
- The WSG Integration Server, on which the Order Promising adapter is configured, must be set up and configured on the same network as the Order Promising Server.
- To use the sample services shipped with the Order Promising adapter, you must load the package in file PSFT_OP_AdapterSamples.zip onto the WSG Integration Server:

Architecture

The Order Promising adapter for WSG Integration Server connects to the Order Promising Application Server using the standard interoperability technologies built into the Order Promising Application. This adapter runs inside the adapter runtime framework, which in turn, runs inside Integration Server. It provides a scalable and reliable runtime framework and exposes the Order Promising services directly to the WSG Integration Server Flows.

This graphic illustrates the adapter architecture:



Order Promising adapter for WSG Integration Server architecture

Configuring the Order Promising Adapter: *Step 1*

To configure the Order Promising Adapter, perform these tasks:

- Configure a new Order Promising server connection.
- Configure a new listener for the Order Promising server.

Or,

- Update the sample Order Promising server connection.
- Use the sample listener shipped with the adapter for the Order Promising server.

Configuring a New Order Promising Server Connection

Before you can use the Order Promising adapter for sending and receiving messages to and from the Order Promising Server, you must configure a connection to the Order Promising server.

► **To configure a new connection to the Order Promising server**

1. Open Integration Server Administrator by entering this URL in your internet browser:

`http://<Host_Name>:5555.`

Where *<Host_Name>* is the name, or IP address, of the Integration Server and 5555 is the default port for the Integration Server.

2. Sign in with the default username and password, Administrator and manage.
3. Start the Order Promising Server
4. In the left pane of the Integration Server Administrator console, click **Adapters**, and then click **Order Promising Adapter**.

Configuring the Order Promising Adapter: Step 1

This example shows the Integration Server Admin Console:

The screenshot displays the Integration Server Admin Console in a Microsoft Internet Explorer browser window. The browser address bar shows `http://localhost:5555`. The console title is `den-hb7106609.peoplesoft.com :: Integration Server`. The left sidebar contains a navigation menu with categories: Server, Logs, Packages, Adapters, Security, and Settings. The main content area is titled `Server > Statistics` and contains three tables and a chart.

Usage			
	Current	Peak	Limit
Total Sessions	2	2	-
Licensed Sessions	0	1	10000
Service Threads	1	3	-
System Threads	73	75	-
Uptime	0h:5m:31s		

Requests		
	Current	Lifetime
Completed Req's	117	-
Average Time	2 ms	2 ms
Service Errors	0	-
Started	Started	Ended
Req's per minute	2/min	2/min

Memory	
Total	131262 KB
Used	91321 KB 70%
Free	39941 KB 30%

Below the memory table is a line chart titled "Memory Usage (average per hour)" showing usage over a 24-hour period. The y-axis ranges from 0 KB to 131262 KB. The usage is relatively stable, fluctuating around 90-100 KB.

Integration Server Admin Console form

Note.

If you do not see the Order Promising Adapter link, then it is not correctly installed. See "Troubleshooting the Order Promising Adapter" in this guide.


5. Click the Configure New Connection link:

The screenshot shows the `Order Promising Application Adapter` configuration page in a Microsoft Internet Explorer browser window. The browser address bar shows `http://localhost:5555/WmRoot/adapter-index.dsp?url=%2FWmART%2FListResources.dsp%3FadapterTypeName%3DPSFT_OP_Adapter%26dspName%3D.LIS1`. The console title is `den-hb7106609.peoplesoft.com :: Integration Server :: Order Promising Application Adapter`. The left sidebar contains a navigation menu with categories: Order Promising Application Adapter, Connections, Listeners, Listener Notifications, and About. The main content area is titled `Adapters > Order Promising Application Adapter > Connections` and contains a link `Configure New Connection`. Below the link is a table titled "Connections" with columns: Connection Name, Package Name, Connection Type, Enabled, Edit, View, Copy, and Delete. The table is empty, and a red box highlights the text "No connections found".

Order Promising Application adapter form

6. In Connection Types, click the "Connection to the Order Promising Application Server" link:

Configuring the Order Promising Adapter: Step 1



Order Promising Application adapter form

Configuring the Order Promising Adapter: Step 1

7. In the Configure Connection Type > Order Promising Application Adapter section, complete these fields (see tables for field definitions).

Connection Connection Type form

In the Configure Connection Type > Order Promising Adapter section, complete these fields:

Property	Value	Typical Setting
Package	Determines the storage location for connection instance. You should not store the connection in the PSFT_OP_Adapter package because whenever you install a new adapter version, the connection is overwritten and lost. Therefore, always store connection instances in a separate package. To do this, you first need to start WSG Developer and create a new package.	Site-dependent variable
Folder Name	Determines the name of the folder inside the package where the connection instance will be stored. The folder must already exist. If it does not exist, then start WSG Developer and create a new folder. Note that the name of the folder must not contain a space.	Site-dependent variable

Configuring the Order Promising Adapter: Step 1

Connection Name	<p>Each connection <i>must</i> be given a unique name to distinguish it from the other connections. Ensure the name is sufficiently descriptive to allow adapter service developers to identify and remember the connection instance if there is more than 1.</p> <p>For example:</p> <p>OP_Server_PROD_Connection</p>	Site-dependent variable
-----------------	--	-------------------------

In the Connection Properties section, complete these fields:


Property	Value	Typical Setting
Order Promising Server Host Name	The IP address or machine name of the machine on which the Order Promising server is running.	Site-dependent variable
Order Promising Server Port Number	The IP Port number on which the Order Promising server listens for incoming client connections.	Site-dependent variable
Order Promising Server Connection Timeout	A value in milliseconds after which the adapter automatically closes its idle socket connections to the Order Promising Server.	This setting is currently NOT used by the adapter. So it is recommended that you leave it as "0."
Temporary Working Folder for the adapter	<p>A folder inside the Integration Server package folder where the adapter will store files created during its operation.</p> <p>Important!</p> <p>You must manually create this folder before enabling the connection.</p>	<p>Important!</p> <p>You must provide a path that is relative to the package for which you are creating the connection, and the path must NOT begin with ./ or .\</p> <p>For example, if the connection is being created in the OP Adapter Samples package, then the value for this parameter should be set to:</p> <p>Packages\PSFT_OP_AdapterSamples\Temp_Working_Folder</p> <p>Important!</p> <p>You must also first create the Temp_Working_Folder before enabling the connection</p>
Absolute Folder Path to a Java Compiler	<p>Provide the absolute, complete path to a Java compiler executable installed on the machine on which you are configuring the adapter.</p> <p>Note.</p> <p>It is highly recommended that you provide a path to the Java Compiler inside the JVM that gets installed with</p>	<p>Important!</p> <p>You can use a JDK that is of the same or higher version as the one used to run the Integration Server instance.</p> <p>Additionally, make sure that the javac.exe file is in the bin folder.</p>

Configuring the Order Promising Adapter: Step 1

	Integration Server. By using this method, if someone accidentally uninstalls the externally installed JDK, it does not affect the OP adapter.	
--	---	--


In the Connection Management Properties section, it is recommended that you use the default values.

8. Click **Save Changes**.



9. On Adapters > Order Promising Application Adapter > Connections, notice that by default, the connection is still disabled. See chapter “Enabling the Order Promising Adapter Connection: Step 2” in this guide for instructions to enable a connection.

Configuring the Order Promising Adapter: Step 1



Adapter Connections form

Configuring a New Listener for the Order Promising Server

To receive response and error notifications, you need to create and configure a listener.

Note.

You must first create and configure a connection instance before creating a listener because a listener requires a connection for its operation. Refer to “Configuring a New Order Promising Server Connection” in this chapter for instructions.

► To configure a new listener for the Order Promising server

1. Open Integration Server Administrator by entering this URL in your internet browser:

`http://<Host_Name>:5555.`


Where *<Host_Name>* is the name or IP address of the Integration Server and 5555 is the default port for the Integration Server.

2. Sign in with the default username and password, Administrator and manage.
3. Same time run the `op_test_server.exe` and Start the `StartOPServer.bat`

Configuring the Order Promising Adapter: Step 1

4. In the left pane of the Integration Server Administrator console, click **Adapters**, and then click **Order Promising Adapter**.

This example shows the Integration Server Administrator console:



Integration Server Admin Console form


Note.

If you do not see the Order Promising Adapter link, then it is not correctly installed. Refer to "Troubleshooting the Order Promising Adapter" in this guide.

► To create a Listener


1. Click **Listeners** in the Order Promising Application Adapter navigation bar:

Configuring the Order Promising Adapter: Step 1



Order Promising Application adapter form


2. Select the Configure New Listener link:



Order Promising adapter Listeners form

If you have not yet configured a connection instance, the system displays the above form.


Configuring the Order Promising Adapter: Step 1



Order Promising Adapter Listeners form


If you have configured a connection instance, the system displays the above screen.

3. Click **Order Promising Server Response Listener**:



Order Promising adapter Listeners form

4. On the Adapters > Order Promising Application Adapter > Configure Listener Type form, complete these fields (see tables for field descriptions).



Order Promising Application adapter form

Configuring the Order Promising Adapter: Step 1

Property	Value	Typical Setting
Package	Determines the storage location for listener instance. You should not store the listener in the PSFT_OP_Adapter package because whenever you install a new adapter version the listener is overwritten and lost. Therefore, always store listener instances in a separate package. To do so, you first need to start WSG Developer and create a new package.	Site-dependent variable
Folder Name	Determines the name of the folder inside the package where the listener instance will be stored. The folder must already exist. If it does not exist, then start WSG Developer and create a new folder. Note that the name of the folder must not contain a space.	Site-dependent variable
Listener Name	Each listener <i>must</i> be given a unique name to distinguish it from the other listeners. Ensure the name is sufficiently descriptive to allow notification developers to identify and remember the listener instance if there is more than 1. It is recommended that you do not attach more than 1 notification to a listener. See the <i>Oracle JD Edwards Order Promising Adapter Programmer's Guide</i> for instructions on how to create a notification. For example: Listener_On_F01901T	Site-dependent variable
Connection Name	Choose from a list of connection instances that you created earlier.	Site-dependent variable
Retry Limit	Number of times to retry starting the listener if it fails to start.	5
Retry Backoff Timeout	The amount of time in milliseconds that Integration Server waits to retry the listener if the listener fails to start when Integration Server attempts to start it.	100
Poll Interval	Amount of time in milliseconds between each poll of the resource by the listener to check for new events.	60000

Configuring the Order Promising Adapter: Step 1

5. Click **Save Listener**.

The screenshot shows a web browser window titled "Order Promising Adapter - denosc1214.mlab.jdedwards.com - Integration Server - Microsoft Internet Explorer". The address bar shows the URL: `http://localhost:5555/WmRoot/adapter-index.dsp?url=%2FWmART%2FListResources.dsp%3FadapterTypeName%3DPSFT_OP_Adapter%26dspName%3D.LISTRESOURCES`. The browser displays the "Order Promising Adapter" configuration page, which is part of the "Integration Server" and "Order Promising Adapter" sections. The page title is "Adapters > Order Promising Adapter > Configure Listener Type".

The configuration form is titled "Configure Listener Type > Order Promising Adapter" and includes the following fields:

- Package: PSFT_OP_Adapter_Tests (dropdown menu)
- Folder Name: Listener (text input)
- Listener Name: Listener_On_F01901T (text input)
- Connection name: Connections:OP_Server_PROD_Connection (dropdown menu)
- Retry Limit: 5 (text input)
- Retry Backoff Timeout: 10 (text input)


Below these fields is a section titled "Listener Properties" with the following field:

- Poll Interval: 60000 (text input)

A "Save Listener" button is located at the bottom of the form. The browser's status bar shows "Local intranet" and the time "9:21 PM".

Configuring the Order Promising Adapter: Step 1

- On Adapters > Order Promising Application Adapter > Listeners, notice that by default, the connection is still disabled. Refer to chapter “Enabling a Listener: Step 3” in this guide for instructions to enable the listener.



The screenshot shows a web browser window displaying the 'Order Promising Adapter Listeners' form. The browser's address bar shows the URL: `http://localhost:5555/WmRoot/adapter-index.dsp?url=%2FWmART%2FListResources.dsp%3FadapterTypeName%3DPSFT_OP_Adapter%26dspName%3D.LISTRESOURCES`. The page title is 'denoscl214.mlab.jdedwards.com :: Integration Server :: Order Promising Adapter'. The breadcrumb navigation is 'Adapters > Order Promising Adapter > Listeners'. A left-hand navigation pane shows 'Order Promising Adapter' with sub-items: 'Connections', 'Listeners', 'Listener Notifications', and 'About'. The main content area has a link for 'Configure New Listener' and a table titled 'Order Promising Adapter Listeners'.

Listener Name	Package Name	Enabled	Status	Edit	View	Copy	Delete
Listeners:Listener_On_F01901T	PSFT_OP_Adapter_Tests	No	Succeeded				

Order Promising Application adapter Listeners form

Enabling the Order Promising Adapter Connection: *Step 2*

After you configure and save a connection, you must enable the connection before the adapter can use it.

► To enable the JD Edwards Order Promising connection

1. Open Integration Server Administrator by entering this URL in your internet browser:

`http://<Host_Name>:5555.`

Where *<Host_Name>* is the name, or IP address, of the Integration Server and 5555 is the default port for the Integration Server.

2. Sign in with the default username and password, Administrator and manage.
3. Same time run the `op_test_server.exe` and Start the `StartOPServer.bat`
4. In the left pane, click **Adapters**, and then select **Order Promising Adapter**.

The screenshot displays the webMethods Integration Server Administration console. The browser address bar shows `http://localhost:5555`. The page title is "den-hb7106609.peoplesoft.com :: Integration Server". The left navigation pane is expanded to "Adapters", with "Order Promising Adapter" selected. The main content area shows the "Server > Statistics" form, which includes several data tables and a memory usage graph.

Usage			
	Current	Peak	Limit
Total Sessions	2	2	-
Licensed Sessions	0	1	10000
Service Threads	1	3	-
System Threads	73	75	-
Uptime	0h:6m:31s		

Requests		
	Current	Lifetime
Completed Req's	117	-
Average Time	2 ms	2 ms
Service Errors	0	-
Req's per minute	Started 2/min	Ended 2/min

Memory

Total 131262 KB
Used 91321 KB 70%
Free 39941 KB 30%

Memory Usage (average per hour)

131262 KB


-24h -12h -1h 0 KB

Server > Statistics form

5. On the Adapters > EnterpriseOne Adapter > Connections form, locate the connection you want to enable.

Enabling the Order Promising Adapter Connection: Step 2

In the Enabled column, click **No** to toggle the value to “Yes.”



Adapters > Order Promising Application Adapter > Connections

By default, the connection is disabled.


6. On the dialog box, click **OK** to enable the connection.



Enable connection dialog box


After a short while, the “No” link in the Enabled column will change to a “Yes” link with a check mark, as shown in this example:

Enabling the Order Promising Adapter Connection: Step 2



Adapters > Order Promising Application Adapter > Connections

If an error occurs while trying to enable the connection, the system displays this error message:



Adapters > Order Promising Application adapter > Connections form

See the "Troubleshooting the Order Promising Adapter" section in this guide for instructions on how to resolve errors that might occur when enabling the connection.

Enabling a Listener: *Step 3*

To enable a listener, you must first enable the connection associated with the listener. Refer to chapter “Enabling the Order Promising Adapter Connection” in this guide.

► To enable a listener

1. Open Integration Server Administrator by entering this URL in your internet browser:

`http://<Host_Name>:5555.`

Where <Host_Name> is the name or IP address of the Integration Server and 5555 is the default port for the Integration Server.

2. Sign in with the default username and password, Administrator and manage.
3. Same time run the op_test_server.exe and Start the StartOPServer.bat
4. Under the Adapters heading, click the **Order Promising Adapter**:

The screenshot shows the webMethods Integration Server Administration console. The left navigation pane is expanded to 'Server > Statistics'. The main content area displays several tables and a chart:

Usage			
	Current	Peak	Limit
Total Sessions	2	2	-
Licensed Sessions	0	1	10000
Service Threads	1	3	-
System Threads	73	75	-
Uptime	0h:6m:31s		

Requests		
	Current	Lifetime
Completed Req's	117	-
Average Time	2 ms	2 ms
Service Errors	0	-
Req's per minute	2/min	2/min

Memory	
Total	131262 KB
Used	91321 KB 70%
Free	39941 KB 30%


Below the tables is a line chart titled 'Memory Usage (average per hour)' showing memory usage over a 24-hour period. The y-axis represents memory usage in KB, with a maximum value of 131262 KB. The x-axis shows time intervals from -24h to -1h.

Server > Statistics form

5. On Adapters > Order Promising Application Adapter > Connections, in the left pane, click **Listeners**.

In the Enabled column, click **No** to toggle the value to “Yes.”

Enabling a Listener: Step 3



Adapters > Order Promising Application Adapter > Connections

By default, the connection is disabled.


6. On the dialog box, click **OK** to enable the Listener.



Enable Listener dialog box


7. After a short while, the “No” link in the Enabled column will change to a “Pending enable” link with a check mark, as shown in this example:

Enabling a Listener: Step 3




Adapters > Order Promising Application Adapter > Listener form

- Typically, after waiting a few seconds, click the Listeners link to verify that the listener has been enabled. The system displays a “Yes” in the Enabled column and “Succeeded” in the Status column.



Copy

Enabling a Listener: Step 3



Adapters > Order Promising Application Adapter > Listeners form

In the Enabled column, if you click the Pending enable link to enable the listener, the status of the listener changes to "Failed."

Enabling a Listener: Step 3


The screenshot shows a web browser window displaying the configuration page for the Order Promising Adapter Listeners. The browser's address bar shows the URL: `http://denosc1214:5555/WmRoot/adapter-index.dsp?url=%2FWmART%2FListResources.dsp%3FadapterTypeName%3DPSFT_OP_Adapter%26dspName%3D.LISTRESOURCI`. The page title is "denosc1214.mlab.jdedwards.com :: Integration Server :: Order Promising Adapter". The breadcrumb navigation is "Adapters > Order Promising Adapter > Listeners". A link "Configure New Listener" is visible. Below this is a table titled "Order Promising Adapter Listeners".

Listener Name	Package Name	Enabled	Status	Edit	View	Copy	Delete
Listeners:Listener_On_F01901T	PSFT_OP_Adapter_Tests	No	Failed				

Adapters > Order Promising Application Adapter > Listeners form

9. If you already created a notification service for this listener, in the Enabled column, click **No** to toggle the value to "Yes."

Enabling a Listener: Step 3



Adapters > Order Promising Application Adapter > Listeners form

10. On the dialog box, click **OK** to enable the listener.




Dialog box

11. Verify that the system displays "Pending enable" in the Enabled column and "Pending" in the Status column. This confirms that the system is starting the listener.

Note.

The amount of time it takes for the system to enable the listener varies depending on machine performance.


Enabling a Listener: Step 3



Adapters > Order Promising Application Adapter > Listeners form

Enabling a Listener: Step 3

12. Typically, after waiting a few seconds, click the Listeners link to verify that the listener has been enabled. The system displays a “Yes” in the Enabled column and “Succeeded” in the Status column.



Adapters > Order Promising Application Adapter > Listeners form

Troubleshooting the Order Promising Adapter

Problem: The Order Promising adapter does not show up under the Adapters section.

Resolution: The Adapter package "PSFT_OP_Adapter" should be installed and activated along with WSG installation. So the Order Promising Adapter should show up in the Adapters section. So if The adapter does not show up try the following resolutions :

1. Some web browsers cache the information. Press Control + F5 in Internet Explorer to refresh the screen.

If this does not work, open Integration Server's Error log and check for Order Promising Adapter startup service errors. If you see this type of error, make sure that the PSFT_OP_Adapter package is installed, loaded, and activated. To verify this, perform these steps:

1. At the main Integration Server page, click the Management link under the Packages section in the left pane:

Package Name	Home	Reload	Enabled	Loaded	Archive	Safe Delete	Delete
Default			Yes	Yes			
PSFT_ConfigurationEditor			Yes	Yes			
PSFT_Dispatcher			Yes	Yes			
PSFT_E1_Adapter			Yes	Yes			
PSFT_JDBCAdapterServices			Yes	Yes			
PSFT_PackageManagement			Yes	Yes			
PSFT_Utils			Yes	Yes			
PSFT_XRefAndSoftCoding			Yes	Yes			
WmART			Yes	Yes			
WmAdmin			Yes	Yes			
WmAdminResource			Yes	Yes			
WmDB			Yes	Yes			
WmFlatFile			Yes	Yes			
WmFlatFileSamples			Yes	Yes			
WmJDBCAdapter			Yes	Yes			
WmJMSAdapter			Yes	Yes			
WmLogUtil			Yes	Yes			

Packages > Management page

2. If the PSFT_OP_Adapter package is not loaded and enabled, then click the corresponding "No" links under each of the headings to load and enable the package. If the package does not load, then contact the Global Support Center for assistance.

Troubleshooting the Order Promising Adapter

The screenshot shows the PeopleSoft WSG Integration Server interface in a Microsoft Internet Explorer browser. The address bar shows <http://localhost:5555/>. The page title is "dends074.mlab.jdedwards.com :: Integration Server". A red banner at the top indicates "License Key is Expired or Invalid." The left sidebar contains navigation menus for Server, Logs, Packages, Adapters, Security, and Settings. The main content area is titled "Packages > Management" and contains a list of management actions and a "Package List" table.

Package List

Package Name	Home	Reload	Enabled	Loaded	Archive	Safe Delete	Delete
Default			Yes	Yes			
PSFT_ConfigurationEditor			Yes	Yes			
PSFT_Dispatcher			Yes	Yes			
PSFT_E1 Adapter			Yes	Yes			
PSFT_JDBCAdapterServices			Yes	Yes			
PSFT_OP Adapter			No	No			
PSFT_PackageManagement			Yes	Yes			
PSFT_Utils			Yes	Yes			
PSFT_XRefAndSoftCoding			Yes	Yes			
WmART			Yes	Yes			
WmAdmin			Yes	Yes			
WmAdminResource			Yes	Yes			
WmDB			Yes	Yes			
WmFlatFile			Yes	Yes			
WmFlatFileSamples			Yes	Yes			
WmJDBCAdapter			Yes	Yes			
WmJMSAdapter			Yes	Yes			

3. If the PSFT_OP_Adapter package is already loaded and enabled, then try reloading the package by clicking the icon in the Reload column. If the package does not load, then contact the Global Support Center.
4. After successfully loading and enabling the package.

Troubleshooting the Order Promising Adapter

The screenshot shows a web browser window displaying the Integration Server interface. The address bar shows `http://localhost:5555/`. The page title is "Cannot find server - Microsoft: Internet Explorer". The main content area is titled "Packages > Management" and displays a "Package List" table. The table has columns for Package Name, Home, Reload, Enabled, Loaded, Archive, Safe Delete, and Delete. The "PSFT_OP_Adapter" package is highlighted in the list.

Package Name	Home	Reload	Enabled	Loaded	Archive	Safe Delete	Delete
Default			Yes	Yes			
PSFT_ConfigurationEditor			Yes	Yes			
PSFT_Dispatcher			Yes	Yes			
PSFT_E1_Adapter			Yes	Yes			
PSFT_JDBCAdapterServices			Yes	Yes			
PSFT_OP_Adapter			Yes	Yes			
PSFT_PackageManagement			Yes	Yes			
PSFT_Utils			Yes	Yes			
PSFT_XRefAndSoftCoding			Yes	Yes			
WmART			Yes	Yes			
WmAdmin			Yes	Yes			
WmAdminResource			Yes	Yes			
WmDB			Yes	Yes			
WmFlatFile			Yes	Yes			
WmFlatFileSamples			Yes	Yes			
WmJDBCAdapter			Yes	Yes			
WmJMSAdapter			Yes	Yes			

Packages > Management pages

5. Click the PSFT_OP_Adapter link in the Package List column.

Troubleshooting the Order Promising Adapter

The screenshot shows a web browser window displaying the Integration Server interface. The address bar shows `http://localhost:5555/`. The page title is "Integration Server" and the logo "PeopleSoft" is visible. A message at the top indicates "License Key is Expired or Invalid." The left sidebar contains a navigation menu with categories: Server, Logs, Packages, Adapters, Security, and Settings. The main content area is titled "Packages > Management > PSFT_OP_Adapter" and contains the following information:

- [Return to Packages Management](#)
- [Browse services in PSFT_OP_Adapter](#)

Package Information	
Package Name	PSFT_OP_Adapter
Version	8.95
Build	12282005
Minimum Version of JVM	1.3.0
Package List ACL	Default
Patches Included	
Description	
Publisher	www.peoplesoft.com
Created on	2005-12-28 18:20:21 MST
Elements Loaded	2
Elements Not Loaded	0
Startup Services	PSFT_OP_Adapter.admin:startup
Shutdown Services	PSFT_OP_Adapter.admin:shutdown
Replication Services	None
Packages on which this package depends	WmART;*,*
Packages that depend on this package	None
Subscribers	None

Load Errors
No errors

Load Warnings
No Warnings

Patch History
No Patches


Packages > Management > PSFT_OP_Adapter page

6. Ensure that the Elements Loaded property displays 2 and that there are no Load Errors and Load Warnings.
7. If everything on this page is correct and the adapter still does not load, then contact the Global Support Center.

Problem: I made some configuration changes to a connection and they do not take effect when I enable the connection.

Resolution: Typically, when you make configuration changes and they do not take effect, it is because the connection was not completely shut down before making the changes. You should ensure that all listeners are disabled before disabling and modifying the connection.

Problem: When creating Adapter Notifications/Services, an exception is thrown saying that compilation of source files failed.




Developer error form

Resolution:

Make sure in the connection configuration that the absolute path to a java compiler (javac) is specified.

Troubleshooting the Order Promising Adapter



Order Promising Adapter > Connections form

Problem: ClassNotFoundException Exceptions thrown during execution of Adapter Services.

Example: `java.lang.ClassNotFoundException: ProcurementNotify`

Resolution: The OP Adapter during design time generates java classes and stores them in a directory. In OP Adapter Configuration, specify the directory (path to working folder) where these classes exist. If these classes don't exist, open the Adapter Services using Developer Tool to generate the classes.

Problem: I get the following error while enabling the listener.

```
Error encountered
[ART.115.3250] Adapter Runtime (Listener): Error setting
properties for listener:
OP_AdapterServices_Listener:OP_AdapterServices_Listener.
[ART.118.5075] Adapter Runtime (Connection): Listener
OP_AdapterServices_Listener:OP_AdapterServices_Listener cannot
use connection Connection:OP_Server_Connection. The connection
is already being used by and adapter service or polling
notification.
```

Resolution: A listener needs a connection which is not being used by any adapter service or notification. So a dedicated connection needs to be created for use by the listener.

Appendix A: Listing of Installable Components

This table describes where each of the Oracle JD Edwards EnterpriseOne Web Services Gateway (WSG) components is installed based on the type of installation (Server or Developer) that you perform.

Category	Components	Web Services Gateway Server	Web Services Gateway Developer
<i>Adapter</i>	ADK	√	√
	EnterpriseOne Adapter	√	√
	EnterpriseOne Adapter Doc	√	√
	JDBC Adapter	√	√
	JDBC Doc	√	√
	JMS Adapter & Doc	√	√
	Order Promising Adapter	√	√
	Order Promising Adapter Doc	√	√
<i>Administration</i>	Administrator	√	√
<i>Broker and JMS</i>	Broker Client API	√	√
<i>Common Files</i>	Database Script	√	√
	Fabric Client API		√
	Servicenet Client API		√
<i>Cross-Component Documentation</i>	Documentation	√	√

Appendix A: Listing of Installable Components

Category	Components	Web Services Gateway Server	Web Services Gateway Developer
<i>Integration Server</i>	IS Program Files	√	√
	C/C++ SDK	√	√
	Cert Toolkit	√	√
	Cert Toolkit Doc	√	√
	Logging Utility	√	√
	IS Documentation	√	√
	PKI support	√	√
	Process Runtime	√	√
	Repository Server	√	√
	Samples	√	√
	WmDB	√	√
<i>Developer</i>	Developer Program Files		√
	C/C++ SDK		√
	Documentation		√
	Samples		√
<i>Foundation Services</i>	PSFT_Utills	√	√
	PSFT_XRefAndSoftcoding	√	√
	PSFT_JDBCAdapterServices	√	√
	PSFT_Dispatcher	√	√
	PSFT_PackageManagement	√	√
<i>Configuration Editor</i>	PSFT_ConfigurationEditor	√	√

Appendix B: Building a Web Services Gateway Developer Package

This appendix describes how to configure Oracle JD Edwards EnterpriseOne to deliver the Oracle JD Edwards EnterpriseOne Web Services Gateway (WSG) Development install with the Oracle JD Edwards EnterpriseOne client install. These three steps are required:

- Configuring the WSG install file on the deployment server.
- Creating a feature.
- Including the feature in the Oracle JD Edwards EnterpriseOne package.

Configuring the Web Services Gateway install file

Download the WSG Developer components from the Update Center and copy them to the directory `<Deployment_Server>\E812\OneWorld Client Install\ThirdParty\WebServicesGateway`, where `<Deployment_Server>` is the name of the deployment server.

Note.

The `WebServicesGateway` folder should be created under the folder `ThirdParty` before copying the WSG Developer components.

The windows installer batch file (`wininstall_silent.bat`) has to be modified by the administrator. The administrator has to qualify the full network path of `wsgInstaller.jar`, `wM65Image_w32.zip` and `wsg.ini` files.

The delivered batch file command line appears as:

```
java -jar %1\wsgInstaller.jar -launchImage %1
\wM65Image_w32.zip -silent %1\wsg.ini
```

Replace “%1” with the network path of the deployment server. For example:

```
java -jar "\\<Deployment_Server>\E812\OneWorld Client Install
\ThirdParty\WebServicesGateway\wsgInstaller.jar"
-launchImage "\\<Deployment_Server>\E812\OneWorld Client Install
\ThirdParty\WebServicesGateway\wM65Image_w32.zip"
-silent "\\<Deployment_Server>\E812\OneWorld Client Install
\ThirdParty\WebServicesGateway\wsg.ini"
```

Creating a feature

► To create a feature


1. Log in to Oracle JD Edwards EnterpriseOne on the machine where you will build the WSG package.

Appendix B: Building a Web Services Gateway Developer Package

2. From the Package and Deployment Tools menu (GH9083), select Package Assembly (P9601).
3. Select the features option from the form exit menu.
4. On the Work with Features form, click **Add**.
5. On the Feature Based Deployment Director form, click **Next**.
6. On the Feature Information form, enter the Feature name, Feature Type, and Description.

Select the Required and Additional Install Processes check boxes, and click **Next**.

This is an example of how to complete the Feature Information form:



Package Assembly [Feature Information] form

On the Additional Install Processes form, enter the Executable Name and Source Path.

Click **Save**, and then click **Next**

This is an example of the Additional Install Processes form, where the Executable Name is wininstall_silent.bat and the Source Path is \\ldcnts5\E810\OneWorld Client Install\ThirdParty\WebServicesGateway:

Additional Install Processes form

7. On the next form, click **End**.
8. On the Work with Feature form, click **Close**.

Creating a Package

► To create a package

1. On the Work with Packages form, Click **Add**.
2. On the Package Assembly Director form, click **Next**.
3. On the Package Information form, enter values for Package Name, Description, and Path Code, and then click **Next**.

This example shows how to complete the Package Information form:

Appendix B: Building a Web Services Gateway Developer Package

Package Assembly - [Package Information]

File Edit Preferences Form Window Help

OK Can... Next Dis... Abo Links Next OLE... Internet

To begin, enter basic information about your package.

Give the package a unique name, a meaningful description, and the Path Code with which it is associated.

The Express Option determines if you go through the Package Assembly Director or right to the Assembly Revisions Form.

Express Option


Director

Express

Package Name

Description

Path Code 



Package Information form


4. On the Package Type Selection form, select Update, Include Object Specifications (for client packages only), enter a value for Parent Package, and then click **Next**.

Package Type Selection form

5. On the Foundation Component form, click **Next**.
6. On the Help Component form, click **Next**.
7. On the Database Component form, click **Next**.
8. On the Object Component form, click **Next**.
9. On the Feature Component form, click **Browse**.

- From the Feature Component Selection form, select **FEATURE** and then click **Close**.

This example shows the Feature column containing the **FEATURE** record:



Feature Component Selection form

- On the next form, click **Next**.
- On the Language Component form, click **Next**.

13. On the Package Component Revisions form, click **End**.

This is an example of the Package Component Revisions form:

The screenshot shows the 'Package Component Revisions' dialog box. At the top, there is a toolbar with buttons: OK, Can..., Prev..., Next, End, Dis..., and Abo. To the right of the toolbar are 'Links', 'Set D...', 'OLE ...', and 'Internet'. The main area contains the following fields and options:


- Package Name: PACKNAME
- Path Code: DV811
- Radio buttons: Full, Update
- Checkbox: Build Mobile Client Package
- Parent Package: DV811FA
- Foundation: No Foundation Selected
- Database: No Database Selected
- Objects: No Objects Selected
- Features: Individual Features Selected
- Language: Default
- Mobile Client Database(s): Disconnected Databases ()

Package Component Revisions form

14. On the Work with Packages form, select **Define Build** from the Row Exit Menu.

15. On the Package Build Definition form, click **Next**.

16. On this Package Build Location form, click **Next**:



The screenshot shows a web browser window titled "Package Assembly - [Package Build Location]". The browser's address bar contains "Links", "Previo...", "OLE...", and "Internet". The page content includes the following elements:

- Text: "You have selected the following package to build. To begin, indicate if you are building this package for the client and/or a server."
- Text: "The Express Option determines if you go through the Package Build Director or right to the Build Revisions form."
- Form fields:
 - Package Name: A text box containing "PACKAGEN" followed by the text "test".
 - Path Code: A text box containing "DV810".
- Radio buttons for "Express Option":
 - Client
 - Server(s)
 - Director
 - Express
- Illustration: A 3D-style illustration of a brown cardboard box with a white wrench and a white gear, set against a light blue and green background.

Package Build Location form

17. On the Build Specification Options form, click **Next**.

18. On this Build Features form, select Build Feature INFs and click **Next**:

Package Assembly - [Build Features]

File Edit Preferences Form Window Help

Find Close Beg... New... Prev... Next Dis... Abo Links View... OLE... Internet

Indicate whether to build the Feature.INF files with this package. If building Feature.INF files, indicate which file sets to compress and which process to run.

Package Name test

Path Code

Build Feature INFs

Compress

Build

Compress File Sets


Build Processes

Build Features form

Appendix B: Building a Web Services Gateway Developer Package

19. On the Package Build Revisions form, click **End**.

20. On the Work With Package Build Definition form, enter values for Package Name and Path code, and then click **Find**.




Work With Package Definition form

21. From the in Row Exit Menu, click **Submit Build**.

22. On the Report Output Destination form, click **OK**.

A PDF is generated and the “Build Created Successfully” message is displayed.

This is an example of the Report Output Destination form:



Report Output Destination form

23. On the Work With Package Build Definition form, select the Row Exit Menu and then click **Deployment**.


24. On the Package Deployment Director form, click **Next**.

25. On the Package Deployment Targets form, select Client Workstation, and then click **Next**:

This is an example of the Package Deployment Targets form:

Package Deployment form

26. On the Package Deployment Attributes form, select Mandatory Installation, and then click **Next**.



Indicate if installation of this package is mandatory, and if it should be pushed to package recipients from the deployment server.

You may indicate the date and time the package should be deployed. If the date and time are left blank, the package will become available immediately.

Package Name test

Path Code

Mandatory Installation

Enable Push Installation

Date/Time

The illustration on the right depicts a central server box with five lines radiating downwards to five desktop computer icons, representing a distribution or deployment process.

Package Deployment Attributes form

27. On the Deployment Client Workstation Selection form, find and select the client workstation, and then click **Close**.

Select the client workstations that should receive the package.

Package Name: test

Path Code:

Client Workstation	Description
<input checked="" type="checkbox"/> BNG-PSFT471	BNG-PSFT471 - PSFT

Select record Row:1

Development Client Workstation Selection form

28. On the Work with Package Build Definition form, click **Close**.
29. On the Work with Package form, click **Close**.

Appendix C: Determining the version of Integration Server components

The ptf.log file contains the version information of Integration Server components developed by JD Edwards. This log file can be found in the pub folder of each package. For example, the EnterpriseOne Adapter ptf.log file resides in directory `<WSG_Install_Directory>\IntegrationServer\packages\PSFT_E1_Adapter\pub`, and the Configuration Editor ptf.log file resides in directory `<WSG_Install_Directory>\IntegrationServer\packages\PSFT_ConfigurationEditor\pub`.