

webMethods EntireX

EntireX RPC Server for IBM® AS/400®

Version 10.3

October 2018

This document applies to webMethods EntireX Version 10.3 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 1997-2018 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://softwareag.com/licenses>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://softwareag.com/licenses/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software AG.

Document ID: EXX-AS4RPC-103-20191129

Table of Contents

1 About this Documentation	1
Document Conventions	2
Online Information and Support	2
Data Protection	3
2 Introduction to the RPC Server for AS/400	5
Overview	6
Post-installation Steps	6
Worker Models	7
3 Administering the RPC Server for AS/400	9
Customizing the RPC Server	10
Configuring the RPC Server Side	12
Configuring the IBM AS/400 Side	14
Using SSL/TLS with the RPC Server	15
Starting the RPC Server	17
Stopping the RPC Server	17
Running an EntireX RPC Server as a Windows Service	17
Application Identification	18

1 About this Documentation

- Document Conventions 2
- Online Information and Support 2
- Data Protection 3

Document Conventions

Convention	Description
Bold	Identifies elements on a screen.
Monospace font	Identifies service names and locations in the format <i>folder.subfolder.service</i> , APIs, Java classes, methods, properties.
<i>Italic</i>	Identifies: Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies: Text you must type in. Messages displayed by the system. Program code.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the symbol.
[]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

Online Information and Support

Software AG Documentation Website

You can find documentation on the Software AG Documentation website at <http://documentation.softwareag.com>. The site requires credentials for Software AG's Product Support site Empower. If you do not have Empower credentials, you must use the TECHcommunity website.

Software AG Empower Product Support Website

If you do not yet have an account for Empower, send an email to empower@softwareag.com with your name, company, and company email address and request an account.

Once you have an account, you can open Support Incidents online via the eService section of Empower at <https://empower.softwareag.com/>.

You can find product information on the Software AG Empower Product Support website at <https://empower.softwareag.com>.

To submit feature/enhancement requests, get information about product availability, and download products, go to [Products](#).

To get information about fixes and to read early warnings, technical papers, and knowledge base articles, go to the [Knowledge Center](#).

If you have any questions, you can find a local or toll-free number for your country in our Global Support Contact Directory at https://empower.softwareag.com/public_directory.asp and give us a call.

Software AG TECHcommunity

You can find documentation and other technical information on the Software AG TECHcommunity website at <http://techcommunity.softwareag.com>. You can:

- Access product documentation, if you have TECHcommunity credentials. If you do not, you will need to register and specify "Documentation" as an area of interest.
- Access articles, code samples, demos, and tutorials.
- Use the online discussion forums, moderated by Software AG professionals, to ask questions, discuss best practices, and learn how other customers are using Software AG technology.
- Link to external websites that discuss open standards and web technology.

Data Protection

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.

2 Introduction to the RPC Server for AS/400

- Overview 6
- Post-installation Steps 6
- Worker Models 7

Overview

The RPC Server for AS/400 acts on one side as an RPC server and on the other side as a client for calling AS/400 server programs.



For local extraction, all source files have to be stored locally on the same machine where the Designer is running. For existing AS/400 programs, use the *Software AG IDL Extractor for COBOL* to extract the *Software AG IDL File* in the IDL Editor documentation for the RPC clients.


Post-installation Steps

After installation of EntireX, the EntireX RPC Server for IBM® AS/400® cannot be started successfully. To access the AS/400 system you need the IBM ToolBox for Java (JTOpen).

➤ To download and install the IBM ToolBox for Java

- 1 From <http://jt400.sourceforge.net/>, click **Downloads**. From <https://sourceforge.net/projects/jt400/>, select the latest version.
- 2 From the downloaded zip file, extract the file `lib/java8/jt400.jar`.
- 3 Copy the file `jt400.jar` to directory `EntireX/Classes`.

Worker Models



RPC requests are worked off inside the RPC server in worker threads. Every RPC request occupies during its processing a worker thread. If you are using RPC conversations, each RPC conversation requires its own thread during the lifetime of the conversation. The RPC Server for AS/400 can adjust the number of worker threads to the number of parallel requests. The RPC server provides two worker models:

- **FIXED**
The *fixed* model creates a fixed number of worker threads. The number of worker threads does not increase or decrease during the lifetime of an RPC server instance.
- **DYNAMIC**
The *dynamic* model creates worker threads depending on the incoming load of RPC requests.

For configuration and technical details, see property `entirex.server.fixedservers` under *Administering the RPC Server for AS/400*.

3 Administering the RPC Server for AS/400

- Customizing the RPC Server 10
- Configuring the RPC Server Side 12
- Configuring the IBM AS/400 Side 14
- Using SSL/TLS with the RPC Server 15
- Starting the RPC Server 17
- Stopping the RPC Server 17
- Running an EntireX RPC Server as a Windows Service 17
- Application Identification 18

The EntireX RPC Server for IBM® AS/400® enables you to remotely call server programs written in all ILE-based languages, for example C, COBOL, RPG.

This chapter describes how to administer the RPC Server for AS/400.

Customizing the RPC Server

The following are used to set up the RPC Server for AS/400:


- [Configuration File](#)
- [Start Script](#)

Configuration File

The default name of the configuration file is *entirex.as400.properties*. The RPC Server for AS/400 searches for this file in the current working directory.

You can set the name of the configuration file with `-Dentirex.server.properties=<your file name>` with `/` as file separator.

The configuration file contains the configuration for both parts of the RPC Server for AS/400.



Configuring more than one RPC Server

If you configure more than one RPC Server for AS/400 that connect to the same broker, the following items must be distinct:

- the trace output file (property `entirex.server.logfile`)
- the log for the Windows Service (property `entirex.server.serverlog`)

Start Script

The start script for the RPC Server for AS/400 is called *as400server.bsh* (UNIX) or *as400server.bat* (Windows) and is provided in the *bin* folder of the installation directory. You may customize this file. The RPC Server for AS/400 itself is contained in the file *entirex.jar*.

Configuring the RPC Server Side

The RPC Server for AS/400 uses the properties that start with “`entirex.server`” for configuring the RPC server side.

Alternatively to the properties, you can use the command-line options. These have a higher priority than the properties set as Java system properties, and these have higher priority than the properties in the configuration file.

Property Name	Command-line Option	Default	Explanation
<code>entirex.server.brokerid</code>	<code>-broker</code>	<code>localhost</code>	Broker ID. See <i>URL-style Broker ID</i> in the EntireX Broker ACI Programming documentation.
<code>entirex.server.serveraddress</code>	<code>-server</code>	<code>RPC/SRV1/CALLNAT</code>	Server address.
<code>entirex.server.userid</code>	<code>-user</code>	<code>AS400RPCServer</code>	The user ID for access to the broker.
<code>entirex.server.fixedservers</code>		<code>no</code>	<p>NO The number of worker threads balances between what is specified in <code>entirex.server.minservers</code> and what is specified in <code>entirex.server.maxservers</code>. This is done by a so-called attach thread. At startup, the number of worker threads is the number specified in <code>entirex.server.minservers</code>. A new worker thread starts if the broker has more requests than there are worker threads waiting. If more than the number specified in <code>entirex.server.minservers</code> are waiting for requests, a worker thread stops if its receive call times out. The timeout period is configured with <code>entirex.server.waitserver</code>. See worker model DYNAMIC.</p> <p>YES The number of worker threads specified in <code>entirex.server.minservers</code> is started and the server can process this number of parallel requests. See worker model FIXED.</p>
<code>entirex.server.minservers</code>		<code>1</code>	Minimum number of server threads.

Property Name	Command-line Option	Default	Explanation
entirex.server.maxservers		32	Maximum number of server threads.
entirex.server.restartcycles	-restartcycles	15	Number of restart attempts if the Broker is not available. This can be used to keep the RPC Server for AS/400 running while the Broker is down for a short time.
entirex.server.password	-password		The password for secured access to the broker. The password is encrypted and written to the property <code>entirex.server.password.e</code> . To change the password, set the new password in the properties file. To disable password encryption, set <code>entirex.server.passwordencrypt=no</code> . Default: yes.
entirex.server.security	-security	no	no yes auto name of BrokerSecurity object
entirex.server.compresslevel	-compresslevel	0	Permitted values (you can enter the text or the numeric value) BEST_COMPRESSION 9 BEST_SPEED 1 DEFAULT_COMPRESSION -1, mapped to 6 DEFLATED 8 NO_COMPRESSION 0 N 0 Y 8
entirex.server.waitattach		600S	Wait timeout for the attach server thread.
entirex.server.waitserver		300S	Wait timeout for the worker threads.
entirex.timeout		20	TCP/IP transport timeout. See <i>Setting the Transport Timeout</i> under <i>Writing Advanced Applications - EntireX Java ACI</i> .
	-help		Display usage of the command-line parameters.
entirex.server.logfile	-logfile		Name of the log file, default is standard output.
entirex.trace	-trace	0	Trace level (1,2,3).

Configuring the IBM AS/400 Side

These properties are used to configure the connection to AS/400.

Name	Default Value	Explanation
as400.host		Host name of AS/400 system (IBM i). Mandatory.
as400.programpath	/QSYS.LIB/%library%.LIB/%program%.PGM	The fully qualified integrated file system path name to the program. %library% is replaced by the IDL file library name and %program% is replaced by the IDL file program name. The library and program name must each be 10 characters or less.
entirex.bridge.targetencoding	cp037	Specify the appropriate EBCDIC encoding which corresponds to the CCSID (Coded Character Set Identifier) of your AS/400 system. This codepage is also used when communicating with the EntireX Broker. Enable character conversion in the broker by setting the service-specific attribute CONVERSION to

Name	Default Value	Explanation
		<p>"SAGTRPC". See also <i>Configuring ICU Conversion</i> under <i>Configuring Broker for Internationalization</i> in the platform-specific Administration documentation. More information can be found under <i>Internationalization with EntireX</i>.</p> <p>Default "cp037" is EBCDIC codepage with full Latin-1 character set.</p>
as400.timeout	50	Maximum time to run the program in seconds.
as400.userid		The user profile name to use to authenticate to the system.
as400.password		The user profile password to use to authenticate to the system.

Using SSL/TLS with the RPC Server

To use SSL with the RPC Server for AS/400, you need to configure the RPC Server Side.

RPC servers can use Secure Sockets Layer/Transport Layer Security (SSL/TLS) as the transport medium. The term "SSL" in this section refers to both SSL and TLS. RPC-based servers are always SSL clients. The SSL server can be either the EntireX Broker or Broker SSL Agent. For an introduction see *SSL/TLS and Certificates with EntireX* in the Platform-independent Administration documentation.

> To use SSL

- 1 To operate with SSL, certificates need to be provided and maintained. Depending on the platform, Software AG provides default certificates, but we strongly recommend that you create your own. See *SSL/TLS Sample Certificates Delivered with EntireX* in the EntireX Security documentation.
- 2 Set up the RPC Server for AS/400 for an SSL connection.

Use the *URL-style Broker ID* with protocol `ssl://` for the Broker ID. If no port number is specified, port 1958 is used as default. Example:

```
ssl://localhost:22101?trust_store=C:\SoftwareAG\EntireX\etc\ExxCACert.jks&verify_server=no
```

If the SSL client checks the validity of the SSL server only, this is known as *one-way SSL*. The mandatory `trust_store` parameter specifies the file name of a keystore that must contain the list of trusted certificate authorities for the certificate of the SSL server. By default a check is made that the certificate of the SSL server is issued for the hostname specified in the Broker ID. The common name of the subject entry in the server's certificate is checked against the hostname. If they do not match, the connection will be refused. You can disable this check with SSL parameter `verify_server=no`.

If the SSL server additionally checks the identity of the SSL client, this is known as *two-way SSL*. In this case the SSL server requests a client certificate (the parameter `verify_client=yes` is defined in the configuration of the SSL server). Two additional SSL parameters must be specified on the SSL client side: `key_store` and `key_passwd`. This keystore must contain the private key of the SSL client. The password that protects the private key is specified with `key_passwd`.

The ampersand (&) character cannot appear in the password.

SSL parameters are separated by ampersand (&). See also *SSL/TLS Parameters for SSL Clients*.

- 3 Make sure the SSL server to which the RPC side connects is prepared for SSL connections as well. The SSL server can be EntireX Broker or Broker SSL Agent. See:
 - *Running Broker with SSL/TLS Transport* in the platform-specific Administration documentation
 - *Setting up and Administering the EntireX Broker SSL Agent* in the UNIX and Windows Administration documentation

Starting the RPC Server

➤ To start the RPC Server for AS/400

- Use the *Start Script*.

Or:

Under Windows you can use the RPC Server for AS/400 as a Windows Service. See [Running an EntireX RPC Server as a Windows Service](#).

Stopping the RPC Server

➤ To stop the RPC Server for AS/400

- Use the command-line utility `etbcmd`. See `ETBCMD` under *Broker Command-line Utilities* in the platform-specific Administration documentation.

Or:

Use `CTRL-C` in the session where you started the RPC server instance.

Or:

Under UNIX, enter command `kill -process-id`.

Running an EntireX RPC Server as a Windows Service

For general information see [Running an EntireX RPC Server as a Windows Service](#).

➤ To run the RPC Server for AS/400 as a Windows Service

- 1 Customize the *Start Script* according to your system installation.



Note: The script must pass external parameters to the RPC server and use the reduced signaling of the JVM (option `-Xrs`):

```
java -Xrs com.softwareag.entirex.as400bridge.AS400RPCServer %*
```

If `-Xrs` is not used, the JVM stops and an entry 10164002 is written to the event log when the user logs off from Windows.

See also [Starting the RPC Server](#).

- 2 Test your RPC server to see whether it will start if you run your script file.
- 3 Use the *EntireX RPC Service Tool* and install the `RPCService` with some meaningful extension, for example `MyServer`. If your *Start Script* is `as400server.bat`, the command will be

```
RPCService -install -ext MyServer -script install_path\EntireX\bin\as400server.bat
```

The log file will be called `RPCservice_MyServer.log`.

- 4 In **Windows Services** menu (**Control Panel** > **Administrative Tools** > **Services**) select the service: `Software AG EntireX RPC Service [MyServer]` and change the property `Startup Type` from "Manual" to "Automatic".

Application Identification

The application identification is sent from the RPC Server for AS/400 to the Broker. It is visible with `Broker Command` and `Information Services`.

The identification consists of four parts: name, node, type, and version. These four parts are sent with each `Broker` call and are visible in the trace information.

For the RPC Server for AS/400, these values are:

Identification Part	Value
Application name	ANAME=RPC Server for IBM® AS/400®
Node name	ANODE=<host name>
Application type	ATYPE=Java
Version	AVERS=10.3.0.0