

# Using Digital Event Services to Communicate between Software AG Products

Innovation Release

Version 10.0

April 2017

---

This document applies to Software AG Product Suite Version 10.0 and to all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 2016-2017 Software AG, Darmstadt, Germany and/or Software AG USA Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://softwareag.com/licenses>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software AG.

# Table of Contents

<b>About this Guide.....</b>	<b>5</b>
Document Conventions.....	5
Online Information.....	6
<b>Understanding Digital Event Services.....</b>	<b>7</b>
Digital Event Services Overview.....	8
Support of Digital Event Services.....	8
The Digital Event Type Model.....	9
Delivery Modes for Digital Event Services.....	9
Store-and-Forward Processing.....	9
Messaging Services and Service Groups.....	10
Storing Digital Events Using Event Persistence.....	10
<b>Administering Digital Event Services.....</b>	<b>13</b>
About Administering Digital Event Services.....	14
Configuring Services.....	14
Configuring Universal Messaging Services.....	15
Configuring Event Persistence Services.....	15
Configuring Event Persistence Services for Elasticsearch.....	16
Configuring Event Persistence Services for HDFS.....	18
Using the In-Process Service.....	20
Configuring Service Groups.....	20
Configuring the Default Service Group.....	20
Configuring Custom Service Groups.....	21
Configuring Event Type Associations.....	23
Configuring Storage Settings for Digital Event Services.....	25
Monitoring Digital Event Services.....	27
Secure Password Handling.....	28
Changing the Master Password.....	28
Lifecycle Actions for Digital Event Services.....	29
Considerations for Deploying Digital Event Types.....	29
Digital Event Services Licensing.....	29
Performance Considerations on Linux.....	30
<b>Configuring Digital Event Services Using Composite Templates.....</b>	<b>31</b>
About Configuring Digital Event Services with Command Central Composite Templates.....	32
Configuring DES for a Single Runtime Instance.....	32
Configuring DES for Multiple Runtime Instances within a Single Installation.....	33
Configuring DES for a Set of Installations.....	34
Creating and Configuring a DES Runtime Instance.....	36
Creating an Event Persistence Service Using Composite Templates.....	37
Updating an Event Persistence Service Using Composite Templates.....	40

---

<b>Digital Event Services MBeans.....</b>	<b>43</b>
Event Type Information MBean.....	44
Universal Messaging Service MBean.....	44
Queue MBean.....	48
Subscriber MBean.....	49
<b>Using Event Persistence.....</b>	<b>53</b>
Using HDFS with Event Persistence.....	54
Configuring SSL for Event Persistence.....	54
SSL Enablement for Elasticsearch.....	54
SSL Enablement for Event Data Store.....	55
Enabling SSL for Event Data Store.....	55
Disabling SSL for Event Data Store.....	55

---

## About this Guide

---

This document gives you an overview of Digital Event Services, which is Software AG's tool for managing simple event-based interactions.

The goal of Digital Event Services is to facilitate the integration between Software AG products and applications by easily allowing them to communicate.

## Document Conventions

---

Convention	Description
<b>Bold</b>	Identifies elements on a screen.
Narrowfont	Identifies storage locations for services on webMethods Integration Server, using the convention <i>folder.subfolder:service</i> .
UPPERCASE	Identifies keyboard keys. Keys you must press simultaneously are joined with a plus sign (+).
<i>Italic</i>	Identifies variables for which you must supply values specific to your own situation or environment. Identifies new terms the first time they occur in the text.
Monospace font	Identifies text you must type or messages displayed by the system.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the   symbol.
[ ]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [ ] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

---

## Online Information

---

### Software AG Documentation Website

You can find documentation on the Software AG Documentation website at "<http://documentation.softwareag.com>". The site requires Empower credentials. If you do not have Empower credentials, you must use the TECHcommunity website.

### Software AG Empower Product Support Website

You can find product information on the Software AG Empower Product Support website at "<https://empower.softwareag.com>".

To submit feature/enhancement requests, get information about product availability, and download products, go to "[Products](#)".

To get information about fixes and to read early warnings, technical papers, and knowledge base articles, go to the "[Knowledge Center](#)".

### Software AG TECHcommunity

You can find documentation and other technical information on the Software AG TECHcommunity website at "<http://techcommunity.softwareag.com>". You can:

- Access product documentation, if you have TECHcommunity credentials. If you do not, you will need to register and specify "Documentation" as an area of interest.
- Access articles, code samples, demos, and tutorials.
- Use the online discussion forums, moderated by Software AG professionals, to ask questions, discuss best practices, and learn how other customers are using Software AG technology.
- Link to external websites that discuss open standards and web technology.

# 1 Understanding Digital Event Services

---

■ Digital Event Services Overview .....	8
■ Support of Digital Event Services .....	8
■ The Digital Event Type Model .....	9
■ Delivery Modes for Digital Event Services .....	9
■ Store-and-Forward Processing .....	9
■ Messaging Services and Service Groups .....	10
■ Storing Digital Events Using Event Persistence .....	10

## Digital Event Services Overview

---

Digital Event Services (DES) enables other Software AG products to intercommunicate by exchanging *digital events*. Digital events are typed and serialized data structures that are used to convey or record information about the execution of a runtime. This information can be application information, such as the state of a business process step, including any associated business data, or it can be system information, for example, how much memory and how many threads an application is using.

Any digital event has a *digital event type*. Each digital event type has an associated *digital event type definition* that is created and stored in the digital event type repository for the installation. Digital event types are created by users in a development environment, and subsequently deployed to production installations. The format of the events is based on Google Protocol Buffers. For more information about the digital event type model, see [“The Digital Event Type Model” on page 9](#).

Digital Event Services uses the *publish-subscribe* model. Applications can both *emit* and *subscribe to* streams of events of a given event type. When publishing a digital event, the originating application *emits* the event without considering whether other applications might receive the event, or whether the event might be archived to an event repository. On the other hand, applications that are consumers of events subscribe to digital events of a specific event type.

The destinations, also known as *destination services*, to which events are routed, are not defined at design time. Instead, a system administrator manages the destination services at run time. For more information about services, see [“Messaging Services and Service Groups” on page 10](#).

Communication using Digital Event Services can be *persistent* or *non-persistent*. With persistent communication, the delivery of a digital event is guaranteed at least once. With non-persistent communication, the delivery of a digital event is not guaranteed.

A developer may set the *delivery preference* for a given event type, but the DES administrator controls the final *delivery mode*. For more information about delivery modes for Digital Event Services, see [“Delivery Modes for Digital Event Services” on page 9](#).

## Support of Digital Event Services

---

Digital Event Services (DES) is used for communication only between webMethods Integration Server, Apama, and MashZone NextGen Business Analytics. You cannot use DES with other Software AG products. For more information about how to use DES from the perspective of the listed products, see the product documentation of the adopting products.



## The Digital Event Type Model

---

Any digital event has a *digital event type*. A digital event type is a high-level definition of the event format that is independent of the underlying over-the-wire representation of an event. The event type model is designed to support an easy conversion of an event type into other Software AG type languages, such as Integration Server Document Type and Apama Event Processing Language.

For more information about the mapping of events from Integration Server and Apama to Digital Event Services, see *webMethods Integration Server Administrator's Guide* and *Connecting Apama Applications to External Components*, respectively.

## Delivery Modes for Digital Event Services

---

Digital Event Services enables an administrator to set a delivery mode per event type. The delivery mode setting governs the quality of service if the DES runtime stops responding and becomes unavailable.

Digital events are stored in-memory or on-disk until their delivery is acknowledged. To ensure that at least one copy of an event is delivered, administrators can define the event type delivery mode as *Persistent*. This means that the events of an event type are stored on-disk. If the runtime where DES is embedded becomes unavailable, the events are resent the next time the runtime starts.

If the delivery mode for an event type is *Non-persistent*, events are stored in-memory. If the runtime where DES is embedded becomes unavailable events are not resent.

For information about how to configure delivery mode per event type, see [“Configuring Event Type Associations” on page 23](#). Administrators can define on-disk and in-memory capacity globally and per event type. For more information about configuring in-memory and on-disk capacity, see [“Configuring Storage Settings for Digital Event Services” on page 25](#).

## Store-and-Forward Processing

---

Instead of directly delivering each event to the configured destination services and waiting for each service to acknowledge the event, Digital Event Services (DES) stores the event in an internal queue.

Depending on the delivery mode setting defined for each event type in Command Central, the queue can be held in-memory or on-disk. After an event is added to the queue, DES is ready to accept new events. In the meantime, the queued events are delivered to their destination services by a separate thread in the order in which they were added to the queue.

For more information about how to configure delivery mode per event type, see [“Configuring Event Type Associations” on page 23](#).

## Messaging Services and Service Groups

---

Messaging services are endpoints where events are published. Depending on your application's capabilities to emit or subscribe to events, you can tag the messaging service as either a destination, a source, or both. Digital Event Services (DES) supports the following service types:

- **Universal Messaging services** - use services of this type to send events to or receive events from a Universal Messaging server realm or cluster.
- **Event Persistence services** - use services of this type to send events to an Event Persistence destination.
- **In-Process service** - use this pre-configured service to send and receive events within the same server runtime.

Services are grouped together as a set of one or more services to which events can be sent. One of the services in a service group can be tagged as the source of events for all event types associated with the service group.

Each Digital Event Services runtime contains a default service group, which is sufficient for most use cases. However, you can also define a custom service group for a particular runtime.

For more information about how to configure services, see [“Configuring Services” on page 14](#). For more information about how to group those services together, see [“Configuring Service Groups” on page 20](#).

### Considerations when Using Service Groups

- If a service group contains no source service and your application creates a subscription for this service group, no events are received. The subscription remains inactive until a source service is configured.
- If an application emits events to a service group that has no destination service configured, then the emitted events are not received anywhere.
- Administrators can create a service group that contains no services for troubleshooting purposes.

## Storing Digital Events Using Event Persistence

---

webMethods Event Persistence is a unified model for storing digital events regardless of the underlying storage technology. With Event Persistence, you can persist event instances sent to and from Digital Event Services to an event store. The event store is

not a transactional or analytic database, but a system of record that supports long-term, high-volume storage.

You use webMethods Event Persistence through the Event Persistence service type for Digital Event Services. You can configure Event Persistence services to persist all instances of a digital event type to an event store within a storage system. Event Persistence supports the following storage technologies:

- Elasticsearch 2.3.2
- Apache Hadoop Distributed File System and Hive, Cloudera distribution (HDFS CDH) 5.3.0

For more information about how to create and configure Event Persistence services, see “[Configuring Event Persistence Services](#)” on page 15.



---

## 2 Administering Digital Event Services

---

■ About Administering Digital Event Services .....	14
■ Configuring Services .....	14
■ Configuring Service Groups .....	20
■ Configuring Event Type Associations .....	23
■ Configuring Storage Settings for Digital Event Services .....	25
■ Monitoring Digital Event Services .....	27
■ Secure Password Handling .....	28
■ Lifecycle Actions for Digital Event Services .....	29
■ Considerations for Deploying Digital Event Types .....	29
■ Digital Event Services Licensing .....	29
■ Performance Considerations on Linux .....	30

---

## About Administering Digital Event Services

---

You can administer Digital Event Services, using the Command Central web user interface, composite templates, or command line interface.

**Note:** Integration Server and Apama developers can also use the Digital Event Services command line tool to configure messaging connectivity without using Command Central. Developers can open a command line prompt and type `java -jar` followed by `Software AG_directory\common\lib\events-configuration-tool.jar` to run the utility.

To administer Digital Event Services within your Software AG installation, you need to have installed the Platform Manager plug-ins for:

- Digital Event Services
- Integration Server
- Apama
- MashZone NextGen Business Analytics

Using Command Central, you can perform the following operations:

- Configure messaging services and service groups.
- Configure event type associations.
- Configure storage settings for digital events.

**Important:** Do not edit configuration files manually.

For information about using composite templates to configure Digital Event Services, see [“Configuring Digital Event Services Using Composite Templates” on page 31](#). For information about using Command Central CLI commands, see *Software AG Command Central Help*.

---

## Configuring Services


---

Digital Event Services (DES) provides a default Universal Messaging service, which you can modify or delete, and a pre-defined In-Process service. In addition, you can create, modify, and delete custom Universal Messaging and Event Persistence services, using Command Central.

## Configuring Universal Messaging Services

You can create and configure services of Universal Messaging type, add them to groups, and associate event types to them.

**To configure a Universal Messaging service:**

1. In Command Central, navigate to **Environments > Instances > All > *instance\_name* > Digital Event Services > Configuration**.
2. Select **Messaging Services** from the drop-down menu, and then click .
3. Specify values for the following fields:

Field	Description
<b>Service Name</b>	Required. A unique name for the service. The service name is not case-sensitive, and must start with a character. You can use the following characters as separators: . (dot) and - (dash).
<b>Description</b>	Required. A description of the purpose of the service.
<b>Provider URL</b>	Required. The host and port of the Universal Messaging server to which the service connects. The default value is <code>nsp://localhost:9000</code> .

**Important:** You cannot rename existing services. If you want to modify a service name, you must delete the existing service and create a new one with a different name.

Before deleting a service, you must first remove it from any service groups to which the service belongs.

4. Optionally, click **Test** to verify that your configuration is valid.

**Note:** The validation is done on a field level, and checks whether the specified configuration information complies with the field requirements. This action will not ping a server to verify that a connection is possible. It only checks if the port number is available.

5. Save your changes.

## Configuring Event Persistence Services

You can create and configure Event Persistence services that use Hadoop Distributed File System (HDFS) and Elasticsearch as storage engines.


## Configuring Event Persistence Services for Elasticsearch

With Event Persistence services, you can store events to an Elasticsearch 2.3.2 storage engine.

**Note:** Event Persistence does not support Elasticsearch clusters with Shield enabled.

When using Elasticsearch, you can persist events using Secure Socket Layer (SSL). For more information about persisting events over SSL to an Elasticsearch instance, see [“Configuring SSL for Event Persistence” on page 54](#).

### To create Digital Event Services (DES) services of type Event Persistence for Elasticsearch:

1. In Command Central, navigate to **Environments > Instances > All > *instance\_name* > Digital Event Services > Configuration**.
2. Select **Event Persistence** from the drop-down menu.
3. Click , and then select **Elasticsearch 2.3.2** for the service type.
4. Specify values for the following fields:

Parameter	Description
<b>Service Name</b>	<p>Required. The name of the new service. Specify a unique service name that starts with a character. Valid separator characters are periods (.) and dashes (-). The service name is not case-sensitive.</p> <p><b>Note:</b> You cannot rename an existing service. If you want to modify the service name, you must delete the existing service and create a new one with a different name.</p>
<b>Service Description</b>	Optional. A description of the new service.
<b>Cluster URI(s)</b>	<p>Required. A comma-separated list of servers in an Elasticsearch cluster to which the Event Persistence service can connect. If the initial host is unavailable, Event Persistence attempts to connect to the other servers in the cluster. Specify the URI of the servers in the Elasticsearch cluster as follows: <code>elasticsearch://host:port</code>, where <i>host</i> is the host name of the server, and <i>port</i> is the port on which the server listens for incoming requests.</p> <p>The default value is <code>elasticsearch://localhost:9300</code>.</p>



Parameter	Description
<b>Cluster Name</b>	Required. The name of the Elasticsearch cluster.
<b>Index Name</b>	Required. The name of the index in which the events are stored.
<b>Core threads</b>	Required. The number of threads to keep in the pool at all times. The default value is 5.
<b>Maximum Threads</b>	Required. The maximum number of threads on which to run bulk indexing tasks. The default value is 10.
<b>Queue Size</b>	Required. The size of the thread pools work queue. A value of 0 indicates an unlimited queue. A value other than 0 sets the number of pending bulk indexing tasks that can be queued before the processing thread blocks. The default value is 10.
<b>Keep Alive(sec)</b>	Required. The time limit in seconds for which threads remain idle before being terminated. The default value is 5.
<b>Pre-Start Core Threads</b>	Required. Whether the core threads start immediately rather than as work is pulled from the queue. Values are <code>true</code> or <code>false</code> (default).
<b>Batch Size</b>	Required. The number of events that are written to Elasticsearch with a single write operation. The default value is 1000.  <b>Note:</b> If the Elasticsearch service queues a batch of events before the batch write timer expires, the service immediately persists all queued events to Elasticsearch.
<b>Batch Write Timer(sec)</b>	Required. Batch write frequency in seconds. The default value is 15.  <b>Note:</b> If the batch write timer expires before the Elasticsearch service queues a batch of events, all currently queued events are persisted to Elasticsearch.

Parameter	Description
<b>Enable SSL</b>	Required. Enable or disable SSL for both REST and TCP ports. The default value is <code>false</code> .  For more information about how to configure SSL for Event Persistence, see <a href="#">“Configuring SSL for Event Persistence”</a> on page 54.
<b>Key Store</b>	Optional. Specify the absolute file path to the Java KeyStore (JKS) file as follows: <i>folder/sub_folder/filename.</i>
<b>Trust Store</b>	Optional. Specify the absolute file path to the JKS truststore file as follows: <i>folder/sub_folder/filename.</i>

- Optionally, click **Test** to verify that your configuration is valid.
- Save your changes.

## Configuring Event Persistence Services for HDFS

With Event Persistence services, you can store events to an Apache Hadoop Distributed File System and Hive, Cloudera distribution (HDFS CDH) 5.3.0 storage engine.

To use HDFS as the storage engine for Event Persistence, you must first configure the Hadoop cluster by deploying the custom Hive SerDe and Joda Date/Time libraries from your Event Persistence installation. For more information about how to configure HDFS for use with Event Persistence services, see [“Using HDFS with Event Persistence”](#) on page 54.

### To create Digital Event Services services of type Event Persistence for HDFS:

- In Command Central, navigate to **Environments > Instances > All > *instance\_name* > Digital Event Services > Configuration**.
- Select **Event Persistence** from the drop-down menu.
- Click **+**, and then select **HDFS CDH 5.3.0** for the service type.
- Specify values for the following fields:

Parameter	Description
<b>Service Name</b>	Required. The name of the new service. Specify a unique service name that starts with a character. Valid separator characters are periods (.) and dashes (-). The service name is not case-sensitive.

Parameter	Description
	<p><b>Note:</b> You cannot rename an existing service. If you want to modify the service name, you must delete the existing service and create a new one with a different name.</p>
<b>Service Description</b>	Optional. A description of the new service.
<b>Name Node URI</b>	Required. The URI of the Name Node in the HDFS cluster as follows: <code>hdfs://host:port</code> , where <i>host</i> is the host name of the server, and <i>port</i> is the port on which the server listens for incoming requests. The default value is <code>hdfs://localhost:8020</code> .
<b>Maximum File Size(MB)</b>	Required. The HDFS block size in megabytes. The default value is 65.
<b>Hive Server URI</b>	Required. Specify the URI of the Apache Hive Server as follows: <code>jdbc:hive2://host:port</code> , where <i>host</i> is the host name of the server, and <i>port</i> is the port on which the server listens for incoming connection requests. The default value is <code>jdbc:hive2://localhost:10000</code> .
<b>Database</b>	Required. The name of the Hive database.
<b>Warehouse Location</b>	Required. The location of the Hive warehouse. The default value is <code>/user/hive/warehouse</code> .
<b>User Id</b>	Required. The username for the Hive user account.
<b>Password</b>	Required. The password for the Hive user account.
<b>Batch Size</b>	<p>Required. The number of events that is written to HDFS with a single write operation. The default value is 10000.</p> <p><b>Note:</b> If the HDFS service queues a batch of events before the batch write timer expires, the service immediately persists all queued events to HDFS.</p>
<b>Batch Write Timer(sec)</b>	Required. Batch write frequency in seconds. The default value is 15.

Parameter	Description
	<b>Note:</b> If the batch write timer expires before the HDFS service queues a batch of events, all currently queued events are persisted to HDFS.

- Optionally, click **Test** to verify that your configuration is valid.
- Save your changes.

## Using the In-Process Service

The In-Process (IP) service is a pre-defined service that enables different parts of an application runtime to exchange digital events without using an external messaging server. Only one In-Process service exists per runtime.

You cannot modify the configuration of the pre-defined In-Process service or create a custom In-Process service. You can only add the In-Process service to a service group. In the service group, you can set the **Usage** property for the In-Process service only to **Source and Destination**.

For more information about how to configure a custom service group, see [“Configuring Custom Service Groups” on page 21](#).

## Configuring Service Groups

A service group is a defined set of services, where each service has a specific usage. Digital Event Services allows administrators to associate event types with a custom service group during the creation of the group. You use Command Central to configure service groups.

### Configuring the Default Service Group

Each product runtime where Digital Event Services is used has a default service group. All event types that are not explicitly associated with a custom service group are associated with the default service group. All events of these event types are delivered to the services within the default service group.

**Note:** You cannot rename or delete the default service group.

You can modify the default behavior of DES by adding services to or removing services from the default service group.

**Note:** You must create the services before adding them to the default service group. For more information about creating services, see [“Configuring Services” on page 14](#).

### To configure the default service group

1. In Command Central, navigate to **Environments > Instances > All > *instance\_name* > Digital Event Services > Configuration**.
2. Select **Service Groups** from the drop-down menu, and then click **Default** in the **Service Group Name** column.
3. Click **+** to add services to the group.
4. Select the services from the drop-down menu in the **Service Name** field.
5. For each service that you add to the default service group, define the **Usage** property:

Usage	Description
<b>Source Only</b>	Specify this option if your application subscribes to digital events.  <b>Note:</b> Your service group must contain at most one source service. You cannot include the same service twice in the same service group.
<b>Destination Only</b>	Specify this option if your application emits events. This is the default value.
<b>Source and Destination</b>	Specify this option if your application both emits and subscribes to events.

6. Optionally, click **Test** to verify that your configuration is valid.

**Note:** The validation is done on a field level, and checks whether the specified information complies with the field requirements.

7. Save your changes.

## Configuring Custom Service Groups

By default, Digital Event Services provides a default service group that contains a pre-configured Universal Messaging service. You can create one or more custom service groups and associate a set of event types with them.

When events of those particular event types are sent or received, they go to all services within the service group. One of the services in the group can be defined as source and/or destination of events for all event types associated with the service group.

---

### To configure a custom service group

1. In Command Central, navigate to **Environments > Instances > All > *instance\_name* > Digital Event Services > Configuration**.
2. Select **Service Groups** from the drop-down menu.
3. Click **+** to add a new custom group.
4. Specify values for the following fields:

Field	Description
<b>Group Name</b>	<p>Required. Specify a unique name for the service group. The name is not case-sensitive, and must start with a character. You can use the following characters as separators: <b>.</b>(dot) and <b>-</b> (dash).</p> <p><b>Note:</b> You cannot rename a service group. If you want to modify a service group name, you must delete the existing service group and recreate the group with a different name.</p>
<b>Description</b>	<p>Required. Specify a description of the purpose of the service group.</p>
<b>Services</b>	<p>Optional. Click <b>+</b> to add services to the group and then do the following:</p> <ul style="list-style-type: none"> <li>■ In the <b>Service Name</b> column, select a service.</li> <li>■ In the <b>Usage</b> column, select one of the following options: <ul style="list-style-type: none"> <li>■ <b>Source Only</b> - if your application subscribes to digital events.</li> <li>■ <b>Destination Only</b> - if your application emits events.</li> <li>■ <b>Source and Destination</b> - if your application both emits and subscribes to events. This is the default value.</li> </ul> </li> </ul> <p><b>Note:</b> Your service group must contain at most one source service. In addition, you cannot include the same service twice in the same service group.</p> <p>If you add the pre-defined In-Process service to a service group, you can set its usage only to <b>Source and Destination</b>. Any other services to the service group, you can only set them as <b>Destination Only</b>.</p>

---

Field	Description
<b>Event Types</b>	<p data-bbox="573 323 1333 394">Optional. Use the dual list box to manage the digital event types assigned to a service group.</p> <p data-bbox="573 415 1299 583">The box on the left shows event types that are not associated with any service group. The box on the right shows the event types currently assigned to this service group. Use the arrows to move event types between the two boxes.</p> <div data-bbox="573 604 1360 804" style="background-color: #f0f0f0; padding: 10px;"> <p data-bbox="589 615 1352 793"><b>Tip:</b> Use the search box to filter the list of available digital event types. You can also select multiple event types by holding down the CTRL button and clicking specific entries, or by holding down SHIFT and clicking the first and last entry of a range.</p> </div> <p data-bbox="573 825 1308 919">You can also manage the association of event types with service groups on the Digital Event Services &gt; Configuration &gt; Event Types page in Command Central.</p> <p data-bbox="573 940 1313 1014">For more information about event type management, see <a href="#">“Configuring Event Type Associations”</a> on page 23.</p> <div data-bbox="573 1035 1360 1266" style="background-color: #f0f0f0; padding: 10px;"> <p data-bbox="589 1045 1352 1245"><b>Important:</b> An event type can only be associated with a single service group. If you want to change the service group with which an event type is associated, you must first dis-associate the event type from its original service group, so that the event type shows in the dual list box.</p> </div>
<p data-bbox="297 1287 548 1360"><b>Note:</b> You cannot delete a custom service group that has event types associated with it.</p>	

5. Optionally, click **Test** to verify that your configuration is consistent.
6. Save your changes.

## Configuring Event Type Associations

When events of a particular event type are sent or received, Digital Event Services delivers them to the services within a service group. To configure to where events are sent you need to associate event types with their respective service groups.

In Digital Event Services version 10.0, applications cannot subscribe for digital event types that are not present in the DES event type repository. For more information about adding event types to the event type repository, see [“Considerations for Deploying Digital Event Types”](#) on page 29.

---

### To configure digital event type associations

1. In Command Central, navigate to **Environments > Instances > All > *instance\_name* > Digital Event Services > Configuration**.
2. Select **Event Types** from the drop-down menu.
3. In the **Name** column, click **Event Types**, and then click **Edit**.
4. For each digital event type in the **Event Types** table, specify the following information:

Field	Description
<b>Delivery Mode</b>	<p>The quality of service per event type, if the runtime in which DES is embedded stops responding and becomes unavailable. Values are:</p> <ul style="list-style-type: none"> <li>■ <b>Follow Preference</b> - events are delivered according to the delivery mode preference set in the event type definition. This is the default value.</li> <li>■ <b>Persistent</b> - events are stored on-disk and resent after the runtime becomes available again.</li> <li>■ <b>Non-persistent</b> - events are stored in-memory and are not resent after the runtime becomes available.</li> </ul> <div style="border: 1px solid #ccc; padding: 10px; margin-top: 10px;"> <p><b>Important</b> Changing the delivery mode preference for an event type in the digital event type definition requires a restart of the runtime in which DES is embedded for the changes to take effect.</p> <p>To avoid restarting the runtime, instead of <b>Follow Preference</b>, you can select either <b>Persistent</b> or <b>Non-Persistent</b> in the <b>Delivery Mode</b> field to reflect the change in the event type.</p> </div> <p>For more information about the quality of service setting, see <a href="#">“Delivery Modes for Digital Event Services” on page 9</a>.</p>
<b>In-Memory Capacity</b>	<p>The maximum number of events that are kept in-memory for an event type. You can specify any positive integer, or you can specify 1K (1024), 1M (1024K), or 1G (1024M).</p> <p>Alternatively, you can leave an empty string or specify <code>Default</code> to use the global default setting of the <b>In-Memory Capacity</b> property.</p> <p>For more information about configuring the global default value for <b>In-Memory Capacity</b>, see <a href="#">“Configuring</a></p>



Field	Description
	<a href="#">Storage Settings for Digital Event Services” on page 25.</a>
<b>On-Disk Capacity</b>	<p>The maximum number of events that are kept on-disk for an event type. You can specify any positive integer, or you can specify 1K (1024), 1M (1024K), or 1G (1024M).</p> <p>Alternatively, you can leave an empty string or specify <code>Default</code> to use the global default setting of the <b>On-Disk Capacity</b> property.</p> <p>For more information about configuring the global default value for <b>On-Disk Capacity</b>, see <a href="#">“Configuring Storage Settings for Digital Event Services” on page 25.</a></p>
<b>Service Group</b>	<p>Select a service group from the drop-down menu with which to associate the event type.</p> <div style="border: 1px solid #ccc; padding: 5px; margin: 10px 0;"> <p><b>Note:</b> Digital event types that are not explicitly associated with a custom service group are associated with the default service group.</p> </div> <p>You can also associate event types with service groups during the configuration of a service group. For more information, see <a href="#">“Configuring Custom Service Groups” on page 21.</a></p>

5. Optionally, click **Test** to verify that your configuration is consistent.
6. Save your changes.

## Configuring Storage Settings for Digital Event Services

Depending on the delivery mode configured for an event type, all events sent to Digital Event Services are stored on-disk or in-memory. For more information about how the delivery preference you set affects DES, see [“Delivery Modes for Digital Event Services” on page 9.](#)

### To configure the storage settings for Digital Event Services

1. In Command Central, navigate to **Environments > Instances > All > *instance\_name* > Digital Event Services > Configuration.**
2. Select **Runtime Configuration** from the drop-down menu.
3. In the **Name** column, select **Runtime Configuration**, and then click **Edit**.

## 4. Specify values for the following fields:

Field	Description
<b>Storage Location</b>	<p>Optional. Defines the location where events are stored on-disk. Specify an existing folder in your file system.</p> <p><b>Important:</b> Before you specify a new storage location, if the existing storage location is in use, you must copy any existing files manually to the new storage location.</p> <p>If you do not specify a value, events are stored in the same directory as the configuration.</p>
<b>Storage Batch Size</b>	<p>Required. Defines the number of events that must be added to the on-disk store-and-forward queue before the queue is persisted to disk.</p> <p>The default value is 100 events.</p>
<b>Sync Timeout</b>	<p>Required. Defines the timeout in milliseconds that the on-disk store-and-forward queue waits before the events in the queue are persisted, in case the batch size has not been reached.</p> <p>The default value is 500 milliseconds.</p>
<b>Default On-Disk Capacity</b>	<p>Required. Defines the maximum number of events of each event type that can be stored on disk. The default value is 1000000.</p> <p><b>Note:</b> You can override the setting by specifying <b>On-Disk Capacity</b> per event type. For more information about configuring the <b>On-Disk Capacity</b> property, see <a href="#">“Configuring Event Type Associations” on page 23</a>.</p>
<b>Default In-Memory Capacity</b>	<p>Required. Defines the maximum number of events of each event type that can be stored in the memory. The default value is 1000.</p> <p><b>Note:</b> You can override the setting by specifying <b>In-Memory Capacity</b> per event type. For more information about configuring the <b>In-Memory Capacity</b> property, see <a href="#">“Configuring Event Type Associations” on page 23</a>.</p>

5. Save your changes.

Digital Event Services detects that the configuration has been updated, and starts to use the new settings for **Default On-Disk Capacity** and **Default In-Memory Capacity** automatically.

**Important:** If you modify the **Storage Batch Size**, **Sync Timeout**, and **Storage Location** properties, you must restart the runtime where the DES component is embedded for the changes to take effect.

For 10.0, this means restarting the Integration Server or Apama runtime. For more information about shutting down and starting Integration Server and Apama, see *webMethods Integration Server Administrator's Guide* and *Deploying and Managing Apama Applications*, respectively.

## Monitoring Digital Event Services

You can monitor the status of Digital Event Services (DES) in real time by using:

- **Optimize for Infrastructure.** Optimize for Infrastructure provides you with a set of default rules for notification of object failure and also enables you to define your own custom rules. For more information about monitoring DES by using Optimize for Infrastructure, see *Administering webMethods Optimize*.
- **The DES Monitoring API.** The monitoring API is based on Java Management Extensions (JMX) and represents services and queues by using managed beans (MBeans). For more information about the MBeans that DES exposes, see “[Digital Event Services MBeans](#)” on page 43 .

To enable monitoring by MBeans, set the `com.softwareag.events.routing.enable.jmx` system property to `true`. For more information about setting the property, see the product documentation of the DES runtime.

In addition, you can use the JMX Remote API to monitor remotely a server runtime where DES is running. To enable monitoring from remote systems, when you start the server runtime set `com.sun.management.jmxremote.port` system property. For more information about setting the property, see the product documentation of the DES runtime.

**Important:** When you enable remote monitoring of DES, ensure that the exposed information can only be accessed after authorization. For more information about securing the DES runtime, see the product documentation of the server runtime and the Java documentation.

## Secure Password Handling

You can use Digital Event Services (DES) services to connect to password-protected systems. For example, you might configure DES to archive events in a database by using Event Persistence services.

DES service configuration files need to contain a password to successfully establish a secure connection to systems that require password authentication. To protect these passwords, DES encrypts and decrypts passwords using a master password that is also encrypted. In a Software AG installation, all runtimes where DES is embedded use a single master password. The master password is stored in *Software AG\_directory/common/DigitalEventServices/security/passman*.

**Important:** When you first install DES, the default master password is "manage". Software AG recommends that you change the default master password shortly after installing DES. For more information about specifying a new master password, see [“Changing the Master Password” on page 28](#).

## Changing the Master Password

Digital Event Services (DES) provides you with a command line tool for changing the master password. The command line tool is installed in *Software AG\_directory/common/lib/events-passman-tool.jar*.

**Note:** You can find usage information for the command line utility by opening a command line prompt in *Software AG\_directory/common/lib* and by executing the following command:

```
java -jar events-passman-tool.jar
```

### To change the master password:

1. Open command line prompt in the *Software AG\_directory /common/lib*.
2. Specify a new master password by typing the following command:

```
java -jar events-passman-tool.jar change-mpw old_mpw new_mpw  
passman_config_location
```

where:

- *old\_mpw* is the old master password that is needed for authentication.
- *new\_mpw* is the new master password.
- *passman\_config\_location* is the storage location of the master password: *Software AG\_directory/common/DigitalEventServices/security/passman*.

**Note:** If the passwords and/or the configuration location contain characters that affect the parameter resolution of the command shell, you need to apply appropriate escaping.

The command line tool changes the master password of the given configuration to the value you specify for *new\_mpw*, and reports the number of updated passwords in service definitions.

## Lifecycle Actions for Digital Event Services

Digital Event Services does not support any lifecycle actions, such as start, stop, or restart. Although the **Lifecycle Actions** setting for DES is active in the Command Central web user interface, administrators should not use this functionality.

For more information about shutting down and starting Integration Server and Apama, see *webMethods Integration Server Administrator's Guide* and *Deploying and Managing Apama Applications*, respectively.

## Considerations for Deploying Digital Event Types

You should consider the following information when deploying digital event types from your local environment to other instances of Integration Server or Apama:

- In Digital Event Services 10.0, applications cannot subscribe for digital event types that are not present in the DES event type repository.
- To deploy event types from your local environment to other instances of Integration Server or Apama, copy the event type manually from *Software AG\_directory/common/DigitalEventServices/TypeRepository/eventtypes/event type name*.
- The relative paths in the source and destination event type repositories must be the same.

**Note:** Do not rename the file name of a digital event type.

- A digital event type can refer to other event types. When copying a digital event type, ensure that all referenced types are included.

## Digital Event Services Licensing

If you do not have a valid license for Digital Event Services, you cannot create events, and your applications cannot emit and subscribe to digital events.

By default, Digital Event Services comes with a 30-day trial license. The original DES license can be overwritten by another license at any time. The DES license is located

in the following file: *Software AG\_directory/common/DigitalEventServices/license/license.xml*.

**Important:** A missing license file is regarded as an invalid license.

For more information about licensing, see *Installing Software AG Products*.

## Performance Considerations on Linux

---

For deployments on a Linux operating system where performance is a concern, use an XFS file system for the Digital Event Services store-and-forward queue. If the throughput is high, XFS file systems perform better compared to the default ext4 file systems.

# 3 Configuring Digital Event Services Using Composite Templates

---

- About Configuring Digital Event Services with Command Central Composite Templates ..... 32
- Configuring DES for a Single Runtime Instance ..... 32
- Configuring DES for Multiple Runtime Instances within a Single Installation ..... 33
- Configuring DES for a Set of Installations ..... 34
- Creating and Configuring a DES Runtime Instance ..... 36
- Creating an Event Persistence Service Using Composite Templates ..... 37
- Updating an Event Persistence Service Using Composite Templates ..... 40

## About Configuring Digital Event Services with Command Central Composite Templates

You can use a composite template and the Command Central Command Line Interface to configure Digital Event Services for one or more runtime components in new or existing installations.

For more information about composite templates and scripting, see *Software AG Command Central Help*.

The following sections contain examples of how composite templates can be used with Digital Event Services.

### Configuring DES for a Single Runtime Instance

The template snippet in this example creates and configures a Digital Event Services messaging service of type Universal Messaging for the default Integration Server instance.

The template defines a single layer, with alias `is1`. The `is1` layer includes the `is1-des-messaging-configuration` inline template, which is defined in the templates section. The `is1` layer maps to the local node in the provision section.

In the configuration section of the Integration Server instance template, the runtime component `OSGI-IS_default-DigitalEventServices` refers to `DES-MESSAGING-CONFIG`, which defines the parameters for the `COMMON-WMMESSAGING-DES` configuration type.

`OSGI-IS_default-DigitalEventServices` is the runtime component ID, which you can obtain by using the `sagcc list inventory components CLI` command.

`COMMON-WMMESSAGING-DES` is the configuration type ID, and `MyUM` is the configuration instance ID. The value of the "`@alias`" parameter should be the same as the configuration instance ID, in this case: "`@alias`": `MyUM`.

Command Central applies `DES-MESSAGING-CONFIG` to the `OSGI-IS_default-DigitalEventServices` runtime component, thus creating and setting up a Universal Messaging service for Digital Event Services.

For more information about working with composite templates and the `sagcc list inventory components` command, see *Software AG Command Central Help*.

```
alias: single-des-config-single-install
description: Configure DES for a single instance
version: 0.1

layers:
  is1:
    templates: [is1-des-messaging-configuration]

DES-MESSAGING-CONFIG: &DES-MESSAGING-CONFIG
```



```

COMMON-WMMESSAGING-DES:
  MyUM:
    Messaging:
      "@alias": MyUM
      Description: NewUM
      Enabled: true
      Provider:
        "@type": UM
        URL: nsp://localhost:1234

templates:
  is1-des-messaging-configuration:
    products:
      integrationServer:
        default:
          configuration:
            OSGI-IS_default-DigitalEventServices: *DES-MESSAGING-CONFIG

provision:
  default:
    is1: local

```

## Configuring DES for Multiple Runtime Instances within a Single Installation

The composite template in this example creates and configures a Digital Event Services messaging service of type Universal Messaging for two Integration Server instances named `IS_default` and `IS_default2`.

The template defines two layers, with aliases `is1` and `is2`. Both layers map to the local node in the provision section.

The inline template applied to the `is1` layer is `is1-des-messaging-configuration`. The template configures the runtime component `OSGI-IS_default-DigitalEventServices` by referring to `DES-MESSAGING-CONFIG`, which defines the parameters for the `COMMON-WMMESSAGING-DES` configuration type.

The inline template applied to the `is2` layer is `is2-des-messaging-configuration`. The template configures the runtime component `OSGI-IS_default2-DigitalEventServices` by referring to `DES-MESSAGING-CONFIG`, which defines the parameters for the `COMMON-WMMESSAGING-DES` configuration type.

`OSGI-IS_default-DigitalEventServices` and `OSGI-IS_default2-DigitalEventServices` are the IDs of the runtime components to be configured. You can obtain the component ID of a runtime by using the `sagcc list inventory components` CLI command.

`COMMON-WMMESSAGING-DES` is the configuration type ID, and `MyUM` is the configuration instance ID. The alias parameter should be the same as the configuration instance ID, in this case: `"@alias": MyUM`.

Command Central applies the `DES-MESSAGING-CONFIG` configuration to the runtime components `OSGI-IS_default-DigitalEventServices` and `OSGI-IS_default2-`

DigitalEventServices. Applying `DES-MESSAGING-CONFIG` creates and configures a Universal Messaging service for both components.

For more information about working with composite templates and the `sagcc list inventory components` command, see *Software AG Command Central Help*.

```
alias: multiple-des-config-single-install
description: Configure DES for multiple instances in a single installation
version: 0.1

layers:
  is1:
    templates:
      - is1-des-messaging-configuration

  is2:
    templates:
      - is2-des-messaging-configuration

DES-MESSAGING-CONFIG: &DES-MESSAGING-CONFIG
COMMON-WMMESSAGING-DES:
  MyUM:
    Messaging:
      "@alias": MyUM
      Description: NewUM
      Enabled: true
      Provider:
        "@type": UM
        URL: nsp://localhost:1234

templates:
  is1-des-messaging-configuration:
    products:
      integrationServer:
        default:
          configuration:
            OSGI-IS_default-DigitalEventServices: *DES-MESSAGING-CONFIG

  is2-des-messaging-configuration:
    products:
      integrationServer:
        default2:
          configuration:
            OSGI-IS_default2-DigitalEventServices: *DES-MESSAGING-CONFIG

provision:
  default:
    is1: local
    is2: local
```

## Configuring DES for a Set of Installations

The composite template in this example configures Digital Event Services for the Integration Server instance `IS_Default` in two different installations.

This template defines two layers, with aliases `is1` and `is2`, which in the provision section map to the nodes `local` and `local2`, respectively.

The templates applied to the `is1` and `is2` layers are `is1-des-messaging-configuration` and `is2-des-messaging-configuration`, respectively. The templates configure the runtime component `OSGI-IS_default-DigitalEventServices` by referring to `DES-MESSAGING-CONFIG`, which defines the parameters for the `COMMON-WMMESSAGING-DES` configuration type.

`OSGI-IS_default-DigitalEventServices` is the ID of the runtime component to be configured. You can obtain the component ID of a runtime by using the `sagcc list inventory components` CLI command.

`COMMON-WMMESSAGING-DES` is the configuration type ID, and `MyUM` is the configuration instance ID. The alias parameter should be the same as the configuration instance ID, in this case: `"@alias": MyUM`.

Command Central applies the `DES-MESSAGING-CONFIG` configuration to the runtime component `OSGI-IS_default-DigitalEventServices`, thus creating and configuring Universal Messaging for multiple instances in multiple installations.

For more information about working with composite templates and the `sagcc list inventory components` command, see *Software AG Command Central Help*.

```
alias: multiple-des-config-multi-install
description: Configure DES for multiple instances in multiple installations
version: 0.1

layers:
  is1:
    templates:
      - is1-des-messaging-configuration

  is2:
    templates:
      - is2-des-messaging-configuration

DES-MESSAGING-CONFIG: &DES-MESSAGING-CONFIG
COMMON-WMMESSAGING-DES:
  MyUM:
    Messaging:
      "@alias": MyUM
      Description: NewUM
      Enabled: true
      Provider:
        "@type": UM
        URL: nsp://localhost:1234

templates:
  is1-des-messaging-configuration:
    products:
      integrationServer:
        default:
          configuration:
            OSGI-IS_default-DigitalEventServices: *DES-MESSAGING-CONFIG

  is2-des-messaging-configuration:
    products:
      integrationServer:
        default:
          configuration:
            OSGI-IS_default-DigitalEventServices: *DES-MESSAGING-CONFIG
```

```

nodes:
  default:
    default:
      secure: true
      credentials:
        username: Administrator
        password: manage
    local:
      host: localhost
      port: 8093
    local2:
      host: localhost
      port: 9815

provision:
  default:
    is1: local
    is2: local2

```

## Creating and Configuring a DES Runtime Instance

The composite template in this example sets up a new installation on the node with alias `local2`, with an Integration Server instance called `IS_default2`, and also configures Digital Event Services.

The template defines the layer `new-is`, which is mapped to the node `local2`, as per the details in specified under `provision`. Integration Server will be installed from the repository called `webMethods-10.0` to the directory `C:/SoftwareAG2`.

The template applied to the `new-is` layer is `[create-and-configure-is]` and configures Digital Event Services and the Integration Server instance `IS_default2`. The template configures the runtime component `OSGI-IS_default-DigitalEventServices` by referring to `DES-MESSAGING-CONFIG`, which defines the parameters for the `COMMON-WMMESSAGING-DES` configuration type.

`COMMON-WMMESSAGING-DES` is the configuration type ID, and `MyUM` is the configuration instance ID. The alias parameter should be the same as the configuration instance ID, in this case: `"@alias": MyUM`.

When applying the template, Command Central applies the `new-is` layer on the `local2` node and installs Digital Event Services and Integration Server with the instance defined in the `[create-and-configure-is]` template. When `IS_default2` is up and running, Command Central applies the `DES-MESSAGING-CONFIG` configuration on the `OSGI-IS_default2-DigitalEventServices` runtime component.

For more information about working with composite templates, see *Software AG Command Central Help*.

```

alias: setup-installation-configure-instance
description: Create a new installation with an IS instance and configure DES
version: 0.1

layers:
  new-is:
    productRepo: webMethods-10.0

```

```

templates: [create-and-configure-is]
DES-MESSAGING-CONFIG: &DES-MESSAGING-CONFIG
COMMON-WMMESSAGING-DES:
  MyUM:
    Messaging:
      "@alias": MyUM
      Description: NewUM
      Enabled: true
      Provider:
        "@type": UM
        URL: nsp://localhost:1234
templates:
  create-and-configure-is:
    products:
      DEV:
        integrationServer:
          default2:
            primary.port: 5805
            diagnostic.port: 5806
            jmx.port: 5807
            configuration:
              OSGI-IS_default2-DigitalEventServices: *DES-MESSAGING-CONFIG
nodes:
  default:
    local2:
      host: localhost
      port: 9815
      secure: true
      bootstrapInfo:
        installDir: C:/SoftwareAG2
provision:
  default:
    new-is: local2

```

## Creating an Event Persistence Service Using Composite Templates

This section includes an example of a composite template that you can use to create a service of type Event Persistence for Digital Event Services (DES), which is embedded in an Integration Server instance.

### Before You Begin

Before you can create the composite template for creating an Event Persistence service, do the following:

- Install a default Integration Server with DES and Event Persistence. When using the sample template in this section, install Integration Server on the local host with default ports.
- See the "Creating Custom Composite Templates" section in *Software AG Command Central Help*.

## Creating the Template Definition File

The following example configures an Event Persistence service with Apache Hadoop 5.3.0 as the storage technology. To configure an Event Persistence service with Elasticsearch 2.3.2 as the storage technology, use the same template but include parameters specific to Elasticsearch.

The template creates a single layer, with alias `local-is` and applies the `create-an-evt-service` inline template on the layer. The `local-is` layer is created in the local installation.

In the configuration section of the template, the configuration details specified in `DES-EVP-CONFIGURATION` are applied on the `OSGI-IS_default-DigitalEventServices` runtime component. `DES-EVP-CONFIGURATION` contains the parameters for the `EVENT-PERSISTENCE-DES` configuration type, and `LocalPersistence` is the instance ID.

`OSGI-IS_default-DigitalEventServices` is the runtime component ID, which you can obtain by using the `sagcc list inventory components` CLI command.

**Important:** To connect to an HDFS server you need to authenticate with a password. To successfully provision an Event Persistence service when you apply the template you must provide the value for `hiveServerPassword` in one of the following ways:

- As a value in the composite template itself.
- As an argument.
- In a properties file.

You must also provide a valid password when updating an Event Persistence service with composite templates. For more information about updating an Event Persistence service with composite templates, see [“Updating an Event Persistence Service Using Composite Templates”](#) on page 40.

## Example

```
alias: evt-configuration
description: Create and configure a EVP service in DES
version: 0.1

layers:
  local-is:
    templates: [create-an-evt-service]

DES-EVP-CONFIGURATION: &DES-EVP-CONFIGURATION
EVENT-PERSISTENCE-DES:
  LocalPersistence:
    serviceName: LocalPersistence
    serviceType: HDFS CDH.5.3.0
    serviceDescription: MyDescription
    eventTypeStoreLocation: default
    nodeNameURI: hdfs://localhost:8020
    hdfsMaxFileSize: 65
    hiveServerURI: jdbc:hive2://localhost:10000
    hiveDatabaseName: Database
```

```

hiveWarehouseLocation: /user/hive/warehouse
hiveServerUser: Admin
hiveServerPassword: my.secret
hdfsBatchSize: 10000
hdfsBatchWriteTimerSec: 15
elasticSearchBatchSize: 1000
elasticSearchBatchWriteTimerSec: 15
elasticSearchCoreThreadPoolSize: 5
elasticSearchMaximumThreadPoolSize: 10
elasticSearchThreadPoolKeepAliveTime: 5
elasticSearchThreadPoolQueueSize: 10
elasticSearchPreStartCoreThreads: false
elasticSearchSSEEnabled: false

templates:
  create-an-evp-service:
    products:
      integrationServer:
        default:
          configuration:
            OSGI-IS_default-DigitalEventServices: *DES-EVP-CONFIGURATION

provision:
  default:
    local-is: local

```

### Importing the Composite Template

Before you can apply the template, you must import the template into Command Central.

Import the template from the example with the following command:

- If you only have a template definition file:

```
sagcc exec templates composite import -i evp-configuration.yaml
```

- If you have a template archive with a template definition and an environment properties file:

```
sagcc exec templates composite import -i evp-configuration.zip
```

### Applying the Composite Template

Importing the template registers it in Command Central. You can apply the template with the following command:

```
sagcc exec templates composite apply evp-configuration
```

Apply the template from the example with the following command:

- With an input argument for `hiveServerPassword`:

```
sagcc exec templates composite apply evp-configuration my.password=my.secret
```

- With an input properties file:

```
sagcc exec templates composite apply -i evp-configuration sample.properties
```

where `sample.properties` is the name of your custom properties file that contains the value for the `hiveServerPassword` parameter.

## Verifying the Template Execution

Verify that the template execution is successful in the following ways:

- Check the **Jobs** view in the Command Central web user interface while applying the template.
- After applying the template, check in Command Central if the service is listed with the correct configuration settings in **Environments > Instances > All > local-is > Digital Event Services > Configuration > Event Persistence**.

## Updating an Event Persistence Service Using Composite Templates

You can update an Event Persistence service with the same template you use to create the service. For more information about how to create an Event Persistence service with composite templates, see [“Creating an Event Persistence Service Using Composite Templates” on page 37](#).

Before updating an Event Persistence service, see the "Updating a Provisioned Environment Using the Same Composite Template" section in *Software AG Command Central Help*.

### Update the Event Persistence Service Details

Make the necessary changes to the configuration section of the same template you use to create Event Persistence services. Use a local copy instead of modifying the template in *Software AG\_directory \profiles\CCE\data\templates\composite*.

### Import the Updated Template

When you import an updated template you should use the `overwrite={true | false}` argument to specify whether you want to create a new version of the original template or whether you want to replace it. Use the following command to update the composite template from the example:

```
sagcc exec templates composite import -i evp-configuration.yaml overwrite=true
```

### Retrieve Encrypted Password

Before applying the template again, you can obtain the encrypted password for the Apache Hadoop 5.3.0 server, and replace the clear text password in the template definition. This step is optional.

To retrieve the password you use in the composite template example, use the following command:

```
cc get configuration data local OSGI-IS_default-DigitalEventServices LocalPersistence -f json
```



When you are using a custom properties file to store the value of the `hiveServerPassword` parameter, you must replace the original value with the updated encrypted password.

### Applying the Updated Composite Template

You can apply the updated composite template with the following command:

```
sagcc exec templates composite apply evp-configuration
```

If you have not specified a value for `hiveServerPassword` in the template definition run the command as follows:

- With an input argument:

```
sagcc exec templates composite apply evp-configuration my.password=my.secret
```

where *my.secret* is the password of the Apache Hadoop Server user.

- With an input properties file:

```
sagcc exec templates composite apply -i evp-configuration sample.properties
```

where *sample.properties* is the name of the custom properties file that contains the value for `hiveServerPassword`.

### Verifying the Template Execution

Verify that the template execution is successful in the following ways:

- Check the **Jobs** view in the Command Central web user interface while applying the template.
- After applying the template, check in Command Central if the service is updated with the correct configuration settings in **Environments > Instances > All > local-is > Digital Event Services > Configuration > Event Persistence**.



# A Digital Event Services MBeans

---

■ Event Type Information MBean .....	44
■ Universal Messaging Service MBean .....	44
■ Queue MBean .....	48
■ Subscriber MBean .....	49

## Event Type Information MBean

Retrieves information about an event type.

### MBean Name

```
com.softwareag.events.routing:type=EventTypes,eventType=event_type_name,
category=Information
```

where *event\_type\_name* is the name of the event type.

### MBean Attributes

Attribute	Description
deliveryMode	String. The delivery mode of the event type. Values are: <ul style="list-style-type: none"> <li>■ Persistent</li> <li>■ Non-Persistent</li> </ul> For more information about delivery modes, see <a href="#">“Delivery Modes for Digital Event Services” on page 9.</a>

## Universal Messaging Service MBean

Retrieves information about the Universal Messaging (UM) services configured in a service group that is associated with an event type.

### MBean Name

```
com.softwareag.events.routing:type=EventTypes,eventType=event_type_name,
category=Services,serviceName=service_name
```

where *event\_type\_name* is the name of the event type and *service\_name* is the name of the Universal Messaging service.

### MBean Attributes

Attribute	Description
name	String. The name of the service.

Attribute	Description
usage	<p>String. The usage of the service. Values are:</p> <ul style="list-style-type: none"> <li>■ <code>SourceOnly</code> - you can subscribe to the service, but you cannot use the service to send events.</li> <li>■ <code>DestinationOnly</code> - you can use the service to only send events.</li> <li>■ <code>SourceAndDestination</code> - you can both subscribe to the service and use the service to send events.</li> </ul> <p>For information about the possible usage of a service, see <a href="#">“Configuring Service Groups” on page 20</a>.</p>
providerUrl	<p>String. The URL of the Universal Messaging server. The providerUrl attribute has the following format: <code>protocol://host:port</code>. The default value is <code>nsp://localhost:9000</code>.</p>
connected	<p>Boolean. Indicates whether the service is connected to the configured Universal Messaging server.</p>
connectTime	<p>Instant. The time when the service connected to the Universal Messaging server, or reconnected to the server after losing connection.</p>
disconnectTime	<p>Instant. The time when the service disconnected from the Universal Messaging server.</p>
activeSharedDurable-SubscribersCount	<p>Integer. The number of active shared durable subscribers to the service. If the service usage is <code>DestinationOnly</code>, the value of this attribute is empty.</p>
activeSharedDurable-SubscribersIds	<p>List&lt;String&gt;. The identifiers of the active shared durable subscribers to the service. If the service usage is <code>DestinationOnly</code>, the value of this attribute is empty.</p>
inactiveSharedDurable-SubscribersCount	<p>Integer. The number of shared durable subscribers to this service that are inactive but still subscribed. If the service usage is <code>DestinationOnly</code>, the value of this attribute is empty.</p>

Attribute	Description
	<p><b>Important</b> The system keeps inactive subscribers only while DES is running. If a shared durable subscriber is closed, but remains unsubscribed, the subscriber ID is added to the <code>inactiveSharedDurableSubscribersIds</code>, list and <code>inactiveSharedDurableSubscribersCount</code> increases. However, when you restart the runtime where DES is embedded, DES will not examine the Universal Messaging channel for available shared named objects. As a result, the <code>inactiveSharedDurableSubscribersIds</code> list is initially be empty and does not contain the subscriber ID that was previously added.</p>
<p><code>inactiveSharedDurableSubscribersIds</code></p>	<p>List&lt;String&gt;. The identifiers of the shared durable subscriber to the service that are inactive, but still unsubscribed. If the service usage is <code>DestinationOnly</code>, the value of this attribute is empty.</p> <p><b>Important</b> The system keeps inactive subscribers only while DES is running. If a shared durable subscriber is closed, but remains unsubscribed, the subscriber ID is added to the <code>inactiveSharedDurableSubscribersIds</code>, list and <code>inactiveSharedDurableSubscribersCount</code> increases. However, when you restart the runtime where DES is embedded, DES will not examine the Universal Messaging channel for available shared named objects. As a result, the <code>inactiveSharedDurableSubscribersIds</code> list is initially be empty and does not contain the subscriber ID that was previously added.</p>
<p><code>nonDurableSubscribersCount</code></p>	<p>Integer. The number of non-durable subscribers to the service. If the service usage is <code>DestinationOnly</code>, the value of this attribute is empty.</p>
<p><code>receivedEvents</code></p>	<p>Long. The number of events received by all subscribers to the service since the service became active. If the service usage is <code>DestinationOnly</code>, the value of this attribute is empty.</p>

Attribute	Description
lastSendingStatus	<p>String. The status of the last sending operation performed by the service. Values are:</p> <ul style="list-style-type: none"> <li>■ Green - when the Universal Messaging server or the network connection to the server is slow, and transactions take a long time.</li> <li>■ Red - when the Universal Messaging server or the network connection the server is so slow that transactions fail due to a timeout.</li> </ul> <p><b>Important:</b> If the Universal Messaging server becomes unavailable, but no events are sent for long time, the lastSendingStatus might still be Green because the status is updated only after a transaction to the server.</p> <p>To determine whether the server is available without sending events, check the connected, connectTime, and disconnectTime attributes.</p>
lastSendingStatusDetails	<p>String. Information about the last sending status. If the status is Red, the explanation also contains the exception that caused the sending operation to fail.</p>
sentEvents	<p>Long. The number of events sent to the service. If the service usage is SourceOnly, the value of this attribute is empty.</p>
acknowledgedSentEvents	<p>Long. The number of events sent to the service and successfully acknowledged by the Universal Messaging server. If the service usage is SourceOnly, the value of this attribute is empty.</p>
lastSendingTime	<p>Instant. The time when the last event was sent to the Universal Messaging server.</p> <p><b>Note:</b> The lastSendingTime attribute reflects the time when an event was last sent to the destination service. The lastSendingTime attribute does not carry information about whether an event was acknowledged by the destination service.</p> <p>To see whether an event was acknowledged by the destination service, check the lastCompletedAcknowledgementTime attribute.</p>

Attribute	Description
lastCompletedAcknowledgementTime	Instant. The last time when an event sent to the service was successfully acknowledged by the Universal Messaging server. If the service usage is <code>SourceOnly</code> , the value of this attribute is empty.
regularDelivery-InterruptionsCount	Integer. The number of times when the service switched to redelivery mode because of a failure to deliver an event to the Universal Messaging server. If the service usage is <code>SourceOnly</code> , the value of this attribute is empty.

## Queue MBean

Retrieves on-disk and in-memory storage details per event type.

### MBean Name

```
com.softwareag.events.routing:type=EventTypes,eventType=event_type_name,
category=Queues,queueType=queue_type
```

where *event\_type\_name* is the name of the event type and *queue\_type* is type of storage used for the queue. Values are `On-Disk` and `In-Memory`.

### MBean Attributes

Attribute	Description
status	String. The status of the queue. Values are: <ul style="list-style-type: none"> <li>■ Green</li> <li>■ Yellow</li> <li>■ Red</li> </ul>
statusDetails	String. An explanation of the current status. Values are: <ul style="list-style-type: none"> <li>■ Green - the utilization is below 90%.</li> <li>■ Yellow - the queue is functioning properly, but the utilization is equal to or greater than 90%.</li> <li>■ Red - the queue is full.</li> </ul>



Attribute	Description
capacity	Long. The maximum number of events that the queue can store.
currentSize	Long. The number of events currently stored in the queue.
averageUtilization	Float. The average <i>size:capacity</i> ratio since the first send operation for the event type that uses the queue.
queueBufferFullCount	Integer. The number of times that the queue becomes full, that is when <i>currentSize</i> is equal to <i>capacity</i> .

## Subscriber MBean

Monitors the subscribers to Digital Event Services (DES) event types.

### MBean Name

```
com.softwareag.events.routing:type=EventTypes,
eventType=event_type_name,category=Subscribers,subscriber=subscriber_name
```

where *event\_type\_name* is the name of the event type and *subscriber\_name* is the unique name that DES generated for the subscriber.

**Note:** You can retrieve the subscriber ID that you specify when creating a shared durable subscriber from the *subscriberId* attribute.

### MBean Attributes

Attribute	Description
subscriberId	String. The identifier of a subscriber.
type	String. The type of the subscribe. Values are: <ul style="list-style-type: none"> <li>■ Shared durable</li> <li>■ Non-durable</li> </ul> For more information about durable and non-durable subscribers, see <i>webMethods Service Development Help</i> .

Attribute	Description
sourceService	String. The name of the source service from which the subscriber receives events.
status	<p>String. The status of the subscriber. Values are:</p> <ul style="list-style-type: none"> <li>■ <code>Active</code> - the subscriber is working as expected.</li> <li>■ <code>Inactive</code> - the subscriber is closed but not yet unsubscribed. This state is valid only for subscribers that are of the <code>Shared durable</code> type.</li> <li>■ <code>Not configured</code> - no source service is configured for the event type, or the source service is removed from the configuration after the subscriber was created.</li> </ul> <p><b>Note:</b> When a subscriber is <i>closed and unsubscribed</i>, its MBean is unregistered. In this case, the subscriber has no status.</p>
statusDetails	String. An explanation of the current subscriber status.
receivedEvents	Long. The number of events received by the subscriber, including redelivered events.
lastReceivedEventTime	Instant. The time when the last event was received by the subscriber.
receivedRedeliveredEvents	Long. The number of redelivered events received by the subscriber.
lastReceivedRedelivered-EventTime	Instant. The time when the last redelivered event was received by the subscriber.
acknowledgedEvents	Long. The number of events acknowledged by the client event processor associated with the subscriber.
lastAcknowledgementTime	Instant. The time of the last event acknowledgement by the client event processor associated with the subscriber.

---

Attribute	Description
negativelyAcknowledged-Events	Long. The number of events acknowledged negatively by the client event processor associated with the subscriber.
lastNegative-AcknowledgementTime	Instant. The time of the last negative event acknowledgement by the client processor associated with the subscriber.

---



# B Using Event Persistence

---

- Using HDFS with Event Persistence ..... 54
- Configuring SSL for Event Persistence ..... 54

---

## Using HDFS with Event Persistence

---

Before you can store events with Event Persistence using HDFS as the storage engine, you must configure the Hadoop cluster. You must copy the custom Hive SerDe and Joda Date/Time libraries from your Event Persistence installation to your HDFS CDH 5.3.0 distribution.

---

### To configure HDFS CDH 5.3.0 as the storage engine for Event Persistence:

1. In your Software AG installation, locate the Joda Date/Time and the Event Persistence Hive SerDe .jar files:
  - `joda-time_2.9.3.jar` - available in the `Software AG_directory\common\runtime\bundles\platform\eclipse\plugins` directory.
  - `com.softwareag.evp.hive.serde_10.0.0.0000-nnnn.jar` - available in the `Software AG_directory\common\runtime\bundles\evs\eclipse\plugins` directory, where `nnnn` is the build number of your Event Persistence installation.
2. Copy both files to the Hive library directory on all nodes in the Hadoop cluster where Hive is running, for example `CDH5.3.0_directory/var/lib/hive/lib`.
3. Copy both files to the Yarn library directory on all data nodes in the Hadoop cluster, for example `CDH5.3.0_directory/var/lib/hadoop-yarn/lib` or `CDH5.3.0_directory/var/lib/hadoop-mapreduce/lib`, if you are using MapReduce MRv1.
4. Restart Hive.

---

## Configuring SSL for Event Persistence

---

You can persist digital events over Secure Socket Layer (SSL) when you use Elasticsearch as the storage technology. To persist events over SSL, you must perform the following steps at a high level:

1. Enable your Elasticsearch or Event Data Store instance for SSL. For more information, see [“SSL Enablement for Elasticsearch” on page 54](#) and [“SSL Enablement for Event Data Store” on page 55](#), respectively.
2. Configure your Event Persistence service of type Elasticsearch to use SSL. For more information about how to configure the service to persist events over SSL, see [“Configuring Event Persistence Services for Elasticsearch” on page 16](#).

### SSL Enablement for Elasticsearch

Before you can persist digital events to Elasticsearch over SSL, you must enable SSL for your Elasticsearch storage engine and have the Search Guard plugin installed for Elasticsearch. For more information about how to install and configure SSL for

Elasticsearch 2.3.2, see the Elasticsearch documentation. For information about using the Search Guard plugin, see the Search Guard plugin documentation.

## SSL Enablement for Event Data Store

If you are using Event Data Store, which is an Elasticsearch packaging that Software AG provides, you can enable SSL automatically with sample certificates for a single Event Data Store instance.

For more information about how to enable or disable SSL for Event Data Store, see [“Enabling SSL for Event Data Store” on page 55](#) and [“Disabling SSL for Event Data Store” on page 55](#), respectively.

When you install Event Data Store it comes with a pre-configured SSL certificate, and default *keystore* and *truststore* files. The keystore and truststore function as repositories for the storage of keys and certificates necessary for SSL authentication, encryption/decryption, and digital signing/verification services. You can find the default truststore and keystore files here:

- *Software AG\_directory/EventDataStore/plugins/search-guard-2/sgconfig/kirk-keystore.jks*
- *Software AG\_directory/EventDataStore/plugins/search-guard-2/sgconfig/truststore.jks*

If you use Event Data Store in a production environment, you should replace the Event Data Store default certificates, keystore and truststore files with custom files. For more information about creating keystores and truststores, importing keys and certificates into keystores and truststores, and other operations with these files, see the documentation for your certificate management tool.

## Enabling SSL for Event Data Store

You automatically enable SSL for a single Event Data Store instance by running one of the following scripts:

- For Linux - *Software AG\_directory/EventDataStore/bin/enable\_ssl.sh*.
- For Windows - *Software AG\_directory\EventDataStore\bin\enable\_ssl.bat*.

## Disabling SSL for Event Data Store

You automatically disable SSL for a single Event Data Store instance by running one of the following scripts:

- For Linux - *Software AG\_directory/EventDataStore/bin/disable\_ssl.sh*.
- For Windows - *Software AG\_directory\EventDataStore\bin\disable\_ssl.bat*.

**Note:** Before you run the script for disabling SSL, you must disconnect all clients connected to the Elasticsearch server.