

webMethods EntireX

CICS ECI RPC Server

Version 9.12

October 2016

This document applies to webMethods EntireX Version 9.12 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 1997-2016 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://softwareag.com/licenses>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://softwareag.com/licenses/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software AG.

Document ID: EXX-CICSECI-912-20181116

Table of Contents

1 About this Documentation	1
Document Conventions	2
Online Information and Support	2
Data Protection	3
2 Introduction to the CICS ECI RPC Server	5
Overview	6
Worker Models	7
3 Administering the EntireX CICS® ECI RPC Server	9
Customizing the CICS ECI RPC Server	10
Configuring the RPC Server Side	12
Configuring the CICS ECI Side	14
Using SSL/TLS with the RPC Server	15
Starting the CICS ECI RPC Server	16
Stopping the RPC Server	16
Running the RPC Server as a Windows Service	17
Application Identification	18
4 Preparing IBM CICS for ECI	19
Defining an ECI Service	20
Installation Verification	20
Error Handling	21
5 Server-side Mapping Files	23
Server-side Mapping Files in the RPC Server	24
Deploying Server-side Mapping Files to the RPC Server	24
Undeploying Server-side Mapping Files from the RPC Server	24
Change Management of Server-side Mapping Files	25
List Deployed Server-side Mapping Files	25
Check if a Server-side Mapping File Revision has been Deployed	25
Is There a Way to Smoothly Introduce Server-side Mapping Files?	25
6 Scenarios	27
COBOL Scenarios	28

1 About this Documentation

▪ Document Conventions	2
▪ Online Information and Support	2
▪ Data Protection	3

Document Conventions

Convention	Description
Bold	Identifies elements on a screen.
Monospace font	Identifies service names and locations in the format <i>folder.subfolder.service</i> , APIs, Java classes, methods, properties.
<i>Italic</i>	Identifies: Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies: Text you must type in. Messages displayed by the system. Program code.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the symbol.
[]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

Online Information and Support

Software AG Documentation Website

You can find documentation on the Software AG Documentation website at <http://documentation.softwareag.com>. The site requires credentials for Software AG's Product Support site Empower. If you do not have Empower credentials, you must use the TECHcommunity website.

Software AG Empower Product Support Website

If you do not yet have an account for Empower, send an email to empower@softwareag.com with your name, company, and company email address and request an account.

Once you have an account, you can open Support Incidents online via the eService section of Empower at <https://empower.softwareag.com/>.

You can find product information on the Software AG Empower Product Support website at <https://empower.softwareag.com>.

To submit feature/enhancement requests, get information about product availability, and download products, go to [Products](#).

To get information about fixes and to read early warnings, technical papers, and knowledge base articles, go to the [Knowledge Center](#).

If you have any questions, you can find a local or toll-free number for your country in our Global Support Contact Directory at https://empower.softwareag.com/public_directory.asp and give us a call.

Software AG TECHcommunity

You can find documentation and other technical information on the Software AG TECHcommunity website at <http://techcommunity.softwareag.com>. You can:

- Access product documentation, if you have TECHcommunity credentials. If you do not, you will need to register and specify "Documentation" as an area of interest.
- Access articles, code samples, demos, and tutorials.
- Use the online discussion forums, moderated by Software AG professionals, to ask questions, discuss best practices, and learn how other customers are using Software AG technology.
- Link to external websites that discuss open standards and web technology.

Data Protection


Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.

2 Introduction to the CICS ECI RPC Server

- Overview 6
- Worker Models 7

Overview

The CICS ECI RPC Server acts on one side as an RPC server and on the other side as a client for CICS ECI. The CICS ECI RPC Server is a Java-based component that can run on a different host to the one where CICS is running. This allows it to operate with a zero footprint of EntireX on the CICS host.




For local extraction, all source files have to be stored locally on the same machine where the EntireX Workbench is running.

- For existing CICS COBOL programs, use the *Software AG IDL Extractor for COBOL* to extract the *Software AG IDL File* in the IDL Editor documentation for the RPC clients.
- For existing CICS PL/I programs, use the *Software AG IDL Extractor for PL/I* to extract the *Software AG IDL File* in the IDL Editor documentation for the RPC clients.

Remote extraction requires an RPC server running under z/OS with Extractor Service (Batch | IMS).

- For COBOL, see *Step 2: Select a COBOL Extractor Environment or Create a New One* in the IDL Extractor for COBOL documentation.
- For PL/I, see *Extract Software AG IDL File from a Remote PL/I RPC Environment* in the IDL Extractor for PL/I documentation.

Worker Models



RPC requests are worked off inside the RPC server in worker threads. Every RPC request occupies during its processing a worker thread. If you are using RPC conversations, each RPC conversation requires its own thread during the lifetime of the conversation. The CICS ECI RPC Server can adjust the number of worker threads to the number of parallel requests. Use the properties `entirex.server.fixedservers`, `entirex.server.maxservers` and `entirex.server.minservers` to configure this scalability. The CICS ECI RPC Server provides two worker models:

The *fixed* model creates a fixed number of worker threads. If `entirex.server.fixedservers=yes`, the number of worker threads is specified in `entirex.server.minservers` is started and the server can process this number of parallel requests.

- **FIXED**

- **SCALE**

The *scale* model creates worker threads depending on the incoming load of RPC requests. If `entirex.server.fixedservers=no`, the number of worker threads balances between what is specified in `entirex.server.minservers` and what is specified in `entirex.server.maxservers`. This is done by a so-called attach thread. At startup, the number of worker threads is the number specified in `entirex.server.minservers`. A new worker thread starts if the broker has more requests than there are worker threads waiting. If more than the number specified in `entirex.server.minservers` are waiting for requests, a worker thread stops if its receive call times out. The timeout period is configured with `entirex.server.waitserver`.

3 Administering the EntireX CICS® ECI RPC Server

- Customizing the CICS ECI RPC Server 10
- Configuring the RPC Server Side 12
- Configuring the CICS ECI Side 14
- Using SSL/TLS with the RPC Server 15
- Starting the CICS ECI RPC Server 16
- Stopping the RPC Server 16
- Running the RPC Server as a Windows Service 17
- Application Identification 18

The EntireX CICS® ECI RPC Server allows standard RPC clients to communicate with CICS programs running on IBM CICS®. It supports the programming languages COBOL and PL/I and transforms the RPC requests from clients into messages to CICS ECI.

Customizing the CICS ECI RPC Server

The following are used to set up the CICS ECI RPC Server:


- [Configuration File](#)
- [Start Script](#)

Configuration File

The default name of the configuration file is *entirex.cicseci.properties*. The CICS ECI RPC Server searches for this file in the current working directory.

You can set the name of the configuration file with `-Dentirex.server.properties=<your file name>` with `/` as file separator.

The configuration file contains the configuration for both parts of the CICS ECI RPC Server.



Configuring more than one CICS ECI RPC Server

If you configure more than one CICS ECI RPC Server that connect to the same broker, the following items must be distinct:

- the trace output file (property `entirex.server.logfile`)
- the log for the Windows Service (property `entirex.server.serverlog`)

Start Script

The start script for the CICS ECI RPC Server is called *cicseciserver.bsh* (UNIX) or *cicseciserver.bat* (Windows) and is provided in the *bin* folder of the installation directory. You may customize this file. The CICS ECI RPC Server itself is contained in the file *entirex.jar*.

Configuring the RPC Server Side

The CICS ECI RPC Server uses the properties that start with “`entirex.server`” for configuring the RPC server side.

Alternatively to the properties, you can use the command-line options. These have a higher priority than the properties set as Java system properties, and these have higher priority than the properties in the configuration file.

Property Name	Command-line Option	Default	Explanation
<code>entirex.bridge.verbose</code>		no	Verbose/trace mode of CICS ECI RPC Server. Set this to "yes" to trace sent to CICS ECI.
<code>entirex.server.brokerid</code>	<code>-broker</code>	localhost	Broker ID. See <i>URL-style Broker ID</i> .
<code>entirex.server.serveraddress</code>	<code>-server</code>	RPC/SRV1/CALLNAT	Server address.
<code>entirex.server.userid</code>	<code>-user</code>	CICSECIRPCServer	The user ID for the Broker for RPC. See <code>entirex.server.password</code> .
<code>entirex.server.fixedservers</code>		no	If no, use attach thread to manage worker threads; see SCALE . Otherwise run a fixed number of worker threads; see FIXED .
<code>entirex.server.minservers</code>		1	Minimum number of server threads.
<code>entirex.server.maxservers</code>		32	Maximum number of server threads.
<code>entirex.server.restartcycles</code>	<code>-restartcycles</code>	15	Number of restart attempts if the Broker is not available. This can be used to keep the CICS ECI RPC Server running while the Broker is down for a short time.
<code>entirex.server.password</code>	<code>-password</code>		The password for secured access to the Broker. The password is encrypted and written to the property <code>entirex.server.password.e</code> . To change the password, set the new password in the properties file (default is <code>entirex.cicseci.properties</code>). To disable password encryption set <code>entirex.server.passwordencrypt=no</code> . Default for this property is "yes".
<code>entirex.server.security</code>	<code>-security</code>	no	no yes auto name of BrokerSecurity object

Property Name	Command-line Option	Default	Explanation
entirex.server.compresslevel	-compresslevel	0	Permitted values (you can enter the text or the numeric value) BEST_COMPRESSION 9 BEST_SPEED 1 DEFAULT_COMPRESSION -1, mapped to 6 DEFLATED 8 NO_COMPRESSION 0 N 0 Y 8
entirex.server.waitattach		600S	Wait timeout for the attach server thread.
entirex.server.waitserver		300S	Wait timeout for the worker threads.
entirex.timeout		20	TCP/IP transport timeout. See <i>Setting the Transport Timeout</i> under <i>Writing Advanced Applications - EntireX Java ACI</i> .
entirex.server.verbose	-verbose	no	Enable verbose output to the log file.
	-help		Display usage of the command-line parameters.
entirex.server.logfile	-logfile		Name of the log file, default is standard output.
entirex.trace	-trace	0	Trace level (1,2,3).

Configuring the CICS ECI Side

These properties are used to configure the connection to CICS ECI.

Alternatively, you can use the command-line options. These have a higher priority than the properties set as Java system properties, and these have higher priority than the properties in the configuration file.

Name	Default Value	Explanation
cics.host		Host name of CICS ECI. Mandatory.
cics.port		Port number of CICS ECI. Mandatory.
cics.transaction		Name of the CICS mirror transaction that will receive transactions. Mandatory.
entirex.bridge.targetencoding	cp037	Specify the appropriate EBCDIC encoding used by your CICS ECI. This codepage is also used when communicating with the EntireX Broker. Note: Enable conversion in the Broker attribute file so the data can be converted correctly, typically by setting service-specific attribute CONVERSION to "SAGTCHA". Default "cp037" is EBCDIC codepage with full Latin-1 character set.
cics.sockettimeout	10000	Socket timeout for connection to CICS ECI (in milliseconds).
cics.userid		RACF user ID. Maximum 8 bytes (optional).
cics.password		RACF password/PassTicket. Maximum 8 bytes (optional).
cics.sslparams		SSL parameters (optional). Same syntax as Broker ID.
cics.mapping.folder		The folder where the RPC server expects server-side mapping files (EntireX Workbench files with extension .svm). See Deploying Server-side Mapping Files to the RPC Server and Undeploying Server-side Mapping Files from the RPC Server . There are also client-side mapping files that do not require configuration here. See Server Mapping Files for COBOL . If <i>no</i> server requires server-side mapping, you can omit this property. If <i>one</i> server requires server-side mapping, this property must be specified.

Using SSL/TLS with the RPC Server

To use SSL with the CICS ECI RPC Server, you need to configure two sides:

■ CICS ECI Side

See parameter `cics.sslparams` under [Configuring the CICS ECI Side](#).

■ RPC Server Side

RPC servers can use Secure Sockets Layer/Transport Layer Security (SSL/TLS) as the transport medium. The term “SSL” in this section refers to both SSL and TLS. RPC-based servers are always SSL clients. The SSL server can be either the EntireX Broker or Broker SSL Agent. For an introduction see *SSL/TLS and Certificates with EntireX* in the EntireX Security documentation.

➤ To use SSL

- 1 To operate with SSL, certificates need to be provided and maintained. Depending on the platform, Software AG provides default certificates, but we strongly recommend that you create your own. See *SSL/TLS Sample Certificates Delivered with EntireX* in the EntireX Security documentation.
- 2 Set up the CICS ECI RPC Server for an SSL connection.

Use the *URL-style Broker ID* with protocol `ssl://` for the Broker ID. If no port number is specified, port 1958 is used as default. Example:

```
ssl://localhost:22101?trust_store=C:\SoftwareAG\EntireX\etc\ExxCACert.jks?verify_server=no
```

If the SSL client checks the validity of the SSL server only, this is known as *one-way SSL*. The mandatory `trust_store` parameter specifies the file name of a keystore that must contain the list of trusted certificate authorities for the certificate of the SSL server. By default a check is made that the certificate of the SSL server is issued for the hostname specified in the Broker ID. The common name of the subject entry in the server's certificate is checked against the hostname. If they do not match, the connection will be refused. You can disable this check with SSL parameter `verify_server=no`.

If the SSL server additionally checks the identity of the SSL client, this is known as *two-way SSL*. In this case the SSL server requests a client certificate (the parameter `verify_client=yes` is defined in the configuration of the SSL server). Two additional SSL parameters must be specified on the SSL client side: `key_store` and `key_passwd`. This keystore must contain the private key of the SSL client. The password that protects the private key is specified with `key_passwd`.

The ampersand (&) character cannot appear in the password.

SSL parameters are separated by ampersand (&). See also *SSL/TLS Parameters for SSL Clients*.

- 3 Make sure the SSL server to which the RPC side connects is prepared for SSL connections as well. The SSL server can be EntireX Broker or Broker SSL Agent. See:
 - *Running Broker with SSL/TLS Transport* in the platform-specific Administration documentation
 - *Setting up and Administering the EntireX Broker SSL Agent* in the UNIX and Windows Administration documentation

Starting the CICS ECI RPC Server

➤ To start the CICS ECI RPC Server

- Use the [Start Script](#).

Or:

Under Windows you can use the CICS ECI RPC Server as a Windows Service. See [Running the RPC Server as a Windows Service](#).

Stopping the RPC Server

➤ To stop the CICS ECI RPC Server

- Use the command `stopServer`. See [Stop EntireX Broker Server Instances in Command Central's Command-line Interface](#).

Or:

Stop the server instance using Command Central's Graphical User Interface. See [Stopping a Server Instance](#).

Or:

Use the command `stopService`. See [Stop Running EntireX Broker Services in Command Central's Command-line Interface](#).

Or:

Stop the service using Command Central's Graphical User Interface. See [Stopping a Service](#).

Or:

Use the command-line utility `etbcmd`. See `ETBCMD` under *Broker Command-line Utilities* in the platform-specific Administration documentation.

Or:

Use `CTRL-C` in the session where you started the RPC server instance.

Or:

Under UNIX, enter command `kill -process-id`.

Running the RPC Server as a Windows Service

For general information see *Running an EntireX RPC Server as a Windows Service*.

➤ To run the CICS ECI RPC Server as a Windows Service

- 1 Customize the *Start Script* according to your system installation.



Note: The script must pass external parameters to the RPC server and use the reduced signaling of the JVM (option `-Xrs`):

```
java -Xrs com.softwareag.entirex.cics.bridge.CicsRPCServer %*
```

If `-Xrs` is not used, the JVM stops and an entry 10164002 is written to the event log when the user logs off from Windows.

See also *Starting the RPC Server*.

- 2 Test your RPC server to see whether it will start if you run your script file.
- 3 Use the *EntireX RPC Service Tool* and install the `RPCService` with some meaningful extension, for example `MyServer`. If your *Start Script* is `cicseciserver.bat`, the command will be

```
RPCService -install -ext MyServer ←  
-script install_path\EntireX\bin\cicseciserver.bat
```

The log file will be called `RPCservice_MyServer.log`.

- 4 In **Windows Services** menu (**Control Panel > Administrative Tools > Services**) select the service: `Software AG EntireX RPC Service [MyServer]` and change the property `Startup Type` from "Manual" to "Automatic".

Application Identification

The application identification is sent from the CICS ECI RPC Server to the Broker. It is visible with Broker Command and Information Services.

The identification consists of four parts: name, node, type, and version. These four parts are sent with each Broker call and are visible in the trace information.

For the CICS ECI RPC Server, these values are:

Identification Part	Value
Application name	ANAME=CICS ECI RPC Server
Node name	ANODE=<host name>
Application type	ATYPE=Java
Version	AVERS=9.12.0.0

4 Preparing IBM CICS for ECI

- Defining an ECI Service 20
- Installation Verification 20
- Error Handling 21

This chapter describes how to set up the External Call Interface (ECI) within CICS

 **Important:** If the terms and concepts in this chapter are unfamiliar to you, please work with the appropriate CICS system programmer. Only authorized personnel should make changes to mainframe computer systems.

Defining an ECI Service

The `DFH$SOT` group contains three TCP/IP services. For our purposes, the pertinent service is ECI. The ECI service has, defined in it, the TCP/IP port number through which the CICS region listens to the ECI. By default, IBM predefines the TCP/IP port number as "1435". If this port is already reserved for another CICS region, you may have to define a different port number in the ECI service. For more information, see your IBM documentation.

You must specify `SOCKETCLOSE(NO)` on the `TCPIPService`. If you need to specify a timeout for a task initiated using ECI over TCP/IP, specify an `RTIMOUT` value on the mirror transaction. Note that the standard mirror, `CPMI`, is defined with profile `DFHCICSA`, which specifies `RTIMOUT(NO)`. This means that long running mirrors will wait indefinitely for data, unless you specify a different `RTIMOUT` for the mirror transaction.

➤ To define an ECI service without security

- 1 Use `CEDA ALTER` to supply the `ECI TCPIPService` with a unique TCP/IP port number.
- 2 Use `CEDA ALTER` to set the `ECI Attachsec` to "LOCAL"

➤ To define an ECI service with security

- 1 Copy the `ECI TCPIPService` to an `ECIS TCPIPService`.
- 2 Use `CEDA ALTER` to supply the `ECIS TCPIPService` with a unique TCP/IP port number.
- 3 Use `CEDA ALTER` to set the `ECIS Attachsec` to "VERIFY".

Installation Verification

A successful installation should pass the following verification tests:

1. `CEMT INQUIRE TCPIPService(*)` should now display your services with status OPE. A status of CLO might indicate an already used (not unique) TCP/IP port number.
2. `CEMT I TCPIPService(ECI)` to verify `TCPIPService` in CICS.
3. `CEMT I TRA(CIEP)` to verify Transaction CIEP in CICS.

4. CEMT I PROGRAM(DFHI EP) to verify Program DFHI EP in CICS.
5. CEMT I TRAN(CPMI) to verify Transaction CPMI in CICS.
6. CEMT I PROGRAM(DFHMIRS) to verify Program DFHMIRS in CICS.
7. CEMT I TD(CIEO) to verify Program TQ Queue CIEO.
8. Verify that the groups DFHISC DFHDCTG and DFHIPECI are added to the active autoinstall.



Tip: You can check the mentioned programs and transactions and TD queues by using CEMT INQUIRE TCP/IP.

Error Handling

This section describes the handling of errors in the CICS ECI connection or the CICS ECI RPC server.

Problem	Handling
A CICS program sends abend code in response.	The CICS session is closed and the next call opens a different session.
The TCP/IP connection is lost with a <code>SocketTimeoutException</code> .	The CICS session is closed and the next call opens a different session.
The TCP/IP connection is lost with an <code>EOFException</code> .	<ul style="list-style-type: none"> ■ The TCP/IP socket is closed and the next call opens a different session. ■ There are no further attempts to send bytes on the TCP/IP connection that received the <code>EOFException</code>.

5 Server-side Mapping Files

- Server-side Mapping Files in the RPC Server 24
- Deploying Server-side Mapping Files to the RPC Server 24
- Undeploying Server-side Mapping Files from the RPC Server 24
- Change Management of Server-side Mapping Files 25
- List Deployed Server-side Mapping Files 25
- Check if a Server-side Mapping File Revision has been Deployed 25
- Is There a Way to Smoothly Introduce Server-side Mapping Files? 25

Server mapping enables the RPC server to correctly support special COBOL syntax such as `REDEFINES`, `SIGN LEADING` and `OCCURS DEPENDING ON` clauses, `LEVEL-88` fields, etc. If one of these elements is used, the IDL Extractor for COBOL automatically extracts a server mapping file in addition to the IDL file (interface definition language). Also, the COBOL Wrapper may generate a server mapping file for RPC server generation. The server mapping is used at runtime to marshal and unmarshal the RPC data stream. There are client-side mapping files (EntireX Workbench files with extension `.cvm`) and server-side mapping files (Workbench files with extension `.svm`). If you have not used server-side mapping, we recommend you use client-side mapping. See *Server Mapping Files for COBOL* in the EntireX Workbench documentation.

See also *Source Control of Server Mapping Files* | *Comparing Server Mapping Files* | *When is a Server Mapping File Required?* | *Migrating Server Mapping Files* in the EntireX Workbench documentation.

Server-side Mapping Files in the RPC Server

Deploying Server-side Mapping Files to the RPC Server

Deploy a server-side mapping file (Workbench file with extension `.svm`) to the RPC server manually. See *Server Mapping Files for COBOL* in the EntireX Workbench documentation.

➤ To deploy a server-side mapping file

- 1 Make sure the server-side mapping container (directory or folder) is configured. See [Server-side Mapping Files in the RPC Server](#).
- 2 Copy the server-side mapping file to the server-side mapping container.

Undeploying Server-side Mapping Files from the RPC Server

Undeploy a server mapping file (Workbench file with extension `.svm`) from the RPC server manually. See *Server Mapping Files for COBOL*.

➤ To undeploy a server-side mapping file manually

- Delete the server-side mapping file from the server-side mapping container (directory or folder). See *Server Mapping Files for COBOL*.

Change Management of Server-side Mapping Files

Under UNIX and Windows, change management for a directory or folder (server-side mapping container, see [Server-side Mapping Files in the RPC Server](#)) is similar to change management within ordinary operating system directories (folders). All updates to the directory or folder done after a backup must be kept.

All EntireX Workbench server-side mapping files (.svm) added since the last backup should be available. See *Server Mapping Files for COBOL* in the EntireX Workbench documentation.

List Deployed Server-side Mapping Files

Use the Windows Explorer or the UNIX `ls` command to list the contents of the server-side mapping container (directory or folder). See [Server-side Mapping Files in the RPC Server](#).

Check if a Server-side Mapping File Revision has been Deployed

Server-side mapping files in the server-side mapping container correspond to EntireX Workbench files with extension .svm (same format). See *Server Mapping Files for COBOL* in the EntireX Workbench documentation. Each line relates to an IDL program and contains a creation timestamp at offset 276 (decimal) in the format `YYYYMMDDHHIISST`. Precision is 1/10 of a second. The creation timestamp can be checked.

The timestamp can be found on the same offset in the server-side mapping files stored in the server-side mapping container (directory or folder). See [Server-side Mapping Files in the RPC Server](#).

Is There a Way to Smoothly Introduce Server-side Mapping Files?

All EntireX RPC servers can be executed without server-side mapping files. See [Server-side Mapping Files in the RPC Server](#). There is no need to install the server-side mapping container if the following conditions are met:

- You do not use features that require server mapping; see *When is a Server Mapping File Required?*
- Server-side type of COBOL mapping is switched on in the EntireX Workbench. If you have not used server-side mapping, we recommend you use client-side mapping. See *Server Mapping Files for COBOL*.

You can also call COBOL servers generated or extracted with previous versions of EntireX mixed with a COBOL server that requires server-side mapping. All EntireX RPC servers are backward compatible.

6 Scenarios

- COBOL Scenarios 28

COBOL Scenarios

Scenario I: Calling an Existing COBOL Server

➤ To call an existing COBOL server

- 1 Use the IDL Extractor for COBOL to extract the Software AG IDL and, depending on the complexity, also a server mapping file. See *When is a Server Mapping File Required?* in the EntireX Workbench documentation.
- 2 Build an EntireX RPC client using any EntireX wrapper. For a quick test you can:
 - use the IDL Tester; see *EntireX IDL Tester* in the EntireX Workbench documentation
 - generate an XML mapping file (XMM) and use the XML Tester for verification; see *EntireX XML Tester* in the XML/SOAP Wrapper documentation

See *Basic RPC Server Examples - CALC, SQUARE* for COBOL RPC Server examples.

Scenario II: Writing a New COBOL Server

➤ To write a new COBOL server

- 1 Use the COBOL Wrapper to generate a COBOL server skeleton and, depending on the complexity, also a server mapping file. See *When is a Server Mapping File Required?* in the EntireX Workbench documentation. Write your COBOL server and proceed as described under *Using the COBOL Wrapper for the Server Side*.
- 2 Build an EntireX RPC client using any EntireX wrapper. For a quick test you can:
 - use the IDL Tester; see *EntireX IDL Tester* in the EntireX Workbench documentation
 - generate an XML mapping file (XMM) and use the XML Tester for verification; see *EntireX XML Tester* in the XML/SOAP Wrapper documentation

See *Basic RPC Server Examples - CALC, SQUARE* for COBOL RPC Server examples.