

webMethods EntireX

Installing EntireX under BS2000/OSD

Version 9.5 SP1

November 2013

This document applies to webMethods EntireX Version 9.5 SP1.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 1997-2013 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors..

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://documentation.softwareag.com/legal/>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://documentation.softwareag.com/legal/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices and license terms, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". This document is part of the product documentation, located at <http://documentation.softwareag.com/legal/> and/or in the root installation directory of the licensed product(s).

Document ID: EXX-INSTALL_BS2000-95SP1-20140628

Table of Contents

Installing EntireX under BS2000/OSD	v
1 Prerequisites	1
2 General Information	5
Distribution Media	6
Installation Jobs	6
Contents of Installation Medium	6
Copying the Contents of the Installation Medium to Disk	7
3 Installing the EntireX Broker under BS2000/OSD	9
Introduction	10
Overview of Broker Installation Steps	10
Verifying the Installation of the Broker	18
4 Installing the BS2000/OSD Batch RPC Server	21
Step 1: Define an RPC SVM File	22
Step 2: Customize the BS2000/OSD Batch RPC Server Configuration File RPC-CONFIG	22
Step 3: Customize ADALNK Parameter File RPC-ADAPARM	24
Step 4: Customize the BS2000/OSD Batch RPC Server Startup JCL	24
Starting the RPC Server	26
Stopping the RPC Server	26
Verifying the Installation of the BS2000/OSD Batch RPC Server	28
5 Installing EntireX Security under BS2000/OSD	29
Installing EntireX Security for Broker Kernel	30
Installing EntireX Security for Applications Using Broker Stubs	30

Installing EntireX under BS2000/OSD

This document describes how to install and operate the BS2000/OSD components of EntireX.

<i>General Information</i>	An overview of resources delivered.
<i>Installing the EntireX Broker under BS2000/OSD</i>	How to install and start the EntireX Broker under BS2000/OSD.
<i>Installing the BS2000/OSD Batch RPC Server</i>	How to install and start the EntireX BS2000/OSD Batch RPC Server.
<i>Installing EntireX Security under BS2000/OSD</i>	Provides information required for installing EntireX Security under BS2000/OSD.



Note: If you want to use EntireX on BS2000/OSD together with the Eclipse-based EntireX Workbench components, you need to install the respective EntireX components under UNIX or Windows, using the Software AG Installer. See the separate Software AG Installer documentation under *webMethods Product Documentation > webMethods Product Suite > Documentation by Product > System Requirements, Installation, and Upgrade* on the [Software AG Product Documentation](#) website.

Related Literature

- *Administration of EntireX under BS2000/OSD*
- *BS2000/OSD Batch RPC Server*

1 Prerequisites

Component	Prerequisites
EntireX Broker	<ul style="list-style-type: none">■ BS2000/OSD V6.0, V7.0, V8.0, V9.0■ WAL814 or above
Batch RPC Server	<ul style="list-style-type: none">■ BS2000/OSD V6.0, V7.0, V8.0, V9.0■ WAL814 or above■ If applicable, see prerequisites for C Wrapper COBOL Wrapper.
Broker Stubs	<ul style="list-style-type: none">■ BS2000/OSD V6.0, V7.0, V8.0, V9.0■ WAL814 or above
Workbench	<ul style="list-style-type: none">■ General Prerequisites<ul style="list-style-type: none">■ EntireX Workbench version 9.0.■ For the client side, see prerequisites for Broker stubs.■ For the server side, an RPC server. See prerequisites for relevant RPC server above.■ COBOL Wrapper<p>To compile the applications generated by the EntireX Workbench component COBOL Wrapper: the IDL types U or UV require a compiler that supports COBOL data type NATIONAL, for example COBOL2000 V01.4B00, otherwise any ILCS-enabled COBOL compiler on BS2000/OSD.</p>■ C Wrapper<p>To compile the applications generated by the EntireX Workbench component C Wrapper: any ILCS-enabled C/C++ compiler on BS2000/OSD</p>■ IDL Extractor for Natural<p>To extract from BS2000/OSD, a standard Natural RPC server is required with one of the following Natural versions. The scope of the generation depends on the version:</p><ul style="list-style-type: none">■ Natural 4.2.7.4 is required for improved handling if IDL extractions fails.■ Natural 4.2.7 or higher is required to make use of the following features:

Component	Prerequisites
	<ul style="list-style-type: none"> ■ during runtime to support a redesigned interface including support for REDEFINES, map to suppress etc. ■ optional replacing of special characters ("@" in parameter names by underscore for object extractions ■ Natural 4.2.6.2 or higher is required for object extractions to make use of the following features (introduced with EntireX 8.1 SP2): <ul style="list-style-type: none"> ■ Optional replacing of special characters ("#", "\$", "&", "/") in parameter names by underscore ■ Hints (comments) in extracted IDL per parameter for restrictions and usage where appropriate. ■ Support for Natural V-arrays (Natural syntax: A100/1:V). They are mapped to IDL unbounded arrays. ■ Combinations of Natural X-array dimensions together with Natural V-array dimensions (Natural syntax: A100/1:*,1:V) are supported. They are mapped to IDL unbounded arrays. ■ Natural 4.2.6.1 or lower can be used, but if extracted from objects there is no support of features supported by Natural 4.2.6.2 (see above). ■ Natural Wrapper <p>To generate a client interface object, a standard Natural RPC server is required with one of the following Natural versions. The scope of the generation depends on the version:</p> <ul style="list-style-type: none"> ■ Natural 4.2.7.11 or higher or Natural 8.2.2.6 or higher is required to disable/enable the generation of Natural client test programs. See <i>Step 4a: Customize Natural Client Names and Save Remotely (Optional)</i> <i>Step 4b: Customize Natural Client Names and Save Locally (Optional)</i>. ■ Natural 4.2.7.8 or higher or Natural 8.2.2.2 or higher is required to adapt the names for the Natural client interface objects (subprograms (NSNs) with their parameter data areas (PDAs)). See <i>Step 4a: Customize Natural Client Names and Save Remotely (Optional)</i> <i>Step 4b: Customize Natural Client Names and Save Locally (Optional)</i>. ■ Natural 4.2.7.4 or higher is required if a CVM File is used in addition to an IDL file to support features introduced with EntireX 8.2 such as multiple Natural subprogram interfaces, REDEFINES or map to suppress. See <i>Redesigning the Extracted Interface</i> in the IDL Extractor for Natural documentation. ■ Natural 4.2.6.2 or higher generates Natural client interface objects, separate Natural parameter data areas (PDAs) and Natural client test programs. ■ Natural 4.2.5.5 to Natural 4.2.6.1 generates Natural client interface objects only. <p>To generate a server skeleton, a standard Natural RPC server is required with Natural version 4.2.7.11 or higher or Natural 8.2.2.6 or higher. See <i>Using the Natural Wrapper for the Server Side</i>.</p>

Additional Notes for BS2000/OSD■ **Entire Net-Work**

EntireX works with any supported version of Entire Net-Work. We recommend you use the latest version, which for BS2000/OSD is currently WCP 6.2.1.

- The Adabas version we recommend is ADA 8.1.4.

2 General Information

- Distribution Media 6
- Instalation Jobs 6
- Contents of Installation Medium 6
- Copying the Contents of the Installation Medium to Disk 7

This chapter covers the following topics:

Distribution Media

All BS2000/OSD components of EntireX are distributed on the supplied mainframe installation medium including the EntireX license certificate. A license certificate can also be sent by e-mail.

Installation Jobs

The installation of Software AG products on mainframe platforms is performed by installation jobs. These jobs are contained in the delivered files. The System Maintenance Aid (SMA) generates the following jobs:

- Copy the contents of the installation medium to disk.
- Load the INPL and ERRN files.

Contents of Installation Medium

The installation medium contains the files listed in the table below. The sequence of the files, the file types, the number of library blocks needed and the space each file requires on disk are shown in the Software AG Product Delivery Report, which accompanies the installation medium. During installation, the files are loaded from the installation medium.

File Name	Type
EXX951.JOBS	EntireX Broker jobs and configuration.
EXX951.LIB	EntireX Broker components, stubs and examples.
EXX951.SYSF	Adabas persistent store FDT.
EXB951.INPL	Contains Natural sample programs (SYSETB).
EXB951.ERRN	SYSETB error messages.
WAL825.MOD	Adabas components required to run EntireX Broker.
WAL825.SRC	Adabas components source library.
EXP951.JOBS	BS2000/OSD Batch RPC Server jobs and configuration.
EXP951.LIB	BS2000/OSD Batch RPC Server components.
EXP951.CSRV	C server examples library.
EXP951.COBS	COBOL server examples library.
EXP951.COBC	COBOL client examples library.

Copying the Contents of the Installation Medium to Disk

If you are not using SMA, use the procedure described below and supply the values specified below.

To copy the data sets from installation medium to disk, perform the following steps:

1. Copy the Library SRVnnn.LIB from Installation Medium to Disk

This step is not necessary if you have already copied the library SRVnnn.LIB from another Software AG installation medium. For more information, refer to the element #READ-ME in this library.

The library SRVnnn.LIB is stored on the installation medium as the sequential file SRVnnn.LIBS containing LMS commands. The current version *nnn* can be obtained from the **Software AG Product Delivery Report**. To convert this sequential file into an LMS library, execute the following commands:

```
/IMPORT-FILE SUPPORT=*TAPE(FILE-NAME=SRVnnn.LIBS, -
/ VOLUME=<volser>, DEV-TYPE=<tape-device>)
/ADD-FILE-LINK LINK-NAME=EDTSAM, FILE-NAME=SRVnnn.LIBS, -
/ SUPPORT=*TAPE(FILE-SEQ=3), ACC-METH=*BY-CAT, -
/ BUF-LEN=*BY-CAT, REC-FORM=*BY-CAT, REC-SIZE=*BY-CAT
/START-EDT
@READ '/'
@SYSTEM 'REMOVE-FILE-LINK EDTSAM'
@SYSTEM 'EXPORT-FILE FILE-NAME=SRVnnn.LIBS'
@WRITE 'SRVnnn.LIBS'
@HALT
/ASS-SYSDTA SRVnnn.LIBS
/MOD-JOB-SW ON=1
/START-PROG $LMS
/MOD-JOB-SW OFF=1
/ASS-SYSDTA *PRIMARY
```

where *tape-device* is the device type of the installation medium, e.g. TAPE-C4

volser is the VOLSER of the installation medium (see Software AG Product Delivery Report)

2. Copy the Procedure COPY.PROC from Installation Medium to Disk

To copy the procedure COPY .PROC to disk, call the procedure P .COPYTAPE in the library SRV vrs.LIB:

```
/CALL-PROCEDURE (SRVnnn.LIB,P.COPYTAPE), -  
/ (VSNT=<volser>, DEVT=<tape-device>)
```

If you use a TAPE-C4 device, you may omit the parameter DEVT.

3. Copy all Product Files from Installation Medium to Disk

To copy all Software AG product files from installation medium to disk, enter the procedure COPY .PROC:

```
/ENTER-PROCEDURE COPY.PROC, DEVT=<tape-device>
```

If you use a TAPE-C4 device, you may omit the parameter DEVT. The result of this procedure is written to the file L.REPORT.SRV.

When the files have been copied to disk, continue with the steps described under *Installing the EntireX Broker under BS2000/OSD* and *Installing the BS2000/OSD Batch RPC Server*.

3 Installing the EntireX Broker under BS2000/OSD

- Introduction 10
- Overview of Broker Installation Steps 10
- Verifying the Installation of the Broker 18

This section explains how to install and start the EntireX Broker on BS2000/OSD. It covers the following topics:

Introduction

When installing EntireX Broker, all modifications are done to the J and S elements - job control (J-elements) and parameter files (S-elements) - located in EXX951.JOBS. All job control and parameter elements contain a preconfiguration which enables you to install EntireX Broker with much less effort. Using this preconfiguration requires that all libraries be located under the same BS2000 user ID.



Note: Installation prerequisites are described centrally. See *BS2000/OSD Prerequisites* in the EntireX Release Notes. Make sure these are met before you start installation. It is important to upgrade your libraries first.

Overview of Broker Installation Steps

This section describes the following installation steps

- [Install the License Certificate](#)
- [Customize the EntireX Broker Attribute File](#)
- [Customize the ADALNK Parameters File](#)
- [Customize the EntireX Broker Startup JCL and Start EntireX Broker](#)
- [Start EntireX Broker](#)
- [Stop EntireX Broker](#)
- [Creating a Broker Persistent Store \(optional\)](#)
- [Set up the EntireX Broker Security Server for BS2000/OSD \(optional\)](#)
- [Load the SYSETB INPL and ERRN Files \(optional\)](#)

Install the License Certificate

There are two types of license file:

- One is delivered on installation medium (EXX951.LICS)
- The other, in ASCII format, you may have received by e-mail (EXX951.XML) or on a CD. To make this file available for EntireX, transfer it in binary format to BS2000/OSD, using FTP. Make sure that the target file on BS2000/OSD is allocated with `FILE-STRUCTURE = SAM` and `BUF-LEN = STD(2)`.

When uploading the license file to BS2000/OSD, you can use the following FTP commands to create the required file structure:

```
LITERAL FILE EXX951.LICS, RECSIZE=0, RECFORM=V, BLKSIZE=(STD,2), OPEN=UPDATE, ←
FCBTYPE=SAM
BIN
PUT EXX951.XML EXX951.LICS
```

Customize the EntireX Broker Attribute File

ETB-ATTR is a sample broker attribute file. Customize the attribute settings to suit your needs.

To run a minimal configuration of EntireX Broker that is suitable to execute the verification programs BCOC and BCOS, set up the following parameters:

Parameter	Description
BROKER-ID= ETB<nnnnn>	Identifies the Broker to which the attribute file applies. The Broker ID must be unique per machine
NODE= <node-id>	A DBID under which EntireX Broker is visible in the system
IDTNAME= ADA<xxxxx>	Specifies the ID table name under which EntireX Broker will be accessible
PORT= <port>	A free port number EntireX Broker listens on for TCP/IP communication. Depending on the system settings, free port numbers under BS2000/OSD start with port numbers greater than 4096

For a full description of all parameters, see *Broker Attributes* in the administration documentation.

Customize the ADALNK Parameters File

The verification programs BCOS and BCOC, the command and information services utilities ETBCMD and ETBINFO, the publish and subscribe examples PUB and SUB as well as the Adabas persistent store require the ADALNK parameter IDTNAME to be set. See also [Verifying the Installation of the Broker](#) and step [Creating a Broker Persistent Store \(optional\)](#) below.

Parameter	Description
ADALNK IDTNAME= ADA<xxxxx>	Specifies the ID table name under which EntireX Broker is accessible.

Customize the EntireX Broker Startup JCL and Start EntireX Broker

The job control delivered with EntireX Broker uses BS2000/OSD S-procedures. We strongly recommend you do not modify START-BROKER. This procedure is recursively called to establish the broker environment. Modifications should only be done to the PARAMETER-DECLARATION section as described below. If all EntireX Broker components are installed under the same BS2000/OSD user ID, and all previous installation steps have been done using the default settings, no modifications to START-BROKER are necessary.

Startup Parameter	Description	Default
LICENSE-FILE	License certificate file.	EXX951.LICS
EXX-LIB	EntireX Broker library.	EXX951.LIB
EXX-JOBS	EntireX Broker jobs library.	EXX951.JOBS
WAL-MOD	WAL module library.	WAL825.MOD
MLC-MOD	Licensing module library.	MLC <i>vrs</i> .MOD
BROKER-ATTRIBUTES	EntireX Broker attribute file.	ETB-ATTR
BROKER-VARIABLES	EntireX Broker attributes variables file.	ETB-VARS
ADABAS-PARAMETERS	Adabas ADALNK parameter file.	ETB-ADAPARM
FILE-PREFIX	File name prefix used for all files written to disk.	ETB
CONFIG-REPORT-FILE	EntireX Broker configuration report file name. <i>file-prefix.tsn.CONFIG.REPORT</i>	CONFIG.REPORT
PSTORE-REPORT-FILE	EntireX Broker Adabas persistent store report file name. <i>file-prefix.tsn.PSTORE.REPORT</i>	PSTORE.REPORT
STORAGE-REPORT-FILE	EntireX Broker storage report file name. <i>file-prefix.tsn.STORAGE.REPORT</i>	STORAGE.REPORT
LICENSE-REPORT-FILE	EntireX Broker license report file name. <i>file-prefix.tsn.LICENSE.REPORT</i>	LICENSE.REPORT
ACCOUNTING-FILE	EntireX Broker cccounting file name. <i>file-prefix.tsn.ACCOUNTING</i>	ACCOUNTING
CLOGR1-FILE	EntireX Broker TRACE-LEVEL=1 command log file 1. <i>file-prefix.tsn.CLOGR1</i>	CLOGR1
CLOGR2-FILE	EntireX Broker TRACE-LEVEL=1 command log file 2. <i>file-prefix.tsn.CLOGR2</i>	CLOGR2
TASK-TYPE	Is filled during runtime with the EntireX Broker task type. Do <i>not</i> modify it !	MAIN
MAIN-TASK-TSN	Is filled during runtime with the main task TSN. The value is used by subsequently entered Broker tasks. Do <i>not</i> modify it!	*ETB

If EntireX Broker requires `SERVICE-UPDATES` to be set to `YES`, the attributes file `ETB-ATTR` cannot be held in LMS. It needs to be located on disk instead. This requires a change the `START-BROKER` procedure. See `SERVICE-UPDATES`.

Copy the attribute file to disk.

```

/ START-LMS
// EXTRACT-ELEMENT ELEMENT=*LIB(LIB=EXXvrs.JOBS,ELEMENT=ETB-ATTR,TYPE=S)
//END

```

Change the ADD-FILE-LINK in the section below in START-BROKER in EXXvrs.JOBS to read the file ETB-ATTR from disk.

```

...
/ "-----"
/ " SET UP FILE LINKS "
/ "-----"
/ ADD-FILE-LINK LINK-NAME = ETBLIC, FILE-NAME = &(LICENSE-FILE)
/&* ADD-FILE-LINK LINK-NAME = ETBFILE, FILE-NAME = #BROKER-ATTRIBUTES
/ ADD-FILE-LINK LINK-NAME = ETBFILE, FILE-NAME = &(BROKER-ATTRIBUTES)
/ ADD-FILE-LINK LINK-NAME = ETBVAR, FILE-NAME = #BROKER-VARIABLES
/ ADD-FILE-LINK LINK-NAME = DDLNKPAR, FILE-NAME = #ADABAS-PARAMETERS
...

```

Start EntireX Broker

▶ To start the broker

- Enter the following SDF command:

```

/ENTER-PROCEDURE *LIB(LIB=EXX951.JOBS,ELE=START-BROKER), -
/JOB-NAME=ETB, LOGGING=*NO, RESOURCES=*PAR(CPU-LIMIT=*NO)

```

We recommend using a three-character job name. The job name is taken as prefix for all subsequently started tasks. Because the job name is limited to eight characters, a longer job name will overwrite the suffix added by EntireX Broker. For example: EntireX Broker running with three worker tasks and NET-TCP communication, JOB-NAME=ETB, CPU-LIMIT=*NO:

NAME	TSN	TYPE	PRI	CPU-USED	CPU-MAX	ACCOUNT#
ETB	5397	2 BATCH	9 255	2.2379	NTL	1
ETBCOM	5398	2 BATCH	9 255	1.3577	NTL	1
ETBWRK00	5399	2 BATCH	9 255	0.8970	NTL	1
ETBWRK01	5400	2 BATCH	9 255	0.7571	NTL	1
ETBWRK02	5401	2 BATCH	9 255	0.7445	NTL	1
ETBTCPO0	5402	2 BATCH	9 255	0.6124	NTL	1
ETBTCPPX	5403	2 BATCH	9 255	0.5417	NTL	1
ETBNET00	5404	2 BATCH	9 255	0.6555	NTL	1
ETBTOM	5407	2 BATCH	9 255	6.4044	NTL	1

The properties assigned to the main task (ETB), e.g. JOB-CLASS, CPU-LIMIT, will be inherited by all subsequently started tasks. For CPU-LIMIT, if specified, only *NO (no time limit) and *STD are inherited.

You can now configure and run the verification jobs BCOS and BCOC. See [Verifying the Installation of the Broker](#).

Stop EntireX Broker

▶ To stop the broker from a privileged user ID

- Enter the following command:

```
/INFORM-PROGRAM MSG='ETBSTOP',JOB-IDENTIFICATION=*TSN(TSN=tsn)
```

where *tsn* is the task number associated with the broker main task (in the example above the TSN of job name ETB)

All other tasks that were created as a result of starting the broker will be stopped automatically.

▶ To stop the broker from an operator console

- Enter the following command:

```
/INTR tsn,ETBSTOP
```

where *tsn* is the task number associated with the broker main task (in the example above the TSN of job name ETB)

All other tasks that were created as a result of starting the broker will be stopped automatically.

▶ To stop the broker from a non-privileged user ID

- Use the S-procedure STOP-BROKER in EXX951.JOBS

Startup Parameter	Description	Default
BROKER-ID	<p>Depending on the communication method, the BrokerId can be specified in two different formats:</p> <ul style="list-style-type: none"> ■ TCP Transport Method <pre><i>ip:port:TCP</i></pre> <p>where <i>ip</i> is the address or DNS host name, <i>port</i> is the port number that EntireX Broker is listening on, and <i>TCP</i> is the protocol name</p>	none

Startup Parameter	Description	Default
	<p>■ XCOM Transport Method</p> <p><code>ETBnnn:SVCmmm:NET</code></p> <p>where <i>nnn</i> is the ID under which EntireX Broker is connected to the Adabas ID table, <i>mmm</i> is the SVC number under which the Adabas ID table can be accessed, and NET is the protocol name</p>	
ADABAS-PARAMETERS	Adabas parameters used for NET communication method.	ETB-ADAPARM
USERID	If EntireX Broker is running with EntireX Security, a user ID needs to be supplied.	none
PASSWORD	If EntireX Broker is running with EntireX Security, a password needs to be supplied.	none
EXX-LIB	EntireX Broker module library.	EXX951.LIB
EXX-JOBS	EntireX Broker jobs library.	EXX951.JOBS
WAL-MOD	WAL module library.	WAL825.MOD

Set the broker ID in the `PARAMETER-DECLARATION` section and enter following command:

```
/CALL-PROCEDURE (EXX951.JOBS, STOP-BROKER)
```

Creating a Broker Persistent Store (optional)

This step may be skipped if no persistent store is required. See *Managing the Broker Persistent Store* in the BS2000/OSD administration documentation for more information. The persistent store resides in an Adabas database, which means that Adabas must be installed. See *BS2000/OSD Prerequisites* in the EntireX Release Notes.

Customize job `CREATE-PSTORE-ADABAS`. Add the appropriate values in the `PARAMETER-DECLARATION` section and run the job.

```
/CALL-PROCEDURE (LIB=EXX951.JOBS, ELE=CREATE-PSTORE-ADABAS)
```

This Adabas `ADALOD` job loads the Adabas persistent store file `FDT` from `EXX951.SYSF` into the database where the Adabas persistent store is to reside.

Set the relevant attributes in the broker attribute file `ETB-ATTR`. See *Adabas-specific Attributes* (`DEFAULTS=ADABAS`) under *Broker Attributes* in the administration documentation and *Managing the Broker Persistent Store* in the BS2000/OSD administration documentation.



Note: The Adabas persistent store requires the ADALNK parameter IDTNAME in ETB-ADAPARM to be set properly. This must be the same ID table as used by the broker. See *Customize the EntireX Broker Attribute File* in the BS2000/OSD installation documentation and *Customize the ADALNK Parameters File* in the BS2000/OSD installation documentation.

Set up the EntireX Broker Security Server for BS2000/OSD (optional)

▶ To activate authentication

- Set the following two parameters in the broker attribute file to switch on security:

- **In the DEFAULTS=BROKER section**

```
SECURITY=YES
```

- **In the DEFAULTS=SECURITY section**

```
ACCESS-SECURITY-SERVER=YES
```

The Broker Security Server requires administrator rights and must be run under a privileged user ID.



Note: If the parameter ACCESS-SECURITY-SERVER is set to "NO", the broker itself must be run under a privileged user ID to allow authentication. In this case, the Broker Security Server is not needed.

▶ To start the Broker Security Server

- 1 Set up the correct broker library within START-SECURITY-SERVER, because the server task does not usually run under same user ID where the module library resides.
- 2 Issue the following command from a privileged user ID (TSOS) to run the server:

```
/ENTER-PROCEDURE *LIB(LIB=$kkk.EXXnnn.JOBS, -  
/  
/ ELE=START-SECURITY-SERVER), -  
/ JOB-NAME=SECUSERV, LOG=*NO
```

where \$kkk is the user ID under which the broker library resides.

▶ To stop the Broker Security Server from a privileged user ID

- Enter:

```
/INFORM-PROGRAM MSG='EOJ',JOB-IDENTIFICATION=*TSN(TSN=tsn)
```

where *tsn* is the BS2000/OSD task number associated with the server.

▶ **To stop the Broker Security Server from an operator console**

- Enter:

```
/INTR tsn,EOJ
```

where *tsn* is the BS2000/OSD task number associated with the server.

▶ **To stop the Broker Security Server from a non-privileged user ID**

- Enter the following SDF command:

```
/CALL-PROCEDURE (EXX951.JOBS, STOP-SECURITY-SERVER)
```



Note: This works from all user IDs in the system.

Load the SYSETB INPL and ERRN Files (optional)

(SMA Job I061, Step 7600 and 7602)

Perform this step only if you want to install the sample Natural programs.

Use the Natural system command INPL and ERRLODUS (see Natural User's Guide) to load the EntireX Broker system objects (EXB951.INPL and EXB951.ERRN).

This loads the following library:

Library	File	Contents
SYSETB	FNAT	Sample Natural programs.

Set the Natural profile parameter ESIZE=40.

Invoke Natural, logon to library SYSETB and edit the member PARM on library SYSETB to set parameters as required at your site, especially the BROKER-ID.

Parameter members can also be made user-dependent. Copy the PARM member and save it in a member with a user ID as name (Natural variable *USER). If a user logs on with this user ID, these parameters take effect instead of the PARM member.

Verifying the Installation of the Broker

Once you have installed the EntireX Broker you can verify that the installation was successful by modifying and using the following client/server pair with the Broker:

- BCOS
- BCOC

These procedures are located in library EXX951.JOBS. They, in turn, execute the BCOC (client) and BCOS (server) test programs, depending on a parameter value. These programs support communication with the Broker using either TCP/IP communication method, or the conventional XCOM (Adabas router) communication method. The communication protocol to be used depends on the format of the Broker ID used.

Both BCOS and BCOC are also delivered as example sources. BCOS and BCOC act as a pair, where BCOS provides a service that BCOC calls.

Customize the verification jobs before you run them. BCOS and BCOC require a `BROKER-ID` to be set up in the job control's `PARAMETER-DECLARATION` section. Since they may access an Adabas ID table (communication method XCOM), an `IDTNAME` must be provided. This `IDTNAME` is read from the `ETB-ADAPARM` element (see *Customize the ADALNK Parameters File* in the BS2000/OSD installation documentation).

Start BCOS using following command.

```
/CALL-PROCEDURE (LIB=EXX951.JOBS,ELE=BCOS)
```

Wait until BCOS has registered the service.

Then start BCOC in a different session. Since BCOS sets a `WAIT` value of 60 seconds, it will terminate with a "WAIT timeout" if BCOC is not started within this time frame. See `WAIT` under *Broker ACI Fields*.

```
/CALL-PROCEDURE (LIB=EXX951.JOBS,ELE=BCOC)
```

Both should now run through 10 iterations of exchanging messages.

If the initialization messages appear but the verification program fails, check for either a TCP port conflict or a problem with the ID table name or version.

The client and server programs that are executed by these procedures need the following to be defined in the Broker attribute file (if the delivered attribute file is used, no changes are needed).

```
CLASS = BCLASS, SERVER = BSERVER, SERVICE = BSERVICE
```

See *Broker Attributes* in the administration documentation for more information.

For further information on the usage of BCOC / BCOS please also see the comments in the delivered job control. For example, by setting the command string to: /COMMAND='-h' detailed information on the usage will be printed.

4 Installing the BS2000/OSD Batch RPC Server

- Step 1: Define an RPC SVM File 22
- Step 2: Customize the BS2000/OSD Batch RPC Server Configuration File RPC-CONFIG 22
- Step 3: Customize ADALNK Parameter File RPC-ADAPARM 24
- Step 4: Customize the BS2000/OSD Batch RPC Server Startup JCL 24
- Starting the RPC Server 26
- Stopping the RPC Server 26
- Verifying the Installation of the BS2000/OSD Batch RPC Server 28

This chapter covers the following topics:

Step 1: Define an RPC SVM File

The SVM file is used at runtime to marshal and unmarshal the RPC data stream. This enables the RPC server to support special COBOL syntax. This server-related information is held in an ISAM file, which needs to be defined and initialized. Each RPC server requires its own SVM file.

Customize S-procedure `CREATE-SVM-FILE` in `EXP951.JOBS`.

Procedure Parameter	Description	Default
EXP-LIB	BS2000/OSD Batch RPC Server load library	EXP951.LIB
SVM-FILE	SVM file name	SVMFILE
SYSOUT-FILE	SYSOUT file name	RPC.SYSOUT.CREASVM

The SVM file name must correspond to the SVM file specified in the BS2000/OSD Batch RPC Server startup job control. See *Step 4: Customize the BS2000/OSD Batch RPC Server Startup JCL* in the BS2000/OSD installation documentation.

See also *Handling SVM Files* in the BS2000/OSD administration documentation.

Step 2: Customize the BS2000/OSD Batch RPC Server Configuration File RPC-CONFIG

RPC-CONFIG in `EXP951.JOBS` contains the RPC server parameters. If the default settings are used, only the `BROKERID` parameter needs to be set up according to your environment. The BS2000/OSD Batch RPC Server will then run in a default configuration.

Depending on the communication method, the Broker ID has two formats:

■ TCP Transport Method

```
ip:port:TCP
```

where *ip* is the address or DNS host name,

port is the port number that EntireX Broker is listening on, and

`TCP` is the protocol name

■ XCOM Transport Method

```
ETBnnn:SVCmmm:NET
```

where *nnn* is the ID under which EntireX Broker is connected to the Adabas ID table,
mmm is the SVC number under which the Adabas ID table can be accessed, and
 NET is the protocol name

If the provided parameter file is used, the RPC server will run as a COBOL server. Besides the RPC service (RPC/SRV1/CALLNAT), it will register the DEPLOYMENT and the EXTRACTOR service. This corresponds to the delivered settings in the broker attribute file on BS2000/OSD and other platforms. The server is configured to run with a fixed number of 3 worker task replicates. System Management Hub support and security are turned off.

See also *Configuring the BS2000/OSD Batch RPC Server* under *Administering the BS2000/OSD Batch RPC Server*.

The default configuration file RPC-CONFIG:

```
* * * * *
*
*           EntireX RPC Server v8.1 Configuration File
*
* * * * *
*
* * * * * EntireX Broker Parameters * * * * *
*
BROKERID=<ipaddr>:<port>:TCP           Broker Id if TCPIP is used
* BROKERID=ETB<nnnnn>::NET           Broker Id if NET is used
*
SERVERNAME=SRV1
SERVICE=CALLNAT
CLASS=RPC
*
TIMEOUT=300                           Seconds
LOGON=YES                               EntireX Broker Logon
*
* CODEPAGE=EDF041
*
* KERNELSECURITY=YES                   EntireX Broker Security
* USERID=<userid>
* PASSWORD=<password>
*
* * * * * EntireX RPC Server Parameter * * * * *
*
RESTARTCYCLES=3                         default is 15
* TRACELEVEL=NONE                       NONE, STANDARD or ADVANCED
```

```
* SMHPOPT=<smhport>
*
* EntireX RPC Cobol Server Configuration
* -----
SVM=PREFERRED
DEPLOYMENT=YES
EXTRACTOR=YES
MARSHALLING=(LANGUAGE=COBOL)
*
* EntireX RPC C Server Configuration
* -----
* EXTRACTOR=YES
* MARSHALLING=(LANGUAGE=C)
*
* Start up a fixed number of workers
* -----
WORKERMODEL=(FIX,3)
*
* Balance the load of available workers
* -----
* WORKERMODEL=(SCALE,2,5)
*
* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * *
```

Step 3: Customize ADALNK Parameter File RPC-ADAPARM

The BS2000/OSD Batch RPC Server requires ADALNK parameters when a local communication with an EntireX Broker on same machine is desired (XCOM communication). Set up the IDTNAME in RPC-ADAPARM in EXP951.JOBS under which the broker has registered at the Adabas ID table.

Parameter	Description
ADALNK IDTNAME=ADA<xxxxx>	Specifies the ID table name under which EntireX Broker is accessible.

Step 4: Customize the BS2000/OSD Batch RPC Server Startup JCL

The job control delivered with BS2000/OSD Batch RPC Server makes use of BS2000/OSD S-procedures. We strongly recommend you do not modify START-RPC-SERVER. This procedure is recursively called to establish the RPC server environment. Modifications should only be done to the PARAMETER-DECLARATION section as described below. If all RPC server components are installed under the same BS2000/OSD user ID and all previous installation steps have been done using the default settings, no modifications to START-RPC-SERVER are necessary to run a COBOL server and execute the delivered examples.

Procedure Parameter	Description	Default
EXP-JOBS	Batch RPC Server jobs library.	EXP951.JOBS
EXP-LIB	Batch RPC Server load library.	EXP951.LIB
EXX-LIB	EntireX Broker load library.	EXX951.LIB
WAL-MOD	WAL library.	WAL825.MOD
PROGRAM-LIB	Server module library. Additional server module libraries can be included in the BLSLIB chain. (See the SET UP FILE LINKS section in the START-RPC-SERVER job control.) There are two sample server libraries delivered: EXP951.COBS COBOL sample server module library. See <i>Client and Server Examples for BS2000/OSD</i> in the COBOL Wrapper documentation. EXP951.CSRV C sample server module library. See <i>Server Examples for BS2000/OSD</i> in the C Wrapper documentation.	EXP951.COBS
ADABAS-PARAMETERS	Adabas parameters used for XCOM communication method.	RPC-ADAPARM
RPC-CONFIG-FILE	RPC configuration parameter file.	RPC-CONFIG
SVM-FILE	Sever mapping ISAM file name.	SVMFILE
PROC-NAME	The name of the START-RPC-SERVER procedure.	START-RPC-SERVER
WORKER-JOB-NAME	Job name of the worker tasks.	RPCWORK
LOG-FILE-PREFIX	File name prefix used for the SYSOUT files of the main and worker tasks. The following SYSOUT files are generated: for the main task: <i>log-file-prefix.tsn.RPCMAIN</i> for each worker task and the SMH task: <i>log-file-prefix.tsn.RPCWORK</i>	RPC.
WORKER-JOB-CLASS	Job class of the worker tasks	*STD
WORKER-CPU-LIMIT	CPU limit of the worker tasks. If this parameter is set to *NO, the user ID requires the permission to run jobs with TIME='NTL' in the job class assigned	*STD
CRTE-LIB	BS2000/OSD Common Runtime Environment (CRTE) library	\$.SYSLNK.CRTE
STUB-TRACE-LEVEL	Trace level of the EntireX Broker stub. For diagnostic purposes it can be set to 1, 2 or 3	0
LOGGING	The logging parameter is passed to the worker task job control and the SYSJ elements executed	*NO
WORKER-PARMS	Is filled during runtime with the worker task parameters. Note: Do <i>not</i> modify it !	*RPC

Procedure Parameter	Description	Default
MAIN-TASK-TSN	Is filled during runtime with the main task TSN. Note: Do <i>not</i> modify it!	*RPC

Starting the RPC Server

▶ To start the BS2000/OSD Batch RPC Server

- Use the following SDF command:

```
/ENTER-PROCEDURE *LIB(LIB=EXP951.JOBS,ELE=START-RPC-SERVER), -  
/JOB-NAME=RPCMAIN,LOG=*NO
```

Stopping the RPC Server

▶ To stop the BS2000/OSD Batch RPC Server using System Management Hub

- Use the RPC server agent in the SMH to stop the BS2000/OSD Batch RPC Server.

▶ To stop the BS2000/OSD Batch RPC Server from a privileged user ID

- Enter the command:

```
/INFORM-PROGRAM MSG='STOP',JOB-IDENTIFICATION=*TSN(TSN=tsn)
```

where *tsn* is the task number associated with the BS2000/OSD Batch RPC Server main task (in the example above the TSN of RPCMAIN)

All other tasks that were created as a result of starting the batch RPC server will be stopped automatically.

▶ To stop the BS2000/OSD Batch RPC Server from an operator console

- Enter the command:

```
/INTR tsn,STOP
```

where *tsn* is the task number associated with the BS2000/OSD Batch RPC Server main task (in the example above the TSN of RPCMAIN)

All other tasks that were created as a result of starting the batch RPC server will be stopped automatically.

► **To stop the BS2000/OSD Batch RPC Server from a non-privileged user ID**

- Use S-procedure STOP-RPC-SERVER in EXP951.JOBS.

Startup Parameter	Description	Default
BROKER-ID	<p>Depending on the communication method, the broker ID can be specified in two different formats:</p> <ul style="list-style-type: none"> ■ TCP Transport Method <pre><i>ip:port:TCP</i></pre> <p>where <i>ip</i> is the address or DNS host name, <i>port</i> is the port number that EntireX Broker is listening on, and <i>TCP</i> is the protocol name</p> <ul style="list-style-type: none"> ■ XCOM Transport Method <pre>ETB<i>nnn</i>:SVC<i>mmm</i>:NET</pre> <p>where <i>nnn</i> is the ID under which EntireX Broker is connected to the Adabas ID table, <i>mmm</i> is the SVC number under which the Adabas ID table can be accessed, and <i>NET</i> is the protocol name</p>	none
CLASS	The class name under which the RPC server is registered at the EntireX Broker.	RPC
SERVER	The server name under which the RPC server is registered at the EntireX Broker.	SRV1
SERVICE	The service name under which the RPC server is registered at the EntireX Broker.	CALLNAT
USERID	If EntireX Broker is running with EntireX Security, a user ID needs to be supplied	none

Startup Parameter	Description	Default
PASSWORD	If EntireX Broker is running with EntireX Security, a password needs to be supplied	none
EXX-JOBS	EntireX Broker jobs library	EXX951.JOBS
EXX-LIB	EntireX Broker module library	EXX951.LIB
WAL-MOD	WAL module library	WAL825.MOD

Set the broker ID in the `PARAMETER-DECLARATION` section and enter following command:

```
/CALL-PROCEDURE (EXP951.JOBS, STOP-RPC-SERVER)
```

Verifying the Installation of the BS2000/OSD Batch RPC Server

The BS2000/OSD Batch RPC Server is delivered with libraries that contain COBOL client sample programs, and COBOL and C server sample programs. The sample client and server programs can be used for installation verification. They also correspond to the basic and reliable RPC examples delivered with the EntireX Developer's Kit on other platforms, for example UNIX and Windows.

See *Client and Server Examples for BS2000/OSD* in the COBOL Wrapper documentation and *Server Examples for BS2000/OSD* in the C Wrapper documentation.

5 Installing EntireX Security under BS2000/OSD

- Installing EntireX Security for Broker Kernel 30
- Installing EntireX Security for Applications Using Broker Stubs 30

Installing EntireX Security for Broker Kernel

This section describes the steps for installing EntireX Security for Broker kernel under BS2000/OSD. The installation procedure has the following steps:

- [Modify Broker Attribute File](#)
- [Start \(Restart\) Broker Kernel](#)

Modify Broker Attribute File

▶ To modify the Broker attribute file

- 1 Insert the following parameter in the section `DEFAULTS=BROKER` of the Broker attribute file:

```
SECURITY=YES
```

- 2 Modify the `DEFAULTS=SECURITY` section of the Broker attribute file according to your requirements. These parameters are used to adjust the security settings. See *Security-specific Attributes (DEFAULTS=SECURITY)* under *Broker Attributes* in the administration documentation. Authorization checks are currently not available.



Note: Setting `SECURITY=YES` will load the provided load module `USRSEC` from the `EXX` load library assigned by `LINK-NAME ETBLIB`. This module will perform privileged operations, such as executing the `SRMUINF` macro for various users, and requires Broker running under `TSOS`.

Start (Restart) Broker Kernel

The Broker must be restarted to pick up changes to the Broker attribute file and to initialize Broker kernel under BS2000/OSD to perform security checks.

Basic installation of EntireX Security for Broker kernel is now complete.

Installing EntireX Security for Applications Using Broker Stubs

This section describes the steps for installing EntireX Security for Broker stub under BS2000/OSD.



Notes:

1. If you are running your application(s) with ACI version 7 or below, the following steps are required to install EntireX Security for the Broker stubs in all environments where applications execute either as clients or servers.
2. The mainframe stubs employ high performance direct cross-memory to send and receive data from buffers in the application's working storage. This is utilized for sending/receiving more than 32 KB of data. Therefore, when encryption is active, the application programmer must not rely on the contents of the SEND buffer after issuing the SEND command, because the contents of the SEND buffer will be encrypted when sending more than 32 KB of data. We recommend to code all applications so that you do not rely on the contents of the SEND buffer after calling Broker. This will be required in future versions (later than 8.1) for all SEND commands regardless of whether the data exceeds 32 KB. Therefore, the application's SEND buffer must not be in read-only memory, where encryption is activated.

These steps are not required if you are running your application(s) with ACI version 8 or above.

Link and Security Components

For applications running on BS2000/OSD using ACI 7 or below, the Broker stub security component NA2PETS must be linked with the stub BROKER. In addition, LLM SECUEXIT must be made available. The following steps are required:

- Relink all applications that contain stub BROKER to include module NA2PETS.
- Assign the EXX load library by using an ADD-FILE-LINK statement with LINK-NAME ETBUSER.



Notes:

1. These steps are needed for backward compatibility if your applications issue any commands using ACI version 7 or below. Applications using ACI version 8 or above do not require these additional components in the stub.
2. For ACI version 7 or below, these components must be added to the stub environment utilized by the application.

Installation of EntireX Security for Broker stubs is now complete. Now you can install the security components for the Broker stubs on the remaining operating systems where your application components are located.

