

## **webMethods EntireX**

### **EntireX z/OS CICS® RPC Server**

Version 9.6

April 2014

This document applies to webMethods EntireX Version 9.6.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 1997-2014 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors..

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://documentation.softwareag.com/legal/>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://documentation.softwareag.com/legal/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices and license terms, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". This document is part of the product documentation, located at <http://documentation.softwareag.com/legal/> and/or in the root installation directory of the licensed product(s).

**Document ID: EXX-CICSRPC-96-20140628**

## Table of Contents

EntireX z/OS CICS® RPC Server .....	v
1 Introduction to the CICS RPC Server .....	1
Worker Models .....	2
Inbuilt Services .....	3
User Exit COBUEx02 .....	6
Impersonation .....	7
Usage of SVM Files .....	8
Supported Interface Types .....	9
2 Administering the CICS RPC Server .....	11
Customizing the RPC Server .....	12
Configuring the RPC Server .....	14
Locating and Calling the Target Server .....	24
Using SSL or TLS with the RPC Server .....	25
User Exit COBUEx02 .....	26
Autostart/Stop during CICS Start/Shutdown .....	28
Multiple RPC Servers in the same CICS .....	29
3 RPC Online Maintenance Facility .....	31
Monitoring the RPC Server .....	32
Starting the RPC Server .....	34
Pinging the RPC Server .....	34
Stopping the RPC Server .....	35
Modifying Parameters of the RPC Server .....	35
Activating Tracing for the RPC Server .....	35
Console Commands for the RPC Server .....	36
4 Deployment Service .....	39
Introduction .....	40
Scope .....	41
Enabling the Deployment Service .....	41
Disabling the Deployment Service .....	42
5 Handling SVM Files .....	43
SVM Files in the EntireX Workbench .....	44
SVM Files in the RPC Server .....	44
Source Control of SVM Files .....	45
Change Management of SVM Files .....	45
Compare SVM Files .....	45
List Deployed SVM Files .....	45
Check if an SVM File Revision has been Deployed .....	46
Access Control: Secure SVM File Deployment .....	46
Ensure that Deployed SVM Files are not Overwritten .....	46
When is an SVM File Required? .....	47
Is There a Way to Smoothly Introduce SVM Files? .....	49
6 Scenarios and Programmer Information .....	51
COBOL Scenarios .....	52

PL/I Scenarios .....	53
Aborting RPC Server Customer Code and Returning Error to RPC Client .....	54
Automatic Syncpoint Handling .....	59

---

## EntireX z/OS CICS® RPC Server

---

The EntireX z/OS CICS® RPC Server allows standard RPC clients to communicate with RPC servers on the operating system z/OS under CICS. It supports the programming languages COBOL and PL/I.

- For COBOL, it works together with the *COBOL Wrapper* and *IDL Extractor for COBOL*.
- For PL/I, it works together with the *PL/I Wrapper* and *IDL Extractor for PL/I*.

Supported compilers are listed under *z/OS Prerequisites* in the EntireX Release Notes in the EntireX Release Notes.

---


# 1 Introduction to the CICS RPC Server

---

▪ Worker Models .....	2
▪ Inbuilt Services .....	3
▪ User Exit COBUEX02 .....	6
▪ Impersonation .....	7
▪ Usage of SVM Files .....	8
▪ Supported Interface Types .....	9

The EntireX z/OS CICS® RPC Server allows standard RPC clients to communicate with RPC servers on the operating system z/OS under CICS. It supports the programming languages COBOL and PL/I.

## Worker Models



RPC requests are worked off inside the RPC server in worker tasks, which are controlled by a main task. Every RPC request occupies during its processing a worker task. If you are using RPC conversations, each RPC conversation requires its own task during the lifetime of the conversation. The CICS RPC Server provides two worker models:

- **FIXED**

The *fixed* model creates a fixed number of worker tasks. The number of worker tasks (defined with **ERXMAIN macro** parameter **MINW**) does not increase or decrease during the lifetime of an RPC server instance. It is configured by setting the **ERXMAIN macro** parameter **ENDW** to value "NEVER". Example:

```
ENDW=NEVER, MINW=4
```

- **SCALE**

The *scale* model creates worker tasks depending on the incoming load of RPC requests.

A maximum number (**ERXMAIN macro** parameter **MAXW**) of the worker tasks created can be set to restrict the system load. The minimum number (**ERXMAIN macro** parameter **MINW**), allows you to define a certain number of tasks - not used by the currently executing RPC request - to wait



for new RPC client requests to process. In this way the RPC server is ready to handle many RPC client requests arriving at the same time. It is configured by setting the `ERXMAIN` macro parameter `ENDW` to value "TIMEOUT" or "IMMEDIATE".

- With value `IMMEDIATE`, worker tasks shrink fast, that is, worker tasks not used are stopped immediately as soon as it has finished its conversation, except for the number of workers specified as minimum being active.
- With value `TIMEOUT`, worker tasks shrink slowly, that is, all worker tasks not used are stopped in the time specified by the `ERXMAIN` macro parameter `TOUT`, except for the number of workers specified as minimum being active.

Example:

```
ENDW=IMMEDIATE, MINW=2, MAXW=6
```

## Inbuilt Services


---

CICS RPC Server provides the following services for ease-of-use:

- [Deployment Service](#)
- [SMH Listener Service](#)

## Deployment Service


The Deployment Service allows you to deploy server mapping files (SVM files) interactively using the Deployment Wizard (see *Server Mapping Deployment*). On the RPC server side, the SVM files are stored in a VSAM file as the container. See *Deployment Service* for configuration information.



## SMH Listener Service

With the SMH Listener Service you use the System Management Hub to monitor the RPC server. See *Administering the EntireX RPC Servers using System Management Hub* in the UNIX and Windows administration documentation.


The SMH Listener Service is switched on if the SMH port number is set. See the [ERXMAIN macro](#) parameter `SMH` under *Configuring the RPC Server*.



## User Exit COBUEX02


The CICS RPC Server provides a user exit COBUEX02 to influence/control the RPC logic. The exit is called on the events START-WORKER, START-USER, CALL-START and CALL-END. The following tasks can be performed:

- 1 START-WORKER event before a CICS worker task is started. This allows you to programmatically set the CICS transaction ID.
- 2 START-USER event. Apply CICS transaction ID and user ID to impersonated worker tasks. See *Impersonation*.
- 3 CALL-START event. Inspect, modify or terminate the RPC request (payload) from the RPC client.
- 4 CALL-END event. Inspect or modify the RPC reply (payload) or give an error to the RPC client.



See also *User Exit COBUEX02* under *Administering the EntireX RPC Server*.

## Impersonation



The CICS RPC Server can be configured to execute the RPC request impersonated under the RPC client user ID. For this, worker tasks start additional impersonated user tasks. This can be useful, for example for accounting. Impersonation is controlled by the **ERXMAIN macro** parameter **IMPS**.

- For **IMPS** value **AUTO**, the CICS RPC Server does not validate RPC passwords, so you have to take care the RPC client is correctly authenticated, either by using a secure EntireX Broker (validation must be against the correct mainframe security repository where CICS user IDs are defined) or with your own security implementation.
- For **IMPS** value **YES**, the CICS RPC Server uses the RPC user ID and password supplied by the RPC client for authentication and impersonation of the client. This means that the RPC server validates the password.

The picture above shows the configuration **IMPS=YES**.


The lifetime of an impersonated user task starts when an open request for an RPC conversation or a non-conversational RPC request is received. It ends when the RPC conversation stops (after a commit operation or timeout) or when the non-conversational RPC request has been performed.

For worker tasks, the slow-shrinking worker model **SCALE** is used - value **TIMEOUT** is forced internally - any value given in the **ERXMAIN macro** parameter **ENDW** is ignored. The lifetime of worker tasks can be controlled with **ERXMAIN macro** parameter **TOUT** as well as the number of workers with macro parameters **MINW** and **MAXW**.

## Usage of SVM Files

There are many situations where the CICS RPC Server requires a server mapping file to correctly support special COBOL syntax such as `JUSTIFIED`, `SYNCHRONIZE` and `OCCURS DEPENDING ON` clauses, `LEVEL-88` fields, etc. the .


SVM files contain COBOL-specific mapping information that is not included in the IDL file and therefore *not* sent by an EntireX RPC client to the RPC server. See also [When is an SVM File Required?](#) under [SVM Files](#).



The RPC server marshalls the data in a two-step process: the RPC request coming from the RPC client (Step 1) is completed with COBOL-specific mapping information taken from the SVM file (Step 2). In this way the COBOL server can be called as expected.

The SVM files are retrieved as a result of the *IDL Extractor for COBOL* extraction process and the *COBOL Wrapper* if a COBOL server is generated.

You can customize the usage of the SVM file using the `ERXMAIN` macro parameter `SVM`. See [Configuring the RPC Server](#).

 **Note:** SVM files are used for COBOL only.

## Supported Interface Types

---

The interface types supported by the CICS RPC Server vary depending on the target programming language. See also [Locating and Calling the Target Server](#).

### COBOL

- *CICS with DFHCOMMAREA Calling Convention* (COBOL Wrapper | Extractor)
- *CICS with Channel Container Calling Convention* (COBOL Wrapper | Extractor)
- *CICS with DFHCOMMAREA Large Buffer Interface* (COBOL Wrapper | Extractor)

### PL/I

- *CICS with DFHCOMMAREA Calling Convention* (PL/I Wrapper | Extractor)





# 2 Administering the CICS RPC Server

---

- Customizing the RPC Server ..... 12
- Configuring the RPC Server ..... 14
- Locating and Calling the Target Server ..... 24
- Using SSL or TLS with the RPC Server ..... 25
- User Exit COBUEX02 ..... 26
- Autostart/Stop during CICS Start/Shutdown ..... 28
- Multiple RPC Servers in the same CICS ..... 29

The EntireX z/OS CICS® RPC Server allows standard RPC clients to communicate with RPC servers on the operating system z/OS under CICS. It supports the programming languages COBOL and PL/I.

## Customizing the RPC Server

---

The following elements are used for setting up the CICS RPC Server:

- [ERXMAIN Control Block](#)
- [ERXMAIN Macro](#)
- [RPC Online Maintenance Facility](#)
- [IBM LE Runtime Options](#)

### ERXMAIN Control Block

- defines a setup of the CICS RPC Server that is persistent over CICS restarts
- is defined with parameters of the [ERXMAIN Macro](#); see column 1 in the table under *Configuring the RPC Server*
- contains the following important settings:
  - connection information such as broker ID, see [BKRN](#), server address, see [CLZN](#), [SRVN](#) and [SVCN](#)
  - location and usage of server mapping files, see [SVM](#)
  - scalability parameters such as `endworker`, `minworker` and `maxworker`, see [ENDW](#), [MINW](#) and [MAXW](#)
  - etc.

### ERXMAIN Macro

- creates an [ERXMAIN Control Block](#), a persistent setup of the CICS RPC Server
- needs to be assembled to define a setup
- is defined in Assembler program `EMAINGEN` (in `EXP960.SRCE`) - use this for assembling; see *Build the ERXMAIN Control Block* under *Installing EntireX RPC Servers under CICS*

## RPC Online Maintenance Facility

- provides commands (see column 2 in the table below) to vary most of the permanently defined parameters in the *ERXMAIN Control Block* currently in use. All modifications are lost if CICS is restarted. Use *ERXMAIN Macro* for permanent modifications
- allows you to try out new setups of the CICS RPC Server easily without the need to reassemble the *ERXMAIN Control Block*.
- supports
  - starting
  - stopping
  - pinging
  - monitoring
  - activating trace

of the CICS RPC Server. See *RPC Online Maintenance Facility*.

## IBM LE Runtime Options

Depending on the feature the CICS RPC Server needs to support (see table below) additional runtime options for IBM's Language Environment need to be set. For a full description of LE runtime options, see *z/OS V1R4.0 Lang Env Prog Guide*.

Feature	LE Runtime Options	Description
Trap abends of called RPC server programs	ABTERMENC(RETCODE) <sup>(1)</sup>	Required to also trap the LE abends within a server program.
Level of information if called RPC server program terminates by unhandled condition	TERMTHDACT(UADUMP) <sup>(1)</sup>	Forces a U4039 system dump for abends not trapped by the server.
Force HANDLE ABEND LABEL getting control for COBOL runtime error and others	USRHDLR=(CEEUUCHA) <sup>(1)</sup>	The server traps abends using CICS HANDLE ABEND. With Enterprise COBOL for z/OS, errors resulting from the COBOL runtime (table overflow, for example) bypass the CICS abend handler. Setting CEEUUCHA enables the CICS abend handler to also trap the COBOL runtime errors.
Call RPC server programs with AMODE 24 as well	ALL31(OFF), STACK( , ,BELOW)	If not specified, AMODE 31 is supported.



**Note:** <sup>(1)</sup> Set internally by the CICS RPC Server using application-specific CSECT CEEUOPT. The options can be changed if CEEUOPT is replaced on CICS RPC Server load module RPCSRVC with IBM Linkage Editor.

There are various ways of specifying LE runtime options, for example installation-specific, region-specific (CEEROPT available in the DFHRPL concatenation) or application-specific (linked CSECT CEEUOPT) etc.

## Configuring the RPC Server

The following rules apply for the *ERXMAIN Macro* syntax (column 1 in table below):

- keywords are given in uppercase
- there are no abbreviations for keywords

The following rules apply for the RPC Online Maintenance Facility commands (column 2 in table below):

- Underscored letters in a command indicate the minimum number of letters that can be used for abbreviation.

For example, in `brokerid=localhost`, `brok` is the minimum number of letters that can be used as an abbreviation, i.e. the commands `brokerid=localhost` and `brok=localhost` are equivalents.

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/Opt
BKRN	<u>brokerid</u>	ETB001	Broker ID used by the server. See <i>Using the Broker ID in Applications</i> in the RPC Programming documentation.  Example: BKRN=myhost.com:1971	R
CLZN	<u>class</u>	RPC	Server class part of the server address used by the server. The server address must be defined as a service in the broker attribute file (see <i>Service-specific Attributes (DEFAULTS=SERVICE)</i> under <i>Broker Attributes</i> in the platform-independent administration documentation). Case-sensitive, up to 32 characters. Corresponds to CLASS attribute of the broker attribute file.  Example: CLZN=MyRPC	R
SRVN	<u>servername</u>	SRV1	Server name part of the server address used by the server. The server address must be defined as a service in the broker attribute file. See <i>Service-specific Attributes (DEFAULTS=SERVICE)</i> under <i>Broker Attributes</i> in the platform-independent administration documentation. Case-sensitive, up to 32 characters. Corresponds to SERVER of the broker attribute file.	R

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/ Opt
			Example: SRVN=mySrv	
SVCN	<u>service</u>	CALLNAT	Service part of the server address used by the server. The server address must be defined as a service in the broker attribute file. See <i>Service-specific Attributes</i> (DEFAULTS=SERVICE) under <i>Broker Attributes</i> in the platform-independent administration documentation. Case-sensitive, up to 32 characters. Corresponds to SERVICE attribute of the broker attribute file.  Example: SVCN=MYSERVICE	R
CODE	<u>codepage</u>	no codepage transferred	Depending on the internationalization approach, the codepage (locale string) where incoming data is provided to the COBOL server. Conversely, the COBOL server must provide outgoing data in the given codepage, otherwise unpredictable results occur. See <i>What is the Best Internationalization Approach to use?</i> under <i>Internationalization with EntireX</i> for information on which internationalization approach requires a codepage (locale string).  By default, no codepage is transferred to the broker. For the most popular internationalization approach, <i>ICU Conversion</i> under <i>Introduction to Internationalization</i> , the correct codepage (locale string) must be provided. This means it must: <ul style="list-style-type: none"> <li>■ follow the rules described under <i>Locale String Mapping</i> in the internationalization documentation</li> <li>■ be a codepage supported by the broker</li> <li>■ be the codepage used in your environment for file and terminal IO, otherwise unpredictable results may occur.</li> </ul> Example: CODE=ibm-273	O
COMP	<u>compresslevel</u>	N	Enforce compression when data is transferred between broker and server. See <i>Data Compression in EntireX Broker</i> in the general administration documentation.  compresslevel= 0   1   2   3   4   5   6   7   8   9   Y   N  0-9 0=no compression 9=max. compression	O

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/ Opt
			<p>N No compression. Y Compression level 6.</p> <p>Example: COMP=6</p>	
CYCL	<u>restartcycles</u>	15	<p>Number of restart attempts if the broker is not available. This can be used to keep the CICS RPC Server running while the broker is down for a short time. A restart cycle will be repeated at an interval which is calculated as follows:</p> <p><code>timeout + ETB_TIMEOUT + 60 seconds</code></p> <p>where <code>timeout</code> is the RPC server parameter (see this table), and <code>ETB_TIMEOUT</code> is the environment variable (see <i>Environment Variables in EntireX</i> in the general administration documentation)</p> <p>When the number of cycles is reached and a connection to the broker is not possible, the RPC server stops.</p> <p>Example: CYCL=30</p>	O
DPLY	<u>deployment</u>	NO	<p>Activates the deployment service, see <a href="#">Deployment Service</a>. Required to use the deployment wizard. See <i>Server Mapping Deployment Wizard</i> in the COBOL Wrapper documentation.</p> <p>YES Activates the deployment service. The RPC server registers the deployment service in the broker. NO The deployment service is deactivated. The RPC server does not register the deployment service in the broker.</p> <p>Example: DPLY=YES</p>	O
ENCR	<u>encryptionlevel</u>	0	<p>Enforce encryption when data is transferred between client and server. Requires EntireX Security. See ENCRYPTION-LEVEL under <i>Broker ACI Fields</i>.</p> <p>0 Encryption is enforced.</p>	O

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/ Opt
			<p>1 Encryption is enforced between server and broker kernel.</p> <p>2 Encryption is enforced between server and broker kernel, and also between client and broker.</p> <p>Example: ENCR=2</p>	
ENDW	<u>endworker</u>	TIMEOUT	<p>NEVER Defines worker model <b>FIXED</b> with a fixed number of worker threads. The number of active workers is defined with <b>ERXMAIN macro</b> parameter <b>MINW</b>.</p> <p>TIMEOUT Defines slow-shrinking worker model <b>SCALE</b>, where the number of worker threads is adjusted to the current number of client requests. With value <b>TIMEOUT</b>, all worker threads not used are stopped in the time specified by the <b>ERXMAIN macro</b> parameter <b>TOUT</b>, except for the minimum number of active workers specified with <b>ERXMAIN macro</b> parameter <b>MINW</b>. The upper limit of workers parallel active is restricted with <b>ERXMAIN macro</b> parameter <b>MAXW</b>.</p> <p>IMMEDIATE Defines fast-shrinking worker model <b>SCALE</b>, where the number of worker threads is adjusted to the current number of client requests. With value <b>IMMEDIATE</b>, worker threads not used are stopped immediately as soon as they have finished their conversation, except for the minimum number of active workers defined with <b>ERXMAIN macro</b> parameter <b>MINW</b>. The upper limit of workers active in parallel is restricted with <b>ERXMAIN macro</b> parameter <b>MAXW</b>.</p> <p>This parameter is forced to value <b>TIMEOUT</b> if impersonation is switched on, see <i>Impersonation</i> and <b>ERXMAIN macro</b> parameter <b>IMPS</b>.</p> <p>Example: ENDW=IMMEDIATE , MINW=2 , MAXW=6</p>	O

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/Opt	
MINW	<u>minworker</u>	1	Minimum number of workers active in parallel with worker model <a href="#">SCALE</a> or number of workers in worker model <a href="#">FIXED</a> . See also <a href="#">ERXMAIN macro</a> parameter <a href="#">ENDW</a> .  Example: MINW=2	O	
MAXW	<u>maxworker</u>	10	Upper limit of workers active in parallel with worker model <a href="#">SCALE</a> . See also <a href="#">ERXMAIN macro</a> parameter <a href="#">ENDW</a> .  Example: MAXW=2	O	
ETBL	<u>etblnk</u>	CICSETB	Define the broker stub to be used. See <i>Administering Broker Stubs</i> in the z/OS administration documentation for available stubs.  Example: ETBL=CICSETB	O	
EXIT	n.a.		At startup, the CICS RPC Server will call the user exit to synchronize its version. If successful, the CICS RPC Server will continue and call the user exit for the implemented events. See <a href="#">User Exit COBUEX02</a> .	O	
IMPS	<u>impersonation</u>	NO	Defines if RPC requests are executed under the user ID of the RPC client. Depending on settings, different levels of checks are done prior to RPC server execution. See also <a href="#">Impersonation</a> .  impersonation= <a href="#">NO</a>   <a href="#">YES</a>   <a href="#">AUTO</a> [ , <a href="#">sameuser</a>   , <a href="#">anyuser</a> ]	O	
			<b>NO</b>		The RPC request is executed anonymously, which means the user ID of the RPC client is not used. RPC requests are executed under the user ID of the RPC server.
			<b>YES</b>		The RPC request runs impersonated under the supplied <i>RPC client user ID</i> . For execution of the RPC request, the CICS RPC Server starts a separate impersonated user task, that is, the client must be know to CICS and the supplied password is validated against CICS. The worker model <a href="#">SCALE</a> is forced; for details see <a href="#">Impersonation</a> .
			<b>AUTO</b>		Same as option <a href="#">YES</a> above, except that no password validation is performed, that is,



ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/ Opt				
			<p>the client is treated as already authenticated. For this setting, make sure the RPC client is correctly authenticated; use either</p> <ul style="list-style-type: none"> <li>■ a secure broker (validation must be against the correct mainframe security repository where the user IDs are defined) and option <code>sameuser</code> or</li> <li>■ your own security implementation (option <code>anyuser</code> is supported for compatibility reasons if you need different broker and server user IDs - the customer-written security implementation must validate the RPC client using the <i>RPC client user ID</i>)</li> </ul> <table border="1" data-bbox="911 940 1422 1373"> <tr> <td data-bbox="911 940 1151 1192"><code>sameuser</code></td> <td data-bbox="1151 940 1422 1192">The CICS RPC Server checks whether the <i>broker client user ID</i> matches the <i>RPC client user ID</i>. This is the default if <code>AUTO</code> is used.</td> </tr> <tr> <td data-bbox="911 1192 1151 1373"><code>anyuser</code></td> <td data-bbox="1151 1192 1422 1373">The <i>RPC client user ID</i> is used for impersonation. The <i>broker client user ID</i> is ignored.</td> </tr> </table>	<code>sameuser</code>	The CICS RPC Server checks whether the <i>broker client user ID</i> matches the <i>RPC client user ID</i> . This is the default if <code>AUTO</code> is used.	<code>anyuser</code>	The <i>RPC client user ID</i> is used for impersonation. The <i>broker client user ID</i> is ignored.	
<code>sameuser</code>	The CICS RPC Server checks whether the <i>broker client user ID</i> matches the <i>RPC client user ID</i> . This is the default if <code>AUTO</code> is used.							
<code>anyuser</code>	The <i>RPC client user ID</i> is used for impersonation. The <i>broker client user ID</i> is ignored.							
<p><b>Note:</b></p> <ol style="list-style-type: none"> <li>EntireX supports two user ID/password pairs: a <i>broker client user ID/password</i> pair and an (optional) <i>RPC user ID/password</i> pair sent from RPC clients to the RPC server.</li> <li>With EntireX Security, the <i>broker client user ID/password</i> pair is checked. The <i>RPC user ID/password</i> pair is designed to be checked by the target RPC server. Thus it is possible to use different user IDs in the broker and target RPC server.</li> <li>RPC clients send the (optional) <i>RPC user ID/password</i> pair in the same way as specifying the Natural user ID/password pair for a Natural RPC Server. See for</li> </ol>								

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/Opt
			<p>example <i>Using Natural Security</i> in the respective section of the documentation.</p> <p>4. If the RPC client does not specify the optional <i>RPC user ID/password pair</i>, the <i>broker client user ID</i> is inherited to the <i>RPC user ID</i> and thus used for impersonation by the CICS RPC Server.</p> <p>Example: IMPS=auto</p>	
LOGN	<u>logon</u>	YES	<p>Execute broker functions LOGON/LOGOFF in worker threads. Must match the setting of the broker attribute AUTOLOGON. Reliable RPC requires logon set to YES. See <i>Reliable RPC</i>.</p> <p>NO No logon/logoff functions are executed. YES Logon/logoff functions are executed.</p> <p>Example: LOGN=no</p>	O
n.a.	<u>mapname</u>		Alias for command <i>memory</i> .	O
n.a.	<u>memory</u>		Command to load an <i>ERXMAIN Control Block</i> . See <i>Modifying Parameters of the RPC Server</i> .	O
OPTS	<u>runoption</u>	0	<p>This parameter is for special purposes. It provides the CICS RPC Server with additional information. The runoptions are normally set to meet the platform's requirements. Set this parameter only if a support representative provides you with an option and asks you to do so.</p> <p>Syntax: OPTS=&lt;option-list&gt; &lt;option-list&gt; = [&lt;option-list&gt;,&lt;option&gt;</p> <p>Example: OPTS=(RUNOPT1,RUNOPT2)</p>	O
PSWD	<u>password</u>		<p>Password for broker logon. Case-sensitive, up to 32 characters. For more information see broker ACI control block field PASSWORD.</p> <p>Example: PSWD=MyPwd</p>	O

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/Opt
PRELOAD	<u>preload</u>	YES	<p>Enable to call CICS RPC Server with AMODE=24</p> <p>YES Enable to call RPC server with AMODE 24 or 31. Internally the CICS RPC Server preloads the called RPC server before execution to check the AMODE and releases the RPC server after this. The disadvantage of this approach is the CICS USECOUNT of the called RPC server program is increased by 2 for every executed RPC call.</p> <p>NO The CICS RPC Server does not preload the called RPC server to check its AMODE. All RPC servers are called as running in AMODE 31. This option is useful for customers who require the CICS USECOUNT in their accounting (increased by 1 for every executed RPC call) but prevents usage of calling RPC Server with AMODE 24.</p>	O
REPL	<u>replicatename</u>	ESRV	<p>CICS transaction ID (uppercase, up to 4 characters) assigned to worker tasks and as default for user tasks if <i>Impersonation</i> is set. In the START-USER event of the user exit (see <i>User Exit COBUEX02</i>) the CICS transaction ID for user tasks can be overridden. See also <i>Introduction to the CICS RPC Server</i>.</p>	O
SMH	<u>smhport</u>	0	<p>The port where the server listens for commands from the System Management Hub (SMH). If this port is 0 (default), no port is used and management by the SMH is disabled.</p> <p>See <i>SMH Listener Service</i> for more information.</p> <p>Example: SMH=3001</p>	O
SVM	<u>svmfile</u>		<p>Usage and location of SVM files. If no SVM parameter is given, the RPC server tries to open the SVM container using CICS file with name ERXSVM. If this CICS file is not available, no server mappings are used. For more information see <i>Usage of SVM Files</i>.</p> <p>Syntax: SVM=NO   <i>cicsname</i></p> <p><i>cicsname</i> The RPC server tries to open the SVM container using the CICS file with name <i>cicsname</i>.</p> <p>no No server mappings are used.</p>	O

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/Opt
			<p>Example: SVM=MYSVM</p> <p>The server mapping file VSAM (container) must be installed and configured. See <i>Install the SVM File for a CICS RPC Server (Optional)</i> in the z/OS installation documentation.</p>	
TOUT	<u>timeout</u>	600	<p>Timeout in seconds, used by the server to wait for broker requests. See broker ACI control block field WAIT for more information. Also influences <a href="#">restartcycles</a>.</p> <p>See worker model <a href="#">SCALE</a> to define the lifetime of worker threads in slow-shrinking worker model SCALE.</p> <p>Example: TOUT=300</p>	O
TRC1	<u>tracedestination</u>	CSSL	Name of the destination for trace output. A valid CICS transient data queue.	O
TRLV	<u>tracelevel</u>	0	<p>Trace level for the server. See also <a href="#">Activating Tracing for the RPC Server</a>.</p> <p>Syntax: TRLV= <u>None</u>   Standard   Advanced   Support</p> <p>None No trace output. Standard For minimal trace output. Advanced For detailed trace output. Support This trace level is for support diagnostics and should only be switched on when requested by Software AG support.</p> <p>Example: TRLV=standard</p>	O
TROP	<u>traceoption</u>	none	<p>Additional trace option if trace is active.</p> <p>None No additional trace options. STUBLOG If <code>tracelevel</code> is Advanced or Support, the trace additionally activates the broker stub log. NOTRUNC Normally if a data buffer larger than 8 KB is traced, the buffer trace is truncated. Set this option to write the full amount of data without truncation.</p>	O

ERXMAIN Macro Syntax	RPC Online Maintenance Facility Commands	Default	Values	Req/ Opt
			<p><b>Note:</b> This can increase the amount of trace output data dramatically if you transfer large data buffers.</p> <p>Example: TROP=(STUBLOG,NOTRUNC)</p>	
USER	<u>userid</u>	ERXSRV1	<p>Used to identify the server to the broker. See broker ACI control block field USER-ID. Case-sensitive, up to 32 characters.</p> <p>Example: USER=MyUId</p>	R

## Locating and Calling the Target Server

---

The IDL library and IDL program names that come from RPC client are used to locate the RPC server. See `library-definition` and `program-definition` under *Software AG IDL Grammar* in the *IDL Editor* documentation. This two-level concept (library and program) has to be mapped to the CICS RPC Server environment. Different mechanisms are used depending on the language:

- COBOL
- PL/I

### COBOL

The approach used to derive the CICS program name for the RPC server depends on whether so-called server mapping files are used or not. See [Usage of SVM Files](#) for an introduction.

- If SVM files are used, the IDL library and IDL program names are used to form a key to locate the SVM entry in the SVM container. If an SVM entry is found, the CICS program name of the RPC server is derived from the SVM entry. In this case the IDL program name can be different to the CICS program name if it is renamed during wrapping process (see *Customize Automatically Generated Server Names*) or during the extraction process in the COBOL Mapping Editor (see *The Software AG IDL Tree Pane*).
- If no SVM files are used at all, the IDL program name is used as the CICS program name of the RPC server (the IDL library name is ignored).

#### ▶ To use the CICS RPC Server with COBOL

- 1 Make sure that all CICS programs called as RPC servers
  - use an interface type supported by the CICS RPC Server for target language COBOL; see [Supported Interface Types](#).
  - can be called with an `EXEC CICS LINK PROGRAM`
  - are accessible through the CICS RPL chain
- 2 Configure the `ERXMAIN` macro parameter `SVM` depending on whether SVM files are used or not.

See also [Scenario I: Calling an Existing COBOL Server](#) or [Scenario II: Writing a New COBOL Server](#).

## PL/I

There is a simple mechanism to derive the RPC server CICS program name:

- The IDL program name is used as the CICS program name.
- The IDL library name is not used.

### ▶ To use the CICS RPC Server with PL/I

- Make sure that all CICS programs called as RPC servers
  - use an interface type supported by the CICS RPC Server for target language PL/I; see [Supported Interface Types](#).
  - can be called with an `EXEC CICS LINK PROGRAM`
  - are accessible through the CICS RPL chain

See also [Scenario III: Calling an Existing PL/I Server](#) or [Scenario IV: Writing a New PL/I Server](#).

## Using SSL or TLS with the RPC Server

The CICS RPC Server does not have direct SSL or TLS support inside. For this purpose, use instead IBM's Application Transparent Transport Layer Security (AT-TLS), where the establishment of the SSL or TLS connection is pushed down the stack into the TCP layer.

See *SSL or TLS and Certificates with EntireX* for more information.

### ▶ To set up SSL or TLS with AT-TLS

- 1 Set up the CICS RPC Server for a TCP/IP connection.
- 2 Configure the rules for the AT-TLS policy agent the CICS RPC Server matches, for example by using the CICS job name and remote port number the CICS RPC Server connects to. Used certificates are also defined with those rules. Refer to your IBM documentation for further information.
- 3 Make sure the target the CICS RPC Server connects to is prepared for SSL/TLS connections as well. See the following sections:
  - *Running Broker with SSL or TLS Transport* in the respective section of the administration documentation
  - *Setting up and Administering the Broker SSL Agent* in the UNIX and Windows administration documentation

- Direct RPC in the EntireX Adapter documentation under *webMethods > Mainframe Integration* on the [Software AG Product Documentation](#) website


## User Exit COBUEX02

The CICS RPC Server provides a user exit COBUEX02 to influence/control the RPC logic. This section covers the following topics:

- User Exit Events
- Writing the User Exit
- Configuring the User Exit

### User Exit Events

The user exit is called on the following events:



- 1 **START-WORKER** event before a CICS worker task is started. This allows you to programmatically set the CICS transaction ID. You can terminate an RPC request by specifying an *ERROR-CODE* and optional *ERROR-TEXT*.
- 2 **START-USER** event. Before an impersonated CICS transaction (worker task) is started, the user exit may change the user ID and CICS transaction ID of the new impersonated worker. See *Impersonation*. You can terminate an RPC request by specifying an *ERROR-CODE* and optional *ERROR-TEXT*.



- 3 CALL-START event. The RPC request (payload data from the RPC client to the RPC server) may be inspected and modified. You can terminate an RPC request by specifying *ERROR-CODE* and optional *ERROR-TEXT*.
- 4 CALL-END event. The RPC reply (payload data from the RPC server to the RPC client) may be inspected and modified. If an *ERROR-CODE* and optional *ERROR-TEXT* is given in the API, this error is returned to the RPC client instead of the payload.

## Writing the User Exit

The Developer's Kit RPC source data set EXP960.SRCE of the EntireX CICS installation provides the user exit skeleton COBUEX02 for COBOL. Copy this skeleton so you have your own user exit source for modifications.

Accordingly, a COBOL copybook COBUEX02 is provided in EXP960.INCL. Please add this library to your COBOL compiler SYSLIB DD chain.

The most important API parameters of the user exit are described below. Other parameters are informational and are described in the source code. The user exit program must comply with the EXEC CICS LINK PROGRAM COMMAREA conventions.

Parameter	Description
VERSION	Required for future changes. Do not change the skeleton code.
ERROR-CODE	You can terminate the current request: Any number between 1 and 9999 will cause the CICS RPC Server to stop execution of the current RPC request and pass back the given error code with message class 1022 to the RPC client. See <i>Message Class 1022 - CICS RPC Server User Exit Messages</i> under <i>Error Messages and Codes</i> . With error code 0000, the CICS RPC Server continues as normal.
ERROR-TEXT	If the error code is not zero, an error text of up to 256 characters may be applied. This is passed to the RPC client.
CICS-TRANSID	Can be applied in the event START-USER, otherwise it is informational. Apply the TRANSID that your business logic requires.
CICS-TERMINID	Can be applied in the event START-USER, otherwise it is informational. In some (rare) cases, RPC server routines require a terminal ID. Apply the TERMINID that your business logic requires.
USERID	Can be applied in the event START-USER otherwise it is informational. Under some circumstances, it might be necessary to change the original RPC-USERID from the calling RPC client.
DATA-POINTER	This pointer refers to the payload data for the events CALL-START and CALL-END. The payload to which this pointer is pointing may be inspected as well as modified. The pointer itself must not be changed.

## Configuring the User Exit

Apply the name of your exit routine to the EntireX RPC server `ERXMAIN` macro parameter `EXIT`. See *Configuring the RPC Server*.

At startup, the CICS RPC Server will call the named user exit to synchronize its version. If successful, the *RPC Online Maintenance Facility* will display the user exit as map field "parameter opts". See *To display the Server parameters* (PF06) under *RPC Online Maintenance Facility*. The CICS RPC Server will continue and call the user exit for the implemented events.

## Autostart/Stop during CICS Start/Shutdown

---

The CICS RPC Server can be started and stopped automatically during start and stop of the CICS region. For manual start/stop, see *Starting the RPC Server* and *Stopping the RPC Server* under *RPC Online Maintenance Facility*.

### ▶ To start the CICS RPC Server during the initialization of CICS

- 1 If the COBOL source `ERXSTART` of the EntireX installation library `EXP960.SCOB` has not been defined in the CICS CSD data sets by the installation job `$INSTALL`, define it.
- 2 Customize and compile `ERXSTART` if necessary.
- 3 Add the following entry to your CICS `PLTPI` table (second phase PLT program):

```
DFHPLT TYPE=ENTRY , PROGRAM=ERXSTART
```

See also *Starting the EntireX RPC Server Automatically on CICS Startup (Optional)* under *Installing EntireX RPC Servers under CICS* under *Installing EntireX RPC Servers under CICS* in the z/OS installation documentation.

### ▶ To stop the CICS RPC Server during the shutdown of CICS

- 1 If the COBOL source `ERXSTOP` of the EntireX installation library `EXP960.SCOB` has not been defined in the CICS CSD data sets by the installation job `$INSTALL`, define it.
- 2 Customize and compile `ERXSTOP` if necessary.
- 3 Add the following entry to your CICS `PLTSD` table (first phase PLT program):

```
DFHPLT TYPE=ENTRY ,PROGRAM=ERXSTOP
```

See also *Stopping the EntireX RPC Server Automatically on CICS Shutdown (Optional)* under *Installing EntireX RPC Servers under CICS* under *Installing EntireX RPC Servers under CICS* in the z/OS installation documentation.

## Multiple RPC Servers in the same CICS

---

If you need to install multiple instances in the same CICS region, see *Installing Multiple EntireX RPC Servers in the same CICS (Optional)* under *Installing EntireX RPC Servers under CICS* under *Installing EntireX RPC Servers under CICS* in the z/OS installation documentation.



# 3

## RPC Online Maintenance Facility

---

- Monitoring the RPC Server ..... 32
- Starting the RPC Server ..... 34
- Pinging the RPC Server ..... 34
- Stopping the RPC Server ..... 35
- Modifying Parameters of the RPC Server ..... 35
- Activating Tracing for the RPC Server ..... 35
- Console Commands for the RPC Server ..... 36

## Monitoring the RPC Server

The parameters in the following screens are described under *Configuring the RPC Server*.

▶ **To call the RPC Online Maintenance Facility and display the RPC Broker Parameters**

- Start the CICS transaction

```
ERXM [MEM=erxmain-control-block]
```

where *erxmain-control-block* is the name of the ERXMAIN control block. See **ERXMAIN Control Block** under *Customizing the RPC Server*.

The RPC Broker Parameter map is displayed:

```
11:56:56          --- ERX CICS Online utility  V960.0 ---          06/02/2014
                    RPC Broker Parameter

Broker parameter
Broker name      = ETB001
Class name       = RPC
Server name      = SRV1
Service name     = CALLNAT
User ID          = ERXSRV1
Code page        =

Logon            = No
Server timeout   = 600
Encryptionlevel = 0
Compression lvl  = N

ETBLNK          = CICSETB

COMMAND ==>

-----
PF01=Help  03=Exit  04=Control  05=Broker parms  06=Server parms
           08=Start server  09=Ping server  10=Stop server
```

Press **PF05** from any map to return to the RPC Broker Parameter map.

▶ **To display the RPC Server Parameters**

- Press **PF06** from any map and the RPC Server Parameters will be displayed:

```

12:03:05          --- ERX CICS Online utility  V960.0 ---          06/02/2014
                    RPC Server Parameter

Server parameter
# Min. Workers =      2              Trace Level      = 0
# Max. Workers =      2              Trace Dest.(TD)= CSSL
Ending Workers = Never
Impersonation  = No
Deployment     = Yes
Restart Cycles =      3
SMH Port      =

Server options = SVM      AutoSYNC
Marshal options=

CICS parameter                Mapping file = ERXSVM   (Prefered)
Memory name   = ERXMAIN   (V900)   Dsn(ENTIREX.SVMDEV.KSDS)
Transaction ID = ESRV              Opn Add Rea Upd Del

COMMAND ===>
-----
PF01=Help   03=Exit   04=Control   05=Broker parms   06=Server parms
              08=Start server  09=Ping server   10=Stop server

```

▶ To display the RPC Server Control map

■ Press **PF04**.

```

12:07:18          --- ERX CICS Online utility  V960.0 ---          06/02/2014
                    RPC Server Control

MAIN Task
Status      Running

WORKER Tasks
Registered      2
Busy            0
Maximum busy    2

USER Tasks
Active          0
Max. active     0

BrokerId in use:  ETB001
Class in use:     RPC
Server Name in use: SRV1
Service in use:   CALLNAT

COMMAND ===>

```

PF01=Help	03=Exit	04=Control	05=Broker parms	06=Server parms
		08=Start server	09=Ping server	10=Stop server

▶ **To display help for the RPC Online Maintenance Facility**

- Enter `Help` or press **PF01**.

▶ **To stop the RPC Online Maintenance Facility**

- Enter `Exit` or press **PF03**.

## Starting the RPC Server

---

▶ **To start the CICS RPC Server using the RPC Online Maintenance Facility**

- 1 Start the CICS transaction `ERXM` to call the RPC Online Maintenance Facility. See also [Monitoring the RPC Server](#).
- 2 Start the server with the **PF08** key or with the command `start`.  
The status of the `MAIN` task (see RPC server control panel) changes to “is running”. The defined number (see `ERXMAIN` macro parameter `MINW`) of worker tasks that are registered is displayed.

If an error occurred and the CICS RPC Server is not correctly registered in the broker, but the number of currently active worker tasks is not zero:

- Check with CICS command `CEMT INQUIRE TASK` whether server instances are already running. If yes, stop them using native CICS commands.
- Verify the server parameters matching your system requirements. See column 2 of table under [Configuring the RPC Server](#).
- Then issue command `start` or use **PF08**.

## Pinging the RPC Server

---

▶ **To ping the CICS RPC Server using the RPC Online Maintenance Facility**

- 1 Start the CICS transaction `ERXM` to call the EntireX RPC Online Maintenance Facility. See [Monitoring the RPC Server](#).
- 2 Issue the command `ping` or use **PF09**.



## Alternative Method

- Use the `ping` command from the console. See [Console Commands for the RPC Server](#).

## Stopping the RPC Server

---

### ▶ To stop the CICS RPC Server using the RPC Online Maintenance Facility

- 1 Start the CICS transaction `ERXM` to call the RPC Online Maintenance Facility. See [Monitoring the RPC Server](#).
- 2 Issue the `stop` command or use **PF10**. This ensures correct deregistration from broker and all worker tasks are shut down.

## Modifying Parameters of the RPC Server

---

With RPC Online Maintenance Facility commands, CICS RPC Server parameters can be temporarily modified. Modifications are lost if CICS is restarted. The purpose of the commands is to try out easily new configurations. For persistent modifications (setup) of the CICS RPC Server, reassemble the **ERXMAIN Control Block** using the **ERXMAIN Macro**.

### ▶ To modify the CICS RPC Server parameters using the RPC Online Maintenance Facility

- 1 Start the CICS transaction `ERXM` to call the EntireX RPC Online Maintenance Facility. See [Monitoring the RPC Server](#).
- 2 Use the appropriate RPC Online Maintenance Facility command to modify the parameters. See the column 2 of table under [Configuring the RPC Server](#).

## Activating Tracing for the RPC Server

---

### ▶ To switch on tracing for the CICS RPC Server using the RPC Online Maintenance Facility

A prerequisite to switch on tracing is a valid defined trace destination. We recommend defining it permanently, see **ERXMAIN macro** parameter `TRC1`.

- 1 Start the CICS transaction `ERXM` to call the EntireX RPC Online Maintenance Facility. See [Monitoring the RPC Server](#).

- 2 Use the command `tracellevel=tracellevel`, where *tracellevel* is one of None, Standard, Advanced or Support. See [ERXMAIN macro](#) parameter `TRLV`.

Example: `tracellevel=Standard`

To evaluate CICS RPC Server return codes, see *EntireX RPC Server Return Codes* under *Error Messages and Codes*.

## Console Commands for the RPC Server

---

The RPC Online Maintenance Facility ERXM can be used directly from a z/OS console using the z/OS command `MODIFY /F`. In the command syntax below:

- *cics-name* is the name of the CICS job
- *erxmain-control-block* is the name of the [ERXMAIN Control Block](#). It can be omitted if the default name ERXMAIN is used.
- No blanks are allowed in the string provided to ERXM, for example  
`MEM=erxmain-control-block,CMD=...`

### ▶ To start the CICS RPC Server from a z/OS console

- Use the following z/OS modify command:

```
F cics-name,ERXM [MEM=erxmain-control-block,]CMD=START
```

### ▶ To ping the CICS RPC Server from a z/OS console

- Use the following z/OS modify command:

```
F cics-name,ERXM [MEM=erxmain-control-block,]CMD=PING
```

### ▶ To stop the CICS RPC Server from a z/OS console

- Use the following z/OS modify command:

---

```
F cics-name,ERXM [MEM=erxmain-control-block,]CMD=STOP
```

▶ **To switch on tracing for the CICS RPC Server from a z/OS console**

- Use the following z/OS modify command:

```
F cics-name,ERXM [MEM=erxmain-control-block,]CMD=TRACELEVEL=tracelevel
```

For *tracelevel*, see [Activating Tracing for the RPC Server](#).



# 4 Deployment Service


---

- Introduction ..... 40
- Scope ..... 41
- Enabling the Deployment Service ..... 41
- Disabling the Deployment Service ..... 42

## Introduction

The deployment service

- is the (server-side) counterpart to the deployment wizard; see *Server Mapping Deployment Wizard*.
- is a built-in service of the EntireX RPC server, which can be enabled/disabled by EntireX RPC server configuration settings
- usage can be restricted to certain users or group of users, using EntireX Security; see *Authorization of Client and Server* under *Overview of EntireX Security* in the EntireX Security documentation.



## Scope

The deployment service is used for the

- IDL Extractor for COBOL to deploy SVM files with the deployment wizard;
- COBOL Wrapper for server generation to deploy SVM files with the deployment wizard.

See *Server Mapping Deployment Wizard*.

The deployment service uses the same class and server names as defined for the EntireX RPC server, and DEPLOYMENT as the service name, resulting in `class/server/DEPLOYMENT` as the broker service. Please note DEPLOYMENT is a service name reserved by Software AG. See broker attribute SERVICE.

## Enabling the Deployment Service

### ▶ To enable the deployment service

- 1 For a CICS RPC Server, the server mapping file VSAM (container) must be installed and configured. See *Install the SVM File for a CICS RPC Server (Optional)* in the z/OS installation documentation.
- 2 Set *ERXMAIN Macro* parameter DPLY=YES. See DPLY under *Configuring the RPC Server*.
- 3 Define in the broker attribute file, under the RPC service, an additional broker service with DEPLOYMENT as the service name and values for class and server identical to those used for the RPC service. For example, if your RPC service is named

```
CLASS = RPC    SERVER = SRV1    SERVICE = CALLNAT
```

the deployment service requires the following additional service definition in the broker attribute file:

```
CLASS = RPC    SERVER = SRV1    SERVICE = DEPLOYMENT
```

- 4 Optional. If you need to restrict the use of the deployment service to a selected group of users, use EntireX Security and define security rules for the `class/server/DEPLOYMENT` broker service. The service name DEPLOYMENT is a constant.
  - For a z/OS broker, see *Resource Profiles in EntireX Security* in the EntireX Security documentation.

- For a UNIX or Windows broker, see *Administering Authorization Rules using System Management Hub* in the UNIX and Windows administration documentation.
- Not applicable to a BS2000/OSD or z/VSE broker.

## Disabling the Deployment Service

---

### ▶ To disable the deployment service

- Set *ERXMAIN Macro* parameter `DPLY=NO`. See *ERXMAIN macro* parameter `DPLY`.

The CICS RPC Server will not register the deployment service in the broker.



# 5 Handling SVM Files

---

- SVM Files in the EntireX Workbench ..... 44
- SVM Files in the RPC Server ..... 44
- Source Control of SVM Files ..... 45
- Change Management of SVM Files ..... 45
- Compare SVM Files ..... 45
- List Deployed SVM Files ..... 45
- Check if an SVM File Revision has been Deployed ..... 46
- Access Control: Secure SVM File Deployment ..... 46
- Ensure that Deployed SVM Files are not Overwritten ..... 46
- When is an SVM File Required? ..... 47
- Is There a Way to Smoothly Introduce SVM Files? ..... 49

A server mapping file (SVM) enables the RPC server to correctly support special COBOL syntax such as `REDEFINES`, `JUSTIFIED`, `SYNCHRONIZE` and `OCCURS DEPENDING ON` clauses, `LEVEL-88` fields, etc. If one of these elements is used, the EntireX Workbench automatically extracts an SVM file in addition to the IDL (interface definition language), or an SVM file is generated by the COBOL Wrapper for a server skeleton. The SVM file is used at runtime to marshal and unmarshal the RPC data stream.

## SVM Files in the EntireX Workbench

---

In the *EntireX Workbench*, an SVM file has to relate to an appropriate IDL file. Therefore, you always have to keep the IDL file and the SVM file together in the same folder.

If there is an SVM file and a corresponding IDL file,

- at least one of the IDL programs in the corresponding IDL file requires server-mapping information to correctly call the target server. For those IDL programs, there is an SVM entry (line) in the Workbench SVM file.
- deployment of the SVM file to the RPC server is mandatory, see *Server Mapping Deployment*.

If there is an IDL file but no corresponding SVM file,

- there is no IDL program that requires server mapping information.

## SVM Files in the RPC Server

---

Under z/OS, SVM entries of the EntireX Workbench SVM files are stored as records within one VSAM file (containing all SVM entries from all Workbench SVM files). The unique key of the VSAM file consists of the first 255 bytes of the record: for the type (1 byte), for the IDL library (127 bytes) and for the IDL program (127 bytes). The CICS, Batch and IMS RPC servers use a VSAM file as the container.

If *one* server requires an SVM file, you need to provide this to the RPC server:

- Development environments: to allow the deployment of new SVM files, enable the deployment service. See *Enabling the Deployment Service*.
- Production environments: provide SVM files to the RPC server. See `ERXMAIN` macro parameter `SVM`.

If *no* server requires an SVM file, you can execute the RPC server without SVM files:

- Development environments: you can disable the deployment service. See *Disabling the Deployment Service*.

- Production environments: there is no need to provide SVM files to the RPC server. See `ERXMAIN` macro parameter `SVM`.

## Source Control of SVM Files

---

Because SVM entries within an SVM file contain text data only, a Workbench SVM file is text-based (although it is not intended for human consumption). Therefore, you can include it in your source control management together with the IDL file and the COBOL source(s) as a triplet that should always be kept in sync.

## Change Management of SVM Files

---

Under z/OS, change management for a VSAM file (SVM container) is similar to change management for a database. The complete VSAM file can be backed up at any time, for example by using IDCAMS. All updates to the VSAM file done after a backup must be kept.

All Workbench SVM files added since the last backup should be available.

## Compare SVM Files

---

For SVM files in the *EntireX Workbench* format, you can use a third party file/text compare tool to check if two files are identical.

The SVM entries (corresponding to lines in a Workbench SVM file) contain a creation timestamp at offset 276 (decimal) in the format `YYYYMMDDHHIISST`. The precision is 1/10 of a second.

## List Deployed SVM Files

---

Use IDCAMS:

```
//EXXPRINT JOB ( , , , 999 ), ENTIREX, NOTIFY=&SYSUID, MSGLEVEL=(1,1),
//          CLASS=K, MSGCLASS=X, REGION=OM
//*-----*
//* PRINT CONTENTS OF AN SVM VSAM CLUSTER *
//*-----*
//SVMPRINT EXEC PGM=IDCAMS
//SYSPRINT DD SYSOUT=*
//IN      DD DISP=SHR, DSN=ETS.SVM.KSDS
//OUT     DD SYSOUT=*
```

```
//SYSIN DD *  
PRINT -  
  INFILE(IN) -  
  DUMP | HEX | CHAR -  
  OUTFILE(OUT)  
/*  
//
```

Use `DUMP` or `CHAR` format to print the SVM records of the VSAM file.

## Check if an SVM File Revision has been Deployed

---

SVM entries (corresponding to lines in Workbench SVM files) contain a creation timestamp at offset 276 (decimal) in the format `YYYYMMDDHHIISST`. Precision is 1/10 of a second. The creation timestamp can be checked.

The timestamp can be found on the same offset in the records in the VSAM file (SVM container).

## Access Control: Secure SVM File Deployment

---

For deployment with the *Server Mapping Deployment Wizard*, use EntireX Security if the broker is running on platforms z/OS, UNIX, Windows or z/VSE. See [Enabling the Deployment Service](#).

For IBM deployment tool IDCAMS, use RACF to secure deployment.

## Ensure that Deployed SVM Files are not Overwritten

---

For IDCAMS, use the `NOREPLACE` option to disallow overwriting of duplicate SVM records in the VSAM file (container). See *Server Mapping Deployment using FTP and IDCAMS*.

## When is an SVM File Required?

### For the IDL Extractor for COBOL

Interface Type	COBOL Syntax	COBOL Mapping Editor	SVM Required	More Information
CICS with DFHCOMMAREA Calling Convention and IN different to OUT	all		yes	<i>CICS with DFHCOMMAREA Calling Convention under Introduction to the IDL Extractor for COBOL   CICS DFHCOMMAREA under COBOL Parameter Selection</i>
CICS Channel Container Calling Convention	all		yes	<i>CICS with Channel Container Calling Convention</i>
CICS with DFHCOMMAREA Large Buffer Interface	all		yes	<i>CICS with DFHCOMMAREA Large Buffer Interface</i>
IMS MPP Message Interface (IMS Connect)	all		yes	<i>IMS MPP Message Interface (IMS Connect)</i>
IMS BMP with Standard Linkage Calling Convention	all		yes	<i>IMS BMP with Standard Linkage Calling Convention</i>
Micro Focus with Standard Linkage Calling Convention	BINARY clause		yes	<i>Micro Focus with Standard Linkage Calling Convention</i>
all	OCCURS DEPENDING ON clause		yes	<i>Tables with Variable Size - DEPENDING ON Clause under COBOL to IDL Mapping in the IDL Extractor for COBOL documentation</i>
all	REDEFINES clause		yes	<i>REDEFINE Clause</i>
all	TRAILING [SEPARATE] clause		yes	<i>SIGN LEADING and TRAILING SEPARATE Clause</i>
all	LEADING [SEPARATE] clause		yes	<i>SIGN LEADING and TRAILING SEPARATE Clause</i>
all	ALIGNED RIGHT attribute		yes	
all	all	Rename of program	yes	<i>The Software AG IDL Tree Pane under Mapping Editor User Interface in the IDL Extractor for COBOL documentation</i>

Interface Type	COBOL Syntax	COBOL Mapping Editor	SVM Required	More Information
all	all	Map to operation	yes	<i>Context Menu</i> under <i>The COBOL Parameters Pane</i>
all	all	Map to constant	yes	<i>Context Menu</i>
all	all	Suppress	yes	<i>Context Menu</i>
other combinations			no	

### For the COBOL Wrapper

This depends on the interface type chosen and the IDL type:

Interface Type	IDL Type	COBOL Wrapper	SVM Required	More Information
CICS with DFHCOMMAREA Large Buffer Interface	all		yes	<i>CICS with DFHCOMMAREA Large Buffer Interface</i> under <i>COBOL Server Interface Types</i>
CICS with Channel Container Calling Convention	all		yes	<i>CICS with Channel Container Calling Convention</i>
IMS BMP with Standard Linkage Calling Convention	all		yes	<i>IMS BMP with Standard Linkage Calling Convention</i>
Micro Focus	I2 or I4		yes	<i>Micro Focus with Standard Linkage Calling Convention</i>   <i>IDL Data Types</i> under <i>Software AG IDL File</i> in the IDL Editor documentation
all	IDL unbounded array		yes	<i>array-definition</i> under <i>Software AG IDL Grammar</i> in the IDL Editor documentation
all	IDL unbounded group		yes	<i>group-parameter-definition</i> under <i>Software AG IDL Grammar</i> in the IDL Editor documentation
all	all	IDL program name is not a valid COBOL name and is therefore adapted, or the COBOL program name is customized	yes	<i>Customize Automatically Generated Server Names</i>
other combinations			no	

## Is There a Way to Smoothly Introduce SVM Files?

---

All EntireX RPC servers can be executed without SVM files. There is no need to install the SVM container (see [SVM Files in the RPC Server](#)) as long as you do not use features that require SVM files (see [When is an SVM File Required?](#)). You can also call COBOL servers generated or extracted with previous versions of EntireX mixed with a COBOL server that requires SVM files. All EntireX RPC servers are backward compatible.





# 6 Scenarios and Programmer Information

---

- COBOL Scenarios ..... 52
- PL/I Scenarios ..... 53
- Aborting RPC Server Customer Code and Returning Error to RPC Client ..... 54
- Automatic Syncpoint Handling ..... 59

## COBOL Scenarios

---

- [Scenario I: Calling an Existing COBOL Server](#)
- [Scenario II: Writing a New COBOL Server](#)

### Scenario I: Calling an Existing COBOL Server

#### ▶ To call an existing COBOL server

- 1 Use the *IDL Extractor for COBOL* to extract the Software AG IDL and, depending on the complexity of the extraction, also an SVM file.
- 2 Build an EntireX RPC client using any EntireX wrapper. See *EntireX Wrappers*. For a quick test you can:
  - use the IDL Tester; see *EntireX IDL Tester* in the EntireX Workbench documentation
  - generate an XML mapping file (XMM) and use the XML Tester for verification; see *EntireX XML Tester*

See *Client and Server Examples for z/OS CICS* for COBOL RPC Server examples.

### Scenario II: Writing a New COBOL Server

#### ▶ To write a new COBOL server

- 1 Use the *COBOL Wrapper* to generate a COBOL server skeleton and, depending on the complexity of the extraction, also an SVM file. Write your COBOL server and proceed as described under *Using the COBOL Wrapper for the Server Side*.
- 2 Build an EntireX RPC client using any EntireX wrapper. See *EntireX Wrappers*. For a quick test you can:
  - use the IDL Tester; see *EntireX IDL Tester* in the EntireX Workbench documentation
  - generate an XML mapping file (XMM) and use the XML Tester for verification; see *EntireX XML Tester*

See *Client and Server Examples for z/OS CICS* for COBOL RPC Server examples.

---

## PL/I Scenarios

---

- Scenario III: Calling an Existing PL/I Server
- Scenario IV: Writing a New PL/I Server

### Scenario III: Calling an Existing PL/I Server

▶ To call an existing PL/I server

- 1 Use the *IDL Extractor for PL/I* to extract the Software AG IDL.
- 2 Build an EntireX RPC client using any EntireX wrapper. See *EntireX Wrappers*. For a quick test you can:
  - use the IDL Tester; see *EntireX IDL Tester* in the EntireX Workbench documentation
  - generate an XML mapping file (XMM) and use the XML Tester for verification; see *EntireX XML Tester*

See *Client and Server Examples for z/OS CICS* for PL/I RPC Server examples.

### Scenario IV: Writing a New PL/I Server

▶ To write a new PL/I server

- 1 Use the *PL/I Wrapper* to generate a PL/I server skeleton. Write your PL/I server and proceed as described under *Using the PL/I Wrapper for the Server Side*.
- 2 Build an EntireX RPC client using any EntireX wrapper. See *EntireX Wrappers*. For a quick test you can:
  - use the IDL Tester; see *EntireX IDL Tester* in the EntireX Workbench documentation
  - generate an XML mapping file (XMM) and use the XML Tester for verification; see *EntireX XML Tester*

See *Client and Server Examples for z/OS CICS* for PL/I RPC Server examples.

## Aborting RPC Server Customer Code and Returning Error to RPC Client

---

This section covers the following topics:

- [Using EXEC CICS ABEND ABCODE](#)
- [Using EXEC CICS ABEND CANCEL](#)
- [Using RETURN-CODE Special Register \(COBOL only\)](#)

### Using EXEC CICS ABEND ABCODE

This approach applies to all CICS scenarios (all programming languages and all interface types); see [Supported Interface Types](#).

The CICS feature `EXEC CICS ABEND ABCODE(myabend)` may be used to indicate application error codes. According to IBM CICS standards, ABEND codes starting with the letter A are reserved for CICS itself and should not be used in your RPC server.

The CICS RPC Server follows these IBM CICS standards and sends back the RPC protocol message

1. 10010018 Abnormal termination during program execution. This is returned when an ABEND code starting with the letter "A" is received from CICS, which is a CICS ABEND.
2. 10010045 CICS ABEND myabend was issued. This is returned when an ABEND code starting with a letter other than "A" is received from CICS, which is an application error situation forced by your RPC server.

### Using EXEC CICS ABEND CANCEL

This approach applies to all CICS scenarios (all programming languages and all interface types) if impersonation is used (YES|AUTO). See [Supported Interface Types](#) and [Impersonation](#). If impersonation is not set, `EXEC CICS ABEND CANCEL` cannot be used.


If the customer server code uses the CICS feature `EXEC CICS ABEND CANCEL` to abort for particular error situations, the RPC server cannot trap the abort and is not able to send back an error to the RPC client. The RPC client gets a Broker timeout without any further information about the RPC server abort. In this case, to notify the RPC client you need to call `RPCUEX01` (immediately before `CICS ABEND CANCEL`) in the customer server code to inform the CICS RPC server that your program is about to abort with `CICS ABEND CANCEL`. EntireX does not recommend using `EXEC CICS ABEND CANCEL`. However, if you do need to call an existing COBOL program with `EXEC CICS ABEND CANCEL`, this can be done if the `RPCUEX01` call is added. Whenever possible use `EXEC CICS ABEND ABCODE` instead. See [Using EXEC CICS ABEND ABCODE](#).

- [Process Flow](#)
- [Usage](#)

- Installation

### Process Flow

The server invokes the server program using `CICS LINK PROGRAM` and expects that the program returns with `CICS RETURN`. However, if the program uses `CICS ABEND CANCEL` to abort for particular error situations, the RPC server cannot trap the abort. If your server program uses `CICS ABEND CANCEL` you need to call the delivered `RPCUEX01` to inform the server that your program is about to abort with `CICS ABEND CANCEL`.



- 1 The customer server program is invoked within the user task.
- 2 The customer server program decides to abort using `CICS ABEND CANCEL`. Immediately before calling `CICS ABEND CANCEL` it calls the `RPCUEX01`. After returning from `RPCUEX01` it performs `CICS ABEND CANCEL` to abort. The `CICS ABEND CANCEL` terminates the user task.
- 3 `RPCUEX01` posts the worker task and informs it about the abort of its associated user task. The worker task sends back the abort information to the RPC client.

## Usage

The server program calls `RPCUEX01` with:

```
EXEC CICS LINK PROGRAM('RPCUEX01')
      COMMAREA(rpcuex01-commarea)
```

After execution, the server program is responsible for aborting the task. If the server program ends without terminating the task, unpredictable results may occur.

Layout of `rpcuex01-commarea`:

- **Return code**

4-byte integer value. Value of -1 indicates failure.

- **Error text**

128-byte text field containing the error description.

If the call of `RPCUEX01` fails, the user program must not abort the task.

COBOL example for calling `RPCUEX01`:

```
01 UEX01-AREA.
   05 RETCODE          PIC S9(9) BINARY.
   05 ERRORTXT         PIC X(128).
   ...
   MOVE -1 TO RETCODE
   MOVE 'ERX: No Commarea access' TO ERRORTXT
   EXEC CICS LINK PROGRAM('RPCUEX01')
         COMMAREA(UEX01-AREA)
         RESP(RESP)
         RESP2(RESP2)
         END-EXEC
   IF RESP NOT = 0
       DISPLAY 'Error invoking RPCUEX01:'
       GO TO MAIN-EXIT
   END-IF
   IF RETCODE IS < 0
       DISPLAY 'Error from RPCUEX01:'
           ' ERRTXT = ' ERRORTXT
       GO TO MAIN-EXIT
   END-IF
* Now cancel the task...
EXEC CICS ABEND CANCEL END-EXEC
```

## Installation

The program `RPCUEX01` must reside in the CICS load library concatenation. The following PPT entry is required:

```
DEFINE PROGRAM(RPCUEX01) GROUP(EXX)
  DESCRIPTION(RPC user exit to abort RPC programs)
  LANGUAGE(C)
```

## Using RETURN-CODE Special Register (COBOL only)

This approach applies to the following CICS scenarios:

- *CICS with DFHCOMMAREA Calling Convention* (COBOL Wrapper | Extractor)
- *CICS with DFHCOMMAREA Large Buffer Interface* (COBOL Wrapper | Extractor)

CICS applications that use the DFHCOMMAREA as communication area (`EXEC CICS LINK` applications) may return error codes if the LINKed application has a C main entry and if this application is running in the same CICS (non-DPL program) as the CICS RPC Server. Under these circumstances, IBM's Language Environment for C provides the application return code to `EIBRESP2`, where it can be detected by the CICS RPC Server.

The following provided modules need to be linked to your application.

- `ERXRCSR`, a C main module that calls the intermediate COBOL subroutine `RCCALL` and catches the error from your RPC server and provides it to the CICS RPC Server. This module is available as source in the source data set `EXP960.SRCE` as well as precompiled in the load data set `EXP960.LD00`, so a C compiler is not needed.
- `RCCALL`, a COBOL subroutine calling your RPC server. This module is available as source in the CICS example server data set `EXP960.DVCO`.

A step-by-step description is given below, but for ease of use we recommend using the job `RCIGY`. See below.

### ▶ To set up your server to be able to return application errors manually

- 1 Change the `CALL` statement of the `RCCALL` program below which your RPC server is called instead of "MyCobol" below

```

IDENTIFICATION DIVISION.
PROGRAM-ID.      RCCALL.

*****
*
* CICS RPC Server
*
* Returning Application Errors from RPC Server to RPC Client
*
* This program calls your target COBOL Server.
*
* For further information and explanation refer to
* - "Writing Applications with the COBOL Wrapper"
* in the delivered documentation.
*
* $Revision: n.n $
*
* Copyright (C) 1997 - 20nn Software AG, Darmstadt, Germany
* and/or Software AG USA, Inc., Reston, VA, United States of
* America, and/or their licensors.
*
*****

ENVIRONMENT DIVISION.

DATA DIVISION.
WORKING-STORAGE SECTION.

LINKAGE SECTION.

01 DFHCOMMAREA.
   10 DFHCOMM-DUMMY          PIC X.

PROCEDURE DIVISION USING DFHCOMMAREA.

MAIN SECTION.
   CALL "my-cobol" USING DFHEIBLK DFHCOMMAREA.

MAIN-EXIT.
   EXIT PROGRAM.

END PROGRAM RCCALL.

```

- 2 In your RPC server, do not use EXEC CICS RETURN, because this prevents the return of the application error code to the CICS RPC server. If you are using a COBOL RPC server generated with the COBOL Wrapper, comment out or remove this line.
- 3 Compile the RCCALL program with a COBOL compiler supported by the COBOL Wrapper.



- 4 Link the compiled `RCCALL` program, the delivered `ERXRCSR` module and your RPC server together to a CICS program to be called by the CICS RPC Server. See also *Using the COBOL Wrapper for the Server Side* for supported CICS scenarios.

▶ **To set up your server to be able to return application errors using job `RCIGY`**

- Execute `RCIGY` as provided in the CICS example source data set `EXP960.DVCO`.

This enhanced job will

1. modify `RCCALL` as needed (step 1 from the manual approach, see above),
2. add the modified `RCCALL` code to your COBOL input source (step 2 from the manual approach, see above),
3. link edit with `ERXRCSR` (step 3 from the manual approach, see above).

## Automatic Syncpoint Handling

---

The CICS RPC Server issues a `SYNCPOINT` command under the following circumstances:

- After a successful non-conversational request or an end-of-conversation, the server issues a `SYNCPOINT COMMIT` command. If you are running under CICS with impersonation, this `SYNCPOINT` command is not executed by the server, but by CICS when the user task is terminated. See *Impersonation*.
- After abnormal termination of a non-conversational request or a conversation due to an error, the server performs a `SYNCPOINT ROLLBACK` command to back out any pending database modifications.

