ADAE* Adabas SAF Security (ADASAF) Messages

Note:
Each of the messages in this section starts with the relevant database ID.

Overview of Messages

ADAE01 | ADAE02 | ADAE03 | ADAE04 | ADAE05 | ADAE06 | ADAE07 | ADAE08 |
ADAE12 | ADAE15 | ADAE16 | ADAE17 | ADAE18

ADAE01   **Unable to load required modules**

Explanation   A required module could not be loaded. Operation terminates with an abend U0042.

Action   Check that the modules NA2PMAC and ESICFG are available.

ADAE02   **Unable to allocate required storage**

Explanation   There is insufficient storage available for ADASAF to operate. Operation terminates with an abend U0042.

Action   Increase the amount of storage (above the 16-megabyte line) available to the failing job.

ADAE03   **Unable to allocate NRS storage**

Explanation   ADASAF needs approximately two KB of storage below the 16-megabyte line. If the storage is not available at initialization (or after a newcopy operator command), ADASAF issues this message and operation terminates.

Action   Ensure that enough storage is available.

ADAE04   **Module *module-name* not loaded**

Explanation   The indicated module could not be loaded during initialization or during the newcopy operator command. If the module is required (rather than optional), operation terminates.

Action   Ensure that the module is available.

ADAE05   **Invalid parameters detected**

Explanation   One or more invalid parameters were specified in DDSAF. Operation terminates.

Action   Correct the invalid parameters.

ADAE06   **Allocation of user file cache failed**

Explanation   ADASAF allocates a user file cache above the 16-megabyte line. If the storage is not
                   available at initialization (or after a newcopy operator command), ADASAF issues this
                   message and operation terminates.

Action   Ensure that enough storage is available or reduce the MAXFILES parameter (this may
                   adversely affect performance).

ADAE07   *input-parameter*

Explanation   ADASAF echoes the parameters read from DDSAF for information and auditing
                   purposes.

ADAE08   **Invalid parameter:** *input-parameter*

Explanation   ADASAF detected incorrect input in DDSAF. ADAE08 is issued for each invalid
                   parameter found and is followed by ADAE05.

Action   Correct the invalid parameter.

ADAE12   **ADASAF is active in {FAIL|WARN} mode**

Explanation   ADASAF has successfully initialized in the mode indicated.

ADAE15   **NEWCOPY of parameter module failed**

Explanation   After a NEWCOPY operator command, ADASAF was unable to reload ESICFG.
                   Operation terminates.

Action   This error occurs only if there is a shortage of storage or the module ESICFG was
                   deleted from the load library after initialization. Determine which of these is the case
                   and correct it.

ADAE16   **NEWCOPY reinitialization failed**

Explanation   This message appears after a failure during NEWCOPY processing. It should be accompanied by a more detailed error message specifying the nature of the failure.

Action   Take the action recommended by the accompanying message.

ADAE17   **Not APF-authorized**

Explanation   ADASAF must run APF-authorized. Operation terminates.

Action   Check that all STEPLIBs are in the APF list and that ADARUN is linked with AC(1).

ADAE18   **No security details for job** *job-name*

Explanation   An Adabas command received from the named job had no security credentials attached to it. The command is rejected with response code 200 (ADARSP200), subcode 3.

Action   Ensure that the security exits are correctly installed in the Adabas SVC and that the source job has been configured correctly to support SAF security systems.