

ADAACK Utility Error Messages

Overview of Messages

ERROR-121	ERROR-122	ERROR-123	ERROR-125	ERROR-126	ERROR-127
ERROR-128	ERROR-129	ERROR-130	ERROR-131	ERROR-132	ERROR-133
ERROR-134	ERROR-135	ERROR-136	ERROR-137	ERROR-138	ERROR-139
ERROR-140	ERROR-141	ERROR-142	ERROR-143	ERROR-144	ERROR-145
ERROR-146					

ERROR-121 **Error counter reached maximum (ERRLIM)**

ERROR-122 **Invalid value for parameter file**

Explanation A range of file numbers must be supplied in ascending order.

Action Supply the correct parameter value and rerun the job.

ERROR-123 **Invalid or missing FROMISN/TOISN parameter**

ERROR-125 **Invalid block length for DS block xxxxxxxx (nnnn)**

ERROR-126 **AC Element contains DS RABN xxxxxxxx (nnnn) (duplicate ISN)**

ERROR-127 **AC element contains DS RABN xxxxxxxx (nnnn)**

ERROR-128 **ISN xxxxxxxx (nnnn) not found AC element contains DS RABN xxxxxxxx (nnnn)**

ERROR-129 **Wrong value for first unused ISN found in FCB**

Explanation FCB+ISNU (offset X'44') contains xxxxxxxx (nnnn) Actual first unused ISN = xxxxxxxx (nnnn)

ERROR-130 **Invalid datastorage block/record length. DS RABN = xxxxxxxx (nnnn)**

Explanation The sum of all record lengths in the block must be equal to the block length minus 4.

Action Run ADADCK to obtain more information.

ERROR-131 ISN found in DS record is greater or equal to the first unused ISN in the file.

Explanation The ISN found in a Data Storage record is greater or equal to the first unused ISN in the address converter.

ERROR-132 Invalid secondary ISN values in FCB

Explanation When spanned records are enabled, the first unused secondary ISN in the secondary address converter (used to map secondary ISNs to the RABNs of secondary records) must not be more than one higher than the maximum ISN included in the secondary address converter. In addition, the maximum ISN included in the secondary address converter must be the same as the highest allocated ISN for the secondary address converter.

ERROR-133 AC2-element contains DS-RABN xxxxxxxx (nnnn) (duplicate ISN)

Explanation When spanned records are enabled, a secondary address converter element contains a duplicate ISN.

ERROR-134 AC2-element contains DS-RABN xxxxxxxx (nnnn)

Explanation When spanned records are enabled, a mismatch exists between the secondary address converter elements and Data Storage.

ERROR-135 Wrong value for first unused AC2ISN found in FCB

Explanation When spanned records are enabled, the first unused ISN allocated in the secondary address converter and the first unused ISN in the secondary address converter do not match.

ERROR-136 AC2 ISN found in DS-record is greater or equal to the first unused AC2 ISN in the file

Explanation When spanned records are enabled, the secondary ISN found in the Data Storage record is larger than or equal to the first unused ISN in the secondary address converter.

ERROR-137 Spanned data storage record is invalid
DS-RABN = xxxxxxxx (nnnn)

Explanation When spanned records are enabled, the Data Storage RABN listed in the message is invalid.

Action Run the ADADCK utility for further details.

ERROR-138 Invalid rotating ISN *isn-num*

Explanation This ISN is outside the valid range.

Action Research the problem and contact your Software AG technical support representative for assistance.

ERROR-139 Cannot keep more than 500 million ISNs in core

Explanation The number of ISNs requested for the ADAACK utility exceeded the limit that can be requested.

Action Limit the ISN range and rerun the ADAACK job.

ERROR-140 Invalid ISN values in FCB

Explanation The first unused ISN must not be higher than the maximum ISN (MAXISN) plus 1. The maximum ISN must correspond to the highest allocated ISN.

ERROR-141 AC2 table overflow

Explanation When spanned records are enabled, a secondary address converter table overflow occurred.

**ERROR-142 ISN *xxxxxxxx (nnnn)* not found
AC2 element contains DS RABN *xxxxxxxx (nnnn)***

Explanation When spanned records are enabled, a Data Storage RABN was found in the secondary address converter, but not in Data Storage.

ERROR-143 Invalid rotating AC2 ISN *isn-num*

Explanation This secondary address converter ISN is outside the valid range.

Action Research the problem and contact your Software AG technical support representative for assistance.

ERROR-144 AC2 RABN *nnnnnnnn (nnnnnnnn)* is invalid

Explanation The secondary address converter RABN listed in the message is invalid.

Action Print the contents of the Associator blocks using the ADAPRI ASSOPRI utility function. Then contact your Software AG technical support representative for assistance.

ERROR-145 Invalid ISN values in FCB

Explanation Invalid ISN values were found in the FCB.

- The top ISN must not be higher than the last formatted ISN.
- The last formatted ISN must not be higher than the MAXISN.

Action Contact your Software AG technical support representative for assistance.

ERROR-146 Invalid secondary ISN values in FCB

Explanation Invalid secondary ISN values were found in the FCB.

- The top AC2 ISN must not be higher than the last formatted AC2 ISN.
- The last formatted AC2 ISN must not be higher than the AC2 MAXISN.

Action Contact your Software AG technical support representative for assistance.