

# ADASM\* Adabas SMF Processing Messages

## Overview of Messages

ADASM1 | ADASM2 | ADASM3 | ADASM4 | ADASM5 | ADASM6 | ADASM7

---

### **ADASM1 SMF=YES not allowed with MODE=SINGLE**

**Explanation** The specified ADARUN parameters are incompatible and cannot be specified at the same time in a nucleus startup job. The nucleus fails to initialize.

**Action** Correct the ADARUN parameters and restart the nucleus.

### **ADASM2 ADASMF unable to obtain storage**

**Explanation** Sufficient virtual storage for Adabas SMF is not available. The nucleus fails to initialize.

**Action** Either increase the size of the nucleus region or disable SMF recording by setting the ADARUN SMF parameter to NO.

### **ADASM3 SMF89 Registration return code *rc***

**Explanation** The IBM z/OS service IFAUSAGE produced a non-zero return code when registering for type 89 SMF records. The nucleus initializes without registering for type 89 SMF records.

**Action** The return codes are documented in the *z/OS MVS System Management Facilities (SMF)*, IBM document SA22-7630. Contact your Software AG technical support representative if you are unable to understand the error. You may disable registration attempts by setting the ADARUN SMF89 parameter to NO.

### **ADASM4 Invalid syntax of value for *parm***

**Explanation** An error was detected in the syntax of the parameter named in the message (*parm*). The parameter may be an ADARUN parameter or an operator command operand. The invalid value is ignored.

**Action** Remove or correct the specified parameter and try again.

**ADASM5      Unknown detail section *dtt* ignored**

**Explanation**    An invalid Adabas SMF record detail section mnemonic was specified in an ADARUN parameter or an operator command operand. The invalid mnemonic is given in the message (*dtt*). The invalid value is ignored.

**Action**            Remove or correct the specified detail section mnemonic and try again.

**ADASM6      *dtt* detail section disabled, maximum size exceeded**

**Explanation**    A single instance of the Adabas SMF record detail section listed in the message (*dtt*) exceeded the size that could be contained in a single Adabas SMF record. The specified detail section is disabled.

**Action**            If the detail section is a USER-type detail section, correct your SMF user exit. Otherwise, contact your Software AG technical support representative for assistance.

**ADASM7      Unknown SMF operator command**

**Explanation**    The SMF operator command was not recognized. It is ignored.

**Action**            Specify a valid SMF operator command.