

ADAVAL Utility Error Messages

Overview of Messages

ERROR-121 | ERROR-122 | ERROR-124 | ERROR-130 | ERROR-131

ERROR-121 Invalid descriptor field list for validate

Explanation The field name (field-name) is either

- not in the FDT; or
- not a descriptor.

Action Supply the correct parameter value, and rerun the ADAVAL job.

ERROR-122 TEMP data set too small; input record count= *count*

Action Supply a larger TEMP data set/file. See the Adabas Utilities documentation for information about calculating TEMP space.

ERROR-124 Invalid file requested: FNR=*file-number*

Explanation The Adabas checkpoint/security file cannot be checked by ADAVAL.

Action Supply a correct file list and rerun the ADAVAL job.

ERROR-130 Error initializing collating user exit - return code=*return-code*

Explanation An error occurred while the collation descriptor user exit was being initialized.

Action Investigate the cause of the error; correct it; and rerun the job.

ERROR-131 Collating user exit not loaded

Explanation The collation descriptor user exit requested is not loaded.

Action Load the exit and rerun the job.