


Development Environment

This chapter covers the following topics:

- Development Environment
- Customizing Your Environment
- Editors
- Code Page Support for Editors, System Commands and Utilities on the Mainframe

Development Environment

The development environment for Unicode applications is Natural Single Point of Development (SPoD).



In a SPoD environment, the Natural objects of a Unicode application which are located on a Natural Development Server (NDV) can be modified using Natural Studio. If supported by the server, the sources are exchanged between client and server in UTF-8 format.

On NDV servers for UNIX and OpenVMS, the setting of the profile parameter `SUTF8` determines the format that is used when storing the Natural object on the server. This is handled just like the local Windows case.

On NDV servers for mainframes, the objects are stored with the default or their original encoding, depending on the setting of the profile parameter `SRETAIN`.

Customizing Your Environment

On Windows, UNIX and OpenVMS platforms, it is important that you define the correct default code page for your environment before changing any Natural code. For more information, see *Migrating Existing Applications*.

If you want to store characters from different languages in your sources, you have to save the sources in UTF-8 format on Windows, UNIX or OpenVMS platforms, or you have to use hexadecimal UH constants in the sources. With the profile parameters `SUTF8` and `SRETAIN` you can control in which format sources are saved. The following table lists some situations and the recommended settings.

Note:

On UNIX and OpenVMS, the parameter `SUTF8` can only be used in a SPoD environment.

Situation	Settings	Effect
Sources are located on Windows; U constants are needed.	SUTF8=ON, SRETAIN=OFF	All sources are saved in UTF-8 format when saving them with Natural 6.2 or above. New sources are created in UTF-8 format. All characters can be stored in a source.
Sources are located on Windows, UNIX and/or OpenVMS; U constants are needed and SPoD is used for development.	SUTF8=ON, SRETAIN=ON	All sources are saved in UTF-8 format when a conversion to the original code page is no longer possible; if it is possible, the code page of a source will not be changed. New sources are created in UTF-8 format. All characters can be stored in a source. A source with UTF-8 format can only be changed with SPoD; it can no longer be handled with the Natural for UNIX or Natural for OpenVMS editors.
Sources are located on Windows; UNIX and/or OpenVMS; no U constants are needed.	SUTF8=OFF, SRETAIN=ON	All sources are saved with the original code page. New sources are saved with the default code page (of server). Only characters from the source code page can be stored in a source. The sources can further be handled with the Natural for UNIX or Natural for OpenVMS editors.
Sources are located on Windows, UNIX, OpenVMS and/or mainframe; U constants are needed and SPoD is used for development.	SUTF8=OFF, SRETAIN=ON	All sources are saved with the original code page. New sources are saved with the default code page (of the server). Only characters from the source code page can be stored in a source. The sources can further be handled with the Natural for UNIX, Natural for OpenVMS and Natural for Mainframes editors. All Unicode constants have to be defined as hexadecimal constants (UH).

If the parameter SUTF8 is set to OFF and you stow a source which contains characters from different character sets, but which was not yet saved in UTF-8 format, it is possible that the generated program is created, but that the source cannot be saved and thus remains unchanged. This happens if characters from different character sets are used in a comment or in a U constant. For this reason, it is recommended that you set the parameter SUTF8 to ON if you want to create sources with characters from different character sets and if your sources do not need to be distributed to mainframe platforms.

If the parameter SRETAIN is set to OFF, all sources are saved with the default code page. You have to be careful with this setting because it may lead to improper code page information if you have sources which were created with an earlier Natural version. In this case, the encoding information of the source is unassigned and the source is always opened with the default code page (value of the system variable *CODEPAGE). This will often work even if the default code page is not the correct encoding of the source. Some language-specific characters will be displayed incorrectly in this case. If such a source is opened with the wrong code page and is saved with SRETAIN being set to ON, no encoding will be stored for the source; the source can later be opened correctly if Natural is started with the correct default code page. However, once you have saved the source with SRETAIN being set to OFF, the default code page will be saved as the encoding of the source; from this time on, the source will only be opened with this code page. For this reason, you should use this setting only if you are certain that all of your Natural sources are encoded in the default code page.

See also: *Regional Settings* in the *Configuration Utility* documentation.

Editors

The Natural for Windows editors are fully Unicode-enabled. Via SPoD they can also be used for mainframe, UNIX and OpenVMS sources. The editors provided with Natural for Mainframes, Natural for UNIX and Natural for OpenVMS are not Unicode-enabled.

Note:

The editors provided with Natural for Mainframes provide code page support. See *Code Page Support for Editors, System Commands and Utilities on the Mainframe*.

When a source is opened with an editor in Natural Studio (Natural for Windows), the content of the source will be converted from the corresponding code page to Unicode before it is loaded into the editor. This will guarantee that all characters can be displayed correctly even if the source contains characters which are not included in the system code page. If the conversion from the source's code page to Unicode fails, an error will be displayed and the editor is not opened. In this case, the user has to define the correct encoding of the source. The source encoding can be changed in the **Properties** dialog box (see *Properties for the Nodes* in the *Using Natural Studio* documentation).

For Windows, UNIX and OpenVMS sources, the Natural for Windows editors allow saving sources which contain characters from different languages in UTF-8 format. On mainframes, it will not be possible to save UTF-8 sources.

Note:

If you save a UNIX or OpenVMS source in UTF-8 format or with a code page which differs from the default code page, the source can no longer be opened with the native Natural for UNIX or Natural for OpenVMS editor. Mainframe sources can be saved with a different code page and can be edited with the native Natural for Mainframes editors.

Even if you do not want to use Unicode strings in your programs and sources, the Unicode-enabled editors have the advantage that you can write sources in all code pages, no matter which system code page is installed. For example, if you have installed the "windows-1252" (Latin 1) code page, you can write a program containing Cyrillic characters and save this program with the "windows-1251" (Cyrillic) code page. You only have to select code page "windows-1251" in the **Save As** dialog box (see *Saving an Object with a New Name* in the *Using Natural Studio* documentation).

Using the Natural for Windows program editor, you can convert text constants into their hexadecimal Unicode representations (see *Converting to Hexadecimal Format* in the *Program Editor* section of the *Natural for Windows Editors* documentation). If you are developing for a platform where UTF-8 sources are not preferred, you can thus enter all characters for a Unicode constant, select all the characters of the constant, convert them to their hexadecimal representation and then add the "UH" prefix for Unicode hexadecimal constants. Furthermore, when you hover the mouse pointer over a character or a selected character range of a text constant, a tool tip shows the corresponding hexadecimal Unicode representation.

A byte order mark (BOM) consists of the character code "U+FEFF" at the beginning of a data stream where it can be used as a signature defining the byte order and encoding form, primarily of unmarked plain-text files. On Windows, a byte order mark is used by some editors (for example, Notepad) to mark UTF-8 files. The Natural for Windows editors will recognize an UTF-8 byte order mark when reading an object. If the object has no other encoding defined so far, Natural will interpret it as UTF-8 and when the object is saved, UTF-8 will be stored as the encoding for the object. The byte order mark is removed in this case.

Code Page Support for Editors, System Commands and Utilities on the Mainframe

The following topics are covered below:

- Editors
- System Commands and Utilities

Editors

The program, map and data area editors provided with Natural for Mainframes are not Unicode-enabled. Instead the sources are stored with code page information. According to the setting of the profile parameter `SRETAIN`, Natural sources with code page information may be converted automatically from the current code page of the source into the default code page of the current Natural session (value of the system variable `*CODEPAGE`) if the source is loaded into the editor. If there are any characters that cannot be converted, a window displays a code point conversion error and asks for substitute values for those code points that cannot be converted. The display of this message is independent from the current setting of the parameter `CPCVERR`. In this case, the user can decide to open the editor with or without converting the source into the default code page. Saving or stowing a converted source will save the new code page information. Sources without code page information (for example, sources that have been saved or stowed with previous Natural versions) are loaded into the editors without any conversion. According to the setting of the profile parameter `SRETAIN`, the current code page information of the source will be retained.

Inserting sources with the `.I` command or the split screen function will also convert sources, if necessary, according to the setting of the profile parameter `SRETAIN`. If characters cannot be converted, the defined substitution character will be inserted instead.

The check and conversion of the source is performed when the editor is started, not when the program is loaded into the source area. If a program is executed via `RUN program-name`, a conversion is not performed. This causes different behavior, depending on whether `RUN program-name` is entered on the `NEXT` screen or on an editor screen. If `RUN program-name` is entered on the `NEXT` screen, no conversion follows; if it is entered on an editor screen, the editor is started right after the execution of the program and a conversion is performed.

See the table below for the code page that is assigned to an existing Natural source that is saved or stowed, depending on the values of the profile parameters `SRETAIN` and `CP`.

Original Source Code Page Information	Setting of SRETAIN	Source Code Page Information after SAVE or STOW if CP is Set to a Value other than OFF	Source Code Page Information after SAVE or STOW if CP is set to OFF
Source without code page information	SRETAIN=ON SRETAIN=(ON, EXCEPTNEW)	No code page information	No code page information
Source without code page information	SRETAIN=OFF	Code page resulting from evaluation of CP	No code page information
Source is encoded in <i>code page 1</i>	SRETAIN=ON SRETAIN=(ON, EXCEPTNEW)	Original code page (<i>code page 1</i>)	Original code page (<i>code page 1</i>)
Source is encoded in <i>code page 1</i>	SRETAIN=OFF	Code page resulting from evaluation of CP	Original code page (<i>code page 1</i>)

The table below shows the code page that is assigned to a new Natural source that is saved or stowed, depending on the values of the profile parameters SRETAIN and CP.

Setting of SRETAIN	Source Code Page Information after SAVE or STOW if CP is Set to a Value other than OFF	Source Code Page Information after SAVE or STOW if CP is set to OFF
SRETAIN=ON	Code page resulting from evaluation of CP	No code page information
SRETAIN=OFF	Code page resulting from evaluation of CP	No code page information
SRETAIN=(ON, EXCEPTNEW)	No code page information	No code page information

System Commands and Utilities

LIST

By default, the system command LIST displays sources as they are stored in the system file without any conversions.

The CONVERTED option of the LIST command converts the source into the default code page (value of the system variable *CODEPAGE) if the code page information of the source is provided. All non-convertible characters are then replaced by the defined substitution character.

LIST DIR

The system command LIST DIR shows the used code page information of a Natural source in the directory window.

SCAN

Similar to the editors, the system command `SCAN` converts the sources before executing the actual `SCAN` command.

Object Handler (SYSOBJH)

The Object Handler unloads and loads sources with different code page information and preserves the original code page information.

The transfer format option `UTF-8` converts sources from any code page to `UTF-8` format while unloading, and stores information about the original code page in the work file. The corresponding load function converts the source back to the original code page or to another code page, if specified. This option can also be used to provide code page information for sources which have been saved or stowed with previous Natural versions and which therefore do not contain any code page information.

Unload and load sources in internal format will keep the code page information, if available.

SYSCP Utility - Code Page Administration

The `SYSCP` utility can be used to obtain information on code pages and to check or change the code page assignment of a source.