

Adabas Cluster Services

Entire Net-Work Diagnostic Utilities

Version 7.4.2

September 2009

This document applies to Adabas Cluster Services Version 7.4.2 and to all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © Software AG 2009. All rights reserved.

The name Software AG, webMethods and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. Other company and product names mentioned herein may be trademarks of their respective owners.




Table of Contents

1 Entire Net-Work Diagnostic Utilities	1
2 NETPFIL1 Utility	3
NETPFIL1 Parameters	4
3 NETPFIL2 Utility	7
NETPFIL2 Parameters	8
4 Example JCL	11
Index	13

1 Entire Net-Work Diagnostic Utilities

This documentation describes the Entire Net-Work diagnostic utilities provided in the Entire Net-Work load library. The Adabas modules required by the utilities are provided in the WALvrs library. See the *Report of Tape Creation* and the *Release Notes*.

The Entire Net-Work Diagnostic Utilities documentation is organized in the following topics:

	NETPFIL1 Utility
	NETPFIL2 Utility
	Example JCL

2 NETPFIL1 Utility

- NETPFIL1 Parameters 4

The NETPFIL1 utility is used to select the information to be printed from the Entire Net-Work NETPRNT file. The Entire Net-Work NETPRNT file contains tracing, logging, and dump output. The NETPRNT file should be used as input to the NETPFIL1 utility for the NETFILE file.

NETPFIL1 can be used to select

- only those records that fall within a certain date and time frame;
- only logging and dump records that match the title or any desired portion of the title;
- only trace records that match the title or any desired portion of the title; or
- any combination of the above.

The output from NETPFIL1 can be used as input to the [NETPFIL2 Utility](#) to perform additional filtering.

NETPFIL1 Parameters

This section describes the parameters for the NETPFIL1 utility.

```
DATE= yyyyymmdd
```

Only records created on the specified date are written to DDPRINT. The default value is all dates.

```
STARTTIME= hhmmssst
```

Records created before the specified time are not written to DDPRINT and are not checked for other selection criteria. The default is no restriction on the start time.

```
ENDTIME= hhmmssst
```

Records created after the specified time are not written to DDPRINT and are not checked for other selection criteria. The default is no restriction on the end time.

```
LOG= log-title
```

Log and dump records with a title that matches the specified log title are written to DDPRINT.

The log title must be specified exactly as it appears in the NETPRNT file; the value specified can be limited to the number of characters necessary to select the desired records. All characters following the last nonblank character are considered wild cards. Spaces are valid in the log title, but the check is performed only up to the last nonblank character.

LOG= selects all log and dump records. The default value is that no log or dump records are written.

```
TRACE= trace-title
```


Trace records that have a title matching the specified trace title are written to DDPRINT.

The trace title must be specified exactly as it appears in the NETPRNT file; the value specified can be limited to the number of characters necessary to select the desired records. All characters following the last nonblank character are considered wild cards. Spaces are valid in the trace title, but the check is performed only up to the last nonblank character.

TRACE= selects all trace records. The default value is that no trace records are written.

Anything else is written to the output file as a comment along with the parameters specified to the beginning of the DDPRINT file.

An asterisk (*) in column 1 causes this parameter record to be ignored.

Examples

1. The following selects all records for a five minute period with a comment:

```
ALL INFORMATION FROM 2:23 to 2:29
STARTTIME=14230000
ENDTIME=14290000
LOG=
TRACE=
```

2. The following selects log records for IDDDATA and IDDBLK using implied wild cards:

```
LOG=IDD
```

3. The following selects log records for IDDDATA only:

```
LOG=IDDDATA
```

4. The following selects dump records for M Y B L K, D R I V B L K, and L I N K B L K:

```
LOG=M Y B L K
LOG=D R I V B L K
LOG=L I N K B L K
```

3 NETPFIL2 Utility

- NETPFIL2 Parameters 8

The NETPFIL2 utility is used to search for a control block or storage area snapped by either the logging function or a dump. When the desired dump entries are found, they are printed.

Optionally, NETPFIL2 can also print all non log entries, including the trace and time stamp records. NETPFIL2 is therefore suitable as a second step in a job where NETPFIL1 is run first.

To summarize, NETPFIL2 can be used to

- find and print a control block or data area that contains a specified value at a specified offset;
- optionally print all non logging and dump records; and
- find multiple control blocks and multiple values.

The Entire Net-Work NETPRNT file contains tracing, logging, and dump output. The NETPRNT file should be used as input to the NETPFIL2 utility for the NETFILE file.

NETPFIL2 Parameters

This section describes the parameters for the NETPFIL2 utility.

NONLOG = { Y | N }

The NONLOG parameter specifies whether all nonlog and dump records should be written to DDPRINT:

NONLOG=Y	Writes all nonlog and dump records.
NONLOG=N	Ignores all nonlog and dump records. This is the default value.

FIND = *log-title* (OFFSET=*xxx* VALUE= *characters* | *X'hex-values'*)

Log and dump records that have a log title matching the specified log title are evaluated to determine whether the hexadecimal offset matches either the character or hexadecimal value specified. If it matches, the whole dumped area is written to DDPRINT.

The log title must be specified exactly as it appears in the NETPRNT file; the value specified can be limited to the number of characters necessary to select the desired records. All characters following the last non blank character are considered wild cards. Spaces are valid in the log title, but

the evaluation is performed only up to the last non blank character. To select all log and dump records, use the LOG= parameter (see section *NETPFIL1 Parameters*).

OFFSET=xxx must be specified as a valid hexadecimal number. This number specifies the first byte of the location in the dumped area to compare. The comparison is performed in such a way that the value must start at this location. Each additional character of the value is checked at the next logical position in the dump, even if the next logical position is on the next record.

VALUE=characters specifies the right hand portion of the value, which is in character format. The character form of the value is compared to the interpreted part of the dumped records.

VALUE=X'hex values' specifies the left hand portion of the value, following the address and offset. The hexadecimal form of the value is compared to the hexadecimal part of the dumped records.

The following example finds the driver block (D R I V B L K) for the XCF (NETXCF) driver.

```
FIND=D R I V B L K,OFFSET=10,VALUE=NETXCF  
FIND=D R I V B L K,OFFSET=10,VALUE=X'D5C5E3E3C3D7C9'
```


4 Example JCL

The following example JCL can be used to run NETPFIL1 or NETPFIL2 in an OS/390 or z/OS environment.

```
//YOURJOB JOB (0),'NET-WORK',
//          CLASS=A,MSGCLASS=X,MSGLEVEL=(1,1)
//FILTER1 EXEC PGM=NETPFIL1                <--- see Note 1
//STEPLIB DD DSN=NETWRK.vrs.LOAD,DISP=SHR   <--- see Note 2
//          DD DSN=ADABAS.vrs.LOAD,DISP=SHR <--- see Note 3
//NETFILE DD DSN=NETWRK.vrs.NETPRNT,DISP=SHR <--- see Note 4
//DDCARD DD *                               <--- see Note 5
        THIS COMMENT WILL BE PRINTED AT THE BEGINNING OF THE OUTPUT
        DATE=20000316
        STARTTIME=12570000
        ENDTIME=12580000
        LOG=T R A C E
* LOG=IDDDATA
        TRACE=
* TRACE=SENDOUT
//DDPRINT DD SYSOUT=*,DCB=(LRECL=121,BLKSIZE=1210,RECFM=FBA)
/*
```



Notes:

1. Specify the utility program you want to run.
2. This is the same load library you use to run Entire Net-Work.
3. This is the same Adabas or WAL load library you use to run Entire Net-Work.
4. This is the file that was created by Entire Net-Work with DDNAME NETPRNT.
5. This is the parameter file and may be any sequential file with LRECL=80.

Index

E

Entire Net-Work
 diagnostic utilities, 1

