z/OS Installation z/OS Installation

# z/OS Installation

- The Installation Tape
- Installation Checklist
- System Programming Considerations
- Installation Procedure

# **The Installation Tape**

The installation tape contains the data sets listed in the table below. The sequence of the data sets is shown in the *Report of Tape Creation* that accompanies the installation tape.

Data Set	Contents
AFPvrs.LOAD	AFP load modules
AFPvrs.INPL	SYSAFP objects
AFPvrs.ERRN	SYSAFP error messages

where vrs in data set names represents the version, revision, and system maintenance level of the product.

# **Installation Checklist**

The Adabas System Coordinator must be installed prior to the installation of Adabas Fastpath. See the *Adabas System Coordinator* documentation for detailed information.

Once the required System Coordinator components have been installed, you can proceed to install Adabas Fastpath. The following checklist identifies the steps necessary to complete the installation:

Step	Description
1	Restore the Adabas Fastpath libraries from the installation tape
2	Prepare SYSAFP
3	Enable the client process
4	Enable the Adabas server process
5	Prepare the asynchronous buffer manager
6	Verify the installation

# **System Programming Considerations**

Buffer storage is acquired from extended CSA (ECSA subpool 241). The operating system parameter CSA in the IEASYSxx member of SYS1.PARMLIB defines the size available. It may need to be increased if a large buffer is required.

z/OS Installation Installation Procedure

## **Installation Procedure**

Following is the general Adabas Fastpath installation procedure. The actual installation depends on your particular requirements and the specific contents of the release package provided by Software AG for your site. Information in the release package is intended for your system. If that information differs from the information in this section, use the release package information or contact your Software AG technical support representative for assistance.

- Step1: Copying the Tape Contents to Disk
- Step 2. Prepare SYSAFP
- Step 3. Enable the client process
- Step 4. Enable the database process
- Step 5. Prepare the asynchronous buffer manager
- Step 6. Verify the installation

## **Step1: Copying the Tape Contents to Disk**

If you are using System Maintenance Aid (SMA), refer to the SMA documentation (included on the current edition of the Natural documentation CD). If you are not using SMA, perform steps 1a, 1b and 1c as described in this section:

- Step 1a: Copy Data Set COPY.JOB from Tape to Disk
- Step 1b: Modify COPY.JOB
- Step 1c: Submit COPY.JOB

#### Note:

If the data sets for more than one product are delivered on the tape, the data set COPY.JOB contains the JCL to unload the data sets for all delivered products from the tape to your disk. After that, you will have to perform the individual install procedure for each component.

#### Step 1a: Copy Data Set COPY.JOB from Tape to Disk

The data set COPY.JOB (label 2) contains the JCL to unload all other existing data sets from tape to disk. To unload COPY.JOB, use the following sample JCL:

```
// DCB=*.SYSUT1
//SYSPRINT DD SYSOUT=*
//SYSIN DD DUMMY
//
where:
<hilev> is a valid high level qualifier
<Tnnnnn> is the tape number
<vvvvvvv> is the desired volser
```

#### **Step 1b: Modify COPY.JOB**

Modify COPY.JOB to conform with your local naming conventions and set the disk space parameters before submitting this job:

- set HILEV to a valid high level qualifier
- set LOCATION to a storage location
- set EXPDT to a valid expiration date

#### **Step 1c: Submit COPY.JOB**

Submit COPY.JOB to unload all other data sets from the tape to your disk.

## **Step 2. Prepare SYSAFP**

The Adabas Fastpath Online Services (SYSAFP) objects are delivered on the Adabas Fastpath installation tape.

# To prepare SYSAFP:

1. Use your everyday Natural INPL job to load the administration tool (Natural application SYSAFP) and associated message texts into your Natural system. For reference a sample Natural INPL job called CORI061 can be found with the sibling System Coordinator product in the *jobs* distribution file. The INPL job's work file 1 must reference the distribution file AFP*vrs*.INPL and work file 2 must reference AFP*vrs*.ERRN.

#### Note:

If you use Natural Security in this system, define the libraries SYSAFP and SYSMW*vrs* (where *vrs* is the level you are installing, for example 821) and protect as you require. You may define MENU as the startup transaction for SYSAFP. However, you **must not** define a startup transaction for SYSMW*vrs*.

2. Use the following parameter to define the Natural session where SYSAFP is to be used:

```
\texttt{LFILE=(152,} dbid, fnr<, passw><, ciph>)
```

where *dbid* and *fnr* define the location of the Adabas System Coordinator configuration file.

Alternatively, assemble the Natural parameter module with

NTFILE, ID=152, DBID=dbid, FNR=fnr

## Step 3. Enable the client process

To enable the Adabas Fastpath client process

- 1. for the Adabas System Coordinator:
  - make the modified Adabas link module available (COMPLIB for Com-plete, DFHRPL for CICS, STEPLIB for all other client systems);
  - make the generated configuration module CORCFG available (COMPLIB for Com-plete, STEPLIB for all other client systems); and
  - make the Adabas System Coordinator load library available (COMPLIB for Com-plete, STEPLIB for all other client systems).
- 2. for Adabas Fastpath:
  - make the Adabas Fastpath load library available (COMPLIB for Com-plete, STEPLIB for all other client systems).

## **Step 4. Enable the database process**

To enable the Adabas Fastpath database process

- 1. for the Adabas System Coordinator:
  - make the Adabas System Coordinator load library available.
- 2. for Adabas Fastpath:
  - set the Adabas parameter ADARUN FASTPATH=YES; and
  - make the Adabas Fastpath load library available.

#### Note:

An unmodified ADALNK must be available to the database in preference to the ADALNK created during the installation of the Adabas System Coordinator.

## Step 5. Prepare the asynchronous buffer manager

The asynchronous buffer manager (ABM) runs as an optional service within the Adabas System Coordinator daemon.

To enable the ABM for the Adabas System Coordinator daemon:

- make the generated primary and alternate (if used) configuration module CORCFG available;
- set the daemon service startup parameter PRODUCT=AFP; and
- make the Adabas Fastpath load library available.

For more information, refer to the Adabas System Coordinator documentation.

## Step 6. Verify the installation

Use the procedure described in section Verifying the Installation to ensure that the installation has been successful.