

# CORD\* - Adabas System Coordinator Daemon Messages

CORDnn messages are issued by the Adabas System Coordinator daemon.

## Overview of Messages

CORD01S	CORD02S	CORD03E	CORD04I	CORD05E	CORD06E	CORD07E
CORD08E	CORD10E	CORD11I	CORD12I	CORD13E	CORD14I	CORD15I
CORD16S	CORD21I	CORD22E	CORD30E	CORD31E	CORD34E	CORD35S
CORD37S	CORD38S	CORD39I	CORD40S	CORD45E	CORD46I	CORD47S
CORD49W	CORD50E	CORD52I	CORD53I			

---

### CORD01S      COORDINATOR CANNOT INITIALIZE, GETMAIN ERROR

**Explanation**    The Adabas System Coordinator cannot initialize because of a memory shortage.

**Action**            Increase the region specification for the daemon job.

### CORD02S      COORDINATOR CANNOT INITIALIZE, KERNEL LOAD ERROR

**Explanation**    The daemon failed to locate or load the runtime kernel module CORKRN.

**Action**            Ensure that the load library containing the kernel module is available to the job.

### CORD03E      DDCARD OPEN ERROR: ## - TERMINATING

**Explanation**    The DDCARD control file could not be opened.

**Action**            Ensure that the daemon job has a DDCARD file containing the required control cards.

### CORD04I      INPUT PARAMETER: #####

**Explanation**    The input parameters contained in the DDCARD file are echoed in the job message output file.

**Action**            None. This message is for information only.

### CORD05E      INVALID PARAMETER: #####

**Explanation**    An invalid input parameter was found in the DDCARD file. The daemon terminates.

**Action**            Correct or delete the invalid parameter.

**CORD06E     PRODUCT PARAMETER NOT SPECIFIED**

**Explanation**    There was no PRODUCTparameter in the DDCARD file. The daemon does not know which product(s) to load.

**Action**            Add the required PRODUCT parameter and restart the daemon.

**CORD07E     MPM FAILURE - FUNCTION: ## ERROR ##**

**Explanation**    An error occurred when trying to:

- sign on to the Adabas SVC (Function=24 - x'18')
- sign off from the Adabas SVC (Function=20 - x'14')
- Post command completion to caller (Function=12 - x'0C')
- get the command queue element (CQE) (Function=8 - x'08')

**Action**            For a sign on error, ensure that the correct SVC and Node ID have been specified in the Adabas System Coordinator group member.

A sign-off error indicates an internal problem with the System Coordinator Daemon. Contact your Software AG technical support representative for assistance.

A Get CQE error or a Post error indicates a problem with the daemon caller. This will be accompanied by an Adabas "User Gone" message (ADAM91 or ADAM92), identifying the calling Job and session Id. Examine the calling job to determine the reason for the failure. Probably the job has abnormally terminated. No action is required in the Coordinator Daemon.

**CORD08E     IOR FAILURE - FUNCTION: ## ERROR ##**

**Explanation**    An error occurred during an ADAIOR service call.

**Action**            Contact your Software AG technical support representative for assistance.

**CORD10E     GETMAIN FOR COMMAND QUEUE FAILED**

**Explanation**    The daemon cannot acquire memory for the command queue.

**Action**            Increase the region specification for the Adabas System Coordinator daemon task.

**CORD11I**      **CORD11I SYSCO IS ACTIVE ON NODE ##### ###**

**Explanation**    The daemon successfully signed on to the Adabas SVC and is ready for communication. The message indicates the node and SVC number used.

**Action**            None. This message is for information only.

**CORD12I**      **OPER TYPEIN: #####**

**Explanation**    The operator entered a console command to the daemon. The command is echoed back to the message output file.

**Action**            None. This message is for information only.

**CORD13E**                      **INVALID OPERATOR COMMAND**

**Explanation**                      The command entered is not valid.

**Action**                              Correct the command and enter it again.

**CORD14I**      **TARGET ##### TERMINATION IN PROGRESS**

**Explanation**    The daemon is terminating because of operator request or unrecoverable error.

**Action**            None. This message is for information only.

**CORD15I**      **TARGET ##### ENDED NORMALLY**

**Explanation**    The daemon terminated normally as a result of an operator request.

**Action**            None. This message is for information only.

**CORD16S**      **TARGET ##### ENDED ABNORMALLY**

**Explanation**    The daemon terminated abnormally as a result of a previous error.

**Action**            A previous message will identify the cause of the abnormal termination. Examine the message and take appropriate recovery action.

**CORD21I**                      **OPERATOR COMMAND PROCESSED SUCCESSFULLY**

**Explanation**                      An operator command completed successfully.

**Action**                              None. This message is for information only.

**CORD22E      LOAD FOR MODULE: ##### FAILED**

**Explanation**    The requested module could not be located or loaded.

**Action**            Ensure that the requested module is available to the Adabas System Coordinator daemon task.

**CORD30E            GETMAIN FOR PRODUCT PARM BLOCK FAILED**

**Explanation**        A memory allocation failed during the initialization.

**Action**            Increase the region specification for the job.

**CORD31E            CAB ALLOCATION ERROR**

**Explanation**        A memory allocation failed during the initialization of the daemon.

**Action**            Increase the region specification for the job.

**CORD34E            ASA ALLOCATION ERROR**

**Explanation**        A memory allocation failed during the initialization of the daemon.

**Action**            Increase the region specification for the job.

**CORD35S      CONFIGURATION MODULE CORCFG CANNOT BE LOCATED**

**Explanation**    The configuration module CORCFG cannot be loaded. This module contains the SVC, DBID, and file number for reading the configuration file. The daemon will not function correctly without this module.

**Action**            Refer to the Adabas System Coordinator Installation documentation for information about assembling a configuration module.

**CORD37S      SYSCO DAEMON member-name NOT FOUND IN CONFIGURATION FILE,  
RESPONSE=nnnn, SUBCODE=nnnn**

**Explanation**    The named Adabas System Coordinator group member was not found in the group in the configuration file. Every daemon must have an equivalent group member parameter.

**Action**            Add the member entry for this daemon to the appropriate Adabas System Coordinator group.

**CORD38S**     **GROUP group-name NOT FOUND IN CONFIGURATION FILE,  
RESPONSE=nnnn, SUBCODE=nnnn**

**Explanation**     The named group cannot be located.

**Action**     An error occurred while searching for the Adabas System Coordinator group parameters. Define the Adabas System Coordinator group. If the problem persists, contact your Software AG technical support representative.

**CORD39I**     **SHUTDOWN PENDING**

**Explanation**     A shutdown request was entered. One or more of the subcomponents of the Adabas System Coordinator daemon suspended the request until it completes its own shutdown processing. The daemon should terminate when this is completed.

**Action**     None. This message is for information only.

**CORD40S**     **ABEND ##### PSW #####**

**Explanation**     An error occurred in the Adabas System Coordinator daemon. The registers, PSW, and failing module at the time of the error are displayed. The Adabas System Coordinator writes additional diagnostic information to the CORDUMP file, deletes any common memory pools in use, and terminates.

**Action**     Contact your Software AG technical support representative.

**CORD45E**     **THREAD ##### TIMEOUT, TARGET=#####, USER=#####**

**Explanation**     The Adabas System Coordinator daemon sent an Adabas command to the indicated target, and has not received a response within the timeout interval as specified by DDCARD parameter CT.

**Action**     Check that the target database is operating correctly. If the problem persists, try increasing the CT timeout value. If there is still a problem, contact your Software AG technical support representative.

**CORD46I**     **##### Start pending, configuration file (dbid ##### fnr #####) not active**

**Explanation**     An Adabas System Coordinator daemon has been started, but the required configuration file is not active. The daemon will wait for 60 seconds and try again. If the configuration file is still not active after 60 minutes the daemon will terminate.

**Action**     Start the database that contains the configuration file.

**CORD47S    Halt-Load library is not Authorized**

**Explanation**    z/OS only. An Adabas System Coordinator daemon has been started from a load library that is not APF-authorized.

**Action**            Ensure the specified load library is authorized and restart the daemon.

**CORD49W    (jobname) shutdown rejected, configuration file (dbid ddddd fnr fffff) not active**

**Explanation**    A daemon shutdown request was made, but either the primary or the alternate configuration file is not active.

This message appears only when Alternate Configuration File support is specified.

**Action**            Make the required Configuration File available and re-issue the shutdown request.

**CORD50E    Shutdown rejected**

**Explanation**    A daemon shutdown request was made, but there are active client DTR jobs connected to the daemon.

This message will be preceded by message CAS004I, identifying the names of the active DTR job(s).

**Action**            Terminate the active client jobs and re-issue the shutdown request.

**CORD52I    Configuration file: ##### / #####**

**Explanation**    This message shows the database ID and file number of the configuration file in use by this System Coordinator daemon.

**Action**            None. This message is for information only.

**CORD53I    Alternate file : ##### / #####**

**Explanation**    This message shows the database ID and file number of the alternate configuration file in use by this System Coordinator daemon. The message only appears if an alternate configuration file has been specified.

**Action**            None. This message is for information only.