

ARIS USER MANAGEMENT COMMAND-LINE TOOL

VERSION 10.0 - SERVICE RELEASE 18 MAY 2022

This document applies to ARIS Version 10.0 and to all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 2010 - 2022 Software AG, Darmstadt, Germany and/or Software AG USA Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at https://softwareag.com/licenses.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at https://softwareag.com/licenses and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at https://softwareag.com/licenses and/or in the root installation directory of the licensed product(s).

Contents

Co	ntents	5	
1	Com	mand line tools for the ARIS Administration	1
	1.1	Password encryption	2
	1.2	Tenant Management	
	1.3	Parameters for y-tenantmgmt.bat/y-tenantmgmt.sh	
	1.4	List of technical names of audit events	20
	1.5	LDAP synchronization	23
	1.6	Data migration	27
2	Lega	ıl information	29
	2.1	Documentation scope	29
	2.2	Support	

1 Command line tools for the ARIS Administration

ARIS provides a set of command-line tools that can be used to perform administrative operations.

There are always at least two tenants, the tenant **default** and the tenant **master**. Most command-line operations require user authentication. The provided user must have sufficient permissions to perform the requested operation, for example, a tenant create, read, update or delete can only be performed by administrators of tenant **master**.

- ARIS must be running.
- The command-line tools must be executed in the following path:

ARIS installation path>/server/bin/work/word_umcadmin_< your installation size, for example, s,m, or I>/tools/bin for Windows® operating systems and

ARIS installation path>/cloudagent/bin/work/word_umcadmin_< your installation size, for example, s,m, or l>/tools/bin for Linux operating systems.

The following command line tools are provided:

- y-datadump.bat
- y-elasticsearch.bat
- y-ldapsync.bat
- y-password.bat
- y-tenantmgmt.bat

For more information about parameters and commands please type the tool name followed by /? or -?, for example y-datadump.bat -?.

For Unix operating systems, command-line tools (sh files) can only be started by the **aris10** user, for example, enter: **su -c y-datadump.sh aris10**.

The following command line tools are provided:

- y-datadump.sh
- y-elasticsearch.sh
- y-ldapsync.sh
- y-password.sh
- y-tenantmgmt.sh

1.1 Password encryption

There are many places where you might want to use and store a password. The **y-password.bat** can be used to encrypt these passwords. Enter the tool name followed by **/?** or **-?** to see the usage instructions, for example **y-password.bat -?**.

Procedure

Open a command prompt on the above folder (Start > Run > cmd).

- 1. Enter y-password.bat <option> <password>
- 2. Mark and copy the encrypted password and paste it to your configuration file or use it directly from command line.

The following is output:

[CLI] Setting verbosity level... [VALUE: 0=0FF]

[CLI] Plain: <password>

[CLI] Encrypted: f4a28327ad2f0c87336dd74fe0a70c39

Options	Description
-?, -h,help	Show help
	Default: false

Commands	Description
encrypt	encrypts the password

Example

Input

y-password.bat encrypt aris

Output

[CLI] Setting verbosity level... [VALUE: 0=0FF]

[CLI] Plain: aris

[CLI] Encrypted: f4a28327ad2f0c87336dd74fe0a70c39

Usage of an encrypted password from command line

This example shows how to use the encrypted password while executing the LDAP synchronization from the command line.

Input

y-Idapsync.bat syncUser -au <user_name> -u system -p {crypted}f4a28327ad2f0c87336dd74fe0a70c39

Output

Connected to User Management at end point 'http://servername:1080/umc' for tenant 'default'. Synchronizing user 'system' with LDAP... Synchronization of user with LDAP is complete.

1.2 Tenant Management

The batch file **y-tenantmgmt.bat** can be used to manage tenants. Enter the tool name followed by **/?** or **-?** to see the usage instructions, for example **y-tenantmgmt.bat -?**.

Please use **y-tenantmgmt.bat** for Windows® operating systems and **y-tenantmgmt.sh** for Unix operating systems.

Warning

To avoid data inconsistencies and possible data loss, you must not perform any of the following activities in parallel, neither manually nor scheduled:

- Deleting any Process Governance process instance, process version, or process
- Archiving Process Governance process instances
- Backup/restore tenant (containing Process Governance or ARIS document storage data)

Using some advanced ACC commands, you can create a tenant, import a license and restore a database in one step. If you do not use the standard database system, please make sure to create additional schemes in your Oracle or Microsoft SQL database management system and you have assigned the tenants to these schemes.

You must redirect the ports in case of a Linux operating system.

Prerequisites

- ARIS Server installation
- Users need the function privileges License administrator, User administrator,
 Technical configuration administrator.

Users need to login as **superuser** or they need either an **ARIS Architect** license or an **ARIS UML Designer** license.

Procedure

- Open a command prompt (Start > Run > cmd).
- Enter y-tenantmgmt.bat followed by /? or -? to display the help, for example y-tenantmgmt.bat -?.

Enter y-tenantmgmt.bat -t <tenant name> <command> -u <user name> -p <password> to enter a command (page 5). Parameters may differ.

After creating a tenant, you must import the relevant license and create the users. You can do so from the command line or using the graphical user interface ARIS Administration.

You are recommended to change the password of the default user **system** immediately after the installation.

1.3 Parameters for y-tenantmgmt.bat/y-tenantmgmt.sh

Options	Description
-?, -h,help	Show help, default: false
-s,server	URL of the server, for example, http://my_host_url: <port 1080="" 80="" default="" number="" or="" other="" port="" than=""></port>

Commands	Description	Parameters
anonymize	Anonymizes the audit log files. This is compliant to GDPR. The General Data Protection Regulation (GDPR) protects individuals' personal data within the European Union. It also regulates the export of personal data outside the EU. GDPR is a regulation by the European Parliament, the Council of the European Union, and the European Commission.	Please note that you must wait at least 30 minutes after the deletion of the user from User Management before you can start the anonymization process. Usage: anonymize [options] Options: * -n,name Name of the user or user group -p,password Password of executor, default: superuser * -type,type UUID type is user or user group -u,user User name of the executor, default: superuser

Commands	Description	Parameters
assignLicense	Assigns a license to	Usage: assignLicense [options]
	user.	Options:
		-ag,affectedGroup
		Name of affected user group, default: []
		-au,affectedUser
		User name of affected user, default: []
		* -I,license
		Product code, default: []
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser
assignPrivilege	Assigns privileges	Usage: assignPrivilege [options]
		Options:
		-ag,affectedGroup
		Name of affected user group, default: []
assignPrivilege Assigns privileges Assigns privileges User name of affected user group, default: [] -p,password Password of the executor, default: [] -u,user User name of the executor, default: [] -p,password Password of the executor, default: [] -u,user User name of the executor, default: [] Options: -ag,affectedGroup Name of affected user group, default: [] -u,password Password of the executor, default: [] -u,user	-au,affectedUser	
		User name of affected user, default: []
		-p,password
		Options: -ag,affectedGroup Name of affected user group, default: [] -au,affectedUser User name of affected user, default: [] * -l,license Product code, default: [] -p,password Password of the executor, default: superuser -u,user User name of the executor, default: superuser signs privileges Usage: assignPrivilege [options] Options: -ag,affectedGroup Name of affected user group, default: [] -au,affectedUser User name of affected user, default: [] -p,password Password of the executor, default: superuser * -pr,privilege Privilege, default: []
		* -pr,privilege
		Privilege, default: []
		-u,user
		User name of the executor, default: superuser

Commands	Description	Parameters
assignUser	Associates a user to a	Usage: assignUser [options]
	user group.	Options:
		* -ag,affectedGroup
		Name of affected user group
		* -au,affectedUser
		User name of affected user
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser
changePasswor	Changes a password.	Usage: changePassword [options]
d		Options:
		* -ap,affectedPassword
		Password of affected user
		* -au,affectedUser
		User name of affected user
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser
checkLicense	Checks tenant license.	Usage: checkLicense [options]
		Options:
		* -I,license
		Product code, default: []
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser

Commands	Description	Parameters
createGroup	Creates a user group.	Usage: createGroup [options]
		Options:
		-ad,affectedDescription
		Description of affected user group
		* -ag,affectedGroup
		Name of affected user group
		-p,password
		Password of the executor, default: superuser
-u,user	-u,user	
		User name of the executor, default: superuser
createMiningSe	Creates ARIS Process	Usage: createMiningServer [options]
rver	Mining server	Options:
	application	-aid,applicationClientId
		Client ID of the affected application
	-asec,applicationClientSecret	-asec,applicationClientSecret
		Client secret of the affected application
		-as,applicationScopes
		API scopes of the affected application
		-p,password
		Password of editor
	Default: superuser	Default: superuser
		-u,user
		User name of editor
		Default: superuser

Commands	Description	Parameters
createTenant	Creates a new tenant.	Usage: createTenant [options]
		Options:
		-u,user
		User name of the executor, default: superuser
		-p,password
		Password of the executor, default: superuser
		-t,tenant <tenantname> (mandatory)</tenantname>
		For tenant names please only use up to 25
		lowercase ASCII characters and numbers. The
		name must begin with a character. Special
		characters, such as _ and characters, for example,
		in Chinese, Cyrillic or Arabic cannot be used.
		arisservicePassword (-arisservicep)
		<password></password>
		superuserPassword (-superuserp) <password></password>
		systemPassword (-systemp) <password></password>

Commands	Description	Parameters
createUser	Creates a new user.	Usage: createUser [options]
		Options:
		-ad,affectedDescription
createUser		Description of affected user
		-ae,affectedEmail
		E-mail address of affected user
		-af,affectedFirstName
		First name of affected user
		-al,affectedLastName
		Last name of affected user
		-ap,affectedPassword
		Password of affected user
		* -au,affectedUser
		User name of affected user
		-p,password
		Password of the executor, default: superuser
deleteGroup		-u,user
		User name of the executor, default: superuser
deleteGroup	Deletes a user group.	Usage: deleteGroup [options]
		Options:
		* -ag,affectedGroup
		Name of affected user group
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser

Commands	Description	Parameters
deleteLicense	Deletes the licenses	Usage: deleteLicense [options]
	for a product.	Options:
		* -I,license
		Product code
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser
deleteTenant	Deletes an existing	Usage: deleteTenant [options]
	tenant.	Options:
* -au,affectedUser	* -au,affectedUser	
		Options: * -au,affectedUser User name of affected user -p,password
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser
deleteUser	Deletes an existing	Usage: deleteUser [options]
	user.	Options:
		user (-u) <username> (mandatory)</username>
		password (-p) <password> (mandatory)</password>
		tenant (-t) <tenantname> (mandatory)</tenantname>
		affectedUser (-au) <userlogin> (mandatory)</userlogin>

Commands	Description	Parameters
exportAuditLog	Exports audit events	Usage: exportAuditLog [options]
Export		Options:
		-ed,endDate
		End date in format yyyy-MM-dd HH:mm:ss
		-ev,eventTypes
		Comma-separated list of events (page 4)
		Default: ALL
		-f,file
		Name and location of the export file
		* -ff,fileFormat
		Format of the file to be exported as CSV or JSON. If
		the format is not specified, events will be exported
		in CSV format.
		Default: CSV
		-p,password
		Password of editor
		Default: superuser
		-sd,startDate
		Start date in format yyyy-MM-dd HH:mm:ss
		-u,user
		User name of editor
		Default: superuser
exportConfig	Exports configuration	Usage: exportConfig [options]
	of tenant.	Options:
		-f,file
		Configuration file, default: umc.properties
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser

Commands	Description	Parameters
getTenant	Prints information	Usage: getTenant [options]
	about a tenant.	Options:
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser
getUser	Prints information	Usage: getUser [options]
	about a user.	Options:
		* -au,affectedUser
		User name of affected user
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser
importConfig	Updates configuration	Usage: importConfig [options]
	of tenant.	Options:
		-f,file
		Configuration file, default: umc.properties
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser

Commands	Description	Parameters
importConfigFil	Updates the tenant	Usage: importConfigFile [options]
е	configuration file.	Options:
		-f,file
		Configuration file
		-o,option
		Configuration option
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser
importLicense	Imports license files	Usage: importLicense [options]
	for a tenant .	Options:
		-f,file
		Lincense file, default: license.zip
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser
listPrivileges	Lists the privileges of the user mentioned in the command	Usage: listPrivileges [options]
		Options:
		-au,affectedUser
		User name of affected user
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser

Commands	Description	Parameters
listTenants	Lists all existing	Usage: listTenants [options]
	tenants.	Options:
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser
purgeAuditLog	Deletes all audit logs of	Usage: purgeAuditLogByUser [options]
ByUser	a deleted user.	Options:
		* -ed,endDate
		End date in format (yyyy-MM-dd HH:mm:ss)
		-p,password
		Password of the executor, default: superuser
		-sd,startDate
		Start date in format (yyyy-MM-dd HH:mm:ss)
		u,user
		User name of the executor, default: superuser

Commands	Description	Parameters
saveApplication	Registers an external	Usage: saveApplication [options]
	application.	Options:
		-aid,applicationClientId
		Client ID of the affected application
		-asec,applicationClientSecret
		Client secret of the affected application
		-ad,applicationDescription
		Description of the affected application
		-an,applicationName
		Application name of the affected application
		-as,applicationScopes
		API scopes of the affected application
		-p,password
		Password of editor
		Default: superuser
		-u,user
		User name of editor
		Default: superuser
unassignLicens	Removes a license	Usage: unassignLicense [options]
е	from user.	Options:
		-ag,affectedGroup
		Name of affected user group
		-au,affectedUser
		User name of affected user
		* -I,license
		Product code
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser

Commands	Description	Parameters
unassignPrivile	Removes the privilege	Usage: unassignPrivilege [options]
ge	assignment.	Options:
		-ag,affectedGroup
		Name of affected user group
		-au,affectedUser
		User name of affected user
		-p,password
		Password of the executor, default: superuser
		* -pr,privilege
		Privilege
		-u,user
		User name of the executor, default: superuser
unassignUser	Removes a user from a	Usage: unassignUser [options]
	user group.	Options:
		* -ag,affectedGroup
		Name of affected user group
		* -au,affectedUser
		User name of affected user
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser

Commands	Description	Parameters
updateLicense	611 6	Usage: updateLicense [options]
		Options:
		-f,file
		Lincense file, default: license.zip
		* -I,license
		Product code, default: []
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser
updateUser	Updates an existing	Usage: updateUser [options]
	user.	Options:
		-ad,affectedDescription
		Description of affected user
		-ae,affectedEmail
		E-mail address of affected user
		-af,affectedFirstName
		First name of affected user
		-al,affectedLastName
		Last name of affected user
		* -au,affectedUser
		User name of affected user
		-p,password
		Password of the executor, default: superuser
		-u,user
		User name of the executor, default: superuser

Examples

The following line creates a tenant with name **test**. Please pay attention to the order of parameters.

```
y-tenantmgmt.bat -s http://my_aris_host.com -t test createTenant -u system
-p manager
```

The following line creates a new tenant with name **test01**, port used 81, and initial system user password **abc**. Please pay attention to the order of parameters.

```
y-tenantmgmt.bat -s http://my_aris_host.com:81 -t test01 createTenant -u system -p manager -systemp abc
```

The following line gets information of the default tenant.

```
y-tenantmgmt.bat -s http://my_aris_host.com -t default getTenant -u system -p manager
```

The following line updates the configuration of default tenant.

```
y-tenantmgmt.bat -s http://my_aris_host.com -t default importConfig -f sldapconfig.properties -u superuser -p superuser
```

The following line assigns a license configuration to the user my_user.

```
y-tenantmgmt.bat -s http://my_aris_host.com-t default -assignLicense au
my_user -l YCZUS -u system -p manager
```

1.4 List of technical names of audit events

- CONFIG_CHANGE
- CONFIG_FILE_IMPORT
- CONFIG_FILE_DELETION
- DATA_IMPORT
- GROUP_CREATION
- GROUP_UPDATE
- GROUP_DELETION
- GROUP_GROUP_ASSIGNMENT
- USER_GROUP_ASSIGNMENT
- ESCALATION_MANAGER_GROUP_ASSIGNMENT
- GROUP_GROUP_UNASSIGNMENT
- USER_GROUP_UNASSIGNMENT
- ESCALATION_MANAGER_GROUP_UNASSIGNMENT
- LDAP_IMPORT
- LDAP_SYNC
- LICENSE_IMPORT
- LICENSE_DELETION
- LICENSE_SEAT_ALLOCATION
- LICENSE_SEAT_DEALLOCATION
- LICENSE_USER_LIMIT_VIOLATION
- LICENSE_USER_GROUP_LIMIT_VIOLATION
- LOGIN_SUCCESSFUL
- LOGIN_FAILED
- LOGIN_RENEWAL
- LOGOUT
- LOGOUT_FORCED
- ORGCHART_UPDATE
- ORGCHART_DELETION
- OTP_GENERATION
- PASSWORD_CHANGE
- PASSWORD_RESET
- PASSWORD_TRANSFER

- PICTURE_IMPORT
- PICTURE_DELETION
- PRIVILEGE_ASSIGNMENT
- PRIVILEGE_UNASSIGNMENT
- TENANT_CREATION
- TENANT_UPDATE
- TENANT_DELETION
- USER_CREATION
- USER_UPDATE
- USER_DELETION
- USER_SETTING_ADDED
- USER_SETTING_REMOVED
- IMPERSONATION_SUCCESSFUL
- IMPERSONATION_FAILED
- AUDIT_PURGE
- LICENSE_RULE_CREATED
- LICENSE_RULE_UPDATED
- LICENSE_RULE_DELETED
- LICENSE_RULE_ACTIVATED
- LICENSE_RULE_DEACTIVATED
- APPLICATION_CREATION
- APPLICATION_UPDATE
- APPLICATION_DELETION
- APPLICATION_TOKEN_REFRESH
- APPLICATION_SESSION_CREATION
- APPLICATION_SESSION_DESTROY
- APPLICATION_CLIENT_CREDENTIALS_GENERATED
- API_SCOPE_CREATION
- API_SCOPE_UPDATE
- API_SCOPE_DELETION
- API_CREATION
- API_UPDATE
- API_DELETION

- AUTHORIZATION_CODE_CREATION
- AUTHORIZATION_CODE_DELETION
- CONFIRM_CONSENT_CREATION
- CONFIRM_CONSENT_DELETION
- EXTERNAL_ACCESS_TOKEN_CREATION
- EXTERNAL_ACCESS_TOKEN_DELETION
- REFRESH_TOKEN_CREATION
- REFRESH_TOKEN_DELETION
- SCIM_PROVISION_SUCCESSFUL
- SCIM_PROVISION_FAILED

1.5 LDAP synchronization

The batch file **y-Idapsync.bat** can be used to synchronize the ARIS Administration with LDAP. Enter the tool name followed by **/?** or **-?** to see the usage instructions, for example **y-Idapsync.bat -?**.

You must redirect the ports in case of a Linux operating system.

Procedure

- 1. Open a command prompt (Start > Run > cmd).
- 2. Enter y-idapsync.bat -s <a href="http://host_url:<port number other than default port 80">http://host_url:<port number other than default port 80</p>
 or 1080>> -t <tenant name> <command> -u <user name> -p <password>

Users are synchronized or imported from an LDAP system.

Options	Description
-?, -h,help	Show help
-u	User name of the relevant user.
-p	Password of the relevant user.
-f	LDAP search filter
-s,server	URL of the server, for example, http://my_host_url: <port 1080="" 80="" default="" number="" or="" other="" port="" than=""></port>
-t,tenant	Tenant name Default: default

Commands	Description
importUsers	Imports users from an LDAP system, the spelling is case sensitive. * -f,filter Search filter for LDAP as defined in RFC 2254, for example, '(cn=*)'. The filter will be combined with the configured import filters. -p,password Password of the executor Default: superuser -u,user User name of the executor Default: superuser
importGroups	Imports a hierarchy from an LDAP system, the spelling is case sensitive. * -f,filter Search filter for LDAP as defined in RFC 2254, for example, '(cn=*)'. The filter will be combined with the configured import filters. -p,password Password of the executor Default: superuser User name of the executor Default: superuser
removeUserAttr ibute	Deletes an attribute of a user in the ARIS Administration. -au,affectedUser User name of affected user -aa,-affectedAttribute Attribute of affected user
syncUser	Synchronizes a specific existing user with an LDAP system, the spelling is case sensitive.

Commands	Description
syncUsers	Synchronizes existing users with an LDAP system, the spelling is case sensitive. * -au,affectedUser User name of affected user -p,password Password of the executor Default: superuser -u,user User name of the executor Default: superuser
syncGroup	Synchronizes a specific existing group with an LDAP system, the spelling is case sensitive. * -ag,affectedGroup Name of the affected user group -p,password Password of the executor Default: superuser -u,user User name of the executor Default: superuser
syncGroups	Synchronizes existing groups with an LDAP system, the spelling is case sensitive. -p,password Password of the executor Default: superuser -u,user User name of the executor Default: superuser

Example 1

y-ldapsync.bat -s http://my_aris_host.com -t default importUsers -u system -p manager -f (cn=userID)

[CLI] Setting verbosity level... [VALUE: 0=0FF]

[CLI] Importing users... [TENANT: 30ff3081-aa9e-33e7-a7d7-5f9d00ae89ee, FILTER: (cn=userID)]

[CLI] Users successfully imported. [TENANT: 30ff3081-aa9e-33e7-a7d7-5f9d00ae89ee, COUNT: 1]

[CLI] CN=myuser,OU=Users,DC=mydomain

Example 2

Import all users from an LDAP system.

y-ldapsync.bat -s http://my_aris_host.com:81 -t default importUsers -u system -p manager -f (cn=*)

1.6 Data migration

Enter the tool name followed by /? or -? to display the instructions, for example y-datadump.bat -?. In case of a data import, the target database has to be empty.

You must redirect the ports in case of a Linux operating system.

Warning

Do not store backup files in ARIS document storage.

Procedure

- 1. Open a command prompt (**Start > Run > cmd**).
- 2. Enter y-datadump.bat -s <a href="http://host_url:<port number other than default port 80">http://host_url:<port number other than default port 80 or 1080>> -t <tenant name > -u <user name">command>-u <user name -p >password> -f <dump file>

In this case, a dump file written containing the database content. The following is output:

[CLI] Setting verbosity level... [VALUE: 0=0FF]

[CLI] Exporting data... [TENANT: 30ff3081-aa9e-33e7-a7d7-5f9d00ae89ee, FILE: C:\out.zip]

[CLI] Data successfully exported. [TENANT: 30ff3081-aa9e-33e7-a7d7-5f9d00ae89ee]

Options	Description
-?, -h,help	Show help
-f	File name of the dump file.
-s,server	URL of the server, URL of the server, for example, http://my_host_url: <port 80="" <b="" default="" number="" other="" port="" than="">or 1080></port>
-t,tenant	Tenant name Default: default

Commands	Description
export	Exports all data of the specified tenant to a data dump file. Currently, a dump contains the following information:
	tenant
	users
	groups
	 user-group assignments
	profile pictures (optional)
	 permissions, dependent on the privileges of the user who enters the command
	 licenses, dependent on the privileges of the user who enters the command
	 configuration, dependent on the privileges of the user who enters the command
	The data is stored in JSON format and packed into an encrypted ZIP file. The ZIP file can be restored using the same command line tool.
import	Imports a data base dump from a file.

Example

In this example, data is exported into a dump file.

y-datadump.bat -s -t default export -u system -p manager -f "C:\backup\backup.zip"

2 Legal information

2.1 Documentation scope

The information provided describes the settings and features as they were at the time of publishing. Since documentation and software are subject to different production cycles, the description of settings and features may differ from actual settings and features. Information about discrepancies is provided in the Release Notes that accompany the product. Please read the Release Notes and take the information into account when installing, setting up, and using the product.

If you want to install technical and/or business system functions without using the consulting services provided by Software AG, you require extensive knowledge of the system to be installed, its intended purpose, the target systems, and their various dependencies. Due to the number of platforms and interdependent hardware and software configurations, we can describe only specific installations. It is not possible to document all settings and dependencies.

When you combine various technologies, please observe the manufacturers' instructions, particularly announcements concerning releases on their Internet pages. We cannot guarantee proper functioning and installation of approved third-party systems and do not support them. Always follow the instructions provided in the installation manuals of the relevant manufacturers. If you experience difficulties, please contact the relevant manufacturer.

If you need help installing third-party systems, contact your local Software AG sales organization. Please note that this type of manufacturer-specific or customer-specific customization is not covered by the standard Software AG software maintenance agreement and can be performed only on special request and agreement.

2.2 Support

If you have any questions on specific installations that you cannot perform yourself, contact your local Software AG sales organization

(https://www.softwareag.com/corporate/company/global/offices/default.html). To get detailed information and support, use our websites.

If you have a valid support contract, you can contact **Global Support ARIS** at: **+800 ARISHELP**. If this number is not supported by your telephone provider, please refer to our Global Support Contact Directory.

ARIS COMMUNITY

Find information, expert articles, issue resolution, videos, and communication with other ARIS users. If you do not yet have an account, register at ARIS Community.

PRODUCT DOCUMENTATION

You can find the product documentation on our documentation website.

In addition, you can also access the cloud product documentation. Navigate to the desired product and then, depending on your solution, go to **Developer Center**, **User Center** or **Documentation**.

PRODUCT TRAINING

You can find helpful product training material on our Learning Portal.

TECH COMMUNITY

You can collaborate with Software AG experts on our Tech Community website. From here you can, for example:

- Browse through our vast knowledge base.
- Ask questions and find answers in our discussion forums.
- Get the latest Software AG news and announcements.
- Explore our communities.
- Go to our public GitHub and Docker repositories and discover additional Software AG resources.

PRODUCT SUPPORT

Support for Software AG products is provided to licensed customers via our Empower Portal (https://empower.softwareag.com/). Many services on this portal require that you have an account. If you do not yet have one, you can request it. Once you have an account, you can, for example:

- Download products, updates and fixes.
- Add product feature requests.
- Search the Knowledge Center for technical information and tips.
- Subscribe to early warnings and critical alerts.
- Open and update support incidents.