

# Natural System Error Messages 7951-8000

## **NAT7997: PRNTWORK buffer overflow.**

Text	PRNTWORK buffer overflow.
Expl.	Natural tried to allocate storage in the PRNTWORK buffer for a new work file area which was requested by a DEFINE PRINTER statement, but there was not enough storage available.
Actn.	Contact Natural support.

## **NAT7998: Initialization of access method :1: failed.**

Text	Initialization of access method :1: failed.
Expl.	The initialization of a print/work file access method has failed. This access method cannot be used during the current session. Any print or work files defined for this access method cannot be used.
Actn.	Check for the access method error message previously displayed. It should give more detailed information. Correct the problem and restart the session.

## **NAT7999: GETMAIN failed for print / work file buffer.**

Text	GETMAIN failed for print / work file buffer.
Expl.	Natural tried to allocate storage for print/work files which were requested either via JCL or via entries in the parameter module. However, there was not enough space available for these files in the Natural partition/region/thread.
Actn.	Enlarge size of partition/region/thread, or delete requests for print/work files. If the problem remains, contact your Natural administrator for review of printer/work file parameters.

## **NAT8000: ADABAS response code to initial call from NATURAL.**

Text	ADABAS response code to initial call from NATURAL.
Expl.	An ADABAS response code was received upon the initial call from NATURAL to ADABAS. The error is displayed as "NAT8nnn", "nnn" being the response code.
Actn.	Make sure that the ADABAS system has been started.