


# DOWNLOAD PC FILE



This chapter covers the following topics:

- Function
- Syntax Description
- Examples

For an explanation of the symbols used in the syntax diagram, see *Syntax Symbols*.

Related Statements: CLOSE PC FILE | UPLOAD PC FILE | WRITE WORK FILE

Belongs to Function Group: *Control of Work Files / PC Files*

## Function

This statement is used to transfer data from a mainframe platform to the PC.

See also the Natural Connection and Entire Connection documentation

## Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S	A	G	A	U	N	P	I	F	B	D	T	L	C	yes	no	
<i>operand2</i>	C	S			A											yes	yes	

Neither Format C not G is valid for Natural Connection.

Syntax Element Description:

<i>work-file-number</i>	The work file number to be used. This number must correspond to one of the work file numbers for the PC as defined to Natural.
<b>VARIABLE</b>	The records in the PC file will be written in variable format. Note that variable records cannot be converted to PC spreadsheet formats.
<i>operand1</i>	<p><b>Field Specification:</b></p> <p>With <i>operand1</i> you specify the fields to be downloaded to the PC.</p>
<b>COMMAND</b>	<p>With the <b>COMMAND</b> clause you can send PC commands (i.e any command that can be entered in the command line of Entire Connection on the PC) from the mainframe to the PC.</p> <p>Entire Connection checks whether the command sent is valid or not. A command that cannot be recognized by the PC is rejected. In this case, Natural issues the error message that the downloaded command was rejected by the PC.</p> <p>You can use the <b>COMMAND</b> clause, for example, to execute Entire Connection tasks from the mainframe. If you have the task <b>DIR</b> which lists PC directory information, you can initiate this directly out of your Natural program on the mainframe with the following statement:</p> <pre>DOWNLOAD PC FILE 7 COMMAND 'DIR'</pre> <p>In <i>Example 2</i> below, the <b>COMMAND</b> clause is used to define the name of the PC file that is to receive the downloaded data. In this way, you can avoid prompting for the name of the file.</p>
<i>operand2</i>	<p><b>COMMAND Specification:</b></p> <p>With <i>operand2</i> you specify the DOS command or Entire Connection task that is to be executed on the PC. <i>operand2</i> must be an alphanumeric constant or variable.</p>
<b>SYNC</b>	With <b>SYNC</b> , you specify that the PC returns control to Natural after executing and terminating <b>COMMAND</b> . <b>SYNC</b> can be used, for example, to ensure that the command <b>SET PCFILE</b> has been executed before a file transfer starts.
<b>ASYNC</b>	With <b>ASYNC</b> , you specify that the PC immediately returns control to Natural, regardless of whether the execution of <b>COMMAND</b> has terminated or not.

## Examples

- Example 1 - Use of **DOWNLOAD PC FILE** Statement
- Example 2 - Use of **COMMAND** Clause

### Example 1 - Use of **DOWNLOAD PC FILE** Statement

The following program demonstrates the use of the **DOWNLOAD PC FILE** statement. The data is first selected and then downloaded to the PC by using Work File 7.

```

** Example 'PCDOEX1': DOWNLOAD PC FILE
**
** NOTE: Example requires that Natural Connection is installed.
*****
DEFINE DATA LOCAL
01 PERS VIEW OF EMPLOYEES
   02 PERSONNEL-ID
   02 NAME
   02 CITY
END-DEFINE
*
FIND PERS WITH CITY = 'NEW YORK'           /* Data selection
   DOWNLOAD PC FILE 7 CITY NAME PERSONNEL-ID /* Data download
END-FIND
END

```

### Output of Program PCDOEX1:

When you run the program, a window appears in which you specify the name of the PC file into which the data is to be downloaded. The data is then downloaded to the PC.

## Example 2 - Use of COMMAND Clause

The following program demonstrates the use of the COMMAND clause in the DOWNLOAD PC FILE statement. The name of the receiving PC file is first defined. Then the data is selected and downloaded to this file.

```

** Example 'PCDOEX2': DOWNLOAD PC FILE
**
** NOTE: Example requires that Natural Connection is installed.
*****
DEFINE DATA LOCAL
01 PERS VIEW OF EMPLOYEES
   02 PERSONNEL-ID
   02 NAME
   02 CITY
01 CMD (A80)           /* Variable for transfer
END-DEFINE           /* of the PC command
*
MOVE 'SET PCFILE 7 DOWN DATA PERS.NCD' TO CMD /* PC command to define
*
DOWNLOAD PC FILE 6 COMMAND CMD           /* Command download
*
FIND PERS WITH CITY = 'NEW YORK'       /* Data selection
   DOWNLOAD PC FILE 7 CITY NAME PERSONNEL-ID /* Data download
END-FIND
END

```

### Note:

The PC file number in two successive DOWNLOAD PC FILE statements must be different.

### Output of Program PCDOEX2:

When you run the program, the data is downloaded to the PC file that was specified in the program. A window does not appear.