

# **System Maintenance Aid**

## **Installing System Maintenance Aid**

Version 2.2.1

September 2024

This document applies to System Maintenance Aid Version 2.2.1 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 2024 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://softwareag.com/licenses>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://softwareag.com/licenses/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software AG.

**Document ID: SMA-INSTALL-221-20240927**

## Table of Contents

1 About this Documentation .....	1
Document Conventions .....	2
Online Information and Support .....	2
Data Protection .....	3
2 Installing System Maintenance Aid .....	5
3 Install System Maintenance Aid .....	7
Prerequisites .....	8
Copying Data Sets from the Installation Medium .....	8
SMA Installation .....	10
Installation Verification .....	12
4 Install System Maintenance Aid Using Starter System .....	15
Prerequisites .....	16
Required Products and Data Sets .....	16
Copying the Tape Contents to a z/OS Disk .....	18
Installation Steps .....	20



# 1

## About this Documentation

---

■ Document Conventions .....	2
■ Online Information and Support .....	2
■ Data Protection .....	3

## Document Conventions

---

Convention	Description
<b>Bold</b>	Identifies elements on a screen.
Monospace font	Identifies service names and locations in the format <i>folder.subfolder.service</i> , APIs, Java classes, methods, properties.
<i>Italic</i>	Identifies:  Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies:  Text you must type in. Messages displayed by the system. Program code.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the   symbol.
[ ]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [ ] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

## Online Information and Support

---

### Product Documentation

You can find the product documentation on our documentation website at <https://documentation.softwareag.com>.

In addition, you can also access the cloud product documentation via <https://www.software-ag.cloud>. Navigate to the desired product and then, depending on your solution, go to “Developer Center”, “User Center” or “Documentation”.

### Product Training

You can find helpful product training material on our Learning Portal at <https://knowledge.softwareag.com>.

## Tech Community

You can collaborate with Software AG experts on our Tech Community website at <https://tech-community.softwareag.com>. From here you can, for example:

- Browse through our vast knowledge base.
- Ask questions and find answers in our discussion forums.
- Get the latest Software AG news and announcements.
- Explore our communities.
- Go to our public GitHub and Docker repositories at <https://github.com/softwareag> and <https://hub.docker.com/publishers/softwareag> and discover additional Software AG resources.

## Product Support

Support for Software AG products is provided to licensed customers via our Empower Portal at <https://empower.softwareag.com>. Many services on this portal require that you have an account. If you do not yet have one, you can request it at <https://empower.softwareag.com/register>. Once you have an account, you can, for example:

- Download products, updates and fixes.
- Search the Knowledge Center for technical information and tips.
- Subscribe to early warnings and critical alerts.
- Open and update support incidents.
- Add product feature requests.

## Data Protection

---

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.





## 2 Installing System Maintenance Aid

---

This section describes how to install SMA.

SMA is an application completely written in Natural and the SMA data is stored in an Adabas database. Therefore, both Adabas and Natural must be installed prior to installing and using SMA.

If Adabas and Natural are already installed at your site, proceed to section [Install System Maintenance Aid](#).

If Adabas and Natural are *not* already installed at your site, proceed to section [Install SMA Using SMA Starter System for z/OS](#).



# 3

## Install System Maintenance Aid

---

■ Prerequisites .....	8
■ Copying Data Sets from the Installation Medium .....	8
■ SMA Installation .....	10
■ Installation Verification .....	12

This section describes how to install SMA and assumes that Adabas and Natural have already been previously installed.

SMA is an application completely written in Natural. SMA data is stored in an Adabas database.

SMA can be installed easily into an existing Adabas/Natural environment.

## Prerequisites

---

SMA requires the following Software AG products:

- A supported version of Natural must be installed. For the supported operating systems and versions, refer to the **Product Version Availability** section of Software AG's Empower web site at <https://empower.softwareag.com/>.
- A supported version of Adabas must be installed. For the supported operating systems and versions, refer to the **Product Version Availability** section of Software AG's Empower web site at <https://empower.softwareag.com/>.

## Copying Data Sets from the Installation Medium

---

- [Installation Medium](#)
- [Copying Data Sets to Disk under z/OS](#)

### Installation Medium

The product installation medium (e.g., tape or CD-ROM) contains the data sets listed in the table below. The sequence of the data sets is shown in the *Software AG Product Delivery Report* which accompanies the installation medium.

Data Set	Description
SMA $\nu$ rs.INPL	SMA programs
SMA $\nu$ rs.SYSF	SMA system file
SMA $\nu$ rs.JOBS	Library with SMA example jobs (z/OS)

The notation  $\nu$ rs in data set names represents the version number of the product.

The data set type and the space each data set requires on disk is shown in the *Software AG Product Delivery Report*.

## Copying Data Sets to Disk under z/OS

Copy the data sets from the supplied installation medium to your disk before you perform the individual installation procedure for each component to be installed.

The way you copy the data sets depends on the installation method and the medium used:

- If you are already using SMA, refer to the section *Installing Software AG Products with SMA*.
- If you are not using SMA and want to copy the data sets from CD-ROM, refer to the README.TXT file on the CD-ROM.
- If you are not using SMA and want to copy the data sets from tape, follow the instructions in this section.

This section explains how to copy all data sets from tape to disk.

- [Step 1: Copy Data Set COPY.JOB from Tape to Disk](#)
- [Step 2: Modify hilev.COPY.JOB on Your Disk](#)
- [Step 3: Submit COPY.JOB](#)

### Step 1: Copy Data Set COPY.JOB from Tape to Disk

- Modify the following sample job according to your requirements:

```
//SAGTAPE JOB
SAG,CLASS=1,MSGCLASS=X /* ----- //COPY EXEC
PGM=IEBGENER //SYSUT1 DD DSN=COPY.JOB, // DISP=(OLD,PASS), //
UNIT=(CASS,,DEFER), //
VOL=(,RETAIN,SER=tape-volser), // LABEL=(2,SL)
//SYSUT2 DD DSN=hilev.COPY.JOB, //
DISP=(NEW,CATLG,DELETE), //
UNIT=3390,VOL=SER=disk-volser, //
SPACE=(TRK,(1,1),RLSE), // DCB=*.SYSUT1 //SYSPRINT DD SYSOUT=* //SYSIN DD DUMMY
//
```

where:

*tape-volser* is the VOLSER of the tape, for example: T12345,  
*hilev* is a valid high-level qualifier, and  
*disk-volser* is the VOLSER of the disk.

- Execute the job to copy the data set COPY.JOB to your disk.

## Step 2: Modify hilev.COPY.JOB on Your Disk

- Modify *hilev.COPY.JOB* according to your requirements:

Set EXPDT to a valid expiration date, for example, 99365.

Set HILEV to a valid high-level qualifier, for example, USERLIB.

Set LOCATION to a storage location, for example, STORCLAS=ABC or UNIT=3390,VOL=SER=USR123.

## Step 3: Submit COPY.JOB

- Execute *hilev.COPY.JOB* to copy single, multiple, or all data sets to your disk.

# SMA Installation

---

The following steps are required for installation of SMA:

- [Step 1: Prepare the SMA System File](#)
- [Step 2: Load Natural Programs and Load Error Messages](#)
- [Step 3: Specify Natural Parameters](#)
- [Step 4: SMA Under Natural Security](#)
- [Step 5: Load SMA Tables](#)

## Step 1: Prepare the SMA System File

- [Creating a New SMA System File](#)
- [Using an Existing SMA System File](#)

### Creating a New SMA System File

If you want to create a new SMA system file, you can use job I050, step 1800.

This job loads the empty SMA system file (data set SMA<sub>vrs</sub>.SYSF) using the ADALOD utility.

Use the following options in this ADALOD step:

```
USERISN=YES  
ISNREUSE=YES  
VERSION=6  
MAXISN=40000, DSSIZE=300B, NISIZE=300B, UISIZE=100B
```



**Note:** Option USERISN is essential for the correct operation of SMA. For the Adabas nucleus, allow for approximately 500 ISNs to be kept in the hold queue: NH=2000 NI=500.

## Using an Existing SMA System File

If you want to continue to use an existing SMA system file from SMA Version 1.3, you must migrate this system file to an SMA Version 2.1 system file.

Submit job I051, step 1800 to perform the migration from SMA Version 1.3 or 2.1.1.

Additionally, submit job I051, steps 1801 and 1802 to perform the migration from SMA Version 1.3.

## Step 2: Load Natural Programs and Load Error Messages

Load the SMA Natural programs (SMA *vs.* INPL) into the Natural system file using the Natural INPL utility (job I061, step 1800).

## Step 3: Specify Natural Parameters

Whenever you invoke Natural to work with SMA, do either of the following:

- append the following macro definition:

```
NTFILE ID=208,DBID=dbid,FNR=fnr
```

in your Natural parameter module, where *dbid* is the database ID and *fnr* is the file number where you loaded the SMA data file. Then re-assemble and re-link the Natural parameter module.

- or, use the dynamic parameter

```
LFILE=(208,dbid,fnr)
```

The following Natural parameters should be specified:

```
ESIZE=64 MADIO=0 MAXCL=0
```

The `PRINTER` parameter should allow for at least 1 printer in online mode and 3 printers in batch mode. If no physical or logical printer is available, set Printer ID to DUMMY or blank in the SMA Profile. See SMA Profile in the section Menus and Line Commands for an explanation of this parameter.

SMA uses the Software AG Editor. For more information, refer to the section *Installing the Software AG Editor* in the Natural documentation.

Depending on the Natural TP environment, the following specification may also be necessary:

```
RJESIZE=32
```

### Step 4: SMA Under Natural Security

When using SMA with Natural Security, the following prerequisites must be fulfilled:

- The library SYSSMA1 must be defined in Natural Security
- SMA uses the Natural Command Processor, which must also be defined in Natural Security. This can be done by performing the following actions:
  - enter Natural Security Library Maintenance
  - modify library SYSSMA1
  - select *Additional Options*
  - select *Functional Security*
  - enter SMACPROC in the field Command Processor, and mark the *Keyword default* field. After pressing Enter, the field *Functional security defined* should be set to Yes, and *Keyword default* should be allowed.
  - exit Natural Security

### Step 5: Load SMA Tables

Submit job TABLOAD to load the SMA tables from the product installation medium into the SMA system file.

## Installation Verification

---

Perform the following steps to verify correct SMA installation:

1. Invoke online Natural by entering the following command:

```
LOGON SYSSMA1  
MENU  
A
```

2. Adapt the GLOBAL parameters and the SMA profile.
3. Use function *Tabload* from the SMA administration menu to load the TABS data from the installation medium.
4. Enter the SMA *Environment* function, issue line command C0 for your default environment, in the new environment mark the most current version of ADA to be installed.



5. Enter the *SMA Report* function, invoke report P for the newly created environment, mark for printing.
6. Submit a batch Natural job, with the following input:

```
LOGON SYSSMA1  
MENU  
SET ENV <your-new-environment>  
GEN  
FIN
```

7. Enter online Natural again, enter the *Environment* function, and issue line command J0 to see the jobs generated to install Adabas.



**Note:** At this point, the generated JCL is intended only for installation verification testing.



# 4

## Install System Maintenance Aid Using Starter System

---

■ Prerequisites .....	16
■ Required Products and Data Sets .....	16
■ Copying the Tape Contents to a z/OS Disk .....	18
■ Installation Steps .....	20

This section describes how to install SMA using the SMA Starter System and assumes that Adabas and Natural have *not* been previously installed.



**Note:** The SMA Starter System is only available under z/OS.

The SMA Starter System can be used to quickly and easily install SMA in a new environment. For this purpose, Adabas und Natural under TSO are needed and will be installed. The SMA Starter System essentially consists of a CLIST which is used to generate four install jobs. These jobs must be executed in the same order as generated in order to complete the installation. Following successful installation, all subsequent Software AG products which are to be installed using SMA can be installed and configured as described in the section Installing Software AG Products with SMA.

## Prerequisites

---

The SMA Starter System requires the following:

- TSO (including ISPF) must be installed.
- The SMA Starter System requires approximately 320 cylinders of space in the Adabas database to store the Natural and SMA objects supplied by Software AG.
- A free SVC number for the temporary Adabas SVC must be available.
- APF authorization is needed for 2 data sets (see Installation Step 4 below).

## Required Products and Data Sets

---

The following products and data sets are needed for an SMA first time installation:

### Products

Data Set Name	Contents
SMA	System Maintenance Aid
ADA	Adabas
NAT	Natural
NTI	Natural TSO Monitor Interface

**Data Sets for Adabas (ADA)**

Data Set Name	Contents
ADA $\nu$ rs.LICS	Adabas license key file
ADA $\nu$ rs.LOAD	Adabas load modules
ADA $\nu$ rs.SRCE	Adabas source modules and macros

**Data Sets for Natural (NAT)**

Data Set Name	Contents
NAT $\nu$ rs.LICS	Natural license key file
NAT $\nu$ rs.LOAD	Natural load modules
NAT $\nu$ rs.SRCE	Natural source modules and macros
NAT $\nu$ rs.INPL	Natural system objects
NAT $\nu$ rs.ERRN	Natural error messages
NAT $\nu$ rs.SYSF	Empty Natural system file

**Data Sets for the Natural TSO Monitor interface (NTI)**

Data Set Name	Contents
NTI $\nu$ rs.LOAD	TSO-dependent source programs

**Data Sets for the System Maintenance Aid (SMA)**

Data Set Name	Contents
SMA $\nu$ rs.CLST	SMA clist
SMA $\nu$ rs.SYSF	Empty SMA system file
SMA $\nu$ rs.INPL	SMA system objects
SMT $\nu$ rs.TABS	SMA product tables

There are more data sets and products on the installation medium than the ones mentioned above. Please ignore these additional data sets and products. Verify the medium contents using the *Software AG Product Delivery Report* which accompanies the medium. After the data sets have been copied from the medium to disk (see Copy step described below), they will be extended with a high level qualifier (*hilev*). This high level qualifier must also be used in Step 1 of the installation described below.

**Example:**

If 'SAG' is used as a high-level qualifier (*hilev*) and the SMA version on medium is '211', the following libraries will be copied:

```
SAG.SMA211.CLST
SAG.SMA211.SYSF
SAG.SMA211.INPL
SAG.SMA211.ERRN
```

↩

## Copying the Tape Contents to a z/OS Disk

---

This section explains how to:

- Copy data set COPY.JOB from tape to disk.
- Modify this data set to conform with your local naming conventions.

The JCL in this data set is then used to copy all data sets from tape to disk (except the data set SMT<sub>vrs</sub>.TABS).

If the data sets for more than one product are delivered on the tape, the data set COPY.JOB contains the JCL to unload the data sets for all delivered products from the tape to your disk.

After completing the above, you will have to perform the individual install procedure for each component.

### Copying the Installation Tape to Disk under z/OS

If you are already using SMA and wish to use SMA to copy the installation tape for the new SMA version, refer to the section Installing Products.

If you are not using SMA, you must perform the following as described in this section:

- [Step 1: Copy Data Set COPY.JOB from Tape to Disk](#)
- [Step 2: Modify COPY.JOB for Conformance with Local Naming Conventions](#)
- [Step 3: Submit COPY.JOB to Unload Data Sets](#)



**Note:** If the data sets for more than one product are delivered on the tape, the data set COPY.JOB contains the JCL to unload the data sets for all delivered products from the tape to your disk. After unloading all the data sets, you will have to perform the individual install procedure for each component.

**Step 1: Copy Data Set COPY.JOB from Tape to Disk**

The data set COPY.JOB (label 2) contains the JCL to unload all other data sets from tape to disk. To unload COPY.JOB, use the following sample JCL:

```
//SAGTAPE JOB SAG,CLASS=1,MSGCLASS=X
//* -----
//COPY EXEC PGM=IEBGENER
//SYSUT1 DD DSN=COPY.JOB,
// DISP=(OLD,PASS),
// UNIT=(CASS,,DEFER),
// VOL=(,RETAIN,SER=<Tnnnnn>),
// LABEL=(2,SL)
//SYSUT2 DD DSN=<hilev>.COPY.JOB,
// DISP=(NEW,CATLG,DELETE),
// UNIT=3390,VOL=SER=<vvvvvv>,
// SPACE=(TRK,(1,1),RLSE),
// DCB=*,SYSUT1
//SYSPRINT DD SYSOUT=*
//SYSIN DD DUMMY
//
```

where:

<hilev> is a valid high-level qualifier

<Tnnnnn> is the tape number

<vvvvvv> is the desired volume serial number

**Step 2: Modify COPY.JOB for Conformance with Local Naming Conventions**

Modify the COPY.JOB to conform with your local naming conventions and set the disk space parameters before submitting this job:

- set HILEV to a valid high-level qualifier
- set LOCATION to a storage location
- set EXPDT to a valid expiration date

### Step 3: Submit COPY.JOB to Unload Data Sets

Submit COPY.JOB to unload all other data sets from the tape to your disk.

## Installation Steps

---

Perform the following installation steps:

- [Step 1: Invoke the CLIST](#)
- [Step 2: Enter the Parameters](#)
- [Step 3: Check the Information Screen](#)
- [Step 4: Give APF Authorization to Data Sets](#)
- [Step 5: Submit Jobs JOBI001, JOBI002 and JOBI003](#)
- [Step 6: Start Adabas](#)
- [Step 7: Submit Job JOBI004](#)
- [Step 8: Invoke SMA](#)

### Step 1: Invoke the CLIST

Enter the ISPF command mode and invoke the CLIST MENU from the source library that you just copied with the command:

```
EX '<hilev>.SMAvrs.CLST(MENU)'
```

The following screen will appear:

```
=====
===== SMA Initial Installation =====
=====
>> Please enter High Level Qualifier (<hilev>) or '.' to exit:
```

The CLIST requests the high level qualifier (<hilev>) of the source library from which it was called. Enter the <hilev> and press Enter. (This is necessary because in the CLIST language it is not possible to determine the library from which the CLIST was called.).

```
>> Please enter the 3 digit SMA version (i.e.211) or '.' to exit:
```

This next line asks you for the version of the SMA (for example: '211') which is used on the product installation medium. Enter the 3-digit version of SMA and press Enter.



## Step 2: Enter the Parameters

A screen similar to the following will now appear:

```
*****
Please enter the following parameters:

NATURAL Version (ie: 424): ...
ADABAS Version  (ie: 813): ...

Adabas SVC numb.(ie: 249): ...

Tape Volume  (ie: T12345): T.....

Job Line 1.. //JOB@JNR JOB ACCT,REGION=4M,MSGLEVEL=(1,1),
Job Line 2.. // CLASS=G,MSGCLASS=X
Job Line 3.. /*JOBPARM LINES=9999

Note: @JNR in Job Line 1 is used as a parameter, which will
be replaced during generation with the job number.
It is recommended to leave it untouched.
*****
Enter '.' to exit or 'OK' to start job generation:
```

Enter the following parameters:

Parameter	Description
Natural and Adabas Version	Enter the 3-digit version of Natural and Adabas which is on the installation medium.
Adabas SVC number	Enter an SVC number as required for the Adabas installation. The SMA Starter system will generate a job to install the Adabas SVC temporarily, i.e. the SVC will be active until the next IPL.
Tape Volume Name	Enter the volume name of the delivered tape/cartridge. You can obtain this information from the <i>Software AG Product Delivery Report</i> .
Job Lines 1-3	Enter up to 3 individual joblines which you wish to use for the JCL generation. @JNR is used as a parameter which will be replaced during generation with the job number.

Example:

```

*****
Please enter the following parameters:

NATURAL Version (ie: 424): 424
ADABAS Version  (ie: 813): 813

Adabas SVC numb.(ie: 249): 232

Tape Volume  (ie: T12345): T23545

Job Line 1.. //SAG@JNR JOB ACCT,REGION=4M,MSGLEVEL=(1,1),
Job Line 2.. // CLASS=0,MSGCLASS=Z
Job Line 3.. //*JOBPARM LINES=9999

Note: @JNR in Job Line 1 is used as a parameter, which will
be replaced during generation with the job number.
It is recommended to leave it untouched.
*****
Enter '.' to exit or 'OK' to start job generation:

```

After you entered all the necessary parameters, enter 'OK' and press Enter.

The SMA Starter System for z/OS now generates the JCL (JOBI001-JOBI004) and creates the following 3 libraries:

Data Set name	Contents
<hilev>.SMAvrs.JCL	The CLIST will write the generated jobs as well as a member containing the user's parameter values to this library.
<hilev>.SMAvrs.SMASRCE	This data set is used as a work library which is used by the installation jobs to store the created source modules.
<hilev>.SMAvrs.SMALOAD	This data set is used as a work library which is used by the installation jobs to store the created load modules.



**Note:** These libraries will always be overwritten each time you initiate the installation process.

There will be 4 jobs generated into library <hilev>.SMAvrs.JCL:

### JOBI001: Prepare the necessary license keys

Step	Description
CNVADA	Convert Adabas license file
ASMADA	Assemble Adabas license file
LKDADA	Link Adabas license file
CNVNAT	Convert Natural license file
ASMNAT	Assemble Natural license file

Step	Description
LKDNAT	Link Natural license file

### **JOB1002: Installs the Adabas Components**

Step	Description
ADASIP	Start the temporary Adabas SVC with program ADASIR
FRMDB	Format the database
DEFDB	Define the database
ADDRUN	Add the ADARUN card member
ADDTASK	Add the member for the Adabas started task
ADDLKBA	Create global parameter member for ADALINK in batch mode
ASMLKBA	Assemble global parameter member for ADALINK in batch mode
LNKLKBA	Link global parameter member for ADALINK in batch mode
LNKFIBA	Final link of ADALNK in batch mode
ADDLKTS	Create global parameter member for ADALINK under TSO
ASMLKTS	Assemble global parameter member for ADALINK under TSO
LNKLKTS	Link global parameter member for ADALINK under TSO
LNKFITS	Final link of ADALNK under TSO
LODFNAT	Load the Natural system file with ADALOD
LODFSMA	Load the SMA system file with ADALOD

### **JOB1003: Installs the Natural Components**

Step	Description
ADDNTOS	Create source NATOS
ASMNTOS	Assemble source NATOS
LKDNTOS	Link module NATOS
ADDPRMB	Create source for Natural batch parameter module
ASMPRMB	Assemble Natural batch parameter source
LKDPRMB	Link Natural batch parameter module
LKDNUCB	Link Natural batch nucleus NATBATCH
ADDCLST	Create source for Natural SMA clist
ADDADAR	Create source for DDCARD input file
ADDNTSO	Create source for NATTSO
ASMNTSO	Assemble source NATTSO
LKDNTSO	Link module NATTSO.
ADDPRMT	Create source for Natural online parameter module

Step	Description
ASMPRMT	Assemble Natural online parameter source
LKDPRMT	Link Natural online parameter module
LKDNUCT	Link Natural TSO nucleus NATTSORE

### **JOB1004: Load Data into the Adabas System Files**

Step	Description
INPLNAT	Load Natural programs into Adabas system file
ERRLNAT	Load Natural error messages into Adabas system file
INPLSMA	Load SMA programs into Adabas system file
ERRLSMA	Load SMA error messages into Adabas system file
TABLOAD	Load SMA tables into SMA system file

### **Step 3: Check the Information Screen**

After successful generation of the installation jobs into the library *hilev.SMAvrs.JCL*, the following information screen will appear:

```
Now perform the following steps to complete the installation:
```

```
-----  
(Step 4) The following libraries needs APF authorization:
```

```
>> hilev.SMAvrs.SMALOAD
```

```
>> hilev.ADAvrs.LOAD
```

```
(Step 5) Submit the jobs JOB1001-003 in lib hilev.SMAvrs.JCL.
```

```
(Step 6) Start ADABAS with the procedure hilev.SMAvrs.SMASRCE(ADATASK).
```

```
(Step 7) Submit the job JOB1004 in lib hilev.SMAvrs.JCL.
```

```
(Step 8) Start SMA with the CLIST hilev.SMAvrs.SMASRCE(SMA).
```

```
-----  
Enter '.' to exit:
```

This screen gives you information of what to do next (see also Steps 4-8 below).

**Step 4: Give APF Authorization to Data Sets**

The Adabas SVC installation requires that the data sets *hilev.SMAvrs.SMALOAD* and *hilev.ADAvrs.LOAD* are APF authorized. Please contact your system administrator to perform this step.

**Step 5: Submit Jobs JOBI001, JOBI002 and JOBI003**

JOBI001 will prepare the license key files for Natural and Adabas. JOBI002 will prepare the Adabas components. JOBI003 will prepare the Natural components.

**Step 6: Start Adabas**

Copy the procedure created as member *ADATASK* in library *hilev.SMAvers.SMASRCE* to the z/OS user proclib where started tasks reside. Then start the Adabas database from that library.

**Step 7: Submit Job JOBI004**

JOBI004 will load all necessary data into the SMA system files.

**Step 8: Invoke SMA**

Enter TSO command mode. Enter `EX 'hilev.SMAvrs.SMASRCE(SMA)'` to start the TSO CLIST and invoke SMA. SMA is now installed and can be used to install other SAG products.

