

Adabas Parallel Services

Introducing Adabas Parallel Services

Version 7.5.1

September 2009

Adabas Parallel Services

This document applies to Adabas Parallel Services Version 7.5.1 and to all subsequent releases.
Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.
Copyright © Software AG 2009. All rights reserved.
The name Software AG, webMethods and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. Other company and product names mentioned herein may be trademarks of their respective owners.

Table of Contents

1 Introducing Adabas Parallel Services	1
2 Conventions	3
Syntax	4
Data Set Names	
3 What is Adabas Parallel Services?	
4 Adabas Parallel Services and Adabas Cluster Services	7
5 Assigning Users	9
6 Cluster Tasks	11
ADACOM	12
Cluster of Adabas Nuclei	14
Router Cluster Component SVCCLU	14
7 Global Areas	17
Global Cache Area and Manager	19
Global Lock Area and Manager	20
8 Global Messaging Services	23
9 Global Commands	25
10 Logs and Log Merges	27
Protection Logs	28
Command Logs	30
Coordinated Log Switching	31
11 Parallel Participant Table (PPT)	33
Acquiring the PPT	34
Registering Nuclei during Session Initialization	34
Registering PLOG, CLOG, and Work Data Sets for Each Nucleus	35
Nucleus Termination Processing	35
Using PPT Information	35
PPT Unavailable	36
SBLKNUM Parameter for ADARES PLCOPY NOPPT	36
12 Dynamic Allocation	39
JCL Considerations (OS/390 and z/OS Only)	40
13 Components Summary	41
14 Switching Between Cluster and Noncluster Modes / PLOG Handling	43
Scenario 1	44
Scenario 2	44
Scenario 3	44
15 Adabas Parallel Services and Other Software AG Products	47
Adabas Online System	48
Adabas Caching Facility	48
Adabas Delta Save Facility	48
Adabas Fastpath	49
Adabas Vista	49
Adabas SAF Security	49
Adabas Review	50

Adabas Transaction Manager	50
16 Restricted Support for Adabas Features	51
Triggers and Stored Procedures Facility	52
Limited Distributed Transaction Support	53
User Table Cleanup	53
17 Migration from ADASMP	55
18 ADARUN Parameter Terminology	57
19 Getting Started	59
ADACOM Starts	
First Cluster Nucleus Starts	60
Additional Cluster Nuclei	60
Index	61

1

Introducing Adabas Parallel Services

Adabas Parallel Services (formerly Adabas Support for Multiprocessing or ADASMP) is a selectable unit of Adabas that helps you make full use of multiple-engine processors by allowing a single physical database to be accessed simultaneously by up to 31 nuclei.

Adabas Parallel Services extends the earlier Adabas SMP capability to allow all nuclei in a cluster to process updates concurrently.

This document is organized as follows:

•	What is Adabas Parallel Services?	Provides a high-level description of the product.
•	Adabas Parallel Services and Adabas Cluster Services	Describes the differences between Adabas Parallel Services and Adabas Cluster Services.
•	Assigning Users	Describes how Adabas Parallel Services assigns users to nuclei in a cluster.
•	Cluster Tasks	Describes the types of tasks that comprise an Adabas Parallel Services cluster.
•	Global Areas	Describes global area usage in Adabas Parallel Services.
•	Global Messaging Services	Describes the messaging services that are essential to communication among the active nuclei of an Adabas Parallel Services cluster.
•	Global Commands	Describes the global operator commands available with Adabas Parallel Services.
•	Logs and Log Merges	Describes the protection log (PLOG) and command log (CLOG) usage in Adabas Parallel Services.
•	Parallel Participant Table (PPT)	Discusses the use of the Parallel Participant Table (PPT) in Adabas Parallel Services.
•	Dynamic Allocation	Describes the use of dynamic allocation by ADARES for Adabas Parallel Services data sets and files.
•	Components Summary	Provides a component summary for Adabas Parallel Services.

•	Switching Between Cluster and Noncluster Modes / PLOG Handling	Describes switching between cluster and non-cluster modes in Adabas Parallel Services.
•	Adabas Parallel Services and Other Software AG Products	Describes the support for Adabas Parallel Services provided by other Software AG products.
•	Restricted Support for Adabas Features	Describes facilities that are not supported for cluster nuclei running under Adabas Parallel Services or for which restricted support is provided.
•	Migration from ADASMP	Describes the procedures for migrating from ADASMP.
•	ADARUN Parameter Terminology	Describes ADARUN parameter terminology specific to Adabas Parallel Services.
•	Getting Started	Describes how to get started using Adabas Parallel Services and where to go for more information.

2 Conventions

Syntax
Data Set Names

This document covers the following topics:

- Syntax
- Data Set Names

Syntax

This following syntax conventions are used in this documentation when describing ADARUN parameters and operator commands:

- The vertical bar (|) separates parameter options or values, one of which must be chosen.
- Curly brackets or braces ({ }) delimit the series of options or values.
- (Square) brackets ([]) indicate a term that may optionally be specified.
- The underline (_) identifies the default value.
- Three dots preceded by a comma or a slash (, ... or / ...) indicates that the previous term can be repeated but must be preceded by the comma or slash as indicated.
- A range of values is indicated by two instances of a variable (for example, "fnr", "rabn", "csn") separated by a hyphen (for example, "fnr fnr"). The first instance represents the low value and the second the high value of the range. The range specification comprises the two numbers separated by the hyphen with no intervening spaces.
- Parentheses (()) are part of the term and must be included as part of the parameter statement.

Data Set Names

Data set names starting with DD are referred to in Adabas documentation with a slash separating the DD from the remainder of the data set name to accommodate VSE/ESA data set names that do not contain the DD prefix. The slash is not part of the data set name.

3

What is Adabas Parallel Services?

Adabas Parallel Services implements multinucleus, multithread parallel processing and optimizes Adabas in a multiple-engine processor environment on a single operating system image.

Up to 31 Adabas nuclei in an Adabas Parallel Services cluster are distributed over the multiple engines provided by the system.

All nuclei in the cluster access a single physical database simultaneously. A "single physical database" is one set of Associator and Data Storage data sets identified by a single database ID number (DBID). Each nucleus writes its protection data to its own private work data set and protection logs (PLOGs). Each nucleus also records the commands it executes in its own command logs (CLOGs).

The nuclei communicate and cooperate with each other to process the users' work. Compression, decompression, format buffer translation, sorting, retrieving, searching, and updating operations can all occur in parallel.

In addition to the increased throughput that results from parallel processing, Adabas Parallel Services increases database availability during planned or unplanned outages: the database can remain available when a particular cluster nucleus requires maintenance or goes down unexpectedly.

A practically unlimited number of Adabas Parallel Services clusters can operate in the same operating system image under the same or different SVCs or IDTNAMEs; that is, a practically unlimited number of separate databases can be processed, each with its own Adabas Parallel Services cluster of up to 31 nuclei.

Applications see only one database target; no interface changes are required. Applications still communicate with their intended databases and communicate with an Adabas Parallel Services cluster of nuclei without modification.

4

Adabas Parallel Services and Adabas Cluster Services

Adabas Parallel Services is very similar to another Adabas add-on product, Adabas Cluster Services. As shown in the following table, the differences between the two are the mechanisms used for inter-nucleus communication and for maintaining and accessing the shared cache and lock data:

Service	Adabas Parallel Services	Adabas Cluster Services
Architecture	all nuclei on same system image	nuclei on different system images in parallel sysplex (OS/390 and z/OS only)
Communication (inter-nucleus)	via inter-process communication (ADALNK)	via cross-system coupling (XCF) services
Cache	in shared data space and 64-bit addressable virtual storage	in coupling facility
Lock	in shared data space	in coupling facility

5 Assigning Users

When a user program issues the first command to the cluster database, the user is assigned to an active nucleus in the cluster. All commands from that user are routed to the assigned nucleus until the user issues a close (CL) command. At this point, the user is free to be assigned to another nucleus with the next open (OP) command.

Adabas Parallel Services keeps track of the number of users assigned to each nucleus and assigns new users to nuclei evenly to balance the load.

6 Cluster Tasks

ADACOM	12
Cluster of Adabas Nuclei	
Router Cluster Component SVCCLU	14

Adabas Parallel Services ensures data integrity and enables intercommunication among the Adabas nuclei in each cluster.

All nuclei in a cluster share the same database (ASSO and DATA data sets, DBID), global cache and lock areas, and global nucleus and user table.

ADARAI maintains a recovery log (RLOG) for each database; all nuclei in the cluster support a database write to the same RLOG and concurrent updates to the RLOG are controlled by a lock.

The Adabas Parallel Services characteristics of a particular DBID are fully transparent to the Adabas link routines.

Two types of tasks together build an Adabas Parallel Services cluster:

- a control task (ADACOM);
- one or more nuclei up to a maximum of 31.

This chapter covers the following topics:

ADACOM



Note: Router ID is the SVC number except on BS2000/OSD systems, where it is the IDTNAME.

The ADACOM task must be run to set up the Adabas Parallel Services cluster environment before any cluster nucleus is started. A common storage area is allocated for maintaining information about active users and the nuclei to which they are assigned. Any changes are sent to ADACOM and to the cluster nuclei.

ADACOM also holds the cache and lock data spaces that the cluster nuclei use for sharing information. The data spaces can exist only as long as their owner, ADACOM, is active. For this reason, ADACOM cannot terminate if it is holding data spaces for an active Adabas Parallel Services cluster. Note that with Adabas Cluster Services, ADACOM does not have to be active all of the time.



Important: Canceling ADACOM causes all Parallel Services nuclei it manages to fail.

One ADACOM can manage multiple cluster databases on different routers. ADACOM parameters specify the Router ID / DBID combinations (sets) that the ADACOM is to manage:

■ The Router ID identifies the SVC number on OS/390, z/OS, or VSE, or the IDTNAME on BS2000. The Router ID value must be the same within a cluster; however, the same Router ID may be used for different clusters.

■ The DBID identifies the external physical database shared by a particular cluster of nuclei and known to the application.

You can dynamically add or terminate Router ID / DBID combinations during an Adabas Parallel Services session. ADACOM itself, however, cannot be terminated as long as any of the Router ID / DBID sets it manages is still active.

Although a single ADACOM job can run all Router ID / DBID sets in a cluster environment, it is possible to run multiple ADACOM tasks simultaneously with the same, mixed, or completely different Router ID / DBID sets. An ADACOM subtask is attached to each Router ID / DBID set for each ADACOM task in which it occurs.

A COMPRINT data set is used to hold global messages that apply to all Router ID / DBID sets defined to an ADACOM task.

In addition, on OS/390 or z/OS platforms, Adabas Parallel Services dynamically allocates a spool data set for command output to each Router ID / DBID set. The format of its DD name is Pssddddd where ss is the last two digits of the SVC number and ddddd is the DBID.

Alternatively, for each Router ID / DBID combination, you can set up an output data set in the startup JCL by specifying the DD name/link name in the format Pssddddd as just explained. (On BS2000, the ss number is derived for each separate IDTNAME as the first available number, counting backward from 255.) The logical record length (LRECL) must be set to 80. The command output for the corresponding Router ID / DBID combination, whether defined in the startup JCL or dynamically allocated, is written to that data set. You might want to preset the spool output modules to control the data set's link name or the message class, which otherwise defaults to "X".

When you dynamically terminate a Router ID / DBID combination, the related spool output module is retained. On VSE or BS2000, this information is written to SYSLST.

The first ADACOM started governs the size of the global user table (NU parameter): different values set for subsequent ADACOMs or for nuclei are ignored. If NU is set to zero, ADACOM frees the environment. If you do not set a value for NU, it defaults to 200. ADACOM parameters are discussed in the section *Initialization Parameters* in the *Adabas Parallel Services Reference Guide*.

After initialization, ADACOM functions as a command manager to monitor and control cluster nuclei running under Router ID / DBID sets it manages and to dynamically create or terminate Router ID / DBID sets. ADACOM commands are available to:

- exercise some control over the assignment of users to nuclei
- display the number of commands and user assignments for each active nucleus
- dynamically create or terminate Router ID / DBID combinations (sets).

Cluster of Adabas Nuclei

The ADARUN parameter CLUSTER=LOCAL is used to identify a nucleus as a member of an Adabas Parallel Services cluster. The NUCID parameter identifies the Adabas Parallel Services cluster nucleus for communication via the Adabas router. The NUCID must be a unique number in the range 1-65000. A non-cluster nucleus has the parameter CLUSTER=NO (the default value); its NUCID is zero.

The NUCID is the only ID table entry for a Parallel Services nucleus.

Additionally, each nucleus has its own:

- command queue
- local buffer pool (LBP) and manager;
- Work data set, which must have the same device type and physical size for each nucleus in the cluster:
- dual or multiple protection log (PLOG) data sets (optional)
- dual or multiple command log (CLOG) data sets (optional)
- workpool
- format pools, etc.

Dual or multiple protection logs are optional but if supplied, each nucleus must have its own and all must use the same type. The same is true for command logs.

The nucleus handles all updates and protection logging. Updates are handled in a timely manner to ensure that the other cluster nuclei access the most recent data.

The ADADBS OPERCOM functions provide the NUCID parameter to route the command to a specific nucleus in the Adabas Parallel Services cluster. If NUCID is not specified, the command goes either to the nucleus assigned to ADADBS or AOS, or to all nuclei, depending on the inherent logic of the command.

Router Cluster Component SVCCLU

The Adabas version 7.4 router, (ADASVC on OS/390, z/OS, VSE systems) always contains the SVCCLU component. On BS2000/OSD systems, the SVCCLU component is loaded together with the ADARER Router module into the ID Table common memory. The SVCCLU component includes functionality for Adabas cluster environments. The resulting SVC routes commands to the cluster nuclei in an Adabas Parallel Services cluster. To make routing decisions, it uses the nucleus and user tables in local common storage, which are updated based on nucleus or ADACOM information.

There is no predefined limit to the number of Adabas Parallel Services clusters, each servicing a separate database, that can run under a single router (ID table).

SVCCLU is invoked by the router as an "exit". It:

- maintains a table of active users and the nucleus to which each is currently assigned;
- assigns new users to the least loaded active cluster nucleus; and
- routes user commands according to the established assignment to cluster nuclei.

7 Global Areas

Global Cache Area and Manager	. 19
Global Lock Area and Manager	

Adabas Parallel Services uses global areas in dataspaces for cluster caching and locking functions. Under z/OS version 1 release 5 or later releases, cache can also be maintained in shared 64-bit addressable virtual storage.

On BS2000/OSD systems, the global areas are also in dataspaces and will restrict this operation to ESA machines for the time being.

The global cache area ensures that current data is available to all nuclei in a cluster. It helps keep Associator and Data Storage blocks in the local buffer pools up to date.

The global lock area is used to protect the resources needed during command execution against conflicting use by multiple cluster nuclei.

Global cache and lock areas are sized in each nucleus using the ADARUN parameters CLUCACHESIZE and CLULOCKSIZE, respectively.

The first cluster nucleus that starts provides its <code>CLUCACHExxxx</code> and <code>CLULOCKxxxx</code> parameters to ADACOM, which uses a subtask to allocate the global areas for the cluster in which the nucleus participates. In addition, ADACOM dynamically allocates a data set to each cluster for cluster-related message output if the file is not defined in the ADACOM startup JCL.



Note: Read *Performance and Tuning* in the *Adabas Parallel Services Operations Guide* for a formula for estimating cache and lock size.

ADACOM maintains the global areas. It refuses to terminate normally as long as it owns any global areas, because doing so would cause all active nuclei in all clusters using these global areas to fail.

For each Parallel Services cluster, ADACOM prints dataspace-related messages to an output data set/file with the DD name/link name <code>Dssddddd</code>, where <code>ss</code> is the last two digits of the SVC number and <code>ddddd</code> is the DBID. (On BS2000, the <code>ss</code> number is derived for each separate IDTNAME as the first available, counting backward from 255.) On OS/390 and z/OS, ADACOM automatically allocates this data set in the spool with SYSOUT=X, if it is not explicitly specified.

The global areas are not persistent; that is, they disappear when the last active nucleus terminates, whether normally or abnormally. No manual cleanup is required.

This chapter covers the following topics:

Global Cache Area and Manager

A global cache area is allocated to each Adabas Parallel Services cluster for ASSO and DATA blocks that have been updated during the session.

This section covers the following topics:

- Buffer Flush
- Local Buffer Pool and Manager
- Global Cache Storage Options

Buffer Flush

Any active nucleus may perform buffer flushes.

The buffer flush accomodates the fact that all updated blocks are located in the global cache area. From the global cache area, modified blocks are "cast out" to the flush I/O pool (FIOP) buffer before they are written to disk. The FIOP buffer is sized using the ADARUN LFIOP parameter, and the frequency of buffer flushing depends on the limit set. Until such blocks are written to the database, the global cache area holds more current information than the database.

The global cache manager handles the deletion of blocks in the global cache area when it becomes necessary to overwrite them.

Local Buffer Pool and Manager

Every nucleus in an Adabas cluster has a local buffer pool and manager.

The buffer pool manager (BPM) oversees all nucleus requests for database resource blocks. For each block in its local buffer pool, the BPM:

- registers its interest in the block with the global cache manager;
- checks the global cache manager for the status of the registered block to ensure that its nucleus always has the most current copy of the block; and
- writes changed blocks to the global cache area.

The size of the local buffer pool of each nucleus is determined by the ADARUN parameter LBP.

The global cache area must be large enough to hold the active working set of blocks from the local buffer pool of each nucleus in the cluster. The global cache manager oversees all requests for Associator and Data Storage blocks and copies changed blocks between the local buffer pools and the global cache area to maintain data integrity.

When a nucleus requests a block, it checks the global cache area as well as its local buffer pool to locate the block. If an up-to-date copy of the block is already in the local buffer pool, it is used straight away. Otherwise, if the block is in the global cache area, it is copied to the local buffer pool. If neither is the case, the block is read in from the database. In any case, the global cache manager keeps track of the existence of the block in the local buffer pool and invalidates the local copy if another nucleus updates the same block.

Global Cache Storage Options

Global cache data can be maintained in a dataspace. On z/OS systems running version 1 release 5 or later, global cache data can also be maintained in shared 64-bit addressable virtual storage.

When only a dataspace is used for global cache, the maximum size is 2 GB, a limit imposed by the operating system. However, using shared 64-bit addressable virtual storage eases this virtual storage constraint and extends the maximum size of the cache from 2 GB to tens of GB.

Use the CLUCACHETYPE parameter of ADARUN to specify the virtual storage construct for global cache. The default is "DSP", indicating a dataspace of the size specified by the CLUCACHESIZE parameter of ADARUN will be used for both control structures and cached data.

The other value (valid only on z/OS systems running version 1 release 5 or later) for the CLUCACHETYPE parameter is "V64", which indicates that the CLUCACHESIZE parameter should specify the amount of shared 64-bit virtual storage that will be used for cached data. In this case, a dataspace will still be created to contain control structures such as cache directories and indices. It is not necessary to specify the size of the control structure dataspace, but note that the dataspace is constrained by its 2 GB limit for control structures. Consequently, the maximum size of the shared 64-bit cache depends on ADARUN parameters DIRRATIO and ELEMENTRATIO (the ratio of directrory entries to data elements) and the block sizes of the DATA and ASSO database files.

To use the 64-bit global cache, your system programmer must also enabe shared 64-bit virtual storage in SYS1.PARMLIB.

Global Lock Area and Manager

Each Adabas Parallel Services cluster uses a global lock area to manage the setting, status, and release of various locks imposed during multiple update nucleus processing. The global lock manager synchronizes the nuclei, users, and transaction processing to ensure data integrity.

The global lock manager is used to:

- connect to and disconnect from the global lock area;
- obtain (conditional or unconditional), release, and alter the ownership (shared or exclusive) of resource locks; and
- read recovery information about a failed peer nucleus.

Lock manager calls may be asynchronous, meaning that the nucleus may continue processing in other threads before a call has completed.

If a lock request is conditional, it is rejected if the lock is not free; if the lock request is unconditional, the nucleus thread waits until the requested lock is free before continuing.

In general, locks are used to prevent two cluster nuclei from using the same resource at the same time. Such resources include:

- data records, which are protected by hold queue element (HQE) locks;
- unique descriptor values, which are protected by unique descriptor element (UQDE) locks;
- end-transaction IDs, which are protected by the ETID lock; and
- various other single-instance resources.

8 Global Messaging Services

Messaging services are essential to communication among the active nuclei of an Adabas Parallel Services cluster. Parallel Services nuclei communicate among one another using the standard Adabas communication environment.

For example, messages need to be sent between nuclei when:

- the general control block (GCB) is modified
- a global parameter is modified
- a buffer flush occurs
- a PLOG or CLOG switches.

Adabas Parallel Services messaging statistics are produced during normal nucleus termination and reported using the ADAX14 and ADAX15 messages. For more information, read your *Adabas Messages and Codes Manual*.

9 Global Commands

For routing operator commands to all nuclei in an Adabas Parallel Services cluster, the following console operator and ADADBS OPERCOM commands have a "GLOBAL" option:

ADAEND CANCEL FEOFCL FEOFPL HALT

When "GLOBAL" is specified, the nucleus receiving the command passes it on to all active nuclei in the cluster. When "GLOBAL" is not specified for a command from this list, the command applies only to the nucleus receiving it. This is either the nucleus directly addressed by the command (console operator command or ADADBS or Adabas Online System command with NUCID parameter) of the nucleus to which ADADBS or AOS was assigned by Adabas Parallel Services.

10 Logs and Log Merges

Protection Logs	. 2	8
Command Logs		
Coordinated Log Switching		

In an Adabas cluster environment, the protection logs (and optionally, the command logs) of all individual nuclei in the cluster are merged into single log files in chronological order for the cluster database shared by all the nuclei as a whole. The chronological order is determined by timestamps on all individual private protection and command records. Once the private records are merged, the timestamps are removed. The timestamp is the only difference between an unmerged (that is, private) and merged record.

Given that each cluster nucleus has its own PLOG data sets, checkpoints are no longer identified only by their name, PLOG number, and PLOG block number, but also by the NUCID of the nucleus that writes the checkpont.

ADARES is the only utility that handles both the unmerged and merged PLOGs and CLOGs. The log merge process:

- merges PLOG or CLOG records into correct chronological sequence.
- avoids a single point of failure by partially merging as much PLOG or CLOG data as possible if a nucleus is unable to respond to a switch.
- is automatic; merges directly from the dual or multiple PLOGs or CLOGs, which eliminates the need to retain control information for tracking unmerged logs.
- quickly copies and merges so that the PLOG or CLOG can be reused.
- uses an identical PLOG or CLOG record layout for an unmerged or a merged record.
- produces a consistent amount of data from each PLCOPY or CLCOPY.

For more detailed information, read *Adabas Parallel Services Operations* in the *Adabas Parallel Services Operations Manual* and read abou the ADARES utility in the *Adabas Utilities Manual*.

This chapter covers the following topics:

Protection Logs

Either all nuclei in an Adabas Parallel Services cluster must run without protection logs (PLOGs) or all nuclei must run with PLOGs. The same ADARUN PLOGRQ setting is enforced for all nuclei in a cluster. This value cannot be modified during a session.

If the nuclei in the cluster are running with PLOGs, they must be dual or multiple PLOGs: sequential PLOGs are not allowed. For more information, read your *Adabas Operations Manual*.

Each nucleus in the cluster writes its protection data to its own Work and PLOG data sets: no synchronization is required. However, every protection record is preceded by an 8-byte timestamp indicating the time of its creation. The timestamp is the only difference between protection records written by a cluster nucleus and those written by a noncluster nucleus. The timestamp is required for the merge process and is removed after the protection log is merged but before it is written to the sequential data set.

This section covers the following topics:

- Merging Protection Logs
- Intermediate Data Sets
- User Exits for Merging Protection Logs

Merging Protection Logs

For recovery processing, all protection log data sets are automatically merged into a single log stream for each cluster database when an ADARES PLCOPY is executed in an Adabas Parallel Services nucleus cluster environment. The PLCOPY process accesses the parallel participant table (read *Parallel Participant Table (PPT*) elsewhere in this chapter) to determine which protection logs to copy and opens the appropriate data sets using dynamic allocation (read *Dynamic Allocation* elsewhere in this chapter). PLCOPY copies and merges as much data as possible; if a nucleus is still writing to a protection log data set, PLCOPY partially merges the data set.

ADARES expects that at least one of the protection logs being merged is at 'completed' status. If this is not the case, ADARES reports that there is no data to be copied.

The merge begins with the lowest timestamp from all protection logs being merged and ends with the lowest of the ending timestamps from all data sets. Records beyond this point are written to an 'intermediate' data set, which must be supplied as input to the subsequent merge.

Intermediate Data Sets

It is necessary to supply two intermediate data sets to the PLCOPY merge process: one is used as input and the other as output. ADARES analyzes both data sets to determine which is which. A cross-check ensures that the correct input intermediate data set has been supplied; the utility will not continue if the correct data set has not been supplied. The input intermediate data set contains "leftover unmerged" data from the last run of the utility, without which the merged protection data would be incomplete.

User Exits for Merging Protection Logs

A user exit is necessary for merging protection logs automatically: user exit 2 (UEX2) for dual logs or user exit 12 (UEX12) for multiple logs. However, you may choose to run without the user exit. This may be advisable for testing purposes, for example. If one nucleus in a cluster has the user exit specified, then all other nuclei in the cluster must also supply the user exit. The user exit supplied must be the same across all nuclei.

Sample user exits (USEREX2P and UEX12) are provided that illustrate the necessary changes for the intermediate data sets/files. Once the Link (DD) statements for the PLOG files/data sets have been supplied on the session start-up JCL, you do not need to supply them again for ADARES as these are opened using dynamic allocation. If the Link (DD) statements are supplied, they are ignored.

If there is a problem with the user exit, the Extended Error Recovery logic allows you to disable the exit and load a new exit without bringing the nucleus down.

Command Logs

In order to log commands during a session, a nucleus requires a command log data set. Command logging is activated by setting the ADARUN parameter LOGGING=YES.

Dual or multiple command logging requires that you set ADARUN parameters correctly. For more information about the ADARUN utility, read your *Adabas Operations Manual*.

This section covers the following topics:

- Merging Command Logs Manually
- Merging Command Logs Automatically
- Dynamically Modifying the CLOGMRG Parameter Setting

Merging Command Logs Manually

You can copy the dual or multiple command logs into a single sequential data set for a nucleus using the default ADARES CLCOPY function. Then, using the output from the CLCOPY execution as input, you can use the ADARES MERGE CLOG function to create a single cluster-wide command log containing, in chronological order, all Adabas commands executed by any of the cluster nuclei in the time period covered by the log:

ADARES MERGE CLOG NUMLOG=n

where n is the number of command logs to be merged, but not more than 32.

The ADARES MERGE CLOG function takes as input the sequential command log data sets/files from each of the cluster nuclei that were produced by running CLCOPY, merges them and copies the resulting command log data set from disk to a sequential data set.

Merging Command Logs Automatically

For accounting or other tracking purposes, you may want to automate the CLOG merge process. If you are using dual or multiple command logging, you set the ADARUN parameter <code>CLOGMRG=YES</code>, and if the correct user exit is available (user exit 2 for dual logs or user exit 12 for multiple logs), CLOGs are merged automatically as part of the CLCOPY process in much the same way that PLOGs are merged as part of the PLCOPY process. The ADARUN parameter <code>LOGGING=YES</code> must also be specified.

Existing CLCOPY jobs must be modified to include intermediate data sets/files. The sample CLCOPY job ADARESMC illustrates the necessary addition of the intermediate data sets/files.

When intermediate data sets/files are used for both PLCOPY and CLCOPY merge processes, the data set names must be unique so that they are not overwritten.

You can use the same exit for the CLOG merge process that is supplied for the PLOG merge process (see the sample exit USEREX2P or UEX12):

- When CLOGMRG=YES, use a single user exit 2 or user exit 12 for both PLOG and CLOG merging; both PLOG and CLOG data sets/files are dynamically allocated. Data sets/files specified in the user exit JCL are ignored.
- When CLOGMRG=NO (the default), CLOG data sets/files are *not* dynamically allocated and must be specified in the ADARES JCL; therefore, user exit 2 or user exit 12 must submit different CLCOPY jobs that are appropriate for the nucleus that calls the exit.

Note: If CLOGMRG=NO, you can manually merge CLOGs across a cluster.

Likewise, CLOG data sets/files with slightly modified names can be included in the user exit 2 or user exit 12 JCL used for other NUCIDs.

Dynamically Modifying the CLOGMRG Parameter Setting

The <code>CLOGMRG</code> parameter setting can be changed dynamically with the new operator command <code>CLOGMRG</code>, the new ADADBS OPERCOM CLOGMRG function, or with the Modify Parameters function of Adabas Online System.

CLOGMRG is a global (that is, cluster-wide) parameter. A change made to one nucleus is automatically propagated to all nuclei in the cluster.

Coordinated Log Switching

The log merge process (PLOG or CLOG) makes it necessary to coordinate the log switching process so that the merge process can copy as much data as possible without causing too many switches.

The first cluster nucleus that needs to switch logs (when a log is full or the FEOFPL command for PLOGs or the FEOFCL command for CLOGs has been issued) sends a broadcast message to the other nuclei in the cluster indicating that it is switching. It then goes on as normal, switching and calling the appropriate user exit.



Note: User exit 2 for dual logs or user exit 12 for multiple logs is recommended and is required if PLOGRQ=FORCE is set. If it is supplied to one nucleus in a cluster, it must be supplied to all the other nuclei. PLOGRQ must have the same setting across all nuclei in the cluster. If running with PLOGs, only dual or multiple PLOGs are allowed.

When a cluster nucleus receives the message that another nucleus is switching logs, it must decide if it will switch based on the current status of its current log and whether it has an available log data set:

- If it switches, it does so without calling user exit 2 (dual logs) or user exit 12 (multiple logs).
- If it does not switch, it forces a log write of the current block so that ADARES has as much data as possible.

ADARES briefly waits at the start to give all nuclei time to switch. If a nucleus does not switch logs, ADARES copies as much data as possible from the active log (partial merge).

This section covers the following topics:

Global FEOFPL and FEOFCL Commands

Global FEOFPL and FEOFCL Commands

The GLOBAL option has been added to both the ADADBS OPERCOM FEOFPL and FEOFCL commands:

- When the GLOBAL option is not specified, consideration is given to how full the PLOG or CLOG is before an attempt is made to switch them.
- When the GLOBAL option is specified, a log switch is forced for each nucleus in the cluster if there is an available log data set to write to. This may be useful in situations where all nuclei need to switch at the same time to capture all merged records in the output data set.

If a log data set to write to is not available, the switch does not occur even if GLOBAL has been specified. This functions the same way when the FEOFPL or FEOFCL command is issued for a single nucleus.

11 Parallel Participant Table (PPT)

Acquiring the PPT	34
Registering Nuclei during Session Initialization	
Registering PLOG, CLOG, and Work Data Sets for Each Nucleus	35
Nucleus Termination Processing	35
Using PPT Information	35
■ PPT Unavailable	
SBLKNUM Parameter for ADARES PLCOPY NOPPT	36

The parallel participant table (PPT), located in a database's Associator, tracks all active Adabas nuclei in the cluster. As each nucleus becomes active, it registers itself in the PPT. Each PPT entry can be modified by the nucleus or by ADARES.

This chapter covers the following topics:

Acquiring the PPT

The PPT is created by ADADEF for a new database or by ADACNV for an existing database.


Before you can run an existing Adabas database defined for Adabas version 7.1 or earlier with Adabas Parallel Services version 7.5, you must run ADACNV to convert the database to Adabas version 7.4. ADACNV accesses the free space table (FST) to acquire 32 contiguous blocks from the Associator and reserve them for the PPT.

ADACNV acquires 32 contiguous blocks in the Associator for each existing database and ADADEF acquires 32 contiguous blocks in the Associator for each new database. The location of the 32 contiguous blocks of Associator space is written to the general control block (GCB).

PPT blocks exist for both cluster nuclei and a single noncluster nucleus, eliminating the need to run the conversion process if switching from an Adabas cluster nucleus to an Adabas noncluster nucleus.

Registering Nuclei during Session Initialization

During session initialization as each Adabas cluster nucleus becomes active, it registers in the PPT based on the setting of its ADARUN NUCID parameter. The nucleus chooses the first of the 32 PPT blocks that is not yet assigned to another NUCID. If this is not the first run of this nucleus, the nucleus reuses its previously used PPT block. The relative block number of the chosen PPT block within the PPT (a number between 1 and 32) is called the *internal nucleus ID*.



Registering PLOG, CLOG, and Work Data Sets for Each Nucleus

Each active nucleus writes information to the Work, protection log (PLOG), and command log (CLOG) data sets that it is using for that session. The internal nucleus ID is also written to the PLOG records.

As each Work, PLOG, and CLOG data set becomes active, it is registered in the PPT. Information about these data sets is logged in the PPT entry of its nucleus.

When the PLOG or CLOG is merged, its PPT entry is updated with the information. ADARES and the cluster nuclei synchronize their PPT updates against one another to ensure that only one modification occurs at a time.

Work data set, protection log, and command log information remains in the PPT, even when CLOGs or PLOGs are merged or the session terminates.

Nucleus Termination Processing

If the nucleus terminates normally, the PPT entry is retained and marked as inactive. If a nucleus terminates abnormally, its entry in the PPT remains unchanged until the recovery process is complete.

Using PPT Information

The information about each Adabas nucleus maintained in the PPT is used when ADARES PLCOPY is copying and merging all active protection logs in the cluster.

It is also used during nucleus initialization to ensure that the data set/file information required for autorestart and PLOG merge is available:

- If the previously used Work data set or file and PLOG data sets or files are already in use by another nucleus, the nucleus will not start.
- If a different Work data set or file is provided and the original Work data set or file contains autorestart information, the nucleus will start but a warning will be printed.
- If different PLOGs or no PLOGs are provided and the previous session had PLOGs still to be copied, the nucleus will not start until those PLOGs have been copied/merged if PLOGRQ=FORCE is specified. If PLOGRQ=FORCE is not specified, the nucleus will start but a warning will be printed.

PPT Unavailable

In the case where the PPT becomes unavailable for some reason, the new parameter NOPPT is added to the ADARES PLCOPY function for emergency use. It specifies that the PPT is to be ignored and that the PLOG data sets of all cluster nuclei are to be taken from the JCL.

If you need to merge CLOGs while the PPT is unavailable, run a normal CLCOPY and then use the CLOG MERGE function to merge the sequential data sets.

SBLKNUM Parameter for ADARES PLCOPY NOPPT

The parameter SBLKNUM for the ADARES PLCOPY NOPPT function can be used in an emergency case when a last set of PLOGs must be copied and merged after the parallel participant table (PPT) in the Associator has been destroyed. In this case the ADARES utility does not know the last serial block number of the sequential PLOGs produced so far. By default, it starts numbering the blocks at 1 on the next sequential PLOG data set. If this sequential PLOG is concatenated to its predecessor in a REGENERATE function, ADARES would report an error in the PLOG block number sequence. The SBLKNUM parameter can be used to specify the correct starting block number for the sequential PLOG produced by the PLCOPY NOPPT function.

There are two ways to copy and merge the PLOGs when the PPT has been destroyed:

- 1. Without using the SBLKNUM parameter.
 - Run ADARES PLCOPY NOPPT, specifying all direct-access PLOG data sets of all cluster nuclei as DD/PLOGnn data sets for the ADARES utility. ADARES copies and merges the relevant PLOGs and produces a sequential PLOG data set starting with PLOG block number 1.
 - In case the database or individual files need to be restored and regenerated, run the regenerate in two (or more) job steps. The first REGENERATE should cover all sequential PLOGs produced by PLCOPY functions without the NOPPT parameter; these PLOGs may be concatenated into one sequential input. If the REGENERATE is performed with ET logic (REGENERATE database or with CONTINUE parameter), specify the NOAUTOBACKOUT parameter. The second REGENERATE should cover the sequential PLOG produced by the PLCOPY with NOPPT.
- 2. Using the SBLKNUM parameter:
 - Determine the highest PLOG block number written so far by the regular PLOG merge processes. This number can be determined from an up-to-date checkpoint listing, from an ADARAI LIST protocol, or from the job protocol of the most recent PLCOPY execution.
 - Run ADARES PLCOPY NOPPT, specifying all direct-access PLOG data sets of all cluster nuclei as DD/PLOGnn data sets for the ADARES utility. Specify the SBLKNUM parameter with value n+1, where n is the highest PLOG block number written so far, as determined in the

- previous step. ADARES copies and merges the relevant PLOGs and produces a sequential PLOG data set starting with the specified PLOG block number.
- In case the database or individual files need to be restored and regenerated, no special arrangements need to be made to run the REGENERATE in separate job steps.

12 Dynamic Allocation

If used, protection log and command log data sets and files for use in Adabas Parallel Services cluster environments are specified in the session startup JCL. Session initialization writes the log data set names to the PPT and ADARES uses dynamic allocation to access them.

The same is true of the Work data set or file: it is specified in the session startup JCL. Session initialization writes the Work data set or file name to the PPT and, in the event of an autorestart, a nucleus is able to access the Work data set or file of a peer nucleus using dynamic allocation.

Dynamic allocation is currently available only in cluster environments (when the NUCID is greater than zero). However, dynamic allocation is used by a noncluster nucleus to determine that the previous nucleus session was a cluster session and PLOGs or CLOGs remain to be copied.

This chapter covers the following topics:

JCL Considerations (OS/390 and z/OS Only)

Files that are eligible for dynamic allocation by another database must be cataloged, rather than being accessed using explicit UNIT and VOLSER keywords in the JCL. If JOBCAT or STEPCAT DD statements are used to define a catalog search structure, these statements must be used in a consistent way on all database start-up jobs in the cluster.

13 Components Summary

Component	Number
ADASVC(ADARER)/SVCCLU	One or more per operating system image
ADACOM	One or more per operating system image
PPT	One per cluster; located in the database Associator
Adabas DBIDs	One per cluster; a practically unlimited number per operating system image
global cache structures	One per cluster; specified in each nucleus
global lock structures	One per cluster; specified in each nucleus
Adabas nuclei	Up to 31 per cluster

3 Switching Between Cluster and Noncluster Modes / PLOG

Handling

Scenario 1	. 44
Scenario 2	
Scenario 3	

Switching from cluster to noncluster mode (or vice versa) is possible only after normal termination. A starting nucleus checks in the PPT whether the previous session ended abnormally with a pending autorestart. If this is the case and the previous nucleus ran in the same mode as the starting nucleus, the session autorestart logic will be executed. If the previous nucleus ran in a different mode than the starting nucleus, the session start will terminate with an error.

The following sections illustrate a few scenarios where a cluster nucleus starts after the normal termination of a noncluster nucleus. PLOGRQ is not set to FORCE. These scenarios apply to two PLOGs as well as up to eight PLOGs.

Scenario 1

The previous session was noncluster mode, there are remaining PLOGs to be copied, there is no UEX2/12 in use, and the PLOG data sets are different from what was used in the previous session. The results of this scenario are as follows:

- The information in the PPT entry of the noncluster nucleus remains, and the new entry of the cluster nucleus is written.
- Initialization continues.

Scenario 2

The previous session was noncluster mode, there are remaining PLOGs to be copied, there is no UEX2/12 in use, and the PLOG data sets are the same as what was used in the previous session of a noncluster nucleus. The results of this scenario are as follows:

- A warning that the PLOG is being overwritten will occur and the PLOG flag in the previously used PPT block will be reset or the PPT entry will be overwritten (whichever is appropriate).
- Initialization continues.

Scenario 3

The previous session was noncluster mode, there are remaining PLOGs to be copied, UEX2/12 is in use, and the PLOG data sets are different from what was used in the previous session of a noncluster nucleus. The results of this scenario are as follows:

■ UEX2/12 is called to submit a PLCOPY job that will copy and merge the PLOGs. The information in the PPT entry of the noncluster nucleus remains, and the new entry of the cluster nucleus is written.

- Initialization continues.
- **Note:** If ADARES detects that there is data to be copied both from a cluster nuclei and from a noncluster nucleus (different PLOGs), it will copy the oldest data first.

Adabas Parallel Services and Other Software AG Products

Adabas Online System	48
Adabas Caching Facility	
Adabas Delta Save Facility	48
Adabas Fastpath	49
Adabas Vista	49
Adabas SAF Security	49
Adabas Review	50
Adabas Transaction Manager	50

This chapter covers the following topics:

Adabas Online System

Adabas Online System communicates with all nuclei within an Adabas Parallel Services cluster and with all Adabas Parallel Services clusters on the operating system image. It includes functions related to Adabas Parallel Services.

Adabas Caching Facility

Software AG's Adabas Caching Facility can provide a performance boost to the Adabas cluster. It augments the Adabas buffer manager by reducing the number of read "execute channel programs" (EXCPs) to the database so that the available operating system facilities can be used without monopolizing valuable virtual memory resources.

Note: Write EXCPs are always issued to maintain the integrity of the database.

Under z/OS version 1.2 or above, Adabas Caching Facility provides support for 64-bit virtual storage.

Adabas Delta Save Facility

Software AG's Adabas Delta Save Facility (DSF) offers significant enhancements to ADASAV utility processing by backing up and restoring only the changed (delta) portions of Adabas databases. Version 7.4 and above support the Adabas Parallel Services environment.

DSF is intended for Adabas sites with one or more large, heavily updated databases that need to be available most of the time. Especially for sites where the volume of data changed on a day-to-day basis is considerably smaller than the total database volume, DSF provides for

- more frequent saves without interrupting database availability;
- enhanced "24 x 7 x 52" operation;
- full offline saving in parallel with the active database; and
- shorter REGENERATE duration during recovery.

Adabas Fastpath

Whenever possible, Adabas Fastpath reduces CPU consumption and increases throughput for Adabas systems by processing Adabas calls to completion in the client process. Database processing is thus avoided and capacity is increased for the whole operation.

Fastpath optimizes two types of database calls: direct access and sequential access. The results of direct access calls to the database are saved in a cache and repeat calls are satisfied from the cache rather than directly from the database. Read-ahead optimization routines are applied to sequences of commands to reduce redundant activity and thus accelerate the sequence.

Adabas Fastpath seamlessly optimizes database processing across multiple nuclei in one or more operating system images.

Adabas Vista

Adabas Vista is used to partition an Adabas file into multiple, separate files, each containing a part of the original larger whole. Partitioning makes it possible to distribute a file across multiple volumes or computers based on a criterion such as region or date. Adabas Vista is also used to translate Adabas database and file numbers, which allows an application to remain independent of the underlying physical layer.

Adabas Vista supports Adabas Parallel Services environments.

Adabas SAF Security

Adabas SAF Security enhances the scope of standard security packages based on the System Authorization Facility (SAF) such as RACF, CA-ACF2, and CA-Top Secret to encompass Adabas resources. It integrates Adabas into a central security repository and enables you to derive maximum benefit from your investment in that repository.

Adabas SAF Security adds protection for Adabas resources in Adabas Parallel Services environments.

Adabas Review

Adabas Review monitors the performance of Adabas environments and the applications executing within them. You can use information retrieved about Adabas usage when tuning application programs to achieve maximum performance with minimal resources.

Adabas Review supports Adabas Parallel Services version 7.4 and greater.

Adabas Transaction Manager

The Adabas Transaction Manager (ATM), a selectable unit of Adabas, is a server for coordinating "distributed transaction processing" (DTP) in distributed Adabas environments. It manages global transactions that are distributed across multiple Adabas databases by coordinating changes to the databases in a seamless, integrated way, using a two-phase commit protocol when necessary.

At any time, ATM can account for in-flight transactions, suspect transactions, participating databases, and more.

ATM addresses two basic needs of the enterprise object revolution:

- the need to deliver industrial strength enterprise objects for widespread commercial use in mainstream, critical business systems.
- the need to spread the masses of data that Adabas customers manage more evenly across the computer(s) and organization.

ATM includes an online administration system based on Natural and available through Adabas Online System.

ATM provides limited support for Adabas Parallel Services. For more information, read *Limited Distribution Transaction Support*, elsewhere in this chapter.

Restricted Support for Adabas Features

Triggers and Stored Procedures Facility	. 52
Limited Distributed Transaction Support	
User Table Cleanup	

This chapter describes facilities that are not supported for cluster nuclei running under Adabas Parallel Services or for which restricted support is provided.

The following facilities are supported normally for noncluster nuclei; however, for an Adabas cluster nucleus running in an Adabas Parallel Services environment, the following features are not available and cannot be specified:

- MODE=SINGLE
- sequential protection log (DDSIBA)
- synchronous buffer flush (LFIOP=0)

The following features are not currently supported for an Adabas cluster nucleus running in an Adabas Parallel Services version 7.4 environment, but will be supported in subsequent versions of the product:

- READONLY=YES (receives PARM ERROR 71 if attempted)
- UTIONLY=YES can be specified for a cluster nucleus; if you start cluster nuclei with conflicting settings of UTIONLY, the system will change them to conform to the setting of the first active nucleus. Currently, however, the UTIONLY setting cannot be changed using an ADADBS OPERCOM or Adabas Online System function. Once the cluster is started, the only way to change the UTIONLY setting is to bring down the whole cluster and restart it with a different setting.
- advance file lock (ALOCKF)
- two-phase commit processing (DTP=RM), but limited support (DTP=ET) for distributed transactions is available. Read *Limited Distributed Transaction Support*, elsewhere in this chapter, for more information.
- online reorder

Enhanced error recovery is supported; however, option changes are effective only for the local nucleus. TCP/IP direct links are supported; however, the IP address/port is tied to an individual nucleus.

Triggers and Stored Procedures Facility

The triggers and stored procedures facility (SPT) is fully supported in a cluster environment:

- The ADARUN SPT parameter is global and must be set the same on all active nuclei.
- When a REFRESH is executed, the trigger table is passed to all active nuclei.
- Only the first nucleus to initialize reads the trigger file to create the trigger table; all subsequent nuclei obtain the trigger table from one of the already active nuclei.

Limited Distributed Transaction Support

Adabas Parallel Services can in a limited way participate in distributed Adabas transactions coordinated by the Adabas Transaction Manager, as follows:

- In each distributed transaction, a single cluster database is allowed to participate. Different cluster databases can participate in different distributed transactions.
- All nuclei of a cluster database participating in distributed transactions must be run with the new ADARUN parameter setting DTP=ET.
- Cluster databases can participate in distributed transactions only if all resource managers involved in these transactions are Adabas databases running with DTP=RM. DTP=ET cannot be supported when an external transaction framework is included in the transaction (CICS/RMI or RRMS).

Full support by cluster databases for distributed transactions will be provided in a subsequent release of Adabas Parallel Services.

User Table Cleanup

The operator command and AOS function CLUFREEUSER is available for situations where leftover User Table Elements in common storage need to be cleaned up. This function deletes such User Table Elements according to specified criteria.

By default, the cluster nucleus receiving this function deletes all User Table Elements assigned to itself which it does not know of (i.e., for which it has no User Queue Elements). If the GLOBAL option is specified, all User Table Elements are deleted that are assigned to nuclei that are no longer active, or that have no associated User Queue Elements in their assigned nuclei. For more information about the User Table Cleanup, see *Maintain the User Table* in the *Adabas Parallel Services Reference Guide*.

17

Migration from ADASMP

All nuclei of an ADASMP cluster must be migrated to Adabas Parallel Services version 7.5 at one time. The Adabas ADACNV utility must be used to convert Adabas internal structures and all PLOGs must be reformatted before the Adabas Parallel Services version 7.5 nucleus is started.

It is not possible for a nucleus running ADASMP to participate in an Adabas Parallel Services version 7.5 environment. And the reverse: it is not possible for an Adabas Parallel Services version 7.5 nucleus to run in an ADASMP environment.

However, it is possible to run an ADASMP cluster in parallel with the Adabas router (SVC) from version 7.4. To this end, the SMPSVC mudle from the Adabas 7.4.2 load library must be linked to the router (ADASVC) and zap AH713018 must be applied to the ADASMP library.

18

ADARUN Parameter Terminology

If you used Adabas Support for Multiprocessing (ADASMP), you are familiar with the ADARUN parameter SMPID. This parameter has been replaced with the more general NUCID parameter that identifies nuclei for any type of Adabas cluster. You will need to make this change; the SMPID parameter has been removed and is no longer accepted.

The type of cluster as a Parallel Services cluster is identified by the new ADARUN parameter CLUSTER=LOCAL.

Other ADARUN parameters needed for use with Adabas Parallel Services begin with "CLU". In addition, the CLOGMRG parameter can be used to control automated CLOG merging across a cluster and the LRDP parameter can be used to size a *redo* pool that is required if deferred caching is used in the cluster environment.

All ADARUN parameters associated with Adabas cluster processing are documented in the *Adabas Operations Manual*.

19 Getting Started

ADACOM Starts	60
First Cluster Nucleus Starts	
Additional Cluster Nuclei	60

Nuclei start "open" to new users. To modify the status of nuclei throughout the cluster, read about the ADACOM command *SN* - *Set Nucleus Status* in the *Adabas Parallel Services Reference Guide*.

NUCIDs and DBIDs must have unique values in the range 1 through 65000.

This chapter covers the following topics:

ADACOM Starts

The ADACOM task must be run to set up the Adabas Parallel Services cluster environment before any cluster nucleus is started. ADACOM must be maintained in operation until the last cluster nucleus it manages is terminated.

A common storage area is allocated for maintaining information about active users and the nuclei to which they are assigned.

First Cluster Nucleus Starts

When a nucleus with a nonzero NUCID starts, it determines whether its ADACOM is running. If not, it will not start.

If its ADACOM is running, the first nucleus

- builds an ID table header (IDTH) element for the DBID, which marks the database as a cluster database. The DBID must be unique across the image in the range 1-65000. If LOCAL=NO is in effect, the DBID must be unique across all Entire Net-Work target IDs.
- sets an ID table entry (IDTE) to its NUCID in the nucleus table in CSA space to indicate that it is active. The NUCID must be unique across the image in the range 1-65000.

Additional Cluster Nuclei

If another nucleus for the same Adabas Parallel Services cluster comes up, the global DBID is already set and it sets its nucleus IDTE equivalent to its NUCID.

Index

_	Dynamic anocation, 40
A	G
Adabas Caching Facility	•
use in a cluster environment, 48	Global cache area and manager, 19
Adabas Fastpath, 49	
Adabas features	1
restricted support for, 52	·
Adabas Online System, 48	ID table
Adabas Parallel Services	entry, 14
migrating from ADASMP, 55	<i>,</i> ,
multiple thread processing, 5	1
parallel processing, 5	L
Adabas Review, 50	LBP
Adabas SAF Security, 49	ADARUN parameter, 19
Adabas Transaction Manager, 50	LFIOP
Adabas Vista, 49	ADARUN parameter, 19
ADACNV	Tibrikow parameter, 19
converting and existing database, 34	
ADACOM	M
definition, 12, 60	Mi 22
role in building a cluster, 12	Messaging services, 23
ADADEF	Migration
defining a new database, 34	from ADASMP, 55
ADARES	N.
merging logs, 29	N
ADASMP, 55	NHICID
Autorestart, 40	NUCID
	ADABAS OPERCOM function, 14
B	ADARUN parameter, 14
	Nuclei
Buffer pool and manager	role in building a cluster, 12
local, 19	Nucleus
	cluster
<u>C</u>	definition of, 5
9	resources shared by all nuclei, 12
CLOG	Nucleus cluster
activating, 30	defined, 14
merging, 30	_
synchronized switching, 31	Р
Cluster components, 12	DI OC
Conversion	PLOG
to Adabas Parallel Services, 34	merging, 29
	requirements, 28
ח	synchronized switching, 31
	PPT
Database	definition, 34
single physical	
defined, 5	

S

SVC

for cluster environments, 14

T

Triggers and stored procedures restricted support for, 52

U

Update nucleus function, 14 User assigning to a nucleus, 9