INatAutoResultViews INatAutoResultViews

# **INatAutoResultViews**

This chapter covers the following topics:

- Purpose
- Properties
- Methods

# **Purpose**

Collection of the currently open result views.

# **Properties**

The following properties are available:

- Parent
- Studio
- Count

## **Parent**

Used to navigate to the parent interface of this interface.

Natural Data Format	Variant Type	Remark
HANDLE OF OBJECT	VT_DISPATCH (INatAutoStudio)	Get only

## **Studio**

Used to navigate to the root interface.

Natural Data Format	Variant Type	Remark
HANDLE OF OBJECT	VT_DISPATCH (INatAutoStudio)	Get only

# **Count**

The number of currently open result views.

Natural Data Format	Variant Type	Remark
I4	VT_I4	Get only

INatAutoResultViews Methods

# **Methods**

The following methods are available:

- Item
- Show
- Open

## **Item**

Returns a specific plug-in defined result view from the collection.

#### **Parameters**

Name	Natural Data Format	Variant Type	Remark
Return value	HANDLE OF OBJECT	VT_DISPATCH (INatAutoResultView)	
Index	I4	VT_I4	

#### **Return value**

The result view identified by the value specified in Index. If the result view was not defined by a plug-in, the method returns NULL-HANDLE.

#### Index

The index of the result view in the collection (a value between 1 and Count).

## **Show**

Shows or hides the entire result view control bar. This corresponds to checking or unchecking the View/Results command in the Natural Studio menu.

#### **Parameters**

Name	Natural Data Format	Variant Type	Remark
Show	L	VT_BOOL	Optional

#### **Show**

Decides if the result view control bar is shown or not. The default is TRUE.

# **Open**

Opens a new result view.

Open INatAutoResultViews

#### **Parameters**

Name	Natural Data Format	Variant Type	Remark
Return value	HANDLE OF OBJECT	VT_DISPATCH (INatAutoResultView)	
Caption	A	VT_BSTR	
Image	A HANDLE OF OBJECT	VT_BSTR VT_DISPATCH	Optional
Headers	A	VT_BSTR	Optional

#### **Return value**

The newly opened result view.

#### **Caption**

The caption to be displayed on the result view tab.

### **Image**

An image to be displayed on the result view tab. The image must be a 16 color, 16x16 bitmap, using RGB(192,192,192) as the background color.

The image can be specified in two ways:

- As an absolute path name of a .bmp file.
- As an IPictureDisp interface. An IPictureDisp interface can be created in Natural using the method INatAutoImages::LoadImage. An IPictureDisp interface cannot be passed across process boundaries. This is due to a Microsoft restriction (MSDN Q150034). Therefore this alternative can only be used with plug-ins running as in-process servers. Natural written plug-ins always run as local servers and can therefore not use this alternative.

#### **Headers**

Defines the attributes of the nodes to be displayed in the result view and their respective captions. It contains the attribute definitions as an XML document according to the DTD used with the method INaturalStudioPlugInTree::GetAttributes.