



Natural für Windows

Web Technology

Version 6.3.8 für Windows

Februar 2010

Natural

Dieses Dokument gilt für Natural ab Version 6.3.8 für Windows.

Hierin enthaltene Beschreibungen unterliegen Änderungen und Ergänzungen, die in nachfolgenden Release Notes oder Neuauflagen bekanntgegeben werden.

Copyright © 1992-2010 Software AG, Darmstadt, Deutschland und/oder Software AG USA, Inc., Reston, VA, Vereinigte Staaten von Amerika, und/oder ihre Lizenzgeber..

Der Name Software AG, webMethods und alle Software AG Produktnamen sind entweder Warenzeichen oder eingetragene Warenzeichen der Software AG und/oder der Software AG USA, Inc und/oder ihrer Lizenzgeber. Andere hier erwähnte Unternehmens- und Produktnamen können Warenzeichen ihrer jeweiligen Eigentümer sein.

Die Nutzung dieser Software unterliegt den Lizenzbedingungen der Software AG. Diese Bedingungen sind Bestandteil der Produkt-dokumentation und befinden sich unter <http://documentation.softwareag.com/legal/> und/oder im Wurzelverzeichnis des lizenzierten Produkts.

Diese Software kann Teile von Drittanbieterprodukten enthalten. Die Hinweise zu den Urheberrechten und Lizenzbedingungen der Drittanbieter entnehmen Sie bitte den "License Texts, Copyright Notices and Disclaimers of Third Party Products". Dieses Dokument

ist Bestandteil der Produktdokumentation und befindet sich unter <http://documentation.softwareag.com/legal/> und/oder im Wurzelverzeichnis des lizenzierten Produkts.

Inhaltsverzeichnis

1 Web Technology	1
2 Natural Web Interface	3
3 Introducing the Natural Web Interface	5
What is the Natural Web Interface	6
Architecture	6
Natural Web Interface Modules	9
Features	10
Functionality	11
Security	12
4 Natural Web Interface Installation and Configuration	15
5 Configuring the Natural Web Interface	17
Supported HTTP Servers	18
Configuring RPC and RPC Server	18
Configuring the DCOM Server	20
Configuring the Web Interface	20
Configuring an HTTP Server	24
Communication with Natural Security	25
6 Web Interface Troubleshooting	27
7 Natural Web Interface Essentials	29
8 Working with the Natural Web Interface	31
Setting up your Environment	32
Building Subprograms in Natural	33
9 Natural Web Server Extensions	49
10 Natural Web Server Extensions - Introduction for SYSWEB	51
General Information	52
Installation - RPC / DCOM	52
Transformations	53
Variables	53
Error Logging and Messages	53
Calling Programs	53
11 Natural Web Server Extensions - Introduction for SYSWEB3	55
General Information	56
Installation - RPC / DCOM	56
Transformations	57
Variables	57
Error Logging and Messages	57
Calling Programs	58
12 Natural Web Server Extensions - Initialization File	59
General Information	60
RPC Parameters	60
PAL Parameters	61
DCOM Parameters	61
Natural Web Server Extension Settings	61

Data Transfer Settings	64
HTTP Server Variables	65
Additional Variables	65
Error Templates	65
13 Natural Web Server Extensions - Error Messages	69
14 Test Utility WEB-ONL with SYSWEB	73
Prerequisites	74
Running the Application	74
Supported Content Types	75
Input/Output Fields	76
15 Test Utility WEB-ONL3 with SYSWEB3	79
Prerequisites	80
Running the Application	80
Supported Content Types	81
Input/Output Fields	82
16 Programming Tips	85
Editing in Lower Case	86
Quote vs. Apostrophe	86
Variables defined by Value	87
Access to Resources	87
Constant Values	87
Creating a New Page	88
DCOM / RPC	88
17 Web Interface Administration	89
Set the Size of the Return-Page Transport Buffer	90
Create a User-Defined Error Page	91
Create a User-Defined Error Page XML-Style	91
Alphanumeric-to-HTML Conversion	92
Alphanumeric-to-URL Conversion	92
18 Demonstration Application - without JavaScript	93
Business Requirements	94
Design Decisions	95
Libraries, Modules and Naming Conventions	95
Starting the Demonstration Application	96
Starting the Natural Web Interface Online Manual	96
Requirements	96
19 Demonstration Application - with JavaScript	97
Business Requirements	98
Design Decisions	99
Starting the Demonstration Application	99
Requirements	99
20 Natural Web Interface Error Messages	101
Error Messages	102
21 Migrate Natural Web Interface SYSWEB to SYSWEB3	103
22 Web Interface Plug-In	105

Before You Start	106
Invoking Web Interface Plug-In Commands	106
Web Interface Plug-In Functions	107
23 Natural Web Online Documentation SYSWEB	131
General Information	132
Basic Modules	132
Template / XSLT Processing	134
HTML Extension	134
Utilities	136
Demonstration Applications	136
24 Clear Output Area	139
25 Set Document Content-Type	141
26 Count Size of Output Area	143
27 Generate Error Page	145
28 Writes to the Document and Converts to Valid HTML	147
29 Writes HTTP Settings to the Document	149
30 Info About Internal Values	151
31 End and Initialize Document	153
32 List All Environment Variables	155
33 Set Document Location	157
34 Read Environment Variable	159
35 Read Environment Variables Groups	161
36 Read Environment Text Area Variables	163
37 Write Text to Document	165
38 Write Newline to Output Area	167
39 Text to HTML	169
40 Text to XML	171
41 Text to URL	173
42 Replace Inside Return Document	175
43 Load Resource	177
44 Read Resource	179
45 Write Resource	181
46 Check Resource	183
47 Delete Resource	185
48 Apply XSLT Processing on Return Document	187
49 Apply XSLT Processing on Return Document from Resource	189
50 Load Style Sheet from the Resource Directory and Apply XSLT Processing on Return Document	191
51 Read Output Page	193
52 Anchor	195
53 Button	197
54 Checkbox Group	199
55 Comment Line	201
56 Level n Header	203
57 Image	205

58 Input	207
59 Line Break	209
60 Form	211
61 HTML Document	213
62 List	215
63 Paragraph	219
64 Radio Button Group	221
65 Horizontal Rule	223
66 Scrolling List	225
67 Table	227
68 Universal Tag	231
69 Text Area	233
70 Text to URL - Decoded	235
71 Time/Date String	237
72 List all Natural Libraries	239
73 Run Online Natural Web Interface Subprograms	241
74 Generate Natural Subprogram to use with Natural Web Interface	243
75 List Directory of a Natural Library	245
76 List All Parameters Passed From a HTTP Server To a Called Natural Subprogram	247
77 Return an HTML Page Saved as Natural Source Object	249
78 List the Current Natural Web Interface Settings	251
79 List Source of Natural Object	253
80 Online Documentation	255
81 List non-Natural File - Resource	257
82 Natural Web Online Documentation SYSWEB3	259
General Information	260
Basic Modules	260
Template / XSLT Processing	262
HTML Extension	263
Utilities	264
Demonstration Applications	265
83 Writes Binary to the Document	267
84 Clear Output Area	269
85 Set Document Content-Type	271
86 Count Size of Output Area	273
87 Generate Error Page	275
88 Writes to the Document and Converts to Valid HTML	277
89 Writes HTTP Settings to the Document	279
90 Info About Internal Values	281
91 End and Initialize Document	283
92 List All Environment Variables	285
93 Evaluate Mime-Type and Transfer/Data-Type	287
94 Evaluate Mime-Type and File Extension	289
95 Set Document Location	291

96 Read Environment Variable	293
97 Read Environment Variables Groups	295
98 Read Environment Text Area Variables	297
99 Write Text to Document	299
100 Write Newline to Output Area	301
101 Read Natural Source into X-Array of Dynamic	303
102 Text to HTML	305
103 Text to XML	307
104 Text to URL	309
105 Replace Inside Return Document	311
106 Load Resource	313
107 Read Resource	315
108 Write Resource	317
109 Check Resource	319
110 Delete Resource	321
111 Apply XSLT Processing on Return Document	323
112 Apply XSLT Processing on Return Document from Resource	325
113 Load Style Sheet from the Resource Directory and Apply XSLT Processing on Return Document	327
114 List Resource Files	329
115 Read Input Page	331
116 Read Output Page	333
117 Anchor	335
118 Button	337
119 Checkbox Group	339
120 Comment Line	341
121 Level n Header	343
122 Image	345
123 Input	347
124 Line Break	349
125 Form	351
126 HTML Document	353
127 List	355
128 Paragraph	359
129 Radio Button Group	361
130 Horizontal Rule	363
131 Scrolling List	365
132 Table	367
133 Universal Tag	371
134 Text Area	373
135 Text to URL - Decoded	375
136 Time/Date String	377
137 List all Natural Libraries	379
138 Run Online Natural Web Interface Subprograms	381
139 Generate Natural Subprogram to use with Natural Web Interface	383

140 List All Data Passed From a HTTP Server to a Called Natural Subprogram	385
141 List Directory of a Natural Library	387
142 List Resources of a Natural Library	389
143 List All Parameters Passed From a HTTP Server To a Called Natural Subprogram	391
144 Return an HTML Page Saved as Natural Source Object	393
145 List the Current Natural Web Interface Settings	395
146 List Source of Natural Object	397
147 Online Documentation	399
148 List non-Natural File - Resource	401
149 XML Toolkit Plug-In	403
150 Introduction	405
XML Toolkit Features	406
XML Toolkit Description	406
Considerations and Limitations	410
151 Using the XML Toolkit	415
Invoking the Application	416
Getting Help	416
152 Setting up Specific Generation Options	417
Invoking the Natural XML Options Menu	418
Generation	418
Path	422
Saving Your Options Permanently	423
153 Using a Natural Data Source	425
Select Natural Data Area	426
Select Data Type	428
Generate File with DTD Definition or XML Schema	429
Generate a serializer for an XML document	431
Generate a parser for an XML document	432
Parameter Settings	433
Select Root Group	434
Show Generation Report	435
154 Using an external Data Source	437
Generate from Document Type Definition or XML Schema	438
Select Root Element or Document Type	440
Select Recursion Level	440
Generate Natural Data Area	442
Generate Copycode for Serialization	443
Generate Subprogram for Serialization	445
Generate Copycode for XML Parser Callback	445
Generate Subprogram for XML Parser Callback	447
Show Generation Results	447
155 Natural Simple XML Parser	449
Parser Description and Example	450
Parser Restrictions	457

156 Examples	459
Serialize Copycode	460
Serialize Subroutine	462
Generated Natural Data Area	470
Natural DTD Parser	472
Generated Type Definition	473
Parser CALLBACK Copycode	474
157 Parser Error Messages	479

1 Web Technology

This documentation provides an overview of the Natural web technologies and a short summary of their functions.

The following topics are covered:

	Natural Web Interface	The Natural Web Interface is a link between a Web Server (HTTP server) and your Natural environment.
	Web Interface Plug-In	The Web Interface plug-in is an optional plug-in unit for Natural Studio.
	XML Toolkit Plug-In	The XML Toolkit plug-in enables developers to process XML documents within Natural.

For further details on the Natural statements that can be used together with Natural's web technologies, please refer to Statements Grouped by Functions > Internet and XML in the *Statements documentation*.

2 Natural Web Interface

The Natural Web Interface is a link between a Web Server (more precisely: HTTP server) and your Natural environment.

The Natural Web Interface documentation comprises the following documents:

- [Introducing the Natural Web Interface](#)
 - [Natural Web Interface Installation and Configuration](#)
 - [Natural Web Interface Essentials](#)
 - [Migrate Natural Web Interface SYSWEB to SYSWEB3](#)
 - [Natural Web Online Documentation SYSWEB](#)
 - [Natural Web Online Documentation SYSWEB3](#)
-  **Note:** For compatibility reasons, the new Natural Web Interface SYSWEB3 and the previous version SYSWEB are delivered with Natural. The Natural Web Interface documentation applies to both versions of the Natural Web Interface unless mentioned otherwise.

3 Introducing the Natural Web Interface

■ What is the Natural Web Interface	6
■ Architecture	6
■ Natural Web Interface Modules	9
■ Features	10
■ Functionality	11
■ Security	12

More and more organizations need to offer information or services via the Internet. Gone are the days where static HTML pages were sufficient for the daily visitors to a web page. Today, increasingly sophisticated HTML pages are competing in the web, and the demand for full access to business logic via the Internet is increasing tremendously. The database management systems containing business-critical information are mostly based on heavy-duty servers like mainframes.

This section covers the following topics:

What is the Natural Web Interface

The Natural Web Interface is a link between a Web Server (more precisely: HTTP server) and your Natural environment. This can be on a separate server machine (such as a mainframe) or on the same machine as the HTTP server (e.g. Apache or Microsoft IIS).

Contents of web pages can easily be created dynamically by a Natural program. This is a basis for implementing a real interactive application on the web.

An interactive application enables users to input information and react by issuing output depending on that input. Examples of Web-based applications are order entry systems, travel booking services and parcel tracking systems. This considerably increases the scope of Natural applications. Not just in-house users, but also potential customers all over the world can now use the same application.

And best of all: to implement such an application, Natural users do not have to learn a new programming language. Navigation and user input/output are implemented fully in Natural (with some additional embedded HTML statements).


Architecture

The following topics are covered:


- [Communication Using Natural RPC Techniques](#)
- [Communication Using DCOM Techniques](#)

- Communication Using PAL Techniques


Communication Using Natural RPC Techniques



Communication Using DCOM Techniques



Communication Using PAL Techniques



Natural Web Interface Modules

The Natural Web Interface comprises three internal modules:

1. **Natural Web Interface**
the HTML API and the HTTP API of Natural
2. **Natural Web Server Extensions**
the part which provides the interface to the web server on the same machine
3. **Necessary middleware**
EntireX Communicator including EntireX Broker using RPC, PAL or DCOM technology

Features

Calling Natural Subprograms from a Web Page

One of the main features of the Natural Web Interface is, that Natural subprograms can be called from a web page. This can be done using forms on a web page that contain input fields and buttons. Users can enter data and submit these data by clicking one of the buttons. This executes a Natural subprogram which passes the user data as parameters.

This allows easy access to application functions (= subprograms). Simple database access for retrieving data using SQL (and an ODBC driver) as offered by most Web Servers is not enough for implementing an interactive application. You also need business logic to ensure data consistency and processing of the user data.

Business logic such as consistency and plausibility checks usually already exist, as they were implemented for operational applications in the past. If they were implemented as separate Natural modules (such as subprograms, programs, or subroutines) they can easily be re-used and do not have to be re-implemented in a different environment or different language.

Therefore, no special interface program has to be written to connect the web server with the business functions. The Natural Web Interface is a standardized interface for that purpose.

No programming language has to be learned and existing skills can be leveraged (except for HTML statements to format the output pages).

Feedback to the User with a Formatted Web Page

The second important part of an interactive application on the web is the feedback to the user with formatted web pages. With Natural Web Interface these web pages can be formatted dynamically according to the application's needs.

A benefit is that the control of layout and contents of these pages is fully at the application/program level, not outside in separate directories.

And also: as Natural can gather data and information from a wide variety of sources (Adabas, RDBMSs, sequential files, even system information with Entire System Server) the type of application is virtually unlimited - any application you can build with Natural you can integrate with the web.

Proven Middleware

The Natural Web Interface is based on the proven set of middleware products from Software AG: the Entire product family.

This allows seamless integration in an existing client/server environment. The web connection is just another client, which can be connected to existing Natural servers. If Entire Net-Work is installed, you do not need to install another set of middleware products.

On Natural for Windows, the interface can call Natural DCOM classes. The methods called, with a specific interface, can map to the same subroutines used through remote procedure call (RPC).


Web Page Creation

Web pages can be created with standard tools (e.g. Macromedia Dreamweaver or Microsoft Frontpage) or with the web page creation tool using the Natural generation functionality. From the Natural server, subprograms can be generated. There is no need to acquire knowledge about any other programming language or web-page creation tool.

Functionality

Requests from a web page in the user's browser are passed to the web (or HTTP) server. Provided that this was a form requesting execution of a Natural subprogram, this request is then passed to the Natural Web Server Extensions part which executes the Natural subprogram via EntireX RPC, PAL or DCOM. The program takes any user data as parameters and then issues a set of programs to provide the feedback to the user.

The following diagram illustrates how the Natural subprograms are called from an HTML browser. Each stage of the process is identified by a number; what happens at these stages is explained below.



1. HTML Browser Requests URL.

Your browser requests a URL identifying the program you want to call on the server side.

2. Web Server calls the Natural Web Server Extension CGI.

The web server takes the URL and calls Natural Web Server Extensions.

3. Natural Web Server Extension converts the call to RPC.

The Natural Web Server Extension program "translates" the URL into a Natural RPC that invokes the Natural server program originally identified by the URL.

4. Natural subprogram is executed and generates a return page.

The Natural subprogram on the server is executed and generates an HTML return page.

5. Return Page is sent back to the Natural Web Server Extension.

The HTML return page is sent back as response of the subroutine call.

6. Natural Web Server Extension sends back the return page to the Web Server.

The Web Server adds header information and sends it to the browser.

7. The browser receives the answer to what it was sent out as a request for an URL.



Note: In the context of the Natural Web Interface, only external subroutines can return output.

Security

Pages called via Natural Web Interface can work together with Natural Security. This is accomplished as follows:

- First your Natural Web Server Extension has to be defined as restricted page at your HTTP server.

- If this is done, you will be prompted for user ID and password by your browser if you request a page.
- The HTTP server will now verify the given data with its database.
- If the user is authorized, Natural Web Server Extension is called with the remote user's name.
- If the Natural RPC server is started with Natural Security, the given name will be set as *USER.
- As an authentication is already done by the HTTP server, no password checking will be done on the Natural side. Therefore, the Natural RPC server has to be started with AUTO=ON.

A second scenario is that when the initialization file is started, a specific, fixed, defined user ID and password is set to communicate with a Natural RPC server with Natural Security. See also [Communication with Natural Security](#).

4 Natural Web Interface Installation and Configuration

The Natural Web Interface is installed in the course of the Natural for Windows installation procedure.

-  **Note:** Only during the custom installation it is possible to install the Natural Web Interface. There you can specify the Natural Web Server Extensions you prefer.

Refer to the section *Setup Type* in the *Natural for Windows Installation documentation* for further details.

This document contains the following sections:

-  **Configuring the Natural Web Interface** Describes how to configure the Natural Web Interface. If you are not familiar with a specific product, please read the corresponding installation instructions for more information.
-  **Troubleshooting** Provides hints for known problems.

5 Configuring the Natural Web Interface

■ Supported HTTP Servers	18
■ Configuring RPC and RPC Server	18
■ Configuring the DCOM Server	20
■ Configuring the Web Interface	20
■ Configuring an HTTP Server	24
■ Communication with Natural Security	25

This section provides information on how to configure the Natural Web Interface. If you are not familiar with a specific product, refer to the corresponding product documentation for more information.

This section covers the following topics:

The latest documentation updates are published on Software AG's documentation site:
<http://documentation.softwareag.com>.

Supported HTTP Servers

Operating System	HTTP Server
Windows (Intel)	<ul style="list-style-type: none">■ Microsoft Internet Information Server Version 5.0/6.0■ Apache Version 2.0.x■ Apache Version 2.2.x
(*)	<ul style="list-style-type: none">■ Apache Version 2.0.x■ Apache Version 2.2.x

Configuring RPC and RPC Server

In the following configuration description, ETB255 is the name of a Broker and NATWEB1 the name of an RPC Server used for the examples.

For the installation and configuration, refer to the Natural RPC, *Entire Net-Work*, and *EntireX Communicator* documentation.

The following topics are documented below:

- General RPC Configuration Setting for All Platforms using SYSWEB3
- Current Version of Natural for Mainframes, UNIX or Windows

- EntireX Communicator / EntireX Developer's Kit

General RPC Configuration Setting for All Platforms using SYSWEB3

ACIVERS Settings

You are recommended to set the profile parameter ACIVERS to a value of 6 or above. Refer to Set the ACI Version in the Natural RPC documentation for further details.

MAXBUFF and MAX-MESSAGE-LENGTH Settings

You are recommended to set the profile parameter MAXBUFF on the Natural RPC server to a value of 1024 or above. This also requires setting the value of MAX-MESSAGE-LENGTH to 1048576 or above on the EntireX Broker that is included in EntireX Communicator.

Current Version of Natural for Mainframes, UNIX or Windows

On Windows and UNIX Systems using SYSWEB

To change your NATPARM file so that two additional steplibs can be accessed in the RPC environment:

- In the *Natural Execution Configuration* parameter group, add the two steplibs SYSWEB and SYSEXT to the steplib parameter subsection.

On Windows and UNIX Systems using SYSWEB3

To change your NATPARM file so that two additional steplibs can be accessed in the RPC environment:

- In the *Natural Execution Configuration* parameter group, add the two steplibs SYSWEB3 and SYSEXT to the steplib parameter subsection.

In a Mainframe Environment using SYSWEB

If Natural Security is installed:

- Define the steplibs SYSWEB and SYSEXT for your library.

If Natural Security is **not** installed:

- Modify the Natural program WEB-STLB in library SYSWEB by entering the DBID and file number of the associated FNAT system file of the libraries SYSWEB and SYSEXT. If required, you can add additional steplibs.
- STOW the program.
- The STACK parameter for your RPC server should have the following value: STACK=(LOGON SYSWEB;WEB-STLB)

EntireX Communicator / EntireX Developer's Kit

On Windows Systems

Setting the environment variables is not required.

On UNIX (All Platforms)

All EntireX-relevant environment variables must be passed by the HTTP server.

Configuring the DCOM Server

To install and configure the DCOM server, proceed as described in the NaturalX documentation.

In the following configuration description, NATWEBEXT is the name of an external DCOM Server and NATWEB is the name of a local DCOM Server.

This section covers the following topics:

- [NaturalX Server](#)

NaturalX Server

For all servers supporting the Natural Web Interface, add the libraries SYSWEB3 (or SYSWEB) and SYSEXT as steplibs, as described above in the section [Current Version of Natural for Mainframes, UNIX or Windows](#).

Configuring the Web Interface

The following topics are covered below:

- [Natural Web Interface](#)
- [Natural Web Server Extensions for RPC](#)
- [Natural Web Server Extensions for DCOM](#)

- Natural Web Server Extensions for MOD

Natural Web Interface

For mainframe, Windows and UNIX environments no configuration is required.

Natural Web Server Extensions for RPC

Adjust the configuration file using an external editor:

```
RPC_ETB_ID_NAME=ETB255  
RPC_SERVER_NAME=NATWEB1
```

With a Natural RPC Server Running in a non-ASCII Environment

The parameter `NWW_OUT_CSS_TRANSLATE` must be set in the Configuration File. Its value depends on the code page used.

Natural Web Server Extensions for DCOM

Local DCOM (All Platforms)

No adjustments are required for local communication.

External DCOM (All Platforms)

For external communication, see the NaturalX documentation for registry changes, or adjust the configuration file using an external editor:

```
DCOM_SERVER_NAME=NATWEBEXT
```

On Windows (Internet Information Server)

If you use the Internet Information Server, the username for anonymous logon, e.g. NATWEB, is used. NATWEB must belong to the group USER, or the GUEST account must be enabled.

On Windows (Apache)

If you use the Apache Server, the default settings for User/Group specified at httpd.conf can be used:

User/Group: The name (or # number) of the user/group to run httpd as User nobody Group #-1

Natural Web Server Extensions for MOD

 **Note:** This section applies to SYSWEB3 only.

- Using an RPC Server
- Using a DCOM Server
- Using a SPoD Server

Using an RPC Server

1. Install the Natural Web Server Extensions
2. Open the ..\conf\httpd.conf file of the HTTP Server and add the the following new lines for the RPC Interface:

For Apache 2.0.x

```
...
LoadModule nww3_module modules/nww3mod2.dll
<Location /nww3/mod>
    AllowOverride None
    NWWiniFile "<yourRoot>/nww3/nww3mod.ini"
    SetHandler nww3
</Location>
...
```

For Apache 2.2.x

```
...
LoadModule nww3_module modules/nww3mod22.dll
<Location /nww3/mod>
    AllowOverride None
    NWWiniFile "<yourRoot>/nww3/nww3mod.ini"
    SetHandler nww3
</Location>
...
```

3. Specify additional files at the /nww3 directory, if not only one service or broker are to be used.

4. If a static read of the .ini file is wanted (this influences the performance), add the line shown in *italics* to your obj.conf.

Using a DCOM Server

1. Install the Natural Web Server Extensions.
2. Open the ..\conf\httpd.conf file of the HTTP Server and add the the following new lines for the DCOM Interface:

For Apache 2.0.x

```
...
LoadModule nww3d_module modules/nww3dmod2.dll
<Location /nww3d/mod>
  AllowOverride None
  NWWiniFile "<yourRoot>/nww3d/nww3dmod.ini"
  SetHandler nww3d
</Location>
...
```

For Apache 2.2.x

```
...
LoadModule nww3d_module modules/nww3dmod22.dll
<Location /nww3d/mod>
  AllowOverride None
  NWWiniFile "<yourRoot>/nww3d/nww3dmod.ini"
  SetHandler nww3d
</Location>
...
```

3. Specify additional files at the /nww3d directory, if not only one service or broker are to be used.
4. If a static read of the .ini file is wanted (this influences the performance), add the line shown in *italics* to your obj.conf.

Using a SPoD Server

1. Install the Natural Web Server Extensions.
2. Open the ..\conf\httpd.conf file of the HTTP Server and add the the following new lines for the SPoD (PAL) Interface:

For Apache 2.0.x

```
...
LoadModule nww3p_module modules/nww3pmod2.dll
<Location /nww3p/mod>
    AllowOverride None
    NWWiniFile "<yourRoot>/nww3p/nww3pmod.ini"
    SetHandler nww3p
</Location>
...
```

For Apache 2.2.x

```
...
LoadModule nww3p_module modules/nww3pmod22.dll
<Location /nww3p/mod>
    AllowOverride None
    NWWiniFile "<yourRoot>/nww3p/nww3pmod.ini"
    SetHandler nww3p
</Location>
...
```

3. Specify additional files at the /nww3p directory, if not only one service or broker are to be used.
4. If a static read of the .ini file is wanted (this influences the performance), add the line shown in *italics* to your obj.conf.

Configuring an HTTP Server

Windows (Internet Information Server 5.0 and 6.0)

If you use the Internet Information Server, the username for anonymous logon, e.g. !USR_NATWEB, is used. !USR_NATWEB must belong to the group USER, or the GUEST account must be enabled.

Communication with Natural Security

The new version of the EntireX Developer's Kit supports the usage of two passwords and user IDs.

The first user ID is used to get access through EntireX Security and the second for Natural Security.

The HTTP Server Security is involved as a third security system.

HTTP Server Security

Restrict the access of the NWW interface at your HTTP Server. For details, refer to your HTTP server documentation.

EntireX Security

In the configuration file the `NWW_USER_ID` and `NWW_PASSWORD` have to be specified.

Natural Security

A second User ID/Password (`RPC_USER_ID`, `RPC_PASSWORD`) has to be set.

If the parameter `USE_REMOTE_USER` is activated, the `RPC_USER_ID` will be set/overwritten. The `RPC_PASSWORD` remains unchanged.

It is necessary to set up Natural Security with "AUTO=ON" to pass security without password. If no `RPC_USER_ID`/`RPC_PASSWORD` pair is set, the `NWW_USER_ID`/`NWW_PASSWORD` will be used to ensure compatibility with the existing implementation.

6 Web Interface Troubleshooting

This section provides information on known problems:

Error	Description	Recommended Action
NWW0003 .ini File not found.	NWW initialization file not found.	<p>Check your server extension initialization file:</p> <ul style="list-style-type: none">■ It has to have the same name as the executable with the extension .INI■ The server extension initialization file has to be placed at the same directory as the server extension executable.■ If the server extension can be started from the command prompt and does not run when called by the HTTP Server, check whether the .INI file can be found if it is copied to the same directory your HTTP server is started from.
NWW0011 ERX error 00000000 occurred. Severity = Success Message:... 9999 NAT0935 Conflicting number of parameters (Subprogram...). Lib=... Pgm=D3MENU.	Wrong suprogram called, or wrong Steplib used	<p>Check your Call:</p> <ul style="list-style-type: none">■ Check if the called subprogram uses the parameter data area W3PARM.■ Check if the RPC Server uses the Steplib SYSWEB if called from a nww* interface.■ Check if the RPC Server uses the Steplib SYSWEB3 if called from a nww3* interface.■ Check if the called program is compiled with the correct SYSWEB/SYSWEB3 Library - Call NAT-DIR (see docu) to see

Error	Description	Recommended Action
		what interface has been used during compile time.
NWW0011 ERX error 80010014 occurred. Severity = Error Facility = 65536 Returncode = 20 Subfacility = 3 Location = 0 Message: ERX_E_SERVICE_NOT_AVAILABLE - ETB error code 00070007	Natural RPC Server not started/found.	Check your RPC Server: <ul style="list-style-type: none"> ■ Start your Natural RPC Server. ■ or check your RPC_SERVER_NAME at the NWW initialization file.
NWW0011 ERX error 80010014 occurred. Severity = Error Facility = 65536 Returncode = 20 Subfacility = 3 Location = 0 Message: ERX_E_SERVICE_NOT_AVAILABLE - ETB error code 02150148	Broker not started/found.	Check your Broker: <ul style="list-style-type: none"> ■ Start your Broker and Natural RPC Server. ■ or check your RPC_SERVER_NAME and RPC_ETB_ID at the NWW initialization file.
Processing of subprogram TEST in library W3RPCDMO failed. Message: Status = O, Library = W3RPCDMO, Program = NATSRVD , Level = 01, Error = 00082, Line = 4190 Subfacility = 255 Location = 0	The program you have called does not exist or is not accessible. At the moment it is not possible to switch dynamically the Natural libraries.	Check your Natural: <ul style="list-style-type: none"> ■ Does the program really exist? ■ If the program exists, check your logon library or the steplibs or your NATPARM if the given library is included.
Natural RPC Server crash. Test with WEB-ONL on the same subprogram gets: WEB-ONL 1420 NAT0937 Conflicting array def.in parm.3 (Subprogram ..).	Natural RPC does not check the boundaries of arrays.	Recatalog your Programs.
Demonstration application does not work.	You use different file numbers.	Recatalog the library SYSWEB3 (or SYSWEB respectively).
NAT3048 File/USERID not available at open time.	Natural uses same ETID for different sessions.	Set your ETID parameter to \$\$. This generates a new ETID for every running Natural.

7 Natural Web Interface Essentials

This part of the Natural Web Interface documentation describes how the Natural Web Interface enables you to create web-enabled Natural subprograms and how a web browser can call these subprograms and can receive a page in return.

This part of the documentation also outlines those functions of the Software AG product EntireX Communicator which are relevant for the operation of the Natural Web Interface. For more information, see the EntireX Communicator documentation.

You should know the essentials of HTML, of web browsers and of the environments in which the web browsers operate. You should also have a sound knowledge of Natural in a client-server environment.

This part of the Natural Web Interface documentation contains the following sections:

-  **Working with the Natural Web Interface** Describes how to set up the environment and how to work with subprograms.
-  **Natural Web Server Extensions** Describes how the Natural Web Interface enables you to create web-enabled Natural subprograms and how a web browser can call these subprograms and can receive a page in return.
-  **Test Utility WEB-ONL with SYSWEB** Describes how to use the Test Utility with SYSWEB.
-  **Test Utility WEB-ONL3 with SYSWEB3** Describes how to use the Test Utility with SYSWEB3.
-  **Tips on Programming** Contains tips for the usage of the Natural Web Interface to enable you to build better web programs.
-  **Administration** Describes how to set formats, how to define error pages, how to convert to HTML and to decode an URL.
-  **Demonstration Application without JavaScript** Contains a demonstration application which shows the use and programming of the Natural Web Interface.

-  **Demonstration Application with JavaScript** Contains a more comprehensive demonstration application. This demonstration application requires a browser which supports Java.
-  **Natural Web Interface Error Messages** Contains a list of error messages you may receive when you are working with the Natural Web Interface.

The Natural library SYSWEB3 (or SYSWEB respectively) contains all modules of the Natural Web Interface.

8

Working with the Natural Web Interface

■ Setting up your Environment	32
■ Building Subprograms in Natural	33

This section covers the following topics:

Setting up your Environment

Prerequisites on the Web Environment Side

The following software must be installed:

On the web client Browser software, such as Mozilla Firefox or Microsoft Internet Explorer.

On the web server HTTP server software, such as Apache Server or Microsoft Internet Information Server.

Middleware Prerequisites

Different prerequisites must be met if communication is to be used by RPC:

RPC The broker of the Software AG product EntireX Communicator must be installed (for installation information, see the EntireX Communicator documentation).

The Natural Web Server Extensions part is needed for communication between a web browser and a Natural RPC server.

Prerequisites on Natural Server Side

For Natural Web Interface **SYSWEB** the following prerequisites must be met:

- Current Natural Version must be installed.
- The library SYSWEB.
Either Natural steplibs must be available or the contents of the library SYSWEB must be copied to the library SYSTEM or to the user library that will be called by the RPC.
- The parameter data Area W3PARM.
- The Natural RPC stub or NaturalX.

For Natural Web Interface **SYSWEB3** the following prerequisites must be met:

- Current Natural Version must be installed.
- The library SYSWEB3.
Either Natural steplibs must be available or the contents of the library SYSWEB3 must be copied to the library SYSTEM or to the user library that will be called by the RPC.
- The parameter data Area W3PARM.


- The Natural RPC stub or NaturalX.

Building Subprograms in Natural

The following diagram illustrates how you can build a subprogram:

1. Using an HTML editor
2. You use an HTML editor to enter HTML and Natural code.
3. Then convert it to Natural source.
4. Finally move the generated program to Natural. (You code directly in Natural.)

Each stage of the process is identified by a number; what happens at these stages is explained below.



- 1a. Natural Code is written and stored in User Library.

You write Natural code on the server side either by including HTML tags in the code or by calling pre-fabricated subprograms that generate HTML tags. Then you store it as a server program or use the subprogram WEB-WIZ to generate a default program.

- 1b. Natural Code is entered as HTML. Continue with 2.

You use an HTML editor to create HTML pages.

2. Program HTML2NAT generates Natural Sources out of HTML.

You start the Web Interface Plug-in out of the library SYSWEB3 (or SYSWEB respectively) and let it convert your HTML pages created in step 1b.

3. Generated Natural Source is moved to the User Library.

Before You Write Your Subprograms

Keep the following things in mind:

- The returning HTML page is limited to the maximum data that can be transmitted. This maximum is determined by the return page variable.
- You must initialize and end the access to the Natural server subroutines by calling the subroutines W3INIT and W3END in the library SYSWEB3 (or SYSWEB respectively).
- Always use the parameter data areas W3PARM and W3CONST.
- Use the subprogram WEB-WIZ to generate a frame (default program) for your own program.

Ways to Create Your Subprograms

There are two basic alternatives. You can either start coding directly in Natural or use an HTML editor.

Alternative 1: Coding Directly In Natural

When coding directly in Natural again there are two alternatives:

- Entering calls to SYSWEB3 (or SYSWEB) subroutines (such as W3HTML or W3TEXT) for your return page in the program editor. See the programs in the library SYSWEB3 (or SYSWEB), which help you perform only basic system functions; this approach requires a good knowledge of the data type you are creating, for example HTML or XML; or
- calling subprograms that generate HTML tags. See the library SYSWEB3 (or SYSWEB respectively); the programs in the library SYSWEB3 (or SYSWEB respectively) enable you to perform basic system functions and in addition, the programs in the library SYSWEB3 (or SYSWEB respectively) generate HTML tags; this approach requires less explicit HTML knowledge and you can still modify the programs you are calling.

Example: Entering Calls to SYSWEB3 (or SYSWEB) Subroutines in the Program Editor

```
*  
* Example E3END  
  
DEFINE DATA  
PARAMETER USING W3PARM  
LOCAL USING W3CONST  
LOCAL  
1 W3VALUE      (A250)  
END-DEFINE  
* --- ERROR HANDLING ---  
ON ERROR  
    PERFORM W3ERROR ##W3ERROR  
    PERFORM W3END ##RPC  
    ESCAPE ROUTINE  
END-ERROR  
*  
* --- INITIALIZE W3 PROCESSING ---  
PERFORM W3INIT ##RPC  
*  
* --- SET TYPE OF RETURN-PAGE ---  
PERFORM W3CONTENT-TYPE 'text/html'  
* --- WRITE THE DOCUMENT ---  
PERFORM W3TEXT '<HTML><BODY><H2>Initialize</H2>'  
*  
* --- END THE HTML PAGE ---  
COMPRESS '<HR>generated:' *DATE *TIME ##HTTP_NEWLINE  
        '</BODY></HTML>' ##HTTP_END INTO W3VALUE  
PERFORM W3TEXT W3VALUE  
*  
* --- END W3 PROCESSING ---  
PERFORM W3END ##RPC  
*  
END
```

Example: Calling Subprograms that Generate HTML Tags

```
*  
* Example E3IMAGE  
  
DEFINE DATA  
PARAMETER USING W3PARM  
LOCAL USING W3CONST  
LOCAL  
1 H3VALUE      (A250)  
1 H3VALUE-MAX  (I004)  
1 H3URL        (A250)  
*
```

```

1 II          (I001)
1 GIF          (A064)
END-DEFINE
* --- ERROR HANDLING ---
ON ERROR
    PERFORM W3ERROR ##W3ERROR
    PERFORM W3END ##RPC
    ESCAPE ROUTINE
END-ERROR
*
* --- INITIALIZE W3 PROCESSING ---
PERFORM W3INIT ##RPC
*
* --- Pathname of picture ---
PERFORM W3READ-ENVIRONMENT "PICTURES" ' ' H3VALUE H3VALUE-MAX
IF H3VALUE-MAX EQ 0 THEN
    GIF := "/pictures"
ELSE
    GIF := H3VALUE
END-IF
*
* --- START HTML API ---
PERFORM H3-OPEN-HTML 'HTML Api -Image' " " " "
* --- THE LEVEL 2 HEADER ---
PERFORM H3-HEADER 2 'Image'
*
PERFORM H3-RULE 0
*
PERFORM H3-HEADER 4 'left:'
*
COMPRESS GIF '/natw_sam.gif' INTO H3URL LEAVING NO
PERFORM H3-IMAGE H3URL 'NATweb left' 219 229 "L"
*
FOR II 1 TO 10
    PERFORM H3-LINE-BREAK
END-FOR
PERFORM H3-RULE 80
*
PERFORM H3-HEADER 4 'small right:'
*
COMPRESS GIF '/natw_sam.gif' INTO H3URL LEAVING NO
PERFORM H3-IMAGE H3URL 'NATweb small right' 100 100 'R'
*
FOR II 1 TO 5
    PERFORM H3-LINE-BREAK
END-FOR
*
PERFORM H3-RULE 0
*
PERFORM H3-TIME_DATE
*
* --- END HTML API ---

```

```
PERFORM H3-CLOSE-HTML
* --- END W3 PROCESSING ---
PERFORM W3END ##RPC
*
END
```

Alternative 2: Using an HTML Editor

There are two alternatives:

- Creating static pages (you only enter HTML, which will be converted to a Natural subprogram)
- Creating dynamic pages (you enter HTML plus Natural program code).

You can, of course, also create pages that are partly dynamic, partly static.

Example: Creating Static Pages

```
<HTML>
<TITLE>NATweb - Test</TITLE>
<BODY bgColor=d3d3d3 >
<BR>
<center>
<h2>
This Natural subprogram was generated by a HTML page.
</h2>
</CENTER>
</BODY></HTML>
```

This Natural subprogram will be generated from the above HTML page:

```
* ----- SUBPROGRAM generated out of file:
* ----- C:\static.htm
DEFINE DATA
PARAMETER USING W3PARM
LOCAL USING W3CONST
LOCAL
* ----- PRIVATE VARIABLES -----
1 W3VALUE      (A250)
END-DEFINE
*
* ----- ERROR HANDLER -----
ON ERROR
    PERFORM W3ERROR ##W3ERROR
    PERFORM W3END ##RPC
    ESCAPE ROUTINE
END-ERROR
* ----- INITIALISE HTTP API -----
PERFORM W3INIT ##RPC
```

```

* ----- HEADER FOR SERVER -----
PERFORM W3CONTENT-TYPE 'text/html'
*
PERFORM W3TEXTLINE '<HTML>'
PERFORM W3TEXTLINE '<TITLE>NATweb - Test</TITLE>'
PERFORM W3TEXTLINE '<BODY bgColor=d3d3d3 >'
PERFORM W3TEXTLINE '<BR>'
PERFORM W3TEXTLINE '<center>'
PERFORM W3TEXTLINE '<h2>'
PERFORM W3TEXTLINE 'This Natural subprogram was generated by a HTML page.'
PERFORM W3TEXTLINE '</h2>'
PERFORM W3TEXTLINE '</CENTER>'
PERFORM W3TEXTLINE '</BODY></HTML>'
* ----- END HTTP API -----
PERFORM W3END ##RPC
* ----- END MAIN PROGRAM -----
*
* ----- SUBROUTINES -----
*
END

```

Example: Creating Dynamic Pages

```

<Natural><!--
*
* Read form Pers-View starting with value given by the
* Parameter START
*
* Use HTML2NAT to generate a Natural Program
*
* 22.09.03
*
--></Natural>
<! --- Variables to read the environment --->
<Natural data><!--
* ----- DATA -----
1 H3VALUE      (A250)
1 H3MAX        (I4)
--></Natural>
<! --- Head of the HTML page --->
<HTML>
<TITLE>Natural - Environment Test</TITLE>
<BODY bgColor=d3d3d3 >
<BR>
<center>
<h2>
This Natural subprogram was generated by a HTML page. The program had been
precompiled out of a HTML page.
<br><br>
</h2>

```

```

</center>
<br>
<hr>
<! --- Subprogram to write the output to work file,
      from where the server will read it --- >
<Natural DATA><!--
1 #CONTENT (A1/1:48)
1 REDEFINE #CONTENT
2 #PERSONNEL-NUMBER  (N8)
2 FILLER 1X
2 #NAME              (A20)
2 FILLER 1X
2 #FIRST-NAME        (A15)
2 FILLER 1X
2 #AGE               (N2)
--></Natural>
<Natural SUB><!--
* ----- Do the OUTPUT -----
DEFINE SUBROUTINE WRITELINE
  PERFORM W3TEXT "<LI>"*
*
#PERSONNEL-NUMBER:=PERSONNEL-NUMBER
#NAME:=NAME
#FIRST-NAME:=FIRST-NAME
#AGE:=AGE
  PERFORM W3HTMLARRAY #CONTENT(*) 48
*
  PERFORM H3-LINE-BREAK
END-SUBROUTINE
--></Natural>
<UL><PRE>
<! --- Parameter used for reading data from the DATABASE --->
<Natural DATA><!--
* ----- DATA -----
1 #VALUE (A20)
1 PERS-VIEW VIEW OF PERSONNEL
  2 PERSONNEL-NUMBER
  2 NAME
  2 FIRST-NAME
  2 AGE
--></Natural>
<! --- Main program to read the data --->
<Natural NOT>
<LI>Value1
<LI>Value2
<LI>...
</Natural>
<Natural><!--
* --- READ ENVIRONMENT ---
PERFORM W3READ-ENVIRONMENT 'START' 'P' H3VALUE H3MAX
IF H3MAX GT 0 THEN
  #VALUE := H3VALUE

```

```

ELSE
  #VALUE := "A"
END-IF
*
* ----- MAIN -----
F. FIND (100) PERS-VIEW NAME > #VALUE
  IF NO
    COMPRESS 'Sorry nothing found for:' #value '!' INTO H3VALUE
    PERFORM W3HTMLLINE H3VALUE
  END-NOREC
  IF *NUMBER > 0
    PERFORM WRITELINE
  END-IF
END-FIND
*
IF *NUMBER(F.) > 0
  PERFORM H3-RULE 0
*
  COMPRESS 'well done for: ' #value '!' ##HTTP_END INTO H3VALUE
  PERFORM W3HTMLLINE H3VALUE
END-IF
--></Natural>
</PRE></UL>
<! --- The footer of the HTML page --- >
<hr>
<BR>
<center>
<A HREF="index.htm">back to Index</A>
This program has been generated.
<Natural><!--
PERFORM H3-TIME_DATE
--></Natural>
</P>
</CENTER>
</BODY></HTML>

```

This Natural subprogram will be generated from the above HTML page:

```

* ----- SUBPROGRAM generated out of file:
* ----- C:\doit.htm
DEFINE DATA
PARAMETER USING W3PARM
LOCAL USING W3CONST
LOCAL
* ----- DATA -----
1 H3VALUE      (A250)
1 H3MAX       (I4)
1 #CONTENT (A1/1:48)
1 REDEFINE #CONTENT
  2 #PERSONNEL-NUMBER (N8)

```

```

2 FILLER 1X
2 #NAME          (A20)
2 FILLER 1X
2 #FIRST-NAME    (A15)
2 FILLER 1X
2 #AGE           (N2)
* ----- DATA -----
1 #VALUE (A20)
1 PERS-VIEW VIEW OF PERSONNEL
2 PERSONNEL-NUMBER
2 NAME
2 FIRST-NAME
2 AGE
* ----- PRIVATE VARIABLES -----
1 W3VALUE        (A250)
END-DEFINE
*
* ----- ERROR HANDLER -----
ON ERROR
  PERFORM W3ERROR ##W3ERROR
  PERFORM W3END ##RPC
  ESCAPE ROUTINE
END-ERROR
* ----- INITIALISE HTTP API -----
PERFORM W3INIT ##RPC
* ----- HEADER FOR SERVER -----
PERFORM W3CONTENT-TYPE 'text/html'
*
* ----- MAIN PROGRAM -----
*
* Read form Pers-View starting with value given by the
* Parameter START
*
* Use HTML2NAT to generate a Natural Program
*
* 22.09.2003
*
PERFORM W3TEXTLINE '<! --- Variables to read the environment --->'
PERFORM W3TEXTLINE '<! --- Head of the HTML page --->'
PERFORM W3TEXTLINE '<HTML>'
PERFORM W3TEXTLINE '<TITLE>Natural - Environment Test</TITLE>'
PERFORM W3TEXTLINE '<BODY bgColor=d3d3d3 >'
PERFORM W3TEXTLINE '<BR>'
PERFORM W3TEXTLINE '<center>'
PERFORM W3TEXTLINE '<h2>'
PERFORM W3TEXTLINE 'This Natural subprogram was generated by a HTML page. Th'
 -'e program had been'
PERFORM W3TEXTLINE 'precompiled out of a HTML page.'
PERFORM W3TEXTLINE '<br><br>'
PERFORM W3TEXTLINE '</h2>'
PERFORM W3TEXTLINE '</center>'
PERFORM W3TEXTLINE '<br>'
```

```

PERFORM W3TEXTLINE '<hr>'
PERFORM W3TEXTLINE '<! --- Subprogram to write the output to work file'
PERFORM W3TEXTLINE '           from where the server will read it --- >'
PERFORM W3TEXTLINE '<PRE>'
PERFORM W3TEXTLINE '<! --- Parameter used for reading data from the'
  - ' DATABASE --->'
PERFORM W3TEXTLINE '<! --- Main Program to read the data --->'
* --- READ ENVIRONMENT ---
PERFORM W3READ-ENVIRONMENT 'START' 'P' H3VALUE H3MAX
IF H3MAX GT 0 THEN
  #VALUE := H3VALUE
ELSE
  #VALUE := "A"
END-IF
*
* ----- MAIN -----
F. FIND (100) PERS-VIEW NAME > #VALUE
  IF NO
    COMPRESS 'Sorry nothing found for:' #value '!' INTO H3VALUE
    PERFORM W3HTMLLINE H3VALUE
  END-NOREC
  IF *NUMBER > 0
    PERFORM WRITELINE
  END-IF
END-FIND
*
IF *NUMBER(F.) > 0
  PERFORM H3-RULE 0
*
  COMPRESS 'well done for: ' #value '!' ##HTTP_END INTO H3VALUE
  PERFORM W3HTMLLINE H3VALUE
END-IF
PERFORM W3TEXTLINE '</PRE>'
PERFORM W3TEXTLINE '<! --- The footer of the HTML page --- >'
PERFORM W3TEXTLINE '<hr>'
PERFORM W3TEXTLINE '<BR>'
PERFORM W3TEXTLINE '<center>'
PERFORM W3TEXTLINE '<A HREF="index.htm">back to Index</A>'
PERFORM W3HTMLLINE 'This program has been generated.'
PERFORM H3-TIME_DATE
PERFORM W3TEXTLINE '</P>'
PERFORM W3TEXTLINE '</CENTER>'
PERFORM W3TEXTLINE '</BODY></HTML>'
* ----- END HTTP API -----
PERFORM W3END ##RPC
* ----- END MAIN PROGRAM -----
*
*
* ----- SUBROUTINES -----
* ----- Do the OUTPUT -----
DEFINE SUBROUTINE WRITELINE
  PERFORM W3TEXT "<LI>"
```

```
* #PERSONNEL-NUMBER:=PERSONNEL-NUMBER
#NAME:=NAME
#FIRST-NAME:=FIRST-NAME
#AGE:=AGE
PERFORM W3HTMLARRAY #CONTENT(*) 48
*
PERFORM H3-LINE-BREAK
END-SUBROUTINE
END
```

General Programming Considerations

Constant Values in the Local Data Area W3CONST

The local data area W3CONST contains a number of constant values which you might find useful:

##HTTP_NEWLINE, ##HTTP_NEWLINE_LENGTH

If you enter the ##HTTP_NEWLINE string into your HTML, you can use all the subroutines beginning with W3TEXT in the library SYSWEB3 (or SYSWEB) to create a physical new line by compressing ##HTTP_NEWLINE into the string by using W3TextDynamic.

##W3ERROR

Parameter used for calling W3ERROR.

##HTML_LT

Constant HTML value for "less than" sign (<).

##HTML_GT

Constant HTML value for "greater than" sign (>).

##HTML_AMP

Constant HTML value for "ampersand" sign (&).

##HTML_QUOT

Constant HTML value for "double quote" sign (").

##HTML_REG

Constant HTML value for "Registered Trademark" sign.

##HTML_COPY

Constant HTML value for "copyright" sign.

##HTML_NBSP

Constant HTML value for "no page breaking" space (' ').

Variables Defined by Value

All input variables are defined BY VALUE, that is, every value which is MOVE compatible can be used, especially strings.

Creating a Next Page

If your output possibly exceeds the limits of your return page, use the subroutine W3COUNTER in the library SYSWEB3 (or SYSWEB) to evaluate how many bytes are free in the return page.

Testing Subprograms

There are three ways to test your subprograms:

When using SYSWEB:

1. Call the subprogram from your web browser.
2. Call the subprogram NAT-DIR in the library SYSWEB to see the contents of a Natural library. You can also specify the name of the library in the parameters, for example *http://.../sysweb/NAT-DIR?LIB=SYSEXT*. Click on your program to start it.
3. If you do not want to call your subprogram from the web, you can use the Natural program WEB-ONL to simulate a remote call. The output of this program will be saved as a Natural text object. This "online execution" allows you to use the Natural Debugger.

When using SYSWEB3:

1. Call the subprogram from your web browser.
2. Call the subprogram NAT-DIR in the library SYSWEB3 to see the contents of a Natural library. You can also specify the name of the library in the parameters, for example *http://.../sysweb3/NAT-DIR?LIB=SYSEXT*. Click on your program to start it.
3. If you do not want to call your subprogram from the web, you can use the Natural program WEB-ONL3 to simulate a remote call. The output of this program will be saved as a Natural text object. This "online execution" allows you to use the Natural Debugger.

Natural Web Server Extensions

The Natural Web Server Extension is called from a HTTP server. The program repackages the parameters it receives from the HTTP server and performs an Entire Broker RPC or a DCOM call to the specified Natural subprogram or method.

Parameters

Data sent by the HTTP server is recognized and preprocessed. The URL, which was transmitted to the HTTP server in a URL-decoded (modified) form, is reset to its original state. All non-binary data can be transmitted as data and will be converted from ASCII to EBCDIC and vice versa, if necessary.

Initialization File

Only variables specified in your HTML page will automatically be transferred to the subprogram called. All other variables to be transferred must be specified in an ENV= entry of the .ini file. In this way, it is possible to add variables which will be treated as system environment variables. To add a system environment variable, specify a SETENV= entry in the .ini file.

Example .ini file

```
ENV=HTTP_REFERER  
ENV=HTTP_HOST  
;  
SETENV=VERSION:=alpha  
SETENV=BROKER:=local
```

Error Logging

To save the last HTML page that was transmitted from the server to a file, specify the TRACE_FILE parameter in your configuration file.

To return an error log, specify the ERROR_LOG_FILE parameter as log-file name in your configuration file.

To get your own error screen, specify the ERROR_TEMPLATE parameter in your configuration file with your desired HTML error page's name. Environment variables can be specified in the HTML error page by using the prefix "\$". With the environment variable \$NWW_ENVIRONMENT, all environment variables transmitted to the subroutine called will be written as comment lines to the error page.

Naming Conventions of the Libraries SYSWEB and SYSWEB3

Subroutines W3*

W3* subroutines access the interface to your HTTP server in the Natural Web Server Extension. Such an interface consists (basically) of a parameter data area and of a log of the data transmitted. The W3* subroutines used by the subprogram are called by the HTTP server using the Natural RPC.

Subroutines H3*

If you call one the H3* subroutines from one of your subroutines, it creates a basic HTML tag.

Subprograms NAT*

The NAT* subprograms are utilities that can be called from the Internet.

Natural Text Members T3*

The T3* text members describe the contents of the library SYSWEB3 (or SYSWEB respectively), what the subroutine names are and which parameters can be passed. They also provide a code sample of how to invoke them. Use the utility nat-docu to access this online documentation.

Subprograms E3*

Sample code of the online documentation.

Members D3* and D4*

The D3* and D4* members are demonstration applications.

Programs Web*

The Web* programs are utilities that run from the Natural NEXT prompt.

9 Natural Web Server Extensions

This document comprises the following sections:

-  **Introduction for SYSWEB** Get an insight into the working and installation procedures of the Natural Web Server Extensions when using SYSWEB.
-  **Introduction for SYSWEB3** Get an insight into the working and installation procedures of the Natural Web Server Extensions when using SYSWEB3.
-  **Initialization File** Here we describe parameters and variables of the initialization file.
-  **Error Messages** Here we list likely errors.

10 Natural Web Server Extensions - Introduction for SYSWEB

■ General Information	52
■ Installation - RPC / DCOM	52
■ Transformations	53
■ Variables	53
■ Error Logging and Messages	53
■ Calling Programs	53

This section covers the following topics:

General Information

The Natural Web Server Extensions part is basically a program called from an HTTP server. The Natural Web Server Extensions takes parameters, given by the HTTP server, repackages them and performs a broker RPC call to the requested Natural program using a standard parameter data area. Calls are transmitted by the EntireX Broker that is included in EntireX Communicator.

As of Natural Version 4.1, three HTTP Server interfaces will be supported:

- Common Gateway Interface (CGI), for supported server and platforms,
- Internet Server Application Programming Interface (ISAPI) only for Microsoft Internet Information Server on Windows.
- Netscape Server Application Programming Interface (NSAPI) only for Netscape FastTrack Server.

Installation - RPC / DCOM

Each Natural Web Server Extension consists of two files:

- an executable and
- an **initialization file**.

These files can be renamed. The initialization file has the same name as the executable file, but with the extension .ini. The two files must be in the same directory.

Copy the files to appropriate locations of the web server, or parameterize the web server so that it accesses the files direct.

	RPC	DCOM
CGI	nwwcgi.exe nwwcgi.ini	nwwdcgi.exe nwwdcgi.ini
ISAPI	nwwisapi.dll nwwisapi.ini	nwwdisapi.dll nwwdisapi.ini
NSAPI	nwwnsapi.dll nww/nsapi	nwwdnsapi.dll nwwd/nsapi
Parameters	RPC_ETB_ID_NAME = broker name RPC_SERVER_NAME = service name NWW_INOUT_LENGTH = amount of transferred data	NWW_INOUT_LENGTH = amount of transferred data



Note: Some HTTP servers allow executable files without the extension .exe. This means that executables with and without the .exe extension are possible.

Transformations

Parameters sent by the HTTP server via the interface are given by means of specific variables or a transfer area. User data contained in a transfer area or the variable QUERY_STRING will be recognized and preprocessed. In particular, the encoding of the URL will be undone.

The design of the Natural Web Server Extensions allows only the transmission of non-binary data, because the data is converted from ASCII to EBCDIC and vice-versa if needed.

Variables

Only variables specified on your HTML page will be automatically transferred to your called program. Other variables available from the HTTP server must be specified.

Each variable to be transferred needs an entry in the [initialization file](#).

It is also possible to add variables that will be treated as system environment variables.

Error Logging and Messages

You can set up your own error screen with a specific HTML page. Variables of the environment can be specified in this error page.

The page last transferred can be copied to a file and errors can be written to an error log file.

Calling Programs

To call a program from your browser, you have to specify a uniform resource locator (URL) which contains the name of your HTTP server and the name of a cgi-enabled directory, where you have copied the files of the Natural Web Server Extension. Then you have to specify the Natural Web Server Extension program name followed by a Natural library and a subprogram name.

	URL for RPC	
CGI	<code>http://server-name/cgi-library/nwwcgi.exe/your-library/your-program</code>	<code>http://server-name/cgi-</code>
ISAPI	<code>http://server-name/cgi-library/nwwisapi.dll/your-library/your-program</code>	<code>http://server-name/cgi-</code>
NSAPI	<code>http://server-name/nww/nsapi/your-library/your-program</code>	<code>http://server-name/nwwo</code>

11 Natural Web Server Extensions - Introduction for SYSWEB3

■ General Information	56
■ Installation - RPC / DCOM	56
■ Transformations	57
■ Variables	57
■ Error Logging and Messages	57
■ Calling Programs	58

This section covers the following topics:

General Information

The Natural Web Server Extensions part is basically a program called from an HTTP server. The Natural Web Server Extensions program takes parameters, given by the HTTP server, repackages them and performs a broker RPC call to the requested Natural program using a standard parameter data area. Calls are transmitted by the EntireX Broker that is included in EntireX Communicator.

As of Natural Version 6.2, three HTTP Server interfaces are supported:

- Common Gateway Interface (CGI), for supported server and platforms,
- Internet Server Application Programming Interface (ISAPI) only for Microsoft Internet Information Server on Windows.
- Apache Module (mod) only for Apache Server.

Installation - RPC / DCOM

Each Natural Web Server Extension consists of two files:

- an executable and
- an **initialization file**.

These files can be renamed. The initialization file has the same name as the executable file, but with the extension .ini.

Copy the files to appropriate locations of the web server, or parameterize the web server so that it accesses the files directly.

	RPC	DCOM
CGI	nww3cgi.exe nww3cgi.ini	nww3dcgi.exe nww3dcgi.ini
ISAPI	nww3isapi.dll nww3isapi.ini	nww3disapi.dll nww3disapi.ini
Apache 2.0.x (UNIX)	nww3mod2.so nww3/mod	nww3dmod2.so nww3d/mod
Apache 2.0.x (PC)	nww3mod2.dll nww3/mod	nww3dmod2.dll nww3d/mod
Parameters	RPC_ETB_ID_NAME = broker name RPC_SERVER_NAME = service name	NWW_INOUT_LENGTH = amount of transferred data

	RPC	DCOM
	NWW_INOUT_LENGTH = amount of transferred data	

-  **Note:** On some HTTP servers (Windows only) executable files without the extension .exe can be used.

Transformations

Parameters sent by the HTTP server via the interface are given by means of specific variables or a transfer area. User data contained in a transfer area or the variable QUERY_STRING will be recognized and preprocessed. In particular, the encoding of the URL will be undone.

The design of the Natural Web Server Extensions allows only the transmission of non-binary data, because the data is converted from ASCII to EBCDIC and vice-versa if required.

Variables

Only variables specified on your HTML page will automatically be transferred to the program called. Other variables available from the HTTP server must be specified.

Each variable to be transferred requires an entry in the [initialization file](#).

It is also possible to add variables that will be treated as system environment variables.

Error Logging and Messages

You can set up your own error screen with a specific HTML page. Variables of the environment can be specified in this error page.

The page last transferred can be copied to a file and errors can be written to an error log file.

Calling Programs

To call a program from your browser, you have to specify a uniform resource locator (URL) which contains the name of your HTTP server and the name of a CGI-enabled directory, where the files of the Natural Web Server Extension are located. Then you have to specify the Natural Web Server Extension program name followed by a Natural library and a subprogram name.

	URL for RPC	
CGI (PC)	<code>http://server-name/cgi-library/nww3cgi.exe/your-library/your-program</code>	<code>http://server-name/c</code>
ISAPI	<code>http://server-name/cgi-library/nww3isapi.dll/your-library/your-program</code>	<code>http://server-name/c</code>
mod	<code>http://server-name/nww3/mod/your-library/your-program</code>	<code>http://server-name/n</code>

12 Natural Web Server Extensions - Initialization File

■ General Information	60
■ RPC Parameters	60
■ PAL Parameters	61
■ DCOM Parameters	61
■ Natural Web Server Extension Settings	61
■ Data Transfer Settings	64
■ HTTP Server Variables	65
■ Additional Variables	65
■ Error Templates	65

This section covers the following topics:

General Information

The Natural Web Server Extension processes runtime parameters from an initialization file. The executable file looks for an initialization file with the same name and extension .ini in the current working directory.

The names of the variables are not case sensitive, as all variables used on the WWW. Variables are limited to 72 characters; blanks are recognized as characters, so parameters can be specified multiple times.

RPC Parameters

These parameters are required for communication with EntireX RPC.

Parameter	Description
RPC_CLASS_NAME	Defines the class of the service used. Always use RPC.
RPC_ETB_ID_NAME	Name of the EntireX Broker to be called.
RPC_NO_LOGON	Logon to the library specified at the URL. Default is 0.
RPC_SERVER_NAME	Name of the called Broker Service.
RPC_SERVICE_NAME	Defines the called service. Always use CALLNAT.
RPC_TIME_OUT	Defines the timeout for the call. Default is 7000.
RPC_USER_ID	User ID used for the RPC. If not specified, either <ul style="list-style-type: none">■ NWW_USER_ID is used or■ REMOTE_USER is used, if REMOTE_USER is set to 1
RPC_PASSWORD	User password used for the RPC. If not specified NWW_PASSWORD is used.
RPC_SSL_PARAMETER	Connect string for RPC using SSL.

PAL Parameters

These parameters are required for communication with the SPoD (PAL) interface.

Parameter	Description
PAL_SERVER_NODE	Name of the called PAL server node.
PAL_SERVER_PORT	Number of the called PAL server port.
PAL_SESSION_PARAMETER	If dynamic parameters are required for your server, specify the session parameters using single quotes ('...').

DCOM Parameters

This parameter is required for the communication with DCOM (on Windows platforms only).

Parameter	Description
DCOM_SERVER_NAME	Name of the called DCOM Server. Specify only if the Natural Server is not running on the same computer.

Natural Web Server Extension Settings

This group of parameters defines the settings of the Natural Web Server Extension.

Parameter	Description
ECHO_ENVIRONMENT	This parameter is only useful if the default error page is used. If this parameter is specified and set to 1, equal to the \$NWW_ENVIRONMENT of the user-defined error page, all environment variables will be written as comment lines to the error page.
ERROR_LOG_FILE	Defines a file for error logging. If this parameter is not specified, the log is disabled. Each log entry has the same layout and can easily be located in the error-log file by searching for the CGI string. Sample Log Entry: [Thu Jun 28 10:51:19 2005] nwwcgi.exe 04.02.05 Win32: processing of /cgi-bin/nwwcgi.exe failed for Lib:{library} Sub:{subprogram} Path:{path_info}, for natweb.software-ag.de reason NWW0001 No subprogram and library specified.

Parameter	Description				
ERROR_STDERR	If this parameter is set to 1, all errors are logged via stderr. The location of the log file depends on the HTTP server used and the way it has been parameterized. See also ERROR_LOG_FILE . Some HTTP servers do not support the use of stderr.				
ERROR_TEMPLATE	Defines an error template file. If this parameter is not specified, a default error page will be generated. See Error Templates below.				
NWW_INOUT_FORMAT NWW_INOUT_LENGTH	<p>Anmerkung: Use these parameters with SYSWEB only.</p> <p>Defines the amount of the transferred data. These parameters define the dimension of the parameter Out_Page of the IDL file.</p> <p>Used IDL File:</p> <pre>DEFINE DATA PARAMETER 1 Version-Nr (A15) In 1 Log-Time (A30) In 1 Out_Page (A RPC_INOUT_FORMAT 1:RPC_INOUT_LENGTH) In Out 1 Out_Page_Count(I04) In Out 1 Result (I04) Out END-DEFINE</pre> <p>Default values for the SYSWEB3 interface are:</p> <ul style="list-style-type: none"> ■ NWW_INOUT_FORMAT=0 ■ NWW_INOUT_LENGTH=0 				
NWW_PASSWORD	Defines the password for the user ID.				
NWW_PATH_INFO	To test the Natural Web Server Extension in stand-alone mode (test environment), set this parameter to specify the library and program name. If you use the Natural Web Server Extension in the regular mode (with HTTP-Server) you must disable this parameter. Example: NWW_PATH_INFO=/syshtml/nat-env				
NWW_PATHINFO_PREFIX	This parameter can only be used in conjunction with the ISAPI interface. If the interface is defined as application mapping (e.g. for directory nww and the extension .nww), the PATH_INFO variable delivers a prefixed URL with directory and file name (e.g. /nww/my.nww/sysweb/nat-env). This prefix (shown in <i>italics</i>) has to be removed. Use this parameter to remove the specified prefix. Example: NWW_PATHINFO_PREFIX=/nww/my.nww				
NWW_OUT_CSS	Replaces the strings with the specific character(s): <table style="margin-left: 100px; border-collapse: collapse;"> <tr> <td style="padding-right: 20px;">String</td> <td>Character</td> </tr> <tr> <td>&#09;</td> <td>- - > (Tab)</td> </tr> </table>	String	Character			- - > (Tab)
String	Character				
		- - > (Tab)				

Parameter	Description																		
	<pre data-bbox="577 291 747 587">&#64; @ &#91; [&#92; \ &#93;] &#123; { &#124; / &#125; }</pre> <p data-bbox="577 618 1476 724">This setting can be useful if cascading style sheets are used and the RPC server is placed on a computer which uses the EBCDIC code. Default is 0. Use 1 to activate.</p>																		
NWW_OUT_CSS_TRANSLATE	<p data-bbox="577 734 1476 798">Replaces the specified characters with the corresponding hexadecimal values: (Default value for ASCII)</p> <table data-bbox="577 840 1019 1241"> <thead> <tr> <th data-bbox="577 840 709 872">Character</th><th data-bbox="780 840 1019 872">Hexadecimal value</th></tr> </thead> <tbody> <tr> <td data-bbox="577 889 747 920">- - > (Tab)</td><td data-bbox="780 889 816 920">09</td></tr> <tr> <td data-bbox="577 937 621 969">@</td><td data-bbox="780 937 816 969">40</td></tr> <tr> <td data-bbox="577 986 605 1017">[</td><td data-bbox="780 986 816 1017">5B</td></tr> <tr> <td data-bbox="577 1034 605 1066">\</td><td data-bbox="780 1034 816 1066">5C</td></tr> <tr> <td data-bbox="577 1083 605 1115">]</td><td data-bbox="780 1083 816 1115">5D</td></tr> <tr> <td data-bbox="577 1132 605 1163">{</td><td data-bbox="780 1132 816 1163">7B</td></tr> <tr> <td data-bbox="577 1180 605 1212"> </td><td data-bbox="780 1180 816 1212">7C</td></tr> <tr> <td data-bbox="577 1229 605 1260">}</td><td data-bbox="780 1229 816 1260">7D</td></tr> </tbody> </table> <p data-bbox="577 1273 1117 1305">Example for English EBCDIC (Code Page 37):</p> <pre data-bbox="577 1332 1274 1400">#(tab), @, [, \,], { , , } NWW_OUT_CSS_TRANSLATE=05,7C,AD,61,BD,C0,4F, D0</pre>	Character	Hexadecimal value	- - > (Tab)	09	@	40	[5B	\	5C]	5D	{	7B		7C	}	7D
Character	Hexadecimal value																		
- - > (Tab)	09																		
@	40																		
[5B																		
\	5C																		
]	5D																		
{	7B																		
	7C																		
}	7D																		
NWW_USER_ID	User ID used for the RPC.																		
NWW_RETRY	If an error (NAT3009 Transaction aborted) occurs, this parameter defines how often the program will be called again. Default is 3.																		
INI_RELOAD	Load initialization file only once during the first call. Not for CGI interface. Default is 1.																		
REMOVE_USER_DOMAIN	IIS server on NT delivers as REMOTE_USER the username prefixed with the name of the domain the user belongs to. Natural can only handle user names with a maximum length of 8 characters. If USE_REMOTE_USER is set to 1 and REMOVE_USER_DOMAIN is set to 1 also, the used domain name from the given REMOTE_USER name is removed. This means the information after the last "/" is delivered to Natural as the user name.																		

Parameter	Description
TRACE_FILE	If a file name is specified, the last pages returned to the HTTP server will be saved to this file. If this parameter is specified, no output is written.
USE_REMOTE_USER	Replace the RPC_USER_ID with the given REMOTE_USER. Set to 1 to activate it.

Data Transfer Settings



Note: This group of parameters can only be used with SYSWEB3.

This group of parameters defines the data transfer to the Natural server.

Parameter	Description
SETMIMETYPE	<p>This parameter defines the transfer type for an incoming mime-type. The definition contains the name of a mime-type and the appropriate transfer type. The mime-type can contain asterisks as wildcard for one or any character. The application always uses the first matching mime-type.</p> <p>Valid transfer types are binary or alpha.</p> <p>Examples:</p> <pre>SETMIMETYPE=text/*;*charset*=*utf-16 binary SETMIMETYPE=text/* alpha SETMIMETYPE=image/svg alpha SETMIMETYPE=image/* binary SETMIMETYPE=multipart/form-data* binary SETMIMETYPE=* alpha</pre> <p>Anmerkung: The line SETMIMETYPE=* alpha defines the default setting, for all unknown mime-types, if not set, alpha is used.</p>

HTTP Server Variables

All HTTP server variables that are to be transferred to the called program must be specified. To do this, specify the variable ENV with the name of the variable to be transferred. The ENV variable can be specified multiple times.

Some useful variables:

```
ENV=REMOTE_HOST  
ENV=REMOTE_ADDR  
ENV=SCRIPT_NAME  
ENV=HTTP_REFERER  
ENV=HTTP_HOST  
ENV=HTTP_COOKIE
```

For further information on variables, see <http://hoohoo.ncsa.illinois.edu/cgi/env.html>.

Additional Variables

With the Natural Web Server Extension, it is possible to transfer additional variables to the called program. To do this, specify the variable SETENV with the name of the variable followed by := and the value to be transferred. The SETENV variable can be specified multiple times.

Example:

```
SETENV=PICTURES:=/pictures
```

Error Templates

Default Error Report

If parameter ERROR TEMPLATE is not specified, a default is used.

This is an example of a default error report:

nwwcgi.exe Error Report	
<i>Natural Web Interface NWW5100c Win32</i>	
The following error has been logged in the error log file:	
/cgi-bin/nwwcgi.exe:	processing of subprogram/method NAT-INFO at library/class SYSWEB failed.
reason:	NWW0011 ERX error 80010014 occurred. Severity = Error Facility = 65536 Returncode = 20 Subfacility = 3 Location = 0 Message: ERX_E_SERVICE_NOT_AVAILABLE - ETB error code 02150148
for:	pcnatweb.software-ag.de:80
path:	/sysweb/nat-info
NWW Error - Fri Mar 15 10:20:28 2005	<u>Natural</u>

Specifying Your Own Error Template

You can also specify your own error template. The error template is basically a normal return page. As for all return pages, the content type must be set. The only addition is the replacement of variables. To do this, specify the environment variable beginning with a \$ sign. See [Example of an Error Template](#) below.

The following "environment variables" are additionally available for error templates:

Environment Variable	Description
NWW_LOGTIME	Time and date the error will be logged if an ERROR_LOG_FILE is specified.
NWW_VERSION	Version number of the Natural Web Server Extension.
NWW_RUN	Name of the program that was called.
NWW_ERROR	Number of the error that has occurred.
NWW_LIBRARY NWW_CLASS	Name of the library/class that was called.

Environment Variable	Description
NWW_SUBPROGRAM	Name of the subprogram/method that was called.
NWW_METHOD	
NWW_ENVIRONMENT	All environment variables will be written as comment lines to the error page.

Example of an Error Template

```
<!DOCTYPE HTML PUBLIC '-//W3C//DTD HTML 3.2//EN'>
<HTML>
<HEAD>
<META http-equiv="Content-Type" content="text/html; charset=iso-8859-1">
<TITLE>$NWW_RUN Error Report - $NWW_LOGTIME</TITLE>
</HEAD>
<BODY bgcolor="#FFFFFF" text="#000000">
<TABLE border="0" width="100%" cellspacing="0" cellpadding="5">
<TR bgcolor="#CCFFCC">
<TD><H2 align="center">
      $NWW_RUN Error Report
    </H2>
    <P align="center">
      <I><SMALL>Natural Web Server Extension Interface: $NWW_VERSION</SMALL></I></TD>
    </TR>
    <TR>
      <TD><B>The following error has been logged in the error log file:</B></TD>
    </TR>
</TABLE>
<TABLE border="0" width="100%" cellspacing="15" cellpadding="0">
<TR valign="top">
  <TD align="right"><B>$SCRIPT_NAME:</B></TD>
  <TD><TT>processing of subprogram/method <B>$RPC_SUBPROGRAM</B><BR>
      at library/class <B>$RPC_LIBRARY</B> failed.</TT></TD>
</TR>
<TR valign="top">
  <TD align="right"><B>reason:</B></TD>
  <TD><PRE>$RPC_ERROR
</PRE>
  </TD>
</TR>
<TR valign="top">
  <TD align="right"><B>for:</B></TD>
  <TD><TT>$SERVER_NAME:$SERVER_PORT</TT></TD>
</TR>
<TR valign="top">
  <TD align="right"><B>path:</B></TD>
  <TD><TT>$PATH_INFO</TT></TD>
</TR>
</TABLE>
<TABLE border="0" width="100%" cellspacing="0" cellpadding="5">
```

```
<TR bgcolor="#CCFFCC">
  <TD>NWW Error Template - $NWW_LOGTIME</TD>
  <TD align="right">Natural</TD>
</TR>
</TABLE>
<P>
$NWW_ENVIRONMENT
</BODY></HTML>
```

13 Natural Web Server Extensions - Error Messages

This section lists error messages you may receive when working with the Natural Web Server Extensions.

Error Number	Error Message	Description	User	Programmer	Administrator
NWW0001	No library and subprogram specified.	The specified URL is not correct. Names of library and subprogram are missing.	Correct the URL.	None.	None.
NWW0002	No library specified.	The specified URL is not correct.	Correct the URL.	None.	None.
NWW0003	File ... not found.	The initialization file for your adapter cannot be found.	None.	None.	Check your ...
NWW0004	No subprogram specified.	The specified URL is not correct.	Correct the URL.	None.	None.
NWW0010	RPC call failed.	EntireX RPC cannot be initialized.	None.	None.	Check instal...
NWW0011	ERX error ... occurred ...	Internal ERX error. See EntireX Communicator documentation for further information. If the error contains the following part: <i>Message:</i> ... <i>Program = NATSRVD</i> ... <i>Error = 00082</i> ... The called program does not work.	Correct URL.	Check and stow your program.	Check instal...
NWW0012	ERX error register.	EntireX RPC Service cannot be initialized.	None.	None.	Check config...

Error Number	Error Message	Description	User	Programmer	Administrator
NWW0013	erx.dll cannot be loaded. Subcode:	EntireX Communicator erx.dll not found.	None.	None.	Check installation.
NWW0014	ERX logon failed.	EntireX Communicator logon cannot be performed.	Check User-ID, Password	Check installation file for Check User-ID, Password.	Check installation.
NWW0015	ERX logoff failed.	Logoff from EntireX Communicator failed.	None.	None.	Contact Software AC
NWW0033	File ... not found (Error: ...).	The initialization file for your adapter cannot be found.	None.	None.	Check your obj.conf for NSAPI.
NWW0034	NWW_USER_ID too long.	User ID only with a maximum of 8 characters allowed.	None.	None.	Specify only user ID 8 characters or fewer if other system will allow more.
NWW0035	NWW_PASSWORD too long.	Passwords only with a maximum of 8 characters allowed.	None.	None.	Specify only (user-) passwords with 8 characters or fewer, even if other system will allow more.
NWW0036	Natural Library Name too long.	Natural allows only library names up to 8 characters.	Check URL.	Check URL specification.	None.
NWW0037	Natural Subprogram Name too long.	Natural allows only Subprogram names up to 8 characters.	Check URL.	Check URL specification.	None.
NWW0099	CONTENT_TYPE: ... is not supported.	Only data with CONTENT_TYPE = application/x-www-form-urlencoded is supported.	None.	Do not use the attribute ENCTYPE at your FORM tag.	None.
NWW0100	RPC_INOUT_LENGTH is greater than 30000.	The output returned to the HTTP server is limited to restrictions of Natural RPC. Anmerkung: This message does not apply to SYSWEB3.	None.	None.	Change configuration
NWW0101	Number of parameters is greater than 200.	The input parameter given from the HTTP server is limited to 200 parameters. Anmerkung: This message does not apply to SYSWEB3.	None.	Reduce number of parameters transferred to the Web Interface.	None.
NWW0200	No Header specified.	Each page needs a header section at the return page.	None.	Each page should contain a CONTENT_TYPE. The header section has to be separated	None.

Error Number	Error Message	Description	User	Programmer	Administrator
				from the data by a blank line.	
NWW0201	Page contains no Data.	Every return page has to contain data.	None.	Correct the program.	None.
NWW0815	Interface A1(1:v) no longer supported.	Wrong interface specified.	None.	None.	Remove NWW_INO and NWW_INO parameter.
NWW1001	No class and method specified.	The specified URL is not correct. Names of class and method are missing.	Correct the URL.	None.	None.
NWW1002	No class specified.	The specified URL is not correct.	Correct the URL.	None.	None.
NWW1004	No method specified.	The specified URL is not correct.	Correct the URL.	None.	None.
NWW1005	ASCII Unicode conversion failed.	The transferred data has to be converted.	None.	None.	Contact Soft
NWW1006	Unicode ASCII conversion failed.	The transferred data has to be converted.	None.	None.	Contact Soft
NWW1007	Method ... not found.	A specified method cannot be called.	Correct the URL.	Add method to your class.	Check your configuration
NWW1008	Class ... not found.	A specified class cannot be called.	Correct the URL.	Create class and register with REGISTER *	Check your configuration
NWW1009	Initialization of Class ... failed.	A specified class cannot be called.	Correct the URL.	Create class and register with REGISTER *	Check your configuration
NWW1010	DCOM call failed, error	The call to DCOM failed.	None.	None.	Check your
NWW1011	DCOM error ... occurred ...	Internal DCOM error. See DCOM documentation for further information.	Correct the URL.	Correct the program.	Correct the Configuration
NWW1012	DCOM initialization failed.	The initial call to DCOM failed.	None.	None.	Correct the Configuration
NWW1013	DCOM release failed.	The deletion of class and close of DCOM failed.	None.	None.	Correct the Configuration
NWW1036	DCOM Class Name too long.	Natural allows only library names up to 32 characters.	Check the URL.	Check the URL specification.	None.
NWW1037	DCOM Method Name too long.	Natural allows only subprogram names up to 32 characters.	Check the URL.	Check the URL specification.	None.

Error Number	Error Message	Description	User	Programmer	Administrator
NWW2009	Logon to Library ... failed (Error: ...).	The specified library name is not correct.	Correct the URL.	None.	None.
NWW2010	PAL call failed (Error: ...).	The call to PAL failed.	None.	None.	Check your configuration.
NWW2011	PAL error ... occurred.	Internal PAL error. See PAL documentation for further information.	Correct the URL.	Correct the program.	Correct the Configuration/Installation.
NWW2012	PAL initialization failed (Subcode: ...).	The initial call to PAL failed.	None.	None.	Correct the Configuration/Installation.
NWW2013	PAL Transport not initialized. (Subcode: ...).	Natural allows only subprogram names up to 32 characters.	Check the URL.	Check the URL specification.	None.
NWW2014	PAL Transport failed. (Subcode: ...).	Natural allows only subprogram names up to 32 characters.	Check the URL.	Check the URL specification.	None.

14 Test Utility WEB-ONL with SYSWEB

■ Prerequisites	74
■ Running the Application	74
■ Supported Content Types	75
■ Input/Output Fields	76

The Test Utility **Web Online** is a component of the Natural Web Interface. You have the ability to check your subprogram locally without involving an HTTP server. The transfer parameters for your web page are transferred into the Test Utility and are posted directly to the business logic. As communication platform, you can choose either RPC or DCOM as in real remote communications. The result is either the web page expected or an error message. The web page can be viewed with the browser or a viewer of your choice. If you receive an error message, you can easily debug your business logic locally without writing an extra test routine. No remote debugging is needed.

Features:

- Local application checking.
- No need for remote debugging.
- Simplified error checking.
- Comfortable operation by user friendly interface.
- No need to write an extra test routine.

This section covers the following topics:

Prerequisites

- Web browser which supports different content types, for example, Microsoft Internet Explorer Version 5.0 or higher.
- Any available text editor.

Running the Application

► To define path adjustments

- 1 Start the main dialog.
- 2 Select a browser and viewer of your choice with Tools > Options...
- 3 Set the browser, viewer and work file path.
- 4 Press the OK button.

► To start the application

- 1 Start the dialog **WEB-ONL**.
- 2 Select a library and subprogram name.


- 3 Optional: add parameters.
- 4 Choose RPC or DCOM.
- 5 Press the Execute button.
- 6 View the result by pressing either the Result... or the Browse... button.

Supported Content Types

The following Content Types are supported by the Test Utility:

Content Type	Extension
"application/rtf"	".rtf"
"application/powerpoint"	".ppt"
"application/msword"	".doc"
"application/excel"	".xls"
"text/html"	".htm"
"text/plain"	".txt"
"text/xml"	".xml"
"text/richtext"	".rtf"

If you need further Content Types, change the subroutine HTML2CONTENT-TYPE (SYSWEB/W3CO2EXT) and extend the translation table to your own needs.



Input/Output Fields

Field	Explanation
Subprogram: Library/Name	Enables you to specify the library and the name of the required subprogram. The available libraries and subprograms are automatically taken from the library workspace and listed in selection boxes.
Server	If any of the name-value-pairs are server variables, you need to check this toggle button. Note that any status will last until you change it again.
Interface	Can be selected with either DCOM or RPC as communication form. For DCOM, you have to register your classes first. Default: RPC
Parameters: Name/Value	Here you can enter the name-value-pairs needed from the subprogram. To take them over into the parameter list, press the Add button. To modify the entries, use the Modify button. You do not have to substitute &, =, %; this will be done by the

Field	Explanation
	<p>WEB-ONL program. If you use server parameters, check the Server toggle button before you add the parameter to the parameter list.</p> <p>In the parameter list, all name-value-pairs are displayed. &, =, % are substituted. To delete a pair, select the item and press the Delete button. Every selected item will be inserted into the Name and Value fields. If you wish to modify a pair, select the item, change it in the Name and Value fields and press the Modify button.</p>

Object

Execute Subprogram

Starts the editor chosen with the Options dialog.

Save to Natural Text

Saves the returned data as Natural object of the type Text.

Exit

Leaves the dialog.

View

Result...

Executes the selected subprogram.

Browser...

Starts the browser chosen with the Options dialog.

Options...

Opens the Options dialog.

Help

Contents

Displays this HTML-based help file.

About

Provides general program information.

15 Test Utility WEB-ONL3 with SYSWEB3

■ Prerequisites	80
■ Running the Application	80
■ Supported Content Types	81
■ Input/Output Fields	82

The Test Utility **Web Online** is a component of the Natural Web Interface. You have the ability to check your subprogram locally without involving an HTTP server. The transfer parameters for your web page are transferred into the Test Utility and are posted directly to the business logic. As communication platform, you can choose either RPC or DCOM as in real remote communications. The result is either the web page expected or an error message. The web page can be viewed with the browser or a viewer of your choice. If you receive an error message, you can easily debug your business logic locally without writing an extra test routine. No remote debugging is needed.

Features:

- Local application checking.
- No need for remote debugging.
- Simplified error checking.
- Comfortable operation by user friendly interface.
- No need to write an extra test routine.

This section covers the following topics:

Prerequisites

- Web browser which supports different content types, for example, Microsoft Internet Explorer Version 5.0 or higher.
- Any available text editor.

Running the Application

► To define path adjustments

- 1 Start the main dialog.
- 2 Select a browser and viewer of your choice with Tools > Options...
- 3 Set the browser, viewer and work file path.
- 4 Press the OK button.

► To start the application

- 1 Start the dialog **WEB-ONL3**.
- 2 Select a library and subprogram name.


- 3 Optional: add parameters.
- 4 Choose RPC or DCOM.
- 5 Press the Execute button.
- 6 View the result by pressing either the Result... or the Browse... button.

Supported Content Types

The following Content Types are supported by the Test Utility:

Content Type	Extension
"application/rtf"	"rtf"
"application/powerpoint"	"ppt"
"application/msword"	"doc"
"application/excel"	"xls"
"text/html"	"htm"
"text/plain"	"txt"
"text/xml"	"xml"
"text/richtext"	"rtf"

If you need further Content Types, change the subroutine HTML2CONTENT-TYPE (SYS-WEB3/W3CO2EXT) and extend the translation table to your own needs.



Input/Output Fields

Field	Explanation
Subprogram: Library Name	Enables you to specify the library and the name of the required subprogram. The available libraries and subprograms are automatically taken from the library workspace and listed in selection boxes.
Interface	Can be selected with either DCOM or RPC as communication form. For DCOM, you have to register your classes first. Default: RPC
Parameters: Name Value Server	Here you can enter the name-value-pairs required from the subprogram. To add them to the parameter list, use the Add button. To modify the entries, use the Modify button. You do not have to substitute &, =, %; this will be done by the WEB-ONL3 program. If you use server parameters, check the Server toggle button before you add the parameter to the parameter list.

Field	Explanation
	<p>In the parameter list, all name-value-pairs are displayed. &, =, % are substituted. To delete a pair, select the item and press the Delete button. Every selected item will be inserted into the Name and Value fields. If you wish to modify a pair, select the item, change it in the Name and Value fields and press the Modify button.</p> <p>Server: If any of the name-value-pairs are server variables, you need to check this toggle button. Note that any status will last until you change it again.</p>
HTTP Method	<p>In this drop-down list you can select the HTTP request/submit method to be used:</p> <ul style="list-style-type: none"> ■ HEAD Identical to a GET request, but without the response body. This is useful for retrieving meta-information written in response headers, without having to transport the entire content. ■ GET Requests a representation of the specified resource. ■ POST Submits data from the identified resource. The data is included in the body of the request. You can use this method to submit data with a different content type, for example XML files or binary data (such as graphics). If you specify this method, an additional Browse... button and the Binary checkbox are available on the screen. Use the Browse... button to choose a file and the Binary checkbox, if you want to submit binary data. If you specify this method without an input file, the default mime type "application/x-www-form-urlencoded" is set. If you use an input file, the content type of that file will be used, for example with an XML file, the content type will automatically be set to "text/xml". You can specify a different mime type in the input field manually. Anmerkung: A mime type which has been set manually will always override the default mime type. ■ PUT Uploads a representation of the specified resource. You can use this method to submit data with a different content type, for example XML files or binary data (such as graphics). If you specify this method, an additional Browse... button and the Binary checkbox are available on the screen. Use the Browse... button to choose a file and the Binary checkbox, if you want to submit binary data.

Object

Execute Subprogram

Starts the editor chosen with the Options dialog.

Save to Natural Text

Saves the returned data as Natural object of the type Text.

Exit

Leaves the dialog.

View

Result...

Executes the selected subprogram.

Browser...

Starts the browser chosen with the Options dialog.

Options...

Opens the Options dialog.

Help

Contents

Displays this HTML-based help file.

About

Provides general program information.

16 Programming Tips

■ Editing in Lower Case	86
■ Quote vs. Apostrophe	86
■ Variables defined by Value	87
■ Access to Resources	87
■ Constant Values	87
■ Creating a New Page	88
■ DCOM / RPC	88

This section provides some tips on using the Natural Web Interface.

This section covers the following topics:

Editing in Lower Case

If you use Natural on a mainframe, you may set at your Editor the following:

Set your Editor in Lower Case

1. Follow the following menu structure: **Profile > Additional Options > General Defaults > Editing in Lower Case**
 2. Enter **Y** in the field **Editing in Lower Case**.
- All programs delivered with the Natural Natural Web Server Extension use ' (quotation) and " (double quotation) in a way, that conversion to uppercase depends on which pair of characters is used.
 - Strings surrounded by pairs of ' (quotation) will not be converted to upper case and strings surrounded by pairs of " (double quotation) will be converted.

Quote vs. Apostrophe

To use both quote and apostrophe within your application, check the Natural parameter Translation of quotations marks (TQ). This parameter controls the translation of a quotation mark ("') within a Natural text constant. It takes effect at compilation time only. Turn this parameter to OFF or use W3-QUOTE-DQUOTE.

Parameters

```
1 W3QUOTE          (A001) /* o/ : Quote ("")
1 W3APOSTROPHE    (A001) /* o/ : Apostrophe ('')
```

How To Invoke

```
PERFORM W3-QUOTE-DQUOTE W3QUOTE W3APOSTROPHE
```

Variables defined by Value

All input variables are defined **BY VALUE**, this means, every value which is **MOVE** compatible can be used, especially constant strings.

Access to Resources

All resources, such as pictures, sounds or Java applets, are saved at the HTTP server. If you want to create and relocate the program, do not hardcode the pathname of these resources.

When defining an environment variable, you specify the current path of the resource. The environment variable can be set at the Natural Web Server Extensions. If no variable is set, use a default setting.

Constant Values

The parameter data area W3CONST contains some useful constant values:

##HTTP_NEWLINE

Writing to the return page, a physical new line can be created by compressing the string ##HTTP_NEWLINE into the string.

##HTTP_NEWLINE_LENGTH

The length of the string ##HTTP_NEWLINE may differ for different implementations. Use ##HTTP_NEWLINE_LENGTH if the length of ##HTTP_NEWLINE is needed.

Creating a New Page

If your output may exceed the limits of your return page, use `W3COUNTER` to evaluate how many bytes are free at the return page.

DCOM / RPC

When you write an application that works with both RPC and DCOM, there are some aspects you should consider:

- Do not exceed the name sign limitation for Natural libraries and subprograms. With the DCOM interface, you can use up to 32 characters to name a class and its methods (see NaturalX documentation).
- Use the same name for a class and the library into which all your subprograms are located. This may not be according to object-oriented design principles, but gives you the possibility to access your subprograms via RPC or DCOM. EntireX Communicator supports a dynamic logon to a given Natural library.
- Now the library is the equivalent to a class, and all programs contained in that library are the methods of this class. Calling with RPC is now ready. To call with DCOM, you only have to specify all subprogram as methods of your class.
- To generate a class for a Natural library, use the **Class Generation** in the Web Interface Plug-In.

17 Web Interface Administration

■ Set the Size of the Return-Page Transport Buffer	90
■ Create a User-Defined Error Page	91
■ Create a User-Defined Error Page XML-Style	91
■ Alphanumeric-to-HTML Conversion	92
■ Alphanumeric-to-URL Conversion	92

This section covers the following topics:

Set the Size of the Return-Page Transport Buffer

This section applies to SYSWEB only.

Changing the Transport Send Buffer Width

► **To change the transport send buffer width:**

- 1 Change the upper bound of the variable RETURN_PAGE in the parameter data area W3PARM.

Use this value for the parameter NWW_INOUT_LENGTH in the initialization file used for the Natural Web Server Extension program and the initialization of the value ##HTTP_RETURN_PAGE_PART in the Local Data Area W3LIMITS.

This defines the maximum length of the transport buffer.

- 2 Recatalog all W3* sources from library SYSWEB.
- 3 Recatalog all subprograms that are to be called using the Natural Web Server Extension, all NAT-*, HTTP* and NAT-* programs from the library SYSWEB.

Changing the Received Data Buffer Width

► **To change the received data buffer width:**

- 1 Initialize ##HTTP_ENVIRONMENT_MAX in the local data area W3LIMITS.

This defines the maximum length of received data.

This value must be less than or equal to the maximum length of the transport buffer (see above).

- 2 Recatalog all W3* sources from the library SYSWEB.
- 3 Recatalog all subprograms which are to be called using the Natural Web Server Extension, all NAT-*, HTTP* and NAT-* programs from library SYSWEB.

Changing Your Return Page

► To change your return page:

- 1 Initialize ##HTTP_RETURN_PAGE_MAX in the local data area W3LIMITS.
This defines the maximum length of return page.
- 2 Recatalog all W3* sources from library SYSWEB.
- 3 Recatalog all subprograms that are to be called using the Natural Web Server Extension, all NAT-*, HTTP* and NAT-* programs from the library SYSWEB.

Create a User-Defined Error Page

If a Natural error occurs and the default ON ERROR block is specified, W3ERROR will be called and a predefined error page will be generated.

If you want to change this error page, change the Subroutine W3ERROR-TEMPLATE (SYSWEB/W3ERRTMP or SYSWEB3/W3ERRTMP accordingly).

This program generates a complete HTML page.

Create a User-Defined Error Page XML-Style

If a Natural error occurs and the default ON ERROR block is specified, W3ERROR will be called and a predefined error page will be generated.

If you want to change this error page to an XML-conform HTML, proceed as follows:

1. Uncatalog the subroutine (SYSWEB/W3ERRTMP or SYSWEB3/W3ERRTMP accordingly).
2. Open the subroutine SYSWEB/W3ERXTMP or SYSWEB3/W3ERXTMP accordingly).
3. Rename W3ERROR-TEMPLATE-XML to W3ERROR-TEMPLATE.
4. Stow the program.

This program now generates a complete XML-conform HTML page.

Alphanumeric-to-HTML Conversion

For a conversion to HTML, special characters have to be replaced by the correct HTML representation.

- The subroutine W3-ASCII-HTML-TABLE (SYSWEBP/W3AS2HT) contains the settings for the replacement of characters.
- W3INIT and W3-TEXT-TO-HTML will call W3-ASCII-HTML-TABLE.

It is possible to save up to 128 replacements.

If HEX values are used for the definition (e.g. quote), a value for the ASCII and one for the EBCDIC character set has to be defined. Otherwise the file is not portable.

Alphanumeric-to-URL Conversion

For URL decoding, some special characters have to be replaced by the correct URL-conform representations.

- The subroutine H3-ASCII-URL-TABLE (SYSWEB/H3AS3URL or SYSWEB3/H3AS3URL accordingly) contains the settings for the replacement of characters.
- H3-ASCII-URL-TABLE will be called by H3-TEXT-TO-URL.

It is possible to save up to 128 replacements.

If HEX values are used for the definition (e.g. quote), a value for the ASCII and one for the EBCDIC character set has to be defined. Otherwise the file is not portable.

18

Demonstration Application - without JavaScript


■ Business Requirements	94
■ Design Decisions	95
■ Libraries, Modules and Naming Conventions	95
■ Starting the Demonstration Application	96
■ Starting the Natural Web Interface Online Manual	96
■ Requirements	96

This section covers the following topics:

Business Requirements

The demonstration application shows the use and programming of the Natural Web Interface. The functionality includes simple file maintenance with various selection functions as shown in the graphic below.

The demonstration is platform independent and is based on the Adabas files EMPLOYEES and VEHICLES.



Design Decisions

The HTML-GUI has some restrictions for application design:

- a unique layout is not possible for different browsers.
- the HTML-GUI elements have restricted functionality. For example, no input in selection box, only predefined fonts or buttons for submit (no default button).

So in the demonstration application we use:

- forms with submit buttons.
- global data exchange with hidden fields on the forms.
- usage of the form send back method GET (URL plus visible parameters for bookmarks).
- no usage of VB / JAVA Scripts for implementation of processing rules.
- a command dispatcher module (D3CHOOSE) for navigation.
- standard pictures for group/male/female persons because of copyright reasons.

Libraries, Modules and Naming Conventions

The demonstration contains one module (see also the installation of the [Natural Web Server Extension](#)):

SYSWEB

This library contains the following modules:

- T3 HTML text for online documentation
- E3 Examples for online documentation
- D3 Demonstration application modules

SYSWEB3

This library contains the following modules:

- T3 HTML text for online documentation
- E3 Examples for online documentation
- D3 Demonstration application modules

Starting the Demonstration Application

The start module for the demonstration is D3MENU.

To start the demonstration application (depending on your installation of the Natural Web Server Extension), call the subprogram D3MENU in library SYSWEB or SYSWEB3 accordingly.

Example of the URL to call the demonstration application with SYSWEB:

`http://yourserver/yourcgi/sysweb/d3menu`

Example of the URL to call the demonstration application with SYSWEB3:

`http://yourserver/yourcgi/sysweb3/d3menu`

Starting the Natural Web Interface Online Manual

You can start the online documentation from the Natural Web Interface.

The start module for the demonstration is D3MENU.

To start the online manual, call the subprogram D3MENU in library SYSWEB or SYSWEB3 accordingly.

Example of the URL to call the demonstration application with SYSWEB:

`http://yourserver/yourcgi/sysweb/d3menu`

Example of the URL to call the demonstration application with SYSWEB3:

`http://yourserver/yourcgi/sysweb3/d3menu`

Requirements

The following software must be installed:

- Natural Web Server Extensions, a part of Natural Web Interface.
- Adabas with the file EMPLOYEES.

Perform a CATALOG for the programs D3* in the library SYSWEB (or SYSWEB3 accordingly) to activate the demonstration application.

To view the pictures of the example delivered with the Natural Web Server Extension, copy all pictures to a directory /pictures of your HTTP server or set the environment variable PICTURES for the Natural Web Server Extension to the specific directory.

19 Demonstration Application - with JavaScript


■ Business Requirements	98
■ Design Decisions	99
■ Starting the Demonstration Application	99
■ Requirements	99

This section covers the following topics:

Business Requirements

The demonstration application shows the usage and programming of the Natural Web Interface. The functionality includes simple file maintenance with various selection functions as shown in the graphic below.

For the purpose of cross-platform availability, this demonstration is based on the Adabas files EMPLOYEES and VEHICLES.



Design Decisions

Use state of the art web design:

- Javascript.
- 'global' data exchange with hidden fields on the forms.
- usage of the form send back method GET (URL plus visible parameters for bookmarks).
- a command dispatcher module (D4CHOOSE) for navigation.

Starting the Demonstration Application

The start module for the demonstration is D4ENTER. Depending on your installation of the Natural Web Server Extension, call the subprogram D4ENTER in library SYSWEB or SYSWEB3 accordingly.

Example for the URL to call the demonstration application:

`http://yourserver/yourcgi`

Requirements

Natural Web Server Extensions, a part of Natural Web Interface, and Adabas with file Employee have to be installed. Perform a CATALL for the programs D4* in the library SYSWEB (or SYSWEB3 accordingly) to activate the demonstration application.

To view the pictures in the example, you must install the Natural Web Server Extension demonstration part in your HTTP Server root.

20 Natural Web Interface Error Messages

- Error Messages 102

This section lists error messages you may receive when you are working with the Natural Web Interface. A description of each error and a solution is provided.

Error Messages

Error Number	Error Message	Description	Action
NWW9002	No elements defined.	The number of array values is set to 0.	Correct the program.
NWW9003	Can only be used inside a FORM tag.	This tag can only be used inside a FORM tag.	Initialize a FORM with H3-OPEN-FORM.
NWW9004	A FORM tag without ACTION is not allowed.	For each FORM, an ACTION has to be specified.	Correct the program.
NWW9005	LI tag outside a list not allowed.	LI has to be placed inside a list.	Initialize a FORM with H3-OPEN-LIST.
NWW9006	List nested too deep: ...	Only 10 level are supported for lists.	Decrease your level.
NWW9007	Radio Button Group has no name.	To generate a Radio Button Group, a name is needed.	Add a name.
NWW9008	Element ... has no name.	Each element of a Checkbox Group needs a name.	Add name.
NWW9009	Textarea has no name.	To generate a Textarea, a name is needed.	Add name.

21

Migrate Natural Web Interface SYSWEB to SYSWEB3

This section provides you with a step-by-step introduction on how to update your programs written for the Natural Web Interface (SYSWEB) to run with the new interface (SYSWEB3).

1. You have to use the new interface programs `nww3*` instead of the old `nww*` programs. Copy the appropriate programs to your HTTP server, and configure your HTTP server.
2. Adapt your `nww3*.ini` file settings.
3. Adapt external URLs to `nww3*` instead of `nww*`



Note: It is possible to rename the `nww3*` interface programs - but the new interface programs will only work with Natural subprograms stowed with SYSWEB3 and the old interface programs will only work with Natural subprograms stowed with SYSWEB.

4. If you are running a Natural RPC server

- On Windows or UNIX without Natural Security modify your steplib settings at NATPARM. Replace steplib SYSWEB with steplib SYSWEB3 (or use a new, different RPC server instead)
- On mainframe systems without Natural Security modify your server startup logon from SYSWEB to SYSWEB3 (or use a new, different RPC server instead)
- With Natural Security (all platforms) modify your steplib settings at Natural Security. Replace steplib SYSWEB with steplib SYSWEB3 (or use a new, different RPC server instead)
- Check your EntireX Broker settings. You may have to expand your NUM-COMBUF, NUM-LONG-BUFFER, MAX-MSG settings, depending on the maximum page length you want to transfer.

5. If you are running a DCOM server (Windows only),

- Unregister your class (usually named according to your library name) first.
- Delete your class (usually named according to your library name) and the associated LDA (usually named L)

- Use the Web Interface plug-in and generate a new class for SYSWEB3 with a new LDA (new GUIs).
 - Register the new class.
6. Adapt URLs, read work files, templates, etc. to point to SYSWEB3 instead of SYSWEB.
-  **Note:** If you rename SYSWEB3 to SYSWEB your application may work, but internal programs delivered with SYSWEB3 may not work correctly and may deliver wrong or unexpected results.
7. Recatalog all your programs that reference web interface programs by using SYSWEB3 as steplib instead of SYSWEB.
8. All your programs should now run the same way, they did with SYSWEB before.

22 Web Interface Plug-In

▪ Before You Start	106
▪ Invoking Web Interface Plug-In Commands	106
▪ Web Interface Plug-In Functions	107

This section covers the following topics:

Before You Start

The Web Interface Plug-In is an optional plug-in unit for Natural Studio. Therefore, before any action can be taken, the Web Interface Plug-In must be activated in your Plug-In Manager. For detailed information on the activation procedure, see the section [Plug-In Manager](#).

Web Interface Plug-In Interface

Once the Web Interface Plug-In is activated, your Natural Studio interface will be changed in the following way:

- the Tools menu will display the relevant Web Interface Plug-In commands,
- a toolbar will be available for the commands most frequently used.

The commands available depend on your working context.

Invoking Web Interface Plug-In Commands

▶ To invoke Program Generation commands from the main menu

- From the main menu, choose **Tools > Development Tools >  Web Interface Program Generation...**

The available commands are described in detail in the section [Program Generation](#).

▶ To invoke Class Generation commands from the main menu

- From the main menu, choose **Tools > Development Tools >  Web Interface Class Generation...**

The available commands are described in detail in the section [Class Generation](#).

▶ To invoke Test Utility commands from the main menu

- From the main menu, choose **Tools > Development Tools >  Web Interface Test Utility...**

The available commands are described in detail in the section [Online Test Utility](#).

► To invoke Web Interface options from the main menu

- From the main menu, choose Tools > Development Tools >  Web Interface Options...

The available commands are described in detail in the section [Options](#).

► To invoke Web Interface Plug-In commands, use the following toolbar buttons

- For the Generation Wizards:

 Selects the HTML page that should be used for the generation process.

 Starts the external editor for the selected HTML file.

Or:

For the Test Utility:

 Starts the editor.

It is disabled as long as you have not executed the program and if you have not changed the subprogram library or name.

You can choose the editor within the [Options](#) dialog.

 Starts the browser..

It is disabled as long as you have not executed the program and if you have not changed the subprogram library or name.

You can choose the browser in the [Options](#) dialog.

Web Interface Plug-In Functions

Program Generation



Note: The Program Generation Wizard is not applicable to mainframe systems.

This section describes the use of the Program Generation Wizard, a plug-in that enables you to generate basic web Interface programs and programs that use HTML templates with the Natural Web Interface.

The basic generation can be used to generate necessary parts for a subprogram called from the internet with the web interface. Then your specific coding can be added.

The template generation works with ready designed HTML pages. These HTML pages will be loaded from the resource directory. Then specific parts can be replaced with your individual parts. The program generator reads these HTML pages, searches for the parts to be replaced (marked with special characters) and then generates an external subroutine that can be used equal to output only maps.

This section covers the following topics:


- [Using the Conversion Program](#)
- [Inserting Replacement Strings](#)
- [Options](#)
- [View](#)
- [Class Generation](#)
- [Online Test Utility](#)

Using the Conversion Program

If your basic web pages are designed with editing tools, it takes some effort to include such a page in a Natural subprogram that can be called from the web.

The Web Wizard is a dialog that uses an HTML page as input and generates a Natural subprogram, which can be called by the Natural Web Server Extensions using the Natural Web Interface, or a subroutine which can be called to generate the output.

With the basic generation of the Web Wizard, a standalone Natural subprogram that can be called by the Natural Web Server Extensions using the Natural Web Interface can be produced.



Generating a Basic Subprogram to be Called Directly from the Web

► To generate a subprogram/subroutine to be called directly from the Web:

- 1 Select Type of generation: Basic.
- 2 Select your Generated Natural object.
- 3 Start the generation.
- 4 If you generated this subprogram the first time and you want to call the generated subprogram via DCOM, regenerate the DCOM class (see: [Class Generation](#)).
- 5 After the generation, this page can be called from the internet, but because this page does not set any data, the page will be empty.

Example of a basic generation

Generated Natural subprogram, to be called directly from the internet:

```
0010 * ----- GENERATED BY NATURAL WEB INTERFACE
* Library .....: SYSPLWEB
* Source Name .: BASIC
* -----
DEFINE DATA
PARAMETER USING W3PARM
LOCAL USING W3CONST
* ----- PRIVATE VARIABLES -----
* LOCAL
* 1 W3VALUE          (A250)
END-DEFINE
* ----- ERROR HANDLER -----
ON ERROR
PERFORM W3ERROR ##W3ERROR
PERFORM W3END ##RPC
ESCAPE ROUTINE
END-ERROR
* ----- INITIALISE HTTP API -----
PERFORM W3INIT ##RPC
* --- READ ENVIRONMENT ---
* PERFORM W3READ-ENVIRONMENT-DYNAMIC 'varname' '' W3VALUE
* set default value
* IF *length(W3VALUE) = 0 THEN
*   W3VALUE := ??
* END-IF
* ----- HEADER FOR SERVER -----
* PERFORM W3CONTENT-TYPE 'text/html'
*
*
* Add your individual coding using W3* subroutines or
* call your own subroutines.
*
*
* ----- END HTTP -----
PERFORM W3END ##RPC
* ----- END MAIN PROGRAM -----
*
END
```

Generating a Standalone Subprogram to be Called Directly from the Web

► To generate a subprogram to be called directly from the Web:

- 1 Select Type of generation: Standalone.
- 2 Select your Generated Natural object.
- 3 Start the generation.
- 4 If you generated this subprogram for the first time and you want to call the generated subprogram via DCOM, regenerate the DCOM class (see: [Class Generation](#)).
- 5 After the generation, you can call the Natural Web Interface to show the page.

Example of a standalone generation

Generated Natural subprogram, to be called directly from the internet:

```
* ----- GENERATED BY NATURAL WEB INTERFACE
* Library .....: SYSPLWEB
* Source Name .: ALONE
* -----
DEFINE DATA
PARAMETER USING W3PARM
LOCAL USING W3CONST
* ----- PRIVATE VARIABLES -----
LOCAL
1 W3VALUE          (A250)
END-DEFINE
* ----- ERROR HANDLER -----
ON ERROR
PERFORM W3ERROR ##W3ERROR
PERFORM W3END ##RPC
ESCAPE ROUTINE
END-ERROR
* ----- INITIALISE HTTP API -----
PERFORM W3INIT ##RPC
* ----- HEADER FOR SERVER -----
PERFORM W3CONTENT-TYPE 'text/html'
*
* --- READ ENVIRONMENT ---
* PERFORM W3READ-ENVIRONMENT-DYNAMIC 'varname' '' W3VALUE
* set default value
* IF *length(W3VALUE) = 0 THEN
*   W3VALUE := ??
* END-IF
* --- WRITE THE HEAD OF THE DOCUMENT ---
PERFORM W3TEXT "<!DOCTYPE 'HTML PUBLIC-//W3C//DTD HTML 3.2//EN'>-
'<html>' -"
```

```
'<head>'-  
" <meta http-equiv='Content-Type' content='"-  
"text/html; charset=iso-8859-1'>"-  
'<title>SYSPLWEB/TEST</title>' -  
'</head>'  
* --- WRITE THE BODY OF THE DOCUMENT ---  
PERFORM W3TEXT '<body>' -  
'<h2>SYSPLWEB/TEST</h2>' -  
'<hr>'  
*  
PERFORM W3TEXT '<p>This is your output</p>'  
*  
COMPRESS '<hr>generated:' *DATE *TIME INTO W3VALUE  
PERFORM W3TEXT W3VALUE  
* --- END THE BODY OF THE DOCUMENT ---  
PERFORM W3TEXT '</body>' -  
'</html>'  
*  
* ----- END HTTP -----  
PERFORM W3END ##RPC  
* ----- END MAIN PROGRAM -----  
*  
END
```

Generating a Subprogram/Subroutine using Natural Tags

► To generate a subprogram/subroutine to be called directly from the Web:

- 1 Select Type of generation: Transformation.
- 2 Select your input file of type HTML.
- 3 You can view your selected HTML page with an editor/browser.
- 4 Choose the Natural library you want to generate to.
- 5 Select the object type you want to generate.
- 6 Select your Generated Natural object.
- 7 Start the generation.
- 8 If you generated this subprogram for the first time and you want to call the generated subprogram via DCOM, regenerate the DCOM class (see: [Class Generation](#)).
- 9 After the generation, you can call the Natural Web Interface to show the page.

Inserting a Natural Tag

It is possible to specify Natural coding directly in the HTML page. After generation, the program needs no additional changes.

The HTML2NAT dialog can recognize a <NATURAL> tag. All lines between <NATURAL> and </NATURAL> will be copied, as they are, to the generated Natural source object.

Appearance

```
<NATURAL> </NATURAL>
```

Below is information on:

- Attributes DATA, LDA, GDA, SUB, NOT
- Comment Tag
- ASP-like Script Commands
- Additional Script Directives
- Example of a Simple Generation
- Example of a Simple Generation with a Natural Tag

Attributes DATA, LDA, GDA, SUB, NOT

Listed below are attributes provided to define coding sections that are to be moved within the program or excluded from the program.

Attribute	Explanation
DATA	<NATURAL DATA> or <NATURAL LDA> moves the defined section to the DEFINE DATA LOCAL part of your program.
LDA	
GDA	<NATURAL GDA> moves the defined section to the DEFINE DATA GLOBAL part of your program.
SUB	<NATURAL SUB> moves the defined section to the end of the program. This enables you to specify inline subroutines.
NOT	<NATURAL NOT> excludes the defined section from the program. This enables you to specify the design of part of a page that will be generated by a program.

Comment Tag

Use the comment tag `<!-- -->` to hide the display of defined sections of your coding. If you use the comment tag and `<NATURAL NOT>`, you can display the predefined page with a normal browser. This helps you to specify your page and replace parts of the page dynamically.

ASP-like Script Commands

Not only `<NATURAL>` and `</NATURAL>` can be used, but also ASP-like (Active Server Pages) script commands which are differentiated from the text by using the `<%` and `%>` delimiters.

Additional Script Directives

The following Natural-specific directives must be used when writing a Natural subprogram:

Output directive: `<%= ... %>`

Short form for `<% PERFORM W3HTML ... %>` tag

Subprogram directive: `<%SUB ... %>`

equal to the `<NATURAL SUB> ... </NATURAL>` tag

Global Data Area directive: `<%GDA ... %>`

equal to the `<NATURAL GDA> ... </NATURAL>` tag

directive: `<%LDA ... %>`

equal to the `<NATURAL LDA> ... </NATURAL>` tag

Not directive: `<%NOT ... %>`

equal to the `<NATURAL NOT> ... </NATURAL>` tag

Processing directive `<%@ LANGUAGE=NATURAL %>`

indicates that the used language is Natural.

Example 1 of a Simple Generation

HTML document:

```
<HTML><HEAD><TITLE>
Example1 genNat
</TITLE></HEAD><BODY><H2>
Example1 genNat
</H2><HR>
<P>This is for your output
</BODY></HTML>
```

Generated Natural subprogram:

```
* ----- GENERATED BY NATURAL WEB INTERFACE
* File .....
*   E:\SAG\Natural\6.2\Fnat\SYSWEB\RES\example1.html
* Library ....: SYSWEB
* Source Name ...: EXAMPLE1
* Crunch Lines...: 1
* Save Source....: 1
* Line Length....: 128
* Long Constants.: 1
* ----
DEFINE DATA
PARAMETER USING W3PARM
LOCAL USING W3CONST
LOCAL
* ----- PRIVATE VARIABLES -----
1 W3VALUE (A250)
END-DEFINE
*
* ----- ERROR HANDLER -----
ON ERROR
  PERFORM W3ERROR ##W3ERROR
  PERFORM W3END ##RPC
  ESCAPE ROUTINE
END-ERROR
* ----- INITIALIZE HTTP API -----
PERFORM W3INIT ##RPC
* ----- HEADER FOR SERVER -----
PERFORM W3CONTENT-TYPE 'text/html'
*
* ----- MAIN PROGRAM -----
PERFORM
  W3TEXTLINE'<HTML><HEAD><TITLE>''
PERFORM W3TEXTLINE 'Example genNat'
PERFORM
  W3TEXTLINE'</TITLE></HEAD><BODY><H2>''
PERFORM W3TEXTLINE 'Example genNat'
PERFORM W3TEXTLINE '</H2><HR>'
PERFORM W3TEXTLINE '<P>This is for your output'
PERFORM W3TEXTLINE '</BODY></HTML> '
* ----- END HTTP API -----
PERFORM W3END ##RPC
* ----- END MAIN PROGRAM -----
*
*
* ----- SUBROUTINES -----
END
```

Example 2 of a Simple Generation with a Natural Tag

HTML document:

```
<HTML><HEAD><TITLE>
Example2 genNat
</TITLE></HEAD><BODY><H2>
Example2 genNat
</H2><HR>
<P>This is for your output
<HR>
<P>generated at:
<NATURAL NOT>
Time/Date
</NATURAL>
<NATURAL><!--
  PERFORM DOTIME
--></NATURAL>
<NATURAL SUB><!--
DEFINE SUBROUTINE DOTIME
  COMPRESS *TIME *DATE INTO #VALUE
  PERFORM W3TEXTLINE #VALUE
END-SUBROUTINE
--></NATURAL>
<NATURAL DATA><!--
1 #VALUE (A30)
--></NATURAL>
</BODY></HTML>
```

Generated Natural subprogram:

```
* ----- GENERATED BY NATURAL WEB INTERFACE
* File .....: E:\SAG\Natural\6.2\Fnat\SYSWEB\RES\example2.html
* Library ....: SYSWEB
* Source Name ...: EXAMPLE2
* Crunch Lines....: 1
* Save Source....: 1
* Line Length....: 128
* Long Constants.: 1
*
* -----
DEFINE DATA
PARAMETER USING W3PARM
LOCAL USING W3CONST
1 #VALUE (A30)
* ----- PRIVATE VARIABLES -----
1 W3VALUE (A250)
END-DEFINE
*
```

```

* ----- ERROR HANDLER -----
ON ERROR
  PERFORM W3ERROR ##W3ERROR
  PERFORM W3END ##RPC
  ESCAPE ROUTINE
END-ERROR
* ----- INITIALIZE HTTP API -----
PERFORM W3INIT ##RPC
* ----- HEADER FOR SERVER -----
PERFORM W3CONTENT-TYPE 'text/html'
*
* ----- MAIN PROGRAM -----
PERFORM W3TEXTLINE '<HTML><HEAD><TITLE>'
PERFORM W3TEXTLINE 'Example2 genNat'
PERFORM W3TEXTLINE '</TITLE></HEAD><BODY><H2>'
PERFORM W3TEXTLINE 'Example2 genNat'
PERFORM W3TEXTLINE '</H2><HR>'
PERFORM W3TEXTLINE '<P>This is for your output'
PERFORM W3TEXTLINE '<HR>'
PERFORM W3TEXTLINE '<P>generated at:'
  PERFORM DOTIME
PERFORM W3TEXTLINE '</BODY></HTML>'
* ----- END HTTP API -----
PERFORM W3END ##RPC
* ----- END MAIN PROGRAM -----
*
*
* ----- SUBROUTINES -----
DEFINE SUBROUTINE DOTIME
  COMPRESS *TIME *DATE INTO #VALUE
  PERFORM W3TEXTLINE #VALUE
END-SUBROUTINE
END

```



Note: The syntax of the Natural program will not be checked during conversion.

Generating a Subprogram/Subroutine using a Template that is Called Directly from the Web

► To generate a subprogram/subroutine using a template that is called directly from the Web:

- 1 Select type of generation: Template.
- 2 Select your input file of type HTML.
- 3 You can view your selected HTML page with an editor/browser.
- 4 Select the object type you want to generate.
- 5 Select your Generated Natural object.
- 6 Start the generation.

- 7 If you generated this subprogram the first time and you want to call the generated subprogram via DCOM, regenerate the DCOM class (see: [Class Generation](#)).
- 8 After generation, you can call the Natural Web Interface to show the page.

Inserting Replacement Strings

It is necessary to specify the replacement strings directly in the HTML page. The replacement strings have to start and end with a specific character, e.g. \$ (see [Options](#)). The name (content) of a string has to comply with the Natural rules for variable names. If not, subroutines may not stow.

If the name of the replacement string is prefixed with "HTML", unsaved characters as "<" or ">" will be replaced during replacement at runtime.

The following prefixes for automatic conversion at runtime are implemented:

- HTML
- URL
- XML

For more information, see the documentation of the subroutine [W3REPLACE-AT-OUTPUT](#).

Example of Template Generation

HTML document:

```
<HTML>
<HEAD>
  <TITLE>Template Processing</TITLE>
</HEAD>
<BODY>
<H2>
  Template Processing
</H2>
<P>
  <HR>
<TABLE BORDER="0">
<TR><TD>Log-Time:</TD><TD>$log$<TD></TR>
<TR><TD>HTTPs Extension:</TD><TD>$html-ext$<TD></TR>
<TR><TD>Web Interface:</TD><TD>$html-ver$<TD></TR>
</TABLE>
<P>
<TABLE BORDER='0' WIDTH='100%' CELLSPACING='0' CELLPADDING=5>
  <TR BGCOLOR='#00cc66'>
    <TD>$prog$ - $log$</TD>
    <TD ALIGN='RIGHT'>Natural</TD>
```

```

</TR>
</TABLE>
</BODY></HTML>
```

Generated Natural subroutine, that has to be called from a subprogram that is called from the internet:


```

* ----- GENERATED BY NATURAL WEB INTERFACE
* File .....: E:\SAG\Natural\6.2\Fnat\SYSWEB\RES\templ.html
* Library ....: SYSWEB
* Source Name .: TEMPL
* Delimiter ...: $
* ----
DEFINE DATA PARAMETER
1 log                      (A) DYNAMIC BY VALUE
1 html-ext                  (A) DYNAMIC BY VALUE
1 html-ver                  (A) DYNAMIC BY VALUE
1 prog                      (A) DYNAMIC BY VALUE
END-DEFINE
*
*
DEFINE SUBROUTINE e3templm
*
* ----- HEADER FOR SERVER -----
PERFORM W3CLEAR
PERFORM W3CONTENT-TYPE 'text/html'
* ----- MAIN PROGRAM -----
* --- LOAD THE HTML TEMPLATE ---
PERFORM W3LOAD-RESOURCE ' ' 'e3templ.html'
*
* --- REPLACE PLACEHOLDER ---
PERFORM W3REPLACE-AT-OUTPUT ' ' '$log$' log
PERFORM W3REPLACE-AT-OUTPUT 'HTML' '$ext$' ext
PERFORM W3REPLACE-AT-OUTPUT 'HTML' '$ver$' ver
PERFORM W3REPLACE-AT-OUTPUT ' ' '$prog$' prog
* ----- END MAIN PROGRAM -----
*
END-SUBROUTINE
*
END
```

Generated Natural subprogram, to be called directly from the internet:

```
* ----- GENERATED BY NATURAL WEB INTERFACE
* File .....: E:\SAG\Natural\6.2\Fnat\SYSWEB\RES\templ.html
* Library ....: SYSWEB
* Source Name .: TEMPL
* Delimiter ...: $
*
* -----
DEFINE DATA
PARAMETER USING W3PARM
LOCAL USING W3CONST
LOCAL
* ----- PRIVATE VARIABLES -----
1 W3VALUE      (A250)
END-DEFINE
*
* ----- ERROR HANDLER -----
ON ERROR
  PERFORM W3ERROR ##W3ERROR
  PERFORM W3END ##RPC
  ESCAPE ROUTINE
END-ERROR
* ----- INITIALISE HTTP API -----
PERFORM W3INIT ##RPC
* ----- HEADER FOR SERVER -----
PERFORM W3CONTENT-TYPE 'text/html'
*
* ----- MAIN PROGRAM -----
* --- LOAD THE HTML TEMPLATE ---
PERFORM W3LOAD-RESOURCE 'SYSWEB'    'e3templ.html'
*
* --- REPLACE PLACEHOLDER ---
PERFORM W3REPLACE-AT-OUTPUT ' '$log$' 'replace-string-1'
PERFORM W3REPLACE-AT-OUTPUT 'HTML' '$ext$' 'replace-string-2'
PERFORM W3REPLACE-AT-OUTPUT 'HTML' '$ver$' 'replace-string-3'
PERFORM W3REPLACE-AT-OUTPUT ' '$prog$' 'replace-string-4'
* ----- END HTTP -----
PERFORM W3END ##RPC
* ----- END MAIN PROGRAM -----
*
END
```

Options




Input/Output Fields

Field	Explanation
Delete unnecessary white space	If checked, multiple white-space characters such as blank, new line, tab, will be reduced to a single white space. For special HTML tags such as <PRE> <TEXTAREA> or <SCRIPT>, the white space will not be collapsed. Default value: unchecked
Save <NATURAL NOT> ... <NATURAL> at source	If checked, the content of <NATURAL NOT> tags will not usually be generated into the Natural source. This option generates the content of <NATURAL NOT> as comment into the Natural source. Default value: unchecked
Stow after generation	If checked, the generated program will be stowed if the generation has been successful. Default value: checked
Use long text constants	Generate text constants longer than 253 characters for better performance. Default value: checked

Field	Explanation
Natural line length	The length of the generated Natural source lines: the minimum value is 20, the maximum 246. Default value: platform dependant
Delimiter	Delimiter string for replacement strings. Default value: \$

View



Below is information on:

- Input/Output Fields
- Buttons

Input/Output Fields

Field	Explanation
HTML Editor	The external program that is used to edit the source of the HTML page. Default Value: NOTE PAD
HTML Browser	The external program that is used to display the HTML page. Default: Microsoft Web browser ActiveX Control
Use internal browser	The external program that is used to display the HTML page. To select your own browser, uncheck this box. Default value: checked

Field	Explanation
Temporary work file	The default output file to be used for displaying data in the HTML-browser. Default value: C:\Temp\web-out

Buttons

OK	Leaves the dialog and saves the changes.
Cancel	Leaves the dialog without saving your changes.
Apply	Saves the current input.


Class Generation

If the Natural Web Interface subprograms should be called using DCOM instead of RPC, a DCOM class is needed. This class contains as methods all relevant Natural subprograms for the Natural Web Interface.

The program HTML to Natural automatically generates the specified class. To store the generated class, a Local Data Area (LDA) is needed to specify the Global Unique IDs (GUIDs) of the DCOM objects. The name of the LDA starts with L followed by the first seven characters of the [Library](#).

Below is information on:

- [Input/Output Fields](#)
- [Radio Buttons](#)
- [Buttons](#)
- [Example for Library SYSWEB](#)
- [Example for Library SYSWEB3](#)



Input/Output Fields

Field	Explanation
Library	The name of the library to be scanned.
Class source	The name of the class source. We recommend that the name you choose for Class source is identical to the name of the library.
Class name	The name of the class that can be called later from the Internet. We recommend that the name you choose for Class name is identical to the name of the library for which the class is generated.
LDA name	The name of the LDA containing the GUIDs for the class ID and the Natural Web Interface ID. For the naming conventions that apply, see Example for Library SYSWEB below.

Radio Buttons

Radio Button	Explanation
SYSWEB	Choose this option if you want to generate a class to be used with library SYSWEB.
SYSWEB3	Choose this option if you want to generate a class to be used with library SYSWEB3.

Buttons

Button	Explanation
OK	Generates the class and leaves the dialog.
Cancel	Leaves the dialog without generation.
Set Default Values	This button is enabled if no relevant class is found for the library. The defaults for Class source and Class name are given. The required LDA has to be generated in advance.

Example for Library SYSWEB

The LDA name is LSYSWEB. Name the first GUID CLSID- followed by the library name and the second GUID IID-NATWEB.

T	Comment
	*** Top of Data Area ***
X U 1 CLSID- SYSWEB	A 36
X U 1 IID-NATWEB	A 36
	*** End of Data Area ***

 **Caution:** Do *not* copy and rename or move an LDA in order to get new GUIDs for your classes. If an LDA is copied and renamed or moved, the preset GUID is not changed. This may cause major problems

Example for Library SYSWEB3

The LDA name is LSYSWEB3. Name the first GUID CLSID- followed by the library name and the second GUID IID-NATWEB3.

T	Comment
	*** Top of Data Area ***
X U 1	CLSID- SYSWEB3 A 36
X U 1	IID-NATWEB3 A 36
	*** End of Data Area ***

 **Caution:** Do *not* copy and rename or move an LDA in order to get new GUIDs for your classes. If an LDA is copied and renamed or moved, the preset GUID is not changed. This may cause major problems


Online Test Utility

This test utility is a component of the Natural Web Interface. You can check your subprogram locally without involving an HTTP server. The transfer parameters for your web page are transferred into the test utility and are posted directly to the business logic.

As communication platform, you can choose either RPC or DCOM as in real remote communications. The result is either the web page expected or an error message. The web page can be viewed with the browser or a viewer of your choice. If you receive an error message, you can easily debug your business logic locally without writing an extra test routine. No remote debugging is necessary.

Features:

- Local application checking.
- No need for remote debugging.
- Simplified error checking.
- Comfortable operation by user friendly interface.
- No need to write an extra test routine.



Below is information on:

- Prerequisites
- Running the Application
- Supported Content Types
- Input/Output Fields

- Buttons:

Prerequisites

- Web browser which supports different content types, for example, Microsoft Internet Explorer Version 5.0 or higher.
- Any available text editor.

Running the Application

▶ To define path adjustments

- 1 Start the main dialog.
- 2 Select a browser and viewer of your choice via **Tools > Development Tools > Web Interface Options...**.
- 3 Set the browser, viewer and work file path.
- 4 Press the OK button.

▶ To start the application

- 1 Start the dialog WEB-ONL for SYSWEB or WEB-ONL3 for SYSWEB3.
- 2 Select a library and subprogram name.
- 3 Optional: add parameters.
- 4 Choose RPC or DCOM.
- 5 Press the Execute button.
- 6 View the result by pressing either the Result... or the Browse button.

Supported Content Types

The following Content Types are supported by the Test Utility:

Content Type	Extension
"application/rtf"	".rtf"
"application/powerpoint"	".ppt"
"application/msword"	".doc"
"application/excel"	".xls"
"text/html"	".htm"
"text/plain"	".txt"
"text/xml"	".xml"

Content Type	Extension
"text/richtext"	"rtf"

If you need further Content Types, change the subroutine HTML2CONTENT-TYPE (SYSWEB/W3CO2EXT or SYSWEB3/W3CO2EXT) and extend the translation table to suit your own needs.

Input/Output Fields

Field	Explanation
Subprogram: Library Name	Enables you to specify the library and the name of the required subprogram. The available libraries and subprograms are automatically taken from the library workspace and listed in selection boxes.
Interface	Can be selected with either DCOM or RPC as communication form. For DCOM, you have to register your classes first. Default: RPC
Parameters: Name Value Server	Here you can enter the name-value-pairs needed from the subprogram. To take them over into the parameter list, press the Add button. To modify the entries, use the Modify button. You do not have to substitute &, =, %; this will be done by the WEB-ONL program. If you use server parameters, check the Server toggle button before you add the parameter to the parameter list. In the parameter list, all name-value-pairs are displayed. &, =, % are substituted. To delete a pair, select the item and press the Delete button. Every selected item will be inserted into the Name and Value fields. If you wish to modify a pair, select the item, change it in the Name and Value fields and press the Modify button. Server: If any of the name-value-pairs are server variables, you need to check this toggle button. Note that any status will last until you change it again.
HTTP Method	In this drop-down list you can select the HTTP request/submit method to be used: <ul style="list-style-type: none"> ■ HEAD Identical to a GET request, but without the response body. This is useful for retrieving meta-information written in response headers, without having to transport the entire content. ■ GET Requests a representation of the specified resource. ■ POST Submits data from the identified resource. The data is included in the body of the request. You can use this method to submit data with a different content type, for example XML files or binary data (such as graphics). If you specify this method an additional Browse... button and the Binary checkbox are available on the screen.

Field	Explanation
	<p>Use the Browse... button to choose a file and the Binary checkbox, if you want to submit binary data.</p> <p>If you specify this method without an input file, the default mime type "application/x-www-form-urlencoded" is set. If you use an input file, the content type of that file will be used, for example with an XML file, the content type will automatically be set to "text/xml". You can specify a different mime type in the input field manually.</p> <p>Anmerkung: A mime type which has been set manually will always override the default mime type.</p> <ul style="list-style-type: none"> ■ PUT Uploads a representation of the specified resource. <p>You can use this method to submit data with a different content type, for example XML files or binary data (such as graphics).</p> <p>If you specify this method, an additional Browse... button and the Binary checkbox are available on the screen.</p> <p>Use the Browse... button to choose a file and the Binary checkbox, if you want to submit binary data.</p>

Buttons:

-  Runs the process of receiving the output from the requested subprogram. The status of the process can be seen in the status bar at the bottom of the WEB-ONL or WEB-ONL3 dialog window.
-  Starts the editor. It is disabled as long as you have not executed the program and if you have not changed the subprogram library or name. You can choose the editor with the Options dialog.
-  Starts the browser chosen with the Options dialog. It is disabled as long as you have not executed the program.

23

Natural Web Online Documentation SYSWEB

■ General Information	132
■ Basic Modules	132
■ Template / XSLT Processing	134
■ HTML Extension	134
■ Utilities	136
■ Demonstration Applications	136

This section covers the following topics:

General Information

The online documentation files are prefixed with E3* and T3*. The online documentation contains example programs that can be displayed and executed online. Depending on your installation of the Natural Web Interface, call the subprogram NAT-DOCU from the library SYSWEB to display the main page of online documentation at your web-browser.

Example of the URL to call the online documentation:

`http://yourserver/yourcgi/sysweb/nat-docu`

 **Note:** To display the online documentation, the HTTP Server Extensions of the Natural Web Interface, must be installed, and a correct Natural RPC/DCOM Server has to be started. To access the program USR1057N, of library SYSEXT, add a steplib to SYSEXT or copy the programs to your system library.

Definition of Parameters	
i /	Input Variable
o /	Output Variable
/o	Optional Variable
/m	Mandatory Variable (has to be specified)
/M	Mandatory Variable. If empty, specific parts will not be generated.
/H	Variable will be translated to HTML
/X	Variable will be translated to XML
/U	Variable will be translated to URL

Basic Modules

The basic module names of the Natural Web Interface, start with the prefix W3.

They provide the communication between Natural Subprograms and the HTTP Server Extension. All other programs of the Natural Web Interface use these programs.

It is possible to make some administrative changes to define the amount and format of the transferred data, to change conversion tables and to change the error page.

 **Note:** All new programs available are displayed in *italics* font in the tables below. Program names in brackets will be discontinued in the near future. Please use the program name mentioned in the description.

Program	Description
W3CLEAR	Clear the output page.
W3CONTENT-TYPE	Sets the content type of a document.
W3COUNTER	Returns the maximum number of bytes and the number of currently written or free bytes in the output area .
W3ERROR W3ERROR-TEMPLATE W3ERROR-TEMPLATE-XML W3ERROR-TEXT	Generates a default error page .
W3HTML W3HTMLLINE W3HTMLDYNAMIC W3HTMLINEDYNAMIC W3HTMLARRAY	Writes an HTML string to the output page and converts special characters to an HTML-valid representation.
W3HTTP W3HTTPDYNAMIC W3HTTP-HEADER W3HTTPARRAY	Writes HTTP settings to the output page.
W3INFO	Returns internal settings.
W3INIT W3END	Initializes SYSWEB and prepares the document for returning to the HTTP server.
W3LIST-ENVIRONMENT W3LIST-ENVIRONMENT-TO-DYNAMIC	Lists all variables .
W3LOCATION	Sets the location of a page that is to be called instead this page.
W3READ-ENVIRONMENT W3READ-ENVIRONMENT-ARRAY W3READ-ENVIRONMENT-TO-DYNAMIC	Reads a variable sent by the HTTP server.
W3READ-ENVIRONMENT-TEXTAREA	Reads a variable set by a text area and splits the variable into separate lines.
W3READ-ENVIRONMENT-GROUP	Reads all environment variables with the same name.
W3TEXT W3TEXTLINE W3TEXTDYNAMIC W3TEXTLINEDYNAMIC W3TEXTARRAY	Writes a text string to the output page.
W3NEWLINE	Writes a linebreak to the output page.
(W3SPACE)	replace with -> W3TEXTDYNAMIC " "
W3-QUOTE-DQUOTE	Returns special character independent of characterset.
W3TEXT-TO-HTML W3-ASCII-HTML-TABLE	Converts ASCII to the specific encoding of HTML .
W3TEXT-TO-XML W3-ASCII-XML-TABLE	Converts ASCII to the specific encoding of XML .

Program	Description
W3TEXT-TO-URL W3-ASCII-URL-TABLE	Converts ASCII to the specific encoding of URL.

Template / XSLT Processing

Program	Description
W3REPLACE	Search the output page for a specific string and replace with a new one.
W3LOAD-RESOURCE	Load a file from the resource directory of a specific natural library as result document.
W3READ-RESOURCE	Read a file from the resource directory of a specific natural library into a dynamic variable.
W3WRITE-RESOURCE	Write a dynamic variable to a file at the resource directory of a specific natural library.
W3CHECK-RESOURCE	Check if resource exists. If not, a new resource can be created.
W3DELETE-RESOURCE	Delete a resource from the resource directory.
W3APPLY-XSLT-XML	Apply a stylesheet to transformation on the output page.
W3APPLY-XSLT-RESOURCE	Apply a stylesheet , saved as resource on the output page.
W3APPLY-XSLT-XML-TO-DYNAMIC	Apply a stylesheet , to transformation to an dynamic variable.
W3READ-OUTPUT	Read the already written output page.

HTML Extension

The prefix H3 is used for all program names of the HTML extension. This external subroutines, delivered with source code, generate HTML and use the basic modules of the Natural Web Interface.

The programs do not cover the complete syntax of HTML. They also do not support special enhancements of specific web browser. If you need enhancements, feel free to extend the programs delivered in source code, or create your own ones.

Program	Description	HTML Tag
H3-ANCHOR	Creates an anchor tag.	<A...>...
H3-BUTTON	Creates reset/submit buttons .	<INPUT...>
H3-CHECKBOX-GROUP	Generates a checkbox group.	<INPUT...>
H3-COMMENT	Creates a comment line.	<!...>
H3-HEADER	Generates a header tag.	<Hn>

Program	Description	HTML Tag
H3-IMAGE	Generates an image tag.	<IMG...>
H3-INPUT	Generates a text, password or hidden input field.	<INPUT...>
H3-LINE-BREAK H3-LINE_BREAK	Sets a line break with or without additional text.	
H3-OPEN-FORM H3-CLOSE-FORM	Starts a form tag for input fields.	<FORM>...</FORM>
H3-OPEN-HTML H3-OPEN-HTML-JAVASCRIPT H3-CLOSE-HTML	Starts and ends an HTML Document .	<HTML>...</HTML>
H3-OPEN-LIST H3-LIST-ITEM H3-CLOSE-LIST	Generates an ordered, unordered, menu or directory list <DIR>......</DIR> <MENU>......</MENU>
H3-PARAGRAPH	Generates a paragraph with additional text.	<P...>
H3-RADIO-GROUP	Generates a radio button group.	<INPUT...>
H3-RULE	Sets a horizontal rule .	<HR...>
H3-SCROLLING-LIST	Generates a scrolling list.	<SELECT> ...<OPTION>... <SELECT>
H3-TABLE H3-TABLE-COLOR	Generates a table .	<TABLE> ... <TR> <TH>...</TH> </TR> <TR> <TD>...</TD> </TR> ... </TABLE>
H3-TAG	Generates a universal tag .	<tag>
H3-TEXT-AREA	Generates a ' text area '.	<TEXTAREA>...</TEXTAREA>
H3-TEXT-TO-HTML	Converts the content of a Natural string to ' HTML '. replace with -> W3TEXT-TO-HTML	
H3-TEXT-TO-URL H3-ASCII-URL-TABLE	Converts the content of a Natural string to ' URL decoded '. replace with -> W3TEXT-TO-URL	
H3-TIME_DATE H3-TIME-DATE	Generates a ' time/date ' string.	generated: Mon, 17 Jan 2005 15:35:18 GMT

Utilities

Web Interface Plugin

Plugin	Description
Program Generation	see Natural documentation
Class Generation	see Natural documentation
Online Test Utility WEB-ONL	see Natural documentation

Online

Dialog	Description
WEB-ONL	See Natural documentation

Remote

Program	Description
NAT-LIB	Lists all Natural libraries.
NAT-DIR	Lists the contents of a specific Natural library.
NAT-ENV	Lists all parameters passed to a called Natural subprogram.
NAT-HTML	Displays a Natural source containing HTML.
NAT-INFO	Displays the current Natural Web Interface settings.
NAT-LIST	Displays a Natural source object.
NAT-DOCU	Displays the online documentation.
NAT-RES	Displays a non-Natural file - resource (only platform shared resources are available).

Demonstration Applications

The demonstration application delivered shows simple file maintenance with select functions. The demonstration is based on the Adabas file EMPLOYEES. To run the application, Adabas has to be active.

Three implementations of the demonstration applications are delivered:

1. one using templates, xml and xslt, name prefix D6*

Depending on your installation of the HTTP Server Extensions, call the subprogram D6INDEX from the library SYSWEB.

Example of the URL to call the demonstration application:

`http://yourserver/yourcgi/sysweb/d6index`

2. one using JavaScript, name prefix D4*

Depending on your installation of the HTTP Server Extensions, call the subprogram D4ENTER from the library SYSWEB.

Example of the URL to call the demonstration application:

`http://yourserver/yourcgi/sysweb/d4enter`

3. one using standard HTML 3.2, name prefix D3*

Depending on your installation of the HTTP Server Extensions, call the subprogram D3MENU from the library SYSWEB.

Example of the URL to call the demonstration application:

`http://yourserver/yourcgi/sysweb/d3menu`

All pictures used are delivered with the Natural Web Interface. Save them in the directory `pictures` on your HTTP-server in the remote directory `PICTURES`. If you want to use another remote directory name, set the environment variable `PICTURES` at the initialization file of your HTTP Server Extension with the specific remote directory name.

A JavaScript file for the D4* example is delivered with the Natural Web Interface. Save it in the directory `javascript` on your HTTP-server in the remote directory `/javascript`. If you want to use another remote directory name, set the environment variable `JAVASCRIPT` at the initialization file of your HTTP Server Extension with the specific remote directory name.

24 Clear Output Area

Subroutine Name	Executable Example	Viewable Example
W3CLEAR	E3CLEAR	E3CLEAR

Description

Deletes all data already written to the output area.

Parameters

*/ NONE

How To Invoke

```
PERFORM W3CLEAR
```


25 Set Document Content-Type

Subroutine Name	Executable Example	Viewable Example
W3CONTENT-TYPE	E3CONTYP	E3CONTYP

Description

Sets the content type of the document. This setting is used by the browser programs to find out how the content is to be displayed.

W3CONTENT-TYPE or [W3LOCATION](#) has to be the first output of a document.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Parameters

```
1 H3VALUE (A) DYNAMIC /* i /m : Content type to be set
```

How To Invoke

```
PERFORM W3CONTENT-TYPE H3VALUE
```


26 Count Size of Output Area

Subroutine Name	Executable Example	Viewable Example
W3COUNT	E3COUNT	E3COUNT

Description

Returns the current size of the output area and the number of bytes already written there.

Parameters

```
1 W3WRITTEN (I4) /* o/m : Currently written bytes  
1 W3MAXPAGE (I4) /* o/m : Maximum bytes possible  
1 W3FREE     (I4) /* o/m : Free bytes
```

How To Invoke

```
PERFORM W3COUNTER W3WRITTEN W3MAXPAGE W3FREE
```


27 Generate Error Page

Subroutine Name	Executable Example	Viewable Example
W3ERROR	E3ERROR	E3ERROR
W3ERROR-TEMPLATE		
W3ERROR-TEMPLATE-XML		
W3ERROR-TEXT		

Description

Errors generated by the Natural runtime should be handled to avoid screen output. Therefore, an `ON ERROR` section must be added to all programs called with the Natural Web Interface. The PDA `W3CONST` must be added as well.

The subroutine `W3ERROR-TEMPLATE` is called if an error occurs. This routine can be changed for your own needs.

The subroutine `W3ERROR-TEMPLATE-XML` returns the error page as XHTML page. This routine can be changed for your own needs. To activate this template, uncatalog `W3ERROR-TEMPLATE` and rename the subroutine from `W3ERROR-TEMPLATE-XML` to `W3ERROR-TEMPLATE` and stow.

The subroutine `W3ERROR-TEXT` is for internal use only.

Parameters

```
1 ##W3ERROR
2 NR          (I4)   /* i /m : Number of the error
2 LINE        (I4)   /* i /m : Line in the Natural program
2 SUBPROGRAM (A008) /* i /m : Subprogram name
2 SUBROUTINE (A032) /* i /m : Subroutine name
2 TEXT        (A250) /* i /m : Error text
```

How To Invoke

```
ON ERROR
  PERFORM W3ERROR ##W3ERROR
  PERFORM W3END ##RPC
  ESCAPE ROUTINE
END-ERROR
```

28 Writes to the Document and Converts to Valid HTML

Subroutine Name	Executable Example	Viewable Example
W3HTML	E3HTMLA	E3HTMLA
W3HTMLDYNAMIC		
W3HTMLLINE		
W3HTMLINEDYNAMIC		
W3HTMLARRAY		

Description

Writes a string to the document and converts special characters, such as "<" , ">" , "Ã¼" ,

...

If you want to create a line break after your output, use W3HTMLLINE or W3HTMLINEDYNAMIC. If you want to create a line break inside your string, compress ##HTTP-NEWLINE into your string.

W3HTML and W3HTMLLINE will delete trailing blanks from the given string.

For better performance use dynamic variables.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Parameters

1. W3HTML

```
1 H3HTML          (A) DYNAMIC BY VALUE /* i /mH: Output string
```

2. W3HTMLDYNAMIC

```
1 H3DYNAMIC        (A) DYNAMIC BY VALUE /* i /mH: Output string
```

3. W3HTMLLINE

```
1 H3HTML          (A) DYNAMIC BY VALUE /* i /mH: Output string
```

4. W3HTMLLINEDYNAMIC

```
1 H3DYNAMIC        (A) DYNAMIC BY             /* i /mH: Output string
```

5. W3HTMLARRAY

```
1 H3ARRAYVALUE  (A/1:v) DYNAMIC           /* i /mH: Output array  
1 H3VALUELENGTH (I4)                      /* i /m : Length of output array
```

How To Invoke

```
PERFORM W3HTML H3HTML  
PERFORM W3HTMLDYNAMIC H3DYNAMIC  
PERFORM W3HTMLLINE H3HTML PERFORM W3HTMLLINEDYNAMIC H3DYNAMIC  
PERFORM W3HTMLARRAY H3ARRAYVALUE H3VALUELENGTH
```

29 Writes HTTP Settings to the Document

Subroutine Name	Executable Example	Viewable Example
W3HTTP	E3HTTP	E3HTTP
W3HTTPDYNAMIC		
W3HTTP-HEADER		
W3HTTPARRAY		

Description

Writes a text line to the HEAD of a document. In these text line settings, you can specify COOKIES, EXPIRE-DATES or other settings of an HTTP-compatible document.

Physical new lines in the output can be created by compressing ##HTTP_NEWLINE into a Natural string.

If you want to create a line break inside your string, compress ##HTTP-NEWLINE into your string.

W3HTTP will delete trailing blanks from the given string.

For better performance use dynamic variables.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Parameters

1. W3HTTP

```
1 W3STRING      (A) DYNAMIC    /* i /m : Header name value pairs
```

2. W3HTTPDYNAMIC

```
1 W3DYNAMIC      (A) DYNAMIC    /* i /m : Header name value pairs
```

3. W3HTTP-HEADER

```
1 W3HTTPNAME     (A) DYNAMIC    /* i /m : Header name  
1 W3HTTPVALUE    (A) DYNAMIC    /* i /m : Header value
```

4. W3HTTPARRAY

```
1 W3ARRAYVALUE   (A/1:V) DYNAMIC /* i /m : Header name value pairs  
1 W3VALUELENGTH (I4)           /* i /m : Length of output array
```

How To Invoke

```
PERFORM W3HTTP W3STRING  
PERFORM W3HTTPDYNAMIC W3DYNAMIC  
PERFORM W3HTTP-HEADER W3HTTPNAME W3HTTPVALUE  
PERFORM W3HTTPARRAY W3ARRAYVALUE W3VALUELENGTH
```

30 Info About Internal Values

Subroutine Name	Executable Example	Viewable Example
W3INFO	E3INFO	E3INFO

Description

This program enables you to set and read some internal values of the Web Interface.

Read (Action ' ')

The values for ERROR-NR VERSION, LOG-TIME, FORM, LIST(*) and LIST_MAX will be returned.

Set List (Action 'L')

For H3-OPEN-LIST, H3-CLOSE-LIST and H3-LIST-ITEM, an internal array is used to save the style of the generated list. This style will be used to generate the correct close tag.

Set Form (Action 'F')

For all programs, you can generate tags that can only be used inside a FORM tag. A flag can be called to check if a FORM is open or not. The flag will be changed by H3-OPEN-FORM and H3-CLOSE-FORM.

Parameters

```
LOCAL USING WPINFO
```

PDA W3PINFO

```
1 ##W3INFO
2 ACTION      (A1)          /* i /m : Action to be called
2 LOG-TIME    (A030)        /* o/m : Log time set by the Natural Web Interface
2 VERSION     (A015)        /* o/m : Version set by the HTTP Server Extension
2 WEBAPI      (A015)        /* o/m : Version set by the Natural Web Interface
2 ERROR-NR    (I4)          /* o/m : Error number set by the Natural Web Interface
2 FORM        ( L)          /* io/m : Indicates whether a FORM is open
2 LIST         (A001/1:10)   /* io/m : Saves the type of LIST
2 LIST_MAX    (N002)        /* io/m : Current number of nested LISTs
```

How To Invoke

```
PERFORM W3INFO ##W3INFO
```

31 End and Initialize Document

Subroutine Name	Executable Example	Viewable Example
W3INIT	E3END	E3END
W3END		

Description

Each Program needs to initialize and end the web interface by special programs. The initialisation is done by W3INIT.

The W3PARM PDA must be passed to initialize passed parameters for further use.

W3END ends the document and prepares the return to the HTTPserver. The W3PARM PDA defined at the initial program has to be passed to W3END.

If W3* calls are performed after W3END, the written output will not be transferred to the HTTP server.

Parameters

1. W3INIT

```
USING W3PARM /* io/m : Parameter of Subprogram
```

2. W3END

```
USING W3PARM /* io/m : Parameter of Subprogram
```

3. W3PARM

```
1 ##RPC
2 VERSION          (A010)      /* i /m : Interface version
2 LOG-TIME         (A030)      /* i /m : Timestamp
2 RETURN_PAGE      (A250/1:V)  /* io/m : Transfer area
2 RETURN_PAGE_COUNT (I004)     /* io/m : Bytes sent
2 ERROR-NR         (I004)     /* o/m : Error number
```

How To Invoke

```
PERFORM W3INIT ##RPC
PERFORM W3END ##RPC
```

32 List All Environment Variables

Subroutine Name	Executable Example	Viewable Example
W3LIST-ENVIRONMENT	E3ENVLIS	E3ENVLIS
W3LIST-ENVIRONMENT-TO-DYNAMIC		

Description

List all variables sent by the HTTP server.

Parameters

1. W3LIST-ENVIRONMENT

```
1 W3START          (I4)      /* io/m : Offset to be started at
*                           /*           out: 0 no occurrences

*                           /*           out: >0 more occurrences
1 W3ARRAYCOUNTER   (A72/1:V)  /* io/m : Length of array returned values
1 W3ARRAYNAME      (A250/1:V) /* o/m : Name of variables
1 W3ARRAYVALUE     (I4/1:V)   /* o/m : Value of variables
1 W3ARRAYVALUELENGTH (L/1:V)  /* o/m : Length of variables
1 W3ARRAYVALUESERVER (I4)    /* o/m : Variable belongs to
1 W3ARRAYMAXIMUM   /* o/m : Total number of variables
```

2. W3LIST-ENVIRONMENT-TO-DYNAMIC

```
1 W3START          (I4)      /* io/m : Offset to be started at
*                           /*           out: 0 no occurrences
*                           /*           out: >0 more occurrences
1 W3ARRAYCOUNTER   (A/1:V)dynamic /* io/m : Length of array returned values
1 W3ARRAYNAME      (A/1:V)dynamic /* o/m : Name of variables
1 W3ARRAYVALUE     (I4/1:V)    /* o/m : Value of variables
1 W3ARRAYVALUELENGTH (L/1:V)  /* o/m : Length of variables
```

```
1 W3ARRAYVALUESERVER (I4)          /* o/m : Variable belongs to
1 W3ARRAYMAXIMUM                  /* o/m : Total number of variables
```

How To Invoke

```
PERFORM W3LIST-ENVIRONMENT W3START W3NAME W3ARRAYCOUNTER
      W3ARRAYNAME(*) W3ARRAYVALUE(*) W3ARRAYVALUELENGTH(*)
      W3ARRAYVALUESERVER(*) W3ARRAYMAXIMUM
```

33 Set Document Location

Subroutine Name	Executable Example	Viewable Example
W3LOCATION	E3LOCAT	E3LOCAT

Description

Sets the location of a document that is to be loaded. This subroutine can be used to call a static page instead of a dynamic one from a Natural program.

W3LOCATION or [W3CONTENT-TYPE](#) has to be the first output of a document.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Parameters

```
1 W3CONTENT (A) DYNAMIC /* i /m : Content type to be set
```

How To Invoke

```
PERFORM W3CONTENT-TYPE W3CONTENT
```


34 Read Environment Variable

Subroutine Name	Executable Example	Viewable Example
W3READ-ENVIRONMENT-ARRAY	E3ENVARY	E3ENVARY
W3READ-ENVIRONMENT		
W3READ-ENVIRONMENT-TO-DYNAMIC		

Description

Reads the first occurrence of a single variable. With W3READ-ENVIRONMENT-ARRAY, a variable can be read beginning with an offset. This can be used to read multiple occurrences of the same variable.

Parameters

1. W3READ-ENVIRONMENT-ARRAY

```
1 W3START          (I4)      /* io/m : Offset to be started at
*
*                                /* out: 0 no occurrences
*                                /* out: >0 more occurrences
1 W3NAME           (A072)    /* i /m : Name of the variable to
*
*                                /* be searched for
1 W3VALUESERVER   (A1)     /* i /m : Search for variables from
*
*                                /* 'S' server
*                                /* 'P' page or URL
*                                /* ' ' both
1 W3ARRAYCOUNTER  (I4)     /* io/m : Size of array,
*
*                                /* characters read
1 W3VALUEARRAY    (A001/1:V) /* o/m : Array with the returned value
1 W3VALUELENGTH   (I4)     /* o/m : length of the value
```

2. W3READ-ENVIRONMENT

```
1 W3NAME          (A072) /* i /m : Name of the variable
                           /*           searched for
1 W3VALUESERVER (A1)  /* i /m : Search for variables in
*                      /*           'S' server
*                      /*           'P' page or URL
*                      /*           ' ' both
1 W3VALUE         (A250) /* o/m : Returned value
1 W3VALUELENGTH (I4)   /* o/m : Length of the value
```

3. W3READ-ENVIRONMENT-TO-DYNAMIC

```
1 W3NAME          (A072)      /* i /m : Name of the variable
                           /*           searched for
1 W3VALUESERVER (A1)       /* i /m : Search for variables in
*                      /*           'S' server
*                      /*           'P' page or URL
*                      /*           ' ' both
1 W3VALUEDYNAMIC (A) DYNAMIC /* o/m : Returned value
```

How To Invoke

```
PERFORM W3READ-ENVIRONMENT-ARRAY W3START W3NAME
       W3VALUESERVER W3ARRAYCOUNTER
       W3VALUEARRAY(*) W3VALUELENGTH

PERFORM W3READ-ENVIRONMENT W3NAME W3VALUESERVER W3VALUE
       W3VALUELENGTH

PERFORM W3READ-ENVIRONMENT-TO-DYNAMIC W3NAME W3VALUESERVER
       W3VALUEDYNAMIC
```

35 Read Environment Variables Groups

Subroutine Name	Executable Example	Viewable Example
W3READ-ENVIRONMENT-GROUP	E3ENVGRO?test=a&test=bb&test=cc	E3ENVGRO

Description

Reads all variables with the same name, e.g. set from a multiple select.

Parameters

```
1 W3START          (I4)      /* io/m : Offset to be started at
*                           /*           out: 0 no occurrences
*                           /*           out: >0 more occurrences
1 W3NAME           (A) DYNAMIC /* i /m : Name of variable
1 W3VALUESERVER   (A1)       /* i /m : Search for variables in
*                           /*           'S' server
*                           /*           'P' page or URL
*                           /*           ' ' both
1 W3ARRAYCOUNTER  (I4)       /* io/m : Length of array,
*                           /*           returned values
1 W3ARRAYVALUES   (A250/1:V)  /* o/m : Values of variable
1 W3ARRAYMAXIMUM (I4)       /* o/m : Total number of variables
```

How To Invoke

```
PERFORM W3READ-ENVIRONMENT-GROUP W3START W3NAME
      W3VALUESERVER W3ARRAYCOUNTER
      W3ARRAYVALUES(*) W3ARRAYMAXIMUM
```


36 Read Environment Text Area Variables

Subroutine Name	Executable Example	Viewable Example
W3READ-ENVIRONMENT-TEXTAREA	E3ENVTX	E3ENVTX E3ENVTX1

Description

Reads a variable set by a text area tag and separates the text lines.

Parameters

```
1 W3START          (I4)      /* io/m : Offset to be started at
*
*                           /*           out: 0 no occurrences
*                           /*           out: >0 more occurrences
1 W3NAME           (A072)    /* i /m : Name of variable
1 W3VALUESERVER   (A1)      /* i /m : Search for variables in
*
*                           /*           'S' server
*                           /*           'P' page or URL
*                           /*           ' ' both
1 W3ARRAYCOUNTER  (A250/1:V) /* io/m : Length of array,
*                           /*           returned values
1 W3ARRAYVALUE     (I4/1:V)  /* o/m : Value of variables
1 W3ARRAYVALUELLENGTH (I4)  /* o/m : Length of variables
1 W3ARRAYMAXIMUM   /* o/m : Total number of variables
```

How To Invoke

```
PERFORM W3READ-ENVIRONMENT-TEXTAREA W3START W3NAME  
      W3VALUESERVER W3ARRAYCOUNTER(*)  
      W3ARRAYVALUE(*) W3ARRAYVALUELENGTH(*)  
      W3ARRAYMAXIMUM
```

37 Write Text to Document

Subroutine Name	Executable Example	Viewable Example
W3TEXT	E3TEXT	E3TEXT
W3TEXTDYNAMIC		
W3TEXTLINE		
W3TEXTLINEDYNAMIC		
W3TEXTARRAY		

Description

Writes a character string to the document.

If you want to create a line break after your output, use W3HTMLLINE or W3HTMLLINEDYNAMIC.

If you want to create a line break inside your string, compress ##HTTP-NEWLINE into your string.

W3TEXT and W3TEXTLINE will delete trailing blanks from the given string.

For better performance use dynamic variables.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Parameters

1. W3TEXT

```
1 W3TEXT          (A) DYNAMIC      /* i /m : Output string
```

2. W3TEXTDYNAMIC

```
1 W3DYNAMIC        (A) DYNAMIC      /* i /m : Output array
```

3. W3TEXTLINE

```
1 W3TEXT          (A) DYNAMIC      /* i /m : Output string with new line
```

4. W3TEXTLINEDYNAMIC

```
1 W3DYNAMIC        (A) DYNAMIC      /* i /m : Output string with new line
```

5. W3TEXTARRAY

```
1 H3ARRAYVALUE  (A/1:v) DYNAMIC /* i /m : Output array  
1 H3VALUELENGTH (I4)           /* i /m : Length of output array
```

How To Invoke

```
PERFORM W3TEXT W3TEXT  
PERFORM W3TEXTDYNAMIC W3TEXT  
PERFORM W3TEXTLINE W3TEXT  
PERFORM W3TEXTLINEDYNAMIC W3TEXT  
PERFORM W3TEXTARRAY W3ARRAYVALUE W3VALUELENGTH
```

38 Write Newline to Output Area

Subroutine Name
W3NEWLINE

Description

Adds a single newline (##HTTP_NEWLINE) to the output area.

This subroutine will be deleted in one of the next versions. Use W3TEXTDYNAMIC ##HTTP_NEWLINE instead.

Parameters

* / NONE

How To Invoke

```
PERFORM W3NEWLINE
```


39 Text to HTML

Subprogram Name	Executable Example	Viewable Example
W3TEXT-TO-HTML	E3TX2HTM	E3TX2HTM
W3-ASCII-HTML-TABLE		

Description

Converts a string to HTML syntax. Useful if special characters are included.

The subprogram W3-ASCII-HTML-TABLE will be called from W3TEXT-TO-HTML and W3HTML and contains a list of all conversations that will be made.

This program can be changed and extended for the user's needs.

Parameters

```
1 W3HTML (A) DYNAMIC /* io/mH: HTML text conversion
```

How To Invoke

```
PERFORM W3TEXT-TO-HTML W3HTML
```


40 Text to XML

Subprogram Name	Executable Example	Viewable Example
W3TEXT-TO-XML	E3TX2XML	E3TX2XML
W3-ASCII-XML-TABLE		

Description

Converts a string to XML syntax. Useful if special characters are included.

The subprogram W3-ASCII-XML-TABLE will be called from W3TEXT-TO-XML and contains a list of all conversations that will be made.

This program can be changed and extended for the user's needs.

Parameters

```
1 W3XML (A) DYNAMIC /* io/mX: XML text conversion
```

How To Invoke

```
PERFORM W3TEXT-TO-XML W3XML
```


41 Text to URL

Subprogram Name	Executable Example	Viewable Example
W3TEXT-TO-URL	E3TX2URL	E3TX2URL
W3-ASCII-URL-TABLE		

Description

Converts a string to URL syntax. Useful if special characters are included.

The subprogram W3-ASCII-URL-TABLE will be called from W3TEXT-TO-URL and contains a list of all conversations that will be made.

This program can be changed and extended for the user's needs.

Parameters

```
1 W3URL (A) DYNAMIC /* io/mU: URL text conversion
```

How To Invoke

```
PERFORM W3TEXT-TO-URL W3URL
```


42 Replace Inside Return Document

Subroutine Name	Executable Example	Viewable Example	Resources
W3REPLACE	E3TEMPL	E3TEMPL	E3TEMPL.HTML

Description

Search the already written output page for a specific string and replace all occurrences with a new string. Use this with W3LOAD-RESOURCE for template processing. With the encoding parameter, the given data will be encoded before the replacement is done:

- " " -> no encoding
- "HTML" -> HTML encoding (e.g. <-> <)
- "URL" -> URL encoding
- "XML" -> XML encoding (e.g. <-> <)

Parameters

```
1 W3ENCODING (A) DYNAMIC BY VALUE /* i /m : encoding
1 W3OLD      (A) DYNAMIC BY VALUE /* i /m : old string
1 W3NEW      (A) DYNAMIC BY VALUE /* i /m : new string
```

How To Invoke

```
PERFORM W3REPLACE "$weather$" "fine, no clouds"
```


43 Load Resource

Subroutine Name	Executable Example	Viewable Example	Resources
W3LOAD-RESOURCE	E3RESOUR	E3RESOUR	E3SAVE.HTML

Description

Load a file from the resource directory of a given library into the output page.

If no library is specified, use the current library.

Use together with [W3REPLACE](#) for template processing.

Parameters

```
1 W3LIBRARY      (A8) BY VALUE OPTIONAL /* i /o : Natural Library ID  
1 W3RESOURCE-FILE (A) DYNAMIC BY VALUE /* i /m : File Name  
1 W3RESPONSE     (I4) OPTIONAL           /* o/o : Response
```

If the W3RESPONSE parameter is not specified, the Web Interface error processing is triggered if an error occurs.

If the W3RESPONSE parameter is specified, the parameter contains the Natural message number if an error occurred, or zero on success.

How To Invoke

```
PERFORM W3LOAD-RESOURCE W3LIBRARY W3RESOURCE-FILE  
PERFORM W3LOAD-RESOURCE " " "temp1.html"
```

Restriction

Load Resource is only available on Natural for Windows and UNIX supporting non-natural files/resources. Internally uses workfile 12.

44 Read Resource

Subroutine Name	Executable Example	Viewable Example	Resources
W3READ-RESOURCE	E3RESOUR	E3RESOUR	E3SAVE.HTML

Description

Read a resource file from the given library into a dynamic variable. If no library is specified, use the current library. Use together with [W3APPLY-XSLT](#) for template processing.

Parameters

```
1 W3LIBRARY  (A8) BY VALUE optional /* i /o : Natural Library ID
1 W3FILE      (A) DYNAMIC BY VALUE   /* i /m : File Name
1 W3DYN       (A) DYNAMIC           /* o/m : Read Resource
1 W3RESPONSE (I4) OPTIONAL        /* o/o : Response
```

If the `W3RESPONSE` parameter is not specified, the Web Interface error processing is triggered if an error occurs.

If the `W3RESPONSE` parameter is specified, the parameter contains the Natural message number if an error occurred, or zero on success.

How To Invoke

```
PERFORM W3READ-RESOURCE W3LIBRARY W3FILE W3DYN
PERFORM W3READ-RESOURCE W3LIBRARY W3FILE W3DYN W3RESPONSE
```

Restriction

Load Resource is only available on Natural for Windows and UNIX supporting non-natural files/resources. Internally uses workfile 12.

45 Write Resource

Subroutine Name	Executable Example	Viewable Example	Resources
W3WRITE-RESOURCE	E3RESOUR	E3RESOUR	E3SAVE.HTML

Description

Write a resource file to the given library and fill with a given dynamic variable. If no library is specified, use the current library.

Parameters

```
1 W3LIBRARY  (A8) BY VALUE OPTIONAL /* i /o : Natural Library
1 W3FILE      (A) DYNAMIC BY VALUE   /* i /m : File Name
1 W3DYN       (A) DYNAMIC BY VALUE   /* i /m : Read Resource
1 W3RESPONSE  (I4) OPTIONAL        /* o/o : Response ID
```

If the W3RESPONSE parameter is not specified, the Web Interface error processing is triggered if an error occurs.

If the W3RESPONSE parameter is specified, the parameter contains the Natural message number if an error occurred, or zero on success.

How To Invoke

```
PERFORM W3WRITE-RESOURCE W3LIBRARY W3FILE W3DYN
PERFORM W3WRITE-RESOURCE W3LIBRARY "Test.txt" W3DYN
PERFORM W3WRITE-RESOURCE W3LIBRARY W3FILE W3DYN W3RESPONSE
```

Restriction

Load Resource is only available on Natural for Windows and UNIX supporting non-natural files/resources. Internally uses workfile 12.

46 Check Resource

Subroutine Name	Executable Example	Viewable Example	Resources
W3CHECK-RESOURCE	E3RESOUR	E3RESOUR	E3SAVE.HTML

Description

Check if a read a resource file exists at the given library.

With the create flag, a new empty resource can be created if one does not already exist.

If no library is specified, use the current library.

Parameters

```
1 W3LIBRARY  (A8) BY VALUE OPTIONAL /* i /o : Natural Library ID
1 W3FILE     (A)  DYNAMIC BY VALUE   /* i /m : File Name
1 W3CREATE    (L)  BY VALUE          /* i /m : If true, create new file
1 W3PATH      (A)  DYNAMIC          /* o/m : Resource path
1 W3RESPONSE  (I4) OPTIONAL        /* o/o : Response
```

If the W3RESPONSE parameter is not specified, the Web Interface error processing is triggered if an error occurs.

If the W3RESPONSE parameter is specified, the parameter contains the Natural message number if an error occurred, or zero on success.

How To Invoke

```
PERFORM W3CHECK-RESOURCE W3LIBRARY W3FILE W3CREATE W3PATH  
PERFORM W3CHECK-RESOURCE " " 'test.html' TRUE W3PATH  
PERFORM W3CHECK-RESOURCE 1x 'test.html' TRUE W3PATH  
PERFORM W3CHECK-RESOURCE W3LIBRARY W3FILE W3CREATE W3PATH W3RESOURCE
```

Restriction:

Check Resource is only available on Natural for Windows and UNIX supporting non-natural files/resources.

47 Delete Resource

Subroutine Name	Executable Example	Viewable Example	Resources
W3DELETE-RESOURCE	E3RESOUR	E3RESOUR	E3SAVE.HTML

Description

Delete a resource file from the given library. If no library is specified, use the current library.

Parameters

```
1 W3LIBRARY  (A8) BY VALUE OPTIONAL /* i /o : Natural Library ID  
1 W3FILE      (A) DYNAMIC BY VALUE   /* i /m : File Name  
1 W3RESPONSE (I4) OPTIONAL          /* o/o : Response
```

If the W3RESPONSE parameter is not specified, the Web Interface error processing is triggered if an error occurs.

If the W3RESPONSE parameter is specified, the parameter contains the Natural message number if an error occurred, or zero on success.

How To Invoke

```
PERFORM W3DELETE-RESOURCE W3LIBRARY W3FILE  
PERFORM W3DELETE-RESOURCE " " 'test.html'  
PERFORM W3DELETE-RESOURCE 1x 'test.html'  
PERFORM W3DELETE-RESOURCE W3LIBRARY W3FILE W3RESPONSE
```

Restriction

Check Resource is only available on Natural for Windows and UNIX supporting non-natural files/resources.

48 Apply XSLT Processing on Return Document

Subroutine Name	Executable Example	Viewable Example
W3APPLY-XSLT-XML	E3XSLT	E3XSLT

Description

Call an XSLT processor with the given XML and replace the output page with the generated data.

Parameters

```
1 W3XSL      (A) DYNAMIC BY VALUE /* i /m : xsl template  
1 W3XML      (A) DYNAMIC BY VALUE /* i /m : xml data  
1 W3RESPONSE (I4) OPTIONAL           /* o/o : result
```

If the W3RESPONSE parameter is not specified, the Web Interface error processing is triggered if an error occurs.

If the W3RESPONSE parameter is specified, the parameter contains the Natural message number if an error occurred, or zero on success.

How To Invoke

```
PERFORM W3APPLY-XSLT-XML W3XSL W3XML  
PERFORM W3APPLY-XSLT-XML W3XSL W3XML W3RESPONSE
```

Restriction

Apply XSLT Processing is only available on Natural for Windows and UNIX that contain the User Exit USR 6001P.

49 Apply XSLT Processing on Return Document from Resource

Subroutine Name	Executable Example	Viewable Example	Resource
W3APPLY-XSLT-RESOURCE	E3XSLT2	E3XSLT2	E3XSLT2.XML E3XSLT2.XSL

Description

Call an XSLT processor with the given XSL Resource and replace the output page with the generated data.

Parameters

```
1 W3LIBRARY      (A8) BY VALUE OPTIONAL /* i /o : Natural Library ID
1 W3RESOURCE-FILE (A) DYNAMIC BY VALUE   /* i /m : File Name
1 W3RESPONSE     (I4) OPTIONAL          /* o/o : result
```

If the W3RESPONSE parameter is not specified, the Web Interface error processing is triggered if an error occurs.

If the W3RESPONSE parameter is specified, the parameter contains the Natural message number if an error occurred, or zero on success.

How To Invoke

```
PERFORM W3APPLY-XSLT-RESOURCE W3XSL W3XML
```

Restriction

Apply XSLT Processing is only available on Natural for Windows and UNIX that contain the User Exit USR6001P.

50

Load Style Sheet from the Resource Directory and Apply XSLT Processing on Return Document

Subroutine Name	Executable Example	Viewable Example	Used Resource
W3APPLY-XSLT-XML-TO-DYNAMIC	E3XSLT3	E3XSLT3	E3XSLT3.HTML E3XSLT3.XSL E3XSLT3.XML

Description

Call an XSLT processor and transform the output page with a stylesheet loaded from the resource directory of the given Natural library. If no library is specified, use the current library.

Parameters

```
1 W3XSLT      (A) DYNAMIC BY VALUE /* i /m : xslt
1 W3XML       (A) DYNAMIC BY VALUE /* i /m : xml
1 W3RESULT    (A) DYNAMIC           /* o/m : result
1 W3RESPONSE  (I4) OPTIONAL        /* o/o : result
```

If the W3RESPONSE parameter is not specified, the Web Interface error processing is triggered if an error occurs. If the W3RESPONSE parameter is specified, the parameter contains the Natural message number if an error occurred, or zero on success.

How To Invoke

```
PERFORM W3APPLY-XSLT-XML-TO-DYNAMIC W3XSLT W3XML W3RESULT
PERFORM W3APPLY-XSLT-XML-TO-DYNAMIC W3XSLT W3XML W3RESULT W3RESPONSE
```

Restriction

Load Style Sheet and Apply XSLT Processing is available only on Natural for Windows and UNIX supporting non-natural files/resources and that contain the User Exit USR 6001P. Internally uses workfile 12.

51 Read Output Page

Subroutine Name	Executable Example	Viewable Example
W3READ-OUTPUT	E3RESOUR	E3RESOUR

Description

Read into dynamic variables the output page already written.

Parameters

```
1 W3HEADER (A) DYNAMIC /* o/m : written header  
1 W3BODY   (A) DYNAMIC /* o/m : written body
```

How To Invoke

```
PERFORM W3READ-OUTPUT W3HEADER W3BODY
```


52 Anchor

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-ANCHOR	H3ANCHOR	E3ANCHOR	E3ANCHOR

Description

Creates a hyperlink.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

Supported Attributes

NAME=*string*

Parameters

```
1 H3URL          (A) DYNAMIC /* i /m : URL of the Link. Enter
*                  /*      'THIS' to reference
*                  /*      the current page as URL.
1 H3NAME         (A) DYNAMIC /* i /M : Name of the anchor.
1 H3STRING        (A) DYNAMIC /* i /MH: String to be displayed
*                  /*      as anchor text.
```

How To Invoke

```
PERFORM H3-ANCHOR H3URL H3NAME H3STRING
```

53 Button

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-BUTTON	H3BUTTON	E3BUTTON	E3BUTTON

Description

Creates a reset/submit button.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

```
<INPUT TYPE="submit|reset|image" NAME="string"> </INPUT>
```

Supported Attributes

VALUE="*string*", SRC="*URL*"

Parameters

```
1 H3TYPE  (A1)          /* i /m : 'R' reset button
*                  /* 'S' submit button
*                  /* 'I' submit button with image
1 H3NAME  (A) DYNAMIC /* i /M : Name of the button
1 H3VALUE (A) DYNAMIC /* i /M : Value of the input variable
1 H3URL   (A) DYNAMIC /* i /M : URL of the picture to be used
```

How To Invoke

```
PERFORM H3-BUTTON H3TYPE H3NAME H3VALUE H3URL
```

54 Checkbox Group

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-CHECKBOX-GROUP	H3RCGROU	E3RCGROU	E3RCGROU

Description

Creates a checkbox group. The group can be formatted inside a table.

Appearance

```
<INPUT TYPE="CHECKBOX" NAME="string">
```

Supported Attributes

VALUE=*string*, CHECKED

Parameters

```
1 H3ARRAYCOUNT    (I4)          /* i /m : Number of group elements
1 H3ARRAYNAME     (A/1:V) dynamic /* i /m : Name of the group variable
1 H3ARRAYVALUE    (A/1:V) dynamic /* i /M : Default value of the
*                  /* group variable
1 H3ARRAYLABEL    (A/1:V)         /* i /MH: Label of the group element
1 H3ARRAYCHECKED  ( L/1:V)        /* i /M : Button selected by default
1 H3LINEBREAK     ( L)           /* i /m : Set line breaks between by
*                  /* the elements
1 H3ROW           (N4)           /* i /m : Set number of rows for
*                  /* tables
1 H3COLUMN        (N4)           /* i /m : Set number of columns for
*                  /* tables
```

How To Invoke

```
PERFORM H3-CHECKBOX-GROUP H3ARRAYCOUNT H3ARRAYNAME(*)
      H3ARRAYVALUE(*) H3ARRAYLABEL(*)
      H3ARRAYCHECKED(*) H3LINEBREAK H3ROW H3COLUMN
```

55 Comment Line

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-COMMENT	H3COMMEN	E3COMMEN	E3COMMEN

Description

Creates a comment line inside an HTML page.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

```
<!-- value -->
```

Parameters

```
1 H3VALUE (A) DYNAMIC /* i /m : Value to set as comment
```

How To Invoke

```
PERFORM H3-COMMENT H3VALUE
```


56 Level n Header

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-HEADER	H3HEADER	E3HEADER	E3HEADER

Description

Creates a header of a specified level. Levels 1 to 6 are allowed.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

<H1> </H1> or

<H2> </H2> or

<H3> </H3> or

<H4> </H4> or

<H5> </H5> or

<H6> </H6>

Parameters

```
1 H3LEVEL (N2)      /* i /m : Level of the header  
1 H3HTML  (A) DYNAMIC /* i /mH: HTML text to be set
```

How To Invoke

```
PERFORM H3-HEADER H3LEVEL H3HTML
```

57 Image

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-IMAGE	H3IMAGE	E3IMAGE	E3IMAGE

Description

Displays an image. The image itself cannot be saved inside Natural. Therefore, all pictures must be saved with the HTTP Server.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

Supported Attributes

ALT=*string*, HEIGHT=*n*, WIDTH=*n*, ALIGN=*left|right|top|middle|bottom*

Parameters

```
1 H3URL      (A) DYNAMIC /* i /m : URL of the picture source
1 H3STRING   (A) DYNAMIC /* i /M : Alternative name string
*           /* for non-GUI browsers
1 H3HEIGHT   (N4)    /* i /M : Height if the picture
1 H3WIDTH   (N4)    /* i /M : Width of the picture
1 H3ALIGN   (A1)    /* i /M : Align the picture to
*           /* 'L' Left
*           /* 'R' Right
*           /* 'T' Top
*           /* 'B' Bottom
*           /* 'M' Middle
```

How To Invoke

```
PERFORM H3-IMAGE H3URL H3STRING H3HEIGHT H3WIDTH H3ALIGN
```

58 Input

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-INPUT	H3INPUT	E3INPUT	E3INPUT

Description

Creates an input field. Possible field types are text, password and hidden.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

```
<INPUT TYPE="text|password|hidden" NAME="string">
```

Supported Attributes

VALUE=*string*, MAXLENGTH=*n*, SIZE=*n*

Parameters

```
1 H3TYPE  (A1)          /* i /m : Type of the input field
*
*                      /*          'T' Text (default)
*
*                      /*          'P' Password
*
*                      /*          'H' Hidden
1 H3NAME  (A) DYNAMIC /* i /M : Name of the input variable
1 H3VALUE (A) DYNAMIC /* i /M : Default value of the input variable
1 H3SIZE   (N4)          /* i /M : Size of the input box
1 H3MAX    (N4)          /* i /M : Maximum length of the input text
```

How To Invoke

```
PERFORM H3-INPUT H3TYPE H3NAME H3VALUE H3SIZE H3MAX
```

59 Line Break

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-LINE-BREAK	H3LBREA	E3LBREAK	E3LBREAK
H3-LINE_BREAK	H3LBREAK		

Description

Forces a line break, with or without additional HTML text.

Changes from previous versions

Both versions can be used equivalently, because the parameter is marked as optional. Use only the version H3-LINE-BREAK. H3-LINE-BREAK will be removed in one of the next versions.

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE. There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

Parameters

1. H3-LINE-BREAK

```
1 H3HTML (A) DYNAMIC /* i /0H: HTML text after the line break
```

2. H3-LINE_BREAK

```
1 H3HTML (A) DYNAMIC /* i /OH: HTML text after the line break
```

How To Invoke

```
PERFORM H3-LINE-BREAK  
PERFORM H3-LINE-BREAK 1X  
PERFORM H3-LINE-BREAK H3HTML
```

60 Form

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-OPEN-FORM	H3OFORM	E3FORM	E3FORM
H3-CLOSE-FORM	H3CFORM		

Description

Creates a form. You must perform H3-OPEN-FORM before and H3-CLOSE-FORM afterwards.

If no H3-CLOSE-FORM is performed, H3-CLOSE-HTML will close all open forms.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

```
<FORM ACTION="URL" METHOD="get|post"> </FORM>
```

Supported Attributes

ACTION=*URL*, METHOD=*get|post*

Parameters

1. H3-OPEN-FORM

```
1 H3METHOD (A1)          /* i /m : 'G' GET
*                      /*      : 'P' POST
1 H3URL    (A) DYNAMIC /* i /m : URL to be called
```

2. H3-CLOSE-FORM

```
/* none
```

How To Invoke

```
PERFORM H3-OPEN-FORM H3METHOD H3URL  
PERFORM H3-CLOSE-FORM
```

61 HTML Document

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-OPEN-HTML	H3OHTML	E3HTML	E3HTML
H3-OPEN-HTML-JAVASCRIPT	H3CHTML		
H3-CLOSE-HTML			

Description

Creates an HTML document with a head, title and beginning of body.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

1. H3-OPEN-HTML

```
<HTML>
<HEAD>
<TITLE>TITLE</TITLE>
</HEAD>
<BODY BACKGROUND="URL", BGCOLOR="#RPG">
```

2. H3-OPEN-HTML-JAVASCRIPT

```
<HTML>
<HEAD>
<SCRIPT LANGUAGE='JavaScript' SRC='URL'></SCRIPT>
<SCRIPT LANGUAGE='JavaScript'>
<!-- hide script from old browsers
PROGRAM
// end hiding from old browsers -->
```

```
</SCRIPT>
<TITLE>TITLE</TITLE>
</HEAD>
<BODY BACKGROUND="URL", BGCOLOR="#RGB">
```

3. H3-CLOSE-HTML

```
</BODY>
</HTML>
```

Supported Attributes

```
BACKGROUND=URL, BGCOLOR="#RGB, SRC='URL'
```

Parameters

1. H3-OPEN-HTML

```
1 H3TITLE      (A) DYNAMIC    /* i /m: Title of the HTML document
1 H3BGCOLOR    (A) DYNAMIC    /* i /M: Background colour
1 H3BGPICUTURE (A) DYNAMIC    /* i /M: Background picture
```

2. H3-OPEN-HTML-JAVASCRIPT

```
1 H3TITLE      (A) DYNAMIC    /* i /m: Title of the HTML document
1 H3BGCOLOR    (A) DYNAMIC    /* i /M: Background colour
1 H3BGPICUTURE (A) DYNAMIC    /* i /M: Background picture
1 H3JAVASRC    (A) DYNAMIC    /* i /M: ULR to a JavaScript source
1 H3JAVA        (A/1:V) DYNAMIC /* i /M: JavaScript
1 H3JAVACOUNTER (I4)          /* i /M: Number of JavaScript source lines
1 H3ONLOAD      (A) DYNAMIC    /* i /M: onload event handler
1 H3ONUNLOAD    (A) DYNAMIC    /* i /M: onunload event handler
```

3. H3-CLOSE-FORM

```
/* none
```

How To Invoke

```
PERFORM H3-OPEN-HTML H3TITLE H3BGCOLOR H3BGPICUTURE
PERFORM H3-OPEN-HTML-JAVASCRIPT H3TITLE H3BGCOLOR H3BGPICUTURE H3JAVASRC H3JAVA
H3JAVACOUNTER H3ONLOAD H3ONUNLOAD
PERFORM H3-CLOSE-HTML
```

62 List

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-OPEN-LIST	H3OLIST	E3LIST	E3LIST
H3-LIST-ITEM	H3LISTI		
H3-CLOSE-LIST	H3CLIST		

Description

Creates various types of lists. Possible types are:

- unordered list,
- ordered list,
- menu-item list and
- directory list.

Cascading lists of up to 10 levels are supported. It is also possible to close more than one level at once.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

1. H3-OPEN-LIST

<DIR> or
<MENU> or
 or

2. H3-LIST-ITEM

```
<LI>
```

3. H3-CLOSE-LIST

```
</DIR> or  
</MENU> or  
</OL> or  
</UL>
```

Supported Attributes

```
TYPE=disc|square|circle TYPE=1|a|A|i|I
```

Parameters

1. H3-OPEN-LIST

```
1 H3TYPE  (A1) /* i /m: Set list as:  
*          /* 'O' ordered list  
*          /* 'U' unordered list  
*          /* 'D' directory list  
*          /* 'M' menu list  
1 H3BULLET (A1) /* i /m: Type of list if ordered list:  
*          /* '1' Arabic numbers (default) (1, 2, 3, ...)  
*          /* 'a' Alphanumeric, lowercase (a, b, c, ...)  
*          /* 'A' Alphanumeric, uppercase (A, B, C, ...)  
*          /* 'i' Roman numbers, lowercase (i, ii, iii, ...)  
*          /* 'I' Roman numbers, uppercase (I, II, III, ...)  
*          /* i /m: Type of bullet if unordered list:  
*          /* 'D' Disc  
*          /* 'S' Square  
*          /* 'C' Circle
```

2. H3-LIST-ITEM

```
1 H3VALUE (A) DYNAMIC /* i /m: Item text
```

3. H3-CLOSE-LIST

```
1 H3LEVEL (N2)      /* i /m: Levels to be closed
```

How To Invoke

```
PERFORM H3-OPEN-LIST H3TYPE H3BULLET  
PERFORM H3-LIST-ITEM H3VALUE  
PERFORM H3-CLOSE-LIST H3LEVEL
```


63 Paragraph

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-PARAGRAPH	H3PARAGR	E3PARAGR	E3PARAGR

Description

Creates a new paragraph.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

<P ALIGN="left|right|center"> or <P>

Supported Attributes

ALIGN=left|right|center

Parameters

```
1 H3ALIGN (A1)      /* i /m : Align the paragraph to:  
*          /*      'L' Left (default)  
*          /*      'R' Right  
*          /*      'C' Center  
1 H3HTML  (A) DYNAMIC /* i /mh: HTML text after the paragraph
```

How To Invoke

```
PERFORM H3-PARAGRAPH H3ALIGN H3HTML
```

64 Radio Button Group

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-RADIO-GROUP	H3RBGROU	E3RBGROU	E3RBGROU

Description

Creates a radio button group. The group can be formatted inside a table.

Appearance

```
<INPUT TYPE=RADIO NAME=string>
```

Supported Attributes

VALUE=*string*, CHECKED

Parameters

```
1 H3ARRAYCOUNT (I4)          /* i /m : Number of group elements
1 H3NAME      (A) dynamic    /* i /m : Name of the group variable
1 H3ARRAYVALUE (A/1:V) dynamic /* i /M : Default value of the default group
*               /*           variable
1 H3ARRAYLABEL (A/1:V)        /* i /mH: Label of the group element
1 H3ISCHECKED (I4)           /* i /M : Number of default selected
*               /*           button
1 H3LINEBREAK  (L)           /* i /M : Set line breaks between
*               /*           buttons
1 H3ROW       (N4)            /* i /m : Set number of rows for tables
1 H3COLUMN    (N4)            /* i /m : Set number of columns for
*               /*           tables
```

How To Invoke

```
PERFORM H3-RADIO-GROUP H3ARRAYCOUNT H3NAME  
      H3ARRAYVALUE(*) H3ARRAYLABEL(*)  
      H3ISCHECKED H3LINEBREAK H3ROW H3COLUMN
```

65 Horizontal Rule

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-RULE	H3RULE	E3RULE	E3RULE

Description

Creates a horizontal rule with a width specified in percentage points.

Appearance

```
<HR> or  
<HR WIDTH="p%">
```

Supported Attributes

WIDTH=*p%*

Parameters

```
1 H3WIDTH (N4) /* i /m : Width in percent
```

How To Invoke

```
PERFORM H3-RULE H3WIDTH
```


66 Scrolling List

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-SCROLLING-LIST	H3SCLIST	E3SCLIST	E3SCLIST

Description

Creates a scrolling list. It can be displayed as a combo box or as a list box. Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

```
<SELECT NAME=string>
<OPTION> </OPTION>
</SELECT>
```

Supported Attributes

SIZE=*n*, MULTIPLE

VALUE=*string*, SELECTED

Parameters

```
1 H3SIZE          (N4)           /* i /m : Number of lines:  
*                                /*      =1 combo box  
*                                /*      >1 list box  
1 H3ARRAYCOUNT   (I4)           /* i /m : Number of list elements  
1 H3NAME          (A)dynamic    /* i /m : Name of the group variable  
1 H3ARRAYVALUE    (A/1:V) dynamic /* i /M : Default value of the list values  
1 H3ARRAYLABEL    (A/1:V) dynamic /* i /MH: Label of the list elements  
1 H3ARRAYSELECTED (L/1:V)       /* i /M : Elements selected by  
*                                /*      default  
1 H3MULTIPLE      (L)            /* i /M : Multiple selection allowed
```

How To Invoke

```
H3-SCROLLING-LIST H3SIZE H3ARRAYCOUNT H3NAME  
      H3ARRAYVALUE(*) H3ARRAYLABEL(*)  
      H3ARRAYSELECTED(*) H3MULTIPLE
```

67 Table

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-TABLE	H3TABLE	E3TABLE	E3TABLE
H3-TABLE-COLOR	H3TABLEC		

Description

Creates a simple table for a given array. With H3-TABLE-COLOR, for headline and table, different background colors can be set. The rows will be colored alternately.

Appearance

```
<TABLE>
<TR>
<TH>... </TH>
</TR>
...
<TR>
<TD>... </TD>
</TR>
...
</TABLE>
```

Supported Attributes

ALIGN=left|right|center , BORDER=n, NOWRAP

Parameters**1. H3-TABLE**

1 H3ROW	(N4)	/* i /m : Number of rows
1 H3COLUMN	(N4)	/* i /m : Number of columns
1 H3ARRAY2VALUE	(A/1:V,1:V)dynamic	/* i /mh: Table elements
1 H3ARRAY2ALIGN	(A1/1:V,1:V)	/* i /M : Alignment of the table cells * ' L' Left (default) * ' R' Right * ' C' Center
1 H3ARRAY2NOWRAP	(L/1:V,1:V)	/* i /m : No automatic wrapping
1 H3HEADLINE	(L)	/* i /M : 1st line as headline
1 H3ALIGN	(A1)	/* i /M : Alignment of the table * ' L' Left (default) * ' R' Right * ' C' Center
1 H3SUPPRESSEEMPTY	(L)	/* i /m : Set to TRUE if cell is * to be displayed * despite being empty
1 H3ISHTML	(L)	/* i /m : Transform value to * HTML
1 H3BORDER	(N4)	/* i /M : Set border size

2. H3-TABLE-COLOR

1 H3ROW	(N4)	/* i /m : Number of rows
1 H3COLUMN	(N4)	/* i /m : Number of columns
1 H3TITLECOLOR	(A032)	/* i /M : Color of headline
1 H3LINECOLOR	(A032)	/* i /M : Color of lines
1 H3ARRAY2VALUE	(A/1:V,1:V) dynamic	/* i /mh: Table elements
1 H3ARRAY2ALIGN	(A001/1:V,1:V)	/* i /m : Alignment of the table cells * ' L' Left (default) * ' R' Right * ' C' Center
1 H3ARRAY2NOWRAP	(L/1:V,1:V)	/* i /m : No automatic wrapping
1 H3HEADLINE	(L)	/* i /m : 1st line as headline
1 H3ALIGN	(A1)	/* i /M : Alignment of the table * ' L' Left * ' R' Right * ' C' Center (default)
1 H3SUPPRESSEEMPTY	(L)	/* i /m : Set to TRUE if cell is * to be displayed * despite being empty
1 H3ISHTML	(L)	/* i /m : Transform value to * HTML
1 H3BORDER	(N4)	/* i /m : Set border size

How To Invoke

```
PERFORM H3-TABLE H3ROW H3COLUMN H3ARRAY2VALUE(*,*)  
    H3ARRAY2ALIGN(*,*) H3ARRAY2NOWRAP(*,*)  
    H3HEADLINE H3ALIGN H3SUPPRESSEEMPTY  
    H3ISHTML H3BORDER  
  
PERFORM H3-TABLE-COLOR H3ROW H3COLUMN H3TITLECOLOR H3LINECOLOR  
    H3ARRAY2VALUE(*,*) H3ARRAY2ALIGN(*,*) H3ARRAY2NOWRAP(*,*)  
    H3HEADLINE H3ALIGN H3SUPPRESSEEMPTY  
    H3ISHTML H3BORDER
```


68 Universal Tag

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-TAG	H3TAG	E3TAG	E3TAG

Description

Creates a universal tag (tag template) inside an HTML page. This tag template creates the framework into which code can be written.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

<tag> </tag>

Parameters

```
1 H3PRE  (A) DYNAMIC /* i /m : Open tag value
1 H3HTML (A) DYNAMIC /* i /m : HTML inside the tag
1 H3POST (A) DYNAMIC /* i /m : Close tag value
```

How To Invoke

```
PERFORM H3-TAG H3PRE H3HTML H3POST
```

69 Text Area

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-TEXT-AREA	H3TXAREA	E3TXAREA	E3TXAREA

Description

Creates a text area. Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

```
<TEXTAREA NAME="string"> </TEXTAREA>
```

Supported Attributes

ROWS=*n*, COLS=*n*

Parameters

```
1 H3ARRAYCOUNT (I4)          /* i /m : Number of text
1 H3NAME      (A) dynamic    /* i /m : Name of the text variable
1 H3ARRAYTEXT (A/1:V) dynamic /* i /M : Default value of the text variable
1 H3ROW       (N4)           /* i /M : Set number of rows
1 H3COLUMN    (N4)           /* i /M : Set number of columns
```

How To Invoke

```
PERFORM H3-TEXT-AREA H3ARRAYCOUNT H3NAME H3ARRAYTEXT(*)
      H3ROW H3COLUMN
```

70 Text to URL - Decoded

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-TEXT-TO-URL	H3TX2URL	E3TX2URL	E3TX2URL
H3-ASCII-URL-TABLE			

Description

Converts a string to URL-decoded syntax. Useful if special characters are included. Use [W3-TEXT-TO-URL](#) instead of H3-TEXT-TO-URL. Use [W3-ASCII-URL-TABLE](#) instead of H3-ASCII-URL-TABLE.

The subprogram W3-ASCII-URL-TABLE will be called from H3-TEXT-TO-URL and contains a list of all conversions that will be made. This program can be changed and extended for the user's needs.

Parameters

```
1 H3COUNT  (I4)    /* o/m : Length of the converted string  
1 H3STRING (A250) /* io/m : URL-decoded text after conversion
```

How To Invoke

```
PERFORM H3-TEXT-TO-URL H3COUNT H3STRING
```


71 Time/Date String

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-TIME_DATE	H3TIMDAT	E3TIMDAT	E3TIMDAT
H3-TIME-DATE	H3TIMDA		

Description

Creates a 'generated: ...' string using the LOG time or an HTTP-compatible time/date string with offset, using the current time/date (because GMT or offset to GMT is not known by Natural).

Appearance

generated: *time/date*

Parameters

1. H3-TIME_DATE

```
/* none
```

2. H3-TIME-DATE

```
1 H3ADDMINUTE (I4) /* i /m : Adds minutes to time
1 H3ADDDAY   (I4) /* i /m : Adds days to date
1 H3DATETIME (A29) /* o/m : Generated string
```

How To Invoke

```
PERFORM H3-TIME_DATE  
PERFORM H3-TIME-DATE H3ADDMINUTE H3ADDDAY H3DATETIME
```

72 List all Natural Libraries

Subprogram Name	Executable Example	Viewable Example
NAT-LIB	NAT-LIB NAT-LIB?FNAT=N	NAT-LIB

Description

Generates an HTML page and displays all available Natural libraries. If no FNAT parameter is given, the default user libraries will be displayed.

Parameters

FNAT=	N = system libraries U = user libraries (default)
EXPIRE=	Adds days to current date and sets it as expiry date.
START=	Wildcard selection for the displayed object set.

How To Invoke

```
NAT-LIB NAT-LIB?FNAT=N
```


73 Run Online Natural Web Interface Subprograms

Natural Program
WEB-ONL

Description

For reasons of debugging or testing, it is useful to run Natural Web Interface subprograms online. The output of the generated page will be saved as a Natural text object. Lines longer than 92 characters will be split. It is possible to set environment variables. If the variables should be set as server variables, add an ampersand in front of the name.

How To Invoke

Run Program WEB-ONL from the Natural *next* prompt.

74 Generate Natural Subprogram to use with Natural Web Interface

Natural Program	Executable Generation Result	Viewable Generation Result
WEB-WIZ	Basic Subroutines HTML Extension	HTTPApi HTMLApi

Description

Generates a default program. This function will be deleted in one of the next versions. Under Windows, use the [Web Interface Plug-In](#).

Input Map

```
12:12:40      ***** Natural Web Subprogram Wizard *****      2003-01-15
               - Main Menu -          Library SYSWEB

Subprogram Name ..... DUMMY_
Title ..... HTTP/HTML API WIZARD
Header ..... HTTP/HTML API WIZARD

Use HTML extension .. X
```

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
Exit

How To Invoke

Run Program WEB-WIZ from the Natural *next* prompt.

75 List Directory of a Natural Library

Subprogram Name	Executable Example	Viewable Example
NAT-DIR	NAT-DIR?lib=sysweb NAT-DIR?lib=sysweb&start=E3*	NAT-DIR

Description

Generates an HTML page with the directory information of a Natural library. If no library parameter has been defined, the current library will be displayed.

Parameters

LIB=	Natural LIBRARY
EXPIRE=	Adds days to current date and sets it as expiry date.
START=	Wildcard selection for the object set displayed.

How To Invoke

```
nat-dir?lib=sysweb
```


76

List All Parameters Passed From a HTTP Server To a Called Natural Subprogram

Subprogram Name	Executable Example	Viewable Example
NAT-ENV	NAT-ENV	NAT-ENV

Description

Generates an HTML page with all parameters passed from the HTTP server to a called Natural subprogram.

How To Invoke

```
nat-env
```


77

Return an HTML Page Saved as Natural Source Object

Subprogram Name	Executable Example	Viewable Example	Text Object
NAT-HTML	NAT-HTML?lib=sysweb&source=t3-html	NAT-HTML	T3-HTML

Description

Displays an HTML page saved as a Natural source object.

Parameters

LIB=	Natural LIBRARY
SOURCE=	SOURCE NAME

How To Invoke

```
nat-html?lib=sysweb&source=HTML
```


78

List the Current Natural Web Interface Settings

Subprogram Name	Executable Example	Viewable Example
NAT-INFO	NAT-INFO	NAT-INFO

Description

Generates an HTML page with information about your HTTP Browser, HTTP Server, communication software (RPC/DCOM) and Natural environment.

How To Invoke

```
nat-info
```


79 List Source of Natural Object

Subprogram Name	Executable Example	Viewable Example
NAT-LIST	NAT-LIST?lib=sysweb&source=h3image	NAT-LIST

Description

Generates an HTML page with the listing of a Natural source object.

Parameters

LIB=	Natural LIBRARY
SOURCE=	SOURCE NAME
EXPIRE=	Adds days to current date and sets it as expiry date.
LINE-NUMBERS=	The only value possible is OFF

How To Invoke

```
nat-list?lib=sysweb&source=H3IMAGE
```


80 Online Documentation

Subprogram Name	Executable Example
NAT-DOCU	NAT-DOCU

Description

Displays the online documentation saved as Natural source objects.

Parameters

LIB=	Natural LIBRARY
SOURCE=	SOURCE NAME
EXPIRE=	Adds days to current date and sets it as expiry date.

How To Invoke

```
nat-docu
```


81 List non-Natural File - Resource

Subprogram Name	Executable Example	Viewable Example
NAT-RES	NAT-RES?source=e3xslt2.xml&lib=sysweb	NAT-RES

Restriction

Only available on platforms with shared resources.

Description

Generates an HTML page with the listing of a Natural source object.

Parameters

LIB=	Natural LIBRARY
SOURCE=	Resource name with extension

How To Invoke

```
nat-res?source=e3xslt2.xml&lib=sysweb
```


82

Natural Web Online Documentation SYSWEB3

■ General Information	260
■ Basic Modules	260
■ Template / XSLT Processing	262
■ HTML Extension	263
■ Utilities	264
■ Demonstration Applications	265

This section covers the following topics:

General Information

The online documentation files are prefixed with E3* and T3*. The online documentation contains example programs that can be displayed and executed online. Depending on your installation of the Natural Web Interface, call the subprogram NAT-DOCU from the library SYSWEB3 to display the main page of online documentation at your web browser.

Example of the URL to call the online documentation:

`http://yourserver/yourcgi3/sysweb3/nat-docu`

 **Note:** To display the online documentation, the HTTP Server Extensions of the Natural Web Interface must be installed and a correct Natural RPC/DCOM Server has to be started. To access the program USR1057N, of library SYSEXT, add a steplib to SYSEXT or copy the programs to your system library.

Definition of Parameters	
i /	Input Variable.
o /	Output Variable.
/o	Optional Variable.
/m	Mandatory Variable (has to be specified) .
/M	Mandatory Variable. If empty, specific parts will not be generated.
/H	Variable will be translated to HTML.
/X	Variable will be translated to XML.
/U	Variable will be translated to URL.

Basic Modules

The basic module names of the Natural Web Interface, start with the prefix W3.

They provide the communication between Natural subprograms and the HTTP Server Extension. All other programs of the Natural Web Interface use these programs.

It is possible to make some administrative changes to define the amount and format of the transferred data, to change conversion tables and to change the error page.

Program	Description
W3BINARY	Writes binary data to the internal binary buffer.
W3CLEAR	Clear the output page.
W3CONTENT-TYPE	Sets the content type of a document.
W3COUNTER	Returns the maximum number of bytes and the number of currently written or free bytes in the output area .
W3ERROR W3ERROR-TEMPLATE W3ERROR-TEMPLATE-XML W3ERROR-TEXT	Generates a default error page .
W3HTML W3HTMLLINE W3HTMLDYNAMIC W3HTMLLINEDYNAMIC W3HTMLARRAY	Writes an HTML string to the output page and converts special characters to an HTML-valid representation.
W3HTTP W3HTTPDYNAMIC W3HTTP-HEADER W3HTTPARRAY	Writes HTTP settings to the output page.
W3INFO	Returns internal settings.
W3INIT W3END	Initializes SYSWEB3 and prepares the document for returning to the HTTP server.
W3LIMIT	Sets the maximum return page size. See W3COUNTER above.
W3LIST-ENVIRONMENT W3LIST-ENVIRONMENT-TO-DYNAMIC	Lists all variables .
W3LOCATION	Sets the location of a page that is to be called instead this page.
W3MIME-DATA	Evaluates the required data type (binary or alpha) for the given mime-type.
W3MIME-TYPE	Evaluates the file extension for a given mime-type . Evaluates the mime-type for a given file extension.
W3READ-ENVIRONMENT W3READ-ENVIRONMENT-ARRAY W3READ-ENVIRONMENT-TO-DYNAMIC	Reads a variable sent by the HTTP server.
W3READ-ENVIRONMENT-TEXTAREA W3READ-ENVIRONMENT-TEXTAREA-DYN	Reads a variable set by a text area and splits the variable into separate lines.
W3READ-ENVIRONMENT-GROUP	Reads all environment variables with the same name.
W3READ-INPUT	Reads all data delivered from the HTTP server.
W3TEXT W3TEXTLINE	Writes a text string to the output page.

Program	Description
W3TEXTDYNAMIC W3TEXTLINEDYNAMIC W3TEXTARRAY	
W3NEWLINE	Writes a linebreak to the output page.
W3SOURCE-TO-XARRAY	Reads a complete Natural source into one single x-array.
W3TEXT-TO-HTML W3-ASCII-HTML-TABLE	Converts ASCII to the specific encoding of HTML .
W3TEXT-TO-XML W3-ASCII-XML-TABLE	Converts ASCII to the specific encoding of XML .
W3TEXT-TO-URL W3-ASCII-URL-TABLE	Converts ASCII to the specific encoding of URL .

Template / XSLT Processing

Program	Description
W3REPLACE	Search the output page for a specific string and replace with a new one.
W3READ-OUTPUT	Read the already written output page.

Program	Description
W3REPLACE	Search the output page for a specific string and replace with a new one.
W3LOAD-RESOURCE	Load a file from the resource directory of a specific Natural library as result document.
W3READ-RESOURCE	Read a file from the resource directory of a specific Natural library into a dynamic variable.
W3WRITE-RESOURCE	Write a dynamic variable to a file at the resource directory of a specific Natural library.
W3CHECK-RESOURCE	Check if resource exists. If not, a new resource can be created.
W3DELETE-RESOURCE	Delete a resource from the resource directory.
W3APPLY-XSLT-XML	Apply a stylesheet to transformation on the output page.
W3APPLY-XSLT-RESOURCE	Apply a stylesheet , saved as resource on the output page.
W3APPLY-XSLT-XML-TO-DYNAMIC	Apply a stylesheet , to transformation to an dynamic variable.
W3LIST-RESOURCE	List all resource files of a specific Natural library.
W3READ-OUTPUT	Read the already written output page.

HTML Extension

The prefix H3 is used for all program names of the HTML extension. This external subroutines, delivered with source code, generate HTML and use the basic modules of the Natural Web Interface.

The programs do not cover the complete syntax of HTML. They also do not support special enhancements of specific web browser. If you need enhancements, feel free to extend the programs delivered in source code, or create your own ones.

Program	Description	HTML Tag
H3-ANCHOR	Creates an anchor tag.	<A... >...
H3-BUTTON	Creates reset/submit buttons .	<INPUT... >
H3-CHECKBOX-GROUP	Generates a checkbox group.	<INPUT... >
H3-COMMENT	Creates a comment line.	<!... >
H3-HEADER	Generates a header tag.	<Hn>
H3-IMAGE	Generates an image tag.	<IMG... >
H3-INPUT	Generates a text, password or hidden input field.	<INPUT... >
H3-LINE-BREAK H3-LINE_BREAK	Sets a line break with or without additional text.	
H3-OPEN-FORM H3-CLOSE-FORM	Starts a form tag for input fields.	<FORM>... </FORM>
H3-OPEN-HTML H3-OPEN-HTML-JAVASCRIPT H3-CLOSE-HTML	Starts and ends an HTML Document.	<HTML>... </HTML>
H3-OPEN-LIST H3-LIST-ITEM H3-CLOSE-LIST	Generates an ordered, unordered, menu or directory list <DIR>... ... </DIR> <MENU>... ... </MENU>
H3-PARAGRAPH	Generates a paragraph with additional text.	<P... >
H3-RADIO-GROUP	Generates a radio button group.	<INPUT... >
H3-RULE	Sets a horizontal rule .	<HR... >
H3-SCROLLING-LIST	Generates a scrolling list.	<SELECT> ... <OPTION> ... <SELECT>
H3-TABLE H3-TABLE-COLOR	Generates a table .	<TABLE... > <TR><TH> ... </TH></TR> <TR><TD... > ... </TD></TR> ... </TABLE>

Program	Description	HTML Tag
H3-TAG	Generates a universal tag .	<tag>
H3-TEXT-AREA	Generates a ' text area '.	<TEXTAREA> ... </TEXTAREA>
H3-TEXT-TO-HTML	Converts the content of a Natural string to ' HTML '. replace with -> W3TEXT-TO-HTML	
H3-TEXT-TO-URL H3-ASCII-URL-TABLE	Converts the content of a Natural string to ' URL decoded '. replace with -> W3TEXT-TO-URL	
H3-TIME_DATE H3-TIME-DATE	Generates a ' time/date ' string.	generated: Mon, 17 Jan 2005 15:35:18 GMT

Utilities

Web Interface Plugin

Plugin	Description
Program Generation	See Natural documentation
Class Generation	See Natural documentation
Online Test Utility	See Natural documentation

Online

Dialog	Description
WEB-ONL or WEB-ONL3	See Natural documentation

Remote

Program	Description
NAT-LIB	Lists all Natural libraries.
NAT-DATA	Lists all header/data (binary, alpha, unicode?) delivered from the HTTP server.
NAT-DIR	Lists the contents of a specific Natural library.
NAT-DIRR	Lists the resource contents of a specific Natural library.
NAT-ENV	Lists all parameters passed to a called Natural subprogram.
NAT-HTML	Displays a Natural source containing HTML.
NAT-INFO	Displays the current Natural Web Interface settings .
NAT-LIST	Displays a Natural source object .

Program	Description
NAT-DOCU	Displays the online documentation .
NAT-RES	Displays a non-Natural file - resource (only platform shared resources are available).

Demonstration Applications

The demonstration application delivered shows simple file maintenance with select functions. The demonstration is based on the Adabas file EMPLOYEES. To run the application, Adabas has to be active.

The implementation of the demonstration application uses templates, XML and XSLT, name prefix D6* Depending on your installation of the HTTP Server Extensions, call the subprogram D6INDEX from the library SYSWEB3.

Example of the URL to call the demonstration application:

<http://yourserver/yourcgi/sysweb3/d6index>

All pictures used are delivered with the Natural Web Interface. Save them in the directory **pictures** on your HTTP-server in the remote directory **PICTURES**. If you want to use another remote directory name, set the environment variable **PICTURES** at the initialization file of your HTTP Server Extension with the specific remote directory name.

83 Writes Binary to the Document

Subroutine Name	Executable Example	Viewable Example
W3BINARY	E3BINARY	E3BINARY

Description

Writes a binary to the document. A document can only contain either a binary or an alphanumeric return value - never both.

Parameters

W3BINARY

```
1 H3BINARY (A) DYNAMIC BY VALUE /* i /mH: Output string
```

How To Invoke

```
PERFORM W3BINARY H3BINARYDYNAMIC
```


84 Clear Output Area

Subroutine Name	Executable Example	Viewable Example
W3CLEAR	E3CLEAR	E3CLEAR

Description

Deletes all data already written to the output area.

Parameters

```
/* NONE
```

How To Invoke

```
PERFORM W3CLEAR
```


85 Set Document Content-Type

Subroutine Name	Executable Example	Viewable Example
W3CONTENT-TYPE	E3CONTYP	E3CONTYP

Description

Sets the content type of the document. This setting is used by the browser programs to find out how the content is to be displayed.

W3CONTENT-TYPE or [W3LOCATION](#) has to be the first output of a document.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Parameters

```
1 H3VALUE (A) DYNAMIC /* i /m : Content type to be set
```

How To Invoke

```
PERFORM W3CONTENT-TYPE H3VALUE
```


86 Count Size of Output Area

Subroutine Name	Executable Example	Viewable Example
W3COUNT W3LIMIT	E3COUNT	E3COUNT

Description

Returns the number of bytes already written there.

Changes from previous versions

New with Natural Version 6.2: The size of the output area is no longer limited by internal settings during compile time. Therefore the maximum size is only limited by the maximum size of a Natural dynamic variable and the parameter settings used for the RPC or DCOM server. The return value of W3MAXPAGE can now be set within the program W3LIMIT, but has no effect on the maximum output size generated and stored internally.

Parameters

```
1 W3WRITTEN (I4) /* o/m : Currently written bytes
1 W3MAXPAGE (I4) /* o/m : Maximum bytes possible
1 W3FREE     (I4) /* o/m : Free bytes
```

How To Invoke

```
PERFORM W3COUNTER W3WRITTEN W3MAXPAGE W3FREE
```


87 Generate Error Page

Subroutine Name	Executable Example	Viewable Example
W3ERROR	E3ERROR	E3ERROR
W3ERROR-TEMPLATE		
W3ERROR-TEMPLATE-XML		
W3ERROR-TEXT		

Description

Errors generated by the Natural runtime should be handled to avoid screen output. Therefore, an `ON ERROR` section must be added to all programs called with the Natural Web Interface. The PDA `W3CONST` must be added as well.

The subroutine `W3ERROR-TEMPLATE` is called if an error occurs. This routine can be changed for your own needs.

The subroutine `W3ERROR-TEMPLATE-XML` returns the error page as XHTML page. This routine can be changed for your own needs. To activate this template, uncatalog `W3ERROR-TEMPLATE` and rename the subroutine from `W3ERROR-TEMPLATE-XML` to `W3ERROR-TEMPLATE` and stow.

The subroutine `W3ERROR-TEXT` is for internal use only.

Parameters

```
1 ##W3ERROR
2 NR          (I4)    /* i /m : Number of the error
2 LINE        (I4)    /* i /m : Line in the Natural program
2 SUBPROGRAM (A008) /* i /m : Subprogram name
2 SUBROUTINE (A032) /* i /m : Subroutine name
2 TEXT        (A250) /* i /m : Error text
```

How To Invoke

```
ON ERROR
  PERFORM W3ERROR ##W3ERROR
  PERFORM W3END ##RPC
  ESCAPE ROUTINE
END-ERROR
```

88

Writes to the Document and Converts to Valid HTML

Subroutine Name	Executable Example	Viewable Example
W3HTML	E3HTMLA	E3HTMLA
W3HTMLDYNAMIC		
W3HTMLLINE		
W3HTMLINEDYNAMIC		
W3HTMLARRAY		

Description

Writes a string to the document and converts special characters, such as "<" , ">" , "Ã¼" etc.

If you want to create a line break after your output, use W3HTMLLINE or W3HTMLINEDYNAMIC.

If you want to create a line break inside your string, compress ##HTTP-NEWLINE into your string.

W3HTML and W3HTMLLINE will delete trailing blanks from the given string. For better performance use dynamic variables.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Parameters

1. W3HTML

```
1 H3HTML (A) DYNAMIC BY VALUE /* i /mH: Output string
```

2. W3HTMLDYNAMIC

```
1 H3DYNAMIC (A) DYNAMIC BY VALUE /* i /mH: Output string
```

3. W3HTMLLINE

```
1 H3HTML (A) DYNAMIC BY VALUE /* i /mH: Output string
```

4. W3HTMLLINEDYNAMIC

```
1 H3DYNAMIC (A) DYNAMIC BY VALUE /* i /mH: Output string
```

5. W3HTMLARRAY

```
1 H3ARRAYVALUE (A/1:v) DYNAMIC /* i /mH: Output array  
1 H3VALUELENGTH (I4)           /* i /m : Length of output array
```

How To Invoke

```
PERFORM W3HTML H3HTML  
PERFORM W3HTMLDYNAMIC H3DYNAMIC  
PERFORM W3HTMLLINE H3HTML  
PERFORM W3HTMLLINEDYNAMIC H3DYNAMIC  
PERFORM W3HTMLARRAY H3ARRAYVALUE H3VALUELENGTH
```

89 Writes HTTP Settings to the Document

Subroutine Name	Executable Example	Viewable Example
W3HTTP	E3HTTP	E3HTTP
W3HTTPDYNAMIC		
W3HTTP-HEADER		
W3HTTPARRAY		

Description

Writes a text line to the HEAD of a document. In these text line settings, you can specify COOKIES, EXPIRE-DATES or other settings of an HTTP-compatible document.

Physical new lines in the output can be created by compressing `##HTTP_NEWLINE` into a Natural string.

If you want to create a line break inside your string, compress `##HTTP-NEWLINE` into your string.

`W3HTTP` will delete trailing blanks from the given string.

For better performance use dynamic variables.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Parameters

1. W3HTTP

```
1 W3STRING (A) DYNAMIC /* i /m : Header name value pairs
```

2. W3HTTPDYNAMIC

```
1 W3DYNAMIC (A) DYNAMIC /* i /m : Header name value pairs
```

3. W3HTTP-HEADER

```
1 W3HTTPNAME (A) DYNAMIC /* i /m : Header name  
1 W3HTTPVALUE (A) DYNAMIC /* i /m : Header value
```

4. W3HTTPARRAY

```
1 W3ARRAYVALUE (A/1:V) DYNAMIC /* i /m : Header name value pairs  
1 W3VALUELENGTH (I4) /* i /m : Length of output array
```

How To Invoke

```
PERFORM W3HTTP W3STRING  
PERFORM W3HTTPDYNAMIC W3DYNAMIC  
PERFORM W3HTTP-HEADER W3HTTPNAME W3HTTPVALUE  
PERFORM W3HTTPARRAY W3ARRAYVALUE W3VALUELENGTH
```

90 Info About Internal Values

Subroutine Name	Executable Example	Viewable Example
W3INFO	E3INFO	E3INFO

Description

This program enables you to set and read some internal values of the Web Interface.

Read (Action ' ')

The values for ERROR-NR VERSION, LOG-TIME, FORM, LIST(*) and LIST_MAX will be returned.

Set List (Action 'L')

For H3-OPEN-LIST, H3-CLOSE-LIST and H3-LIST-ITEM, an internal array is used to save the style of the generated list. This style will be used to generate the correct close tag.

Set Form (Action 'F')

For all programs, you can generate tags that can only be used inside a FORM tag. A flag can be called to check if a FORM is open or not. The flag will be changed by H3-OPEN-FORM and H3-CLOSE-FORM.

Changes from previous version

The LDA W3INFO has been changed, and the variables LOG-TIME, VERSION and WEBAPI have been changed to (A) dynamic.

Parameters

LOCAL USING W3INFO

PDA W3PINFO

```
1 ##W3INFO
2 ACTION      (A1)          /* i /m : Action to be called
2 LOG-TIME    (A) DYNAMIC   /* o/m : Log time set by the Natural Web Interface
2 VERSION     (A) DYNAMIC   /* o/m : Version set by the HTTP Server Extension
2 WEBAPI      (A) DYNAMIC   /* o/m : Version set by the Natural Web Interface
2 ERROR-NR    (I4)          /* o/m : Error number set by the Natural Web Interface
2 FORM        (L)           /* io/m : Indicates whether a FORM is open
2 LIST         (A1/1:10)    /* io/m : Saves the type of LIST
2 LIST_MAX    (N2)          /* io/m : Current number of nested LISTs
```

How To Invoke

```
PERFORM W3INFO ##W3INFO
```

91 End and Initialize Document

Subroutine Name	Executable Example	Viewable Example
W3INIT	E3END	E3END
W3END		

Description

Each Program needs to initialize and end the web interface by special programs. The initialisation is done by W3INIT. The PDA W3PARM must be passed to initialize passed parameters for further use. W3END ends the document and prepares the return to the HTTPserver. The PDA W3PARM defined at the initial program has to be passed to W3END. If W3* calls are performed after W3END, the written output will not be transferred to the HTTP server.

With SYSWEB3, W3PARM has been changed to provide an improved interface to the HTTP server. The new interface is capable of transferring binary or alpha data, using other mime-types such as 'application/x-www-form-urlencoded' for incoming data and allows the usage of HTTP PUT requests.

For compatibility reasons, the new features HTTP PUT and other mime-types for data input can only be used, if W3INIT is called with an additional parameter:

2nd Parameter := TRUE - activates other mime-types then 'application/x-www-form-urlencoded' for incoming data

3rd Parameter := TRUE - activates HTTP PUT requests.

Changes from previous version

New optional parameters added.

Parameters

1. W3INIT

```
##RPC /* i /m : Parameter of Subprogram
TRUE /* io/ : TRUE to activate mime-types
TRUE /* io/ : TRUE to activate HTTP PUT
```

2. W3END

```
##RPC /* o/m : Parameter of Subprogram
```

3. W3PARM

```
1 ##RPC          /* use only with SYSWEB3
2 LOG-TIME      (A30)        /* i /m : Timestamp
2 VERSION       (A) DYNAMIC /* i /m : Interface version
2 HTTP_HEADER   (A) DYNAMIC /* io/m : HTTP header
2 C_HTTP_HEADER (I4)         /* io/m : Bytes sent
2 HTTP_BODY     (A) DYNAMIC /* io/m : HTTP body alphanumeric
2 HTTP_BINARY   (B) DYNAMIC /* io/m : HTTP body binary
2 C_HTTP_DATA   (I4)         /* io/m : Bytes sent
2 MIME-TYPE     (A) DYNAMIC /* io/m : Mime-type sent
2 ERROR-NR     (I4)         /* io/m : Generation result
```

How To Invoke

```
PERFORM W3INIT ##RPC
PERFORM W3INIT ##RPC TRUE /* activate mime-types ne
'application/x-www-form-urlencoded'
PERFORM W3INIT ##RPC TRUE TRUE /* activate mime-types and HTTP PUT
PERFORM W3END ##RPC
```

92 List All Environment Variables

Subroutine Name	Executable Example	Viewable Example
W3LIST-ENVIRONMENT	E3ENVLIS	E3ENVLIS
W3LIST-ENVIRONMENT-TO-DYNAMIC		

Description

List all variables sent by the HTTP server.

Parameters

1. W3LIST-ENVIRONMENT

```
1 W3START          (I4)      /* IN/OUT: START FORM
*
*                                     /* out: = 0 :all read
*                                     /*           > 0 :data left, reread form here
1 W3ARRAYCOUNTER   (I4)      /* IN/OUT: LENGTH OF THE ARRAY TO RETURN
1 W3ARRAYNAME       (A72/1:V) /* OUT: NAME OF THE VARIABLE
1 W3ARRAYVALUE      (A250/1:V)/* OUT: VALUE OF THE VARIABLE
1 W3ARRAYVALUELENGTH (I4/1:V) /* OUT: LEN OF THE VARIABLE
1 W3ARRAYVALUESERVER (L/1:V)  /* OUT: Server Variable
1 W3ARRAYMAXIMUM    (I4)      /* OUT: NUMBER OF THE VALUES
```

2. W3LIST-ENVIRONMENT-TO-DYNAMIC

```
1 W3START          (I4)      /* IN/OUT: START FORM
*
*                                     /* out: = 0 :all read
*                                     /*           > 0 :data left, reread form here
1 W3ARRAYCOUNTER   (I4)      /* IN/OUT: LENGTH OF THE ARRAY TO RETURN
1 W3ARRAYNAME       (A/1:V) DYNAMIC /* OUT: NAME OF THE VARIABLE
1 W3ARRAYVALUE      (A/1:V) DYNAMIC /* OUT: VALUE OF THE VARIABLE
1 W3ARRAYVALUESERVER (L/1:V)  /* OUT: Server Variable
1 W3ARRAYMAXIMUM    (I4)      /* OUT: NUMBER OF THE VALUES
```

How To Invoke

1.

```
PERFORM W3LIST-ENVIRONMENT W3START W3NAME W3ARRAYCOUNTER  
      W3ARRAYNAME(*) W3ARRAYVALUE(*) W3ARRAYVALUELENGTH(*)  
      W3ARRAYVALUESERVER(*) W3ARRAYMAXIMUM
```

2.

```
PERFORM W3LIST-ENVIRONMENT-TO-DYNAMIC W3START W3NAME W3ARRAYCOUNTER  
      W3ARRAYNAME(*) W3ARRAYVALUE(*) W3ARRAYVALUESERVER(*)  
      W3ARRAYMAXIMUM
```

93 Evaluate Mime-Type and Transfer/Data-Type

Subroutine Name	Executable Example	Viewable Example
W3MIME-DATA MIMEDATA	NAT-RES?source=e3xslt2.xml&lib=sysweb3 NAT-RES?source=composing_natural_logo.jpg&lib=sysweb3	NAT-RES

Description

Each Program needs to initialize and end the web interface by special programs. The initialisation is done by W3INIT. The W3PARM PDA must be passed to initialize passed parameters for further use. W3END ends the document and prepares the return to the HTTPserver. The W3PARM PDA defined at the initial program has to be passed to W3END. If W3* calls are performed after W3END, the written output will not be transferred to the HTTP server.

Parameters

1. W3INIT

```
USING W3PARM /* io/m : Parameter of Subprogram
```

2. W3END

```
USING W3PARM /* io/m : Parameter of Subprogram
```

3. W3PARM

```
1 ##RPC
2 VERSION          (A010)    /* i /m : Interface version
2 LOG-TIME         (A030)    /* i /m : Timestamp
2 RETURN_PAGE      (A250/1:V) /* io/m : Transfer area
2 RETURN_PAGE_COUNT (I004)   /* io/m : Bytes sent
2 ERROR-NR         (I004)   /* o/m : Error number
```

How To Invoke

```
PERFORM W3INIT ##RPC
PERFORM W3END ##RPC
```

94 Evaluate Mime-Type and File Extension

Subroutine Name	Executable Example	Viewable Example
W3MIME-TYPE MIMETYPE	NAT-RES?source=e3xslt2.xml&lib=sysweb3 NAT-RES?source=composing_natural_logo.jpg&lib=sysweb3	NAT-RES

Description

Natural Web Interface holds an own table for mime-type / file extension settings. This table is saved in the Natural text member MIMETYPE. The text member contains pairs of mime-type names and file extension(s):

```
text/html      html  htm
text/plain    txt
text/xml      xml
text/richtext rtf
```

W3MIME-TYPE reads the internal table and offers the following translations:

- Evaluate a mime-type for a given file extension.
- Evaluate a file extension for a given mime-type

The functionality is used internally at the W3LOAD-RESOURCE subprogram.

Parameters

1. W3MIME-TYPE

```
W3MIME-TYPE      (A) DYNAMIC /* i /m : requested mime-type  
W3FILE-EXTENTION (A) DYNAMIC /* o/m : found file extension
```

2. W3MIME-TYPE

```
W3MIME-TYPE      (A) DYNAMIC /* o/m : found mime-type  
W3FILE-EXTENTION (A) DYNAMIC /* i /m : requested file extension
```

How To Invoke

```
PERFORM W3MIME-TYPE W3FILE-EXTENTION
```

95 Set Document Location

Subroutine Name	Executable Example	Viewable Example
W3LOCATION	E3LOCAT	E3LOCAT

Description

Sets the location of a document that is to be loaded. This subroutine can be used to call a static page instead of a dynamic one from a Natural program.

W3LOCATION or [W3CONTENT-TYPE](#) has to be the first output of a document.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Parameters

```
1 W3CONTENT (A) DYNAMIC /* i /m : Content type to be set
```

How To Invoke

```
PERFORM W3CONTENT-TYPE W3CONTENT
```


96

Read Environment Variable

Subroutine Name	Executable Example	Viewable Example
W3READ-ENVIRONMENT-ARRAY	E3ENVARY	E3ENVARY
W3READ-ENVIRONMENT		
W3READ-ENVIRONMENT-TO-DYNAMIC		

Description

Reads the first occurrence of a single variable. With W3READ-ENVIRONMENT-ARRAY, a variable can be read beginning with an offset. This can be used to read multiple occurrences of the same variable.

Parameters

1. W3READ-ENVIRONMENT-ARRAY

```
1 W3START          (I4)      /* io/m : Offset to be started at
*                           /*           out: 0 no occurrences
*                           /*           out: >0 more occurrences
1 W3NAME           (A072)    /* i /m : Name of the variable to
*                           /*           be searched for
1 W3VALUESERVER   (A1)      /* i /m : Search for variables from
*                           /*           'S' server
*                           /*           'P' page or URL
*                           /*           ' ' both
1 W3ARRAYCOUNTER  (I4)      /* io/m : Size of array,
*                           /*           characters read
1 W3VALUEARRAY    (A001/1:V) /* o/m : Array with the returned value
1 W3VALUELENGTH   (I4)      /* o/m : length of the value
```

2. W3READ-ENVIRONMENT

```
1 W3NAME          (A072)  /* i /m : Name of the variable
                           /*           searched for
1 W3VALUESERVER (A1)   /* i /m : Search for variables in
*                      /*           'S' server
*                      /*           'P' page or URL
*                      /*           ' ' both
1 W3VALUE         (A250)  /* o/m : Returned value
1 W3VALUELENGTH (I4)    /* o/m : Length of the value
```

3. W3READ-ENVIRONMENT-TO-DYNAMIC

```
1 W3NAME          (A072)  /* i /m : Name of the variable
                           /*           searched for
1 W3VALUESERVER (A1)   /* i /m : Search for variables in
*                      /*           'S' server
*                      /*           'P' page or URL
*                      /*           ' ' both
1 W3VALUEDYNAMIC (A) DYNAMIC /* o/m : Returned value
```

How To Invoke

```
PERFORM W3READ-ENVIRONMENT-ARRAY W3START W3NAME W3VALUESERVER
       W3ARRAYCOUNTER W3VALUEARRAY(*) W3VALUELENGTH

PERFORM W3READ-ENVIRONMENT W3NAME W3VALUESERVER W3VALUE
       W3VALUELENGTH

PERFORM W3READ-ENVIRONMENT-TO-DYNAMIC W3NAME W3VALUESERVER
       W3VALUEDYNAMIC
```

97 Read Environment Variables Groups

Subroutine Name	Executable Example	Viewable Example
W3READ-ENVIRONMENT-GROUP	E3ENVGRO?test=a&test=bb&test=cc	E3ENVGRO

Description

Reads all variables with the same name, e.g. set from a multiple select.

Parameters

```
1 W3START          (I4)      /* io/m : Offset to be started at
*                      /*          out: 0 no occurrences
*                      /*          out: >0 more occurrences
1 W3NAME           (A) DYNAMIC /* i /m : Name of variable
1 W3VALUESERVER    (A1)       /* i /m : Search for variables in
*                      /*          'S' server
*                      /*          'P' page or URL
*                      /*          ' ' both
1 W3ARRAYCOUNTER   (I4)       /* io/m : Length of array,
*                      /*          returned values
1 W3ARRAYVALUES    (A250/1:V) /* o/m : Values of variable
1 W3ARRAYMAXIMUM   (I4)       /* o/m : Total number of variables
```

How To Invoke

```
PERFORM W3READ-ENVIRONMENT-GROUP W3START W3NAME
      W3VALUESERVER W3ARRAYCOUNTER
      W3ARRAYVALUES(*) W3ARRAYMAXIMUM
```


98 Read Environment Text Area Variables

Subroutine Name	Executable Example	Viewable Example
W3READ-ENVIRONMENT-TEXTAREA	E3ENVTX	E3ENVTX
W3READ-ENVIRONMENT-TEXTAREA-DYN	E3ENVTXD	E3ENVTX1 E3ENVTXD E3ENVTX2

Description

Reads a variable set by a text area tag and separates the text lines.

Parameters

1. W3READ-ENVIRONMENT-TEXTAREA

```
1 W3START          (I4)      /* io/m : Offset to be started at
*                           /*           out: 0 no occurrences
*                           /*           out: >0 more occurrences
1 W3NAME           (A072)    /* i /m : Name of variable
1 W3VALUESERVER   (A1)      /* i /m : Search for variables in
*                           /*           'S' server
*                           /*           'P' page or URL
*                           /*           ' ' both
1 W3ARRAYCOUNTER  (A250/1:V) /* io/m : Length of array,
*                           /*           returned values
1 W3ARRAYVALUE    (I4/1:V)   /* o/m : Value of variables
1 W3ARRAYVALUELENGTH (I4)    /* o/m : Length of variables
1 W3ARRAYMAXIMUM (I4)      /* o/m : Total number of variables
```

2. W3READ-ENVIRONMENT-TEXTAREA-DYN

```
1 W3START          (I4)           /* io/m : Offset to be started at
*                                /*          out: 0 no occurrences
*                                /*          out: >0 more occurrences
1 W3NAME-DYN       (A) DYNAMIC   /* i /m : Name of variable
1 W3VALUESERVER    (A1)          /* i /m : Search for variables in
*                                /*          'S' server
*                                /*          'P' page or URL
*                                /*          ' ' both
1 W3ARRAYCOUNTER   (I4)          /* io/m : Length of array,
*                                /*          returned values
1 W3ARRAYVALUE-DYN (A/1:V) DYNAMIC /* o/m : Value of variables
1 W3ARRAYVALUELENGTH (I4/1:V)    /* o/m : Length of variables
1 W3ARRAYMAXIMUM   (I4)          /* o/m : Total number of variables
```

How To Invoke

```
PERFORM W3READ-ENVIRONMENT-TEXTAREA W3START W3NAME
      W3VALUESERVER W3ARRAYCOUNTER(*)
      W3ARRAYVALUE(*) W3ARRAYVALUELENGTH(*)
      W3ARRAYMAXIMUM

PERFORM W3READ-ENVIRONMENT-TEXTAREA-DYN W3START W3NAME-DYN
      W3VALUESERVER W3ARRAYCOUNTER(*)
      W3ARRAYVALUE-DYN(*) W3ARRAYVALUELENGTH(*)
      W3ARRAYMAXIMUM
```

99 Write Text to Document

Subroutine Name	Executable Example	Viewable Example
W3TEXT	E3TEXT	E3TEXT
W3TEXTDYNAMIC		
W3TEXTLINE		
W3TEXTLINEDYNAMIC		
W3TEXTARRAY		

Description

Writes a character string to the document.

If you want to create a line break after your output, use W3HTMLLINE or W3HTMLLINEDYNAMIC.

If you want to create a line break inside your string, compress ##HTTP-NEWLINE into your string.

W3TEXT and W3TEXTLINE will delete trailing blanks from the given string.

For better performance use dynamic variables.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Parameters

1. W3TEXT

```
1 W3TEXT (A) DYNAMIC /* i /m : Output string
```

2. W3TEXTDYNAMIC

```
1 W3DYNAMIC (A) DYNAMIC /* i /m : Output array
```

3. W3TEXTLINE

```
1 W3TEXT (A) DYNAMIC /* i /m : Output string with new line
```

4. W3TEXTLINEDYNAMIC

```
1 W3DYNAMIC (A) DYNAMIC /* i /m : Output string with new line
```

5. W3TEXTARRAY

```
1 H3ARRAYVALUE      (A/1:v) DYNAMIC   /* i /m : Output array  
1 H3VALUELENGTH    (I4)           /* i /m : Length of output array
```

How To Invoke

```
PERFORM W3TEXT W3TEXT  
PERFORM W3TEXTDYNAMIC W3TEXT  
PERFORM W3TEXTLINE W3TEXT  
PERFORM W3TEXTLINEDYNAMIC W3TEXT  
PERFORM W3TEXTARRAY W3ARRAYVALUE W3VALUELENGTH
```

100

Write Newline to Output Area

Subroutine Name
W3NEWLINE

Description

Adds a single newline (#HTTP_NEWLINE) to the output area. This subroutine will be deleted in one of the next versions. Use W3TEXTDYNAMIC #HTTP_NEWLINE instead.

Parameters

*/ NONE

How To Invoke

```
PERFORM W3NEWLINE
```


101

Read Natural Source into X-Array of Dynamic

Subroutine Name	Executable Example	Viewable Example
W3SOURCE-TO-XARRAY	E3NAT2XA	E3NAT2XA

Description

Reads a Natural source from a given library into one single x-array.

Parameters

```
1 W3LIBRARY      (A8) DYNAMIC BY VALUE    /* i /o : Natural Library ID
1 W3SOURCE       (A8) DYNAMIC BY VALUE    /* i /m : Source Name
1 W3OUTSRC-XA   (A/1:*) DYNAMIC          /* o/o : Response Array
1 W3RESPONSE     (I4)                      /* o/o : Response
```

How To Invoke

```
PERFORM W3SOURCE-TO-XARRAY W3LIBRARY W3SOURCE W3OUTSRC-XA(*) W3RESPONSE
```


102 Text to HTML

Subprogram Name	Executable Example	Viewable Example
W3TEXT-TO-HTML	E3TX2HTM	E3TX2HTM
W3-ASCII-HTML-TABLE		

Description

Converts a string to HTML syntax. Useful if special characters are included.

The subprogram W3-ASCII-HTML-TABLE will be called from W3TEXT-TO-HTML and W3HTML and contains a list of all conversations that will be made. This program can be changed and extended for the user's needs.

Parameters

```
1 W3HTML (A) DYNAMIC /* io/mH: HTML text conversion
```

How To Invoke

```
PERFORM W3TEXT-TO-HTML W3HTML
```


103 Text to XML

Subprogram Name	Executable Example	Viewable Example
W3TEXT-TO-XML	E3TX2XML	E3TX2XML
W3-ASCII-XML-TABLE		

Description

Converts a string to XML syntax. Useful if special characters are included.

The subprogram W3-ASCII-XML-TABLE will be called from W3TEXT-TO-XML and contains a list of all conversations that will be made. This program can be changed and extended according to the user's needs.

Parameters

```
1 W3XML (A) DYNAMIC /* io/mX: XML text conversion
```

How To Invoke

```
PERFORM W3TEXT-TO-XML W3XML
```


104 Text to URL

Subprogram Name	Executable Example	Viewable Example
W3TEXT-TO-URL	E3TX2URL	E3TX2URL
W3-ASCII-URL-TABLE		

Description

Converts a string to URL syntax. Useful if special characters are included.

The subprogram W3-ASCII-URL-TABLE will be called from W3TEXT-TO-URL and contains a list of all conversations that will be made. This program can be changed and extended according to the user's needs.

Parameters

```
1 W3URL (A) DYNAMIC /* io/mU: URL text conversion
```

How To Invoke

```
PERFORM W3TEXT-TO-URL W3URL
```


105 Replace Inside Return Document

Subroutine Name	Executable Example	Viewable Example	Resources
W3REPLACE	E3TEMPL	E3TEMPL	E3TEMPL.HTML

Description

Search the already written output page for a specific string and replace all occurrences with a new string. Use together with W3LOAD-RESOURCE for template processing.

With the encoding parameter, the given data will be encoded before the replacement is done:

- " " for no encoding
- "HTML" for HTML encoding (e.g. < becomes < ;)
- "URL" for URL encoding
- "XML" for XML encoding (e.g. < becomes < ;)

Parameters

```
1 W3ENCODING    (A) DYNAMIC BY VALUE    /* i /m : encoding
1 W3OLD         (A) DYNAMIC BY VALUE    /* i /m : old string
1 W3NEW         (A) DYNAMIC BY VALUE    /* i /m : new string
```

How To Invoke

```
PERFORM W3REPLACE "$weather$" "fine, no clouds"
```


106 Load Resource

Subroutine Name	Executable Example	Viewable Example	Resources
W3LOAD-RESOURCE	E3RESOUR	E3RESOUR	E3SAVE.HTML

Description

Load a file from the resource directory of a given library into the output page.

If no library is specified, use the current library.

Use together with [W3REPLACE](#) for template processing.

Data is loaded as binary or alpha - depending on the settings of "MIMEDATA" and "MIMETYPE".

Use [W3MIME-TYPE](#) to evaluate the mime-type for the given file extension.

Parameters

```
1 W3LIBRARY      (A8) DYNAMIC BY VALUE OPTIONAL      /* i /o : Natural Library ID
1 W3RESOURCE-FILE (A) DYNAMIC BY VALUE              /* i /m : File Name
1 W3RESPONSE     (I4) OPTIONAL                      /* o/o : Response
```

If the [W3RESPONSE](#) parameter is not specified, the Web Interface error processing is triggered if an error occurs. If the [W3RESPONSE](#) parameter is specified, the parameter contains the Natural message number if an error occurred, or zero on success.

How To Invoke

```
PERFORM W3LOAD-RESOURCE W3LIBRARY W3RESOURCE-FILE  
PERFORM W3LOAD-RESOURCE " " "templ.html"  
PERFORM W3LOAD-RESOURCE 1X "templ.html"
```

Restriction

Load Resource is only available on Natural for Windows and UNIX supporting non-natural files/resources. Internally it uses workfile 12.

107 Read Resource

Subroutine Name	Executable Example	Viewable Example	Resources
W3READ-RESOURCE	E3RESOUR	E3RESOUR	E3SAVE.HTML

Description

Read a resource file from the given library into a dynamic variable. If no library is specified, use the current library.

Use together with [W3APPLY-XSLT](#) for template processing.

Parameters

```
1 W3LIBRARY      (A8) BY VALUE OPTIONAL  /* i /o : Natural Library ID
1 W3FILE         (A) DYNAMIC BY VALUE    /* i /m : File Name
1 W3DYN          (A) DYNAMIC             /* o/m : Read Resource
1 W3RESPONSE     (I4) OPTIONAL           /* o/o : Response
```

If the W3RESPONSE parameter is not specified, the Web Interface error processing is triggered if an error occurs. If the W3RESPONSE parameter is specified, the parameter contains the Natural message number if an error occurred, or zero on success.

How To Invoke

```
PERFORM W3READ-RESOURCE W3LIBRARY W3FILE W3DYN  
PERFORM W3READ-RESOURCE W3LIBRARY W3FILE W3DYN W3RESPONSE
```

Restriction

Load Resource is only available on Natural for Windows and UNIX supporting non-natural files/resources. Internally it uses workfile 12.

108 Write Resource

Subroutine Name	Executable Example	Viewable Example	Resources
W3WRITE-RESOURCE	E3RESOUR	E3RESOUR	E3SAVE.HTML

Description

Write a resource file to the given library and fill with a given dynamic variable. If no library is specified, use the current library.

Parameters

```
1 W3LIBRARY      (A8) BY VALUE OPTIONAL /* i /o : Natural Library ID
1 W3FILE         (A) DYNAMIC BY VALUE    /* i /m : File Name
1 W3DYN          (A) DYNAMIC BY VALUE    /* i /m : Read Resource
1 W3RESPONSE     (I4)OPTIONAL           /* o/o : Response
```

If the W3RESPONSE parameter is not specified, the Web Interface error processing is triggered if an error occurs. If the W3RESPONSE parameter is specified, the parameter contains the Natural message number if an error occurred, or zero on success.

How To Invoke

```
PERFORM W3WRITE-RESOURCE W3LIBRARY W3FILE W3DYN
PERFORM W3WRITE-RESOURCE W3LIBRARY "Test.txt" W3DYN
PERFORM W3WRITE-RESOURCE W3LIBRARY W3FILE W3DYN W3RESPONSE
```

Restriction

Load Resource is only available on Natural for Windows and UNIX supporting non-natural files/resources. Internally it uses workfile 12.

109 Check Resource

Subroutine Name	Executable Example	Viewable Example	Resources
W3CHECK-RESOURCE	E3RESOUR	E3RESOUR	E3SAVE.HTML

Description

Check if a read a resource file exists at the given library. With the create flag, a new empty resource can be created if one does not already exist. If no library is specified, use the current library.

Parameters

```
1 W3LIBRARY      (A8) BY VALUE OPTIONAL /* i /o : Natural Library ID
1 W3FILE         (A) DYNAMIC BY VALUE    /* i /m : File Name
1 W3CREATE        (L) BY VALUE          /* i /m : If true, create new file
1 W3PATH          (A) DYNAMIC           /* o/m : Resource path
1 W3RESPONSE     (I4) OPTIONAL         /* o/o : Response
```

If the W3RESPONSE parameter is not specified, the Web Interface error processing is triggered if an error occurs. If the W3RESPONSE parameter is specified, the parameter contains the Natural message number if an error occurred, or zero on success.

How To Invoke

```
PERFORM W3CHECK-RESOURCE W3LIBRARY W3FILE W3CREATE W3PATH
PERFORM W3CHECK-RESOURCE " " 'test.html' TRUE W3PATH
PERFORM W3CHECK-RESOURCE 1x 'test.html' TRUE W3PATH
PERFORM W3CHECK-RESOURCE W3LIBRARY W3FILE W3CREATE W3PATH W3RESOURCE
```

Restriction:

Check Resource is only available on Natural for Windows and UNIX supporting non-natural files/resources.

110 Delete Resource

Subroutine Name	Executable Example	Viewable Example	Resources
W3DELETE-RESOURCE	E3RESOUR	E3RESOUR	E3SAVE.HTML

Description

Delete a resource file from the given library. If no library is specified, use the current library.

Parameters

```
1 W3LIBRARY      (A8) BY VALUE OPTIONAL /* i /o : Natural Library ID
1 W3FILE         (A) DYNAMIC BY VALUE    /* i /m : File Name
1 W3RESPONSE     (I4)OPTIONAL           /* o/o : Response
```

If the W3RESPONSE parameter is not specified, the Web Interface error processing is triggered if an error occurs. If the W3RESPONSE parameter is specified, the parameter contains the Natural message number if an error occurred, or zero on success.

How To Invoke

```
PERFORM W3DELETE-RESOURCE W3LIBRARY W3FILE
PERFORM W3DELETE-RESOURCE " " 'test.html'
PERFORM W3DELETE-RESOURCE 1x 'test.html'
PERFORM W3DELETE-RESOURCE W3LIBRARY W3FILE W3RESPONSE
```

Restriction

Check Resource is only available on Natural for Windows and UNIX supporting non-natural files/resources.

111

Apply XSLT Processing on Return Document

Subroutine Name	Executable Example	Viewable Example
W3APPLY-XSLT-XML	E3XSLT	E3XSLT

Description

Call an XSLT processor with the given XML and replace the output page with the generated data.

Parameters

```
1 W3XSL      (A) DYNAMIC BY VALUE /* i /m : xsl template  
1 W3XML      (A) DYNAMIC BY VALUE /* i /m : xml data  
1 W3RESPONSE (I4) OPTIONAL      /* o/o : result
```

If the W3RESPONSE parameter is not specified, the Web Interface error processing is triggered if an error occurs. If the W3RESPONSE parameter is specified, the parameter contains the Natural message number if an error occurred, or zero on success.

How To Invoke

```
PERFORM W3APPLY-XSLT-XML W3XSL W3XML  
PERFORM W3APPLY-XSLT-XML W3XSL W3XML W3RESPONSE
```

Restriction

Apply XSLT Processing is only available on versions of Natural for Windows and UNIX that contain the User Exit USR 6001P.

112

Apply XSLT Processing on Return Document from Resource

Subroutine Name	Executable Example	Viewable Example	Resource
W3APPLY-XSLT-RESOURCE	E3XSLT2	E3XSLT2	E3XSLT2.XML E3XSLT2.XSL

Description

Call an XSLT processor with the given XSL Resource and replace the output page with the generated data.

Parameters

```
1 W3LIBRARY      (A8) BY VALUE OPTIONAL /* i /o : Natural Library ID
1 W3RESOURCE-FILE (A) DYNAMIC BY VALUE    /* i /m : File Name
1 W3RESPONSE     (I4) OPTIONAL           /* o/o : result
```

If the W3RESPONSE parameter is not specified, the Web Interface error processing is triggered if an error occurs. If the W3RESPONSE parameter is specified, the parameter contains the Natural message number if an error occurred, or zero on success.

How To Invoke

```
PERFORM W3APPLY-XSLT-RESOURCE W3XSL W3XML
```

Restriction

Apply XSLT Processing is only available on versions of Natural for Windows and UNIX that contain the User Exit USR6001P.

113 Load Style Sheet from the Resource Directory and Apply XSLT Processing on Return Document

Subroutine Name	Executable Example	Viewable Example	Used Resource
W3APPLY-XSLT-XML-TO-DYNAMIC	E3XSLT3	E3XSLT3	E3XSLT3.HTML E3XSLT3.XSL E3XSLT3.XML

Description

Call an XSLT processor and transform the output page with a style sheet loaded from the resource directory of the given Natural library. If no library is specified, use the current library.

Parameters

```
1 W3XSLT      (A) DYNAMIC BY VALUE    /* i /m : xslt
1 W3XML       (A) DYNAMIC BY VALUE    /* i /m : xml
1 W3RESULT     (A) DYNAMIC           /* o/m : result
1 W3RESPONSE   (I4) OPTIONAL        /* o/o : result
```

If the W3RESPONSE parameter is not specified, the Web Interface error processing is triggered if an error occurs. If the W3RESPONSE parameter is specified, the parameter contains the Natural message number if an error occurred, or zero on success.

How To Invoke

```
PERFORM W3APPLY-XSLT-XML-TO-DYNAMIC W3XSLT W3XML W3RESULT
PERFORM W3APPLY-XSLT-XML-TO-DYNAMIC W3XSLT W3XML W3RESULT W3RESPONSE
```

Restriction

Load Style Sheet and Apply XSLT Processing is available only on versions of Natural for Windows and UNIX supporting non-natural files/resources and containing the User Exit USR 6001P. Internally it uses workfile 12.

114 List Resource Files

Subroutine Name	Executable Example	Viewable Example
W3LIST-RESOURCE	nat-dirr	nat-dirr

Description

List all resource files of a specific Natural library. Use W3PATTERN for wildcard selection.

Parameters

```
1 W3LIBRARY      (A) DYNAMIC BY VALUE OPTIONAL /* i / : library
1 W3PATTERN       (A) DYNAMIC BY VALUE           /* i /m : selcection pattern
1 W3FILES         (A/1:*) DYNAMIC             /* o/m : array with all file names
1 W3RESPONSE      (I4) OPTIONAL              /* o/ : response code
```

How To Invoke

```
PERFORM W3LIST-RESOURCE 1x '*' W3FILES(*)
PERFORM W3LIST-RESOURCE 'SYSWEB' '*.HTM' W3FILES(*)
PERFORM W3LIST-RESOURCE 'SYSTEM' '*.BMP' W3FILES(*) W3RESPONSE
```


115 Read Input Page

Subroutine Name	Executable Example	Viewable Example
W3READ-INPUT	E3MULTIP	E3MULTIP NAT-DATA

Description

Read the input data given from the HTTP server into dynamic variables.

W3BODY contains alphanumeric data delivered with "POST/PUT".

W3BINARY contains binary data delivered with "POST/PUT".

W3HEADER contains all delivered http header.

W3DATA contains the data of the QUERY_STRING, and/or data delivered with POST if the content-type is application/x-www-form-urlencoded.

Parameters

```
1 W3BODY      (A) DYNAMIC          /* o/m : given body
1 W3BINARY    (A) DYNAMIC OPTIONAL /* o/ : given binary
1 W3HEADER    (A) DYNAMIC OPTIONAL /* o/ : given header
1 W3DATA      (A) DYNAMIC OPTIONAL /* o/ : given parameter data
```

How To Invoke

```
PERFORM W3READ-INPUT W3BODY

PERFORM W3READ-INPUT W3BODY 2X W3DATA

PERFORM W3READ-INPUT W3BODY W3BINARY W3HEADER W3DATA
```


116 Read Output Page

Subroutine Name	Executable Example	Viewable Example
W3READ-OUTPUT	E3RESOUR	E3RESOUR

Description

Read into dynamic variables the output page already written.

Changes from previous versions

With Natural Version 6.2 the optional parameter W3BINARY has been added.

Parameters

```
1 W3HEADER  (A) DYNAMIC          /* o/m : written header
1 W3BODY    (A) DYNAMIC          /* o/m : written body
1 W3BINARY  (A) DYNAMIC OPTIONAL /* o/ : written binary
```

How To Invoke

```
PERFORM W3READ-OUTPUT W3HEADER W3BODY
PERFORM W3READ-OUTPUT W3HEADER W3BODY W3BINARY
```


117 Anchor

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-ANCHOR	H3ANCHOR	E3ANCHOR	E3ANCHOR

Description

Creates a hyperlink.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

Supported Attributes

NAME="*string*"

Parameters

```
1 H3URL          (A) DYNAMIC /* i /m : URL of the Link. Enter
*                  /*      'THIS' to reference
*                  /*      the current page as URL.
1 H3NAME         (A) DYNAMIC /* i /M : Name of the anchor.
1 H3STRING        (A) DYNAMIC /* i /MH: String to be displayed
*                  /*      as anchor text.
```

How To Invoke

```
PERFORM H3-ANCHOR H3URL H3NAME H3STRING
```

118 Button

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-BUTTON	H3BUTTON	E3BUTTON	E3BUTTON

Description

Creates a reset/submit button.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

```
<INPUT TYPE="submit|reset|image" NAME="string"> </INPUT>
```

Supported Attributes

VALUE="*string*", SRC="*URL*"

Parameters

```
1 H3TYPE      (A1)          /* i /m : 'R' reset button
*
*                      /*           'S' submit button
*
*                      /*           'I' submit button with image
1 H3NAME      (A) DYNAMIC /* i /M : Name of the button
1 H3VALUE     (A) DYNAMIC /* i /M : Value of the input variable
1 H3URL       (A) DYNAMIC /* i /M : URL of the picture to be used
```

How To Invoke

```
PERFORM H3-BUTTON H3TYPE H3NAME H3VALUE H3URL
```

119

Checkbox Group

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-CHECKBOX-GROUP	H3RCGROU	E3RCGROU	E3RCGROU

Description

Creates a checkbox group. The group can be formatted inside a table.

Appearance

```
<INPUT TYPE="CHECKBOX" NAME="string">
```

Supported Attributes

VALUE="*string*", CHECKED

Parameters

```
1 H3ARRAYCOUNT      (I4)          /* i /m : Number of group elements
1 H3ARRAYNAME        (A/1:V) DYNAMIC /* i /m : Name of the group variable
1 H3ARRAYVALUE        (A/1:V) DYNAMIC /* i /M : Default value of the
*                                /* group variable
1 H3ARRAYLABEL        (A/1:V)          /* i /MH: Label of the group element
1 H3ARRAYCHECKED      (L/1:V)          /* i /M : Button selected by default
1 H3LINEBREAK         (L)            /* i /m : Set line breaks between
*                                /* the elements
1 H3ROW               (N4)          /* i /m : Set number of rows for
*                                /* tables
1 H3COLUMN             (N4)          /* i /m : Set number of columns for
*                                /* tables
```

How To Invoke

```
PERFORM H3-CHECKBOX-GROUP H3ARRAYCOUNT H3ARRAYNAME(*)
      H3ARRAYVALUE(*) H3ARRAYLABEL(*)
      H3ARRAYCHECKED(*) H3LINEBREAK H3ROW H3COLUMN
```

120 Comment Line

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-COMMENT	H3COMMEN	E3COMMEN	E3COMMEN

Description

Creates a comment line inside an HTML page.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

```
<!-- value -->
```

Parameters

```
1 H3VALUE (A) DYNAMIC /* i /m : Value to set as comment
```

How To Invoke

```
PERFORM H3-COMMENT H3VALUE
```


121 Level n Header

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-HEADER	H3HEADER	E3HEADER	E3HEADER

Description

Creates a header of a specified level. Levels 1 to 6 are allowed.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

```
<H1> </H1> or  
<H2> </H2> or  
<H3> </H3> or  
<H4> </H4> or  
<H5> </H5> or  
<H6> </H6>
```

Parameters

```
1 H3LEVEL    (N2)          /* i /m : Level of the header  
1 H3HTML     (A) DYNAMIC   /* i /mH: HTML text to be set
```

How To Invoke

```
PERFORM H3-HEADER H3LEVEL H3HTML
```

122 Image

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-IMAGE	H3IMAGE	E3IMAGE	E3IMAGE

Description

Displays an image. The image itself cannot be saved inside Natural. Therefore, all pictures must be saved with the HTTP Server.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

Supported Attributes

ALT="*string*", HEIGHT="*n*", WIDTH="*n*", ALIGN="*left|right|top|middle|bottom*"

Parameters

```
1 H3URL      (A) DYNAMIC /* i /m : URL of the picture source
1 H3STRING    (A) DYNAMIC /* i /M : Alternative name string
*           /*          for non-GUI browsers
1 H3HEIGHT   (N4)      /* i /M : Height of the picture
1 H3WIDTH    (N4)      /* i /M : Width of the picture
1 H3ALIGN    (A1)      /* i /M : Align the picture to
*           /*          'L' Left
*           /*          'R' Right
*           /*          'T' Top
*           /*          'B' Bottom
*           /*          'M' Middle
```

How To Invoke

```
PERFORM H3-IMAGE H3URL H3STRING H3HEIGHT H3WIDTH H3ALIGN
```

123 Input

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-INPUT	H3INPUT	E3INPUT	E3INPUT

Description

Creates an input field. Possible field types are text, password and hidden.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

```
<INPUT TYPE="text|password| hidden" NAME="string">
```

Supported Attributes

VALUE="string", MAXLENGTH="n", SIZE="n"

Parameters

```
1 H3TYPE      (A1)          /* i /m : Type of the input field
*
*                      /*          'T' Text (default)
*
*                      /*          'P' Password
*
*                      /*          'H' Hidden
1 H3NAME      (A) DYNAMIC /* i /M : Name of the input variable
1 H3VALUE     (A) DYNAMIC /* i /M : Default value of the input variable
1 H3SIZE      (N4)           /* i /M : Size of the input box
1 H3MAX       (N4)           /* i /M : Maximum length of the input text
```

How To Invoke

```
PERFORM H3-INPUT H3TYPE H3NAME H3VALUE H3SIZE H3MAX
```

124 Line Break

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-LINE-BREAK	H3LBREA	E3LBREAK	E3LBREAK
H3-LINE_BREAK	H3LBREAK		

Description

Forces a line break, with or without additional HTML text.

Changes from previous versions

Both versions can be used equivalently, because the parameter is marked as optional. You are recommended to use only the version H3-LINE-BREAK. H3-LINE_BREAK will be removed in one of the next versions.

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

Parameters

1. H3-LINE-BREAK

```
1 H3HTML (A) DYNAMIC /* i /0H: HTML text after the line break
```

2. H3-LINE_BREAK

```
1 H3HTML (A) DYNAMIC /* i /OH: HTML text after the line break
```

How To Invoke

```
PERFORM H3-LINE-BREAK  
PERFORM H3-LINE-BREAK 1X  
PERFORM H3-LINE-BREAK H3HTML
```

125 Form

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-OPEN-FORM	H3OFORM	E3FORM	E3FORM
H3-CLOSE-FORM	H3CFORM	E3FORM2 ^(utf-8)	E3FORM2

Description

Creates a form. You must perform H3-OPEN-FORM before and H3-CLOSE-FORM afterwards.

If no H3-CLOSE-FORM is performed, H3-CLOSE-HTML will close all open forms.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

```
<FORM ACTION="URL" METHOD="get|post"> </FORM>
```

Supported Attributes

ACTION="*URL*", METHOD="get|post"

Parameters

1. H3-OPEN-FORM

```
1 H3METHOD (A1)          /* i /m : 'G' Get
*                      /*      : 'P' Post
1 H3URL     (A) DYNAMIC  /* i /m : URL to be called
```

2. H3-CLOSE-FORM

```
/* none
```

How To Invoke

```
PERFORM H3-OPEN-FORM H3METHOD H3URL  
PERFORM H3-CLOSE-FORM
```

126 HTML Document

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-OPEN-HTML	H3OHTML	E3HTML	E3HTML
H3-OPEN-HTML-JAVASCRIPT	H3CHTML		
H3-CLOSE-HTML			

Description

Creates an HTML document with a head, title and beginning of body.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

1. H3-OPEN-HTML

```
<HTML>
<HEAD>
<TITLE>TITLE</TITLE>
</HEAD>
<BODY BACKGROUND="URL", BGCOLOR="#RPG">
```

2. H3-OPEN-HTML-JAVASCRIPT

```
<HTML>
<HEAD>
<SCRIPT LANGUAGE='JavaScript' SRC='URL'></SCRIPT>
<SCRIPT LANGUAGE='JavaScript' >
<!-- hide script from old browsers
PROGRAM
// end hiding from old browsers -->
```

```
</SCRIPT>
<TITLE>TITLE</TITLE>
</HEAD>
<BODY BACKGROUND="URL", BGCOLOR="#RPG">
```

3. H3-CLOSE-HTML

```
</BODY>
</HTML>
```

Supported Attributes

```
BACKGROUND="URL", BGCOLOR="#RPG", SRC='URL'
```

Parameters

1. H3-OPEN-HTML

```
1 H3TITLE      (A) DYNAMIC /* i /m: Title of the HTML document
1 H3BGCOLOR    (A) DYNAMIC /* i /M: Background colour
1 H3BGPICUTURE (A) DYNAMIC /* i /M: Background picture
```

2. H3-OPEN-HTML-JAVASCRIPT

```
1 H3TITLE      (A) DYNAMIC      /* i /m: Title of the HTML document
1 H3BGCOLOR    (A) DYNAMIC      /* i /M: Background colour
1 H3BGPICUTURE (A) DYNAMIC      /* i /M: Background picture
1 H3JAVASRC    (A) DYNAMIC      /* i /M: ULR to a JavaScript source
1 H3JAVA        (A/1:V) DYNAMIC /* i /M: JavaScript
1 H3JAVACOUNTER (I4)           /* i /M: Number of JavaScript source lines
1 H3ONLOAD      (A) DYNAMIC      /* i /M: onload event handler
1 H3ONUNLOAD    (A) DYNAMIC      /* i /M: onunload event handler
```

3. H3-CLOSE-FORM

```
/* none
```

How To Invoke

```
PERFORM H3-OPEN-HTML H3TITLE H3BGCOLOR H3BGPICUTURE
PERFORM H3-OPEN-HTML-JAVASCRIPT H3TITLE H3BGCOLOR H3BGPICUTURE H3JAVASRC H3JAVA
H3JAVACOUNTER H3ONLOAD H3ONUNLOAD
PERFORM H3-CLOSE-HTML
```

127 List

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-OPEN-LIST	H3OLIST	E3LIST	E3LIST
H3-LIST-ITEM	H3LISTI		
H3-CLOSE-LIST	H3CLIST		

Description

Creates various types of lists. Possible types are:

- unordered list,
- ordered list,
- menu-item list and
- directory list.

Cascading lists of up to 10 levels are supported. It is also possible to close more than one level at once.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

1. H3-OPEN-LIST

<DIR> or
<MENU> or
 or

2. H3-LIST-ITEM

```
<LI>
```

3. H3-CLOSE-LIST

```
</DIR> or  
</MENU> or  
</OL> or  
</UL>
```

Supported Attributes

```
TYPE="disc|square| circle" TYPE="1| a|A|i|I"
```

Parameters

1. H3-OPEN-LIST

```
1 H3TYPE    (A1) /* i /m: Set list as:  
*          /* 'O' ordered list  
*          /* 'U' unordered list  
*          /* 'D' directory list  
*          /* 'M' menu list  
1 H3BULLET  (A1) /* i /m: Type of list if ordered list:  
*          /* '1' Arabic numbers (default) (1, 2, 3, ...)  
*          /* 'a' Alphanumeric, lowercase (a, b, c, ...)  
*          /* 'A' Alphanumeric, uppercase (A, B, C, ...)  
*          /* 'i' Roman numbers, lowercase (i, ii, iii, ...)  
*          /* 'I' Roman numbers, uppercase (I, II, III, ...)  
*          /* i /m: Type of bullet if unordered list:  
*          /* 'D' Disc  
*          /* 'S' Square  
*          /* 'C' Circle
```

2. H3-LIST-ITEM

```
1 H3VALUE (A) DYNAMIC /* i /m: Item text
```

3. H3-CLOSE-LIST

```
1 H3LEVEL (N2) /* i /m: Levels to be closed
```

How To Invoke

```
PERFORM H3-OPEN-LIST H3TYPE H3BULLET  
PERFORM H3-LIST-ITEM H3VALUE  
PERFORM H3-CLOSE-LIST H3LEVEL
```


128 Paragraph

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-PARAGRAPH	H3PARAGR	E3PARAGR	E3PARAGR

Description

Creates a new paragraph.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

<P ALIGN="left|right| center"> or <P>

Supported Attributes

ALIGN="left|right|center"

Parameters

```
1 H3ALIGN    (A1)      /* i /m : Align the paragraph to:  
*                      /*      'L' Left (default)  
*                      /*      'R' Right  
*                      /*      'C' Center  
1 H3HTML     (A) DYNAMIC /* i /mh: HTML text after the paragraph
```

How To Invoke

```
PERFORM H3-PARAGRAPH H3ALIGN H3HTML
```

129 Radio Button Group

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-RADIO-GROUP	H3RBGROU	E3RBGROU	E3RBGROU

Description

Creates a radio button group. The group can be formatted inside a table.

Appearance

```
<INPUT TYPE="RADIO" NAME="string">
```

Supported Attributes

VALUE="*string*", CHECKED

Parameters

```
1 H3ARRAYCOUNT (I4)          /* i /m : Number of group elements
1 H3NAME      (A) DYNAMIC    /* i /m : Name of the group variable
1 H3ARRAYVALUE (A/1:V) DYNAMIC /* i /M : Default value of the group
*               /*           variable
1 H3ARRAYLABEL (A/1:V)        /* i /mH: Label of the group element
1 H3ISCHECKED (I4)           /* i /M : Number of default selected
*               /*           button
1 H3LINEBREAK  (L)           /* i /M : Set line breaks between
*               /*           buttons
1 H3ROW        (N4)           /* i /m : Set number of rows for tables
1 H3COLUMN     (N4)           /* i /m : Set number of columns for
*               /*           tables
```

How To Invoke

```
PERFORM H3-RADIO-GROUP H3ARRAYCOUNT H3NAME H3ARRAYVALUE(*)
      H3ARRAYLABEL(*) H3ISCHECKED H3LINEBREAK H3ROW H3COLUMN
```

130 Horizontal Rule

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-RULE	H3RULE	E3RULE	E3RULE

Description

Creates a horizontal rule with a width specified in percentage points.

Appearance

<HR> or <HR WIDTH="*p%*">

Supported Attributes

WIDTH="*p%*"

Parameters

```
1 H3WIDTH (N4) /* i /m : Width in percent
```

How To Invoke

```
PERFORM H3-RULE H3WIDTH
```


131 Scrolling List

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-SCROLLING-LIST	H3SCLIST	E3SCLIST	E3SCLIST

Description

Creates a scrolling list. It can be displayed as a combo box or as a list box.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

```
<SELECT NAME="string"> </SELECT> <OPTION> </OPTION>
```

Supported Attributes

SIZE="*n*", MULTIPLE, VALUE="*string*", SELECTED

Parameters

```
1 H3SIZE          (N4)           /* i /m : Number of lines:  
*                                /*      =1 combo box  
*                                /*      >1 list box  
1 H3ARRAYCOUNT   (I4)           /* i /m : Number of list elements  
1 H3NAME          (A) DYNAMIC    /* i /m : Name of the group variable  
1 H3ARRAYVALUE    (A/1:V) DYNAMIC /* i /M : Default value of the list values  
1 H3ARRAYLABEL    (A/1:V) DYNAMIC /* i /MH: Label of the list elements  
1 H3ARRAYSELECTED (L/1:V)       /* i /M : Elements selected by  
*                                /*      default  
1 H3MULTIPLE      (L)            /* i /M : Multiple selection allowed
```

How To Invoke

```
H3-SCROLLING-LIST H3SIZE H3ARRAYCOUNT H3NAME  
H3ARRAYVALUE(*) H3ARRAYLABEL(*)  
H3ARRAYSELECTED(*) H3MULTIPLE
```

132 Table

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-TABLE	H3TABLE	E3TABLE	E3TABLE
H3-TABLE-COLOR	H3TABLEC		

Description

Creates a simple table for a given array. With H3-TABLE-COLOR, for headline and table, different background colors can be set. The rows will be colored alternately.

Appearance

```
<TABLE>
<TH>
<TD> ... </TD>
</TH>
<TR>
<TD> ... </TD>
</TR>
</TABLE>
```

Supported Attributes

ALIGN="left|right|center", BORDER="n", NOWRAP

Parameters**1. H3-TABLE**

1 H3ROW	(N4)	/* i /m : Number of rows
1 H3COLUMN	(N4)	/* i /m : Number of columns
1 H3ARRAY2VALUE	(A/1:V,1:V) DYNAMIC	/* i /mh: Table elements
1 H3ARRAY2ALIGN	(A1/1:V,1:V)	/* i /M : Alignment of the table cells * 'L' Left (default) * 'R' Right * 'C' Center
*		
*		
*		
1 H3ARRAY2NOWRAP	(L/1:V,1:V)	/* i /m : No automatic wrapping
1 H3HEADLINE	(L)	/* i /M : 1st line as headline
1 H3ALIGN	(A1)	/* i /M : Alignment of the table * 'L' Left (default) * 'R' Right * 'C' Center
*		
*		
*		
1 H3SUPPRESSEMPY	(L)	/* i /m : Set to TRUE if cell is * to be displayed * despite being empty
*		
*		
1 H3ISHTML	(L)	/* i /m : Transform value to * HTML
*		
1 H3BORDER	(N4)	/* i /M : Set border size

2. H3-TABLE-COLOR

1 H3ROW	(N4)	/* i /m : Number of rows
1 H3COLUMN	(N4)	/* i /m : Number of columns
1 H3TITLECOLOR	(A032)	/* i /M : Color of headline
1 H3LINECOLOR	(A032)	/* i /M : Color of lines
1 H3ARRAY2VALUE	(A/1:V,1:V) DYNAMIC	/* i /mh: Table elements
1 H3ARRAY2ALIGN	(A001/1:V,1:V)	/* i /m : Alignment of the table cells * 'L' Left (default) * 'R' Right * 'C' Center
*		
*		
*		
1 H3ARRAY2NOWRAP	(L/1:V,1:V)	/* i /m : No automatic wrapping
1 H3HEADLINE	(L)	/* i /m : 1st line as headline
1 H3ALIGN	(A1)	/* i /M : Alignment of the table * 'L' Left (default) * 'R' Right * 'C' Center
*		
*		
*		
1 H3SUPPRESSEMPY	(L)	/* i /m : Set to TRUE if cell is * to be displayed * despite being empty
*		
*		
1 H3ISHTML	(L)	/* i /m : Transform value to * HTML
*		
1 H3BORDER	(N4)	/* i /m : Set border size

How To Invoke

```
PERFORM H3-TABLE H3ROW H3COLUMN H3ARRAY2VALUE(*,*)  
    H3ARRAY2ALIGN(*,*) H3ARRAY2NOWRAP(*,*) H3HEADLINE H3ALIGN  
    H3SUPPRESSEEMPTY H3ISHTML H3BORDER  
  
PERFORM H3-TABLE-COLOR H3ROW H3COLUMN H3TITLECOLOR H3LINECOLOR  
    H3ARRAY2VALUE(*,*) H3ARRAY2ALIGN(*,*) H3ARRAY2NOWRAP(*,*) H3HEADLINE H3ALIGN  
    H3SUPPRESSEEMPTY H3ISHTML H3BORDER
```


133 Universal Tag

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-TAG	H3TAG	E3TAG	E3TAG

Description

Creates a universal tag (tag template) inside an HTML page. This tag template creates the framework into which code can be written.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

<tag> </tag>

Parameters

```
1 H3PRE  (A) DYNAMIC /* i /m : Open tag value
1 H3HTML (A) DYNAMIC /* i /m : HTML inside the tag
1 H3POST (A) DYNAMIC /* i /m : Close tag value
```

How To Invoke

```
PERFORM H3-TAG H3PRE H3HTML H3POST
```

134 Text Area

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-TEXT-AREA	H3TXAREA	E3TXAREA	E3TXAREA

Description

Creates a text area.

Changes from previous versions

All (A250) BY VALUE variables at the interfaces have been changed to (A) DYNAMIC BY VALUE.

There is no need to recatalog the programs, because the old interface (A250) is compatible with the new one.

Appearance

```
<TEXTAREA NAME="string"> </TEXTAREA>
```

Supported Attributes

ROWS="*n*", COLS="*n*"

Parameters

```
1 H3ARRAYCOUNT (I4)          /* i /m : Number of text lines
1 H3NAME      (A) DYNAMIC    /* i /m : Name of the text variable
1 H3ARRAYTEXT (A/1:V) DYNAMIC /* i /M : Default value of the text
                               /*           variable
1 H3ROW       (N4)           /* i /M : Set number of rows
1 H3COLUMN    (N4)           /* i /M : Set number of columns
```

How To Invoke

```
PERFORM H3-TEXT-AREA H3ARRAYCOUNT H3NAME H3ARRAYTEXT(*) H3ROW H3COLUMN
```

135 Text to URL - Decoded

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-TEXT-TO-URL	H3TX2URL	E3TX2URL	E3TX2URL
H3-ASCII-URL-TABLE			

Description

Converts a string to URL-decoded syntax. Useful if special characters are included. Use [W3-TEXT-TO-URL](#) instead of H3-TEXT-TO-URL. Use [W3-ASCII-URL-TABLE](#) instead of H3-ASCII-URL-TABLE.

The subprogram W3-ASCII-URL-TABLE will be called from H3-TEXT-TO-URL and contains a list of all conversations that will be made. This program can be changed and extended according to the user's needs.

Parameters

```
1 H3COUNT    (I4)      /* o/m : Length of the converted string  
1 H3STRING   (A250)    /* io/m : URL-decoded text after conversion
```

How To Invoke

```
PERFORM H3-TEXT-TO-URL H3COUNT H3STRING
```


136 Time/Date String

Subprogram Name	Source Name	Executable Example	Viewable Example
H3-TIME_DATE	H3TIMDAT	E3TIMDAT	E3TIMDAT
H3-TIME-DATE	H3TIMDA		

Description

Creates a 'generated: ...' string using the LOG time or an HTTP-compatible time/date string with offset, using the current time/date (because GMT or offset to GMT is not recognized by Natural).

Appearance

generated: *time/date*

Parameters

1. H3-TIME_DATE

```
/* none
```

2. H3-TIME-DATE

```
1 H3ADDMINUTE  (I4)  /* i /m : Adds minutes to time
1 H3ADDDAY     (I4)  /* i /m : Adds days to date
1 H3DATETIME   (A29) /* o/m : Generated string
```

How To Invoke

```
PERFORM H3-TIME_DATE PERFORM H3-TIME-DATE H3ADDMINUTE H3ADDDAY H3DATETIME
```

137 List all Natural Libraries

Subprogram Name	Executable Example	Viewable Example
NAT-LIB	NAT-LIB NAT-LIB?FNAT=N	NAT-LIB

Description

Generates an HTML page and displays all available Natural libraries. If no FNAT parameter is given, the default user libraries will be displayed.

Parameters

FNAT=	N = system libraries U = user libraries (default)
EXPIRE=	Adds days to current date and sets it as expiry date.
START=	Wildcard selection for the displayed object set.

How To Invoke

```
NAT-LIB  
NAT-LIB?FNAT=N
```


138

Run Online Natural Web Interface Subprograms

Natural Program
WEB-ONL

Description

For reasons of debugging or testing, it is useful to run Natural Web Interface subprograms online. The output of the generated page will be saved as a Natural text object. Lines longer than 92 characters will be split.

It is possible to set environment variables. If the variables should be set as server variables, add an ampersand in front of the name.

How To Invoke

Run Program WEB-ONL from the Natural *next* prompt.

139 Generate Natural Subprogram to use with Natural Web Interface

Natural Program	Executable Generation Result	Viewable Generation Result
WEB-WIZ	Basic Subroutines HTML Extension	HTTPApi HTMLApi

Description

Generates a default program. This function will be deleted in one of the next versions. Under Windows, use the [Web Interface Plug-In](#).

Input Map

```
12:12:40      ***** Natural Web Subprogram Wizard *****      2005-11-15
               - Main Menu -          Library SYSWEB
```

```
Subprogram Name ..... DUMMY_
Title ..... HTTP/HTML API WIZARD_____
Header ..... HTTP/HTML API WIZARD_____
```

```
Use HTML extension .. X
```

Enter - PF1 --- PF2 --- PF3 --- PF4 --- PF5 --- PF6 --- PF7 --- PF8 --- PF9 --- PF10 -- PF11 -- PF12 ---
Exit

How To Invoke

Run Program WEB-WIZ from the Natural NEXT prompt.

140 List All Data Passed From a HTTP Server to a Called Natural Subprogram

Subprogram Name	Executable Example	Viewable Example
NAT-DATA	NAT-DATA NAT-DATA?parm1=test1&parm2=test2 E3MULTIP	NAT-DATA E3MULTIP

Description

Generates an HTML page with all data passed from the HTTP server to a called Natural subprogram, including mime-type, HTTP header, parameters, alphanumeric data and binary data.

Parameters

```
/* none
```

How To Invoke

```
NAT-DATA
```


141 List Directory of a Natural Library

Subprogram Name	Executable Example	Viewable Example
NAT-DIR	NAT-DIR?lib=sysweb NAT-DIR?lib=sysweb3&version=no&start=E3* NAT-DIR?lib=sysweb&start=E3*	NAT-DIR

Description

Generates an HTML page with the directory information of a Natural library. If no library parameter has been defined, the current library will be displayed.

New with Natural Version 6.2

Version check for the subprogram modules added. Displays SYSWEB if cataloged with library SYSWEB and SYSWEB3 if cataloged with library SYSWEB3. If NAT-DIR is called with the SYSWEB interface then no run link will be displayed.

Parameters

LIB=	Natural LIBRARY
EXPIRE=	Adds days to current date and sets it as expiry date.
START=	Wildcard selection for the object set displayed.
VERSION=	If set to NO, subprograms will not be checked on the SYSWEB version used during runtime (either SYSWEB or SYSWEB3). Default is YES.

How To Invoke

```
nat-dir?lib=sysweb3
```

142

List Resources of a Natural Library

Subprogram Name	Executable Example	Viewable Example
NAT-DIRR	NAT-DIRR?lib=sysweb3 NAT-DIRR?lib=sysweb3&start=*.jpg NAT-DIRR?lib=sysweb&start=*.htm	NAT-DIRR

Description

Generates an HTML page with the resource file information of a Natural library. If no library parameter has been defined, the current library will be displayed.

Parameters

LIB=	Natural LIBRARY
EXPIRE=	Adds days to current date and sets it as expiry date.
START=	Wildcard selection for the object set displayed.

How To Invoke

```
nat-dirr?lib=sysweb3
```


143 List All Parameters Passed From a HTTP Server To a Called Natural Subprogram

Subprogram Name	Executable Example	Viewable Example
NAT-ENV	NAT-ENV	NAT-ENV

Description

Generates an HTML page with all parameters passed from the HTTP server to a called Natural subprogram.

How To Invoke

```
nat-env
```


144

Return an HTML Page Saved as Natural Source Object

Subprogram Name	Executable Example	Viewable Example	Text Object
NAT-HTML	NAT-HTML?lib=sysweb&source=t3-html	NAT-HTML	T3-HTML

Description

Displays an HTML page saved as a Natural source object.

Parameters

LIB=	Natural LIBRARY
SOURCE=	SOURCE NAME

How To Invoke

```
nat-html?lib=sysweb&source=HTML
```


145

List the Current Natural Web Interface Settings

Subprogram Name	Executable Example	Viewable Example
NAT-INFO	NAT-INFO	NAT-INFO

Description

Generates an HTML page with information about your HTTP Browser, HTTP Server, communication software (RPC/DCOM) and Natural environment.

How To Invoke

```
nat-info
```


146 List Source of Natural Object

Subprogram Name	Executable Example	Viewable Example
NAT-LIST	NAT-LIST?lib=sysweb&source=h3image	NAT-LIST

Description

Generates an HTML page with the listing of a Natural source object.

Parameters

LIB=	Natural LIBRARY
SOURCE=	SOURCE NAME
EXPIRE=	Adds days to current date and sets it as expiry date.
LINE-NUMBERS=	The only value possible is OFF

How To Invoke

```
nat-list?lib=sysweb&source=H3IMAGE
```


147 Online Documentation

Subprogram Name	Executable Example
NAT-DOCU	NAT-DOCU

Description

Displays the online documentation saved as Natural source objects.

Parameters

LIB=	Natural LIBRARY
SOURCE=	SOURCE NAME
EXPIRE=	Adds days to current date and sets it as expiry date.

How To Invoke

```
nat-docu
```


148 List non-Natural File - Resource

Subprogram Name	Executable Example	Viewable Example
NAT-RES	NAT-RES?source=e3xslt2.xml&lib=sysweb NAT-RES?source=composing_natural_logo.jpg&lib=sysweb3 NAT-RES/sysweb3/e3put.html	NAT-RES

Restriction

Only available on platforms with shared resources.

Description

Generates an HTML page with the listing of a Natural source object. Depending on the definition at the text member **MIMEDATA** the data will be transferred as binary or as alphanumeric data.

Parameters

LIB=	Natural LIBRARY
SOURCE=	Resource name with extension

How To Invoke

```
nat-res?source=e3xslt2.xml&lib=sysweb3
```

How To Invoke with extended URL syntax

Instead of specifying the parameters LIB= and SOURCE=, library and source name can be added directly after the program name. nat-res/<yourlibrary>/<yourresource>

Extended Functionality

If the HTTP server is PUT enabled, NAT-RES can be used to write back to the HTTP server with an HTTP put request.

To activate the PUT capability, modify the subprogram NAT-RES by setting the variable F_PUT to TRUE and recatalog the subprogram NAT-RES.

149 XML Toolkit Plug-In

The XML Toolkit plug-in enables developers to process XML documents within Natural.

The toolkit includes a wizard which generates Natural source code and provides the following features:

- Mapping Natural data definitions to DTDs or XML schemas;
- Serializing a Natural data structure and assigning its contents to an XML file;
- Mapping DTDs to Natural data definitions;
- Parsing an XML file and assigning its contents to a Natural data structure.

The wizard is included in the library SYSXTK.

This document describes an example application that demonstrates the use of XML within a Natural-for-Windows environment without external program parts.

The following topics are covered:

- [Introduction](#)
- [Using the XML Toolkit](#)
- [Setting Up Specific Generation Options](#)
- [Using a Natural Data Source](#)
- [Using an external Data Source](#)
- [Natural Simple XML Parser](#)
- [Examples](#)



Parser Error Messages

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes and new editions.

150 Introduction

■ XML Toolkit Features	406
■ XML Toolkit Description	406
■ Considerations and Limitations	410

The following topics are covered:

XML Toolkit Features

- Natural-based XML parser using dynamic variables.
- Functions for
 - conversion of Natural data structures into DTD definitions;
 - generation of COMPRESS statements to save a Natural data structure as an XML document;
 - generation of callback for the Natural-based parser.

XML Toolkit Description

Objective

The objective of the Natural XML Toolkit is to provide additional XML functionality with Natural and improve the integration of Natural applications with XML.

General Architecture

The Natural XML Toolkit is implemented as a Natural plug-in. The Toolkit programs may be integrated into customer applications to provide access to XML data or to deliver data from Natural in XML format.

The Natural XML Toolkit calls the functions listed below:

XML Toolkit Functions

1. Mapping of Natural Data Definition to DTD or XML Schema and vice versa.

2. XML Token => NAT

Data After the Natural data structure has been created, the XML document has to be parsed and saved into the data structure. A Natural implementation is generated that is capable of saving the given data into the Natural data structure.

3. NAT Data => XML Document ("Serialize")

Serialization is the process of taking the data stored in the Natural data structures and creating an XML document according to the description provided.

A Natural dialog implements the user interface to the XML Toolkit functions. The DTD or XML Schema will be accessed as a work file and the generated Natural objects will be saved directly to the Natural system file.

Map Natural Data Definitions to DTD

This mapping is the first step to bind Natural data structures to XML tags and is required to implement a representation of Natural data as XML tags. The example below shows the mapping as well as some obvious differences between Natural and a DTD.

Natural PDA

```

Press ESC to enter command mode
Mem: EMPL      Lib: SYSXTK   Type: PARAMETER  Bytes: 1072  Line: 0 of: 26
C T  Comment
*   *** Top of Data Area ***
1 EMPLOYEE
2 ATTRIBUTES_OF_EMPLOYEE
3 PERSONNEL-ID           A          8
*
2 FULL-NAME
3 FIRST-NAME             A          20
3 NAME                    A          20
*
2 FULL-ADDRESS
3 C@ADDRESS-LINE          I          4
3 ADDRESS-LINE            A          20 (1:6)
3 CITY                     A          20
3 ZIP                      A          20
3 COUNTRY                 A          3
*
2 TELEPHONE
3 AREA-CODE               A          6
3 PHONE                    A          15

```

Generated DTD

```

<!ELEMENT EMPLOYEE (PERSONNEL-ID, FULL-NAME, FULL-ADDRESS, TELEPHONE, INCOME* )>
<!ELEMENT PERSONNEL-ID (#PCDATA ) >

<!ELEMENT FULL-NAME (FIRST-NAME, NAME )>
  <!ELEMENT FIRST-NAME (#PCDATA )>
  <!ELEMENT NAME (#PCDATA )>

<!ELEMENT FULL-ADDRESS (ADDRESS-LINE*, CITY, ZIP, COUNTRY )>
  <!ELEMENT ADDRESS-LINE (#PCDATA )>
  <!ELEMENT CITY (#PCDATA )>
  <!ELEMENT ZIP (#PCDATA )>
  <!ELEMENT COUNTRY (#PCDATA )>
...

```

The generated DTD will be used later on during serialization to a XML document (see below).

Serialize Data to XML

During execution of a Natural program, the content of the data defined in the DEFINE DATA statement will be filled with "real" content. This content will be written to a dynamic variable in XML format during serialization and will use the formerly generated DTD as input.

The XML Toolkit generates the program to serialize the data.

```
<?xml version="1.0" encoding="iso-8859-1" ?>
<EMPLOYEE PERSONNEL-ID="30016509">
<FULL-NAME>
  <FIRST-NAME>ELSPETH</FIRST-NAME>
  <NAME>TROWBRIDGE</NAME>
</FULL-NAME>
<FULL-ADDRESS>
  <ADDRESS-LINE>91 BACK LANE</ADDRESS-LINE>
  <ADDRESS-LINE>BILSTON</ADDRESS-LINE>
  <ADDRESS-LINE>STAFFORDSHIRE</ADDRESS-LINE>
  <CITY>BILSTON</CITY>
  <ZIP>ST2 3KA</ZIP>
  <COUNTRY>UK</COUNTRY>
</FULL-ADDRESS>
<TELEPHONE>
  <PHONE>863322</PHONE>
  <AREA-CODE>0602</AREA-CODE>
</TELEPHONE>
...
...
```

Map DTD to Natural Data Definitions

The mapping of a DTD to Natural data structures again shows differences. The DTD does not specify how many person records will be included in the XML document, therefore the Toolkit assumes that a maximum number of "v" persons will be included. The application programmer might know the exact number and the data structure could be adapted accordingly. A similar limitation exists with the length of the data. The DTD does not include information about the length of the data in a person's record. Therefore the Toolkit creates fields in the data structure with a length of A dynamic, the current maximum.

```

* DTD E:\SAG\nat\6.3\fnat\SYSXTK\RES\empl.dtd
COMPRESS &1& '<EMPLOYEE'
    ' PERSONNEL-ID=""EMPLOYEE.PERSONNEL-ID ""
    '>' INTO &1& LEAVING NO
/* now the children
COMPRESS &1& '<FULL-NAME'
    ' '>' INTO &1& LEAVING NO
/* now the children
COMPRESS &1& '<FIRST-NAME'
    ' '>
    EMPLOYEE.FIRST-NAME
    '</FIRST-NAME>' INTO &1& LEAVING NO
COMPRESS &1& '<NAME'
    ' '>
    EMPLOYEE.NAME
    '</NAME>' INTO &1& LEAVING NO
/*
COMPRESS &1& '</FULL-NAME>' INTO &1& LEAVING NO
COMPRESS &1& '<FULL-ADDRESS'
    ' '>' INTO &1& LEAVING NO
/* now the children
FOR &2& = 1 TO EMPLOYEE.C@ADDRESS-LINE
    COMPRESS &1& '<ADDRESS-LINE'
        ' '>
        EMPLOYEE.ADDRESS-LINE(&2&)
        '</ADDRESS-LINE>' INTO &1& LEAVING NO
END-FOR
...

```

Parse XML File and Assign to Natural Data

```

* DTD E:\SAG\nat\6.3\fnat\SYSXTK\RES\empl.dtd
DECIDE ON FIRST &1&
    VALUE 'EMPLOYEE'
        RESET INITIAL EMPLOYEE
    VALUE 'EMPLOYEE/@PERSONNEL-ID'
        /* #REQUIRED
        EMPLOYEE.PERSONNEL-ID := &3&
    VALUE 'EMPLOYEE/FULL-NAME'
        IGNORE
    VALUE 'EMPLOYEE/FULL-NAME/FIRST-NAME'
        IGNORE
    VALUE 'EMPLOYEE/FULL-NAME/FIRST-NAME/$'
        EMPLOYEE.FIRST-NAME := &3&
    VALUE 'EMPLOYEE/FULL-NAME/NAME'
        IGNORE
    VALUE 'EMPLOYEE/FULL-NAME/NAME/$'
        EMPLOYEE.NAME := &3&

```

...

Considerations and Limitations

The XML Toolkit only supports fully assembled XML Schema (Layer 1). For detailed information, refer to the W3C recommendation on [XML Schema \(Layer 1\)](#)

When using the XML Toolkit, the following further limitations should be considered.

- [Very Large Data Structures](#)
- [Multi-Dimensional Arrays](#)
- [XML Schema: Access and Composition](#)
- [DTD: Add external parsed data](#)
- [Conditional DTD](#)
- [Wildcards](#)

Very Large Data Structures

Data structures which will result in more than approximately 700 data fields and groups will end up with the message:

Input Structure too big

Solution

Split up the data structure into smaller sections.

Multi-Dimensional Arrays

The following limitations apply, when generating an XML document from a [Natural data area](#), if the source data contains arrays:

- For each array, exactly one dimension is allowed.
- For each level, exactly one dimension can be added.
- Each array must have a counter variable.
- The counter variable
 - must be located before the array and

- the counter variable name must start with the character C followed by the **counter separator field**.
- The *LBOUND (lower boundary) of the array must be 1.

XML Schema: Access and Composition

<include>

Include adds multiple schemas with the same target namespace to a document. The document needs to be included, without any changes.

<import>

Import adds multiple schemas with different target namespaces to a document. First the document to be imported requires a namespace prefix translation, then the document can be included.

<redefine>

Redefine selects out specific simple and complex types, groups, and attribute groups from an external schema, and enables you to modify the given specification for your own needs.



Note: With all of the above elements, only relative URIs are allowed. Absolute URIs (e.g. <http://www.yourdomain.com/your/path> or <file:///your/path>) can not be used.

DTD: Add external parsed data

The external data has to be included into the document. There are no conversions necessary.

Conditional DTD

If a <! [INCLUDE] is found, the contained definition will be used for generation.

If a <! [IGNORE] is found, the contained definition will not be used for generation.

Wildcards

The XML Toolkit supports two different kinds of wildcard representations:

- Save all subsequent elements or
- Save all attributes that are not specified

For wildcard support the following rules and/or limitations apply.

XML Schema <anyAttribute>

For attributes an attributes_of_<entity-name> group is generated. All attributes connected to this group are added. The name of an attribute is saved as a variable name; the content is the content of the variable.

To add `<any>` attributes, it is required to add a variable that contains all attributes not specified.

-  **Note:** The `<any>` attributes are no "real" attributes; they are used as a container for the not parsed data and contain the attribute/value pairs. An `<any>` attribute is represented by a `##ANY` variable of type (A) dynamic.

Because it can be necessary to access this data, a more specific name should be used instead of `##ANY` followed by a generic number. It is recommended to add the name of the parent entity and the keyword ATTR, or ATTRIBUTE. See below for an example:

```
1 HTML
2 BODY
3 ATTRIBUTES_OF_BODY
4 BGCOLOR      (A) DYNAMIC
4 ##ANY_ATTR_BODY (A) DYNAMIC
```

If, during the parse process, an attribute that is not named inside the XML Schema is found, the variable name and value will be saved at the `all_attributes_of_<element-name>` group as they are, this means with the standard XML syntax:

`<attribute-name1>=<attribute-value1> <attribute-name2>=<attribute-value2> etc.`

When serializing, the above string will be added.

XML Schema `<any>` or DTD `<!ELEMENT element-name ANY>`

To add the `<any>` data type, it is necessary to save all subsequent data of an entity, regardless of the names and values of this entity.

-  **Note:** The `<any>` entities do not specify "real" entities; they are used as a container for the not parsed data and contain the entities with their entire content (attributes, etc.). An `<any>` entity is represented by a `##ANY` variable of type (A) dynamic.

Because it can be necessary to access this data, a more specific name should be used instead of `##ANY` followed by a generic number. It is recommended to add the name of the parent entity. See below for an example:

```
1 HTML
2 BODY
3 ATTRIBUTES_OF_BODY
4 BGCOLOR      (A) DYNAMIC
4 ##ANY_ATTR_BODY (A) DYNAMIC
3 ##ANY_BODY      (A) DYNAMIC
```

If, during the parse process, an element of type `<any>` is found, all subsequent data is collected.

When serializing, all data is taken without changes and is added to the resulting XML document.

Restrictions for xs:any

Even if the attributes "maxOccurs" and/or "minOccurs" for xs:any are specified, the Natural variable implementing xs:any is always a scalar. The Natural variable may contain data of more than one entity.

The attribute "namespace" for xs:any is not evaluated, the Natural variable implementing xs:any may contain entities of different namespaces.

The attribute "processContents" for xs:any is not evaluated, because the parser used is not validating.

If a xs:choice or xs:sequence contains more than one definition of xs:any, the generation ends with an error, because during parse different <any> containers can not be recognized.

If a document contains entities that are not specified at the XML schema, and at the same level xs:any is defined, the Natural variable implementing xs:any may contain this "nonspecified" entity data.

Natural: Generation of an XML Schema or DTD with ##ANY Wildcards

During generation of an external data structure, each variable prefixed with ##ANY will be converted to the specific wildcard functions:

- ##ANY_ -> any entity type. Applies to DTDs and XML Schema.
- ##ANY_ATTR_ -> any attribute type. Applies to XML Schema only.

151 Using the XML Toolkit

■ Invoking the Application	416
■ Getting Help	416

The following topics are covered:

Invoking the Application

The XML toolkit is included in the library SYSXTK.

- ▶ **To use the XML Toolkit**
 - Select the library SYSXTK from the library workspace.

In the Dialogs folder choose dialog Menu.

Or:

In the Natural command line, enter LOGON SYSXTK.

Enter Menu.

The first screen of the dialog wizard is displayed.

The following functions are available:

- **Generate from Natural Data Structure** Uses the Natural Data Area as a data source.
- **Generate from Document Type Definition/XML Schema** Uses the Document Type Definition (.dtd), XML Schema (.xsd) or Tamino Schema 2 (.tsd) as a data source.
- **Set up Specific Generation Options**

Getting Help

- ▶ **To get help with the XML Toolkit**

- In the XML Toolkit main dialog choose XML Toolkit Help from the Help menu.

Or:

Press F1 in the XML Toolkit main dialog.

152 Setting up Specific Generation Options

▪ Invoking the Natural XML Options Menu	418
▪ Generation	418
▪ Path	422
▪ Saving Your Options Permanently	423

The generation options are arranged on three different tabs and are grouped into generation, view and path definitions.

The following topics are covered below:

Invoking the Natural XML Options Menu

- ▶ **To invoke the Natural XML Options Menu**
 - Choose Options from the Generate menu.

The Generation tab of the Natural XML Options menu is displayed. The fields of the menu tabs are described below.

Generation

Special characters that are not valid in XML have to be converted into valid names. The following menu enables you to change the default conversion settings, if required.



Field Descriptions

Counter Separator Character

Belongs to Group:	Additional Fields
Default Value:	@

Namespace Separator Character ":" WITH:

Belongs to Group:	XML Name Replacements
Default Value:	\$

Dot Sign '.' WITH:

Belongs to Group:	XML Name Replacements
Default Value:	/

Plus Sign '+' WITH:

Belongs to Group:	XML Variable Name Replacements
Default Value:	plus

Hash / Number Sign '#' WITH:

Belongs to Group:	Natural Variable Name Replacements
Default Value:	hash

Slash Sign '/' WITH:

Belongs to Group:	Natural Variable Name Replacements
Default Value:	slash

At Sign '@' WITH:

Belongs to Group:	Natural Variable Name Replacements
Default Value:	at

Paragraph Sign '§' WITH:

Belongs to Group:	Natural Variable Name Replacements
Default Value:	para

Ampersand Sign '&' WITH:

Belongs to Group:	Natural Variable Name Replacements
Default Value:	amp

Dollar Sign '\$' WITH:

Belongs to Group:	Natural Variable Name Replacements
Default Value:	dollar

Parse Statement


Belongs to Group:	Code Generation
Default Value:	checked (Yes)

X-Arrays

Belongs to Group:	Code Generation
Default Value:	checked (Yes)

Path

The Path tab of the Natural XML Options menu serves to define the location of the target or source DTD file used for the conversion.



Field Descriptions

External file

Default Value:	(Resource directory of current library)
-----------------------	---

Natural library

Default Value:	(current library)
-----------------------	-------------------

Saving Your Options Permanently

All settings made in the XML Options menu are written to the text member XML-INI.

Whenever a new Natural patch level or service pack is installed, all settings made in the XML Options menu are overwritten.

In order to keep your settings permanently, you are recommended to save the text member XML-INI to the FUSER before you install a patch level or service pack.

153 Using a Natural Data Source

▪ Select Natural Data Area	426
▪ Select Data Type	428
▪ Generate File with DTD Definition or XML Schema	429
▪ Generate a serializer for an XML document	431
▪ Generate a parser for an XML document	432
▪ Parameter Settings	433
▪ Select Root Group	434
▪ Show Generation Report	435

This function enables you to generate an XML document from a data definition held in a Natural local, global or parameter data area.

The following topics are covered:

See also:

- [Using a Document Type Definition as Data Source](#)
- [Setting up Specific Generation Options](#)

Select Natural Data Area

This dialog serves to select generation from a Natural Data Structure or a XML Schema or Document Type Definiton.

► To invoke the dialog shown below

1 Activate the XML Plug-In in 'Tools' > 'Configuration Tools' > 'Plug-In Manager' > 'XML Toolkit'.


Or:

Alternatively choose the  button to open the Plug-In Manager.

2 Select 'Tools' > 'Development Tools' > ' XML Toolkit'.



Note: The entries shown in the dialogs below are default or example values.



Choose if you would like to generate from a Natural Data Source or from a XML Schema or DTD.

Select **Next** to continue.

Field Descriptions

Library

Belongs to Group:	Select Input Data Area
Default Value:	(All libraries)

Type


Belongs to Group:	Select Input Data Area
--------------------------	------------------------

Name

Belongs to Group:	Select Input Data Area
Format/Length:	A8
Default Value:	(All objects of the selected library and type)

Select Data Type

This dialog is used to select the data type.



Field Descriptions

Library

Belongs to Group:	Library
Default Value:	(All libraries)

Type

Belongs to Group:	Type
Possible Values:	Local Data Area Parameter Data Area Global Data Area

Name


Belongs to Group:	Name
Default Value:	(All objects of the selected library and type)

Select the desired element, e.g. EMPLOYEE .

Choose **Next** to continue.


Generate File with DTD Definition or XML Schema

In this dialog you can specify a file name for the output data area.



Choose **Next** to continue.

Generate a serializer for an XML document



This dialog is used to specify a Natural Library, file type and file name for the output source.

Field Descriptions

Library

Belongs to Group:	Library
Default Value:	(All libraries)

Type

Belongs to Group:	Type
Possible Values:	Copycode Subprogram


Name

Belongs to Group:	Name
Default Value:	(All objects of the selected library and type)

Choose **Next** to continue.

Generate a parser for an XML document

This dialog is used to generate copycode as implementation for the serialization of the given group into an XML document.



Field Descriptions

Library

Belongs to Group:	Library
Default Value:	(All libraries)

Type


Belongs to Group:	Type
Possible Values:	Copycode Subprogram

Name

Belongs to Group:	Name
Default Value:	(All objects of the selected library and type)

Choose **Next** to continue.


Parameter Settings



This screen shows you the settings used for the generation process.

Choose **Next** to continue.

Select Root Group




In this dialog you can select the Root Group .

Choose **OK** to continue.

Show Generation Report

After the generation is complete, the generation report is displayed.



Choose **Finish** to end the generation process.

154 Using an external Data Source

▪ Generate from Document Type Definition or XML Schema	438
▪ Select Root Element or Document Type	440
▪ Select Recursion Level	440
▪ Generate Natural Data Area	442
▪ Generate Copycode for Serialization	443
▪ Generate Subprogram for Serialization	445
▪ Generate Copycode for XML Parser Callback	445
▪ Generate Subprogram for XML Parser Callback	447
▪ Show Generation Results	447

This function enables you to parse an XML document into a Natural variable defined in a local, global or parameter data area.

The following topics are covered:

See also:

- [Using a Natural Data Area as Data Source](#)
- [Setting up Specific Generation Options](#)

 **Note:** When using an XML Schema (XSD) as input document type, the first XSD element will be used as the root element.

Generate from Document Type Definition or XML Schema

This dialog is used to select a Document Type Definition (DTD), XML Schema (XSD) or Tamino Schema 2 (TSD) as input Document Type.


- ▶ **To invoke the dialog shown below**
- Choose From DTD/XSD from the Generate menu.

Or:



Choose the  button.

 **Note:** The field entries shown in the dialogs below are default or example values.



Field Descriptions


Input File

Select a DTD, XSD or TSD file. You can use the browse button to search for an existing DTD, XSD or TSD file.

Choose **Next** to continue.

Select Root Element or Document Type

This dialog is used to select an element or document type that should be the root of your XML document.



Field Descriptions

Root Element (for DTDs)

Default Value: (All Elements)

Select the desired element, e.g. EMPLOYEE, and choose **OK**.


Document Type (for Tamino Schema)

Default Value: (All Elements)

Select the desired element, e.g. EMPLOYEE, and choose **OK**.

Select Recursion Level

This dialog is only displayed, if the DTD, XSD or TSD selected in the first dialog includes recursive elements.



Field descriptions

Recursive Element

Name of the Element that is used recursively.

Default Value: (All Libraries)

Level

Number of recursion levels that should be generated.

Default Value: 3

Use same level for all following recursive elements


If another recursive element is found, the same recursion level will be used.

Default Value: unchecked

Choose **OK** to continue.

Generate Natural Data Area

This dialogsreen is used to generate a Natural Data Area with definition of a group that represents the XML document.



Field Descriptions

Library

Belongs to Group:	Select Output Copycode
Default Value:	(All libraries)

Type

Belongs to Group:	Select Output Copycode
Default Value:	L - Local Data Area


Name

Belongs to Group:	Select Output Copycode
Default Value:	(All objects of the selected library and type)

Choose **Next** to continue.

Generate Copycode for Serialization

This dialog is used to generate copycode as implementation for the serialization of the given group into an XML document.



See also [Serialize Copycode](#) (in the Examples document).

Field Descriptions

Library

Belongs to Group:	Select Output Copycode
Default Value:	(All libraries)

Type

Belongs to Group:	Select Output Copycode
Default Value:	Copycode

Name

Belongs to Group:	Select Output Copycode
Default Value:	(All objects of the selected library and type)

Choose **Next** to continue.


Generate Subprogram for Serialization

This dialog is used to generate a subprogram as implementation for the serialization of the given group into an XML document.

It uses the same entries as the above dialog for copycode, except that the Type field contains the entry Subprogram.

Generate Copycode for XML Parser Callback

This dialog is used to generate copycode as implementation for the XML Parser Callback for the given group.



Generates the parser CALLBACK copycode. See also [Parser CALLBACK Copycode](#) (in the Examples document).

Field Descriptions

Library

Belongs to Group:	Select Output
Default Value:	(All libraries)

Type

Belongs to Group:	Select Output
Default Value:	Copycode

Name

Belongs to Group:	Select Output
Default Value:	(All objects of the selected library and type)

Choose **Next** to continue.


Generate Subprogram for XML Parser Callback

This dialog is used to generate a subprogram as implementation for the XML Parser Callback for the given group.

It uses the same entries as the above dialog for copycode, except that the Type field contains the entry Subprogram.

Show Generation Results

After the generation is complete, the generation results summary is displayed.



Choose **Finish** to end the generation process.

155 Natural Simple XML Parser

■ Parser Description and Example	450
■ Parser Restrictions	457

The following topics are covered:

Parser Description and Example

The Natural simple XML Parser enables you to parse XML documents with standard Natural programs. The parser sends an event, or runs an internal subroutine callback if the next part of the document is parsed. The inline subroutine "CALLBACK" is called with the name of the current element, text, comment within an xpath-like syntax. The parser engine is included as copy code "PARSER_X". If an error occurs during parsing, e.g. the document is not wellformed, the "PARSER_ERROR" inline subroutine is called and then the parser is canceled with "ESCAPE SUBROUTINE" (see also [Parser Restrictions](#)).

For extended error handling, it is possible to change the operand6 "Error Message Text" and operand7 "Error Number" to a value less than or equal to -9000. Then the "PARSER_ERROR" inline subroutine is called and the (sub)program is canceled with "ESCAPE SUBROUTINE". If other values are less than or equal to -8000, only the parser is canceled with "ESCAPE SUBROUTINE".

The major variables of the parser are defined at the Local Data Area "PARSER-X".

The parser copycode takes the following operands:

Operand	Format/Length	Description
1	A	XML file to be parsed
2	A	ex-XPATH to represent element structure
3	A1	Type of the XPATH content: ? Processing instruction D DOCTYPE ! Comment C CDATA section T Starting Tag @ Attribute / Close Tag
4	A	Parsed Data
5	L	Is TRUE if Parsed Data is empty
6	A	Error Message Text
7	I4	Error Number

Return value of the XPATH data:

ex-Xpath	XML Structure
?	<? ... ?>
!DOCTYPE	<!DOCTYPE ... >
!DOCTYPE[<!DOCTYPE .. [...]>
![CDATA[<![CDATA[...]]>
--	<!-- -->
!	<! .. >
doc	<doc>
doc	<doc><foo>text</foo></doc>
doc/foo	
doc/foo/\$	
doc/foo//	
doc//	
doc	<doc a1="a" />
doc/@a1	
doc//	
doc	<doc a1="a" a2="b">text</doc>
doc/@a1	
doc/@a2	
doc/\$	
doc//	
doc	<doc>
doc/\$	<foo>text</foo>
doc/foo	</doc>
doc/foo/\$	
doc/foo//	
doc/\$	
doc//	
doc	<doc><![CDATA[...]]></doc>
doc/![CDATA[
doc//	
doc	<doc><!-- ... --></doc>
doc!--	
doc//	

Program Example:

```
* -----  
* CLASS  NATURAL XML TOOLKIT - UTILITIES  
*  
*          PARSER  
*  
* DESCRIPTION      Parse given XML  
*  
*  
* AUTHOR          SAG   01.2006  
*  
* VERSION         6.2.  
*  
* (c) Copyright Software AG 2006. All rights reserved.  
*  
* -----  
*  
DEFINE DATA LOCAL  
1 XML_PARSER_INPUT           (A) DYNAMIC  
1 XML_PARSER_ERROR_TEXT     (A253)  
1 XML_PARSER_RESPONSE       (I4)  
LOCAL USING PARSER-X        /* parser internal data - do not change  
LOCAL  
1 XML_PARSER_XPATH          (A) DYNAMIC  
1 XML_PARSER_XPATH_TYPE     (A1)  
1 XML_PARSER_CONTENT         (A) DYNAMIC  
1 XML_PARSER_CONTENT_IS_EMPTY (L)  
*  
1 ANFANG                    (T)  
* OUT                       (A) DYNAMIC  
1 OUT                       (A126)  
*  
END-DEFINE  
*  
FORMAT (0) LS=128 PS=40  
*  
DEFINE WORK FILE 12 "E:\EMPLOYEE1.XML" TYPE "UNFORMATTED"  
READ WORK FILE 12 XML_PARSER_INPUT  
END-WORK  
CLOSE WORK FILE 12  
*  
*----- INCLUDE THE PARSER  
INCLUDE PARSER_X 'XML_PARSER_INPUT' /* XML file to be parsed  
  'XML_PARSER_XPATH'             /* XPATH to represent element...  
  'XML_PARSER_XPATH_TYPE'       /* Type of callback  
  'XML_PARSER_CONTENT'         /* Content of element found  
  'XML_PARSER_CONTENT_IS_EMPTY' /* Is TRUE if element is empty
```

```

'XML_PARSER_ERROR_TEXT'          /* error Message
'XML_PARSER_RESPONSE'           /* Error NR; 0 = OK
*/
/*
DEFINE SUBROUTINE CALLBACK
IF XML_PARSER_CONTENT_IS_EMPTY THEN
  IF XML_PARSER_XPATH_TYPE NE "T" AND XML_PARSER_XPATH_TYPE NE "/" THEN
    COMPRESS XML_PARSER_XPATH "(NULL)" INTO OUT WITH DELIMITER "="
  ELSE
    OUT := XML_PARSER_XPATH
  END-IF
ELSE
  COMPRESS XML_PARSER_XPATH XML_PARSER_CONTENT INTO OUT WITH DELIMITER "="
END-IF
WRITE OUT
END-SUBROUTINE
*/
DEFINE SUBROUTINE PARSER_ERROR
OUT := XML_PARSER_ERROR_TEXT
WRITE OUT
END-SUBROUTINE
END

```

With a given result document from Tamino for the Employee data, the result of this program looks like this:

```

<?xml version="1.0" encoding="ISO-8859-1" ?>
<Employee xmlns:ino="http://namespaces.softwareag.com/tamino/response2" ino:id="560"
Personnel-ID="20006900">
<Full-Name>
<First-Name>JOE</First-Name>
<Name>ATHERTON</Name>
</Full-Name>
<Mar-Stat>S</Mar-Stat>
<Sex>M</Sex>
<Birth>1941-02-21</Birth>
<Full-Address>
<Address-Line>11603 HUNTERS GREEN</Address-Line>
<Address-Line>SYRACUSE</Address-Line>
<Address-Line>NY</Address-Line>
<City>SYRACUSE</City>
<Zip>13201</Zip>
<Post-Code>13201</Post-Code>
<Country>USA</Country>
</Full-Address>
<Telephone>
<Phone>173-9859</Phone>
<Area-Code>315</Area-Code>
</Telephone>
<Dept>TECH10</Dept>

```

```
<Job-Title>ANALYST</Job-Title>
<Income>
<Curr-Code>USD</Curr-Code>
<Salary>43000</Salary>
</Income>
<Income>
<Curr-Code>USD</Curr-Code>
<Salary>39500</Salary>
</Income>
<Income>
<Curr-Code>USD</Curr-Code>
<Salary>36700</Salary>
</Income>
<Income>
<Curr-Code>USD</Curr-Code>
<Salary>34400</Salary>
</Income>
<Income>
<Curr-Code>USD</Curr-Code>
<Salary>32600</Salary>
</Income>
<Leave-Data>
<Leave-Due>19</Leave-Due>
<Leave-Taken>4</Leave-Taken>
</Leave-Data>
<Leave-Booked>
<Leave-Start>19980112</Leave-Start>
<Leave-End>19980112</Leave-End>
</Leave-Booked>
<Leave-Booked>
<Leave-Start>19980605</Leave-Start>
<Leave-End>19980605</Leave-End>
</Leave-Booked>
<Leave-Booked>
<Leave-Start>19980916</Leave-Start>
<Leave-End>19980916</Leave-End>
</Leave-Booked>
<Lang>ENG</Lang>
</Employee>
```



Note: There is no line break in the whole document.

The result of the above Natural program looks like this:

```
?=xml version="1.0" encoding="ISO-8859-1"
Employee
Employee/@xmlns:ino=http://namespaces.softwareag.com/tamino/response2
Employee/@ino:id=560
Employee/@Personnel-ID=20006900
Employee/Full-Name
Employee/Full-Name/First-Name
Employee/Full-Name/First-Name/$=JOE
Employee/Full-Name/First-Name// 
Employee/Full-Name/Name
Employee/Full-Name/Name/$=ATHERTON
Employee/Full-Name/Name// 
Employee/Full-Name// 
Employee/Mar-Stat
Employee/Mar-Stat/$=$
Employee/Mar-Stat// 
Employee/Sex
Employee/Sex/$=M
Employee/Sex// 
Employee/Birth
Employee/Birth/$=1941-02-21
Employee/Birth// 
Employee/Full-Address
Employee/Full-Address/Address-Line
Employee/Full-Address/Address-Line/$=11603 HUNTERS GREEN
Employee/Full-Address/Address-Line// 
Employee/Full-Address/Address-Line
Employee/Full-Address/Address-Line/$=SYRACUSE
Employee/Full-Address/Address-Line// 
Employee/Full-Address/Address-Line
Employee/Full-Address/Address-Line/$=NY
Employee/Full-Address/Address-Line// 
Employee/Full-Address/City
Employee/Full-Address/City/$=SYRACUSE
Employee/Full-Address/City// 
Employee/Full-Address/Zip
Employee/Full-Address/Zip/$=13201
Employee/Full-Address/Zip// 
Employee/Full-Address/Post-Code
Employee/Full-Address/Post-Code/$=13201
Employee/Full-Address/Post-Code// 
Employee/Full-Address/Country
Employee/Full-Address/Country/$=USA
Employee/Full-Address/Country// 
Employee/Full-Address// 
Employee/Telephone
Employee/Telephone/Phone
Employee/Telephone/Phone/$=173-9859
```

```
Employee/Telephone/Phone//  
Employee/Telephone/Area-Code  
Employee/Telephone/Area-Code/$=315  
Employee/Telephone/Area-Code//  
Employee/Telephone//  
Employee/Dept  
Employee/Dept/$=TECH10  
Employee/Dept//  
Employee/Job-Title  
Employee/Job-Title/$=ANALYST  
Employee/Job-Title//  
Employee/Income  
Employee/Income/Curr-Code  
Employee/Income/Curr-Code/$=USD  
Employee/Income/Curr-Code//  
Employee/Income/Salary  
Employee/Income/Salary/$=43000  
Employee/Income/Salary//  
Employee/Income//  
Employee/Income  
Employee/Income/Curr-Code  
Employee/Income/Curr-Code/$=USD  
Employee/Income/Curr-Code//  
Employee/Income/Salary  
Employee/Income/Salary/$=39500  
Employee/Income/Salary//  
Employee/Income//  
Employee/Income  
Employee/Income/Curr-Code  
Employee/Income/Curr-Code/$=USD  
Employee/Income/Curr-Code//  
Employee/Income/Salary  
Employee/Income/Salary/$=36700  
Employee/Income/Salary//  
Employee/Income//  
Employee/Income  
Employee/Income/Curr-Code  
Employee/Income/Curr-Code/$=USD  
Employee/Income/Curr-Code//  
Employee/Income/Salary  
Employee/Income/Salary/$=34400  
Employee/Income/Salary//  
Employee/Income//  
Employee/Income  
Employee/Income/Curr-Code  
Employee/Income/Curr-Code/$=USD  
Employee/Income/Curr-Code//  
Employee/Income/Salary  
Employee/Income/Salary/$=32600  
Employee/Income/Salary//  
Employee/Income//  
Employee/Leave-Data
```

```

Employee/Leave-Data/Leave-Due
Employee/Leave-Data/Leave-Due/$=19
Employee/Leave-Data/Leave-Due//
Employee/Leave-Data/Leave-Taken
Employee/Leave-Data/Leave-Taken/$=4
Employee/Leave-Data/Leave-Taken//
Employee/Leave-Data//
Employee/Leave-Booked
Employee/Leave-Booked/Leave-Start
Employee/Leave-Booked/Leave-Start/$=19980112
Employee/Leave-Booked/Leave-Start//
Employee/Leave-Booked/Leave-End
Employee/Leave-Booked/Leave-End/$=19980112
Employee/Leave-Booked/Leave-End//
Employee/Leave-Booked//
Employee/Leave-Booked
Employee/Leave-Booked/Leave-Start
Employee/Leave-Booked/Leave-Start/$=19980605
Employee/Leave-Booked/Leave-Start//
Employee/Leave-Booked/Leave-End
Employee/Leave-Booked/Leave-End/$=19980605
Employee/Leave-Booked/Leave-End//
Employee/Leave-Booked//
Employee/Leave-Booked
Employee/Leave-Booked/Leave-Start
Employee/Leave-Booked/Leave-Start/$=19980916
Employee/Leave-Booked/Leave-Start//
Employee/Leave-Booked/Leave-End
Employee/Leave-Booked/Leave-End/$=19980916
Employee/Leave-Booked/Leave-End//
Employee/Leave-Booked//
Employee/Lang
Employee/Lang/$=ENG
Employee/Lang//
Employee//

```

Parser Restrictions

The parser does not handle:

- Composition of a tag (incl. processing instruction). Only start-tag must be equal to end-tag (incl. processing instruction).

Example:

```
<.doc></.doc> <!-- invalid character in tag -->
<doc><? ?></doc> <!-- invalid whitespace -->
<doc>&#RE;</doc> <!-- invalid character in tag -->
```

■ Character or entity references

Example:

```
<doc>& no refc</doc> <!-- missing semicolon --> <doc a1=v1></doc>
<!-- string literal expected -->
```

■ Exact handling of CDATA-Sections

Example:

```
<doc><![CDATA [ stuff]]></doc> <!-- must be CDATA[ -->
```

■ Content of an entity/processing instruction

Example:

```
<doc>]]></doc> <!-- ]] not allowed -->
```

- Number of tags/attributes
- Headerinformation
- Unicode-charset (supports ISO-8859-1)

156 Examples

■ Serialize Copycode	460
■ Serialize Subroutine	462
■ Generated Natural Data Area	470
■ Natural DTD Parser	472
■ Generated Type Definition	473
■ Parser CALLBACK Copycode	474

The following examples are included:

Serialize Copycode

Using the XML Toolkit, a copycode can be generated that can be used to convert a Natural group structure into an XML document.

The callback copycode takes the following operands:

Operand	Format/Length	Description	from PARSER-X
1	A	ex-XPATH to represent element structure	operand2
2	A1	Type of the XPATH content: ? Processing instruction D DOCTYPE ! Comment C CDATA section T Starting Tag @ Attribute / Close Tag	operand3
3	A	Parsed Data	operand4
4	L	Is TRUE if Parsed Data is empty	operand5
5	I4	Counter Variable 1st Dimension	
6	I4	Counter Variable 2nd Dimension	
7	I4	Counter Variable 3rd Dimension	

Copycode Example EMPL-C:

```
*----- * Parameter
Definition * * &1& 'XML' /* XML Document * &2& '#CX' /* Counter
Variable 1st Dimension * &3& '#CY' /* Counter Variable 2nd Dimension *
&4& '#CZ' /* Counter Variable 3rd Dimension *

* DTD E-\SAG\nat\NATAPPS\FUSER\XMLTK\RES\empl.dtd COMPRESS &1& '<EMPLOYEE'
' PERSONNEL-ID=""EMPLOYEE.PERSONNEL-ID "' ' '>' INTO &1& LEAVING NO
/* now the children COMPRESS &1& '<FULL-NAME' ' '>' INTO &1&
LEAVING NO /* now the children COMPRESS &1& '<FIRST-NAME' ' '>' EMPLOYEE.FIRST-NAME
'</FIRST-NAME>' INTO &1& LEAVING NO COMPRESS &1& '<NAME'
'>' EMPLOYEE.NAME '</NAME>' INTO &1& LEAVING NO /* COMPRESS &1&
'</FULL-NAME>' INTO &1& LEAVING NO COMPRESS &1& '<FULL-ADDRESS'
```

```
'>' INTO &1& LEAVING NO /* now the children FOR &2& = 1 TO
EMPLOYEE.C@ADDRESS-LINE COMPRESS &1& '<ADDRESS-LINE' '>' EMPLOYEE.ADDRESS-LINE(&2&)
'</ADDRESS-LINE>' INTO &1& LEAVING NO END-FOR COMPRESS &1&
'<CITY' '>' EMPLOYEE.CITY '</CITY>' INTO &1& LEAVING NO COMPRESS
&1& '<ZIP' '>' EMPLOYEE.ZIP '</ZIP>' INTO &1& LEAVING
NO COMPRESS &1& '<COUNTRY' '>' EMPLOYEE.COUNTRY '</COUNTRY>'
INTO &1& LEAVING NO /* COMPRESS &1& '</FULL-ADDRESS>' INTO
&1& LEAVING NO COMPRESS &1& '<TELEPHONE' '>' INTO &1&
LEAVING NO /* now the children COMPRESS &1& '<PHONE' '>' EMPLOYEE.PHONE
'</PHONE>' INTO &1& LEAVING NO COMPRESS &1& '<AREA-CODE'
'>' EMPLOYEE.AREA-CODE '</AREA-CODE>' INTO &1& LEAVING NO /* COMPRESS
&1& '</TELEPHONE>' INTO &1& LEAVING NO COMPRESS
&1& '<JOB-TITLE' '>' EMPLOYEE.JOB-TITLE '</JOB-TITLE>' INTO
&1& LEAVING NO FOR &2& = 1 TO EMPLOYEE.C@INCOME COMPRESS &1&
'<INCOME' '>' INTO &1& LEAVING NO /* now the children COMPRESS &1&
'<SALARY' '>' EMPLOYEE.SALARY(&2&) '</SALARY>' INTO &1&
LEAVING NO FOR &3& = 1 TO EMPLOYEE.C@BONUS(&2&) COMPRESS &1&
'<BONUS' '>' EMPLOYEE.BONUS(&2&,&3&) '</BONUS>' INTO
&1& LEAVING NO END-FOR /* COMPRESS &1& '</INCOME>' INTO
&1& LEAVING NO END-FOR /* COMPRESS &1& '</EMPLOYEE>' INTO
&1& LEAVING NO
```

XML Schema Example:

```
<?xml
version="1.0" encoding="ISO-8859-1"?> <xsschema
xmlns:xss="http://www.w3.org/2001/XMLSchema">
<xselement name="EMPLOYEE"> <xsccomplexType> <xsssequence>
<xselement ref="FULL-NAME"/> <xselement ref="FULL-ADDRESS"/>
<xselement ref="TELEPHONE"/> <xselement ref="JOB-TITLE"/>
<xselement ref="INCOME" minOccurs="0" maxOccurs="6"/>
</xsssequence> <xselement name="PERSONNEL-ID" use="optional">
<xssimpleType> <xselement base="xs:string"/> </xssimpleType>
</xselement> </xsccomplexType> </xselement> <xselement
name="FULL-NAME"> <xsccomplexType> <xsssequence> <xselement
ref="FIRST-NAME"/> <xselement ref="NAME"/> </xsssequence>
</xsccomplexType> </xselement> <xselement name="FIRST-NAME">
<xssimpleType> <xselement base="xs:string"> <xssmaxLength
value="20"/> </xselement> </xssimpleType> </xselement>
<xselement name="NAME"> <xssimpleType> <xselement
base="xs:string"> <xssmaxLength value="20"/> </xselement>
</xssimpleType> </xselement> <xselement name="FULL-ADDRESS">
<xsccomplexType> <xsssequence> <xselement ref="ADDRESS-LINE"
minOccurs="0" maxOccurs="6"/> <xselement ref="CITY"/>
<xselement ref="ZIP"/> <xselement ref="COUNTRY"/>
</xsssequence> </xsccomplexType> </xselement> <xselement
name="ADDRESS-LINE"> <xssimpleType> <xselement
base="xs:string"> <xssmaxLength value="20"/> </xselement>
</xssimpleType> </xselement> <xselement name="CITY">
<xssimpleType> <xselement
base="xs:string"> <xssmaxLength value="20"/> </xselement>
</xssimpleType> </xselement> </xselement>
```

Examples

```
name="ZIP"> <xs:simpleType> <xs:restriction base="xs:string">
<xsmaxLength value="20"/> </xs:restriction> </xs:simpleType>
</xs:element> <xs:element name="COUNTRY"> <xs:simpleType>
<xs:restriction base="xs:string"> <xsmaxLength value="3"/>
</xs:restriction> </xs:simpleType> </xs:element> <xs:element
name="TELEPHONE"> <xs:complexType> <xs:sequence> <xs:element
ref="AREA-CODE"/> <xs:element ref="PHONE"/> </xs:sequence>
</xs:complexType> </xs:element> <xs:element name="AREA-CODE">
<xs:simpleType> <xs:restriction base="xs:string"> <xsmaxLength
value="6"/> </xs:restriction> </xs:simpleType> </xs:element>
<xs:element name="PHONE"> <xs:simpleType> <xs:restriction
base="xs:string"> <xsmaxLength value="15"/> </xs:restriction>
</xs:simpleType> </xs:element> <xs:element name="JOB-TITLE">
<xs:simpleType> <xs:restriction base="xs:string"> <xsmaxLength
value="25"/> </xs:restriction> </xs:simpleType> </xs:element>
<xs:element name="INCOME"> <xs:complexType> <xs:sequence>
<xs:element ref="SALARY"/> <xs:element ref="BONUS"
minOccurs="0" maxOccurs="4"/> </xs:sequence> </xs:complexType>
</xs:element> <xs:element name="SALARY"> <xs:simpleType>
<xs:restriction base="xs:string"> <xsmaxLength value="9"/>
</xs:restriction> </xs:simpleType> </xs:element> <xs:element
name="BONUS"> <xs:simpleType> <xs:restriction base="xs:string">
<xsmaxLength value="9"/> </xs:restriction> </xs:simpleType>
</xs:element> </xs:schema>
```

Natural PDA EMPL Used:

```
DEFINE DATA PARAMETER 1 EMPLOYEE 2 ATTRIBUTES_OF_EMPLOYEE
3 PERSONNEL-ID(A8) * 2 FULL-NAME 3 FIRST-NAME(A20) 3 NAME(A20) * 2 FULL-ADDRESS
3 C@ADDRESS-LINE(I4) 3 ADDRESS-LINE(A20/1:6) 3 CITY(A20) 3 ZIP(A20) 3 COUNTRY(A3)
* 2 TELEPHONE 3 AREA-CODE(A6) 3 PHONE(A15) * 2 JOB-TITLE(A25) * 2 C@INCOME(I4)
2 INCOME(1:6) 3 SALARY(A9) 3 C@BONUS(I4) 3 BONUS(A9/1:4) END-DEFINE
```

Serialize Subroutine

Using the XML Toolkit, a subroutine can be generated that can be used to convert a Natural group structure into an XML Schema.

Subroutine Example EMPLP:

```

* -----
* Generated from NATURAL XML TOOLKIT
*
*      'EMPLP'
*
* DESCRIPTION
*             XML Parser implementation
*             using PARSE XML statement for
*             datastructure 'EMPL'
*
* -----
*
* DEFINE DATA PARAMETER
1 #XML_INPUT          (A) DYNAMIC BY VALUE
PARAMETER USING EMPL
*
LOCAL
1 #XML_PATH           (A) DYNAMIC
1 #XML_VALUE          (A) DYNAMIC
*
LOCAL
1 #CX                 (I4)
1 #CY                 (I4)
1 #CZ                 (I4)
END-DEFINE
*
* ----- INCLUDE THE PARSER
PARSE XML #XML_INPUT INTO PATH #XML_PATH VALUE #XML_VALUE
*
* DTD SYSEXXT EMPL
DECIDE ON FIRST #XML_PATH
    VALUE 'EMPLOYEE'
        RESET EMPLOYEE
    VALUE 'EMPLOYEE/@PERSONNEL-ID'
        /* #IMPLIED
        EMPLOYEE.PERSONNEL-ID := #XML_VALUE
    VALUE 'EMPLOYEE/FULL-NAME'
        IGNORE
    VALUE 'EMPLOYEE/FULL-NAME/FIRST-NAME'
        IGNORE
    VALUE 'EMPLOYEE/FULL-NAME/FIRST-NAME/$'
        EMPLOYEE.FIRST-NAME := #XML_VALUE
    VALUE 'EMPLOYEE/FULL-NAME/NAME'
        IGNORE
    VALUE 'EMPLOYEE/FULL-NAME/NAME/$'
        EMPLOYEE.NAME := #XML_VALUE
    VALUE 'EMPLOYEE/FULL-ADDRESS'
        IGNORE

```

Examples

```
VALUE 'EMPLOYEE/FULL-ADDRESS/ADDRESS-LINE'
/* optional multiple
ADD 1 TO EMPLOYEE.C@ADDRESS-LINE
EXPAND ARRAY EMPLOYEE.ADDRESS-LINE TO
(1:EMPLOYEE.C@ADDRESS-LINE)
VALUE 'EMPLOYEE/FULL-ADDRESS/ADDRESS-LINE/$'
#CX := EMPLOYEE.C@ADDRESS-LINE
EMPLOYEE.ADDRESS-LINE(#CX) := #XML_VALUE
VALUE 'EMPLOYEE/FULL-ADDRESS/CITY'
IGNORE
VALUE 'EMPLOYEE/FULL-ADDRESS/CITY/$'
EMPLOYEE.CITY := #XML_VALUE
VALUE 'EMPLOYEE/FULL-ADDRESS/ZIP'
IGNORE
VALUE 'EMPLOYEE/FULL-ADDRESS/ZIP/$'
EMPLOYEE.ZIP := #XML_VALUE
VALUE 'EMPLOYEE/FULL-ADDRESS/COUNTRY'
IGNORE
VALUE 'EMPLOYEE/FULL-ADDRESS/COUNTRY/$'
EMPLOYEE.COUNTRY := #XML_VALUE
VALUE 'EMPLOYEE/TELEPHONE'
IGNORE
VALUE 'EMPLOYEE/TELEPHONE/AREA-CODE'
IGNORE
VALUE 'EMPLOYEE/TELEPHONE/AREA-CODE/$'
EMPLOYEE.AREA-CODE := #XML_VALUE
VALUE 'EMPLOYEE/TELEPHONE/PHONE'
IGNORE
VALUE 'EMPLOYEE/TELEPHONE/PHONE/$'
EMPLOYEE.PHONE := #XML_VALUE
VALUE 'EMPLOYEE/JOB-TITLE'
IGNORE
VALUE 'EMPLOYEE/JOB-TITLE/$'
EMPLOYEE.JOB-TITLE := #XML_VALUE
VALUE 'EMPLOYEE/INCOME'
/* optional multiple
ADD 1 TO EMPLOYEE.C@INCOME
EXPAND ARRAY EMPLOYEE.INCOME TO
(1:EMPLOYEE.C@INCOME)
VALUE 'EMPLOYEE/INCOME/SALARY'
IGNORE
VALUE 'EMPLOYEE/INCOME/SALARY/$'
#CX := EMPLOYEE.C@INCOME
EMPLOYEE.SALARY(#CX) := #XML_VALUE
VALUE 'EMPLOYEE/INCOME/BONUS'
/* optional multiple
#CX := EMPLOYEE.C@INCOME
ADD 1 TO EMPLOYEE.C@BONUS(#CX)
EXPAND ARRAY EMPLOYEE.BONUS TO
(*:*,1:EMPLOYEE.C@BONUS(#CX))
VALUE 'EMPLOYEE/INCOME/BONUS/$'
#CX := EMPLOYEE.C@INCOME
```

```

#CY := EMPLOYEE.C@BONUS(#CX)
EMPLOYEE.BONUS(#CX,#CY) := #XML_VALUE
NONE
IGNORE
END-DECIDE
*
END-PARSE
*
END

```

Subroutine Example EMPL2S:

```

* -----
* Generated from NATURAL XML TOOLKIT
*
*      'EMPL2S'
*
* DESCRIPTION
*             XML serialize implementation for
*             'EMPL' datastructure
*
* -----
*
DEFINE DATA PARAMETER
1 #XML_SERIALIZE_OUTPUT (A) DYNAMIC
PARAMETER USING EMPL
LOCAL
1 #CX          (I4)
1 #CY          (I4)
1 #CZ          (I4)
END-DEFINE
*
#XML_SERIALIZE_OUTPUT := '<?xml version="1.0" encoding="ISO-8859-1"?>'
*
* DTD SYSEXXT EMPL
COMPRESS #XML_SERIALIZE_OUTPUT '<EMPLOYEE'
  ' PERSONNEL-ID=""EMPLOYEE.PERSONNEL-ID ""'
  '>' INTO #XML_SERIALIZE_OUTPUT LEAVING NO
/* now the children
COMPRESS #XML_SERIALIZE_OUTPUT '<FULL-NAME'
  '>' INTO #XML_SERIALIZE_OUTPUT LEAVING NO
/* now the children
COMPRESS #XML_SERIALIZE_OUTPUT '<FIRST-NAME'
  '>'
  EMPLOYEE.FIRST-NAME
  '</FIRST-NAME>' INTO #XML_SERIALIZE_OUTPUT LEAVING NO
COMPRESS #XML_SERIALIZE_OUTPUT '<NAME'
  '>'
  EMPLOYEE.NAME
  '</NAME>' INTO #XML_SERIALIZE_OUTPUT LEAVING NO
/*

```

Examples

```
COMPRESS #XML_SERIALIZE_OUTPUT '</FULL-NAME>'  
INTO #XML_SERIALIZE_OUTPUT LEAVING NO  
COMPRESS #XML_SERIALIZE_OUTPUT '<FULL-ADDRESS'  
'>' INTO #XML_SERIALIZE_OUTPUT LEAVING NO  
/* now the children  
FOR #CX = 1 TO EMPLOYEE.C@ADDRESS-LINE  
    COMPRESS #XML_SERIALIZE_OUTPUT '<ADDRESS-LINE'  
'>'  
    EMPLOYEE.ADDRESS-LINE(#CX)  
    '</ADDRESS-LINE>' INTO #XML_SERIALIZE_OUTPUT LEAVING NO  
END-FOR  
COMPRESS #XML_SERIALIZE_OUTPUT '<CITY'  
'>'  
EMPLOYEE.CITY  
'</CITY>' INTO #XML_SERIALIZE_OUTPUT LEAVING NO  
COMPRESS #XML_SERIALIZE_OUTPUT '<ZIP'  
'>'  
EMPLOYEE.ZIP  
'</ZIP>' INTO #XML_SERIALIZE_OUTPUT LEAVING NO  
COMPRESS #XML_SERIALIZE_OUTPUT '<COUNTRY'  
'>'  
EMPLOYEE.COUNTRY  
'</COUNTRY>' INTO #XML_SERIALIZE_OUTPUT LEAVING NO  
/*  
COMPRESS #XML_SERIALIZE_OUTPUT '</FULL-ADDRESS>'  
INTO #XML_SERIALIZE_OUTPUT LEAVING NO  
COMPRESS #XML_SERIALIZE_OUTPUT '<TELEPHONE'  
'>' INTO #XML_SERIALIZE_OUTPUT LEAVING NO  
/* now the children  
COMPRESS #XML_SERIALIZE_OUTPUT '<AREA-CODE'  
'>'  
EMPLOYEE.AREA-CODE  
'</AREA-CODE>' INTO #XML_SERIALIZE_OUTPUT LEAVING NO  
COMPRESS #XML_SERIALIZE_OUTPUT '<PHONE'  
'>'  
EMPLOYEE.PHONE  
'</PHONE>' INTO #XML_SERIALIZE_OUTPUT LEAVING NO  
/*  
COMPRESS #XML_SERIALIZE_OUTPUT '</TELEPHONE>'  
INTO #XML_SERIALIZE_OUTPUT LEAVING NO  
COMPRESS #XML_SERIALIZE_OUTPUT '<JOB-TITLE'  
'>'  
EMPLOYEE.JOB-TITLE  
'</JOB-TITLE>' INTO #XML_SERIALIZE_OUTPUT LEAVING NO  
FOR #CX = 1 TO EMPLOYEE.C@INCOME  
    COMPRESS #XML_SERIALIZE_OUTPUT '<INCOME'  
'>' INTO #XML_SERIALIZE_OUTPUT LEAVING NO  
/* now the children  
COMPRESS #XML_SERIALIZE_OUTPUT '<SALARY'  
'>'  
EMPLOYEE.SALARY(#CX)  
'</SALARY>' INTO #XML_SERIALIZE_OUTPUT LEAVING NO
```

```

FOR #CY = 1 TO EMPLOYEE.C@BONUS(#CX)
  COMPRESS #XML_SERIALIZE_OUTPUT '<BONUS'
    '>'
    EMPLOYEE.BONUS(#CX,#CY)
    '</BONUS>' INTO #XML_SERIALIZE_OUTPUT LEAVING NO
  END-FOR
/*
  COMPRESS #XML_SERIALIZE_OUTPUT '</INCOME>'
  INTO #XML_SERIALIZE_OUTPUT LEAVING NO
END-FOR
/*
COMPRESS #XML_SERIALIZE_OUTPUT '</EMPLOYEE>'
INTO #XML_SERIALIZE_OUTPUT LEAVING NO
END

```

Program Example:

```

* -----
* CLASS  NATURAL XML TOOLKIT
*
*
* DESCRIPTION
*           Serialize a given Data structure.
*
*
* AUTHOR      SAG   01.2006
*
* VERSION     6.2.
*
* (c) Copyright Software AG 2006. All rights reserved.
*
* -----
*
DEFINE DATA
LOCAL USING EMPL /* add generated data structure
LOCAL
1 XML          (A) DYNAMIC
*
1 OUT          (A72)
1 II           (I4)
*
1 OUTDYN (A) DYNAMIC
1 OBJLEN (I4)
1 OBJEND (I4)
1 OBJSTART (I4)
1 OBJLINE (I4)
*
1 #CX          (I4)
1 #CY          (I4)
1 #CZ          (I4)
END-DEFINE

```

Examples

```
*  
EMPLOYEE.PERSONNEL-ID      := 4711  
*  
EMPLOYEE.FIRST-NAME        := "ADKINSON"  
EMPLOYEE.NAME               := "MARTHA"  
*  
EMPLOYEE.C@ADDRESS-LINE    := 2  
EMPLOYEE.ADDRESS-LINE(1)   := "8603 GARLAND COURT"  
EMPLOYEE.ADDRESS-LINE(2)   := "FRAMINGHAM"  
EMPLOYEE.ADDRESS-LINE(2)   := "MA"  
EMPLOYEE.CITY               := "FRAMINGHAM"  
EMPLOYEE.ZIP                := "17010"  
EMPLOYEE.COUNTRY            := "USA"  
*  
EMPLOYEE.AREA-CODE         := "617"  
EMPLOYEE.PHONE              := "210-4703"  
*  
EMPLOYEE.JOB-TITLE          := "MANAGER"  
EMPLOYEE.C@INCOME           := 2  
EMPLOYEE.SALARY(1)          := 47000  
EMPLOYEE.C@BONUS(1)          := 2  
EMPLOYEE.BONUS(1,1)          := 10500  
EMPLOYEE.BONUS(1,2)          := 7875  
*  
EMPLOYEE.SALARY(2)          := 47000  
EMPLOYEE.C@BONUS(2)          := 1  
EMPLOYEE.BONUS(2,1)          := 35700  
*  
INCLUDE EMPL-C "XML" "#CX" "#CY" "#CZ" /* add generated Serialize  
*  
FOR II = 1 TO *LENGTH(XML) STEP 72  
  OUT := SUBSTR(XML,II)  
  WRITE OUT  
END-FOR  
*  
NEWPAGE  
*  
/* WRITE COMPLETE (A) DYNAMIC VARIABLE IF POSSIBLE USE CR AND IGNORE LF  
OBJSTART := 1  
*  
EXAMINE xml FOR "><" REPLACE WITH ">" - H'0A' - "<"  
EXAMINE xml FOR H'0A' GIVING POSITION OBJEND  
*  
REPEAT WHILE OBJEND NE 0  
/*  
  IF OBJSTART GT 0 THEN  
    ADD OBJSTART TO OBJEND  
  END-IF  
/*  
  OBJLEN := OBJEND - OBJSTART -1  
/*  
  IF OBJLEN > 0 THEN
```

```

OUTDYN := SUBSTRING(xml, OBJSTART, OBJLEN)
/*
FOR OBJLINE = 1 TO *LENGTH(OUTDYN) STEP 72
    OUT := SUBSTR (OUTDYN,OBJLINE)
    WRITE OUT
END-FOR
ELSE
    WRITE " "
END-IF
/*
OBJSTART := OBJEND
IF OBJSTART GT *LENGTH(xml)
    ESCAPE BOTTOM
ENDIF
/*
EXAMINE SUBSTRING(xml,OBJSTART) FOR H'OA' GIVING POSITION OBJEND
END-REPEAT
*
END

```

Natural PDA EMPL Used:

```

DEFINE DATA PARAMETER
1 EMPLOYEE
  2 ATTRIBUTES_OF_EMPLOYEE
    3 PERSONNEL-ID(A8)
*
  2 FULL-NAME
    3 FIRST-NAME(A20)
    3 NAME(A20)
*
  2 FULL-ADDRESS
    3 C@ADDRESS-LINE(I4)
    3 ADDRESS-LINE(A20/1:*)
    3 CITY(A20)
    3 ZIP(A20)
    3 COUNTRY(A3)
*
  2 TELEPHONE
    3 AREA-CODE(A6)
    3 PHONE(A15)
*
  2 JOB-TITLE(A25)
*
  2 C@INCOME(I4)
  2 INCOME(1:*)
    3 SALARY(A9)
    3 C@BONUS(I4)
    3 BONUS(A9/1:*)
END-DEFINE

```

Generated Natural Data Area

Using the XML Toolkit, a Natural Data Area, or more precisely a Local Data Area, Parameter Data Area or Global Data Area, can be generated that represents a given Document Type Definition.

Generation Rules:

- Each Empty Element without Attributes (`<!ELEMENT br EMPTY>`) is generated as a Natural variable of Type B1. This is necessary, because empty Natural groups are not allowed.
- Each Empty Element with Attributes (`<!ELEMENT br EMPTY><!ATTLIST br width CDATA #IMPLIED>`) is generated as a Natural group.
- Each Element with content (`<!ELEMENT b (#PCDATA)>`) is generated as a Natural variable of type A253.
- Each Sequence of Elements (`<!ELEMENT spec (front, body*, back?)>`) or Choice of Elements (`<!ELEMENT div1 (p | list | note)>`) is generated as a Natural group.
- Each clasped Sequence or Choice (`<!ELEMENT address ((street, housenumber), (zip, city))>`) is generated as a special group with the name prefix "`##PSEUDO`". This gives the possibility to represent the context or possible multiplicities.
- Each Attribute (`<!ATTLIST br width CDATA #IMPLIED>`) of an Element is generated as variable of Type A253 belonging to a group with the name prefix "`ATTRIBUTES_OF_`" followed by the name of the element.
- Multiple Elements are always generated as arrays of Dimension 1:v. The upper bound of the generated array has to be changed manually.
- If an Element is defined multiple (`<!ELEMENT spec (front, body*)>`), an additional counter field `C@BODY`, is generated to specify the number of available elements.
- All names used inside the DTD are converted into upper case, because Natural names are not case sensitive. Duplicate names inside a generated group will be extended with an suffix to make the names unique.
- Special Characters not valid for Natural names are converted into valid Natural names. For the conversion settings, see the option dialog of the XML Toolkit.

Restrictions:

- Elements with Mixed content data (`<!ELEMENT p (#PCDATA | a | ul | b | i | em)*>`) are not supported.
- DTDs that result in Natural data structures can not be used within Natural, because Natural only supports data structures with a maximum of three dimensions.

Example DTD:

```
<!ELEMENT EMPLOYEE (FULL-NAME , FULL-ADDRESS , TELEPHONE ,JOB-TITLE, INCOME* )>
<!ATTLIST EMPLOYEE PERSONNEL-ID CDATA #REQUIRED >

<!ELEMENT FULL-NAME (FIRST-NAME , NAME )>
<!ELEMENT FIRST-NAME (#PCDATA )>
<!ELEMENT NAME (#PCDATA )>

<!ELEMENT FULL-ADDRESS (ADDRESS-LINE* , CITY , ZIP , COUNTRY )>
<!ELEMENT ADDRESS-LINE (#PCDATA )>
<!ELEMENT CITY (#PCDATA )>
<!ELEMENT ZIP (#PCDATA )>
<!ELEMENT COUNTRY (#PCDATA )>

<!ELEMENT TELEPHONE (PHONE , AREA-CODE )>
<!ELEMENT PHONE (#PCDATA )>
<!ELEMENT AREA-CODE (#PCDATA )>

<!ELEMENT JOB-TITLE (#PCDATA )>

<!ELEMENT INCOME (SALARY , BONUS* )>
<!ELEMENT SALARY (#PCDATA )>
<!ELEMENT BONUS (#PCDATA )>
```

Generated Natural Data Area (*italic* written parts of the DTD, but necessary for Natural):

```
DEFINE DATA PARAMETER
1 EMPLOYEE
  2 ATTRIBUTES_OF_EMPLOYEE
    3 PERSONNEL-ID(A253)
*
  2 FULL-NAME
    3 FIRST-NAME(A253)
    3 NAME(A253)
*
  2 FULL-ADDRESS
    3 C@ADDRESS-LINE(I4)
    3 ADDRESS-LINE(A253/1:v)
    3 CITY(A253)
    3 ZIP(A253)
    3 COUNTRY(A253)
*
  2 TELEPHONE
    3 AREA-CODE(A253)
    3 PHONE(A253)
*
  2 JOB-TITLE(A253)
*
```

Examples

```
2 C@INCOME(I4)
2 INCOME(1:v)
3 SALARY(A253)
3 C@BONUS(I4)
3 BONUS(A253/1:v)
END-DEFINE
```

Natural DTD Parser

Translation Rules:

Natural	Document Type Definition
1 G1 2 E1 (A [*])	<!ELEMENT G1 (E1)> <!ELEMENT E1 (#PCDATA)>
1 G1 2 E1 (A [*]) 2 E2 (A [*]) 2 E3 (A [*])	<!ELEMENT G1 (E1, E2, E3)> <!ELEMENT E1 (#PCDATA)> <!ELEMENT E2 (#PCDATA)> <!ELEMENT E3 (#PCDATA)>
1 C@E1_MAX (I4) CONST <10> 1 G1 2 C@E1 (I4) 2 E1 (A [*] /1:C@E1_MAX)	<!ELEMENT G1 (E1*)> <!ELEMENT E1 (#PCDATA)>
1 C@E1_MAX (I4) CONST <10> 1 G1 2 C@E1 (I4) 2 E1 (A [*] /1:C@E1_MAX)	<!ELEMENT G1 (E1+)> <!ELEMENT E1 (#PCDATA)>
1 G1 2 E1 (A [*])	<!ELEMENT G1 (E1?)> <!ELEMENT E1 (#PCDATA)>
1 G1 2 E1 (A [*]) 2 E2 (A [*]) 2 E3 (A [*])	<!ELEMENT G1 (E1 E2 E3)> <!ELEMENT E1 (#PCDATA)> <!ELEMENT E2 (#PCDATA)> <!ELEMENT E3 (#PCDATA)>
1 G1 2 E1 (A [*]) 2 E2 (A [*]) 2 G2 2 E1_2 (A [*]) 2 E3 (A [*])	<!ELEMENT G1 (E1, E2, G2)> <!ELEMENT E1 (#PCDATA)> <!ELEMENT E2 (#PCDATA)> <!ELEMENT G2 (E1, E3)> <!ELEMENT E3 (#PCDATA)>
1 #G1 2 #E1 (A [*])	<!ELEMENT G1 (E1)> <!ELEMENT E1 (#PCDATA)>
2 E1 (A [*]) 3 ATTRIBUTES_OF_E1 4 A1 (A [*]) CONST <'schema'>	<!ELEMENT E1 (#PCDATA)> <!ATTLIST E1 A1 #FIXED "schema" A2 NMTOKEN #IMPLIED

Natural	Document Type Definition
4 A2 (A€!)	A3 ID #REQUIRED>
4 A3 (A€!)	

Generated Type Definition

Using the XML Toolkit, a Natural Data Area, or more precisely a Local Data Area, Parameter Data Area or Global Data Area, can be used to generate a Document Type Definition.

Generation Rules:

- A Natural variable will result in an element with content.
- A Natural group will result in a sequence of elements.
- Multiple variables or groups will be generated with multiplicity "zero or more".
- Special characters not valid for XML names are converted into valid names. For the conversion settings, see the [options dialog](#) of the XML Toolkit.

Example Natural Data Area:

```

DEFINE DATA LOCAL
1 NAT$EMPLOYEE
  2 ATTRIBUTES_OF_NAT$EMPLOYEE
    3 PERSONNEL/ID(A8)
  2 C@MAN@WORK(I4)
  2 MAN@WORK
    3 JOB(A10)
  2 A$TEST$MAKL(I4)
  2 AS/FA/SD(P7.5)
  2 #ASDFAS(F4)
  2 ASF#AS(N9)
  2 A-SF-D(A) Dynamic
  2 INC@OME(1:6)
    3 C@BONUS(I4)
    3 BONUS(A9/1:4)
END-DEFINE

```

Generated DTD:

```
<!-- DTD XMLTOOLS BEISP -->
<!ELEMENT NAT$EMPLOYEE ( MAN@WORK , AdollarTEST$MAKL ,
    AS$FAS$SD , hashASDFAS , ASFhashAS , A-SF-D , INCatOME* ) >
<!ATTLIST NAT$EMPLOYEE PERSONNEL$ID CDATA #IMPLIED >
<!ELEMENT MAN@WORK ( JOB ) >
<!ELEMENT JOB (#PCDATA) >
<!ELEMENT AdollarTEST$MAKL (#PCDATA) >
<!ELEMENT AS$FAS$SD (#PCDATA) >
<!ELEMENT hashASDFAS (#PCDATA) >
<!ELEMENT ASFhashAS (#PCDATA) >
<!ELEMENT A-SF-D (#PCDATA) >
<!ELEMENT INCatOME ( BONUS* ) >
<!ELEMENT BONUS (#PCDATA) >
```

Parser CALLBACK Copycode

Using the XML Toolkit, a copycode can be generated that can be used with the Natural Simple XML Parser.

The callback copycode takes the following operands:

Operand	Format/Length	Description	from PARSER-X
1	A	ex-XPATH to represent element structure	operand2
2	A1	Type of the XPATH content: ? Processing instruction D DOCTYPE ! Comment C CDATA section T Starting Tag @ Attribute / Close Tag	operand3
3	A	Content of found element	operand4
4	L	Is TRUE if Parsed Data is empty	operand5
5	I4	Counter Variable 1st Dimension	
6	I4	Counter Variable 2nd Dimension	
7	I4	Counter Variable 3rd Dimension	

Copycode Example EMPL-P:

```

* -----*
* Parameter Definition
*
* &1& 'XML_PARSER_XPATH'          /* XPATH to represent element...
* &2& 'XML_PARSER_XPATH_TYPE'    /* Type of the XPATH:
*                                ? Processing instruction
*                                D DOCTYPE
*                                ! Comment
*                                C CDATA section
*                                T Starting Tag
*                                @ Attribute
*                                / Close Tag
*                                $ Parsed Data
*
* &3& 'XML_PARSER_CONTENT'       /* Content of found element
* &4& 'XML_PARSER_CONTENT_IS_EMPTY' /* Is TRUE if Content is empty
* &5& '#CX'                      /* Counter Variable 1st Dimension
* &6& '#CY'                      /* Counter Variable 2nd Dimension
* &7& '#CZ'                      /* Counter Variable 3rd Dimension
* -----*
*
DECIDE ON FIRST &1&
VALUE 'EMPLOYEE'
RESET EMPLOYEE
VALUE 'EMPLOYEE/@PERSONNEL-ID'
/* #REQUIRED
EMPLOYEE.PERSONNEL-ID := &3&
VALUE 'EMPLOYEE/FULL-NAME'
IGNORE
VALUE 'EMPLOYEE/FULL-NAME/FIRST-NAME'
IGNORE
VALUE 'EMPLOYEE/FULL-NAME/FIRST-NAME/$'
EMPLOYEE.FIRST-NAME := &3&
VALUE 'EMPLOYEE/FULL-NAME/NAME'
IGNORE
VALUE 'EMPLOYEE/FULL-NAME/NAME/$'
EMPLOYEE.NAME := &3&
VALUE 'EMPLOYEE/FULL-ADDRESS'
IGNORE
VALUE 'EMPLOYEE/FULL-ADDRESS/ADDRESS-LINE'
/* OPTIONAL MULTIPLE LIST: 18 PARENT: FULL-ADDRESS
ADD 1 TO EMPLOYEE.C@ADDRESS-LINE
VALUE 'EMPLOYEE/FULL-ADDRESS/ADDRESS-LINE/$'
&5& := EMPLOYEE.C@ADDRESS-LINE
EMPLOYEE.ADDRESS-LINE(&5&) := &3&
VALUE 'EMPLOYEE/FULL-ADDRESS/CITY'
IGNORE
VALUE 'EMPLOYEE/FULL-ADDRESS/CITY/$'
EMPLOYEE.CITY := &3&

```

Examples

```
VALUE 'EMPLOYEE/FULL-ADDRESS/ZIP'
    IGNORE
VALUE 'EMPLOYEE/FULL-ADDRESS/ZIP/$'
    EMPLOYEE.ZIP := &3&
VALUE 'EMPLOYEE/FULL-ADDRESS/COUNTRY'
    IGNORE
VALUE 'EMPLOYEE/FULL-ADDRESS/COUNTRY/$'
    EMPLOYEE.COUNTRY := &3&
VALUE 'EMPLOYEE/TELEPHONE'
    IGNORE
VALUE 'EMPLOYEE/TELEPHONE/PHONE'
    IGNORE
VALUE 'EMPLOYEE/TELEPHONE/PHONE/$'
    EMPLOYEE.PHONE := &3&
VALUE 'EMPLOYEE/TELEPHONE/AREA-CODE'
    IGNORE
VALUE 'EMPLOYEE/TELEPHONE/AREA-CODE/$'
    EMPLOYEE.AREA-CODE := &3&
VALUE 'EMPLOYEE/JOB-TITLE'
    IGNORE
VALUE 'EMPLOYEE/JOB-TITLE/$'
    EMPLOYEE.JOB-TITLE := &3&
VALUE 'EMPLOYEE/INCOME'
/* OPTIONAL MULTIPLE IST: 18 PARENT: EMPLOYEE
   ADD 1 TO EMPLOYEE.C@INCOME
VALUE 'EMPLOYEE/INCOME/SALARY'
    IGNORE
VALUE 'EMPLOYEE/INCOME/SALARY/$'
    &5& := EMPLOYEE.C@INCOME
    EMPLOYEE.SALARY(&5&) := &3&
VALUE 'EMPLOYEE/INCOME/BONUS'
/* OPTIONAL MULTIPLE IST: 18 PARENT: INCOME
   &5& := EMPLOYEE.C@INCOME
   ADD 1 TO EMPLOYEE.C@BONUS(&5&)
VALUE 'EMPLOYEE/INCOME/BONUS/$'
    &5& := EMPLOYEE.C@INCOME
    &6& := EMPLOYEE.C@BONUS(&5&)
    EMPLOYEE.BONUS(&5&,&6&) := &3&
NONE
IGNORE
END-DECIDE
```

Subprogram Example:

```

* -----
* CLASS  NATURAL XML TOOLKIT - UTILITIES
*
*
* DESCRIPTION
*             Parse a given XML document.
*
*
* AUTHOR      SAG   01.2006
*
* VERSION     6.2.
*
* (c) Copyright Software AG 2006. All rights reserved.
*
*
* -----
*
DEFINE DATA PARAMETER
1 XML_PARSER_INPUT          (A) DYNAMIC
PARAMETER USING EMPL
PARAMETER
1 XML_PARSER_ERROR_TEXT     (A253)
1 XML_PARSER_RESPONSE       (I2)
*
LOCAL USING PARSER-X
LOCAL
1 XML_PARSER_XPATH          (A) DYNAMIC
1 XML_PARSER_XPATH_TYPE     (A1)
1 XML_PARSER_CONTENT         (A) DYNAMIC
1 XML_PARSER_CONTENT_IS_EMPTY (L)
*
LOCAL
1 #CX                      (I4)
1 #CY                      (I4)
1 #CZ                      (I4)
END-DEFINE
*
* ----- INCLUDE THE PARSER
INCLUDE PARSER_X 'XML_PARSER_INPUT' /* XML file to be parsed
  'XML_PARSER_XPATH'           /* XPATH to represent element...
  'XML_PARSER_XPATH_TYPE'     /* Type of callback
  'XML_PARSER_CONTENT'        /* Content of found element
  'XML_PARSER_CONTENT_IS_EMPTY' /* Is TRUE if element is empty
  'XML_PARSER_ERROR_TEXT'     /* error Message
  'XML_PARSER_RESPONSE'       /* Error NR; 0 = OK
*
* ----- CALLBACK HANDLER
DEFINE SUBROUTINE CALLBACK
*
```

Examples

```
INCLUDE EMPL-P 'XML_PARSER_XPATH' /* XPATH to represent element...
'XML_PARSER_XPATH_TYPE'          /* Type of callback
'XML_PARSER_CONTENT'            /* Content of found element
'XML_PARSER_CONTENT_IS_EMPTY'   /* Is TRUE if element is empty
'#CX'
'#CY'
'#CZ'
*
END-SUBROUTINE
/*
DEFINE SUBROUTINE PARSER_ERROR
IGNORE
END-SUBROUTINE
END
```

Natural PDA EMPL Used:

```
DEFINE DATA PARAMETER
1 EMPLOYEE
  2 ATTRIBUTES_OF_EMPLOYEE
    3 PERSONNEL-ID(A8)
*
  2 FULL-NAME
    3 FIRST-NAME(A20)
    3 NAME(A20)
*
  2 FULL-ADDRESS
    3 C@ADDRESS-LINE(I4)
    3 ADDRESS-LINE(A20/1:6)
    3 CITY(A20)
    3 ZIP(A20)
    3 COUNTRY(A3)
*
  2 TELEPHONE
    3 AREA-CODE(A6)
    3 PHONE(A15)
*
  2 JOB-TITLE(A25)
*
  2 C@INCOME(I4)
  2 INCOME(1:6)
    3 SALARY(A9)
    3 C@BONUS(I4)
    3 BONUS(A9/1:4)
END-DEFINE
```

157 Parser Error Messages

The following error messages will be produced by the parser:

Response	Error Text	Example
00	Parse ended without errors.	valid/*
-01	Wrong character set/Document does not start with '<'.	not-wf(sa/147.xml
-02	Processing instruction was not closed. Position %2%.	not-wf(sa/004.xml
-03	A CDATA section was not closed. Position %2%.	esi/001.xml
-04	!DOCTYPE section was not closed. Position %2%.	not-wf(sa/055.xml
-05	Incorrect syntax was used in a comment. Position %2%.	not-wf(sa/006.xml
-06	A comment was not closed. Position %2%.	not-wf(sa/027.xml
-07	A CDATA section was not closed. Position %2%	not-wf(sa/017.xml
-08	A comment section was not closed. Position %2%.	esi/002.xml
-09	Closing tag name was started with an invalid character. Position %2%.	not-wf(sa/019.xml
-10	Closing tag without starting element. Position %2%.	not-wf(sa/042.xml
-11	Closing tag '%3%' does not match the start tag '%1%'. Position %2%.	not-wf(sa/039.xml
-12	Closing tag was not closed. Position %2%.	esi/003.xml
-13	Closing tag '%1%' was not closed. Position %2%.	no example available
-14	Starting tag name was started with an invalid character. Position %2%.	not-wf(sa/035.xml
-15	Attribute name of tag '%1%' not found. Position %2%.	no example available
-16	Attribute name of tag '%1%' contains an invalid character. Position %2%.	not-wf(sa/001.xml
-17	Attribute value of tag '%1%' ending quotation mark missing. Position %2%.	not-wf(sa/013.xml
-18	Attribute value of tag '%1%' ending apostrophe missing. Position %2%.	esi/005.xml
-19	Starting tag section was not closed. Position %2%.	esi/006.xml
-20	Tag '%1%' section was not closed. Position %2%.	not-wf(sa/176.xml
-21	A section was not closed. Position %2%.	not-wf(sa/025.xml

Response	Error Text	Example
< -8000	User defined error messages, parser ends.	no example available
< -9000	User defined error messages, PARSE_ERROR is called and parser ends.	no example available