HE - Helproutine HE - Helproutine

# **HE - Helproutine**

With this session parameter, you assign a helproutine or a help map to a field.

Possible settings		See HE Parameter Syntax below.	
<b>Default setting</b>	none		
Specification within session	yes	Applicable Statements:	INPUT
		Applicable Command:	none

Helproutines can be created with the Natural program editor, help maps with the Natural map editor.

The helproutine or help map may then be invoked during processing of an INPUT statement or a map by choosing either of the following methods:

- In the field for which to invoke the help request, enter the help character (question mark (?) by default) and press ENTER.
- Place the cursor in the field for which to invoke the help request and press the PF key defined as help function key with the SET KEY statement.

The following topics are covered below:

- HE Parameter Syntax
- Execution of Helproutines
- Examples

# **HE Parameter Syntax**

The syntax of this parameter is:

**Operand Definition Table:** 

Operand			ossi) cuct					Po	SS	ibl	le I	For	ma	ıts		Referencing Permitted	Dynamic Definition		
operand1	C	S			A													no	no
operand2	C	S	A		A	U	N	P	I	F	В	D	Т	L	C	G	o	no	no

#### Syntax Description:

operand1	operand1 is the name of the helproutine or help map to be invoked. The name may be a 1 to 8 character alphanumeric constant or user-defined variable. If a variable is used, it must have been previously defined. The name may contain an ampersand (&); at execution time, this character will be replaced by the one-character code corresponding to the current value of the Natural system variable *LANGUAGE. This feature allows the use of multi-lingual helproutines or help maps.								
operand2	You may specify 1 to 20 parameters ( <i>operand2</i> ) which are passed to the helproutine or help map. They may be specified as constants or as user-defined variables which contain the values of the parameters.								
=	<ul> <li>The equals sign (=) is used to pass an object or a field name to a helproutine or help map:</li> <li>If the equals sign is entered in the HE= specification at statement level, the name of the object (as contained in the system variable *PROGRAM) being executed is passed to the helproutine or help map. In Example 3, the object name passed is PROGRAM1.</li> <li>If the equals sign is entered in the HE= specification at field level, the name of the field is passed to the helproutine or help map. In Example 3, the field name passed is #PARM1.</li> <li>If the equals sign is used as a parameter, the corresponding parameter in the helproutine or help map must be specified with format/length A65.</li> </ul>								
nX	The notation nX can be used to specify parameters to be omitted, that is, for which no values are to be passed. The corresponding receiving parameters in the called helproutine's DEFINE DATA PARAMETER statement must be defined as OPTIONAL.								

#### **Notes:**

- 1. The operands must be separated either by the input delimiter character (as specified with the session parameter ID) or by a comma. However, a comma must not be used for this purpose if the comma is defined as decimal character (with the session parameter DC).
- 2. If parameters are specified, the helproutine must begin with a DEFINE DATA PARAMETER statement which defines fields that correspond with the parameters in format and length.
- 3. The value of the field for which a helproutine is specified may be referenced within the helproutine. This is done by specifying a field in the DEFINE DATA PARAMETER statement which corresponds in format and length with the original field. In the block of fields defined within the DEFINE DATA PARAMETER statement, this field must always be defined behind the parameters, if present.
- 4. If the field for which a helproutine is specified is an array element, its indices may be referenced by the helproutine. To do so, you specify index parameters with format I (integer), N (numeric unpacked), or P (packed numeric) at the end of the DEFINE DATA PARAMETER statement. You may specify up to three index parameters according to array dimensions.

## **Execution of Helproutines**

If a helproutine or help map is requested - by entering a question mark (?) in the field, or by pressing the help key (as defined with a SET KEY statement), or via a REINPUT USING HELP statement - all other data that may have been entered into fields are not assigned to the program variables until all help requests have been processed.

#### Note:

Only one help request per INPUT statement is possible; that is, if help is requested for more than one field (for example, by entering question marks in multiple fields), only the first help request will be executed.

## **Examples**

### Example 1:

```
/* MAIN PROGRAM
DEFINE DATA
1 #A(A20/1:3)
END-DEFINE
...
SET KEY PF1=HELP
...
INPUT #A (2) (HE='HELPA',=)
...
END
```

### Example 2:

```
/* HELP-ROUTINE 'HELPA'
DEFINE DATA PARAMETER
1 #VARNAME (A65)
1 #PARM1 (A20)
1 #VARINDEX (I2)
END-DEFINE
```

### Example 3:

HE - Helproutine Examples

### Parameter Data Area in Example Helproutine HELP1:

```
* Helproutine 'HELP1'

*

DEFINE DATA PARAMETER
1 #FLD1 (A65)
END-DEFINE
...
```