

Natural

Natural Optimizer Compiler

Version 9.1.1

April 2019

This document applies to Natural Version 9.1.1 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 1979-2019 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://softwareag.com/licenses>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://softwareag.com/licenses/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software AG.

Document ID: NATMF-NOC-911-20190618

Table of Contents

Preface	v
1 About this Documentation	1
Document Conventions	2
Online Information and Support	2
Data Protection	3
I NOC - General Information	5
2 NOC - General Information	7
Natural Nucleus Optimization	8
Natural Optimizer Compiler	10
II Using the Optimizer Compiler - Overview	11
3 What is Compiled and What is Not	13
Statements Compiled by the Natural Optimizer Compiler	14
Statements that are Not Compiled	15
4 NOCSTAT Command	17
Invoking NOCSTAT	18
Generating Reports	19
Report Formats	22
Batch Execution	28
5 Displaying the Size of the Machine Code	31
6 Optimizer Usage Examples	33
Example 1 - No Improvement	34
Example 2 - Considerable Improvement	34
Examples 3 and 4 - CPU Usage	36
III	39
7 Activating the Optimizer Compiler	41
Macro NTOPT	42
Dynamic Profile Parameter OPT	42
System Command NOCOPT	43
Natural Statement OPTIONS	43
8 Optimizer Options	45
List of Options	46
ARCH Option	50
ARROPT Option	52
PGEN Option	53
Prerequisites for Code Generation with Unicode Operands	58
UNICC Option	58
Influence of other Natural Parameters	59
9 Performance Considerations	61
Formats	62
Arrays	62
Alphanumeric Fields	63
DECIDE ON	63
Numeric Values	63

Variable Positioning	64
Variable Caching	64
NODBG	65
10 Listing Zaps	67

Preface

This documentation for Natural Optimizer Compiler describes various aspects which should be taken into consideration when the Natural Optimizer Compiler is installed at your site.

In the remainder of the Natural Optimizer Compiler documentation the Natural Optimizer Compiler is also referred to as NOC, which is the product code.

For an explanation of the format abbreviations used in this documents, see the section *Possible Formats* in the *Natural Statements* documentation.

General Information	Various aspects of the Natural Optimizer Compiler and how to benefit most from the Natural Optimizer Compiler.
Using the Optimizer Compiler	Statements and programs used for compilation. Statistical data on programs suitable for processing by the Natural Optimizer Compiler: NOCSTAT command. Examples of when to use the Optimizer Compiler.
Activating the Optimizer Compiler	How to switch on the Natural Optimizer Compiler.
Optimizer Options	Various options of the Natural Optimizer Compiler. How to apply PGEN to output generated code and internal Natural structures for examination. Influence by other Natural parameters.
Performance Considerations	How to achieve best performance considering data formats, arrays, alpha fields, DECIDE ON and numeric values.
Listing Zaps	How to receive an overview of the Zaps that have been applied to the Natural Optimizer Compiler.

Related Documentation:

Installing the Natural Optimizer Compiler on z/OS, z/VSE and BS2000 in the *Natural Installation* documentation

1 About this Documentation

- Document Conventions 2
- Online Information and Support 2
- Data Protection 3

Document Conventions

Convention	Description
Bold	Identifies elements on a screen.
Monospace font	Identifies service names and locations in the format <code>folder.subfolder.service</code> , APIs, Java classes, methods, properties.
<i>Italic</i>	Identifies: Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies: Text you must type in. Messages displayed by the system. Program code.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the symbol.
[]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

Online Information and Support

Software AG Documentation Website

You can find documentation on the Software AG Documentation website at <http://documentation.softwareag.com>. The site requires credentials for Software AG's Product Support site Empower. If you do not have Empower credentials, you must use the TECHcommunity website.

Software AG Empower Product Support Website

If you do not yet have an account for Empower, send an email to empower@softwareag.com with your name, company, and company email address and request an account.

Once you have an account, you can open Support Incidents online via the eService section of Empower at <https://empower.softwareag.com/>.

You can find product information on the Software AG Empower Product Support website at <https://empower.softwareag.com>.

To submit feature/enhancement requests, get information about product availability, and download products, go to [Products](#).

To get information about fixes and to read early warnings, technical papers, and knowledge base articles, go to the [Knowledge Center](#).

If you have any questions, you can find a local or toll-free number for your country in our Global Support Contact Directory at https://empower.softwareag.com/public_directory.asp and give us a call.

Software AG TECHcommunity

You can find documentation and other technical information on the Software AG TECHcommunity website at <http://techcommunity.softwareag.com>. You can:

- Access product documentation, if you have TECHcommunity credentials. If you do not, you will need to register and specify "Documentation" as an area of interest.
- Access articles, code samples, demos, and tutorials.
- Use the online discussion forums, moderated by Software AG professionals, to ask questions, discuss best practices, and learn how other customers are using Software AG technology.
- Link to external websites that discuss open standards and web technology.

Data Protection

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.

I NOC - General Information

2 NOC - General Information


- Natural Nucleus Optimization 8
- Natural Optimizer Compiler 10

This section describes various aspects which should be taken into consideration when the Natural Optimizer Compiler is installed at your site. The information provided in this documentation helps you to make full use of the benefits offered by the Natural Optimizer Compiler.

Natural Nucleus Optimization

The Natural nucleus optimizes simple arithmetic, assignment, and comparison statements by translating parts of them into machine code. All programs are optimized automatically in this way.

The following graphic illustrates how the Natural Optimizer Compiler generates machine code when a Natural object is compiled or executed:



Natural Optimizer Compiler

The Natural Optimizer Compiler goes one step further than standard optimization. It compiles not only simple statements to machine code, but also complex statements and statement sequences.

The compiled code is further optimized as far as array range operations, field concatenation, and optimum base register assignment are concerned.

All statements (including arithmetic operations) optimized with the Natural Optimizer Compiler provide the same results as the same statements generated by standard Natural.

To activate the Natural Optimizer Compiler (see the relevant section), use the macro `NTOPT` in the Natural parameter module, the dynamic profile parameter `OPT`, the system command `NCOPT`, or the `OPTIONS` statement.

All programs that are cataloged (`STOW` or `CATALOG` system command) with the Natural Optimizer Compiler activated are compiled to machine code. This will also result in the object code size of the programs being larger than usual, depending on how much of the program can be optimized.

A program executed with the `RUN` system command is compiled to machine code if the Natural Optimizer Compiler is activated with the system command `NCOPT`, the macro `NTOPT` or the `OPTIONS` statement for all or part of the program.

To see if a program is suitable for compilation with the Natural Optimizer Compiler, use the `NOCSTAT` command as described in the relevant section.



Note: The dynamic recatalog feature (profile parameter `RECAT` set to `ON`) cannot be used with programs compiled to machine code.

To execute programs that have been compiled with the Natural Optimizer Compiler, it is not necessary that the Natural Optimizer Compiler is installed.

II

Using the Optimizer Compiler - Overview

[What is Compiled and What is Not](#)

[NOCSTAT Command](#)

[Displaying the Size of the Machine Code](#)

[Optimizer Usage Examples](#)

3

What is Compiled and What is Not

- Statements Compiled by the Natural Optimizer Compiler 14
- Statements that are Not Compiled 15

The Natural Optimizer Compiler is particularly effective for programs that contain a considerable amount of data manipulation, such as computation, transfer, and logical condition processing.

This section contains an overview of the statements which are compiled to machine code and those which are not compiled.



Note: The options the Natural Optimizer Compiler provides cannot be used for specifying statements to be optimized as described in the *Optimizer Options*.

Statements Compiled by the Natural Optimizer Compiler

The Natural Optimizer Compiler compiles the following statements to machine code:

■ Statements for Arithmetic and Data Movement Operations:

- ADD
- ASSIGN
- COMPRESS
- COMPUTE
- DIVIDE
- EXAMINE, with the following clauses:
 - DIRECTION (with constant values only; that is FORWARD or BACKWARD),
 - GIVING NUMBER, GIVING POSITION (also concurrently),
 - GIVING LENGTH

Example:

```
EXAMINE #TEXT FOR #A GIVING NUMBER #NMB1
EXAMINE #TEXT FOR #A GIVING POSITION #POSEX5
EXAMINE #TEXT FOR #A GIVING LENGTH #LGHEX6 ←
```

Restrictions:

- GIVING INDEX is not optimized.
- *operand1* and *operand4* can be fix array occurrences; that is, no ranges are admissible, for example:

EXAMINE #A(#J) FOR #B(#K)

- MOVE (ROUNDED, SUBSTRING, BY NAME, LEFT/RIGHT JUSTIFIED,)
- MOVE ALL
- MULTIPLY
- RESET
- SUBTRACT
- **Statements for Processing of Logical Conditions:**
 - IF
 - DECIDE FOR
 - DECIDE ON
- **Statements for Loop Execution:**
 - FOR
 - ESCAPE
 - REPEAT

Statements that are Not Compiled

The Natural Optimizer Compiler *does not* compile the following statements:

- I/O statements (DISPLAY, WRITE, READ/WRITE WORK FILE).
- complex special statements such as SEPARATE.
- statements that pass control to another object such as FETCH, PERFORM, CALLNAT, CALL.
- statements that perform database access (READ, FIND, HISTOGRAM, GET, UPDATE, DELETE, END TRANSACTION, BACKOUT TRANSACTION)

4 NOCSTAT Command

- Invoking NOCSTAT 18
- Generating Reports 19
- Report Formats 22
- Batch Execution 28

For programs optimized with the Natural Optimizer Compiler, certain statements can be directly converted into machine code when cataloged. As a result, when executing the optimized objects with Natural at runtime, the performance can be improved considerably.

The **NOCSTAT** command analyses cataloged objects and provides statistical information to help decide whether program statements benefit from optimization with the Natural Optimizer Compiler and, if so, to what extent they can be optimized.

If a program is cataloged (`STOW`, `CATALL`), the Natural compiler generates an internal (pseudo) object code based on the statements in the source program. In most cases, one source statement is transformed into one pseudo-code instruction. However, for complex statements, such as `FOR` and `REPEAT`, several pseudo-code instructions are generated. The **NOCSTAT** analyses are based on the generated pseudo-code instructions. Therefore, the number of statements indicated in the statistical reports may exceed the number of statements in the source program.

Invoking NOCSTAT

> To use the Natural **NOCSTAT** command

- Enter the direct command `NOCSTAT`.

The main `NOCSTAT` screen is displayed:


```

16:41:00          ***** NATURAL NOCSTAT COMMAND *****          2017-11-24

Name ..... _____
Library ..... SAGTEST_

NOCable Objects only .. _

Output Report ..... X Statement Category
                   _ Statement Type
                   _ Code Profile

Output Destination .... X Screen
                   _ CSV to Work File
                   _ XML to Work File
                   with XSL _____

Progress Control ..... X
Download to PC ..... _

Command ==>

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit                                     Canc
  
```

To obtain field-specific help information, either enter a question mark in the relevant field and press ENTER, or place the cursor in the field and press PF1. Press PF3 to exit NOCSTAT.

Generating Reports

You can generate statistical reports for a single program or a set of programs. If you analyze more than one program at a time, the reports are produced in series. When you have finished looking at one report, press ENTER to view the next report.

The main NOCSTAT menu provides the following options:

Field	Explanation
Name	Enter a name or a range of names to specify the program(s) you want to examine: <i>value</i> is any combination of one or more characters.
	<i>value</i> Single program.
	* All programs.
	<i>value</i> * All programs whose names begin with <i>value</i> .
	<i>value</i> > All programs whose names are greater/equal <i>value</i> .

Field	Explanation	
	<i>value</i> <	All programs whose names are less/equal <i>value</i> .
Library	<p>Enter the name of a library or specify a range; the same applies as described for the Name field above.</p> <p>The current library is the default.</p>	
NOCable Objects only	<p>Mark this option to exclude programs already compiled with the Natural Optimizer Compiler.</p> <p>Otherwise, the NOCSTAT command selects all Natural programs specified in the Name and Library fields by default, including NOC-compiled programs.</p>	
Output Report	<p>Mark any of the options to select statements by category, type or code profile.</p> <p>See <i>Statement Category</i>, <i>Statement Type</i> and <i>Code Profile</i> below.</p>	
Output Destination	<p>Mark any of the following options to determine the output format and destination:</p>	
	Screen	<p>Displays the report on the screen or writes the report data to Print File 7 if <i>Download to PC</i> is selected for processing.</p>
	CSV to Work File	<p>Generates spreadsheets with comma-separated values.</p> <p>The report data is written to either of the following files:</p> <ol style="list-style-type: none"> 1. Work File 7 if running online and <i>Download to PC</i> is selected. 2. Work File 1 in all other cases. <p>Use the file extension <i>.csv</i> to write the work file directly to your PC for further processing.</p> <p>You can only route reports to a PC if Entire Connection is installed.</p>
	XML to Work File	<p>Generates XML documents.</p> <p>The report data is written to either of the following files:</p> <ol style="list-style-type: none"> 1. Work File 7 if running online and <i>Download to PC</i> is selected. 2. Work File 1 in all other cases. <p>Use the file extension <i>.txt</i> to write the work file data directly to your PC and change the file name afterwards to the extension <i>.xml</i> for further processing.</p> <p>You can only route reports to a PC if Entire Connection is installed.</p> <p>If a value is entered in the field with <i>XSL</i>, a processing instruction is added at the top of the XML output document:</p>

Field	Explanation
	<pre data-bbox="787 243 1377 306"><?xml-stylesheet type="text/xsl" href=" value "></pre> <p data-bbox="787 333 1463 401">The <i>value</i> entered should be the absolute or relative URL of the style sheet, for example:</p> <pre data-bbox="787 443 951 470">nocstat.xsl</pre> <p data-bbox="787 506 813 533">or</p> <pre data-bbox="787 575 1406 602">http://natural.software-ag.de/nocstat.xsl</pre> <p data-bbox="787 638 1458 806">The processing instruction causes the document to be transformed according to the given style sheet when it is viewed by an XSLT-capable browser or transformed by a batch XSLT run. A typical use of this feature is to convert the output XML to an HTML page.</p> <p data-bbox="787 842 1471 932">There are two XSLT style sheets delivered with Natural as text objects NOCSTLS1 and NOCSTLS2 in the Natural library SYSEXUEX in the FNAT system file.</p> <p data-bbox="787 968 1471 1058">NOCSTLS1 provides formatting instructions for report type <i>Statement Category</i>, NOCSTLS2 for report type <i>Statement Type</i> as described below.</p> <p data-bbox="787 1094 1458 1157">Download the style sheets with file extension <code>.xsl</code> to the same directory in which the XML work files are stored.</p>
Progress Control	<p data-bbox="420 1178 1455 1241">Only applies in an online environment and if one of the following options is selected for processing:</p> <ol data-bbox="420 1272 704 1398" style="list-style-type: none"> 1. CSV to Work File, 2. XML to Work File, 3. Download to PC. <p data-bbox="420 1430 1455 1493">If one of these options is selected, a brief message appears for each program listed in the generated report.</p>
Download to PC	<p data-bbox="420 1514 1471 1577">Only applies if Entire Connection is installed, and if you run online with Print/Work File 7 defined as the PC file (see the WORK and PRINT profile parameters).</p> <p data-bbox="420 1608 1471 1640">Download report output data with Entire Connection to a PC by using either of the following:</p> <ol data-bbox="420 1671 907 1745" style="list-style-type: none"> 1. Print File 7 for the Screen destination. 2. Work File 7 for CSV or XML output.

Report Formats

You can choose between three output formats described below to display the statistics NOCSTAT provides for the statements analyzed. Different report layouts are produced for programs already optimized with the Natural Optimizer Compiler and for programs to be considered for optimization. The example reports below show the difference. Press PF3to interrupt report processing and return to the NOCSTAT menu.

Below is information on:

- [Statement Category](#)
- [Statement Type](#)
- [Code Profile](#)

Statement Category

The statistical report generated with the option `Statement Category` lists various categories of statements with the corresponding number of occurrences and the total number of statements already optimized or suitable for optimization, depending on whether or not the program was optimized with the Natural Optimizer Compiler.

Example of Program without NOC Optimization:

```

11:49:46          ***** NATURAL NOCSTAT COMMAND *****          2017-05-29
                Library SAGTEST Name NOCTEST1 Type Program

                No NOC          NOCable
                -----          -
Database Loop:          0          0
Database Simple:        0          0
SORT / WORK I/O:        0          0
FOR / REPEAT:           0          1
Screen / Printer:        1          0
String Manipulation:     6          34
Arith / Logical:         0          996
Program Calls:          20          0
Control Transfer:        2          182
Block Start:             1          0
Set Environment:         7          0
System Functions:        2          0
Miscellaneous:           0          1

                Total Statements:      1254
                NOC optimizable:      1214 ( Ratio: 96 % )
                Longest NOC Run:       216 Statements
    
```

Example of NOC-Optimized Program:

```

11:51:25          ***** NATURAL NOCSTAT COMMAND *****          2017-05-29
                Library SAGTEST Name NOCTEST1 Type Program

MCG Options: (ON,OVFLW,INDX,MIX,I0)

Database Loop:          0
Database Simple:       0
SORT / WORK I/O:      0
FOR / REPEAT:         0
Screen / Printer:     1
String Manipulation:  36
Arith / Logical:      0
Program Calls:        20
Control Transfer:     2
Block Start:          1
Set Environment:      7
System Functions:     2
Miscellaneous:        1

Total Statements:     1255
NOC optimized:       1185 ( Ratio: 94 % )
Longest NOC Run:     136 Statements

```

Report Columns and Fields:

Column	Explanation
No NOC	Statements not suitable for optimization.
NOCable	Statements suitable for optimization. Note: The number of NOCable statements is only a reasonable assumption but cannot be considered an absolutely reliable value. This is because the NOCSTAT command cannot perform all analytical queries and, occasionally, very complex code investigations that definitely decide whether a statement can be optimized with the Natural Optimizer Compiler.
Field	
Database Loop	The number of database statements that generate a processing loop, such as FIND and READ.
Database Simple	Database statements that do not generate a processing loop, such as STORE, UPDATE, DELETE and GET.
SORT / WORK I/O	SORT and work file statements.
FOR / REPEAT	Statements generating loops.
Screen / Printer	Screen and printer I/O, such as WRITE, DISPLAY and INPUT.
String Manipulation	String statements, such as EXAMINE and COMPRESS.

Column	Explanation
Arith / Logical	Arithmetic and logical statements, such as MOVE, COMPUTE and IF.
Program Calls	Transfer of control to a subroutine or subprogram, such as PERFORM, CALLNAT and FETCH.
Control Transfer	Jumps within the program, such as ESCAPE BOTTOM, FOR and REPEAT loops.
Block Start	Non-executed statements that demarcate code blocks, such as DEFINE SUBROUTINE and AT END. These statements are never optimized because they are never executed.
Set Environment	Statements that set the environment, such as SET CONTROL, SET GLOBALS and SET KEY.
System Functions	Statements, such as TOTAL, SUM, COUNT, MAX, MIN and *COUNT.
Miscellaneous	Pseudo-code statements not relevant for optimization and, therefore, ignored by the NOC.
Totals	
Total Statements	The total number of statements found in the program. This number may not correspond to the actual source statements as described in the introduction to NOCSTAT command above.
NOC optimized	For an optimized program, these are the actual pseudo-code statements (as described in the introduction to NOCSTAT command above) that have been NOC-optimized to machine code.
NOC optimizable	For non-optimized programs, this is the possible number of statements that could be optimized. The figure may be slightly higher than the actual number, since certain factors are not considered in the NOCSTAT program. For example, a SUBSTRING statement that has more than four arrays will be indicated as "optimizable" though it will not be optimized.
Ratio	Relation between Total Statements and NOC-optimized statements or Total Statements and NOC-optimizable statements in percent.
Longest NOC Run	NOC-optimized program: The number of contiguous optimized statements - the fewer fragment sequences, the better the performance.
	Non-optimized program: The number of contiguous statements to be expected if the program were optimized.

Statement Type

The statistical report generated with the option `Statement Type` lists single statements with the corresponding number of occurrences and the NOC coding generated for optimized objects.

Example of Program without NOC Optimization:

```
12:29:23          ***** NATURAL NOCSTAT COMMAND *****          2017-05-29
                    Library SAGTEST Name NOCTEST1 Type Program
```

Statement	No NOC	NOCable
MOVE/COMPUTE/ASSIGN	0	615
EXAMINE	6	0
SEPARATE	0	30
COMPRESS	0	4
MOVE TO SYSTEM FUNCTION	2	0
CALLNAT/PERFORM EXTERNAL	17	0
MOVE EDITED	1	0
ELSE/CLOSE LOOP	0	182
ON ERROR	1	0
END	1	0
STOP	1	0
IF	0	51
IF IN REPEAT UNTIL	0	1
REPEAT	0	1
RESET	0	74
IF	0	255
FETCH	3	0
IGNORE	0	1
STACK TOP CMD/DATA	2	0
MCG OPTIONS	1	0
OPTIONS	1	0
SET CONTROL	4	0

Example of NOC-Optimized Program:

```

12:31:30          ***** NATURAL NOCSTAT COMMAND *****                2017-05-29
                Library SAGTEST Name NOCTEST1 Type Program
MCG Options: (ON,OVFLW,INDX,MIX,IO)
Statement          Number
-----
EXAMINE            6
SEPARATE          30
MOVE TO SYSTEM FUNCTION  2
CALLNAT/PERFORM EXTERNAL 17
MOVE EDITED       1
NOC CODE          1183
ON ERROR          1
END               1
STOP              1
FETCH             3
IGNORE            1
STACK TOP CMD/DATA  2
MCG OPTIONS       2
OPTIONS           1
SET CONTROL       4
    
```

Code Profile

The statistical report generated with the option `Code Profile` displays contiguous sequences of statements grouped by categories in a source program suitable for optimization, or lists the NOC coding generated for an optimized program. Occurrences are highlighted.

Example of Program without NOC Optimization:

```
12:38:52          ***** NATURAL NOCSTAT COMMAND *****          2017-05-29
                Library SAGTEST  Name NOCTEST1 Type Program

Line   Statement
-----
0000   ON ERROR
0000   MCG OPTIONS
0000   OPTIONS
0295   CALLNAT/PERFORM EXTERNAL
0295   MOVE/COMPUTE/ASSIGN      <-- NOCable
0295   MOVE/COMPUTE/ASSIGN      <-- NOCable
0295   MOVE/COMPUTE/ASSIGN      <-- NOCable
0295   MOVE/COMPUTE/ASSIGN      <-- NOCable
0740   MOVE/COMPUTE/ASSIGN      <-- NOCable
0745   IF                        <-- NOCable
0750   MOVE/COMPUTE/ASSIGN      <-- NOCable
0755   MOVE/COMPUTE/ASSIGN      <-- NOCable
0760   CALLNAT/PERFORM EXTERNAL
0765   IF                        <-- NOCable
0770   MOVE/COMPUTE/ASSIGN      <-- NOCable
0775   ELSE                       <-- NOCable
0780   MOVE/COMPUTE/ASSIGN      <-- NOCable
0810   RESET                      <-- NOCable
MORE
```

Example of NOC-Optimized Program:

```

12:39:47          ***** NATURAL NOCSTAT COMMAND *****                2017-05-29
                    Library SAGTEST  Name NOCTEST1 Type Program

Line   Statement
-----
0000   MCG OPTIONS
0005   MCG OPTIONS
0000   OPTIONS
0295   CALLNAT/PERFORM EXTERNAL
0295   NOC CODE
0295   NOC CODE
0295   NOC CODE
0295   NOC CODE
0740   NOC CODE
0745   NOC CODE
0750   NOC CODE
0755   NOC CODE
0760   CALLNAT/PERFORM EXTERNAL
0765   NOC CODE
0770   NOC CODE
0775   NOC CODE
0780   NOC CODE
0810   NOC CODE
MORE
    
```

Batch Execution

Below are job examples for processing NOCSTAT reports in batch mode to create a CSV work file. After job execution, the work files generated can be transferred from host to PC for further processing with standard transfer tools.

Example Job z/OS:

```

//NOCBATCH JOB  (NOC,,30),CLASS=K,MSGCLASS=X                00000100
//NATEX EXEC  PGM=NATvrsBA,REGION=6200K,PARM=('IM=D')        00000200
//STEPLIB   DD  DISP=SHR,DSN=TESTNAT.LOAD                    00000300
//CMPRINT   DD  SYSOUT=X                                     00000400
//CMWKF01   DD  DSN='NOC.NOCSTAT.OUT',DISP=(NEW,CATLG),      00000500
              SPACE=(CYL,(1,1)),UNIT=SYSDA,VOL=SER=SAG001    00000600
//SYSOUT    DD  SYSOUT=X                                     00000700
//CMSYNIN   DD  *                                           00000800
NOCSTAT                                             00000900
*,library,,X,,,X                                       00001000
.                                                                 00001100
    
```

```
FIN 00001200
/* 00001300
```

Example Job z/VSE:

```
* $$ JOB JNM=NOCTST,CLASS=5,DISP=D
* $$ LST CLASS=Q,DISP=D
// JOB NOCTST
// ASSGN SYS001,DISK,VOL=xxxxxx,SHR
// DLBL CMWKF01,'NOCSTAT.FILE.ONE',0
// EXTENT SYS001,xxxxxx,1,0,1,150
// EXEC NATvrsBA,SIZE=NATvrsBA,PARM='SYSRDR'
IM=D,OBJIN=R
/*
ADARUN DBID=185
/*
NOCSTAT
*,library,,X,,,X
.
FIN
/*
/&
```

Example Job BS2000:

```
/.BAT234 LOGON NAT,1
/      SYSFILE SYSOUT=NATvrs.OUT
/      SYSFILE SYSLST=NATvrs.LST
/SKIP  .NOP000

=====
NAME      : E.NATvrs          S T A R T  B A T C H  N A T U R A L
=====
/.NOP000 REMARK
/      OPTION  DUMP=YES,MSG=FL
/      FILE    NOCSTAT.OUT,LINK=W01
/      FILE    ADAUSER  ,LINK=DDCARD
/      FILE    $SAG.ADAvrs.MOD      ,LINK=BLSLIB00
/      SYSFILE TASKLIB=MODvrs
/      SYSFILE SYSDTA=(SYSCMD)
/      FILE    NATvrs.CMPRMIN,LINK=CMPRMIN
/      DCLJV   NATJV1,LINK=*NATB2JV
/      FILE    $NAT.ADALNK.PARMS,LINK=DDLNKPAR
/      REMARK  %%%%%%%%%% BATCH-PHASE %%%%%%%%%%
/      EXEC    NATvrs
NOCSTAT
*,library,,X,,,X
.
FIN
```


5

Displaying the Size of the Machine Code

With the Natural system command `LIST DIRECTORY`, you can see whether a program has been compiled to machine code and also the size of the machine code.

> To list compiled programs

- Enter the Natural system command

```
LIST DIR object-name
```

The directory information for the specified object will be displayed, showing at the bottom of the screen the size of the machine code, the `OPT` parameters used for the compilation and the Natural Optimizer Compiler version under which the program was cataloged.

Further details of the `LIST` command are provided in the *System Commands* documentation.

6 Optimizer Usage Examples

- Example 1 - No Improvement 34
- Example 2 - Considerable Improvement 34
- Examples 3 and 4 - CPU Usage 36

The examples below illustrate when to use the Natural Optimizer Compiler to the best advantage and to give an indication of its power:

Example 1 - No Improvement

Nothing would be gained by using the Natural Optimizer Compiler for the following program, since it contains a statement that performs database access and an I/O statement (see *Statements that are Not Compiled*):

```

DEFINE DATA LOCAL
  1 EMPLOYEES VIEW OF EMPLOYEES
    2 JOB-TITLE
    2 BIRTH
    2 NAME
  END-DEFINE
  FIND EMPLOYEES WITH JOB-TITLE = 'PROGRAMMER' OR = 'ANALYST'
                                OR = 'PROGRAMMER/ANALYST'
                                OR = 'SYSTEM ANALYST'
    DISPLAY JOB-TITLE BIRTH NAME
  END-FIND
END
    
```

Example 2 - Considerable Improvement

If the following program is compiled with the Natural Optimizer Compiler, you will see a performance improvement of approximately 30 % (that is a 30 % reduction in CPU load). The program performs a statistical analysis of the age of IT-employees. Optimized statements are indicated in boldface.

In this example, the Natural Optimizer Compiler increases the object size by 20.5 %, due to 952 bytes of additional machine code:

Profile Parameter Setting	Size in Buffer Pool	Size of Machine Code Generated by NOC
OPT=NODBG	5768	952
OPT=OFF	4784	0


```

DEFINE DATA
LOCAL
1 EMPLOY VIEW OF EMPLOYEES
  2 JOB-TITLE      (A25)
  2 BIRTH          (D)
1 I               (I1)  INIT <1>
1 CDATE           (D)
1 NUMB            (N4)
1 SUMM            (P7.2)
1 SQUARE          (F8)
1 DEVI            (F8)
1 DEVIATION       (N3.4)
1 MEAN            (P2.3)
1 AGEDIS          (F8/1:70)
1 AGEMAX          (F8)
1 AGEH            (P3)
1 AGE             (P3)
1 AGEDAYS         (P15)
1 LINE            (A71/1:20)
1 REDEFINE LINE
  2 POINTS         (A1/1:20,0:70)
END-DEFINE
*
MOVE *DATX TO CDATE
*
FIND EMPLOY WITH JOB-TITLE = 'PROGRAMMER' OR = 'ANALYST'
OR = 'PROGRAMMER/ANALYST' OR = 'SYSTEM ANALYST'
AGEDAYS:= CDATE - BIRTH
AGE:=AGEDAYS / 365
ADD 1 TO AGEDIS(AGE)          /* DISTRIBUTION
ADD 1 TO NUMB
ADD AGE TO SUMM
COMPUTE SQUARE = SQUARE + AGE * AGE
END-FIND
*
*****
* COMPUTE ESTIMATES
*****
*
COMPUTE DEVI = NUMB * SQUARE / (SUMM * SUMM) - 1
COMPUTE DEVIATION = SQRT(DEVI)
COMPUTE MEAN = SUMM / NUMB
*
*****
* GRAPHIC DISPLAY
*****
*
FOR I 1 70
  IF AGEDIS(I) > AGEMAX MOVE AGEDIS(I) TO AGEMAX
  END-IF
END-FOR

```

```

FOR I 1 70
  COMPUTE AGEDIS(I) = AGEDIS(I) * 20 / AGEMAX
END-FOR
FOR I 1 70
  COMPUTE AGEH = 21 - AGEDIS(I)
  IF AGEH < 21 MOVE '*' TO POINTS(AGEH:20,I)
  END-IF
END-FOR
*
*****
* COMPLETE GRAPHIC DISPLAY
*****
*
MOVE '! ' TO POINTS(*,0)
WRITE TITLE LEFT
  AGEMAX(EM=999) 20X 'DISTRIBUTION OF IT-EMPLOYEES BY AGE'
WRITE NOTITLE NOHDR
LINE(*) /
'0-----10-----20-----30-----40-----50-----60-----'
/ 'MEAN='

```

Examples 3 and 4 - CPU Usage

The following program illustrates the difference in CPU usage, depending on the options you select when compiling the program. The table below lists the CPU usage in seconds and percent. The figures provided in the table were determined during a test run in an IBM z/OS environment. They can only serve as general orientation, since absolute values vary depending on the hardware applied.

```

DEFINE DATA LOCAL
1 #I1      (I4) INIT <1>
1 #I2      (I4) INIT <2>
1 #J1      (I4) INIT <3>
1 #J2      (I4) INIT <4>
1 #F       (I4)
1 #ARR1    (N7/10,5)
1 #ARR2    (N5/10,5)
END-DEFINE
*
FOR #F = 1 TO 1000000
  MOVE #ARR1(#I1,#I2) TO #ARR2(#J1,#J2)
END-FOR
*
END

```

Option	CPU seconds	CPU percentage
OFF	8.78	100
ON	0.63	7.18
INDX	0.85	9.68
OVFLW	1.71	19.48
INDX,OVFLW	2.00	22.78
INDX,OVFLW,NODBG	1.61	18.34
INDX,OVFLW,NODBG,NOSGNTR	1.61	18.34
NODBG	0.44	5.01
NOSGNTR	0.63	7.18
NODBG,NOSGNTR	0.44	5.01

```

DEFINE DATA LOCAL
1 #I1      (P7) INIT <1>
1 #I2      (P7) INIT <2>
1 #J1      (N7) INIT <3>
1 #J2      (N7) INIT <4>
1 #K1      (I4) INIT <5>
1 #K2      (I4) INIT <6>
1 #F       (I4)
1 #FIELD1  (P5)
1 #FIELD2  (N5)
1 #FIELD3  (I2)
END-DEFINE
*
FOR #F = 1 TO 500000
*
  #FIELD1:= #I1 - #I2 + (13 * 10 / 5)
  #FIELD2:= #J1 - #J2 + (13 * 10 / 5)
  #FIELD3:= #K1 - #K2 + (13 * 10 / 5)
*
END-FOR
*
END
    
```

Option	CPU seconds	CPU percentage
OFF	18.61	100.00
ON	4.95	26.60
INDX	4.95	26.60
OVFLW	5.38	28.91
INDX,OVFLW	5.38	28.91
INDX,OVFLW,NODBG	5.26	28.26
INDX,OVFLW,NODBG,NOSGNTR	5.09	27.35

Option	CPU seconds	CPU percentage
NODBG	4.79	25.74
NOSGNTR	4.81	25.85
NODBG ,NOSGNTR	4.63	24.88
NODBG ,NOSGNTR ,ZD=OFF	4.51	24.23
NODBG ,NOSGNTR ,ZD=OFF ,SIGNCHCK=OFF	4.41	23.70

III

■ 7 Activating the Optimizer Compiler	41
■ 8 Optimizer Options	45
■ 9 Performance Considerations	61
■ 10 Listing Zaps	67

7 Activating the Optimizer Compiler

- Macro NTOPT 42
- Dynamic Profile Parameter OPT 42
- System Command NOCOPT 43
- Natural Statement OPTIONS 43

To activate the Natural Optimizer Compiler, use one of the methods described in the following sections, where the first alternative is the most static one and the last alternative the most dynamic one.

All alternatives use the Optimizer options as described in the section *Optimizer Options*. Using these options you can control how and when machine code is generated, what tracing options are to be used and what the target architecture will be. The Optimizer options are the only control mechanism for the Natural Optimizer Compiler.

Macro NTOPT

With the macro `NTOPT` in the Natural parameter module, you can activate the Natural Optimizer Compiler statically for a linked Natural nucleus. Every time this Natural nucleus is started, the same Optimizer options are used again.

Example 1:

```
NTOPT 'INDX,OVFLW,ZD=OFF'
```

Example 2:

```
NTOPT 'INDX,OVFLW,ZD=OFF,TRGPT', *  
      'TRSTMT,OPTLEV03'
```

Note the continuation character "*" in column 72.

See the section *Optimizer Options* for an explanation of the options setting used.

Dynamic Profile Parameter OPT

When starting a Natural session, you can dynamically activate the Optimizer Compiler by specifying the Natural profile parameter `OPT`. As a synonym for `OPT`, you can use `MCG`. The specification of the parameter module is overwritten. The options are only valid for the current session.

Example:

```
OPT=(INDX,OVFLW,ZD=OFF)
```

or

```
MCG=(INDX,OVFLW,ZD=OFF)
```

See the section *Optimizer Options* for an explanation of the option setting used.

System Command NOCOPT

When you have started a Natural session, you can invoke the Optimizer command screen with the Natural system command `NOCOPT`. The screen monitors the current setting of the Natural Optimizer Compiler options as they were specified during Natural startup. You can now modify the setting online.

The updated parameter setting is only valid for the current session.

Natural Statement OPTIONS

The `MCG` parameter of the Natural compiler statement `OPTIONS` provides the most flexible and powerful control over machine code generation, since different options can be set for individual statements in a program. So, within one Natural program, the Natural Optimizer Compiler can be activated and deactivated several times to enclose ranges of statements with different options settings.

Example

```
OPTIONS MCG=(OVFLW,INDX,ZD=OFF)
```

or

```
OPTIONS MCG=OVFLW,INDX,ZD=OFF
```

The options string of the MCG parameter may start with a plus (+) or minus (-) sign, indicating that the values of options not mentioned should be left unaltered, and only the options present should be set (+) or reset (-), for example:

Example:

```
OPTIONS MCG=+PGEN          /* turns tracing on
(statements to be traced)
OPTIONS MCG=-PGEN         /* turns tracing off
```

If the string starts with anything other than “+” or “-”, all options are reset before the string is parsed.



Note: The Natural statement `OPTIONS` also provides other Natural compiler parameters than MCG.

See the section [Optimizer Options](#) for an explanation of the options setting used.

8 Optimizer Options

- List of Options 46
- ARCH Option 50
- ARROPT Option 52
- PGEN Option 53
- Prerequisites for Code Generation with Unicode Operands 58
- UNICC Option 58
- Influence of other Natural Parameters 59

When the Natural Optimizer has been activated, you can specify checks by setting the options explained in this section.

The options cannot be used for specifying statements to be optimized.

List of Options

The following table lists and describes the Natural Optimizer Compiler options. Default values are underlined (this is the value that will be assumed if the option is not present).

A Natural Optimizer Compiler option consists of a string surrounded by brackets or single quotation marks (except in the Natural `OPTIONS` statement), with options separated by commas. Some options have values, while the very existence of some options in the option string is sufficient to modify the environment.

The following rules apply:

- Optional clauses are surrounded by square brackets [].
- Choices are surrounded by curly braces { }.
- Each choice is separated by vertical lines “|”.
- Only one of these choices can be specified;

`ON` is equivalent to `Y` (Yes),

`OFF` to `N` (No).

- Options specified without the optional clause `ON` or `OFF` (if applicable), or their equivalent values, are interpreted as set to `ON`. For example, `OVFLW` is identical to `OVFLW=ON`.
- Except for the option `OFF`, any specified option switches on optimizing (as if `ON` was specified) and the default values apply. For example, `INDEX` is identical to `ON, INDEX`.

Option	Explanation
ABEND	Forces the Natural Optimizer Compiler to generate code which causes Natural to be abnormally terminated immediately when the ABEND option is encountered by the Natural Optimizer Compiler during compilation. The option must appear by itself or it will be ignored. Other parameters are not changed or reset by this option. This option can be useful for debugging purposes.
ARCH	Specifies the architecture level to be used for code generation: see ARCH Option in the following section.
ARROPT	Specifies the generation to be used for array assignments of the type <code>A(*) := scalar</code> . See ARROPT Option in the following section.
CACHE[={ON <u>OFF</u> Y N}]	Switches variable caching on or off. See also Variable Caching in the section <i>Performance Considerations</i> .

Option	Explanation
CPU= /370	Specifies the target architecture.
DIGTCHCK[={ON OFF Y N}]	Specifies whether the digits of packed and unpacked numeric fields (formats P and N) are to be checked when moving to another variable of the same type and precision. For example, if DIGTCHCK is ON and an unpacked numeric variable (format N) contains an invalid digit, such as X'FA', moving to another unpacked numeric variable with the same precision will generate a SOC7 (or NAT0954) error. If DIGTCHCK is OFF, no error is generated but the generated code is much faster.
ERRDUMP[={ON OFF Y N}]	Specifies whether NOC should abend if an error condition is detected during the compile phase. This is useful for debugging the Natural Optimizer Compiler itself.
INDEX[={ON OFF Y N}]	Specifies whether array indexes will be checked for out-of-bound values in the optimized code. See also the following Note .
INDX[={ON OFF Y N}]	Specifies whether array indexes will be checked for out-of-bound values in the optimized code. Additionally, RANGE will be set on. Therefore, this option is equivalent to INDEX=ON, RANGE=ON. See also the following Note .
IO[={ON OFF Y N}]	Provided for compatibility reasons only. No effect.
LOOPS[={ON OFF Y N}]	Provided for compatibility reasons only. No effect.
MIX[={ON OFF Y N}]	Provided for compatibility reasons only. No effect.
NODBG[={ON OFF Y N}]	If NODBG=OFF/N (default), the Natural Debugger can be used to debug optimized code (then, additional code is generated to check whether TEST mode has been set on). If NODBG=ON/Y, less code will be generated, the program will run faster and consume less CPU time. On the other hand, the functionality of the Natural Debugger will be limited, because the Natural Debugger might not receive control for optimized statements. See also NODBG in the section <i>Performance Considerations</i> .
NOSGNTR[={ON OFF Y N}]	Applies to packed numbers only. If NOSGNTR=OFF (default), signs of positive packed numbers which are the result of an arithmetic operation or the target of an assignment are set according to the COMOPT parameter PSIGNF. If NOSGNTR=ON, the signs resulting from execution of the generated machine instruction are left unchanged. See also the section Influence of other Natural Parameters .
ON	Switches on optimizing. If no additional option is specified, the default value defined for each option is in effect. As indicated in the following Note , this may

Option	Explanation
	cause unintended results, in particular regarding the options INDEX, INDX, OVFLW, and RANGE.
OFF	Switches off optimizing.
OPTLEV={ 2 3}	Specifies optimization level - roughly equivalent to the number of passes through the program. OPTLEV=3 is useful when PGEN is specified, since some branch targets cannot be determined during the first pass and PGEN output is made during the last pass. Thus, some values may be shown improperly.
OVFLW[={ON OFF Y N}]	Specifies whether checks for overflow in arithmetic operations or assignments will be included in the optimized code. See also the following <i>Note</i> .
PGEN[={ON OFF Y N}]	Specifies whether a disassembly of the optimized code should be output. This option also enables all other tracing options: see <i>PGEN Option</i> in the following section.
RANGE[={ON OFF Y N}]	Specifies whether range checks will be performed in operations with arrays. This ensures that array ranges will have an equal number of elements in corresponding dimensions of all operands. See also the following <i>Note</i> .
SIGNCHCK[={ON OFF Y N}]	Specifies whether the result of a multiplication with a packed or unpacked numeric multiplier should be checked for a negative zero. If zero is multiplied by a negative number, the MP machine instruction generates a negative zero result. If SIGNCHCK is on, this negative zero is converted to a positive zero. The check for a negative zero is done for every multiplication with a packed or unpacked numeric multiplier.
TRENTRY	For internal use by Software AG only. Do not change the setting of this parameter.
UNICC	Specifies whether optimized code is generated for IF and DECIDE statements with Unicode operands: see <i>UNICC Option</i> in the following section.
ZD[={ ON OFF Y N}]	Specifies whether divisors should be checked for zero. If this option is specified, then code is inserted, so that the program behaves according to the ZD profile parameter of Natural, that is, Natural error NAT1302 is issued or the result is zero. If this option is not specified, Natural error NAT0954 occurs if the divisor is zero. See also <i>ZD - Zero-Division Check</i> in the <i>Natural Parameter Reference</i> documentation.

Note for INDEX, INDX, OVFLW and RANGE:

If the option INDEX, INDX, OVFLW or RANGE is set, extra instructions are added to the generated code to detect data overflow and index-out-of-range situations should they occur during program execution. Although the use of these options slightly increases the generated code, we recommend

to use them to guarantee that erroneous programs are detected and cannot lead to unpredictable results, storage corruptions or abnormal program terminations.

- [Example of INDEX and OVFLW](#)
- [Optimum Code Generation](#)

Example of INDEX and OVFLW

```

DEFINE DATA LOCAL
...
1 P1 (P1/9)
...
1 P3 (P3/9)
...
1 I (I4)
1 J (I4)
1 K (I4)
1 L (I4)
END-DEFINE
...
P1(I:J) := P3(K:L)
...
END

```

Explanation of Example

With `INDX=ON` or `INDEX=ON` set, code is generated to verify that I, J, K and L are within the ranges defined for P1 and P3 respectively.

With `INDX=ON` or `RANGE=ON` set, code is generated to verify that I:J and K:L denote ranges of the same length.

With `OVFLW=ON` set, code is generated to verify that the value of P3 fits into the corresponding P1 variable.

For example: Value 100 would cause an overflow here.

Example Error Situation:

If one of the occurrences of P3 contains the value 100, with `OVFLW=OFF` set, the value assigned to the corresponding P1 occurrence will be zero. If the index variable I is zero or greater than 9, with `INDX=OFF` set, storage areas that do not belong to Array P1 will be corrupted. If these options (`OVFLW` and `INDX`) are set to `ON`, a Natural error occurs like it does in standard Natural runtime.

For the `NOC` option specified above, additional code is generated. However, this is well compensated for by the advantage of a check that, for example, protects against hard-to-debug errors. Undetected errors can, of course, lead to unpredictable results.

Optimum Code Generation

To assure that the least amount of code is generated and thus achieve optimum performance, use:

```
OPT=' NODBG , NOSGNTR , SIGNCHCK=OFF , ZD=OFF '
```

However, only apply this setting to objects that have been thoroughly debugged; see also [Note for INDEX, INDX, OVFLW and RANGE](#).

ARCH Option

The ARCH option specifies the hardware architecture level to be used for generating code for executable Natural objects.

When you specify an ARCH value (the higher the better), the Natural Optimizer Compiler generates newer and faster machine instructions that can improve the performance of the generated code. You cannot specify a value that is higher than the architecture level of your current machine. An executable Natural object cataloged with an ARCH level can only run on a machine with the same or a higher architecture level. Therefore, we recommend not to use the ARCH option if the cataloged objects are intended to execute on any machine, especially on a machine with a lower architecture level (for example, BS2000).

For detailed information on architecture levels, see the related literature from IBM (z/Architecture, Principles of Operation).

The following architecture levels are supported by the ARCH option of the Natural Optimizer Compiler:

Architecture Level	IBM Hardware Facility Required
0	Specifies that no architecture level is used. This is the default setting for compatibility with all mainframe platforms supported by Natural.
1 to 4	These values are not evaluated and treated as ARCH=0.
5 to 6	<ul style="list-style-type: none"> ■ z800 or z900 Extended-Translation Facility 2 ■ z890 or z990 HFP Multiply-and-Add/Subtract Facility
7	<ul style="list-style-type: none"> ■ z9 to z109 Extended-Immediate Facility
8	<ul style="list-style-type: none"> ■ z10 General-Instructions-Extension Facility ■ z10

Architecture Level	IBM Hardware Facility Required
	Execute-Extensions Facility
9	<ul style="list-style-type: none"> ■ zEnterprise 196 Load/Store-on Condition Facility Floating-Point-Extension-Facility Distinct-Operands Facility High-Word-Facility
10	<ul style="list-style-type: none"> ■ zEnterprise EC12 (zEC12) Decimal Floating-Point Facility Decimal Floating-Point Zoned-Conversion Facility
11	<ul style="list-style-type: none"> ■ zEnterprise z13 Decimal Floating-Point Packed-Conversion Facility

- [Support for Architecture Level 10](#)
- [Support for Architecture Level 11](#)

Support for Architecture Level 10

When ARCH=10 is set, the Natural Optimizer Compiler uses the decimal floating point (DFP) format for calculating intermediate results. This can increase the performance by up to 40 % for statements that perform particular arithmetic operations.

This section describes the statement operations that benefit from ARCH=10 and the restrictions that apply when using ARCH=10.

Suitable Operations

The following arithmetic operations on variables of the Natural data formats I (integer), N (numeric unpacked) and P (packed numeric) benefit from ARCH=10:

- Value assignments, except the following:
 - I to I,
 - N to N with identical length and precision, and DIGTCHCK=OFF,
 - P to I,
 - P to P, and
 - $P(m,n)$ to N if $m+n$ is greater than 15.
- Addition, subtraction, division and multiplication, except the following:
 - $P(m,n) + P(o,p)$ if $\max(m,o) + \max(n,p)$ is greater than 34, and

$P(m,n) * P(o,p)$ if $m+n+o+p$ is greater than 34.

- Comparison between variables, except the following:

P with P

Compatibility

Consider the following Natural runtime incompatibilities between ARCH=10 and ARCH=8:

- A variable of the Natural data format N (numeric zoned) must contain numbers only; blank and non-numeric characters are not allowed and cause an SOC7 termination error. If such an error occurs, Natural issues a NAT7024 error instead of a NAT0954 to clearly indicate that the error is caused by a variable that does not contain numeric data.
- Natural can issue a NAT1305 (truncated numeric value) instead of a NAT1301 error (intermediate result too large) for the following reason: The DFP format is used for calculating intermediate results and an overflow is only detected at the end of the arithmetic operation when the DFP is converted into the format of the result.

Support for Architecture Level 11

When ARCH=11 is set, the Natural Optimizer Compiler uses the decimal floating point (DFP) format for calculating arithmetic operations with packed operands. This can improve the execution speed for assignments, comparisons and calculations if at least one packed operand is involved.

ARROPT Option

The ARROPT option determines the generation algorithm to be used for array assignments of the type $A(*) := scalar$.

Valid values for ARROPT are:

Value	Explanation
ON	Recommended setting for arrays with a minimum of 50 occurrences. ON is the default setting.
OFF	Recommended setting for arrays with less than 50 occurrences.

PGEN Option

The PGEN option causes the Natural Optimizer Compiler to output the generated code and internal Natural structures. Thus, code and structures can be examined, for example, for bug fixing, performance review and support issues.

An understanding of IBM's /370 assembler is required to interpret the results produced by the PGEN option.

We recommend that you use this option with the assistance of your local Software AG representative.

- [Setting PGEN](#)
- [Sub-Options of the PGEN Option](#)
- [Output of the PGEN Option](#)
- [Working with the PGEN Output](#)

Setting PGEN

To use the PGEN facility, set the PGEN option when activating on the Optimizer Compiler.

Since the buffer is kept in memory, it is possible that the user thread will not be big enough to hold the trace information. In this case, try setting PGEN on only for the portion of the program which is to be traced, for example:

OPTIONS MCG=(PGEN=ON, TRGPT=ON) or OPTIONS MCG=+PGEN, TRGPT	Turns tracing on, including tracing of the GPT entries
OPTIONS MCG=(PGEN=OFF) or OPTIONS MCG=-PGEN	Turns tracing off

Various options affect the content of the output. The basic PGEN option causes a formatted listing of Natural source lines and a disassembly of the corresponding code to be generated and kept in memory for extraction by the NOCSHOW utility as described below, under [Output of the PGEN Option](#).

The TRSTMT, TRGPT, TRMPT and TRVDT options cause hex dumps of internal data structures associated with each line to be output.

The TRBASES and TRCACHE options cause information on base registers and cache variables to be printed out.

Sub-Options of the PGEN Option

The following table describes the options when PGEN=ON. For an explanation of the syntax used see the introduction to *List of Options* above.

Option	Explanation
LPP={5 .. 55 .. 255}	Lines-per-page for the trace output, only used when TREST=ON.
NOsrcE[={ON OFF Y N}]	If NOsrcE=OFF, the Natural source statement is included in the output.
TRACELEV={0 .. 255}	Specifies the trace level. Each bit in this one byte value specifies a buffer type to trace; these bits can be set on by using the TRxxx options as well.
TRBASES[={ON OFF Y N}]	Specifies whether base register allocations are traced.
TRCACHE[={ON OFF Y N}]	Specifies whether CACHE entries are traced.
TREST[={ON OFF Y N}]	If TREST=ON, trace is directed to the user exit NOCPRIINT as described below.
TRGPT[={ON OFF Y N}]	Specifies whether GPT entries are traced.
TRMPT[={ON OFF Y N}]	Specifies whether MPT entries are traced.
TRSTMT[={ON OFF Y N}]	Specifies whether STMT entries are traced.
TRVDT[={ON OFF Y N}]	Specifies whether VDT entries are traced.

See also the examples below.

Output of the PGEN Option

There are two places to where the Natural Optimizer Compiler can direct the output of PGEN:

- Internal Buffer
- User Exit NOCPRIINT

Internal Buffer

The contents of this buffer is overwritten each time a CHECK, CAT, STOW or RUN command is executed. A system utility NOCSHOW is provided whereby the contents of this buffer can be viewed, searched or printed.

➤ To invoke the NOCSHOW utility

- Enter the direct command NOCSHOW after a CHECK, STOW, CAT or RUN where the Natural Optimizer Compiler has been active.

The following PF keys are available on the screen:

PF Key	Function
PF2	Position to top of output
PF4	Position one line backward
PF5	Position one line forward
PF6	Print to report (1)
PF7	Position one page backward
PF8	Position one page forward
PF9	Print via Entire Connection to report (7)
PF10	Scan for text string
PF11	Repeat scan

User Exit NOCPRINT

If `TREXT=ON` is specified, the Natural Optimizer Compiler passes every output line to the user exit `NOCPRINT` instead of adding it to the trace buffer.

`NOCPRINT` is invoked following normal OS register conventions. Register 1 points to a full word containing the address of the 81 byte print line with ANSI carriage control characters in position 1. Register 13 points to an area of 18*4 bytes which may be used as a save area. Register 14 contains the return address and Register 15 contains the entry address of `NOCPRINT`.

The user exit `NOCPRINT` can be written in any language which supports the register conventions described above. It must be linked to the Natural nucleus together with the Natural Optimizer Compiler nucleus.

Working with the PGEN Output

This section provides hints and explanations on how to interpret the output created with the `PGEN` option.

- At the top of the `PGEN` output are some disassembled lines which do not appear to belong to any source line. These are the instructions which make up the prologue, which is executed whenever control passes from non-optimized to optimized code. Permanent base registers are loaded and control is passed to the correct point in the prologue. See [Example Section A](#) below.
- Sometimes a lot of source lines are printed without any code. This is because the Natural compiler puts a single line number in the object of statements which may span more than one line. See [Example Section B](#) below.
- If the `NODBG=OFF` (default) has been specified, a sequence of instructions is generated at the start of each Natural statement:

```
BALR R9,R11
DC X'....'
```

This sequence sets the line number (in case of error) and checks whether the TEST mode is switched ON. Without this sequence, debugging of NOC-compiled statements by the Natural Debugger is not possible. See [Example Section C](#) below.

- Sometimes there is a line break between disassembled lines. This break indicates an internal statement separation. It happens because often a single Natural statement will generate multiple internal (pseudo-code) statements.

Example Section A:

```
000000 5880 D354          L      R8,RTADR+4
000004 5870 D370          L      R7,RTADR+32
000008 4810 6006          LH     R1,6(,R6)
00000C 1F60                SLR   R6,R0
00000E 47F1 A000          BC    15,0(R1,R10)
```

Example Section B:

```
0010 OPTIONS MCG=(PGEN=ON,TRGPT=ON)
0020 DEFINE DATA LOCAL
0030 1 I(I4)
0040 1 P(P7.2)
0050 1 T(P7.2)
0060 END-DEFINE
0070 *

0080 SETTIME
0090 *

000012 45E0 B040          BAL   R14,RETH
000016 0036              DC    X'0036'

0100 FOR I=1 TO 100000
```

Example Section C:

```
000018 059B              BALR  R9,R11
00001A 003E              DC    X'003E'
00001C D203 7000 833B      MVC  I,#VAR033B

000022 059B              BALR  R9,R11
000024 004C              DC    X'004C'
000026 47F0 A040          BC    15,64(,R10)

00002A 059B              BALR  R9,R11
```

```

00002C 005A          DC    X'005A'
00002E BFFF 8343    ICM   R15,15,#VAR0343
000032 BF0F 7000    ICM   R0,15,I
000036 1A0F          AR    R0,R15
000038 BE0F 7000    STCM  R0,15,I

00003C 059B          BALR  R9,R11
00003E 006C          DC    X'006C'
000040 BFFF 833F    ICM   R15,15,#VAR033F
000044 BF0F 7000    ICM   R0,15,I
000048 190F          CR    R0,R15
00004A 4720 A066    BC    2,102(,R10)

0110  ADD 1.00 TO P

00004E 059B          BALR  R9,R11
000050 0082          DC    X'0082'
000052 FA41 7004 8347 AP    P,#VAR0347
000058 DC00 7008 B488 TR    P+4(1),PSGNTR

0120  END-FOR
0130  *

00005E 059B          BALR  R9,R11
000060 0094          DC    X'0094'
000062 47F0 A02A    BC    15,42(,R10)

0140  T:=*TIMD(0080)

000066 059B          BALR  R9,R11
000068 009C          DC    X'009C'
00006A 45E0 B0D8    BAL   R14,SYSFUNC
00006E 0330 B881          DC    X'0330B881'

000072 F246 7009 8330 PACK  T,#VAR0330
000078 F040 7009 0002 SRP   T,2,0
00007E DC00 700D B488 TR    T+4(1),PSGNTR

0150  T:=T / 10
0160  *

000084 059B          BALR  R9,R11
000086 00AE          DC    X'00AE'
000088 F864 D100 7009 ZAP   OP1(7),T
00008E F811 D130 8349 ZAP   WORK2(2),#VAR0349
000094 45E0 B104          BAL   R14,ZDCHECK
000098 F240 7009 B355 PACK  T,ZEROZ
00009E 47F0 E01C          BC    15,28(,R14)
0000A2 FD61 D100 8349 DP    OP1(7),#VAR0349
0000A8 D204 7009 D100 MVC   T,OP1
0000AE DC00 700D B488 TR    T+4(1),PSGNTR

```

```

0170 DISPLAY 'ELAPSED TIME (S)' T

0000B4 45E0 B040          BAL   R14,RETH
0000B8 00C0              DC    X'00C0'

0180 END
    
```

Prerequisites for Code Generation with Unicode Operands

The Natural Optimizer Compiler generates optimized code for Natural statements with Unicode strings if the following requirements are met:

Statement	Requirement
All statements	All operands used in the statement must be of the type Unicode.
EXAMINE	The ARCH option must be set to a value greater than or equal to 6.
IF DECIDE FOR DECIDE ON	<ul style="list-style-type: none"> ■ All Unicode character strings must be normalized. ■ The ARCH option must be set to a value greater than or equal to 5. ■ The UNICC option must be set to ON or FORCE. ■ The COLLATE option of the CFICU profile parameter must be set to OFF (see the <i>Parameter Reference</i> documentation).
MOVE MOVE SUBSTRING RESET	The ARCH option must be set to a value greater than or equal to 5.

UNICC Option

The UNICC option controls the generation of optimized code for IF, DECIDE FOR and DECIDE ON statements that contain Unicode operands.

Valid values for UNICC are:

Value	Explanation
ON	<p>Generates optimized code and checks whether COLLATE=OFF is set (see the CFICU profile parameter in the <i>Parameter Reference</i> documentation).</p> <p>If COLLATE=ON is set, execution of the optimized code will fail with a NAT7023 Natural system error.</p>

Value	Explanation
FORCE	Generates optimized code analogous to ON but without COLLATE=OFF check. The code optimized with FORCE performs better than the code optimized with ON but can cause wrong results if COLLATE=ON is set.
OFF	Optimized code is not generated. OFF is the default setting.

Influence of other Natural Parameters

The global parameter ZD influences the behavior of the NOC compiler. See the description of the ZD option as described under [List of Options](#) above.

The COMPOPT parameter PSIGNF (see also the system command COMPOPT in the *Natural System Commands* documentation) influences the behavior by forcing the signs of positive packed decimal numbers to F if ON, and to C if OFF. The parameter is applied if NOSGNTR=OFF is specified.

See the chart below for packed data (Format P) “:”

NOSGNTR=OFF	and	PSIGNF=ON	All signs are normalized to F (default).
NOSGNTR=OFF	and	PSIGNF=OFF	All signs are normalized to C.
NOSGNTR=ON			All signs are left as they were generated by the last operation.

For numeric data (Format N) the signs are always normalized to F, regardless of the settings of NOSGNTR and PSIGNF.

9 Performance Considerations

▪ Formats	62
▪ Arrays	62
▪ Alphanumeric Fields	63
▪ DECIDE ON	63
▪ Numeric Values	63
▪ Variable Positioning	64
▪ Variable Caching	64
▪ NODBG	65

Formats

Best performance is achieved when you use the data formats packed numeric (P) and integer (I4) in arithmetic operations.

Avoid converting data between the formats packed numeric (P), unpacked numeric (N), integer (I), and floating point (F), as this causes processing overhead even with optimized code.

As there is no interpretation overhead with optimized code, the differences between the various data formats become much more prominent: with optimized code the performance improvement gained by using format P instead of N, for example, is even higher than with normal code.

Example:

```
A = A + 1
```

In the above numeric calculation

- with non-optimized code, format P executes approximately 13 % faster than format N.
- with optimized code, however, format P executes approximately 56 % faster than format N.

The performance gain which would be achieved by applying the Natural Optimizer Compiler to this simple statement is

- with unpacked operands (N): 8 times faster
- with packed operands (P): 15 times faster

Arrays

Array range operations, such as

```
MOVE A(*) TO B(*)
```

are executed more efficiently than if the same function were programmed using a FOR statement processing loop. This is also true for optimized code.

When indexes are used, integer format I4 should be used to achieve optimum performance.

Alphanumeric Fields

We recommend that you adjust the length of the alphanumeric constant to the length of the variable, when moving an alphanumeric constant to an alphanumeric variable (format A), or when comparing an alphanumeric variable with an alphanumeric constant. This will significantly speed up operation, for example:

```
A(A5) := 'XYZAB'
...
IF A = 'ABC ' THEN ...
```

is faster than

```
IF A = 'ABC' THEN ...
```

DECIDE ON

When using the `DECIDE ON` statement with a system variable, array or parameter *operand1*, it is more efficient to move the value to a scalar variable of the same type and length defined in the `LOCAL` storage section.

Numeric Values

When using numeric constants in assignments or arithmetic operations, try to force the constants to have the same type as the operation.

Rules of Thumb

- Any numeric constant with or without a decimal but without an exponent is compiled to a packed number having the minimum length and precision to represent the value, unless the constant is an array index or substring starting position or length, in which case it becomes a four-byte integer (I4). This rule applies irrespective of the variable types participating in the operation.
- Operations containing floating point will be executed in floating point. Add `E00` to numeric values to force them to be floating point, for example:

```
ADD 1E00 to F(F8)
```

- Operations not containing floating point, but containing packed numeric, unpacked numeric, date or time variables will be executed in packed decimal. For `ADD`, `SUBTRACT` and `IF`, force numeric constants to have the same number of decimal places as the variable with the highest precision by adding a decimal place and trailing zeros, for example:

```
ADD 1.00 TO P(P7.2)
```

This technique is unnecessary for `MULTIPLY` and `DIVIDE`.

Variable Positioning

To ease the optimization process, try to keep all scalar references at the front of the data section and all array references at the end of the data section.

Variable Caching

The Natural Optimizer Compiler contains an algorithm to enhance the performance even further. In terms of performance, a statement will differ depending on the types of operands. The statement will execute more slowly if one or more of the operands is a parameter, array or scalar field of Type N (numeric) or combinations of these operands. The NOC analyzes the program flow and determines which variables with one or more of these characteristics are read two or more times without being written to. It then moves the value of each variable to a temporary cache area where it can be accessed quickly under the following conditions:

- The variable is accessed often but seldom modified *and*
- The variable is an array of any type or a scalar field of Type N (numeric).

Most suitable for variable caching are programs with long sequences that repeatedly access the same variable, in particular if the variable is an array. Variable caching then avoids complex and recurring address computation.

Example of Variable Caching

The example program displayed below demonstrates the advantage of variable caching. Cataloged with `NODBG` (see below) and `CACHE=ON`, executing this program in a test environment took 47 % of the time required to execute the program with `NODBG` and `CACHE=OFF`. Cataloging the program with `CACHE=ON`, reduces the code generated by the `NOC` from 856 bytes to 376 bytes.

```
DEFINE DATA LOCAL
1 ARR(N2/10,10,10)
1 I(I4) INIT <5>
1 J(I4) INIT <6>
1 K(I4) INIT <7>
END-DEFINE
DECIDE ON EVERY ARR(I,J,K)
  VALUE 10 IGNORE
  VALUE 20 IGNORE
  VALUE 30 IGNORE
  VALUE 40 IGNORE
  VALUE 50 IGNORE
  VALUE 60 IGNORE
  VALUE 70 IGNORE
  VALUE 80 IGNORE
  VALUE 90 IGNORE
  NONE IGNORE
END-DECIDE
```



Caution: If the content of a cached variable is modified with the command `MODIFY VARIABLE` of the Natural Debugger, only the content of the original variable is modified. The cached value (which may still be used in subsequent statements) remains unchanged. Therefore, variable caching should be used with great care if the Natural Debugger is used. See also the Natural *Debugger* documentation.

NODBG

Once a program has been thoroughly tested and put into production, you should catalog the program with the `NODBG` option as described in the section *Optimizer Options*. Without debug code, the optimized statements will execute from 10% to 30% faster.

The code to facilitate debugging is removed when this option is specified, even with `INDX` or `OVFLW` options turned on.

10

Listing Zaps

If you want to have an overview of the Zaps that have been applied to the Natural Optimizer Compiler at your site, use the `DUMP` system command.

> To obtain a Zap overview

- Enter the Natural system command

```
DUMP ZAPS NOC
```

A list of the Zaps that have been applied is displayed.

If no Zaps have been applied to the Natural Optimizer Compiler, you will receive the appropriate message.

