

Natural

Statements

Version 9.1.2

October 2021

This document applies to Natural Version 9.1.2 and all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 1979-2021 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://softwareag.com/licenses>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://softwareag.com/licenses/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at <http://softwareag.com/licenses> and/or in the root installation directory of the licensed product(s).

Use, reproduction, transfer, publication or disclosure is prohibited except as specifically provided for in your License Agreement with Software AG.

Document ID: NATMF-NNATSTATEMENTS-912-20211009

Table of Contents

Preface	xxi
1 About this Documentation	1
Document Conventions	2
Online Information and Support	2
Data Protection	3
I	5
2 Statements Grouped by Function	7
Database Access and Update	8
Arithmetic and Data Movement Operations	10
Loop Execution	10
Creation of Output Reports	10
Screen Generation for Interactive Processing	11
Processing of Logical Conditions	12
Invoking Programs and Routines	12
Functions	12
Program and Session Termination	13
Control of Work Files / PC Files	13
Component Based Programming	13
Memory Management Control for Dynamic Variables or X-Arrays	14
Natural Remote Procedure Call	14
Internet and XML	15
Miscellaneous	15
Reporting Mode Statements	15
Statements Available with Predict Case and Entire DB	17
3 Syntax Symbols and Operand Definition Tables	19
Syntax Symbols	20
Operand Definition Table	21
II Using Natural SQL Statements	25
4 Common Set and Extended Set	27
5 Basic Syntactical Items	29
Constants	30
Names	30
Parameters	34
Include Columns Clause	37
Period Clause	38
Natural Formats and SQL Data Types	39
6 Natural View Concept	41
7 Scalar Expressions	43
Scalar Expression	44
Scalar Operator	44
Factor	45
Row Value Expression	55
8 Search Conditions	57

Search Condition	58
Predicate	58
9 Select Expressions	65
Selection	66
Table Expression	67
10 Flexible SQL	77
Using Flexible SQL	78
Specifying Text Variables in Flexible SQL	79
III Referenced Example Programs	81
11 Referenced Example Programs	83
ASSIGN	84
AT BREAK	85
AT END OF DATA	87
AT END OF PAGE	88
AT START OF DATA	88
AT TOP OF PAGE	90
DEFINE SUBROUTINE	91
FIND	92
FOR	94
HISTOGRAM	95
IF	95
PERFORM BREAK PROCESSING	97
READ	98
REPEAT	99
SORT	100
STORE	101
UPDATE	103
Example Programs for System Variables	104
IV	109
12 ACCEPT/REJECT	111
Function	112
Syntax Description	112
Processing of Multiple ACCEPT/REJECT Statements	113
Limit Notation	113
Hold Status	114
Examples	114
13 ADD	117
Function	118
Syntax 1 - ADD Statement without GIVING Clause	118
Syntax 2 - ADD Statement with GIVING Clause	119
Example	121
14 ASSIGN	123
15 AT BREAK	125
Function	126
Syntax Description	127

Multiple Break Levels	128
Examples	129
16 AT END OF DATA	133
Function	134
Restrictions	135
Syntax Description	135
Example	136
17 AT END OF PAGE	139
Function	140
Syntax Description	142
Example	143
18 AT START OF DATA	147
Function	148
Syntax Description	149
Example	149
19 AT TOP OF PAGE	153
Function	154
Restriction	155
Syntax Description	155
Example	156
20 BACKOUT TRANSACTION	159
Function	160
Restriction	161
Database-Specific Considerations	161
Example	161
21 BEFORE BREAK PROCESSING	163
Function	164
Restrictions	165
Syntax Description	165
Example	166
22 CALL	167
Function	168
Syntax Description	168
Return Code	169
Register Usage	169
Storage Alignment	170
Adabas Calls	171
Direct/Dynamic Loading	171
Linkage Conventions	173
Program Properties	174
Calling a PL/I Program	174
Calling a C Program	177
INTERFACE4	180
23 CALL FILE	193
Function	194

Restriction	194
Syntax Description	194
Example	196
24 CALL LOOP	199
Function	200
Restriction	200
Syntax Description	201
Example	201
25 CALLDDBPROC (SQL)	203
Function	204
Restriction	205
Syntax Description	205
Example	207
26 CALLNAT	209
Function	210
Syntax Description	211
Parameter Transfer with Dynamic Variables	213
Examples	214
27 CLOSE CONVERSATION	217
Function	218
Syntax Description	218
Further Information and Examples	219
V	221
28 CLOSE PC FILE	223
Function	224
Syntax Description	224
Example	224
29 CLOSE PRINTER	227
Function	228
Syntax Description	228
Example	229
30 CLOSE WORK FILE	231
Function	232
Syntax Description	232
Example	233
31 COMMIT (SQL)	235
Function	236
Consideration for Non-Natural-Programs	236
Example	236
32 COMPOSE	237
Function	238
Syntax Description	239
Formatting Process	252
Dialog Mode Processing	253
Input/Output Processing by Non-Natural Programs	255

Examples	256
33 COMPRESS	265
Function	266
Syntax Description	266
Processing	270
Examples	270
34 COMPUTE	275
Function	276
Syntax Description	278
Result Precision of a Division	280
Examples	281
35 CREATE OBJECT	283
Function	284
Syntax Description	284
36 DECIDE FOR	287
Function	288
Syntax Description	288
Examples	289
37 DECIDE ON	293
Function	294
Syntax Description	294
Examples	296
38 DEFINE CLASS	299
Function	300
Syntax Description	300
VI DEFINE DATA	303
39 Function and Basic Syntax Rules	305
Function	306
General Syntax Rules	306
Programming Modes	306
40 Defining Global Data	309
Function	310
Syntax Description	310
41 Defining Parameter Data	313
Function	314
Restrictions	314
Syntax Description	314
42 Defining Local Data	319
Function	320
Restriction	320
Syntax Description	320
43 Defining Application-Independent Variables	325
Function	326
Syntax Description	326
44 Defining Context Variables for Natural RPC	329

Function	330
Restrictions	331
Syntax Description	331
45 Defining NaturalX Objects	333
Function	334
Syntax Description	334
46 Variable Definition	337
Syntax Description	338
47 View Definition	341
Syntax Description	342
48 Redefinition	347
Restrictions	348
Syntax Description	348
49 Array Dimension Definition	351
Syntax Description	352
50 Initial-Value Definition	355
Restriction	356
Syntax Description	356
51 Initial/Constant Values for an Array	359
Restriction	360
Syntax Description	361
52 EM, HD, PM Parameters for Field/Variable	365
Syntax Description	366
53 Examples of DEFINE DATA Statement Usage	367
Example 1 - DEFINE DATA LOCAL (Local Data Definition)	368
Example 2 - DEFINE DATA LOCAL (Array Definition/Initialization)	368
Example 3 - DEFINE DATA (View Definition, Array Redefinition)	372
Example 4 - DEFINE DATA (Global, Parameter and Local Data Areas)	373
Example 5 - DEFINE DATA (Initialization)	374
Example 6 - DEFINE DATA (Variable Array)	374
VII	377
54 DEFINE FUNCTION	379
Function	380
Syntax Description	380
Examples	384
55 DEFINE PRINTER	385
Function	386
Syntax Description	386
Printer Name under z/OS Batch, TSO and Server	390
Printer Name under z/VSE Batch	393
Printer Name under BS2000 Batch and TIAM	394
Printer Name under CICS	399
Printer Name under Com-plete	400
Printer Name under Com-plete/SMARTS	400
Printer Names under Natural Advanced Facilities	400

Printer Name for Additional Reports and Remote Destinations	401
Examples	401
56 DEFINE PROTOTYPE	405
Function	406
Syntax Description	407
Examples	410
57 DEFINE SUBROUTINE	413
Function	414
Restrictions	415
Syntax Description	416
Examples	416
58 DEFINE WINDOW	421
Function	422
Syntax Description	423
Protection of Input Fields in a Window	427
Invoking Different Windows	427
Example	427
59 DEFINE WORK FILE	429
Function	430
Syntax Description	430
Work File Name under z/OS Batch, TSO and Server	432
Work File Name under z/VSE Batch	435
Work File Name under BS2000 Batch and TIAM	436
Work File Name under CICS	440
Work File Name under Com-plete/SMARTS	440
VIII	441
60 DELETE	443
Function	444
Restriction	444
Syntax Description	444
Database-Specific Considerations	445
Examples	445
61 DELETE (SQL)	447
Function	448
Syntax 1 - Searched DELETE	448
Syntax 2 - Positioned DELETE	450
62 DISPLAY	451
Function	452
Syntax Description	452
Defaults Applicable for a DISPLAY Statement	464
Examples	465
63 DIVIDE	473
Function	474
Syntax 1 - DIVIDE Statement without GIVING Clause	474
Syntax 2 - DIVIDE Statement with GIVING Clause	475

Syntax 3 - DIVIDE Statement with REMAINDER Clause	476
Example	477
64 DO/DOEND	479
Function	480
Restrictions	480
Example	481
65 DOWNLOAD PC FILE	483
Function	484
Syntax Description	484
Examples	485
66 EJECT	489
Function	490
Syntax Description	490
Processing	492
Example	492
67 END	495
Function	496
Syntax Description	496
Examples	497
68 END TRANSACTION	499
Function	500
Restriction	500
Syntax Description	501
Databases Affected	501
Database-Specific Considerations	502
Examples	502
69 ESCAPE	505
Function	506
Syntax Description	507
Example	508
70 EXAMINE	511
Syntax 1 - EXAMINE	512
Syntax 2 - EXAMINE TRANSLATE	520
Syntax 3 - EXAMINE for Unicode Graphemes	522
Examples	524
71 EXPAND	533
Function	534
Syntax Description	534
IX	539
72 FETCH	541
Function	542
Syntax Description	542
Example	544
73 FIND	547
Function	548

Restrictions	550
Syntax 1 - FIND Statement with Processing Loop	550
Syntax 2 - FIND Statement without Processing Loop	550
Syntax Description	551
Examples	576
74 FOR	587
Function	588
Syntax Description	588
Example	590
75 FORMAT	593
Function	594
Syntax Description	594
Applicable Parameters	595
Example	597
76 GET	599
Function	600
Restrictions	600
Syntax Description	601
Example	602
77 GET SAME	605
Function	606
Restrictions	606
Syntax Description	607
Example	607
78 GET TRANSACTION DATA	609
Function	610
Restriction	611
Syntax Description	611
Example	611
79 HISTOGRAM	613
Function	614
Restrictions	615
Syntax Description	615
System Variables Available with HISTOGRAM	620
Examples	621
80 IF	625
Function	626
Syntax Description	626
Example	627
81 IF SELECTION	629
Function	630
Syntax Description	630
Example	632
82 IGNORE	633
Function	634

Example	634
83 INCLUDE	635
Function	636
Syntax Description	636
Examples	637
X INPUT	643
84 INPUT Syntax 1 - Dynamic Screen Layout Specification	649
INPUT Syntax 1 - Description	650
Examples - Syntax 1	659
85 INPUT Syntax 2 - Using Predefined Map Layout	663
INPUT USING MAP without Parameter List	664
INPUT Fields Defined in the Program	665
INPUT Syntax 2 - Description	665
Using the INPUT Statement in Non-Screen Modes	666
Processing Data from the Natural Stack	669
Using the INPUT Statement in Batch Mode	669
XI	673
86 INSERT (SQL)	675
Function	676
Syntax Description	676
Example	681
87 INTERFACE	683
Function	684
Syntax Description	684
88 LIMIT	691
Function	692
Syntax Description	693
Examples	693
89 LOOP	695
Function	696
Restriction	696
Syntax Description	697
Examples	697
90 MERGE (SQL)	699
Function	700
Restriction	700
Syntax Description	700
Examples	705
91 METHOD	707
Function	708
Syntax Description	708
Example	709
92 MOVE	713
Function	714
Syntax 1 - MOVE	714

Syntax 2 - MOVE SUBSTRING	716
Syntax 3 - MOVE BY NAME / POSITION	718
Syntax 4 - MOVE EDITED (Edit Mask Specified with operand2)	719
Syntax 5 - MOVE EDITED (Edit Mask Specified with operand1)	720
Syntax 6 - MOVE LEFT / RIGHT JUSTIFIED	721
Syntax 7 - MOVE NORMALIZED	722
Syntax 8 - MOVE ENCODED	724
Syntax 9 - MOVE ALL	727
Examples	729
93 MOVE INDEXED	735
94 MULTIPLY	737
Function	738
Syntax 1 - MULTIPLY Statement without GIVING Clause	738
Syntax 2 - MULTIPLY Statement with GIVING Clause	739
Example	740
95 NEWPAGE	743
Function	744
Syntax Description	744
Example	745
96 OBTAIN	749
Function	750
Restriction	750
Syntax Description	751
Examples	755
97 ON ERROR	757
Function	758
Restriction	758
Syntax Description	759
ON ERROR Processing within Objects on Different Levels	759
System Variables	760
Example	760
98 OPEN CONVERSATION	763
Function	764
Syntax Description	764
Further Information and Examples	765
99 OPTIONS	767
Function	768
Processing of Multiple OPTIONS Statements	768
XII	769
100 PARSE XML	771
Function	772
Syntax Description	773
Examples	776
101 PASSW	781
Function	782

Restriction	783
Syntax Description	783
Example	784
102 PERFORM	785
Function	786
Syntax Description	786
Examples	789
103 PERFORM BREAK PROCESSING	793
Function	794
Syntax Description	794
Example	795
104 PRINT	797
Function	798
Syntax Description	799
Example	804
105 PROCESS	807
Function	808
Restriction	808
Syntax Description	808
106 PROCESS COMMAND	811
Function	813
Syntax Description	814
Examples	824
107 PROCESS PAGE	827
Function	828
Syntax 1 - PROCESS PAGE	828
Syntax 2 - PROCESS PAGE USING	831
Syntax 3 - PROCESS PAGE UPDATE	834
Syntax 4 - PROCESS PAGE MODAL	837
Examples	839
108 PROCESS SQL (SQL)	841
Function	842
Syntax Description	842
Examples	843
109 PROPERTY	845
Function	846
Syntax Description	846
Example	847
XIII	849
110 READ	851
Function	852
Syntax Description	853
System Variables Available with READ	864
Examples	865
111 READ RESULT SET (SQL)	873

Function	874
Restriction	875
Syntax Description	875
Example	877
112 READ WORK FILE	879
Function	880
Syntax 1 - READ WORK FILE with Processing Loop	880
Syntax 2 - READ WORK FILE without Processing Loop	881
Syntax Description	881
Field Lengths	884
Variable Index Range	884
Handling of Dynamic Variables	885
Handling of X-Arrays	885
Examples	885
113 READLOB	891
Function	892
Restrictions	892
Syntax Description	893
System Variables Available with READLOB	895
Functional Considerations	896
Examples	896
114 REDEFINE	899
Function	900
Restriction	900
Syntax Description	900
Examples	901
115 REDUCE	903
Function	904
Syntax Description	904
116 REINPUT	909
Function	910
Syntax Description	911
Examples	917
117 REJECT	921
118 RELEASE	923
Function	924
Syntax Description	924
Example	925
119 REPEAT	927
Function	928
Syntax Description	928
Examples	929
120 REQUEST DOCUMENT	933
Function	934
Syntax Description	934

Automatically Generated Headers	940
URL Encoding for Special Characters	941
HTTP/HTTPS Responses Redirected and Denied	943
Examples	944
121 RESET	951
Function	952
Syntax Description	952
Example	953
122 RESIZE	955
Function	956
Syntax Description	956
123 ROLLBACK (SQL)	961
Function	962
Consideration for Non-Natural Programs	962
Example	963
124 RETRY	965
Function	966
Restriction	966
Example	966
125 RUN	969
Function	970
Syntax Description	970
Dynamic Source Text Creation/Execution	971
Example	972
XIV	975
126 SELECT (SQL)	977
Function	978
Syntax 1 - Cursor-Oriented Selection	978
Syntax 2 - Non-Cursor Selection	979
Syntax Element Description	980
Join Queries	996
127 SEND METHOD	997
Function	998
Syntax Description	998
Example	1001
128 SEPARATE	1009
Function	1010
Syntax Description	1010
Rules and Operational Considerations	1014
Examples	1016
129 SET CONTROL	1023
Function	1024
Syntax Description	1024
Examples	1024
130 SET GLOBALS	1027

	Function	1028
	Syntax Description	1028
	Parameters	1029
	Example	1030
131	SET KEY	1031
	Function	1032
	Syntax Description	1032
	Making Keys Program-Sensitive and Deactivating Keys	1033
	Assigning Commands/Programs	1035
	Assigning Input DATA	1035
	COMMAND OFF/ON	1036
	Assigning HELP	1036
	DYNAMIC Option	1037
	DISABLED Option	1037
	SET KEY Statements on Different Program Levels	1038
	Assigning Names	1040
	Example	1041
132	SET TIME	1043
	Function	1044
	Example	1044
133	SET WINDOW	1047
	Function	1048
	Syntax Description	1048
	Example	1048
134	SKIP	1049
	Function	1050
	Syntax Description	1050
	Example	1051
135	SORT	1053
	Function	1054
	Restrictions	1055
	Syntax Description	1055
	Three-Phase SORT Processing	1058
	Example	1059
	Using External Sort Programs	1063
136	STACK	1065
	Function	1066
	Syntax Description	1066
	Example	1069
137	STOP	1071
	Function	1072
	Example	1072
XV		1075
138	STORE	1077
	Function	1078

Database-Specific Considerations	1079
Syntax Description	1079
Example	1081
139 SUBTRACT	1085
Function	1086
Syntax 1 - SUBTRACT Statement without GIVING Clause	1086
Syntax 2 - SUBTRACT Statement with GIVING Clause	1087
Example	1088
140 SUSPEND IDENTICAL SUPPRESS	1089
Function	1090
Syntax Description	1090
Examples	1090
141 TERMINATE	1095
Function	1096
Syntax Description	1096
Program Receiving Control after Termination	1097
Example	1097
142 UPDATE	1099
Function	1100
Restrictions	1101
Database-Specific Considerations	1101
Syntax Description	1102
Example	1103
143 UPDATE (SQL)	1105
Function	1106
Syntax 1 - Searched UPDATE	1106
Syntax 2 - Positioned UPDATE	1109
Examples	1110
144 UPDATELOB	1113
Function	1114
Restrictions	1114
Syntax Description	1115
System Variable Available with UPDATELOB	1116
Functional Considerations	1117
Examples	1117
145 UPLOAD PC FILE	1121
Function	1122
Syntax Description	1123
Example	1124
146 WRITE	1125
Function	1126
Syntax 1 - Dynamic Formatting	1126
Syntax 2 - Using Predefined Form/Map	1134
Examples	1135
147 WRITE TITLE	1141

Function	1142
Restrictions	1143
Syntax Description	1143
Example	1147
148 WRITE TRAILER	1149
Function	1150
Restrictions	1151
Syntax Description	1151
Example	1155
149 WRITE WORK FILE	1157
Function	1158
Syntax Description	1158
External Representation of Fields	1160
Handling of Large and Dynamic Variables	1161
Example	1161

Preface

This document describes native Natural programming language (DML) statements and Natural SQL statements. It is organized under the following headings:

Statements Grouped by Function	Provides an overview of the Natural statements ordered by functional groups.
Syntax Symbols and Operand Definition Tables	Information on the symbols that are used within the diagrams that describe the syntax of Natural statements and on operand definition tables.
Using Natural SQL Statements	Describes rules specific to using Natural SQL statements.
Referenced Example Programs	Contains additional example programs that are referenced in the <i>Statements</i> and <i>System Variables</i> documentation.

Related Topics:

See also the *Programming Guide* for statement usage related topics such as: *User-Defined Variables* | *Dynamic and Large Variables* | *User-Defined Constants* | *Report Specification* | *Text Notation* | *User Comments* | *Rules for Arithmetic Assignment* | *Logical Condition Criteria* | *Function Call*

Statements in Alphabetical Order:

A - C	D - F	G - O	P - R	S - Z
ACCEPT/REJECT	DECIDE FOR	GET	PARSE XML	SELECT (SQL)
ADD	DECIDE ON	GET SAME	PASSW	SEND METHOD
ASSIGN	DEFINE CLASS	GET	PERFORM	SEPARATE
AT BREAK	DEFINE DATA	TRANSACTION	PERFORM BREAK	SET CONTROL
AT END OF DATA	DEFINE FUNCTION	DATA	PROCESSING	SET GLOBALS
AT END OF PAGE	DEFINE PRINTER	HISTOGRAM	PRINT	SET KEY
AT START OF DATA	DEFINE PROTOTYPE	IF	PROCESS	SET TIME
AT TOP OF PAGE	DEFINE	IF SELECTION	PROCESS COMMAND	SET WINDOW
BACKOUT	SUBROUTINE	IGNORE	PROCESS PAGE	SKIP
TRANSACTION	DEFINE WINDOW	INCLUDE	PROCESS	SORT
BEFORE BREAK	DEFINE WORK FILE	INPUT	SQL (SQL)	STACK
PROCESSING	DELETE	INSERT (SQL)	PROPERTY	STOP
CALL	DELETE (SQL)	INTERFACE	READ	STORE
CALL FILE	DISPLAY	LIMIT	READ RESULT SET	SUBTRACT
CALL LOOP	DIVIDE	LOOP	(SQL)	SUSPEND
CALLDBPROC (SQL)	DO/DOEND	MERGE (SQL)	READ WORK FILE	IDENTICAL
CALLNAT	DOWNLOAD PC FILE	METHOD	READLOB	SUPPRESS
CLOSE	EJECT	MOVE	REDEFINE	TERMINATE
CONVERSATION	END	MOVE INDEXED	REDUCE	UPDATE
CLOSE PC FILE	END TRANSACTION	MULTIPLY	REINPUT	UPDATE (SQL)
CLOSE PRINTER	ESCAPE	NEWPAGE	REJECT	UPDATELOB

A - C	D - F	G - O	P - R	S - Z
CLOSE WORK FILE COMMIT (SQL) COMPOSE COMPRESS COMPUTE CREATE OBJECT	EXAMINE EXPAND FETCH FIND FOR FORMAT	OBTAIN ON ERROR OPEN CONVERSATION OPTIONS	RELEASE REPEAT REQUEST DOCUMENT RESET RESIZE RETRY ROLLBACK (SQL) RUN	UPLOAD PC FILE WRITE WRITE TITLE WRITE TRAILER WRITE WORK FILE

1

About this Documentation

■ Document Conventions	2
■ Online Information and Support	2
■ Data Protection	3

Document Conventions

Convention	Description
Bold	Identifies elements on a screen.
Monospace font	Identifies service names and locations in the format <i>folder.subfolder.service</i> , APIs, Java classes, methods, properties.
<i>Italic</i>	Identifies: Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies: Text you must type in. Messages displayed by the system. Program code.
{ }	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the symbol.
[]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [] symbols.
...	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis (...).

Online Information and Support

Software AG Documentation Website

You can find documentation on the Software AG Documentation website at <https://documentation.softwareag.com>.

Software AG Empower Product Support Website

If you do not yet have an account for Empower, send an email to empower@softwareag.com with your name, company, and company email address and request an account.

Once you have an account, you can open Support Incidents online via the eService section of Empower at <https://empower.softwareag.com/>.

You can find product information on the Software AG Empower Product Support website at <https://empower.softwareag.com>.

To submit feature/enhancement requests, get information about product availability, and download products, go to [Products](#).

To get information about fixes and to read early warnings, technical papers, and knowledge base articles, go to the [Knowledge Center](#).

If you have any questions, you can find a local or toll-free number for your country in our Global Support Contact Directory at https://empower.softwareag.com/public_directory.aspx and give us a call.

Software AG Tech Community

You can find documentation and other technical information on the Software AG Tech Community website at <https://techcommunity.softwareag.com>. You can:

- Access product documentation, if you have Tech Community credentials. If you do not, you will need to register and specify "Documentation" as an area of interest.
- Access articles, code samples, demos, and tutorials.
- Use the online discussion forums, moderated by Software AG professionals, to ask questions, discuss best practices, and learn how other customers are using Software AG technology.
- Link to external websites that discuss open standards and web technology.

Data Protection

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.

I

■ 2 Statements Grouped by Function	7
■ 3 Syntax Symbols and Operand Definition Tables	19

2 Statements Grouped by Function

■ Database Access and Update	8
■ Arithmetic and Data Movement Operations	10
■ Loop Execution	10
■ Creation of Output Reports	10
■ Screen Generation for Interactive Processing	11
■ Processing of Logical Conditions	12
■ Invoking Programs and Routines	12
■ Functions	12
■ Program and Session Termination	13
■ Control of Work Files / PC Files	13
■ Component Based Programming	13
■ Memory Management Control for Dynamic Variables or X-Arrays	14
■ Natural Remote Procedure Call	14
■ Internet and XML	15
■ Miscellaneous	15
■ Reporting Mode Statements	15
■ Statements Available with Predict Case and Entire DB	17

**Notes:**

1. Certain statements can be used both in structured mode and in reporting mode, while others can be used in reporting mode only. See *Natural Programming Modes* in the *Programming Guide*.
2. The statements `DLOGOFF`, `DLOGON`, `SHOW`, `IMPORT` and `EXPORT` are only available when Entire DB is installed. For a description, see the *Entire DB* documentation.

Database Access and Update

The following types of statements are available:

- [Natural DML Statements](#)
- [Natural SQL Statements](#)

Natural DML Statements

The following Natural data manipulation language (DML) statements are used to access and manipulate information contained in a database.

READ	Reads a database file in physical or logical sequence of records.
READLOB	Reads a LOB field (Large OBject field) in fixed length segments using multiple database calls.
FIND	Selects records from a database file based on user-specified criteria.
HISTOGRAM	Reads the values of a database field.
GET	Reads a record with a given ISN (internal sequence number) or RNO (record number).
GET SAME	Re-reads the record currently being processed.
ACCEPT/REJECT	Accepts/reject records based on user-specified criteria.
PASSW	Provides password for access to a password-protected file.
LIMIT	Limits the number of executions of a <code>READ</code> , <code>FIND</code> or <code>HISTOGRAM</code> processing loop.
STORE	Adds a new record to the database.
UPDATE	Updates a record in the database.
UPDATELOB	Updates a data segment of a LOB field (Large OBject field) in a database record.
DELETE	Deletes a record from the database.
END TRANSACTION	Indicates the end of a logical transaction.
BACKOUT TRANSACTION	Backs out a partially completed logical transaction.
GET TRANSACTION DATA	Reads transaction data stored with a previous <code>END TRANSACTION</code> statement.

RETRY	Attempts to re-read a record which is in hold status for another user.
AT START OF DATA	Specifies statements to be performed when the first of a set of records is processed in a processing loop.
AT END OF DATA	Specifies statements to be performed after the last of a set of records has been processed in a processing loop.
AT BREAK	Specifies statements to be performed when the value of a control field changes (break processing).
BEFORE BREAK PROCESSING	Specifies statements to be performed before performing break processing.
PERFORM BREAK PROCESSING	Immediately invokes break processing.

Natural SQL Statements

In addition to the Natural DML statements, Natural also provides SQL statements for use in Natural programs that manipulate data on an SQL database.

The following Natural SQL statements are available:

CALLDBPROC	Invokes a stored procedure of the SQL database system to which Natural is connected.
COMMIT	Indicates the end of a logical transaction and releases all data locked during the transaction. All data modifications are committed and made permanent.
DELETE	Deletes either rows in a table without using a cursor (" searched " DELETE) or rows in a table to which a cursor is positioned (" positioned " DELETE).
INSERT	Adds one or more new rows to a table.
MERGE	Updates a table using the specified input data. Rows in the target table that match the input data are updated as specified, and rows that do not exist in the target table are inserted.
PROCESS SQL	Issues SQL statements to the underlying database.
READ RESULT SET	Reads a result set which was created by a stored procedure that was invoked by a previous CALLDBPROC statement.
ROLLBACK	Undoes all database modifications made since the beginning of the last recovery unit.
SELECT	Supports both the cursor-oriented selection that is used to retrieve an arbitrary number of rows and the non-cursor selection (singleton SELECT) that retrieves at most one single row.
UPDATE	Performs an update operation on either rows in a table without using a cursor (" searched " UPDATE) or columns in a row to which a cursor is positioned (" positioned " UPDATE).

Arithmetic and Data Movement Operations

The following statements are used for arithmetic and data movement operations:

COMPUTE	Performs arithmetic operations or assigns values to fields.
ADD	Adds two or more operands.
SUBTRACT	Subtracts one or more operands from another operand.
MULTIPLY	Multiplies two or more operands.
DIVIDE	Divides one operand into another.
EXAMINE TRANSLATE	Translates the characters contained in a field into upper-case or lower-case, or into other characters.
MOVE	Moves the value of an operand to one or more fields.
MOVE ALL	Moves multiple occurrences of a value to another field.
COMPRESS	Concatenates the value of two or more fields into a single field.
SEPARATE	Separates the content of a field into two or more fields.
EXAMINE	Scans a field for a specific value and replaces it, and/or counts how often it occurs.
RESET	Sets the value of a field to zero (if numeric) or blank (if alphanumeric), or to its initial value.

Loop Execution

The following statements are related to the execution of processing loops:

ESCAPE	Stops the execution of a processing loop.
FOR	Initiates a processing loop and controls the number of times the loop is to be processed.
REPEAT	Initiates a processing loop (and terminates it based on a specified condition).
SORT	Sorts records.

Creation of Output Reports

The following statements are used for the creation of output reports:

FORMAT	Specifies output parameter settings.
DISPLAY	Specifies fields to be output in column form.
WRITE / PRINT	Specifies fields to be output in non-column form.
WRITE TITLE	Specifies text to be output at the top of each page of a report.
WRITE TRAILER	Specifies text to be output at the bottom of each page of a report.
AT TOP OF PAGE	Specifies processing to be performed when a new output page is started.
AT END OF PAGE	Specifies processing to be performed when the end of an output page is reached.
SKIP	Generates one or more blank lines in a report.
EJECT	Causes a page advance without titles or headings.
NEWPAGE	Causes a page advance with titles and headings.
SUSPEND IDENTICAL SUPPRESS	Suspends identical suppression for a single record.
DEFINE PRINTER	Allocates a report to a logical output destination.
CLOSE PRINTER	Closes a printer.

Screen Generation for Interactive Processing

The following statements are used to create data screens (maps) for the purpose of interactive processing of data:

INPUT	Creates a formatted screen (map) for data display/ entry.
REINPUT	Re-executes an INPUT statement (if invalid data were entered in response to the previous INPUT statement).
DEFINE WINDOW	Specifies the size, position and attributes of a window.
SET WINDOW	Activates and de-activates a window.
PROCESS PAGE	Creates a data mapping to a web rich GUI screen.
PROCESS PAGE USING	Performs rich GUI I/O processing using an adapter object generated from a page layout.
PROCESS PAGE UPDATE	Re-executes a PROCESS PAGE statement.
PROCESS PAGE MODAL	Initiates a processing block and controls the lifetime of a rich GUI window.

Processing of Logical Conditions

The following statements are used to control the execution of statements based on conditions detected during the execution of a Natural program:

IF	Performs statements depending on a logical condition.
IF SELECTION	Verifies that in a sequence of alphanumeric fields one and only one contains a value.
DECIDE FOR	Performs statements depending on logical conditions.
DECIDE ON	Performs statements depending on the contents of a variable.

Invoking Programs and Routines

The following statements are used in conjunction with the execution of programs and routines:

CALL	Invokes a non-Natural program from a Natural program.
CALLNAT	Invokes a Natural subprogram.
CALL FILE	Invokes a non-Natural program to read a record from a non-Adabas file.
CALL LOOP	Generates a processing loop containing a call to a non-Natural program.
DEFINE SUBROUTINE	Defines a Natural subroutine.
ESCAPE	Stops the execution of a routine.
FETCH	Invokes a Natural program.
PERFORM	Invokes a Natural subroutine.
PROCESS COMMAND	Invokes a command processor.
RUN	Compiles and executes a source program.

Functions

The following Natural statements are used to create functions:

DEFINE FUNCTION	Creates functions which can be called instead of operands in Natural statements. Functions are defined in Natural objects of type function.
DEFINE PROTOTYPE	Specifies the properties to be used for a function call.
Function Call	Used to call Natural objects of type function.

Program and Session Termination

The following Natural statements are used to terminate the execution of an application or to terminate the Natural session.

STOP	Terminates the execution of an application.
TERMINATE	Terminates the Natural session.

Control of Work Files / PC Files

The following Natural statements are used to read/write data to a physical sequential (non-Adabas) work file:

WRITE WORK FILE	Writes data to a work file.
DOWNLOAD PC FILE	Enables transfer data from a mainframe, UNIX or OpenVMS platform to the PC.
READ WORK FILE	Reads data from a work file.
UPLOAD PC FILE	Enables transfer data from a PC to a mainframe, UNIX or OpenVMS platform.
CLOSE WORK FILE	Closes a work file.
CLOSE PC FILE	Closes a specific PC work file.
DEFINE WORK FILE	Assigns a file name to a work file.

Component Based Programming

The following Natural statements are used in conjunction with component based programming:

DEFINE CLASS	Specifies a class from within a Natural class module.
CREATE OBJECT	Creates an object (also known as an instance) of a given class.
SEND METHOD	Invokes a method of an object.
INTERFACE	Defines an interface (a collection of methods and properties) for a certain feature of a class.
METHOD	Assigns a subprogram as the implementation of a method, outside an interface definition.
PROPERTY	Assigns an object data variable as the implementation to a property, outside an interface definition.

Memory Management Control for Dynamic Variables or X-Arrays

EXPAND	Expands the allocated memory of dynamic variables to a given size.
REDUCE	Reduces the size of a dynamic variable.
RESIZE	Adjusts the size of a dynamic variable.

Natural Remote Procedure Call

OPEN CONVERSATION	Allows the RPC Client to open a conversation and specify the remote subprograms to be included in the conversation.
CLOSE CONVERSATION	Allows the client to close conversations. You can close the current conversation, another open conversation, or all open conversations.
DEFINE DATA CONTEXT	Defines variables known as context variables, which are meant to be available to multiple remote subprograms within one conversation, without having to explicitly pass the variables as parameters with the corresponding CALLNAT statements.

See also the section *Natural Statements Involved in the Natural RPC (Remote Procedure Call) documentation*.

Internet and XML

PARSE	Allows you to parse XML documents from a Natural program.
REQUEST DOCUMENT	Allows you to access an external system.

Miscellaneous

DEFINE DATA	Defines the data elements which are to be used in a Natural program or routine.
END	Indicates the end of the source code of a Natural program or routine.
INCLUDE	Incorporates Natural copycode at compilation.
ON ERROR	Intercepts runtime errors which would otherwise result in a Natural error message, followed by the termination of the Natural program.
RELEASE	Deletes the contents of the Natural stack; releases sets of ISN sets retained via a FIND statement; releases Natural global variables.
SET CONTROL	Performs a Natural terminal command from within a Natural program.
SET KEY	Assigns functions to terminal keys.
SET GLOBALS	Sets values for session parameters.
SET TIME	Establishes a point-in-time reference for a *TIMD system variable.
STACK	Places data and/or commands into the Natural stack.

Reporting Mode Statements

The following statements are for reporting mode only:

LOOP	Closes a processing loop.
DO/DOEND	Specify a group of statements to be executed based on a logical condition.
OBTAIN	Causes one or more fields to be read from a file.
REDEFINE	Redefines a field.

The following statements can be used both in structured mode and in reporting mode, however, the statement structure and, with some of them, the functionality is different:

AT START OF DATA	Specifies statements to be performed when the first of a set of records is processed in a processing loop.
AT END OF DATA	Specifies statements to be performed after the last of a set of records has been processed in a processing loop.
AT BREAK	Specifies statements to be performed when the value of a control field changes (break processing).
AT TOP OF PAGE	Specifies processing to be performed when a new output page is started.
AT END OF PAGE	Specifies processing to be performed when the end of an output page is reached.
BEFORE BREAK PROCESSING	Specifies statements to be performed before performing break processing.
CALL LOOP	Generates a processing loop containing a call to a non-Natural program.
CALL FILE	Invokes a non-Natural program to read a record from a non-Adabas file.
COMPUTE	Performs arithmetic operations or assigns values to fields.
DEFINE SUBROUTINE	Defines a Natural subroutine.
ESCAPE	Stops the execution of a processing loop.
FIND	Selects records from a database file based on user-specified criteria.
GET SAME	Re-reads the record currently being processed.
HISTOGRAM	Reads the values of a database field.
IF	Performs statements depending on a logical condition.
IF SELECTION	Verifies that in a sequence of alphanumeric fields one and only one contains a value.
ON ERROR	Intercepts runtime errors which would otherwise result in a Natural error message, followed by the termination of the Natural program.
READ	Reads a database file in physical or logical sequence of records.
READ WORK FILE	Reads data from a work file.
REPEAT	Initiates a processing loop (and terminates it based on a specified condition).
SORT	Sorts records.
STORE	Adds a new record to the database.
UPDATE	Updates a record in the database.
UPLOAD PC FILE	Enables transfer data from a PC to a mainframe, UNIX or OpenVMS platform.

Statements Available with Predict Case and Entire DB

The following Natural statements can be used in conjunction with Predict Case and Entire DB Engine:

- DLOGOFF/DLOGON
- IMPORT
- EXPORT
- SHOW

For more information about these statements, see the Predict Case documentation.

3

Syntax Symbols and Operand Definition Tables

■ Syntax Symbols	20
■ Operand Definition Table	21

Syntax Symbols

The following symbols are used within the diagrams that describe the syntax of Natural statements:

Syntax Symbol	Description
ABCDEF	Upper-case non-italic letters indicate that the term is either a Natural keyword or a Natural reserved word that must be entered exactly as specified.
<u>ABCDEF</u>	If an optional term in upper-case letters is completely underlined (not a hyperlink!), this indicates that the term is the default value. If you omit the term, the underlined value applies.
<u>ABC</u> DEF	If a term in upper-case letters is partially underlined (not a hyperlink!), this indicates that the underlined portion is an acceptable abbreviation of the term.
<i>abcdef</i>	Letters in italics are used to represent variable information. You must supply a valid value when specifying this term. Note: In place of <i>statement</i> or <i>statements</i> , you must supply one or several suitable statements, depending on the situation. If you do not want to supply a specific statement, you may insert the IGNORE statement.
[]	Elements contained within square brackets are optional. If the square brackets contain several lines stacked one above the other, each line is an optional alternative. You may choose at most one of the alternatives.
{ }	If the braces contain several lines stacked one above the other, each line is an alternative. You must choose exactly one of the alternatives.
	The vertical bar separates alternatives.
...	A term preceding an ellipsis may optionally be repeated. A number after the ellipsis indicates how many times the term may be repeated. If the term preceding the ellipsis is an expression enclosed in square brackets or braces, the ellipsis applies to the entire bracketed expression.
,...	A term preceding a comma-ellipsis may optionally be repeated; if it is repeated, the repetitions must be separated by commas. A number after the comma-ellipsis indicates how many times the term may be repeated. If the term preceding the comma-ellipsis is an expression enclosed in square brackets or braces, the comma-ellipsis applies to the entire bracketed expression.
:...	A term preceding a colon-ellipsis may optionally be repeated; if it is repeated, the repetitions must be separated by colons. A number after the colon-ellipsis indicates how many times the term may be repeated. If the term preceding the colon-ellipsis is an expression enclosed in square brackets or braces, the colon-ellipsis applies to the entire bracketed expression.

Syntax Symbol	Description
Other symbols (except [] { } ... ,... :...)	All other symbols except those defined in this table must be entered exactly as specified. <i>Exception:</i> The SQL scalar concatenation operator is represented by two vertical bars that must be entered literally as they appear in the syntax definition.

Example:

```
WRITE [USING] { FORM  
                MAP } operand1 [operand2 ... ]
```

- WRITE, USING, MAP and FORM are Natural keywords which you must enter as specified.
- *operand1* and *operand2* are user-supplied variables for which you specify the names of the objects you wish to deal with.
- The braces indicate that you must choose whether to specify either FORM or MAP; however, you must specify one of the two.
- The square brackets indicate that USING and *operand2* are optional elements which you can, but need not, specify.
- The ellipsis indicates that you may specify *operand2* several times.

Operand Definition Table

Whenever one or more operands appear in the syntax of a Natural statement, the following table is provided:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	C S A G N/M E	A U N P I F B D T L C O	yes/no	yes/no

This table provides the following information on each operand:

Possible Structure

Indicates the structure which the operand may take:

C	Constant.	
S	Single occurrence (scalar; that is, a field/variable which is neither an array nor a group).	
A	Array.	
G	Group.	
N/M	Natural system variable:	
	N	All system variables can be used.
	M	Only <i>modifiable</i> system variables can be used. For information on whether the content of a system variable is modifiable or not, see the <i>Natural System Variables</i> documentation.
E	Arithmetic expressions.	

Possible Formats

Indicates the format which the operand may take:

A	Alphanumeric (EBCDIC code page)
U	Alphanumeric (Unicode)
N	Numeric unpacked
P	Packed numeric
I	Integer
F	Floating point
B	Binary
D	Date
T	Time
L	Logical
C	Attribute control
O	HANDLE OF OBJECT

Referencing Permitted

Indicates whether the operand may be referenced or not, using a statement label or the source code line number.

Dynamic Definition

Indicates whether the field may be dynamically defined within the body of the program. This is possible in reporting mode only.

II Using Natural SQL Statements

In addition to the native Natural DML statements, Natural provides Natural SQL statements for use in Natural programs that maintain data contained in an SQL or SQL-compliant database.

This chapter describes the special syntax rules and conventions that apply when using Natural SQL statements.

[Common Set and Extended Set](#)

[Basic Syntactical Items](#)

[Natural View Concept](#)

[Scalar Expressions](#)

[Search Conditions](#)

[Select Expressions](#)

[Flexible SQL](#)

Overview of Natural SQL Statements:

[CALLDBPROC](#) | [COMMIT](#) | [DELETE](#) | [INSERT](#) | [MERGE](#) | [PROCESS SQL](#) | [READ RESULT SET](#) | [ROLLBACK](#)
| [SELECT](#) | [UPDATE](#)

4 Common Set and Extended Set

The SQL statements available within the Natural programming language comprise two different syntax sets:

- **Common Set**

The Common Set basically corresponds to the standard SQL syntax definitions and is provided for each SQL-compliant database system supported by Natural.

- **Extended Set**

The Extended Set, in addition, provides special enhancements to the Common Set to support specific features of the various supported database systems. The supported part of the Extended Set differs with each of these database systems.

The Natural SQL statements documentation mainly describes the Natural SQL Common Set. The statement syntax adheres as far as possible to the syntax described in the relevant literature on SQL; refer to this literature for further details. For details on the Natural SQL Extended Set, see the documentation of the Natural database management interface *Natural for DB2*.

5

Basic Syntactical Items

▪ Constants	30
▪ Names	30
▪ Parameters	34
▪ Include Columns Clause	37
▪ Period Clause	38
▪ Natural Formats and SQL Data Types	39

This chapter describes basic syntactical items, which are referenced within the individual SQL statement descriptions.

Constants

The constants used in the syntactical descriptions of the Natural SQL statements are:

<i>constant</i>	The item <i>constant</i> refers to either a Natural constant or an SQL <i>datetime constant</i> .
<i>integer</i>	The item <i>integer</i> always represents an integer constant.



Note: If the character for decimal point notation (session parameter `DC`) is set to a comma (,), any specified numeric constant must not be followed directly by a comma, but must be separated from it by a blank character; otherwise an error or wrong results occur.

Invalid Syntax:	Valid Syntax:
VALUES (1, 'A') leads to a syntax error.	VALUES (1 , 'A')
VALUES (1,2,3) leads to wrong results.	VALUES (1 ,2 ,3)

SQL Datetime Constants

An SQL datetime constant is a character string constant of a particular format that specifies one of the following:

DATE <i>string-constant</i>	Specifies an SQL date constant, for example: DATE '2013-15-01'.
TIME <i>string-constant</i>	Specifies an SQL time constant, for example: TIME '10:30:15'.
TIMESTAMP <i>string-constant</i>	Specifies an SQL time stamp constant, for example: TIMESTAMP '2014-15-01 10:20:15.123456'.

For information on the valid *string-constant* formats, refer to IBM's *DB2 SQL reference information*.

Names

The names used in the syntactical descriptions of the Natural SQL statements are:

- [authorization-identifier](#)
- [ddm-name](#)
- [view-name](#)
- [column-name](#)
- [location-name](#)

- [table-name](#)
- [correlation-name](#)

authorization-identifier

The item *authorization-identifier*, which is also called creator name, is used to qualify database tables and views. See also [authorization-identifier](#) under [table-name](#) below.

ddm-name

The item *ddm-name* always refers to the name of a Natural data definition module (DDM) as created with the Natural utility SYSDDM.

view-name

The item *view-name* always refers to the name of a Natural view as defined in the [DEFINE DATA](#) statement.

column-name

The item *column-name* always refers to the name of a physical database column.

location-name

The item *location-name* always denotes the location of the table. Specification of location-name is optional and belongs to the [SQL Extended Set](#).

table-name

The item *table-name* in this section is used to reference both SQL base tables and SQL viewed tables.

Syntax of item *table-name*:

[\[\[*location-name*.\]*authorization-identifier*.\]*ddm-name*](#)

Syntax Element Description:

Syntax Element	Description
<i>ddm-name</i>	A Natural data definition module (DDM) must have been created for a table to be used. The name of such a DDM must be the same as the corresponding database table name or view name.
<i>location-name</i>	This optional item specifies the location of the table to be accessed.
<i>authorization-identifier</i>	There are two ways of specifying the <i>authorization-identifier</i> of a database table or view. One way corresponds to the standard SQL syntax, in which the <i>authorization-identifier</i> is separated from the table name by a period. Using this form, the name of the DDM must be the same as the name of the database table without the <i>authorization-identifier</i>. Example: <pre> DEFINE DATA LOCAL 01 PERS VIEW OF PERSONNEL 02 NAME 02 AGE END-DEFINE SELECT * INTO VIEW PERS FROM SQL.PERSONNEL ... </pre> Alternatively, you can define the <i>authorization-identifier</i> as part of the DDM name. The DDM name then consists of the <i>authorization-identifier</i> and the database table name separated by a hyphen (-). The hyphen between the <i>authorization-identifier</i> and the table name is converted internally into a period. Note: This form of DDM name can also be used with a FIND or READ statement, because it conforms to the DDM naming conventions applicable to these statements. Example: <pre> DEFINE DATA LOCAL 01 PERS VIEW OF SQL-PERSONNEL 02 NAME 02 AGE END-DEFINE SELECT * INTO VIEW PERS FROM SQL-PERSONNEL ... </pre> If the <i>authorization-identifier</i> has been specified neither explicitly nor within the DDM name, it is determined by the SQL database system.

Syntax Element	Description
	In addition to being used in SELECT statements, table names can also be specified in DELETE, INSERT and UPDATE statements. Examples: <pre> ... DELETE FROM SQL.PERSONNEL WHERE AGE IS NULL INSERT INTO SQL.PERSONNEL (NAME,AGE) VALUES ('ADKINSON',35) UPDATE SQL.PERSONNEL SET SALARY = SALARY * 1.1 WHERE AGE > 30 ... </pre>

correlation-name

The item *correlation-name* represents an alias name for a [table-name](#). It can be used to qualify column names; it also serves to implicitly qualify fields in a Natural view when used with the [INTO](#) clause of the [SELECT](#) statement.

Example:

```

DEFINE DATA LOCAL
01 PERS-NAME      (A20)
01 EMPL-NAME      (A20)
01 AGE            (I2)
END-DEFINE
...
SELECT X.NAME , Y.NAME , X.AGE
  INTO PERS-NAME , EMPL-NAME , AGE
  FROM SQL-PERSONNEL X , SQL-EMPLOYEES Y
  WHERE X.AGE = Y.AGE
END-SELECT
...

```

Although in most cases the use of *correlation-names* is not necessary, they may help to make the statement clearer.

Parameters

Syntax of item *parameter*:

[[*sql-type*][:] *host-variable* [INDICATOR [:] *host-variable*] [LINDICATOR [:] *host-variable*]

Syntax Element Description:

Syntax Element	Description																					
<i>sql-type</i>	An <i>sql-type</i> specifies the SQL data type of the <i>host-variable</i> when it is used for DB2 access. The specification of <i>sql-type</i> is optional as most SQL data types are implicitly assigned to Natural host-variables. However, for some Natural host-variables the SQL data type cannot be associated implicitly. <i>sql-type</i> belongs to the SQL Extended Set. If a <i>sql-type</i> is specified, it has to be surrounded by colons (:). Valid sql-types are: <table><tr><th><i>sql-type</i></th><th>Natural Format</th><th>DB2 SQL Data Type</th></tr><tr><td>BLOBFILE</td><td>group(I4,I4,I4,A255)</td><td>BLOB file reference(916/917)</td></tr><tr><td>CLOBFILE</td><td>group(I4,I4,I4,A255)</td><td>CLOB file reference(920/921)</td></tr><tr><td>DBCLOBFILE</td><td>group(I4,I4,I4,A255)</td><td>DBCLOB file reference(924/925)</td></tr><tr><td>BLOBLOC</td><td>(I4)</td><td>BLOB locator960/961)</td></tr><tr><td>CLOBLOC</td><td>(I4)</td><td>CLOB locator(964/965)</td></tr><tr><td>DBCLOBLOC</td><td>(I4)</td><td>DBCLOB locator(968/969)</td></tr></table> See also <i>Natural Formats and SQL Data Types</i>.	<i>sql-type</i>	Natural Format	DB2 SQL Data Type	BLOBFILE	group(I4,I4,I4,A255)	BLOB file reference(916/917)	CLOBFILE	group(I4,I4,I4,A255)	CLOB file reference(920/921)	DBCLOBFILE	group(I4,I4,I4,A255)	DBCLOB file reference(924/925)	BLOBLOC	(I4)	BLOB locator960/961)	CLOBLOC	(I4)	CLOB locator(964/965)	DBCLOBLOC	(I4)	DBCLOB locator(968/969)
<i>sql-type</i>	Natural Format	DB2 SQL Data Type																				
BLOBFILE	group(I4,I4,I4,A255)	BLOB file reference(916/917)																				
CLOBFILE	group(I4,I4,I4,A255)	CLOB file reference(920/921)																				
DBCLOBFILE	group(I4,I4,I4,A255)	DBCLOB file reference(924/925)																				
BLOBLOC	(I4)	BLOB locator960/961)																				
CLOBLOC	(I4)	CLOB locator(964/965)																				
DBCLOBLOC	(I4)	DBCLOB locator(968/969)																				
<i>host-variable</i>	A <i>host-variable</i> is a Natural user-defined variable (no system variable) which is referenced in an SQL statement. It can be either an individual field or defined as part of a Natural view. When defined as a receiving field (for example, in the INTO clause), a <i>host-variable</i> identifies a variable to which a value is assigned by the database system. When defined as a sending field (for example, in the WHERE clause), a <i>host-variable</i> specifies a value to be passed from the program to the database system. See also <i>Natural Formats and SQL Data Types</i>.																					
[:]	Colon: To comply with SQL standards, a <i>host-variable</i> can also be prefixed by a colon (:). When used with flexible SQL, <i>host-variables</i> must be qualified by colons. Example:																					

Syntax Element	Description
	<pre>SELECT NAME INTO :#NAME FROM PERSONNEL WHERE AGE = :VALUE</pre> The colon is always required if the variable name is identical to an SQL reserved word. In a context in which either a <i>host-variable</i> or a column can be referenced, the use of a name without a colon is interpreted as a reference to a column.
INDICATOR	INDICATOR Clause: The INDICATOR clause is an optional feature to distinguish between a “null” value (that is, no value at all) and the actual values 0 or “blank”. When specified with a receiving <i>host-variable</i> (target field), the INDICATOR <i>host-variable</i> (null indicator field) serves to find out whether a column to be retrieved is “null”. Example: <pre>DEFINE DATA LOCAL 1 NAME (A20) 1 NAMEIND (I2) END-DEFINE SELECT * INTO NAME INDICATOR NAMEIND ...</pre> In this example, NAME represents the receiving <i>host-variable</i> and NAMEIND the null indicator field. If a null indicator field has been specified and the column to be retrieved is null, the value of the null indicator field is negative and the target field is set to 0 or “blank” depending on its data type. Otherwise, the value of the null indicator field is greater than or equal to 0. When specified with a sending <i>host-variable</i> (source field), the null indicator field is used to designate a null value for this field. Example: <pre>DEFINE DATA LOCAL 1 NAME (A20) 1 NAMEIND (I2) UPDATE ... SET NAME = :NAME INDICATOR :NAMEIND WHERE ...</pre> In this example, :NAME represents the sending <i>host-variable</i> and :NAMEIND the null indicator field. By entering a negative value as input for the null indicator field, a null value is assigned to a database column. An INDICATOR <i>host-variable</i> is of format/length I2.

Syntax Element	Description
LINDICATOR	LINDICATOR Clause: The LINDICATOR clause is an optional feature which is used to support columns of varying lengths, for example, VARCHAR or LONG VARCHAR type. When specified with a receiving <i>host-variable</i> (target field), the LINDICATOR <i>host-variable</i> (length indicator field) contains the number of characters actually returned by the database into the target field. The target field is always padded with blanks. If the VARCHAR or LONG VARCHAR column contains more characters than fit in the target field, the length indicator field is set to the length actually returned (that is, the length of the target field) and the null indicator field (if specified) is set to the total length of this column. Example <pre> DEFINE DATA LOCAL 1 ADDRESSLIND (I2) 1 ADDRESS (A50/1:6) END-DEFINE SELECT * INTO :ADDRESS(*) LINDICATOR :ADDRESSLIND ... </pre> In this example, :ADDRESS(*) represents the target field which receives the first 300 bytes (if available) of the addressed VARCHAR or LONG VARCHAR column, and :ADDRESSLIND represents the length indicator field which contains the number of characters actually returned. When specified with a sending <i>host-variable</i> (source field), the length indicator field specifies the number of characters of the source field which are to be passed to the database. Example: <pre> DEFINE DATA LOCAL 1 NAMELIND (I2) 1 NAME (A20) 1 AGE (I2) END-DEFINE MOVE 4 TO NAMELIND MOVE 'ABC%' TO NAME SELECT AGE INTO :AGE WHERE NAME LIKE :NAME LINDICATOR :NAMELIND ... </pre>

Syntax Element	Description
	A <code>LINDICATOR host-variable</code> is of format/length I2 or I4. For performance reasons, it should be specified immediately before the corresponding target or source field; otherwise, the field is copied to the temporary storage at runtime. If the <code>LINDICATOR</code> field is defined as an I2 field, the SQL data type <code>VARCHAR</code> is used for sending or receiving the corresponding column. If the <code>LINDICATOR host-variable</code> is specified as I4, a large object data type (<code>CLOB/BLOB</code>) is used. If the field is defined as <code>DYNAMIC</code>, the column is read in an internal loop up to its real length. The <code>LINDICATOR</code> field and <code>*LENGTH</code> are set to this length. In case of a fixed length field, the column is read up to the defined length. In both cases, the field is written up to the value defined in the <code>LINDICATOR</code> field. Let a fixed length field be defined with a <code>LINDICATOR</code> field specified as I2. If the <code>VARCHAR</code> column contains more characters than fit into this fixed length field, the length indicator field is set to the length actually returned and the null indicator field (if specified) is set to the total length of this column (retrieval). This is not possible for fixed length fields greater than or equal to 32 KB (length does not fit into null indicator field).

Include Columns Clause

include-columns

This clause belongs to the **SQL Extended Set**. It is available in the statements `DELETE`, `INSERT`, `MERGE` and `UPDATE`.

Syntax of *include-columns* clause:

```
INCLUDE (column-name data-type,...)
```

Syntax Element Description:

Syntax Element	Description
INCLUDE	The keyword <code>INCLUDE</code> introduces a list of columns that is to be included in the result table of a <code>DELETE</code> , <code>INSERT</code> , <code>MERGE</code> or <code>UPDATE</code> statement. <code>INCLUDE</code> can only be specified when a <code>DELETE</code> , <code>INSERT</code> , <code>MERGE</code> or <code>UPDATE</code> statement is nested in the <code>FROM</code> clause of a <code>SELECT</code> statement.
<i>column-name</i>	Specifies the name of a column of the result table of the <code>MERGE</code> statement that is not the same name as another include column or a column in the target table.
<i>data-type</i>	Specifies the data type of the include column. See below .

data-type

```
{ built-in-type  
  distinct-type }
```

Syntax Element Description:

Syntax Element	Description
<i>built-in-type</i>	Specifies a built-in data type. See the <i>IBM DB2 for z/OS</i> documentation for a description of built-in types.
<i>distinct-type</i>	Specifies a distinct type.

Period Clause

period-clause

This clause belongs to the [SQL Extended Set](#). It is available in the statements [searched DELETE](#) and [searched UPDATE](#).

Syntax:

```
FOR PORTION OF BUSINESS_TIME FROM expr1 TO expr2
```

Syntax Element Description:

Syntax Element	Description
FOR PORTION OF BUSINESS_TIME	Specifies that the DELETE or UPDATE only applies to row values for the portion of the BUSINESS_TIME period in the row that is specified by the period clause. BUSINESS_TIME must be a period that is defined for the table referenced in the DELETE and UPDATE statement.
FROM <i>expr1</i> TO <i>expr2</i>	Specifies that the update applies to rows for the period that is specified by FROM <i>expr1</i> TO <i>expr2</i>. If the period that is specified by the start value and the end value for the BUSINESS_TIME of a row is fully contained in the specified period (if the start value for the period in the row is less than <i>expr2</i> and the end value for the period in the row is greater than <i>expr1</i>), that row is updated or deleted, and the start and end values for the BUSINESS_TIME period remain unchanged. If the period that is specified by the start value and the end value for the BUSINESS_TIME of a row is only partially contained in the specified period (if the start value for the period in the row is greater than <i>expr2</i> or the end value for the period

Syntax Element	Description
	in the row is less than <i>expr1</i>), that row is updated or deleted and then one or two additional rows are inserted. The inserted rows represent the original row values for the periods that were not updated or deleted by the update operation. For the inserted rows, the start value and end value for the BUSINESS_TIME are set in such a way that either the start value for the BUSINESS_TIME is the start value for the BUSINESS_TIME of the original row and the end value is <i>expr1</i> , or the start value is <i>expr2</i> and the end value is the end value for the BUSINESS_TIME of the original row.
<i>expr1</i> and <i>expr2</i>	Specify expressions that return a value of a built-in data type. The result of each expression must be comparable to the data type of the columns of the specified period. Timestamp with TIME_ZONE is not allowed as the result data type for <i>expr1</i> or <i>expr2</i> .

Natural Formats and SQL Data Types

The Natural data format of a **host-variable** is converted to an SQL data type according to the following table:

Natural Format/Length	SQL Data Type
A <i>n</i> , A DYNAMIC	CHAR(<i>n</i>), VARCHAR(<i>n</i>), CLOB(<i>n</i>)
B2 (COMPOPT DB2BIN=OFF)	SMALLINT
B4 (COMPOPT DB2BIN=OFF)	INT
F4	REAL
F8	DOUBLE PRECISION
I2	SMALLINT
I4	INT
N <i>nn.m</i>	NUMERIC(<i>nn+m</i> , <i>m</i>)
P <i>nn.m</i>	NUMERIC(<i>nn+m</i> , <i>m</i>)
T, A8	TIME
T (COMPOPT DB2TSTI=ON)	TIMESTAMP
D, A10	DATE
A26	TIMESTAMP
A19	TIMESTAMP(<i>l</i>)
A20+ <i>n</i>	TIMESTAMP(<i>n</i>) (1≤ <i>n</i> ≤12)
A25	TIMESTAMP(<i>l</i>) WITH TIMEZONE
A26+ <i>n</i>	TIMESTAMP(<i>n</i>) WITH TIMEZONE (1≤ <i>n</i> ≤12)
G <i>n</i> ; for view fields only	GRAPHIC(<i>n</i>)

Natural Format/Length	SQL Data Type
Un, U DYNAMIC	GRAPHIC (n) ,VARGRAPHIC(n), DBCLOB(n) CCSID 1200
Bn, B DYNAMIC (COMPOPT DB2BIN=ON)	BINARY(n), VARBINARY(n), BLOB(n)
Bn, B DYNAMIC (COMPOPT DB2BIN=OFF)	CHAR(n), VARCHAR(n), BLOB(n)
P19.0	BIGINT
F8	DECFLOAT(n)
A DYNAMIC, B DYNAMIC, U DYNAMIC	XML
Group structure(I4,I4,I4,A255) prefixed with :BLOBFILE:	BLOB-file-reference
Group structure(I4,I4,I4,A255) prefixed with :CLOBFILE:	CLOB-file-reference
Group structure(I4,I4,I4,A255) prefixed with :DBCLOBFILE:	DBCLOB-file-reference
I4 prefixed with :BLOBLOC:	BLOB-locator
I4 prefixed with :CLOBLOC:	CLOB-locator
I4 prefixed with :DBCLOBLOC:	DBCLOB-locator

Natural does not check whether the converted SQL data type is compatible to the database column. Except for fields of format N, no data conversion is done.

In addition, the following extensions to standard Natural formats are available with Natural SQL:

- A one-dimensional array of format A can be used to support alphanumeric columns longer than 253 bytes. This array must be defined beginning with index 1 and can only be referenced by using an asterisk (*) as the index. The corresponding SQL data type is `CHAR (n)`, where *n* is the total number of bytes in the array.
- A special *host-variable* indicated by the keyword `LINDICATOR` can be used to support variable-length columns. The corresponding SQL data type is `VARCHAR (n)`; see also the [LINDICATOR](#) clause.
- The Natural formats date (D) and time (T) can be used with Natural for DB2. They are converted to DB2 `DATE` and `TIME`.

A sending field specified as one-dimensional array without a `LINDICATOR` field is converted into the SQL data type `VARCHAR`. The length is the total number of bytes in the array, not taking into account trailing blanks.

6 Natural View Concept

Some Natural SQL statements also support the use of Natural views.

A Natural view can be specified instead of a parameter list, where each field of the view - except group fields, redefining fields and fields prefixed with L@ or N@- corresponds to one parameter (host variable).

Fields with names prefixed with L@ or N@ can only exist with corresponding master fields; that is, fields of the same name, where:

- L@ fields are converted into LINDICATOR fields,
- N@ fields are converted into INDICATOR fields.

L@ fields should have been specified at view definition, immediately before the master fields to which they apply.

```
DEFINE DATA LOCAL
01 PERS VIEW OF SQL-PERSONNEL
  02 PERSID      (I4)
  02 NAME        (A20)
  02 N@NAME      (I2)                /* null indicator of NAME
  02 L@ADDRESS   (I2)                /* length indicator of ADDRESS
  02 ADDRESS     (A50/1:6)
  02 N@ADDRESS   (I2)                /* null indicator of ADDRESS
01 #PERSID      (I4)
END-DEFINE

...
SELECT *
  INTO VIEW PERS
  FROM SQL-PERSONNEL
  WHERE PERSID = #PERSID
...
END-SELECT
```

The above example is equivalent to the following one:

```
...  
SELECT *  
  INTO PERSID,  
        NAME INDICATOR N@NAME,  
        ADDRESS(*)INDICATOR N@ADDRESS LINDICATOR L@ADDRESS  
  FROM SQL-PERSONNEL  
  WHERE PERSID = #PERSID  
...  
END-SELECT
```


7

Scalar Expressions

■ Scalar Expression	44
■ Scalar Operator	44
■ Factor	45
■ Row Value Expression	55

$$\left\{ \begin{array}{l} \left[\begin{array}{c} + \\ - \end{array} \right] \left\{ \begin{array}{l} \text{factor} \\ (\text{scalar-expression}) \end{array} \right\} \\ \\ \text{scalar-expression scalar-operator scalar-expression} \end{array} \right\}$$

Scalar Expression

A *scalar-expression* consists of a **factor** or other scalar expressions including scalar operators.

Concerning reference priority, scalar expressions behave as follows:

- When a non-qualified variable name is specified in a scalar expression, the first approach is to resolve the variable name as column name of the referenced table.
- If no column with the specified name is available in the referenced table, Natural tries to resolve this variable as a Natural user-defined variable (host variable).

Scalar Operator

$$\left\{ \begin{array}{l} + \\ - \\ * \\ / \\ | \quad | \\ \text{CONCAT} \end{array} \right\}$$

A *scalar-operator* can be any of the operators listed above. The minus (-) and slash (/) operators must be separated by at least one blank from preceding operators.

Factor

Common Set Syntax:

$\left\{ \begin{array}{l} \textit{atom} \\ \textit{column-reference} \\ \textit{aggregate-function} \\ \textit{special-register} \end{array} \right\}$

Extended Set Syntax:

$\left\{ \begin{array}{l} \textit{atom} \\ \textit{column-reference} \\ \textit{aggregate-function} \\ \textit{olap-specification} \\ \textit{row-change-expression} \\ \textit{special-register} \\ \textit{scalar-function} \\ (\textit{scalar-expression}, \dots) \\ \textit{labeled-duration} \\ \textit{case-expression} \\ \textit{cast-expression} \\ \textit{user-defined-function-reference} \\ \textit{sequence-reference} \\ \textit{time-zone-specific-expression} \\ \textit{scalar-fullselect} \end{array} \right\}$

A *factor* can consist of one of the items listed in the above diagram and described in the text below.

Atom

$\left\{ \begin{array}{l} \textit{parameter} \\ \textit{constant} \end{array} \right\}$

An *atom* can be either a *parameter* or a *constant*.

Column Reference

$$\left[\begin{array}{l} \text{table-name.} \\ \text{correlation-name.} \end{array} \right] \text{column-name}$$

A *column-reference* is a column name optionally qualified by either a *table-name* or a *correlation-name* (see also the section [Basic Syntactical Items](#)). Qualified names are often clearer than unqualified names and sometimes they are essential.



Note: A table name in this context must not be qualified explicitly with an authorization identifier. Use a correlation name instead if you need a qualified table name.

If a column is referenced by a *table-name* or *correlation-name*, it must be contained in the corresponding table. If neither a *table-name* nor a *correlation-name* is specified, the respective column must be in one of the tables specified in the [FROM](#) clause (see [Table Expression](#)).

Aggregate Function

Common Set Syntax:

$$\left\{ \begin{array}{l} \text{COUNT} \quad \left\{ \begin{array}{l} (*) \\ (\text{DISTINCT } \text{column-reference}) \end{array} \right\} \\ \left\{ \begin{array}{l} \text{AVG} \\ \text{MAX} \\ \text{MIN} \\ \text{SUM} \end{array} \right\} \quad \left\{ \begin{array}{l} (\text{DISTINCT } \text{column-reference}) \\ ([\text{ALL}] \text{ scalar-expression}) \end{array} \right\} \end{array} \right\}$$

Extended Set Syntax:

$\left\{ \begin{array}{l} \text{COUNT} \\ \text{COUNT-BIG} \end{array} \right\} (\left\{ \begin{array}{l} \text{ALL} \\ \text{DISTINCT} \end{array} \right\} \text{scalar-expression})$	*	$\left\{ \begin{array}{l} \text{AVG} \\ \text{MAX} \\ \text{MIN} \\ \text{SUM} \\ \text{STDDEV} \\ \text{STDDEV\_SAMP} \\ \text{VARIANCE} \\ \text{VARIANCE\_SAMP} \end{array} \right\} (\left\{ \begin{array}{l} \text{ALL} \\ \text{DISTINCT} \end{array} \right\} \text{scalar-expression})$
$\left\{ \begin{array}{l} \text{CORRELATION} \\ \text{COVARIANCE} \\ \text{COVARIANCE\_SAMP} \end{array} \right\} (\text{scalar-expression-1}, \text{scalar-expression-2})$		

SQL provides a number of special functions to enhance its basic retrieval power. The so-called SQL aggregate functions currently available and supported by Natural are:

AVG	gives the average of the values in a column
COUNT	gives the number of values in a column
MAX	gives the highest value in a column
MIN	gives the lowest value in a column
SUM	gives the sum of the values in a column

Apart from `COUNT(*)`, each of these functions operates on the collection of scalar values in an argument (that is, a single column or a *scalar-expression*) and produces a scalar value as its result.

Example:

```

DEFINE DATA LOCAL
1  AVGAGE  (I2)
END-DEFINE
...
SELECT AVG (AGE)
  INTO AVGAGE
  FROM SQL-PERSONNEL
  ...

```

DISTINCT

In general, the argument can optionally be preceded by the keyword `DISTINCT` to eliminate redundant duplicate values before the function is applied.

If `DISTINCT` is specified, the argument must be the name of a single column; if `DISTINCT` is omitted, the argument can consist of a general *scalar-expression*.

`DISTINCT` is not allowed with the special function `COUNT(*)`, which is provided to count all rows without eliminating any duplicates.

ROW CHANGE Expression

`ROW CHANGE {
 TIMESTAMP
 TOKEN
} FOR table-designator`

A `ROW CHANGE` expression returns a token or a timestamp that represents the last change to a row.

TIMESTAMP	Specifies a timestamp is returned that represents the last time when a row was changed.
TOKEN	Specifies a token of type <code>BIGINT</code> is returned that represents a relative point in the modification sequence of a row.
FOR <i>table-designator</i>	Identifies the table in which the expression is referenced. <i>table-designator</i> has to be a valid Natural SQL DDM.

OLAP Specification

`{
 ordered-OLAP-specification
 numbering-specification
 aggregation-specification
}`

ordered-OLAP-specification

`{
 RANK
 DENSE_RANK
} () OVER ([window-partition-clause] window-order-clause)`

numbering-specification

```
ROW_NUMBER ( ) OVER ([window-partition-clause] [window-order-clause])
```

aggregation-specification

```
aggregate-function OVER ( [window-partition-clause])
{
    RANGE BETWEEN UNBOUNDED PRECEDING AND UNBOUNDED FOLLOWING
    {
        window-order-clause {
            RANGE BETWEEN UNBOUNDED
            PRECEDING AND UNBOUNDED
            FOLLOWING
            window-aggregation-group-clause
        }
    }
}
```

aggregate-function

```
{
    AVG function
    CORRELATION function
    COUNT function
    COUNT_BIG function
    COVARIANCE function
    MAX function
    MIN function
    STDDEV function
    SUM function
    VARIANCE function
}
```

window-aggregation-group-clause

```
{ ROWS } { group-start }
{ RANGE } { group-between }
           { group-end }
```

group-start

```
{ UNBOUNDED PRECEDING }
{ unsigned-constant PRECEDING }
{ CURRENT ROW }
```

group-between

BETWEEN *group-bound-1* AND *group-bound-2*

group-bound-1

$$\left\{ \begin{array}{l} \text{UNBOUNDED PRECEDING} \\ \text{unsigned-constant PRECEDING} \\ \text{unsigned-constant FOLLOWING} \\ \text{CURRENT ROW} \end{array} \right\}$$

group-bound-2

$$\left\{ \begin{array}{l} \text{UNBOUNDED FOLLOWING} \\ \text{unsigned-constant PRECEDING} \\ \text{unsigned-constant FOLLOWING} \\ \text{CURRENT ROW} \end{array} \right\}$$

group-end

$$\left\{ \begin{array}{l} \text{UNBOUNDED FOLLOWING} \\ \text{unsigned-constant FOLLOWING} \end{array} \right\}$$

window-partition-clause

PARTITION BY *partitioning-expression*,...

window-order-clause

$$\left[\begin{array}{l} \text{ORDER BY} \\ \{ \text{sort-key-expression} \} \end{array} \left[\begin{array}{l} \text{ASC} \\ \left\{ \begin{array}{l} \text{NULLS LAST} \\ \text{ASC NULLS FIRST} \\ \text{DESC} \\ \text{DESC NULLS FIRST} \end{array} \right\} \\ \text{DESC NULLS LAST} \end{array} \right] \right], \dots$$

Online analytical processing (OLAP) specifications provide the ability to return ranking, row numbering and aggregation information as a scalar value in the result of a query. An OLAP specification can be included in an expression, in a select-list, or in the ORDER BY clause of a SELECT statement. The query result to which the OLAP specifications are applied is the result table of the innermost subselect that includes the OLAP specifications.

RANK	Specifies that the rank of a row is defined as 1 plus the number of rows that strictly precede the row.
DENSE_RANK	Specifies that the rank of a row is defined as 1 plus the number of preceding rows that are distinct with respect to the ordering.
ROW_NUMBER	Specifies that a sequential row number is computed for the row that is defined by the ordering, starting with 1 for the first row.
PARTITION BY	Defines the partition within which the OLAP operation is applied.
ORDER BY	Defines the ordering of rows within a partition that is used to determine the value of the OLAP specification.
ASC	Specifies that the values of <i>sort-key-expression</i> are used in ascending order.
DESC	Specifies that the values of <i>sort-key-expression</i> are used in descending order.
NULLS_FIRST	Specifies that the window ordering considers null values before all non-null values in the sort order.
NULLS_LAST	Specifies that the window ordering considers null values after all non-null values in the sort order.

Example:

Display the ranking of employees that have a total salary of more than \$30,000, in order by last name.

```
SELECT EMPNO, LASTNAME, FIRSTNAME, SALARY+BONUS AS TOTAL_SALARY,
       RANK() OVER(ORDER BY SALARY+BONUS DESC) AS RANK_SALARY
FROM DSN8910-EMP WHERE SALARY+BONUS > 30000
ORDER BY LASTNAME;
```

Time-Zone-Specific Expression

time-zone-specific-expression

Specifies a timestamp with time zone value: **AT LOCAL** or **AT TIME ZONE**

AT LOCAL

$\left\{ \begin{array}{l} \textit{function-invocation} \\ \textit{(expression)} \\ \textit{constant} \\ \textit{column-name} \\ \textit{variable} \\ \textit{special-register} \\ \textit{scalar-fullselect} \\ \textit{case-expression} \\ \textit{cast-specification} \end{array} \right\}$	{AT LOCAL}

AT TIME ZONE

$\left\{ \begin{array}{l} \textit{function-invocation} \\ \textit{(expression)} \\ \textit{constant} \\ \textit{column-name} \\ \textit{variable} \\ \textit{special-register} \\ \textit{scalar-fullselect} \\ \textit{case-expression} \\ \textit{cast-specification} \end{array} \right\}$	{AT TIME ZONE}	$\left\{ \begin{array}{l} \textit{function-invocation} \\ \textit{(expression)} \\ \textit{constant} \\ \textit{column-name} \\ \textit{variable} \\ \textit{special-register} \\ \textit{scalar-fullselect} \\ \textit{case-expression} \\ \textit{cast-specification} \end{array} \right\}$

Special Register

special-register

A reference to a special register returns a scalar value.

For more information on the special registers that are supported by Natural, see *special-register* in the section *Syntactical Items Common to Natural SQL Statements* in the *Database Management System Interfaces* documentation.

Scalar Function

scalar-function

A scalar function is a built-in function that can be used in the construction of scalar computational expressions.

For information on the scalar functions that are supported by Natural, see *scalar-function* in the section *Syntactical Items Common to Natural SQL Statements* in the *Database Management System Interfaces* documentation.

Labeled Duration

labeled-duration

<i>scalar-expression</i>	{	YEAR	}
		YEARS	
		MONTH	
		MONTHS	
		DAY	
		DAYS	
		HOUR	
		HOURS	
		MINUTE	
		MINUTES	
		SECOND	
		SECONDS	
		MICROSECOND	
		MICROSECONDS	

A *labeled-duration* denotes a specific unit of time as expressed by a number which can be an expression followed by one of the duration keywords.

labeled-duration does not conform to standard SQL, and is therefore supported by the Natural **SQL Extended Set** only.

Case Expression

case-expression

```
CASE { searched-when-clause } [ ELSE { NULL scalar-expression } ] END
```

A *case-expression* does not conform to standard SQL and is therefore supported by the Natural **SQL Extended Set** only.

Searched WHEN Clause

```
WHEN search-condition THEN { NULL scalar-expression }
```

A Searched When Clause does not conform to standard SQL and is therefore supported by the Natural **SQL Extended Set** only.

See details on *search-condition*.

Simple WHEN Clause

scalar-expression { WHEN *scalar-expression* THEN { NULL
scalar-expression } } ...

A Simple WHEN Clause does not conform to standard SQL and is therefore supported by the Natural **SQL Extended Set** only.

Cast Expression

cast-expression

CAST (*scalar-expression* AS *data-type*)

A CAST expression does not conform to standard SQL and is therefore supported by the Natural **SQL Extended Set** only.

User-Defined Function Reference

The option *user-defined-function-reference* belongs to the Natural **SQL Extended Set**. This option enables you to invoke any user-defined function. Arguments have to be placed in brackets and separated by commas. The user-defined function must be declared in the target RDBMS.

Sequence Reference

The option *sequence-reference* belongs to the Natural **SQL Extended Set**.

{ NEXT VALUE FOR *sequence-name*
PREVIOUS VALUE FOR *sequence-name* }

This option enables you to reference the next value or the previous value of a sequence object. The sequence object has to be created in the target RDBMS before it could be referenced at runtime.

Scalar Fullselect

(*fullselect*)

The option *scalar-fullselect* belongs to the Natural **SQL Extended Set**.

A *scalar-fullselect* as supported in an expression is a *fullselect* - enclosed in parentheses - that returns a single row consisting of a single column value. If the *fullselect* does not return a row, the result of the expression is the null value. If more than one row is to be returned for a *scalar-fullselect*, an error occurs.

Row Value Expression


`(scalar-expression,...)`

A *row-value-expression* returns a single row that consists of one or more column values. The values can be specified as a list of expressions. The number of columns that are returned by the *row-value-expression* is equal to the number of expressions. *row-value-expression* can be used as an operand of several predicates (**quantified**, **DISTINCT**, **comparison**, and **IN**).

8

Search Conditions

■ Search Condition	58
■ Predicate	58



Search Condition

A *search-condition* can consist of a simple *predicate* or multiple *search-conditions*. Multiple *search-conditions* are combined with the Boolean operators AND, OR and NOT, and can contain parentheses if required to indicate a desired order of evaluation.

Example

```
DEFINE DATA LOCAL
01 NAME    (A20)
01 AGE     (I2)
END-DEFINE
...
SELECT *
  INTO NAME, AGE
  FROM SQL-PERSONNEL
  WHERE AGE = 32 AND NAME > 'K'
END-SELECT
...
```

Predicate

<i>scalar-expression</i>	{	<i>scalar-expression</i>	}	
<i>comparison</i>		<i>subquery</i>		
<i>scalar-expression</i> [NOT] BETWEEN <i>scalar-expression</i> AND <i>scalar-expression</i>				
<i>scalar-expression</i> IS [NOT] DISTINCT FROM <i>scalar-expression</i>				
<i>column-reference</i>	{	<i>atom</i>	}	[ESCAPE <i>atom</i>]
[NOT] LIKE		<i>special-register</i>		
<i>column-reference</i> IS [NOT] NULL				
<i>scalar-expression</i> [NOT] IN { <i>subquery</i> }				
	[	{ <i>atom</i>	}	...]
		<i>special-register</i>		
<i>scalar-expression</i>	{	ALL	}	<i>subquery</i>
<i>comparison</i>		ANY		
		SOME		
EXISTS <i>subquery</i>				
XMLEXISTS (<i>xquery-expression-constant</i> {BY REFIPASSING <i>xquery-argument</i> ,...})				

A *predicate* specifies a condition that can be “true”, “false” or “unknown”.

In a *search-condition*, a *predicate* can consist of a simple or complex comparison operation or other kinds of conditions.

Example:

```
SELECT NAME, AGE
  INTO VIEW PERS
  FROM SQL-PERSONNEL
 WHERE AGE BETWEEN 20 AND 30
    OR AGE IN ( 32, 34, 36 )
    AND NAME LIKE '%er'
 ...
```



Note: The percent sign (%) may conflict with Natural terminal commands. If so, you must define a terminal command control character different from %; see *Changing the Terminal Command Control Character* in the *Terminal Commands* documentation.

The individual predicates are explained in the following topics (for further information on predicates, please refer to the relevant literature). According to the syntax above, they are called as follows:

- Comparison Predicate
- BETWEEN Predicate
- DISTINCT Predicate
- LIKE Predicate
- NULL Predicate

- IN Predicate
- Quantified Predicate
- EXISTS Predicate
- XMLEXISTS Predicate

Comparison Predicate

$$\left\{ \begin{array}{l} \textit{scalar-expression} \quad \textit{comparison} \quad \textit{scalar-expression} \\ \textit{row-value-expression} \quad \textit{comparison} \quad \textit{row-value-expression} \end{array} \right\}$$

A comparison predicate compares two values or a set of values with another set of values.

In the syntax diagram above, *comparison* can be one of the following operators:

=	equal to
<	less than
>	greater than
<=	less than or equal to
>=	greater than or equal to
<>	not equal to

See information on *scalar-expression*.

Subquery

$$(\textit{select-expression})$$

A *subquery* is a *select-expression* that is nested inside another such expression.

Example:

```
DEFINE DATA LOCAL
1 #NAME      (A20)
1 #PERSNR    (I4)
END-DEFINE
...
SELECT NAME, PERSNR
  INTO #NAME, #PERSNR
  FROM SQL-PERSONNEL
  WHERE PERSNR IN
    ( SELECT PERSNR
      FROM SQL-AUTOMOBILES
      WHERE COLOR = 'black' )
```

```
...
END-SELECT
```

For further information, see [Select Expressions](#).

BETWEEN Predicate

```
scalar-expression [NOT] BETWEEN scalar-expression AND scalar-expression
```

A BETWEEN predicate compares a value with a range of values.

See information on [scalar-expression](#).

DISTINCT Predicate

```
{ scalar-expression IS [NOT] DISTINCT FROM scalar-expression
  row-value-expression IS [NOT] DISTINCT FROM row-value-expression }
```

A DISTINCT predicate compares a value with another value or a set of values with another set of values.

LIKE Predicate

```
column-reference [NOT] LIKE { atom
                               special-register } [ESCAPE atom]
```

A LIKE predicate searches for strings that have a certain pattern.

See information on [column-reference](#), [atom](#) and [special-register](#).

NULL Predicate

```
column-reference IS [NOT] NULL
```

A NULL predicate tests for null values.

If the compiler option DB2ARRY is set to ON, it is possible to specify an Natural array or an fixed index range of an array as *atom*. The Natural SQL compiler will then decompose the array or fixed index range into a list of scalar host variables.

See information on [column-reference](#).

IN Predicate

$$\left\{ \begin{array}{l} \text{scalar-expression} \text{ [NOT] IN } \left\{ \begin{array}{l} \text{subquery} \\ \text{row-value-expression} \end{array} \right\} \\ \text{row-value-expression} \text{ [NOT] IN subquery} \end{array} \right\}$$

An IN predicate compares a value or a set of values with a collection of values.

See information on *scalar-expression*, *atom* and *special-register*.

See information on *subquery*.

Quantified Predicate

$$\left\{ \begin{array}{ll} \text{scalar-expression} & \text{comparison} \left\{ \begin{array}{l} \text{SOME} \\ \text{ANY} \\ \text{ALL} \end{array} \right\} \text{subquery} \\ \text{row-value-expression} & = \left\{ \begin{array}{l} \text{SOME} \\ \text{ANY} \end{array} \right\} \text{subquery} \\ \text{row-value-expression} & <> \text{ALL subquery} \end{array} \right\}$$

A quantified predicate compares a value or a set of values with a collection of values.

See information on *scalar-expression*, *comparison* and *subquery*.

EXISTS Predicate

EXISTS *subquery*

An EXISTS predicate tests for the existence of certain rows.

The EXISTS predicate evaluates to true only if the result of evaluating the *subquery* is not empty; that is, if there exists at least one record (row) in the FROM table of the *subquery* satisfying the search condition of the WHERE clause of this *subquery*.

Example of EXISTS:

```

DEFINE DATA LOCAL
1 #NAME      (A20)
END-DEFINE
...
SELECT NAME
  INTO #NAME
  FROM SQL-PERSONNEL
  WHERE EXISTS
    ( SELECT *
      FROM SQL-EMPLOYEES
      WHERE PERSNR > 1000
        AND NAME < 'L' )
    ...
END-SELECT
...

```

See information on [subquery](#).

XMLEXISTS Predicate

XMLEXISTS (<i>xquery-expression-constant</i> [BY REF PASSING <i>xquery-argument</i> ,...])

xquery-argument

{ <i>xquery-context-item-expression</i> <i>xquery-context-item-expression</i> AS <i>identifier</i> }

The XMLEXISTS predicate belongs to the Natural SQL Extended Set.

The XMLEXISTS predicate tests whether an XPATH expression returns a sequence of one or more items. For further information, see the IBM *DB2 XML Guide*.

9

Select Expressions

■ Selection	66
■ Table Expression	67

SELECT *selection table-expression*

A *select-expression* specifies a result table. It is used in the following Natural SQL statements:
[INSERT](#) | [SELECT](#) | [UPDATE](#)

Selection

[
 ALL
 DISTINCT
]

{
 {
 scalar-expression [[AS] *correlation-name*]
 }, ...
}

*

A *selection* specifies the columns of the result set tables to be selected.

Syntax Element Description:

Syntax Element	Description
ALL DISTINCT	Elimination of Duplicate Rows: Duplicate rows are not automatically eliminated from the result of a <i>select-expression</i> . To request this, specify the keyword <code>DISTINCT</code> . The alternative to <code>DISTINCT</code> is <code>ALL</code> . <code>ALL</code> is assumed if neither is specified.
<i>scalar-expression</i>	Scalar Expression: Instead of, or as well as, simple column names, a selection can also include general scalar expressions containing scalar operators and scalar functions which provide computed values (see also the section Scalar Expressions). Example: SELECT NAME, 65 - AGE FROM SQL-PERSONNEL ...
AS	The optional keyword <code>AS</code> introduces a <i>correlation-name</i> for a column.
<i>correlation-name</i>	Correlation Name: A <i>correlation-name</i> can be assigned to a <i>scalar-expression</i> as an alias name for a result column. The <i>correlation-name</i> need not be unique. If no <i>correlation-name</i> is specified for a result column, the corresponding <i>column-name</i> will be used (if the result column is derived from a column name; if not, the result table will have no name).

Syntax Element	Description
	The name of a result column may be used, for example, as column name in the ORDER BY clause of a SELECT statement.
*	Asterisk Notation: All columns of the result table are selected. Example: <pre>SELECT * FROM SQL-PERSONNEL, SQL-AUTOMOBILES . . .</pre>

Table Expression

from-clause [*where-clause*]

The *table-expression* specifies from where and according to what criteria rows are to be selected.

The following topics are covered below:

- FROM Clause
- Table Reference
- WHERE Clause
- GROUP BY Clause
- HAVING Clause
- ORDER BY Clause
- INPUT SEQUENCE
- ORDER OF table-designator
- FETCH FIRST Clause
- Examples of Table Expressions

FROM Clause

FROM *table-reference*,...

This clause specifies from which tables the result set is built.

Table Reference

```

{
  table-name [period-specification] [correlation-clause]
  [TABLE] subquery correlation-clause
  joined-table
  TABLE (function-name (scalar-expression,...)) correlation-clause
  data-change-table-reference [correlation-clause]
  xmltable-function correlation-clause
}

```

The tables specified in the `FROM` clause must contain the column fields used in the selection list.

You can either specify a single table or produce an intermediate table resulting from a subquery or a “join” operation (see below).

Since various tables (that is, DDMs) can be addressed in one `FROM` clause and since a *table-expression* can contain several `FROM` clauses if *subqueries* are specified, the database ID (DBID) of the first DDM specified in the first `FROM` clause of the whole expression is used to identify the underlying database involved.

TABLE function-name Clause

The `TABLE function-name` clause belongs to the [SQL Extended Set](#) and requires a *correlation-clause* with a *column-name* list.

Period Specification

The *period-specification* clause belongs to the [SQL Extended Set](#).

```

FOR { SYSTEM_TIME
      BUSINESS_TIME } { AS OF expr
                        FROM expr1 TO expr2
                        BETWEEN expr1 AND expr2 } ...

```

period-specification optionally specifies that a period specification applies to the temporal table *table-name*. The same period name (`SYSTEM_TIME` or `BUSINESS_TIME`) must not be specified more than one time for the same table.

Syntax Element	Description
FOR SYSTEM_TIME	Specifies that the <code>SYSTEM_TIME</code> period is used for the period-specification. <code>SYSTEM_TIME</code> must be a period that is defined in the table and the table must be a system-maintained temporal table that is defined with system data versioning.
FOR BUSINESS_TIME	Specifies that the <code>BUSINESS_TIME</code> period is used for the <i>period-specification</i> . <code>BUSINESS_TIME</code> must be a period that is defined in the table.

Syntax Element	Description
<i>expr, expr1, expr2</i>	Specify expressions that return a value of a built-in data type that is comparable to the data type of the columns of the specified period and must not contain a TIME ZONE.
AS OF <i>expr</i>	Specifies that the table includes each row for which the start value for the specified period is less than or equal to <i>expr</i> and the end value for the period is greater than <i>expr</i> .
FROM <i>expr1</i> TO <i>expr2</i>	Specifies that the table includes rows that exist for the period specified from <i>expr1</i> up to <i>expr2</i> . A row is included in the table if the start value for the period in the row is less than <i>expr2</i> and the end value for the period in the row is greater than <i>expr1</i> .
BETWEEN <i>expr1</i> AND <i>expr2</i>	Specifies that the table includes a row in which the specified period overlaps at any point in time between <i>expr1</i> and <i>expr2</i> . A row is included in the table if the start value for the period in the row is less than or equal to <i>expr2</i> and the end value for the period in the row is greater than <i>expr1</i> .

Optionally, a *correlation-clause* can be assigned to a *table-name*. For a *subquery*, a *correlation-clause* must be assigned.

Correlation Clause

```
[AS] correlation-name [(column-name,...)]
```

A *correlation-clause* consists of optional keyword AS and a *correlation-name* and is optionally followed by a plain *column-name* list. The *column-name* list belongs to the [SQL Extended Set](#).

Joined Table

```

{
  table-reference [ { { INNER
                     LEFT [OUTER]
                     RIGHT [OUTER]
                     FULL [OUTER]
                   } } ] JOIN table-reference ON join-condition
}
(joined-table)

```

A *joined-table* specifies an intermediate table resulting from a “join” operation.

The “join” can be an INNER, LEFT OUTER, RIGHT OUTER or FULL OUTER JOIN. If you do not specify anything, INNER applies.

Multiple “join” operations can be nested; that is, the tables which create the intermediate result table can themselves be intermediate result tables of a “join” operation or a *subquery*; and the latter, in turn, can also have a *joined-table* or another *subquery* in its FROM clause.

Join Condition

For INNER, LEFT OUTER, and RIGHT OUTER joins:

search-condition

For FULL OUTER joins:

full-join-expression = *full-join-expression* [AND ...]

Full Join Expression

$$\left\{ \begin{array}{l} \textit{column-name} \\ \left\{ \begin{array}{l} \text{VALUE} \\ \text{COALESCE} \end{array} \right\} (\textit{column-name}, \dots) \end{array} \right\}$$

Within a *join-expression* only *column-names* and the *scalar-function* VALUE (or its synonym COALESCE) are allowed.

See details on [column-name](#).

Data Change Table Reference

The *data-change-table-reference* clause belongs to the **SQL Extended Set**.

$$\left\{ \begin{array}{l} \text{FINAL TABLE} (\textit{INSERT-statement}) \\ \left\{ \begin{array}{l} \text{FINAL} \\ \text{OLD} \end{array} \right\} \text{TABLE} (\textit{searched-UPDATE-statement}) \\ \text{OLD TABLE} (\textit{searched-DELETE-statement}) \\ \text{FINAL TABLE} (\textit{MERGE-statement}) \end{array} \right\}$$

A *data-change-table-reference* specifies an intermediate result table, which is based on the rows that are changed by the SQL change statement specified in the clause. A *data-change-table-reference* can only be specified as the only table reference in the FROM clause.

Syntax Element Description:

Syntax Element	Description
FINAL TABLE	Specifies that the rows of the intermediate result table represent the set of rows that are changed by the SQL data change statement as they appear at the completion of the SQL data change statement.
OLD TABLE	Specifies that the rows of the intermediate result table represent the set of rows that are changed by the SQL data change statement as they exist prior to the application of the SQL data change statement.

XMLTABLE Function

The *xmltable-function* clause belongs to the [SQL Extended Set](#).

The item *xmltable-function* specifies an invocation of the built-in XMLTABLE function.

WHERE Clause

[WHERE *search-condition*]

The WHERE clause is used to specify the selection criteria (*search-condition*) for the rows to be selected.

Example:

```

DEFINE DATA LOCAL
01 NAME    (A20)
01 AGE     (I2)
END-DEFINE
...
SELECT *
  INTO NAME, AGE
  FROM SQL-PERSONNEL
  WHERE AGE = 32
END-SELECT
...

```

For further information, see [Search Conditions](#).

GROUP BY Clause

[GROUP BY *column-reference*,...]

The GROUP BY clause rearranges the table represented by the FROM clause into groups in a way that all rows within each group have the same value for the GROUP BY columns.

Each *column-reference* in the selection list must be either a GROUP BY column or specified within an *aggregate-function*. Aggregate functions are applied to the individual groups (not to the entire table). The result table contains as many rows as groups.

For further information, see [Column Reference](#) and [Aggregate Function](#).

Example:

```
DEFINE DATA LOCAL
1 #AGE      (I2)
1 #NUMBER   (I2)
END-DEFINE
...
SELECT AGE , COUNT(*)
      INTO #AGE, #NUMBER
      FROM SQL-PERSONNEL
      GROUP BY AGE
...
```

If the GROUP BY clause is preceded by a WHERE clause, all rows that do not satisfy the WHERE clause are excluded before any grouping is done.

HAVING Clause

[HAVING *search-condition*]

If the HAVING clause is specified, the GROUP BY clause should also be specified.

Just as the WHERE clause is used to exclude rows from a result table, the HAVING clause is used to exclude groups and therefore also based on a *search-condition*. Scalar expressions in a HAVING clause must be single-valued per group.

For further information, see [Scalar Expressions](#) and [Search Conditions](#).

Example:

```

DEFINE DATA LOCAL
1 #NAME      (A20)
1 #AVGAGE    (I2)
1 #NUMBER    (I2)
END-DEFINE
...
SELECT NAME, AVG(AGE), COUNT(*)
  INTO #NAME, #AVGAGE, #NUMBER
  FROM SQL-PERSONNEL
  GROUP BY NAME
  HAVING COUNT(*) > 1
  ...

```

ORDER BY Clause

ORDER BY	{	<i>sort-key</i> [ASC]	, ...	}
		DESC		
		INPUT SEQUENCE		
		ORDER OF <i>table-designator</i>		

The *order-by* clause specifies row ordering of the result table.

sort-key

{	<i>column-name</i>	}
	<i>integer</i>	
	<i>sort-key-expression</i>	

A *sort-key-expression* is an expression which is more than a *column-name* or an unsigned *integer* constant.

INPUT SEQUENCE

INPUT SEQUENCE belongs to the [SQL Extended Set](#).

INPUT SEQUENCE indicates that the result table reflects the input order of the rows specified in the VALUES clause of an INSERT statement.

INPUT SEQUENCE can only be specified if an INSERT statement is specified in the *from-clause*.

ORDER OF *table-designator*

ORDER OF *table-designator* belongs to the [SQL Extended Set](#).

ORDER OF specifies that the row ordering of the designated table by the *table-designator* is applied to the result table of the query.

table-designator uniquely identifies a base table, a view, or the nested table expression of a subselect.

FETCH FIRST Clause

The *fetch-first* clause belongs to the [SQL Extended Set](#).

$$\left[\text{FETCH FIRST } \left\{ \begin{array}{c} \underline{1} \\ integer \end{array} \right\} \left\{ \begin{array}{c} \text{ROWS} \\ \text{ROW} \end{array} \right\} \text{ ONLY} \right]$$

The *fetch-first* clause limits the number of rows that can be fetched. It improves the performance of queries when only a limited number of rows are needed.

Examples of Table Expressions

Example 1:

```
DEFINE DATA LOCAL
01 #NAME      (A20)
01 #FIRSTNAME (A15)
01 #AGE       (I2)
...
END-DEFINE
...
SELECT NAME, FIRSTNAME, AGE
  INTO #NAME, #FIRSTNAME, #AGE
  FROM SQL-PERSONNEL
    WHERE NAME IS NOT NULL
      AND AGE > 20
...
  DISPLAY #NAME #FIRSTNAME #AGE
END-SELECT
...
END
```

Example 2:


```
DEFINE DATA LOCAL
01 #COUNT      (I4)
...
END-DEFINE
...
SELECT SINGLE COUNT(*) INTO #COUNT FROM SQL-PERSONNEL
...
```


10

Flexible SQL

■ Using Flexible SQL	78
■ Specifying Text Variables in Flexible SQL	79

The so-called “Flexible SQL”, which is a further possibility of issuing SQL statements, enables you to use arbitrary SQL syntax.

Using Flexible SQL

In addition to the SQL syntax described in the previous sections, flexible SQL enables you to use arbitrary SQL syntax.

Characters << and >>

Flexible SQL is enclosed in << and >> characters. It can include arbitrary SQL text and host variables. Within flexible SQL, host variables *must* be prefixed by a colon (:).

The flexible SQL string can cover several statement lines. Comments are possible, too (see also the statement `PROCESS SQL`).

Flexible SQL can be used as a replacement for any of the following syntactical SQL items:

- *atom*
- *column-reference*
- *scalar-expression*
- *predicate*

Flexible SQL can also be used between the clauses of a select expression:

```
SELECT selection
  << ... >>
  INTO ...
  FROM ...
  << ... >>
  WHERE ...
  << ... >>
  GROUP BY ...
  << ... >>
  HAVING ...
  << ... >>
  ORDER BY ...
  << ... >>
```



Note: The SQL text used in flexible SQL is not recognized by the Natural compiler. The SQL text (with replaced host variables) is simply copied into the SQL string passed to the database system. Syntax errors in flexible SQL are detected at runtime when the database executes the corresponding statement.

Example 1

```
SELECT NAME
FROM SQL-EMPLOYEES
WHERE << MONTH (BIRTH) >> = << MONTH (CURRENT_DATE) >>
```

Example 2:

```
SELECT NAME
FROM SQL-EMPLOYEES
WHERE << MONTH (BIRTH) = MONTH (CURRENT_DATE) >>
```

Example 3:

```
SELECT NAME
FROM SQL-EMPLOYEES
WHERE SALARY > 50000
<< INTERSECT
  SELECT NAME
  FROM SQL-EMPLOYEES
  WHERE DEPT = 'DEPT10'
>>
```

Specifying Text Variables in Flexible SQL

Within flexible SQL, you can also specify so-called “text variables”.

```
<<:T:host-variable [LINDICATOR:host-variable]>>
```

The syntax items are described below:

:T:	A text variable is a <i>host-variable</i> prefixed by :T:. It must be in alphanumeric format. At runtime, a text variable within an SQL statement will be replaced by its contents that is, the text string contained in the text variable will be inserted into the SQL string. After the replacement, trailing blanks will be removed from the inserted text string. You have to make sure yourself that the content of a text variable results in a syntactically correct SQL string. In particular, the content of a text variable must not contain <i>host-variables</i>. A statement containing a text variable will always be executed in dynamic SQL mode.
LINDICATOR	LINDICATOR Option:

	The text variable can be followed by the keyword <code>LINDICATOR</code> and a length indicator variable (that is, a <i>host-variable</i> prefixed by colon). The length indicator variable has to be of format/length I2. If no <code>LINDICATOR</code> variable is specified, the entire content of the text variable will be inserted into the SQL string. If you specify a <code>LINDICATOR</code> variable, only the first n characters (n being the value of the <code>LINDICATOR</code> variable) of the text variable content will be inserted into the SQL string. If the number in the <code>LINDICATOR</code> variable is greater than the length of the text variable content, the entire text variable content will be inserted. If the number in the <code>LINDICATOR</code> variable is negative or 0, nothing will be inserted. See general information on <i>host-variable</i>.

Example Using Text Variable

```

DEFINE DATA LOCAL
  01 TEXTVAR (A200)
  01 TABLES VIEW OF SYSIBM-SYSTABLES
    02 NAME
    02 CREATOR
END-DEFINE
*
MOVE 'WHERE NAME > ''SYS'' AND CREATOR = ''SYSIBM''' TO TEXTVAR
*
SELECT * INTO VIEW TABLES
  FROM SYSIBM-SYSTABLES
  << :T:TEXTVAR >>
  DISPLAY TABLES
END-SELECT
*
END

```

The generated SQL statement (as displayed with the `LISTSQL` system command) will look as follows:

```
SELECT NAME, CREATOR FROM SYSIBM.SYSTABLES:T: FOR FETCH ONLY
```

The executed SQL statement will look as follows:

```
SELECT TABNAME, CREATOR FROM SYSIBM.SYSTABLES
WHERE TABNAME > 'SYS' AND CREATOR = 'SYSIBM'
```

III

Referenced Example Programs

11

Referenced Example Programs

▪ ASSIGN	84
▪ AT BREAK	85
▪ AT END OF DATA	87
▪ AT END OF PAGE	88
▪ AT START OF DATA	88
▪ AT TOP OF PAGE	90
▪ DEFINE SUBROUTINE	91
▪ FIND	92
▪ FOR	94
▪ HISTOGRAM	95
▪ IF	95
▪ PERFORM BREAK PROCESSING	97
▪ READ	98
▪ REPEAT	99
▪ SORT	100
▪ STORE	101
▪ UPDATE	103
▪ Example Programs for System Variables	104

This chapter contains additional example programs that are referenced in the Natural statements and system variables reference documentation. All these examples are contained in the library SYSEXSYN.



Note: Generally, the example programs shown in the statement descriptions are written in structured mode. For statements where the reporting-mode syntax differs considerably from the structured-mode syntax, references to equivalent reporting-mode examples are also provided. The example programs are available in source-code form in the Natural library SYSEXSYN. Further example programs of using Natural statements are documented in the section *Referenced Example Programs* in the *Programming Guide*. These example programs are provided in the Natural library SYSEXPG. Ask your Natural administrator about the availability of these libraries at your site. The example programs use data from the files EMPLOYEES and VEHICLES, which are supplied by Software AG for demonstration purposes.

ASSIGN

The following example is referenced in the [ASSIGN/COMPUTE](#) statement description:

ASGEX1R - ASSIGN (reporting mode)

```
** Example 'ASGEX1R': ASSIGN (reporting mode)
*****
RESET #A (N3)
      #B (A6)
      #C (N0.3)
      #D (N0.5)
      #E (N1.3)
      #F (N5)
      #G (A25)
      #H (A3/1:3)
*
#A = 5                                WRITE NOTITLE '=' #A
#B = 'ABC'                            WRITE '=' #B
#C = .45                              WRITE '=' #C
#D = #E = -0.12345                    WRITE '=' #D / '=' #E
ASSIGN ROUNDED #F = 199.999            WRITE '=' #F
#G = 'HELLO'                          WRITE '=' #G
*
#H (1) = 'UVW'                        WRITE '=' #H (1:3)
#H (3) = 'XYZ'
*
END
```

Output of Program AEDEX1R:

```
#A: 5
#B: ABC
#C: .450
#D: -.12345
#E: -0.123
#F: 200
#G: HELLO
#H: UVW XYZ
```

AT BREAK

The following examples are referenced in the [AT BREAK](#) statement description:

ATBEX1R - AT BREAK (reporting mode)

```
** Example 'ATBEX1R': AT BREAK (reporting mode)
*****
*
LIMIT 10
READ EMPLOYEES BY CITY
  AT BREAK OF CITY DO
    SKIP 1
  DOEND
/*
  DISPLAY NOTITLE CITY (IS=ON) COUNTRY (IS=ON) NAME
LOOP
END
```

Output of Program ATBEX1R:

CITY	COUNTRY	NAME
-----	-----	-----
AIKEN	USA	SENKO
AIX EN OTHE	F	GODEFROY
AJACCIO		CANALE
ALBERTSLUND	DK	PLOUG
ALBUQUERQUE	USA	HAMMOND ROLLING FREEMAN LINCOLN
ALFRETON	UK	GOLDBERG

ALICANTE E GOMEZ

ATBEX5R - AT BREAK statement with multiple break levels (reporting mode)

```
** Example 'ATBEX5R': AT BREAK (multiple break levels) (reporting mode)
*****
RESET LEAVE-DUE-L (N4)
*
LIMIT 5
FIND EMPLOYEES WITH CITY = 'PHILADELPHIA' OR = 'PITTSBURGH'
      SORTED BY CITY DEPT
      MOVE LEAVE-DUE TO LEAVE-DUE-L
      DISPLAY CITY (IS=ON) DEPT (IS=ON) NAME LEAVE-DUE-L
      AT BREAK OF DEPT
        WRITE NOTITLE /
          T*DEPT OLD(DEPT) T*LEAVE-DUE-L SUM(LEAVE-DUE-L) /
      AT BREAK OF CITY
        WRITE NOTITLE
          T*CITY OLD(CITY) T*LEAVE-DUE-L SUM(LEAVE-DUE-L) //
LOOP
*
END
```

Output of Program ATBEX5R:

CITY	DEPARTMENT CODE	NAME	LEAVE-DUE-L

PHILADELPHIA	MGMT30	WOLF-TERROINE	11
		MACKARNESS	27
	MGMT30		38
	TECH10	BUSH	39
		NETTLEFOLDS	24
	TECH10		63
			101
PITTSBURGH	MGMT10	FLETCHER	34
	MGMT10		34
PITTSBURGH			34

AT END OF DATA

The following example is referenced in the [AT END OF DATA](#) statement description:

AEDEX1R - AT END OF DATA (reporting mode)

```
** Example 'AEDEX1R': AT END OF DATA (reporting mode)
*****
LIMIT 5
EMP. FIND EMPLOYEES WITH CITY = 'STUTTGART'
  IF NO RECORDS FOUND
    ENTER
  DISPLAY PERSONNEL-ID NAME FIRST-NAME
    SALARY (1) CURR-CODE (1)
  /*
  AT END OF DATA DO
    IF *COUNTER (EMP.) = 0 DO
      WRITE 'NO RECORDS FOUND'
      ESCAPE BOTTOM
    DOEND
    WRITE NOTITLE / 'SALARY STATISTICS:'
      / 7X 'MAXIMUM:' MAX(SALARY(1)) CURR-CODE (1)
      / 7X 'MINIMUM:' MIN(SALARY(1)) CURR-CODE (1)
      / 7X 'AVERAGE:' AVER(SALARY(1)) CURR-CODE (1)
  DOEND
LOOP
END
```

Output of Program AEDEX1R:

PERSONNEL ID	NAME	FIRST-NAME	ANNUAL SALARY	CURRENCY CODE
11100328	BERGHAUS	ROSE	70800	DM
11100329	BARTHEL	PETER	42000	DM
11300313	AECKERLE	SUSANNE	55200	DM
11300316	KANTE	GABRIELE	61200	DM
11500304	KLUGE	ELKE	49200	DM
SALARY STATISTICS:				
	MAXIMUM:	70800	DM	
	MINIMUM:	42000	DM	
	AVERAGE:	55680	DM	

AT END OF PAGE

The following example is referenced in the [AT END OF PAGE](#) statement description:

AEPEX1R - AT END OF PAGE (reporting mode)

```
** Example 'AEPEX1R': AT END OF PAGE (reporting mode)
*****
FORMAT PS=10
LIMIT 10
READ EMPLOYEES BY PERSONNEL-ID FROM '20017000'
  DISPLAY NOTITLE GIVE SYSTEM FUNCTIONS
    NAME JOB-TITLE 'SALARY' SALARY(1) CURR-CODE (1)
  /*
  AT END OF PAGE DO
    WRITE / 28T 'AVERAGE SALARY: ...' AVER(SALARY(1)) CURR-CODE (1)
  DOEND
  /*
LOOP
END
```

Output of Program AEPEX1R:

NAME	CURRENT POSITION	SALARY	CURRENCY CODE

CREMER	ANALYST	34000	USD
MARKUSH	TRAINEE	22000	USD
GEE	MANAGER	39500	USD
KUNEY	DBA	40200	USD
NEEDHAM	PROGRAMMER	32500	USD
JACKSON	PROGRAMMER	33000	USD
AVERAGE SALARY: ...		33533	USD

AT START OF DATA

The following example is referenced in the [AT START OF DATA](#) statement description:

ASDEX1R - AT START OF DATA (reporting mode)

```

** Example 'ASDEX1R': AT START OF DATA (reporting mode)
*****
RESET #CITY (A20) #CNTL (A1)
*
REPEAT
  INPUT 'ENTER VALUE FOR CITY' #CITY
  /*
  IF #CITY = ' ' OR= 'END' DO
    STOP
  DOEND
  FIND EMPLOYEES WITH CITY = #CITY
  IF NO RECORDS FOUND DO
    WRITE NOTITLE NOHDR 'NO RECORDS FOUND'
    ESCAPE
  DOEND
  /*
  AT START OF DATA DO
    INPUT (AD=0) 'RECORDS FOUND' *NUMBER //
                          'ENTER ''D'' TO DISPLAY RECORDS' #CNTL (AD=A)
    IF #CNTL NE 'D' DO
      ESCAPE BOTTOM
    DOEND
  DOEND
  /*
  DISPLAY NAME FIRST-NAME
LOOP
LOOP
END

```

Output of Program ASDEX1R:

```
ENTER VALUE FOR CITY PARIS
```

After entering and confirming city name:

```
RECORDS FOUND          26
ENTER 'D' TO DISPLAY RECORDS D
```

After entering and confirming D:

NAME	FIRST-NAME
MAIZIERE	ELISABETH
MARX	JEAN-MARIE
REIGNARD	JACQUELINE
RENAUD	MICHEL
REMOUE	GERMAINE
LAVENDA	SALOMON
BROUSSE	GUY
GIORDA	LOUIS
SIECA	FRANCOIS
CENSIER	BERNARD
DUC	JEAN-PAUL
CAHN	RAYMOND
MAZUY	ROBERT
FAURIE	HENRI
VALLY	ALAIN
BRETON	JEAN-MARIE
GIGLEUX	JACQUES
KORAB-BRZOZOWSKI	BOGDAN
XOLIN	CHRISTIAN
LEGRIS	ROGER
VVVV	

AT TOP OF PAGE

The following example is referenced in the [AT TOP OF PAGE](#) statement description:

ATPEX1R - AT TOP OF PAGE (reporting mode)

```

** Example 'ATPEX1R': AT TOP OF PAGE (reporting mode)
*****
*
FORMAT PS=15
LIMIT 15
*
READ EMPLOYEES BY NAME STARTING FROM 'L'
  DISPLAY 2X NAME 4X FIRST-NAME CITY DEPT
  WRITE TITLE UNDERLINED 'EMPLOYEE REPORT'
  WRITE TRAILER '-' (78)
/*
  AT TOP OF PAGE DO
    WRITE 'BEGINNING NAME:' NAME
  DOEND
/*
  AT END OF PAGE DO
    SKIP 1
    WRITE 'ENDING NAME:  ' NAME

```



```
DOEND
LOOP
END
```

DEFINE SUBROUTINE

The following example is referenced in the [DEFINE SUBROUTINE](#) statement description:

DSREX1R - DEFINE SUBROUTINE (reporting mode)

```
** Example 'DSREX1R': DEFINE SUBROUTINE (reporting mode)
*****
RESET #ARRAY-ALL (A300)
    #X (N2) #Y (N2)
REDEFINE #ARRAY-ALL (#ARRAY (A75/1:4))
    #ARRAY-ALL (#ALINE (A25/1:4,1:3))
*
FORMAT PS=20
LIMIT 5
*
MOVE 1 TO #X #Y
*
FIND EMPLOYEES WITH NAME = 'SMITH'
    OBTAIN ADDRESS-LINE (1:2)
    /*
    MOVE NAME                TO #ALINE (#X,#Y)
    MOVE ADDRESS-LINE(1) TO #ALINE (#X+1,#Y)
    MOVE ADDRESS-LINE(2) TO #ALINE (#X+2,#Y)
    MOVE PHONE              TO #ALINE (#X+3,#Y)
    IF #Y = 3 DO
        MOVE 1 TO #Y
        PERFORM PRINT
    DOEND
    ELSE DO
        ADD 1 TO #Y
    DOEND
    AT END OF DATA DO
        PERFORM PRINT
    DOEND
LOOP
*
DEFINE SUBROUTINE PRINT
    WRITE NOTITLE (AD=OI) #ARRAY(*)
    RESET #ARRAY(*)
    SKIP 1
RETURN
*
END
```

Output of Program AEDEX1R:

SMITH ENGLANDSVEJ 222 554349	SMITH 3152 SHETLAND ROAD MILWAUKEE 877-4563	SMITH 14100 ESWORTHY RD. MONTERREY 994-2260
SMITH 5 HAWTHORN OAK BROOK 150-9351	SMITH 13002 NEW ARDEN COUR SILVER SPRING 639-8963	

FIND

The following examples are referenced in the [FIND](#) statement description:

FNDFIR - FIND statement with FIRST option (reporting mode)

```

** Example 'FNDFIR': FIND FIRST
*****
*
FIND FIRST EMPLOYEES WITH CITY = 'DERBY'
*
WRITE NOTITLE 'TOTAL RECORDS SELECTED:' *NUMBER
SKIP 2
WRITE '***FIRST PERSON SELECTED***' //
      'NAME:      ' NAME /
      'DEPARTMENT:' DEPT /
      'JOB TITLE: ' JOB-TITLE
*
END

```

Output of Program FNDFIR:

```

TOTAL RECORDS SELECTED:      141

***FIRST PERSON SELECTED***

NAME:      DEAKIN
DEPARTMENT: SALE01
JOB TITLE:  SALES ACCOUNTANT

```

FNDNUM - FIND statement with NUMBER option (reporting mode)

```

** Example 'FNDNUM': FIND NUMBER
*****
RESET #BIRTH (D)
*
MOVE EDITED '19500101' TO #BIRTH (EM=YYYYMMDD)
*
FIND NUMBER EMPLOYEES WITH CITY = 'MADRID'
      WHERE BIRTH LT #BIRTH
*
WRITE NOTITLE 'TOTAL RECORDS SELECTED:      ' *NUMBER
      / 'TOTAL BORN BEFORE 1 JAN 1950: ' *COUNTER
*
END

```

Output of Program FNDNUM:

```

TOTAL RECORDS SELECTED:      41
TOTAL BORN BEFORE 1 JAN 1950: 16

```

FNDUNQ - FIND statement with UNIQUE option (reporting mode)

```

** Example 'FNDUNQ': FIND UNIQUE
*****
RESET #NAME (A20)
*
*
INPUT 'ENTER EMPLOYEE NAME: ' #NAME
IF #NAME = ' '
    STOP
*
FIND UNIQUE EMPLOYEES WITH NAME = #NAME
*
DISPLAY NOTITLE NAME FIRST-NAME JOB-TITLE
*
ON ERROR DO
    WRITE 'NAME EITHER NOT UNIQUE OR DOES NOT EXIST'
    FETCH 'FNDUNQ'
DOEND
*
END

```

Output of Program FNDUNQ:

ENTER EMPLOYEE NAME: HEURTEBISE

After entering and confirming name HEURTEBISE:

NAME	FIRST-NAME	CURRENT POSITION
HEURTEBISE	MICHEL	CONTROLEUR DE GESTION

FOR

The following example is referenced in the [FOR](#) statement description:

FOREX1R - FOR (reporting mode)

```
** Example 'FOREX1R': FOR (reporting mode)
*****
RESET #INDEX (I1)
      #ROOT (N2.7)
*
FOR #INDEX 1 TO 5
  COMPUTE #ROOT = SQRT (#INDEX)
  WRITE NOTITLE '=' #INDEX 3X '=' #ROOT
LOOP
*
SKIP 1
FOR #INDEX 1 TO 5 STEP 2
  COMPUTE #ROOT = SQRT (#INDEX)
  WRITE '=' #INDEX 3X '=' #ROOT
LOOP
*
END
```

Output of Program FOREX1R:

```
#INDEX:    1  #ROOT:    1.0000000
#INDEX:    2  #ROOT:    1.4142135
#INDEX:    3  #ROOT:    1.7320508
#INDEX:    4  #ROOT:    2.0000000
#INDEX:    5  #ROOT:    2.2360679

#INDEX:    1  #ROOT:    1.0000000
#INDEX:    3  #ROOT:    1.7320508
#INDEX:    5  #ROOT:    2.2360679
```

HISTOGRAM

The following example is referenced in the [HISTOGRAM](#) statement description:

HSTEX1R - HISTOGRAM (reporting mode)

```
** Example 'HSTEX1R': HISTOGRAM (reporting mode)
*****
*
LIMIT 8
HISTOGRAM EMPLOYEES CITY STARTING FROM 'M'
  DISPLAY NOTITLE CITY
    'NUMBER OF/PERSONS' *NUMBER *COUNTER
LOOP
*
END
```

Output of Program HSTEX1R:

CITY	NUMBER OF PERSONS	CNT
-----	-----	-----
MADISON	3	1
MADRID	41	2
MAILLY LE CAMP	1	3
MAMERS	1	4
MANSFIELD	4	5
MARSEILLE	2	6
MATLOCK	1	7
MELBOURNE	2	8

IF

The following example is referenced in the [IF](#) statement description:

IFEX1R - IF (reporting mode)

```
** Example 'IFEX1R': IF (reporting mode)
*****
RESET #BIRTH (D)
*
MOVE EDITED '19450101' TO #BIRTH (EM=YYYYMMDD)
SUSPEND IDENTICAL SUPPRESS
LIMIT 20
*
FND. FIND EMPLOYEES WITH CITY = 'FRANKFURT'
      SORTED BY NAME BIRTH
  IF SALARY (1) LT 40000
    WRITE NOTITLE '*****' NAME 30X 'SALARY LT 40000'
  ELSE DO
    IF BIRTH GT #BIRTH DO
      FIND VEHICLES WITH PERSONNEL-ID = PERSONNEL-ID (FND.)
      DISPLAY (IS=ON) NAME BIRTH (EM=YYYY-MM-DD)
      SALARY (1) MAKE (AL=8)
    LOOP
  DOEND
DOEND
LOOP
END
```

Output of Program IFEX1R:

NAME	DATE OF BIRTH	ANNUAL SALARY	MAKE
BAECKER	1956-01-05	74400	BMW
***** BECKER			SALARY LT 40000
BLOEMER	1979-11-07	45200	FIAT
FALTER	1954-05-23	70800	FORD
***** FALTER			SALARY LT 40000
***** GROTHE			SALARY LT 40000
***** HEILBROCK			SALARY LT 40000
***** HESCHMANN			SALARY LT 40000
HUCH	1952-09-12	67200	MERCEDES
***** KICKSTEIN			SALARY LT 40000
***** KLEENE			SALARY LT 40000
***** KRAMER			SALARY LT 40000

PERFORM BREAK PROCESSING

The following example is referenced in the [PERFORM BREAK PROCESSING](#) statement description:

PBPEX1R - PERFORM BREAK PROCESSING (reporting mode)

```

** Example 'PBPEX1R': PERFORM BREAK PROCESSING (reporting mode)
*****
RESET #LINE (N2) #INDEX (N2)
*
MOVE 1 TO #LINE
FOR #INDEX 1 TO 18
  PERFORM BREAK PROCESSING
  /*
  AT BREAK OF #INDEX /1/ DO
    WRITE NOTITLE / 'PLEASE COMPLETE LINES 1-9 ABOVE' /
    MOVE 1 TO #LINE
  DOEND
  /*
  WRITE NOTITLE '_' (64) '=' #LINE
  ADD 1 TO #LINE
LOOP
END

```

Output of Program PBPEX1R:

```

#LINE: 1
#LINE: 2
#LINE: 3
#LINE: 4
#LINE: 5
#LINE: 6
#LINE: 7
#LINE: 8
#LINE: 9

PLEASE COMPLETE LINES 1-9 ABOVE

#LINE: 1
#LINE: 2
#LINE: 3
#LINE: 4
#LINE: 5
#LINE: 6
#LINE: 7
#LINE: 8
#LINE: 9

PLEASE COMPLETE LINES 1-9 ABOVE

```

READ

The following example is referenced in the [READ](#) statement description:

REAEX1R - READ (reporting mode)

```
** Example 'REAEX1R': READ (reporting mode)
*****
LIMIT 3
*
WRITE 'READ IN PHYSICAL SEQUENCE'
READ EMPLOYEES IN PHYSICAL SEQUENCE
  DISPLAY NOTITLE PERSONNEL-ID NAME *ISN *COUNTER
LOOP
*
WRITE / 'READ IN ISN SEQUENCE'
READ EMPLOYEES BY ISN STARTING FROM 1 ENDING AT 3
  DISPLAY PERSONNEL-ID NAME *ISN *COUNTER
LOOP
*
WRITE / 'READ IN NAME SEQUENCE'
READ EMPLOYEES BY NAME
  DISPLAY PERSONNEL-ID NAME *ISN *COUNTER
LOOP
*
WRITE / 'READ IN NAME SEQUENCE STARTING FROM 'M''
READ EMPLOYEES BY NAME STARTING FROM 'M'
  DISPLAY PERSONNEL-ID NAME *ISN *COUNTER
LOOP
*
END
```

Output of Program REAEX1R:

PERSONNEL ID	NAME	ISN	CNT

READ IN PHYSICAL SEQUENCE			
50005800	ADAM	1	1
50005600	MORENO	2	2
50005500	BLOND	3	3
READ IN ISN SEQUENCE			
50005800	ADAM	1	1
50005600	MORENO	2	2
50005500	BLOND	3	3
READ IN NAME SEQUENCE			

60008339	ABELLAN	478	1
30000231	ACHIESON	878	2
50005800	ADAM	1	3
READ IN NAME SEQUENCE STARTING FROM 'M'			
30008125	MACDONALD	923	1
20028700	MACKARNESS	765	2
40000045	MADSEN	508	3

REPEAT

The following examples are referenced in the [REPEAT](#) statement description:

RPTEX1R - REPEAT (reporting mode)

```
** Example 'RPTEX1R': REPEAT (reporting mode)
*****
RESET #PERS-NR (A8)
*
REPEAT
  INPUT 'ENTER A PERSONNEL NUMBER:' #PERS-NR
  IF #PERS-NR = ' '
    ESCAPE BOTTOM
  FIND EMPLOYEES WITH PERSONNEL-ID = #PERS-NR
  IF NO RECORD FOUND
    REINPUT 'NO RECORD FOUND'
  DISPLAY NOTITLE NAME
LOOP
LOOP
*
END
```

Output of Program RPTEX1R:

```
ENTER A PERSONNEL NUMBER:
```

RPTEX2R - REPEAT with WHILE and UNTIL option (reporting mode)

```
** Example 'RPTEX2R': REPEAT (with WHILE and UNTIL option)
*****
RESET #X (I1) #Y (I1)
*
*
REPEAT WHILE #X <= 5
  ADD 1 TO #X
  WRITE NOTITLE '=' #X
LOOP
*
```

```
SKIP 3
REPEAT
  ADD 1 TO #Y
  WRITE '=' #Y
  UNTIL #Y = 6
LOOP
*
```

Output of Program RPTX2R:

```
#X: 1
#X: 2
#X: 3
#X: 4
#X: 5
#X: 6
```

```
#Y: 1
#Y: 2
#Y: 3
#Y: 4
#Y: 5
#Y: 6
```

SORT

The following example is referenced in the [SORT](#) statement description:

SRTEX1R - SORT (reporting mode)

```
** Example 'SRTEX1R': SORT (reporting mode)
*****
RESET #AVG (P11) #TOTAL-TOTAL (P11) #TOTAL-SALARY (P11)
      #AVER-PERCENT (N3.2)
*
LIMIT 3
FIND EMPLOYEES WITH CITY = 'BOSTON'
  OBTAIN SALARY(1:2)
  COMPUTE #TOTAL-SALARY = SALARY (1) + SALARY (2)
  ACCEPT IF #TOTAL-SALARY GT 0
/*
  SORT BY PERSONNEL-ID USING #TOTAL-SALARY SALARY(*) CURR-CODE
  GIVE AVER(#TOTAL-SALARY)
/*
AT START OF DATA DO
```

```

    WRITE NOTITLE '*' (40)
        'AVG CUMULATIVE SALARY:' *AVER (#TOTAL-SALARY) /
    MOVE *AVER (#TOTAL-SALARY) TO #AVG
DOEND
COMPUTE ROUNDED #AVER-PERCENT = #TOTAL-SALARY / #AVG * 100
ADD #TOTAL-SALARY TO #TOTAL-TOTAL
/*
DISPLAY NOTITLE PERSONNEL-ID SALARY (1) SALARY (2)
        #TOTAL-SALARY CURR-CODE (1)
        'PERCENT/OF/AVER' #AVER-PERCENT
AT END OF DATA
    WRITE / '*' (40) 'TOTAL SALARIES PAID: ' #TOTAL-TOTAL
LOOP
*
END

```

Output of Program SRTEX1R:

PERSONNEL ID	ANNUAL SALARY	ANNUAL SALARY	#TOTAL-SALARY	CURRENCY CODE	PERCENT OF AVER

***** AVG CUMULATIVE SALARY:					44633
20000100	31000	29400	60400	USD	135.30
20019200	18000	17100	35100	USD	78.60
20020400	20000	18400	38400	USD	86.00
***** TOTAL SALARIES PAID:					133900

STORE

The following example is referenced in the [STORE](#) statement description:

STOEX1R - STORE (reporting mode)

```

** Example 'STOEX1R': STORE (reporting mode)
**
** CAUTION: Executing this example will modify the database records!
*****
RESET #PERSONNEL-ID (A8)
    #NAME (A20)
    #FIRST-NAME (A15)
    #BIRTH-D (D)
    #MAR-STAT (A1)
    #BIRTH (A8)
    #CITY (A20)

```

```

        #COUNTRY      (A3)
        #CONF         (A1)
*
REPEAT
    INPUT 'ENTER A PERSONNEL ID AND NAME (OR ''END'' TO END)' //
        'PERSONNEL-ID : ' #PERSONNEL-ID //
        'NAME          : ' #NAME          /
        'FIRST-NAME    : ' #FIRST-NAME

    /*
    /*  VALIDATE ENTERED DATA
    /*
    IF #PERSONNEL-ID = 'END' OR #NAME = 'END'
        STOP
    IF #NAME = ' '
        REINPUT WITH TEXT 'ENTER A LAST-NAME' MARK 2 AND SOUND ALARM
    IF #FIRST-NAME = ' '
        REINPUT WITH TEXT 'ENTER A FIRST-NAME' MARK 3 AND SOUND ALARM
    /*
    /*  ENSURE PERSON IS NOT ALREADY ON FILE
    /*
    FIND NUMBER EMPLOYEES WITH PERSONNEL-ID = #PERSONNEL-ID
    IF *NUMBER > 0
        REINPUT 'PERSON WITH SAME PERSONNEL-ID ALREADY EXISTS'
            MARK 1 AND SOUND ALARM
    MOVE 'N' TO #CONF
    /*
    /*  GET FURTHER INFORMATION
    /*
    INPUT
        'ADDITIONAL PERSONNEL DATA'          ////
        'PERSONNEL-ID          : ' #PERSONNEL-ID (AD=IO) /
        'NAME                  : ' #NAME          (AD=IO) /
        'FIRST-NAME            : ' #FIRST-NAME    (AD=IO) ///
        'MARITAL STATUS        : ' #MAR-STAT      /
        'DATE OF BIRTH (YYYYMMDD) : ' #BIRTH      /
        'CITY                  : ' #CITY          /
        'COUNTRY (3 CHARACTERS) : ' #COUNTRY      //
        'ADD THIS RECORD (Y/N)   : ' #CONF        (AD=M)

    /*
    /*  ENSURE REQUIRED FIELDS CONTAIN VALID DATA
    /*
    IF NOT (#MAR-STAT = 'S' OR = 'M' OR = 'D' OR = 'W')
        REINPUT TEXT 'ENTER VALID MARITAL STATUS S=SINGLE ' -
            'M=MARRIED D=DIVORCED W=WIDOWED' MARK 1
    IF NOT (#BIRTH = MASK(YYYYMMDD) AND #BIRTH = MASK(1582-2699))
        REINPUT TEXT 'ENTER CORRECT DATE' MARK 2
    IF #CITY = ' '
        REINPUT TEXT 'ENTER A CITY NAME' MARK 3
    IF #COUNTRY = ' '
        REINPUT TEXT 'ENTER A COUNTRY CODE' MARK 4
    IF NOT (#CONF = 'N' OR = 'Y')
        REINPUT TEXT 'ENTER Y (YES) OR N (NO)' MARK 5

```

```

IF #CONF = 'N'
  ESCAPE TOP
/*
/*  ADD THE RECORD
/*
MOVE EDITED #BIRTH TO #BIRTH-D (EM=YYYYMMDD)
/*
STORE RECORD IN EMPLOYEES
  WITH PERSONNEL-ID = #PERSONNEL-ID
      NAME           = #NAME
      FIRST-NAME     = #FIRST-NAME
      MAR-STAT       = #MAR-STAT
      BIRTH          = #BIRTH-D
      CITY           = #CITY
      COUNTRY        = #COUNTRY
END OF TRANSACTION
/*
WRITE NOTITLE 'RECORD HAS BEEN ADDED'
/*
LOOP
END

```

UPDATE

The following example is referenced in the [UPDATE](#) statement description:

UPDEX1R - UPDATE (reporting mode)

```

** Example 'UPDEX1R': UPDATE (reporting mode)
**
** CAUTION: Executing this example will modify the database records!
*****
RESET #NAME (A20)
*
INPUT 'ENTER A NAME:' #NAME (AD=M)
IF #NAME = ' '
  STOP
*
FIND EMPLOYEES WITH NAME = #NAME
IF NO RECORDS FOUND
  REINPUT WITH 'NO RECORDS FOUND'  MARK 1
/*
INPUT 'NAME:      ' NAME (AD=0) /
      'FIRST NAME:' FIRST-NAME (AD=M) /
      'CITY:      ' CITY (AD=M)
/*
UPDATE USING SAME RECORD
/*
END TRANSACTION

```

```
/*
LOOP
*
END
```

Output of Program UPDEX1R:

```
ENTER A NAME:
```

Example Programs for System Variables

The following examples are referenced in the *OCCURRENCE system variable description:

OCC1P - System Variable *OCCURRENCE

```
** Example 'OCC1P': *OCCURRENCE
*****
DEFINE DATA LOCAL
1 #N1 (N7/1:10)
1 #N2 (N7/1:10,1:10)
1 #N3 (N7/1:10,1:10,1:10)
END-DEFINE
*
CALLNAT 'OCC1N' #N1(*) #N2(1:2,1:4) #N3(1:6,1:7,1:8)
*
END
```

Subprogram OCC1N Called by Program OCC1P:

```
** Example 'OCC1N': *OCCURRENCE (called by OCC1P)
*****
DEFINE DATA
PARAMETER
1 PARM1 (N7/1:V)
1 PARM2 (N7/1:V,1:V)
1 PARM3 (N7/1:V,1:V,1:V)
LOCAL
1 #OCC2 (I4/1:2)
1 #OCC3 (I4/1:3)
1 #OCC1 (I4)
END-DEFINE
*
MOVE *OCC(PARM1) TO #OCC1
MOVE *OCC(PARM2,*) TO #OCC2(*)
MOVE *OCC(PARM3,*) TO #OCC3(*)
*
DISPLAY #OCC1 #OCC2(*) #OCC3(*)
DISPLAY *OCC(PARM1,*) *OCC(PARM2,*) *OCC(PARM3,*)
```

```

*
NEWPAGE
*
WRITE NOHDR
    'Occurrences of 1. parameter:' *OCC(PARM1)
    / 'Occurrences of 1. parameter:' *OCC(PARM1,1)
    / 'Occurrences of 1. parameter:' *OCC(PARM1,*)
    / 'Occurrences of 2. parameter:' *OCC(PARM2,1) *OCC(PARM2,2)
    / 'Occurrences of 2. parameter:' *OCC(PARM2,*)
    / 'Occurrences of 3. parameter:' *OCC(PARM3,1) *OCC(PARM3,2)
    *OCC(PARM3,3)
    / 'Occurrences of 3. parameter:' *OCC(PARM3,*)
*
END

```

Output of Program OCC1P - Page 1:

Page	1			05-01-18	10:21:30
#OCC1	#OCC2	#OCC3			

10	2	6			
	4	7			
		8			
10	2	6			
	4	7			
		8			

Output of Program OCC1P - Page 2:

Page	2			05-01-18	10:21:30
Occurrences of 1. parameter:	10				
Occurrences of 1. parameter:	10				
Occurrences of 1. parameter:	10				
Occurrences of 2. parameter:	2	4			
Occurrences of 2. parameter:	2	4			
Occurrences of 3. parameter:	6	7	8		
Occurrences of 3. parameter:	6	7	8		

OCC2P - System Variable *OCCURRENCE

```
** Example 'OCC2P': *OCCURRENCE
*****
DEFINE DATA LOCAL
1 #N (N7/1:10)
1 #I (I4)
END-DEFINE
*
FOR #I=1 TO 10
    MOVE #I TO #N(#I)
END-FOR
*
WRITE 'Passing occurrences 1:5'
CALLNAT 'OCC2N' #N(1:5)
*
WRITE 'Passing occurrences 5:10'
CALLNAT 'OCC2N' #N(5:10)
*
END
```

Subprogram OCC2N Called by Program OCC2P:

```
** Example 'OCC2N': *OCCURRENCE (called by OCC2P)
*****
DEFINE DATA
PARAMETER
1 #ARR (N7/1:V)
LOCAL
1 I (N7)
END-DEFINE
*
FOR I=1 TO *OCC(#ARR)
    DISPLAY #ARR(I)
END-FOR
*
END
```

Output of Program OCC2P:

```
Page          1                                05-01-18  10:33:03

Passing occurrences 1:5
    1
    2
    3
    4
    5
Passing occurrences 5:10
    5
    6
```


7
8
9
10

IV

■ 12 ACCEPT/REJECT	111
■ 13 ADD	117
■ 14 ASSIGN	123
■ 15 AT BREAK	125
■ 16 AT END OF DATA	133
■ 17 AT END OF PAGE	139
■ 18 AT START OF DATA	147
■ 19 AT TOP OF PAGE	153
■ 20 BACKOUT TRANSACTION	159
■ 21 BEFORE BREAK PROCESSING	163
■ 22 CALL	167
■ 23 CALL FILE	193
■ 24 CALL LOOP	199
■ 25 CALldbPROC (SQL)	203
■ 26 CALLNAT	209
■ 27 CLOSE CONVERSATION	217

12

ACCEPT/REJECT

■ Function	112
■ Syntax Description	112
■ Processing of Multiple ACCEPT/REJECT Statements	113
■ Limit Notation	113
■ Hold Status	114
■ Examples	114

{

ACCEPT
REJECT

}

[IF] *logical-condition*

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [AT BREAK](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [DELETE](#) | [END TRANSACTION](#) | [FIND](#) | [HISTOGRAM](#) | [GET](#) | [GET SAME](#) | [GET TRANSACTION DATA](#) | [LIMIT](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [RETRY](#) | [STORE](#) | [UPDATE](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The statements [ACCEPT](#) and [REJECT](#) are used for accepting/rejecting a record based on user-specified logical criterion. The [ACCEPT/REJECT](#) statement may be used in conjunction with statements which read data records in a processing loop ([FIND](#), [READ](#), [HISTOGRAM](#), [CALL FILE](#), [SORT](#) or [READ WORK FILE](#)). The criterion is evaluated *after* the record has been selected/read.

Whenever an [ACCEPT/REJECT](#) statement is encountered for processing, it will internally refer to the innermost currently active processing loop initiated with one of the above mentioned statements.

When [ACCEPT/REJECT](#) statements are placed in a subroutine, in case of a record reject, the subroutine(s) entered in the processing loop will automatically be terminated and processing will continue with the next record of the innermost currently active processing loop.

Syntax Description

Syntax Element	Description
IF	IF Clause: An IF clause may be used with an ACCEPT or REJECT statement to specify logical condition criteria in addition to that specified when the record was selected/read with a FIND , READ , or HISTOGRAM statement. The logical condition criteria are evaluated after the record has been read and after record processing has started.
<i>logical-condition</i>	Logical Condition Criterion: The basic criterion is a relational expression. Multiple relational expressions may be combined with logical operators (AND, OR) to form complex criteria. Arithmetic expressions may also be used to form a relational expression.

Syntax Element	Description
	The fields used to specify the logical criterion may be database fields or user-defined variables. For additional information on logical conditions, see <i>Logical Condition Criteria</i> in the <i>Programming Guide</i>. Note: When ACCEPT/REJECT is used with a HISTOGRAM statement, only the database field specified in the HISTOGRAM statement may be used as a logical criterion.

Processing of Multiple ACCEPT/REJECT Statements

Normally, only one ACCEPT or REJECT statement is required in a single processing loop. If more than one ACCEPT/REJECT is specified *consecutively*, the following conditions apply:

- If consecutive ACCEPT and REJECT statements are contained in the same processing loop, they are processed in the specified order.
- If an ACCEPT condition is satisfied, the record will be accepted and consecutive ACCEPT/REJECT statements will be ignored.
- If a REJECT condition is satisfied, the record will be rejected and consecutive ACCEPT/REJECT statements will be ignored.
- If the processing continues to the last ACCEPT/REJECT statement, the last statement will determine whether the record is accepted or rejected.

If other statements are interleaved between multiple ACCEPT/REJECT statements, each ACCEPT/REJECT will be handled independently.

Limit Notation

If a LIMIT statement or other limit notation has been specified for a processing loop containing an ACCEPT or REJECT statement, each record processed is counted against the limit regardless of whether or not the record is accepted or rejected.

Hold Status

ACCEPT/REJECT processing does not cause a held record to be released from hold status unless the profile parameter RI (Release ISNs) has been set to RI=ON.

Examples

- [Example 1 - ACCEPT](#)
- [Example 2 - ACCEPT / REJECT](#)

Example 1 - ACCEPT

```
** Example 'ACREX1': ACCEPT
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 SEX
  2 MAR-STAT
END-DEFINE
*
LIMIT 50
READ EMPLOY-VIEW
  ACCEPT IF SEX='M' AND MAR-STAT = 'S'
  WRITE  NOTITLE '=' NAME '=' SEX 5X '=' MAR-STAT
END-READ
END
```

Output of Program ACREX1:

NAME: MORENO	S E X: M	MARITAL STATUS: S
NAME: VAUZELLE	S E X: M	MARITAL STATUS: S
NAME: BAILLET	S E X: M	MARITAL STATUS: S
NAME: HEURTEBISE	S E X: M	MARITAL STATUS: S
NAME: LION	S E X: M	MARITAL STATUS: S
NAME: DEZELUS	S E X: M	MARITAL STATUS: S
NAME: BOYER	S E X: M	MARITAL STATUS: S
NAME: BROUSSE	S E X: M	MARITAL STATUS: S
NAME: DROMARD	S E X: M	MARITAL STATUS: S
NAME: DUC	S E X: M	MARITAL STATUS: S
NAME: BEGUERIE	S E X: M	MARITAL STATUS: S
NAME: FOREST	S E X: M	MARITAL STATUS: S
NAME: GEORGES	S E X: M	MARITAL STATUS: S

Example 2 - ACCEPT / REJECT

```

** Example 'ACREX2': ACCEPT/REJECT
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 FIRST-NAME
  2 SALARY      (1)
*
1 #PROC-COUNT (N8) INIT <0>
END-DEFINE
*
EMP. FIND EMPLOY-VIEW WITH NAME = 'JACKSON'
  WRITE NOTITLE *COUNTER NAME FIRST-NAME 'SALARY:' SALARY(1)
  /*
  ACCEPT IF SALARY (1) LT 50000
  WRITE *COUNTER 'ACCEPTED FOR FURTHER PROCESSING'
  /*
  REJECT IF SALARY (1) GT 30000
  WRITE *COUNTER 'NOT REJECTED'
  /*
  ADD 1 TO #PROC-COUNT
END-FIND
*
SKIP 2
WRITE NOTITLE 'TOTAL PERSONS FOUND ' *NUMBER (EMP.) /
              'TOTAL PERSONS SELECTED' #PROC-COUNT
END

```

Output of Program ACREX2:

1 JACKSON	CLAUDE	SALARY:	33000
1	ACCEPTED FOR FURTHER PROCESSING		
2 JACKSON	FORTUNA	SALARY:	36000
2	ACCEPTED FOR FURTHER PROCESSING		
3 JACKSON	CHARLIE	SALARY:	23000
3	ACCEPTED FOR FURTHER PROCESSING		
3	NOT REJECTED		
TOTAL PERSONS FOUND	3		
TOTAL PERSONS SELECTED	1		

13

ADD

■ Function	118
■ Syntax 1 - ADD Statement without GIVING Clause	118
■ Syntax 2 - ADD Statement with GIVING Clause	119
■ Example	121

Related Statements: [COMPRESS](#) | [COMPUTE](#) | [DIVIDE](#) | [EXAMINE](#) | [MOVE](#) | [MOVE ALL](#) | [MULTIPLY](#) | [RESET](#) | [SEPARATE](#) | [SUBTRACT](#)

Belongs to Function Group: *Arithmetic and Data Movement Operations*

Function

The `ADD` statement is used to add two or more operands.

This statements has two different syntax structures.

 Notes:

1. At the time the `ADD` statement is executed, each operand used in the arithmetic operation must contain a valid value.
2. For additions involving arrays, see also the section *Arithmetic Operations with Arrays*.
3. As for the formats of the operands, see also the section *Performance Considerations for Mixed Formats*.

Syntax 1 - ADD Statement without GIVING Clause

ADD [\[ROUNDED\]](#) { *(arithmetic-expression)* } ... TO *operand2*
operand1

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Operand Definition Table (Syntax 1):

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S	A		N			N	P	I	F	D	T			yes	no
<i>operand2</i>		S	A		M			N	P	I	F	D	T			yes	yes

Syntax Element Description:

Syntax Element	Description:
<i>arithmetic-expression</i>	See Arithmetic Expression in the COMPUTE statement.
<i>operand1</i> TO <i>operand2</i>	Operands: <i>operand1</i> and <i>operand2</i> are summands. The result is stored in <i>operand2</i> (result field). Hence, the statement is equivalent to: <pre><i>operand2</i> := <i>operand2</i> + <i>operand1</i> + ...</pre>
ROUNDED	ROUNDED Option: If the keyword ROUNDED is used, the result will be rounded. For information on rounding, see <i>Rules for Arithmetic Assignment, Field Truncation and Field Rounding</i> in the <i>Programming Guide</i> .

Example:

The statement

```
ADD #A(*) TO #B(*) is equivalent to COMPUTE #B(*) := #A(*) + #B(*)
ADD #S      TO #R      is equivalent to COMPUTE #R      := #S + #R
ADD #S #T TO #R      is equivalent to COMPUTE #R      := #S + #T + #R
ADD #A(*) TO #R      is equivalent to COMPUTE #R      := #A(*) + #R
```

Syntax 2 - ADD Statement with GIVING Clause

ADD [ROUNDED] { *(arithmetic-expression)* } ... GIVING *operand2*
operand1

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Operand Definition Table (Syntax 2):

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	C S A N	N P I F D T	yes	no
<i>operand2</i>	S A M	A U N P I F B* D T	yes	yes

* Format B of *operand2* may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description:
<i>arithmetic-expression</i>	See Arithmetic Expression in the COMPUTE statement.
<i>operand1</i> GIVING <i>operand2</i>	Operands: <i>operand1</i> is a summand. <i>operand2</i> is only used to receive the result of the operation; it is <i>not included</i> in the addition. Hence, the statement is equivalent to: <pre><i>operand2</i> := <i>operand1</i> + ...</pre>
ROUNDED	ROUNDED Option: If the keyword ROUNDED is used, the result will be rounded. For information on rounding, see <i>Rules for Arithmetic Assignment, Field Truncation and Field Rounding</i> in the <i>Programming Guide</i> .



Note: If Syntax 2 is used, the following applies: Only the (*operand1*) field(s) left of the keyword GIVING are the terms of the addition, the field right of the keyword GIVING (*operand2*) is just used to receive the result value. If just a single (*operand1*) field is supplied, the ADD operation turns into an assignment.

Example:

The statement

```
ADD #S      GIVING #R  is equivalent to  COMPUTE #R := #S
ADD #S #T   GIVING #R  is equivalent to  COMPUTE #R := #S + #T
ADD #A(*) 0  GIVING #R  is equivalent to  COMPUTE #R := #A(*) + 0
                                     which is a legal operation, due to the rules defined
                                     in Arithmetic Operations with Arrays
ADD #A(*)   GIVING #R  is equivalent to  COMPUTE #R := #A(*)
                                     which is an illegal operation, due to the rules
                                     defined in Assignment Operations with Arrays
```

Example

```

** Example 'ADDEX1': ADD
*****
DEFINE DATA LOCAL
1 #A      (P2)
1 #B      (P1.1)
1 #C      (P1)
1 #DATE   (D)
1 #ARRAY1 (P5/1:4,1:4) INIT (2,*) <5>
1 #ARRAY2 (P5/1:4,1:4) INIT (4,*) <10>
END-DEFINE
*
ADD +5 -2 -1 GIVING #A
WRITE NOTITLE 'ADD +5 -2 -1 GIVING #A' 15X '=' #A
*
ADD .231 3.6 GIVING #B
WRITE          / 'ADD .231 3.6 GIVING #B' 15X '=' #B
*
ADD ROUNDED 2.9 3.8 GIVING #C
WRITE          / 'ADD ROUNDED 2.9 3.8 GIVING #C' 8X '=' #C
*
MOVE *DATX TO #DATE
ADD 7 TO #DATE
WRITE          / 'CURRENT DATE:'          *DATX (DF=L) 13X
                'CURRENT DATE + 7:' #DATE (DF=L)
*
WRITE          / '#ARRAY1 AND #ARRAY2 BEFORE ADDITION'
                / '=' #ARRAY1 (2,*) '=' #ARRAY2 (4,*)
ADD #ARRAY1 (2,*) TO #ARRAY2 (4,*)
WRITE          / '#ARRAY1 AND #ARRAY2 AFTER ADDITION'
                / '=' #ARRAY1 (2,*) '=' #ARRAY2 (4,*)
*
END

```

Output of Program ADDEX1:

```

ADD +5 -2 -1 GIVING #A          #A:   2
ADD .231 3.6 GIVING #B          #B:   3.8
ADD ROUNDED 2.9 3.8 GIVING #C   #C:   7
CURRENT DATE: 2005-01-10        CURRENT DATE + 7: 2005-01-17

#ARRAY1 AND #ARRAY2 BEFORE ADDITION
#ARRAY1:      5      5      5      5 #ARRAY2:      10      10      10      10

```

ADD

#ARRAY1 AND #ARRAY2 AFTER ADDITION

#ARRAY1:	5	5	5	5	#ARRAY2:	15	15	15	15

14

ASSIGN

See the statement [COMPUTE](#).

15

AT BREAK

■ Function	126
■ Syntax Description	127
■ Multiple Break Levels	128
■ Examples	129

Structured Mode Syntax

```
[AT] BREAK [(r)] [OF] operand1 [/n/]  
    statement ...  
END-BREAK
```

Reporting Mode Syntax

```
[AT] BREAK [(r)] [OF] operand1 [/n/]  
    { statement  
      DO statement ... DOEND }  
}
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [ACCEPT/REJECT](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [DELETE](#) | [END TRANSACTION](#) | [FIND](#) | [GET](#) | [GET SAME](#) | [GET TRANSACTION DATA](#) | [HISTOGRAM](#) | [LIMIT](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [RETRY](#) | [STORE](#) | [UPDATE](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The `AT BREAK` statement is used to cause the execution of one or more statements whenever a change in value of a **control field** occurs. It is used in conjunction with automatic break processing and is available with the following statements: [FIND](#), [READ](#), [HISTOGRAM](#), [SORT](#), [READ WORK FILE](#).

The automatic break processing works as follows: Immediately after a record was read by the processing loop, the control field is checked. If a value change is detected in comparison to the previous record, the statements included in the `AT BREAK` statement block are executed. This does not apply to the very first record in the processing loop. In addition, when the processing loop is terminated (as reading of records is complete or due to an [ESCAPE BOTTOM](#) statement), a final execution of the statements in the `AT BREAK` statement block is triggered.

For further information, see *Automatic Break Processing* in the *Programming Guide*.

An `AT BREAK` statement block is only executed if the object which contains the statement is active at the time when the break condition occurs.

It is possible to initiate a new processing loop within an `AT BREAK` condition. This loop must also be closed within the same `AT BREAK` condition.

This statement is non-procedural (that is, its execution depends on an event, not on where in a program it is located).

Natural system functions may be used in conjunction with an `AT BREAK` statement, see *Natural System Functions for Use in Processing Loops* in the *System Functions* documentation and *Example of System Functions with AT BREAK Statement* in the *Programming Guide*.

For further information, see also the section *AT BREAK Statement* in the *Programming Guide*. It covers topics such as:

- *Control Break Based on a Database Field*
- *Control Break Based on a User-Defined Variable*

Syntax Description

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	S	A U N P I F B D T L	yes	no

Syntax Element Description:

Syntax Element	Description
(<i>r</i>)	Reference Notation: By default, the final <code>AT BREAK</code> condition (for loop termination) is always related to the outermost active processing loop initiated with a <code>FIND</code>, <code>READ</code>, <code>READ WORK FILE</code>, <code>HISTOGRAM</code> or <code>SORT</code> statement. With the notation (<i>r</i>) you can relate the final break condition of an <code>AT BREAK</code> statement to another specific currently open processing loop (that is, the loop in which the <code>AT BREAK</code> statement is located or any outer loop). Example: <pre> ... READ ... FIND ... FIND ... AT BREAK ... FIND ... END-FIND END-BREAK END-FIND END-FIND END-READ ... </pre>

Syntax Element	Description
	In this example, the final AT BREAK condition is related to the READ loop initiated in line 0120. It would be possible to have it related to one of the FIND loops initiated in line 0130 and 0140, but not to the one initiated in line 0160. If (<i>r</i>) is specified for a break hierarchy, it must be specified with the first AT BREAK statement and applies also to all AT BREAK statements which follow.
<i>operand1</i>	Control Field: The field used as the break control field is usually a database field. If a user-defined variable is used, it must be initialized prior to the evaluation of automatic break processing (see BEFORE BREAK PROCESSING statement). A specific occurrence of an array can also be used as a control field.
<i>/n/</i>	Notation /n/: The notation <i>/n/</i> may be used to indicate that only the first <i>n</i> positions (counting from left to right) of the control field are to be checked for a change in value. This notation can only be used with operands of format A, B, N or P. A control break occurs when the value of the control field changes, or when all records in the processing loop for which the AT BREAK statement applies have been processed.
<i>statement ...</i>	Statement(s) to be Executed at Break Condition: In structured mode, you must supply one or several suitable statements, depending on the situation. For an example of a statement, see Examples below.
END-BREAK	End of AT BREAK Statement:
<i>statement</i> <i>DO statement</i> <i>... DOEND</i>	In structured mode, the Natural reserved word END-BREAK must be used to end the AT BREAK statement. In reporting mode, use the DO ... DOEND statements to supply one or several suitable statements, depending on the situation, and to end the AT BREAK statement. If you specify only a single statement, you can omit the DO ... DOEND statements. With respect to good coding practice, this is not recommended.

Multiple Break Levels

Multiple AT BREAK statements may be specified within a processing loop within the same program module. If multiple BREAK statements are specified for the same processing loop, they form a hierarchy of break levels independent of whether they are specified consecutively or interspersed within other statements. The first AT BREAK statement represents the lowest control break level, and each additional AT BREAK statement represents the next higher control break level.

Every processing loop in a loop hierarchy may have its own break hierarchy attached.

Example:

Structured Mode:	Reporting Mode:
<pre> FIND ... AT BREAK ... END-BREAK AT BREAK ... END-BREAK AT BREAK ... END-BREAK END-FIND ... </pre>	<pre> FIND ... AT BREAK DO ... DOEND AT BREAK DO ... DOEND ... </pre>

A change in the value of a control field in a break level causes break processing to be activated for that break level and all lower break levels, regardless of the values of the control fields for the lower break levels.

For easier program maintenance, it is recommended to specify multiple breaks consecutively.

See also [Example 3](#) below and the section *Multiple Control Break Levels* in the *Programming Guide*.

Examples

This section covers the following topics:

- [Example 1 - AT BREAK](#)
- [Example 2 - AT BREAK Using /n/ Notation](#)
- [Example 3 - AT BREAK with Multiple Break Levels](#)

For further examples of AT BREAK, see *Natural System Functions for Use in Processing Loops*, Examples ATBEX3 and ATBEX4.

Example 1 - AT BREAK

```
** Example 'ATBEX1S': AT BREAK (structured mode)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 CITY
  2 COUNTRY
  2 NAME
END-DEFINE
*
LIMIT 10
READ EMPLOY-VIEW BY CITY
AT BREAK OF CITY
  SKIP 1
  END-BREAK
  DISPLAY NOTITLE CITY (IS=ON) COUNTRY (IS=ON) NAME
END-READ
*
END
```

Output of Program ATBEX1S:

CITY	COUNTRY	NAME
AIKEN	USA	SENKO
AIX EN OTHE	F	GODEFROY
AJACCIO		CANALE
ALBERTSLUND	DK	PLOUG
ALBUQUERQUE	USA	HAMMOND ROLLING FREEMAN LINCOLN
ALFRETON	UK	GOLDBERG
ALICANTE	E	GOMEZ

Equivalent reporting-mode example: [ATBEX1R](#).

Example 2 - AT BREAK Using /n/ Notation

```

** Example 'ATBEX2': AT BREAK (with /n/ notation)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 DEPT
  2 NAME
END-DEFINE
*
LIMIT 10
READ EMPLOY-VIEW BY DEPT STARTING FROM 'A'
AT BREAK OF DEPT /4/
  SKIP 1
  END-BREAK
  DISPLAY NOTITLE DEPT NAME
END-READ
*
END

```

Output of Program ATBEX2:

DEPARTMENT CODE	NAME
-----	-----
ADMA01	JENSEN
ADMA01	PETERSEN
ADMA01	MORTENSEN
ADMA01	MADSEN
ADMA01	BUHL
ADMA02	HERMANSEN
ADMA02	PLOUG
ADMA02	HANSEN
COMP01	HEURTEBISE
COMP01	TANCHOU

Example 3 - AT BREAK with Multiple Break Levels

```

** Example 'ATBEX5S': AT BREAK (multiple break levels) (structured mode)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 CITY
  2 DEPT
  2 NAME
  2 LEAVE-DUE
1 #LEAVE-DUE-L (N4)
END-DEFINE

```

```
*
LIMIT 5
FIND EMPLOY-VIEW WITH CITY = 'PHILADELPHIA' OR = 'PITTSBURGH'
      SORTED BY CITY DEPT
  MOVE LEAVE-DUE TO #LEAVE-DUE-L
  DISPLAY CITY (IS=ON) DEPT (IS=ON) NAME #LEAVE-DUE-L
/*
AT BREAK OF DEPT
  WRITE NOTITLE /
    T*DEPT OLD(DEPT) T*#LEAVE-DUE-L SUM(#LEAVE-DUE-L) /
END-BREAK
AT BREAK OF CITY
  WRITE NOTITLE
    T*CITY OLD(CITY) T*#LEAVE-DUE-L SUM(#LEAVE-DUE-L) //
END-BREAK
END-FIND
*
END
```

Output of Program ATBEX5:

CITY	DEPARTMENT CODE	NAME	#LEAVE-DUE-L

PHILADELPHIA	MGMT30	WOLF-TERROINE	11
		MACKARNES	27
	MGMT30		38
	TECH10	BUSH	39
		NETTLEFOLDS	24
	TECH10		63
PHILADELPHIA			101
PITTSBURGH	MGMT10	FLETCHER	34
	MGMT10		34
PITTSBURGH			34

Equivalent reporting-mode example: [ATBEX5R](#).

16

AT END OF DATA

■ Function	134
■ Restrictions	135
■ Syntax Description	135
■ Example	136

Structured Mode Syntax

```
[AT] END [OF] DATA [(r)]  
    statement ...  
END-ENDDATA
```

Reporting Mode Syntax

```
[AT] END [OF] DATA [(r)]  
{  
    statement  
    DO statement ... DOEND  
}
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT START OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [DELETE](#) | [END TRANSACTION](#) | [FIND](#) | [GET](#) | [GET SAME](#) | [GET TRANSACTION DATA](#) | [HISTOGRAM](#) | [LIMIT](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [RETRY](#) | [STORE](#) | [UPDATE](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The `AT END OF DATA` statement is used to specify processing to be performed when all records selected for a database processing loop have been processed.

This section covers the following topics:

- [Processing](#)
- [Values of Database Fields](#)
- [Positioning](#)
- [System Functions](#)

See also *AT START/END OF DATA Statements* in the *Programming Guide*.

Processing

This statement is non-procedural, that is, its execution depends on an event, not on where in a program it is located.

Values of Database Fields

When the AT END OF DATA condition for the processing loop occurs, all database fields contain the data from the last record processed.

Positioning

This statement must be specified within the same program module which contains the loop creating statement.

System Functions

Natural system functions may be used in conjunction with an AT END OF DATA statement as described in *Using System Functions in Processing Loops* in the *System Functions* documentation.

Restrictions

- This statement can only be used in a processing loop that has been initiated with one of the following statements: [FIND](#), [READ](#), [READ WORK FILE](#), [HISTOGRAM](#) or [SORT](#).
- It may be used only once per processing loop.
- It is *not* evaluated if the processing loop referenced for END OF DATA processing is not entered.

Syntax Description

Syntax Element	Description
<code>(r)</code>	Reference to a Specific Processing Loop: An AT END OF DATA statement may be related to a specific active processing loop by using the notation <code>(r)</code> . If this notation is not used, the AT END OF DATA statement will be related to the outermost active database processing loop.
<code>statement ...</code>	Statement(s) to be Executed at End of Data Condition: In structured mode, you must supply one or several suitable statements, depending on the situation. For an example of a statement, see Example below.

Syntax Element	Description
END-ENDDATA	End of AT END OF DATA Statement:
<i>statement ...</i> DO <i>statement ...</i> DOEND	In structured mode, the Natural reserved word END-ENDDATA must be used to end the AT END OF DATA statement. In reporting mode, use the DO ... DOEND statements to supply one or several suitable statements, depending on the situation, and to end the AT END OF DATA statement. If you specify only a single statement, you can omit the DO ... DOEND statements. With respect to good coding practice, this is not recommended.

Example

```

** Example 'AEDEX1S': AT END OF DATA
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
  2 FIRST-NAME
  2 SALARY      (1)
  2 CURR-CODE (1)
END-DEFINE
*
LIMIT 5
EMP. FIND EMPLOY-VIEW WITH CITY = 'STUTTGART'
  IF NO RECORDS FOUND
    ENTER
  END-NOREC
  DISPLAY PERSONNEL-ID NAME FIRST-NAME
           SALARY (1) CURR-CODE (1)
/*
  AT END OF DATA
    IF *COUNTER (EMP.) = 0
      WRITE 'NO RECORDS FOUND'
      ESCAPE BOTTOM
    END-IF
    WRITE NOTITLE / 'SALARY STATISTICS:'
                  / 7X 'MAXIMUM:' MAX(SALARY(1)) CURR-CODE (1)
                  / 7X 'MINIMUM:' MIN(SALARY(1)) CURR-CODE (1)
                  / 7X 'AVERAGE:' AVER(SALARY(1)) CURR-CODE (1)

  END-ENDDATA
/*
END-FIND
*
END

```

See also *Natural System Functions for Use in Processing Loops* in the *System Functions* documentation.

Output of Program AEDEX1S:

PERSONNEL ID	NAME	FIRST-NAME	ANNUAL SALARY	CURRENCY CODE

11100328	BERGHAUS	ROSE	70800	DM
11100329	BARTHEL	PETER	42000	DM
11300313	AECKERLE	SUSANNE	55200	DM
11300316	KANTE	GABRIELE	61200	DM
11500304	KLUGE	ELKE	49200	DM
SALARY STATISTICS:				
	MAXIMUM:	70800	DM	
	MINIMUM:	42000	DM	
	AVERAGE:	55680	DM	

Equivalent reporting-mode example: [AEDEX1R](#).

17

AT END OF PAGE

■ Function	140
■ Syntax Description	142
■ Example	143

Structured Mode Syntax

```
[AT] END [OF] PAGE [(rep)]  
    statement ...  
END-ENDPAGE
```

Reporting Mode Syntax

```
[AT] END [OF] PAGE [(rep)]  
{  
    statement  
    DO statement ... DOEND  
}
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [AT TOP OF PAGE](#) | [CLOSE PRINTER](#) | [DEFINE PRINTER](#) | [DISPLAY](#) | [EJECT](#) | [FORMAT](#) | [NEWPAGE](#) | [PRINT](#) | [SKIP](#) | [SUSPEND IDENTICAL SUPPRESS](#) | [WRITE](#) | [WRITE TITLE](#) | [WRITE TRAILER](#)

Belongs to Function Group: [Creation of Output Reports](#)

Function

The `AT END OF PAGE` statement is used to specify processing that is to be performed when an end-of-page condition is detected (see session parameter `PS` in the *Parameter Reference*). An end-of-page condition may also occur as a result of a [SKIP](#) or [NEWPAGE](#) statement, but not as a result of an [EJECT](#) or [INPUT](#) statement.

See also the following sections in the *Programming Guide*:

- *Report Format and Control*
- *Report Specification - (rep) Notation*
- *Layout of an Output Page*
- *AT END OF PAGE Statement*

Processing

An `AT END OF PAGE` statement block is only executed if the object which contains the statement block is active at the time when the end-of-page condition occurs.

An `AT END OF PAGE` statement must not be placed within an inline subroutine.

This statement is non-procedural, that is, its execution depends on an event, not on where in a program it is located.

Logical Page Size

The end-of-page check is performed after the processing of a `DISPLAY` or `WRITE` statement is completed. Therefore, if a `DISPLAY` or `WRITE` statement produces multiple lines of output, overflow of the physical page may occur before an end-of-page condition is detected.

A logical page size (session parameter `PS`) which is less than the physical page size must be specified to ensure that information printed by an `AT END OF PAGE` statement appears on the same physical page as the title.

Last-Page Handling

Within a main program, an end-of-page condition is activated when the execution of the main program terminates via `ESCAPE`, `STOP` or `END`.

Within a subroutine, an end-of-page condition is not activated when the execution of the subroutine terminates via `ESCAPE-ROUTINE`, `RETURN` or `END-SUBROUTINE`.

System Functions

Natural system functions may be used in conjunction with an `AT END OF PAGE` statement as described in the section *Using System Functions in Processing Loops* in the *System Functions* documentation.

If a system function is to be used within an `AT END OF PAGE` statement block, the `GIVE SYSTEM FUNCTIONS` clause must be specified in the corresponding `DISPLAY` statement.

INPUT Statement with AT END OF PAGE

If an **INPUT** statement is specified within an **AT END OF PAGE** statement block, no new page operation is performed. The page size (session parameter **PS**) must be reduced to a value that allows the lines created by the **INPUT** statement to appear on the same physical page.

See also:

- [Split Screen Feature](#) of **INPUT** Statement
- [Example 2 - AT END OF PAGE with INPUT Statement](#)

Syntax Description

Syntax Element	Description
<code>(rep)</code>	Report Specification: The notation <code>(rep)</code> may be used to specify the identification of the report for which the AT END OF PAGE statement is applicable. A value in the range 0 - 31 or a logical name which has been assigned using the DEFINE PRINTER statement may be specified. If <code>(rep)</code> is not specified, the AT END OF PAGE statement will apply to the first report (Report 0). For information on how to control the format of an output report created with Natural, see <i>Report Format and Control</i> in the <i>Programming Guide</i>.
<code>statement</code>	Statement(s) to be Executed at End of Page Condition: In structured mode, you must supply one or several suitable statements, depending on the situation. For an example of a statement, see Example below.
<code>END-ENDPAGE</code>	End of AT END OF PAGE Statement:
<code>statement</code> <code>DO statement ...</code> <code>DOEND</code>	In structured mode, the Natural reserved word END-ENDPAGE must be used to end the AT END OF PAGE statement. In reporting mode, use the DO ... DOEND statements to supply one or several suitable statements, depending on the situation, and to end the AT END OF PAGE statement. If you specify only a single statement, you can omit the DO ... DOEND statements. With respect to good coding practice, this is not recommended.

Example

- [Example 1 - AT END OF PAGE](#)
- [Example 2 - AT END OF PAGE with INPUT Statement](#)

Example 1 - AT END OF PAGE

```

** Example 'AEPEX1S': AT END OF PAGE (structured mode)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
  2 JOB-TITLE
  2 SALARY      (1)
  2 CURR-CODE (1)
END-DEFINE
*
FORMAT PS=10
LIMIT 10
READ EMPLOY-VIEW BY PERSONNEL-ID FROM '20017000'
  DISPLAY NOTITLE GIVE SYSTEM FUNCTIONS
    NAME JOB-TITLE 'SALARY' SALARY(1) CURR-CODE (1)
  /*

  AT END OF PAGE
    WRITE / 28T 'AVERAGE SALARY: ...' AVER(SALARY(1)) CURR-CODE (1)
  END-ENDPAGE

END-READ
*
END

```

See also *Natural System Functions for Use in Processing Loops*.

Output of Program AEPEX1S:

NAME	CURRENT POSITION	SALARY	CURRENCY CODE
CREMER	ANALYST	34000	USD
MARKUSH	TRAINEE	22000	USD
GEE	MANAGER	39500	USD
KUNEY	DBA	40200	USD
NEEDHAM	PROGRAMMER	32500	USD
JACKSON	PROGRAMMER	33000	USD

AVERAGE SALARY: ... 33533 USD

Equivalent reporting-mode example: [AEPEX1R](#).

Example 2 - AT END OF PAGE with INPUT Statement

```
** Example 'AEPEX2': AT END OF PAGE (with INPUT)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 FIRST-NAME
  2 POST-CODE
  2 CITY
*
1 #START-NAME (A20)
END-DEFINE
*
FORMAT PS=21
*
REPEAT
  READ (15) EMPLOY-VIEW BY NAME = #START-NAME
  DISPLAY NOTITLE NAME FIRST-NAME POST-CODE CITY
  END-READ
  NEWPAGE
/*
AT END OF PAGE
  MOVE NAME TO #START-NAME
  INPUT / '-' (79)
    / 10T 'Reposition to name ==>'
    #START-NAME (AD=MI) '('.'.' to exit)'
  IF #START-NAME = '.'
    STOP
  END-IF
END-ENDPAGE
/*
END-REPEAT
END
```

Output of Program AEPEX2S:

NAME	FIRST-NAME	POSTAL ADDRESS	CITY

ABELLAN	KEPA	28014	MADRID
ACHIESON	ROBERT	DE3 4TR	DERBY
ADAM	SIMONE	89300	JOIGNY
ADKINSON	JEFF	11201	BROOKLYN
ADKINSON	PHYLLIS	90211	BEVERLEY HILLS

ADKINSON	HAZEL	20760	GAITHERSBURG
ADKINSON	DAVID	27514	CHAPEL HILL
ADKINSON	CHARLIE	21730	LEXINGTON
ADKINSON	MARTHA	17010	FRAMINGHAM
ADKINSON	TIMMIE	17300	BEDFORD
ADKINSON	BOB	66044	LAWRENCE
AECKERLE	SUSANNE	7000	STUTTGART
AFANASSIEV	PHILIP	39401	HATTIESBURG
AFANASSIEV	ROSE	60201	EVANSTON
AHL	FLEMMING	2300	SUNDBY

Reposition to name ==> AHL

('.' to exit)

18

AT START OF DATA

■ Function	148
■ Syntax Description	149
■ Example	149

Structured Mode Syntax

```
[AT] START [OF] DATA [(r)]  
    statement ...  
END-START
```

Reporting Mode Syntax

```
[AT] START [OF] DATA [(r)]  
{  
    statement  
    DO statement... DOEND  
}
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [DELETE](#) | [END TRANSACTION](#) | [FIND](#) | [GET](#) | [GET SAME](#) | [GET TRANSACTION DATA](#) | [HISTOGRAM](#) | [LIMIT](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [RETRY](#) | [STORE](#) | [UPDATE](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The statement `AT START OF DATA` is used to perform processing immediately after the first of a set of records is read for a processing loop that has been initiated by one of the following statements: [READ](#), [FIND](#), [HISTOGRAM](#), [SORT](#) or [READ WORK FILE](#).

See also *AT START/END OF DATA Statements* in the *Programming Guide*.

Processing

If the loop-initiating statement contains a `WHERE` clause, the at-start-of-data condition will be true when the first record is read which meets both the basic search and the `WHERE` criteria.

This statement is non-procedural, that is, its execution depends on an event, not on where in a program it is located.

Value of Database Fields

All database fields contain the values of the record which caused the at-start-of-data condition to be true (that is, the first record of the set of records to be processed).

Positioning

This statement must be positioned *within* a processing loop, and it may be used only once per processing loop.

Syntax Description

Syntax Element	Description
(<i>r</i>)	Reference to a Specific Processing Loop: An AT START OF DATA statement may be related to a specific outer active processing loop by using the notation (<i>r</i>). If this notation is not used, the statement is related to the outermost active processing loop.
<i>statement</i> ...	Statement(s) to be Executed at Start of Data Condition: In structured mode, you must supply one or several suitable statements, depending on the situation. For an example of a statement, see Example below.
END-START	End of AT START OF DATA Statement:
<i>statement</i> ... DO <i>statement</i> ... DOEND	In structured mode, the Natural reserved word END-START must be used to end the AT START OF DATA statement. In reporting mode, use the DO ... DOEND statements to supply one or several suitable statements, depending on the situation, and to end the AT START OF DATA statement. If you specify only a single statement, you can omit the DO ... DOEND statements. With respect to good coding practice, this is not recommended.

Example

```
** Example 'ASDEX1S': AT START OF DATA (structured mode)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 FIRST-NAME
  2 CITY
*
1 #CNTL (A1) INIT <' '>
```

```
1 #CITY (A20) INIT <' '>
END-DEFINE
*
REPEAT
  INPUT 'ENTER VALUE FOR CITY'  #CITY
  IF #CITY = ' ' OR = 'END'
    STOP
  END-IF
  FIND EMPLOY-VIEW WITH CITY = #CITY
  IF NO RECORDS FOUND
    WRITE NOTITLE NOHDR 'NO RECORDS FOUND'
    ESCAPE BOTTOM
  END-NOREC
/*
  AT START OF DATA
    INPUT (AD=0) 'RECORDS FOUND' *NUMBER //
    'ENTER ''D'' TO DISPLAY RECORDS' #CNTL (AD=A)
    IF #CNTL NE 'D'
      ESCAPE BOTTOM
    END-IF
  END-START
/*
  DISPLAY NAME FIRST-NAME
END-FIND
END-REPEAT
END
```

Output of Program ASDEX1S:

```
ENTER VALUE FOR CITY PARIS
```

After entering and confirming name of city:

```
RECORDS FOUND      26
```

```
ENTER 'D' TO DISPLAY RECORDS D
```

Records displayed:

NAME	FIRST-NAME
-----	-----
MAIZIERE	ELISABETH
MARX	JEAN-MARIE
REIGNARD	JACQUELINE
RENAUD	MICHEL
REMOUE	GERMAINE
LAVENDA	SALOMON
BROUSSE	GUY
GIORDA	LOUIS
SIECA	FRANCOIS

CENSIER	BERNARD
DUC	JEAN-PAUL
CAHN	RAYMOND
MAZUY	ROBERT
FAURIE	HENRI
VALLY	ALAIN
BRETON	JEAN-MARIE
GIGLEUX	JACQUES
KORAB-BRZozowski	BOGDAN
XOLIN	CHRISTIAN
LEGRIS	ROGER
VVVV	

Equivalent reporting-mode example: [ASDEX1R](#).

19

AT TOP OF PAGE

■ Function	154
■ Restriction	155
■ Syntax Description	155
■ Example	156

Structured Mode Syntax

```
[AT] TOP [OF] PAGE [(rep)]  
    statement ...  
END-TOPPAGE
```

Reporting Mode Syntax

```
[AT] TOP [OF] PAGE [(rep)]  
    { statement  
      DO statement ... DOEND }  
}
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [AT END OF PAGE](#) | [CLOSE PRINTER](#) | [DEFINE PRINTER](#) | [DISPLAY](#) | [EJECT](#) | [FORMAT](#) | [NEWPAGE](#) | [PRINT](#) | [SKIP](#) | [SUSPEND IDENTICAL SUPPRESS](#) | [WRITE](#) | [WRITE TITLE](#) | [WRITE TRAILER](#)

Belongs to Function Group: [Creation of Output Reports](#)

Function

The statement `AT TOP OF PAGE` is used to specify processing which is to be performed when a new page is started.

See also the following sections in the *Programming Guide*:

- *Report Format and Control*
- *Report Specification - (rep) Notation*
- *Layout of an Output Page*
- *AT TOP OF PAGE Statement*

Processing

A new page is started when the internal line counter exceeds the page size set with the session parameter PS (page size for Natural reports), or when a [NEWPAGE](#) statement is executed. Either of these events cause a top-of-page condition to be true. An [EJECT](#) statement causes a new page to be started but does not cause a top-of-page condition.

An AT TOP OF PAGE statement block is only executed when the object which contains the statement is active at the time when the top-of-page condition occurs.

Any output created as a result of AT TOP OF PAGE processing will appear following the title line with an intervening blank line.

This statement is non-procedural, that is, its execution depends on an event, not on where in a program it is located.

Restriction

An AT TOP OF PAGE statement must not be placed within an inline subroutine.

Syntax Description

Syntax Element	Description
<i>(rep)</i>	Report Specification: The notation <i>(rep)</i> may be used to specify the identification of the report for which the AT TOP OF PAGE statement is applicable. A value in the range 0 - 31 or a logical name which has been assigned using the DEFINE PRINTER statement may be specified. If <i>(rep)</i> is not specified, the AT TOP OF PAGE statement applies to the first report (Report 0). For information on how to control the format of an output report created with Natural, see <i>Report Format and Control</i> in the <i>Programming Guide</i>.
<i>statement ...</i>	Statement(s) to be Executed at Start of Data Condition: In structured mode, you must supply one or several suitable statements, depending on the situation. For an example of a statement, see Example below.
END-TOPPAGE	End of AT TOP OF PAGE Statement:
<i>statement ...</i> DO <i>statement ...</i> DOEND	In structured mode, the Natural reserved word END-TOPPAGE must be used to end the AT TOP OF PAGE statement.

Syntax Element	Description
	In reporting mode, use the <code>DO . . . DOEND</code> statements to supply one or several suitable statements, depending on the situation, and to end the <code>AT TOP OF PAGE</code> statement. If you specify only a single statement, you can omit the <code>DO . . . DOEND</code> statements. With respect to good coding practice, this is not recommended.

Example

```
** Example 'ATPEX1S': AT TOP OF PAGE (structured mode)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 FIRST-NAME
  2 CITY
  2 DEPT
END-DEFINE
*
FORMAT PS=15
LIMIT 15
READ EMPLOY-VIEW BY NAME STARTING FROM 'L'
  DISPLAY 2X NAME 4X FIRST-NAME CITY DEPT
  WRITE TITLE UNDERLINED 'EMPLOYEE REPORT'
  WRITE TRAILER '-' (78)
/*
AT TOP OF PAGE
  WRITE 'BEGINNING NAME:' NAME
END-TOPPAGE
/*
AT END OF PAGE
  SKIP 1
  WRITE 'ENDING NAME:  ' NAME
END-ENDPAGE
END-READ
END
```

Output of Program ATPEX1S:

EMPLOYEE REPORT			

BEGINNING NAME: LAFON			
NAME	FIRST-NAME	CITY	DEPARTMENT CODE
-----	-----	-----	-----
LAFON	CHRISTIANE	PARIS	VENT18
LANDMANN	HARRY	ESCHBORN	MARK29
LANE	JACQUELINE	DERBY	MGMT02

LANKATILLEKE	LALITH	FRANKFURT	PROD22
LANNON	BOB	LINCOLN	SALE20
LANNON	LESLIE	SEATTLE	SALE30
LARSEN	CARL	FARUM	SYSA01
LARSEN	MOGENS	VERMELEV	SYSA02

ENDING NAME: LARSEN

Equivalent reporting-mode example: [ATPEX1R](#).

20

BACKOUT TRANSACTION

■ Function	160
■ Restriction	161
■ Database-Specific Considerations	161
■ Example	161

BACKOUT [TRANSACTION]

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BEFORE BREAK PROCESSING](#) | [DELETE](#) | [END TRANSACTION](#) | [FIND](#) | [GET](#) | [GET SAME](#) | [GET TRANSACTION DATA](#) | [HISTOGRAM](#) | [LIMIT](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [RETRY](#) | [STORE](#) | [UPDATE](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The `BACKOUT TRANSACTION` statement is used to back out all database updates performed during the current logical transaction. This statement also releases all records held during the transaction.

The statement is executed only if a database transaction under control of Natural has taken place. For which databases the statement is executed depends on the setting of the profile parameter `ET` (execution of `END/BACKOUT TRANSACTION` statements):

- If `ET=OFF`, the statement is executed only for the database affected by the transaction.
- If `ET=ON`, the statement is executed for all databases that have been referenced since the last execution of a `BACKOUT TRANSACTION` or [END TRANSACTION](#) statement.

Backout Transaction Issued by Natural

If the user interrupts the current Natural operation with a terminal command (command `%%` or `CLEAR` key), Natural issues a `BACKOUT TRANSACTION` statement.

See also the terminal command `%%` in the *Terminal Commands* documentation.

Additional Information

For additional information on the use of the transaction backout feature, see the sections *Database Update - Transaction Processing* and *Backing Out a Transaction* in the *Programming Guide*.

Restriction

This statement is not available with Entire System Server.

Database-Specific Considerations

DL/I Databases	Because PSB scheduling is terminated by a syncpoint request, Natural saves the PSB position before executing the BACKOUT TRANSACTION statement. Before the next command execution, Natural re-schedules the PSB and tries to set the PCB position as it was before the backout. The PCB position might be shifted forward if any pointed segment had been deleted in the time period between the backout and the following command.
SQL Databases	As most SQL databases close all cursors when a logical unit of work ends, a BACKOUT TRANSACTION statement must not be placed within a database modification loop; instead, it has to be placed after such a loop.

Example

```

** Example 'BOTEX1': BACKOUT TRANSACTION
**
** CAUTION: Executing this example will modify the database records!
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 DEPT
  2 LEAVE-DUE
  2 LEAVE-TAKEN
*
1 #DEPT (A6)
1 #RESP (A3)
END-DEFINE
*
LIMIT 3
INPUT 'DEPARTMENT TO BE UPDATED:' #DEPT
IF #DEPT = ' '
  STOP
END-IF
*
FIND EMPLOY-VIEW WITH DEPT = #DEPT
  IF NO RECORDS FOUND
    REINPUT 'NO RECORDS FOUND'
  END-NOREC

```

BACKOUT TRANSACTION

```
INPUT 'NAME:      ' NAME (AD=0) /
      'LEAVE DUE:  ' LEAVE-DUE (AD=M) /
      'LEAVE TAKEN:' LEAVE-TAKEN (AD=M)
UPDATE
END-FIND
*
INPUT 'UPDATE TO BE PERFORMED? YES/NO:' #RESP
DECIDE ON FIRST #RESP
  VALUE 'YES'
    END TRANSACTION
  VALUE 'NO'
    BACKOUT TRANSACTION
  NONE
    REINPUT 'PLEASE ENTER YES OR NO'
END-DECIDE
*
END
```

Output of Program BOTEX1:

DEPARTMENT TO BE UPDATED: MGMT30

Result for department MGMT30:

```
NAME:      POREE
LEAVE DUE:  45
LEAVE TAKEN: 31
```

Confirmation query:

UPDATE TO BE PERFORMED YES/NO: NO

21

BEFORE BREAK PROCESSING

■ Function	164
■ Restrictions	165
■ Syntax Description	165
■ Example	166

Structured Mode Syntax

```
BEFORE [BREAK] [PROCESSING]  
  statement ...  
END-BEFORE
```

Reporting Mode Syntax

```
BEFORE [BREAK] [PROCESSING]  
{  
  statement  
  DO statement ... DOEND  
}
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [DELETE](#) | [END TRANSACTION](#) | [FIND](#) | [GET](#) | [GET SAME](#) | [GET TRANSACTION](#) | [HISTOGRAM](#) | [LIMIT](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [RETRY](#) | [STORE](#) | [UPDATE](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The `BEFORE BREAK PROCESSING` statement may be used in conjunction with automatic break processing to perform processing:

- before the value of the break control field is checked;
- before the statements specified with an `AT BREAK` statement are executed;
- before Natural system functions are evaluated.

This statement is most often used to initialize or compute values of user-defined variables which are to be used in break processing (see `AT BREAK` statement).

This statement is non-procedural (that is, its execution depends on an event, not on where in a program it is located).

See also the following sections in the *Programming Guide*:

- *Control Breaks*
- *BEFORE BREAK PROCESSING Statement*
- *Example of BEFORE BREAK PROCESSING Statement*

Restrictions

- The `BEFORE BREAK PROCESSING` statement may only be used with a processing loop that has been initiated with one of the following statements:
 - `FIND`
 - `READ`
 - `HISTOGRAM`
 - `SORT`
 - `READ WORK FILE`

It may be placed anywhere within the processing loop and is always related to the processing loop in which it is contained. Only one `BEFORE BREAK PROCESSING` statement may be specified per processing loop.

- The `BEFORE BREAK PROCESSING` statement must not be used in conjunction with the statement `PERFORM BREAK PROCESSING`.

Syntax Description

Syntax Element	Description
<i>statement...</i>	Statement(s) for Break Processing: In place of <i>statement</i>, you must supply one or several suitable statements, depending on the situation. For an example of a statement, see Example below. If no break processing is to be performed (that is, no <code>AT BREAK</code> statement is specified for the processing loop), any statements specified with a <code>BEFORE BREAK PROCESSING</code> statement will <i>not</i> be executed.
END-BEFORE	End of BEFORE BREAK PROCESSING Statement:
<i>statement ...</i> <code>DO statement ... DOEND</code>	In structured mode, the Natural reserved word <code>END-BEFORE</code> must be used to end the <code>BEFORE BREAK PROCESSING</code> statement. In reporting mode, use the <code>DO ... DOEND</code> statements to supply one or several suitable statements, depending on the situation, and to end the <code>BEFORE BREAK PROCESSING</code> statement. If you specify only a single statement, you can omit the <code>DO ... DOEND</code> statements. With respect to good coding practice, this is not recommended.

Example

```
** Example 'BBPEX1': BEFORE BREAK PROCESSING
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 CITY
  2 NAME
  2 SALARY (1)
  2 BONUS (1,1)
*
1 #INCOME (P11)
END-DEFINE
*
LIMIT 7
READ EMPLOY-VIEW BY CITY = 'L'
/*
  BEFORE BREAK PROCESSING
    COMPUTE #INCOME = SALARY (1) + BONUS (1,1)
  END-BEFORE
/*
  AT BREAK OF CITY
    WRITE NOTITLE 'AVERAGE INCOME FOR' OLD (CITY) 20X AVER(#INCOME) /
  END-BREAK
/*
  DISPLAY CITY 'NAME' NAME 'SALARY' SALARY (1) 'BONUS' BONUS (1,1)
END-READ
END
```

Output of Program BBPEX1:

CITY	NAME	SALARY	BONUS

LA BASSEE	HULOT	165000	70000
AVERAGE INCOME FOR LA BASSEE			235000
LA CHAPELLE ST LUC	GUILLARD	124100	23000
LA CHAPELLE ST LUC	BERGE	198500	50000
LA CHAPELLE ST LUC	POLETTE	124090	23000
LA CHAPELLE ST LUC	DELAUNEY	115000	23000
LA CHAPELLE ST LUC	SCHECK	125600	23000
LA CHAPELLE ST LUC	KREEBS	184550	50000
AVERAGE INCOME FOR LA CHAPELLE ST LUC			177306

22

CALL

■ Function	168
■ Syntax Description	168
■ Return Code	169
■ Register Usage	169
■ Storage Alignment	170
■ Adabas Calls	171
■ Direct/Dynamic Loading	171
■ Linkage Conventions	173
■ Program Properties	174
■ Calling a PL/I Program	174
■ Calling a C Program	177
■ INTERFACE4	180

```
CALL [INTERFACE4] operand1 [[USING] operand2 ... 128]
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [CALL FILE](#) | [CALL LOOP](#) | [CALLNAT](#) | [DEFINE SUBROUTINE](#) | [ESCAPE](#) | [FETCH](#) | [PERFORM](#)

Belongs to Function Group: [Invoking Programs and Routines](#)

Function

The `CALL` statement is used to call an external program written in another standard programming language from a Natural program and then return to the next statement after the `CALL` statement.

The called program may be written in any programming language which supports a standard `CALL` interface. Multiple `CALL` statements to one or more external programs may be specified.

A `CALL` statement may be issued within a program to be executed under control of a TP monitor, provided that the TP monitor supports a `CALL` interface.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats															Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S				A															yes	no
<i>operand2</i>	C	S	A	G		A	U	N	P	I	F	B	D	T	L	C	G				yes	yes

Syntax Element Description:

Syntax Element	Description
INTERFACE4	Interface Usage: The optional keyword <code>INTERFACE4</code> specifies the type of the interface that is used for the call of the external program. See the section INTERFACE4 below.
<i>operand1</i>	Program Name: The name of the program to be called (<i>operand1</i>) can be specified as a constant or - if different programs are to be called dependent on program logic - as an alphanumeric variable of length 1 to 8. A program name must be placed left-justified in the variable.

Syntax Element	Description
[USING] <i>operand2</i>	Parameters to be Passed: The CALL statement may contain up to 128 parameters (<i>operand2</i>), unless the INTERFACE4 option is used. In that case, the number of parameters is limited by the size of the cataloged object. Depending on all other statements in the Natural object, up to 16370 parameters may be used. Standard linkage register conventions are used. One address is passed in the parameter list for each parameter field specified. If a group name is used, the group is converted to individual fields; that is, if a user wishes to specify the beginning address of a group, the first field of the group must be specified. Note: The internal representation of positive signs of packed numbers is changed to the value specified by the PSIGNF parameter of the NTCMP0 macro (Compilation Options) before control is passed to the external program.

Return Code

The condition code of any called program (content of Register 15 upon return to Natural) may be obtained by using the Natural system function RET (Return Code Function).

Example:

```
...
RESET #RETURN(B4)
CALL 'PROG1'
IF RET ('PROG1') > #RETURN
  WRITE 'ERROR OCCURRED IN PROGRAM1'
END-IF
...
```

Register Usage

Register	Contents
R1	Address pointer to the parameter address list.
R2	Address pointer to the field (parameter) description list. The field description list contains information on the first 128 fields passed in the parameter list. Each description is a 4-byte entry containing the following information: ■ the 1st byte contains the type of variable (A, B,...); ■ if a variable of type A exceeds a size of 32767 bytes, it is passed as type Y;

Register	Contents
	■ if a variable of type B exceeds a size of 32767 bytes, it is passed as type X; the types X and Y have been introduced to support long alpha and binary variables with the standard CALL interface. If field type is N or P: ■ the 2nd byte contains the total number of digits; ■ the 3rd byte contains the number of digits before the decimal point; ■ the 4th byte contains the number of digits after the decimal point. If field type is X or Y: ■ the 2nd byte is unused; ■ the 3rd-4th byte contain zero; ■ the length of the field is passed via R4. All other field types: ■ the 2nd byte is unused; ■ the 3rd-4th byte contain the length of field.
R3	Address pointer to list of field lengths. Each length field is a 4-byte entry containing the length of each field passed in the parameter list. In the case of an array, the length is the sum of the individual occurrences' lengths.
R4	Only for type X and Y: ■ a 4-byte long entry for each variable of type A or B that exceeds the size of 32767 bytes.
R13	Address of 18-word save area.
R14	Return address.
R15	Entry address/return code.

Storage Alignment

See the section *Storage Alignment* in the *Programming Guide*.

Adabas Calls

A called program may contain a call to Adabas. The called program must not issue an Adabas open or close command. Adabas will open all database files referenced.

If Adabas exclusive (EXU) update mode is to be used, the Natural profile parameter `OPRB` (Database Open/Close Processing) must be used in order to open all referenced files. Before you attempt to use EXU update mode, you should consult your Natural administrator.

If a called program issues Adabas commands that begin or end a transaction, Natural will not be able to recognize the change of the transaction status.

Calls to Adabas must comply with the calling conventions for the Adabas application programming interface (API) for the respective TP monitor or operating system. This applies also if Natural is acting as a server, for example, under z/OS or SMARTS.

Direct/Dynamic Loading

The called program may either be directly linked to the Natural nucleus (that is, the program is specified with the profile parameter `CSTATIC` (Programs Statically Linked to Natural) in the Natural parameter module (described in the *Operations* documentation), or it may be loaded dynamically the first time it is called.

If it is to be loaded dynamically, the load module library containing the called program must be concatenated to the Natural load library in the Natural execution JCL or in the appropriate TP-monitor program library. Ask your Natural administrator for additional information.

Example:

The example below shows a Natural program which calls the COBOL program `TABSUB` for the purpose of converting a country code into the corresponding country name. Two parameter fields are passed by the Natural program to `TABSUB`:

- the first parameter is the country code, as read from the database;
- the second parameter is used to return the corresponding country name.

Calling Natural Program:

```

** Example 'CALEX1': CALL PROGRAM 'TABSUB'
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 BIRTH
  2 COUNTRY
*
1 #COUNTRY      (A3)
1 #COUNTRY-NAME (A15)
1 #FIND-FROM    (D)
1 #FIND-TO      (D)
END-DEFINE
*
MOVE EDITED '19550701' TO #FIND-FROM (EM=YYYYMMDD)
MOVE EDITED '19550731' TO #FIND-TO   (EM=YYYYMMDD)
*
FIND EMPLOY-VIEW WITH BIRTH = #FIND-FROM THRU #FIND-TO
  MOVE COUNTRY TO #COUNTRY
  /*
  CALL 'TABSUB' #COUNTRY #COUNTRY-NAME
  /*
  DISPLAY NAME BIRTH (EM=YYYY-MM-DD) #COUNTRY-NAME
END-FIND
END

```

Called COBOL program TABSUB:

```

IDENTIFICATION DIVISION.
PROGRAM-ID. TABSUB.
REMARKS. THIS PROGRAM PROVIDES THE COUNTRY NAME
        FOR A GIVEN COUNTRY CODE.
ENVIRONMENT DIVISION.
DATA DIVISION.
WORKING-STORAGE SECTION.
LINKAGE SECTION.
01 COUNTRY-CODE  PIC X(3).
01 COUNTRY-NAME  PIC X(15).
PROCEDURE DIVISION USING COUNTRY-CODE COUNTRY-NAME.
P-CONVERT.
  MOVE SPACES TO COUNTRY-NAME.
  IF COUNTRY-CODE = 'BLG' MOVE 'BELGIUM' TO COUNTRY-NAME.
  IF COUNTRY-CODE = 'DEN' MOVE 'DENMARK' TO COUNTRY-NAME.
  IF COUNTRY-CODE = 'FRA' MOVE 'FRANCE' TO COUNTRY-NAME.
  IF COUNTRY-CODE = 'GER' MOVE 'GERMANY' TO COUNTRY-NAME.
  IF COUNTRY-CODE = 'HOL' MOVE 'HOLLAND' TO COUNTRY-NAME.
  IF COUNTRY-CODE = 'ITA' MOVE 'ITALY' TO COUNTRY-NAME.
  IF COUNTRY-CODE = 'SPA' MOVE 'SPAIN' TO COUNTRY-NAME.
  IF COUNTRY-CODE = 'UK'  MOVE 'UNITED KINGDOM' TO COUNTRY-NAME.
P-RETURN.
GOBACK.

```

Linkage Conventions

Standard linkage register notation is used in batch mode. Each TP monitor has its own conventions. These conventions must be followed; otherwise, unpredictable results could occur.

The following sections describe conventions that apply for the supported TP monitors.

- [CALL Using Com-plete](#)
- [CALL Using CICS](#)

CALL Using Com-plete

The called program must reside in the Com-plete online load library. This allows Com-plete to load the program dynamically. The Com-plete utility `ULIB` may be used to catalog the program.

CALL Using CICS

The called non-Natural subprogram must reside in either a load module library concatenated to the CICS library or the `DFHRPL` library. The subprogram must have a PPT entry in the operating PPT so that CICS can locate the subprogram and load it.

The `CALLRPL` parameter of the `NTCICSP` macro controls where and how the parameter list addresses are passed to the external subroutine program.

If you wish the parameter values themselves, rather than the address of their address list, to be passed in a CICS `COMMAREA` (or Container), issue the Natural (call options) `%P=C` (or `%P=CC`) terminal command before the call. Alternatively, you can define the call options by using the `PGP` profile parameter.

When a Natural program calls a non-Natural subprogram under CICS, the call is accomplished by an `EXEC CICS LINK` request.

If you use standard linkage conventions (direct branch using a `BASR` instruction) for the call instead, issue the terminal command `%P=S`, or specify the `STDL` property with the `PGP` profile parameter. In this case, the called subprogram must adhere to standard linkage conventions with standard register usage.

Issue the `%P=SQ` terminal command, or specify the `STDLQ` property with the `PGP` profile parameter if both of the following conditions apply:

- The subprogram called using standard linkage conventions is quasi-reentrant only (but not threadsafe and fully reentrant), that is, it is defined with the `CICS CONCURRENCY (QUASIRENT)` attribute.
- Natural is defined with the `CICS CONCURRENCY (THREADSAFE)` attribute.

As a result, the called subprogram is executed under the CICS QR TCB.

If a program linked with `AMODE=24` is called in a 31-bit-mode environment and the threads are allocated above the 16 MB memory line, a “call by value” will be performed automatically; that is, the specified parameters which are to be passed to the called program will be copied below the 16 MB memory line.

Return Codes under CICS

CICS itself does not support return codes for a call with CICS conventions (`EXEC CICS LINK`), with the exception of calling C/C++ programs where values passed by the `exit()` function or the `return()` statement are saved in the `EIBRESP2` field. However, the Natural CICS Interface supports return codes for the `CALL` statement: When control is returned from the called program, Natural first checks the `EIBRESP2` field for a non-zero return code.

Then Natural checks whether the first fullword of the `COMMAREA` has changed (only if `COMMAREA` was used for parameter address lists). If it has, its new content will be taken as the return code. If it has not changed, the first fullword of the `TWA` will be checked (only if `TWA` was used for parameter address lists) and its new content taken as the return code. If neither of the two fullwords has changed, the return code will be 0.



Note: When parameter values are passed in the `COMMAREA (%P=C)`, only the `EIBRESP2` field is checked for a return code; that is, for non-C/C++ programs the return code is always 0.

Program Properties

To define properties permanently for external programs to be called, use the profile parameter `PGP`. To define temporary properties for external programs to be called, use the terminal command `%P=`.

Calling a PL/I Program

A called program written in PL/I requires the following additional procedure:

- Since the parameter list is a standard list and is not an argument list being passed from another PL/I program, the addresses passed do not point at a `LOCATOR DESCRIPTOR`. This problem may be resolved by defining the parameter fields as arithmetic variables. This causes PL/I to treat the parameter list as addresses of data instead of addresses of `LOCATOR DESCRIPTOR` control blocks.

The technique suggested for defining the parameter fields is illustrated in the following example:

```

PLIPROG: PROC(INPUT_PARM_1, INPUT_PARM_2) OPTIONS(MAIN);
  DECLARE (INPUT_PARM_1, INPUT_PARM_2) FIXED;
  PTR_PARM_1 = ADDR(INPUT_PARM_1);
  PTR_PARM_2 = ADDR(INPUT_PARM_2);
  DECLARE FIRST_PARM      PIC '99'    BASED (PTR_PARM_1);
  DECLARE SECOND_PARM     CHAR(12)    BASED (PTR_PARM_2);

```

Each parameter in the input list should be treated as a unique element. The number of input parameters should exactly match the number being passed from the Natural program. The input parameters and their attributes must match the Natural definitions or unpredictable results may occur. For additional information on passing parameters in PL/I, see the relevant IBM PL/I documentation.

The following topics are covered below:

- [Example of Calling a PL/I Program](#)
- [Example of Calling a PL/I Program which is Operating under CICS](#)

Example of Calling a PL/I Program

```

** Example 'CALEX2': CALL PROGRAM 'NATPLI'
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 AREA-CODE
  2 REDEFINE AREA-CODE
    3 #AC          (N1)
*
1 #INPUT-NUMBER   (N2)
1 #OUTPUT-COMMENT (A15)
END-DEFINE
*
READ EMPLOY-VIEW IN LOGICAL SEQUENCE BY NAME
                  STARTING FROM 'WAGNER'
  MOVE ' ' TO #OUTPUT-COMMENT
  MOVE #AC TO #INPUT-NUMBER
/*
  CALL 'NATPLI' #INPUT-NUMBER #OUTPUT-COMMENT
/*
END-READ
*
END

```

Called PL/I program NATPLI:

```

NATPLI:  PROC(PARM_COUNT, PARM_COMMENT) OPTIONS(MAIN);
/*
/* THIS PROGRAM ACCEPTS AN INPUT NUMBER
/* AND TRANSLATES IT TO AN OUTPUT CHARACTER
/* STRING FOR PLACEMENT ON THE FINAL
/* NATURAL REPORT
/*
/*
/*
DECLARE (PARM_COUNT, PARM_COMMENT) FIXED;
DECLARE ADDR BUILTIN;
COUNT_PTR = ADDR(PARM_COUNT);
COMMENT_PTR = ADDR(PARM_COMMENT);
DECLARE INPUT_NUMBER PIC '99' BASED (COUNT_PTR);
DECLARE OUTPUT_COMMENT CHAR(15) BASED (COMMENT_PTR);
DECLARE COMMENT_TABLE(9) CHAR(15) STATIC INITIAL
('COMMENT1 ',
 'COMMENT2 ',
 'COMMENT3 ',
 'COMMENT4 ',
 'COMMENT5 ',
 'COMMENT6 ',
 'COMMENT7 ',
 'COMMENT8 ',
 'COMMENT9 ');
OUTPUT_COMMENT = COMMENT_TABLE(INPUT_NUMBER);
RETURN;
END NATPLI;

```

Example of Calling a PL/I Program which is Operating under CICS

```

** Example 'CALEX3': CALL PROGRAM 'CICSP'
*****
DEFINE DATA LOCAL
1 #MESSAGE (A10) INIT <' '>
END-DEFINE
*
CALL 'CICSP' #MESSAGE
DISPLAY #MESSAGE
*
END

```

Called PL/I program CICSP:

```

CICSP: PROCEDURE OPTIONS (MAIN REENTRANT);
      DCL TWA_ADDRESS      BASED(TWA_POINTER);
      DCL LIST_ADDRESS     POINTER;
      DCL PTR_TO_LIST      POINTER BASED(LIST_ADDRESS);
      DCL PARM_01          POINTER;
      DCL MESSAGE          CHAR(10) BASED(PARM_01);
      EXEC CICS ADDRESS TWA(TWA_POINTER);
      MESSAGE='SUCCESS'; EXEC CICS RETURN; END CICSP;

```

Calling a C Program

Before using a C program, you need to compile and link it.

- Use for instance IBM's C compiler to build the executable module. Since IBM's C compiler produces LE code, the sample is only executable in an LE environment. To execute LE programs, the Natural front-end needs to be installed LE enabled.
- If you intend to use any other C compiler, such as Dignus or SASC, you need to build a module which is callable from a non-C environment. Refer to the appropriate compiler documentation for further information.
- The include file NATUSER needs to be included in the C program.

C programs written for INTERFACE4 can be used on mainframe systems as well as on UNIX, OpenVMS or Windows systems, whereas C programs, written for the standard Call Interface, are platform-dependent.

If it is intended to call the C Program via CALL INTERFACE4 or if a Natural subprogram is called from the C Program, NATXCAL4 needs to be linked to the executable module. Use one of the INTERFACE4 Call Back Functions to retrieve the parameter description and parameter values. The Call Back Functions are described below.

Use function `ncxr_if4_callnat`, to execute a Natural subprogram from the C program.

Prototype:

```

int ncxr_if4_callnat ( char *natpgm, int parmnum, struct parameter_description
*descr );

```

Parameter description:

natpgm	Name of the Natural subprogram to be invoked.	
parmnum	Number of parameter fields to be passed to the subprogram.	
descr	Address of a struct parameter_description. See Operand Structure for INTERFACE4 for a detailed description of this structure.	
return	Return Value:	Information:
	0	OK If a Natural error occurs while the subprogram is executed, information about this error will be returned in the variable natpgm in the form *NATnnnn, where nnnn is the corresponding Natural error number.
	-1	Illegal parameter number.
	-2	Internal error.

The following topics are covered below:

- [Example of Calling a C Program via Standard CALL](#)
- [Example of Calling a C Program via CALL INTERFACE4](#)

Example of Calling a C Program via Standard CALL

```

** Example 'CALEX4': CALL PROGRAM 'ADD'
*****
DEFINE DATA LOCAL
1 #OP1 (I4)
1 #OP2 (I4)
1 #SUM (I4)
END-DEFINE
*
CALL 'ADD' #OP1 #OP2 #SUM
DISPLAY #SUM
*
END

```

Called C program ADD:

```

/*
** Example C Program ADD.c
*/
NATFCT ADD (int *op1, int *op2, int *sum)
{
sum = *op1 + *op2;    /* add operands */

return 0;              /* return successfully */
} /* ADD */

```


Example of Calling a C Program via CALL INTERFACE4

```

** Example 'CALEX5': CALL PROGRAM 'ADD4'
*****
DEFINE DATA LOCAL
1 #OP1  (I4)
1 #OP2  (I4)
1 #SUM  (I4)
END-DEFINE
*
CALL INTERFACE4 'ADD4' #OP1 #OP2 #SUM
DISPLAY #SUM
*
END

```

Called C program ADD4:

```

NATFCT ADD4 NATARGDEF(numparm, parmhandle, parmdec)
{
  NATTYP_I4 op1, op2, sum;          /* local integers */
  int i;                            /* loop counter */
  struct parameter_description desc;
  int rc;                           /* return code access functions */

  /*
  ** test number of arguments
  */
  if (numparm != 3) return 1;

  /*
  ** test types of arguments
  */
  for (i = 0; i < (int) numparm; i++)
  {
    rc = ncxr_get_parm_info( i, parmhandle, &desc );
    if ( rc ) return rc;

    if ( desc.format != 'I' || desc.length != sizeof(NATTYP_I4) || desc.dimensions
    != 0 )
    {
      return 2;          /* invalid parameter */
    }
  }

  /*
  ** get arguments
  */
  rc = ncxr_get_parm( 0, parmhandle, sizeof op1, (void *)&op1 );
  if ( rc ) return rc;

  rc = ncxr_get_parm( 1, parmhandle, sizeof op2, (void *)&op2 );

```

```
if ( rc ) return rc;

/*
** perform the addition
*/
sum = op1 + op2;

/*
** move the result back to operand 3
*/
rc = ncxr_put_parm( 2, parmhandle, sizeof sum, (void *)&sum );
if ( rc ) return rc;

/*
** all ok, return success to the caller
*/
return 0;
} /* ADD4 */
```

INTERFACE4

The keyword `INTERFACE4` specifies the type of the interface that is used for the call of the external program. This keyword is optional. If this keyword is specified, the interface, which is defined as `INTERFACE4`, is used for the call of the external program.

The following table lists the differences between the `CALL` statement used with `INTERFACE4` and the one used without `INTERFACE4`:

	CALL statement without keyword INTERFACE4	CALL statement with keyword INTERFACE4
Number of parameters possible	128	16370 or less
Maximum data size of one parameter	no restriction	1 GB
Retrieve array information	no	yes
Support of large and dynamic operands	full read access, write without changing size of operand	yes
Parameter access via API	direct	via API

The maximum number of parameters is limited by the maximum size of the generated program (GP) and by the maximum size of a statement. 16370 parameters are possible if the program contains only the `CALL` statement. The maximum number is lower if other statements are used.

The following topics are covered below:

- [INTERFACE4 - External 3GL Program Interface](#)
- [Operand Structure for INTERFACE4](#)

- [INTERFACE4 - Parameter Access](#)
- [Exported Functions](#)

INTERFACE4 - External 3GL Program Interface

The interface of the external 3GL program is defined as follows, when `INTERFACE4` is specified with the `Natural CALL` statement:

```
NATFCT functionname (numparm, parmhandle, traditional)
```

USR_WORD	numparm;	16 bit unsigned short value, containing the total number of transferred operands (<i>operand2</i>).
void	*parmhandle;	Pointer to the parameter passing structure.
void	*traditional;	Check for interface type (if it is not a NULL pointer it is the traditional <code>CALL</code> interface).

Operand Structure for INTERFACE4

The operand structure of `INTERFACE4` is named `parameter_description` and is defined as follows. The structure is delivered with the header file *natuser.h*.

struct parameter_description			
void *	address	Address of the parameter data, not aligned, realloc() and free() are not allowed.	
int	format	Field data format: NCXR_TYPE_ALPHA, etc. (natuser.h).	
int	length	Length (before decimal point, if applicable).	
int	precision	Length after decimal point (if applicable).	
int	byte_length	Length of field in bytes int dimension number of dimensions (0 to IF4_MAX_DIM).	
int	dimensions	Number of dimensions (0 to IF4_MAX_DIM).	
int	length_all	Total data length of array in bytes.	
int	flags	Several flag bits combined by bitwise OR operation, meaning:	
		IF4_FLG_PROTECTED:	The parameter is write-protected.
		IF4_FLG_DYNAMIC:	The parameter is a dynamic variable.
		IF4_FLG_NOT_CONTIGUOUS:	The array elements are not contiguous (have spaces between them).
		IF4_FLG_AIV:	The parameter is an application-independent variable.
		IF4_FLG_DYNVAR:	The parameter is a dynamic variable.

		IF4_FLG_XARRAY:	The parameter is an X-array.
		IF4_FLG_LBVAR_0:	The lower bound of dimension 0 is variable.
		IF4_FLG_UBVAR_0:	The upper bound of dimension 0 is variable.
		IF4_FLG_LBVAR_1:	The lower bound of dimension 1 is variable.
		IF4_FLG_UBVAR_1:	The upper bound of dimension 1 is variable.
		IF4_FLG_LBVAR_2:	The lower bound of dimension 2 is variable.
		IF4_FLG_UBVAR_2:	The upper bound of dimension 2 is variable.
int	occurrences[IF4_MAX_DIM]	Array occurrences in each dimension.	
int	indexfactors[IF4_MAX_DIM]	Array index factors for each dimension.	
void *	dynp	Reserved for internal use.	
void *	pops	Reserved for internal use.	

The address element is null for arrays of dynamic variables and for X-arrays. In these cases, the array data cannot be accessed as a whole, but must be accessed through the parameter access functions described below.

For arrays with fixed bounds of variables with fixed length, the array contents can be accessed directly using the address element. In these cases the address of an array element (i,j,k) is computed as follows (especially if the array elements are not contiguous):

```
elementaddress = address + i * indexfactors[0] + j * indexfactors[1] + k * ↵
indexfactors[2]
```

If the array has less than 3 dimensions, leave out the last terms.

INTERFACE4 - Parameter Access

A set of functions is available to be used for the access of the parameters. The process flow is as follows:

- The 3GL program is called via the `CALL` statement with the `INTERFACE4` option, and the parameters are passed to the 3GL program as described above.
- The 3GL program can now use the exported functions of Natural, to retrieve either the parameter data itself, or information about the parameter, such as format, length, array information, etc.
- The **exported functions** can also be used to pass back parameter data.

There are also functions to create and initialize a new parameter set in order to call arbitrary sub-programs from a 3GL program. With this technique a parameter access is guaranteed to avoid

memory overwrites done by the 3GL program. (Natural's data is safe: memory overwrites within the 3GL program's data are still possible).

Exported Functions

The following topics are covered below:

- [Get Parameter Information](#)
- [Get Parameter Data](#)
- [Write Back Operand Data](#)
- [Create, Initialize and Delete a Parameter Set](#)
- [Create Parameter Set](#)
- [Delete Parameter Set](#)
- [Initialize a Scalar of a Static Data Type](#)
- [Initialize an Array of a Static Data Type](#)
- [Initialize a Scalar of a Dynamic Data Type](#)
- [Initialize an Array of a Dynamic Data Type](#)
- [Resize an X-array Parameter](#)

Get Parameter Information

This function is used by the 3GL program to receive all necessary information from any parameter. This information is returned in the `struct parameter_description`, which is documented [above](#).

Prototype:

```
int ncxr_get_parm_info ( int parmnum, void *parmhandle, struct parameter_description *descr );
```

Parameter Description:

parmnum	Ordinal number of the parameter. This identifies the parameter of the passed parameter list. Range: 0 ... numparm-1.	
parmhandle	Pointer to the internal parameter structure	
descr	Address of a <code>struct parameter_description</code>	
return	Return Value:	Information:
	0	OK
	-1	Illegal parameter number.
	-2	Internal error.
	-7	Interface version conflict.

Get Parameter Data

This function is used by the 3GL program to get the data from any parameter.

Natural identifies the parameter by the given parameter number and writes the parameter data to the given buffer address with the given buffer size.

If the parameter data is longer than the given buffer size, Natural will truncate the data to the given length. The external 3GL program can make use of the function `ncxr_get_parm_info`, to request the length of the parameter data.

There are two functions to get parameter data: `ncxr_get_parm` gets the whole parameter (even if the parameter is an array), whereas `ncxr_get_parm_array` gets the specified array element.

If no memory of the indicated size is allocated for “buffer” by the 3GL program (dynamically or statically), results of the operation are unpredictable. Natural will only check for a null pointer.

If data gets truncated for variables of the type I2/I4/F4/F8 (buffer length not equal to the total parameter length), the results depend on the machine type (little endian/big endian). In some applications, the user exit must be programmed to use no static data to make recursion possible.

Prototypes:

```
int ncxr_get_parm( int parmnum, void *parmhandle, int buffer_length, void *buffer )

int ncxr_get_parm_array( int parmnum, void *parmhandle, int buffer_length, void *buffer, int *indexes )
```

This function is identical to `ncxr_get_parm`, except that the indexes for each dimension can be specified. The indexes for unused dimensions should be specified as 0.

Parameter Description:

parmnum	Ordinal number of the parameter. This identifies the parameter of the passed parameter list. Range: 0 ... numparm-1.	
parmhandle	Pointer to the internal parameter structure	
buffer_length	Length of the buffer, where the requested data has to be written to	
buffer	Address of buffer, where the requested data has to be written to. This buffer should be aligned to allow easy access to I2/I4/F4/F8 variables.	
indexes	Array with index information	
return	Return Value:	Information:
	< 0	Error during retrieval of the information:
	-1	Illegal parameter number.
	-2	Internal error.
	-3	Data has been truncated.

	-4	Data is not an array.
	-7	Interface version conflict.
	-100	Index for dimension 0 is out of range.
	-101	Index for dimension 1 is out of range.
	-102	Index for dimension 2 is out of range.
	0	Successful operation.
	> 0	Successful operation, but the data was only this number of bytes long (buffer was longer than the data).

Write Back Operand Data

These functions are used by the 3GL program to write back the data to any parameter. Natural identifies the parameter by the given parameter number and writes the parameter data from the given buffer address with the given buffer size to the parameter data. If the parameter data is shorter than the given buffer size, the data will be truncated to the parameters data length, that is, the rest of the buffer will be ignored. If the parameter data is longer than the given buffer size, the data will be copied only to the given buffer length, the rest of the parameter stays untouched. This applies to arrays in the same way. For dynamic variables as parameters, the parameter is resized to the given buffer length.

If data gets truncated for variables of the type I2/I4/F4/F8 (buffer length not equal to the total parameter length), the results depend on the machine type (little endian/big endian). In some applications, the user exit must be programmed to use no static data to make recursion possible.

Prototypes:

```
int ncxr_put_parm      ( int parmnum, void *parmhandle,
                        int buffer_length, void *buffer );
int ncxr_put_parm_array ( int parmnum, void *parmhandle,
                        int buffer_length, void *buffer,
                        int *indexes );
```

Parameter Description:

parmnum	Ordinal number of the parameter. This identifies the parameter of the passed parameter list. Range: 0 ... numparm-1.	
parmhandle	Pointer to the internal parameter structure.	
buffer_length	Length of the data to be copied back to the address of buffer, where the data comes from.	
indexes	Index information	
return	Return Value:	Information:
	< 0	Error during copying of the information:
	-1	Illegal parameter number.

-2	Internal error.
-3	Too much data has been given. The copy back was done with parameter length.
-4	Parameter is not an array.
-5	Parameter is protected (constant or AD=0).
-6	Dynamic variable could not be resized due to an “out of memory” condition.
-7	Interface version conflict.
-13	The given buffer includes an incomplete Unicode character.
-100	Index for dimension 0 is out of range.
-101	Index for dimension 1 is out of range.
-102	Index for dimension 2 is out of range.
0	Successful operation.
> 0	Successful operation, but the parameter was this number of bytes long (length of parameter greater than given length).

Create, Initialize and Delete a Parameter Set

If a 3GL program wants to call a Natural subprogram, it needs to build a parameter set that corresponds to the parameters the subprogram expects. The function `ncxr_create_parm` is used to create a set of parameters to be passed with a call to `ncxr_if_callnat`. The set of parameters created is represented by an opaque parameter handle, like the parameter set that is passed to the 3GL program with the `CALL INTERFACE4` statement. Thus, the newly created parameter set can be manipulated with functions `ncxr_put_parm*` and `ncxr_get_parm*` as described above.

The newly created parameter set is not yet initialized after having called the function `ncxr_create_parm`. An individual parameter is initialized to a specific data type by a set of `ncxr_parm_init*` functions described below. The functions `ncxr_put_parm*` and `ncxr_get_parm*` are then used to access the contents of each individual parameter. After the caller has finished with the parameter set, they must delete the parameter handle. Thus, a typical sequence in creating and using a set of parameters for a subprogram to be called through `ncxr_if4_callnat` will be:

```
ncxr_create_parm
ncxr_init_ parm*
ncxr_init_ parm*
...
ncxr_put_ parm*
ncxr_put_ parm*
...
ncxr_get_parm_info*
ncxr_get_parm_info*
...
ncxr_if4_callnat
```



```

...
ncxr_get_parm_info*
ncxr_get_parm_info*
...
ncxr_get_parm*
ncxr_get_parm*
...
ncxr_delete_parm

```

Create Parameter Set

The function `ncxr_create_parm` is used to create a set of parameters to be passed with a call to `ncxr_if_callnat`.

Prototype:

```
int ncxr_create_parm( int parmnum, void** pparmhandle )
```

Parameter Description:

parmnum	Number of parameters to be created.	
pparmhandle	Pointer to the created parameter handle.	
return	Return Value:	Information:
	< 0	Error:
	-1	Illegal parameter count.
	-2	Internal error.
	-6	Out of memory condition.
	0	Successful operation.

Delete Parameter Set

The function `ncxr_delete_parm` is used to delete a set of parameters that was created with `ncxr_create_parm`.

Prototype:

```
int ncxr_delete_parm( void* parmhandle )
```

Parameter Description:

parmhandle	Pointer to the parameter handle to be deleted.	
return	Return Value:	Information:
	< 0	Error:
	-2	Internal error.
	0	Successful operation.

Initialize a Scalar of a Static Data Type

Prototype:

```
int ncxr_init_parm_s( int parmnum, void *parmhandle,
    char format, int length, int precision, int flags );
```

Parameter Description:

parmnum	Ordinal number of the parameter. This identifies the parameter in the passed parameter list. Range: 0 ... numparm-1.	
parmhandle	Pointer to the parameter handle.	
format	Format of the parameter.	
length	Length of the parameter.	
precision	Precision of the parameter.	
flags	IF4_FLG_PROTECTED	
return	Return Value:	Information:
	< 0	Error:
	-1	Invalid parameter number.
	-2	Internal error.
	-6	Out of memory condition.
	-8	Invalid format.
	-9	Invalid length or precision.
	0	Successful operation.

Initialize an Array of a Static Data Type

Prototype:

```
int ncxr_init_parm_sa( int parmnum, void *parmhandle,
    char format, int length, int precision,
    int dim, int *occ, int flags );
```

Parameter Description:

parmnum	Ordinal number of the parameter. This identifies the parameter in the passed parameter list. Range: 0 ... numparm-1.	
parmhandle	Pointer to the parameter handle.	
format	Format of the parameter.	
length	Length of the parameter.	
precision	Precision of the parameter.	
dim	Dimension of the array.	
occ	Number of occurrences per dimension.	
flags	A combination of the flags IF4_FLG_PROTECTED IF4_FLG_LBVAR_0 IF4_FLG_UBVAR_0 IF4_FLG_LBVAR_1 IF4_FLG_UBVAR_1 IF4_FLG_LBVAR_2 IF4_FLG_UBVAR_2	
return	Return Value:	Information:
	< 0	Error:
	-1	Invalid parameter number.
	-2	Internal error.
	-6	Out of memory condition.
	-8	Invalid format.
	-9	Invalid length or precision.
	-10	Invalid dimension count.
	-11	Invalid combination of variable bounds.
	0	Successful operation.

Initialize a Scalar of a Dynamic Data Type

Prototype:

```
int ncxr_init_parm_d( int parmnum, void *parmhandle,
    char format, int flags );
```

Parameter Description:

parmnum	Ordinal number of the parameter. This identifies the parameter in the passed parameter list. Range: 0 ... numparm-1.	
parmhandle	Pointer to the parameter handle.	
format	Format of the parameter.	
flags	IF4_FLG_PROTECTED	
return	Return Value:	Information:
	< 0	Error:
	-1	Invalid parameter number.
	-2	Internal error.
	-6	Out of memory condition.
	-8	Invalid format.
	0	Successful operation.

Initialize an Array of a Dynamic Data Type

Prototype:

```
int ncxr_init_parm_da( int parmnum, void *parmhandle,
    char format, int dim, int *occ, int flags );
```

Parameter Description:

parmnum	Ordinal number of the parameter. This identifies the parameter in the passed parameter list. Range: 0 ... numparm-1.	
parmhandle	Pointer to the parameter handle.	
format	Format of the parameter.	
dim	Dimension of the array.	
occ	Number of occurrences per dimension.	
flags	A combination of the flags IF4_FLG_PROTECTED IF4_FLG_LBVAR_0 IF4_FLG_UBVAR_0 IF4_FLG_LBVAR_1 IF4_FLG_UBVAR_1 IF4_FLG_LBVAR_2 IF4_FLG_UBVAR_2	
return	Return Value:	Information:
	< 0	Error:
	-1	Invalid parameter number.
	-2	Internal error.
	-6	Out of memory condition.

	-8	Invalid format.
	-10	Invalid dimension count.
	-11	Invalid combination of variable bounds.
	0	Successful operation.

Resize an X-array Parameter

Prototype:

```
int ncxr_resize_parm_array( int parmnum, void *parmhandle, int *occ );
```

Parameter Description:

parmnum	Ordinal number of the parameter. This identifies the parameter in the passed parameter list. Range: 0 ... numparm-1.	
parmhandle	Pointer to the parameter handle.	
occ	New number of occurrences per dimension.	
return	Return Value:	Information:
	< 0	Error:
	-1	Invalid parameter number.
	-2	Internal error.
	-6	Out of memory condition.
	-12	Operand is not resizable (in one of the specified dimensions).
	0	Successful operation.

All function prototypes are declared in the file `natuser.h`.

23

CALL FILE

■ Function	194
■ Restriction	194
■ Syntax Description	194
■ Example	196

Structured Mode Syntax

```
CALL FILE 'program-name' operand1 operand2
    statement ...
END-FILE
```

Reporting Mode Syntax

```
CALL FILE 'program-name' operand1 operand2
    statement ...
LOOP
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [CALL](#) | [CALL LOOP](#) | [CALLNAT](#) | [DEFINE SUBROUTINE](#) | [ESCAPE](#) | [FETCH](#) | [PERFORM](#)

Belongs to Function Group: [Invoking Programs and Routines](#)

Function

The `CALL FILE` statement is used to call a non-Natural program which reads a record from a non-Adabas file and returns the record to the Natural program for processing.

Restriction

The statements [AT BREAK](#), [AT START OF DATA](#) and [AT END OF DATA](#) must not be used within a `CALL FILE` processing loop.

Syntax Description

Operand Definition Table:

Operand	Possible Structure			Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>		S	A	A U N P I F B D T L C	yes	yes
<i>operand2</i>		S	A G	A U N P I F B D T L C	yes	yes

Syntax Element Description:

Syntax Element	Description
' <i>program-name</i> '	Program to be Called: The name of the non-Natural program to be called. The length of the program name should be 1 to 8.
<i>operand1</i>	Control Field: <i>operand1</i> is used to provide control information.
<i>operand2</i>	Record Area: <i>operand2</i> defines the record area. The format of the record to be read can be described using field definitions (or FILLER <i>nX</i>) entries following the name of the first field in the record. The fields used to define the record format must not have been previously defined in the Natural program. This ensures that fields are allocated in the contiguous storage by Natural.
<i>statement ...</i>	Processing Loop: The CALL FILE statement initiates a processing loop which must be terminated with an ESCAPE or STOP statement. More than one ESCAPE statement may be specified to escape from a CALL FILE loop based on different conditions.
END-FILE	End of CALL FILE Statement: In structured mode, the Natural reserved keyword END-FILE must be used to end the CALL FILE statement. In reporting mode, the Natural statement LOOP is used to end the CALL FILE statement.
LOOP	

Example

Calling Program:

```

** Example 'CFIEX1': CALL FILE
*****
DEFINE DATA LOCAL
1 #CONTROL (A3)
1 #RECORD
  2 #A      (A10)
  2 #B      (N3.2)
  2 #FILL1  (A3)
  2 #C      (P3.1)
END-DEFINE
*
CALL FILE 'USER1' #CONTROL #RECORD
  IF #CONTROL = 'END'
    ESCAPE BOTTOM
  END-IF
END-FILE
/*****
/* ... PROCESS RECORD ...
/*****
END

```

The byte layout of the record passed by the called program to the Natural program in the above example is as follows:

```

CONTROL #A      #B      FILLER #C
(A3)    (A10)    (N3.2) 3X    (P3.1)

xxx xxxxxxxxxxx xxxxx   xxx   xxx

```

Called COBOL Program:

```

ID DIVISION.
PROGRAM-ID. USER1.
ENVIRONMENT DIVISION.
INPUT-OUTPUT SECTION.
FILE-CONTROL.
    SELECT USRFILE ASSIGN UT-S-FILEUSR.
DATA DIVISION.
FILE SECTION.
FD  USRFILE RECORDING F LABEL RECORD OMITTED
    DATA RECORD DATA-IN.
01  DATA-IN          PIC X(80).
LINKAGE SECTION.
01  CONTROL-FIELD     PIC XXX.

```

```
01  RECORD-IN      PIC X(21).  
PROCEDURE DIVISION USING CONTROL-FIELD RECORD-IN.  
BEGIN.  
    GO TO FILE-OPEN.  
FILE-OPEN.  
    OPEN INPUT USRFILE  
    MOVE SPACES TO CONTROL-FIELD.  
    ALTER BEGIN TO PROCEED TO FILE-READ.  
FILE-READ.  
    READ USRFILE INTO RECORD-IN  
    AT END  
        MOVE 'END' TO CONTROL-FIELD  
        CLOSE USRFILE  
        ALTER BEGIN TO PROCEED TO FILE-OPEN.  
GOBACK.
```


24

CALL LOOP

■ Function	200
■ Restriction	200
■ Syntax Description	201
■ Example	201

Structured Mode Syntax

```
CALL LOOP operand1 [operand2] ...40
    statement ...
END-LOOP
```

Reporting Mode Syntax

```
CALL LOOP operand1 [operand2] ...40
    statement ...
LOOP
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [CALL](#) | [CALL FILE](#) | [CALLNAT](#) | [DEFINE SUBROUTINE](#) | [ESCAPE](#) | [FETCH](#) | [PERFORM](#)

Belongs to Function Group: [Invoking Programs and Routines](#)

Function

The `CALL LOOP` statement is used to generate a processing loop that contains a call to a non-Natural program.

Unlike the [CALL](#) statement, the `CALL LOOP` statement results in a processing loop which is used to repeatedly call the non-Natural program. See the [CALL](#) statement for a detailed description of the `CALL` processing.

Restriction

The statements [AT BREAK](#), [AT START OF DATA](#) and [AT END OF DATA](#) must not be used within a `CALL LOOP` processing loop.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S				A												yes	no
<i>operand2</i>	C	S	A	G		A	U	N	P	I	F	B	D	T	L	C		yes	yes

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Program to be Called: The name of the non-Natural program to be called can be specified as a constant or - if different programs are to be called dependent on program logic - as an alphanumeric variable of length 1 to 8. A program name must be placed left-justified in the variable.
<i>operand2</i>	Parameters: The CALL LOOP statement can have a maximum of 40 parameters. The parameter list is constructed as described for the CALL statement. Fields used in the parameter list may be initially defined in the CALL LOOP statement itself or may have been previously defined.
<i>statement ...</i>	Processing Loop: The CALL LOOP statement initiates a processing loop which must be terminated with an ESCAPE statement.
END-LOOP	End of CALL LOOP Statement: In structured mode, the Natural reserved word END-LOOP must be used to end the CALL LOOP statement. In reporting mode, the Natural statement LOOP is used to end the CALL LOOP statement.
LOOP	

Example

```

DEFINE DATA LOCAL
1 PARAMETER1 (A10)
END-DEFINE
CALL LOOP 'ABC' PARAMETER1
  IF PARAMETER1 = 'END'
    ESCAPE BOTTOM
  END-IF
END-LOOP
END

```


25

CALLDBPROC (SQL)

■ Function	204
■ Restriction	205
■ Syntax Description	205
■ Example	207

```
CALLDBPROC dbproc ddm-name
[ [USING] { parameter [ AD= { M
                                O
                                A } ] } ... ]
[RESULT SETS result-set...]
[GIVING sqlcode]
[ CALLMODE= { NONE
              NATURAL } ]
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Belongs to Function Group: [Database Access and Update](#)

See also *CALLDBPROC - SQL* in the *Natural for DB2* part of the *Database Management System Interfaces* documentation.

Function

The `CALLDBPROC` statement is used to invoke a stored procedure of the SQL database system to which Natural is connected.

The stored procedure can be either a Natural subprogram (only available when executed from DB2 for z/OS) or a program written in another programming language.

In addition to the passing of parameters between the invoking object and the stored procedure, `CALLDBPROC` supports “result sets”; these make it possible to return a larger amount of data from the stored procedure to the invoking object than would be possible via parameters.

The result sets are “temporary result tables” which are created by the stored procedure and which can be read and processed by the invoking object via a `READ RESULT SET` statement.



Note: In general, the invoking of a stored procedure could be compared with the invoking of a Natural subprogram: when the `CALLDBPROC` statement is executed, control is passed to the stored procedure; after processing of the stored procedure, control is returned to the invoking object and processing continues with the statement following the `CALLDBPROC` statement.

Restriction

This statement is available only with Natural for DB2.

Syntax Description

Syntax Element	Description						
<i>dbproc</i>	Stored Procedure to be Invoked: As <i>dbproc</i> you specify the name of the stored procedure to be invoked. The name can be specified either as an alphanumeric variable or as a constant (enclosed in apostrophes). The name must adhere to the rules for stored procedure names of the target database system. If the stored procedure is a Natural subprogram, the actual procedure name must not be longer than 8 characters.						
<i>dgm-name</i>	Name of a Natural Data Definition Module: The name of a DDM must be specified to provide the “address” of the database which executes the stored procedure. For further information, see dgm-name.						
[USING] <i>parameter</i>	Parameter(s) to be Passed: As <i>parameter</i>, you can specify parameters which are passed from the invoking object to the stored procedure. A <i>parameter</i> can be ■ a host-variable (optionally with INDICATOR and LINDICATOR clauses), ■ a constant, or ■ the keyword NULL. See further details on host-variable.						
AD=	Attribute Definition: If parameter is a <i>host-variable</i>, you can mark it as follows: <table> <tr> <td>AD=0</td><td>Non-modifiable, see session parameter AD=0. (Corresponding procedure notation in DB2 for z/OS: IN.)</td></tr> <tr> <td>AD=M</td><td>Modifiable, see session parameter AD=M. (Corresponding procedure notation in DB2 for z/OS: INOUT.)</td></tr> <tr> <td>AD=A</td><td>For input only, see session parameter AD=A.</td></tr> </table>	AD=0	Non-modifiable, see session parameter AD=0. (Corresponding procedure notation in DB2 for z/OS: IN.)	AD=M	Modifiable, see session parameter AD=M. (Corresponding procedure notation in DB2 for z/OS: INOUT.)	AD=A	For input only, see session parameter AD=A.
AD=0	Non-modifiable, see session parameter AD=0. (Corresponding procedure notation in DB2 for z/OS: IN.)						
AD=M	Modifiable, see session parameter AD=M. (Corresponding procedure notation in DB2 for z/OS: INOUT.)						
AD=A	For input only, see session parameter AD=A.						

Syntax Element	Description	
		(Corresponding procedure notation in DB2 for z/OS: OUT.)
	If <i>parameter</i> is a constant, AD cannot be explicitly specified. For constants, AD=0 always applies.	
RESULT SETS <i>result-set</i>	Field for Result-Set Locator Variable: As <i>result-set</i> you specify a field in which a result-set locator is to be returned. A result set has to be a variable of format/length I4. The value of a result set variable is merely a number which identifies the result set and which can be referenced in a subsequent READ RESULT SET statement. The sequence of the <i>result-set</i> values corresponds to the sequence of the result sets returned by the stored procedure. The contents of the result sets can be processed by a subsequent READ RESULT SET statement. If no result set is returned, the corresponding result-set variable will contain 0. Multiple result sets can be specified only when the stored procedure is invoked via Natural for DB2. See also <i>Result Sets</i> in the <i>Natural for DB2</i> part of the <i>Database Management System Interfaces</i> documentation.	
GIVING <i>sqlcode</i>	GIVING <i>sqlcode</i> Option: This option may be used to obtain the SQLCODE of the SQL CALL statement invoking the stored procedure. If this option is specified and the SQLCODE of the stored procedure is not 0, no Natural error message will be issued. In this case, the action to be taken in reaction to the SQLCODE value has to be coded in the invoking Natural object. The <i>sqlcode</i> field has to be a variable of format/length I4. If the GIVING <i>sqlcode</i> option is omitted, a Natural error message will be issued if the SQLCODE of the stored procedure is not 0.	
CALLMODE=	CALLMODE Parameter: Possible settings are:	
	CALLMODE=NATURAL	This setting applies if the stored procedure is a Natural subprogram which is defined with PARAMETER STYLE GENERAL or PARAMETER STYLE GENERAL WITH NULL , otherwise specify NONE (default).

Syntax Element	Description	
		This setting also has an impact on internal parameters that are passed to/from the stored procedure. For details, see <i>CALLMODE=NATURAL</i> in the section <i>CALLDBPROC</i> of the <i>Natural for DB2</i> documentation.
	CALLMODE=NONE	This is the default.

Example

The following example shows a Natural program that calls the stored procedure `DEMO_PROC` to retrieve all names of table `PERSON` that belong to a given range.

Three parameter fields are passed to `DEMO_PROC`: the first and second parameters pass starting and ending values of the range of names to the stored procedure, and the third parameter receives a name that meets the criterion.

In this example, the names are returned in a result set that is processed using the [READ RESULT SET](#) statement.

```

DEFINE DATA LOCAL
1 PERSON VIEW OF DEMO-PERSON
  2 PERSON_ID
  2 LAST_NAME
1 #BEGIN      (A2) INIT <'AB'>
1 #END        (A2) INIT <'DE'>
1 #RESPONSE   (I4)
1 #RESULT     (I4)
1 #NAME       (A20)
END-DEFINE

...

CALLDBPROC 'DEMO_PROC' DEMO-PERSON #BEGIN (AD=0) #END (AD=0) #NAME (AD=A)
      RESULT SETS #RESULT
      GIVING #RESPONSE

READ RESULT SET #RESULT INTO #NAME FROM DEMO-PERSON
      GIVING #RESPONSE
      DISPLAY #NAME
END-RESULT

...

END


```

For further examples, see *Example of CALLDBPROC/READ RESULT SET* in the section *CALLDBPROC* of the *Natural for DB2* documentation.

26

CALLNAT

■ Function	210
■ Syntax Description	211
■ Parameter Transfer with Dynamic Variables	213
■ Examples	214



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [CALL](#) | [CALL FILE](#) | [CALL LOOP](#) | [DEFINE SUBROUTINE](#) | [ESCAPE](#) | [FETCH](#) | [PERFORM](#)

Belongs to Function Group: [Invoking Programs and Routines](#)

Function

The `CALLNAT` statement is used to invoke a Natural subprogram for execution. (A Natural subprogram can only be invoked via a `CALLNAT` statement; it cannot be executed by itself.)

When the `CALLNAT` statement is executed, the execution of the invoking object (that is, the object containing the `CALLNAT` statement) will be suspended and the invoked subprogram will be executed. The execution of the subprogram continues until either its `END` statement is reached or processing of the subprogram is stopped by an [ESCAPE ROUTINE](#) statement being executed. In either case, processing of the invoking object will then continue with the statement following the `CALLNAT` statement.



Notes:

1. A subprogram can in turn invoke other subprograms.
2. A subprogram has no access to the global data area used by the invoking object. If a subprogram in turn invokes a subroutine or helproutine, it can establish its own global data area to be shared with the subroutine/helproutine.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats															Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S				A															yes	no
<i>operand2</i>	C	S	A	G		A	U	N	P	I	F	B	D	T	L	C	G	O			yes	yes

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Subprogram to be Invoked: As <i>operand1</i>, you specify the name of the subprogram to be invoked. The name may be specified either as a constant of 1 to 8 characters, or - if different subprograms are to be called dependent on program logic - as an alphanumeric variable of length 1 to 8. The case of the specified name is not translated. The subprogram name may contain an ampersand (&); at execution time, this character will be replaced by the one-character code corresponding to the current value of the system variable *LANGUAGE. This makes it possible, for example, to invoke different subprograms for the processing of input, depending on the language in which input is provided.
<i>operand2</i>	Parameters: If parameters are passed to the subprogram, the structure of the parameter list must be defined in a DEFINE DATA PARAMETER statement. The parameters specified with the CALLNAT statement are the only data available to the subprogram from the invoking object. By default, the parameters are passed <i>by reference</i>, that is, the data are transferred via address parameters, the parameter values themselves are not moved. However, it is also possible to pass parameters <i>by value</i>, that is, pass the actual parameter values. To do so, you define these fields in the DEFINE DATA PARAMETER statement of the subprogram with the option BY VALUE or BY VALUE RESULT (see <i>parameter-data-definition</i> in the description of the DEFINE DATA statement). ■ If parameters are passed <i>by reference</i>, the following applies: The sequence, format and length of the parameters in the invoking object must match exactly the sequence, format and length of the DEFINE DATA PARAMETER structure in the invoked subprogram. The names of the variables in the invoking object and the invoked subprogram may be different. ■ If parameters are passed <i>by value</i>, the following applies: The sequence of the parameters in the invoking object must match exactly the sequence in the DEFINE DATA PARAMETER structure of the invoked subprogram. Formats and lengths of the variables in the invoking object and the subprogram may be different; however, they have to be data transfer compatible;

Syntax Element	Description						
	see the corresponding table in the section <i>Rules for Arithmetic Assignments, Data Transfer</i> in the <i>Programming Guide</i>. The names of the variables in the invoking object and the subprogram may be different. If parameter values that have been modified in the subprogram are to be passed back to the invoking object, you have to define these fields with BY VALUE RESULT. When BY VALUE is specified without RESULT, it is not possible to pass modified parameter values back to the invoking object (regardless of the AD specification; see also below). Note: With BY VALUE, an internal copy of the parameter values is created. The subprogram accesses this copy and can modify it, but this will not affect the original parameter values in the invoking object. With BY VALUE RESULT, an internal copy is likewise created, however, after termination of the subprogram, the original parameter values are overwritten by the (modified) values of the copy. For both ways of passing parameters, the following applies: If a group is specified as <i>operand2</i>, the individual fields contained in that group are passed to the subprogram; that is, for each of these fields a corresponding field must be defined in the subprogram's parameter data area. In the parameter data area of the invoked subprogram, a redefinition of groups is only permitted within a REDEFINE block. If an array is passed, its number of dimensions and occurrences in the subprogram's parameter data area must be the same as in the CALLNAT parameter list. Note: If multiple occurrences of an array that is defined as part of an indexed group are passed with the CALLNAT statement, the corresponding fields in the subprogram's parameter data area must not be redefined, as this would lead to the wrong addresses being passed. When the option PCHECK of the COMPOPT command is set to ON, the compiler will check the number, format, length and array index bounds of the parameters that are specified in a CALLNAT statement. Also, the OPTIONAL feature of the DEFINE DATA PARAMETER statement is considered in the parameter check.						
AD=	Attribute Definition: If <i>operand2</i> is a variable, you can mark it in one of the following ways: <table> <tr> <td>AD=0</td><td>Non-modifiable, see session parameter AD=0. Note: Internally, AD=0 is processed in the same way as BY VALUE (see parameter-data-definition in the description of the DEFINE DATA statement).</td></tr> <tr> <td>AD=M</td><td>Modifiable, see session parameter AD=M. This is the default setting.</td></tr> <tr> <td>AD=A</td><td>Input only, see session parameter AD=A.</td></tr> </table> If <i>operand2</i> is a constant, AD cannot be explicitly specified. For constants AD=0 always applies.	AD=0	Non-modifiable, see session parameter AD=0. Note: Internally, AD=0 is processed in the same way as BY VALUE (see parameter-data-definition in the description of the DEFINE DATA statement).	AD=M	Modifiable, see session parameter AD=M. This is the default setting.	AD=A	Input only, see session parameter AD=A.
AD=0	Non-modifiable, see session parameter AD=0. Note: Internally, AD=0 is processed in the same way as BY VALUE (see parameter-data-definition in the description of the DEFINE DATA statement).						
AD=M	Modifiable, see session parameter AD=M. This is the default setting.						
AD=A	Input only, see session parameter AD=A.						

Syntax Element	Description
<i>nX</i>	Parameters to be Skipped: With the notation <i>nX</i> you can specify that the next <i>n</i> parameters are to be skipped (for example, 1X to skip the next parameter, or 3X to skip the next three parameters); this means that for the next <i>n</i> parameters no values are passed to the subprogram. The possible range of values for <i>n</i> is 1 - 4096. A parameter that is to be skipped must be defined with the keyword OPTIONAL in the subprogram's DEFINE DATA PARAMETER statement. OPTIONAL means that a value can - but need not - be passed from the invoking object to such a parameter.

Parameter Transfer with Dynamic Variables

Dynamic variables may be passed as parameters to a called program object (CALLNAT, **PERFORM**). A call by reference is possible because the value space of a dynamic variable is contiguous. A call by value causes an assignment with the variable definition of the caller as the source operand and the parameter definition as the destination operand. In addition, a call by value result causes the movement to change to the opposite direction. When using a call-by-reference, both definitions must be **DYNAMIC**. If only one of them is **DYNAMIC**, a runtime error is raised. In case of a call by value (result) all combinations are possible.

The following table illustrates the valid combinations of statically and dynamically defined variables of the caller, and statically and dynamically defined parameters concerning the parameter transfer.

Call By Reference

<i>operand2</i> of caller	Parameter definition	
	Static	Dynamic
Static	yes	no
Dynamic	no	yes

The formats of the dynamic variables A or B must match.

Call by Value (Result)

<i>operand2</i> of caller	Parameter definition	
	Static	Dynamic
Static	yes	yes
Dynamic	yes	yes



Note: When using static/dynamic or dynamic/static definitions, a value truncation may occur according to the data transfer rules of the appropriate assignments.

Examples

- [Example 1](#)
- [Example 2](#)

Example 1

Calling Program:

```
** Example 'CNTEX1': CALLNAT
*****
DEFINE DATA LOCAL
1 #FIELD1 (N6)
1 #FIELD2 (A20)
1 #FIELD3 (A10)
END-DEFINE
*
CALLNAT 'CNTEX1N' #FIELD1 (AD=M) #FIELD2 (AD=0) #FIELD3 'P4 TEXT'
*
WRITE '=' #FIELD1 '=' #FIELD2 '=' #FIELD3
*
END
```

Called Subprogram CNTEX1N:

```
** Example 'CNTEX1N': CALLNAT (called by CNTEX1)
*****
DEFINE DATA PARAMETER
1 #FIELDA (N6)
1 #FIELDB (A20)
1 #FIELD C (A10)
1 #FIELD D (A7)
END-DEFINE
*
*
```

```

#FIELDA := 4711
*
#FIELDB := 'HALLO'
*
#FIELD C := 'ABC'
*
WRITE '=' #FIELD A '=' #FIELDB '=' #FIELD C '=' #FIELDD
*
END

```

Example 2

Calling Program:

```

** Example 'CNTEX2': CALLNAT
*****
DEFINE DATA LOCAL
1 #ARRAY1 (N4/1:10,1:10)
1 #NUM (N2)
END-DEFINE
*
*
CALLNAT 'CNTEX2N' #ARRAY1 (2:5,*)
*
FOR #NUM 1 TO 10
WRITE #NUM #ARRAY1(#NUM,1:10)
END-FOR
*
END

```

Called Subprogram CNTEX2N:

```

** Example 'CNTEX2N': CALLNAT (called by CNTEX2)
*****
DEFINE DATA
PARAMETER
1 #ARRAY (N4/1:4,1:10)
LOCAL
1 I (I2)
END-DEFINE
*
*
FOR I 1 10
#ARRAY(1,I) := I
#ARRAY(2,I) := 100 + I
#ARRAY(3,I) := 200 + I
#ARRAY(4,I) := 300 + I
END-FOR
*
END

```


27

CLOSE CONVERSATION

■ Function	218
■ Syntax Description	218
■ Further Information and Examples	219



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [DEFINE DATA CONTEXT](#) | [OPEN CONVERSATION](#)

Belongs to Function Group: [Natural Remote Procedure Call](#)

Function

The statement `CLOSE CONVERSATION` is used in conjunction with the Natural RPC (Remote Procedure Call). It allows the client to close conversations. You can close the current conversation, another open conversation, or all open conversations.

 **Note:** A logon to another library does not automatically close conversations.

Syntax Description

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	S A	I	yes	no

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Identifier of Conversation to be Closed: To close a specific open conversation, specify its ID as <i>operand1</i> . <i>operand1</i> must be a variable of format/length I4.
*CONVID	Closing the Current Conversation: To close the current conversation, specify *CONVID. The ID of the current conversation is determined by the value of the system variable *CONVID.
ALL	Closing All Open Conversations: To close all open conversations, specify ALL.

Further Information and Examples

See the following sections in the *Natural RPC (Remote Procedure Call)* documentation:

- *Natural RPC Operation in Conversational Mode*
- *Using a Conversational RPC*

V

■ 28 CLOSE PC FILE	223
■ 29 CLOSE PRINTER	227
■ 30 CLOSE WORK FILE	231
■ 31 COMMIT (SQL)	235
■ 32 COMPOSE	237
■ 33 COMPRESS	265
■ 34 COMPUTE	275
■ 35 CREATE OBJECT	283
■ 36 DECIDE FOR	287
■ 37 DECIDE ON	293
■ 38 DEFINE CLASS	299

28

CLOSE PC FILE

■ Function	224
■ Syntax Description	224
■ Example	224

`CLOSE { PC
WORK } [FILE] work-file-number`

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [DOWNLOAD PC FILE](#) | [UPLOAD PC FILE](#)

Belongs to Function Group: [Control of Work Files / PC Files](#)

Function

The statement `CLOSE PC FILE` is used to close a specific PC work file. It allows you to explicitly specify in a program that a PC work file is to be closed.

A work file is also closed automatically when command mode is reached.

The settings in the `NETWORK` macro apply.

See also the Natural Connection and Entire Connection documentation.

Syntax Description

Syntax Element	Description
<i>work-file-number</i>	The <i>work-file-number</i> is the number of the PC work file to be closed. This number must correspond to one of the work file numbers for the PC as defined to Natural.

Example

The following program demonstrates the use of the `CLOSE PC FILE` statement.

```
** Example 'PCCLEX1': CLOSE PC FILE
**
** NOTE: Example requires that Natural Connection is installed.
*****
DEFINE DATA LOCAL
01 W-DAT    (A40)
01 REC-NUM (N3)
01 I       (P3)
END-DEFINE
```

```
*
REPEAT
UPLOAD PC FILE 7 ONCE W-DAT          /* Data upload
  AT END OF FILE
  ESCAPE BOTTOM
  END-ENDFILE
  INPUT 'Processing file' W-DAT (AD=0)
  /   'Enter record number to display' REC-NUM
  IF REC-NUM = 0
    STOP
  END-IF
  FOR I = 1 TO REC-NUM
    UPLOAD PC FILE 7 ONCE W-DAT
    AT END OF FILE
      WRITE 'Max. record number reached, last record is'
      ESCAPE BOTTOM
    END-ENDFILE
  END-FOR
  I := I - 1
  WRITE 'Record' I ':' W-DAT
CLOSE PC FILE 7                      /* Close PC file 7
END-REPEAT
END
```

Output of Program PCCLEX1:

When you run the program, a window appears in which you specify the name of the PC file from which the data is to be uploaded. The data is then uploaded from the PC. At the end of each loop, the PC file is closed.

29

CLOSE PRINTER

■ Function	228
■ Syntax Description	228
■ Example	229

<code>CLOSE PRINTER</code> $\left\{ \begin{array}{l} (\textit{logical-printer-name}) \\ (\textit{printer-number}) \end{array} \right\}$

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [AT END OF PAGE](#) | [AT TOP OF PAGE](#) | [DEFINE PRINTER](#) | [DISPLAY](#) | [EJECT](#) | [FORMAT](#) | [NEWPAGE](#) | [PRINT](#) | [SKIP](#) | [SUSPEND IDENTICAL SUPPRESS](#) | [WRITE](#) | [WRITE TITLE](#) | [WRITE TRAILER](#)

Belongs to Function Group: [Creation of Output Reports](#)

Function

The `CLOSE PRINTER` statement is used to close a specific printer. With this statement, you explicitly specify in a program that a printer is to be closed.

A printer is also closed automatically in one of the following cases:

- when a [DEFINE PRINTER](#) statement in which the same printer is defined again is executed;
- when command mode is reached.

When a printer is closed, the profile associated with the printer (see [PROFILE](#) clause of the [DEFINE PRINTER](#) statement) is deleted, that is, any further writes to the printer are affected.

Syntax Description

Syntax Element	Description
<i>logical-printer-name</i>	Logical Printer Name: With the <i>logical-printer-name</i> you specify which printer is to be closed. The name is the same as in the corresponding DEFINE PRINTER statement in which you defined the printer. Naming conventions for the <i>logical-printer-name</i> are the same as for user-defined variables, see <i>Naming Conventions for User-Defined Variables</i> in <i>Using Natural</i> .
<i>printer-number</i>	Printer Number: Alternatively to the <i>logical-printer-name</i> , you may define the <i>printer-number</i> to specify which printer is to be closed. The <i>printer-number</i> may be a number in the range from 0 - 31. This is the number also to be used in a DISPLAY / WRITE or DEFINE PRINTER statement.

Syntax Element	Description
	Printer number 0 indicates the hardcopy printer.

Example

```

** Example 'CLPEX1': CLOSE PRINTER
*****
DEFINE DATA LOCAL
1 EMP-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
  2 FIRST-NAME
  2 BIRTH
*
1 #I-NAME (A20)
END-DEFINE
*
DEFINE PRINTER (PRT01=1)
*
REPEAT
  INPUT 'SELECT PERSON' #I-NAME
  IF #I-NAME = ' '
    STOP
  END-IF
  FIND EMP-VIEW WITH NAME = #I-NAME
  WRITE (PRT01) 'NAME           :' NAME ',' FIRST-NAME
              /      'PERSONNEL-ID :' PERSONNEL-ID
              /      'BIRTH          :' BIRTH (EM=YYYY-MM-DD)
  END-FIND
/*
  CLOSE PRINTER (PRT01)
/*
END-REPEAT
END

```


30

CLOSE WORK FILE

■ Function	232
■ Syntax Description	232
■ Example	233

CLOSE WORK [FILE] *work-file-number*

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [DEFINE WORK FILE](#) | [READ WORK FILE](#) | [WRITE WORK FILE](#)

Belongs to Function Group: [Control of Work Files / PC Files](#)

Function

The statement `CLOSE WORK FILE` is used to close a specific work file. It allows you to explicitly specify in a program that a work file is to be closed.

A work file is closed automatically:

- When command mode is reached.
- When an end-of-file condition occurs during the execution of a [READ WORK FILE](#) statement.
- Before a [DEFINE WORK FILE](#) statement is executed which assigns another data set to the work file number concerned.
- According to sub-parameter `CLOSE` of profile parameter `WORK`.

`CLOSE WORK FILE` is ignored for work files for which `CLOSE=FIN` is specified in profile parameter `WORK`.

Syntax Description

Syntax Element	Description
<i>work-file-number</i>	The number of the work file (as defined to Natural) to be closed.

Example

```

** Example 'CWFEX1': CLOSE WORK FILE
*****
DEFINE DATA LOCAL
1 W-DAT   (A20)
1 REC-NUM (N3)
1 I       (P3)
END-DEFINE
*
REPEAT
  READ WORK FILE 1 ONCE W-DAT  /* READ MASTER RECORD
  /*
  AT END OF FILE
    ESCAPE BOTTOM
  END-ENDFILE
  INPUT 'PROCESSING FILE' W-DAT (AD=0)
    / 'ENTER RECORDNUMBER TO DISPLAY' REC-NUM
  IF REC-NUM = 0
    STOP
  END-IF
  FOR I = 1 TO REC-NUM
    /*
    READ WORK FILE 1 ONCE W-DAT
    /*
    AT END OF FILE
      WRITE 'RECORD-NUMBER TOO HIGH, LAST RECORD IS'
      ESCAPE BOTTOM
    END-ENDFILE
  END-FOR
  I := I - 1
  WRITE 'RECORD' I ':' W-DAT
  /*
  CLOSE WORK FILE 1
  /*
END-REPEAT
END

```


31

COMMIT (SQL)

■ Function	236
■ Consideration for Non-Natural-Programs	236
■ Example	236

COMMIT

Belongs to Function Group: *Database Access and Update*

See also *COMMIT - SQL* in the *Natural for DB2* part of the *Database Management System Interfaces* documentation:

Function

The SQL `COMMIT` statement corresponds to the `END TRANSACTION` statement. It indicates the end of a logical transaction and releases all data locked during the transaction. All data modifications are committed and made permanent.



Important: As all cursors are closed when a logical unit of work ends, a `COMMIT` statement must not be placed within a database modification loop; instead, it has to be placed outside such a loop or after the outermost loop of nested loops.

Consideration for Non-Natural-Programs

If an external program written in another standard programming language is called from a Natural program, this external program should not contain its own `COMMIT` statement if the Natural program issues database calls, too. The calling Natural program should issue the `COMMIT` statement on behalf of the external program.

Example

```
...  
DELETE FROM SQL-PERSONNEL WHERE NAME = 'SMITH'  
COMMIT  
...
```

32

COMPOSE

■ Function	238
■ Syntax Description	239
■ Formatting Process	252
■ Dialog Mode Processing	253
■ Input/Output Processing by Non-Natural Programs	255
■ Examples	256

This statement can only be used if the office system Con-nect and the text formatter Con-form are installed.

```
COMPOSE
  [RESETTING-clause]
  [MOVING-clause]
  [ASSIGNING-clause]
  [FORMATTING-clause]
  [EXTRACTING-clause]
```

If you specify more than one clause, these clauses and their subclauses will be processed in the order shown above.

For explanations of the symbols used in the syntax diagrams, see [Syntax Symbols](#).

Function

The `COMPOSE` statement may be used to initiate text formatting by Con-form directly from a Natural program. Con-form is a text formatter which is automatically installed with Con-nect.

The text to be formatted can either be supplied using variables or it may be retrieved from a Con-nect text block (a document containing Con-form formatting instructions).

The contents of Natural variables can be passed to Con-form as variables for dynamic inclusion in the formatted text.

The values contained in a Con-form variable can also be returned to the Natural program from the text formatter.

When the Con-form instructions are completed (resulting in a formatted document), the output is passed to one of the following places:

- a Natural report,
- a document in the Con-nect system file,
- variables in the Natural program that executes the `COMPOSE` statement,
- a **non-Natural program**.

Syntax Description

- [RESETTING-clause](#)
- [MOVING-clause](#)
- [ASSIGNING-clause](#)
- [FORMATTING-clause](#)
- [EXTRACTING-clause](#)

RESETTING-clause

This clause may be used to delete information from the text format area of the Con-form buffer and to release memory from the Con-form buffer allocated by the `CSIZE` profile parameter in the Natural parameter module.

RESETTING	[DATAAREA TEXTAREA MACROAREA ALL]

Syntax Element Description:

Syntax Element	Description
DATAAREA	Deletes all active text variables.
TEXTAREA	Deletes all text input data. Note: For compatibility reasons, the keyword TEXTAREA refers to DATAAREA as used in the MOVING clause.
MACROAREA	Deletes all text macros.
ALL	Deletes all of the above.

See also [Example 1](#) and [Example 2](#).

MOVING-clause

You can use this clause to move text lines to the text format area of the Con-form buffer, or directly to the formatter, and to retrieve formatted text output from the Con-form buffer.

It may be used to move one or more text values to the text format area (see [Syntax 1](#)). This area may be used as a source of input for formatting operations.

If the text formatter is currently waiting for input (see [Dialog Mode Processing](#)), the text will be passed directly to it without being stored in Con-form's buffer (see [Syntax 1](#) and [Syntax 2](#)). The source input is terminated with the `LAST` option.

If the formatted text is currently waiting for output (see *Dialog Mode Processing*), *Syntax 3* of the `MOVING` clause is used to pass control back from the Natural program to the formatter.

For description of the status variables, see *FORMATTING-clause*.

Depending on the status of the dialog mode processing, one of the following forms of the `MOVING` clause may be used:

Syntax 1 - Dialog Mode for Input

Syntax 1 of the `MOVING` clause is applicable when formatting has not begun or the formatter is in dialog mode for input and is waiting for input (TERM in the status variable “State”).

```
MOVING [operand1] ... 37 [TO DATAAREA] [LAST]
[STATUS [T0] operand2 [operand3 [operand4 [operand5]]]]
```

Syntax 2 - Dialog Mode for Both Input and Output

Syntax 2 of the `MOVING` clause is applicable when the formatter is in dialog mode for both input and output, and is waiting for further input (status TERM in the status variable “State”). The formatter will not accept more than one line of input in this mode.

The execution context may change between succession of executed `COMPOSE` statements. Therefore, it is necessary to re-specify the output variables even when the formatter is waiting for input.

```
MOVING [ { operand1 [TO DATAAREA] } ] [OUTPUT] TO
      [ LAST ] [VARIABLES operand6]
      ... 20
[STATUS [T0] operand2 [operand3 [operand4 [operand5]]]]
```

Syntax 3 - Dialog Mode for Output

Syntax 3 of the `MOVING` clause is applicable when the formatter is in dialog mode for output (and possibly for input at the same time), and is passing output to the Natural program (status STRG in the status variable “State”).

```
MOVING OUTPUT [TO VARIABLES] operand6 ... 20
[STATUS [T0] operand2 [operand3 [operand4 [operand5]]]]
```

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S	A			A	N	P									yes	no
<i>operand2</i>		S				A											yes	yes
<i>operand3</i>		S								B							yes	yes
<i>operand4</i>		S								B							yes	yes
<i>operand5</i>		S								B							yes	yes
<i>operand6</i>		S	A			A											yes	no

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Contains the input (unformatted) text lines. Format/length: (A <i>n</i>), where <i>n</i> is a maximum value of 253, (N <i>n</i>) or (P <i>n</i>), where <i>n</i> is a maximum value of 29.
<i>operand2</i>	Contains the status variable "State" . Format/length: (A4)
<i>operand3</i>	Contains the status variable "Position" (page number). Format/length: (B4)
<i>operand4</i>	Contains the status variable "Position" (line number). Format/length: (B4)
<i>operand5</i>	Contains the status variable "Amount of output data" (number of lines). Format/length: (B4)
<i>operand6</i>	Contains the output (formatted) text lines. Format/length: (A <i>n</i>), where <i>n</i> is a maximum value of 253.

ASSIGNING-clause

You can use this clause to assign the values of Natural variables to Con-form text variables. These text variables may subsequently be referred to in formatting operations.

```
ASSIGNING [TEXTVARIABLE] {operand1=operand2}, ... 19
```

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S				A											yes	no
<i>operand2</i>	C	S				A	N	P									yes	yes

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	<i>operand1</i> is the name of the Con-form text variable. The text variable must be specified in upper case. Format/length: (A <i>n</i>), where <i>n</i> is a maximum value of 253.
<i>operand2</i>	<i>operand2</i> is the name of a given Natural variable. Format/length: (A <i>n</i>), where <i>n</i> is a maximum value of 253, (N <i>n</i>) or (P <i>n</i>), where <i>n</i> is a maximum value of 29.

See also [Example 3](#) and [Example 4](#).

FORMATTING-clause

This clause causes Con-form to produce formatted output. You can use it to create text in final form, that is, with correct line and page breaks, using input which can be a combination of text and Con-form instructions.

The formatting options are specified in one or more subclauses. If subclauses are omitted, Con-form will apply default formatting options.

The status variable is used in dialog mode.

FORMATTING	OUTPUT-subclause INPUT-subclause STATUS-subclause PROFILE-subclause MESSAGES-subclause ERRORS-subclause ENDING-subclause STARTING-subclause	...

Syntax Element Description:

Syntax Element	Description									
<i>OUTPUT-subclause</i>	The output medium. This can be a Natural report, a document in a Con-nect cabinet, one or more Natural variables (or an array of Natural variables), or a non-Natural program. See Output-subclause in the following section.									
<i>INPUT-subclause</i>	The input medium. This can be a Con-nect document, the text format area of the Con-form buffer (see DATAAREA in the MOVING clause), the environment of the Natural program(s) executing the COMPOSE statement(s) (see the MOVING clause), a non-Natural program, or a mixture of these four possibilities.									
<i>STATUS-subclause</i>	The status of the formatting operation. The formatting operation may involve multiple executions of a COMPOSE statement (in dialog mode processing). For example, the input is fed into the text format area by a Natural program, and the output is passed from the text format area into the environment of a Natural program (that is, one or more Natural variables). Therefore it is necessary to inform the Natural program of the formatting status. The following variables are passed to the Natural program during the formatting process: <table> <tr> <td rowspan="4">State</td><td>TERM when the dialog mode is ready for input.</td></tr> <tr> <td>STRG when the dialog mode is ready for output.</td></tr> <tr> <td>END if the formatting process was completed successfully.</td></tr> <tr> <td>ENDX if the formatting process was completed unsuccessfully.</td></tr> <tr> <td>Position</td><td>Page and line number of the document that is being formatted. The page and line numbers are kept separately in two variables (page position and line position).</td></tr> <tr> <td>Amount of Output Data</td><td>The number of lines of formatted output which are being passed to the Natural program. The formatter uses this number as the pointer to the next output variable to be filled. The value is incremented by 1 before the output line is issued. If the current value is out of range, the value is set to 1.</td></tr> </table>	State	TERM when the dialog mode is ready for input.	STRG when the dialog mode is ready for output.	END if the formatting process was completed successfully.	ENDX if the formatting process was completed unsuccessfully.	Position	Page and line number of the document that is being formatted. The page and line numbers are kept separately in two variables (page position and line position).	Amount of Output Data	The number of lines of formatted output which are being passed to the Natural program. The formatter uses this number as the pointer to the next output variable to be filled. The value is incremented by 1 before the output line is issued. If the current value is out of range, the value is set to 1.
State	TERM when the dialog mode is ready for input.									
	STRG when the dialog mode is ready for output.									
	END if the formatting process was completed successfully.									
	ENDX if the formatting process was completed unsuccessfully.									
Position	Page and line number of the document that is being formatted. The page and line numbers are kept separately in two variables (page position and line position).									
Amount of Output Data	The number of lines of formatted output which are being passed to the Natural program. The formatter uses this number as the pointer to the next output variable to be filled. The value is incremented by 1 before the output line is issued. If the current value is out of range, the value is set to 1.									
<i>PROFILE-subclause</i>	Text block to be processed before input is processed. See PROFILE-subclause in the following section.									
<i>MESSAGES-subclause</i>	Controls the output of warning messages and statistical information and error processing. See MESSAGES-subclause and ERRORS-subclause in the following section.									
<i>ERRORS-subclause</i>										
<i>ENDING-subclause</i>	Defines the page where output of formatted text is to stop. See ENDING-subclause in the following section.									

<i>STARTING-subclause</i>	Defines the page where output of formatted text is to start. See <i>STARTING-subclause</i> in the following section.

OUTPUT-subclause

This subclause enables you to direct Con-form's formatted text output to a specific destination.

If this subclause is omitted, Natural's main printer will be used as the default output device.

OUTPUT	(<i>rep</i>) SUPPRESSED CALLING <i>operand1</i> TO VARIABLES [CONTROL <i>operand2 operand3</i>] <i>operand4</i> ... 20 DOCUMENT-option

Operand Definition Table:

Operand	Possible Structure				Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S			A										yes	no
<i>operand2</i>	C	S			A										yes	no
<i>operand3</i>	C	S			A										yes	no
<i>operand4</i>		S	A		A										yes	no

Syntax Element Description:

Syntax Element	Description
(<i>rep</i>)	If the output is directed to a printer (that is, the report number is not 0 and a Con-nect printer profile has been loaded (by the Con-nect API subprogram Z-DRIVER), the settings of that profile will be used to control the text highlighting options of the formatted output text. If a printer profile is active and the logical form feed controls were not specified, page ejects will be inserted by use of the appropriate internal Natural nucleus functions. Any other highlighting text option which is not reflected in the currently active Con-nect printer profile will be ignored. Note: Executions of the COMPOSE RESETTNG ALL or COMPOSE FORMATTNG statement with non-report output destination will unload a printer profile from the text format area.

	If output is directed to Report 0 or if a printer profile is not active, Con-nect will pass the responsibility of the output handling to the Natural nucleus routines. In this case, only the highlighting text options boldface, underline and italics will be recognized. Note: A report which is referred to in a <code>DEFINE PRINTER (n) OUTPUT 'CONNECT'</code> statement must not be specified as output destination in a <code>COMPOSE FORMATTING</code> statement.
SUPPRESSED	This option causes the output to be suppressed.
CALLING <i>operand1</i>	<i>operand1</i> is the name of the called program. Format/length: (A<i>n</i>), where <i>n</i> is a maximum value of 8. See the section Input/Output Processing by Non-Natural Programs.
TO VARIABLES [CONTROL <i>operand2</i> <i>operand3</i>] <i>operand4</i>	Generally, the formatted text will be passed in final format to an array of Natural variables. Each line fills one variable (if necessary, the line may be truncated to fit into the variables). Text highlighting options will be ignored, with the exception of the CONTROL variables specified, which will be used to emphasize sections of the text (that is, boldface or underscore). If the CONTROL variables I and N are specified, the formatted text will be produced in an intermediate format (that is, with interspersed logical control sequences). <i>operand2</i> is the starting character. Format/length: (A1). <i>operand3</i> is the ending character. Format/length: (A1). Example using angle brackets as starting and ending characters: <pre><ABC...XYZ></pre> <i>operand4</i> is the output field. Format/length: (A<i>n</i>), where <i>n</i> is a maximum value of 253. For further information, see the section Dialog Mode Processing, and in particular the subsection Dialog Mode for Output.
DOCUMENT-option	See DOCUMENT-option below.

DOCUMENT-option

The DOCUMENT option of the OUTPUT subclause enables you to direct Con-form's formatted text to a Con-nect cabinet in final (Txt) or intermediate (Int) format. The document text of Int format cannot be modified.

DOCUMENT	$\left\{ \begin{array}{l} \text{INTQ} \left[\left\{ \begin{array}{l} \text{FINAL} \\ \text{INTERMEDIATE} \end{array} \right\} \right] [\text{CABINET}] \text{operand1} [\text{PASSW=operand2}] \\ [\text{GIVING}] \left\{ \begin{array}{l} \text{operand3} [\text{operand4}] \\ \text{operand4} [\text{operand3}] \end{array} \right\} \end{array} \right\}$

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
operand1	C S	A	yes	no
operand2	S	A	yes	no
operand3	S	B	yes	yes
operand4	S	B	yes	yes

Syntax Element Description:

Syntax Element	Description
INTQ FINAL INTERMEDIATE CABINET	If the keyword FINAL is specified, the document will be created in final form text. In this case, specific text highlighting options such as boldface or italics will be ignored. If the keyword INTERMEDIATE is specified, the document will be added to the folder COMPOSE without a document name. The subject line will be filled with the name of the program executing the COMPOSE FORMATTING statement along with the date and time of execution.
CABINET operand1	operand1 may be used to identify a specific cabinet. Format/length: (An), where <i>n</i> is a maximum value of 8. If operand1 is not specified, the document will be added to the current user's cabinet (that is, to the cabinet whose ID is identical to the currently active Natural user ID). Con-form enforces adherence to Con-nect access restrictions and only accepts cabinet IDs which have been defined to Con-nect. Note: Cabinet IDs must be specified in upper case.
PASSW=operand2	A password must be specified if storing the document in a cabinet to which the currently assumed user ID has no access. Format/length: (An), where <i>n</i> is a maximum value of 8.
operand3	operand3 is used by the formatter to pass a unique key from the document back to the Natural program. It is supported for compatibility reasons only. Format/length: (B10)

<i>operand4</i>	<i>operand4</i> is used by the formatter to pass an ISN, which points to the formatted output document, back to the Natural program. This ISN can be useful when referencing the document in successive calls to Con-nect APIs. Format/length: (B4)

INPUT-subclause

This subclause may be used to specify the sources which will supply input for the text formatter.



Note: If this subclause is omitted, the DATAAREA (text format area of the Con-form buffer) will be processed by default.

INPUT	DATAAREA	FROM	{	EXIT <i>operand2</i> CABINET <i>operand2</i> [PASSW= <i>operand3</i>]	}...9	]
	<i>operand1</i>	FROM	{	EXIT <i>operand2</i> CABINET <i>operand2</i> [PASSW= <i>operand3</i>]	}...10	]

Operand Definition Table:

Operand	Possible Structure				Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S			A										yes	no
<i>operand2</i>	C	S			A										yes	no
<i>operand3</i>		S			A										yes	no

Syntax Element Description:

Syntax Element	Description
DATAAREA	The input may be taken from Con-form's data area (or a mixture of text from the text format area and from the dialog mode is also possible) which must be filled by one or more MOVING operations; see the MOVING clause.
<i>operand1</i>	Alternatively, the input may be taken from a text block. The name of the text block is specified by <i>operand1</i>. Note: Text block IDs must be specified in upper case. Format/length: (A<i>n</i>), where <i>n</i> is a maximum value of 253. The text block may be contained in a Con-nect cabinet, or it may be supplied by a non-Natural program. It will be invoked using the same conventions which apply to the CALL statement. A hierarchy of Con-nect cabinets or non-Natural programs may be specified, each of which will be scanned in turn for the text block specified in <i>operand1</i>.

CABINET <i>operand2</i>	The input (a text block specified by <i>operand1</i>) might be taken from a specific Con-nect cabinet. <i>operand2</i> is the name of the Con-nect cabinet. Note: Cabinet IDs must be specified in upper case. Format/length: (A<i>n</i>), where <i>n</i> is a maximum value of 8.
EXIT <i>operand2</i>	<i>operand2</i> is the name of the exit. Format/length: (A<i>n</i>), where <i>n</i> is a maximum value of 8.
PASSW= <i>operand3</i>	A password must be specified if the document is stored in a cabinet to which the currently assumed user ID has no access. Format/length: (A<i>n</i>), where <i>n</i> is a maximum value of 8. Con-form enforces adherence to Con-nect access restrictions and only accepts cabinet IDs which have been defined to Con-nect.

See also [Example 4](#).

STATUS-subclause

The STATUS subclause used in the FORMATTING clause corresponds to the STATUS subclause of the MOVING clause. It should be used to make sure that the formatting process is always in the appropriate status for a given processing step.

STATUS *operand1* [*operand2* [*operand3* [*operand4*]]]

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>	S				A												yes	no
<i>operand2</i>	S												B				yes	no
<i>operand3</i>	S												B				yes	no
<i>operand4</i>	S												B				yes	no

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Contains the status variable “ State ” (status of formatting process). Format/length: (A4)
<i>operand2</i>	Contains the status variable “ Position ” (page number). Format/length: (B4)
<i>operand3</i>	Contains the status variable “ Position ” (line number). Format/length: (B4)
<i>operand4</i>	Contains the status variable “ Amount of Output Data ” (number of lines). Format/length: (B4)

PROFILE-subclause

This subclause causes the content of the specified text block to be processed prior to any input which has been specified with the **INPUT subclause** (by default, a text block will not be processed as a profile).

```
PROFILE operand1
```

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S				A											yes	no

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	<i>operand1</i> is the name of the text block (for example, FPROFILE - formatting profile). Format/length: (A <i>n</i>), where <i>n</i> is a maximum value of 32.

MESSAGES-subclause

When this subclause is specified, warning messages and statistical information are to be displayed upon completion of formatting or the error may be simply suppressed (ignored).

MESSAGES	{ [LISTED] [ON] (<i>rep</i>) SUPPRESSED }

Syntax Element Description:

Syntax Element	Description
(<i>rep</i>)	The notation (<i>rep</i>) specifies the report for which the subclause is applicable. A value in the range 0 - 31 or a logical name which has been assigned using the <code>DEFINE PRINTER</code> statement may be specified. For information on how to control the format of an output report created with Natural, see <i>Report Format and Control</i> in the <i>Programming Guide</i>.
SUPPRESSED	When specified, this keyword indicates that no messages are to be displayed and errors are to be ignored.

ERRORS-subclause

You can use the `ERRORS` subclause to specify the actions to be performed when a formatting error occurs. The error may be processed by Natural's standard error-processing routine, or it may be listed on a specified Natural report.

ERRORS	{ [LISTED] [ON] (<i>rep</i>) INTERCEPTED }

Syntax Element Description:

Syntax Element	Description
(<i>rep</i>)	The notation (<i>rep</i>) specifies the report for which the subclause is applicable. A value in the range 0 - 31 or a logical name which has been assigned using the <code>DEFINE PRINTER</code> statement may be specified. For information on how to control the format of an output report created with Natural, see <i>Report Format and Control</i> in the <i>Programming Guide</i>.
INTERCEPTED	When specified, this keyword indicates that the error is to be processed by Natural's standard error-processing routine.



Note: Errors and messages are mutually exclusive. Some errors may cause the standard Natural error-process routine to be invoked, even if a different option was specified. Errors or messages must not be directed to a report which is directed to the Con-nect system by a `DEFINE PRINTER (n) OUTPUT 'CONNECT'` statement.

ENDING-subclause

This subclause causes output of formatted text to be suppressed after a specific page number. Alternatively, it limits the amount of formatted output to a specified number of pages.

ENDING { [AT] [PAGE] *operand1*
AFTER *operand1* [PAGES] }

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S				N	P									yes	no

Syntax Element Description:

Syntax Element	Description
[AT] [PAGE] <i>operand1</i>	Causes output of formatted text to be suppressed following a page with a number specified in <i>operand1</i> . Format/length: (N <i>n</i>) or (P <i>n</i>), where <i>n</i> is a maximum value of 5.
AFTER <i>operand1</i> [PAGES]	Limits the amount of formatted output to a number of pages as specified with <i>operand1</i> .

STARTING-subclause

This subclause causes output of formatted text to be suppressed until the page with the specified number (*operand1*) is reached.

STARTING [FROM] [PAGE] *operand1*

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S				N	P									yes	no

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	The output of formatted text to be suppressed until the page with the number specified in <i>operand1</i> is reached. Format/length: (N<i>n</i>) or (P<i>n</i>), where <i>n</i> is a maximum value of 5.

EXTRACTING-clause

You can use this clause to assign the values of Con-form text variables to Natural variables. The current text variable settings may be the result of previous formatting operations.

```
EXTRACTING [TEXTVARIABLE] {operand1=operand2},... 19
```

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	S	A N P	yes	yes
<i>operand2</i>	C S	A	yes	no

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	<i>operand1</i> is the name of a given Natural variable. Format/length: (A<i>n</i>), where <i>n</i> is a maximum value of 253, (N) or (P<i>n</i>), where <i>n</i> is a maximum value of 29.
<i>operand2</i>	<i>operand2</i> is the name of a Con-form text variable. It must be specified in upper case. Format/length: (A<i>n</i>), where <i>n</i> is a maximum value of 253.

See also [Example 6](#).

Formatting Process

The formatting process begins when the **FORMATTING** clause of the **COMPOSE** statement is executed (even if text input via a **MOVING** clause is intended, but no such input has been provided yet). While the formatting process is active, the text input resulting from the execution of the **COMPOSE MOVING** statement is fed directly for formatting (and cannot be re-used in a later formatting process). If the formatting process is inactive, the text input is stored intermediately in the text format area of the Con-form buffer. Thus the input can be re-used for multiple formatting processes.

Since the Con-form buffer is not cleared at the end of the Natural program, the respective COMPOSE statements need not be executed within one Natural program; they can be issued in several successively invoked programs.

The execution of a [RESETTING](#) or [FORMATTING](#) clause, or a serious formatting error, causes the termination of an ongoing formatting pass.

End-of-input is specified by the [LAST](#) subclause of the [MOVING](#) clause.

When a Con-nect document is specified as the source of input, end-of-input is assumed when the end of that document is reached.



Note: It is recommended to use the [STATUS](#) subclause of the [FORMATTING](#) or [MOVING](#) clause to make sure that the formatting process is always in the appropriate status for a given processing step.

Dialog Mode Processing

Dialog mode processing is the set of interactions which are performed between a user program and the formatter while formatting input and producing output.

Dialog mode allows a user program to supply raw text as input to the formatter at any level of the input hierarchy. It also accepts formatted output directly in the current program environment.

The dialog is achieved by subdividing the formatting process into a series of steps, each of which is separately invoked by a COMPOSE statement.

- [Dialog Mode for Input](#)
- [Dialog Mode for Output](#)
- [Dialog Mode for Input and Output](#)
- [Execution of COMPOSE Statements in Dialog Mode](#)

Dialog Mode for Input

Dialog mode for input is activated if the source of the input text is [DATAAREA](#) (text format area), or if the Con-form instruction `.TE ON` for terminal input is encountered, and the text format area does not contain any more text to be processed. Dialog mode for input is signaled by the value `TERM` in the status variable **“State”**.

The user program should respond by supplying the required input by invoking the [MOVING](#) function in a subsequently-processed COMPOSE statement. The user program can terminate terminal input by specifying the [LAST](#) option of the [MOVING](#) clause (or `.TE OFF` if terminal input was invoked by `.TE ON`) as text through the [MOVING](#) function. The formatter will signal the end of the formatting process with `END`, or `ENDX` in the case of an error, in the status variable **“State”**.

See also [Example 7](#).

Dialog Mode for Output

Dialog mode for output is activated if the destination of the output is `TO VARIABLES`. The formatter passes control back to the Natural program environment as soon as the supplied Natural variables are filled or a page break is reached (whichever occurs first). Dialog mode for output is signaled with `STRG` in the status variable `"State"`.

The user program should respond by taking the formatted output just placed into the Natural variables and designate another set of Natural variables as the output destination in a subsequently processed `COMPOSE MOVING` statement. The end of the formatting process is indicated with `END` (or `ENDX` in the case of an error) in the status variable `"State"`.



Note: When dialog mode is used (see the `INPUT` and `OUTPUT` subclauses), the formatting operation is usually spread across several executions of a `COMPOSE` statement.

Dialog Mode for Input and Output

Dialog mode can be activated for combined input and output processing. Therefore, when the formatter requests for further input (indicated in the status variable `"State"` by `TERM`) or when the formatter provides output (indicated by `STRG`), the Natural program must take the appropriate action.

When dialog mode is entered for combined input and output processing, only one line of input is accepted by the formatter at a time. In the case of input mode only, multiple lines are accepted at one time.

Execution of COMPOSE Statements in Dialog Mode

While it has been pointed out that dialog mode is entered via a `COMPOSE FORMATTING` statement which encompasses a series of `COMPOSE MOVING` executions, please note the following:

- `COMPOSE ASSIGNING` and `COMPOSE EXTRACTING` statements are valid while dialog mode is active.
- `COMPOSE RESETTING` and `COMPOSE FORMATTING` will force the immediate termination of all formatting.

Input/Output Processing by Non-Natural Programs

Depending on the parameters specified with the [FORMATTING](#) clause, input and output may be processed by non-Natural programs. Such programs are invoked by the same mechanism that is used within the Natural [CALL](#) statement.

The `COMPOSE` statement exchanges parameters with these programs using the standard [linkage conventions](#) (dynamic loading is not possible in a CICS environment).



Note: Input/output processing by non-Natural programs is only possible on mainframe computers; on other platforms, the appropriate parts of the `COMPOSE` statement are ignored.

Depending on the status of the formatting process, two or three parameters are passed between the formatter and the non-Natural programs:

Parameter 1 (format/length A1)	Function code is passed from the formatter to non-Natural programs. Possible values:	
	I	Initiate (input, output).
	O	Open document (input).
	R	Read one line of document (input).
	W	Write one line of output (output).
	C	Close document (input).
	T	Terminate (input, output).
Parameter 2 (format/length B1)	Response code is passed from non-Natural programs to the formatter.	
	Possible values:	
	X'00'	Function successfully completed.
	X'01'	In response to function O: document could not be found.
		In response to function R: end of document was reached.
	X'FF'	Function not completed.
Parameter 3 (format A1/256)	In the case of the functions O and W, these parameters are passed from the formatter to non-Natural programs. However, the parameters from the function R are passed from non-Natural programs to the formatter.	
	Bytes 1 - 2	Signify the length <i>n</i> of this parameter.
	Bytes 3 - 4	Empty.
	Bytes 5 - <i>n</i>	Function O: Document name.
		Function R: Line read by the non-Natural program.
		Function W: Line of output from the formatter.
	Output is preceded by N if a form feed is required, otherwise by 1.	
	Specific options for highlighting text such as boldface and italics are ignored if the output is passed to a non-Natural program.	

Examples

- [Example 1](#)
- [Example 2](#)
- [Example 3](#)
- [Example 4](#)
- [Example 5](#)
- [Example 6](#)
- [Example 7](#)

Example 1

The following COMPOSE statement results in a formatted output of the text block TEXT within the Con-nect cabinet TLIB which is produced on Report 1. Errors and statistical messages are displayed on Report 0 (the default printer).

```
COMPOSE RESETTNG ALL
      FORMATTNG INPUT 'TEXT' FROM CABINET 'TLIB'
      OUTPUT (1)
      MESSAGES LISTED ON (0)
```

Example 2

The following COMPOSE statements result in a formatted output of text on Report 0 (default printer).

```
COMPOSE RESETTNG ALL
COMPOSE MOVING '.FI ON' 'This is an example'
COMPOSE MOVING 'for use of Con-form from'
      'within Natural applications' LAST
COMPOSE FORMATTNG
```

Example 3

The following COMPOSE statement results in the assignment of values to Con-form text variables &VAR1 and &VAR2 in a Con-nect procedure.

```
COMPOSE ASSIGNING 'VAR1' = 'Text1', 'VAR2' = 540
```

Example 4

Text block XYZ in cabinet XYLIB:

```
.FI ON
Dear Mr &name.,
.IL
I am pleased to invite you to a presentation of our new product &prod..
```

Natural program:

```
...
INPUT #NAME (A32) #PROD (A32)
COMPOSE ASSIGNING 'NAME' = #NAME, 'PROD' = #PROD
          FORMATTING INPUT 'XYZ' FROM CABINET 'XYLIB'
          OUTPUT (1) MESSAGES SUPPRESSED
...
```

Input map produced by program:

```
#NAME Davenport
#PROD NaturalONE
```

Resulting output:

```
Dear Mr Davenport,

I am pleased to invite you to a presentation of our new product NaturalONE.
```

Example 5

This is an example of formatting in dialog mode with combined input/output handling. The example program initiates the line-oriented formatting mode of Con-form, passes some instructions/variables to Con-form, and performs a subroutine which displays status information and formatted output lines on the screen.

```
DEFINE DATA LOCAL
01 #LINES_PER_PERFORM(P5) /* counts repeat loops per PERFORM CNF_OUT
01 #TRACE(A1) IINT<'N'> /* if 'Y' displays additional trace info
01 #OUT_FORM(A1) INIT<'F'> /* output format
01 #START_PAGE (P3) INIT<1> /* beginning of display
01 #CNTR (P5) /* Loop counter
01 #STATI /* Status information
02 #STATUS (A4) /* can be STRG TERM END or ENDX
02 #PAGE (B4) /* current page number
02 #LINE (B4) /* current line number on page (not .tt/.bt)
02 #NO_LINES (B4) /* number of lines returned
02 REDEFINE #NO_LINES
03 #NO_LINES_I (I4)
```

```

01 #OUTPUT(A30/4)          /* output of formatted line
01 #INDEX (P3)             /* index as pointer to output line
END-DEFINE
*
SET KEY ALL
SET CONTROL 'M9'
INPUT
    008/008 'Demonstration of formatted output to variable'(I)
    /    08X 'Enter page to start display      :' #START_PAGE(AD=MIL)
    /    08X 'Display additional trace data ?:' #TRACE(AD=MIT)
    /    08X 'Please select the output format:' #OUT_FORM(AD=MIT)
        '(F=Final without BP/US-marks'
    /    44X 'M=Final with BP/US marks "<>"'
    /    44X 'I=Intermediate)'
    /    50X 'PF3=Exit'(I)
*
IF *PF-KEY EQ 'PF3'
    SET CONTROL 'MB'
    STOP
END-IF
*
IF NOT (#OUT_FORM EQ 'F' OR EQ 'M' OR EQ 'I')
    REINPUT ' Please enter valid code!' MARK *#OUT_FORM ALARM
END-IF
*
WRITE TITLE LEFT
    'Stat * Page      * Line      * No.Lines >> Formatted Output'(I)
    / '-'(79)(I)
*
SET CONTROL 'MB'
COMPOSE RESETING ALL /* clear all text format area of Con-form buffer
RESET #NO_LINES
*
* start line-oriented formatting-mode here
* starting from 0
DECIDE ON FIRST VALUE OF #OUT_FORM
    VALUE 'F'
        COMPOSE FORMATTING
            OUTPUT TO VARIABLES #OUTPUT (1:4)      /* to Output
            STATUS #STATUS #PAGE #LINE #NO_LINES  /* get Status
    VALUE 'M'
        COMPOSE FORMATTING
            OUTPUT TO VARIABLES CONTROL '<' '>'
                #OUTPUT (1:4)      /* to output
            STATUS #STATUS #PAGE #LINE #NO_LINES  /* get Status
    VALUE 'I'
        COMPOSE FORMATTING
            OUTPUT TO VARIABLES CONTROL 'I' 'N'
                #OUTPUT (1:4)      /* to output
            STATUS #STATUS #PAGE #LINE #NO_LINES  /* get Status
    NONE
        STOP

```



```

END-DECIDE
*
RESET #NO_LINES
*
* Put some commands to Con-form to see something
*
COMPOSE MOVING
    '.pl 16;.hs 2;.tt 1Formatting in Variable//;.tt 2//' /* Cmd
    OUTPUT TO VARIABLES #OUTPUT (1:4)          /* to Output
    STATUS #STATUS #PAGE #LINE #NO_LINES      /* get Status
*
COMPOSE MOVING
    '.fs 1;.bt Page End #//;.fi on;.tb *=15' /* Commands
    OUTPUT TO VARIABLES #OUTPUT (1:4)          /* to Output
    STATUS #STATUS #PAGE #LINE #NO_LINES      /* get Status
*
*
* loop 40-times, send commands to con-form and display output
*
COMPOSE ASSIGNING 'Value' = '1-20' /* Assign value to variable &Value
*
FOR #CNTR 1 40                                /* Loop some time
    IF #STATUS NE 'TERM' /* no wait-for-input => error!!!!
        IF #STATUS EQ 'STRG'
            IGNORE
        ELSE
            WRITE 'Unexpected Status-code' #STATUS(AD=OI) 'found!'
            / 'Execution has stopped....'
            STOP
        END-IF
    END-IF
*
    IF #CNTR EQ 21
        COMPOSE ASSIGNING 'Value' = '21-40' /* Assign a variable-value
    END-IF
    COMPOSE ASSIGNING 'CNTR' = #CNTR /* Again assignment
    COMPOSE MOVING
        '.BP;&Value *Pass &CNTR;.BR'          /* Commands
        OUTPUT TO VARIABLES #OUTPUT (1:4)      /* to output
        STATUS #STATUS #PAGE #LINE #NO_LINES  /* get status
    PERFORM CNF-OUT                            /* show result
END-FOR
COMPOSE MOVING
    LAST                                /* End of processing
    OUTPUT TO VARIABLES #OUTPUT (1:4)          /* to output
    STATUS #STATUS #PAGE #LINE #NO_LINES      /* get status
*
IF #TRACE EQ 'Y'
    WRITE 'End of processing...(I)
END-IF
*
* Subroutines

```

```
*
PERFORM CNF-OUT
*
* Subroutine to display any waiting output from Con-form
*
DEFINE SUBROUTINE CNF-OUT
  RESET #LINES_PER_PERFORM
  REPEAT UNTIL #STATUS EQ 'TERM' /* TERM = input waiting
    PERFORM BREAK                /* do some break processing
  AT BREAK OF #PAGE
    IF #PAGE GT #START_PAGE
      WRITE '- '(79)(I)
    END-IF
    IF #TRACE EQ 'Y'
      WRITE 'End of this page...'(I)
    END-IF
    NEWPAGE
  END-BREAK
  IF #PAGE GE #START_PAGE      /* show line of output
    IF #NO_LINES_I GT 0
      FOR #INDEX 1 #NO_LINES_I
        ADD 1 TO #LINES_PER_PERFORM /* count loops
        WRITE NOTIT NOHDR #STATUS '*' #PAGE '*' #LINE
          '*' #NO_LINES
          '>>' #OUTPUT (#INDEX)
      END-FOR
    END-IF
  END-IF
  IF #STATUS NE 'STRG'        /* if no wait on output
    ESCAPE BOTTOM
  END-IF
  RESET #NO_LINES
  COMPOSE MOVING
    OUTPUT TO VARIABLES #OUTPUT (1:4) /* get output
    STATUS #STATUS #PAGE #LINE #NO_LINES /* Status
  END-REPEAT
*
  IF #TRACE EQ 'Y'
    WRITE 'Count of lines per PERFORM was'(I) #LINES_PER_PERFORM(AD=0I)
  END-IF
*
END-SUBROUTINE
SET CONTROL 'MB'
END
```

Example 6

Text block 'ABC' in cabinet 'ZLIB':

```
.op das=6
.CV c=(&A+&B+&D)*&A/12345678901234567.89
```

Natural Program:

```
DEFINE DATA LOCAL
. . .
01 NA      (P14.1) INIT <-12345678.1>
01 NB      (N15.1) INIT <1234567890.1>
01 ND      (P15.1) INIT <1122334455.1>
01 NC      (N03.6)
01 NCOMP   (N03.6)
. . .
END-DEFINE
COMPOSE RESETTNG ALL
COMPOSE ASSIGNING 'A'=NA,'B'=NB,'D'=ND
COMPOSE FORMATTING INPUT 'ABC' FROM CABINET 'ZLIB'
COMPOSE EXTRACTING NC='C'
COMPUTE ROUNDED NCOMP=(NA+NB+ND) * NA /12345678901234567.89
WRITE (0) 'CONFORM C =' NC / 'NATURAL C =' NCOMP
END
```

Resulting Output:

```
CONFORM C =   -2.344557
NATURAL C =   -2.344557
```

Example 7

The following is an example of using the Con-form instruction .TE ON/OFF in dialog mode for input. A Natural program calls the Con-form document LETTER containing this instruction from cabinet XYLIB.

Natural program:



Note: This simplified Natural program is intended for demonstration purposes only; for example, the required fields SALUTATION, LASTNAME, STREET, CITY are not verified.

```
DEFINE DATA LOCAL
01 #ENTER (A15) INIT <'Special offer:'>
01 SLINE (A15) INIT <'.SL 1'>
01 #TEXT (A60/1:4)
01 SALUTATION (A30)
01 LASTNAME (A30)
01 STREET (A30)
01 CITY (A30)
01 #STATUS (A4)
01 #PAGE (B4)
01 #LINE (B4)
01 #NUMBER (B4)
END-DEFINE
COMPOSE RESETING ALL
INPUT 25X 'Advertising letter'
/ '-' (75)
/ 'Salutation: ' SALUTATION (AD='_')
/ 'Lastname : ' LASTNAME (AD='_')
/ 'Street : ' STREET (AD='_')
/ 'City : ' CITY (AD='_')
/ '-' (75)
// '-' #ENTER (AD=0I)
/ '-' #TEXT(1) (AD='_')
/ '-' #TEXT(2) (AD='_')
/ '-' #TEXT(3) (AD='_')
/ '-' #TEXT(4) (AD='_')
COMPOSE ASSIGNING 'SALUT' = SALUTATION,
                  'NAME' = LASTNAME,
                  'STREET' = STREET,
                  'TOWN' = CITY
COMPOSE FORMATTING INPUT 'LETTER' FROM CABINET 'XYLIB '
DECIDE FOR FIRST CONDITION
  WHEN #TEXT(4) NE ' '
    COMPOSE MOVING SLINE #TEXT(1) #TEXT(2) #TEXT(3) #TEXT(4)
      '.TE OFF' STATUS #STATUS #PAGE #LINE #NUMBER
  WHEN #TEXT(3) NE ' '
    COMPOSE MOVING SLINE #TEXT(1) #TEXT(2) #TEXT(3)
      '.TE OFF' STATUS #STATUS #PAGE #LINE #NUMBER
  WHEN #TEXT(2) NE ' '
    COMPOSE MOVING SLINE #TEXT(1) #TEXT(2)
      '.TE OFF' STATUS #STATUS #PAGE #LINE #NUMBER
  WHEN #TEXT(1) NE ' '
    COMPOSE MOVING SLINE #TEXT(1)
      '.TE OFF' STATUS #STATUS #PAGE #LINE #NUMBER
  WHEN NONE
    COMPOSE MOVING
      '.TE OFF' STATUS #STATUS #PAGE #LINE #NUMBER
END-DECIDE
END
```

Con-form document LETTER:

```
.PL 22;.LM 0;.RM 60;.HS 0;.HM 0;.FM 0;.FS 0
&salut &name
&street
&town
.SL 2
Dear &salut &name.,
.SL
.LM 0;.JU OFF;.FI ON
Your subscription with MAGNIFICENT WILDLIFE magazine will soon expire.
If you act now and renew your subscription for one full year, you will
receive a 40% discount - a savings of $25.00 off the newsstand price!$
.TE ON
.SL 2
Sincerely,$
J. Baker$
Vice President of Sales
```

Screen prior to input:

Advertising letter

Salutation: _____

Lastname : _____

Street : _____

City : _____

Special offer:

Screen after input:

Advertising letter

Salutation: Mister_____

Lastname : Poe_____

Street : 203 North Amity Street_____

City : Baltimore, Maryland_____

Special offer:

Take \$500 off a trip to one of the world's premier wildlife-viewing destinations through our travel partner._____

Resulting letter after formatting is complete:

COMPOSE

MISTER POE
203 NORTH AMITY STREET
BALTIMORE, MARYLAND

Dear MISTER POE,

Your subscription with MAGNIFICENT WILDLIFE magazine will soon expire. If you act now and renew your subscription for one full year, you will receive a 40% discount - a savings of \$25.00 off the newsstand price!


TAKE \$500 OFF A TRIP TO ONE OF THE WORLD'S PREMIER WILDLIFE-VIEWING DESTINATIONS THROUGH OUR TRAVEL PARTNER.

Sincerely,
J. Baker
Vice President of Sales

33

COMPRESS

■ Function	266
■ Syntax Description	266
■ Processing	270
■ Examples	270



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [ASSIGN](#) | [COMPUTE](#) | [EXAMINE](#) | [MOVE](#) | [MOVE ALL](#) | [SEPARATE](#)

Belongs to Function Group: [Arithmetic and Data Movement Operations](#)

Function

The COMPRESS statement is used to transfer (combine) the contents of one or more operands into a single field.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats												Referencing Permitted	Dynamic Definition	
<i>operand1</i>	C	S	A	G	N	A	U	N	P	I	F	B	D	T			G	O	yes	no
<i>operand2</i>		S				A	U					B							yes	yes
<i>operand3</i>	C	S						N	P	I		B*							yes	no
<i>operand4</i>	C	S						N	P	I		B*							yes	no
<i>operand5</i>	C	S						N	P	I		B*							yes	no
<i>operand6</i>	C	S						N	P	I		B*							yes	no
<i>operand7</i>	C	S				A	U					B							yes	no

* Format B of operand3, operand4, operand5 and operand6 may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
NUMERIC	Handling of Sign Characters: This option determines how sign characters and decimal characters are to be handled: Without NUMERIC, decimal points and signs in numeric source values are suppressed before the values are transferred. For example: <pre>COMPRESS -123 1.23 INTO #TARGET WITH DELIMITER '*' Content of #TARGET is: 123*123</pre> With NUMERIC, decimal points and signs in numeric source values are also transferred to the target field. For floating point source values, decimal points and signs are transferred, regardless of whether NUMERIC has been specified or not. Example 1: <pre>COMPRESS NUMERIC -123 1.23 INTO #TARGET WITH DELIMITER '*' Content of #TARGET is: -123*1.23</pre> Example 2: <pre>COMPRESS NUMERIC 'ABC' -0056.00 -0056.10 -0056.01 INTO #TARGET WITH DELIMITER '*' Content of #TARGET is: ABC*-56*-56.1*-56.01</pre> Example 3: <pre>COMPRESS NUMERIC FULL 'ABC' -0056.00 -0056.10 -0056.01 INTO #TARGET WITH DELIMITER '*' Content of #TARGET is: ABC*-0056.00*-0056.10*-0056.01</pre>
FULL	Handling of Source Field Values: Without FULL, the following are removed from the source fields before the values are transferred: ■ leading zeros before the decimal point for fields of format N, P or I ■ trailing zeros after the decimal point for fields of format N or P ■ trailing blanks for fields of format A ■ and leading binary zeros for fields of format B For a numeric source field containing all zeros, one zero will be transferred. For example:

Syntax Element	Description		
	<pre>COMPRESS 'ABC ' 001 INTO #TARGET WITH DELIMITER '*'</pre> Content of #TARGET is: ABC*1 With FULL, the values of the source fields in their actual lengths will be transferred to the target field. In other words: ■ leading zeros before the decimal point for fields of format N, P or I ■ trailing zeros after the decimal point for fields of format N or P ■ and trailing blanks for fields of format A ■ leading binary zeros for fields of format B are displayed as entered. For example: <pre>COMPRESS FULL 'ABC ' 001 INTO #TARGET WITH DELIMITER '*'</pre> Content of #TARGET is: ABC *001		
<i>operand1</i>	Source Fields: As <i>operand1</i>, you specify the fields whose contents are to be transferred. Note: If <i>operand1</i> is not of format A or B, its content is converted into alphanumeric representation before it is transferred. If necessary, the alphanumeric representation is truncated. If <i>operand1</i> is a time variable (format T), only the time component of the variable content is transferred, but not the date component.		
<i>operand2</i>	Target Field: As <i>operand2</i>, you specify the field which is to receive the values of the source fields. If the target field is of format U (Unicode) and if a source field of format B is involved, the length of the sending binary field must be even.		
LEAVING SPACE	Values in Target Field Separated by a Blank: If you use the COMPRESS statement without any further options, or if you specify LEAVING SPACE (which also applies by default), the values in the target field will be separated from one another by a blank.		
LEAVING NO SPACE	Values in Target Field Not Separated: If you specify LEAVING NO SPACE, the values in the target field will not be separated from one another by a blank or any other character.		
<i>parameter</i>	Print Mode/Date Format Parameters: As <i>parameter</i>, you can specify the session parameter PM or the session parameter DF: <table> <tr> <td>PM=I</td><td>In order to support languages whose writing direction is from right to left, you can specify PM=I so as to transfer the value of <i>operand1</i> in inverse (right-to-left) direction to <i>operand2</i>. For</td></tr> </table>	PM=I	In order to support languages whose writing direction is from right to left, you can specify PM=I so as to transfer the value of <i>operand1</i> in inverse (right-to-left) direction to <i>operand2</i> . For
PM=I	In order to support languages whose writing direction is from right to left, you can specify PM=I so as to transfer the value of <i>operand1</i> in inverse (right-to-left) direction to <i>operand2</i> . For		

Syntax Element	Description
	example, as a result of the following statements, the content of #B would be ZYXABC: <pre>MOVE 'XYZ' TO #A COMPRESS #A (PM=I) 'ABC' INTO #B LEAVING NO SPACE</pre> Any trailing blanks in <i>operand1</i> will be removed (except if FULL is specified), then the value is reversed character by character and transferred to <i>operand2</i>.
	DF If <i>operand1</i> is a date variable, you can specify the session parameter DF as <i>parameter</i> for this variable.
SUBSTRING (<i>operand1</i> , <i>operand3</i> , <i>operand4</i>)	SUBSTRING Option: If <i>operand1</i> is of alphanumeric (A), Unicode (U) or binary (B) format, you can use the SUBSTRING option to transfer only a certain part of a source field. After the field name (<i>operand1</i>) you specify first the starting position (<i>operand3</i>) and then the length (<i>operand4</i>) of the field portion to be transferred.
INTO SUBSTRING (<i>operand2</i> , <i>operand5</i> , <i>operand6</i>)	INTO Clause: Also, you can use the SUBSTRING option in the INTO clause to transfer source values into a certain part of the target field. In both cases, the use of the SUBSTRING option in a COMPRESS statement corresponds to that in a MOVE statement. See the MOVE statement for details on the SUBSTRING option.
WITH DELIMITERS	Input Delimiter Character: If you wish the values in the target field to be separated from one another by a specific character, you use the DELIMITERS option. If you specify WITH DELIMITERS without <i>operand7</i>, the values will be separated by the input delimiter character as defined with the session parameter ID.
WITH DELIMITERS <i>operand7</i>	Specific Delimiter Character: If you specify WITH DELIMITERS <i>operand7</i>, the values will be separated by the character specified with <i>operand7</i>. <i>operand7</i> must be a single character. If <i>operand7</i> is a variable, it must be of format/length (A1) or (B1). If the target field is of format A or B, the format/length of the delimiter has to be (A1), (B1) or (U1). If the target field is of format U (Unicode), the format/length of the delimiter has to be (A1), (B2) or (U1).
WITH ALL	Handling of Delimiters: Without ALL, a delimiter is placed in the target field only between values actually transferred. For example:

Syntax Element	Description
	<pre>COMPRESS 'A' ' ' 'C' ' ' INTO #TARGET WITH DELIMITERS '*'</pre> Content of #TARGET is: A*C With ALL, a delimiter is also placed in the target field for each blank value that is not actually transferred. This means that the number of delimiters in the target field corresponds to the number of source fields minus 1. This may be useful, for example, if the content of the target field is to be separated again with a subsequent SEPARATE statement. For example: <pre>COMPRESS 'A' ' ' 'C' ' ' INTO #TARGET WITH ALL DELIMITERS '*'</pre> Content of #TARGET is: A**C*

Processing

A destination field of format B is handled like a destination field of format A.

The COMPRESS operation terminates when either all operands have been processed or the target field (*operand2*) is filled.

If the target field contains more positions than all operands combined, all remaining positions of *operand2* will be filled with blanks. If the target field is shorter, the value will be truncated.

If *operand2* is a dynamic variable, the COMPRESS operation terminates when all source operands have been processed. No truncation will be performed. The length of *operand2* after the COMPRESS operation will correspond to the combined length of the source operands. The current length of a dynamic variable can be ascertained by using the system variable *LENGTH.

Examples

This section covers the following topics:

- [Example 1 - Compress](#)
- [Example 2 - Compress Leaving No Space](#)

■ Example 3 - Compress with Delimiter

Example 1 - Compress

```

** Example 'CMPEX1': COMPRESS
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 FIRST-NAME
  2 MIDDLE-I
*
1 #COMPRESSED-NAME (A20)
END-DEFINE
*
LIMIT 4
READ EMPLOY-VIEW BY NAME
  COMPRESS FIRST-NAME MIDDLE-I NAME INTO #COMPRESSED-NAME
  DISPLAY NOTITLE
    FIRST-NAME MIDDLE-I NAME 5X #COMPRESSED-NAME
END-READ
*
END

```

Output of Program CMPEX1:

FIRST-NAME	MIDDLE-I	NAME	#COMPRESSED-NAME
-----	-----	-----	-----
KEPA		ABELLAN	KEPA ABELLAN
ROBERT	W	ACHIESON	ROBERT W ACHIESON
SIMONE		ADAM	SIMONE ADAM
JEFF	H	ADKINSON	JEFF H ADKINSON

Example 2 - Compress Leaving No Space

```

** Example 'CMPEX2': COMPRESS (with LEAVING NO SPACE)
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 CURR-CODE (1)
  2 SALARY (1)
*
1 #CCSALARY (A20)
END-DEFINE
*
LIMIT 4
READ EMPL-VIEW BY NAME

```

```
COMPRESS CURR-CODE (1) SALARY (1) INTO #CCSALARY
      LEAVING NO SPACE
DISPLAY NOTITLE
      NAME CURR-CODE (1) SALARY (1) 5X #CCSALARY
END-READ
*
END
```

Output of Program CMPEX2:

NAME	CURRENCY CODE	ANNUAL SALARY	#CCSALARY
-----	-----	-----	-----
ABELLAN	PTA	1450000	PTA1450000
ACHIESON	UKL	11300	UKL11300
ADAM	FRA	159980	FRA159980
ADKINSON	USD	34500	USD34500

Example 3 - Compress with Delimiter

```
** Example 'CMPEX3': COMPRESS (with delimiter)
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 CURR-CODE (1)
  2 SALARY (1)
*
1 #CCSALARY (A20)
END-DEFINE
*
LIMIT 4
READ EMPL-VIEW BY NAME
  COMPRESS CURR-CODE (1) SALARY (1) INTO #CCSALARY
      WITH DELIMITER '*'
  DISPLAY NOTITLE NAME CURR-CODE (1) SALARY (1) 5X #CCSALARY
END-READ
*
END
```

Output of Program CMPEX3:


NAME	CURRENCY CODE	ANNUAL SALARY	#CCSALARY
-----	-----	-----	-----
ABELLAN	PTA	1450000	PTA*1450000
ACHIESON	UKL	11300	UKL*11300
ADAM	FRA	159980	FRA*159980
ADKINSON	USD	34500	USD*34500

34


COMPUTE

■ Function	276
■ Syntax Description	278
■ Result Precision of a Division	280
■ Examples	281

Structured Mode Syntax



Reporting Mode Syntax



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [ADD](#) | [COMPRESS](#) | [DIVIDE](#) | [EXAMINE](#) | [MOVE](#) | [MOVE ALL](#) | [MULTIPLY](#) | [RESET](#) | [SEPARATE](#) | [SUBTRACT](#)

Belongs to Function Group: [Arithmetic and Data Movement Operations](#)

Function

The COMPUTE statement is used to perform an arithmetic or assignment operation.

A COMPUTE statement with multiple target operands (*operand1*) is identical to the corresponding individual COMPUTE statements if the source operand (*operand2*) is not an arithmetic expression.

```
#TARGET1 := #TARGET2 := #SOURCE
```

is identical to

```
#TARGET1 := #SOURCE
#TARGET2 := #SOURCE
```

Example:

```

DEFINE DATA LOCAL
1 #ARRAY(I4/1:3) INIT <3,0,9>
1 #INDEX(I4)
1 #RESULT(I4)
END-DEFINE
*
#INDEX := 1
*
#INDEX :=      /* #INDEX is 3
#RESULT :=     /* #RESULT is 9
#ARRAY(#INDEX)
*
#INDEX := 2
*
#INDEX :=      /* #INDEX is 0
#ARRAY(3) :=   /* returns runtime error NAT1316
#ARRAY(#INDEX)
END

```

If the source operand is an arithmetic expression, the expression is evaluated and its result is stored in a temporary variable. Then the temporary variable is assigned to the target operands.

```

#TARGET1 := #TARGET2 := #SOURCE1 + 1
is identical to
#TEMP := #SOURCE1 + 1
#TARGET1 := #TEMP
#TARGET2 := #TEMP

```

Example:

```

DEFINE DATA LOCAL
1 #ARRAY(I4/1:3) INIT <2, 0, 9>
1 #INDEX(I4)
1 #RESULT(I4)
END-DEFINE
*
#INDEX := 1
*
#INDEX :=      /* #INDEX is 3
#RESULT :=     /* #RESULT is 3
#ARRAY(#INDEX) + 1
*
#INDEX := 2
*
#INDEX :=      /* #INDEX is 0
#ARRAY(3) :=   /* returns run time error NAT1316
#ARRAY(#INDEX)
END

```

For further information, see *Rules for Arithmetic Assignment* in the *Programming Guide* and particularly the following sections:

- *Arithmetic Operations with Arrays*
- *Data Transfer* (for information on data transfer compatibility and the rules for data transfer)

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats												Referencing Permitted	Dynamic Definition		
<i>operand1</i>		S	A		M		A	U	N	P	I	F	B	D	T	L	C	G	O	yes	yes
<i>operand2</i>	C	S	A		N	E	A	U	N	P	I	F	B	D	T	L	C	G	O	yes	no
<i>operand3</i>	C	S							N	P	I		B*							yes	no
<i>operand4</i>	C	S							N	P	I		B*							yes	no

* If *operand3* or *operand4* is a binary variable, it may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
COMPUTE ASSIGN [:]=	Usage of Keywords: This statement may be issued in short form by omitting the statement keyword COMPUTE (or ASSIGN). In structured mode, when the statement keyword COMPUTE (or ASSIGN) is omitted, the equal sign (=) must be preceded by a colon (:). However, when the ROUNDED option is used, the statement keyword COMPUTE (or ASSIGN) must be specified.
ROUNDED	ROUNDED Option: If you specify the keyword ROUNDED, the value will be rounded before it is assigned to <i>operand1</i>. For information on rounding, see <i>Rules for Arithmetic Assignments, Field Truncation and Field Rounding</i> in the <i>Programming Guide</i>.
<i>operand1</i>	Result Field: <i>operand1</i> will contain the result of the arithmetic/assignment operation. For the precision of the result, see <i>Precision of Results of Arithmetic Operations</i> in the <i>Programming Guide</i>. If <i>operand1</i> is a database field, the field in the database is not updated.

Syntax Element	Description														
	If <i>operand1</i> is a dynamic variable, it is filled with exactly the data and length of <i>operand2</i> or the length of the result of the arithmetic-operation, including trailing blanks. The current length of a dynamic variable can be obtained by using the system variable *LENGTH. For general information on dynamic variables, see <i>Using Dynamic and Large Variables</i>.														
<i>arithmetic-expression</i>	Arithmetic Expression: An arithmetic expression consists of one or more constants, database fields, and user-defined variables. Natural mathematical functions (described in the <i>System Functions</i> documentation) may also be used as arithmetic operands. Operands used in an arithmetic expression must be defined with format N, P, I, F, D, or T. As for the formats of the operands, see also <i>Performance Considerations for Mixed Formats</i> in the <i>Programming Guide</i>. The following connecting operators may be used: <table> <tr> <th>Operator:</th><th>Symbol:</th></tr> <tr> <td>Parentheses</td><td>()</td></tr> <tr> <td>Exponentiation</td><td>**</td></tr> <tr> <td>Multiplication</td><td>*</td></tr> <tr> <td>Division</td><td>/</td></tr> <tr> <td>Addition</td><td>+</td></tr> <tr> <td>Subtraction</td><td>-</td></tr> </table> Each operator should be preceded and followed by at least one blank so as to avoid any conflict with a variable name that contains any of the above characters. The processing order of arithmetic operations is: 1. Parentheses 2. Exponentiation 3. Multiplication/division (left to right as detected) 4. Addition/subtraction (left to right as detected)	Operator:	Symbol:	Parentheses	()	Exponentiation	**	Multiplication	*	Division	/	Addition	+	Subtraction	-
Operator:	Symbol:														
Parentheses	()														
Exponentiation	**														
Multiplication	*														
Division	/														
Addition	+														
Subtraction	-														
<i>operand2</i>	Source Field: <i>operand2</i> is the source field. If <i>operand1</i> is of format C, <i>operand2</i> may also be specified as an attribute constant. See <i>User-Defined Constants</i> in the <i>Programming Guide</i>.														

Syntax Element	Description
SUBSTRING <i>(operand2,operand3,operand4)</i>	SUBSTRING Option: Without the substring option, the whole content of <i>operand2</i> is moved. If <i>operand1</i> and <i>operand2</i> are of alphanumeric, Unicode or binary format, you may use the SUBSTRING option to assign a certain part of <i>operand2</i> to <i>operand1</i>. After the field name (<i>operand2</i>) in the SUBSTRING clause, you specify the starting position (<i>operand3</i>) and then the length (<i>operand4</i>) of the field portion to be moved. For example, to assign the 3rd to 6th position of field #B to field #A, you would specify: <pre>#A := SUBSTRING(#B,3,4)</pre> If you omit <i>operand3</i>, the starting position is assumed to be 1. If you omit <i>operand4</i>, the length is assumed to range from the starting position to the end of the field. Note: ASSIGN with the SUBSTRING option is a byte-by-byte assignment (that is, the rules described under <i>Rules for Arithmetic Assignment</i> in the <i>Programming Guide</i> do not apply). See also MOVE SUBSTRING.

Result Precision of a Division

The precision (number of decimal positions) of the result of a division in a COMPUTE statement is determined by the precision of either the first operand (dividend) or the first result field, whichever is greater.

For a division of integer operands, however, the following applies: For a division of two integer constants, the precision of the result is determined by the precision of the first result field; however, if at least one of the two integer operands is a variable, the result is also of integer format (that is, without decimal positions, regardless of the precision of the result field).

Examples

- [Example 1 - ASSIGN Statement](#)
- [Example 2 - COMPUTE Statement](#)

Example 1 - ASSIGN Statement

```

** Example 'ASGEX1S': ASSIGN (structured mode)
*****
DEFINE DATA LOCAL
1 #A (N3)
1 #B (A6)
1 #C (N0.3)
1 #D (N0.5)
1 #E (N1.3)
1 #F (N5)
1 #G (A25)
1 #H (A3/1:3)
END-DEFINE
*
ASSIGN #A = 5                                WRITE NOTITLE '=' #A
ASSIGN #B = 'ABC'                            WRITE '=' #B
ASSIGN #C = .45                              WRITE '=' #C
ASSIGN #D = #E = -0.12345                    WRITE '=' #D / '=' #E
ASSIGN ROUNDED #F = 199.999                  WRITE '=' #F
#G      := 'HELLO'                           WRITE '=' #G
#H (1)  := 'UVW'
#H (3)  := 'XYZ'                             WRITE '=' #H (1:3)
*
END

```

Output of Program ASGEX1S:

```

#A:      5
#B: ABC
#C:    .450
#D: - .12345
#E: -0.123
#F:     200
#G: HELLO
#H: UVW   XYZ

```

Equivalent reporting-mode example: [ASGEX1R](#).

Example 2 - COMPUTE Statement

```

** Example 'CPTEX1': COMPUTE
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 SALARY      (1:2)
*
1 #A            (P4)
1 #B            (N3.4)
1 #C            (N3.4)
1 #CUM-SALARY  (P10)
1 #I            (P2)
END-DEFINE
*
COMPUTE #A = 3 * 2 + 4 / 2 - 1
WRITE NOTITLE 'COMPUTE #A = 3 * 2 + 4 / 2 - 1' 10X '=' #A
*
COMPUTE ROUNDED #B = 3 -4 / 2 * .89
WRITE 'COMPUTE ROUNDED #B = 3 -4 / 2 * .89' 5X '=' #B
*
COMPUTE #C = SQRT (#B)
WRITE 'COMPUTE #C = SQRT (#B)' 18X '=' #C
*
LIMIT 1
READ EMPLOY-VIEW BY PERSONNEL-ID STARTING FROM '20017000'
  WRITE / 'CURRENT SALARY:' 4X SALARY (1)
    / 'PREVIOUS SALARY:' 4X SALARY (2)
  FOR #I = 1 TO 2
    COMPUTE #CUM-SALARY = #CUM-SALARY + SALARY (#I)
  END-FOR
  WRITE 'CUMULATIVE SALARY:' #CUM-SALARY
END-READ
*
END

```

Output of Program CPTEx1:

```

COMPUTE #A = 3 * 2 + 4 / 2 - 1      #A:      7
COMPUTE ROUNDED #B = 3 -4 / 2 * .89  #B:      1.2200
COMPUTE #C = SQRT (#B)              #C:      1.1045

CURRENT SALARY:      34000
PREVIOUS SALARY:     32300
CUMULATIVE SALARY:   66300

```


35

CREATE OBJECT

■ Function	284
■ Syntax Description	284

```
CREATE OBJECT operand1 OF [CLASS] operand2
    [GIVING operand3]
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [DEFINE CLASS](#) | [INTERFACE](#) | [METHOD](#) | [PROPERTY](#) | [SEND METHOD](#)

Belongs to Function Group: [Component Based Programming](#)

Function

The `CREATE OBJECT` statement is used to create an instance of a class.

Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>		S														O	no	no
<i>operand2</i>	C	S				A											yes	no
<i>operand3</i>		S			N				I								yes	no

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Object Handle: <i>operand1</i> must be defined as an object handle (<code>HANDLE OF OBJECT</code>). The object handle is filled when the object is successfully created. When not successfully returned, <i>operand1</i> contains the value <code>NULL -HANDLE</code> .
OF CLASS <i>operand2</i>	Class-Name: <i>operand2</i> is the name of the class of which the object is to be created. For classes that are not registered as DCOM classes, it must contain the class name defined in the DEFINE CLASS statement. For classes that are registered as DCOM classes, it must contain either the ProgID of the class or the class GUID. For Natural classes that are registered as DCOM classes, the ProgID corresponds to the class name specified in the DEFINE CLASS statement.

Syntax Element	Description
	CREATE OBJECT #01 OF CLASS "Employee" or CREATE OBJECT #01 OF CLASS "653BCFE0-84DA-11D0-BEB3-10005A66D231"
GIVING <i>operand3</i>	GIVING Clause: If this clause is specified, <i>operand3</i> contains either the Natural message number if an error occurred, or zero on success. If this clause is not specified, Natural run time error processing is triggered if an error occurs.

36

DECIDE FOR

■ Function	288
■ Syntax Description	288
■ Examples	289

```
DECIDE FOR      { FIRST      }      CONDITION
                  { EVERY    }
{WHEN logical-condition statement ...} ...
[WHEN ANY statement ...]
[WHEN ALL statement ...]
WHEN NONE statement ...
END-DECIDE
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [DECIDE ON](#) | [IF](#) | [IF SELECTION](#) | [ON ERROR](#)

Belongs to Function Group: [Processing of Logical Conditions](#)

Function

The `DECIDE FOR` statement is used to decide for one or more actions depending on multiple conditions (cases).



Note: If *no* action is to be performed under a certain condition, you must specify the statement `IGNORE` in the corresponding clause of the `DECIDE FOR` statement.

Syntax Description

Syntax Element	Description
FIRST CONDITION	Processing of First Condition Only: Only the first true condition is to be processed. See also Example 1 .
EVERY CONDITION	Processing of Every Condition: Every true condition is to be processed. See also Example 2 .
WHEN <i>logical-condition statement</i>	Logical Condition(s) to be Processed: With this clause, you specify the logical condition(s) to be processed. See the section <i>Logical Condition Criteria</i> in the <i>Programming Guide</i> .
WHEN ANY <i>statement</i>	WHEN ANY Clause:

Syntax Element	Description
	With WHEN ANY, you can specify the statement(s) to be executed when any of the logical conditions are true.
WHEN ALL <i>statement</i>	WHEN ALL Clause: With WHEN ALL, you can specify the statement (s) to be executed when all logical conditions are true. This clause is applicable only if EVERY has been specified.
WHEN NONE <i>statement</i>	WHEN NONE Clause: With WHEN NONE, you specify the statement(s) to be executed when none of the logical conditions are true.
END-DECIDE	End of DECIDE FOR Statement: The Natural reserved word END-DECIDE must be used to end the DECIDE FOR statement.

Examples

- [Example 1 - DECIDE FOR with FIRST Option](#)
- [Example 2 - DECIDE FOR with EVERY Option](#)

Example 1 - DECIDE FOR with FIRST Option

```

** Example 'DECEX1': DECIDE FOR (with FIRST option)
*****
DEFINE DATA LOCAL
1 #FUNCTION (A1)
1 #PARM      (A1)
END-DEFINE
*
INPUT #FUNCTION #PARM
*
DECIDE FOR FIRST CONDITION
  WHEN #FUNCTION = 'A' AND #PARM = 'X'
    WRITE 'Function A with parameter X selected.'
  WHEN #FUNCTION = 'B' AND #PARM = 'X'
    WRITE 'Function B with parameter X selected.'
  WHEN #FUNCTION = 'C' THRU 'D'
    WRITE 'Function C or D selected.'
  WHEN NONE
    REINPUT 'Please enter a valid function.'
    MARK *#FUNCTION
END-DECIDE

```

```
*  
END
```

Output of Program DECEX1:

```
#FUNCTION    #PARM
```

After entering A and Y and pressing ENTER:

```
#FUNCTION A #PARM Y  
  
Please enter a valid function.
```

Example 2 - DECIDE FOR with EVERY Option

```
** Example 'DECEX2': DECIDE FOR (with EVERY option)  
*****  
DEFINE DATA LOCAL  
1 #FIELD1 (N5.4)  
END-DEFINE  
*  
INPUT #FIELD1  
*  
DECIDE FOR EVERY CONDITION  
    WHEN #FIELD1 >= 0  
        WRITE '#FIELD1 is positive or zero.'  
    WHEN #FIELD1 <= 0  
        WRITE '#FIELD1 is negative or zero.'  
    WHEN FRAC(#FIELD1) = 0  
        WRITE '#FIELD1 has no decimal digits.'  
    WHEN ANY  
        WRITE 'Any of the above conditions is true.'  
    WHEN ALL  
        WRITE '#FIELD1 is zero.'  
    WHEN NONE  
        IGNORE  
END-DECIDE  
*  
END
```


Output of Program DECEX2:

```
#FIELD1 42
```

After pressing ENTER:


```
Page      1                                05-01-11  14:56:26
```

```
#FIELD1 is positive or zero.  
#FIELD1 has no decimal digits.  
Any of the above conditions is true.
```


37

DECIDE ON

■ Function	294
■ Syntax Description	294
■ Examples	296



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [DECIDE FOR](#) | [IF](#) | [IF SELECTION](#) | [ON ERROR](#)

Belongs to Function Group: [Processing of Logical Conditions](#)

Function

The `DECIDE ON` statement is used to specify multiple actions to be performed depending on the value (or values) contained in a variable.

 **Note:** If *no* action is to be performed under a certain condition, you must specify the statement `IGNORE` in the corresponding clause of the `DECIDE ON` statement.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats											Referencing Permitted	Dynamic Definition	
op1		S	A		N	A	U	N	P	I	F	B	D	T	L	G	O	yes	no
op2	C	S	A			A	U	N	P	I	F	B	D	T	L	G	O	yes	no
op3		S	A			A	U					B						yes	no
op4	C	S	A			A	U					B						yes	no
op5	C	S						N	P	I		B *						yes	no
op6	C	S						N	P	I		B *						yes	no
op7	C	S						N	P	I		B *						yes	no

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>op8</i>	C	S						N	P	I	B *					yes	no

* Format B of *op5*, *op6*, *op7* and *op8* may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
FIRST/EVERY	Processing of Values: With one of these keywords, you indicate whether only the first or every value that is found is to be processed.
<i>op1</i>	Selection Field: As <i>op1</i> or <i>op2</i> you specify the name of the field whose content is to be checked.
VALUES <i>op2</i> [, <i>op2</i>] ... [: <i>op2</i>] <i>statement</i> ...	VALUES Clause: With this clause, you specify the value (<i>op2</i>) of the selection field, as well as the <i>statement(s)</i> which are to be executed if the field contains that value. You can specify one value, multiple values, or a range of values optionally preceded by one or more values. Multiple values must be separated from one another either by the input delimiter character (as specified with the session parameter ID) or by a comma. A comma must not be used for this purpose, however, if the comma is defined as decimal character (with the session parameter DC). For a range of values, you specify the starting value and ending value of the range, separated from each other by a colon.
SUBSTRING	SUBSTRING Option: Without the SUBSTRING option, the whole content of a field is checked. The SUBSTRING option allows you to check only a certain part of an alphanumeric, Unicode or binary field. After the field name (<i>op3</i>), you specify first the starting position (<i>op5</i>) and then the length (<i>op6</i>) of the field portion to be checked.
SUBSTRING (<i>op4</i> , <i>op7</i> , <i>op8</i>)	SUBSTRING Option: After the field name (<i>op4</i>), you specify first the starting position (<i>op7</i>) and then the length (<i>op8</i>) of the field portion to be checked.
ANY <i>statement</i>	ANY Clause: With ANY, you specify the <i>statement(s)</i> which are to be executed if any of the values in the VALUES clause are found. These statements are to be executed in addition to the statement specified in the VALUES clause.

Syntax Element	Description
ALL <i>statement</i>	ALL Clause: With ALL, you specify the <i>statement(s)</i> which are to be executed if all of the values in the VALUES clause are found. These statements are to be executed in addition to the statement specified in the VALUES clause. The ALL clause applies only if the keyword EVERY is specified.
NONE <i>statement</i>	NONE Clause: With NONE, you specify the <i>statement(s)</i> which are to be executed if none of the specified values are found.
END-DECIDE	End of DECIDE ON Statement: The Natural reserved word END-DECIDE must be used to end the DECIDE ON statement.

Examples

- [Example 1 - DECIDE ON with FIRST Option](#)
- [Example 2 - DECIDE ON with EVERY Option](#)

Example 1 - DECIDE ON with FIRST Option

```
** Example 'DECEX3': DECIDE ON (with FIRST option)
*****
*
SET KEY ALL
INPUT 'Enter any PF key' /
      'and check result' /
*
DECIDE ON FIRST VALUE OF *PF-KEY
  VALUE 'PF1'
    WRITE 'PF1 key entered.'
  VALUE 'PF2'
    WRITE 'PF2 key entered.'
  ANY VALUE
    WRITE 'PF1 or PF2 key entered.'
  NONE VALUE
    WRITE 'Neither PF1 nor PF2 key entered.'
END-DECIDE
*
END
```

Output of Program DECEX3:

Enter any PF key
and check result

Output after pressing PF1:

Page 1 05-01-11 15:08:50
PF1 key entered.
PF1 or PF2 key entered.

Example 2 - DECIDE ON with EVERY Option

```
** Example 'DECEX4': DECIDE ON (with EVERY option)
*****
DEFINE DATA LOCAL
1 #FIELD (N1)
END-DEFINE
*
INPUT 'Enter any value between 1 and 9:' #FIELD (SG=OFF)
*
DECIDE ON EVERY VALUE OF #FIELD
  VALUE 1 : 4
    WRITE 'Content of #FIELD is 1-4'
  VALUE 2 : 5
    WRITE 'Content of #FIELD is 2-5'
  ANY VALUE
    WRITE 'Content of #FIELD is 1-5'
  ALL VALUE
    WRITE 'Content of #FIELD is 2-4'
  NONE VALUE
    WRITE 'Content of #FIELD is not 1-5'
  END-DECIDE
*
END
```

Output of Program DECEX4:

ENTER ANY VALUE BETWEEN 1 AND 9: 4


After entering and confirming 4:

Page	1	05-01-11	15:11:45
Content of #FIELD is	1-4		
Content of #FIELD is	2-5		
Content of #FIELD is	1-5		
Content of #FIELD is	2-4		

38

DEFINE CLASS

■ Function	300
■ Syntax Description	300



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [CREATE OBJECT](#) | [INTERFACE](#) | [METHOD](#) | [PROPERTY](#) | [SEND METHOD](#)

Belongs to Function Group: [Component Based Programming](#)

Function

The `DEFINE CLASS` statement is used to specify a class from within a Natural class module. A Natural class module consists of one `DEFINE CLASS` statement followed by an `END` statement.


Syntax Description

Syntax Element	Description
<i>class-name</i>	Class Name: This is the name that is used by clients to create objects of this class. The name can be up to a maximum of 32 characters long. The name may contain periods: this can be used to construct class names such as <i>company-name.application-name.class-name</i> Each part between the periods (...) must conform to the <i>Naming Conventions for User-Defined Variables</i> .

Syntax Element	Description
	If the class is planned to be used by clients written in different programming languages, the class name should be chosen in a way that it does not conflict with the naming conventions that apply in these languages.
OBJECT	OBJECT Clause: This clause is used to define the object data. The syntax of the OBJECT clause is the same as for the LOCAL clause of the DEFINE DATA statement. For further information, see the description of the LOCAL clause of the DEFINE DATA statement.
LOCAL	LOCAL Clause: This clause is only used to include globally unique IDs (GUIDs) in the class definition. GUIDs need only be defined if a class is to be registered with DCOM. GUIDs are mostly defined in a local data area. The syntax of the LOCAL clause is the same as for the LOCAL clause of the DEFINE DATA statement. For further information, see the description of the LOCAL clause of the DEFINE DATA statement.
INTERFACE USING	INTERFACE USING Clause: This clause is used to include copycode that contains INTERFACE statements.
<i>copycode</i>	Copycode: The copycode used by the INTERFACE USING clause may contain one or more INTERFACE statements.
<i>interface-statement</i>	INTERFACE Statement: The INTERFACE statement is used to define methods and properties for a class.
<i>property-statement</i>	PROPERTY Statement: The PROPERTY statement is used to assign an object data variable operand as the implementation to a property, outside an interface definition.
<i>method-statement</i>	METHOD Statement: The METHOD statement is used to assign a subprogram as the implementation to a method, outside an interface definition.
END-CLASS	End of DEFINE CLASS Statement: The Natural reserved word END-CLASS must be used to end the DEFINE CLASS statement.

VI

DEFINE DATA



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related topics in the *Programming Guide: Use and Structure of DEFINE DATA Statement* | *Data Areas* | *Storage Alignment*

The DEFINE DATA documentation is organized under the following headings:

■ Function and Basic Syntax Rules

Data Definitions:

■ Defining Global Data

■ Defining Parameter Data

■ Defining Local Data

- [Defining Application-Independent Variables](#)
- [Defining Context Variables for Natural RPC](#)
- [Defining NaturalX Objects](#)

Clauses and Options:

- [Variable Definition](#)
- [View Definition](#)
- [Redefinition](#)
- [Array Dimension Definition](#)
- [Initial-Value Definition](#)
- [Initial/Constant Values for an Array](#)
- [EM, HD, PD Parameters for Field/Variable](#)

Examples:

- [Examples of DEFINE DATA Statement Usage](#)

39

Function and Basic Syntax Rules

■ Function	306
■ General Syntax Rules	306
■ Programming Modes	306

Function

The `DEFINE DATA` statement offers a number of clauses to declare data definitions for use within a Natural program, either by referencing predefined data definitions contained in a local data area (LDA), global data area (GDA) or parameter data area (PDA), or by writing in-line definitions.

General Syntax Rules

- When a `DEFINE DATA` statement is used, it must be the first statement of the program/routine.
- An “empty” `DEFINE DATA` statement is not allowed; at least one clause (`GLOBAL`, `PARAMETER`, `LOCAL`, `INDEPENDENT`, `CONTEXT` or `OBJECT`) must be specified.
- You can specify more than one clause. However, if the `GLOBAL` and the `PARAMETER` clauses are used, `GLOBAL` must be the first clause of the statement and `PARAMETER` must follow `GLOBAL` (without `GLOBAL`, `PARAMETER` comes first if used). All other clauses can be specified in any order.
- The Natural reserved word `END-DEFINE` must be used to end the `DEFINE DATA` statement.

Programming Modes

The `DEFINE DATA` statement is available in structured mode and in reporting mode. Differences are marked accordingly in the `DEFINE DATA` statement description.

Generally, the following applies:

- [Structured Mode](#)
- [Reporting Mode](#)

Structured Mode

All variables to be used, except [application-independent variables](#) (AIVs), must be defined in the `DEFINE DATA` statement; they must not be defined elsewhere in the program. If a `DEFINE DATA INDEPENDENT` statement is used, AIVs must not be defined elsewhere in the program.

Reporting Mode

The `DEFINE DATA` statement is not mandatory since variables may be defined in the body of the program. However, if a `DEFINE DATA LOCAL` statement is used in reporting mode, variables, except application-independent variables (AIVs), must not be defined elsewhere in the program; and if a `DEFINE DATA INDEPENDENT` statement is used, **application-independent variables** (AIVs) must not be defined elsewhere in the program.

40

Defining Global Data

■ Function	310
■ Syntax Description	310

General syntax of `DEFINE DATA GLOBAL`:

```
DEFINE DATA  
  GLOBAL USING global-data-area [WITH block[.block...]]  
END-DEFINE
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Function

The `DEFINE DATA GLOBAL` statement is used to define data elements using a GDA (see Global Data Area).

Syntax Description

Syntax Element	Description
<code>USING</code> <i>global-data-area</i>	GDA Name: Specify the name of a global data area (GDA) to be referenced. A GDA is created with the source editor. It contains predefined data elements which can be included in the <code>DEFINE DATA GLOBAL</code> statement. In contrast to an LDA, the data elements defined in a GDA can be referenced by more than one Natural object. For further information, see Global Data Area in the <i>Programming Guide</i> .
<code>WITH block</code>	Data Blocks: To save data storage space, you can create a global data area with data blocks. Data blocks can overlay one another during program execution, thereby saving storage space. The maximum number of block levels is 8 (including the master block). For further information, see <i>Data Blocks</i> in the <i>Programming Guide</i> .
<i>.block</i>	Block(s) to be Used: A single or multiple <i>.block</i> notations specify the block(s) which are used in the program.
<code>END-DEFINE</code>	End of DEFINE DATA Statement:

Syntax Element	Description
	The Natural reserved word <code>END-DEFINE</code> must be used to end the <code>DEFINE DATA</code> statement.

41

Defining Parameter Data

■ Function	314
■ Restrictions	314
■ Syntax Description	314

General syntax of `DEFINE DATA PARAMETER`:

```
DEFINE DATA
  PARAMETER [ USING parameter-data-area
              parameter-data-definition ... ]
END-DEFINE
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Function

The `DEFINE DATA PARAMETER` statement is used to define the data elements that are to be used as incoming parameters in a Natural subprogram, external subroutine or help routine. These parameters can be defined within the statement itself (see [Parameter Data Definition](#)); or they can be defined outside the program in a [parameter data area](#) (PDA), with the statement referencing that data area.

Restrictions

- Parameter data elements must not be assigned initial or constant values, and they must not have edit mask (EM), header (HD) or print mode (PM) definitions; see also [EM, HD, PM Parameters for Field/Variable](#).
- The parameter data area and the objects which reference it must be contained in the same library (or in a steplib).

Syntax Description

Syntax Element	Description
<code>USING <i>parameter-data-area</i></code>	Parameter Data Area (PDA) Name: The name of the <i>parameter-data-area</i> (PDA) that contains data elements which are used as parameters in a subprogram, external subroutine or dialog.
<code><i>parameter-data-definition</i></code>	Parameter Data Definition: Instead of using a PDA, you can define parameter data directly. See Parameter Data Definition .

Syntax Element	Description
END-DEFINE	End of DEFINE DATA Statement: The Natural reserved word END-DEFINE must be used to end the DEFINE DATA statement.

Parameter Data Definition

For parameter data definition, the following syntax applies:

$\left\{ \begin{array}{l} \text{group-name} [(\text{array-definition})] \\ \text{redefinition} \\ \text{level} \left\{ \begin{array}{l} (\text{format-length} [/\text{array-definition}]) \\ \text{variable-name} \left\{ \begin{array}{l} (\left\{ \begin{array}{l} A \\ U \\ B \end{array} \right\} [/\text{array-definition}]) \\ [(\text{array-definition})] \text{ HANDLE OF OBJECT} \end{array} \right\} \text{ DYNAMIC} \left\{ \begin{array}{l} [\text{BY VALUE}] \\ [\text{RESULT}] \\ [\text{OPTIONAL}] \end{array} \right\} \end{array} \right\} \end{array} \right\}$

Syntax Element Description:

Syntax Element	Description
<i>level</i>	Level Number: Level number is a 1- or 2-digit number in the range from 01 to 99 (the leading zero is optional) used in conjunction with field grouping. Fields assigned a level number of 02 or greater are considered to be a part of the immediately preceding group which has been assigned a lower level number. The definition of a group enables reference to a series of fields (may also be only 1 field) by using the group name. With certain statements (CALL , CALLNAT , RESET , WRITE , etc.), you may specify the group name as a shortcut to reference the fields contained in the group. A group may consist of other groups. When assigning the level numbers for a group, no level numbers may be skipped.
<i>group-name</i>	Group Name: The name of a group. The name must adhere to the rules for defining a Natural variable name. See also the following sections: ■ <i>Naming Conventions for User-Defined Variables in Using Natural.</i> ■ <i>Qualifying Data Structures in the Programming Guide.</i>
<i>array-definition</i>	Array Dimension Definition:

Syntax Element	Description
	With an <i>array-definition</i>, you define the lower and upper bounds of dimensions in an array-definition. For further information, see Array Dimension Definition and Variable Arrays in a Parameter Data Area.
<i>redefinition</i>	Redefinition: A <i>redefinition</i> may be used to redefine a group or a single field/variable (that is a scalar or an array). See Redefinition. Note: In a <i>parameter-data-definition</i>, a redefinition of groups is only permitted within a REDEFINE block.
<i>variable-name</i>	Variable Name: The name to be assigned to the variable. Rules for Natural variable names apply. For information on naming conventions for user-defined variables. For further information, see <i>Naming Conventions for User-Defined Variables in Using Natural</i>.
<i>format-length</i>	Format/Length Definition: The format and length of the field. For information on format/length definition of user-defined variables, see <i>Format and Length of User-Defined Variables in the Programming Guide</i>.
HANDLE OF OBJECT	Handle of Object: Used in conjunction with NaturalX. A handle identifies a dialog element in code and is stored in handle variables. For further information, see <i>NaturalX in the Programming Guide</i>.
A, U or B	Data Type: Alphanumeric (A), Unicode (U) or binary (B) for dynamic variable.
DYNAMIC	DYNAMIC Option: A parameter may be defined as DYNAMIC. For further information on processing dynamic variables, see <i>Introduction to Dynamic Variables and Fields in the Programming Guide</i>.
	Call Mode: Depending on whether call-by-reference, call-by-value or call-by-value-result is used, the appropriate transfer mechanism is applicable. For further information, see the CALLNAT statement.
(without BY VALUE)	Call-by-Reference: Call-by-reference is active by default when you omit the BY VALUE keywords. In this case, a parameter is passed to a subprogram/subroutine/function by reference (that

Syntax Element	Description		
	is, via its address); therefore a field specified as parameter in a CALLNAT/PERFORM statement must have the same format/length as the corresponding field in the invoked subprogram/subroutine/function.		
BY VALUE	Call-by-Value: When you specify BY VALUE, a parameter is passed to a subprogram/subroutine/function by value; that is, the actual parameter value (instead of its address) is passed. Consequently, the field in the subprogram/subroutine/function need not have the same format/length as the parameter passed in the CALLNAT/PERFORM statement or in the function call. The formats/lengths must only be data transfer compatible. For data transfer compatibility, the <i>Rules for Arithmetic Assignment</i> and <i>Data Transfer</i> apply (see <i>Programming Guide</i>). BY VALUE allows you, for example, to increase the length of a field in a subprogram/subroutine/function (if this should become necessary due to an enhancement of the subprogram/subroutine) without having to adjust any of the objects that invoke the subprogram/subroutine/function. Example of BY VALUE: <table> <tr> <td> <pre>* Program DEFINE DATA LOCAL 1 #FIELD A (P5) ... END-DEFINE ... CALLNAT 'SUBR01' #FIELD A...</pre> </td><td> <pre>* Subroutine SUBR01 DEFINE DATA PARAMETER 1 #FIELD B (P9) BY VALUE END-DEFINE ...</pre> </td></tr> </table>	<pre>* Program DEFINE DATA LOCAL 1 #FIELD A (P5) ... END-DEFINE ... CALLNAT 'SUBR01' #FIELD A...</pre>	<pre>* Subroutine SUBR01 DEFINE DATA PARAMETER 1 #FIELD B (P9) BY VALUE END-DEFINE ...</pre>
<pre>* Program DEFINE DATA LOCAL 1 #FIELD A (P5) ... END-DEFINE ... CALLNAT 'SUBR01' #FIELD A...</pre>	<pre>* Subroutine SUBR01 DEFINE DATA PARAMETER 1 #FIELD B (P9) BY VALUE END-DEFINE ...</pre>		
BY VALUE RESULT	Call-by-Value-Result: While BY VALUE applies to a parameter passed to a subprogram/subroutine/function, BY VALUE RESULT causes the parameter to be passed by value in both directions; that is, the actual parameter value is passed from the invoking object to the subprogram/subroutine/function and, on return to the invoking object, the actual parameter value is passed from the subprogram/subroutine/function back to the invoking object. With BY VALUE RESULT, the formats/lengths of the fields concerned must be data transfer compatible in both directions.		
OPTIONAL	Optional Parameters: For a parameter defined without OPTIONAL (default), a value <i>must</i> be passed from the invoking object. For a parameter defined with OPTIONAL, a value can, but need not be passed from the invoking object to this parameter. In the invoking object, the notation <i>nX</i> is used to indicate parameters which are skipped, that is, for which no values are passed.		

Syntax Element	Description
	With the SPECIFIED option you can find out at run time whether an optional parameter has been defined or not.




Note: See also *Matching Format Specification of Array Dimensions* in the *Programming Guide*.

42

Defining Local Data

■ Function	320
■ Restriction	320
■ Syntax Description	320

General syntax of `DEFINE DATA LOCAL`:



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Function

The `DEFINE DATA LOCAL` statement is used to define the data elements that are to be used exclusively by a single Natural module in an application. These elements or fields can be defined in different ways:

- either within the `DEFINE DATA LOCAL` statement itself, using the *local-data-definition* syntax (see [Local Data Definition](#))
- or outside the program in a separate LDA (*Local Data Area*) or PDA (*Parameter Data Area*), with the `DEFINE DATA LOCAL USING` statement referencing that data area.

Restriction

The LDA and the objects which reference it must be contained in the same library (or in a steplib).

Syntax Description

Syntax Element	Description
<i>local-data-area</i>	LDA Name: Specify the name of the local data area (LDA) to be referenced. An LDA is created with the source editor. It contains predefined data elements which can be included in the <code>DEFINE DATA LOCAL</code> statement. You may reference more than one data area; in that case you have to repeat the reserved words <code>LOCAL</code> and <code>USING</code> , for example:

Syntax Element	Description
	<pre> DEFINE DATA LOCAL LOCAL USING DATX_L LOCAL USING DATX_P ... END-DEFINE ; </pre> For further information, see also <i>Defining Fields in a Separate Data Area</i> and <i>Local Data Area, Example 2</i> in the <i>Programming Guide</i>.
<i>parameter-data-area</i>	PDA Name: Specify the name of a parameter data area (PDA). Note: A data area referenced with <code>DEFINE DATA LOCAL</code> may also be a parameter data area (PDA). By using a PDA as an LDA you can avoid the extra effort of creating an LDA that has the same structure as the PDA. A PDA is created with the source editor. It contains predefined data elements which can be included in the <code>DEFINE DATA LOCAL</code> statement. For further information, see <i>Parameter Data Area</i> in the <i>Programming Guide</i>.
<i>local-data-definition</i>	Local Data Definition: For information on how to define elements or fields within the statement itself, that is, without using an LDA or PDA, see the section Local Data Definition below.
END-DEFINE	End of DEFINE DATA Statement: The Natural reserved word <code>END-DEFINE</code> must be used to end the <code>DEFINE DATA</code> statement.

Local Data Definition

Local data can be defined directly. For local data definition, the following syntax applies:

$\left\{ \begin{array}{l} \text{level} \left\{ \begin{array}{l} \text{group-name} [(\text{array-definition})] \\ \text{variable-definition} \\ \text{view-definition} \\ \text{redefinition} \end{array} \right\} \end{array} \right\}$

For further information, see

- [Example 1 - DEFINE DATA LOCAL \(Local Data Definition\)](#)
- *Defining Fields within a DEFINE DATA Statement in the Programming Guide*
- *Local Data Area, Example 1 in the Programming Guide*

Syntax Element Description for Local Data Definition:

Syntax Element	Description
<i>level</i>	Level Number: Level number is a 1- or 2-digit number in the range from 01 to 99 (the leading zero is optional) used in conjunction with field grouping. Fields assigned a level number of 02 or greater are considered to be a part of the immediately preceding group which has been assigned a lower level number. The definition of a group enables reference to a series of fields (may also be only 1 field) by using the group name. With certain statements (CALL, CALLNAT, RESET, WRITE, etc.), you may specify the group name as a shortcut to reference the fields contained in the group. A group may consist of other groups. When assigning the level numbers for a group, no level numbers may be skipped. A view-definition must always be defined at Level 1.
<i>group-name</i>	Group Name: The name of a group. The name must adhere to the rules for defining a Natural variable name. See also the following sections: ■ <i>Naming Conventions for User-Defined Variables in Using Natural.</i> ■ <i>Qualifying Data Structures in the Programming Guide.</i>
<i>array-definition</i>	Array Dimension Definition: With an <i>array-definition</i>, you define the lower and upper bounds of dimensions in an array-definition. See Array Dimension Definition.
<i>variable-definition</i>	Variable Definition: A <i>variable-definition</i> is used to define a single field/variable that may be single-valued (scalar) or multi-valued (array). See Variable Definition.
<i>view-definition</i>	View Definition: A <i>view-definition</i> is used to define a view as derived from a data definition module (DDM). See View Definition.
<i>redefinition</i>	Redefinition:

Syntax Element	Description
	A <i>redefinition</i> may be used to redefine a group, a view, a DDM field or a single field/variable (that is a scalar or an array). See Redefinition.

43

Defining Application-Independent Variables

■ Function	326
■ Syntax Description	326

General syntax of `DEFINE DATA INDEPENDENT`:

```
DEFINE DATA
  INDEPENDENT [aiv-data-definition ...]
END-DEFINE
```

For explanations of the symbols used in the syntax diagrams, see [Syntax Symbols](#).

Function

The `DEFINE DATA INDEPENDENT` statement is used to define application-independent variables (AIVs).

An application-independent variable is referenced by its name, and its content is shared by all Natural objects executed within one application that refer to that name. The variable is allocated by the first executed Natural object that references this variable and is deallocated by the `LOGON` command or a `RELEASE VARIABLES` statement.

The optional `INIT` clause is evaluated in each executed Natural object that contains this clause (not only in the Natural object that allocates the variable).



Note: In an RPC server, application-independent variables (AIVs) are not deallocated implicitly, but stay active across RPC requests, because different clients may have access to the same variables on the RPC server. This means they must be deallocated explicitly using the `RELEASE VARIABLES` statement. See *Application-Independent Variables in the Natural RPC (Remote Procedure Call)* documentation.

Syntax Description

Syntax Element	Description
<i>aiv-data-definition</i>	AIV Data Definition: The <code>DEFINE DATA INDEPENDENT</code> statement can be used to define a single or multiple application-independent variables (AIVs). For each AIV, the syntax shown in AIV Data Definition applies.
END-DEFINE	End of DEFINE DATA Statement: The Natural reserved word <code>END-DEFINE</code> must be used to end the <code>DEFINE DATA</code> statement.

AIV Data Definition

```
level { variable-definition
      redefinition }
```

Syntax Element Description:

Syntax Element	Description
<i>level</i>	Level Number: An application-independent variable must be defined at Level 01. Other levels are only used in a redefinition.
<i>variable-definition</i>	Variable Definition A <i>variable definition</i> is used to define a single field/variable that may be single-valued (scalar) or multi-valued (array). For further information, see Variable Definition. Note: The name of an application-independent variable must start with a plus (+) character.
<i>redefinition</i>	Redefinition: With a <i>redefinition</i>, you can partition an application-independent variable into one or more subfields. For further information, see Redefinition. The subfields resulting from the redefinition must not be application-independent variables; that is, their name must not start with a plus sign (+). These fields are treated as local variables.




Note: The first character of the name must be a plus (+). Rules for Natural variable names apply, see *Naming Conventions for User-Defined Variables* in *Using Natural*.

44

Defining Context Variables for Natural RPC

■ Function	330
■ Restrictions	331
■ Syntax Description	331

General syntax of `DEFINE DATA CONTEXT`:



For explanations of the symbols used in the syntax diagrams, see [Syntax Symbols](#).

Belongs to Function Group: [Natural Remote Procedure Call](#)

Function

The `DEFINE DATA CONTEXT` statement is used in conjunction with the Natural RPC (Remote Procedure Call). It is used to define variables known as context variables, which are meant to be available to multiple remote subprograms within one conversation, without having to explicitly pass the variables as parameters with the corresponding `CALLNAT` statements.

A context variable is referenced by its name, and its content is shared by all Natural objects executed in one conversation that refer to that name. The variable is allocated by the first executed Natural object that contains the definition of the variable and is deallocated when the conversation ends.

A context variable is not shared with subprograms that are called within the conversation. If such a subprogram or one of its callees references a context variable, a separate storage area is allocated for this variable.

Context variables can also be used in a non-conversational `CALLNAT`. In this case, the context variables only exist during a single invocation of this `CALLNAT`. The variable is allocated when the remote subprogram is started and deallocated when it ends. The content is shared by all Natural objects except subprograms executed by this non-conversational `CALLNAT`.

The optional `INIT` clause is evaluated in each executed Natural object that contains this clause (not only in the Natural object that allocates the variable). This is different to the way the `INIT` works for global variables.

For further information, see *Defining a Conversation Context in the Natural RPC (Remote Procedure Call)* documentation.

Restrictions

A context variable must be defined at Level 01. Other levels are only used in a redefinition.

Syntax Description

Syntax Element	Description
USING <i>local-data-area</i>	LDA Name: A local data area (LDA) contains data elements which are to be used in a single Natural module. You may reference more than one data area; in that case you have to repeat the reserved words <code>CONTEXT</code> and <code>USING</code>, for example: <pre>DEFINE DATA CONTEXT USING DATX_L CONTEXT USING DATX_P ... END-DEFINE ;</pre> For further information, see <i>Defining Fields in a Separate Data Area</i> in the <i>Programming Guide</i>.
USING <i>parameter-data-area</i>	PDA Name: A parameter data area contains data elements which are used as parameters in a subprogram, external subroutine or dialog.
<i>context-data-definition</i>	Context Data Definition: Context data can be defined directly within a program or routine. For context data definition, the syntax shown below applies.
END-DEFINE	End of DEFINE DATA Statement: The Natural reserved word <code>END-DEFINE</code> must be used to end the <code>DEFINE DATA</code> statement.

Context Data Definition

Context data can be defined directly within a program or routine. For context data definition, the following syntax applies:

```
level { variable-definition
      redefinition }
```

For further information, see *Defining Fields within a DEFINE DATA Statement* in the *Programming Guide*.

Syntax Element	Description
<i>level</i>	Level Number: An application-independent variable must be defined at Level 01. Other levels are only used in a redefinition.
<i>variable-definition</i>	Variable Definition: A <i>variable-definition</i> is used to define a single field/variable that may be single-valued (scalar) or multi-valued (array). For further information, see Variable Definition . Note: The <code>CONSTANT</code> clause must not be used in this context
<i>redefinition</i>	Redefinition: A <i>redefinition</i> may be used to redefine a group, a view, a DDM field or a single field/variable (that is a scalar or an array). For further information, see Redefinition .



Note: The fields resulting from the redefinition are not considered a context variable. These fields are treated as local variables.

45

Defining NaturalX Objects

■ Function	334
■ Syntax Description	334

General syntax of DEFINE DATA OBJECT:

```
DEFINE DATA

OBJECT      [ USING {      local-data-area
                    parameter-data-area } ]
            local-data-definition ...

END-DEFINE
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Function

The DEFINE DATA OBJECT statement is used in a subprogram or class in conjunction with NaturalX.

Syntax Description


Syntax Element	Description
USING local-data-area	LDA Name: A local data area (LDA) contains data elements which are to be used in a single Natural module. You may reference more than one data area; in that case you have to repeat the reserved words OBJECT and USING, for example: <pre>DEFINE DATA OBJECT USING DATX_L OBJECT USING DATX_P ... END-DEFINE ;</pre> For further information, see also <i>Defining Fields in a Separate Data Area</i> in the <i>Programming Guide</i>.
USING parameter-data-area	PDA Name: A data area defined with DEFINE DATA OBJECT may be a parameter data area (PDA). By using a PDA as an object data area you can avoid the extra effort of creating an object data area that has the same structure as the PDA.
local-data-definition	Local Data Definition: Data can also be defined directly using the syntax shown in Local Data Definition in the section <i>Defining Local Data</i>.
END-DEFINE	End of DEFINE DATA Statement:

Syntax Element	Description
	The Natural reserved word <code>END-DEFINE</code> must be used to end the <code>DEFINE DATA</code> statement.

46

Variable Definition


■ Syntax Description	338



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

The *variable-definition* option is used to define a single field/variable that may be single-valued (*scalar-definition*) or multi-valued (*array-definition*).

scalar-definition



Syntax Element	Description
	For further information, see <i>NaturalX</i> in the <i>Programming Guide</i> .
A, U or B	Data Type: Alphanumeric (A), Unicode (U) or binary (B) for dynamic variables.
<i>array-definition</i>	Array Dimension Definition: With an <i>array-definition</i> you define the lower and upper bounds of dimensions in an array-definition. For further information, see Array Dimension Definition .
DYNAMIC	DYNAMIC Option: A field may be defined as DYNAMIC. For more information on processing dynamic variables, see <i>Introduction to Dynamic Variables and Fields</i> .
CONSTANT	CONSTANT Option: The variable/array is to be treated as a named constant. The constant value(s) assigned will be used each time the variable/array is referenced. The value(s) assigned cannot be modified during program execution. See also <i>Field Definitions, User-Defined Constants, Defining Named Constants</i> in the <i>Programming Guide</i> . Note: - For reasons of internal handling, it is not allowed to mix variable definitions and constant definitions within one group definition; that is, a group may contain either variables only or constants only. - The CONSTANT clause must not be used with DEFINE DATA INDEPENDENT and DEFINE DATA CONTEXT. The CONSTANT option cannot be used with X-arrays. - The CONSTANT option must not be used with DEFINE DATA INDEPENDENT and DEFINE DATA CONTEXT.
INIT	INIT Option: The variable/array is to be assigned an initial value. This value will also be used when this variable/array is referenced in a RESET INITIAL statement. If no INIT specification is supplied, a field will be initialized with a default initial value depending on its format (see table Default Initial Values below). For further information, see <i>Field Definitions, Initial Values</i> in the <i>Programming Guide</i> .

Syntax Element	Description
	With DEFINE DATA INDEPENDENT and DEFINE DATA CONTEXT , the <code>INIT</code> clause is evaluated in each executed Natural object that contains this clause (not only in the Natural object that allocates the variable). This is different to the way the <code>INIT</code> works for global variables. The <code>INIT</code> option cannot be used with X-arrays.
<i>init-definition</i>	Initial-Value Definition: With the <i>init-definition</i> option, you define the initial/constant values for a variable. See Initial-Value Definition .
<i>array-init-definition</i>	Initial/Constant Values for an Array: The array is to be assigned an initial value. This value will also be used when this array is referenced in a RESET INITIAL statement. With an <i>array-init-definition</i> , you define the initial/constant values for an array. For further information, see Initial/Constant Values for an Array .
<i>emhdpm</i>	EM, HD, PM Parameters for Field/Variable: With this option, additional parameters to be in effect for a field/variable may be defined. For further information, see EM, HD, PM Parameters for Field/Variable .

Default Initial Values

The following table shows the default initial values that are provided with the various formats:

Format	Default Initial Value
B, F, I, N, P	0
A, U	(blank)
L	FALSE
D	D' '
T	T'00:00:00'
C	(AD=D)
Object Handle	NULL-HANDLE

Fields declared as `DYNAMIC` do not have any initial value because their field length is zero by default.

47

View Definition

■ Syntax Description	342

$$\left[\begin{array}{l} \text{view-name VIEW [OF] ddm-name} \\ \left\{ \begin{array}{l} \text{ddm-field} \\ \text{redefinition} \end{array} \right. \left[\begin{array}{l} \left(\left[\text{format-length} \right] \left[\text{/array-definition} \right] \right) \\ \left(\left\{ \begin{array}{c} \text{A} \\ \text{U} \\ \text{B} \end{array} \right\} \left[\text{/array-definition} \right] \right) \text{DYNAMIC} \end{array} \right\} \left[\text{emhdpm} \right] \end{array} \right] \left. \right\} \left. \right] \dots$$

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

The *view-definition* option is used to define a data view as derived from a data definition module (DDM).

Note: In a parameter data area, *view-definition* is not permitted.

For further information, see *Accessing Data in an Adabas Database* in the *Programming Guide* and particularly the following topics:

- *Data Definition Modules - DDMs*
- *Database Arrays*
- *Defining a Database View*

Syntax Description

Syntax Element	Description
<i>view-name</i>	View Name: The name to be assigned to the view. Rules for Natural variable names apply; see <i>Naming Conventions for User-Defined Variables</i> in <i>Using Natural</i>.
VIEW [OF] <i>dgm-name</i>	DDM Name: The name of the data definition module (DDM) from which the view is to be taken.
<i>level</i>	Level Number: Level number is a 1- or 2-digit number in the range from 01 to 99 (the leading zero is optional) used in conjunction with field grouping. Fields assigned a level number of 02 or greater are considered to be a part of the immediately preceding group which has been assigned a lower level number. The definition of a group enables reference to a series of fields (may also be only one field) by using the group name. With certain statements (CALL, CALLNAT, RESET,

Syntax Element	Description
	WRITE, etc.), you may specify the group name as a shortcut to reference the fields contained in the group. A group may consist of other groups. When assigning the level numbers for a group, no level numbers may be skipped.
<i>ddm-field</i>	DDM Field Name: The name of a field to be taken from the DDM. When you define a view for a HISTOGRAM statement, the view must contain only the descriptor for which HISTOGRAM is to be executed.
<i>redefinition</i>	Redefinition: A <i>redefinition</i> may be used to redefine a group, a view, a DDM field or a single field/variable (that is a scalar or an array). For further information, see Redefinition.
<i>format-length</i>	Format/Length Definition: Format and length of the field. If omitted, these are taken from the DDM. In structured mode, the definition of format and length (if supplied) must be the same as those in the DDM. In reporting mode, the definition of format and length (if supplied) must be type-compatible with those in the DDM.
A, U or B	Data Type: Alphanumeric (A), Unicode (U) or binary (B) for dynamic variables. Note: 1. For Adabas on mainframe computers, format U is available for LA fields (length <= 16381 bytes), but not for LB fields (length: <= 1 GB). 2. Format B is not available with Adabas.
<i>array-definition</i>	Array Definition: Depending on the programming mode used, arrays (periodic-group fields, multiple-value fields) may have to contain information about their occurrences. For further information, see Array Definition in a View below.
<i>emhdpm</i>	EM, HD, PM Parameters for Field/Variable: With this option, additional parameters to be in effect for a field/variable may be defined. See EM, HD, PM Parameters for Field/Variable.
DYNAMIC	DYNAMIC Option:

Syntax Element	Description
	Defines a view field as DYNAMIC. For further information on processing dynamic variables, see <i>Introduction to Dynamic Variables and Fields</i> in the <i>Programming Guide</i> .

Array Definition in a View

Depending on the programming mode used, arrays (periodic-group fields, multiple-value fields) may have to contain information about their occurrences.

Structured Mode

If a field is used in a view that represents an array, the following applies:

- An index value must be specified for MU/PE fields
- When no format/length specification is supplied, the values are taken from the DDM.
- When a format/length specification is supplied, it must be the same as in the DDM.

Database-Specific Considerations in Structured Mode:

Adabas:	If MU/PE fields (defined in a DDM) are to be used inside a view, these fields must include an array index specification. For an MU field or ordinary PE field, you specify a one-dimensional index range, e.g. (1:10). For an MU field inside a PE group, you specify a two-dimensional index range, e.g. (1:10,1:5).

Examples of Structured Mode:

```

DEFINE DATA LOCAL
1 EMP1 VIEW OF EMPLOYEES
  2 NAME(A20)
  2 ADDRESS-LINE(A20 / 1:2)

1 EMP2 VIEW OF EMPLOYEES
  2 NAME
  2 ADDRESS-LINE(1:2)

1 EMP3 VIEW OF EMPLOYEES
  2 NAME
  2 ADDRESS-LINE(2)

1 #K (I4)
1 EMP4 VIEW OF EMPLOYEES
  2 NAME
  2 ADDRESS-LINE(#K:#K+1)
END-DEFINE
END

```

Reporting Mode

In this mode, the same rules are valid as for structured mode, however, there are two exceptions:

- An index value needs not be supplied. In this case, the index range for the missing dimensions is set to (1:1).
- The format/length specification may differ from the specification in the DDM. Then the definition of format and length must be type-compatible with those in the DDM.

Examples:

```
DEFINE DATA LOCAL
1 EMP1 VIEW OF EMPLOYEES
  2 NAME(A30)
  2 ADDRESS-LINE(A35 / 5:10)

1 EMP2 VIEW OF EMPLOYEES
  2 NAME
  2 ADDRESS-LINE(A40)          /* ADDRESS LINE (1:1) IS ASSUMED

1 EMP3 VIEW OF EMPLOYEES
  2 NAME
  2 ADDRESS-LINE              /* ADDRESS LINE (1:1) IS ASSUMED

1 #K (I4)
1 EMP4 VIEW OF EMPLOYEES
  2 NAME
  2 ADDRESS-LINE(#K:#K+1)
END-DEFINE
END
```


48

Redefinition

■ Restrictions	348
■ Syntax Description	348

REDEFINE *field-name*

{

$\left\{ \begin{array}{l} \text{rgroup } [(array-definition)] \\ \text{rfield } (format-length [/array-definition]) \\ \text{FILLER } nX \end{array} \right\}$

$\left\{ \begin{array}{l} \text{level } \left\{ \begin{array}{l} \text{rgroup } [(array-definition)] \\ \text{rfield } (format-length [/array-definition]) \\ \text{FILLER } nX \end{array} \right\} \end{array} \right\}$

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

The *redefinition* option is used to redefine a group, a view, a DDM field or a single field/variable (that is a scalar or an array).

See also *Redefining Fields* in the *Programming Guide*.

Restrictions

- A *redefinition* of a view or a DDM field is not applicable to a *parameter-data-definition*.
- Handles, X-arrays and dynamic variables cannot be redefined and cannot be contained in a redefinition clause.
- A group that contains a handle, X-array or a dynamic variable can only be redefined up to - but not including or beyond - the element in question.

Syntax Description

Syntax Element	Description
<i>field-name</i>	Name of Field to be Redefined: The name of the group, view, DDM field or single field that is being redefined.
<i>level</i>	Level Number of Field being Redefined: Level number is a 1- or 2-digit number in the range from 01 to 99 (the leading zero is optional) used in conjunction with field grouping. Fields assigned a level number of 02 or greater are considered to be a part of the immediately preceding group, which has been assigned a lower level number.
<i>rgroup</i>	Name of Resulting Group: The name of the group resulting from the redefinition. Note: In a <i>redefinition</i> within a <i>view-definition</i> , the name of <i>rgroup</i> must be different from any field name in the underlying DDM.
<i>rfield</i>	Name of Resulting Field: The name of the field resulting from the redefinition.

Syntax Element	Description
	Note: In a <i>redefinition</i> within a <i>view-definition</i> , the name of <i>rfield</i> must be different from any field name in the underlying DDM.
<i>format-length</i>	Format/Length of Resulting Field: The format and length of the resulting field (<i>rfield</i>).
<i>array-definition</i>	Array Dimension Definition: With an <i>array-definition</i> , you define the lower and upper bounds of dimensions in an array-definition. For further information, see Array Dimension Definition .
FILLER <i>n</i> X	Filler Byte Definition: With this notation, you define <i>n</i> filler bytes - that is, segments which are not to be used - in the field that is being redefined. The definition of trailing filler bytes is optional.

Examples of REDEFINE Usage

Example 1:

```

DEFINE DATA LOCAL
  01 #VAR1 (A15)
  01 #VAR2
    02 #VAR2A (N4.1) INIT <0>
    02 #VAR2B (P6.2) INIT <0>
  01 REDEFINE #VAR2
    02 #VAR2RD (A10)
END-DEFINE
...

```

Example 2:

```

DEFINE DATA LOCAL
  01 MYVIEW VIEW OF STAFF
    02 NAME
    02 BIRTH
    02 REDEFINE BIRTH
      03 BIRTH-YEAR (N4)
      03 BIRTH-MONTH (N2)
      03 BIRTH-DAY (N2)
END-DEFINE
...

```

Example 3:

```
DEFINE DATA LOCAL
1 #FIELD (A12)
1 REDEFINE #FIELD
2 #RFIELD1 (A2)
2 FILLER 2X
2 #RFIELD2 (A2)
2 FILLER 4X
2 #RFIELD3 (A2)
END-DEFINE
...
```

49

Array Dimension Definition

■ Syntax Description	352

{[*bound*:] *bound*},... 3

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

The *array-dimension-definition* option is used to define the lower and upper bound of a dimension in an array definition.

You can define up to 3 dimensions for an array.

Syntax Description

Syntax Element	Description
<i>bound</i>	Lower/Upper Bound: A bound can be one of the following: ■ a numeric integer constant; ■ a previously defined named constant; ■ (for database arrays) a previously defined user-defined variable; or ■ an asterisk (*) defines an extensible bound, otherwise known as an X-array (eXtensible array). If only one bound is specified, the value represents the upper bound and the lower bound is assumed to be 1.

X-Arrays

If at least one bound in at least one dimension of an array is specified as extensible, that array is then called an X-array (eXtensible array). Only one bound (either upper or lower) may be extensible in any one dimension, but not both. Multi-dimensional arrays may have a mixture of constant and extensible bounds, for example: `#a(1:100, 1:*)`.

Example:

```
DEFINE DATA LOCAL
1 #ARRAY1(I4/1:10)
1 #ARRAY2(I4/10)
1 #X-ARRAY3(I4/1:*)
1 #X-ARRAY4(I4/*,1:5)
1 #X-ARRAY5(I4/*:10)
1 #X-ARRAY6(I4/1:10,100:*,*:1000)
END-DEFINE
```

In the following table you can see the bounds of the arrays in the above program more clearly.

	Dimension 1		Dimension 2		Dimension 3	
	Lower bound	Upper bound	Lower bound	Upper bound	Lower bound	Upper bound
#ARRAY1	1	10	-	-	-	-
#ARRAY2	1	10	-	-	-	-
#X-ARRAY3	1	eXtensible	-	-	-	-
#X-ARRAY4	1	eXtensible	1	5	-	-
#X-ARRAY5	eXtensible	10	-	-	-	-
#X-ARRAY6	1	10	100	eXtensible	eXtensible	1000

Examples of array definitions:

```
#ARRAY2(I4/10)           /* a one-dimensional array with 10 occurrences (1:10)
#X-ARRAY4(I4/*,1:5)       /* a two-dimensional array
#X-ARRAY6(I4/1:10,100:*,*:1000) /* a three-dimensional array
```

Variable Arrays in a Parameter Data Area

In a parameter data area, you may specify an array with a variable number of occurrences. This is done with the index notation 1:V.

Example 1: #ARR01 (A5/1:V)

Example 2: #ARR02 (I2/1:V,1:V)

A parameter array which contains a variable index notation 1:V can only be redefined in the length of

- its elementary field length, if the 1:V index is right-most; for example:

```
#ARR(A6/1:V) can be redefined up to a length of 6 bytes
#ARR(A6/1:2,1:V) can be redefined up to a length of 6 bytes
#ARR(A6/1:2,1:3,1:V) can be redefined up to a length of 6 bytes
```

- the product of the right-most fixed occurrences and the elementary field length; for example:

```
#ARR(A6/1:V,1:2) can be redefined up to a length of 2*6 = 12 bytes
#ARR(A6/1:V,1:3,1:2) can be redefined up to a length of 3*2*6 = 36 bytes
#ARR(A6/1:2,1:V,1:3) can be redefined up to a length of 3*6 = 18 bytes
```

A variable index notation 1:V cannot be used within a redefinition.

Example:

```
DEFINE DATA PARAMETER
  1 #ARR(A6/1:V)
  1 REDEFINE #ARR
    2 #R-ARR(A1/1:V) /* (1:V) is not allowed in a REDEFINE block
END-DEFINE
```

As the number of occurrences is not known at compilation time, it must not be referenced with the index notation (*) in the statements [INPUT](#), [WRITE](#), [READ WORK FILE](#), [WRITE WORK FILE](#). Index notation (*) may be applied either to all dimensions or to none.

Valid examples:

```
#ARR01 (*)
#ARR02 (*,*)
#ARR01 (1)
#ARR02 (5,#FIELDX)
#ARR02 (1,1:3)
```

Invalid example:

```
#ARRAYY (1,*) /* not allowed
```

To avoid runtime errors, the maximum number of occurrences of such an array should be passed to the subprogram/subroutine/function via another parameter. Alternatively, you may use the system variable *OCCURRENCE.




Notes:

1. If a parameter data area that contains an index 1:V is used as a local data area (that is, specified in a [DEFINE DATA LOCAL](#) statement), a variable named V must have been defined as [CONSTANT](#).
2. In a dialog, an index 1:V cannot be used in conjunction with [BY VALUE](#).

50

Initial-Value Definition

■ Restriction	356
■ Syntax Description	356



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

The *init-definition* option is used to define the initial/constant values for a variable.

 **Note:** If, in the *variable-definition* option, the keyword **INIT** was used for the initialization, the value may be modified by any statement that affects the content of a variable. If the keyword **CONST** was used for the initialization, any attempt to change the value will be rejected by the compiler.

See also *Field Definitions, Initial Values* in the *Programming Guide*.

Restriction

For a redefined field, an *init-definition* is not permitted.

Syntax Description



Syntax Element	Description
<constant>	Constant Value Option: The constant value with which the variable is to be initialized; or the constant value to be assigned to the field. For further information, see <i>User-Defined Constants</i> in the <i>Programming Guide</i>.
<system-variable>	System Variable Option: The initial value for a variable may also be the value of a Natural system variable, for example: <pre> DEFINE DATA LOCAL 1 #MYDATE (D) INIT <*DATX> END-DEFINE </pre> Note: When the variable is referenced in a RESET INITIAL statement, the system variable is evaluated again; that is, it will be reset not to the value it contained when program execution started but to the value it contains when the RESET INITIAL statement is executed.

Syntax Element	Description
FULL LENGTH <code><character-string></code> LENGTH <i>n</i> <code><character-string></code>	Character String Option for Alphanumeric/Unicode Variables: For a variable of the Natural data format A or U, a <i>character-string</i> (for example, 'ABC ') can be used as an initial value which fills all or part of the variable field. A <i>character-string</i> is a constant of the Natural data format A or U as described in <i>Alphanumeric Constants</i> and <i>Unicode Constants</i> in the <i>Programming Guide</i>. FULL LENGTH Option: With the FULL LENGTH option, a particular <i>character-string</i> is repeatedly moved to the specified field until the field is completely filled. In the following example, the entire field is filled with asterisks: <pre>DEFINE DATA LOCAL 1 #FIELD (A25) INIT FULL LENGTH <'*> END-DEFINE</pre> LENGTH Option: With the LENGTH <i>n</i> option, a particular <i>character-string</i> is repeatedly moved to the specified field until the first <i>n</i> positions of the field are filled. <i>n</i> must be a numeric constant. In the following example, the first four positions of the field are filled with exclamation marks: <pre>DEFINE DATA LOCAL 1 #FIELD (A25) INIT LENGTH 4 <'!> END-DEFINE</pre>

51

Initial/Constant Values for an Array

■ Restriction	360
■ Syntax Description	361

For selected occurrences:**For all occurrences:**

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

The *array-init-definition* option is used to define the initial/constant values for an array.



Note: If, in the *variable-definition* option, the keyword **INIT** was used for the initialization, the value may be modified by any statement that affects the content of a variable. If the keyword **CONST** was used for the initialization, any attempt to change the value will be rejected by the compiler.

See also *Field Definitions* in the *Programming Guide*, particularly the following sections:

- *Initial Values*
- *User-Defined Constants*

Restriction

For a redefined field, an *array-init-definition* is not permitted.

Syntax Description

Syntax Element	Description
ALL	ALL Option: All occurrences of the array are initialized with the same value. The ALL option cannot be combined with any other initialization definitions.
<i>index</i>	Index Option: The array occurrences specified by <i>index</i> are initialized. If a single index or an index range is used, you can only specify a unique value (<i>constant</i> or <i>system-variable</i>) which is assigned to all occurrences. Examples: <pre> DEFINE DATA LOCAL 1 #FLD1 (A4/1:4) INIT (1:3) <'A'> /* A fills occurrences ↵ (1:3) 1 #FLD2 (A4/1:4) INIT (*) <'B'> /* B fills all occurrences 1 #FLD3 (A4/1:2,1:4) INIT (2,3) <'C'> /* C fills occurrence ↵ (2,3) END-DEFINE </pre>
V	Index Notation V: The special index notation V is used to fill a consecutive sequence of array occurrences with individual values (<i>constant</i> or <i>system-variable</i>). You can specify the V notation for one dimension of an array only. The number of values provided must not exceed the number of occurrences of the specified dimension. You can omit the V notation for a one-dimensional array because the V index is then used by default. Example showing which values fill which occurrences when V is used: <pre> DEFINE DATA LOCAL 1 #FLD4 (A4/1:3) INIT (V) <'A','B'> /* A fills (1) B ↵ fills (2) 1 #FLD5 (A4/1:2,1:3) INIT (1,V) <'C','D'> /* C, D fill ↵ (1,1:2) (2,V) <'F','G','H'> /* F, G, H fill ↵ (2,1:3) END-DEFINE </pre>

Syntax Element	Description
<i>constant</i>	Constant Value Option: The constant (value) with which the array is to be initialized. Occurrences for which no values are specified, are initialized with a default value. In a list of consecutive occurrences, you can skip single occurrences by specifying commas (,) only. However, you must end the list with a particular value for the last occurrence. For further information, see <i>User-Defined Constants</i> in the <i>Programming Guide</i>. Note: Multiple constant values/system variables must be separated either by the input delimiter character (as specified with the session parameter ID) or by a comma. If numbers are provided in the value list and a comma is defined as the decimal character (with the session parameter DC), either separate the comma from the value with an extra blank character or use the input delimiter character. Example with ID= ; and DC= , delimiter settings: <pre>DEFINE DATA LOCAL 1 #FLD1 (A4/1:3) INIT <'A', , 'C'> 1 #NUM1 (N4,2/1:3) INIT <1 , 2 , 3> 1 #NUM2 (N4,2/1:3) INIT <1;2;3> END-DEFINE</pre>
<i>system-variable</i>	System Variable Option: The initial value for an array can also be the value of a Natural system variable. See also the Note for <i>constant</i>.
FULL LENGTH <character-string> LENGTH <i>n</i> <character-string>	Character String Option for Alphanumeric/Unicode Variables: For a variable of the Natural data format A or U, a <i>character-string</i> (for example, 'ABC ') can be used as an initial value which fills all or part of the variable field. A <i>character-string</i> is a constant of the Natural data format A or U as described in <i>Alphanumeric Constants</i> and <i>Unicode Constants</i> in the <i>Programming Guide</i>. FULL LENGTH Option: With the FULL LENGTH option, a particular <i>character-string</i> is repeatedly moved to the specified array occurrence until the occurrence is completely filled. LENGTH Option: With the LENGTH <i>n</i> option, a particular <i>character-string</i> is repeatedly moved to the specified array occurrence until the first <i>n</i> positions of the occurrence are filled.

Syntax Element	Description
	Example showing which values fill which occurrences: <pre> DEFINE DATA LOCAL 1 #FLD1 (A6/1:3) INIT ALL FULL LENGTH <'X'> /* XXXXXX in all ← occ. 1 #FLD2 (A6/1:3) INIT ALL LENGTH 5 <'NO'> /* NONON in all ← occ. 1 #FLD3 (A6/1:3) INIT (1:2) LENGTH 4 <'AB'> /* ABAB in occ ← (1:2) 1 #FLD4 (A6/1:3) INIT (V) FULL LENGTH <'X','Y'> /* XXXXXX in occ. ← (1), /* YYYYYY in occ. ← (2) END-DEFINE </pre> Within one <i>array-init-definition</i>, only FULL LENGTH or LENGTH <i>n</i> can be specified; both notations must not be mixed.



Note: For further example definitions of assigning initial values to arrays, see [Example 2 - DEFINE DATA \(Array Definition/Initialization\)](#).

52

EM, HD, PM Parameters for Field/Variable

■ Syntax Description	366

```
( [ EM=value  
  EMU=value ] [HD='text'] [PM=value])
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

The *emhdp*m option is used to define additional parameters to be in effect for a field/variable.



Note: If for a database field you specify neither an edit mask (EM= or EMU=) nor a header (HD=), the default edit mask and default header as defined in the data definition module (**DDM**) will be used. However, if you specify one of the two, the other's default from the DDM will *not* be used.

Syntax Description

Syntax Element	Description
EM=value	Edit Mask: The EM parameter may be used to define an edit mask used when the field is displayed with an I/O statement. For further information, see the session parameter EM in the <i>Parameter Reference</i> .
EMU=value	Unicode Edit Mask: The EMU parameter may be used to define a Unicode edit mask used when the field is displayed with an I/O statement. For further information, see the session parameter EMU in the <i>Parameter Reference</i> .
HD='text'	Header Definition: The HD parameter may be used to define the header to be used as the default header for the field. For further information, see the session parameter HD in the <i>Parameter Reference</i> .
PM=value	Print Mode: The PM parameter may be used to set the print mode, which indicates how fields are to be output. For further information, see the session parameter PM in the <i>Parameter Reference</i> .

53

Examples of DEFINE DATA Statement Usage

■ Example 1 - DEFINE DATA LOCAL (Local Data Definition)	368
■ Example 2 - DEFINE DATA LOCAL (Array Definition/Initialization)	368
■ Example 3 - DEFINE DATA (View Definition, Array Redefinition)	372
■ Example 4 - DEFINE DATA (Global, Parameter and Local Data Areas)	373
■ Example 5 - DEFINE DATA (Initialization)	374
■ Example 6 - DEFINE DATA (Variable Array)	374

The following topics are covered:

Example 1 - DEFINE DATA LOCAL (Local Data Definition)

```
** Example 'DDAEX1': DEFINE DATA
*****
DEFINE DATA LOCAL
1 #VAR1      (A15)
1 #VAR2
  2 #VAR2A   (N4.1) INIT <1111>
  2 #VAR2B   (N6.2) INIT <222222>
1 REDEFINE #VAR2
  2 #VAR2C   (A2)
  2 #VAR2D   (A2)
  2 #VAR2E   (A6)
END-DEFINE
*
WRITE NOTITLE '=' #VAR2A / '=' #VAR2B /
              '=' #VAR2C / '=' #VAR2D / '=' #VAR2E
*
END
```

Output of Program DDAEX1:

```
#VAR2A:  1111.0
#VAR2B:  222222.00
#VAR2C:  11
#VAR2D:  11
#VAR2E:  022222
```

Example 2 - DEFINE DATA LOCAL (Array Definition/Initialization)

```
** EXAMPLE 'DDAEX2': DEFINE DATA (array definition/initialization)
*****
DEFINE DATA LOCAL
**=====
1 #A01 (A5/1:4) INIT      <'A','B',,'D'>
1 #A02 (A5/1:4) INIT   (V)  <'A','B'>
                        (4)  <'D'>
1 #A03 (A5/1:4) INIT   (*)  <'A'>
1 #A04 (A5/1:4) INIT   (2)  <'B'>
                        (3)  <'C'>
1 #A05 (A5/1:4) INIT   (2:3) <'X'>
                        (4)  <'D'>
1 #A06 (A5/1:4) INIT   (*)  <'X'>
```

```

                (3)    <'C'>
**-----
1 #A10 (A5/1:4) INIT          FULL LENGTH <'X'>
1 #A11 (A5/1:4) INIT          FULL LENGTH <,'B',,'D'>
1 #A12 (A5/1:4) INIT (V)      FULL LENGTH <'A','B'>
1 #A13 (A5/1:4) INIT (2)      FULL LENGTH <'B'>
1 #A14 (A5/1:4) INIT (*)      FULL LENGTH <'X'>
**-----
1 #A20 (A5/1:4) INIT          LENGTH 2    <'A'>
1 #A21 (A5/1:4) INIT (2)      LENGTH 2    <'B'>
                                (3)      LENGTH 3    <'C'>
1 #A22 (A5/1:4) INIT (3:4)    LENGTH 2    <'X'>
1 #A23 (A5/1:4) INIT (V)      LENGTH 2    <,'B',,'D'>
**-----
1 #A30 (A5/1:4) INIT ALL          <'Z'>
1 #A31 (A5/1:4) INIT ALL FULL LENGTH <'Z'>
1 #A32 (A5/1:4) INIT ALL LENGTH 2  <'Z'>
**=====
1 #B01 (A5/1:2,1:4) INIT (2,V)  <'A','B',,'D'>
1 #B02 (A5/1:2,1:4) INIT (1,*)  <'X'>
                                (1,2)  <'B'>
                                (2,3)  <'F'>
1 #B03 (A5/1:2,1:4) INIT (1,1:2) <'X'>
                                (1,4)  <'Y'>
1 #B04 (A5/1:2,1:4) INIT (V,1)  <'A1','A2'>
1 #B05 (A5/1:2,1:4) INIT (V,*)  <'X','Y'>
**-----
1 #B10 (A5/1:2,1:4) INIT ALL    <'Z'>
1 #B11 (A5/1:2,1:4) INIT (1,*)  FULL LENGTH <'Z'>
1 #B12 (A5/1:2,1:4) INIT (*,*)  FULL LENGTH <'Z'>
1 #B13 (A5/1:2,1:4) INIT (1,*)  LENGTH 2    <'Z'>
1 #B14 (A5/1:2,1:4) INIT (1,V)  FULL LENGTH <'A',,'C'>
                                (2,V)  FULL LENGTH <'E','F'>
1 #B15 (A5/1:2,1:4) INIT (1,*)  FULL LENGTH <'X'>
                                (2,*)  FULL LENGTH <'Y'>
                                (2,4)  FULL LENGTH <'Z'>
*
END-DEFINE
**=====
WRITE 7X '(1) (2) (3) (4)'
WRITE (AD=V) '=' #A01(*)
WRITE (AD=V) '=' #A02(*)
WRITE (AD=V) '=' #A03(*)
WRITE (AD=V) '=' #A04(*)
WRITE (AD=V) '=' #A05(*)
WRITE (AD=V) '=' #A06(*)
SKIP 1
WRITE (AD=V) '=' #A10(*)
WRITE (AD=V) '=' #A11(*)
WRITE (AD=V) '=' #A12(*)
WRITE (AD=V) '=' #A13(*)
WRITE (AD=V) '=' #A14(*)

```

```
SKIP 1
WRITE (AD=V) '=' #A20(*)
WRITE (AD=V) '=' #A21(*)
WRITE (AD=V) '=' #A22(*)
WRITE (AD=V) '=' #A23(*)
SKIP 1
WRITE (AD=V) '=' #A30(*)
WRITE (AD=V) '=' #A31(*)
WRITE (AD=V) '=' #A32(*)
SKIP 1
**=====
WRITE 6X '(1,1) (1,2) (1,3) (1,4) (2,1) (2,2) (2,3) (2,4)'
WRITE (AD=V) '=' #B01(1,*) 2X #B01(2,*)
WRITE (AD=V) '=' #B02(1,*) 2X #B02(2,*)
WRITE (AD=V) '=' #B03(1,*) 2X #B03(2,*)
WRITE (AD=V) '=' #B04(1,*) 2X #B04(2,*)
WRITE (AD=V) '=' #B05(1,*) 2X #B05(2,*)
SKIP 1
WRITE (AD=V) '=' #B10(1,*) 2X #B10(2,*)
WRITE (AD=V) '=' #B11(1,*) 2X #B11(2,*)
WRITE (AD=V) '=' #B12(1,*) 2X #B12(2,*)
WRITE (AD=V) '=' #B13(1,*) 2X #B13(2,*)
WRITE (AD=V) '=' #B14(1,*) 2X #B14(2,*)
WRITE (AD=V) '=' #B15(1,*) 2X #B15(2,*)
**=====
END
```


Output of Program DDAEX2:

Page 1

	(1)	(2)	(3)	(4)				
#A01:	A	B		D				
#A02:	A	B		D				
#A03:	A	A	A	A				
#A04:		B	C					
#A05:		X	X	D				
#A06:	X	X	C	X				
#A10:	XXXXX							
#A11:		BBBBB		DDDDD				
#A12:	AAAAA	BBBBB						
#A13:		BBBBB						
#A14:	XXXXX	XXXXX	XXXXX	XXXXX				
#A20:	AA							
#A21:		BB	CCC					
#A22:			XX	XX				
#A23:		BB		DD				
#A30:	Z	Z	Z	Z				
#A31:	ZZZZZ	ZZZZZ	ZZZZZ	ZZZZZ				
#A32:	ZZ	ZZ	ZZ	ZZ				
	(1,1)	(1,2)	(1,3)	(1,4)	(2,1)	(2,2)	(2,3)	(2,4)
#B01:					A	B		D
#B02:	X	B	X	X			F	
#B03:	X	X		Y				
#B04:	A1				A2			
#B05:	X	X	X	X	Y	Y	Y	Y
#B10:	Z	Z	Z	Z	Z	Z	Z	Z
#B11:	ZZZZZ	ZZZZZ	ZZZZZ	ZZZZZ				
#B12:	ZZZZZ	ZZZZZ	ZZZZZ	ZZZZZ	ZZZZZ	ZZZZZ	ZZZZZ	ZZZZZ
#B13:	ZZ	ZZ	ZZ	ZZ				
#B14:	AAAAA		CCCCC		EEEEE	FFFFFF		
#B15:	XXXXX	XXXXX	XXXXX	XXXXX	VVVVV	VVVVV	VVVVV	ZZZZZ

Example 3 - DEFINE DATA (View Definition, Array Redefinition)

```

** Example 'DDAEX3': DEFINE DATA (view definition, array redefinition)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 ADDRESS-LINE (A20/2)
  2 PHONE
*
1 #ARRAY      (A75/1:4)
1 REDEFINE #ARRAY
  2 #ALINE    (A25/1:4,1:3)
1 #X          (N2) INIT <1>
1 #Y          (N2) INIT <1>
END-DEFINE
*
FORMAT PS=20
LIMIT 5
FIND EMPLOY-VIEW WITH NAME = 'SMITH'
  MOVE NAME              TO #ALINE (#X,#Y)
  MOVE ADDRESS-LINE(1) TO #ALINE (#X+1,#Y)
  MOVE ADDRESS-LINE(2) TO #ALINE (#X+2,#Y)
  MOVE PHONE             TO #ALINE (#X+3,#Y)
  IF #Y = 3
    RESET INITIAL #Y
    PERFORM PRINT
  ELSE
    ADD 1 TO #Y
  END-IF
  AT END OF DATA
    PERFORM PRINT
  END-ENDDATA
END-FIND
*
DEFINE SUBROUTINE PRINT
  WRITE NOTITLE (AD=OI) #ARRAY(*)
  RESET #ARRAY(*)
  SKIP 1
END-SUBROUTINE
*
END

```

Output of Program DDAEX3:

SMITH ENGLANDSVEJ 222 554349	SMITH 3152 SHETLAND ROAD MILWAUKEE 877-4563	SMITH 14100 ESWORTHY RD. MONTERREY 994-2260
SMITH 5 HAWTHORN OAK BROOK 150-9351	SMITH 13002 NEW ARDEN COUR SILVER SPRING 639-8963	

Example 4 - DEFINE DATA (Global, Parameter and Local Data Areas)

```

** Example 'DDAEX4': DEFINE DATA (global and local data area definition)
*****
DEFINE DATA
GLOBAL
  USING DDAEX4G
LOCAL
  1 #FIELD1 (A10)
  1 #FIELD2 (N5)
END-DEFINE
*
MOVE 'HELLO' TO #FIELD1
MOVE 123     TO #FIELD2
*
CALLNAT 'DDAEX4N' #FIELD1 #FIELD2
*
END

```

Global Data Area DDAEX4G Used by Program DDAEX4:

1 GLOBAL-FIELD	A	10

Subprogram DDAEX4N Called by Program DDAEX4:

```

** Example 'DDAEX4N': DEFINE DATA PARAMETER (called by DDAEX4)
*****
DEFINE DATA
PARAMETER
  1 #FIELD A (A10)
  1 #FIELD B (N5)
END-DEFINE
*
WRITE '=' #FIELD A '=' #FIELD B
END

```

Output of Program DDAEX4:

```
Page          1                                05-01-12   08:55:53
#FIELD A: HELLO          #FIELD B:      123
```

Example 5 - DEFINE DATA (Initialization)

```
** Example 'DDAEX5': DEFINE DATA (initialization)
*****
DEFINE DATA LOCAL
1 #START-DATE (D)   INIT <*DATX>
1 #UNDERLINE   (A50) INIT FULL LENGTH <'_'>
1 #SCALE       (A65) INIT LENGTH 65 <'....+..../'>
END-DEFINE
*
WRITE NOTITLE #START-DATE (DF=L)
              / #UNDERLINE
              / #SCALE
END
```

Output of Program DDAEX5:

```
2005-01-12
.....+...../.....+...../.....+...../.....+...../.....+...../.....+
```

Example 6 - DEFINE DATA (Variable Array)

```
** Example 'DDAEX6': DEFINE DATA (variable array with (1:V))
*****
DEFINE DATA LOCAL
1 #ARRAY   (A1/1:10)
1 #MAX-ARR (P3)
END-DEFINE
*
#ARRAY (1) := 'R'
#ARRAY (2) := 'E'
#ARRAY (3) := 'D'
#MAX-ARR   := 4
*
WRITE #ARRAY(*)
*
CALLNAT 'DDAEX6N' #ARRAY(1:4) #MAX-ARR
*
```

```

WRITE #ARRAY(*)
*
*
#MAX-ARR      := 5
*
CALLNAT 'DDAEX6N' #ARRAY(1:5) #MAX-ARR
*
WRITE #ARRAY(*)
*
END

```

Subprogram DDAEX6N Called by Program DDAEX6:

```

** Example 'DDAEX6N': DEFINE DATA (variable array with (1:V))
*****
DEFINE DATA
PARAMETER
1 #STRING (A1/1:V)
1 #MAX      (P3)
END-DEFINE
*
IF #MAX = 4
    MOVE 'B' TO #STRING (1)
    MOVE 'L' TO #STRING (2)
    MOVE 'U' TO #STRING (3)
    MOVE 'E' TO #STRING (4)
END-IF
*
IF #MAX = 5
    MOVE 'W' TO #STRING (1)
    MOVE 'H' TO #STRING (2)
    MOVE 'I' TO #STRING (3)
    MOVE 'T' TO #STRING (4)
    MOVE 'E' TO #STRING (5)
END-IF
END

```

Output of Program DDAEX4:

```

Page          1                                05-01-12  09:06:43

R E D
B L U E
W H I T E

```


VII

■ 54 DEFINE FUNCTION	379
■ 55 DEFINE PRINTER	385
■ 56 DEFINE PROTOTYPE	405
■ 57 DEFINE SUBROUTINE	413
■ 58 DEFINE WINDOW	421
■ 59 DEFINE WORK FILE	429

54

DEFINE FUNCTION

■ Function	380
■ Syntax Description	380
■ Examples	384

```

DEFINE FUNCTION function-name
  [return-data-definition]
  [function-data-definition]
  statement...
END-FUNCTION
  
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statement: `DEFINE PROTOTYPE`

Function

The `DEFINE FUNCTION` statement is used to define a function which is stored as a Natural object of the type function. A function object may contain only one `DEFINE FUNCTION` statement.

The `DEFINE FUNCTION` statement defines the function name, the parameters, the local and application-independent variables, the function result and the statements forming the operation logic. These statements are executed when the function is called.

For further information, see the following sections in the *Programming Guide*:

- Natural object type Function
- *Function Call*

Syntax Description

Syntax Element	Description
<i>function-name</i>	Function Name: <i>function-name</i> is the name of the function to be called. It must comply with the naming conventions for user-defined variables described in the <i>Using Natural</i> documentation. <i>function-name</i> is not necessarily the same as the name of the stored object that contains the function definition. You may not use the same function name twice in one library.
<i>return-data-definition</i>	Return Data Definition Clause: For details on this clause, see Return Data Definition .
<i>function-data-definition</i>	Function Data Definition Clause:

Syntax Element	Description
	For details on this clause, see Function Data Definition .
<i>statement...</i>	Statement(s) to be Executed: Defines the operation section which is executed when the function is called. It forms the function logic.
END - FUNCTION	End of DEFINE FUNCTION Statement: The Natural reserved word END - FUNCTION must be used to terminate the DEFINE FUNCTION statement.

Return Data Definition

RETURNS [<i>variable-name</i>]	$\left\{ \begin{array}{l} (\textit{format-length}[\textit{array-definition}]) \\ [(\textit{array-definition})] \text{ HANDLE OF OBJECT} \\ \left(\left\{ \begin{array}{c} \textit{A} \\ \textit{U} \\ \textit{B} \end{array} \right\} [(\textit{array-definition})] \text{ DYNAMIC} \right) \end{array} \right\}$	[BY VALUE]

The *return-data-definition* clause defines the format/length and, if applicable, the array structure of the result value returned by the function.

Syntax Element Description:

Syntax Element	Description
<i>variable-name</i>	Return Value Name: Optionally, you may specify a name which is used to access the return field within the function coding. If no such name is specified, the function name is used instead.
<i>format-length</i>	Format/Length Definition: The format and length of the result field. For information on format/length definition of user-defined variables, see <i>Format and Length of User-Defined Variables</i> in the <i>Programming Guide</i> .
<i>array-definition</i>	Array Dimension Definition: With <i>array-definition</i> , you define the lower and upper bounds of a dimension in an array-definition, if the function result is an array field. For further information, see DEFINE DATA statement, Array Dimension Definition .
HANDLE OF OBJECT	Handle of Object: Used in conjunction with NaturalX.

Syntax Element	Description
	For further information, see <i>NaturalX</i> in the <i>Programming Guide</i> .
A, U or B	Data Type: Alphanumeric (A), Unicode (U) or binary (B) for a dynamic result.
DYNAMIC	Dynamic Variable: The function result may be defined as DYNAMIC. For information on processing dynamic variables, see <i>Introduction to Dynamic Variables and Fields</i> in the <i>Programming Guide</i> .
BY VALUE	BY VALUE Option: If BY VALUE is specified, the format/length of the “sending” field (defined inside the <i>return-data-definition</i> clause) and the “receiving” field (which receives the result at the place where the function is called) must only be transfer compatible. The format/length of the “receiving” field is either ■ defined via an explicit (IR=) clause in the function call; or ■ defined with a DEFINE PROTOTYPE statement; or ■ taken over from the RETURNS field of the function object, which must already exist. For data transfer compatibility the rules outlined in <i>Rules for Arithmetic Assignment and Data Transfer</i> in the <i>Programming Guide</i> apply. If BY VALUE is not specified, the format and length of the “receiving” field must exactly match the characteristics of the “sending” field.

Function Data Definition

```

DEFINE DATA
[
    PARAMETER { USING parameter-data-area
                parameter-data-definition ... } ] ...
[
    LOCAL { USING { local-data-area
                  parameter-data-area }
            local-data-definition ... } ] ...
[INDEPENDENT aiv-data-definition ...]
END-DEFINE
    
```

The *function-data-definition* clause defines the parameters which are to be provided when the function is called, and the data fields used by the function, such as local and application-independent variables. A global data area (GDA) cannot be referenced inside the function definition.

Syntax Element Description:

Syntax Element	Description
PARAMETER USING <i>parameter-data-area</i>	PDA Name: Specify the name of the parameter data area (PDA) that contains data elements which are used as parameters in a function call. See also Defining Parameter Data in the DEFINE DATA statement description.
PARAMETER <i>parameter-data-definition</i>	Parameter Data Definition: Instead of defining a parameter data area, parameter data can also be defined directly within a function call. See also Parameter Data Definition in the DEFINE DATA statement description.
LOCAL USING <i>local-data-area</i>	LDA Name: Specify the name of the local data area (LDA) to be referenced. See also Defining Local Data in the DEFINE DATA statement description.
LOCAL USING <i>parameter-data-area</i>	PDA Name: Specify the name of a parameter data area (PDA). Note: A data area referenced with DEFINE DATA LOCAL may also be a parameter data area (PDA). By using a PDA as an LDA you can avoid the extra effort of creating an LDA that has the same structure as the PDA. See also Defining Local Data in the DEFINE DATA statement description.
LOCAL <i>local-data-definition</i>	Local Data Definition: For information on how to define elements or fields within the statement itself, that is, without using an LDA or PDA, see the section Local Data Definition in the DEFINE DATA statement description.
INDEPENDENT <i>aiv-data-definition</i>	AIV Data Definition: Can be used to define a single or multiple application-independent variables (AIVs). See Defining Application-Independent Variables in the DEFINE DATA statement description.
END-DEFINE	End of Clause: The Natural reserved word END-DEFINE must be used to end the <i>function-data-definition</i> clause.

Examples

- [Example 1 - DEFINE FUNCTION](#)
- [Example 2 - DEFINE FUNCTION with Result Value Array](#)

Example 1 - DEFINE FUNCTION

```

** Example 'DFUEX1': DEFINE FUNCTION
*****
DEFINE FUNCTION F#FIRST-CHAR
  RETURNS #RESULT (A1)
  DEFINE DATA PARAMETER
    1 #PARM (A10)
  END-DEFINE
  /*
  #RESULT := #PARM          /* First character as return value.
END-FUNCTION
*
END

```

The function F#FIRST-CHAR is used in the example program DPTX2 in library SYSEXSYN. See [Examples](#) in the DEFINE PROTOTYPE statement description.

Example 2 - DEFINE FUNCTION with Result Value Array

```

** Example 'DFUEX2': DEFINE FUNCTION
*****
DEFINE FUNCTION F#FACTOR
  RETURNS (I2/1:3)
  DEFINE DATA PARAMETER
    1 #VALUE (I2)
  END-DEFINE
  /*
  F#FACTOR(1) := #VALUE * 1
  F#FACTOR(2) := #VALUE * 2
  F#FACTOR(3) := #VALUE * 3
  /*
END-FUNCTION
*
END

```

The function F#FACTOR is used in the example program DPTX1 in library SYSEXSYN. See [Examples](#) in the DEFINE PROTOTYPE statement description.

55

DEFINE PRINTER

■ Function	386
■ Syntax Description	386
■ Printer Name under z/OS Batch, TSO and Server	390
■ Printer Name under z/VSE Batch	393
■ Printer Name under BS2000 Batch and TIAM	394
■ Printer Name under CICS	399
■ Printer Name under Com-plete	400
■ Printer Name under Com-plete/SMARTS	400
■ Printer Names under Natural Advanced Facilities	400
■ Printer Name for Additional Reports and Remote Destinations	401
■ Examples	401

```
DEFINE PRINTER ([logical-printer-name]=]n)

[OUTPUT operand1]
[
    PROFILE operand2
    CODEPAGE operand2
    FORMS operand2
    NAME operand2
    DISP operand2
    CLASS operand2
    COPIES operand3
    PRTY operand4
] ...
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [AT END OF PAGE](#) | [AT TOP OF PAGE](#) | [CLOSE PRINTER](#) | [DISPLAY](#) | [EJECT](#) | [FORMAT](#) | [NEWPAGE](#) | [PRINT](#) | [SKIP](#) | [SUSPEND IDENTICAL SUPPRESS](#) | [WRITE](#) | [WRITE TITLE](#) | [WRITE TRAILER](#)

Belongs to Function Group: [Creation of Output Reports](#)

Function

The `DEFINE PRINTER` statement is used to assign a symbolic name to a report number and to control the allocation of a report to a logical destination. This provides you with additional flexibility when creating output for various logical print queues.

When this statement is executed and the specified printer is already open, the statement will implicitly cause that printer to be closed. To explicitly close a printer, however, you should use the [CLOSE PRINTER](#) statement.

For further information on the `DEFINE PRINTER` statement, see *Unicode and Code Page Support in the Natural Programming Language*, section *Statements*.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S				A	U									yes	no
<i>operand2</i>	C	S				A	U									yes	no
<i>operand3</i>	C	S					N									yes	no
<i>operand4</i>	C	S					N	P	I							yes	no

Syntax Element Description:

Syntax Element	Description
<i>(n)</i>	Printer Number: All print files to be used during a session must be preassigned to an access method by means of subparameter AM (Type of Access Method) of profile parameter PRINT or automatically by definition in the JCL (with AM=STD only). The printer number <i>n</i> may be a value in the range of 0 - 31. This is the number also to be used in a DISPLAY / WRITE or CLOSE PRINTER statement. Printer number 0 indicates the hardcopy printer. Some access methods do not support the hardcopy printer, for example, AM=PC.
<i>logical-printer-name</i>	Logical Printer Name: Optionally you can assign a logical name <i>logical-printer-name</i> to printer <i>n</i>. This name can be used for the <i>rep</i> notation in a DISPLAY / WRITE statement. Naming conventions for <i>logical-printer-name</i> are the same as for user-defined variables. Multiple logical names may be assigned to the same printer number. Unlike the value of the OUTPUT operand (see below), <i>logical-printer-name</i> is evaluated at compile time and therefore independent of the program control flow.
OUTPUT <i>operand1</i>	Printer Name: As <i>operand1</i> you can specify one of the following: ■ the printer name within the online spooling system, ■ the print file name to be assigned to the printer number, ■ the name of an additional printer, or ■ a remote JES printer. See also Printer Name for Additional Reports and Remote Destinations The 8-byte logical printer name can be defined initially by keyword subparameter DEST of profile parameter PRINT. Its default value depends on the access method type and may be overwritten by <i>operand1</i>.

Syntax Element	Description
	<i>operand1</i> can be 1 to 253 characters long. If <i>operand1</i> is a variable, its length must be at least 8 bytes. You can specify either a printer or a logical or physical data set name. The possible format depends on the operating system environment and the access method defined by keyword subparameter AM of profile parameter PRINT for this printer number. If the specified name is already defined for a different printer number and this printer is unused; that is, in closed state, the print output will be routed to this printer if keyword subparameter ROUTE=ON of profile parameter PRINT was specified for the specified printer number. If no printer name matches with <i>operand1</i>, the unused printer with the highest number is used and its name will be overwritten by <i>operand1</i>. Print routing is not visible to the user by means of the SYSFILE command. Information on operating-system- or TP-monitor-dependent printer naming conventions is included in the following sections: ■ Printer Name under z/OS Batch, TSO and Server ■ Printer Name under z/VSE Batch ■ Printer Name under BS2000 Batch and TIAM ■ Printer Name under CICS ■ Printer Name under Com-plete ■ Printer Name under Com-plete/SMARTS ■ Printer Name under Natural Advanced Facilities ■ Printer Name for Additional Reports and Remote Destinations
	With the following clauses, you can provide printing control information to be interpreted by the spooling system of the TP monitor or operating system respectively. You can specify one or more of these clauses, but each of them only once.
PROFILE <i>operand2</i>	Name of Printer Control Characters Table: With the PROFILE clause, you specify the name of a printer control characters table as <i>operand2</i>. The maximum length is 8 bytes. You define the printer control characters table by the profile parameter CCTAB (Printer Escape Sequence Definition). Note: With Natural Advanced Facilities, the printer control characters table can be maintained online as described in the <i>Natural Advanced Facilities</i> documentation.
CODEPAGE <i>operand2</i>	Name of Code Page: CODEPAGE denotes the name (format/length: A64) of a code page as specified in the NATCONFIG module.

Syntax Element	Description
	CODEPAGE is ignored if it does not apply to the respective OUTPUT destination.

Spooling System Parameters

With the following clauses, you can provide values for parameters of the TP monitor's spooling system. The default value of these clauses can be set with the corresponding keyword subparameters of profile parameter PRINT. See *PRINT Keyword Subparameters for DEFINE PRINTER Statement* in the *Parameter Reference*.

When a printer is closed, all options are reset to their default values. If the definitions are not clear in a Natural environment, Software AG recommends to set them in each module using `DEFINE PRINTER` statement.

Syntax Element Description:

Syntax Element	Description
FORMS <i>operand2</i>	Form: Maximum length of operand: 8 bytes. The default value of this clause can be set with subparameter FORMS of profile parameter PRINT.
NAME <i>operand2</i>	List Name: Maximum length of operand: 8 bytes. The default value of this clause can be set with subparameter NAME of profile parameter PRINT.
DISP <i>operand2</i>	Disposition: Maximum length of operand: 4 bytes. For the DISP clause, the possible values for <i>operand2</i> are DEL, HOLD, KEEP and LEAV. The default value of this clause can be set with keyword subparameter DISP of profile parameter PRINT. If the DISP clause is omitted (or incorrectly specified), DEL applies by default.
CLASS <i>operand2</i>	Spool Class: Maximum length of operand: 1 byte. The default value of this clause can be set with keyword subparameter CLASS of profile parameter PRINT.
COPIES <i>operand3</i>	Number of Copies: <i>operand3</i> must be an integer value.

Syntax Element	Description
	The default value of this clause can be set with keyword subparameter <code>COPIES</code> of profile parameter <code>PRINT</code> .
<code>PRTY operand4</code>	Listing Priority: Possible values: 1 - 255. <i>operand4</i> must be an integer value. The default value of this clause can be set with keyword subparameter <code>PRTY</code> of profile parameter <code>PRINT</code>.

Printer Name under z/OS Batch, TSO and Server

This section covers the following topics:

- [Logical Data Set Names](#)
- [Physical Data Set Names](#)
- [HFS File](#)
- [JES Spool File Class](#)
- [NULLFILE](#)
- [Allocation and De-Allocation of Data Sets](#)
- [Print Files in Server Environments](#)

For a printer number that is defined with access method `AM=STD`, you can use *operand1* to specify a logical or a physical data set name to be assigned to that printer number.

operand1 can be 1 to 253 characters long and can be one of the following:

- a logical data set name (DD name, 1 to 8 characters);
- a physical data set name of a cataloged data set (1 to 44 characters), or a physical data set member name (1 to 44 characters for the data set name, plus 1 to 8 characters in parentheses for the member name);
- a path name and member name of an HFS file (1 to 253 characters) in an MVS UNIX Services environment;
- a JES spool file class;
- `NULLFILE` (to indicate a dummy data set).

Logical Data Set Names

For example:

```
DEFINE PRINTER (21) OUTPUT 'SYSPRINT'
```

The specified data set with DD-name `SYSPRINT` must have been allocated before the `DEFINE PRINTER` statement is executed. For further information, see [Allocation and De-Allocation of Data Sets](#).

The allocation can be done via JCL, CLIST (TSO) or dynamic allocation (SVC 99). For dynamic allocation you can use the application programming interface `USR2021N` in library `SYSEXT`.

The data set name specified in the `DEFINE PRINTER` statement overrides the name specified with the keyword subparameter `DEST` of profile parameter `PRINT`.

Optionally, the data set name may be prefixed by `DDN=` to indicate that it is a DD-name and to avoid name conflicts with additional reports. For example:

```
DEFINE PRINTER (22) OUTPUT 'DDN=SOURCE'
```

Physical Data Set Names

For example:

```
DEFINE PRINTER (23) OUTPUT 'TEST.PRINT.FILE'
```

The specified data set must exist in cataloged form. When the `DEFINE PRINTER` statement is executed, the data set is allocated dynamically by SVC 99 with the current DD-name and JCL option `DISP=SHR`. For further information, see [Allocation and De-Allocation of Data Sets](#).

If the data set name is 8 characters or shorter and does not contain a period (`.`), it might be misinterpreted as a DD-name. To avoid this, prefix the name with `DSN=`. For example:

```
DEFINE PRINTER (22) OUTPUT 'DSN=PRINTXYZ'
```

If the data set is a PDS member, you specify the PDS member name (1 to 8 characters) in parentheses after the data set name (1 to 44 characters). For example:

```
DEFINE PRINTER (4) OUTPUT 'TEST.PRINT.PDS(TEST1)'
```

If the specified member does not exist, a new member of that name will be created.

HFS File

For example:

```
DEFINE PRINTER (14) OUTPUT '/u/nat/rec/test.txt'
```

The specified path name must exist. When the `DEFINE PRINTER` statement is executed, the HFS file is allocated dynamically. If the specified member does not exist, a new member of that name will be created.

For the dynamic allocation of the data set, the following z/OS path options are used:

```
PATHOPTS=(OCREAT,OTRUNC,ORDWR)
PATHMODE=(SIRUSR,SIWUSR,SIRGRP,SIWGRP)
FILEDATA=TEXT
```

When an HFS file is closed, it is automatically de-allocated by z/OS (regardless of the setting of keyword subparameter `FREE` of profile parameter `PRINT`).

JES Spool File Class

To create a JES spool data set, you specify `SYSOUT=x` (where *x* is the desired spool file class). For the default spool file class, you specify `SYSOUT=*`.

Examples:

```
DEFINE PRINTER (10) OUTPUT 'SYSOUT=A'
DEFINE PRINTER (12) OUTPUT 'SYSOUT=*
```

To specify additional parameters for the dynamic allocation, use application programming interface `USR2021N` in library `SYSEXT` instead of the `DEFINE PRINTER` statement.

NULLFILE

To allocate a dummy data set, you specify `NULLFILE` as *operand1*:

```
DEFINE PRINTER (n) OUTPUT 'NULLFILE
```

This corresponds to the JCL definition:

```
// DD-name DD DUMMY
```

Allocation and De-Allocation of Data Sets

When the `DEFINE PRINTER` statement is executed and a physical data set name, HFS file, spool file class or dummy data set has been specified, the corresponding data set is allocated dynamically. If the logical print file is already open, it will be closed automatically, except when the keyword subparameter `CLOSE=FIN` (Time of Closure) of profile parameter `PRINT` has been specified, in which case an error will be issued. Moreover, an existing data set allocated with the same current DD-name is automatically de-allocated before the new data set is allocated.

To avoid unnecessary overhead by unsuccessful premature opening of print files not yet allocated at the start of the program, print files should be defined with keyword subparameter `OPEN=ACC` (open at first access) of profile parameter `PRINT`.

In the case of an HFS file, or a print file defined with the keyword subparameter `FREE=ON` of profile parameter `PRINT`, the print file is automatically de-allocated as soon as it has been closed.

As an alternative for the dynamic allocation and de-allocation of data sets, the application programming interface `USR2021N` in library `SYSEXT` is provided. This API also allows you to specify additional parameters for dynamic allocation.

Print Files in Server Environments

In server environments, errors may occur if multiple Natural sessions attempt to allocate or open a data set with the same DD-name. To avoid this, you either specify the print file with keyword subparameter `DEST=*` of profile parameter `PRINT`, or you specify `OUTPUT '*'` in the `DEFINE PRINTER` statement; Natural then generates a unique DD-name at the physical data set allocation when the first `DEFINE PRINTER` statement for that print file is executed.

All print files whose DD-names begin with `CM` are shared by all sessions in a server environment. A shared print file is opened by the first session, and is physically closed when the server is terminated. For further information, see the section *Natural as a Server* in the *Operations* documentation.

Printer Name under z/VSE Batch

For a printer number that is defined with the access method `AM=STD`, *operand1* can be:

- a logical data set name (DD-name, 1 to 7 characters);
- `NULLFILE` (to indicate a dummy data set).

Logical Data Set Names

Example:

```
DEFINE PRINTER (2) OUTPUT 'SYSOUT1'
```

The specified data set `SYSOUT1` must have been defined in the JCL or in the z/VSE standard or partition labels.

The data set name specified in the `DEFINE PRINTER` statement overrides the name specified with keyword subparameter `DEST` of the `PRINT` profile parameter.

Optionally, the data set name may be prefixed by `DDN=` to indicate that it is a DD-name. For example:

```
DEFINE PRINTER (5) OUTPUT 'DDN=MYPRINT'
```

NULLFILE

To allocate a dummy data set, you specify `NULLFILE` as *operand1*:

```
DEFINE PRINTER (n) OUTPUT 'NULLFILE'
```

Printer Name under BS2000 Batch and TIAM

For a printer number that is defined with the access method `AM=STD`, you can use *operand1* to specify a file name, link name or system file that is allocated to this printer number.

In this case, *operand1* can have a length of from 1 to 253 characters and one of the following meanings:

- Link Name
- File Name
- Generic File Name
- File Name and Link Name
- Generic File Name and Link Name
- System File `SYSOUT`
- System File `SYSLST`
- System File `SYSLSTnn` - `nn=01,...,99`
- System File `SYSLSTnn` with Implicit Allocation

■ *DUMMY

The following rules apply:

1. File name and link name can be specified as positional parameters or keyword parameters. The corresponding keywords are `FILE=` and `LINK=`. Mixing positional and keyword parameters is allowed but not recommended.
2. A string with a length of 1 to 8 characters without commas is interpreted as a link name. This notation is compatible with earlier versions of Natural. Example:

```
DEFINE PRINTER (1) OUTPUT 'P01'
```

The corresponding definition with a keyword subparameter is:

```
DEFINE PRINTER (1) OUTPUT 'LINK=P01'
```

3. A string of 9 to 54 characters without commas is interpreted as a file name. Example:

```
DEFINE PRINTER (2) OUTPUT 'NATURAL $\nu r$ .TEST.PRINTER02'
```

where νr represents the relevant product version.

The corresponding definition with a keyword subparameter is:

```
DEFINE PRINTER (2) OUTPUT 'FILE=NATURAL $\nu r$ .TEST.PRINTER02'
```

4. The following input is interpreted without considering the length and therefore forms exceptions to Rules 2 and 3:

- keyword input: `LINK=`, `FILE=`
- `*DUMMY`
- `NULLFILE` (equivalent to `*DUMMY`)
- `*`
- `*,*`
- `SYSOUT`
- `SYSLST` or `SYSLST( $nn$ )`

Example: `DEFINE PRINTER (7) OUTPUT 'FILE=Y'` is a valid file allocation and not a link name, although the string of characters contains fewer than 9 characters.

5. Generic file names are formed as follows:

```
Pnn.userid.tsn.date.time.number
```

where

<i>nn</i>	is a report number
<i>userid</i>	is a Natural user-ID, 8 characters
<i>tsn</i>	is the BS2000 TSN of the current task, 4 digits
<i>date</i>	is <i>DDMMYYYY</i>
<i>time</i>	is <i>HHIISS</i>
<i>number</i>	is a sequential number, 5 digits

6. Generic link names are formed as follows:

```
NPFnnnnn
```

where *nnnnn* is a 5-digit number that is increased by one after every generation of a dynamic link name.

7. Changing the file allocation for a printer number causes an implicit `CLOSE` of the print file allocated so far.

You are strongly recommended, in all cases except when you only specify a link name (for example: `P01`), to work with keyword parameters. This avoids conflicts of names with additional reports and is essential for file names with fewer than 9 characters.

Examples:

```
DEFINE PRINTER (1) OUTPUT 'LINK=SOURCE'
DEFINE PRINTER (1) OUTPUT 'FILE=SOURCE'
DEFINE PRINTER (1) OUTPUT 'SOURCE'
```

Link Name

Example:

```
DEFINE PRINTER (1) OUTPUT 'LINKP01'
```

means the same as

```
DEFINE PRINTER (1) OUTPUT 'LINK=LINKP01'
```

A file with the link `LINKP01` must exist at runtime. This can be created either by using JCL before starting Natural or by dynamic allocation from the current application. For dynamic allocation, the application programming interface `USR2029` in the library can be used. If, before execution, the link was active as a destination to another file, for example `P01`, this will be released or retained depending on the value of the keyword subparameter `FREE` of profile parameter `PRINT` (possible values are `ON` and `OFF`). Release is done via an explicit `RELEASE` call to the BS2000 command processor.

File Name

Example:

```
DEFINE PRINTER (2) OUTPUT 'NATURALvr.TEST.PRINTER02'
```

where *vr* represents the relevant product version;

means the same as

```
DEFINE PRINTER (2) OUTPUT 'FILE=NATURALvr.TEST.PRINTER02'
```

The file specified in *operand1* is set up using a `FILE` macro call and inherits the link name that was valid for the corresponding print file before execution of the `DEFINE PRINTER` statement.

Generic File Name

Example:

```
DEFINE PRINTER (21) OUTPUT '*'
```

means the same as

```
DEFINE PRINTER (21) OUTPUT 'FILE=*
```

A file with a name created according to Rule 4 is set up using a `FILE` macro call and inherits the link name that was valid for the corresponding print file before execution of the `DEFINE PRINTER` statement.

```
DEFINE PRINTER (22) OUTPUT 'FILE=*,LINK=GENFLK22'
```

A file with a name created according to Rule 4 is set up with the specified link name using a `FILE` macro call.

File Name and Link Name

Example:

```
DEFINE PRINTER (11) OUTPUT 'NATURAL $\nu r$ .TEST.PRINTER11,LNKP11'
```

where νr represents the relevant product version;

means the same as

```
DEFINE PRINTER (11) OUTPUT 'FILE=NATURAL $\nu r$ .TEST.PRINTER11,LINK=LNKP11'
```

which means the same as

```
DEFINE PRINTER (11) OUTPUT 'FILE=NATURAL $\nu r$ .TEST.PRINTER11,LNKP11'
```

The file specified in *operand1* is set up with the specified link name using a FILE macro call and allocated to the corresponding printer number.

Generic File Name and Link Name

Example:

```
DEFINE PRINTER (27) OUTPUT '*',*'
```

means the same as

```
DEFINE PRINTER (27) OUTPUT 'FILE=*,LINK=*'
```

A file with a file name and link name created according to Rule 4 and Rule 5 is set up using a FILE macro call and allocated to the specified printer number (27).



Note: When file name and link name are specified, the previous link name is not released, regardless of the value of keyword subparameter FREE of profile parameter PRINT.

System File SYSOUT

Example:

```
DEFINE PRINTER (14) OUTPUT 'SYSOUT'
```

Report 14 is written to SYSOUT.

Under TIAM: SYSOUT is by default output on the screen.

System File SYSLST

Example:

```
DEFINE PRINTER (15) OUTPUT 'SYSLST'
```

Report 15 is written to the system file SYSLST.

System File SYSLSTnn - nn=01,...,99

Example:

```
DEFINE PRINTER (16) OUTPUT 'SYSLST16'
```

Report 16 is written to the system file SYSLST16.

System File SYSLSTnn with Implicit Allocation

Examples:

```
DEFINE PRINTER (11) OUTPUT 'SYSLST=LST.PRINTER11'
```

The system file SYSLST is allocated to the file LST.PRINTER11; Report 11 is written to the system file SYSLST.

```
DEFINE PRINTER (13) OUTPUT 'SYSLST13=LST.PRINTER13'
```

The system file SYSLST13 is allocated to the file LST.PRINTER13; Report 13 is written to the system file SYSLST13.

```
DEFINE PRINTER (19) OUTPUT 'SYSLST19=*'
```

The system file SYSLST19 is allocated to a file with a name generated according to Rule 4; Report 19 is written to the system file SYSLST19.

Printer Name under CICS

For a printer number defined with the access method AM=CICS, *operand1* can be a transient data or temporary storage queue name (1 to 8 characters), depending on keyword subparameter TYPE of profile parameter PRINT for the printer. For TYPE=TD (transient data), only the first 4 characters of *operand1* are honored and the transient data destination must be predefined to CICS.

For further information, see also *Natural Print and Work Files under CICS* (in the *TP Monitor Interfaces* documentation).

Printer Name under Com-plete

With AM=COMP, a valid printer number (TID) or a logical printer name can be assigned. For example:

```
DEFINE PRINTER (1) OUTPUT '11'
DEFINE PRINTER (2) OUTPUT 'P102'
```

Printer Name under Com-plete/SMARTS

With AM=SMARTS, any printer name can be assigned. For example:

```
DEFINE PRINTER (14) OUTPUT '/nat/path/printer'
DEFINE PRINTER (14) OUTPUT '/nat/path/printer/file/'
DEFINE PRINTER (14) OUTPUT 'printer'
```

It depends on the MOUNT_FS parameter of SMARTS whether the file is located on a SMARTS portable file system or on the native file system. The first element of the path (/nat/) determines the target file system.

If the string is terminated with a slash (/), the last element is taken as the name of the print file. Otherwise, the name of the file is generated from the Natural user ID and a sequence number. If the string does not start with a slash, the path of the file is taken from the environment variable \$NAT_PRINT_ROOT.

The specified path name must exist. When the DEFINE PRINTER statement is executed, the file is allocated dynamically. If the specified member does not exist, a new member of that name will be created.

Printer Names under Natural Advanced Facilities

For Natural Advanced Facilities users, the name of any predefined logical printer profile can be specified. This logical printer profile needs not belong to the currently active user profile. It may be any logical printer profile defined on the NATSPool file. It will be active only for the duration of the Natural program which contains the DEFINE PRINTER statement. For further information, see the *Natural Advanced Facilities* documentation.

Printer Name for Additional Reports and Remote Destinations

Additional reports and remote print destinations can be assigned by default with the following names:

Report	Function
BROADCAST	Output message line to a TP monitor terminal. Same function as MESSAGE (see below), except that under Com-plete, the message is not sent to the desired terminal until no transactions are active on that terminal.
CCONTROL	CCONTROL is the name of a special printer control table associated to the printer <i>n-1</i> ; it must not be modified. For further information, refer to <i>Printer-Advance Control Characters</i> (in the <i>Operations</i> documentation).
CONNECT	Output into a Con-nect folder. Note for Natural installation: The NATPCNT module of Natural must be linked to the Natural nucleus.
DUMMY	Output to be deleted.
HARDCOPY	Output to the current hardcopy device.
INCORE	Output into the NSPF incore database.
INFOLINE	Output to the Natural infoline. For details on the infoline, see the Natural terminal command %X.
MESSAGE	Output message line to a TP monitor terminal. The first 8 bytes of a message must contain the target terminal ID. TSO require the user ID instead of the terminal ID. An example program MSGSW is supplied in the library SYSEXTP.
SOURCE	Output to the Natural source area.
WORKPOOL	Output into the Natural ISPF workpool.

Printing Data in a Remote JES Environment

You can use the write-to-spool file feature (see the *Operations* documentation) to route data through a remote JES node and send it to a user or print it on a device defined in the remote JES environment.

Examples

- [Example 1 - Printer Name Definition for Com-plete](#)
- [Example 2 - Printer Name Definition for Batch Environment](#)
- [Example 3 - Print Output to Infoline](#)

- [Example 4 - Using a Session with Predefined Printer](#)

Example 1 - Printer Name Definition for Com-plete

```
/* PRINTER NAME DEFINITION FOR COM-LETE
*
DEFINE PRINTER (1) OUTPUT 'TID100'
WRITE (1) 'PRINTED ON PRINTER TID100'
END
```

Example 2 - Printer Name Definition for Batch Environment

```
/* OUTPUT ON 'SYSPRINT' (FOR BATCH ENVIRONMENTS)
*
DEFINE PRINTER (REPORT1 = 1) OUTPUT 'SYSPRINT'
WRITE (REPORT1) 'REPORT 1 PRINTED ON PRINTER SYSPRINT'
*
/* OUTPUT TO DEFAULT PRINTER DESTINATION
/* DEFINED WITH PROFILE PARAMETER 'PRINT', SUBPARAMETER 'DEST'
*
DEFINE PRINTER (REPORT2 = 2)
WRITE (REPORT2) 'REPORT PRINTED TO DESTINATION'
```

Example 3 - Print Output to Infoline

```
** Example 'DPIEX1': DEFINE PRINTER
*****
*
SET CONTROL 'XI+'          /* SWITCH INFOLINE MODE ON
SET CONTROL 'XT'          /* INFOLINE TOP
*
DEFINE PRINTER (1) OUTPUT 'INFOLINE'
WRITE (1) 'EXECUTING' *PROGRAM 'BY' *INIT-USER
WRITE 'TEST OUTPUT'
EJECT                     /* FORCE PHYSICAL I/O
*
SET CONTROL 'X'           /* SWITCH BACK TO NORMAL
*
END
```


Output of Program DPIEX1:

```
EXECUTING DPIEX1   BY HTR
Page           1
TEST OUTPUT
```

05-01-13 14:54:33


Example 4 - Using a Session with Predefined Printer

```
** Example 'DPREX1': DEFINE PRINTER
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 NAME
END-DEFINE
*
*  USE SESSION WITH DEFINED PRINTER 1
*
DEFINE PRINTER (INVOICE-LIST=1) OUTPUT 'OUTQ1'
LIMIT 5
READ EMPL-VIEW BY NAME
  WRITE (INVOICE-LIST) NAME
END-READ
*
END
```

56

DEFINE PROTOTYPE

■ Function	406
■ Syntax Description	407
■ Examples	410



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statement: [DEFINE FUNCTION](#)

Function

The `DEFINE PROTOTYPE` statement is used to specify the properties for calling a function including the following:

- the parameters to be passed in the function call,
- the result value to be returned by the function call, and
- whether the function is called with the function name defined in the `DEFINE FUNCTION` statement, or with an alphanumeric variable that contains the function name.

This information is used to resolve a function call within a Natural object at compile time.

A `DEFINE PROTOTYPE` statement is only needed for a function call if any of the following is true:

- The specified function name is an alphanumeric variable which contains the name of the function to be called at execution time.
- An `(IR=)` clause is not specified in the function call and a cataloged object of the called function is not available.
- The parameters provided in the function call are to be validated and the cataloged object of the called function is not available.

The `DEFINE PROTOTYPE` statement can be included in a copycode object if the function is to be called from multiple objects.

For further information, see the following sections in the *Programming Guide*:

- Natural object type Function

■ *Function Call*

Syntax Description

Syntax Element	Description
[VARIABLE] <i>prototype-name</i>	Prototype Name: <i>prototype-name</i> is either of the following: ■ the name of the prototype whose parameter and result field definitions are to be used. This name typically matches the <i>function-name</i> in the DEFINE FUNCTION statement of the referenced function; ■ the name of an alphanumeric field specified as <i>function-name</i> in a function call if the keyword VARIABLE is specified. This field must contain the name of the function to be called at execution time. An array index expression must not be specified with the field name.
UNKNOWN	UNKNOWN Option: The keyword UNKNOWN specifies that the function interface is currently undefined. In this case, the cataloged object (if available) will not be used to extract the function result and the parameter description. When a function call is embedded in a Natural statement, this requires to give the result layout explicitly with an (IR=) clause. In addition, parameters provided in the function call are not checked.
<i>return-data-definition</i>	See Return Data Definition below.
<i>parameter-definition</i>	See Parameter Definition below.
<i>same-as-clause</i>	See SAME AS Clause below.
USING FUNCTION [DEFINITION [OF]] <i>function-name</i>	USING FUNCTION Clause: <i>function-name</i> is the name of an existing cataloged object of the type function. The parameters and the result field definitions of this function are used to resolve the function call.
END-PROTOTYPE	End of DEFINE PROTOTYPE Statement: The Natural reserved word END-PROTOTYPE must be used to terminate the DEFINE PROTOTYPE statement.

Return Data Definition

RETURNS	(<i>format-length</i> [/array-definition])
[<i>variable-name</i>]	[[<i>array-definition</i>]] HANDLE OF OBJECT
	({ A } [/array-definition]) DYNAMIC
	U
	B

The *return-data-definition* clause defines the format/length and, if applicable, the array structure of the return value.

When no return data definition is specified, a function call can only be used within a statement if an explicit (IR=) clause is provided. If such a clause is missing, the function can only be called as a statement, but not in place of an operand within a statement.

Syntax Element Description:

Syntax Element	Description
<i>variable-name</i>	Return Value Name: The optional <i>variable-name</i> has no meaning. It is just there to have a syntax structure similar to the <i>Return Data Definition</i> clause of the DEFINE FUNCTION statement.
<i>format-length</i>	Format/Length Definition: The format and length of the result field. For information on format/length definition of user-defined variables, see <i>Format and Length of User-Defined Variables</i> in the <i>Programming Guide</i> .
<i>array-definition</i>	Array Dimension Definition: With <i>array-definition</i> , you define the lower and upper bounds of a dimension in an array-definition, if the function result is an array field. For further information, see <i>Array Dimension Definition</i> in the description of the DEFINE DATA statement.
HANDLE OF OBJECT	Handle of Object: Used in conjunction with NaturalX.
A, U or B	Data Type: Alphanumeric (A), Unicode (U) or binary (B) for a dynamic result.
DYNAMIC	Dynamic Variable: The function result may be defined as DYNAMIC. For information on processing dynamic variables, see <i>Introduction to Dynamic Variables and Fields</i> in the <i>Programming Guide</i> .

Parameter Definition

```

DEFINE DATA
    {
        PARAMETER UNKNOWN
        {
            {
                PARAMETER [
                    USING parameter-data-area
                    parameter-data-definition
                ]
            } ...
        }
    }
END-DEFINE

```

The *parameter-definition* clause defines the parameters which are to be provided in a function call. This definition layout is checked against the parameters given in a function call. If this clause is omitted, this declares the function as free of parameters. In this case, every attempt to provide parameters in the function call is rejected.

The identifiers used to name the parameter fields have no meaning. They are just there to have a syntax structure similar to the `DEFINE DATA PARAMETER` syntax.

Syntax Element Description:

Syntax Element	Description
PARAMETER UNKNOWN	UNKNOWN Option: With this option, no parameter is specified and the parameter check in the function call is disabled. As a consequence, any number of parameters in the function call will be accepted.
USING <i>parameter-data-area</i>	PDA Name: The name of the <i>parameter-data-area</i> that contains data elements which are used as parameters in a function call. See also Defining Parameter Data in the <code>DEFINE DATA</code> statement description.
<i>parameter-data-definition</i>	Parameter Data Definition: Instead of defining a parameter data area, parameter data can also be defined directly within a function call. See also Parameter Data Definition in the <code>DEFINE DATA</code> statement description.
END-DEFINE	End of Clause: The Natural reserved word <code>END-DEFINE</code> must be used to end the <i>parameter-definition</i> clause.

SAME AS Clause

```
SAME AS [PROTOTYPE] prototype-name
```

With the SAME AS clause you can use the parameter and result field definitions of another prototype which has been defined before in the same Natural object.

Examples

- [Example 1 - DEFINE PROTOTYPE with a Defined Function Name](#)
- [Example 2 - DEFINE PROTOTYPE with a Variable Function Name](#)

Example 1 - DEFINE PROTOTYPE with a Defined Function Name

This is a prototype definition for a function named F#FACTOR where the *prototype-name* corresponds to the *function-name* specified in the referenced [DEFINE FUNCTION](#) statement. The result returned by the function is of format (I2/1:3), and a single parameter of format (I2) is required.

```
** Example 'DPTEX1': DEFINE PROTOTYPE and function call
*****
DEFINE DATA LOCAL
  1 #NUM (I2)
END-DEFINE
*
DEFINE PROTOTYPE F#FACTOR
  RETURNS (I2/1:3)
  DEFINE DATA PARAMETER
    1 #VALUE (I2)
  END-DEFINE
END-PROTOTYPE
*
#NUM := 3
*
WRITE 'Function call:' F#FACTOR(<#NUM>)(*)
*
END
```

The function F#FACTOR is defined in the example function DFUEX2 in library SYSEXSYN. See [Examples](#) in the [DEFINE FUNCTION](#) statement description.

Output of Program DPTX1:

```
Function call:      3      6      9
```

Example 2 - DEFINE PROTOTYPE with a Variable Function Name

Due to the keyword `VARIABLE`, this prototype specifies a function call where the referenced *prototype-name* is an alphanumeric variable which contains the function name at execution time.

```
** Example 'DPTX2': DEFINE PROTOTYPE and function call
*****
DEFINE DATA LOCAL
  1 #NAME (A20)
  1 #TEXT (A10)
END-DEFINE
*
DEFINE PROTOTYPE VARIABLE #NAME
  RETURNS #RETURN (A1)
  DEFINE DATA PARAMETER
    1 #IN (A10)
  END-DEFINE
END-PROTOTYPE
*
#NAME := 'F#FIRST-CHAR'
#TEXT := 'ABCDEFGHIJ'
*
WRITE 'First character:' #NAME(<#TEXT>)
*
END
```

The function `F#FIRST-CHAR` is defined in the example function `DFUEX1` in library `SYSEXSYN`. See [Examples](#) in the `DEFINE FUNCTION` statement description.

Output of Program DPTX2:

```
First character: A
```


57

DEFINE SUBROUTINE

■ Function	414
■ Restrictions	415
■ Syntax Description	416
■ Examples	416

```

DEFINE [SUBROUTINE] subroutine-name
    statement ...
{
    END-SUBROUTINE (structured mode only)
    RETURN (reporting mode only)
}
    
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [CALL](#) | [CALL FILE](#) | [CALL LOOP](#) | [CALLNAT](#) | [ESCAPE](#) | [FETCH](#) | [PERFORM](#)

Belongs to Function Group: [Invoking Programs and Routines](#)

Function

The `DEFINE SUBROUTINE` statement is used to define a Natural subroutine. A subroutine is invoked with a [PERFORM](#) statement.

Inline/External Subroutines

A subroutine may be defined within the object which contains the [PERFORM](#) statement that invokes the subroutine (**inline subroutine**); or it may be defined external to the object that contains the [PERFORM](#) statement (**external subroutine**). An inline subroutine may be defined before or after the first [PERFORM](#) statement which references it.



Note: Although the structuring of a program function into multiple external subroutines is recommended for achieving a clear program structure, please note that a subroutine should always contain a larger function block because the invocation of the external subroutine represents an additional overhead as compared with inline code or subroutines.

Data Available in a Subroutine

Inline Subroutines

No explicit parameters can be passed from the invoking program via the [PERFORM](#) statement to an internal subroutine.

An inline subroutine has access to the currently established global data area as well as to the local data area used by the invoking program.

External Subroutines

An external subroutine has access to the currently established global data area. In addition, parameters can be passed directly with the [PERFORM](#) statement from the invoking object to the external subroutine; thus, you may reduce the size of the global data area.

An external subroutine has no access to the local data area defined in the calling program; however, an external subroutine may have its own local data area.

Restrictions

- Any processing loop initiated within a subroutine must be closed before `END-SUBROUTINE` is issued.
- An inline subroutine must not contain another `DEFINE SUBROUTINE` statement (see [Example 1](#) below).
- An external subroutine (that is, an object of type subroutine) must not contain more than one `DEFINE SUBROUTINE` statement block (see [Example 2](#) below). However, an external `DEFINE SUBROUTINE` block may contain further inline subroutines (see [Example 1](#) below).
- You may not use the name of an external subroutine twice in one library.

Example 1

The following construction is possible in an object of type subroutine, but not in any other object (where `SUBR01` would be considered an inline subroutine):

```
...
DEFINE SUBROUTINE SUBR01
  ...
  PERFORM SUBR02
  PERFORM SUBR03
  ...
  DEFINE SUBROUTINE SUBR02
  /* inline subroutine...
  END-SUBROUTINE
  ...
  DEFINE SUBROUTINE SUBR03
  /* inline subroutine...
  END-SUBROUTINE
END-SUBROUTINE
END
```

Example 2 (invalid):

The following construction is *not* allowed in an object of type subroutine:

```
...
DEFINE SUBROUTINE SUBR01
...
END-SUBROUTINE
DEFINE SUBROUTINE SUBR02
...
END-SUBROUTINE
END
```

Syntax Description

Syntax Element	Description
<i>subroutine-name</i>	Name of Subroutine: For a subroutine name (maximum 32 characters), the same naming conventions apply as for user-defined variables; see <i>Naming Conventions for User-Defined Variables</i> in the <i>Using Natural</i> documentation. The subroutine name is independent of the name of the module in which the subroutine is defined (it may but need not be the same).
<i>statement</i>	Statement(s) to be Executed: In place of <i>statement</i>, you must supply one or several suitable statements, depending on the situation. For an example of a statement, see Examples below.
END-SUBROUTINE RETURN	End of DEFINE SUBROUTINE Statement: In structured mode, the subroutine definition is terminated with END-SUBROUTINE. In reporting mode, RETURN may be used to terminate a subroutine.

Examples

- [Example 1 - Define Subroutine](#)

■ Example 2 - Sample Structure for External Subroutine Using GDA Fields

Example 1 - Define Subroutine

```

** Example 'DSREX1S': DEFINE SUBROUTINE (structured mode)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 ADDRESS-LINE (A20/2)
  2 PHONE
*
1 #ARRAY (A75/1:4)
1 REDEFINE #ARRAY
  2 #ALINE (A25/1:4,1:3)
1 #X (N2) INIT <1>
1 #Y (N2) INIT <1>
END-DEFINE
*
FORMAT PS=20
LIMIT 5
FIND EMPLOY-VIEW WITH NAME = 'SMITH'
  MOVE NAME TO #ALINE (#X,#Y)
  MOVE ADDRESS-LINE(1) TO #ALINE (#X+1,#Y)
  MOVE ADDRESS-LINE(2) TO #ALINE (#X+2,#Y)
  MOVE PHONE TO #ALINE (#X+3,#Y)
  IF #Y = 3
    RESET INITIAL #Y
    PERFORM PRINT
  ELSE
    ADD 1 TO #Y
  END-IF
  AT END OF DATA
    PERFORM PRINT
  END-ENDDATA
END-FIND
*
DEFINE SUBROUTINE PRINT
  WRITE NOTITLE (AD=01) #ARRAY(*)
  RESET #ARRAY(*)
  SKIP 1
END-SUBROUTINE
*
END

```

Output of Program DSREX1S:

SMITH ENGLANDSVEJ 222 554349	SMITH 3152 SHETLAND ROAD MILWAUKEE 877-4563	SMITH 14100 ESWORTHY RD. MONTERREY 994-2260
SMITH 5 HAWTHORN OAK BROOK 150-9351	SMITH 13002 NEW ARDEN COUR SILVER SPRING 639-8963	

Equivalent reporting-mode example: [DSREX1R](#).

Example 2 - Sample Structure for External Subroutine Using GDA Fields

```

** Example 'DSREX2': DEFINE SUBROUTINE (using GDA fields)
*****
DEFINE DATA
GLOBAL
  USING DSREX2G
END-DEFINE
*
INPUT 'Enter value in GDA field' GDA-FIELD1
*
* Call external subroutine in DSREX2S
*
PERFORM DSREX2-SUB
*
END

```

Global Data Area DSREX2G Used by Program DSREX2:

1 GDA-FIELD1	A	2

Subroutine DSREX2S Called by Program DSREX2:

```

** Example 'DSREX2S': SUBROUTINE (external subroutine using global data)
*****
DEFINE DATA
GLOBAL
  USING DSREX2G
END-DEFINE
*
DEFINE SUBROUTINE DSREX2-SUB
*
  WRITE 'IN SUBROUTINE' *PROGRAM '=' GDA-FIELD1
*
END-SUBROUTINE


```


*
END

58

DEFINE WINDOW

■ Function	422
■ Syntax Description	423
■ Protection of Input Fields in a Window	427
■ Invoking Different Windows	427
■ Example	427



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [INPUT](#) | [REINPUT](#) | [SET WINDOW](#)

Belongs to Function Group: [Screen Generation for Interactive Processing](#)

Function

The `DEFINE WINDOW` statement is used to specify the size, position and attributes of a window.

A window is that segment of a logical page, built by a program, which is displayed on the terminal screen. There is always a window present, although you may not be aware of its existence: unless specified differently, the size of the window is identical to the physical size of your terminal screen.

A `DEFINE WINDOW` statement does not activate a window; this is done with a `SET WINDOW` statement or with the `WINDOW` clause of an `INPUT` statement.

See also *Windows* in the *Screen Design* section of *Designing Application User Interfaces* in the *Programming Guide*.



Note: There is always only *one* Natural window, that is, the most recent window. Any previous windows may still be visible on the screen, but are no longer active and are ignored by Natural. You may enter input only in the most recent window. If there is not enough space to enter input, the window size must be adjusted first.

Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats																Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S						N	P	I											yes	no
<i>operand2</i>	C	S						N	P	I											yes	no
<i>operand3</i>	C	S						N	P	I											yes	no
<i>operand4</i>	C	S						N	P	I											yes	no
<i>operand5</i>	C	S					A	U													yes	no

Syntax Element Description:


Syntax Element	Description
<i>window-name</i>	The <i>window-name</i> identifies the window. The name may be up to 32 characters long. For a window name, the same naming conventions apply as for user-defined variables, see <i>Naming Conventions for User-Defined Variables</i> in the <i>Using Natural</i> documentation.
SIZE	With the SIZE clause, you specify the size of the window. Note: On mainframe computers, Natural requires additional columns for so-called attribute bytes to be able to display data on the screen (on other platforms, such attribute bytes are not needed). Consequently, on mainframe computers the screen area overlaid by a window is wider, and the size of the page segment visible inside a window is smaller than on other platforms. Example: Assume a window whose size is defined as SIZE 5 * 15 (that is, with a width of 15 columns): ■ On mainframe computers, the screen area overlaid by the window is 16 columns; the size of what is visible inside the window is 14 columns without frame, and 10 columns with frame respectively. ■ On other platforms, the screen area overlaid by the window is 15 columns; the size of what is visible inside the window is 15 columns without frame, and 13 columns with frame respectively.
SIZE AUTO	The size of the window is determined automatically by Natural at runtime. The size is determined by the data generated into the window as follows: ■ The number of window lines will be the number of INPUT lines generated (plus possibly the PF-key lines, message line, and infoline/statistics line). ■ The number of window columns is determined by the longest INPUT line: Natural scans, starting from the ends of the lines, for the rightmost significant byte in a

Syntax Element	Description
	line. This may cause an input-only or modifiable field (<code>AD=A</code> or <code>AD=M</code>) to be truncated; to avoid this, you either put a single-character text string after such a field or explicitly set the window size with the following: <pre>SIZE operand1 * operand2</pre> If you omit the <code>SIZE</code> clause, <code>SIZE AUTO</code> applies by default. Note: The title is not part of the window data. Therefore, if the window size has been determined as described above <i>and</i> the title is longer than the window, it will be truncated.
<code>SIZE QUARTER</code>	The size of the window will be one quarter of the physical screen.
<code>SIZE operand1 * operand2</code>	The size of the window will be <i>n</i> lines by <i>n</i> columns. The number of lines is determined by <i>operand1</i>, the number of columns by <i>operand2</i>. Neither of the two operands must contain decimal digits. If the window is <code>FRAMED</code>, the specified size will be inclusive of the frame. The minimum possible window size is: ■ without frame: 2 lines by 10 columns, ■ with frame: 4 lines by 13 columns. The maximum possible window size is the size of the physical screen.
<code>BASE</code>	With the <code>BASE</code> clause, you determine the position of the window on the physical screen. If you omit the <code>BASE</code> clause, <code>BASE CURSOR</code> applies by default.
<code>BASE CURSOR</code>	Places the top left corner of the window at the current cursor position. The cursor position is the physical position of the cursor on the screen. If the size of the window makes it impossible to place the window at the cursor position, Natural automatically places the window as close as possible to the desired position.
<code>BASE TOP/BOTTOM LEFT/RIGHT</code>	Places the window at the top-left, bottom-left, top-right, or bottom-right corner respectively of the physical screen.
<code>BASE operand3/operand4</code>	This places the top left corner of the window at the specified line/column of the physical screen. The line number is determined by <i>operand3</i>, the column number by <i>operand4</i>. Neither of the two operands must contain decimal digits. If the size of the window makes it impossible to place the window at the specified position, you will get an error message.
<code>REVERSED</code>	<code>REVERSED</code> will cause the window to be displayed in reverse video (if the screen used supports this feature; if it does not, <code>REVERSED</code> will be ignored).
<code>REVERSED CD= background-color</code>	This will cause the window to be displayed in reverse video and the background of the window in the specified color (if the screen used supports these features; if it does not, the respective specification will be ignored).

Syntax Element	Description
	For information on valid color codes, see session parameter CD in the <i>Parameter Reference</i> .
TITLE <i>operand5</i>	With the TITLE clause, you may specify a heading for the window. The specified title (<i>operand5</i>) will be displayed centered in the top frame-line of the window. The title can be specified either as a text constant (in apostrophes) or as the content of a user-defined variable. If the title is longer than the window, it will be truncated. The title is only displayed if the window is FRAMED; if FRAMED OFF is specified for the window, the TITLE clause will be ignored. Note: If the title contains trailing blanks, these will be removed. If the first character of the title is a blank, one blank will automatically be appended to the title.
CONTROL	With the CONTROL clause, you determine whether the PF-key lines, the message line and the statistics line are displayed in the window or on the full physical screen.
CONTROL WINDOW	CONTROL WINDOW causes the lines to be displayed inside the window. If you omit the CONTROL clause, CONTROL WINDOW applies by default.
CONTROL SCREEN	CONTROL SCREEN causes the lines to be displayed on the full physical screen outside the window.
FRAMED	By default, that is, if you omit the FRAMED clause, the window is framed. The top and bottom frame lines are cursor-sensitive: where applicable, you can page forward, backward, left or right within the window by simply placing the cursor over the appropriate symbol (<, -, +, or >; see position-clause below) and then pressing ENTER. If no symbols are displayed, you can page backward and forward within the window by placing the cursor in the top frame line (for backward positioning) or bottom frame line (for forward positioning) and then pressing ENTER. Note: If the window size is smaller than 4 lines by 12 (or 13 on mainframe computers) columns, the frame will not be visible.
FRAMED OFF	If you specify FRAMED OFF, the framing and everything attached to the frame (window title and position information) will be switched off.
FRAMED (CD= <i>frame-color</i>)	This causes the frame of the window to be displayed in the specified color (if the screen used is a color screen; if it is not, the color specification will be ignored). For information on valid color codes, see session parameter CD (in the <i>Parameter Reference</i>). Note: In Natural for Windows, this specification is ignored.
<i>position-clause</i>	The POSITION clause is only evaluated on mainframe computers; on all other platforms it is ignored. For details, refer to Position Clause below.

POSITION Clause

The `POSITION` clause is only evaluated on mainframe computers; on all other platforms it is ignored.



The `POSITION` clause causes information on the position of the window on the logical page to be displayed in the frame of the window. This applies only if the logical page is larger than the window; if it is not, the `POSITION` clause will be ignored. The position information indicates in which directions the logical page extends above, below, to the left and to the right of the current window.

If the `POSITION` clause is omitted, `POSITION SYMBOL TOP RIGHT` applies by default.

Syntax Element Description:

Syntax Element	Description
POSITION SYMBOL	Causes the position information to be displayed in form of symbols: More: < - + >. The information is displayed in the top and/or bottom frame line.
TOP/BOTTOM	Determines whether the position information is displayed in the top or bottom frame line.
AUTO	Is only applicable if the logical page is fully visible in the window as far as its horizontal size is concerned, that is, if only a minus sign character (-) and/or a plus sign character (+) are to be displayed. In this case, <code>AUTO</code> automatically switches from the symbols to the words <code>Top</code> , <code>Bottom</code> and <code>More</code> respectively.
SHORT	Causes the word <code>More:</code> before the symbols < - + > to be suppressed.
LEFT/RIGHT	Determines whether the position information is displayed in the left or right part of the frame line.
POSITION TEXT	Causes the position information to be displayed in text form. The information is displayed in the top and/or bottom frame line with the words <code>More</code> , <code>Top</code> and <code>Bottom</code> . The text is language-dependent and may also be displayed in another language if the language code is set accordingly.
POSITION TEXT MORE	Suppresses the words <code>Top</code> and <code>Bottom</code> and only displays the word <code>More</code> where applicable, i.e., in the top or bottom frame line or both.
LEFT/RIGHT	Determines whether the position information is displayed in the left or right part of the top frame line.
POSITION OFF	Causes the position information to be suppressed; no position information will be displayed.

Protection of Input Fields in a Window

The following rules apply to input fields (with AD=A or AD=M) which are not entirely within the window:

- Input fields whose beginning is not inside the window are always made protected.
- Input fields which begin inside and end outside the window are only made protected if the values they contain cannot be displayed completely in the window. Please note that in this case it is decisive whether the *value length*, not the *field length*, exceeds the window size. Filler characters (as specified with the profile parameter FC) do not count as part of the value.

If you wish to access input fields thus protected, you have to adjust the window size accordingly so that the beginning of the field/end of the value is within the window.

Invoking Different Windows

A `DEFINE WINDOW` statement must not be placed within a logical condition statement block. To invoke different windows depending on a condition, use different `SET WINDOW` statements (or `INPUT` statements with a `WINDOW` clause respectively) in a condition.

Example

```
** Example 'DWDEX1': DEFINE WINDOW
*****
DEFINE DATA LOCAL
01 #I (P3)
END-DEFINE
*
SET KEY PF1='%W<<' PF2='%W>>' PF4='%W--' PF5='%W++'
*
DEFINE WINDOW WIND1
    SIZE QUARTER
    BASE TOP RIGHT
    FRAMED ON POSITION SYMBOL AUTO
*
SET WINDOW 'WIND1'
FOR #I = 1 TO 10
    WRITE 25X #I 'THIS IS SOME LONG TEXT' #I
END-FOR
*
END
```

Output of Program DWDEX1:

```

> r                                     +-----More:      + >+
All      ....+....1....+....2....+....3.. !                !
0010 ** Example 'DWDEX1': DEFINE WIND !                1 THIS !
0020 ***** !                2 THIS !
0030 DEFINE DATA LOCAL !                3 THIS !
0040 01 #I (P3) !                4 THIS !
0050 END-DEFINE !                5 THIS !
0060 * !                6 THIS !
0070 SET KEY PF1='%W<<' PF2='%W>>' PF !                7 THIS !
0080 * ! MORE !
0090 DEFINE WINDOW WIND1 +-----+
0100     SIZE QUARTER
0110     BASE TOP RIGHT
0120     FRAMED ON POSITION SYMBOL AUTO
0130 *
0140 SET WINDOW 'WIND1'
0150 FOR #I = 1 TO 10
0160     WRITE 25X #I 'THIS IS SOME LONG TEXT' #I
0170 END-FOR
0180 *
0190 END
0200
      ....+....1....+....2....+....3....+....4....+....5....+... S 19   L 1

```

59

DEFINE WORK FILE

■ Function	430
■ Syntax Description	430
■ Work File Name under z/OS Batch, TSO and Server	432
■ Work File Name under z/VSE Batch	435
■ Work File Name under BS2000 Batch and TIAM	436
■ Work File Name under CICS	440
■ Work File Name under Com-plete/SMARTS	440

DEFINE WORK FILE *n* { *operand1* [TYPE *operand2*] } [ATTRIBUTES {*operand3*}...]
TYPE *operand2*

 **Note:** The elements shown in square brackets [...] are optional, however, at least one of them must be specified with this statement.

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [CLOSE WORK FILE](#) | [READ WORK FILE](#) | [WRITE WORK FILE](#)

Belongs to Function Group: [Control of Work Files / PC Files](#)

Function

The statement `DEFINE WORK FILE` is used to assign a file name to a Natural work file number within a Natural application. This allows you to make or change work file assignments dynamically within a Natural session or overwrite work file assignments made at another level.

When this statement is executed and the specified work file is already open, the statement will implicitly close the work file.

All work files to be used during a session must be preassigned to an access method by means of keyword subparameter `AM` of profile parameter `WORK` or automatically by definition in the JCL.

 **Note:** For Unicode and code page support on mainframe platforms, see *Work Files and Print Files* in the *Unicode and Code Page Support* documentation.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats															Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S				A	U														yes	no
<i>operand2</i>	C	S				A	U														yes	no
<i>operand3</i>	C	S				A	U														yes	no

Syntax Element Description:

Syntax Element	Description		
DEFINE WORK FILE <i>n</i>	Work File Number: <i>n</i> is the work file number (1 to 32). This is the number to be used in a WRITE WORK FILE, READ WORK FILE or CLOSE WORK FILE statement.		
<i>operand1</i>	Work File Name: <i>operand1</i> is the name of the work file. As <i>operand1</i> you can specify the name of the data set to be assigned to the work file number. <i>operand1</i> can be 1 to 253 characters long. You can specify either a logical or a physical data set name. The possible format depends on the operating system environment and the access method defined by keyword subparameter AM of profile parameter WORK. Some access methods do not support a work file name as <i>operand1</i>, for example, AM=COMP and AM=PC. If <i>operand1</i> is not specified, the value of <i>operand1</i> is determined by taking the current name specified with the previously performed DEFINE WORK FILE statement for this work file number. If no previous DEFINE WORK FILE statement was performed, the name is taken from the Natural parameter module. Note: If <i>operand1</i> is not specified, the behavior of Natural for Mainframes and Natural for Windows/UNIX/OpenVMS is different. Information on operating-system- or TP-monitor-dependent work file naming conventions is included in the following sections: ■ Work File Name under z/OS Batch, TSO and Server ■ Work File Name under z/VSE Batch ■ Work File Name under BS2000 Batch and TIAM ■ Work File Name under CICS ■ Work File Name under Com-plete/SMARTS		
TYPE <i>operand2</i>	TYPE Clause: <i>operand2</i> specifies the type of work file. The value of <i>operand2</i> is handled in a case insensitive way and must be enclosed in quotes or provided in an alphanumeric variable. <table border="1"> <tr> <td>UNFORMATTED</td><td> A completely unformatted file. No formatting information is written (neither for fields nor for records). UNFORMATTED treats a work file as a byte-stream with no record boundaries. Note that type UNFORMATTED will be rejected by Entire Connection. </td></tr> </table>	UNFORMATTED	A completely unformatted file. No formatting information is written (neither for fields nor for records). UNFORMATTED treats a work file as a byte-stream with no record boundaries. Note that type UNFORMATTED will be rejected by Entire Connection.
UNFORMATTED	A completely unformatted file. No formatting information is written (neither for fields nor for records). UNFORMATTED treats a work file as a byte-stream with no record boundaries. Note that type UNFORMATTED will be rejected by Entire Connection.		

Syntax Element	Description	
		Format: UNFORMATTED
	FORMATTED	FORMATTED defines a regular record-oriented work file, which is subject to the same handling as in previous Natural versions.
ATTRIBUTES { <i>operand3</i> } . . .	ATTRIBUTES Clause: This clause makes sense only in Natural for Open Systems; in Natural for Mainframes it is ignored.	

Examples:

```
DEFINE WORK FILE 17 #FILE TYPE 'UNFORMATTED'
#TYPE := 'FORMATTED'
DEFINE WORK FILE 18 #FILE TYPE #TYPE
```

Work File Name under z/OS Batch, TSO and Server

The following topics are covered:

- [Work File Name - operand1](#)
- [Allocation and De-Allocation of Data Sets](#)
- [Work Files in Server Environments](#)

Work File Name - operand1

Under z/OS, for a work-file number that is defined with the access method AM=STD, *operand1* can be:

- a **logical data set name** (DD name, 1 to 8 characters);
- a **physical data set name** of a cataloged data set (1 to 44 characters) or a physical data set member name;
- a path name and member name of an **HFS file** (1 to 253 characters) in an MVS UNIX Services environment;
- a **JES spool file class**;
- NULLFILE.

Logical Data Set Names	Example: <pre>DEFINE WORK FILE 21 'SYSOUT1'</pre> The specified data set <code>SYSOUT1</code> must have been allocated before the <code>DEFINE WORK FILE</code> statement is executed. The allocation can be done via JCL, CLIST (TCO) or dynamic allocation (SVC 99). For dynamic allocation you can use the application programming interface <code>USR2021N</code>, which is located in library <code>SYSEXT</code>. The data set name specified in the <code>DEFINE WORK FILE</code> statement overrides the name specified with keyword subparameter <code>DEST</code> of profile parameter <code>WORK</code>. Optionally, the data set name may be prefixed by <code>DDN=</code> to indicate that it is a DD name. For example: <pre>DEFINE WORK FILE 22 'DDN=MYWORK'</pre>
Physical Data Set Names	Example: <pre>DEFINE WORK FILE 23 'TEST.WORK.FILE'</pre> The specified data set must exist in cataloged form. When the <code>DEFINE WORK FILE</code> statement is executed, the data set is allocated dynamically by <code>SVC 99</code> with the current DD name and option <code>DISP=SHR</code>. If the data set name is 8 characters or shorter and does not contain a period (<code>.</code>), it might be misinterpreted as a DD name. To avoid this, prefix the name with <code>DSN=</code>. For example: <pre>DEFINE WORK FILE 22 'DSN=WORKXYZ'</pre> If the data set is a PDS member, you specify the PDS member name (1 to 8 characters) in parentheses after the data set name (1 to 44 characters). For example: <pre>DEFINE WORK FILE 4 'TEST.WORK.PDS(TEST1)'</pre> If the specified member does not exist, a new member of that name will be created.
HFS Files	Example: <pre>DEFINE WORK FILE 14 '/u/nat/rec/test.txt'</pre> The specified path name must exist. When the <code>DEFINE WORK FILE</code> statement is executed, the HFS file is allocated dynamically. If the specified member does not exist, a new member of that name will be created. For the dynamic allocation of the data set, the following z/OS path options are used:

	<pre> PATHOPTS=(OCREAT,OTRUNC,ORDWR) PATHMODE=(SIRUSR,SIWUSR,SIRGRP,SIWGRP) FILEDATA=TEXT </pre> When an HFS file is closed, it is automatically de-allocated by z/OS (regardless of the setting of keyword subparameter <code>FREE</code> of profile parameter <code>WORK</code>). To read an HFS file, you have to use the application programming interface <code>USR2021N</code> (dynamic data set allocation) instead of the <code>DEFINE WORK FILE</code> statement, because of the <code>OTRUNC</code> option. This option resets the HFS file at the first read access, which results in an empty file.
JES Spool File Class	To create a JES spool data set, you specify <code>SYSOUT=x</code> (where <i>x</i> is the desired spool file class). For the default spool file class, you specify <code>SYSOUT=*</code>. Examples: <pre> DEFINE WORK FILE 10 'SYSOUT=A' DEFINE WORK FILE 12 'SYSOUT=*' </pre> To specify additional parameters for the dynamic allocation, use the application programming interface <code>USR2021N</code> (dynamic data set allocation) in the library <code>SYSEXT</code> instead of the <code>DEFINE WORK FILE</code> statement.
NULLFILE	To indicate a dummy data set.

Allocation and De-Allocation of Data Sets

When the `DEFINE WORK FILE` statement is executed and a physical data set name, HFS file, spool file class or dummy data set has been specified, the corresponding data set is allocated automatically. If the logical file is already open, it will be closed automatically, except when the keyword subparameter `CLOSE=FIN` of profile parameter `WORK` has been specified, in which case an error will be issued. Moreover, an existing data set allocated with the same current DD name is automatically de-allocated before the new data set is allocated. To avoid unnecessary overhead by unsuccessful premature opening of work files not yet allocated at the start of the program, work files should be defined with keyword subparameter `OPEN=ACC` (open at first access) of profile parameter `WORK`.

In the case of an HFS file, or a work file defined with keyword subparameter `FREE=ON` of profile parameter `WORK`, the work file is automatically de-allocated as soon as it has been closed.

As an alternative for the dynamic allocation and de-allocation of data sets, the application programming interface `USR2021N` (dynamic data set allocation) in the library `SYSEXT` is provided. This API also allows you to specify additional parameters for dynamic allocation.

Work Files in Server Environments

In server environments, errors may occur if multiple Natural sessions attempt to allocate or open a data set with the same DD name. To avoid this, you either specify the work file with keyword subparameter `DEST=*` of profile parameter `WORK`, or you specify `DEFINE WORK FILE '*'` in your program before the actual `DEFINE WORK FILE` statement. Natural then generates a unique DD name at the physical data set allocation when the first `DEFINE WORK FILE` statement for that work file is executed.

All work files whose DD names begin with `CM` are shared by all sessions in a server environment. A shared work file opened for output by the first session is physically closed when the server is terminated. A shared work file opened for input is physically closed when the last session closes it, that is, when it receives an end-of-file condition. When a work file is read concurrently, one file record is supplied to one `READ WORK FILE` statement only.

Work File Name under z/VSE Batch

Under z/VSE, for a work-file number that is defined with the access method `AM=STD`, *operand1* can be:

- a **logical data set name** (DD name, 1 to 7 characters);
- `NULLFILE` (to indicate a dummy data set).

Logical Data Set Names	Example: <pre>DEFINE WORK FILE 21 'SYSOUT1'</pre> The specified data set <code>SYSOUT1</code> must have been defined in the JCL or in the z/VSE standard or partition labels. The data set name specified in the <code>DEFINE WORK FILE</code> statement overrides the name specified with keyword subparameter <code>DEST</code> of profile parameter <code>WORK</code>. Optionally, the data set name may be prefixed by <code>DDN=</code> to indicate that it is a DD name. For example: <pre>DEFINE WORK FILE 22 'DDN=MYWORK'</pre>

NULLFILE	To allocate a dummy data set, you specify NULLFILE as <i>operand1</i> : <pre>DEFINE WORK FILE <i>n</i> 'NULLFILE'</pre>

Work File Name under BS2000 Batch and TIAM

Under BS2000, for a work-file number that is defined with the access method `AM=STD`, you can use *operand1* to specify a file name or a link name that is allocated to this work file.

In this case, *operand1* can have a length of 1 to 253 characters and one of the following meanings:

- a BS2000 **link name** (1 to 8 characters)
- a BS2000 **file name** (9 to 54 characters)
- a **generic BS2000 file name** (wildcard)
- a BS2000 **file name and link name**
- a **generic BS2000 file name and link name** (wildcard)
- ***DUMMY**

The following rules apply.

1. File name and link name can be specified as positional parameters or keyword parameters. The corresponding keywords are `FILE=` and `LINK=`. Mixing positional and keyword parameters is allowed but not recommended.
2. A string with a length of 1 to 8 characters without commas is interpreted as a link name. This notation is compatible with earlier versions of Natural. Example:

```
DEFINE WORK FILE 1 'W01'
```

The corresponding definition with a keyword parameter is:

```
DEFINE WORK FILE 1 'LINK=W01'
```

3. A string of 9 to 54 characters without commas is interpreted as a file name.

Example:

```
DEFINE WORK FILE 2 'NATURAL $\nu$ r.TEST.WORKFILE02'
```

where ν r represents the relevant product version.

The corresponding definition with a keyword parameter is:

```
DEFINE WORK FILE 2 'FILE=NATURAL $\nu$ r.TEST.WORKFILE02'
```

4. The following input is interpreted without considering the length and therefore forms exceptions to Rules 2 and 3:

- keyword input: LINK=, FILE=
- *DUMMY
- NULLFILE (equivalent to *DUMMY)
- *
- **, ,

Example: DEFINE WORK FILE 7 'FILE=Y' is a valid file allocation and not a link name, although the string of characters contains fewer than 9 characters.

5. Generic file names are formed as follows:

```
 $wnn.userid.tsn.date.time.number$ 
```

where

nn	is a work-file number
$userid$	is a Natural user ID, 8 characters
tsn	is the BS2000 TSN of the current task, 4 digits
$date$	is DDMMYYYY
$time$	is HHIISS
$number$	is a number, 5 digits

6. Generic link names are formed as follows:

```
NWF $nnnnn$ 
```

$nnnnn$ is a 5-digit number that is increased by one after every generation of a dynamic link name.

7. Changing the file allocation for a work-file number causes an implicit CLOSE of the work file allocated so far.

You are strongly recommended, in all cases except when you only specify a link name (for example: W01), to work with keyword parameters. This avoids conflicts of interpretation with additional reports and is essential for file names with fewer than 9 characters.

Example:

```
DEFINE WORK FILE 3 'LINK=/#W03'
DEFINE WORK FILE 3 'FILE=/#W03'
```

Link Name	Example: <pre>DEFINE WORK FILE 1 'LINKW01'</pre> means the same as <pre>DEFINE WORK FILE 1 'LINK=LINKW01'</pre> A file with the link LINKW01 must exist at runtime. This can be created either using JCL before starting Natural or by dynamic allocation from the current application. For dynamic allocation, the application programming interface USR2029N (dynamic file allocation) in the library SYSEXT can be used. If, before execution, the link was active on another file, for example: W01, this will be released or retained depending on the value of the profile parameter FREE (possible values are ON and OFF). Release is done via an explicit RELEASE call to the BS2000 command processor.
File Name	Example: <pre>DEFINE WORK FILE 2 'NATURALvr.TEST.WORK02'</pre> means the same as <pre>DEFINE WORK FILE 2 'FILE=NATURALvr.TEST.WORK02'</pre> where <i>vr</i> represents the relevant product version. The file specified in <i>operand1</i> is set up using a FILE macro call and inherits the link name that was valid for the corresponding work file before execution of the DEFINE WORK FILE statement.
Generic File Name	Example: <pre>DEFINE WORK FILE 21 '*'</pre> means the same as

	<pre>DEFINE WORK FILE 21 'FILE=*</pre> A file with a name created according to Rule 4 is set up using a <code>FILE</code> macro call and inherits the link name that was valid for the corresponding work file before execution of the <code>DEFINE WORK FILE</code> statement. <pre>DEFINE WORK FILE 22 'FILE=*,LINK=WFLK22'</pre> A file with a name created according to Rule 4 is set up with the specified link name, using a <code>FILE</code> macro call.
File Name and Link Name	Example: <pre>DEFINE WORK FILE 11 'NATURALνr.TEST.WORKF11,LNKW11'</pre> means the same as <pre>DEFINE WORK FILE 11 'FILE=NATURALνr.TEST.WORKF11,LINK=LNKW11'</pre> which means the same as <pre>DEFINE WORK FILE 11 'FILE=NATURALνr.TEST.WORKF11,LNKW11'</pre> where νr represents the relevant product version. The file given in <i>operand1</i> is set up with the specified link name, using a <code>FILE</code> macro call and allocated to the corresponding work-file number.
Generic File Name and Link Name	Example: <pre>DEFINE WORK FILE 27 '*',*'</pre> means the same as <pre>DEFINE WORK FILE 27 'FILE=*,LINK=*'</pre> A file with a file name and link name created according to Rule 4 and Rule 5 is set up using a <code>FILE</code> macro call and allocated to the specified work file 27. Note: When file name and link name are specified, the previous link name is not released, regardless of the value of keyword subparameter <code>FREE</code> of profile parameter <code>WORK</code>.
*DUMMY	To indicate a dummy data set.

Work File Name under CICS

For a work-file number defined with access method `AM=CICS`, *operand1* can be a transient data or temporary storage queue name (1 to 8 characters), depending on keyword subparameter `TYPE` of profile parameter `WORK` for the work file. For `TYPE=TD`, only the first 4 characters of *operand1* are honored and the transient data destination must be predefined to CICS.

For further information on work files, see *Natural Print and Work Files under CICS* in the *TP Monitor Interfaces* documentation.

Work File Name under Com-plete/SMARTS

Under Com-plete with access method `AM=SMARTS`, PFS files are available. Any work file name can be assigned, even if it has not been defined to Natural. For example:

```
DEFINE WORK (14) '/nat/path/workfile'
DEFINE WORK (14) 'workfile'
```

It depends on the `MOUNT_FS` parameter of SMARTS whether the file is located on a SMARTS portable file system or on the native file system. The first element of the path (*/nat/*) determines the target file system.

If the string does not start with a slash (/), the path of the file is taken from the environment variable `$NAT_WORK_ROOT`.

The specified path name must exist. When the `DEFINE WORK FILE` statement is executed, the file is allocated dynamically. If the specified member does not exist, a new member of that name will be created.

VIII

■ 60 DELETE	443
■ 61 DELETE (SQL)	447
■ 62 DISPLAY	451
■ 63 DIVIDE	473
■ 64 DO/DOEND	479
■ 65 DOWNLOAD PC FILE	483
■ 66 EJECT	489
■ 67 END	495
■ 68 END TRANSACTION	499
■ 69 ESCAPE	505
■ 70 EXAMINE	511
■ 71 EXPAND	533

60

DELETE

■ Function	444
■ Restriction	444
■ Syntax Description	444
■ Database-Specific Considerations	445
■ Examples	445

DELETE [RECORD] [IN] [STATEMENT] [(*r*)]

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [END TRANSACTION](#) | [FIND](#) | [GET](#) | [GET SAME](#) | [GET TRANSACTION DATA](#) | [HISTOGRAM](#) | [LIMIT](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [RETRY](#) | [STORE](#) | [UPDATE](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The `DELETE` statement is used to delete a record from a database.

Hold Status

The use of the `DELETE` statement causes each record selected in the corresponding [FIND](#) or [READ](#) statement to be placed in exclusive hold.

Record hold logic is explained in the section *Database Update - Transaction Processing* (in the *Programming Guide*).

Restriction

A `DELETE` statement cannot be specified in the same statement line as a [FIND](#), [READ](#), or [GET](#) statement.

Syntax Description

Syntax Element	Description
(<i>r</i>)	Statement Reference: The notation (<i>r</i>) is used to reference the statement which was used to select/read the record to be deleted. If no statement reference is specified, the <code>DELETE</code> statement will reference the innermost active processing loop in which a database record was selected/read.

Database-Specific Considerations

DL/I Databases	The DELETE statement is used to delete a segment from a DL/I database, which also results in the deletion of all descendants of the segment. Due to GSAM restrictions, the UPDATE statement cannot be used for GSAM databases.
VSAM Databases	The DELETE statement is not valid for VSAM entry-sequenced data sets (ESDS).
SQL Databases	The DELETE statement is used to delete a row from the database table. It corresponds with the SQL statement <code>DELETE WHERE CURRENT OF CURSOR-NAME</code>, that is, only the row which was read last can be deleted. With most SQL databases, a row that was read with a FIND SORTED BY or READ LOGICAL statement cannot be deleted.

Examples

- [Example 1](#)
- [Example 2](#)

Example 1

In this example, all records with the name ALDEN are deleted.

```

** Example 'DELEX1': DELETE
**
**
CAUTION: Executing this example will modify the database records!
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
END-DEFINE
*
FIND EMPLOY-VIEW WITH NAME = 'ALDEN'
/*
DELETE
END TRANSACTION
/*
AT END OF DATA
  WRITE NOTITLE *NUMBER 'RECORDS DELETED'
END-ENDDATA
END-FIND
END

```

Example 2

If no records are found in the VEHICLES file for the person named ALDEN, the EMPLOYEE record for ALDEN is deleted.

```
** Example 'DELEX2': DELETE
**
**
CAUTION: Executing this example will modify the database records!
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
1 VEHIC-VIEW VIEW OF VEHICLES
  2 PERSONNEL-ID
END-DEFINE
*
EMPL. FIND EMPLOY-VIEW WITH NAME = 'ALDEN'
/*
  VEHIC. FIND VEHIC-VIEW WITH PERSONNEL-ID = PERSONNEL-ID (EMPL.)
    IF NO RECORDS FOUND
      /*
        DELETE (EMPL.)
      /*
    END TRANSACTION
  END-NOREC
END-FIND
/*
END-FIND
END
```

61

DELETE (SQL)

■ Function	448
■ Syntax 1 - Searched DELETE	448
■ Syntax 2 - Positioned DELETE	450

Belongs to Function Group: [Database Access and Update](#)

See also *DELETE - SQL* in the *Natural for DB2* part of the *Database Management System Interfaces* documentation:

Function

The SQL `DELETE` statement is used to delete either rows in a table without using a cursor (“**searched**” `DELETE`) or rows in a table to which a cursor is positioned (“**positioned**” `DELETE`).

Two different structures are possible.

Syntax 1 - Searched DELETE

The “searched” `DELETE` statement is a stand-alone statement not related to any `SELECT` statement. With a single statement you can delete zero, one, multiple or all rows of a table. The rows to be deleted are determined by a *search-condition* that is applied to the table. Optionally, the table name can be assigned a *correlation-name*.



Note: The number of rows that have actually been deleted with a “searched” `DELETE` can be ascertained by using the system variable `*ROWCOUNT`; see *System Variables* documentation.

Common Set Syntax:

```
DELETE FROM table-name [correlation-name] [WHERE search-condition]
```

Extended Set Syntax:

```
DELETE FROM table-name [period-clause] [correlation-name]  
[include-columns [SET assignment-clause]]  
[WHERE search-condition]  
[  
    WITH {  
        RR  
        RS  
        CS  
    }  
] [SKIP LOCKED DATA] [QUERYNO integer]
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Syntax Element Description:

Syntax Element	Description	
FROM <i>table-name</i>	FROM Clause: This clause specifies the table from which the rows are to be deleted.	
<i>period-clause</i>	Period Clause: Specifies that a period clause applies to the target of the update operation. For further information, see Period Clause in the section <i>Basic Syntactical Items</i> .	
<i>correlation-name</i>	Correlation Name: Optional. The table name can be assigned a <i>correlation-name</i> .	
<i>include-columns</i>	Include Columns Clause: Optional. Specifies a set of columns that are included, along with the columns of <i>table-name</i> , in the result table of the DELETE statement, when it is nested in the FROM clause of a SELECT statement. For further details, see include-columns .	
SET <i>assignment-clause</i>	SET Assignment Clause: Introduces the assignment of values to the included columns of the <i>include-columns</i> clause. See assignment clause of SQL UPDATE statement.	
WHERE <i>search-condition</i>	WHERE Clause: This clause is used to specify the selection criteria for the rows to be deleted. If no WHERE clause is specified, the entire table is deleted.	
WITH	WITH Isolation Level Clause: This clause belongs to the SQL Extended Set . This clause enables the explicit specification of the isolation level used when locating the row to be deleted.	
	CS	Cursor Stability
	RR	Repeatable Read
	RS	Read Stability
SKIP LOCKED DATA	SKIP LOCKED DATA Clause: This clause specifies that rows are skipped when incompatible locks are held on the row by other transactions.	
QUERYNO <i>integer</i>	QUERYNO Clause: This clause belongs to the SQL Extended Set . This clause explicitly specifies the number to be used in EXPLAIN output and trace records for this statement. The number is used as QUERYNO column in the PLAN_TABLE for the rows that contain information on this statement.	

Syntax 2 - Positioned DELETE

The “positioned” `DELETE` statement always refers to a cursor within a database loop. Therefore the table referenced by a positioned `DELETE` statement must be the same as the one referenced by the corresponding `SELECT` statement, otherwise an error message is returned. A positioned `DELETE` cannot be used with a non-cursor selection.

The functionality of the positioned `DELETE` statement corresponds to that of the “**native**” **Natural DELETE statement**.

Common Set Syntax:

```
DELETE FROM table-name WHERE CURRENT OF CURSOR [(r)]
```

Extended Set Syntax:

```
DELETE FROM table-name WHERE CURRENT OF CURSOR [(r)] [ FOR ROW { [:]host-variable } OF ROWSET ]
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Syntax Element Description:

Syntax Element	Description
FROM <i>table-name</i> WHERE CURRENT OF CURSOR	FROM Clause: This clause specifies the table from which the rows are to be deleted.
(<i>r</i>)	Statement Reference: The (<i>r</i>) notation is used to reference the statement which was used to select the row to be deleted. If no statement reference is specified, the <code>DELETE</code> statement is related to the innermost active processing loop in which a database record was selected.
FOR ROW ... OF ROWSET	FOR ROW ... OF ROWSET Clause: This clause belongs to the SQL Extended Set . The optional <code>FOR ROW ... OF ROWSET</code> clause for positioned SQL <code>DELETE</code> statements specifies which row of the current rowset has to be deleted. It should only be specified if the <code>DELETE</code> statement is related to a <code>SELECT</code> statement which uses rowset positioning and which has column arrays in its <code>INTO</code> clause, see into-clause . If this clause is omitted, all rows of the current rowset are deleted.

62

DISPLAY

■ Function	452
■ Syntax Description	452
■ Defaults Applicable for a DISPLAY Statement	464
■ Examples	465

DISPLAY [(*rep*)] [*options*] {[/ ...] [*output-format*] *output-element*} ...

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: AT END OF PAGE | AT TOP OF PAGE | CLOSE PRINTER | DEFINE PRINTER EJECT | FORMAT | NEWPAGE | PRINT | SKIP | SUSPEND IDENTICAL SUPPRESS | WRITE | WRITE TITLE | WRITE TRAILER

Belongs to Function Group: [Creation of Output Reports](#)

Function

The DISPLAY statement is used to specify the fields to be output on a report in column format. A column is created for each field and a field header is placed over the column.

 **Note:** The statements WRITE and PRINT can be used to produce output in free (non-column) format.

See also the following topics (in the *Programming Guide*):

- *Report Format and Control*
- *Statements DISPLAY and WRITE*
- *Index Notation for Multiple-Value Fields and Periodic Groups*
- *Column Headers*
- *Layout of an Output Page*

Syntax Description

Syntax Element	Description
(<i>rep</i>)	Report Specification: The notation (<i>rep</i>) may be used to specify the identification of the report for which the DISPLAY statement is applicable. As report identification, a value in the range 0 - 31 or a logical name which has been assigned using the DEFINE PRINTER statement may be specified. If (<i>rep</i>) is not specified, the statement will apply to the first report (Report 0). If this printer file is defined to Natural as PC, the report will be downloaded to the PC, see Example 8.

Syntax Element	Description
	For information on how to control the format of an output report created with Natural, see <i>Report Format and Control</i> in the <i>Programming Guide</i> .
<i>options</i>	Display Options: For details, see Display Options below.
<i>output-format</i>	Output Format Definitions: For details, see Output Format Definitions below.
/	Line Advance - Slash Notation: When specified within a text element, a slash (/) causes a line advance for the text displayed. When specified between output elements, it causes the output element specified by the slash (/) to be placed vertically within the same column. The header for this column will be constructed by placing the headers of the vertically displayed elements vertically above the column. See also the following topics in the <i>Programming Guide</i> : ■ <i>Line Advance - Slash Notation</i> ■ <i>Example 1 - Line Advance in DISPLAY Statement</i> ■ <i>Suppressing Column Headers - Slash Notation</i>
<i>output-element</i>	Output Element: For details, see Output Element below.

Display Options

```
[NOTITLE] [NOHDR] [ [AND] [GIVE] [SYSTEM] FUNCTIONS ] [(statement-parameters)]
```

Syntax Element Description:

Syntax Element	Description
NOTITLE	Default Page Title Suppression: By default, Natural generates a single title line for each page resulting from a DISPLAY statement. This title contains the page number, the time of day, and the date. Time of day is set at the beginning of the program execution (TP mode) or at the beginning of the job (batch mode). The default title line may be overridden by using a WRITE TITLE statement, or it may be suppressed by specifying the keyword NOTITLE in the DISPLAY statement. Examples:

Syntax Element	Description
	■ Default title will be produced: <pre>DISPLAY NAME</pre> ■ User title will be produced: <pre>DISPLAY NAME WRITE TITLE 'user-title'</pre> ■ No title will be produced: <pre>DISPLAY NOTITLE NAME</pre> Note: If the NOTITLE option is used, it applies to all DISPLAY, PRINT and WRITE statements within the same object which write data to the same report.
NOHDR	Column Headers: Column headers are produced for each field specified in the DISPLAY statement using the following rules: ■ The header text may be explicitly specified in the DISPLAY statement before the field name. For example: <pre>DISPLAY 'EMPLOYEE' NAME 'SALARY' SALARY</pre> ■ If you do not specify an explicit header for a field, the header as defined in the DEFINE DATA statement will be used. ■ If for a database field no header is defined in the DEFINE DATA statement, the default header as defined in the DDM will be used. ■ If no default header is defined in the DDM, the field name will be used as header. ■ If for a user-defined variable no header is defined in the DEFINE DATA statement, the variable name will be used as header. See also the DEFINE DATA statement for header definition. <pre>DISPLAY NAME SALARY #NEW-SALARY</pre> ■ Natural always underlines column headings and generates one blank line between the underlining and the data being displayed. ■ If there are multiple DISPLAY statements in a program, the first DISPLAY statement determines the column header(s) to be used; this is evaluated at compilation time. Column Header Suppression: To suppress the column header for a single field

Syntax Element	Description
	■ Specify the following characters (apostrophe-slash-apostrophe) before the field name: <pre>' / '</pre> For example: <pre>DISPLAY ' / ' NAME 'SALARY' SALARY</pre> To suppress all column headers ■ Specify the keyword NOHDR: <pre>DISPLAY NOHDR NAME SALARY</pre> Note: 1. NOHDR only takes effect for the first DISPLAY statement, as subsequent DISPLAY statements cannot create column headers anyhow. 2. If both NOTITLE and NOHDR are used, they must be specified in the following order: DISPLAY NOTITLE NOHDR NAME SALARY
GIVE SYSTEM FUNCTIONS	Natural System Function Usage: The GIVE SYSTEM FUNCTIONS clause is used to make available the following Natural system functions: AVER, COUNT, MAX, MIN, NAVER, NCOUNT, NMIN, SUM, TOTAL. These are evaluated when the DISPLAY statement containing the GIVE SYSTEM FUNCTIONS clause is executed. These functions may then be referred to in a statement executed as a result of an end-of-page condition. Note: 1. Only one DISPLAY statement per report may contain a GIVE SYSTEM FUNCTIONS clause. When system functions are evaluated from a DISPLAY statement, they are evaluated on a page basis, which means that all functions (except TOTAL) are reset to zero when a new page is initiated. 2. When system functions are used within a DISPLAY statement within a subroutine, the end-of-page processing must occur within the same routine. 3. In place of the keyword GIVE, the keyword GIVING may be used. See also Example 2 - DISPLAY Statement Using GIVE SYSTEM FUNCTIONS Clause.
statement-parameters	Parameter Definition at Statement Level:

Syntax Element	Description
	One or more parameters, enclosed within parentheses, may be specified at statement level, that is, immediately after the <code>DISPLAY</code> statement. Each parameter specified will override the corresponding parameter previously specified in a <code>GLOBALS</code> command, SET GLOBALS (Reporting Mode only) or FORMAT statement. If more than one parameter is specified, they must be separated by one or more blanks from one another. Each parameter specification must not be split between two statement lines. Note: The parameter settings applied here will only be regarded for variable fields, but they have no effect on text-constants. If you would like to set field attributes for a text-constant, they have to be set explicitly for this element, see Parameter Definition at Element (Field) Level. See also: ■ List of Parameters ■ Example of Parameter Usage at Statement and Element (Field) Level ■ Example 7 - DISPLAY Statement Using Parameters on Statement/Element Level

List of Parameters

The following parameters can be specified with the `DISPLAY` statement

Parameter Name	Explanation	Specification possible at statement level (S), at element level (E) or both (SE)
AD	Attribute Definition	SE
AL	Alphanumeric Length for Output	SE
BX	Box Definition	SE
CD	Color Definition	SE
CV	Control Variable	SE
DF	Date Format	SE
DL	Display Length for Output	SE
DY	Dynamic Attributes	SE
EM	Edit Mask	SE
EMU	Unicode Edit Mask	E
ES	Empty Line Suppression	S
FC	Filler Character	SE
FL	Floating Point Mantissa Length	SE

Parameter Name	Explanation	Specification possible at statement level (S), at element level (E) or both (SE)
GC	Filler Character for Group Headers	SE
HC	Header Centering	SE
HW	Heading Width	SE
IC	Insertion Character	SE
ICU	Unicode Insertion Character	SE
IS	Identical Suppress	SE
LC	Leading Characters	SE
LCU	Unicode Leading Characters	SE
LS	Line Size	S
MC	Multiple-Value Field Count	S
MP	Maximum Number of Pages of a Report	S
NL	Numeric Length for Output	SE
PC	Periodic Group Count	S
PM	Print Mode	SE
PS	Page Size	S
SF	Spacing Factor	SE
SG	Sign Position	SE
TC	Trailing Characters	SE
TCU	Unicode Trailing Characters	SE
UC	Underlining Character	SE
ZP	Zero Printing	SE

The individual parameters are described in the *Parameter Reference* (session parameters).


See also the following topics in the *Programming Guide*:

- *Centering of Column Headers - HC Parameter*
- *Width of Column Headers - HW Parameter*
- *Filler Characters for Headers - Parameters FC and GC*
- *Underlining Character for Titles and Headers - UC Parameter*

Example of Parameter Usage at Statement and Element (Field) Level

```
DEFINE DATA LOCAL
1 VARI (A4)      INIT <'1234'>          /*      Output
END-DEFINE      /*      Produced
*              /*      -----
DISPLAY NOHDR    'Text'                  '='  VARI      /*      Text 1234
DISPLAY NOHDR (PM=I) 'Text'              '='  VARI      /*      Text 4321
DISPLAY NOHDR    'Text' (PM=I)           '='  VARI (PM=I)/*      txeT 4321
DISPLAY NOHDR    'Text' (PM=I)           '='  VARI      /*      txeT 1234
END
```

Output Format Definitions



Field Positioning Notations

Syntax Element	Description
nX	Column Spacing: This notation inserts n spaces between columns. n must not be zero. Example: <pre>DISPLAY NAME 5X SALARY</pre> See also: ■ Example 1 - DISPLAY Statement Using nX and nT Notation (below) ■ Column Spacing - SF Parameter and nX Notation (in the Programming Guide)
nT	Tab Setting: The nT notation causes positioning (tabulation) to display position n. Backward positioning is not permitted.

Syntax Element	Description
	In the following example, NAME is displayed beginning in position 25, and SALARY beginning in position 50: <pre>DISPLAY 25T NAME 50T SALARY</pre> See also: ■ Example 1 - DISPLAY Statement Using nX and nT Notation (below) ■ Tab Setting - nT Notation (in the <i>Programming Guide</i>)
<i>x/y</i>	x/y Positioning: The <i>x/y</i> notation causes the next element to be placed <i>x</i> lines below the output of the last statement, beginning in column <i>y</i>. <i>y</i> must not be zero. Backward positioning is not permitted.
<i>T*field-name</i>	Field Related Positioning: The <i>T*</i> notation is used to position to a specific print position of a field used in a previous DISPLAY statement. Backward positioning is not permitted.
<i>P*field-name</i>	Field and Line Related Positioning: The <i>P*</i> notation is used to position to a specific print position and line of a field used in a previous DISPLAY statement. It is most often used in conjunction with vertical display mode. Backward positioning is not permitted. See also: ■ Example 3 - DISPLAY Statement Using P* Notation (below) ■ Tab Notation P*field (in the <i>Programming Guide</i>)

Override Column Heading Assignment

Syntax Element	Description
'text'	Text Assignment:
'/'	If placed immediately before a field, the text enclosed by single quotes overrides the column heading. The slash character '/' before a field causes the header for the field to be suppressed.

Syntax Element	Description
	DISPLAY 'EMPLOYEE' NAME 'MARITAL/STATUS' MAR-STAT If multiple ' <i>text</i> ' elements are specified before a field name, the <i>last</i> ' <i>text</i> ' element will be used as the column header and the other text elements will be placed before the value of the field within the column. See also: ■ <i>Define Your Own Column Headers (in the Programming Guide)</i> ■ <i>Text Notation, Defining a Text to Be Used with a Statement (in the Programming Guide)</i> ■ Example 4 - DISPLAY Statement Using 'text', 'c(n)' and Attribute Notation
' <i>c</i> ' (<i>n</i>)	Character Repetition: The character enclosed by single quotes is displayed <i>n</i> times immediately before the field value. For example: DISPLAY '*' (5) '=' NAME results in ***** SMITH See also: ■ <i>Text Notation, Defining a Character to Be Displayed <i>n</i> Times before a Field Value (in the Programming Guide)</i> ■ Example 4 - DISPLAY Statement Using 'text', 'c(n)' and Attribute Notation

Output Attributes

attributes indicates the output attributes to be used for text display. Attributes can be:

AD=<i>ad-value</i> ... BX=<i>bx-value</i> ... CD=<i>cd-value</i> PM=<i>pm-value</i>
<i>ad-value</i> <i>cd-value</i> ...

Where:

ad-value, *bx-value*, *cd-value* and *pm-value* denote the possible values of the corresponding session parameters AD, BX, CD and PM described in the relevant sections of the *Parameter Reference* documentation.

The compiler actually accepts more than one attribute value for an output field. For example, you can specify: AD=BDI. In such a case, however, only the last value applies. In the given example, only the value I becomes effective and the output field is displayed intensified.

For an alphanumeric/Unicode constant (Natural data format A or U), you can specify *ad-value* and/or *cd-value* without preceding CD= or AD=, respectively. The single value entered is then checked against all possible CD values first. For example: a value of IRE will be interpreted as intensified/red but not as intensified/right-justified/mandatory. You cannot combine a single *cd-value* or *ad-value* with a value preceded by CD= or AD=.

Vertical/Horizontal Display

The VERT clause may be used to cause multiple field values to be positioned underneath one another in the same column. In vertical mode, a new column may be initiated by specifying the keyword VERT or HORIZ.

The column heading in vertical mode is controlled using the entry or entries specified with the AS clause as described below.

Syntax Element	Description
<u>VERTICALLY</u>	DISPLAY VERT without AS Clause: Vertical column orientation. No column heading is produced if the AS clause is omitted. <pre>DISPLAY VERT NAME SALARY</pre> For an example, see <i>DISPLAY VERT without AS Clause</i> in the <i>Programming Guide</i>.
AS 'text'	DISPLAY VERT AS 'text' Clause: Vertical column orientation. If AS 'text' is specified, the text enclosed by single quotes is used as the column heading. For an example, see <i>DISPLAY VERT AS 'text'</i> in the <i>Programming Guide</i>. The slash character / in the character string of 'text' will cause multiple lines of column headings. <pre>DISPLAY VERT AS 'LAST/NAME' NAME</pre>

Syntax Element	Description
AS 'text' CAPTIONED	DISPLAY VERT AS 'text' CAPTIONED Clause: Vertical column orientation. If AS 'text' CAPTIONED is specified, 'text' is used as the column heading and the standard heading text or field name is inserted immediately before the field value in each detail display line. DISPLAY VERT AS 'PERSONS/SELECTED' CAPTIONED NAME FIRST-NAME For an example, see <i>DISPLAY VERT AS 'text' CAPTIONED</i> in the <i>Programming Guide</i> .
AS CAPTIONED	DISPLAY VERT AS CAPTIONED Clause: Vertical column orientation. If AS CAPTIONED is specified, the standard heading text for the field (either heading text or the field name) will be used as the column heading. DISPLAY VERT AS CAPTIONED NAME FIRST-NAME
<u>HORIZONTALLY</u>	DISPLAY HORIZ Clause: Horizontal column orientation. This is the default display mode.

Vertical and horizontal column orientation may be intermixed by using the respective keyword.

To suspend vertical display for a single output element, you may place a dash (-) in front of the element. For example:

```
DISPLAY VERT NAME - FIRST-NAME SALARY
```

In the above example, FIRST-NAME will be output horizontally next to NAME, while SALARY will be output vertically again, i.e. below NAME.

The standard display mode is horizontal. A column is constructed for each field to be displayed.

Column headings are obtained and used by Natural according to the following priority:

1. heading 'text' supplied in the DISPLAY statement;
2. the default heading defined in the DDM (database fields), or the name of a user-defined variable;
3. the field name as defined in the DDM (if no heading text was defined for the database field).

For group names, a group heading is produced for the entire group. When specifying a group, only the heading for the entire group may be overridden by a user-specified heading.

The maximum number of column header lines is 15.

Line size overflow is not permitted for output resulting from a DISPLAY statement. If a line overflow occurs, an error message is issued.

For more information about vertical/horizontal display usage, see:

- *Example 5 - DISPLAY Statement Using Horizontal Display*
- *Example 6 - DISPLAY Statement Using Vertical and Horizontal Display*
- *DISPLAY VERT AS CAPTIONED and HORIZ (in the Programming Guide)*

Output Element

$\left[\begin{array}{l} \{ \text{'text' [(attributes)]} \} \\ \{ \text{'c'(n) [(attributes)]} \} \dots \\ nX \\ nT \\ x/y \end{array} \right] \quad [='] \{ operand1 [(parameters)] \}$

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	S A G N	A N P I F B D T L G O	yes	no

Syntax Element Description

Syntax Element	Description
<i>nX</i>	Column Spacing: This is the same as under <i>Output Format Definitions</i> (see above).
<i>nT</i>	Tab Setting: This is the same as under <i>Output Format Definitions</i> (see above).
<i>x/y</i>	x/y Positioning: This is the same as under <i>Output Format Definitions</i> (see above).
<i>'text'</i>	Text Assignment: This is the same as under <i>Output Format Definitions</i> (see above).
<i>'c'(n)</i>	Character Repetition: This is the same as under <i>Output Format Definitions</i> (see above).

Syntax Element	Description
'text' '=' 'c' (n) '=' DISPLAY '*****' '=' NAME	If 'text' '=' is placed immediately before the field, <i>text</i> is output immediately before the field value. This applies analogously with 'c' (n) '='. DISPLAY '*****' '=' NAME
<i>attributes</i>	Output Attributes: This is the same as under <i>Output Attributes</i> (see above).
<i>operand1</i>	The field to be displayed. Note: For DL/I databases: The DL/I AIX fields can be displayed only if a PCB is used with the AIX specified in the parameter PROCSEQ. Otherwise, an error message is returned by Natural at runtime.
<i>parameters</i>	Parameter Definition at Element (Field) Level: One or more parameters, enclosed within parentheses, may be specified at element (field) level, that is, immediately after <i>operand1</i> . Each parameter specified in this manner will override the corresponding parameter previously specified at statement level or in a GLOBALS command, SET GLOBALS (in Reporting Mode only) or FORMAT statement. If more than one parameter is specified, one or more blanks must be placed between each entry. An entry must not be split between two statement lines. See also: ■ List of Parameters ■ Example of Parameter Usage at Statement and Element (Field) Level

Defaults Applicable for a DISPLAY Statement

The following defaults are applicable for a DISPLAY statement:

■ Report Width

The width of the report defaults to the value set when Natural is installed. This default value is normally 132 in batch mode or the line length of the terminal in TP mode. It may be overridden with the session parameter LS. In TP mode, line size (LS) and page size (PS) parameters are set by Natural based on the physical characteristics of the terminal type in use.

■ Terminal Screen Output

When the DISPLAY output is displayed on a terminal (emulation) screen, the output begins in physical Column 2 (because Column 1 must be reserved for possible use as an attribute position on a 3270-type terminal).

■ Printout on Paper

When the `DISPLAY` output is printed on paper, the printout begins in the leftmost column (Column 1).

■ Spacing Factor

The default spacing factor between elements is one position. There is a minimum of one space between columns (reserved for terminal attributes). This default may be overridden with the session parameter `SF`.

■ Field Output

The length of the field or the field heading, whichever is greater, determines the column width for the report (unless the `HW` parameter is used).

- If the field is longer than the heading, the heading will be centered over the column unless the `HC=L` or `HC=R` parameter is used to produce a left-justified or right-justified heading.
- If the heading is longer than the field, the field will be left-justified under the heading.
- The values contained in the field are left-justified for alphanumeric fields and right-justified for numeric fields.
- Numeric fields may be displayed left-justified by specifying `AD=L`.
- Alphanumeric fields may be displayed right-justified by specifying `AD=R`.
- In a vertical display, the longest data value or heading among all fields determines the column width (unless the `HW` parameter is used).

■ Sign

One extra high-order print position is reserved for a sign when printing a numeric field. The session parameter `SG` may be used to suppress the sign position.

■ Page Overflow

Page overflow is checked before execution of a `DISPLAY` statement. No new page title or trailer information is generated during the execution of a `DISPLAY` statement.

Examples

- [Example 1 - DISPLAY Statement Using nX and nT Notation](#)
- [Example 2 - DISPLAY Statement Using GIVE SYSTEM FUNCTIONS Clause](#)
- [Example 3 - DISPLAY Statement Using P* Notation](#)
- [Example 4 - DISPLAY Statement Using 'text ', 'c\(n\)' and Attribute Notation](#)
- [Example 5 - DISPLAY Statement Using Horizontal Display](#)
- [Example 6 - DISPLAY Statement Using Vertical and Horizontal Display](#)
- [Example 7 - DISPLAY Statement Using Parameters on Statement/Element Level](#)

- [Example 8 - Report Specification with Output File Defined to Natural as PC](#)

Example 1 - DISPLAY Statement Using nX and nT Notation

```
** Example 'DISEX1': DISPLAY (with nX, nT notation)
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 JOB-TITLE
END-DEFINE
*
LIMIT 4
READ EMPL-VIEW BY NAME
  DISPLAY NOTITLE 5X NAME 50T JOB-TITLE
END-READ
*
END
```

Output of Program DISEX1:

NAME	CURRENT POSITION
-----	-----
ABELLAN	MAQUINISTA
ACHIESON	DATA BASE ADMINISTRATOR
ADAM	CHEF DE SERVICE
ADKINSON	PROGRAMMER

Example 2 - DISPLAY Statement Using GIVE SYSTEM FUNCTIONS Clause

```
** Example 'DISEX2': DISPLAY (with GIVE SYSTEM FUNCTIONS)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
  2 FIRST-NAME
  2 SALARY (1)
  2 CURR-CODE (1)
END-DEFINE
*
LIMIT 15
FORMAT PS=15
*
READ EMPLOY-VIEW
  DISPLAY GIVE SYSTEM FUNCTIONS
    PERSONNEL-ID NAME FIRST-NAME SALARY (1) CURR-CODE (1)
  AT END OF PAGE
```



```

WRITE / 'SALARY STATISTICS:'
      / 7X 'MAXIMUM:' MAX(SALARY(1)) CURR-CODE (1)
      / 7X 'MINIMUM:' MIN(SALARY(1)) CURR-CODE (1)
      / 7X 'AVERAGE:' AVER(SALARY(1)) CURR-CODE (1)
END-ENDPAGE
END-READ
*
END

```

Output of Program DISEX2:

```

Page      1                                05-01-12  09:47:48

PERSONNEL      NAME      FIRST-NAME      ANNUAL      CURRENCY
  ID                                SALARY      CODE
-----
50005500  BLOND      ALEXANDRE      172000  FRA
50005300  MAIZIERE      ELISABETH      166900  FRA
50004900  CAUDAL      ALBERT      167350  FRA
50004600  VERDIE      BERNARD      170100  FRA
50004200  VAUZELLE      BERNARD      159790  FRA
50004100  CHAPUIS      ROBERT      169900  FRA
50003800  JOUSSELIN      DANIEL      171990  FRA
50006900  BAILLET      PATRICK      188000  FRA
50007600  MARX      JEAN-MARIE      365700  FRA

SALARY STATISTICS:
      MAXIMUM:      365700  FRA
      MINIMUM:      159790  FRA
      AVERAGE:      192414  FRA

```

Example 3 - DISPLAY Statement Using P* Notation

```

** Example 'DISEX3': DISPLAY (with P* notation)
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 SALARY (1)
  2 BIRTH
  2 CITY
END-DEFINE
*
LIMIT 2
READ EMPL-VIEW BY CITY FROM 'N'
  DISPLAY NOTITLE NAME CITY
    VERT AS 'BIRTH/SALARY' BIRTH (EM=YYYY-MM-DD) SALARY (1)
  SKIP 1
  AT BREAK OF CITY
    DISPLAY P*SALARY (1) AVER(SALARY (1))

```

```

SKIP 1
END-BREAK
END-READ
END

```

Output of Program DISEX3:

NAME	CITY	BIRTH SALARY
-----	-----	-----
WILCOX	NASHVILLE	1970-01-01 38000
MORRISON	NASHVILLE	1949-07-10 36000
		37000

Example 4 - DISPLAY Statement Using 'text ', 'c(n)' and Attribute Notation

```

** Example 'DISEX4': DISPLAY (with 'c(n)' notation and attribute)
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 DEPT
  2 LEAVE-DUE
  2 NAME
END-DEFINE
*
LIMIT 4
READ EMPL-VIEW BY DEPT FROM 'T'
  IF LEAVE-DUE GT 40
    DISPLAY NOTITLE
      'EMPLOYEE' NAME /* OVERRIDE STANDARD HEADER
      'LEAVE ACCUMULATED' LEAVE-DUE /* OVERRIDE STANDARD HEADER
      '**(10)(I) /* DISPLAY 10 '** INTENSIFIED

  ELSE
    DISPLAY NAME LEAVE-DUE
  END-IF
END-READ
*
END

```

Output of Program DISEX4:

EMPLOYEE	LEAVE	ACCUMULATED
-----	-----	-----
LAVENDA	33	
BOYER	33	
CORREARD	45	*****
BOUVIER	19	

Example 5 - DISPLAY Statement Using Horizontal Display

```

** Example 'DISEX5': DISPLAY (horizontal display)
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 JOB-TITLE
  2 SALARY      (1:2)
  2 CURR-CODE (1:2)
END-DEFINE
*
LIMIT 4
READ EMPL-VIEW BY NAME
  DISPLAY NOTITLE NAME JOB-TITLE SALARY (1:2) CURR-CODE (1:2)
  SKIP 1
END-READ
*
END

```

Output of Program DISEX5:

NAME	CURRENT POSITION	ANNUAL SALARY	CURRENCY CODE
-----	-----	-----	-----
ABELLAN	MAQUINISTA	1450000 PTA 1392000 PTA	
ACHIESON	DATA BASE ADMINISTRATOR	11300 UKL 10500 UKL	
ADAM	CHEF DE SERVICE	159980 FRA 0	
ADKINSON	PROGRAMMER	34500 USD 31700 USD	

Example 6 - DISPLAY Statement Using Vertical and Horizontal Display

```
** Example 'DISEX6': DISPLAY (vertical and horizontal display)
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 CITY
  2 JOB-TITLE
  2 SALARY      (1:2)
  2 CURR-CODE (1:2)
END-DEFINE
*
LIMIT 1
READ EMPL-VIEW BY NAME
  DISPLAY NOTITLE VERT AS CAPTIONED
    NAME CITY 'POSITION' JOB-TITLE
    HORIZ 'SALARY' SALARY (1:2) 'CURRENCY' CURR-CODE (1:2)
  /*
  SKIP 1
END-READ
END
```

Output of Program DISEX6:

NAME CITY POSITION	SALARY	CURRENCY

ABELLAN	1450000	PTA
MADRID	1392000	PTA
MAQUINISTA		

Example 7 - DISPLAY Statement Using Parameters on Statement/Element Level

```
** Example 'DISEX7': DISPLAY (with parameters for statement/element)
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 PERSONNEL-ID
  2 TELEPHONE
    3 AREA-CODE
    3 PHONE
END-DEFINE
*
LIMIT 3
READ EMPL-VIEW BY NAME
  DISPLAY NOTITLE (AL=16 GC=+ NL=8 SF=3 UC=)
```

```

PERSONNEL-ID NAME TELEPHONE (LC=< TC=>)
END-READ
END

```

Output of Program DISEX7:

PERSONNEL ID	NAME	AREA CODE	TELEPHONE
60008339	ABELLAN	<1 >	<4356726 >
30000231	ACHIESON	<0332 >	<523341 >
50005800	ADAM	<1033 >	<44864858 >

Example 8 - Report Specification with Output File Defined to Natural as PC

```

** Example 'PCDIEX1': DISPLAY and WRITE to PC
**
** NOTE: Example requires that Natural Connection is installed.
*****
DEFINE DATA LOCAL
01 PERS VIEW OF EMPLOYEES
  02 PERSONNEL-ID
  02 NAME
  02 CITY
END-DEFINE
*
FIND PERS WITH CITY = 'NEW YORK'          /* Data selection
  WRITE (7) TITLE LEFT 'List of employees in New York' /
  DISPLAY (7)                             /* (7) designates the output file (here the PC).
    'Location'  CITY
    'Surname'   NAME
    'ID'        PERSONNEL-ID
END-FIND
END

```


63

DIVIDE

■ Function	474
■ Syntax 1 - DIVIDE Statement without GIVING Clause	474
■ Syntax 2 - DIVIDE Statement with GIVING Clause	475
■ Syntax 3 - DIVIDE Statement with REMAINDER Clause	476
■ Example	477

Related Statements: [ADD](#) | [COMPRESS](#) | [COMPUTE](#) | [EXAMINE](#) | [MOVE](#) | [MOVE ALL](#) | [MULTIPLY](#) | [RESET](#) | [SEPARATE](#) | [SUBTRACT](#)

Belongs to Function Group: *Arithmetic and Data Movement Operations*

Function

The `DIVIDE` statement is used to divide an arithmetic expression or operand into two operands.

 **Note:** Concerning Division by Zero: If an attempt is made to use a divisor (*operand1*) which is zero, either an error message or a result equal to zero will be returned; this depends on the setting of the session parameter `ZD` (described in the *Parameter Reference* documentation).

Syntax 1 - DIVIDE Statement without GIVING Clause

`DIVIDE` `[ROUNDED]` { *(arithmetic-expression)* } INTO *operand2*
operand1

For explanations of the symbols used in the syntax diagrams, see *Syntax Symbols*.

Operand Definition Table:

Operand	Possible Structure			Possible Formats			Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S	A	N	N	P I F	yes	no
<i>operand2</i>		S	A	M	N	P I F	yes	no

Syntax Element Description:

Syntax Element	Description
<i>arithmetic-expression</i>	See <i>Arithmetic Expression</i> in the <code>COMPUTE</code> statement.
<i>operand1</i> INTO <i>operand2</i>	Operands: <i>operand1</i> is the divisor, <i>operand2</i> is the dividend. The result is stored in <i>operand2</i> (result field), hence the statement is equivalent to:

Syntax Element	Description
	$operand2 := operand2 / operand1$ If an <i>arithmetic-expression</i> is used, <i>operand2</i> must not be an array range. The number of decimal positions for the result of the division is evaluated from the result field (that is, <i>operand2</i>). For the precision of the result, see <i>Rules for Arithmetic Assignments, Precision of Results of Arithmetic Operations</i> in the <i>Programming Guide</i>.
ROUNDED	ROUNDED Option: If you specify the keyword <code>ROUNDED</code>, the result will be rounded. For information on rounding, see <i>Rules for Arithmetic Assignment, Field Truncation and Field Rounding</i> in the <i>Programming Guide</i>.

Syntax 2 - DIVIDE Statement with GIVING Clause

DIVIDE [ROUNDED]	{ <i>(arithmetic-expression)</i> <i>operand1</i> }	INTO	{ <i>(arithmetic-expression)</i> <i>operand2</i> }	GIVING <i>operand3</i>

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition	
<i>operand1</i>	C	S	A		N			N	P	I	F						yes	no
<i>operand2</i>	C	S	A		N			N	P	I	F						yes	no
<i>operand3</i>		S	A			A	U	N	P	I	F	B*					yes	yes

* Format B of *operand3* may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
<i>arithmetic-expression</i>	See Arithmetic Expression in the <code>COMPUTE</code> statement.
<i>operand1</i> INTO <i>operand2</i> GIVING <i>operand3</i>	Operands: <i>operand1</i> is the divisor, <i>operand2</i> is the dividend. The result of the division is stored in <i>operand3</i>, hence the statement is equivalent to:

Syntax Element	Description
	$operand3 := operand2 / operand1$ The number of decimal positions for the result of the division is evaluated from the result field (that is, <i>operand3</i>). For the precision of the result, see <i>Rules for Arithmetic Assignments, Precision of Results of Arithmetic Operations</i> in the <i>Programming Guide</i>.
ROUNDED	ROUNDED Option: If you specify the keyword <code>ROUNDED</code>, the result will be rounded. For information on rounding, see <i>Rules for Arithmetic Assignment, Field Truncation and Field Rounding</i> in the <i>Programming Guide</i>.

Syntax 3 - DIVIDE Statement with REMAINDER Clause

DIVIDE	{	(<i>arithmetic-expression</i>)	}	INTO	{	(<i>arithmetic-expression</i>)	}	[GIVING <i>operand3</i>]
		<i>operand1</i>				<i>operand2</i>		REMAINDER <i>operand4</i>

For explanations of the symbols used in the syntax diagrams, see [Syntax Symbols](#).

Operand Definition Table:

Operand	Possible Structure				Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S	A	N	N P I	yes	no
<i>operand2</i>	C	S	A	N	N P I	yes	no
<i>operand3</i>		S	A		A U N P I F B* T	yes	yes
<i>operand4</i>		S	A		A U N P I F B* T	yes	yes

* Format B of *operand3* and *operand4* may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
<i>arithmetic-expression</i>	See Arithmetic Expression in the <code>COMPUTE</code> statement.
<i>operand1</i> <i>operand2</i>	Operands: <i>operand1</i> is the divisor, <i>operand2</i> is the dividend. If the <code>GIVING</code> clause is not used, the result is stored in <i>operand2</i>.

Syntax Element	Description
	If <i>operand2</i> is a constant or a non-modifiable Natural system variable, the GIVING clause is required.
GIVING <i>operand3</i>	GIVING Clause: If this clause is used, <i>operand2</i> will not be modified and the result will be stored in <i>operand3</i>. The number of decimal positions for the result of the division is evaluated from the result field (that is, <i>operand2</i> if no GIVING clause is used, or <i>operand3</i> if the GIVING clause is used). For the precision of the result, see <i>Rules for Arithmetic Assignments, Precision of Results of Arithmetic Operations</i> (in the <i>Programming Guide</i>).
REMAINDER <i>operand4</i>	REMAINDER Clause: The remainder of the division is placed into the field specified in <i>operand4</i>. ■ If the GIVING clause is used, the statement is equivalent to: <pre>operand3 := operand2 / operand1 operand4 := operand2 - (operand3 * operand1)</pre> None of the four operands may be an array range. ■ If the GIVING clause is not used, the statement is equivalent to: <pre>temporary := operand2 operand2 := operand2 / operand1 operand4 := temporary - (operand2 * operand1)</pre> where <i>temporary</i> is a temporary field with the same format/length as <i>operand2</i>. For each of these steps, the rules described in <i>Precision of Results of Arithmetic Operations</i> in the <i>Programming Guide</i> apply.

Example

```
** Example 'DIVEX1': DIVIDE
*****
DEFINE DATA LOCAL
1 #A (N7) INIT <20>
1 #B (N7)
1 #C (N3.2)
1 #D (N1)
1 #E (N1) INIT <3>
1 #F (N1)
```

```
END-DEFINE
*
DIVIDE 5 INTO #A
WRITE NOTITLE 'DIVIDE 5 INTO #A' 20X '=' #A
*
RESET INITIAL #A
DIVIDE 5 INTO #A GIVING #B
WRITE 'DIVIDE 5 INTO #A GIVING #B' 10X '=' #B
*
DIVIDE 3 INTO 3.10 GIVING #C
WRITE 'DIVIDE 3 INTO 3.10 GIVING #C' 8X '=' #C
*
DIVIDE 3 INTO 3.1 GIVING #D
WRITE 'DIVIDE 3 INTO 3.1 GIVING #D' 9X '=' #D
*
DIVIDE 2 INTO #E REMAINDER #F
WRITE 'DIVIDE 2 INTO #E REMAINDER #F' 7X '=' #E '=' #F
*
END
```

Output of Program DIVEX1:

DIVIDE 5 INTO #A	#A:	4
DIVIDE 5 INTO #A GIVING #B	#B:	4
DIVIDE 3 INTO 3.10 GIVING #C	#C:	1.03
DIVIDE 3 INTO 3.1 GIVING #D	#D:	1
DIVIDE 2 INTO #E REMAINDER #F	#E: 1 #F:	1

64

DO/DOEND

■ Function	480
■ Restrictions	480
■ Example	481

DO *statement* ... DOEND

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Belongs to Function Group: [Reporting Mode Statements](#)

Function

The DO and DOEND statements are used in reporting mode to specify a group of statements to be executed based on a logical condition as specified in any of the statements listed below.

- AT BREAK
- AT END OF DATA
- AT END OF PAGE
- AT START OF DATA
- AT TOP OF PAGE
- BEFORE BREAK PROCESSING
- FIND ... IF NO RECORDS FOUND
- IF
- IF SELECTION
- ON ERROR
- READ WORK FILE ... AT END OF FILE



Note: If you specify a only single statement to be executed based on a logical condition, you can omit the DO and DOEND statements. But with respect to good coding practice, you are not recommended to do so.

Restrictions

- The DO and DOEND statements are only valid in reporting mode.
- WRITE TITLE, WRITE TRAILER, and the AT condition statements AT BREAK, AT END OF DATA, AT END OF PAGE, AT START OF DATA, AT TOP OF PAGE are not permitted *within* a DO/DOEND statement group.
- A loop-initiating statement may be used within a DO/DOEND statement group provided that the loop is closed prior to the DOEND statement.

Example

```

** Example 'DOEEX1': DO/DOEND
*****
*
EMP. FIND EMPLOYEES WITH CITY = 'MILWAUKEE'
  VEH. FIND VEHICLES WITH PERSONNEL-ID = PERSONNEL-ID
    IF NO RECORDS FOUND DO
      ESCAPE
    DOEND
    DISPLAY PERSONNEL-ID (EMP.) NAME (EMP.)
      SALARY (EMP.,1)
      MAKE (VEH.) MAINT-COST (VEH.,1)
  AT END OF DATA DO
    WRITE NOTITLE
      / 10X 'AVG SALARY:'
        T*SALARY (1) AVER(SALARY (1))
      / 10X 'AVG MAINTENANCE (ZERO VALUES EXCLUDED):'
        T*MAINT-COST (1) NAVER(MAINT-COST (1))
    DOEND
  /*
LOOP
LOOP
END

```


Output of Program DOEEX1:

PERSONNEL ID	NAME	ANNUAL SALARY	MAKE	MAINT-COST
20021100	JONES	31000	GENERAL MOTORS	140
20027800	LAWLER	29000	GENERAL MOTORS	0
20027800	LAWLER	29000	TOYOTA	86
20030600	NORDYKE	47000	FORD	194
	AVG SALARY:	35666		
	AVG MAINTENANCE (ZERO VALUES EXCLUDED):			140

65

DOWNLOAD PC FILE

■ Function	484
■ Syntax Description	484
■ Examples	485



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [CLOSE PC FILE](#) | [UPLOAD PC FILE](#) | [WRITE WORK FILE](#)

Belongs to Function Group: [Control of Work Files / PC Files](#)

Function

This statement is used to transfer data from a mainframe platform to the PC.

See also the Natural Connection and Entire Connection documentation

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S	A	G		A	U	N	P	I	F	B	D	T	L	C		yes	no
<i>operand2</i>	C	S				A												yes	yes

Neither Format C not G is valid for Natural Connection.

Syntax Element Description:

Syntax Element	Description
<i>work-file-number</i>	Work File Number: The work file number to be used. This number must correspond to one of the work file numbers for the PC as defined to Natural.
VARIABLE	Variable Format: The records in the PC file will be written in variable format. Note that variable records cannot be converted to PC spreadsheet formats.
<i>operand1</i>	Field Specification: With <i>operand1</i> you specify the fields to be downloaded to the PC.

Syntax Element	Description
COMMAND	COMMAND Clause: With the <code>COMMAND</code> clause, you can send PC commands (that is, any command that can be entered in the command line of Entire Connection on the PC) from the mainframe to the PC. Entire Connection checks whether the command sent is valid or not. A command that cannot be recognized by the PC is rejected. In this case, Natural issues the error message that the downloaded command was rejected by the PC. You can use the <code>COMMAND</code> clause, for example, to execute Entire Connection tasks from the mainframe. If you have the task <code>DIR</code> which lists PC directory information, you can initiate this directly out of your Natural program on the mainframe with the following statement: <pre>DOWNLOAD PC FILE 7 COMMAND 'DIR'</pre> In Example 2 below, the <code>COMMAND</code> clause is used to define the name of the PC file that is to receive the downloaded data. In this way, you can avoid prompting for the name of the file.
<i>operand2</i>	COMMAND Specification: With <i>operand2</i>, you specify the DOS command or Entire Connection task that is to be executed on the PC. <i>operand2</i> must be an alphanumeric constant or variable.
SYNC	SYNC Option: With <code>SYNC</code>, you specify that the PC returns control to Natural after executing and terminating <code>COMMAND</code>. <code>SYNC</code> can be used, for example, to ensure that the command <code>SET PCFILE</code> has been executed before a file transfer starts.
ASYN	ASYN Option: With <code>ASYN</code>, you specify that the PC immediately returns control to Natural, regardless of whether the execution of <code>COMMAND</code> has terminated or not.

Examples

- [Example 1 - Use of DOWNLOAD PC FILE Statement](#)

■ [Example 2 - Use of COMMAND Clause](#)

Example 1 - Use of DOWNLOAD PC FILE Statement

The following program demonstrates the use of the `DOWNLOAD PC FILE` statement. The data is first selected and then downloaded to the PC by using Work File 7.

```

** Example 'PCDOEX1': DOWNLOAD PC FILE
**
** NOTE: Example requires that Natural Connection is installed.
*****
DEFINE DATA LOCAL
01 PERS VIEW OF EMPLOYEES
    02 PERSONNEL-ID
    02 NAME
    02 CITY
END-DEFINE
*
FIND PERS WITH CITY = 'NEW YORK'           /* Data selection
    DOWNLOAD PC FILE 7 CITY NAME PERSONNEL-ID /* Data download
END-FIND
END

```

Output of Program PCDOEX1:

When you run the program, a window appears in which you specify the name of the PC file into which the data is to be downloaded. The data is then downloaded to the PC.

Example 2 - Use of COMMAND Clause

The following program demonstrates the use of the `COMMAND` clause in the `DOWNLOAD PC FILE` statement. The name of the receiving PC file is first defined. Then the data is selected and downloaded to this file.

```

** Example 'PCDOEX2': DOWNLOAD PC FILE
**
** NOTE: Example requires that Natural Connection is installed.
*****
DEFINE DATA LOCAL
01 PERS VIEW OF EMPLOYEES
    02 PERSONNEL-ID
    02 NAME
    02 CITY
01 CMD (A80)           /* Variable for transfer
END-DEFINE             /* of the PC command
*
MOVE 'SET PCFILE 7 DOWN DATA PERS.NCD' TO CMD /* PC command to define
*
DOWNLOAD PC FILE 6 COMMAND CMD           /* Command download

```

```
*  
FIND PERS WITH CITY = 'NEW YORK'          /* Data selection  
  DOWNLOAD PC FILE 7 CITY NAME PERSONNEL-ID /* Data download  
END-FIND  
END
```



Note: The PC file number in two successive DOWNLOAD PC FILE statements must be different.

Output of Program PCDOEX2:

When you run the program, the data is downloaded to the PC file that was specified in the program. A window does not appear.

66

EJECT

■ Function	490
■ Syntax Description	490
■ Processing	492
■ Example	492

Related Statements: [AT END OF PAGE](#) | [AT TOP OF PAGE](#) | [CLOSE PRINTER](#) | [DEFINE PRINTER](#) | [DISPLAY](#) | [FORMAT](#) | [NEWPAGE](#) | [PRINT](#) | [SKIP](#) | [SUSPEND IDENTICAL SUPPRESS](#) | [WRITE](#) | [WRITE TITLE](#) | [WRITE TRAILER](#)

Belongs to Function Group: [Creation of Output Reports](#)

Function

The `EJECT` statement may be used to control page advance/page ejection.

Syntax Description

Two different structures are possible for this statement.

- [EJECT - Syntax 1](#)
- [EJECT - Syntax 2](#)

For explanations of the symbols used in the syntax diagrams below, see [Syntax Symbols](#).

EJECT - Syntax 1

EJECT

ON

OFF

}

[

(rep)

]

Syntax Element Description:

Syntax Element	Description	
EJECT ON/OFF (<i>rep</i>)	With Report Specification - Online and Batch Modes:	
	EJECT OFF (<i>rep</i>)	Causes no page advance (except as specified with Syntax 2 of the EJECT statement) for the specified report to be executed.
	EJECT ON (<i>rep</i>)	Causes page advances for the specified report to be executed.
EJECT ON/OFF	Without Report Specification - Batch Mode only: Without report notation (<i>rep</i>), EJECT ON/OFF may be used in batch mode to control page ejection between the output listings created during the execution of a program.	

Syntax Element	Description	
	EJECT ON	Causes Natural to generate a page eject between the source program listing, the output report and the message EXECUTION COMPLETED . This is the default setting.
	EJECT OFF	Causes Natural to suppress page breaks between the above output. EJECT OFF remains in effect until revoked with a subsequent EJECT ON statement.
(rep)	Report Specification: The notation (rep) may be used to specify the identification of the report for which the EJECT statement is applicable. A value in the range 0 - 31 or a logical name which has been assigned using the DEFINE PRINTER statement may be specified. If (rep) is not specified, the EJECT statement will be applicable to the first report (Report 0). For information on how to control the format of an output report created with Natural, see <i>Report Format and Control</i> in the <i>Programming Guide</i> .	

EJECT - Syntax 2

This form of the EJECT statement may be used to cause a page advance without a title or heading line being generated on the next page and without TOP/END PAGE processing.

```
EJECT [( rep )] [ [ IF ] LESS [THAN] operand1 [LINES] [LEFT] ]
```

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
operand1	C	S				N	P	I								yes	no

Syntax Element Description:

Syntax Element	Description
<code>(rep)</code>	Report Specification: The notation <code>(rep)</code> may be used to specify the identification of the report for which the EJECT statement is applicable. A value in the range 0 - 31 or a logical name which has been assigned using the <code>DEFINE PRINTER</code> statement may be specified. If <code>(rep)</code> is not specified, the EJECT statement will be applicable to the first report (Report 0). For information on how to control the format of an output report created with Natural, see <i>Report Format and Control</i> in the <i>Programming Guide</i>.
<code>IF LESS THAN operand1 LINES LEFT</code>	IF LESS THAN ... LINES LEFT Clause: A page advance will be performed only when the current line for the page is greater than the page size minus <code>operand1</code>. The value for <code>operand1</code> may be specified as a numeric constant or as a variable.

Processing

The execution of an EJECT statement does not cause any statements used with an `AT TOP OF PAGE`, `AT END OF PAGE`, `WRITE TITLE` or `WRITE TRAILER` statement to be executed. It does not affect system functions evaluated by `DISPLAY GIVE SYSTEM FUNCTIONS`.

EJECT causes a new physical page only. It causes the Natural system variable `*LINE-COUNT` to be set to 1 but has no effect on the setting of the Natural system variable `*PAGE-NUMBER`.

Example

```
** Example 'EJTEX1': EJECT
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 CITY
  2 NAME
  2 JOB-TITLE
END-DEFINE
*
FORMAT PS=15
LIMIT 9
READ EMPLOY-VIEW BY CITY
/*
AT START OF DATA
```

```

EJECT
WRITE /// 20T '%' (29) /
          20T '%%'                               47T '%%' /
          20T '%%' 3X 'REPORT OF EMPLOYEES' 47T '%%' /
          20T '%%' 3X '  SORTED BY CITY   ' 47T '%%' /
          20T '%%'                               47T '%%' /
          20T '%' (29) /

EJECT
END-START
EJECT WHEN LESS THAN 3 LINES LEFT
/*
WRITE '*' (64)
DISPLAY NOTITLE NOHDR CITY NAME JOB-TITLE 5X *LINE-COUNT
WRITE '*' (64)
END-READ
END

```

Output of Program EJTEX1:

```

%%%%%%%%%%
%%                               %%
%%  REPORT OF EMPLOYEES         %%
%%  SORTED BY CITY             %%
%%                               %%
%%%%%%%%%%

```

After pressing ENTER:

```

*****
AIKEN          SENKO          PROGRAMMER          2
*****
*****
AIX EN OTHE    GODEFROY      COMPTABLE          5
*****
*****
AJACCIO        CANALE        CONSULTANT          8
*****
*****
ALBERTSLUND    PLOUG         KONTORASSISTENT    11
*****
*****
ALBUQUERQUE    HAMMOND       SECRETARY          14
*****

```

After pressing ENTER:

ALBUQUERQUE	ROLLING	MANAGER	2

ALBUQUERQUE	FREEMAN	MANAGER	5

ALBUQUERQUE	LINCOLN	ANALYST	8

ALFRETON	GOLDBERG	JUNIOR	11

67

END

■ Function	496
■ Syntax Description	496
■ Examples	497



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Function

The `END` statement is used to mark the physical end of a Natural program. No symbols may follow the `END` statement.

In reporting mode, any processing loop which is currently active (that is, which has not been closed with a `LOOP` statement) is closed by the `END` statement.

Considerations for Program Execution

When an `END` statement is executed in a main program (that is, a program executing on Level 1), final end-page processing is performed as well as final break processing for user-initiated breaks (`PERFORM BREAK PROCESSING`) which have not been associated with a processing loop by specifying a reference notation (`r`).

When an `END` statement is executed in a subprogram, or in a program invoked with `FETCH RETURN`, control will be returned to the invoking program without any final processing.

Syntax Description

Syntax Element	Description
END	Keyword: The Natural reserved keyword <code>END</code> is normally used to mark the physical end of a Natural program.
.	Period: Instead of the Natural reserved keyword <code>END</code> , a period (<code>.</code>) may be used. It must be preceded by at least one blank if other statements are contained in the same line.

Examples

For some typical examples, see [Examples of DEFINE DATA Statement Usage](#).

68

END TRANSACTION

■ Function	500
■ Restriction	500
■ Syntax Description	501
■ Databases Affected	501
■ Database-Specific Considerations	502
■ Examples	502

`END [OF] TRANSACTION [operand1 ...]`

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [DELETE](#) | [FIND](#) | [GET](#) | [GET SAME](#) | [GET TRANSACTION DATA](#) | [FIND HISTOGRAM](#) | [LIMIT](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [RETRY](#) | [STORE](#) | [UPDATE](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The `END TRANSACTION` statement is used to indicate the end of a logical transaction. A logical transaction is the smallest logical unit of work (as defined by the user) which must be performed in its entirety to ensure that the information contained in the database is logically consistent.

Successful execution of an `END TRANSACTION` statement ensures that all updates performed during the transaction have been or will be physically applied to the database regardless of subsequent user, Natural, database or operating system interruption. Updates performed within a transaction for which the `END TRANSACTION` statement has not been successfully completed will be backed out automatically.

The `END TRANSACTION` statement also results in the release of all records placed in hold status during the transaction.

The `END TRANSACTION` statement can be executed based upon a logical condition.

For further information, see the section *Database Update - Transaction Processing* (in the *Programming Guide*).

Restriction

This statement cannot be used with Entire System Server.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S			N	A	U	N	P	I	F	B	D	T		yes	no

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Storage of Transaction Data: For a transaction applied to an Adabas database, or to a DL/I database in a batch-oriented BMP region (in IMS environments only), you may also use this statement to store transaction-related information. These transaction data must not exceed 2000 bytes. They may be read with a GET TRANSACTION DATA statement. The transaction data are written to the database specified with the profile parameter ETDB. If the ETDB parameter is not specified, the transaction data are written to the database specified with the profile parameter UDB, except on mainframe computers: here, they are written to the database where the Natural Security system file (FSEC) is located (if FSEC is not specified, it is considered to be identical to the Natural system file, FNAT; if Natural Security is not installed, the transaction data are written to the database where FNAT is located). Note: <code>END TRANSACTION</code> cannot be used if <i>operand1</i> is a dynamic variable.

Databases Affected

An `END TRANSACTION` statement *without* transaction data (that is, without *operand1*) will only be executed if a database transaction under control of Natural has taken place. Depending on the setting of the Natural profile parameter ET, the statement will be executed only for the database affected by the transaction (ET=OFF), or for all databases that have been referenced since the last execution of a [BACKOUT TRANSACTION](#) or `END TRANSACTION` statement (ET=ON).

An `END TRANSACTION` statement *with* transaction data (that is, with specifying *operand1*) will always be executed and the transaction data be stored in a database as described in the following section. It depends on the setting of the ET parameter (see above) for which other databases the `END TRANSACTION` statement will be executed.

Database-Specific Considerations

DL/I Databases	Because PSB scheduling is terminated by a Syncpoint request, Natural saves the PSB position before executing the <code>END TRANSACTION</code> statement. Before the next command execution, Natural re-schedules the PSB and tries to set the PCB position as it was before the <code>END TRANSACTION</code> statement. The PCB position might be shifted forward if any pointed segment had been deleted in the time period between the <code>END TRANSACTION</code> and the following command.
VSAM Databases	For information on the transaction logic that applies when accessing VSAM, see <i>Natural for VSAM</i> in the <i>Database Management System Interfaces</i> documentation.
SQL Databases	As most SQL databases close all cursors when a logical unit of work ends, an <code>END TRANSACTION</code> statement must not be placed within a database modification loop; instead, it has to be placed after such a loop.

Examples

- [Example 1 - END TRANSACTION](#)
- [Example 2 - END TRANSACTION with ET Data](#)

Example 1 - END TRANSACTION

```
** Example 'ETREX1': END TRANSACTION
**
** CAUTION: Executing this example will modify the database records!
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 CITY
  2 COUNTRY
END-DEFINE
*
FIND EMPLOY-VIEW WITH CITY = 'BOSTON'
  ASSIGN COUNTRY = 'USA'
  UPDATE
  END TRANSACTION
/*
  AT END OF DATA
    WRITE NOTITLE *NUMBER 'RECORDS UPDATED'
  END-ENDDATA
/*
END-FIND
END
```

Output of Program ETREX1:

```
7 RECORDS UPDATED
```

Example 2 - END TRANSACTION with ET Data

```
** Example 'ETREX2': END TRANSACTION (with ET data)
**
** CAUTION: Executing this example will modify the database records!
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
  2 FIRST-NAME
  2 CITY
*
1 #PERS-NR (A8) INIT <' '>
END-DEFINE
*
REPEAT
  INPUT 'ENTER PERSONNEL NUMBER TO BE UPDATED:' #PERS-NR
  IF #PERS-NR = ' '
    ESCAPE BOTTOM
  END-IF
  /*
  FIND EMPLOY-VIEW PERSONNEL-ID = #PERS-NR
    INPUT (AD=M)    NAME / FIRST-NAME / CITY
    UPDATE
    END TRANSACTION #PERS-NR
  END-FIND
  /*
END-REPEAT
END
```

Output of Program ETREX2:

```
ENTER PERSONNEL NUMBER TO BE UPDATED: 20027800
```

After entering and confirming the personnel number:


```
NAME LAWLER
FIRST-NAME SUNNY
CITY MILWAUKEE
```


69


ESCAPE

■ Function	506
■ Syntax Description	507
■ Example	508

Structured Mode Syntax



Reporting Mode Syntax



For explanations of the symbols used in the syntax diagram, see *Syntax Symbols*.

Related Statements:

- FIND | FOR | HISTOGRAM | PARSE XML | READ | READ RESULT SET (SQL) | READ WORK FILE | READLOB | REPEAT | SORT
- CALL | CALL FILE | CALL LOOP | CALLNAT | DEFINE SUBROUTINE | FETCH | PERFORM

Belongs to Function Group:

- *Loop Execution*
- *Invoking Programs and Routines*

Function

The `ESCAPE` statement is used to interrupt the linear flow of execution of a processing loop or a routine.

With the keywords `TOP`, `BOTTOM` and `ROUTINE` you indicate where processing is to continue when the `ESCAPE` statement is encountered.

An `ESCAPE TOP/BOTTOM` statement, when encountered for processing, will internally refer to the innermost active processing loop. The `ESCAPE` statement need not be physically placed within the processing loop.

If an `ESCAPE TOP/BOTTOM` statement is placed in a routine (subroutine, subprogram, function, or a program invoked with `FETCH RETURN`), the routine(s) entered during execution of the processing loop will be terminated automatically.

Additional Considerations

More than one `ESCAPE` statement may be contained within the same processing loop.

The execution of an `ESCAPE` statement may be based on a logical condition. If an `ESCAPE` statement is encountered during processing of an `AT END OF DATA`, `AT BREAK` or `AT END OF PAGE` block, the execution of the special condition block will be terminated and `ESCAPE` processing will continue as required.

If an `ESCAPE` statement is encountered during processing of an if-no-records-found condition, no loop-end processing will be performed (equivalent to `ESCAPE IMMEDIATE`).

Syntax Description

Syntax Element	Description
<code>ESCAPE TOP</code>	Top Option: <code>TOP</code> indicates that processing is to continue at the top of the processing loop. This starts the next repetition of the processing loop.
<code>REPOSITION</code>	Top Reposition Option: When an <code>ESCAPE TOP REPOSITION</code> statement is executed, Natural immediately continues processing at the top of the active <code>READ</code> loop, using the current value of the search variable as new start value. At the same time, <code>ESCAPE TOP REPOSITION</code> resets the system variable <code>*COUNTER</code> to zero. <code>ESCAPE TOP REPOSITION</code> can be specified within a <code>READ</code> statement loop accessing an Adabas, DL/I or VSAM database. The <code>READ</code> statement concerned must contain the option <code>WITH REPOSITION</code>.
<code>ESCAPE BOTTOM</code>	Bottom Option: <code>BOTTOM</code> indicates that processing is to continue with the first statement following the processing loop. The loop is terminated and loop-end processing (final <code>BREAK</code> and <code>END DATA</code>) is executed for all loops being terminated. In reporting mode, <code>ESCAPE BOTTOM</code> is the default.
<code>(r)</code>	Statement Reference: Notation <code>(r)</code>: If <code>BOTTOM</code> is followed by a label or reference number, processing will continue with the first statement following the processing loop identified by the label or reference number. A label or a reference number can only be specified if the <code>ESCAPE BOTTOM</code> statement is physically placed within the referenced processing loop.

Syntax Element	Description
IMMEDIATE	Immediate Option: If you specify the keyword <code>IMMEDIATE</code>, no loop-end processing will be performed.
ESCAPE ROUTINE	Routine Option: This option indicates that the current Natural routine, which may have been invoked via a <code>PERFORM</code>, <code>CALLNAT</code>, <code>FETCH RETURN</code>, or as a main program, is to relinquish control. In the case of a subroutine, processing will continue with the first statement after the statement used to invoke the subroutine. In the case of a main program, Natural command mode will be entered. All loops currently active within the routine will be terminated and loop-end processing performed as well as final processing for user-initiated (<code>PERFORM BREAK</code>) processing. If the program containing the <code>ESCAPE ROUTINE</code> is executed as a main program (Level 1), final end-page processing is performed.
ESCAPE MODULE	Module Option: This option indicates that the entire current program level, with all internal subroutines, is to relinquish control. The control is then returned to the object of the former program level. If <code>ESCAPE MODULE</code> is used in a hierarchy of internal subroutines, it allows to escape all routines working at this level at once. If no internal subroutine is active, <code>ESCAPE MODULE</code> has the same result as <code>ESCAPE ROUTINE</code>. <code>ESCAPE MODULE</code> is only relevant in inline subroutines. In external subroutines, subprograms and invoked programs, it has the same effect as <code>ESCAPE ROUTINE</code>. As with <code>ESCAPE ROUTINE</code>, loop-end processing will be performed. However, if you specify the keyword <code>IMMEDIATE</code>, no loop-end processing will be performed.

Example

```

** Example 'ESCEX1': ESCAPE
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 CITY
  2 FIRST-NAME
  2 NAME
  2 AREA-CODE
  2 PHONE
*
1 #CITY (A20) INIT <' '>
1 #CNTL (A1) INIT <' '>
END-DEFINE
*
REPEAT

```

```

INPUT 'ENTER VALUE FOR CITY: ' #CITY
  / 'OR '.' TO TERMINATE '
IF #CITY = '.'
  ESCAPE BOTTOM
END-IF
/*
FND. FIND EMPLOY-VIEW WITH CITY = #CITY
/*
IF NO RECORDS FOUND
  WRITE 'NO RECORDS FOUND'
  ESCAPE BOTTOM (FND.)
END-NOREC
AT START OF DATA
  INPUT (AD=0) 'RECORDS FOUND:' *NUMBER //
    'ENTER 'D' TO DISPLAY RECORDS' #CNTL (AD=M)
  IF #CNTL NE 'D'
    ESCAPE BOTTOM (FND.)
  END-IF
END-START
/*
  DISPLAY NOTITLE NAME FIRST-NAME PHONE
END-FIND
END-REPEAT

```

Output of Program ESCEX1:

```

ENTER VALUE FOR CITY:  PARIS
(OR '.' TO TERMINATE)

```

After entering and confirming city name:

```

RECORDS FOUND:          26
ENTER 'D' TO DISPLAY RECORDS D

```

Result after entering and confirming D:

NAME	FIRST-NAME	TELEPHONE
-----	-----	-----
MAIZIERE	ELISABETH	46758304
MARX	JEAN-MARIE	40738871
REIGNARD	JACQUELINE	48472153
RENAUD	MICHEL	46055008
REMOUE	GERMAINE	36929371
LAVENDA	SALOMON	40155905
BROUSSE	GUY	37502323
GIORDA	LOUIS	37497316
SIECA	FRANCOIS	40487413

ESCAPE

CENSIER	BERNARD	38070268
DUC	JEAN-PAUL	38065261
CAHN	RAYMOND	43723961
MAZUY	ROBERT	44286899
FAURIE	HENRI	44341159
VALLY	ALAIN	47326249
BRETON	JEAN-MARIE	48467146
GIGLEUX	JACQUES	40477399
KORAB-BRZozowski	BOGDAN	45288048
XOLIN	CHRISTIAN	46060015
LEGRIS	ROGER	39341509
VVVV		

70

EXAMINE

▪ Syntax 1 - EXAMINE	512
▪ Syntax 2 - EXAMINE TRANSLATE	520
▪ Syntax 3 - EXAMINE for Unicode Graphemes	522
▪ Examples	524

Related Statements: [ADD](#) | [COMPRESS](#) | [COMPUTE](#) | [DIVIDE](#) | [MOVE](#) | [MOVE ALL](#) | [MULTIPLY](#) | [RESET](#) | [SEPARATE](#) | [SUBTRACT](#)

Belongs to Function Group: *Arithmetic and Data Movement Operations*

Syntax 1 - EXAMINE

```
EXAMINE [DIRECTION-clause]  
  
      [FULL [VALUE [OF]]] { operand1  
                               SUBSTRING  
                               (operand1,operand2,operand3) }  
  
      [POSITION-clause]  
      [FOR] [FULL [VALUE [OF]]] [PATTERN] operand4  
      [DELIMITERS-option]  
{ DELETE-REPLACE-clause  
  GIVING-clause  
  DELETE-REPLACE-clause GIVING-clause }
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Syntax Description - Syntax 1

The `EXAMINE` statement is used to inspect the content of an alphanumeric or binary field, or a range of fields within an array, and to

- return the number of how many times a search-pattern was found;
- return the byte position where a search-pattern appears first;
- return the significant content length of a field; that is, the field length without trailing blanks;
- return the occurrence number (indices) of an array field, where a pattern was found first;
- replace a pattern by another pattern;
- delete a pattern.

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>	C*	S	A			A	U				B					yes	no
<i>operand2</i>	C	S						N	P	I	B*					yes	no
<i>operand3</i>	C	S						N	P	I	B*					yes	no
<i>operand4</i>	C	S	A*			A	U				B					yes	no

* *operand1* can only be a constant if the **GIVING** clause is used, but not if the **DELETE/REPLACE** clause is used.

* *operand4* can also be used as an array, see [Search and Replace with Multiple Values](#).

* Format B of *operand2* and *operand3* may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
<i>DIRECTION-clause</i>	DIRECTION Clause: This clause determines the search direction. For details, see DIRECTION Clause below.
<i>operand1</i>	Field to be Examined: <i>operand1</i> is the field whose content is to be examined. If <i>operand1</i> is a DYNAMIC variable, a REPLACE operation may cause its length to be increased or decreased; a DELETE operation may cause its length to be set to zero. The current length of a DYNAMIC variable can be ascertained by using the system variable *LENGTH.
<i>POSITION-clause</i>	POSITION Clause: This clause may be used to specify a starting and ending position within <i>operand1</i> (or the substring of <i>operand1</i>) for the examination. For details, see POSITION Clause below.
<i>operand4</i>	Value to be Used for EXAMINE Operation: <i>operand4</i> is the value which is searched for in the examined field(s). You may search for a single value or for multiple values. For more information on <i>operand4</i> and <i>operand6</i> , see <i>operand6</i> , which is used in the DELETE REPLACE Clause described below.
FULL	FULL Option: If FULL is specified for an operand, the entire value, including trailing blanks, will be processed. If FULL is not specified, trailing blanks in the operand will be ignored.
SUBSTRING	SUBSTRING Option:

Syntax Element	Description
	Normally, the content of a field is examined from the beginning of the field to the end or to the last non-blank character. With the <code>SUBSTRING</code> option, you examine only a certain part of the field. After the field name (<i>operand1</i>) in the <code>SUBSTRING</code> clause, you specify first the starting position (<i>operand2</i>) and then the length (<i>operand3</i>) of the field portion to be examined. For example, to examine the 5th to 12th position inclusive of a field #A, you would specify: <pre>EXAMINE SUBSTRING(#A,5,8).</pre> Note: 1. If you omit <i>operand2</i>, the starting position is assumed to be 1. 2. If you omit <i>operand3</i>, the length is assumed to be from the starting position to the end of the field. 3. If <code>SUBSTRING</code> is used in conjunction with a <code>DYNAMIC</code> variable, the field behaves like a fixed length variable; that is, the length (<code>*LENGTH</code>) does not change as a result of the <code>EXAMINE</code> operation, regardless of whether a <code>DELETE</code> or <code>REPLACE</code> operation was executed or not.
PATTERN	PATTERN Option: If you wish to examine the field for a value which contains “wild characters”, that is symbols for positions not to be examined, you use the <code>PATTERN</code> option. <i>operand4</i> may then include the following symbols for positions to be ignored: ■ A period (.), question mark (?) or underscore (_) indicates a single position that is not to be examined. ■ An asterisk (*) or a percent sign (%) indicates any number of positions not to be examined. Example: With <code>PATTERN 'NAT*AL'</code> you could examine the field for any value which contains NAT and AL no matter which and how many other characters are between NAT and AL (this would include the values NATURAL and NATIONAL as well as NATAL).
DELIMITERS-option	DELIMITERS Option: This option is used to scan for a value which exhibits delimiters. For details, see DELIMITERS Option below.
DELETE-REPLACE-clause	DELETE REPLACE Clause: The <code>DELETE</code> option of this clause is used to delete each search-value (<i>operand4</i>) found in <i>operand1</i>, whereas the <code>REPLACE</code> option is used to replace each search-value (<i>operand4</i>) found in <i>operand1</i> by the value specified in <i>operand6</i>. For details, see DELETE REPLACE Clause below.

Syntax Element	Description
<i>GIVING-clause</i>	For details, see GIVING Clause below.

DIRECTION Clause

The direction clause determines the search direction.

DIRECTION	FORWARD BACKWARD <i>operand8</i>

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand8</i>	C S	A1	yes	no

Syntax Element Description:

Syntax Element	Description
FORWARD	Examine in Left-to-Right Direction: If you specify FORWARD, the contents of the field are examined from left to right.
BACKWARD	Examine in Right-to-Left Direction: If you specify BACKWARD, the contents of the field are examined from right to left.
<i>operand8</i>	Alternative Specification: If you specify <i>operand8</i> , the search direction is determined by the contents of <i>operand8</i> . <i>operand8</i> must be defined with format/length A1. If <i>operand8</i> contains an F, then the search direction is FORWARD, if <i>operand8</i> contains a B, the search direction is BACKWARD. All other values are invalid and are rejected at compile time if <i>operand8</i> is a constant, or at run time if <i>operand8</i> is a variable.



Note: If the DIRECTION clause is not specified, the default direction is FORWARD.

POSITION Clause

The `POSITION` clause may be used to specify a starting and ending position within *operand1* (or the substring of *operand1*) for the examination.

```
[[[STARTING] FROM [POSITION] operand9] [ { ENDING AT } [POSITION] operand10 ] ]
```

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand9</i>	C	S				N	P	I								yes	no
<i>operand10</i>	C	S				N	P	I								yes	no

Syntax Element Description:

Syntax Element	Description
FROM <i>operand9</i>	Starting Position: <i>operand9</i> is used to define the starting position for the examination.
ENDING AT / THRU <i>operand10</i>	Ending Position: <i>operand10</i> is used to define the ending position for the examination.

The starting position (*operand9*) and the ending position (*operand10*) are relative to *operand1* or the substring of *operand1*, and both are processed.

The search is performed starting from the starting position and ending at the ending position.

If the starting and/or ending position are not specified, the default position value applies. This value is determined by the search direction:

Direction	Default Starting Position	Default Ending Position
FORWARD	1 (first character)	length of <i>operand1</i> (last character)
BACKWARD	length of <i>operand1</i> (last character)	1 (first character)



Note: If the search direction is `FORWARD` and the start position is greater than the end position, or if the search direction is `BACKWARD` and the start position is less than the end position, no search is performed.

DELIMITERS Option

```
{ ABSOLUTE
  WITH [DELIMITERS] [operand5] }
```

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand5</i>	C	S				A	U					B				yes	no

Syntax Element Description:

Syntax Element	Description
ABSOLUTE	Absolute Scan Option: This is the default option. It results in an absolute scan of the field for the specified value regardless of what other characters may surround the value.
WITH DELIMITERS	WITH DELIMITERS Option: This option is used to scan for a value which is delimited by blanks or by any character that is neither a letter nor a numeric character. The definition of delimiters may be modified using the SCTAB profile parameter.
WITH DELIMITERS <i>operand5</i>	Specific Delimiter Option: This option is used to scan for a value which is delimited by the character or any of the characters specified in <i>operand5</i> . If the search value was found at the beginning or end of the examined field, only the right or left side has to be delimited by one of the <i>operand5</i> characters.

DELETE/REPLACE Clause

```
[AND] { DELETE [FIRST]
        REPLACE [FIRST] [WITH] [FULL [VALUE [OF]]] operand6 }
```

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand6</i>	C	S	A*			A	U					B				yes	no

* *operand6* can also be used as an array, see [Search and Replace with Multiple Values](#).

Syntax Element Description:

Syntax Element	Description
DELETE	DELETE Option: This option is used to delete the first (or all) occurrence(s) of the search-value (<i>operand4</i>) in the content of <i>operand1</i> .
REPLACE	REPLACE Option: This option is used to replace the first (or all) occurrence(s) of the search-value (<i>operand4</i>) in <i>operand1</i> by the replace value specified in <i>operand6</i> .
FIRST	FIRST Option: If you specify the keyword <code>FIRST</code> , only the first identical value will be deleted/replaced.

**Notes:**

1. If the `REPLACE` operation results in more characters being generated than will fit into *operand1*, you will receive an error message.
2. If *operand1* is a dynamic variable, a `REPLACE` operation may cause its length to be increased or decreased; a `DELETE` operation may cause its length to be set to zero. The current length of a dynamic variable can be ascertained by using the system variable `*LENGTH`. For general information on dynamic variables, see *Using Dynamic Variables*.

Search and Replace with Multiple Values

The search (*operand4*) and replace value (*operand6*) may also be defined as array fields. This allows to substitute multiple different patterns in the examined field (*operand1*), all with an unique `EXAMINE` statement. It is not necessary to have the same number of occurrences for the search and replace operand. All what is required is the transfer compatibility between these fields; that is, *operand4:=operand6* must be a valid operation; see *Assignment Operations with Arrays* in the *Programming Guide*.

The operation logic for the multi-value search is as follows:

- The field to be examined (*operand1*) is passed through only a single time, either from left to right for direction `FORWARD` or from right to left for direction `BACKWARD`.
- Beginning with the first position, the values in the search array (*operand4*) are tested for a match, one after the other, starting with the array occurrence with the lowest index.
- If no search value was found, the comparison repeats on the next field position.
- If one of the searched patterns is detected in the examined field (*operand1*), it is substituted with the value of the replace array (*operand6*), which overlays the matching pattern in *operand4*, if a *operand4:=operand6* would be executed.
- After a pattern replacement was performed, the compare process continues with the first occurrence for the search array, immediately after the inserted value. This means, a replaced pattern is skipped and may not be replaced a second time.

Example:

This example shows an HTML translation for the characters less than (<), greater than (>), and ampersand (&).

```

DEFINE DATA LOCAL
1 #HTML (A/1:3) DYNAMIC INIT <'&lt;','&gt;','&amp;'>
1 #TAB (A/1:3) DYNAMIC INIT <'<','>','&'>
1 #DOC(A) DYNAMIC /* document to be replaced
END-DEFINE
#DOC := 'a&lt;&lt;b&amp;b&gt;c&gt;'
WRITE #DOC (AL=30) 'before'
/* Replace #DOC using #HTML to #TAB (n:1 replacement)
EXAMINE #DOC FOR #HTML(*) REPLACE #TAB(*)
/* '&lt;' is replaced by '<' (4:1 replacement)
/* '&gt;' is replaced by '>' (4:1 replacement)
/* '&amp;' is replaced by '&' (5:1 replacement)
WRITE #DOC (AL=30) 'after'
END

```

See also [Example 3 - EXAMINE AND REPLACE WITH MULTIPLE VALUES](#).

GIVING Clause

```

[ { GIVING [IN] operand7
    [GIVING] NUMBER [IN] operand7 } ]
[[GIVING] POSITION [IN] operand7]
[[GIVING] LENGTH [IN] operand7]
[[GIVING] INDEX [IN] operand7 ...3]

```

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand7</i>	S	N P I	yes	yes

Syntax Element Description:

Syntax Element	Description
GIVING	GIVING Clause: If only the keyword GIVING is specified, this corresponds to GIVING NUMBER (default).
NUMBER	GIVING NUMBER Clause: Is used to obtain information on how many times the search value (<i>operand4</i>) was found in the field (<i>operand1</i>) whose content is to be examined.

Syntax Element	Description
POSITION	GIVING POSITION Clause: Is used to obtain the byte position within <i>operand1</i> (or the substring of <i>operand1</i>) where the first value identical to <i>operand4</i> was found.
LENGTH	GIVING LENGTH Clause: Is used to obtain the remaining content length of <i>operand1</i> (or the substring of <i>operand1</i>) after all delete/replace operations have been performed. Trailing blanks are ignored.
<i>operand7</i>	Number of Occurrences: The number of occurrences of the search-value. If the REPLACE FIRST or DELETE FIRST option is also used, the number will not exceed 1.
INDEX <i>operand7</i> ...3	GIVING INDEX Clause: This option is only applicable if the underlying field to be examined is an array field. GIVING INDEX is used to obtain the array occurrence number (index) of <i>operand1</i> in which the first search-value (<i>operand4</i>) was found. <i>operand7</i> must be specified as many times as there are dimensions in <i>operand1</i> (maximum three times). <i>operand7</i> will return 0 if the search-value is found in none of the occurrences. Note: If the index range of <i>operand1</i> includes the occurrence 0 (for example, 0 : 5), a value of 0 in <i>operand7</i> is ambiguous. In this case, an additional GIVING NUMBER clause should be used to ascertain whether the search-value was actually found or not.

Syntax 2 - EXAMINE TRANSLATE

EXAMINE	{	<i>operand1</i>	}	[AND]
		SUBSTRING	(<i>operand1,operand2,operand3</i>)	
TRANSLATE	{	INTO {	UPPER	
			LOWER	[CASE]
		USING	[INVERTED] <i>operand4</i>	

For explanations of the symbols used in the syntax diagram, see *Syntax Symbols*.

Syntax Description - Syntax 2

The EXAMINE TRANSLATE statement is used to translate the characters contained in a field into upper-case or lower-case, or into other characters.

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>		S	A			A	U						B				yes	no
<i>operand2</i>	C	S						N	P	I			B*				yes	no
<i>operand3</i>	C	S						N	P	I			B*				yes	no
<i>operand4</i>		S	A			A	U						B				yes	no

*Format B of *operand2* and *operand3* may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
EXAMINE <i>operand1</i>	Complete Field Content Translation: <i>operand1</i> is the field whose content is to be translated.
EXAMINE SUBSTRING <i>operand1 operand2 operand3</i>	Partial Field Content Translation: Normally, the entire content of a field is translated. With the SUBSTRING option, you translate only a certain part of the field. After the field name (<i>operand1</i>) in the SUBSTRING clause, you specify first the starting position (<i>operand2</i>) and then the length (<i>operand3</i>) of the field portion to be examined. For example, to translate the 5th to 12th position inclusive of a field #A, you would specify: <pre>EXAMINE SUBSTRING(#A,5,8) AND TRANSLATE ...</pre> Note: If you omit <i>operand2</i> , the starting position is assumed to be 1. If you omit <i>operand3</i> , the length is assumed to be from the starting position to the end of the field.
TRANSLATE INTO UPPER CASE	Upper Case Translation: The content of <i>operand1</i> will be translated into upper case.
TRANSLATE INTO LOWER CASE	Lower Case Translation: The content of <i>operand1</i> will be translated into lower case.
TRANSLATE USING <i>operand4</i>	Translation Table:

Syntax Element	Description
	<i>operand4</i> is the translation table to be used for character translation. The table must be of format/length A2, U2 or B2. Note: If for a character to be translated more than one translation is defined in the translation table, the last of these translations applies.
INVERTED	INVERTED Option: If you specify the keyword <code>INVERTED</code>, the translation table (<i>operand4</i>) will be used inverted; that is, the translation direction will be reversed.

Syntax 3 - EXAMINE for Unicode Graphemes

EXAMINE [FULL [VALUE [OF]]]	{	<i>operand1</i> SUBSTRING (<i>operand1</i> , <i>operand2</i> , <i>operand3</i>)	}
[<i>POSITION-clause</i>]			
[FOR]	{	CHARPOSITION <i>operand4</i> CHARLENGTH <i>operand5</i> CHARPOSITION <i>operand4</i> CHARLENGTH <i>operand5</i>	}
{	[GIVING] POSITION [IN] <i>operand6</i> [GIVING] LENGTH [IN] <i>operand7</i>		}
	[GIVING] POSITION [IN] <i>operand6</i>		
	[GIVING] LENGTH [IN] <i>operand7</i>		

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Syntax Description - Syntax 3

A “grapheme” is what a user normally thinks of as a character. In most cases, a UTF-16 code unit (= U format character) is a grapheme, however, a grapheme can also consist of several code units. Examples are: a sequence of a base character followed by combining characters or a surrogate pair. For more information on graphemes and other Unicode terms, see *The Unicode Standard* at <http://www.unicode.org/>.

The EXAMINE statement for U format operands in general operates on code units. However, with the CHARPOSITION and CHARLENGTH clauses it is possible to obtain the starting position and length (in terms of code units) of a graphemes sequence. The returned code unit values can then be used in other statements/clauses which require code unit operands (for example, in a SUBSTRING clause).

For further information on this syntax of the EXAMINE statement, see also *Unicode and Code Page Support* in the *Natural Programming Language*, section *Statements, EXAMINE*.

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S	A			U										yes	no
<i>operand2</i>	C	S				N	P	I	B*							yes	no
<i>operand3</i>	C	S				N	P	I	B*							yes	no
<i>operand4</i>	C	S				N	P	I								yes	no
<i>operand5</i>	C	S				N	P	I								yes	no
<i>operand6</i>		S				N	P	I								yes	no
<i>operand7</i>		S				N	P	I								yes	no

* Format B of *operand2* and *operand3* may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
FULL	FULL Option: If FULL is specified for an operand, the entire value, including trailing blanks, will be processed. If FULL is not specified, trailing blanks in the operand will be ignored.
SUBSTRING <i>operand1</i> <i>operand2</i> <i>operand3</i>	SUBSTRING Clause: Normally, the content of a field is examined from the beginning of the field to the end or to the last non-blank character. With the SUBSTRING option, you examine only a certain part of the field. After the field name (<i>operand1</i>) in the SUBSTRING clause, you specify first the starting position (<i>operand2</i>) and then the length (<i>operand3</i>) of the field portion to be examined. <i>operand2</i> and <i>operand3</i> are specified in terms of code units. For example, to examine the 5th to 12th position inclusive of a field #A, you would specify: <pre>EXAMINE SUBSTRING (#A,5,8)</pre> Note: 1. If you omit <i>operand2</i>, the starting position is assumed to be 1. 2. If you omit <i>operand3</i>, the length is assumed to be from the starting position to the end of the field. 3. If SUBSTRING is used in conjunction with a DYNAMIC variable, the field behaves like a fixed length variable; that is, the length (*LENGTH) does not change as a result of the EXAMINE operation, regardless of whether a DELETE or REPLACE operation was executed or not.
POSITION-clause	POSITION Clause:

Syntax Element	Description
	FROM and THRU positions are given in terms of code units. For further information, see POSITION Clause under <i>Syntax 1</i> .
CHARPOSITION <i>operand4</i>	CHARPOSITION Clause: <i>operand4</i> defines the starting position (in terms of Unicode graphemes) of the grapheme sequence. The according position in terms of code units is returned in <i>operand6</i> . This clause can be omitted if the CHARLENGTH clause is specified; in this case the starting position 1 is assumed.
CHARLENGTH <i>operand5</i>	CHARLENGTH Clause: <i>operand5</i> defines the length (in terms of Unicode graphemes) of the grapheme sequence. The length of the grapheme sequence in terms of code units is returned in <i>operand7</i> . This clause can be omitted if the CHARPOSITION clause is specified; in this case the length from the starting position up to the end of the string is returned.
GIVING POSITION IN <i>operand6</i>	GIVING POSITION Clause: <i>operand6</i> receives the starting position (in terms of code units) of the grapheme sequence defined by <i>operand4</i> and <i>operand5</i> . If <i>operand1</i> has less than <i>operand4</i> graphemes, 0 is returned. This clause can be omitted if the GIVING LENGTH clause is specified.
GIVING LENGTH IN <i>operand7</i>	GIVING LENGTH Clause: <i>operand7</i> receives the length (in terms of code units) of the grapheme sequence defined by <i>operand4</i> and <i>operand5</i> . If <i>operand1</i> has less than <i>operand4</i> + <i>operand5</i> graphemes, 0 is returned. This clause can be omitted if the GIVING POSITION clause is specified.

**Notes:**

1. Either the CHARPOSITION or the CHARLENGTH clause or both must be specified.
2. Either the GIVING POSITION or GIVING LENGTH clause or both must be specified.

Examples

- [Example 1 - EXAMINE](#)
- [Example 2 - EXAMINE TRANSLATE](#)
- [Example 3 - EXAMINE AND REPLACE WITH MULTIPLE VALUES](#)

■ Example 4 - EXAMINE for Unicode Graphemes

Example 1 - EXAMINE

```

** Example 'EXMEX1': EXAMINE
*****
DEFINE DATA LOCAL
1 #TEXT    (A45)
1 #ARRAY   (A5/1:3)
1 #A       (A3)
1 #START   (N2)
1 #NUM     (N2)
1 #NUM1    (N2)
1 #NUM2    (N2)
1 #NUM3    (N2)
1 #POS     (N2)
1 #POS1    (N2)
1 #LENG    (N2)
1 #INDEX   (N2)
END-DEFINE
*
MOVE 'ABC   A B C   .A.  .B.  .C.   -A-  -B-  -C-  ' TO #TEXT
*
WRITE / 'EXAMPLE 1 (DELIMITER, GIVING NUMBER)'
WRITE NOTITLE '#TEXT: ' #TEXT
EXAMINE #TEXT FOR 'A' GIVING NUMBER #NUM1
EXAMINE #TEXT FOR 'A' WITH DELIMITER GIVING NUMBER #NUM2
EXAMINE #TEXT FOR 'A' WITH DELIMITER '.' GIVING NUMBER #NUM3
WRITE 'EXAMINE #TEXT FOR "A" ' 57T 'Number found:' #NUM1
WRITE 'EXAMINE #TEXT FOR "A" WITH DELIMITER' 57T 'Number found:' #NUM2
WRITE 'EXAMINE #TEXT FOR "A" WITH DELIMITER "."'
      57T 'Number found:' #NUM3
*
WRITE / 'EXAMPLE 2 (DELIMITER, REPLACE, GIVING NUMBER)'
WRITE 'EXAMINE #TEXT FOR "A" WITH DELIMITER "-" REPLACE WITH "*" '
WRITE 'Before:' #TEXT
EXAMINE #TEXT FOR 'A' WITH DELIMITER '-' REPLACE WITH '*'
      GIVING NUMBER #NUM
WRITE 'After: ' #TEXT 57T 'Number found:' #NUM
*
*
NEWPAGE
*
WRITE / 'EXAMPLE 3 (REPLACE, GIVING NUMBER)'
WRITE 'EXAMINE      #TEXT FOR " " REPLACE WITH "+" '
WRITE 'Before:' #TEXT
EXAMINE #TEXT FOR ' ' REPLACE WITH '+' GIVING NUMBER #NUM
WRITE 'After: ' #TEXT 57T 'Number found:' #NUM
*
WRITE / 'EXAMPLE 4 (FULL, REPLACE, GIVING NUMBER)'
WRITE 'EXAMINE FULL #TEXT FOR " " REPLACE WITH "+" '

```

```

WRITE 'Before:' #TEXT
EXAMINE FULL #TEXT FOR ' ' REPLACE WITH '+' GIVING NUMBER #NUM
WRITE 'After: ' #TEXT 57T 'Number found:' #NUM
*

WRITE / 'EXAMPLE 5 (DELETE, GIVING POSITION)'
WRITE 'EXAMINE #TEXT FOR "+" DELETE GIVING POSITION #POS'
WRITE 'Before:' #TEXT
EXAMINE #TEXT FOR '+' DELETE GIVING POSITION #POS
WRITE 'After: ' #TEXT 57T 'Position found:' #POS
*

WRITE / 'EXAMPLE 6 (DELETE, GIVING LENGTH)'
WRITE 'EXAMINE #TEXT FOR "A" DELETE GIVING LENGTH #LENG'
WRITE 'Before:' #TEXT
EXAMINE #TEXT FOR 'A' DELETE GIVING LENGTH #LENG
WRITE 'After: ' #TEXT 57T 'Length found:' #LENG
*
*
NEWPAGE
*
MOVE 'ABC  A B C  .A. .B. .C.  -A- -B- -C- ' TO #TEXT
*
WRITE / 'EXAMPLE 7 (PATTERN, REPLACE, GIVING NUMBER)'
WRITE 'EXAMINE #TEXT FOR          ".A." AND REPLACE "****"'
WRITE 'Before:' #TEXT
EXAMINE #TEXT FOR          '.A.' AND REPLACE '****' GIVING NUMBER #NUM
WRITE 'After: ' #TEXT 57T 'Number found:' #NUM
*
MOVE 'ABC  A B C  .A. .B. .C.  -A- -B- -C- ' TO #TEXT
*
WRITE 'EXAMINE #TEXT FOR PATTERN ".A." AND REPLACE "****"'
WRITE 'Before:' #TEXT
EXAMINE #TEXT FOR PATTERN '.A.' AND REPLACE '****' GIVING NUMBER #NUM
WRITE 'After: ' #TEXT 57T 'Number found:' #NUM
*
MOVE 'ABC  A B C  .A. .B. .C.  -A- -B- -C- ' TO #TEXT
*
#A      := 'B C'
#POS := 6
#LENG:= 25
*
WRITE / 'EXAMPLE 8 (SUBSTRING, REPLACE, GIVING POSITION)'
WRITE '#A := "B C" ; #POS := 6 ; #LENG:= 25 '
WRITE 'EXAMINE SUBSTRING(#TEXT,#POS,#LENG) FOR #A AND REPLACE "****"'
WRITE 'Before:' #TEXT
EXAMINE SUBSTRING(#TEXT,#POS,#LENG) FOR #A AND REPLACE '****'
      GIVING POSITION #POS1
WRITE 'After: ' #TEXT 57T 'Position found:' #POS1
*
*
NEWPAGE
*
MOVE 'ABC  A B C  .A. .B. .C.  -A- -B- -C- ' TO #TEXT

```

```

*
WRITE / 'EXAMPLE 9 (DELETE, GIVING NUMBER, GIVING POSITION, '-
      'GIVING LENGTH)'
WRITE 'EXAMINE #TEXT FOR "." DELETE GIVING NUMBER    #NUM'
WRITE 30T 'GIVING POSITION #POS'
WRITE 30T 'GIVING LENGTH  #LENG'
WRITE 'Before:' #TEXT
EXAMINE #TEXT FOR '.' DELETE GIVING NUMBER #NUM
                        GIVING POSITION #POS
                        GIVING LENGTH  #LENG

WRITE 'After: ' #TEXT
WRITE 'Number found: ' #NUM
WRITE 'Position found:' #POS
WRITE 'Length found: ' #LENG
*
*
*
MOVE 'ABC ' TO #ARRAY (1)
MOVE '.A.B.' TO #ARRAY (2)
MOVE '-A-B-' TO #ARRAY (3)
*
WRITE / 'EXAMPLE 10 (GIVING NUMBER, GIVING POSITION, GIVING INDEX)'
WRITE '#ARRAY(1):' #ARRAY(1)
WRITE '#ARRAY(2):' #ARRAY(2)
WRITE '#ARRAY(3):' #ARRAY(3)
WRITE 'EXAMINE #ARRAY(*) FOR "B" GIVING NUMBER    #NUM'
WRITE 27T 'GIVING POSITION #POS'
WRITE 27T 'GIVING INDEX  #INDEX'
EXAMINE #ARRAY(*) FOR 'B' GIVING NUMBER    #NUM
                        GIVING POSITION #POS
                        GIVING INDEX  #INDEX

WRITE 'Number found: ' #NUM
WRITE 'Position found:' #POS
WRITE 'Index found:   ' #INDEX
END

```

Output of Program EXMEX1:

```

EXAMPLE 1 (DELIMITER, GIVING NUMBER)
#TEXT: ABC  A B C  .A.  .B.  .C.  -A-  -B-  -C-
EXAMINE #TEXT FOR 'A'                                Number found:  4
EXAMINE #TEXT FOR 'A' WITH DELIMITER                  Number found:  3
EXAMINE #TEXT FOR 'A' WITH DELIMITER '.'              Number found:  1

EXAMPLE 2 (DELIMITER, REPLACE, GIVING NUMBER)
EXAMINE #TEXT FOR 'A' WITH DELIMITER '-' REPLACE WITH '*'
Before: ABC  A B C  .A.  .B.  .C.  -A-  -B-  -C-
After:  ABC  A B C  .A.  .B.  .C.  -*  -B-  -C-      Number found:  1

EXAMPLE 3 (REPLACE, GIVING NUMBER)
EXAMINE      #TEXT FOR ' ' REPLACE WITH '+'
Before: ABC  A B C  .A.  .B.  .C.  -*  -B-  -C-

```

After: ABC+++A+B+C+++A.++.B.++.C.++++-*---B-+-C- Number found: 20

EXAMPLE 4 (FULL, REPLACE, GIVING NUMBER)

EXAMINE FULL #TEXT FOR ' ' REPLACE WITH '+'

Before: ABC+++A+B+C+++A.++.B.++.C.++++-*---B-+-C-

After: ABC+++A+B+C+++A.++.B.++.C.++++-*---B-+-C-+ Number found: 1

EXAMPLE 5 (DELETE, GIVING POSITION)

EXAMINE #TEXT FOR '+' DELETE GIVING POSITION #POS

Before: ABC+++A+B+C+++A.++.B.++.C.++++-*---B-+-C-+

After: ABCABC.A..B..C.-*--B--C- Position found: 4

EXAMPLE 6 (DELETE, GIVING LENGTH)

EXAMINE #TEXT FOR 'A' DELETE GIVING LENGTH #LENG

Before: ABCABC.A..B..C.-*--B--C-

After: BCBC...B..C.-*--B--C- Length found: 21

EXAMPLE 7 (PATTERN, REPLACE, GIVING NUMBER)

EXAMINE #TEXT FOR '.A.' AND REPLACE '***'

Before: ABC A B C .A. .B. .C. -A- -B- -C-

After: ABC A B C *** .B. .C. -A- -B- -C- Number found: 1

EXAMINE #TEXT FOR PATTERN '.A.' AND REPLACE '***'

Before: ABC A B C .A. .B. .C. -A- -B- -C-

After: ABC ***B C *** .B. .C. *** -B- -C- Number found: 3

EXAMPLE 8 (SUBSTRING, REPLACE, GIVING POSITION)

#A := 'B C' ; #POS := 6 ; #LENG:= 25

EXAMINE SUBSTRING(#TEXT,#POS,#LENG) FOR #A AND REPLACE '***'

Before: ABC A B C .A. .B. .C. -A- -B- -C-

After: ABC A *** .A. .B. .C. -A- -B- -C- Position found: 4

EXAMPLE 9 (DELETE, GIVING NUMBER, GIVING POSITION, GIVING LENGTH)

EXAMINE #TEXT FOR '.' DELETE GIVING NUMBER #NUM

GIVING POSITION #POS

GIVING LENGTH #LENG

Before: ABC A B C .A. .B. .C. -A- -B- -C-

After: ABC A B C A B C -A- -B- -C-

Number found: 6

Position found: 15

Length found: 38

EXAMPLE 10 (GIVING NUMBER, GIVING POSITION, GIVING INDEX)

#ARRAY(1): ABC

#ARRAY(2): .A.B.

#ARRAY(3): -A-B-

EXAMINE #ARRAY(*) FOR 'B' GIVING NUMBER #NUM

GIVING POSITION #POS

GIVING INDEX #INDEX

Number found: 3

Position found: 2

Index found: 1

Example 2 - EXAMINE TRANSLATE

```

** Example 'EXMEX2': EXAMINE TRANSLATE
*****
DEFINE DATA LOCAL
1 #TEXT  (A50)
1 #TAB   (A2/1:10)
1 #POS   (N2)
1 #LENG  (N2)
END-DEFINE
*
MOVE 'ABC   A B C   .A.  .B.  .C.   -A-  -B-  -C-  ' TO #TEXT
*
MOVE 'AX' TO #TAB(1)
MOVE 'BY' TO #TAB(2)
MOVE 'CZ' TO #TAB(3)
*
*
WRITE NOTITLE / 'EXAMPLE 1  (WITH TRANSLATION TABLE)'
WRITE 'EXAMINE #TEXT TRANSLATE USING #TAB(*)'
WRITE 'Before:' #TEXT
EXAMINE #TEXT TRANSLATE USING #TAB(*)
WRITE 'After:  ' #TEXT
*
WRITE / 'EXAMPLE 2  (WITH INVERTED TRANSLATION TABLE)'
WRITE 'EXAMINE #TEXT TRANSLATE USING INVERTED #TAB(*)'
WRITE 'Before:' #TEXT
EXAMINE #TEXT TRANSLATE USING INVERTED #TAB(*)
WRITE 'After:  ' #TEXT
*
#POS := 13
#LENG:= 15
*
WRITE / 'EXAMPLE 3  (WITH LOWER CASE TRANSLATION)'
WRITE '#POS := 13 ; #LENG:= 15 '
WRITE 'EXAMINE SUBSTRING(#TEXT,#POS,#LENG) TRANSLATE INTO LOWER CASE'
WRITE 'Before:' #TEXT
EXAMINE SUBSTRING(#TEXT,#POS,#LENG) TRANSLATE INTO LOWER CASE
WRITE 'After:  ' #TEXT
*
END

```

Output of Program EXMEX2:

```

EXAMPLE 1 (WITH TRANSLATION TABLE)
EXAMINE #TEXT TRANSLATE USING #TAB(*)
Before: ABC   A B C   .A. .B. .C.   -A- -B- -C-
After:  XYZ   X Y Z   .X. .Y. .Z.   -X- -Y- -Z-

EXAMPLE 2 (WITH INVERTED TRANSLATION TABLE)
EXAMINE #TEXT TRANSLATE USING INVERTED #TAB(*)
Before: XYZ   X Y Z   .X. .Y. .Z.   -X- -Y- -Z-
After:  ABC   A B C   .A. .B. .C.   -A- -B- -C-

EXAMPLE 3 (WITH LOWER CASE TRANSLATION)
#POS := 13 ; #LENG:= 15
EXAMINE SUBSTRING(#TEXT,#POS,#LENG) TRANSLATE INTO LOWER CASE
Before: ABC   A B C   .A. .B. .C.   -A- -B- -C-
After:  ABC   A B C   .a. .b. .c.   -A- -B- -C-

```

Example 3 - EXAMINE AND REPLACE WITH MULTIPLE VALUES

```

*  EXAMPLE 'EXMEX3': EXAMINE AND REPLACE WITH MULTIPLE VALUES
*****
* This example shows a translation of the pattern
* 'AA', 'Aa' and 'aA' into '++',
* 'BB', 'Bb' and 'bB' into '--' and
* 'CC', 'Cc' and 'cC' into '**'.
*****
DEFINE DATA LOCAL
1 #SV      (A2/1:3,1:3) INIT (1,V) <'AA','BB','CC'>
                                (2,V) <'Aa','Bb','Cc'>
                                (3,V) <'aA','bB','cC'>
1 #RV      (A2/1:3)      INIT      <'++','--','**'>
1 #STRING  (A20)          INIT <'AAABbbbbBCCCcccCaaaA'>
1 #NUM     (N2)
END-DEFINE
*
*
WRITE NOTITLE / 'EXAMINE #STRING FOR #SV(*,*) AND REPLACE WITH #RV(*)' /
*
WRITE 'Before:' #STRING /* shows 'AAABbbbbBCCCcccCaaaA'
*
EXAMINE #STRING FOR #SV(*,*) AND REPLACE WITH #RV(*)
        GIVING NUMBER #NUM
*
WRITE 'After: ' #STRING /* shows '++A--bb--****c**aa++'
        40T 'Number found:' #NUM
*

```


Output of Program EXMEX3:

```
EXAMINE #STRING FOR #SV(*,*) AND REPLACE WITH #RV(*)
```

```
Before: AAABbbbbBCCCcccCaaaA
```

```
After:  ++A--bb--***c**aa++          Number found:  7
```

Example 4 - EXAMINE for Unicode Graphemes

This example demonstrates the analysis of a Unicode string containing the characters ä und ü. Both characters are defined as base character followed by a combining character: ä is coded with U+0061 followed by U+0308, and ü is coded with U+0075 followed by U+0308.

```
DEFINE DATA LOCAL
1 #U (U20)
1 #START (I2)
1 #POS (I2)
1 #LEN (I2)
END-DEFINE
#U := U'AB'-UH'00610308'-U'CD'-UH'00750308'-U'EF'
*
REPEAT
  #START := #START + 1
  EXAMINE #U FOR CHARPOSITION #START
                    CHARLENGTH      1
                    GIVING POSITION IN #POS
                    LENGTH IN #LEN
*
  INPUT (AD=0) MARK POSITION #POS IN FIELD *#U
  '          UNICODE-STRING:' #U      (AD=MI)
// '          CHARACTER NO.:' #START (EM=9)
/ 'STARTS AT BYTE POSITION:' #POS      (EM=9)
/ '          AND THE LENGTH IS:' #LEN  (EM=9)
WHILE #POS NE 0
END-REPEAT
END
```


Output:

Mainframe Environments:	Windows, UNIX and OpenVMS Environments (with Natural Web I/O Interface):
UNICODE-STRING: ABa?CDu?EF CHARACTER NO.: 1 STARTS AT BYTE POSITION: 1 AND THE LENGTH IS: 1	UNICODE-STRING: ABäCDüEF CHARACTER NO.: 1 STARTS AT BYTE POSITION: 1 AND THE LENGTH IS: 1
Press ENTER to continue.	Press ENTER to continue.
UNICODE-STRING: ABa?CDu?EF CHARACTER NO.: 2 STARTS AT BYTE POSITION: 2 AND THE LENGTH IS: 1	UNICODE-STRING: ABäCDüEF CHARACTER NO.: 2 STARTS AT BYTE POSITION: 2 AND THE LENGTH IS: 1
Press ENTER to continue.	Press ENTER to continue.
Note that the character in position 3 is a combining character sequence and is two code units long.	
UNICODE-STRING: ABa?CDu?EF CHARACTER NO.: 3 STARTS AT BYTE POSITION: 3 AND THE LENGTH IS: 2	UNICODE-STRING: ABäCDüEF CHARACTER NO.: 3 STARTS AT BYTE POSITION: 3 AND THE LENGTH IS: 2
And so on.	And so on.

71

EXPAND

■ Function	534
■ Syntax Description	534



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related statements: [REDUCE](#) | [RESIZE](#)

Belongs to Function Group: [Memory Management Control for Dynamic Variables or X-Arrays](#)

Function

The EXPAND statement is used to expand:

- the allocated length of a dynamic variable (*dynamic-clause*), or
- the number of occurrences of X-arrays (*array-clause*).

For further information, see the following sections in the *Programming Guide*:

- [Using Dynamic Variables](#)
- [Allocating/Freeing Memory Space for a Dynamic Variable](#)
- [X-Arrays](#)
- [Storage Management of X-Group Arrays](#)

Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition		
<i>operand1</i>		S	A			A	U				B						no	no		
<i>operand2</i>	C	S							I								no	no		
<i>operand3</i>			A	G		A	U	N	P	I	F	B	D	T	L	C	G	O	yes	no
<i>operand4</i>	C	S						N	P	I								no	no	
<i>operand5</i>		S								I4								no	yes	

Syntax Element Description:

Syntax Element	Description
<i>dynamic-clause</i>	Dynamic Clause: The EXPAND DYNAMIC VARIABLE statement expands the allocated length of a dynamic variable (<i>operand1</i>) to the value specified with <i>operand2</i> . For more information, see Dynamic Clause below.
<i>operand1</i>	Dynamic Variable: <i>operand1</i> is the dynamic variable for which the size is to be expanded.
<i>operand2</i>	Target Length of Dynamic Variable: <i>operand2</i> is used to specify the length to which the dynamic variable is to be expanded. The value specified must be a non-negative integer constant or a variable of type integer.
<i>array-clause</i>	Array Clause: The EXPAND ARRAY statement increases the number of occurrences of the X-array (<i>operand3</i>) to the upper and lower bound specified with (<i>dim</i> [, <i>dim</i> [, <i>dim</i>]]). For more information, see Array Clause below.
<i>operand3</i>	X-Array: <i>operand3</i> is the X-array for which the number of occurrences may be increased. The index notation of the array is optional. As index notation only the complete range notation * is allowed for each dimension.
<i>dim</i> <i>operand4</i>	Dimension: The lower and upper bound notation (<i>operand4</i> or asterisk) to which the X-array should be expanded is specified here. If the current value of the upper or lower bound should be used, an asterisk (*) may be specified in place of <i>operand4</i> . For more information, see Dimension below.
GIVING <i>operand5</i>	GIVING Clause: If the GIVING clause is not specified, Natural runtime error processing is triggered if an error occurs. If the GIVING clause is specified, <i>operand5</i> contains the Natural message number if an error occurred, or zero upon success.

Dynamic Clause

[SIZE OF] DYNAMIC [VARIABLE] *operand1* TO *operand2*

The EXPAND DYNAMIC VARIABLE statement expands the allocated size of a dynamic variable (*operand1*) to the value specified with *operand2*.

If *operand2* is less than the currently allocated length of *operand1*, the statement will be ignored for this dynamic variable. The currently allocated length (*LENGTH) of the dynamic variable is not modified.

Array Clause

[AND RESET] [OCCURRENCES OF] ARRAY *operand3* TO (*dim* [, *dim* [, *dim*]])

The EXPAND ARRAY statement increases the number of occurrences of the X-array (*operand3*) to the upper and lower bound specified with TO (*dim* [, *dim* [, *dim*]]).

The RESET option resets all occurrences of the expanded X-array to its default zero value. By default (no RESET option), the actual values are kept and the expanded (new) occurrences are reset.

When using the EXPAND statement, it is only possible to increase the number of occurrences. If the requested number is smaller than the currently allocated number of occurrences, it will simply be ignored.

An upper or lower bound used in an EXPAND statement must be exactly the same as the corresponding upper or lower bound defined for the array.

Example:

```
DEFINE DATA LOCAL
1 #a(I4/1:*)
1 #g(1:*)
  2 #ga(I4/1:*)

1 #i(i4)
END-DEFINE
...
/* allocating #a(1:10)
EXPAND ARRAY #a TO (1:10)          /* #a is allocated 10
EXPAND ARRAY #a TO (*:10)         /* occurrences.

/* allocating #ga(1:10,1:20)
EXPAND ARRAY #g TO (1:10)          /* 1st dimension is set to (1:10)
EXPAND ARRAY #ga TO (*:*,1:20)    /* 1st dimension is dependent and
                                   /* therefore kept with (*:*)
                                   /* 2nd dimension is set to (1:20)
```

```

EXPAND ARRAY #a TO (5:10)      /* This is rejected because the lower index
                                /* must be 1 or *
EXPAND ARRAY #a TO (#i:10)     /* This is rejected because the lower index
                                /* must be 1 or *

EXPAND ARRAY #ga TO (1:10,1:20) /* (1:10) for the 1st dimension is rejected
                                /* because the dimension is dependent and
                                /* must be specified with (*:*)

```

For further information, see the following topics in the *Programming Guide*:

- *Storage Management of X-Arrays*
- *Storage Management of X-Group Arrays*

Dimension

Each of the dimensions (*dim*) specified in the *Array Clause* is defined using the following syntax:

$$\left\{ \begin{array}{c} * \\ \left\{ \begin{array}{c} * \\ \text{operand4} \end{array} \right\} : \left\{ \begin{array}{c} * \\ \text{operand4} \end{array} \right\} \end{array} \right\}$$

The lower and upper bound notation (*operand4* or asterisk) to which the X-array should be expanded is specified here. If the current value of the upper or lower bound should be used, an asterisk (*) may be specified in place of *operand4*. Instead of *:*, you may also specify a single asterisk.

The number of dimensions (*dim*) must exactly match the defined number of dimensions of the X-array (1, 2 or 3).

If the number of occurrences for a specified dimension is less than the number of the currently allocated occurrences, the number of occurrences is not changed for the corresponding dimension.

IX

■ 72 FETCH	541
■ 73 FIND	547
■ 74 FOR	587
■ 75 FORMAT	593
■ 76 GET	599
■ 77 GET SAME	605
■ 78 GET TRANSACTION DATA	609
■ 79 HISTOGRAM	613
■ 80 IF	625
■ 81 IF SELECTION	629
■ 82 IGNORE	633
■ 83 INCLUDE	635

72

FETCH

■ Function	542
■ Syntax Description	542
■ Example	544



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [CALL](#) | [CALL FILE](#) | [CALL LOOP](#) | [CALLNAT](#) | [DEFINE SUBROUTINE](#) | [ESCAPE](#) | [FETCH](#) | [PERFORM](#)

Belongs to Function Group: [Invoking Programs and Routines](#)

Function

The `FETCH` statement is used to execute a Natural object program written as a main program. The program to be loaded must have been previously stored in the Natural system file (cataloged or stowed). Execution of the `FETCH` statement does not overwrite any source program in the Natural source work area.

For Natural RPC: See *Notes on Natural Statements on the Server* (in the *Natural RPC (Remote Procedure Call)* documentation).

Additional Considerations

In addition to the parameters passed explicitly with `FETCH`, the fetched program also has access to the established global data area.

The `FETCH` statement may cause the internal execution of an `END TRANSACTION` statement based on the setting of the Natural profile parameter `OPRB` (Database Open/Close Processing) as set by the Natural administrator. If a logical transaction is to span multiple Natural programs, the Natural administrator should be consulted to ensure that the `OPRB` parameter is set correctly.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition	
<i>operand1</i>	C	S				A											yes	no
<i>operand2</i>	C	S	A	G		A	U	N	P	I	F	B	D	T	L	G	yes	yes

Syntax Element Description:

Syntax Element	Description
REPEAT	REPEAT Option: The REPEAT option causes Natural to suppress the prompt for user input for each INPUT statement issued during the execution of the FETCHed program. It may be used to send information about the execution of the program to the terminal without the user having to reply with ENTER.
RETURN	RETURN Option: Without the specification of RETURN, the execution of the program issuing the FETCH statement will be terminated immediately and the fetched program will be activated as a “main program” (Level 1). If a program is invoked with FETCH RETURN, the execution of the invoking program will be suspended - not terminated - and the FETCHed program will be activated as a “subordinate program” on a higher level. Control is returned to the invoking program when an END or ESCAPE ROUTINE statement is encountered in the FETCHed program. Processing is continued with the statement following the FETCH RETURN statement.
<i>operand1</i>	Program Name: The name of the program module (maximum 8 characters) can be specified as an alphanumeric constant or the content of an alphanumeric variable of length 1 to 8. The case of the specified name is not translated. Natural will attempt to locate the program in the library currently active at the time the FETCH statement is issued. If the program is not found, Natural will attempt to locate the program in the steplibs. If the program is still not found, an error message will be issued. The program name may contain an ampersand (&); at execution time, this character will be replaced by the one-character code corresponding to the current value of the system variable *LANGUAGE. This makes it possible, for example, to invoke different programs for the processing of input, depending on the language in which input is provided.
<i>operand2</i>	Passing Parameter Fields: The FETCH statement may also be used to pass parameter fields to the invoked program. A parameter field may be defined with any format. The parameters are converted to a format suitable for a corresponding INPUT field. All parameters are placed on the top of the Natural stack. The parameter fields can be read by the FETCHed program using an INPUT statement. The first INPUT statement will result in the insertion of all parameter field values into the fields specified in the INPUT statement. The INPUT statement must have the sign position specification (session parameter SG=ON) for parameter fields defined with numeric format, because each parameter field defined with numeric format in the FETCH statement will receive a sign position if its value is negative. If more parameters are passed than are read by the next INPUT statement, the extra parameters are ignored. The number of parameters may be obtained with the Natural system variable *DATA.

Syntax Element	Description
	Note: If <i>operand2</i> is a time variable (format T), only the time component of the variable content is passed, but not the date component.
<i>parameter</i>	Date Format: If <i>operand2</i> is a date variable, you can specify the session parameter DF (Date Format) as <i>parameter</i> for this variable.

Example

Invoking Program:

```

** Example 'FETEX1': FETCH (with parameter)
*****
DEFINE DATA LOCAL
1 #PNUM (N8)
1 #FNC (A1)
END-DEFINE
*
INPUT 10X 'SELECTION MENU FOR EMPLOYEES SYSTEM' /
      10X '-' (35) //
      10X 'ADD      (A)' /
      10X 'UPDATE   (U)' /
      10X 'DELETE   (D)' /
      10X 'STOP     (.)' //
      10X 'PLEASE ENTER FUNCTION: ' #FNC ///
      10X 'PERSONNEL NUMBER:' #PNUM
*
DECIDE ON EVERY VALUE OF #FNC
  VALUE 'A', 'U', 'D'
    IF #PNUM = 0
      REINPUT 'PLEASE ENTER A VALID NUMBER' MARK *#PNUM
    END-IF
  VALUE 'A'
    FETCH 'FETEXAD' #PNUM
  VALUE 'U'
    FETCH 'FETEXUP' #PNUM
  VALUE 'D'
    FETCH 'FETEXDE' #PNUM
  VALUE '.'
    STOP
  NONE
    REINPUT 'PLEASE ENTER A VALID FUNCTION' MARK *#FNC
END-DECIDE
*
END

```

Invoked Program FETEXAD:

```
** Example 'FETEXAD': FETCH (called by FETEX1)
*****
DEFINE DATA LOCAL
1 #PERS-NR (N8)
END-DEFINE
*
INPUT #PERS-NR
*
WRITE *PROGRAM 'Record added with personnel number:' #PERS-NR
*
END
```

Invoked Program FETEXUP:

```
** Example 'FETEXUP': FETCH (called by FETEX1)
*****
DEFINE DATA LOCAL
1 #PERS-NR (N8)
END-DEFINE
*
INPUT #PERS-NR
*
WRITE *PROGRAM 'Record updated with personnel number:' #PERS-NR
*
END
```

Invoked Program FETEXDE:

```
** Example 'FETEXDE': FETCH (called by FETEX1)
*****
DEFINE DATA LOCAL
1 #PERS-NR (N8)
END-DEFINE
*
INPUT #PERS-NR
*
WRITE *PROGRAM 'Record deleted with personnel number:' #PERS-NR
*
END
```

Output of Program FETEX1:

```
SELECTION MENU FOR EMPLOYEES SYSTEM
```

```
-----
```

```
ADD      (A)
```

```
UPDATE   (U)
```

```
DELETE   (D)
```

```
STOP     (.)
```

```
PLEASE ENTER FUNCTION: D
```

```
PERSONNEL NUMBER: 1150304
```

After entering and confirming function and personnel number:

```
Page      1                                05-01-13  11:58:46
```

```
FETEXDE  Record deleted with personnel number:  1150304
```


73

FIND

■ Function	548
■ Restrictions	550
■ Syntax 1 - FIND Statement with Processing Loop	550
■ Syntax 2 - FIND Statement without Processing Loop	550
■ Syntax Description	551
■ Examples	576

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [DELETE](#) | [END TRANSACTION](#) | [GET](#) | [GET SAME](#) | [GET TRANSACTION](#) | [HISTOGRAM](#) | [LIMIT](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [READLOB](#) | [RETRY](#) | [STORE](#) | [UPDATE](#) | [UPDATELOB](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The `FIND` statement is used to select a set of records from the database based on search criteria consisting of fields defined as descriptors (keys).

This statement causes a processing loop to be initiated and then executed for each record selected. Each field in each record may be referenced within the processing loop. It is not necessary to issue a [READ](#) statement following the `FIND` in order to reference the fields within each record selected.

See also the following sections in the *Programming Guide*:

- *FIND Statement*
- *Loop Processing*
- *Referencing of Database Fields Using (r) Notation*

Database-Specific Considerations

Database	Explanation
DL/I	When accessing a field starting after the last byte of the given segment occurrence, the storage copy of this field is filled according to its format (numeric, blank, etc.). The term segment occurrences should be substituted for the term records as used in this description of the <code>FIND</code> statement.
VSAM	The <code>FIND</code> statement is only valid for key-sequenced (KSDS) and entry-sequenced (ESDS) VSAM data sets. For ESDS, an alternate index for the base cluster must be defined.
SQL	<code>FIND FIRST</code> as well as the <code>PASSWORD</code>, <code>CIPHER</code>, <code>COUPLED</code> and <code>RETAIN</code> clauses are not permitted. <code>FIND UNIQUE</code> is not permitted. (Exception: <code>FIND UNIQUE</code> can be used for primary keys; however, this is only permitted for compatibility reasons and should not be used.) The <code>SORTED BY</code> clause corresponds with the SQL clause <code>ORDER BY</code>. The basic search criteria for an SQL-database table may be specified in the same manner as for an Adabas file. The term record used in this context corresponds with the SQL term “row”.

System Variables Available with the FIND Statement

The Natural system variables *ISN, *NUMBER, and *COUNTER are automatically created for each FIND statement issued. A reference number must be supplied if the system variable was referenced outside the current processing loop or through a [FIND UNIQUE](#), [FIND FIRST](#) or [FIND NUMBER](#) statement. The format/length of each of these system variables is P10; this format/length cannot be changed.

System Variable	Availability/Usage
*ISN	■ Adabas *ISN contains the Adabas internal sequence number (ISN) of the record currently being processed. *ISN is not available for the FIND NUMBER statement. ■ VSAM See *ISN for VSAM in the <i>System Variables</i> documentation. ■ DL/I and SQL *ISN is not available. ■ Entire System Server *ISN is not available.
*NUMBER	See system variable *NUMBER in the <i>System Variables</i> documentation. With Entire System Server, *NUMBER is not available.
*COUNTER	The system variable *COUNTER contains the number of times the processing loop has been entered.

See also [Example 13 - Using System Variables with the FIND Statement](#).

Issuing Multiple FIND Statements

Multiple FIND statements may be issued to create nested loops whereby an inner loop is entered for each record selected in the outer loop.

See also [Example 14 - Multiple FIND Statements](#).

Restrictions

With Entire System Server, `FIND NUMBER` and `FIND UNIQUE` as well as the `PASSWORD`, `CIPHER`, `COUPLED` and `RETAIN` clauses are not permitted.

Syntax 1 - FIND Statement with Processing Loop

```
FIND [ { ALL (operand1) } ] [MULTI-FETCH-clause] [RECORDS] [IN] [FILE] view-name
[PASSWORD=operand2]
[CIPHER=operand3]
[WITH] [[LIMIT] (operand4)] basic-search-criteria
[COUPLED-clause] ... 4/42
[STARTING WITH ISN=operand5]
[SORTED-BY-clause]
[RETAIN-clause]
[[IN] SHARED HOLD [MODE=option]]
[SKIP [RECORDS] IN HOLD]
[WHERE-clause]
[IF-NO-RECORDS-FOUND-clause]
statement ...
END-FIND (structured mode only)
LOOP (reporting mode only)
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Syntax 2 - FIND Statement without Processing Loop

```
FIND [ { FIRST NUMBER UNIQUE } ] [RECORDS] [IN] [FILE] view-name
[PASSWORD=operand2]
[CIPHER=operand3]
[WITH] [[LIMIT] (operand4)] basic-search-criteria
[COUPLED-clause] ... 4/42
```

[<i>SORTED-BY-clause</i>]	(only for FIND FIRST)
[<i>RETAIN-clause</i>]	
[<i>WHERE-clause</i>]	

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Syntax Description

Operand Definition Table:

Operand	Possible Structure			Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S		N P I B*	yes	no
<i>operand2</i>	C	S		A	yes	no
<i>operand3</i>	C	S		N	yes	no
<i>operand4</i>	C	S		N P I B*	yes	no
<i>operand5</i>	C	S		N P I B*	yes	no

* Format B of *operand1*, *operand4* and *operand5* may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
ALL/ <i>operand1</i>	Processing Limit: The number of records to be processed from the selected set may be limited by specifying <i>operand1</i> (enclosed in parentheses, immediately after the keyword FIND) - either as a numeric constant (in the range from 0 to 4294967295) or as the name of a numeric variable. ALL may be optionally specified. It emphasizes that all selected records are to be processed. If you specify a limit with <i>operand1</i>, this limit applies to the FIND loop being initiated. Records rejected for processing by the WHERE clause are not counted against this limit.

Syntax Element	Description
	<pre>FIND (5) IN EMPLOYEES WITH ... MOVE 10 TO #CNT(N2) FIND (#CNT) EMPLOYEES WITH ...</pre> For this statement, the specified limit has priority over a limit set with a <code>LIMIT</code> statement. If a smaller limit is set with the <code>LT</code> parameter, the <code>LT</code> limit applies. Note: 1. If you wish to process a 4-digit number of records, specify it with a leading zero: <code>(0nnnn)</code>; because Natural interprets every 4-digit number enclosed in parentheses as a line-number reference to a statement. 2. <i>operand1</i> has no influence on the size of an ISN set that is to be retained by a <code>RETAIN</code> clause. <i>operand1</i> is evaluated when the <code>FIND</code> loop is entered. If the value of <i>operand1</i> is modified within the <code>FIND</code> loop, this does not affect the number of records processed.
FIND FIRST FIND NUMBER FIND UNIQUE	FIND FIRST, FIND NUMBER, FIND UNIQUE Option: These options are used ■ to select the first record of a selected set (see FIND FIRST), ■ to determine the number of records in a selected set (see FIND NUMBER), or ■ to ensure that only one record satisfies a selection criterion (see FIND UNIQUE). For a detailed description of these options, see below.
MULTI-FETCH-clause	MULTI-FETCH Clause: For Adabas databases, Natural offers a <code>MULTI-FETCH</code> clause that allows you to read more than one record per database access. For further information, see MULTI-FETCH Clause.
view-name	View Name: The name of a view as defined either within a <code>DEFINE DATA</code> block or in a separate global or local data. In reporting mode, <i>view-name</i> is the name of a DDM if no <code>DEFINE DATA LOCAL</code> statement is used.
PASSWORD=operand2	PASSWORD Clause: The <code>PASSWORD</code> clause applies only for Adabas or VSAM databases. This clause is not permitted with Entire System Server.

Syntax Element	Description
	The PASSWORD clause is used to provide a password (<i>operand2</i>) when reading/writing data from an Adabas or VSAM file which is password protected. If you require access to a password-protected file, contact the person responsible for database security concerning password usage/assignment. If the password is specified as a constant, the PASSWORD clause should always be coded at the very beginning of a source-code line; and there should be no blank between the keyword PASSWORD and the equal sign; this ensures that the password is not visible/displayable in the source code of the program. In TP mode, you may enter the PASSWORD clause invisible by entering the terminal command %* before you type in the PASSWORD clause. If the PASSWORD clause is omitted, the default password specified with the PASSW statement applies. The password value must not be changed during the execution of a processing loop. See also Example 1 - PASSWORD Clause.
CIPHER= <i>operand3</i>	CIPHER Clause: The CIPHER clause only applies to Adabas databases. This clause is not permitted with Entire System Server. The CIPHER clause is used to provide a cipher key (<i>operand3</i>) when retrieving data from Adabas files which are enciphered. If you require access to an enciphered file, contact the person responsible for database security concerning cipher key usage/assignment. The cipher key may be specified as a numeric constant with 8 digits or as a user-defined variable with format/length N8. If the cipher key is specified as a constant, the CIPHER clause should always be coded at the very beginning of a source-code line; this ensures that the cipher key is not visible/displayable in the source code of the program. In TP mode, you may enter the CIPHER clause invisible by entering the Natural terminal command %* before you type in the CIPHER clause. The value of the cipher key must not be changed during the processing of a loop initiated by a FIND statement. See also Example 2 - CIPHER Clause.
WITH LIMIT <i>operand4</i> <i>basic-search-criteria</i>	WITH Clause: The WITH clause is required. It is used to specify the <i>basic-search-criteria</i> (see Search Criteria for Adabas Files) consisting of key fields (descriptors) defined in the database.

Syntax Element	Description
	The following database-specific considerations apply. ■ For Adabas files: You may use Adabas descriptors, subdescriptors, superdescriptors, hyperdescriptors, and phonetic descriptors within a <code>WITH</code> clause. A non-descriptor (that is, a field marked in the DDM with <code>N</code>) can also be specified. ■ For DL/I files: You may only use key fields marked with <code>D</code> in the DDM. ■ For VSAM files: You may use VSAM key fields only. The number of records to be selected as a result of a <code>WITH</code> clause may be limited by specifying the keyword <code>LIMIT</code> together with a numeric constant or a user-defined variable, enclosed within parentheses, which contains the limit value (<i>operand4</i>, range from 1 to 4294967295). If the number of records selected exceeds the limit, the program will be terminated with an error message. Note: If the limit is to be a 4-digit number, specify it with a leading zero (<i>0nnnn</i>); because Natural interprets every 4-digit number enclosed in parentheses as a line-number reference to a statement.
<i>COUPLED-clause</i>	COUPLED Clause: This clause may be used to specify a search which involves the use of the Adabas coupling facility. See COUPLED Clause.
<code>STARTING WITH ISN=operand5</code>	STARTING WITH Clause: This clause may be used for repositioning within a <code>FIND</code> loop whose processing has been interrupted. See STARTING WITH Clause.
<i>SORTED-BY-clause</i>	SORTED BY Clause: This clause may be used to cause Adabas to sort the selected records based on the sequence of one to three descriptors. See SORTED BY Clause.
<i>RETAIN-clause</i>	RETAIN Clause: This clause may be used to retain the result of an extensive search in large files for further processing. See RETAIN Clause.
<code>[[IN] SHARED HOLD [MODE=option]]</code>	SHARED HOLD Clause Note: This clause can be used only for access to Adabas. This clause can be used to place records being read in a “shared hold” state. A record can be put in shared hold by many users at the same

Syntax Element	Description		
	time. As long as a record is in a shared hold state, it is protected from being updated, because it cannot be set into an exclusive hold by parallel users. This ensures data consistency for the record data, as no one can update the record while it is being processed. Especially if the same record is fetched with multiple statements to read different MU/PE occurrences (GET SAME statement) or to browse over a LOB field in a piecemeal technique (READLOB statement), the shared hold state can guarantee data stability over this transaction without blocking the record for other users. Although such a hold state is an efficient way to protect read sequences, it is a basic and important matter when to release the record again from this “soft lock”. Since this question depends on individual application aspects, different options can be selected with the MODE subclause.		
	MODE Option	Hold Period	Explanation
	C	Only at the moment of reading the record.	Ensures only that the record version being read has been committed by the last user who updated the record. This option does not really set a lock in hold state, but checks only that the record is not in exclusive hold by another user at time of read.
	Q	Until the next record in a sequence is read.	Releases the record from shared hold when ■ the next record is read in the loop sequence or ■ the loop is terminated or ■ an END TRANSACTION or BACKOUT TRANSACTION is executed.
	S	Until the logical transaction is terminated.	Releases the record from shared hold when a logical transaction is terminated with an END TRANSACTION or BACKOUT TRANSACTION statement.

Syntax Element	Description
	MODE=Q and MODE=S ensure that the record being read cannot be updated concurrently by other users until it has been released from hold again. If the MODE subclause is not specified, MODE=C is the default. See also Example 15 - SHARED HOLD Clause below.
SKIP RECORDS IN HOLD	SKIP RECORDS Clause: Note: This clause can be used only for access to Adabas. Whenever a record is going to be read with hold, a Natural error NAT3145 (Adabas response code 145) might happen if the record is in hold by another user at this time. This occurs if a shared hold is requested and the record is in exclusive hold or if an exclusive hold is requested and the record is in either exclusive or shared hold. Although error NAT3145 is surely the right reaction to assure a “clean data processing”, sometimes it might be useful if a record in hold could be skipped. If it is alright that such a record will not be processed and the loop processing should continue, the SKIP RECORDS clause should be used. If the SKIP RECORDS clause is applied, Natural first tries to read the record with hold. If the record is already in hold and a Natural error NAT3145 would occur, ■ no error processing is initiated; ■ the record (currently in hold by another user) is instantly re-fetched without hold, but not processed in terms of the program logic; ■ the record which comes next after the skipped record is read with hold and the processing continues. See also Example 16 - SKIP RECORDS Clause.
WHERE-clause	WHERE Clause: This clause may be used to specify an additional selection criterion (<i>logical-condition</i>). See WHERE Clause.
IF-NO-RECORDS-FOUND-clause	IF NO RECORDS FOUND Clause: This clause may be used to cause a processing loop initiated with a FIND statement to be entered in the event that no records meet the selection criteria specified in the WITH clause and the WHERE clause. See IF NO RECORDS FOUND Clause.
END-FIND	End of FIND Statement:

Syntax Element	Description
LOOP	In structured mode with processing loop, the Natural reserved keyword <code>END-FIND</code> must be used to end the <code>FIND</code> statement. In reporting mode with processing loop, the Natural statement <code>LOOP</code> is used to end the <code>FIND</code> statement.

FIND FIRST

The `FIND FIRST` statement may be used to select and process the first record which meets the `WITH` and `WHERE` criteria.

For Adabas databases, the record processed will be the record with the lowest Adabas ISN from the set of qualifying records.

This statement does *not* initiate a processing loop.

Restrictions with FIND FIRST

- `FIND FIRST` can only be used in reporting mode.
- `FIND FIRST` is not available for DL/I and SQL databases.

System Variables Available with FIND FIRST

The following Natural system variables are available with the `FIND FIRST` statement:

System Variable	Explanation
*ISN	The system variable *ISN contains the Adabas ISN of the selected record. *ISN will be zero if no record is found after the evaluation of the <code>WITH</code> and <code>WHERE</code> criteria. *ISN is not available for VSAM databases or with Entire System Server.
*NUMBER	The system variable *NUMBER contains the number of records found after the evaluation of the <code>WITH</code> criterion and before evaluation of any <code>WHERE</code> criteria. *NUMBER will be zero if no record meets the <code>WITH</code> criterion. *NUMBER is not available with Entire System Server.
*COUNTER	The system variable *COUNTER contains 1 if a record was found; contains 0 if no record was found.

Example of `FIND FIRST` Statement: See the program `FNDFIR` (reporting mode)

FIND NUMBER

The `FIND NUMBER` statement is used to determine the number of records which satisfy the `WITH/WHERE` criteria specified. It does *not* result in the initiation of a processing loop and *no data fields from the database are made available*.



Note: Use of the `WHERE` clause may result in significant overhead.

Restrictions with FIND NUMBER

- The `WHERE` clause can only be used in reporting mode.
- `FIND NUMBER` is not available for DL/I databases or with Entire System Server.

System Variables Available with FIND NUMBER

The following Natural system variables are available with the `FIND NUMBER` statement:

System Variable	Explanation
*NUMBER	The system variable *NUMBER contains the number of records found after the evaluation of the <code>WITH</code> criterion.
*COUNTER	The system variable *COUNTER contains the number of records found after the evaluation of the <code>WHERE</code> criterion. *COUNTER is only available if the <code>FIND NUMBER</code> statement contains a <code>WHERE</code> clause.

Example for `FIND NUMBER`: See the program `FNDNUM` (reporting mode).

FIND UNIQUE

The `FIND UNIQUE` statement may be used to ensure that only one record is selected for processing. It does *not* result in the initiation of a processing loop. If a `WHERE` clause is specified, an automatic internal processing loop is created to evaluate the `WHERE` clause.

If no records or more than one record satisfy the criteria, an error message will be issued. This condition can be tested with the `ON ERROR` statement.

Restrictions with FIND UNIQUE

- `FIND UNIQUE` can only be used in reporting mode.
- `FIND UNIQUE` is not available for DL/I databases or with Entire System Server.
- For SQL databases, `FIND UNIQUE` cannot be used. (Exception: On mainframe computers, `FIND UNIQUE` can be used for primary keys; however, this is only permitted for compatibility reasons and should not be used.)

System Variables Available with FIND UNIQUE

System Variable	Explanation
*ISN	The system variable *ISN contains the unique ISN number of the record, which itself must be unique.
*NUMBER	The system variable *NUMBER always contains 1 for a valid FIND UNIQUE execution. *NUMBER may contain any other positive value (= 0 or >= 2) if an error has occurred. This error condition may be used by the ON ERROR statement. *NUMBER is not allowed if the WHERE clause is missing.
*COUNTER	The system variable *COUNTER contains the number of records found after the evaluation of the WHERE criterion. *COUNTER is not allowed if the WHERE clause is missing.

Example for FIND UNIQUE: See the Program [FNDUNQ](#) (reporting mode).

MULTI-FETCH Clause


 **Note:** This clause can only be used for Adabas or DB2 databases.

MULTI-FETCH	$\left\{ \begin{array}{l} \text{ON} \\ \text{OFF} \\ [\text{OF}] \text{ multi-fetch-factor} \end{array} \right\}$

For more information, see the section *MULTI-FETCH Clause (Adabas)* in the *Programming Guide* or *Multiple Row Processing (SQL)* in the *Natural for DB2* part of the *Database Management System Interfaces* documentation.

Search Criteria for Adabas Files

1 <i>descriptor</i> [(i)]	$\left\{ \begin{array}{l} \text{EQ} \\ = \\ \text{EQUAL} \\ \text{EQUAL TO} \end{array} \right\}$	<i>value</i>	$\left\{ \begin{array}{l} \text{OR} \\ \left\{ \begin{array}{l} \text{EQ} \\ = \\ \text{EQUAL} \\ \text{EQUAL TO} \end{array} \right\} \text{ } \text{value} \end{array} \right\} \dots$	$\left\{ \begin{array}{l} \text{THRU value [BUT NOT value [THRU value]]} \end{array} \right\}$



Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>descriptor</i>		S	A			A	N	P	I	F	B	D	T	L			no	no
<i>value</i>	C	S				A	N	P	I	F	B	D	T	L			yes	no
<i>set-name</i>	C	S				A											no	no

Syntax Element Description:

Syntax Element	Description
<i>descriptor</i>	Descriptor: Adabas descriptor, subdescriptor, superdescriptor, hyperdescriptor or phonetic descriptor. A field marked as non-descriptor in the DDM can also be specified.
<i>(i)</i>	Index Specification: A descriptor contained within a periodic group may be specified with or without an index. If no index is specified, the record will be selected if the value specified is located in any occurrence. If an index is specified, the record is selected only if the value is located in the occurrence specified by the index. The index specified must be a constant. An index range must not be used. No index must be specified for a descriptor which is a multiple-value field. The record will be selected if the value is located in the record regardless of the position of the value.
<i>value</i>	Search Value: The formats of the descriptor and the search value must be compatible.
<i>set-name</i>	Set Name: Identifies a set of records previously selected with a FIND statement in which the RETAIN clause was specified. The set referenced in a FIND must have been created from the same physical Adabas file. <i>set-name</i> may be specified as a text constant (maximum 32 characters) or as the content of an alphanumeric variable. <i>set-name</i> cannot be used with Entire System Server.

See also:

- [Example 3 - Basic Search Criteria in WITH Clause](#)
- [Example 4 - Basic Search Criteria with Multiple-Value Field](#)

Search Criterion with Null Indicator

<i>null-indicator</i>	$\left\{ \begin{array}{l} = \\ \text{EQ} \\ \text{EQUAL [TO]} \end{array} \right\}$	<i>value</i>

Operand Definition Table:

Operand	Possible Structure				Possible Formats										Referencing Permitted	Dynamic Definition
<i>null-indicator</i>		S						I							no	no
<i>value</i>	C	S				N	P	I	F	B					yes	no

Syntax Element Description:

Syntax Element	Description	
<i>null-indicator</i>	The null indicator.	
<i>value</i>	Possible Values	Meaning
	-1	The corresponding field contains no value.
	0	The corresponding field does contain a value.

Connecting Search Criteria (for Adabas Files)

basic-search-criteria can be combined using the Boolean operators AND, OR and NOT. Parentheses may also be used to control the order of evaluation. The order of evaluation is as follows:

1. (): Parentheses
2. NOT: Negation (only for *basic-search-criteria* of form [2]).
3. AND: AND operation
4. OR: OR operation

basic-search-criteria may be connected by logical operators to form a complex *search-expression*. The syntax for such a complex *search-expression* is as follows:

[NOT] { <i>basic-search-criteria</i> (<i>search-expression</i>) } [{ OR AND } <i>search-expression</i>] ...

See also [Example 5 - Various Samples of Complex Search Expression in WITH Clause](#).

Descriptor-Key Usage

Adabas users may use database fields which are defined as descriptors to construct basic search criteria.

Subdescriptors, Superdescriptors, Hyperdescriptors and Phonetic Descriptors

With Adabas, subdescriptors, superdescriptors, hyperdescriptors and phonetic descriptors may be used to construct search criteria.

- A subdescriptor is a descriptor formed from a portion of a field.
- A superdescriptor is a descriptor whose value is formed from one or more fields or portions of fields.
- A hyperdescriptor is a descriptor which is formed using a user-defined algorithm.
- A phonetic descriptor is a descriptor which allows the user to perform a phonetic search on a field (for example, a person's name). A phonetic search results in the return of all values which sound similar to the search value.

Which fields may be used as descriptors, subdescriptors, superdescriptors, hyperdescriptors and phonetic descriptors with which file is defined in the corresponding DDM.

Values for Subdescriptors, Superdescriptors, Phonetic Descriptors

Values used with these types of descriptors must be compatible with the internal format of the descriptor. The internal format of a subdescriptor is the same as the format of the field from which the subdescriptor is derived. The internal format of a superdescriptor is binary if all of the fields from which it is derived are defined with numeric format; otherwise, the format is alphanumeric. Phonetic descriptors always have alphanumeric format.

Values for subdescriptors and superdescriptors may be specified in the following ways:

- Numeric or hexadecimal constants may be specified. A hexadecimal constant must be used for a value for a superdescriptor which has binary format (see above).
- Values in user-defined variable fields may be specified using the `REDEFINE` statement to select the portions that form the subdescriptor or superdescriptor value.

Using Descriptors Contained within a Database Array


A descriptor which is contained within a database array may also be used in the construction of basic search criterion. For Adabas databases, such a descriptor may be a multiple-value field or a field contained within a periodic group.

A descriptor contained within a periodic group may be specified with or without an index. If no index is specified, the record will be selected if the value specified is located in any occurrence. If an index is specified, the record is selected only if the value is located in the occurrence specified by the index. The index specified must be a constant. An index range must not be used.

No index must be specified for a descriptor which is a multiple-value field. The record will be selected if the value is located in the record regardless of the position of the value.

See also [Example 6 - Various Samples Using Database Arrays](#).

Search Criteria for VSAM Files - basic-search-criteria



Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
descriptor		S	A			A	N	P		B						no	no
value	C	S				A	N	P		B						yes	no

Syntax Element Description:

Syntax Element	Description
<i>descriptor</i>	Descriptor: The descriptor must be defined in a VSAM file as a VSAM key field and is marked in the DDM with P for primary key or A for alternate key.
<i>value</i>	Search Value: The search value.

The formats of the *descriptor* and the search *value* must be compatible.

Search Criteria for DL/I Files - basic-search-criteria

1	<i>descriptor</i>	EQ = EQUAL EQUAL TO NE ¬ = <> NOT = NOT EQ NOTEQUAL NOT EQUAL NOT EQUAL TO LT LESS THAN < GE GREATER EQUAL >= NOT < NOT LT GT GREATER THAN > LE LESS EQUAL <= NOT > NOT GT	<i>value</i>
2	<i>descriptor</i>	EQ = EQUAL EQUAL TO	<i>value</i> THRU <i>value</i> [BUT NOT <i>value</i>]

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>descriptor</i>		S	A			A	N	P		B						no	no
<i>value</i>	C	S				A	N	P		B						yes	no

Syntax Element Description:

Syntax Element	Description
<i>descriptor</i>	Descriptor: The descriptor must be a field defined in DL/I and is marked in the DDM with D.
<i>value</i>	Search Value: The search value.

For HDAM databases, only the following *basic-search-criterion* is possible:

<i>descriptor</i>	$\left\{ \begin{array}{l} \text{EQ} \\ = \\ \text{EQUAL [T0]} \end{array} \right\}$	<i>value</i>

Connecting Search Criteria - for DL/I Files

[NOT]	$\left\{ \begin{array}{l} \text{basic-search-criteria} \\ (\text{search-expression}) \end{array} \right\}$	$\left[\left\{ \begin{array}{l} \text{OR} \\ \text{AND} \end{array} \right\} \text{search-expression} \right] \dots$

basic-search-criteria that refer to different segment types must not be connected with the OR logical operator.

Examples:

```
FIND COURSE WITH COURSEN > 1
FIND COURSE WITH COURSEN > 1 AND COURSEN < 100
FIND OFFERING WITH (COURSEN-COURSE > 1 OR TITLE-COURSE = 'Natural')
AND LOCATION = 'DARMSTADT'
```

Invalid Example:

```
FIND OFFERING WITH COURSEN-COURSE > 1 OR LOCATION = 'DARMSTADT'
```

COUPLED Clause

This clause only applies to Adabas databases.

This clause is not permitted with Entire System Server.

$\left\{ \begin{array}{l} \text{AND} \\ \text{OR} \end{array} \right\} \text{ COUPLED } [TO] [FILE] \text{ view-name}$		$\left[\begin{array}{l} \text{VIA } \text{descriptor1} \\ \\ \text{[WITH]} \\ \text{basic-search-criteria} \end{array} \right. \left. \left\{ \begin{array}{l} \text{EQ} \\ = \\ \text{EQUAL [TO]} \end{array} \right\} \text{descriptor2} \right]$	

Operand Definition Table:

Operand	Possible Structure				Possible Formats										Referencing Permitted	Dynamic Definition
<i>descriptor1</i>	S	A			A	N	P		B						no	no
<i>descriptor2</i>	S	A			A	N	P		B						no	no



Note: Without the *VIA* clause, the *COUPLED* clause may be specified up to 4 times; with the *VIA* clause, it may be specified up to 42 times.

The *COUPLED* clause is used to specify a search which involves the use of the Adabas coupling facility. This facility permits database descriptors from different files to be specified in the search criterion of a single *FIND* statement.

The same Adabas file must not be used in two different *FIND COUPLED* clauses within the same *FIND* statement.

A *set-name* (see *RETAIN Clause*) must not be specified in the *basic-search-criteria*.

Database fields in a file specified within the *COUPLED* clause are not available for subsequent reference in the program unless another *FIND* or *READ* statement is issued separately against the coupled file.



Note: If the *COUPLED* clause is used, the main *WITH* clause may be omitted. If the main *WITH* clause is omitted, the keywords *AND/OR* of the *COUPLED* clause must not be specified.

Physical Coupling without VIA Clause

The files used in a `COUPLED` clause without `VIA` must be physically coupled using the appropriate Adabas utility (as described in the Adabas documentation).

See also [Example 7 - Using Physically Coupled Files](#).

The reference to `NAME` in the `DISPLAY` statement of the above example is valid since this field is contained in the `EMPLOYEES` file, whereas a reference to `MAKE` would be invalid since `MAKE` is contained in the `VEHICLES` file, which was specified in the `COUPLED` clause.

In this example, records will be found only if `EMPLOYEES` and `VEHICLES` have been physically coupled.

Logical Coupling - VIA Clause

The option `VIA descriptor1 = descriptor2` allows you to logically couple multiple Adabas files in a search query, where:

- *descriptor1* is a field from the first view.
- *descriptor2* is a field from the second view.

The two files need not be physically coupled in Adabas.

See also [Example 8 - VIA Clause](#).

STARTING WITH Clause

This clause applies only to Adabas and VSAM databases; for VSAM, it is only valid for ESDS.

You can use this clause to specify as *operand5* an Adabas ISN (internal sequence number) or VSAM RBA (relative byte address) respectively, which is to be used as a start value for the selection of records. *operand5* must be in the range from 0 to 4294967295.

This clause may be used for repositioning within a `FIND` loop whose processing has been interrupted, to easily determine the next record with which processing is to continue. This is particularly useful if the next record cannot be identified uniquely by any of its descriptor values. It can also be useful in a distributed client/server application where the reading of the records is performed by a server program while further processing of the records is performed by a client program, and the records are not processed all in one go, but in batches.



Note: The start value actually used will not be the value of *operand5*, but the next higher value.

Example:

See the program `FNDSISN` in the library `SYSEXSYN`.

SORTED BY Clause

This clause only applies to Adabas and SQL databases.

This clause is not permitted with Entire System Server.

```
SORTED [BY] descriptor... 3 [DESCENDING]
```

The SORTED BY clause is used to cause Adabas to sort the selected records based on the sequence of one to three descriptors. The descriptors used for controlling the sort sequence may be different from those used for selection.

By default, the records are sorted in *ascending* sequence of values; if you want them to be in descending sequence, specify the keyword DESCENDING. The sort is performed using the Adabas inverted lists and does not result in any records being read.



Note: The use of this clause may result in significant overhead if any descriptor used to control the sort sequence contains a large number of values. This is because the entire value list may have to be scanned until all selected records have been located in the list. When a large number of records is to be sorted, you should use the SORT statement.

Adabas sort limits (see the ADARUN LS parameter in the Adabas documentation) are in effect when the SORTED BY clause is used.

A descriptor which is contained in a periodic group must not be specified in the SORTED BY clause. A multiple-value field (without an index) may be specified.

Non-descriptors may also be specified in the SORTED BY clause. However, this function is not available on mainframes.

If the SORTED BY clause is used, the RETAIN clause must not be used.

See also [Example 9 - SORTED BY Clause](#).

Considerations for Combined Use of STARTING WITH and SORTED BY Clauses

If both the STARTING WITH and the SORTED BY clause are used in the same FIND statement and the underlying database is Adabas, the following should be considered.

With Adabas for Mainframes

On Adabas for Mainframes, the FIND statement is executed in the following steps:

1. All records matching the search criterion are gathered and put in ISN sequence.
2. The records are sorted by the descriptor specified in the SORTED BY clause.

3. The record whose ISN value is specified in the `STARTING WITH` clause is positioned in the “sorted-by-descriptor” record list.
4. The records following the record found under Step 3 are returned in the `FIND` loop.

With Adabas for OpenSystems

On Adabas for OpenSystems (UNIX, OpenVMS, Windows) the same statement is executed as follows:

1. All records matching the search criterion are gathered and put in ISN sequence.
2. The record whose ISN value is specified in the `STARTING WITH` clause is positioned in the “sorted-by-ISN” record list.
3. All records following the record found under Step 2 are sorted by the descriptor specified in the `SORTED BY` clause and returned in the `FIND` loop.

Example:

If the following program is executed with Adabas for Mainframes and Adabas for UNIX/OpenVMS/Windows:

```
DEFINE DATA LOCAL
1 V1 VIEW OF EMPLOYEES
  2 NAME
  2 FIRST-NAME
  2 CITY
1 #ISN (I4)
END-DEFINE
FORMAT NL=5 SG=OFF PS=43 AL=15
*
PRINT  'FIND' (I)
FIND V1 WITH NAME = 'B' THRU 'BALBIN'
  RETAIN AS 'SET1'
  IF *COUNTER = 4 THEN
    #ISN := *ISN
  END-IF
  DISPLAY *ISN V1
END-FIND
*
PRINT / 'FIND .. SORTED BY NAME' (I)
FIND V1 WITH 'SET1'
  SORTED BY NAME
  DISPLAY *ISN V1
END-FIND
*
PRINT / 'FIND .. STARTING WITH ISN = ' (I) #ISN (AD=I)
FIND V1 WITH 'SET1'
  STARTING WITH ISN = #ISN
  DISPLAY *ISN V1
END-FIND
```



```

*
PRINT / 'FIND .. STARTING WITH ISN = ' (I) #ISN (AD=I)
      ' .. SORTED BY NAME' (I)
FIND V1 WITH 'SET1'
  STARTING WITH ISN = #ISN
  SORTED BY NAME
  DISPLAY *ISN V1
END-FIND
END

```

The result is as follows:

Results on Natural for Mainframes

ISN	NAME	FIRST-NAME	CITY

FIND V1 WITH NAME = 'B' THRU 'BALBIN'			
12	BAILLET	PATRICK	LYS LEZ LANNOY
58	BAGAZJA	MARJAN	MONTHERME
351	BAECKER	JOHANNES	FRANKFURT
355	BAECKER	KARL	SINDELFINGEN
370	BACHMANN	HANS	MUENCHEN
490	BALBIN	ENRIQUE	BARCELONA
650	BAKER	SYLVIA	OAK BROOK
913	BAKER	PAULINE	DERBY
FIND .. SORTED BY NAME			
370	BACHMANN	HANS	MUENCHEN
351	BAECKER	JOHANNES	FRANKFURT
355	BAECKER	KARL	SINDELFINGEN
58	BAGAZJA	MARJAN	MONTHERME
12	BAILLET	PATRICK	LYS LEZ LANNOY
650	BAKER	SYLVIA	OAK BROOK
913	BAKER	PAULINE	DERBY
490	BALBIN	ENRIQUE	BARCELONA
FIND .. STARTING WITH ISN = 355			
370	BACHMANN	HANS	MUENCHEN
490	BALBIN	ENRIQUE	BARCELONA
650	BAKER	SYLVIA	OAK BROOK
913	BAKER	PAULINE	DERBY
FIND .. STARTING WITH ISN = 355 .. SORTED BY NAME			
58	BAGAZJA	MARJAN	MONTHERME
12	BAILLET	PATRICK	LYS LEZ LANNOY
650	BAKER	SYLVIA	OAK BROOK
913	BAKER	PAULINE	DERBY
490	BALBIN	ENRIQUE	BARCELONA

Results on Natural for Open Systems

ISN	NAME	FIRST-NAME	CITY

FIND V1 WITH NAME = 'B' THRU 'BALBIN'			
12	BAILLET	PATRICK	LYS LEZ LANNOY
58	BAGAZJA	MARJAN	MONTHERME
351	BAECKER	JOHANNES	FRANKFURT
355	BAECKER	KARL	SINDELFINGEN
370	BACHMANN	HANS	MUENCHEN
490	BALBIN	ENRIQUE	BARCELONA
650	BAKER	SYLVIA	OAK BROOK
913	BAKER	PAULINE	DERBY
FIND .. SORTED BY NAME			
370	BACHMANN	HANS	MUENCHEN
351	BAECKER	JOHANNES	FRANKFURT
355	BAECKER	KARL	SINDELFINGEN
58	BAGAZJA	MARJAN	MONTHERME
12	BAILLET	PATRICK	LYS LEZ LANNOY
650	BAKER	SYLVIA	OAK BROOK
913	BAKER	PAULINE	DERBY
490	BALBIN	ENRIQUE	BARCELONA
FIND .. STARTING WITH ISN = 355			
370	BACHMANN	HANS	MUENCHEN
490	BALBIN	ENRIQUE	BARCELONA
650	BAKER	SYLVIA	OAK BROOK
913	BAKER	PAULINE	DERBY
FIND .. STARTING WITH ISN = 355 .. SORTED BY NAME			
370	BACHMANN	HANS	MUENCHEN
650	BAKER	SYLVIA	OAK BROOK
913	BAKER	PAULINE	DERBY
490	BALBIN	ENRIQUE	BARCELONA

A **FIND** statement with at most one of these options (**SORTED BY** or **STARTING WITH ISN**) always returns the same records in the same sequence, regardless under which system the statement is executed. If, however, both clauses are used together, the result returned depends on which Adabas platform is used to serve the database statement.

Therefore, if a Natural program is intended to be used on multiple platforms, the combination of a **SORTED BY** and **STARTING WITH ISN** clause in the same **FIND** statement should be avoided.

RETAIN Clause

This clause only applies to Adabas databases.

This clause is not permitted with Entire System Server.

RETAIN AS *operand6*

Operand Definition Table:

Operand	Possible Structure			Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand6</i>	C	S				A								yes	no

Syntax Element Description:

Syntax Element	Description
RETAIN AS	Retain Result: By using the RETAIN clause, the result of an extensive search in large files can be retained for further processing. The selection is retained as an ISN-set in the Adabas work file. The set may be used in subsequent FIND statements as a basic search criterion for further refinement of the set or for further processing of the records. The set created is file-specific and may only be used in another FIND statement that processes the same file. The set may be referenced by any Natural program.
<i>operand6</i>	Set Name: The set name is used to identify the record set. It may be specified as an alphanumeric constant or as the content of an alphanumeric user-defined variable. Duplicate set names are not checked; consequently, if a duplicate set name is specified, the new set replaces the old set.

See also [Example 10 - RETAIN Clause](#).

Releasing Sets

There is no specific limit for the number of sets that can be retained or the number of ISNs in a set. It is recommended that the minimum number of ISN sets needed at one time be defined. Sets that are no longer needed should be released using the RELEASE SETS statement.

If they are not released with a RELEASE statement, retained sets exist until the end of the Natural session, or until a logon to another library, when they are released automatically. A set created by one program may be referenced by another program for processing or further refinement using additional search criteria.

Updates by Other Users

The records identified by the ISNs in a retained set are not locked against access and/or update by other users. Before you process records from the set, it is therefore useful to check whether the original search criteria which were used to create the set are still valid: This check is done with another `FIND` statement, using the set name in the `WITH` clause as a basic search criterion and specifying in a `WHERE` clause the original search criteria (that is, the basic search criteria as specified in the `WITH` clause of the `FIND` statement which was used to create the set).

Restriction

If the `RETAIN` clause is used, the `SORTED BY` clause must not be used.

WHERE Clause

`WHERE logical-condition`

The `WHERE` clause may be used to specify an additional selection criterion (*logical-condition*) which is evaluated *after* a value has been read and *before* any processing is performed on the value (including the `AT BREAK` evaluation).

The syntax for a *logical-condition* is described in the section *Logical Condition Criteria* in the *Programming Guide*.

If a processing limit is specified in a `FIND` statement containing a `WHERE` clause, records which are rejected as a result of the `WHERE` clause are *not* counted against the limit. These records are, however, counted against a global limit specified in the Natural session parameter `LT`, the `GLOBALS` command or the `LIMIT` statement.

See also [Example 11 - WHERE Clause](#).

IF NO RECORDS FOUND Clause

Structured Mode Syntax

```
IF NO [RECORDS] [FOUND]
{
    ENTER
    statement ...
}
END-NOREC
```

Reporting Mode Syntax

```
IF NO [RECORDS] [FOUND]
{
    ENTER
    statement
    DO statement ... DOEND
}
```

Syntax Element Description:

Syntax Element	Description
IF NO RECORDS FOUND	IF NO RECORDS FOUND Clause: The IF NO RECORDS FOUND clause may be used to cause a processing loop initiated with a FIND statement to be entered in the event that no records meet the selection criteria specified in the WITH clause and the WHERE clause. If no records meet the specified WITH and WHERE criteria, the IF NO RECORDS FOUND clause causes the FIND processing loop to be executed once with an “empty” record. If this is not desired, specify the statement <code>ESCAPE BOTTOM</code> within the IF NO RECORDS FOUND clause.
ENTER <i>statement</i> ...	Statement Execution: If one or more statements are specified with the IF NO RECORDS FOUND clause, the statements will be executed immediately before the processing loop is entered. If no statements are to be executed before entering the loop, the keyword ENTER must be used.
END-NOREC	End of IF NO RECORDS FOUND Clause: In structured mode, the Natural reserved word END-NOREC must be used to end the IF NO RECORDS FOUND clause. In reporting mode, use the <code>DO ... DOEND</code> statements to supply one or several suitable statements, depending on the situation, and to end the IF NO RECORDS FOUND clause. If you specify only a single statement or the keyword ENTER (see above), you can omit the <code>DO ... DOEND</code> statements. With respect to good coding practice, this is not recommended.
ENTER <i>statement</i> DO <i>statement</i> ... DOEND	

See also [Example 12 - IF NO RECORDS FOUND Clause](#).

Database Values

Unless other value assignments are made in the statements accompanying an IF NO RECORDS FOUND clause, Natural will reset to empty all database fields which reference the file specified in the current loop.

Evaluation of System Functions

Natural system functions are evaluated once for the empty record that is created for processing as a result of the `IF NO RECORDS FOUND` clause.

Restriction

This clause cannot be used with `FIND FIRST`, `FIND NUMBER` and `FIND UNIQUE`.

Examples

- [Example 1 - PASSWORD Clause](#)
- [Example 2 - CIPHER Clause](#)
- [Example 3 - Basic Search Criteria in WITH Clause](#)
- [Example 4 - Basic Search Criteria with Multiple-Value Field](#)
- [Example 5 - Various Samples of Complex Search Expression in WITH Clause](#)
- [Example 6 - Various Samples of Using Database Arrays](#)
- [Example 7 - Using Physically Coupled Files](#)
- [Example 8 - VIA Clause](#)
- [Example 9 - SORTED BY Clause](#)
- [Example 10 - RETAIN Clause](#)
- [Example 11 - WHERE Clause](#)
- [Example 12 - IF NO RECORDS FOUND Clause](#)
- [Example 13 - Using System Variables with the FIND Statement](#)
- [Example 14 - Multiple FIND Statements](#)
- [Example 15 - SHARED HOLD Clause](#)
- [Example 16 - SKIP RECORDS Clause](#)

See also the example for `FIND NUMBER`: program [FNDNUM](#).

Example 1 - PASSWORD Clause

```
** Example 'FNDPWD': FIND (with PASSWORD clause)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 PERSONNEL-ID
*
1 #PASSWORD (A8)
END-DEFINE
*
INPUT 'ENTER PASSWORD FOR EMPLOYEE FILE:' #PASSWORD (AD=N)
LIMIT 2
*
```

```

FIND EMPLOY-VIEW PASSWORD = #PASSWORD
      WITH NAME = 'SMITH'
  DISPLAY NOTITLE NAME PERSONNEL-ID
END-FIND
*
END

```

Output of Program FNDPWD:

```
ENTER PASSWORD FOR EMPLOYEE FILE:
```

Example 2 - CIPHER Clause

```

** Example 'FNDCIP': FIND (with PASSWORD/CIPHER clause)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 PERSONNEL-ID
*
1 #PASSWORD (A8)
1 #CIPHER (N8)
END-DEFINE
*
LIMIT 2
INPUT 'ENTER PASSWORD FOR EMPLOYEE FILE: ' #PASSWORD (AD=N)
      / 'ENTER CIPHER KEY FOR EMPLOYEE FILE: ' #CIPHER (AD=N)
*
FIND EMPLOY-VIEW PASSWORD = #PASSWORD
      CIPHER = #CIPHER
      WITH NAME = 'SMITH'
  DISPLAY NOTITLE NAME PERSONNEL-ID
END-FIND
*
END Output of Program FNDCIP:

```

```

ENTER PASSWORD FOR EMPLOYEE FILE:
ENTER CIPHER KEY FOR EMPLOYEE FILE:

```

Example 3 - Basic Search Criteria in WITH Clause

```
FIND STAFF WITH NAME = 'SMITH'  
FIND STAFF WITH CITY NE 'BOSTON'  
FIND STAFF WITH BIRTH = 610803  
FIND STAFF WITH BIRTH = 610803 THRU 610811  
FIND STAFF WITH NAME = 'O HARA' OR = 'JONES' OR = 'JACKSON'  
FIND STAFF WITH PERSONNEL-ID = 100082 THRU 100100  
                                BUT NOT 100087 THRU 100095
```

Example 4 - Basic Search Criteria with Multiple-Value Field

When the descriptor used in the basic search criteria is a multiple-value field, basically four different kinds of results can be obtained (the field MU-FIELD in the following examples is assumed to be a multiple-value field):

```
FIND XYZ-VIEW WITH MU-FIELD = 'A'
```

This statement returns records in which *at least one* occurrence of MU-FIELD has the value A.

```
FIND XYZ-VIEW WITH MU-FIELD NOT EQUAL 'A'
```

This statement returns records in which *at least one* occurrence of MU-FIELD *does not* have the value A.

```
FIND XYZ-VIEW WITH NOT MU-FIELD NOT EQUAL 'A'
```

This statement returns records in which *every* occurrence of MU-FIELD has the value A.

```
FIND XYZ-VIEW WITH NOT MU-FIELD = 'A'
```

This statement returns records in which *none* of the occurrences of MU-FIELD has the value A.

Example 5 - Various Samples of Complex Search Expression in WITH Clause

```
FIND STAFF WITH BIRTH LT 19770101 AND DEPT = 'DEPT06'
```

```
FIND STAFF WITH JOB-TITLE = 'CLERK TYPIST'  
                                AND (BIRTH GT 19560101 OR LANG = 'SPANISH')
```



```
FIND STAFF WITH JOB-TITLE = 'CLERK TYPIST'
                AND NOT (BIRTH GT 19560101 OR LANG = 'SPANISH')
```

```
FIND STAFF WITH DEPT = 'ABC' THRU 'DEF'
                AND CITY = 'WASHINGTON' OR = 'LOS ANGELES'
                AND BIRTH GT 19360101
```

```
FIND CARS WITH MAKE = 'VOLKSWAGEN'
                AND COLOR = 'RED' OR = 'BLUE' OR = 'BLACK'
```

Example 6 - Various Samples of Using Database Arrays

The following examples assume that the field `SALARY` is a descriptor contained within a periodic group, and the field `LANG` is a multiple-value field.

```
FIND EMPLOYEES WITH SALARY LT 20000
```

Results in a search of all occurrences of `SALARY`.

```
FIND EMPLOYEES WITH SALARY (1) LT 20000
```

Results in a search of the first occurrence only.

```
FIND EMPLOYEES WITH SALARY (1:4) LT 20000      /* invalid
```

A range specification must not be specified for a field within a periodic group used as a search criterion.

```
FIND EMPLOYEES WITH LANG = 'FRENCH'
```

Results in a search of all values of `LANG`.

```
FIND EMPLOYEES WITH LANG (1) = 'FRENCH'        /* invalid
```

An index must not be specified for a multiple-value field used as a search criterion.

Example 7 - Using Physically Coupled Files

```
** Example 'FNDCPL': FIND (using coupled files)
** NOTE: Adabas files must be physically coupled when using the
**       COUPLED clause without the VIA clause.
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
1 VEHIC-VIEW VIEW OF VEHICLES
  2 MAKE
```

FIND

```
END-DEFINE
*
FIND EMPLOY-VIEW WITH CITY = 'FRANKFURT'
    AND COUPLED TO
    VEHIC-VIEW WITH MAKE = 'VW'
    DISPLAY NOTITLE NAME
END-FIND
*
END
```

Example 8 - VIA Clause

```
** Example 'FNDVIA': FIND (with VIA clause)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
2 PERSONNEL-ID
2 NAME
2 FIRST-NAME
1 VEHIC-VIEW VIEW OF VEHICLES
2 PERSONNEL-ID
END-DEFINE
*
FIND EMPLOY-VIEW WITH NAME = 'ADKINSON'
    AND COUPLED TO VEHIC-VIEW
    VIA PERSONNEL-ID = PERSONNEL-ID WITH MAKE = 'VOLVO'
    DISPLAY PERSONNEL-ID NAME FIRST-NAME
END-FIND
*
END
```

Output of Program FNDVIA:

Page	1	05-01-17	13:18:22
PERSONNEL ID	NAME	FIRST-NAME	

20011000	ADKINSON	BOB	

Example 9 - SORTED BY Clause

```

** Example 'FNDSOR': FIND (with SORTED BY clause)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 CITY
  2 NAME
  2 FIRST-NAME
  2 PERSONNEL-ID
END-DEFINE
*
LIMIT 10
FIND EMPLOY-VIEW WITH CITY = 'FRANKFURT'
      SORTED BY NAME PERSONNEL-ID

  DISPLAY NOTITLE NAME (IS=ON) FIRST-NAME PERSONNEL-ID
END-FIND
*
END

```

Output of Program FNDSOR:

NAME	FIRST-NAME	PERSONNEL ID
-----	-----	-----
BAECKER	JOHANNES	11500345
BECKER	HERMANN	11100311
BERGMANN	HANS	11100301
BLAU	SARAH	11100305
BLOEMER	JOHANNES	11200312
DIEDRICHS	HUBERT	11600301
DOLLINGER	MARGA	11500322
FALTER	CLAUDIA	11300311
	HEIDE	11400311
FREI	REINHILD	11500301

Example 10 - RETAIN Clause

```

** Example 'RELEX1': FIND (with RETAIN clause and RELEASE statement)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 CITY
  2 BIRTH
  2 NAME
*
1 #BIRTH (D)
END-DEFINE

```

```
*
MOVE EDITED '19400101' TO #BIRTH (EM=YYYYMMDD)
*
FIND NUMBER EMPLOY-VIEW WITH BIRTH GT #BIRTH
    RETAIN AS 'AGESET1'
IF *NUMBER = 0
    STOP
END-IF
*
FIND EMPLOY-VIEW WITH 'AGESET1' AND CITY = 'NEW YORK'
    DISPLAY NOTITLE NAME CITY BIRTH (EM=YYYY-MM-DD)
END-FIND
*
RELEASE SET 'AGESET1'
*
END
```

Output of Example 10:

NAME	CITY	DATE OF BIRTH

RUBIN	NEW YORK	1945-10-27
WALLACE	NEW YORK	1945-08-04

Example 11 - WHERE Clause

```
** Example 'FNDWHE': FIND (with WHERE clause)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
2 PERSONNEL-ID
2 NAME
2 JOB-TITLE
2 CITY
END-DEFINE
*
FIND EMPLOY-VIEW WITH CITY = 'PARIS'
    WHERE JOB-TITLE = 'INGENIEUR COMMERCIAL'
    DISPLAY NOTITLE
        CITY JOB-TITLE PERSONNEL-ID NAME
END-FIND
*
END
```

Output of Program FNDWHE:

CITY	CURRENT POSITION	PERSONNEL ID	NAME
PARIS	INGENIEUR COMMERCIAL	50007300	CAHN
PARIS	INGENIEUR COMMERCIAL	50006500	MAZUY
PARIS	INGENIEUR COMMERCIAL	50004700	FAURIE
PARIS	INGENIEUR COMMERCIAL	50004400	VALLY
PARIS	INGENIEUR COMMERCIAL	50002800	BRETON
PARIS	INGENIEUR COMMERCIAL	50001000	GIGLEUX
PARIS	INGENIEUR COMMERCIAL	50000400	KORAB-BRZOZOWSKI

Example 12 - IF NO RECORDS FOUND Clause

```

** Example 'FNDIFN': FIND (using IF NO RECORDS FOUND)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
  2 FIRST-NAME
1 VEHIC-VIEW VIEW OF VEHICLES
  2 PERSONNEL-ID
  2 MAKE
END-DEFINE
*
LIMIT 15
EMP. READ EMPLOY-VIEW BY NAME STARTING FROM 'JONES'
/*
  VEH. FIND VEHIC-VIEW WITH PERSONNEL-ID = PERSONNEL-ID (EMP.)

  IF NO RECORDS FOUND
    MOVE '*** NO CAR ***' TO MAKE
  END-NOREC
/*
  DISPLAY NOTITLE
    NAME (EMP.) (IS=ON)
    FIRST-NAME (EMP.) (IS=ON)
    MAKE (VEH.)

  END-FIND
/*
END-READ
END

```

Output of Program FNDIFN:

NAME	FIRST-NAME	MAKE

JONES	VIRGINIA	CHRYSLER
	MARSHA	CHRYSLER
		CHRYSLER
	ROBERT	GENERAL MOTORS
	LILLY	FORD
		MG
	EDWARD	GENERAL MOTORS
	MARTHA	GENERAL MOTORS
	LAUREL	GENERAL MOTORS
	KEVIN	DATSUN
	GREGORY	FORD
JOPER	MANFRED	*** NO CAR ***
JOUSSELIN	DANIEL	RENAULT
JUBE	GABRIEL	*** NO CAR ***
JUNG	ERNST	*** NO CAR ***
JUNKIN	JEREMY	*** NO CAR ***
KAISER	REINER	*** NO CAR ***

Example 13 - Using System Variables with the FIND Statement

```
** Example 'FNDVAR': FIND (using *ISN, *NUMBER, *COUNTER)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
  2 CITY
END-DEFINE
*
LIMIT 3
FIND EMPLOY-VIEW WITH CITY = 'MADRID'
  DISPLAY NOTITLE PERSONNEL-ID NAME
    *ISN *NUMBER *COUNTER
END-FIND
*
END
```

Output of Program FNDVAR

PERSONNEL ID	NAME	ISN	NMBR	CNT

60000114	DE JUAN	400	41	1
60000136	DE LA MADRID	401	41	2
60000209	PINERO	405	41	3

Example 14 - Multiple FIND Statements

In the following example, first all people named SMITH are selected from the EMPLOYEES file. Then the PERSONNEL-ID from the EMPLOYEES file is used as the search key for an access to the VEHICLES file.

```

** Example 'FNDMUL': FIND (with multiple files)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
  2 FIRST-NAME
1 VEHIC-VIEW VIEW OF VEHICLES
  2 PERSONNEL-ID
  2 MAKE
END-DEFINE
*
LIMIT 15
EMP. FIND EMPLOY-VIEW WITH NAME = 'SMITH'
/*
  VEH. FIND VEHIC-VIEW WITH PERSONNEL-ID = EMP.PERSONNEL-ID
  IF NO RECORDS FOUND
    MOVE '*** NO CAR ***' TO MAKE
  END-NOREC
  DISPLAY NOTITLE
    EMP.NAME (IS=ON)
    EMP.FIRST-NAME (IS=ON)
    VEH.MAKE
  END-FIND
END-FIND
END

```

Output of Program FNDMUL:

The resulting report shows the NAME and FIRST-NAME (obtained from the EMPLOYEES file) of all people named SMITH as well as the MAKE of each car (obtained from the VEHICLES file) owned by these people.

NAME	FIRST-NAME	MAKE

SMITH	GERHARD	ROVER
	SEYMOUR	*** NO CAR ***
	MATILDA	FORD
	ANN	*** NO CAR ***
	TONI	TOYOTA
	MARTIN	*** NO CAR ***
	THOMAS	FORD
	SUNNY	*** NO CAR ***
	MARK	FORD
	LOUISE	CHRYSLER
	MAXWELL	MERCEDES-BENZ
		MERCEDES-BENZ
	ELSA	CHRYSLER
	CHARLY	CHRYSLER
	LEE	*** NO CAR ***
	FRANK	FORD

Example 15 - SHARED HOLD Clause


```
FIND EMPL-VIEW WITH NAME = ...  
  IN SHARED HOLD MODE=Q  /* Record in shared hold until next record is read.  
  ...  
  GET EMPL-VIEW  *ISN      /* The record remains unchanged!  
  ...  
END-FIND
```

Example 16 - SKIP RECORDS Clause

```
FIND EMPL-VIEW WITH NAME = ... /* Records found are put in hold while reading.  
  SKIP RECORDS IN HOLD        /* Records already held by other users are  
  ...                          /* skipped to prevent error NAT3145.  
  UPDATE  
  END TRANSACTION  
END-FIND
```


74 FOR

■ Function	588
■ Syntax Description	588
■ Example	590



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [REPEAT](#) | [ESCAPE](#)

Belongs to Function Group: [Loop Execution](#)

Function

The `FOR` statement is used to initiate a processing loop and to control the number of times the loop is processed.

Consistency Check

Before the `FOR` loop is entered, the values of the operands are checked to ensure that they are consistent (that is, the value of `operand3` can be reached or exceeded by repeatedly adding `operand4` to `operand2`). If the values are not consistent, the `FOR` loop is not entered (however, no error message is output, except when the `STEP` value is zero).

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition	
<i>operand1</i>		S					N	P	I	F							yes	yes
<i>operand2</i>	C	S			N		N	P	I	F							yes	no
<i>arithmetic-expression</i>		S					N	P	I	F							no	no
<i>operand3</i>	C	S			N		N	P	I	F							yes	no

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand4</i>	C	S			N		N	P	I	F						yes	no

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Loop Control Variable (<i>operand1</i>) and Initial Setting (<i>operand2</i>): <i>operand1</i> is used to control the number of times the processing loop is to be executed. It may be a database field or a user-defined variable. The value specified after the keyword FROM (<i>operand2</i>) is assigned to the loop control variable field before the processing loop is entered for the first time. This value is incremented (or decremented if the STEP value is negative) using the value specified after the STEP keyword (<i>operand4</i>) each additional time the loop is processed. The loop control variable value may be referenced during the execution of the processing loop and will contain the current value of the loop control variable. Note: The keywords [:]=, EQ or FROM can be omitted.
<i>operand2</i>	
<i>operand3</i>	TO Value: The processing loop is terminated when <i>operand1</i> is greater than (or less than if the initial value of the STEP value was negative) the value specified for <i>operand3</i>. Note: The keyword TO or TRU can be omitted.
STEP <i>operand4</i>	STEP Value: The STEP value may be positive or negative. If a STEP value is not specified, an increment of +1 is used. The compare operation will be adjusted to “less than” or “greater than” depending on the sign of the STEP value when the loop is entered for the first time. Note: 1. <i>operand4</i> must not be zero. 2. The keyword STEP can be omitted.
(<i>arithmetic-expression</i>)	Arithmetic Expression: In place of <i>operand2</i>, <i>operand3</i> or <i>operand4</i>, any arithmetic expression may be specified.

Syntax Element	Description
	Note: 1. The arithmetic expressions must be enclosed in parentheses. 2. The preceding keyword cannot be omitted. For further information on arithmetic expressions, see arithmetic-expression in the COMPUTE statement description.
END-FOR	End of FOR Statement:
LOOP	In structured mode, the Natural reserved word END-FOR must be used to end the FOR statement. In reporting mode, the Natural statement LOOP is used to end the FOR statement.

Example

```

** Example 'FOREX1S': FOR (structured mode)
*****
DEFINE DATA LOCAL
1 #INDEX (I1)
1 #ROOT (N2.7)
END-DEFINE
*
FOR #INDEX 1 TO 5
  COMPUTE #ROOT = SQRT (#INDEX)
  WRITE NOTITLE '=' #INDEX 3X '=' #ROOT
END-FOR
*
SKIP 1
FOR #INDEX 1 TO 5 STEP 2
  COMPUTE #ROOT = SQRT (#INDEX)
  WRITE '=' #INDEX 3X '=' #ROOT
END-FOR
*
END

```

Output of Program FOREX1S:

```
#INDEX: 1 #ROOT: 1.0000000
#INDEX: 2 #ROOT: 1.4142135
#INDEX: 3 #ROOT: 1.7320508
#INDEX: 4 #ROOT: 2.0000000
#INDEX: 5 #ROOT: 2.2360679

#INDEX: 1 #ROOT: 1.0000000
#INDEX: 3 #ROOT: 1.7320508
#INDEX: 5 #ROOT: 2.2360679
```

Equivalent reporting-mode example: [FOREX1R](#).

75

FORMAT

■ Function	594
■ Syntax Description	594
■ Applicable Parameters	595
■ Example	597

```
FORMAT [(rep)] parameter ...
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [AT END OF PAGE](#) | [AT TOP OF PAGE](#) | [CLOSE PRINTER](#) | [DEFINE PRINTER](#) | [DISPLAY](#) | [EJECT](#) | [NEWPAGE](#) | [PRINT](#) | [SKIP](#) | [SUSPEND IDENTICAL SUPPRESS](#) | [WRITE](#) | [WRITE TITLE](#) | [WRITE TRAILER](#)

Belongs to Function Group: [Creation of Output Reports](#)

Function

The `FORMAT` statement is used to specify input and output parameter settings.

Settings specified with a `FORMAT` statement override (at compilation time) default settings in effect for the session that have been set by a `GLOBALS` command, `SET GLOBALS` statement, or by the Natural administrator.

These settings may in turn be overridden by parameters specified in a [DISPLAY](#), [INPUT](#), [PRINT](#), [WRITE](#), [WRITE TITLE](#) or [WRITE TRAILER](#) statement.

The settings remain in effect until the end of a program or until another `FORMAT` statement is encountered.

A `FORMAT` statement does not generate any executable code in the Natural program. It is not executed in dependence of the logical flow of a program. It is evaluated during program compilation in order to set parameters for compiling `DISPLAY`, `WRITE`, `PRINT` and `INPUT` statements. The settings defined with a `FORMAT` statement are applicable to all `DISPLAY`, `WRITE`, `PRINT` and `INPUT` statements which follow.

Syntax Description

Syntax Element	Description
(<i>rep</i>)	Report Specification: The notation (<i>rep</i>) may be used to specify the identification of the report for which the <code>FORMAT</code> statement is applicable. A value in the range 0 - 31 or a logical name which has been assigned using the DEFINE PRINTER statement may be specified.

Syntax Element	Description
	If (<i>rep</i>) is not specified, the FORMAT statement will be applicable to the first report (Report 0). For information on how to control the format of an output report created with Natural, see <i>Report Format and Control</i> (in the <i>Programming Guide</i>).
<i>parameter</i>	Parameter(s): The parameters can be specified in any order and must be separated by one or more spaces. A single entry must not be split between two statement lines. Field sensitive parameter settings applied here will only be regarded for variable fields used in an INPUT, a WRITE, DISPLAY or PRINT statement of the selected report. They do not apply for text-constants used in any of the mentioned statements. Example: <pre> DEFINE DATA LOCAL 1 VARI (A4) INIT <'1234'> /* Output END-DEFINE /* Produced FORMAT AD=U /* ----- WRITE 'Text' VARI /* Text 1234 WRITE 'Text' (AD=U) VARI /* Text 1234 END </pre> See also <i>Applicable Parameters</i> below.

Applicable Parameters

See the *Parameter Reference* for a detailed description of the session parameters which may be used.

Parameter	Description
AD	Attribute Definition
AL	Alphanumeric Length for Output
BX	Box Definition
CD	Color Definition
DF	Date Format
DL	Display Length for Output
EM	Edit Mask
ES	Empty Line Suppression
FC	Filler Character
FL	Floating Point Mantissa Length

Parameter	Description
GC	Filler Character for Group Heading
HC	Header Centering
HW	Heading Width
IC	Insertion Character
ICU	Unicode Insertion Character
IP	Input Prompting Text
IS	Identical Suppress
KD	Key Definition
LC	Leading Characters
LCU	Unicode Leading Characters
LS	Line Size
MC	Multiple-Value Field Count (Can only be used in reporting mode.)
MP	Maximum Number of Pages of a Report, see Note below.
MS	Manual Skip
NL	Numeric Length for Output
PC	Periodic Group Count (Can only be used in reporting mode.)
PM	Print Mode
PS	Page Size, see Note below.
SF	Spacing Factor
SG	Sign Position
TC	Trailing Characters
TCU	Unicode Trailing Characters
UC	Underlining Character
ZP	Zero Printing



Note: The parameters `MP` and `PS` do not take effect for a specific I/O statement, but apply to the complete output created for the report. If multiple settings for `MP` and `PS` are performed, the last definition is used.

See also *Underlining Character for Titles and Headers - UC Parameter* (in the *Programming Guide*).

Example

```

** Example 'FMTEX1': FORMAT
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 CITY
  2 POST-CODE
  2 COUNTRY
END-DEFINE
*
FORMAT AL=7      /* Alpha-numeric field output length
          FC=+     /* Filler character for field header
          GC=*     /* Filler character for group header
          HC=L     /* Header left justified
          IC=<<    /* Insert characters
          IS=ON    /* Identical suppress on
          TC=>>    /* Trailing character
          UC==     /* Underline character
          ZP=OFF   /* Zero print off
*
LIMIT 5
READ EMPLOY-VIEW BY NAME
  DISPLAY NOTITLE
    NAME 3X CITY 3X POST-CODE 3X COUNTRY
END-READ
*
END

```

Output of Program FMTEX1:

NAME++++++	CITY++++++	POSTAL++++	COUNTRY++++
=====	=====	=====	=====
		ADDRESS++++	
<<ABELLAN>>	<<MADRID >>	<<28014 >>	<<E >>
<<ACHIESO>>	<<DERBY >>	<<DE3 4TR>>	<<UK >>
<<ADAM >>	<<JOIGNY >>	<<89300 >>	<<F >>
<<ADKINSO>>	<<BROOKLY>>	<<11201 >>	<<USA>>
	<<BEVERLE>>	<<90211 >>	

76

GET

■ Function	600
■ Restrictions	600
■ Syntax Description	601
■ Example	602

In structured mode and in reporting mode using a `DEFINE DATA LOCAL` statement, the following syntax applies:

```
GET [IN] [FILE] view-name
[PASSWORD=operand1]
[CIPHER=operand2]
[ RECORDS ] { operand3 }
               *ISN [r] }
```

In reporting mode using no `DEFINE DATA LOCAL` statement, the following syntax applies:

```
GET [IN] [FILE] ddm-name
[PASSWORD=operand1]
[CIPHER=operand2]
[ RECORDS ] { operand3 } operand4 ...
               *ISN [r] }
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [DELETE](#) | [END TRANSACTION](#) | [FIND](#) | [GET SAME](#) | [GET TRANSACTION](#) | [HISTOGRAM](#) | [LIMIT](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [READLOB](#) | [RETRY](#) | [STORE](#) | [UPDATE](#) | [UPDATELOB](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The `GET` statement is used to read a record with a given Adabas Internal Sequence Number (ISN).

The `GET` statement does not cause a processing loop to be initiated.

Restrictions

- The `GET` statement cannot be used for DL/I and SQL databases.
- The `GET` statement cannot be used with Entire System Server.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S				A										yes	no
<i>operand2</i>	C	S				N										no	no
<i>operand3</i>	C	S			N	N	P	I	B *							yes	no
<i>operand4</i>		S	A			A	N	P	I	F	B	D	T	L		yes	yes

* Format B of *operand3* may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
<i>view-name</i>	View Name: In structured mode and in reporting mode using a <code>DEFINE DATA LOCAL</code> statement, the name of a view as defined either directly within a <code>DEFINE DATA</code> statement or in a separate global or local data area.
<i>dgm-name</i>	DDM Name: In reporting mode using no <code>DEFINE DATA LOCAL</code> statement, the name of the data definition module (DDM) is referenced.
<code>PASSWORD=<i>operand1</i></code> <code>CIPHER=<i>operand2</i></code>	PASSWORD Clause/CIPHER Clause: These clauses are applicable only to Adabas and VSAM databases. The <code>PASSWORD</code> clause is used to provide a password when retrieving data from an Adabas file which is password protected. The <code>CIPHER</code> clause is used to provide a cipher key when retrieving data from an Adabas file which is enciphered. See the statements FIND and PASSW for further information.
<code>*ISN / <i>operand3</i></code>	Internal Sequence Number: The ISN must be provided either in the form of a numeric constant or user-defined variable (<i>operand3</i>) in the range from 1 to 4294967295 or via the Natural system variable <code>*ISN</code> . Note: For VSAM databases: For VSAM ESDS, the RBA must be contained in a user-defined variable (numeric format) or must be specified as an integer constant.

Syntax Element	Description
	The same rules apply to VSAM RRDS with the exception that the RRN must be provided instead of the RBA.
(<i>r</i>)	Statement Reference: The notation (<i>r</i>) is used to specify the statement which contains the FIND or READ statement used to initially read the record. If (<i>r</i>) is not specified, the GET statement will be related to the innermost active processing loop. (<i>r</i>) may be specified as a reference statement number or as a statement label.
<i>operand4</i>	Reference to Database Fields: In reporting mode, subsequent references to database fields that have been read with a GET statement can contain the label or line number of the GET statement.

Example

```

** Example 'GETEX1': GET
*****
DEFINE DATA LOCAL
1 PERSONS VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
  2 FIRST-NAME
1 SALARY-INFO VIEW OF EMPLOYEES
  2 NAME
  2 CURR-CODE (1:1)
  2 SALARY    (1:1)
*
1 #ISN-ARRAY  (B4/1:10)
1 #LINE-NR    (N2)
END-DEFINE
*
FORMAT PS=16
LIMIT 10
READ PERSONS BY NAME
  MOVE *COUNTER TO #LINE-NR
  MOVE *ISN     TO #ISN-ARRAY (#LINE-NR)
  DISPLAY #LINE-NR PERSONNEL-ID NAME FIRST-NAME
/*
AT END OF PAGE
  INPUT / 'PLEASE SELECT LINE-NR FOR SALARY INFORMATION:' #LINE-NR
  IF #LINE-NR = 1 THRU 10
    GET SALARY-INFO #ISN-ARRAY (#LINE-NR)
    WRITE / SALARY-INFO.NAME
           SALARY-INFO.SALARY    (1)

```



```

                SALARY-INFO.CURR-CODE (1)
    END-IF
  END-ENDPAGE
/*
END-READ
END

```

Output of Program GETEX1:

Page 1 05-01-13 13:17:42

#LINE-NR	PERSONNEL ID	NAME	FIRST-NAME
1	60008339	ABELLAN	KEPA
2	30000231	ACHIESON	ROBERT
3	50005800	ADAM	SIMONE
4	20008800	ADKINSON	JEFF
5	20009800	ADKINSON	PHYLLIS
6	20012700	ADKINSON	HAZEL
7	20013800	ADKINSON	DAVID
8	20019600	ADKINSON	CHARLIE
9	20008600	ADKINSON	MARTHA
10	20005700	ADKINSON	TIMMIE

PLEASE SELECT LINE-NR FOR SALARY INFORMATION: 1

ABELLAN 1450000 PTA

77

GET SAME

■ Function	606
■ Restrictions	606
■ Syntax Description	607
■ Example	607

Structured Mode Syntax

GET SAME [(r)]

Reporting Mode Syntax

GET SAME [(r)] [operand1 ...]

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [DELETE](#) | [END TRANSACTION](#) | [FIND](#) | [GET](#) | [GET TRANSACTION DATA](#) | [HISTOGRAM](#) | [LIMIT](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [RETRY](#) | [STORE](#) | [UPDATE](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The GET SAME statement is used to re-read the record currently being processed. It is most frequently used to obtain database array values (periodic groups or multiple-value fields) if the number and range of existing or desired occurrences was not known when the record was initially read.

Restrictions

- GET SAME is only valid for Natural users who are using Adabas or VSAM.
- GET SAME cannot be used with Entire System Server.
- For VSAM databases, GET SAME can only be applied to ESDS and RRDS. For ESDS, the RBA must be contained in a user-defined variable (numeric format) or be specified as an integer constant. The same applies to RRDS, except that the RRN must be provided instead of the RBA.
- An [UPDATE](#) or [DELETE](#) statement must not reference a GET SAME statement. These statements should instead make reference to the [FIND](#), [READ](#) or [GET](#) statement used to read the record initially.

Syntax Description

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	S A	A U N P B	no	yes

Syntax Element Description:

Syntax Element	Description
(<i>r</i>)	Statement Reference: The notation (<i>r</i>) is used to specify the statement which contains the FIND or READ statement used to initially read the record. If (<i>r</i>) is not specified, the GET SAME statement will be related to the innermost active processing loop. (<i>r</i>) may be specified as a reference statement number or as a statement label.
<i>operand1</i>	Fields to Be Made Available: As <i>operand1</i>, you specify the field(s) to be made available as a result of the GET SAME statement. Note: <i>operand1</i> cannot be specified if the field is defined in a DEFINE DATA statement.

Example

```

** Example 'GSAEX1': GET SAME
*****
DEFINE DATA LOCAL
1 I          (P3)
1 POST-ADDRESS VIEW OF EMPLOYEES
  2 FIRST-NAME
  2 NAME
  2 ADDRESS-LINE (I:I)
  2 C*ADDRESS-LINE
  2 POST-CODE
  2 CITY
*
1 #NAME          (A30)
END-DEFINE
*
FORMAT PS=20

```

```
MOVE 1 TO I
*
READ (10) POST-ADDRESS BY NAME
  COMPRESS NAME FIRST-NAME INTO #NAME WITH DELIMITER ','
  WRITE // 12T #NAME
  WRITE / 12T ADDRESS-LINE (I.1)
/*
  IF C*ADDRESS-LINE > 1
    FOR I = 2 TO C*ADDRESS-LINE
      GET SAME /* READ NEXT OCCURRENCE
      WRITE 12T ADDRESS-LINE (I.1)
    END-FOR
  END-IF
  WRITE / POST-CODE CITY
  SKIP 3
END-READ
END
```

Output of Program GSAEX1:

Page 1 05-01-13 13:23:36

```

      ABELLAN,KEPA
      CASTELAN 23-C
28014  MADRID

      ACHIESON,ROBERT
      144 ALLESTREE LANE
      DERBY
      DERBYSHIRE
DE3 4TR  DERBY
```

78

GET TRANSACTION DATA

■ Function	610
■ Restriction	611
■ Syntax Description	611
■ Example	611

GET TRANSACTION [DATA] *operand1* ...

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [DELETE](#) | [END TRANSACTION](#) | [FIND](#) | [GET](#) | [GET SAME](#) | [HISTOGRAM](#) | [LIMIT](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [RETRY](#) | [STORE](#) | [UPDATE](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The `GET TRANSACTION DATA` statement is used to read the data saved with a previous `END TRANSACTION` statement.

`GET TRANSACTION DATA` does not create a processing loop.



Note: For DL/I: The `GET TRANSACTION DATA` statement retrieves checkpoint data saved by an `END TRANSACTION` statement.

System Variable *ETID

The content of the Natural system variable `*ETID` identifies the transaction data to be retrieved from the database.

No Transaction Data Stored

If the `GET TRANSACTION DATA` statement is issued and no transaction data are found, all fields specified in the `GET TRANSACTION DATA` statement will be filled with blanks regardless of format definition.



Caution: Make sure that arithmetic operations are not performed on “empty” transaction data, because this would result in an abnormal termination of the program.

Restriction

The `GET TRANSACTION DATA` statement is only valid for transactions applied to Adabas databases, or to DL/I databases in a batch-oriented BMP region (in IMS TM environments only).

Syntax Description

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	S	A U N P I F B D T	yes	yes

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Field Specification: The sequence, lengths and formats of the fields used in the <code>GET TRANSACTION DATA</code> statement must be identical to the sequence, lengths and formats of the fields specified with the corresponding <code>END TRANSACTION</code> statement. Note: 1. For DL/I: The first <i>operand1</i> must be an 8-byte checkpoint ID. 2. <code>GET TRANSACTION DATA</code> cannot be used if <i>operand1</i> is a dynamic variable.

Example

```

** Example 'GTREX1': GET TRANSACTION
**
** CAUTION: Executing this example will modify the database records!
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
2 PERSONNEL-ID
2 NAME
2 FIRST-NAME
2 MIDDLE-I
2 CITY
*
```

GET TRANSACTION DATA


```
1 #PERS-NR (A8) INIT <' '>
END-DEFINE
*
GET TRANSACTION DATA #PERS-NR
IF #PERS-NR NE ' '
  WRITE 'LAST TRANSACTION PROCESSED FROM PREVIOUS SESSION' #PERS-NR
END-IF
*
REPEAT
  /*
  INPUT 10X 'ENTER PERSONNEL NUMBER TO BE UPDATED:' #PERS-NR
  IF #PERS-NR = ' '
    STOP
  END-IF
  /*
  FIND EMPLOY-VIEW WITH PERSONNEL-ID = #PERS-NR
  IF NO RECORDS FOUND
    REINPUT 'NO RECORD FOUND'
  END-NOREC
  INPUT (AD=M) PERSONNEL-ID (AD=0)
    / NAME
    / FIRST-NAME
    / CITY

  UPDATE
  END TRANSACTION #PERS-NR
END-FIND
  /*
END-REPEAT
END
```

79

HISTOGRAM

■ Function	614
■ Restrictions	615
■ Syntax Description	615
■ System Variables Available with HISTOGRAM	620
■ Examples	621



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [DELETE](#) | [END TRANSACTION](#) | [FIND](#) | [GET](#) | [GET SAME](#) | [GET TRANSACTION DATA](#) | [LIMIT](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [RETRY](#) | [STORE](#) | [UPDATE](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The HISTOGRAM statement is used to read the values of a database field which is defined as a descriptor, subdescriptor or superdescriptor. The values are read directly from the Adabas inverted lists or VSAM index. The HISTOGRAM statement causes a processing loop to be initiated but does not provide access to any database fields other than the field specified in the HISTOGRAM statement.

See also the following sections in the *Programming Guide*:

- *HISTOGRAM Statement*
- *Loop Processing*
- *Referencing of Database Fields Using (r) Notation*



Note: For SQL databases: HISTOGRAM returns the number of rows which have the same value in a specific column.

Restrictions

- This statement cannot be used with DL/I databases or Entire System Server.

When applied to a VSAM database, the HISTOGRAM statement is only valid for KSDS and ESDS.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S					N	P	I	B *						yes	no
<i>operand2</i>	C	S				A										yes	no
<i>operand3</i>		S				A										yes	no
<i>operand4</i>		S				A	N	P	I	F	B	D	T	L		no	no

* Format B of *operand1* may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
<i>operand1</i> / ALL	Number of Descriptor Values: You can limit the number of descriptor values to be processed with the HISTOGRAM statement by specifying <i>operand1</i> - either as a numeric constant (0 - 4294967295) or as a user-defined variable (containing an integer value). ALL may optionally be specified to emphasize that all descriptor values are to be processed. For this statement, the specified limit has priority over a limit set with a LIMIT statement. If a smaller limit is set with the LT parameter (Limit for Processing Loops), the LT limit applies. Note: If you wish to process a 4-digit number of descriptor values, specify it with a leading zero (0nnnn); because Natural interprets every 4-digit number enclosed in parentheses as a line-number reference to a statement. <i>operand1</i> is evaluated when the HISTOGRAM loop is entered. If the value of <i>operand1</i> is modified within the HISTOGRAM loop, this does not affect the number of values read.

Syntax Element	Description
<i>MULTI-FETCH-clause</i>	MULTI-FETCH Clause: See MULTI-FETCH Clause below.
<i>view-name</i>	View Name: As <i>view-name</i>, you specify the name of a view, which is defined either within a DEFINE DATA statement or in a separate global or local data area. The view must not contain any other fields apart from the field used in the HISTOGRAM statement (<i>operand4</i>). If the field in the view is a periodic-group field or multiple-value field that is defined with an index range, only the first occurrence of that range is filled by the HISTOGRAM statement; all other occurrences are not affected by the execution of the HISTOGRAM statement. In reporting mode, <i>view-name</i> is the name of a DDM if no DEFINE DATA LOCAL statement is used.
PASSWORD= <i>operand2</i>	PASSWORD Clause: The PASSWORD clause is used to provide a password (<i>operand2</i>) when retrieving data from an Adabas file which is password-protected. See the statements FIND and PASSW for further information.
SEQUENCE	SEQUENCE Clause: This clause can only be used for Adabas, VSAM and SQL databases. With this clause, you can determine whether the records are to be read in ascending sequence or in descending sequence. ■ The default sequence is ascending (which may, but need not, be explicitly specified by using the keyword ASCENDING). ■ If the records are to be read in descending sequence, you specify the keyword DESCENDING. ■ If, instead of determining it in advance, you want to have the option of determining at runtime whether the records are to be read in ascending or descending sequence, you either specify the keyword VARIABLE or DYNAMIC, followed by a variable (<i>operand3</i>). <i>operand3</i> has to be of format/length A1 and can contain the value A (for “ascending”) or D (for “descending”). ■ If keyword VARIABLE is used, the reading direction (value of <i>operand3</i>) is evaluated at start of the HISTOGRAM processing loop and remains same until the loop is terminated, regardless if the <i>operand3</i> field is altered in the HISTOGRAM loop or not. ■ If keyword DYNAMIC is used, the reading direction (value of <i>operand3</i>) is evaluated before every record fetch in the HISTOGRAM processing loop and may be changed from record to record. This allows to change the

Syntax Element	Description
	scroll sequence from ascending to descending (and vice versa) at any place in the HISTOGRAM loop. Examples of SEQUENCE clause: ■ Example 2 - HISTOGRAM Statement with Records Read in Descending Sequence ■ Example 3 - HISTOGRAM Statement Using Variable Sequence
<i>operand4</i>	Descriptor: As <i>operand4</i>, a descriptor, subdescriptor, superdescriptor or hyperdescriptor may be specified. A descriptor contained within a periodic group may be specified with or without an index. If no index is specified, the descriptor will be selected if the value specified is located in any occurrence. If an index is specified, the descriptor will be selected only if the value is located in the occurrence specified by the index. The index specified must be a constant. An index range must not be used. For a descriptor which is a multiple-value field an index must not be specified; the descriptor will be selected if the value is located in the record regardless of the position of the value.
<i>STARTING-ENDING-clause</i>	STARTING/ENDING Clause: Starting and ending values may be specified using the keywords STARTING and ENDING (or THRU) followed by a constant or a user-defined variable representing the value with which processing is to begin/end. For further information, see Specifying Starting/Ending Values below.
WHERE <i>logical-condition</i>	WHERE Clause: The WHERE clause may be used to specify an additional selection criteria (<i>logical-condition</i>) which is evaluated <i>after</i> a value has been read and <i>before</i> any processing is performed on the value (including the AT BREAK evaluation). The descriptor specified in the WHERE clause must be the same descriptor referenced in the HISTOGRAM statement. No other fields from the selected file are available for processing with a HISTOGRAM statement. The syntax for a <i>logical-condition</i> is described in the section <i>Logical Condition Criteria</i> (in the <i>Programming Guide</i>).
END-HISTOGRAM	End of HISTOGRAM Statement: In structured mode, the Natural reserved word END-HISTOGRAM must be used to end the HISTOGRAM statement.
LOOP	

Syntax Element	Description
	In reporting mode, the Natural statement LOOP must be used to end the HISTOGRAM statement.

MULTI-FETCH Clause

 **Note:** This clause can only be used for Adabas or DB2 databases.

MULTI-FETCH	$\left\{ \begin{array}{l} \text{ON} \\ \text{OFF} \\ [\text{OF}] \text{ multi-fetch-factor} \end{array} \right\}$

For more information, see the section *MULTI-FETCH Clause (Adabas)* in the *Programming Guide* or *Multiple Row Processing (SQL)* in the *Natural for DB2* part in the *Database Management System Interfaces* documentation.

Specifying Starting/Ending Values

Starting and ending values may be specified using the keywords `STARTING` and `ENDING` (or `THRU`) followed by a constant or a user-defined variable representing the value with which processing is to begin/end.

If a starting value is specified and the value is not present, the next higher value is used as the starting value. If no higher value is present, the HISTOGRAM loop will not be entered.

If an ending value is specified, values will be read up to and including the ending value.

Hexadecimal constants may be specified as a starting or ending value for descriptors of format A or B.


Syntax Option 1:

$\left[\begin{array}{l} [\text{STARTING}] \left[\begin{array}{l} \text{WITH} \\ \text{FROM} \end{array} \right] [\text{VALUES}] \text{ operand5} \end{array} \right] \left[\begin{array}{l} \left[\begin{array}{l} \text{THRU} \\ \text{ENDING AT} \end{array} \right] \text{ operand6} \end{array} \right]$

Syntax Option 2:

$[\text{STARTING}] \left[\begin{array}{l} \text{WITH} \\ \text{FROM} \end{array} \right] [\text{VALUES}] \text{ operand5 TO operand6}$

Syntax Option 3:



 **Note:** If the comparators of Diagram 3 are used, the options `ENDING AT`, `THRU` and `TO` may not be used. These comparators are also valid for the `READ` statement.

Operand Definition Table:

Operand	Possible Structure					Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand5</i>	C	S				A	U	N	P	I	F	B	D	T	L			yes	no
<i>operand6</i>	C	S				A	U	N	P	I	F	B	D	T	L			yes	no

Syntax Element Description:

Syntax Element	Description
STARTING FROM ... ENDING AT TO	STARTING FROM / ENDING AT Clauses: The <code>STARTING FROM</code> and <code>ENDING AT</code> clauses are used to limit reading to a user-specified range of values. The <code>STARTING FROM</code> clause (<code>=</code> or <code>EQ</code> or <code>EQUAL TO</code> or <code>[STARTING] FROM</code>) determines the starting value for the read operation. If a starting value is specified, reading will begin with the value specified. If the starting value does not exist, the next higher (or lower for a <code>DESCENDING</code> read) value will be returned. If no higher (or lower for <code>DESCENDING</code>) value exists, the <code>HISTOGRAM</code> loop will not be entered. In order to limit the values to an end-value, you may specify an <code>ENDING AT</code> clause with the terms <code>THRU</code>, <code>ENDING AT</code> or <code>TO</code>, that imply an inclusive range. Whenever the descriptor field exceeds the end-value specified, an automatic loop termination is performed. Although the basic functionality of the <code>TO</code>, <code>THRU</code> and <code>ENDING AT</code> keywords looks quite similar, internally they differ in how they work.
THRU ENDING AT	THRU / ENDING AT Option:

Syntax Element	Description
	If <code>THRU</code> or <code>ENDING AT</code> is used, only the start-value is supplied to the database, but the end-value check is performed by the Natural runtime system, after the value is returned by the database. The <code>THRU</code> and <code>ENDING AT</code> options can be used for all databases which support the <code>HISTOGRAM</code> statements.
<code>T0</code>	Range: If the keyword <code>T0</code> is used, both the start-value and the end-value are sent to the database and Natural does not perform checks for value ranges. If the end-value is exceeded, the database reacts in the same way as when “end-of-file” is reached and the database loop is exited. Since the complete range checking is done by the database, the lower-value (of the range) is always supplied in the start-value and the higher-value filled into the end-value, regardless whether you are browsing in <code>ASCENDING</code> or in <code>DESCENDING</code> order.



Note: The result of `READ/HISTOGRAM THRU/ENDING AT` might differ from the result of `READ/HISTOGRAM T0` if Natural and the accessed database reside on different platforms with different collating sequences.

System Variables Available with HISTOGRAM

The Natural system variables `*ISN`, `*NUMBER`, and `*COUNTER` are available with the `HISTOGRAM` statement.

`*NUMBER` and `*ISN` are only set after the evaluation of the `WHERE` clause. They must not be used in the logical condition of the `WHERE` clause.

System Variable	Explanation
<code>*NUMBER</code>	The system variable <code>*NUMBER</code> contains the number of database records that contain the last value read. For SQL databases, see <i>*NUMBER for SQL Databases</i> in the <i>System Variables</i> documentation.
<code>*ISN</code>	The system variable <code>*ISN</code> contains the number of the occurrence in which the descriptor value last read is contained. <code>*ISN</code> will contain 0 if the descriptor is not contained within a periodic group. <code>*ISN</code> is not available for SQL and VSAM databases.
<code>*COUNTER</code>	The system variable <code>*COUNTER</code> contains a count of the total number of values which have been read (after evaluation of the <code>WHERE</code> clause).

Examples

- [Example 1 - HISTOGRAM Statement](#)
- [Example 2 - HISTOGRAM Statement with Records Read in Descending Sequence](#)
- [Example 3 - HISTOGRAM Statement Using Variable Sequence](#)

Example 1 - HISTOGRAM Statement

```

** Example 'HSTEX1S': HISTOGRAM (structured mode)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 CITY
END-DEFINE
*
LIMIT 8
HISTOGRAM EMPLOY-VIEW CITY STARTING FROM 'M'
  DISPLAY NOTITLE
    CITY 'NUMBER OF/PERSONS' *NUMBER *COUNTER
END-HISTOGRAM
*
END

```

Output of Program HSTEX1S:

CITY	NUMBER OF PERSONS	CNT

MADISON	3	1
MADRID	41	2
MAILLY LE CAMP	1	3
MAMERS	1	4
MANSFIELD	4	5
MARSEILLE	2	6
MATLOCK	1	7
MELBOURNE	2	8

Equivalent reporting-mode example: [HSTEX1R](#).

Example 2 - HISTOGRAM Statement with Records Read in Descending Sequence

```

** Example 'HSTDSCND': HISTOGRAM (with DESCENDING)
*****
DEFINE DATA LOCAL
1 EMPL VIEW OF EMPLOYEES
  2 NAME
END-DEFINE
*
HISTOGRAM (10) EMPL IN DESCENDING SEQUENCE FOR NAME FROM 'ZZZ'
  DISPLAY NAME *NUMBER
END-HISTOGRAM
END

```

Output of Program HSTDSCND:

```

Page          1                                05-01-13   13:41:03

      NAME                NMBR
-----
ZINN                      1
YOT                        1
YNCLAN                    1
YATES                      1
YALCIN                     1
YACKX-COLTEAU             1
XOLIN                      1
WYLLIS                     2
WULFRING                   1
WRIGHT                     1

```

Example 3 - HISTOGRAM Statement Using Variable Sequence

```

** Example 'HSTVSEQ': HISTOGRAM (with VARIABLE SEQUENCE)
*****
DEFINE DATA LOCAL
1 EMPL VIEW OF EMPLOYEES
  2 NAME
*
1 #DIR      (A1)
1 #STARTVAL (A20)
END-DEFINE
*
SET KEY PF3 PF7 PF8
*
MOVE 'ADKINSON' TO #STARTVAL
*
HISTOGRAM (9) EMPL FOR NAME FROM #STARTVAL
  WRITE NAME *NUMBER

```

```

IF *COUNTER = 5
    MOVE NAME TO #STARTVAL
END-IF
END-HISTOGRAM
*
#DIR := 'A'
*
REPEAT
    HISTOGRAM EMPL IN VARIABLE #DIR SEQUENCE
        FOR NAME FROM #STARTVAL
        MOVE NAME TO #STARTVAL
        INPUT NO ERASE (IP=OFF AD=0)
            15/01 NAME *NUMBER
            // 'Direction:' #DIR
            // 'Press PF3 to stop'
            / ' PF7 to go step back'
            / ' PF8 to go step forward'
            / ' ENTER to continue in that direction'
        /*
        IF *PF-KEY = 'PF7' AND #DIR = 'A'
            MOVE 'D' TO #DIR
            ESCAPE BOTTOM
        END-IF
        IF *PF-KEY = 'PF8' AND #DIR = 'D'
            MOVE 'A' TO #DIR
            ESCAPE BOTTOM
        END-IF
        IF *PF-KEY = 'PF3'
            STOP
        END-IF
    END-HISTOGRAM
    /*
    IF *COUNTER(0250) = 0
        STOP
    END-IF
END-REPEAT
END

```

Output of Program HSTVSEQ:

Page	1	05-01-13 13:50:31
ADKINSON	8	
AECKERLE	1	
AFANASSIEV	2	
AHL	1	
AKROYD	1	
ALEMAN	1	
ALESTIA	1	
ALEXANDER	5	
ALLEGRE	1	

MORE

After pressing ENTER:

Page 1 05-01-13 13:50:31

ADKINSON	8
AECKERLE	1
AFANASSIEV	2
AHL	1
AKROYD	1
ALEMAN	1
ALESTIA	1
ALEXANDER	5
ALLEGRE	1

AKROYD	1

Direction: A

Press PF3 to stop
PF7 to go step back
PF8 to go step forward
ENTER to continue in that direction

80

IF

■ Function	626
■ Syntax Description	626
■ Example	627

Structured Mode Syntax

```
IF logical-condition
  [THEN] statement ...
  [ELSE statement ...]
END-IF
```

Reporting Mode Syntax

```
IF logical-condition
  [THEN] { statement
           DO statement ... DOEND }
  [ ELSE { statement
           DO statement ... DOEND } ]
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [DECIDE FOR](#) | [DECIDE ON](#) | [IF SELECTION](#) | [ON ERROR](#)

Belongs to Function Group: [Processing of Logical Conditions](#)

Function

The IF statement is used to control execution of a statement or group of statements based on a logical condition.



Note: If no action is to be performed in case the condition is met, you must specify the statement `IGNORE` in the `THEN` clause.

Syntax Description

Syntax Element	Description
IF <i>logical-condition</i>	Logical Condition Criterion: The logical condition which is used to determine whether the statement or statements specified with the IF statement are to be executed. Examples:

Syntax Element	Description
	<pre>IF #A = #B IF LEAVE-TAKEN GT 30 IF #SALARY(1) * 1.15 GT 5000 IF SALARY (4) = 5000 THRU 6000 IF DEPT = 'A10' OR = 'A20' OR = 'A30'</pre> For further information, see the section <i>Logical Condition Criteria</i> (in the <i>Programming Guide</i>).
THEN <i>statement</i>	THEN Clause: In the THEN clause, you specify the <i>statement</i>(s) to be executed if the logical condition is true.
ELSE <i>statement</i>	ELSE Clause: In the ELSE clause, you specify the <i>statement</i>(s) to be executed if the logical condition is <i>not</i> true.
END-IF	END of IF Statement:
<pre><i>statement</i> DO <i>statement</i> ... DOEND</pre>	In structured mode, the Natural reserved word END-IF must be used to end the IF statement. In reporting mode, use the DO ... DOEND statements to supply one or several suitable statements, depending on the situation, and to end the clauses and the IF statement. If you specify only a single statement, you can omit the DO ... DOEND statements. With respect to good coding practice, this is not recommended.

Example

```
** Example 'IFEX1S': IF (structured mode)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
  2 FIRST-NAME
  2 SALARY (1)
  2 BIRTH
1 VEHIC-VIEW VIEW OF VEHICLES
  2 PERSONNEL-ID
  2 MAKE
*
1 #BIRTH (D)
END-DEFINE
*
MOVE EDITED '19450101' TO #BIRTH (EM=YYYYMMDD)
```

```

SUSPEND IDENTICAL SUPPRESS
LIMIT 20
*
FND. FIND EMPLOY-VIEW WITH CITY = 'FRANKFURT'
      SORTED BY NAME BIRTH
  IF SALARY (1) LT 40000
    WRITE NOTITLE '*****' NAME 30X 'SALARY LT 40000'
  ELSE
    IF BIRTH GT #BIRTH
      FIND VEHIC-VIEW WITH PERSONNEL-ID = PERSONNEL-ID (FND.)
      DISPLAY (IS=ON)
        NAME BIRTH (EM=YYYY-MM-DD)
        SALARY (1) MAKE (AL=8)
    END-FIND
  END-IF
END-IF
END-FIND
END

```

Output of Program IFEX1S:

NAME	DATE OF BIRTH	ANNUAL SALARY	MAKE
BAECKER	1956-01-05	74400	BMW
***** BECKER			SALARY LT 40000
BLOEMER	1979-11-07	45200	FIAT
FALTER	1954-05-23	70800	FORD
***** FALTER			SALARY LT 40000
***** GROTHE			SALARY LT 40000
***** HEILBROCK			SALARY LT 40000
***** HESCHMANN			SALARY LT 40000
HUCH	1952-09-12	67200	MERCEDES
***** KICKSTEIN			SALARY LT 40000
***** KLEENE			SALARY LT 40000
***** KRAMER			SALARY LT 40000

Equivalent reporting-mode example: [IFEX1R](#).

81

IF SELECTION

■ Function	630
■ Syntax Description	630
■ Example	632

Structured Mode Syntax

```
IF SELECTION [NOT UNIQUE [IN [FIELDS]]] operand1 ...  
  [THEN] statement...  
  [ELSE statement...]  
END-IF
```

Reporting Mode Syntax

```
IF SELECTION [NOT UNIQUE [IN [FIELDS]]] operand1...  
  
    [THEN] {      statement      }  
            DO statement... DOEND }  
  
[ ELSE {      statement      }      ]  
        DO statement... DOEND }
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [DECIDE FOR](#) | [DECIDE ON](#) | [IF](#)

Belongs to Function Group: [Processing of Logical Conditions](#)

Function

The IF SELECTION statement is used to verify that in a sequence of alphanumeric fields one and only one contains a value.

Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats										Referencing Permitted	Dynamic Definition	
<i>operand1</i>		S	A		A	U							L	C		yes	no

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Selection Field(s): As <i>operand1</i> you specify the fields which are to be checked. If you specify an attribute control variable (Format C), it is considered to contain a value if its status has been changed to MODIFIED. Note: To check if a specific attribute control variable has been assigned the status MODIFIED, use the MODIFIED option of, for example, an IF statement. This enables you to check that exactly one field was <i>modified</i>.
THEN <i>statement</i> ...	THEN Clause: The statement(s) specified in the THEN clause will be executed if one of the following conditions is true: ■ None of the fields specified in <i>operand1</i> contains a value. ■ More than one of the fields specified in <i>operand1</i> contains a value. This statement is generally used to verify that a terminal user has entered only one function in response to a map displayed via an INPUT statement. Note: If <i>no</i> action is to be performed if one of the conditions is met, you specify the statement IGNORE in the THEN clause.
ELSE <i>statement</i> ...	ELSE Clause: In the ELSE clause, you specify the statement(s) to be executed if exactly one field contains a value.
END-IF	End of IF SELECTION Statement:
<i>statement</i> ... DO <i>statement</i> ... DOEND	In structured mode, the Natural reserved word END-IF must be used to end the IF SELECTION statement. In reporting mode, use the DO ... DOEND statements to supply one or several suitable statements, depending on the situation, and to end the clauses and the IF SELECTION statement. If you specify only a single statement, you can omit the DO ... DOEND statements. With respect to good coding practice, this is not recommended.

Example

```

** Example 'IFSEL': IF SELECTION
*****
DEFINE DATA LOCAL
1 #A (A1)
1 #B (A1)
END-DEFINE
*
INPUT 'Select one function:' //
    9X 'Function A:' #A
    9X 'Function B:' #B
*
IF SELECTION NOT UNIQUE #A #B
    REINPUT 'Please enter one function only.'
END-IF
*
IF #A NE ' '
    WRITE 'Function A selected.'
END-IF
IF #B NE ' '
    WRITE 'Function B selected.'
END-IF
*
END

```

Output of Program IFSEL:

Select one function:

Function A: Function B:

After selecting and confirming function A:

Page 1 05-01-17 11:04:07
Function A selected.

82

IGNORE

■ Function	634
■ Example	634

IGNORE

Function

The `IGNORE` statement is an “empty” statement which itself does not perform any function.

During the development phase of an application, you can insert `IGNORE` temporarily within statement blocks in which one or more statements are required, but which you intend to code later (for example, within `AT BREAK` or `AT START OF DATA / AT END OF DATA`). This allows you to continue programming in another part of the application without the as yet incomplete statement block leading to an error.

The `IGNORE` statement must also be used in condition statements, such as `IF` or `DECIDE FOR`, if no function is to be performed in the case of a condition being met.

Example

```
...  
...  
AT TOP OF PAGE  
  IGNORE      /* top-of-page processing still to be coded  
END-TOPPAGE  
...  
...
```


83

INCLUDE

■ Function	636
■ Syntax Description	636
■ Examples	637

INCLUDE *copycode-name* [*operand1*] ... 99

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Function

The `INCLUDE` statement is used to include source lines from an external object of type copycode into another object at compilation.

The `INCLUDE` statement is evaluated at *compilation* time. The source lines of the copycode will not be physically included in the source of the program that contains the `INCLUDE` statement, but they will be included during the program compilation and thus in the resulting object module.

 **Caution:** A source code line which contains an `INCLUDE` statement must not contain any other statement.

Syntax Description

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	A U	no	no

Syntax Element Description:

Syntax Element	Description
<i>copycode-name</i>	Copycode Name: As <i>copycode-name</i> you specify the name of the copycode whose source is to be included. The case of the specified name is not translated. <i>copycode-name</i> may contain an ampersand (&); at compile time, this character will be replaced by the one-character code corresponding to the current value of the Natural system variable *LANGUAGE. This feature allows the use of multilingual copycode names. The object you specify must be of the type copycode. The copycode must be contained either in the same library as the program which contains the <code>INCLUDE</code> statement or in the respective steplib (the default steplib is SYSTEM). When the source of a copycode is modified, all programs using that copycode must be compiled again to reflect the changed source in their object codes. The source code of the copycode must consist of syntactically complete statements.

Syntax Element	Description
<i>operand1</i>	Insert Values for Dynamic Insertion: You can dynamically insert values in the copycode which is included. These values are specified with <i>operand1</i>. In the copycode, the values are referenced with the following notation: <code>&n&</code> That is, you mark the position where a value is to be inserted with <code>&n&</code>. <i>n</i> is the sequential number of each value passed with the INCLUDE statement. For example, <code>&3&</code> would refer to the third value specified with the statement. For every <code>&n&</code> notation in the copycode you must specify a value in the INCLUDE statement. For example, if the copycode contains <code>&5&</code>, <i>operand1</i> must be specified at least five times. You may write one copy code parameter (<code>&n&</code>) after another without blanks (that is, <code>&1&&2&&3&</code>). This method is used to concatenate multiple copy code parameters to a source. A string may follow one or several copy code parameters without a blank (that is, <code>&1&abc</code> or <code>&1&&2&abc</code>). This method is used to concatenate a string to multiple copy code parameters. Note: Because <code>&n&</code> is a valid part of an identifier, this notation may not be used as a copy code parameter substitution in other positions described above (i.e. <code>abc&1&</code> or <code>&1&abc&2&</code>). In other words, a string may only come after copy code parameters, not before or between. Values that are specified in the INCLUDE statement but not referenced in the copycode will be ignored.

Examples

- [Example 1 - INCLUDE Statement Including Copycode](#)
- [Example 2 - INCLUDE Statement Including Copycode with Parameters](#)
- [Example 3 - INCLUDE Statement Using Nested Copycodes](#)

- [Example 4 - INCLUDE Statement with Concatenated Parameters in Copycode](#)

Example 1 - INCLUDE Statement Including Copycode**Program containing the INCLUDE statement:**

```
** Example 'INCEX1': INCLUDE (include copycode)
*****
*
WRITE 'Before copycode'
*
INCLUDE INCEX1C
*
WRITE 'After copycode'
*
END
```

Copycode INCEX1C to be included:

```
** Example 'INCEX1C': INCLUDE (copycode used by INCEX1)
*****
*
WRITE 'Inside copycode'
```

Output of Program INCEX1:

```
Page          1                                05-01-25  16:26:36

Before copycode
Inside copycode
After copycode
```

Example 2 - INCLUDE Statement Including Copycode with Parameters**Program INCEX2 containing the INCLUDE statement:**

```
** Example 'INCEX2': INCLUDE (include copycode with parameters)
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 NAME
END-DEFINE
*
*
INCLUDE INCEX2C 'EMPL-VIEW' 'NAME' '''ARCHER''' '20' '''BAILLET'''
*
END
```

Copycode INCEX2C to be included:

```

** Example 'INCEX2C': INCLUDE (copycode used by INCEX2)
*****
* Transferred parameters from INCEX2:
*
* &1& : EMPL-VIEW
* &2& : NAME
* &3& : 'ARCHER'
* &4& : 20
* &5& : 'BAILLET'
*
*
READ (&4&) &1& BY &2& = &3&
  DISPLAY &2&
  IF &2& = &5&
    WRITE 5X 'LAST RECORD FOUND' &2&
    STOP
  END-IF
END-READ
*
* Statements above will be completed to:
*
* READ (20) EMPL-VIEW BY NAME = 'ARCHER'
*   DISPLAY NAME
*   IF NAME = 'BAILLET'
*     WRITE 5X 'LAST RECORD FOUND' NAME
*     STOP
*   END-IF
* END-READ

```

Output of Program INCEX2:

```

Page      1                                05-01-25  16:30:43
      NAME
-----
ARCHER
ARCONADA
ARCONADA
ARNOLD
ASTIER
ATHERTON
ATHERTON
ATHERTON
AUBERT
BACHMANN
BAECKER
BAECKER
BAGAZJA

```

```
BAILLET
  LAST RECORD FOUND BAILLET
```

Example 3 - INCLUDE Statement Using Nested Copycodes

Program containing INCLUDE statement:

```
** Example 'INCEX3': INCLUDE (using nested copycodes)
*****
DEFINE DATA LOCAL
1 #A (I4)
END-DEFINE
*
MOVE 123 TO #A
WRITE 'Program INCEX3 ' '=' #A
*
INCLUDE INCEX31C '#A' '5'          /* source line is #A := 5
*
*
MOVE 300 TO #A
WRITE 'Program INCEX3 ' '=' #A
*
INCLUDE INCEX32C '''#A''' '''20''' /* source line is #A := 20
*
WRITE 'Program INCEX3 ' '=' #A
END
```

Copycode INCEX31C to be included:

```
** Example 'INCEX31C': INCLUDE (copycode used by INCEX3)
*****
* Transferred parameters from INCEX3:
*
* &1& : #A
* &2& : 5
*
*
&1& := &2&
*
WRITE 'Copycode INCEX31C' '=' &1&
```

Copycode INCEX32C to be included:

```

** Example 'INCEX32C': INCLUDE (copycode used by INCEX3)
*****
* Transferred parameters from INCEX3:
*
* &1& : '#A'
* &2& : '20'
*
*
WRITE 'Copycode INCEX32C' &1& &2&
*
INCLUDE INCEX31C &1& &2&

```

Output of Program INCEX3:

```

Page          1                                05-01-25  16:35:36

Program INCEX3   #A:           123
Copycode INCEX31C #A:           5
Program INCEX3   #A:          300
Copycode INCEX32C #A 20
Copycode INCEX31C #A:           20
Program INCEX3   #A:           20

```

Example 4 - INCLUDE Statement with Concatenated Parameters in Copycode**Program containing INCLUDE statement:**

```

** Example 'INCEX4': INCLUDE (with concatenated parameters in copycode)
*****
DEFINE DATA LOCAL
1 #GROUP
2  ABC(A10) INIT <'1234567890'>
END-DEFINE
*
INCLUDE INCEX4C  '#GROUP.'  'ABC'  'AB'
*
END

```

Copycode INCX4C to be included:

```
** Example 'INCX4C': INCLUDE (copycode used by INCX4)
*****
* Transferred parameters from INCX4:
*
* &1& : #GROUP.
* &2& : ABC
* &3& : AB
*
*
WRITE  '=' &2&           /* 'ABC'           results into ABC
WRITE  '=' &1&ABC        /* '#GROUP.' ABC   results into #GROUP.ABC
WRITE  '=' &1&&2&        /* '#GROUP.' 'ABC' results into #GROUP.ABC
WRITE  '=' &1&&3&C       /* '#GROUP.' 'AB' C results into #GROUP.ABC
```

Output of Program INCX4:

```
Page      1                                05-01-25  16:37:59

ABC: 1234567890
ABC: 1234567890
ABC: 1234567890
ABC: 1234567890
```


X INPUT

The syntax is described separately. See:

- [INPUT Syntax 1 - Dynamic Screen Layout Specification](#)
- [INPUT Syntax 2 - Using Predefined Map Layout](#)

See also *Screen Design / Windows* in the *Programming Guide*.

Related Statements: [DEFINE WINDOW](#) | [REINPUT](#) | [SET WINDOW](#)

Belongs to Function Group: [Screen Generation for Interactive Processing](#)

Function

The `INPUT` statement is used in interactive mode to create a formatted screen or map for data entry.

It may also be used in conjunction with the Natural stack (see the [STACK](#) statement) and to provide user data for programs being executed in batch mode.

For Natural RPC: See *Notes on Natural Statements on the Server* in the *Natural RPC (Remote Procedure Call)* documentation.

Input Modes

The `INPUT` statement may be used in screen, forms, or keyword/delimiter mode. Screen mode is generally used with video terminals/screens. Forms mode may be used with TTY terminals. Delimiter mode is used with TTY terminals, and also in batch mode. The default mode is screen mode.

You can change the input mode with the session parameter `IM` or the terminal commands `%F` and `%D`.

Screen Mode

In screen mode, execution of the `INPUT` statement results in the display of a screen according to the fields and positioning notation specified. The message line of the screen is used by Natural for error messages. The position of the message line (top or bottom of screen) may be controlled by the terminal command `%M`. The terminal user may position to specific fields using the various tabulation keys.

As Natural allows for screen window processing, the layout of the logical screen map may be larger (theoretically 250 characters per line and 250 lines, but limited by the internal screen buffer) than the physical screen size.

The windowing terminal command `%W` may be used to modify logical and physical window position and size (see the terminal command `%W` for details of window handling).

For input fields (`AD=A` or `AD=M`) that are not fully displayed on the physical screen, the following rules apply:

- Input fields whose beginning is not inside the window are always made protected.
- Input fields which begin inside and end outside the window are only made protected if the values they contain cannot be displayed completely in the window. Please note that in this case it is decisive whether the value length, not the field length, exceeds the window size. Filler characters (as specified with the profile parameter `FC` or session parameter `AD`) do not count as part of the value.
- Before an input field thus protected can be accessed and processed, the window size must be adjusted so as to fully display the field or value respectively (see the terminal command `%W`).

Non-Screen Modes

The `INPUT` statement may be used for an operation on line-oriented devices or for the processing of batch input from sequential files.

The same map layouts as defined for screen mode operation can also be processed in non-screen mode.

Forms mode and keyword/delimiter mode are also available to process the input either by simulating the screen layout in line mode or by just processing the data without any map layout.

See also:

- [*Using the INPUT Statement in Non-Screen Modes*](#)
- [*Using the INPUT Statement in Batch Mode*](#)
- [*Processing Data from the Natural Stack*](#)

Entering Data in Response to an INPUT Statement

Data for an alphanumeric field must be entered left-justified. Any character, including a blank, is meaningful. The data are assigned one character per byte to the internal field. Data entered for an alphanumeric field are not validated.

Lower and upper case translation are controlled by the terminal commands %L and %U as well as the attributes AD=T and AD=W.

Data for a numeric field may be placed anywhere in the input field. Leading and/or trailing blanks, leading zeros, a leading sign and one decimal point are permitted. Natural adjusts the value according to the internal definition of the field. If SG=OFF is specified, Natural does not assume or allocate a position for a sign position. Data for a field defined with format P must be entered in decimal form. Natural will convert decimal to packed wherever necessary. A field containing all blanks is interpreted as a zero value. Data for a numeric field are validated by Natural to ensure that the value consists only of leading and/or trailing blanks, an optional leading sign, an optional decimal point, and numeric characters. If no decimal point is entered, it is assumed to be to the right of the value entered.

Data for a binary field must be entered for all positions (two characters per byte). Only valid hexadecimal characters (0 - 9, A - F) may be used. A blank (H'20' in ASCII or H'40' in EBCDIC respectively) is valid and is converted to binary zeros. Data for a binary field are validated by Natural for hexadecimal characters.

Data for format L fields may be entered as blank (false) or non-blank (true).

Data for format F, D, and T are entered according to the rules stated for F, D, and T constants.

Numeric Edit Mask Free Mode

Within a field element, you may format the representation of the field content with an edit mask. The edit mask is used for two purposes:

- to build the layout for displaying the field on the screen;
- when a string has been modified and ENTER has been pressed, to extract the field data from the string entered.

The advantage of improving the format of the field data displayed with additional insert characters may actually be a disadvantage, because a new data value entered has to perfectly match the format of the edit mask.

Example:

```
SET GLOBALS ID=; DC=,
RESET N (N7,3)
INPUT N (AD=M EM=Z'.'ZZZ'.'ZZZ,999EUR)
END
```

Output value	is displayed as:	Input value	must be entered as:	leads to an input error if entered as:
0	,000EUR	1	1,000EUR	1 1EUR 01,000EUR
1234	1.234,000EUR	1234567	1.234.567,000EUR	1234567 1.234.567 1.234.567EUR
0,123	,123EUR	1,234	1,234EUR	1,234

Another option for entering numeric fields with the edit mask is to use an alternative `INPUT` mode, which is called the edit mask free mode. When activated (either at session startup with the profile parameter `EMFM` or in a running Natural session via the terminal command `%FM+`), all or some of the edit mask insert characters may be left out from input.

However, when a contiguous string of insertion characters appears in the edit mask (like `EUR` in the example below), you may only supply or leave out the string completely. The number of optional or mandatory digits (edit-mask character `Z` and `9`) to be supplied is not affected.

Example with Edit Mask Free Mode activated:

```
SET GLOBALS ID=; DC=,
SET CONTROL 'FM+' /* activate numeric Edit Mask Free Mode
RESET N (N7,3)
INPUT N (AD=M EM=Z'.'ZZZ'.'ZZZ,999EUR)
END
```

Input value	can be entered as:	leads to an error if entered as:
1	1 1,0 001 1,00EUR 0.001 1,EUR	1EUR
1234567	1234567 1.234.567 1234.567 1234567,0 1.234.567,0 1.234.567,EUR	1.234.567EUR

Input value	can be entered as:	leads to an error if entered as:
	1.234.567,0EUR 1.234.567,000EUR	
1 , 234	1,234 1,234EUR 001,234 0.001,234EUR 00001,234EUR	1 , 234EU



Note: The edit mask free mode applies only for `INPUT`, but is ignored in a `MOVE EDITED` statement.

SB - Selection Box

Selection boxes in an `INPUT` statement are available on mainframe computers only. On Windows, selection boxes may be defined in the map editor only. On UNIX and OpenVMS, selection boxes cannot be defined and are ignored, if they are imported from a Windows or mainframe environment.

Selection boxes can be attached to input fields. They are a comfortable alternative to help routines attached to fields, since you can code a selection box direct in your program. You do not need an extra program as with help routines.

For more information, see the session parameter `SB` in the *Parameter Reference*.

Error Correction

If the value entered in an input field does not correspond to the format or edit mask of the field, Natural displays an error message (without terminating the program execution) and positions the cursor in the field in error. The user may then enter a valid value, whereupon processing continues.

Split-Screen Feature

In general, each `INPUT` statement generates a new page (or terminal screen) of output. Any `INPUT` statement which is specified within an `AT END OF PAGE` statement will not produce a new screen. This feature allows for the creation of a split screen where the upper portion of the screen may be used to display multiple lines and the lower portion can be used to create an input map for communication. The profile parameter `PS` (page size) should be used, either in a `SET GLOBALS` or `FORMAT` statement, to set the logical page size to ensure that the input map is built on the same physical screen.

The first `INPUT` line will be placed after the last displayed line. If the `NO ERASE` option is used, the first `INPUT` line will be placed at the top of the page.

System Variables with the INPUT Statement


For information on relevant system variables, see the section *Input/Output Related System Variables* in the *System Variables* documentation.

84

INPUT Syntax 1 - Dynamic Screen Layout Specification

■ INPUT Syntax 1 - Description	650
■ Examples - Syntax 1	659

This form of the INPUT statement is used to create a layout of an INPUT screen, or to create an INPUT data layout which is to be read in batch mode from a sequential input file.



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

INPUT Syntax 1 - Description

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	S A G N A U N P I F B D T L G		yes	yes

Syntax Element Description:

Syntax Element	Description
INPUT WINDOW='window-name'	INPUT WINDOW='window-name' Option: With this option, you indicate that the INPUT statement is to be executed for the specified window. The specified window must be defined in a DEFINE WINDOW statement; see Example 2 - INPUT Statement with DEFINE WINDOW Statement . The specified window is only active for the duration of that INPUT statement, and is automatically deactivated when the INPUT statement has been executed. See also the statements DEFINE WINDOW and SET WINDOW .
NO ERASE	NO ERASE Option:

Syntax Element	Description
	This option causes a screen map of an INPUT statement to be overlaid onto an existing screen without erasing the screen contents. Screen as used here refers to a logical screen rather than a physical screen. All unprotected fields that existed on the screen are converted to protected (display only) fields. The old data remain on the screen until the new layout is displayed. If a field from the new screen content partially overlays an existing field, the one character before the new field and the next character in the existing field will be replaced by a blank.
<i>statement-parameters</i>	Statement Parameter(s): One or more parameters, enclosed within parentheses, may be specified immediately after the INPUT statement or an element being displayed. For a list of parameters that can be specified with the INPUT statement, refer to the section <i>Statement Parameters</i>. Each parameter specified in this manner will override any previous parameter specified in a GLOBALS command, SET GLOBALS or FORMAT statement. If more than one parameter is specified, one or more blanks must be present between each entry. An entry may not be split between two statement lines. The parameter settings applied here will only be regarded for variable fields, but they have no effect on text-constants. If you would like to set field attributes for a text-constant, they have to be set explicitly for this element. Example: <pre> DEFINE DATA LOCAL 1 VARI (A4) INIT <'1234'> /* Displays END-DEFINE /* as FORMAT AD=M /* ----- INPUT 'Text' VARI /* Text 1234 INPUT (PM=I) 'Text' VARI /* Text 4321 INPUT 'Text' (PM=I) VARI (PM=I) /* txeT 4321 INPUT 'Text' (PM=I) VARI /* txeT 1234 END </pre> Examples of using parameters at the statement and element level are provided below.
<i>WITH TEXT-option</i>	WITH TEXT Option: This option is used to provide text which is to be displayed in the message line; see WITH TEXT Option below.
<i>MARK-option</i>	MARK Option: See the section MARK Option below.
<i>ALARM-option</i>	Alarm Option:

Syntax Element	Description
	See the section Alarm Option below.
Other syntax elements (<i>nX</i> , <i>nT</i> , <i>x/y</i> , <i>operand1</i> , etc.)	Field Positioning, Text Specification, Attribute Assignment: See the section Field Positioning, Text Specification, Attribute Assignment below.

Statement Parameters

Parameters that can be specified with the INPUT statement		Specification (S = at statement level, E = at element level)
AD	Attribute Definition	SE
AL	Alphanumeric Length for Output	SE
BX	Box Definition	SE
CD	Color Definition	SE
CV	Control Variable	SE
DF	Date Format	SE
DL	Display Length for Output	SE
DY	Dynamic Attributes	SE
EM	Edit Mask	SE
EMU	Unicode Edit Mask	E
FL	Floating Point Mantissa Length	SE
HE	Help routine	SE
IP	Input Prompting Text	SE
LS	Line Size	S
MC	Multiple-Value Field Count	S
MS	Manual Skip	S
NL	Numeric Length for Output	SE
PC	Periodic Group Count	S
PM	Print Mode	SE
PS	Page Size *	S
SB	Selection Box	E
SG	Sign Position	SE
ZP	Zero Printing	SE

* If the number of occurrences of an array exceeds the PS value, a NAT0303 error will be output.

The individual session parameters are described in the *Parameter Reference*.

WITH TEXT Option

[WITH] TEXT { * <i>operand1</i> <i>operand2</i> } [(<i>attributes</i>)] [, <i>operand3</i>] ... 7

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition	
<i>operand1</i>	C	S					N	P	I		B*						yes	yes
<i>operand2</i>	C	S				A											yes	yes
<i>operand3</i>	C	S				A	N	P	I	F	B	D	T	L			yes	yes

* Format B of *operand1* may be used only with a length of less than or equal to 4.

WITH TEXT is used to provide text which is to be displayed in the message line. This is usually a message indicating what action should be taken to process the screen or to correct an error.

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Message Text Number: <i>operand1</i> represents the number of a message text that is to be retrieved from a Natural message file. You can retrieve either user-defined messages or Natural system messages: ■ If you specify a positive value of up to four digits (for example: 954), you will retrieve user-defined messages. ■ If you specify a negative value of up to four digits (for example: -954), you will retrieve Natural system messages. See also Example 4 - WITH TEXT Options in the description of the REINPUT statement.
<i>operand2</i>	Message Text: <i>operand2</i> represents the message to be placed in the message line. See also Example 4 - WITH TEXT Options in the description of the REINPUT statement.
<i>attributes</i>	Output Attributes: It is possible to assign various output attributes for <i>operand1/2</i>. These attributes and the syntax that may be used are described in the section Output Attributes below.
<i>operand3</i>	Dynamic Replacement of Message Text: <i>operand3</i> represents a numeric or text constant or the name of a variable.

Syntax Element	Description
	The values provided are used to replace parts of a message text that are either specified with <i>operand1</i> or <i>operand2</i>. The notation <i>:n:</i> is used within the message text as a reference to <i>operand3</i> contents, where <i>n</i> represents the <i>operand3</i> occurrence (1 - 7). See also Example 4 - WITH TEXT Options in the description of the REINPUT statement. Note: Multiple specifications of <i>operand3</i> must be separated from each other by a comma. If the comma is used as a decimal character (as defined with the session parameter DC) and numeric constants are specified as <i>operand3</i>, put blanks before and after the comma so that it cannot be misinterpreted as a decimal character. Alternatively, multiple specifications of <i>operand3</i> can be separated by the input delimiter character (as defined with the session parameter ID); however, this is not possible in the case of ID=/ (slash), because the slash has a different meaning in the INPUT statement syntax. Leading zeros or trailing blanks will be removed from the field value before it is displayed in a message.

Output Attributes

attributes indicates the output attributes to be used for text display. Attributes can be:

$\left\{ \begin{array}{l} AD=ad-value \dots \\ BX=bx-value \dots \\ CD=cd-value \\ PM=pm-value \dots \end{array} \right\} \dots$
$\left\{ \begin{array}{l} ad-value \\ cd-value \end{array} \right\} \dots$

Where:

ad-value, *bx-value*, *cd-value* and *pm-value* denote the possible values of the corresponding session parameters AD, BX, CD and PM described in the relevant sections of the *Parameter Reference* documentation.

The compiler actually accepts more than one attribute value for an output field. For example, you can specify: AD=BDI. In such a case, however, only the last value applies. In the given example, only the value I becomes effective and the output field is displayed intensified.

For an alphanumeric/Unicode constant (Natural data format A or U), you can specify *ad-value* and/or *cd-value* without preceding CD= or AD=, respectively. The single value entered is then checked against all possible CD values first. For example: a value of IRE will be interpreted as intensified/red but not as intensified/right-justified/mandatory. You cannot combine a single *cd-value* or *ad-value* with a value preceded by CD= or AD=.

MARK Option

With the MARK option, you can cause the cursor to be placed at any non-protected field on screen. In addition, you can specify the position of the cursor within that field. By default, that is, when the MARK option is omitted, the cursor is placed at the beginning of the first non-protected field.

```
MARK [POSITION operand4 [IN]] [FIELD] { operand1
                                         *fieldname }
```

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand4</i>	C	S				N	P	I								yes	yes
<i>operand1</i>	C	S	A			N	P	I								yes	yes

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Field Reference Number: <i>operand1</i> specifies the number of the field where the cursor is to be positioned in. Each field attribute AD=A or AD=M (that is, non-protected field) specified in an INPUT statement is assigned a field reference number, beginning with 1.
* <i>fieldname</i>	Field Name for Referencing: Instead of the field reference number, the field name may be used to position to a field, using the * <i>fieldname</i> notation.
<i>operand4</i>	Cursor Position within Referenced Field: With MARK POSITION, you can have the cursor placed at a specific position - as specified with <i>operand4</i> - within a field specified with <i>operand1</i> or * <i>fieldname</i> . <i>operand4</i> must not contain decimal digits.

Examples:

```
MARK #NUMBER          /* Field number
MARK 3                 /* Third map field
MARK *#FIELD1          /* Map field
MARK POSITION 3 IN #NUMBER /* Third character in field number
```

See also [Example 3 - INPUT Statement with MARK POSITION Option](#) at the end of this section.

ALARM Option

This option causes the sound alarm feature of the terminal to be activated when the `INPUT` statement is executed. The appropriate hardware must be available to be able to use this feature.

[AND] [SOUND] ALARM

Default Prompting Text

Unless the session parameter `IP` (input prompting) is set to `IP=OFF`, the field name of the field used in an `INPUT` statement will be displayed preceding the field value (forms mode) or as a prompting keyword to select the field (keyword/delimiter mode). This default field name may be overridden by specifying either a `'text'` element (which replaces the default name) or `'-'` (which suppresses the display of the default field name) immediately preceding the field name.

Field Positioning, Text Specification, Attribute Assignment

Several notations are available for field positioning, attribute assignment, and text creation.

Syntax Element Description:

Syntax Element	Description
<i>nX</i>	Insert Option: This option causes <i>n</i> spaces to be inserted between fields. Note: This notation inserts <i>n</i> spaces between columns. <i>n</i> must not be zero.
<i>nT</i>	Tabulator Option: This option causes positioning (tabulation) to print position <i>n</i> .
<i>x/y</i>	Positioning Option: Places the next element on line <i>x</i> , beginning in column <i>y</i> . <i>y</i> must not be zero. Backward positioning in the same line is not permitted.
<i>'text'</i>	Write Protection: Causes <i>text</i> to be displayed write protected; see also <i>Text Notation, Defining a Text to Be Used with a Statement</i> .
<i>'c' (n)</i>	Character Repetition: Identical to <i>'text'</i> , except that the character <i>c</i> is displayed <i>n</i> times. <i>n</i> must be 1 - 132; see also <i>Text Notation, Defining a Character to Be Displayed n Times before a Field Value</i> .
<i>attributes</i>	Display Attributes: Attributes to be used for display. See Attributes below.
<i>'-'</i>	Minus Sign:

Syntax Element	Description
	When placed before a field, ' - ' suppresses the generation of a field name as prompting text. Note: Any text string before a field will replace the field name as prompting text.
' = '	Equal Sign: When placed before a field, ' = ' results in the display of the field heading followed by the field contents.
' / '	Slash Sign: When placed between fields or text elements, ' / ' causes positioning to the beginning of the next print line. The contents of fields may be specified for input, output only, and output for modification using the attribute settings AD=A, AD=O, and AD=M respectively. The default is AD=A. All fields specified with AD=A (input only) or AD=M (output for modification) will create unprotected fields on the screen. A value for such a field may be entered by the user. For TTY devices, output for modification fields will occupy twice the size of the field (one for output, one for input) so that a new value may be entered. An input field (with AD=A or AD=M) specified as non-displayable will always start on a new line on a TTY device. Example: <pre>INPUT #A (AD=A) #B (AD=O) #C (AD=M)</pre> #A is an input field which is unprotected, i.e., a value is to be entered for the field. #B is a field which is to be displayed write-protected, that is, no value may be entered for the field. #C is a field whose current value is to be displayed, and the value may be modified by entering a new value for the field.
*IN, *OUT and *OUTIN	Field Attribute Definition: Equivalent to the attributes AD=A, AD=O, AD=M respectively. Note: If a non-modifiable system variable is used in an INPUT statement, the value will be displayed as an output-only field AD=O or *OUT attribute.
<i>operand1</i>	Field(s) to be Used: <i>operand1</i> represents the field to be used. Database fields or user-defined variables may be specified. Natural directly maps the content of each field from the data area to the INPUT statement, no move operation is necessary. When the content of a database field is modified as a result of INPUT processing, only the value as contained in the data area is modified. Appropriate database UPDATE / STORE statements must be used to change the content of the database.

Syntax Element	Description
	When the name of a group of database fields is referenced in an <code>INPUT</code> statement, all fields belonging to that group will be individually used as input fields. When reference is made to a range of occurrences within an array, all occurrences are individually processed as input fields, but no prompting text will be created for each individual occurrence, only for the first one. On mainframe computers, arrays with ranges that allow to vary the number of occurrences at execution time may not be specified.
<i>parameter(s)</i>	Parameter(s): One or more parameters, enclosed within parentheses, may be specified immediately after <i>operand1</i> (see table and example below). Each parameter specified will override any previous parameter specified in a <code>GLOBALS</code> command, <code>SET GLOBALS</code> (in Reporting Mode) or <code>FORMAT</code> statement. If more than one parameter is specified, they must be separated by one or more blanks from one another. Each parameter specification must not be split between two statement lines. The parameter settings applied here will only be regarded for variable fields, but they have no effect on text constants. If you would like to set field attributes for a text-constant, they have to be set explicitly for this element. For information on the individual parameters, see the table in the section Statement Parameters. Note: The session parameter <code>EM</code> will be referenced dynamically in the DDM if an edit mask is defined for a database field. Edit masks may be specified for output and input fields. When an edit mask is defined for an input field, the data for the field must be entered according to the edit mask specification.

Attributes

The following attributes may be used:

$\left[\begin{array}{c} \left[\begin{array}{c} B \\ C \\ D \\ I \\ N \\ U \\ V \end{array} \right] \end{array} \right]$ 1	$\left[\begin{array}{c} \left[\begin{array}{c} BL \\ GR \\ NE \\ PI \\ RE \\ TU \\ YE \end{array} \right] \end{array} \right]$ 2	$\left[\begin{array}{c} \left[\begin{array}{c} T \\ B \\ L \\ R \\ ON \\ OFF \end{array} \right] \end{array} \right]$ 3	$\left[\begin{array}{c} \left[\begin{array}{c} C \\ D \\ I \\ N \end{array} \right] \end{array} \right]$ 4

1. Display attributes; see the session parameter `AD` (in the *Parameter Reference*).

2. Color attributes; see the session parameter CD (in the *Parameter Reference*).
3. Outlining attributes; see the session parameter BX (in the *Parameter Reference*).
4. Print mode attributes; see the session parameter PM (in the *Parameter Reference*).

Examples - Syntax 1

- [Example 1 - INPUT Statement](#)
- [Example 2 - INPUT Statement with DEFINE WINDOW Statement](#)
- [Example 3 - INPUT Statement with MARK POSITION Option](#)

Example 1 - INPUT Statement

```

** Example 'IPTEX1': INPUT
*****
DEFINE DATA LOCAL
1 #FNC (A1)
END-DEFINE
*
INPUT 10X 'SELECTION MENU FOR EMPLOYEES SYSTEM' /
      10X '-' (35) //
      10X 'ADD      (A)' /
      10X 'UPDATE   (U)' /
      10X 'DELETE   (D)' /
      10X 'STOP     (.)' //
      10X 'PLEASE ENTER FUNCTION: ' #FNC
*
DECIDE ON EVERY VALUE OF #FNC
  VALUE 'A' /* invoke the object containing the add function here
    WRITE 'Add function selected.'
  VALUE 'U' /* invoke the object containing the update function here
    WRITE 'Update function selected.'
  VALUE 'D' /* invoke the object containing the delete function here
    WRITE 'Delete function selected.'
  VALUE '.'
    STOP
  NONE
    REINPUT 'Please enter a valid function.' MARK *#FNC
END-DECIDE
*
END

```

Output of Program IPTEX1:

```
SELECTION MENU FOR EMPLOYEES SYSTEM
-----

ADD      (A)
UPDATE   (U)
DELETE   (D)
STOP     (.)

PLEASE ENTER FUNCTION:
```

Example 2 - INPUT Statement with DEFINE WINDOW Statement

```
** Example 'INPEX1': INPUT (with DEFINE WINDOW statement)
*****
DEFINE DATA LOCAL
1 #STRING (A15)
END-DEFINE
*
DEFINE WINDOW WIND1
  SIZE 10 * 40
  BASE 5 / 10
  FRAMED ON POSITION TEXT
*
INPUT WINDOW='WIND1'
      'PLEASE ENTER HERE:' / #STRING
*
END
```

Output of Program INPEX1:

```
+-----Top+
! PLEASE ENTER HERE:      !
! #STRING                  !
!                          !
!                          !
!                          !
!                          !
!                          !
!                          !
+-----Bottom+
```

Example 3 - INPUT Statement with MARK POSITION Option

```
** Example 'INPEX2': INPUT (with POSITION)
*****
DEFINE DATA LOCAL
1 #START (A30)
END-DEFINE
*
ASSIGN #START = 'EXAM_'
*
INPUT (AD=M) MARK POSITION 5 IN *#START
      / 'PLEASE COMPLETE START VALUE FOR SEARCH'
      / 5X #START
END
```

Output of Program INPEX2:

```
PLEASE COMPLETE START VALUE FOR SEARCH
      #START EXAM[]
```

85

INPUT Syntax 2 - Using Predefined Map Layout

■ INPUT USING MAP without Parameter List	664
■ INPUT Fields Defined in the Program	665
■ INPUT Syntax 2 - Description	665
■ Using the INPUT Statement in Non-Screen Modes	666
■ Processing Data from the Natural Stack	669
■ Using the INPUT Statement in Batch Mode	669

This form of the `INPUT` statement is used to perform input processing using a map layout that has been created using the Natural map editor.

Map layouts can be used in two ways:

- the program does not provide a parameter list;
- the program does provide a parameter list (*operand1*).

```
INPUT [WINDOW='window-name'] [WITH-TEXT-option]
[MARK-option]
[ALARM-option]
[USING] MAP map-name [NO ERASE]
[
    operand1 ...
    NO PARAMETER
]
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

INPUT USING MAP without Parameter List

The following requirements must be met when `INPUT USING MAP` is used without parameter list:

- The *map-name* must be specified as an alphanumeric constant (up to 8 characters).
- The map used in this manner must have been created prior to the compilation of the program which references the map.
- The names of the fields to be processed are taken dynamically from the map source definition at compilation time. The field names used in both program and map must be identical.
- All fields to be referenced in the `INPUT` statement must be accessible at that point.
- In structured mode, fields must have been previously defined (database fields must be properly referenced to processing loops or views).
- In reporting mode, user-defined variables may be newly defined in the map.
- When the map layout is changed, the programs using the map need not be recataloged. However, when array structures or names, formats/lengths of fields are changed, or fields are added/deleted in the map, the programs using the map must be recataloged.
- The map source must be available at program compilation; otherwise the `INPUT USING MAP` statement cannot be compiled.



Note: If you wish to compile the program even if the map is not yet available, specify `NO PARAMETER`: the `INPUT USING MAP` can then be compiled even if the map is not yet available.

INPUT Fields Defined in the Program

By specifying the names of the fields to be processed within the program (*operand1*), it is possible to have the names of the fields in the program differ from the names of the fields in the map.

The sequence of fields in the program must match the map sequence. Please note that the map editor sorts the fields as specified in the map in alphabetical order by field name. For more information, see the map editor description in your Natural Editors documentation.

When the layout of the map is changed, the program using the map need not be recataloged. However, when field names, field formats/lengths, or array structures in the map are changed or fields are added or deleted in the map, the program must be recataloged.

A check is made at execution time to ensure that the format and length of the fields as specified in the program match the fields as specified in the map. If both layouts do not agree, an error message is produced.

INPUT Syntax 2 - Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition	
<i>map-name</i>	C	S				A	U										yes	no
<i>operand1</i>		S	A			A	U	N	P	I	F	B	D	T	L	C	yes	yes

Syntax Element Description:

Syntax Element	Description
INPUT WINDOW='window-name'	INPUT WINDOW='window-name' Option: This option is described under Syntax 1 of the INPUT statement.
WITH TEXT/MARK/ALARM-options	WITH TEXT/MARK/ALARM Options: These options are described under Syntax 1 of the INPUT statement; see WITH TEXT Option , MARK Option , ALARM Option .
USING MAP <i>map-name</i>	USING MAP Clause: USING MAP invokes a map definition which has been previously stored in a Natural system file using the map editor.

Syntax Element	Description
	The <i>map-name</i> may be a 1- to 8-character alphanumeric constant or user-defined variable. If a variable is used, it must have been previously defined. The case of the specified name is not translated. The map name may contain an ampersand (&); at execution time, this character will be replaced by the one-character code corresponding to the current value of the Natural system variable *LANGUAGE. This feature allows the use of multi-lingual maps. The execution of the INPUT statement causes the corresponding map to replace the current contents of the screen, unless the NO ERASE option is specified, in which case the map will overlay the current contents of the screen.
NO ERASE	NO ERASE Option: This option is described under Syntax 1 of the INPUT statement; see NO ERASE.
<i>operand1</i>	Field Specification: A list of database fields and/or user-defined variables. The fields must agree in number, sequence, format, length and (for arrays) number of occurrences with the fields in the referenced map; otherwise, an error occurs. When the content of a database field is modified as a result of INPUT processing, only the value as contained in the data area is modified. Appropriate database UPDATE / STORE statements must be used to change the content of the database.

Using the INPUT Statement in Non-Screen Modes

You can change the input mode with the session parameter IM or the terminal commands %F and %D.

Forms Mode

The terminal command %F causes forms mode to be in effect.

In forms mode (profile/session parameter IM=F), Natural will display all output text of the map layout on the terminal field by field according to the positioning parameters. This permits the user to enter data on a field by field basis. When all data are entered, the hardcopy output is produced exactly as it would have appeared on the screen.

In forms mode, entering %R permits the operator to retype the entire form in case of an error. The input is processed as in the first execution of the INPUT statement.

Keyword/Delimiter Mode

The terminal command %D causes keyword/delimiter mode to be in effect.

In keyword/delimiter mode (profile/session parameter IM=D), data can be entered using keywords or positional input values.

General Validation Rules

Data entered in keyword/delimiter mode are validated as for screen mode. An error message will be returned if an attempt is made to enter more characters than defined for a field.

If the INPUT statement is to be processed in keyword/delimiter mode on a buffered (3270-type) terminal or a workstation, all data to be assigned to one INPUT statement must be entered on one screen. ENTER is only to be used when all data to the INPUT statement have been entered.

Keyword Input

Using keyword input, the terminal operator may enter data for the individual fields using the prompting text that, in forms mode, would have been displayed before the value as a keyword to identify the field. The keyword must be followed by the input assign character (IA parameter), followed immediately by the data. Any spaces following the assign character are taken as data up to the delimiter character (ID parameter). A delimiter character is not required after the last data element. Keyword data for the different fields may be entered in any order separated by the delimiter character. If the operator types in a keyword which is not defined in the INPUT statement, an error message will be returned. Data need not be entered for all input fields. Fields for which no data are entered are set to blank for alphanumeric fields and zero for numeric and hexadecimal fields.

A keyword and the corresponding input field must be on the same logical line. If their aggregate length exceeds the line size, adjust the line size (LS parameter) accordingly so that keyword and field fit onto one line.

Indexed Input

Using indexed input, the terminal operator may enter data for the individual input fields using their ordinal values prefixed with a percent character (%). This index specification must be followed by the input assign character (IA parameter), followed immediately by the data.

Indexed data for the different fields may be entered in any order separated by the delimiter character (ID parameter). If the specified ordinal value does not correspond to that of any existing input field, an error message will be returned. Data need not be entered for all input fields. Fields for which no data are entered are set to blank for alphanumeric fields and zero for numeric and hexadecimal fields.

Positional Input

Using positional value input, the terminal operator enters only data for all input fields separated by the currently defined input delimiter character (ID parameter). The sequence of fields for input must correspond to the sequence of the fields in the INPUT statement.

The user may switch from positional to keyword input by entering a number of values in positional input separated by the delimiter character and then switching to keyword mode for selected fields by specifying keywords in front of the values.

After a keyword has been used to position to a field, any non-keyword input following the keyword will be processed as positional input to be assigned to fields following the previously selected field in the INPUT statement.

Example of Keyword, Indexed and Positional Input

If you execute the following program

```
***** Program PGM1 *****
DEFINE DATA LOCAL
1 #F1 (A10)
1 #F2 (A10)
1 #F3 (A10)
END-DEFINE
INPUT (IP=ON) /  'FLD1' #F1
                /  'FLD2' #F2
                /  'FLD3' #F3
WRITE 'FLD1' #F1
      / 'FLD2' #F2
      / 'FLD3' #F3
END
```

from the command line with any of the following commands, assuming the comma (,) is used as the delimiter character

PGM1 FLD1=AA,FLD3=CC	keyword input
PGM1 %1=AA,%3=CC	indexed input
PGM1 AA,,CC	positional input
PGM1 AA,FLD3=CC	positional input combined with keyword
PGM1 AA,FLD2=,CC	positional input combined with keyword
PGM1 AA,%3=CC	combined positional and indexed input

you will always receive the following output

```
FLD1 AA
FLD2
FLD3 CC
```

Processing Data from the Natural Stack

Data elements that have been placed in the Natural stack via a [FETCH](#), [RUN](#) or [STACK](#) statement will be processed by the next `INPUT` statement encountered for execution.

The `INPUT` statement will process the data in keyword/delimiter mode as described above.

If data elements are not available to fill all input fields, fields will be filled with blank/zero depending on the field format. If more data elements are specified than input fields exist, the remaining data are ignored.

When a field is filled with data from the stack, the field attributes do not apply to the data.

The Natural system variable `*DATA` may be referenced to determine the number of data elements currently available in the Natural stack.

Using the INPUT Statement in Batch Mode

The following topics are covered below:

- [In Batch Forms Mode](#)
- [In Batch Keyword/Delimiter Mode](#)
- [Use of Terminal Commands in Batch Mode](#)

In Batch Forms Mode

In batch forms mode, the `INPUT` map is displayed. A data record is read for each line containing one or more `AD=A` and/or `AD=M` fields, and the data contained in the record are assigned to the appropriate field (or fields).

Input data fields are assumed to be contiguous. Unless the delimiter character is used, input data must be entered in the exact length according to the internal definition of the field. For numeric fields, space must be allowed for a sign (if `SG=ON`) and decimal point when appropriate.

Data may optionally be entered using the delimiter character to separate the values of the individual fields. In this case, data need not be entered in the exact number of positions according to the internal definition but are processed from left to right beginning in position 1. The rules for data entry are the same as described under [Entering Data in Response to an INPUT Statement](#). In ad-

dition, the assign character may be used to specify that the contents of an ***OUTIN** field are not to be reset.

In Batch Keyword/Delimiter Mode

Keyword/delimiter mode, when used in batch mode, functions the same as **keyword/delimiter mode** in TP mode with the following exceptions:

- The entire input map may be printed under the control of the terminal command %0.
- ***OUTIN** fields retain their original values unless explicitly changed.

Use of Terminal Commands in Batch Mode

The following Natural terminal commands may be used when using the **INPUT** statement in batch mode on a mainframe computer:

Command	Explanation
%*	Record Suppression. When entered in position one and two of a record, %* causes the printing of the next input record to be suppressed. DATA RECORD %* SUPPRESSED DATA RECORD
%	Record Continuation. When % is entered as the last non-blank character of a record, the next input record will be treated as a continuation record. DATA, RECORD, WITH, CONTINUATION, % CONTINUATION RECORD INPUT V1 V2 V3 V4 V5 V6 DISPLAY V1 V2 V3 V4 V5 V6 will produce the following output: DATA RECORD WITH CONTINUATION CONTINUATION RECORD
%/	End-of-file. When entered in the first two positions of a record (without any trailing non-blank characters), %/ causes an end-of-file condition.
%%	Set restart point in input data stream.
%.	Reading of input values for the current INPUT statement will be terminated.
%Knn	Simulate PF keys.
%KPn	Simulate PA keys.

Command	Explanation
%Q	This command causes printing of maps used to read input data to be suppressed.

See the *Terminal Commands* documentation for further information.

Additional JCL statements are required when using the `INPUT` statement for data entry in batch mode. The Natural administrator should be contacted to ensure that these statements have been provided before attempting to execute Natural in batch mode.

XI

■ 86 INSERT (SQL)	675
■ 87 INTERFACE	683
■ 88 LIMIT	691
■ 89 LOOP	695
■ 90 MERGE (SQL)	699
■ 91 METHOD	707
■ 92 MOVE	713
■ 93 MOVE INDEXED	735
■ 94 MULTIPLY	737
■ 95 NEWPAGE	743
■ 96 OBTAIN	749
■ 97 ON ERROR	757
■ 98 OPEN CONVERSATION	763
■ 99 OPTIONS	767

86

INSERT (SQL)

■ Function	676
■ Syntax Description	676
■ Example	681

Common Set Syntax:

```
INSERT INTO table-name { (*) [VALUES-clause]
                        [(column-list)] VALUE-LIST }
```

Extended Set Syntax:

```
INSERT INTO table-name { (*) [OVERRIDING USER VALUE] [VALUES-clause]
                        [(column-list)] [include-columns] [OVERRIDING USER VALUE]
                        VALUE-LIST }
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Belongs to Function Group: [Database Access and Update](#)

See also *INSERT - SQL in the Natural for DB2* part of the *Database Management System Interfaces* documentation:

Function

The SQL `INSERT` statement is used to add one or more new rows to a table.

Syntax Description

Syntax Element	Description
<code>INTO <i>table-name</i></code>	INTO Clause: In the <code>INTO</code> clause, the table is specified into which the new rows are to be inserted. See further information on table-name .
<code><i>column-list</i></code>	Column List: Syntax: <code><i>column-name</i>...</code> In the <code>column-list</code> , one or more <code>column-names</code> can be specified, which are to be supplied with values in the row currently inserted. If a <code>column-list</code> is specified, the sequence of the columns must match with the sequence of the values either specified in the <code>insert-item-list</code> or contained in the specified view (see below).

Syntax Element	Description
	If the <i>column-list</i> is omitted, the values in the <i>insert-item-list</i> or in the specified view are inserted according to an implicit list of all the columns in the order they exist in the table.
<i>include-columns</i>	Include Columns Clause: Specifies a set of columns that are included, along with the columns of <i>table-name</i> , in the result table of the INSERT statement when it is nested in the FROM clause of a SELECT statement. For further details, see include-columns .
<i>VALUES-clause</i>	Values Clause: With the VALUES clause, you insert a <i>single</i> row into the table. See VALUES Clause below.
OVERRIDING USER VALUE	OVERRIDING USER VALUE Clause: This clause belongs to the SQL Extended Set . When you specify this clause, the value specified in the VALUES clause or produced by a fullselect for a column that is defined as GENERATED ALWAYS will be ignored.

VALUES Clause

With the VALUES clause, you insert a *single* row into the table. Depending on whether an asterisk (*) or a *column-list* has been specified, the VALUES clause can take one of the following forms:

VALUES Clause with Preceding Asterisk Notation

```
VALUES (VIEW view-name)
```

If asterisk notation is specified, a view *must* be specified in the VALUES clause. With the field values of this view, a new row is inserted into the specified table using the field names of the view as column names of the row.

VALUES Clause with Preceding Column List

```
[(column-list)] [OVERRIDING USER VALUE] VALUE-LIST
```

If a *column-list* is specified and a view is referenced in the VALUES clause, the number of items specified in the column list must correspond to the number of fields defined in the view within the [VALUE-LIST](#).

If no *column-list* is specified, the fields defined in the view are inserted according to an implicit list of all the columns in the order they exist in the specified table.

VALUE-LIST

Common Set Syntax:

$$\left\{ \text{VALUES} \left\{ \begin{array}{l} (\text{VIEW } \textit{view-name}) \\ (\textit{insert-item-list}) \end{array} \right\} [\textit{FOR-n-ROWS-clause}] \right\}$$

Extended Set Syntax:

$$\left\{ \begin{array}{l} \text{VALUES} \left\{ \begin{array}{l} (\text{VIEW } \textit{view-name}) \\ (\textit{insert-item-list}) \end{array} \right\} [\textit{FOR-n-ROWS-clause}] \\ [\textit{WITH\_CTE } \textit{common-table-expression},...] \textit{select-expression} \left[\text{WITH} \left\{ \begin{array}{l} \text{RR} \\ \text{RS} \\ \text{CS} \end{array} \right\} \right] [\textit{QUERYNO } \textit{integer}] \end{array} \right\}$$

Syntax Description:

Syntax Element	Description
VIEW <i>view-name</i>	View Name: With the field values of this view, a new row is inserted into the specified table using the field names of the view as column names of the row.
<i>insert-item-list</i>	INSERT Single Row: In the <i>insert-item-list</i>, you can specify one or more values to be assigned to the columns specified in the <i>column-list</i>. The sequence of the specified values must match the sequence of the columns. If no <i>column-list</i> is specified, the values in the <i>insert-item-list</i> are inserted according to an implicit list of all the columns in the order they exist in the table. The values to be specified in the <i>insert-item-list</i> can be <i>constants</i>, <i>parameters</i>, <i>special-registers</i> or NULL. See the section <i>Basic Syntactical Items</i> for information on <i>view-name</i>, <i>constant</i> and <i>parameter</i>. See also the information on <i>special-register</i>. If the value NULL has been assigned, this means that the addressed field is to receive no value (not even the value 0 or “blank”). Example - INSERT Single Row:

Syntax Element	Description		
	<pre> ... INSERT INTO SQL-PERSONNEL (NAME,AGE) VALUES ('ADKINSON',35) ... </pre>		
<i>FOR-n-ROWS-clause</i>	FOR <i>n</i> Rows Clause: Optional clause, see FOR-n-ROWS-Clause below.		
WITH_CTE <i>common-table-expression</i>	WITH_CTE Clause: This clause belongs to the SQL Extended Set. This optional clause permits defining a result table which can be referenced in any FROM clause of the SELECT statement that follows. Multiple common-table-expressions can be specified following the single WITH_CTE keyword. Each common-table-expression can also be referenced in the FROM clause of subsequent common-table-expression. For more information, see WITH_CTE common-table-expression in the section <i>SELECT - SQL</i>.		
<i>select-expression</i>	INSERT Multiple Rows: This clause belongs to the SQL Extended Set. With a <i>select-expression</i>, you insert <i>multiple</i> rows into a table. The <i>select-expression</i> is evaluated and each row of the result table is treated as if the values in this row were specified as values in a VALUES Clause of a single-row INSERT operation. For further information, see Select Expressions. Example - Insert Multiple Rows: <pre> ... INSERT INTO SQL-RETIREE (NAME,AGE,SEX) SELECT LASTNAME, AGE, SEX FROM SQL-EMPLOYEES WHERE AGE > 60 ... </pre> Note: The number of rows that have actually been inserted can be ascertained by using the system variable *ROWCOUNT.		
WITH RR/RS/CS	WITH Isolation Level Clause: This clause belongs to the SQL Extended Set. This clause allows the explicit specification of the isolation level used when locating the rows to be inserted. <table border="1"> <tr> <td>CS</td><td>Cursor Stability</td></tr> </table>	CS	Cursor Stability
CS	Cursor Stability		

Syntax Element	Description	
	RR	Repeatable Read
	RS	Read Stability
QUERYNO_ <i>integer</i>	QUERYNO Clause: This clause belongs to the SQL Extended Set . This clause explicitly specifies the number to be used in EXPLAIN output and trace records for this statement.	

FOR-*n*-ROWS-Clause

```
FOR { [:]host-variable } ROWS [atomic-clause]
```

This clause is composed of the following subclauses:

FOR [:] *hostvariable/integer* ROWS Clause

```
FOR { [:]host-variable } ROWS
```

The specification of this clause is optional. It should only be specified, if

- compiler option DB2ARRY is specified and
- multiple rows are to be inserted from arrays specified in the *insert-item-list* of the **VALUES Clause**.

If specified, [:]*hostvariable/integer* determines the number of rows to be inserted into the DB2 table from the arrays specified in the *insert-item-list* of the **VALUES Clause** starting with the first occurrence.

The purpose of this clause is to improve the performance of programs inserting rows from Natural arrays in a loop. By using this clause, the rows contained in the arrays can be inserted by one SQL statement.

See example below.

See also the *Natural for DB2* part of the *Database Management System Interfaces* documentation.

ATOMIC Clause

```
{ ATOMIC
  NOT ATOMIC CONTINUE ON SQLEXCEPTION }
```

This clause specifies whether the insertion of multiple rows should be treated by DB2 as an atomic operation or not.

It should only be specified, if

- compiler option DB2ARRY is specified and
- multiple rows are to be inserted from arrays specified in the *insert-item-list* of the **VALUES Clause**.

Syntax Description:

Syntax Element	Description
ATOMIC	Specifies that in case of any error no row is inserted into the target table. This is the default value.
NOT ATOMIC CONTINUE ON SQLEXCEPTION	Specifies that in case of errors all rows for which no error occurred are inserted while those rows for which errors occurred are discarded by DB2.

See the *DB2 SQL REFERENCE* for SQLCODEs returned in such cases.

Example

```
DEFINE DATA LOCAL
01 NAME          (A20/1:10)  INIT <'ZILLER1','ZILLER2','ZILLER3','ZILLER4'
                                , 'ZILLER5','ZILLER6','ZILLER7','ZILLER8'
                                , 'ZILLER9','ZILLERA'>
01 ADDRESS       (A100/1:10) INIT <'ANGEL STREET 1','ANGEL STREET 2'
                                , 'ANGEL STREET 3','ANGEL STREET 4'
                                , 'ANGEL STREET 5','ANGEL STREET 6'
                                , 'ANGEL STREET 7','ANGEL STREET 8'
                                , 'ANGEL STREET 9','ANGEL STREET 10'>
01 DATENATD (D/1:10)  INIT <D'1954-03-27',D'1954-03-27',D'1954-03-27'
                                ,D'1954-03-27',D'1954-03-27',D'1954-03-27'
                                ,D'1954-03-27',D'1954-03-27',D'1954-03-27'
                                ,D'1954-03-27'>
01 SALARY        (P4.2/1:10) INIT <1000,2000,3000,4000,5000
                                ,6000,7000,8000,9000,9999>
01 L$ADDRESS     (I2/1:10)  INIT <14,14,14,14,14,14,14,14,14,15>
```

INSERT (SQL)

```
01 N$ADDRESS    (I2/1:10) INIT <00,00,00,00,00,00,00,00,00,00>
01 ROWS          (I4)
01 INDEX         (I4)
01 V1 VIEW OF NAT-DEMO_ID
02 NAME
02 ADDRESS       (EM=X(20))
02 DATEOFBIRTH
02 SALARY
01 ROWCOUNT    (I4)
END-DEFINE
OPTIONS DB2ARRAY=ON                /* <-- ENABLE DB2 ARRAY
ROWCOUNT := 10
INSERT INTO NAT-DEMO_ID
    (NAME,ADDRESS,DATEOFBIRTH,SALARY)
VALUES
    (:NAME(*),                /* <-- ARRAY
    :ADDRESS(*)                /* <-- ARRAY
    INDICATOR :N$ADDRESS(*)    /* <-- ARRAY
    LINDICATOR :L$ADDRESS(*),  /* <-- ARRAY DB2 VCHAR
    :DATENATD(1:10),          /* <-- ARRAY NATURAL DATES
    :SALARY(01:10)            /* <-- ARRAY NATURAL PACKED
    )
FOR :ROWCOUNT ROWS
SELECT * INTO VIEW V1 FROM NAT-DEMO_ID WHERE NAME > 'Z'
DISPLAY V1                      /* <-- VERIFY INSERT
END-SELECT
END
```


87

INTERFACE

■ Function	684
■ Syntax Description	684

```
INTERFACE  interface-name
[property-definition]
[method-definition]
END-INTERFACE
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [CREATE OBJECT](#) | [DEFINE CLASS](#) | [INTERFACE](#) | [METHOD](#) | [PROPERTY](#) | [SEND METHOD](#)

Belongs to Function Group: [Component Based Programming](#)

Function

In component-based programming, an interface is a collection of methods and properties that belong together semantically and represent a certain feature of a class.

You can define one or several interfaces for a class. Defining several interfaces allows you to structure/group methods according to what they do, for example, you put all methods that deal with persistency (load, store, update) in one interface and put other methods in other interfaces.

The `INTERFACE` statement is used to define an interface. It may only be used in a Natural class module and can be defined as follows:

- within a `DEFINE CLASS` statement. This form is used when the interface is only to be implemented in one class, or
- in a copycode which is included by the `INTERFACE USING` clause of the `DEFINE CLASS` statement. This form is used when the interface is to be implemented in more than one class.

The properties and methods that are associated with the interface are defined by the property and method definitions.

Syntax Description

Syntax Element	Description
<i>interface-name</i>	Interface Name: This is the name to be assigned to the interface. The interface name can be up to a maximum of 32 characters long and must conform to the Natural naming conventions for user-defined variables; see <i>Naming Conventions for User-Defined</i>

Syntax Element	Description
	<i>Variables</i> in the <i>Using Natural</i> documentation. It must be unique per class and different from the class name. If the interface is planned to be used by clients written in different programming languages, the interface name should be chosen in a way that it does not conflict with the naming conventions that apply in these languages.
<i>property-definition</i>	Property Definition: The property definition is used to define a property of the interface. See Property Definition below.
<i>method-definition</i>	Method Definition: The method definition is used to define a method for the interface. See Method Definition below.
END-INTERFACE	End of INTERFACE Statement: The Natural reserved word END-INTERFACE must be used to end the INTERFACE statement.

Property Definition

The property definition is used to define a property of the interface.

```
PROPERTY property-name
  [(format-length/array-definition)]
  [READONLY]
  [IS operand]
END-PROPERTY
```

Properties are attributes of an object that can be accessed by clients. An object that represents an employee might for example have a `Name` property and a `Department` property. Retrieving or changing the name or department of the employee by accessing her `Name` or `Department` property is much simpler for a client than calling one method that returns the value and another method that changes the value.

Each property needs a variable in the object data area of the class to store its value - this is referred to as the object data variable. The property definition is used to make this variable accessible to clients. The property definition defines the name and format of the property and connects it to the object data variable. In the simplest case, the property takes the name and format of the object data variable itself. It is also possible to override the name and format within certain limits.

Syntax Element Description:

Syntax Element	Description
<i>property-name</i>	Property Name: This is the name to be assigned to the property. The property name can contain up to a maximum of 32 characters and must conform to the Natural naming conventions for user variables; see <i>Naming Conventions for User-Defined Variables</i> in the <i>Using Natural</i> documentation. If the property is planned to be used by clients written in different programming languages, the property name should be chosen in a way that it does not conflict with the naming conventions that apply in these languages.
<i>format-length/array-definition</i>	<i>format-length/array-definition</i> Option: This option defines the format of the property as it will be seen by clients. If <i>format-length/array-definition</i> is omitted, the <i>format-length</i> and <i>array-definition</i> will be taken from the object data variable assigned in the IS clause. If <i>format-length/array-definition</i> is specified, it must be data transfer-compatible both to and from the format of the object data variable specified in <i>operand</i> in the IS clause. In the case of a READONLY property, the data transfer-compatibility needs to hold only in one direction: with the object data variable as source operand and the property as destination operand. If an <i>array-definition</i> is specified, it must be equal in dimensions, occurrences per dimension, lower bounds and upper bounds to the array definition of the corresponding object data variable. This is expressed by specifying an asterisk for each dimension.
READONLY	READONLY Option: If the keyword READONLY is specified, the value of the property can only be read and not set. The format of the object data variable specified in <i>operand</i> in the IS clause must be data transfer-compatible to the format specified in <i>format-length/array-definition</i>. It does not have to be data transfer-compatible in the inverse direction. If the keyword READONLY is omitted, the property value can be both read and set.
IS <i>operand</i>	IS Clause: The <i>operand</i> in the IS clause assigns an object data variable as the place to store the property value. The assigned object data variable may not be a group. The variable is referenced in normal operand syntax. This means, if the object data variable is an array, it must

Syntax Element	Description
	be referenced with index notation. Only the full index range notation and asterisk notation is allowed. The IS clause should not be used if the INTERFACE statement will be included from a copycode member and reused in several classes. If you want to reuse the INTERFACE statement, you must assign the object data variable in a PROPERTY statement outside the INTERFACE statement. If the IS clause is omitted, the property is connected to the object data variable with the same name as the property. If a variable with this name is not defined or if it is a group, a syntax error results.
END-PROPERTY	End of Interface Property Definition: The Natural reserved word END-PROPERTY must be used to end the interface PROPERTY definition.

Examples

Let the object data area contain the following data definitions:

```
1 Salary(p7.2)
1 SalaryHistory(p7.2/1:10)
```

Then the following property definitions are allowed:

```
property Salary
  end-property
  property Pay is Salary
  end-property
  property Pay(P7.2) is Salary
  end-property
  property Pay(N7.2) is Salary
  end-property
  property SalaryHistory
  end-property
  property OldPay is SalaryHistory(*)
  end-property
  property OldPay is SalaryHistory(1:10)
  end-property
  property OldPay(P7.2/*) is SalaryHistory(1:10)
  end-property
  property OldPay(N7.2/*) is SalaryHistory(*)
  end-property
```

The following property definitions are not allowed:

```
/* Not data transfer-compatible. */
property Pay(L) is Salary
end-property
/* Not data transfer-compatible. */
property OldPay(L/*) is SalaryHistory(*)
end-property
/* Not data transfer-compatible. */
property OldPay(L/1:10) is SalaryHistory(1:10)
end-property
/* Assigns an array to a scalar. */
property OldPay(P7.2) is SalaryHistory(1:10)
end-property
/* Takes only a sub-array. */
property OldPay(P7.2/3:5) is SalaryHistory(*)
end-property
/* Index specification omitted in ODA variable SalaryHistory. */
property OldPay is SalaryHistory
end-property
/* Only asterisk notation allowed in property format specification. */
property OldPay(P7.2/1:10) is SalaryHistory(*)
end-property
```

Method Definition

The method definition is used to define a method for the interface.

```
METHOD method-name
[IS subprogram-name]
[ PARAMETER { USING parameter-data-area } data-definition... ]...
END-METHOD
```

To make the interface reusable in different classes, include the interface definition from a copycode and define the subprogram after the interface definition with a METHOD statement. Then you can implement the method differently in different classes.

Syntax Element Description:

Syntax Element	Description
<i>method-name</i>	Method Name: This is the name to be assigned to the method. The method name can contain a maximum of up to 32 characters and must conform to the Natural naming conventions; see <i>Naming Conventions for User-Defined Variables</i> in the <i>Using Natural</i> documentation. It must be unique per interface.

Syntax Element	Description
	If the method is planned to be used by clients written in different programming languages, the method name should be chosen in a way that it does not conflict with the naming conventions that apply in these languages.
IS <i>subprogram-name</i>	IS Clause: This clause can be used to specify the name of the subprogram that implements the method. The name of the subprogram consists of up to 8 characters. The default is method-name (if the IS clause is not specified).
PARAMETER	PARAMETER Clause: The PARAMETER clause specifies the parameters of the method, and has the same syntax as the PARAMETER clause of the DEFINE DATA statement. The parameters must match the parameters which are later used in the implementation of the subprogram. This is ensured best by using a parameter data area. Parameters that are marked BY VALUE in the parameter data area are input parameters of the method. Parameters which are not marked BY VALUE are passed “by reference” and are input/output parameters. This is the default. The first parameter that is marked BY VALUE RESULT is returned as the return value for the method. If more than one parameter is marked in this way, the others will be treated as input/output parameters. OPTIONAL parameters need not be specified when the method is called. They can be left unspecified by using the <i>nX notation</i> in the SEND METHOD statement.
END-METHOD	End of Method Definition: The Natural reserved word END-METHOD must be used to end the METHOD definition for the interface.

88

LIMIT

■ Function	692
■ Syntax Description	693
■ Examples	693

LIMIT *n*

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [DELETE](#) | [END TRANSACTION](#) | [FIND](#) | [GET](#) | [GET SAME](#) | [GET TRANSACTION](#) | [HISTOGRAM](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [RETRY](#) | [STORE](#) | [UPDATE](#)

Belongs to Function Group: *[Database Access and Update](#)*

Function

The `LIMIT` statement is used to limit the number of iterations of a processing loop initiated with a [FIND](#), [READ](#), or [HISTOGRAM](#) statement.

The limit remains in effect for all subsequent processing loops in the program until it is overridden by another `LIMIT` statement.

The `LIMIT` statement does not apply to individual statements in which a limit is explicitly specified (for example, [FIND \(n\) ...](#)).

If the limit is reached, processing stops and a message is displayed; see also the session parameter `LE` which determines the reaction when the limit for the processing loop is exceeded.

If no `LIMIT` statement is specified, the default global limit defined with the Natural profile parameter `LT` during Natural installation will be used.

Record Counting

To determine whether a processing loop has reached the limit, each record read in the loop is counted against the limit. If the processing loop has reached the limit, the following will apply:

- A record that is rejected because of criteria specified in a [FIND](#) or [READ](#) statement [WHERE](#) clause is *not* counted against the limit.
- A record that is rejected as a result of an [ACCEPT/REJECT](#) statement is counted against the limit.

Syntax Description

Syntax Element	Description
<code>LIMIT <i>n</i></code>	Limit Specification: The limit <i>n</i> must be specified as a numeric constant in the range from 0 - 4294967295 (leading zeros are optional). The processing loop is not entered if the limit is set to zero.

Examples

- [Example 1 - LIMIT Statement](#)
- [Example 2 - LIMIT Statement \(Valid for Two Database Loops\)](#)

Example 1 - LIMIT Statement

```

** Example 'LMTEX1': LIMIT
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
  2 CITY
END-DEFINE
*
LIMIT 4
*
READ EMPLOY-VIEW BY NAME STARTING FROM 'BAKER'
  DISPLAY NOTITLE
      NAME PERSONNEL-ID CITY *COUNTER
END-READ
*
END

```

Output of Program LMTEX1:

NAME	PERSONNEL ID	CITY	CNT

BAKER	20016700	OAK BROOK	1
BAKER	30008042	DERBY	2
BALBIN	60000110	BARCELONA	3
BALL	30021845	DERBY	4

Example 2 - LIMIT Statement (Valid for Two Database Loops)

```
** Example 'LMTEX2': LIMIT (valid for two database loops)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
END-DEFINE
*
LIMIT 3
*
FIND EMPLOY-VIEW WITH NAME > 'A'
  READ EMPLOY-VIEW BY NAME STARTING FROM 'BAKER'
    DISPLAY NOTITLE 'CNT(0100)' *COUNTER(0100)
                      'CNT(0110)' *COUNTER(0110)
  END-READ
END-FIND
*
END
```

Output of Program LMTEX2:

CNT(0100)	CNT(0110)

1	1
1	2
1	3
2	1
2	2
2	3
3	1
3	2
3	3

89

LOOP

■ Function	696
■ Restriction	696
■ Syntax Description	697
■ Examples	697

[CLOSE] LOOP [(r)]

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Belongs to Function Group: [Reporting Mode Statements](#)

Function

The `LOOP` statement is used to close a processing loop. It causes processing of the current pass through the loop to be terminated and control to be returned to the beginning of the processing loop.

When the processing loop for which the `LOOP` statement is issued is terminated (that is, when all records have been processed or iterations have been performed), execution continues with the statement after the `LOOP` statement.

The `LOOP` statement is used with the following statements: `CALL FILE`, `CALL LOOP`, `FIND`, `FOR`, `HISTOGRAM`, `PARSE XML`, `READ`, `READLOB`, `READ RESULT SET (SQL)`, `READ WORK FILE`, `REPEAT`, `SELECT (SQL)`, `SORT`, `UPLOAD PC FILE`.

Database Variable References

A `LOOP` statement, in addition to closing a processing loop, will eliminate all field references to `FIND`, `FIND FIRST`, `FIND UNIQUE`, `READ` and `GET` statements contained within the loop.

A field within a view may be referenced outside the processing loop by using the view name as a qualifier.

Restriction

- This statement is for reporting mode only.
- A `LOOP` statement may not be specified based on a conditional statement such as `IF` or `AT BREAK`.

Syntax Description

Syntax Element	Description
LOOP (<i>r</i>)	Statement Reference Notation: The LOOP statement may be specified with a statement label or reference number (notation (<i>r</i>)), in which case all inner loops up to and including the loop initiated by the statement referenced will be closed. If no statement reference is specified, the innermost active processing loop will be closed.



Notes:

1. In reporting mode, any processing loop which is currently active, that is, which has not explicitly been closed with a LOOP statement, will be closed automatically by an **END** statement.
2. You can omit the LOOP statement. But with respect to good coding practice, you are not recommended to do so.

Examples

Example 1

```
FIND ...  
  READ ...  
    READ ...  
LOOP (0010)    /* closes all loops
```

Example 2

```
FIND ...  
  READ ...  
    READ ...  
      LOOP      /* closes loop initiated on line 0030  
    LOOP        /* closes loop initiated on line 0020  
  LOOP          /* closes loop initiated on line 0010
```

90

MERGE (SQL)

■ Function	700
■ Restriction	700
■ Syntax Description	700
■ Examples	705

```
MERGE INTO table-name [[AS] correlation-name]  
  [include-columns] USING source-table  
  ON search-condition  
{  
    WHEN MATCHED THEN update-operation  
    WHEN NOT MATCHED THEN insert-operation } ...  
  [NOT ATOMIC CONTINUE ON SQLEXCEPTION]  
  [QUERYNO integer]
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Belongs to Function Group: [Database Access and Update](#)

Function

The `MERGE` statement updates a table using the specified input data. Rows in the target table that match the input data are updated as specified, and rows that do not exist in the target table are inserted.

The `MERGE` statement belongs to the [SQL Extended Set](#).

Restriction

This statement is available only with Natural for DB2.

Syntax Description

Syntax Element	Description
MERGE INTO	MERGE INTO Clause: MERGE INTO initiates an SQL MERGE statement, which is a combination of an SQL INSERT and an SQL Searched UPDATE statement.
<i>table-name</i>	Table Name: Identifies the target of the INSERT or UPDATE operation of the MERGE statement. See table-name specification.
[[AS] <i>correlation-name</i>	[[AS] <i>correlation-name</i> Clause:

Syntax Element	Description
	Specifies an alternate name for the target table. The alternate name can be used as qualifier when referencing columns of the intermediate result table.
<i>include-columns</i>	Include Columns Clause: Specifies a set of columns that are included, along with the columns of the target table, in the result table of the MERGE statement if it is nested in the FROM clause in a SELECT statement. The included columns are appended to end of the column list identified by the target table. For further details, see include-columns .
USING <i>source-table</i>	USING <i>source-table</i> Clause: Specifies the values for the row data to merge into the target table. See source-table .
ON <i>search-condition</i>	ON <i>search-condition</i> Clause: Specifies join conditions between the source-table and the target table. Each column name in the search condition must name a column of the target table or source-table .
WHEN MATCHED THEN <i>update-operation</i>	WHEN MATCHED THEN <i>update-operation</i> Clause: Specifies the <i>update-operation</i> to be performed when the <i>search-condition</i> is true.
WHEN NOT MATCHED THEN <i>insert-operation</i>	WHEN NOT MATCHED THEN <i>insert-operation</i> Clause: Specifies the <i>insert-operation</i> to be performed when when the <i>search-condition</i> is true.
NOT ATOMIC CONTINUE ON SQLEXCEPTION	NOT ATOMIC CONTINUE ON SQLEXCEPTION Clause: Specifies whether merge processing continues in case an error occurred during processing one row of a set of source rows.
QUERYNO <i>integer</i>	QUERYNO <i>integer</i> Clause: Specifies the number for this SQL statement that is used in EXPLAIN output and DB2 trace records.

- [source-table](#)
- [values-single-row](#)
- [values-multiple-row](#)
- [update-operation](#)
- [assignment-clause](#)

▪ insert-operation

source-table

```
(VALUES {      values-single-row
           values-multiple-row }
[AS] correlation-name (column-name,...)
```

Syntax Element	Description
VALUES	VALUES introduces the specification of values for the row data to merge into the target table.
values-single-row	Specifies a single row of source data. See values-single-row .
values-multiple-row	Specifies multiple rows of source data. See values-multiple-row .
[AS] correlation-name	Specifies a correlation name for the source table.
column-name	Specifies a column name to associate the input data to the UPDATE SET assignment-clause clause for an UPDATE operation or the VALUES clause for an INSERT operation.

values-single-row

```
{ { expression }
  NULL
}
( { expression }
  NULL
,...)
```

Syntax Element	Description
expression	Scalar Expression: Specifies a scalar expression as described in Scalar Expressions .
NULL	NULL Value: Specifies the null value.

values-multiple-row

$$\left\{ \begin{array}{l} \left\{ \begin{array}{l} \text{expression} \\ \text{host-variable-array} \\ \text{NULL} \end{array} \right\} \\ \left(\begin{array}{l} \left\{ \begin{array}{l} \text{expression} \\ \text{host-variable-array} \\ \text{NULL} \end{array} \right\}, \dots \end{array} \right) \end{array} \right\} \text{FOR } \left\{ \begin{array}{l} \text{host-variable} \\ \text{integer-constant} \end{array} \right\} \text{ROWS}$$

Syntax Element	Description
<i>expression</i>	Scalar Expression: Specifies a scalar expression as described in Scalar Expressions .
<i>host-variable-array</i>	Host-Variable Array: Specifies a host variable array or an index range of an array. If <i>host-variable-array</i> is specified, the compiler option DB2ARRY has to be set to ON. An optional indicator array can be specified for each host-variable-array by the keyword INDICATOR, that is, <i>host-variable-array</i> INDICATOR <i>[:]indicator-array</i> .
NULL	NULL Value: Specifies the null value.
FOR ... ROWS	Number of Rows to Merge: This clause specifies the number of rows to merge. <i>host-variable</i> or <i>integer-constant</i> is assigned to a value <i>k</i> . <i>k</i> must be in the range of 0 to 32767 and must be lower than or equal to the minimum size of all specified host-variable-arrays.

update-operation

```
UPDATE SET assignment-clause
```

Syntax Element	Description
UPDATE SET	Specifies the UPDATE operation to be performed when the <i>search-condition</i> evaluates to true. See assignment-clause below.

assignment-clause

$$\left\{ \begin{array}{l} \text{column-name} = \left\{ \begin{array}{l} \text{expression} \\ \text{DEFAULT} \\ \text{NULL} \end{array} \right\} \\ (\text{column-name}, \dots) = \left(\left\{ \begin{array}{l} \text{expression} \\ \text{DEFAULT} \\ \text{NULL} \end{array} \right\}, \dots \right) \end{array} \right\}, \dots$$

Syntax Element	Description
<i>column-name</i>	Specifies the column for which an insert value is provided.
<i>expression</i>	Specifies the new value for the column. An <i>expression</i> can contain references to columns of the <i>source-table</i> or target table. <i>expression</i> cannot contain references to included columns.
DEFAULT	Specifies the default value for the column. The value that is assigned depends on how the column is defined.
NULL	Specifies the null value as new value for the column.

insert-operation

$$\text{INSERT } [(\text{column-name}, \dots)] \text{ VALUES } \left(\left\{ \begin{array}{l} \text{expression} \\ \text{DEFAULT} \\ \text{NULL} \end{array} \right\}, \dots \right)$$

Syntax Element	Description
INSERT	Specifies the INSERT operation to be performed when the <i>search-condition</i> evaluates to false.
<i>column-name</i>	Specifies the column for which an insert value is provided.
VALUES	Introduces one or more column values to insert.
<i>expression</i>	Specifies the new value for the column. An <i>expression</i> can contain references to columns of the source table. <i>expression</i> cannot contain references to columns of the target table.
DEFAULT	Specifies the default value for the column. The value that is assigned depends on how the column is defined.
NULL	Specifies the null value as new value for the column.

Examples

Example 1:

Update the inventory at a car dealership. Add new car model to the inventory or update information about existing car model that is already in the inventory.

```

DEFINE DATA LOCAL
01 #MODEL (A20)
01 #DELTA (I4)
END-DEFINE
* Setup input host variables
ASSIGN #MODEL = 'Grand Turbo'
ASSIGN #DELTA := 5
* Insert/Update into INVENTORY table
MERGE INTO CDS-INVENTORY T
  USING (VALUES (:#MODEL, :#DELTA)) AS S(MODEL, DELTA)
  ON T.MODEL = S.MODEL
WHEN MATCHED THEN UPDATE SET T.QUANTITY = T.QUANTITY + S.DELTA
WHEN NOT MATCHED THEN INSERT VALUES (S.MODEL, S.DELTA)
END TRANSACTION
END

```

Example 2:

Update the inventory at a car dealership. Add new car models to the inventory and update information about car models that are already in the inventory. Input comes from Natural arrays. Array specific code is shown in bold face type.

```

OPTIONS DB2ARRAY ON
DEFINE DATA LOCAL
01 #MODEL_ARR (A20/1:20)
01 #DELTA_ARR (I4/1:20))
01 #ROW-COUNT (I4)
01 #NUM-ERRORS (I4)
01 #SQLCODE (I4)
01 #SQLSTATE (A5)
01 #ROW-NUM (I4)
END-DEFINE
* Setup input host variables
ASSIGN #MODEL_ARR(1) = 'Grand Turbo'
ASSIGN #DELTA_ARR(1) := 5
ASSIGN #MODEL_ARR(2) = 'Blue Car'
ASSIGN #DELTA_ARR(2) := 3
. . .
* Insert/Update into INVENTORY table
CALLNAT 'NDBNOERR'
MERGE INTO CDS-INVENTORY T

```

```
    USING (VALUES (:#MODEL_ARR(*), :#DELTA_ARR(*))
    FOR 20 ROWS)
    AS S(MODEL, DELTA)
ON T.MODEL = S.MODEL
WHEN MATCHED THEN UPDATE SET T.QUANTITY = T.QUANTITY + S.DELTA
WHEN NOT MATCHED THEN INSERT VALUES (S.MODEL, S.DELTA)
NOT ATOMIC CONTINUE ON SQLEXCEPTION
* Check outcome of MERGE
PROCESS SQL SYSIBM-SYSDUMMY1
  <<GET DIAGNOSTICS
    :#ROW-COUNT = ROW_COUNT
    ,:#NUM-ERRORS = NUMBER>>
WRITE 'Number of rows merged           :' #ROW-COUNT /
      'NUMBER OF ERRORS                :' #NUM-ERRORS
IF #NUM-ERRORS > 0
  FOR #I = 1 TO #NUM-ERRORS
    PROCESS SQL SYSIBM-SYSDUMMY1
      <<GET DIAGNOSTICS CONDITION :#I
        :#SQLCODE = DB2_RETURNED_SQLCODE,
        :#SQLSTATE = RETURNED_SQLSTATE,
        :#ROW_NUM = DB2_ROW_NUMBER>>
    PRINT 'DB2_RETURNED_SQLCODE:' #SQLCODE
      'RETURNED_SQLSTATE:' #SQLSTATE
      'DB2_ROW_NUMBER:' #ROW_NUM (EM=99Z)
  END-FOR
END-IF
END TRANSACTION
END
```


91

METHOD

▪ Function	708
▪ Syntax Description	708
▪ Example	709

```
METHOD method-name
  OF [INTERFACE] interface-name
  IS subprogram-name
END-METHOD
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [CREATE OBJECT](#) | [DEFINE CLASS](#) | [INTERFACE](#) | [PROPERTY](#) | [SEND METHOD](#)

Belongs to Function Group: [Component Based Programming](#)

Function

The `METHOD` statement assigns a subprogram as the implementation to a method, *outside* an interface definition. It is used if the interface definition in question is included from a copycode and is to be implemented in a class-specific way.

The `METHOD` statement may only be used within the `DEFINE CLASS` statement and after the interface definition. The interface and method names specified must be defined in the `INTERFACE` clause of the `DEFINE CLASS` statement.

Syntax Description


Syntax Element	Description
<i>method-name</i>	Method Name: This is the name assigned to the <i>method</i> .
OF <i>interface-name</i>	Interface Name: This is the name assigned to the <i>interface</i> .
IS <i>subprogram-name</i>	IS Clause: This clause can be used to specify the name of the subprogram that implements the method. The name of the subprogram consists of up to 8 characters. The default is <i>method-name</i> (if the IS clause is not specified).
END-METHOD	End of Method Statement: The Natural reserved word <code>END-METHOD</code> must be used to end the <code>METHOD</code> statement.

Example

The following example shows how the same interface is implemented differently in two classes and how the `PROPERTY` statement and the `METHOD` statement are used to achieve this.

The interface `Measure` is defined in the copycode `iface-c`. The classes `Elephant` and `Mouse` implement both the interface `Measure`. Therefore, they both include the copycode `iface-c`. But the classes implement the property `Height` using different variables from their respective object data areas, and they implement the method `Init` with different subprograms. They use the `PROPERTY` statement to assign the selected data area variable to the property and the `METHOD` statement to assign the selected subprogram to the method.

Now the program `prog` can create objects of both classes and initialize them using the same method `Init`, leaving the specifics of the initialization to the respective class implementation.



The following shows the complete contents of the Natural modules used in the example above:

Copycode: iface-c

```
interface Measure
*
property Height(p5.2)
end-property
*
property Weight(i4)
end-property
*
method Init
end-method
*
end-interface
```

Class: class1

```
define class elephant
object using class1-o
interface using iface-c
*
property Height of interface Measure is height
end-property
*
property Weight of interface Measure is weight
end-property
*
method Init of interface Measure is init1-n
end-method
*
end-class
end
```

LDA Object Data: class1-o

```
*   *** Top of Data Area ***
1  HEIGHT                P 5.2
1  WEIGHT                 I 2
*   *** End of Data Area ***
```

Method Subprogram: init1-n

```
define data
object using class1-o
end-define
*
height := 17.3
weight := 120
*
end
```

Class: class2

```

define class mouse
object using class2-o
interface using iface-c
*
property Height of interface Measure is size
end-property
*
property Weight of interface Measure is weight
end-property
*
method Init of interface Measure is init2-n
end-method
*
end-class
end

```

LDA Object Data: class2-o

```

*   *** Top of Data Area ***
1 SIZE                      P 3.2
1 WEIGHT                     I 1
*   *** End of Data Area ***

```

Method Subprogram: init2-n

```

define data
object using class2-o
end-define
*
size := 1.24
weight := 2
*
end

```

Program: prog

```

define data local
1 #o handle of object
1 #height(p5.2)
1 #weight(i4)
end-define
*
create object #o of class 'Elephant'
send "Init" to #o
#height := #o.Height
#weight := #o.Weight
write #height #weight
*

```

METHOD

```
create object #o of class 'Mouse'  
send "Init" to #o  
#height := #o.Height  
#weight := #o.Weight  
write #height #weight  
*  
end
```

92

MOVE

■ Function	714
■ Syntax 1 - MOVE	714
■ Syntax 2 - MOVE SUBSTRING	716
■ Syntax 3 - MOVE BY NAME / POSITION	718
■ Syntax 4 - MOVE EDITED (Edit Mask Specified with operand2)	719
■ Syntax 5 - MOVE EDITED (Edit Mask Specified with operand1)	720
■ Syntax 6 - MOVE LEFT / RIGHT JUSTIFIED	721
■ Syntax 7 - MOVE NORMALIZED	722
■ Syntax 8 - MOVE ENCODED	724
■ Syntax 9 - MOVE ALL	727
■ Examples	729

For explanations of the symbols used in the syntax diagrams below, see [Syntax Symbols](#).

Related Statements: [ADD](#) | [COMPRESS](#) | [COMPUTE](#) | [DIVIDE](#) | [EXAMINE](#) | [MULTIPLY](#) | [RESET](#) | [SEPARATE](#) | [SUBTRACT](#)

Belongs to Function Group: [Arithmetic and Data Movement Operations](#)

Function

The `MOVE` statement is used to move the value of an operand to one or more operands (field or array).

A Natural system function may be used only if the `MOVE` statement is specified in conjunction with an `AT BREAK`, `AT END OF DATA` or `AT END OF PAGE` statement.

See also the section *Rules for Arithmetic Assignment* in the *Programming Guide*.

Syntax 1 - MOVE

MOVE [ROUNDED] operand1 [(parameter)] TO operand2 ...

For explanations of the symbols used in the syntax diagrams below, see [Syntax Symbols](#).

Operand Definition Table:

Operand	Possible Structure					Possible Formats												Referencing Permitted	Dynamic Definition	
<i>operand1</i>	C	S	A		N	A	U	N	P	I	F	B	D	T	L	C	G	O	yes	no
<i>operand2</i>		S	A		M	A	U	N	P	I	F	B	D	T	L	C	G	O	yes	yes

Syntax Element Description:

Syntax Element	Description
MOVE ROUNDED	MOVE ROUNDED Option: This option causes <i>operand2</i> to be rounded. ROUNDED is ignored if <i>operand2</i> is not numeric or if the source operand has the same or less precision digits than the target operand. See also Example 1 - Various Samples of MOVE Statement Usage .
operand1	Source and Target Operands:

Syntax Element	Description				
<i>operand2</i>	<i>operand1</i> is the source operand whose value is moved to the target operand <i>operand2</i>. For the rules for data transfer and information on data conversion and transfer compatibility, see the section <i>Data Transfer</i> in the <i>Programming Guide</i>. If <i>operand2</i> is a dynamic variable, its length may be modified by the MOVE operation. The current length of a dynamic variable can be ascertained by using the system variable *LENGTH. For general information on the dynamic variable, see the section <i>Using Dynamic and Large Variables</i> in the <i>Programming Guide</i>. A MOVE statement with multiple target operands is identical to the corresponding individual MOVE statements: <pre>MOVE #SOURCE TO #TARGET1 #TARGET2</pre> is identical to <pre>MOVE #SOURCE TO #TARGET1 MOVE #SOURCE TO #TARGET2</pre>				
<i>parameter</i>	Parameter Option: <i>parameter</i> either specifies the session parameter PM or the session parameter DF: <table> <tr> <td>PM=I</td><td> Right-to-Left Display Option: In order to support languages whose writing direction is from right to left, you can specify PM=I so as to transfer the value of <i>operand1</i> in inverse (right-to-left) direction to <i>operand2</i>. For example, as a result of the following statements, the content of #B would be ZYX: <pre>MOVE 'XYZ' TO #A MOVE #A (PM=I) TO #B</pre> PM=I can only be specified if <i>operand2</i> has alphanumeric/Unicode format (Natural data format A or U). Any trailing blanks in <i>operand1</i> will be removed (blanks and binary zeros are removed), then the value is reversed and moved to <i>operand2</i>. If <i>operand1</i> is not of alphanumeric/Unicode format, the value will be converted to alphanumeric/Unicode format before it is reversed. See also the use of PM=I in conjunction with MOVE LEFT/RIGHT JUSTIFIED. </td></tr> <tr> <td>DF=S I L</td><td> Date Format: </td></tr> </table>	PM=I	Right-to-Left Display Option: In order to support languages whose writing direction is from right to left, you can specify PM=I so as to transfer the value of <i>operand1</i> in inverse (right-to-left) direction to <i>operand2</i>. For example, as a result of the following statements, the content of #B would be ZYX: <pre>MOVE 'XYZ' TO #A MOVE #A (PM=I) TO #B</pre> PM=I can only be specified if <i>operand2</i> has alphanumeric/Unicode format (Natural data format A or U). Any trailing blanks in <i>operand1</i> will be removed (blanks and binary zeros are removed), then the value is reversed and moved to <i>operand2</i>. If <i>operand1</i> is not of alphanumeric/Unicode format, the value will be converted to alphanumeric/Unicode format before it is reversed. See also the use of PM=I in conjunction with MOVE LEFT/RIGHT JUSTIFIED.	DF=S I L	Date Format:
PM=I	Right-to-Left Display Option: In order to support languages whose writing direction is from right to left, you can specify PM=I so as to transfer the value of <i>operand1</i> in inverse (right-to-left) direction to <i>operand2</i>. For example, as a result of the following statements, the content of #B would be ZYX: <pre>MOVE 'XYZ' TO #A MOVE #A (PM=I) TO #B</pre> PM=I can only be specified if <i>operand2</i> has alphanumeric/Unicode format (Natural data format A or U). Any trailing blanks in <i>operand1</i> will be removed (blanks and binary zeros are removed), then the value is reversed and moved to <i>operand2</i>. If <i>operand1</i> is not of alphanumeric/Unicode format, the value will be converted to alphanumeric/Unicode format before it is reversed. See also the use of PM=I in conjunction with MOVE LEFT/RIGHT JUSTIFIED.				
DF=S I L	Date Format:				

Syntax Element	Description
	If <i>operand1</i> is a date variable and <i>operand2</i> is an alphanumeric/Unicode field, you can specify the session parameter <i>DF</i> as parameter for this date variable.

Syntax 2 - MOVE SUBSTRING

MOVE	{ <i>operand1</i> SUBSTRING (<i>operand1</i> , <i>operand3</i> , <i>operand4</i>) }	[(<i>parameter</i>)]
TO	{ <i>operand2</i> SUBSTRING (<i>operand2</i> , <i>operand5</i> , <i>operand6</i>) }	...

This syntax only applies if you want to move only part of the field contents (a substring) of a source and/or target operand. Otherwise, [Syntax 1](#) applies.

For explanations of the symbols used in the syntax diagrams below, see [Syntax Symbols](#).

Operand Definition Table:

Operand	Possible Structure				Possible Formats										Referencing Permitted	Dynamic Definition		
<i>operand1</i>	C	S	A			A	U					B					yes	no
<i>operand2</i>		S	A			A	U					B					yes	no
<i>operand3</i>	C	S						N	P	I		B*					yes	no
<i>operand4</i>	C	S						N	P	I		B*					yes	no
<i>operand5</i>	C	S						N	P	I		B*					yes	no
<i>operand6</i>	C	S						N	P	I		B*					yes	no

* See text.

Syntax Element Description:

Syntax Element	Description
MOVE SUBSTRING	MOVE SUBSTRING: Without the SUBSTRING option, the whole content of a field is moved. The SUBSTRING option allows you to move only a certain part of an alphanumeric/ Unicode or a binary field. After the field name (<i>operand1</i>) in the SUBSTRING clause, you specify first the starting position (<i>operand3</i>) and then the length (<i>operand4</i>) of the field portion to be moved.

Syntax Element	Description
	If the underlying field format of <i>operand1</i> is ■ alphanumeric/Unicode (A) or binary (B), then the values supplied with <i>operand3</i> or <i>operand4</i> are considered as byte numbers; ■ Unicode (U), then the values supplied with <i>operand3</i> or <i>operand4</i> are considered as number of Unicode code units; that is, as double-bytes. For example, to move the 5th to 12th position inclusive of the value in a field #A into a field #B, you would specify: <pre>MOVE SUBSTRING(#A,5,8) TO #B</pre> If <i>operand1</i> is a dynamic variable, the specified field portion to be moved must be within its current length; otherwise, a runtime error will occur. Also, you can move a value of an alphanumeric/Unicode or binary field into a certain part of the target field. After the field name (<i>operand2</i>) in the SUBSTRING clause you specify first the starting position (<i>operand5</i>) and then the length (<i>operand6</i>) of the field portion into which the value is to be moved. If the underlying field format of <i>operand2</i> is ■ alphanumeric/Unicode (A/U) or binary (B), then the values supplied with <i>operand5</i> or <i>operand6</i> are considered as byte numbers; ■ Unicode (U), then the values supplied with <i>operand3</i> or <i>operand4</i> are considered as number of Unicode code units; that is, as double-bytes. For example, to move the value of a field #A into the 3rd to 6th position inclusive of a field #B, you would specify: <pre>MOVE #A TO SUBSTRING(#B,3,4)</pre> If <i>operand2</i> is a dynamic variable, the specified starting position (<i>operand5</i>) must not be greater than the variable's current length plus 1; a greater starting position will lead to a runtime error, because it would cause an undefined gap within the content of <i>operand2</i>. If <i>operand3/operand5</i> or <i>operand4/operand6</i> is a binary variable, it may be used only with a length of less than or equal to 4. If you omit <i>operand3/operand5</i>, the starting position is assumed to be 1. If you omit <i>operand4/operand6</i>, the length is assumed to range from the starting position to the end of the field. If <i>operand2</i> is a dynamic variable and the specified starting position (<i>operand5</i>) is the variable's current length plus 1, which means that the MOVE operation is used to increase the length of the variable, <i>operand6</i> must be specified in order to determine the new length of the variable.

Syntax Element	Description
	Note: MOVE with the SUBSTRING option is a byte-by-byte move (that is, the rules described under <i>Rules for Arithmetic Assignment</i> in the <i>Programming Guide</i> do not apply).
<i>parameter</i>	Parameter Option: See parameter in <i>Syntax 1</i> .

Syntax 3 - MOVE BY NAME / POSITION

```
MOVE BY { [NAME]
           POSITION } operand1 TO operand2
```

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>		G	yes	no
<i>operand2</i>		G	yes	no

Syntax Element Description:

Syntax Element	Description
MOVE BY NAME <i>operand1</i> TO <i>operand2</i>	MOVE BY NAME Option: This option is used to move individual fields contained in a data structure to another data structure, independent of their position in the structure. A field is moved only if its name appears in both structures (this includes REDEFINED fields as well as fields resulting from a redefinition). The individual fields may be of any format. The operands can also be views. Note: The sequence of the individual moves is determined by the sequence of the fields in <i>operand1</i>. See also Example 2 - MOVE BY NAME Statement. MOVE BY NAME with Arrays: If the data structures contain arrays, these will internally be assigned the index (*) when moved; this may lead to an error if the arrays do not comply with the rules for assignment operations with arrays; see the section <i>Processing of Arrays</i> in the <i>Programming Guide</i>. See also Example 3 - MOVE BY NAME with Arrays.

Syntax Element	Description
MOVE BY POSITION <i>operand1</i> TO <i>operand2</i>	MOVE BY POSITION Option: This option allows you to move the contents of fields in a group to another group, regardless of the field names. The values are moved field by field from one group to the other in the order in which the fields are defined (this does not include fields resulting from a redefinition). The individual fields may be of any format. The number of fields in each group must be the same; also, the level structure and array dimensions of the fields must match. Format conversion is done according to the rules for arithmetic assignment; see the section <i>Rules for Arithmetic Assignments</i> in the <i>Programming Guide</i>. The operands can also be views. See also Example 4 - MOVE BY POSITION.

Syntax 4 - MOVE EDITED (Edit Mask Specified with operand2)

MOVE EDITED *operand1* TO *operand2* { (EM=value) }
(EMU=value)

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S	A			A	U					B				yes	no
<i>operand2</i>		S	A			A	U	N	P	I	F	B	D	T	L	yes	yes

Syntax Element Description:

Syntax Element	Description
MOVE EDITED	MOVE EDITED Option: If an edit mask is specified for <i>operand2</i>, the value of <i>operand1</i> will be placed into <i>operand2</i> using this edit mask. The edit mask can be considered as an <i>input</i> edit mask for <i>operand2</i> that is used to specify at which positions in the alphanumeric/Unicode contents of <i>operand1</i> the significant input data for <i>operand2</i> can be found. If the edit mask refers more characters or digits than existent in <i>operand2</i>, it is truncated accordingly. The length of <i>operand1</i> may not be smaller than the length of the input value represented by the edit mask. If <i>operand1</i> is longer than the edit mask length, all the overhanging data is ignored.

Syntax Element	Description
	Under the pre-condition not to have an <i>operand1</i> length larger than the edit mask length, you may regard a <pre>MOVE EDITED <i>operand1</i> TO <i>operand2</i> (EM=<i>value</i>)</pre> operation like the execution of <pre>STACK TOP DATA <i>operand1</i> INPUT <i>operand2</i> (EM=<i>value</i>)</pre> See also Example 1 - Various Samples of MOVE Statement Usage.
EM	Edit Mask: For details on edit masks, see the session parameter EM in the <i>Parameter Reference</i>.
EMU	Unicode Edit Mask: For details on Unicode edit masks, see the session parameter EMU in the <i>Parameter Reference</i>.

Syntax 5 - MOVE EDITED (Edit Mask Specified with operand1)

```
MOVE EDITED operand1 { (EM=value) } TO operand2
                { (EMU=value) }
```

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition		
<i>operand1</i>	C	S	A		N	A	U	N	P	I	F	B	D	T	L			yes	no
<i>operand2</i>		S	A			A	U					B						yes	yes

Syntax Element Description:

Syntax Element	Description
MOVE EDITED	MOVE EDITED Option: If an edit mask is specified for <i>operand1</i>, the edit mask will be applied to <i>operand1</i> and the result will be moved to <i>operand2</i>. The edit mask can be considered as an <i>output</i> edit mask for <i>operand1</i> that is used to create an alphanumeric/Unicode string with the layout and length described by the edit mask. Besides data characters or digits originating from <i>operand1</i>, you may include additional decoration characters into the output string.

Syntax Element	Description
	If the edit mask refers more characters or digits than existent in <i>operand1</i>, it is truncated accordingly. The length of the created output string (resulting from <i>operand1</i> value after the edit mask has been applied) must not exceed the length of <i>operand2</i>. Under the pre-condition not to have an <i>operand2</i> length smaller than the edit mask length, you may regard a <pre>MOVE EDITED <i>operand1</i> (EM=<i>value</i>) TO <i>operand2</i></pre> operation like a <pre>WRITE <i>operand1</i> (EM=<i>value</i>)</pre> that does not write the output to the screen, but fills it into variable <i>operand2</i>. See also Example 1 - Various Samples of MOVE Statement Usage.
EM	Edit Mask: For details on edit masks, see the session parameter EM in the <i>Parameter Reference</i>.
EMU	Unicode Edit Mask: For details on Unicode edit masks, see the session parameter EMU in the <i>Parameter Reference</i>.

Syntax 6 - MOVE LEFT / RIGHT JUSTIFIED

```
MOVE { LEFT
      RIGHT } [JUSTIFIED] operand1 [(parameter)] TO operand2
```

Operand Definition Table:

Operand	Possible Structure			Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S	A	N A U N P I F B D T L	yes	no
<i>operand2</i>		S	A	A U	yes	yes

Syntax Element Description:

Syntax Element	Description
MOVE LEFT / RIGHT JUSTIFIED	MOVE LEFT / RIGHT JUSTIFIED Options: This option is used to cause the values to be moved to be left- or right-justified in <i>operand2</i>. MOVE LEFT/RIGHT JUSTIFIED cannot be used if <i>operand2</i> is a dynamic variable.
MOVE LEFT JUSTIFIED	MOVE LEFT Option: With MOVE LEFT JUSTIFIED, any leading blanks in <i>operand1</i> are removed (blanks and binary zeros are removed) before the value is placed left-justified into <i>operand2</i>. The remainder of <i>operand2</i> will then be filled with blanks. If the value is longer than <i>operand2</i>, the value will be truncated on the right-hand side.
MOVE RIGHT JUSTIFIED	RIGHT JUSTIFIED Option: With MOVE RIGHT JUSTIFIED, any trailing blanks in <i>operand1</i> are truncated (blanks and binary zeros are removed) before the value is placed right-justified into <i>operand2</i>. The remainder of <i>operand2</i> will then be filled with blanks. If the value is longer than <i>operand2</i>, the value will be truncated on the left-hand side. See also Example 1 - Various Samples of MOVE Statement Usage.
<i>parameter</i>	Parameter: When you use MOVE LEFT/RIGHT JUSTIFIED in conjunction with PM=I, the move is performed in the following steps: 1. If <i>operand1</i> is not of alphanumeric/Unicode format, the value is converted to alphanumeric/Unicode format. 2. Any trailing blanks in <i>operand1</i> are removed (blanks and binary zeros are removed). 3. In the case of LEFT JUSTIFIED, any leading blanks in <i>operand1</i> are also removed (blanks and binary zeros are removed). 4. The value is reversed, and then moved to <i>operand2</i>. 5. If applicable, the remainder of <i>operand2</i> is filled with blanks, or the value is truncated (see above).

Syntax 7 - MOVE NORMALIZED

The MOVE NORMALIZED statement converts a Unicode string into the “Unicode Normalization Form C” (NFC). The resulting Unicode string does no longer contain combining sequences for characters which are available as pre-composed characters.

If the format of the target operand is not Unicode itself, an implicit conversion from Unicode into the target operand takes place - during this conversion the default code page (see system variable *CODEPAGE) will be used.

For further information on the `MOVE NORMALIZED` statement, see the section *Statements* in the *Unicode and Code Page Support* documentation.

Syntax Diagram:

```
MOVE NORMALIZED operand1 TO operand2
```

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S	A				U										yes	no
<i>operand2</i>		S	A			A	U										yes	yes

Syntax Element Description:

Syntax Element	Description
MOVE NORMALIZED	MOVE NORMALIZED Option: This option is used to convert Unicode fields with potentially unnormalized content into the “Unicode Normalization Form C” (NFC). This composite form of a Unicode string does not contain combining sequences for characters which are available as pre-composed characters. See also: http://www.unicode.org/reports/tr15/#Canonical_Composition_Examples (“Normalization Forms D and C Examples”). Example: <pre>MOVE NORMALIZED #SCR TO #TGT</pre>
<i>operand1</i>	Source Operand: <i>operand1</i> contains the Unicode string to be converted.
<i>operand2</i>	Target Operand: <i>operand2</i> receives the converted Unicode string.

Example:

Some code points have different representations in Unicode. For example, the German letter 'Ä': the decomposed representation in Unicode is U+0041 followed by U+0308 and uses a combining character (U+0308); another representation is the pre-composed character U+00C4. The `MOVE`

`NORMALIZED` statement converts the Unicode representation with combining characters into a normalized Unicode representation using pre-composed characters, where possible.

Syntax 8 - MOVE ENCODED

This section explains the syntax of the `MOVE ENCODED` statement. For information on the purpose of this statement, see the section *Statements in the Unicode and Code Page Support* documentation.

Syntax Diagram:

```
MOVE ENCODED
  operand1 [[IN] CODEPAGE operand2] TO
  operand3 [[IN] CODEPAGE operand4]
  [GIVING operand5]
```

Operand Definition Table:

Operand	Possible Structure				Possible Formats																Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S	A			A	U	B													yes	no
<i>operand2</i>		S				A	U														yes	no
<i>operand3</i>		S				A	U	B													yes	yes
<i>operand4</i>		S	A			A	U														yes	no
<i>operand5</i>		S						I4													yes	yes

Syntax Element Description:

Syntax Element	Description
<code>MOVE ENCODED</code>	MOVE ENCODED Option: This option converts a character string, encoded in one code page, into the equivalent character string of another code page. Note: Natural uses the International Components for Unicode (ICU) library for Unicode conversion. For more information, see the ICU User Guide at http://userguide.icu-project.org/.
<i>operand1</i>	Source Operand: <i>operand1</i> contains the string to be converted.
<code>CODEPAGE operand2</code>	Code Page of Source Operand: As <i>operand2</i>, you specify the code page of <i>operand1</i>.

Syntax Element	Description
	Can only be supplied if <i>operand1</i> is of format A or B. See Note 1 and 3.
T0 <i>operand3</i>	Target Operand: <i>operand3</i> receives the converted string. If the conversion result does not fit into the target field, the result is padded or truncated, respectively, and as padding character the blank of the resulting code page is used. If the target field is defined as a dynamic variable, no padding or truncation is needed, since the length of the dynamic variable is automatically adjusted to the length of the conversion result.
CODEPAGE <i>operand4</i>	Code Page of Target Operand: As <i>operand4</i>, you specify the code page of <i>operand3</i>. Can only be supplied if <i>operand3</i> is of format A or B. See Note 1 and 3.
GIVING <i>operand5</i>	GIVING Clause: If you omit this clause, a Natural error message is returned if an error occurs. If you specify the keyword <code>GIVING</code>, <i>operand5</i> returns 0 or the Natural error code instead of the Natural error message. If the target gets truncated, no Natural error message is given, but when the keyword <code>GIVING</code> is used, <i>operand5</i> will contain an appropriate error code to indicate truncation.

**Notes:**

1. If a code page operand is not supplied, then the default code page (value of the system variable *CODEPAGE) is used.
2. If the session parameter `CPCVERR` in the statement `SET GLOBALS` or in the system command `GLOBALS` is set to `ON`, an error is output if at least one character of the source field could not be converted properly into the destination code page, but was replaced in the target field by a substitution character.
3. Only code page names defined with the macro `NTCPAGE` in the source module `NATCONFIG` can be used. Other code page names are rejected with a corresponding runtime error.

Examples of MOVE ENCODED:

```
MOVE ENCODED A-FIELD1 TO A-FIELD2
```

Invalid: This results in a syntax error, since the code page names are taken by default and are the same for *operand1* and *operand3*.

```
MOVE ENCODED A-FIELD1 CODEPAGE 'IBM01140' TO A-FIELD2 CODEPAGE 'IBM01140'
```

Invalid: This results in an error, since the coded code page names are the same for *operand1* and *operand3*.

```
MOVE ENCODED A-FIELD1 CODEPAGE 'IBM01140' TO A-FIELD2 CODEPAGE 'IBM037'
```

Valid: The string in A-FIELD1 which is coded in IBM01140 is converted into A-FIELD2 which is coded in IBM037.

```
MOVE ENCODED U-FIELD TO U-FIELD
```

Invalid: This results in an error, since at least one operand must be of format A or B.

```
MOVE ENCODED U-FIELD TO A-FIELD
```

Valid: The Unicode string in U-FIELD which, considered to be encoded in UTF-16, is converted into the alphanumeric A-FIELD in the default code page (*CODEPAGE).

```
MOVE ENCODED A-FIELD TO U-FIELD
```

Valid: The string in A-FIELD which, considered to be encoded in the default code page (*CODEPAGE), is converted into the Unicode field U-FIELD.

```
MOVE ENCODED A100-FIELD CODEPAGE 'IBM1140' TO A50-FIELD CODEPAGE 'IBM037'
```

Valid: Conversion is done from A100-FIELD (format/length: A100) to A50-FIELD (format/length: A50), using the relevant code pages. The target is truncated. No Natural error message is returned.

```
MOVE ENCODED A100-FIELD CODEPAGE 'IBM1140' TO A50-FIELD  
CODEPAGE 'IBM037' GIVING RC-FIELD
```

Valid: Conversion is done from A100-FIELD (format/length: A100) to A50-FIELD (format/length: A50), using the relevant code pages. The target is truncated. Since a GIVING clause is supplied, the RC-FIELD receives an error code, indicating that a value truncation has taken place.

Syntax 9 - MOVE ALL

The `MOVE ALL` statement enables you to move repeatedly the content of *operand1* to *operand2* until the complete target field is full or the `UNTIL` value (*operand7*) is reached.

Using a **SUBSTRING Clause**, you may limit the `MOVE ALL` operation to just segments of the source and target field.

Syntax Diagram:

```
MOVE ALL { operand1
           SUBSTRING (operand1,operand3,operand4) }
      TO { operand2
           SUBSTRING (operand2,operand5,operand6) }
      [UNTIL operand7]
```

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S	A			A	U	N ¹			B					yes	no
<i>operand2</i>		S	A			A	U				B					yes	yes
<i>operand3</i>	C	S						N	P	I	B ²					yes	no
<i>operand4</i>	C	S						N	P	I	B ²					yes	no
<i>operand5</i>	C	S						N	P	I	B ²					yes	no
<i>operand6</i>	C	S						N	P	I	B ²					yes	no
<i>operand7</i>	C	S						N	P	I						yes	no

¹ A numeric format (N) for *operand1* is permitted only when used without the `SUBSTRING` clause.

² If *operand3/operand5* or *operand4/operand6* is a binary variable, it may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Source Operand: The source operand contains the value to be moved. All digits of a numeric operand including leading zeros are moved.
T0 <i>operand2</i>	Target Operand: The target operand is not reset before the execution of the MOVE ALL operation. This is of particular importance when using the UNTIL option since data previously in <i>operand2</i> is retained if not explicitly overlaid during the MOVE ALL operation.
UNTIL <i>operand7</i>	UNTIL Option: The UNTIL option can be used to limit the MOVE ALL operation to a given number of positions in <i>operand2</i>. <i>operand3</i> is used to specify the number of positions. The MOVE ALL operation is terminated when this value is reached. If <i>operand7</i> is greater than the length of <i>operand2</i>, the MOVE ALL operation is terminated when <i>operand2</i> is full. The UNTIL option may also be used to assign an initial value to a dynamic variable: if <i>operand2</i> is a dynamic variable, its length after the MOVE ALL operation will correspond to the value of <i>operand7</i>. The current length of a dynamic variable can be ascertained by using the system variable *LENGTH. For general information on dynamic variables, see <i>Usage of Dynamic Variables</i>. Note: The UNTIL option is not allowed when a SUBSTRING clause is used for the target operand.
SUBSTRING	SUBSTRING Clause: The SUBSTRING clause enables you to select a fixed segment of the source or target variable in a MOVE ALL statement - whereas, without the SUBSTRING clause, the whole content of the source or target variable is processed. <i>operand3</i> and <i>operand4</i> describe the start position and length of the <i>operand1</i> segment used as source value. <i>operand5</i> and <i>operand6</i> describe the start position and length of the <i>operand2</i> segment which is filled by the operation. If the start position (<i>operand3</i> or <i>operand5</i>) is omitted, then position 1 is assumed by default. If the substring length (<i>operand4</i> or <i>operand6</i>) is omitted, then the remaining length of the field is assumed. If SUBSTRING is used for the source field, the start value and length (<i>operand3</i> and <i>operand4</i>) must describe a data segment which is completely inside <i>operand1</i>. If SUBSTRING is used for the target field the following rules apply: ■ If <i>operand2</i> is a fixed length variable, the range described by the start-value and length (<i>operand5</i> and <i>operand6</i>) has completely to reside within the field extent. ■ If <i>operand2</i> is a dynamic length variable, the start value (<i>operand5</i>) can either point into or immediately behind the current field length (*LENGTH + 1). When the end of the

Syntax Element	Description
	SUBSTRING range is within the allocated field data, the operation is processed in the same way as for a fixed length field. When the SUBSTRING end exceeds the current field size, the dynamic variable is expanded to this extent. See also <i>Examples of SUBSTRING Clause Usage</i> below.

Examples of SUBSTRING Clause Usage

```

DEFINE DATA LOCAL
1 ALFA (A10) INIT <'AAAAAAAAAA'>
1 DYN (A) DYNAMIC INIT <'1234567890'>
1 #VAL (A4) INIT <'1234'>
END-DEFINE

```

Statement	Result	
	Before	After
MOVE ALL SUBSTRING (#VAL,1,2) TO ALFA	AAAAAAAAAA	1212121212
MOVE ALL '123' TO SUBSTRING (ALFA,3,5)	AAAAAAAAAA	AA12312AAA
MOVE ALL 'x' TO SUBSTRING (DYN,7,3)	1234567890 (*LENGTH=10)	123456xxx0 (*LENGTH=10)
MOVE ALL 'xyz' TO SUBSTRING (DYN,7,6)	1234567890 (*LENGTH=10)	123456xyzxyz (*LENGTH=12)
MOVE ALL 'xyz' TO SUBSTRING (DYN,11,4)	1234567890 (*LENGTH=10)	1234567890xyzx (*LENGTH=14)

Examples

- [Example 1 - Various Samples of MOVE Statement Usage](#)
- [Example 2 - MOVE BY NAME](#)
- [Example 3 - MOVE BY NAME with Arrays](#)
- [Example 4 - MOVE BY POSITION](#)

■ Example 5 - MOVE ALL

Example 1 - Various Samples of MOVE Statement Usage

```

** Example 'MOVEX1': MOVE
*****
DEFINE DATA LOCAL
1 #A (N3)
1 #B (A5)
1 #C (A2)
1 #D (A7)
1 #E (N1.0)
1 #F (A5)
1 #G (N3.2)
1 #H (A6)
END-DEFINE
*
MOVE 5 TO #A
WRITE NOTITLE 'MOVE 5 TO #A'          30X '=' #A
*
MOVE 'ABCDE' TO #B #C #D
WRITE 'MOVE ABCDE TO #B #C #D'      20X '=' #B '=' #C '=' #D
*
MOVE -1 TO #E
WRITE 'MOVE -1 TO #E'              28X '=' #E
*
MOVE ROUNDED 1.995 TO #E
WRITE 'MOVE ROUNDED 1.995 TO #E'    18X '=' #E
*
*
MOVE RIGHT JUSTIFIED 'ABC' TO #F
WRITE 'MOVE RIGHT JUSTIFIED ''ABC'' TO #F'    10X '=' #F
*
MOVE EDITED '003.45' TO #G (EM=999.99)
WRITE 'MOVE EDITED ''003.45'' TO #G (EM=999.99)'  4X '=' #G
*
MOVE EDITED 123.45 (EM=999.99) TO #H
WRITE 'MOVE EDITED 123.45 (EM=999.99) TO #H'    6X '=' #H
*
END

```


Output of Program MOVEX1:

MOVE 5 TO #A	#A: 5
MOVE ABCDE TO #B #C #D	#B: ABCDE #C: AB #D: ABCDE
MOVE -1 TO #E	#E: -1
MOVE ROUNDED 1.995 TO #E	#E: 2
MOVE RIGHT JUSTIFIED 'ABC' TO #F	#F: ABC
MOVE EDITED '003.45' TO #G (EM=999.99)	#G: 3.45
MOVE EDITED 123.45 (EM=999.99) TO #H	#H: 123.45

Example 2 - MOVE BY NAME

```

** Example 'MOVEX2': MOVE BY NAME
*****
DEFINE DATA LOCAL
1 #SBLOCK
  2 #FIELD1 (A10) INIT <'AAAAAAAAAA'>
  2 #FIELD2 (A10) INIT <'BBBBBBBBBB'>
  2 #FIELD3 (A10) INIT <'CCCCCCCCCC'>
  2 #FIELD4 (A10) INIT <'DDDDDDDDDD'>
1 #TBLOCK
  2 #FIELD1 (A15) INIT <' '>
  2 #FIELD2 (A10) INIT <' '>
  2 #FIELD3 (A10) INIT <' '>
  2 #FIELD4 (A10) INIT <' '>
  2 #FIELD5 (A20) INIT <' '>
  2 #FIELD6 (A10) INIT <' '>
END-DEFINE
*
MOVE BY NAME #SBLOCK TO #TBLOCK
*
WRITE NOTITLE 'CONTENTS OF #TBLOCK AFTER MOVE BY NAME:'
  // '=' #TBLOCK.#FIELD1
  / '=' #TBLOCK.#FIELD2
  / '=' #TBLOCK.#FIELD3
  / '=' #TBLOCK.#FIELD4
  / '=' #TBLOCK.#FIELD5
  / '=' #TBLOCK.#FIELD6
*
END

```

Contents of #TBLOCK after MOVE BY NAME Processing:

```
CONTENTS OF #TBLOCK AFTER MOVE BY NAME:
```

```
#FIELD1:  
#FIELD A: AAAAAAAAAA  
#FIELD2:  
#FIELD B: BBBBBBBBBB  
#FIELD3:  
#FIELD C: CCCCCCCCCC
```

Example 3 - MOVE BY NAME with Arrays

```
DEFINE DATA LOCAL  
  1 #GROUP1  
    2 #FIELD (A10/1:10)  
  1 #GROUP2  
    2 #FIELD (A10/1:10)  
END-DEFINE  
...  
MOVE BY NAME #GROUP1 TO #GROUP2  
...
```

In this example, the MOVE statement would internally be resolved as:

```
MOVE #GROUP1.#FIELD (*) TO #GROUP2.#FIELD (*)
```

If part of an indexed group is moved to another part of the same group, this may lead to unexpected results as shown in the example below.

```
DEFINE DATA LOCAL  
  1 #GROUP1 (1:5)  
    2 #FIELD A (N1) INIT <1,2,3,4,5>  
    2 REDEFINE #FIELD A  
      3 #FIELD B (N1)  
END-DEFINE  
...  
MOVE BY NAME #GROUP1 (2:4) TO #GROUP1 (1:3)  
...
```

In this example, the MOVE statement would internally be resolved as:

```
MOVE #FIELDA (2:4) TO #FIELDA (1:3)
MOVE #FIELDB (2:4) TO #FIELDB (1:3)
```

First, the contents of the occurrences 2 to 4 of #FIELDA are moved to the occurrences 1 to 3 of #FIELDA; that is, the occurrences receive the following values:

Occurrence:	1.	2.	3.	4.	5.
Value before:	1	2	3	4	5
Value after:	2	3	4	4	5

Then the contents of the occurrences 2 to 4 of #FIELDB are moved to the occurrences 1 to 3 of #FIELDB; that is, the occurrences receive the following values:

Occurrence:	1.	2.	3.	4.	5.
Value before:	2	3	4	4	5
Value after:	3	4	4	4	5

Example 4 - MOVE BY POSITION

```
DEFINE DATA LOCAL
  1 #GROUP1
    2 #FIELD1A (N5)
    2 #FIELD1B (A3/1:3)
    2 REDEFINE #FIELD1B
      3 #FIELD1BR (A9)
  1 #GROUP2
    2 #FIELD2A (N5)
    2 #FIELD2B (A3/1:3)
    2 REDEFINE #FIELD2B
      3 #FIELD2BR (A9)
END-DEFINE
...
MOVE BY POSITION #GROUP1 TO #GROUP2
...
```

In this example, the content of #FIELD1A is moved to #FIELD2A, and the content of #FIELD1B to #FIELD2B; the fields #FIELD1BR and #FIELD2BR are not affected.

Example 5 - MOVE ALL

```

** Example 'MOAEX1': MOVE ALL
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 FIRST-NAME
  2 NAME
  2 CITY
1 VEH-VIEW VIEW OF VEHICLES
  2 PERSONNEL-ID
  2 MAKE
END-DEFINE
*
LIMIT 4
RD. READ EMPLOY-VIEW BY NAME
  SUSPEND IDENTICAL SUPPRESS
  /*
  FD. FIND VEH-VIEW WITH PERSONNEL-ID = PERSONNEL-ID (RD.)
    IF NO RECORDS FOUND
      MOVE ALL '*' TO FIRST-NAME (RD.)
      MOVE ALL '*' TO CITY (RD.)
      MOVE ALL '*' TO MAKE (FD.)
    END-NOREC
  /*
  DISPLAY NOTITLE (ES=OFF IS=ON ZP=ON AL=15)
    NAME (RD.) FIRST-NAME (RD.)
    CITY (RD.)
    MAKE (FD.) (IS=OFF)
  /*
  END-FIND
END-READ
END

```

Output of Program MOAEX1:

NAME	FIRST-NAME	CITY	MAKE
ABELLAN	*****	*****	*****
ACHIESON	ROBERT	DERBY	FORD
ADAM	*****	*****	*****
ADKINSON	JEFF	BROOKLYN	GENERAL MOTORS

93

MOVE INDEXED

The `MOVE INDEXED` statement is supported for compatibility reasons only.



Caution: In contrast to a `MOVE` statement with array operands, checks for out-of-bound index values are not possible when a `MOVE INDEXED` statement is executed. As a consequence, when executing an incorrect `MOVE INDEXED` statement, you may unintentionally destroy user data.

Therefore, Software AG strongly recommends that you replace `MOVE INDEXED` statements by `MOVE` statements.

See the statement [MOVE](#).

94

MULTIPLY

▪ Function	738
▪ Syntax 1 - MULTIPLY Statement without GIVING Clause	738
▪ Syntax 2 - MULTIPLY Statement with GIVING Clause	739
▪ Example	740

Related Statements: [ADD](#) | [COMPRESS](#) | [COMPUTE](#) | [DIVIDE](#) | [EXAMINE](#) | [MOVE](#) | [MOVE ALL](#) | [RESET](#) | [SEPARATE](#) | [SUBTRACT](#)

Belongs to Function Group: *Arithmetic and Data Movement Operations*

Function

The `MULTIPLY` statement is used to multiply two operands. Depending on the syntax used, the result of the multiplication may be stored in *operand1* or *operand3*.

If a database field is used as the result field, the multiplication results in an update only to the internal value of the field as used within the program. The value for the field in the database remains unchanged.

For multiplications involving arrays, see also *Rules for Arithmetic Assignments, Arithmetic Operations with Arrays* (in the *Programming Guide*).

Two different structures are possible for this statement.

Syntax 1 - MULTIPLY Statement without GIVING Clause

When Syntax 1 used, the result of the multiplication can be stored in *operand1*.

MULTIPLY [\[ROUNDED\]](#) *operand1* BY { *(arithmetic-expression)*
operand2 }

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Operand Definition Table:

Operand	Possible Structure				Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>		S	A		M	N	P	I	F						yes	no
<i>operand2</i>	C	S	A		N	N	P	I	F						yes	no

Syntax Element Description:

Syntax Element	Description
<i>arithmetic-expression</i>	See Arithmetic Expression in the COMPUTE statement.
<i>operand1</i> BY <i>operand2</i>	Operands: <i>operand1</i> is the multiplicand, <i>operand2</i> is the multiplier. The result is stored in <i>operand1</i> , hence the statement is equivalent to: <pre><i>operand1</i> := <i>operand1</i> * <i>operand2</i></pre>
ROUNDED	ROUNDED Option: If you specify the keyword ROUNDED, the value will be rounded before it is assigned to <i>operand1</i> or <i>operand3</i> . For information on rounding, see <i>Rules for Arithmetic Assignment, Field Truncation and Field Rounding</i> in the <i>Programming Guide</i> .

Syntax 2 - MULTIPLY Statement with GIVING Clause

When Syntax 2 is used, the result of the multiplication can be stored in *operand3*.

MULTIPLY [ROUNDED]	{ <i>(arithmetic-expression)</i> <i>operand1</i>	BY	{ <i>(arithmetic-expression)</i> <i>operand2</i>	GIVING <i>operand3</i>

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition	
<i>operand1</i>	C	S	A		M			N	P	I	F						yes	no
<i>operand2</i>	C	S	A		N			N	P	I	F						yes	no
<i>operand3</i>		S	A		M	A	U	N	P	I	F	B*	T				yes	yes

* Format B of *operand3* may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
<i>arithmetic-expression</i>	See Arithmetic Expression in the COMPUTE statement.
<i>operand1</i> BY <i>operand2</i> GIVING <i>operand3</i>	Operands: <i>operand1</i> is the multiplicand, <i>operand2</i> is the multiplier. The result will be stored in <i>operand3</i> , hence the statement is equivalent to: <pre><i>operand3</i> := <i>operand1</i> * <i>operand2</i></pre>
ROUNDED	ROUNDED Option: If you specify the keyword ROUNDED, the value will be rounded before it is assigned to <i>operand1</i> or <i>operand3</i> . For information on rounding, see <i>Rules for Arithmetic Assignment, Field Truncation and Field Rounding</i> in the <i>Programming Guide</i> .

Example

```

** Example 'MULEX1': MULTIPLY
*****
DEFINE DATA LOCAL
1 #A      (N3) INIT <20>
1 #B      (N5)
1 #C      (N3.1)
1 #D      (N2)
1 #ARRAY1 (N5/1:4,1:4) INIT (2,*) <5>
1 #ARRAY2 (N5/1:4,1:4) INIT (4,*) <10>
END-DEFINE
*
MULTIPLY #A BY 3
WRITE NOTITLE 'MULTIPLY #A BY 3'          25X '=' #A
*
MULTIPLY #A BY 3 GIVING #B
WRITE 'MULTIPLY #A BY 3 GIVING #B'        15X '=' #B
*
MULTIPLY ROUNDED 3 BY 3.5 GIVING #C
WRITE 'MULTIPLY ROUNDED 3 BY 3.5 GIVING #C' 6X '=' #C
*
MULTIPLY 3 BY -4 GIVING #D
WRITE 'MULTIPLY 3 BY -4 GIVING #D'         14X '=' #D
*
MULTIPLY -3 BY -4 GIVING #D
WRITE 'MULTIPLY -3 BY -4 GIVING #D'        14X '=' #D
*
MULTIPLY 3 BY 0 GIVING #D
WRITE 'MULTIPLY 3 BY 0 GIVING #D'          14X '=' #D
*

```

```

WRITE / '=' #ARRAY1 (2,*) '=' #ARRAY2 (4,*)
MULTIPLY #ARRAY1 (2,*) BY #ARRAY2 (4,*)
WRITE / 'MULTIPLY #ARRAY1 (2,*) BY #ARRAY2 (4,*)'
      / '=' #ARRAY1 (2,*) '=' #ARRAY2 (4,*)
*
END

```

Output of Program MULEX1:

```

MULTIPLY #A BY 3                      #A: 60
MULTIPLY #A BY 3 GIVING #B            #B: 180
MULTIPLY ROUNDED 3 BY 3.5 GIVING #C   #C: 10.5
MULTIPLY 3 BY -4 GIVING #D            #D: -12
MULTIPLY -3 BY -4 GIVING #D          #D: 12
MULTIPLY 3 BY 0 GIVING #D            #D: 0

#ARRAY1:      5      5      5      5 #ARRAY2:      10      10      10      10


MULTIPLY #ARRAY1 (2,*) BY #ARRAY2 (4,*)
#ARRAY1:      50      50      50      50 #ARRAY2:      10      10      10      10

```


95

NEWPAGE

■ Function	744
■ Syntax Description	744
■ Example	745



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [AT END OF PAGE](#) | [AT TOP OF PAGE](#) | [CLOSE PRINTER](#) | [DEFINE PRINTER](#) | [DISPLAY](#) | [EJECT](#) | [FORMAT](#) | [PRINT](#) | [SKIP](#) | [SUSPEND IDENTICAL SUPPRESS](#) | [WRITE](#) | [WRITE TITLE](#) | [WRITE TRAILER](#)

Belongs to Function Group: [Creation of Output Reports](#)

Function

The NEWPAGE statement is used to cause an advance to a new page. NEWPAGE also causes any [AT END OF PAGE](#) and [WRITE TRAILER](#) statements to be executed. A default title containing the date, time of day and page number will appear on each new page unless a [WRITE TITLE](#), [WRITE NOTITLE](#) or [DISPLAY NOTITLE](#) statement is specified to define specific title processing.

 Notes:

1. The advance to a new page is not performed at the time when the NEWPAGE statement is executed. It is performed only when a subsequent statement which produces output is executed.
2. If the NEWPAGE statement is not used, page advance is controlled automatically based on the Natural profile/session parameter PS (Page Size for Natural Reports).

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
operand1	C	S				N	P	I								yes	no

Syntax Element Description:

Syntax Element	Description
<i>(rep)</i>	Report Specification: The notation <i>(rep)</i> may be used to specify the identification of the report for which the NEWPAGE statement is applicable. A value in the range 0 - 31 or a logical name which has been assigned using the DEFINE PRINTER statement may be specified. If <i>(rep)</i> is not specified, the NEWPAGE statement will be applicable to the first report (Report 0). For information on how to control the format of an output report created with Natural, see <i>Report Format and Control</i> (in the <i>Programming Guide</i>).
EVEN IF TOP OF PAGE	EVEN IF TOP OF PAGE Option: This option is used to cause a new page (with corresponding AT TOP OF PAGE and page title processing) to be generated, even if a new page was initiated immediately before the NEWPAGE statement was encountered.
WHEN LESS THAN <i>operand1</i> LINES LEFT	WHEN LESS THAN ... LINES LEFT Option: This option is used to cause a new page to be generated when there are less than <i>operand1</i> lines left on the current page (current line count compared with value for the Natural profile/session parameter PS).
WITH TITLE <i>title-definition</i>	WITH TITLE Option: This option can be used to specify a title which is to be written to the new page generated. The <i>title-definition</i> is specified using the same syntax as described for the WRITE TITLE statement, except that the SKIP clause is not allowed in a NEWPAGE WITH TITLE <i>title-definition</i> statement.

Example

```

** Example 'NWPEX1': NEWPAGE
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 CITY
  2 NAME
  2 SALARY      (1)
  2 CURR-CODE (1)
END-DEFINE
*
LIMIT 15
READ EMPLOY-VIEW BY CITY FROM 'DENVER'

```

```

DISPLAY CITY (IS=ON) NAME SALARY (1) CURR-CODE (1)
AT BREAK OF CITY
  SKIP 1
/*
  NEWPAGE WHEN LESS THAN 10 LINES LEFT
  WRITE '*****'
    / 'SUMMARY FOR ' OLD(CITY)
    / '*****'
    / '*****'
    / 'SUM OF SALARIES:' SUM(SALARY(1))
    / 'AVG OF SALARIES:' AVER(SALARY(1))
    / '*****'
  NEWPAGE
/*
END-BREAK
END-READ
END

```

Output of Program NWPEX1 - Page 1:

```

Page      1                                05-01-18  10:01:45

      CITY                NAME                ANNUAL  CURRENCY
              SALARY                CODE
-----
DENVER                TANIMOTO                33000  USD
                   MEYER                50000  USD

*****
SUMMARY FOR  DENVER
*****
*****
SUM OF SALARIES:      83000
AVG OF SALARIES:      41500
*****

```

Output of Program NWPEX1 - Page 2:

```

Page      2                                05-01-18  10:01:45

      CITY                NAME                ANNUAL  CURRENCY
              SALARY                CODE
-----
DERBY                DEAKIN                8750  UKL
                   GARFIELD                6750  UKL
                   MUNN                8800  UKL
                   MUNN                5650  UKL
                   GREBBY                9550  UKL
                   WHITT                8650  UKL

```


PONSONBY	5500 UKL
MAGUIRE	4150 UKL
HEYWOOD	3900 UKL
BRYDEN	6750 UKL
SMITH	39000 UKL
CONQUEST	45000 UKL
ACHIESON	11300 UKL

SUMMARY FOR DERBY

Output of Program NWPEX1 - Page 3:

DERBY	DEAKIN	8750 UKL
	GARFIELD	6750 UKL
	MUNN	8800 UKL
	MUNN	5650 UKL
	GREBBY	9550 UKL
	WHITT	8650 UKL
	PONSONBY	5500 UKL
	MAGUIRE	4150 UKL
	HEYWOOD	3900 UKL
	BRYDEN	6750 UKL
	SMITH	39000 UKL
	CONQUEST	45000 UKL
	ACHIESON	11300 UKL

SUMMARY FOR DERBY

SUM OF SALARIES: 163750
AVG OF SALARIES: 12596

96

OBTAIN

■ Function	750
■ Restriction	750
■ Syntax Description	751
■ Examples	755

OBTAIN *operand1* ...

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Belongs to Function Group: [Reporting Mode Statements](#)

Function

The `OBTAIN` statement is used in reporting mode to cause one or more fields to be read from a file. The `OBTAIN` statement does not generate any executable code in the Natural object program. It is primarily used to read a range of values of a multiple-value field or a range of occurrences of a periodic group so that portions of these ranges may be subsequently referenced in the program.

An `OBTAIN` statement is *not* required for each database field to be referenced in the program since Natural automatically reads each database field referenced in a subsequent statement (for example, a `DISPLAY` or `COMPUTE` statement).

When multiple-value or periodic-group fields in the form of an array are referenced, the array must be defined with an `OBTAIN` statement to ensure that it is built for all occurrences of the fields. If individual multiple-value or periodic-group fields are referenced before the array is defined, the fields will not be placed within the array and will exist independent of the array. The fields will contain the same value as the corresponding occurrence within the array.

Individual occurrences of multiple-value or periodic-group fields or subarrays can be held within a previously defined array if the array dimensions of the second individual occurrence or array are contained within the initial array.

References to multiple-value or periodic-group fields with unique variable index cannot be contained in an array of values. If individual occurrences of an array are to be processed with a variable index, the index expression must be prefixed with the unique variable index to denote the individual array.

Restriction

The `OBTAIN` statement is for reporting mode only.

Syntax Description

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	S A G	A U N P I F B D T L	yes	yes

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Fields to be Read: With <i>operand1</i> you specify the field(s) to be made available as a result of the OBTAIN statement.

Examples:

```
READ FINANCE OBTAIN CREDIT-CARD (1-10)
DISPLAY CREDIT-CARD (3-5) CREDIT-CARD (6-8)
SKIP 1 END
```

The above example results in the first 10 occurrences of the field CREDIT-CARD (which is contained in a periodic group) being read and occurrences 3-5 and 6-8 being displayed where the subsequent subarrays will reside in the initial array (1-10).

```
READ FINANCE
MOVE 'ONE' TO CREDIT-CARD (1)
DISPLAY CREDIT-CARD (1) CREDIT-CARD (1-5)
```

Output:

```

CREDIT-CARD  CREDIT-CARD
-----
ONE          DINERS CLUB
             AMERICAN EXPRESS

ONE          AVIS
             AMERICAN EXPRESS
```

OBTAIN

```
ONE          HERTZ
              AMERICAN EXPRESS
```

```
ONE          UNITED AIR TRAVEL
```

The first reference to CREDIT-CARD (1) is not contained within the array. The array which is defined after the reference to the unique occurrence (1) cannot retroactively include a unique occurrence or an array which is shorter than the one being defined.

```
READ FINANCE
OBTAIN CREDIT-CARD (1-5)
MOVE 'ONE' TO CREDIT-CARD (1)
DISPLAY CREDIT-CARD (1) CREDIT-CARD (1-5)
```

Output:

CREDIT-CARD	CREDIT-CARD
-----	-----
ONE	ONE AMERICAN EXPRESS
ONE	ONE AMERICAN EXPRESS
ONE	ONE AMERICAN EXPRESS
ONE	ONE

The individual reference to CREDIT-CARD (1) is contained within the array defined in the OBTAIN statement.

```

MOVE (1) TO INDEX
READ FINANCE
DISPLAY CREDIT-CARD (1-5) CREDIT-CARD (INDEX)

```

Output:

CREDIT-CARD	CREDIT-CARD
DINERS CLUB	DINERS CLUB
AMERICAN EXPRESS	
AVIS	AVIS
AMERICAN EXPRESS	
HERTZ	HERTZ
AMERICAN EXPRESS	
UNITED AIR TRAVEL	UNITED AIR TRAVEL

The reference to CREDIT-CARD using the variable index notation is not contained within the array.

```

RESET A(A20) B(A20) C(A20)
MOVE 2 TO I (N3)
MOVE 3 TO J (N3)
READ FINANCE
OBTAIN CREDIT-CARD (1:3) CREDIT-CARD (I:I+2) CREDIT-CARD (J:J+2)
FOR K (N3) = 1 TO 3
  MOVE CREDIT-CARD (1.K) TO A
  MOVE CREDIT-CARD (I.K) TO B
  MOVE CREDIT-CARD (J.K) TO C
  DISPLAY A B C
LOOP /* FOR
LOOP / * READ
END

```

Output:

A	B	C

CARD 01	CARD 02	CARD 03
CARD 02	CARD 03	CARD 04
CARD 03	CARD 04	CARD 05

The three arrays may be accessed individually by using the unique base index as qualifier for the index expression.

Invalid Example 1

```
READ FINANCE
OBTAIN CREDIT-CARD (1-10)
FOR I 1 10
MOVE CREDIT-CARD (I) TO A(A20)
WRITE A
END
```

The above example will produce error message NAT1006 (value for variable index = 0) because, at the time the record is read (READ), the index I still contains the value 0.

In any case, the above example would not have printed the first 10 occurrences of CREDIT-CARD because the individual occurrence with the variable index cannot be contained in the array and the variable index (I) is only evaluated when the next record is read.

The following is the correct method of performing the above:

```
READ FINANCE
OBTAIN CREDIT-CARD (1-10)
FOR I 1 10
MOVE CREDIT-CARD (1,I) TO A (A20)
WRITE A
END
```

Invalid Example 2

```
READ FINANCE
FOR I 1 10
WRITE CREDIT-CARD (I)
END
```

The above example will produce error message NAT1006 because the index I is zero when the record is read in the **READ** statement.

The following is the correct method of performing the above:


```

READ FINANCE
FOR I 1 10
GET SAME
WRITE CREDIT-CARD (0030/I)
END

```

The **GET SAME** statement is necessary to reread the record after the variable index has been updated in the **FOR** loop.

Examples

- [Example 1 - OBTAIN Statement](#)
- [Example 2 - OBTAIN Statement with Multiple Ranges](#)

Example 1 - OBTAIN Statement

```

** Example 'OBTEX1': OBTAIN
*****
RESET #INDEX (I1)
*
LIMIT 5
READ EMPLOYEES BY CITY
  OBTAIN SALARY (1:4)
  /*
  IF SALARY (4) GT 0 DO
    WRITE '=' NAME / 'SALARIES (1:4):' SALARY (1:4)
    FOR #INDEX 1 TO 4
      WRITE 'SALARY' #INDEX SALARY (1.#INDEX)
    LOOP
    SKIP 1
  DOEND
LOOP
*
END

```

Output of Program OBTEX1:

```

Page      1                                05-02-08  13:37:48

NAME: SENKO
SALARIES (1:4):      31500      29900      28100      26600
SALARY   1      31500
SALARY   2      29900
SALARY   3      28100
SALARY   4      26600

NAME: HAMMOND

```

```
SALARIES (1:4):      22000      20200      18700      17500
SALARY      1      22000
SALARY      2      20200
SALARY      3      18700
SALARY      4      17500
```

Example 2 - OBTAIN Statement with Multiple Ranges

```
** Example 'OBTEX2': OBTAIN (with multiple ranges)
*****
RESET #INDEX (I1) #K (I1)
*
#INDEX      := 2
#K          := 3
*
LIMIT 2
*
READ EMPLOYEES BY CITY
  OBTAIN SALARY (1:5)
    SALARY (#INDEX:#INDEX+3)
/*
IF SALARY (5) GT 0 DO
  WRITE '=' NAME
  WRITE 'SALARIES (1-5):' SALARY (1:5) /
  WRITE 'SALARIES (2-5):' SALARY (#INDEX:#INDEX+3)
  WRITE 'SALARIES (2-5):' SALARY (#INDEX.1:4) /
  WRITE 'SALARY 3:' SALARY (3)
  WRITE 'SALARY 3:' SALARY (#K)
  WRITE 'SALARY 4:' SALARY (#INDEX.#K)
DOEND
LOOP
```

Output of Program OBTEX2:

Page105-02-0813:38:31

```
NAME: SENKO
SALARIES (1-5):      31500      29900      28100      26600      25200

SALARIES (2-5):      29900      28100      26600      25200
SALARIES (2-5):      29900      28100      26600      25200

SALARY 3:      28100
SALARY 3:      28100
SALARY 4:      26600
```

For further examples of using the OBTAIN statement, see *Referencing a Database Array in the Programming Guide*.

97

ON ERROR

■ Function	758
■ Restriction	758
■ Syntax Description	759
■ ON ERROR Processing within Objects on Different Levels	759
■ System Variables	760
■ Example	760

Structured Mode Syntax

```
ON ERROR  
  statement ...  
END-ERROR
```

Reporting Mode Syntax

```
ON ERROR { statement ...  
          DO statement ... DOEND } }
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [DECIDE FOR](#) | [DECIDE ON](#) | [IF](#) | [IF SELECTION](#)

Function

The ON ERROR statement is used to intercept execution time errors which would otherwise result in a Natural error message, followed by termination of Natural program execution, and a return to command input mode.

When the ON ERROR statement block is entered for execution, the normal flow of program execution has been interrupted and cannot be resumed except for Natural error 3145 (record requested in hold), in which case a RETRY statement will cause processing to be resumed exactly where it was suspended.

This statement is non-procedural (that is, its execution depends on an event, not on where in a program it is located).

Restriction

Only one ON ERROR statement is permitted in a Natural object.

Syntax Description

Syntax Element	Description
<code>statement...</code>	Defining the ON ERROR Processing: To define the processing that shall take place when an ON ERROR condition has been encountered, you can specify one or multiple statements. Exiting from an ON ERROR Block: An ON ERROR block may be exited by using a FETCH, STOP, TERMINATE, RETRY, ESCAPE ROUTINE or ESCAPE MODULE statement. If the block is not exited using one of these statements, standard error message processing is performed and program execution is terminated.
END-ERROR	End of ON ERROR Statement Block:
<code>statement ...</code> <code>DO statement ... DOEND</code>	In structured mode, the Natural reserved word END-ERROR must be used to end an ON ERROR statement block. In reporting mode, use the DO ... DOEND statements to supply one or multiple statements, and to end the ON ERROR statement. If you specify only a single statement, you can omit the DO ... DOEND statements. With respect to good coding practice, this is not recommended.

ON ERROR Processing within Objects on Different Levels

In an object call hierarchy created by means of [CALLNAT](#), [PERFORM](#) or [FETCH RETURN](#) statements, each object may contain an ON ERROR statement.

When an error occurs, Natural will trace back the call hierarchy and select the first ON ERROR statement encountered in an object for execution.

For further information, see *Processing of Application Errors* in the *Programming Guide*.

System Variables

The following Natural system variables can be used in conjunction with the `ON ERROR` statement (as shown in the [Example](#) below):

System Variable	Explanation
*ERROR-NR	Contains the number of the error detected by Natural.
*ERROR-LINE	Contains the line number of the statement which caused the error.
*PROGRAM	Contains the name of the Natural object that is currently being executed.

Example

```
** Example 'ONEEX1': ON ERROR
**
**
CAUTION: Executing this example will modify the database records!
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
2 NAME
2 CITY
*
1 #NAME (A20)
1 #CITY (A20)
END-DEFINE
*
REPEAT
  INPUT 'ENTER NAME:' #NAME
  IF #NAME = ' '
    STOP
  END-IF
  FIND EMPLOY-VIEW WITH NAME = #NAME
  INPUT (AD=M) 'ENTER NEW VALUES:' ///
    'NAME:' NAME /
    'CITY:' CITY

  UPDATE
  END TRANSACTION
/*
ON ERROR
  IF *ERROR-NR = 3009
    WRITE 'LAST TRANSACTION NOT SUCCESSFUL'
      / 'HIT ENTER TO RESTART PROGRAM'
    FETCH 'ONEEX1'
  END-IF
```

```
        WRITE 'ERROR' *ERROR-NR 'OCCURRED IN PROGRAM' *PROGRAM  
            'AT LINE' *ERROR-LINE  
        FETCH 'MENU'  
    END-ERROR  
/*  
END-FIND  
END-REPEAT  
END
```


98

OPEN CONVERSATION

■ Function	764
■ Syntax Description	764
■ Further Information and Examples	765

OPEN CONVERSATION USING [SUBPROGRAMS] *operand1* ...

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [CLOSE CONVERSATION](#) | [DEFINE DATA CONTEXT](#)

Belongs to Function Group: [Natural Remote Procedure Call](#)

Function

The statement `OPEN CONVERSATION` is used in conjunction with the Natural RPC (Remote Procedure Call). It allows the RPC Client to open a conversation and specify the remote subprograms to be included in the conversation.

When the `OPEN CONVERSATION` statement is executed, it assigns a unique ID identifying the conversation to the system variable `*CONVID`.

Syntax Description

Operand Definition Table:

Operand	Possible Structure			Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S	A			A								yes	no

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Subprogram Names: As <i>operand1</i> you specify the names of the remote subprograms to be included in the conversation. The name of a subprogram can be specified either as a constant of 1 to 8 characters, or as an alphanumeric variable of length 1 to 8.

Further Information and Examples

See the following sections in the *Natural RPC (Remote Procedure Call)* documentation:

- *Natural RPC Operation in Conversational Mode*
- *Using a Conversational RPC*

99

OPTIONS

■ Function	768
■ Processing of Multiple OPTIONS Statements	768

OPTIONS *parameter* ...

Function

The `OPTIONS` statement can be used to specify compilation options as parameters for the current Natural object. These are the same options that can be specified

- statically with the `NTCMP0` macro;
- dynamically with the `CMPO` parameter;
- within a Natural session with the `COMPOPT` system command.

In addition, the `OPTIONS` statement can be used to specify options for the *Natural Optimizer Compiler*. These options are described in the *Natural Optimizer Compiler* documentation.

Natural Optimizer Compiler options specified with the `MCG` option are checked for validity even if the Natural Optimizer Compiler is not installed.

Processing of Multiple OPTIONS Statements

If multiple `OPTIONS` statements are specified within the same Natural object, the option settings take effect immediately. However, this is not the case with the options `PSIGNF`, `TSENABL`, `GFID`, `DB2BIN` and `DB2PKYU`. For these options, the option value specified with the *last* `OPTIONS` statement applies.

XII

■ 100 PARSE XML	771
■ 101 PASSW	781
■ 102 PERFORM	785
■ 103 PERFORM BREAK PROCESSING	793
■ 104 PRINT	797
■ 105 PROCESS	807
■ 106 PROCESS COMMAND	811
■ 107 PROCESS PAGE	827
■ 108 PROCESS SQL (SQL)	841
■ 109 PROPERTY	845

100

PARSE XML

■ Function	772
■ Syntax Description	773
■ Examples	776

```

PARSE XML operand1 [INTO [PATH operand2] [NAME operand3] [VALUE operand4]]
  [[NORMALIZE] NAMESPACE operand5 PREFIX operand6]
  statement...
END-PARSE                                (structured mode only)
LOOP                                     (reporting mode only)

```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statement: [REQUEST DOCUMENT](#)

Belongs to Function Group: [Internet and XML](#)

Function

The `PARSE XML` statement allows you to parse XML documents from a Natural program. See also *Statements for Internet and XML Access* in the *Programming Guide*.

It is recommended that you use dynamic variables when using the `PARSE` statement, because it is impossible to determine the length of a static variable. Using static variables could in turn lead to the truncation of the value that is to be written into the variable.

For information on Unicode support, see `PARSE XML` in the *Unicode and Code Page Support* documentation.

Mark-Up

The following are markings used in path strings to represent the different data types in an XML document (on ASCII-based systems):

Marking	XML Data	Location in Path String
?	Processing instruction (except for <code><?XML . . . ?></code>)	end
!	Comment	end
C	CDATA section	end
@	Attribute (on mainframes: § or @, depending on session code page and terminal emulation)	before the attribute name
/	Closing tag and/or parent name separator in a path	end or between parent names
\$	Parsed data - character data string	end

By using this additional markup in the path string, one can more easily identify the different elements of the XML document in the output document.

Global Namespace

To specify the global namespace, use a colon (:) as prefix and an empty URI.

Related System Variables

The following Natural system variables are automatically created for each `PARSE XML` statement issued:

- *PARSE-TYPE
- *PARSE-LEVEL
- *PARSE-ROW
- *PARSE-COL
- *PARSE-NAMESPACE-URI

The notation (*r*) after *PARSE-TYPE, *PARSE-LEVEL, *PARSE-ROW, *PARSE-COL and *PARSE-NAMESPACE-URI is used to indicate the label or statement number of the statement in which the `PARSE` was issued. If (*r*) is not specified, the corresponding system variable represents the system variable of the XML data currently being processed in the active `PARSE` processing loop.

For more information on these system variables, see the *System Variables* documentation.

Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats																Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S				A	U	B													yes	no
<i>operand2</i>		S				A	U	B													yes	yes
<i>operand3</i>		S				A	U	B													yes	yes
<i>operand4</i>		S				A	U	B													yes	yes
<i>operand5</i>		S	A			A	U	B													yes	yes
<i>operand6</i>		S	A			A	U	B													yes	yes

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	XML Document: <i>operand1</i> represents the XML document in question. The XML document may not be changed while it is being parsed. If you try to change the XML document during parsing (by writing into it, for example), an error message will be displayed.
<i>operand2</i>	Path: <i>operand2</i> represents the PATH of the data in the XML document. The PATH contains the name of the identified XML part, the names of all parents, as well as the type of the XML part. Note: The information given with PATH can be used to easily fill a tree view. See also Example 1 - Using operand2.
<i>operand3</i>	Data Element Name: <i>operand3</i> represents the NAME of a data element in the XML document. If NAME has no value, then the dynamic variable associated with it will be set to *length()=0, which is a static variable filled with a blank. See also Example 2 - Using operand3.
<i>operand4</i>	Data Element Content: <i>operand4</i> represents the content (VALUE) of a data element in the XML document. If there is no value, a given dynamic variable will be set to *length()=0, which is a static variable filled with a blank. See also Example 3 - Using operand4.
<i>operand5</i> and <i>operand6</i> NORMALIZE NAMESPACE PREFIX	Namespace URI and Prefix: The NAMESPACE URI or Uniform Resource Identifier (<i>operand5</i>) and the namespace PREFIX (<i>operand6</i>) are copied during runtime. Therefore, modifying the namespace mapping arrays inside the PARSE XML loop will not affect the parser. <i>operand5</i> and <i>operand6</i> are one-dimensional arrays with an equal number of occurrences. Namespace normalization is a feature of the PARSE statement. XML is capable of defining namespaces for the element names: <pre><myns:myentity xmlns:myns="http://myuri" /></pre> The NAMESPACE definition consists of two parts: ■ a namespace PREFIX (which is, in this case, myns) and ■ a URI (myuri) to define the namespace.

Syntax Element	Description
	The namespace PREFIX is part of the element name. This means, that for the PARSE statement, and especially for <i>operand2</i>, the generated PATH strings depend on the namespace PREFIX. If the path inside a Natural program is used to indicate specific tags, then this will fail if an XML document uses the correct NAMESPACE (URI), but with a different PREFIX. With namespace normalization, all namespace PREFIXes can be set to defaults which have been defined in the NAMESPACE clause. The first entry will be the one used if a URI is specified more than once. If more than one PREFIX is used in the XML document, then only the first one will be taken into account for the output. The rest will be ignored. The NAMESPACE clause contains pairs of namespace URIs and prefixes. For example: <pre>uri(1) := 'http://namespaces.softwareag.com/natural/demo' pre(1) := 'nat:'</pre> If NAMESPACE is defined inside an XML document, the parser checks to see if that namespace (URI) exists in the normalization table. The prefix of the normalization table is used for all output data from the PARSE statement, instead of the namespace defined in the XML document. See also: ■ Example 4 - Using operand5 and operand6 ■ Example 5 - Using operand5 and operand6 with Namespace Normalization Additional Information Concerning PREFIX: In addition, the following applies to the prefix definition: ■ The prefix definition in the namespace normalization array always has to end in a colon (:), since this is the string that will be replaced. ■ A PREFIX or a URI may only occur once in a namespace normalization array. ■ If a PREFIX or the NAMESPACE URI contains trailing blanks (e.g. when using a static variable), the trailing blanks will be removed before the external parser is called. ■ If the PREFIX definition at the namespace normalization only contains a colon (:), the NAMESPACE PREFIX will be reduced to a colon (:). ■ If the PREFIX definition at the namespace normalization is empty, then the NAMESPACE PREFIX will be deleted.
END-PARSE	End of PARSE XML Statement:
LOOP	In structured mode, the Natural reserved keyword END-PARSE must be used to end the PARSE XML statement. In reporting mode, the Natural statement LOOP is used to end the PARSE XML statement.

Examples

- [Example 1 - Using operand2](#)
- [Example 2 - Using operand3](#)
- [Example 3 - Using operand4](#)
- [Example 4 - Using operand5 and operand6](#)
- [Example 5 - Using operand5 and operand6 with Namespace Normalization](#)

Example 1 - Using operand2

The following XML code

```
myxml := '<?xml version="1.0" ?>' -
        '<employee personnel-id="30016315" >' -
        '<full-name>' -
        '<!--this is just a comment-->' -
        '<first-name>RICHARD</first-name>' -
        '<name>FORDHAM</name>' -
        '</full-name>' -
        '</employee>'
```

processed by the following Natural code:

```
PARSE XML myxml INTO PATH mypath
PRINT mypath
END-PARSE
```

produces the following output:

```
employee
employee/@personnel-id
employee/full-name
employee/full-name/!
employee/full-name/first-name
employee/full-name/first-name/$
employee/full-name/first-name//
employee/full-name/name
employee/full-name/name/$
employee/full-name/name//
employee/full-name//
employee//
```

Example 2 - Using operand3

The following XML code

```
myxml := '<?xml version="1.0" ?>' -
        '<employee personnel-id="30016315" >' -
        '<full-name>' -
        '<!--this is just a comment-->' -
        '<first-name>RICHARD</first-name>' -
        '<name>FORDHAM</name>' -
        '</full-name>' -
        '</employee>'
```

processed by the following Natural code:

```
PARSE XML myxml INTO PATH mypath NAME myname
  DISPLAY (AL=39) mypath myname
END-PARSE
```



Note: produces the following output:

----- MYPATH	----- MYNAME
employee	employee
employee/@personnel-id	personnel-id
employee/full-name	full-name
employee/full-name/!	
employee/full-name/first-name	first-name
employee/full-name/first-name/\$	
employee/full-name/first-name//	first-name
employee/full-name/name	name
employee/full-name/name/\$	
employee/full-name/name//	name
employee/full-name//	full-name
employee//	employee

Example 3 - Using operand4

The following XML code

```
myxml := '<?xml version="1.0" ?>'-
        '<employee personnel-id="30016315" >'-
        '<full-name>'-
        '<!--this is just a comment-->'-
        '<first-name>RICHARD</first-name>'-
        '<name>FORDHAM</name>'-
        '</full-name>'-
        '</employee>'
```

processed by the following Natural code:

```
PARSE XML myxml INTO PATH mypath VALUE myvalue
  DISPLAY (AL=39) mypath myvalue
END-PARSE
```

produces the following output:

-----	-----
MYPATH	MYVALUE
employee	
employee/@personnel-id	30016315
employee/full-name	
employee/full-name/!	this is just a comment
employee/full-name/first-name	
employee/full-name/first-name/\$	RICHARD
employee/full-name/first-name//	
employee/full-name/name	
employee/full-name/name/\$	FORDHAM
employee/full-name/name//	
employee/full-name//	
employee//	

Example 4 - Using operand5 and operand6

The following XML code

```
myxml := '<?xml version="1.0" ?>'-
        '<nat:employee nat:personnel-id="30016315"'-
        ' xmlns:nat="http://namespaces.softwareag.com/natural/demo">'-
        '<nat:full-Name>'-
        '<nat:first-name>RICHARD</nat:first-name>'-
        '<nat:name>FORDHAM</nat:name>'-
        '</nat:full-Name>'-
        '</nat:employee>'
```

processed by the following Natural code:


```

PARSE XML myxml INTO PATH mypath
  PRINT mypath
END-PARSE

```

produces the following output:

```

nat:employee
nat:employee/@nat:personnel-id
nat:employee/@xmlns:nat
nat:employee/nat:full-Name
nat:employee/nat:full-Name/nat:first-name
nat:employee/nat:full-Name/nat:first-name/$
nat:employee/nat:full-Name/nat:first-name//
nat:employee/nat:full-Name/nat:name
nat:employee/nat:full-Name/nat:name/$
nat:employee/nat:full-Name/nat:name//
nat:employee/nat:full-Name//
nat:employee//

```

Example 5 - Using operand5 and operand6 with Namespace Normalization

Using [NORMALIZE NAMESPACE](#), the same XML document as in Example 4 with a different NAMESPACE PREFIX would produce exactly the same output.

XML code:

```

myxml := '<?xml version="1.0" ?>'-
  '<natural:employee natural:personnel-id="30016315"'-
  ' xmlns:natural="http://namespaces.softwareag.com/natural/demo">'-
  '<natural:full-Name>'-
  '<natural:first-name>RICHARD</natural:first-name>'-
  '<natural:name>FORDHAM</natural:name>'-
  '</natural:full-Name>'-
  '</natural:employee>'

```

Natural code:

```

uri(1) := 'http://namespaces.softwareag.com/natural/demo'
pre(1) := 'nat:'
*
PARSE XML myxml INTO PATH mypath NORMALIZE NAMESPACE uri(*) PREFIX pre(*)
  PRINT mypath
END-PARSE

```

Output of above program:

```
nat:employee
nat:employee/@nat:personnel-id
nat:employee/@xmlns:nat
nat:employee/nat:full-Name
nat:employee/nat:full-Name/nat:first-name
nat:employee/nat:full-Name/nat:first-name/$
nat:employee/nat:full-Name/nat:first-name//
nat:employee/nat:full-Name/nat:name
nat:employee/nat:full-Name/nat:name/$
nat:employee/nat:full-Name/nat:name//
nat:employee/nat:full-Name//
nat:employee//
```

101

PASSW

■ Function	782
■ Restriction	783
■ Syntax Description	783
■ Example	784

PASSW=*operand1*

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [DELETE](#) | [END TRANSACTION](#) | [FIND](#) | [HISTOGRAM](#) | [GET](#) | [GET SAME](#) | [GET TRANSACTION](#) | [LIMIT](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [RETRY](#) | [STORE](#) | [UPDATE](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The `PASSW` statement is used to specify a default password for access to Adabas or VSAM files which have been password-protected.



Note: This password can be overwritten using the `PASSWORD` clause of the database access statements [FIND](#), [GET](#), [HISTOGRAM](#), [READ](#), [STORE](#).

Natural Security Considerations

In the security profile of a library, you can specify a default Adabas password (as described in the *Natural Security* documentation); this password applies to all database access statements for which neither an individual password is specified nor a `PASSW` statement applies. It applies within the library in whose security profile it is specified, and also remains in effect in other libraries you subsequently log on to and in whose security profiles no password is specified.

Password Display Protection

If the password is specified as a constant, the `PASSW` statement should always be coded at the very beginning of a source-code line, and there should be no blank between the keyword `PASSW` and the equal sign; this ensures that the password is not visible/displayable in the source code of the program.

In TP mode:	You may enter the <code>PASSW</code> statement invisible by entering the terminal command <code>%*</code> before you type in the <code>PASSW</code> statement.

In batch mode:	A password may be provided by specifying the following statements in the line editor: <pre>EDT PASSW='password' END .E RUN</pre> The password value will not appear in the printed output.

Restriction

This statement is not valid for DL/I and DB2 databases.

Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S				A											yes	no

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Password: The password (<i>operand1</i>) may be specified as an alphanumeric constant or the content of an alphanumeric variable. It may consist of up to 8 characters, and must not contain special characters or embedded blanks. If the password is specified as a constant, it must be enclosed in apostrophes. The password specified with the <code>PASSW</code> statement applies to all database access statements (<code>FIND</code>, <code>GET</code>, <code>HISTOGRAM</code>, <code>READ</code>, <code>STORE</code>) for which no individual password is specified. It remains in effect until another password is specified in the execution of a subsequent <code>PASSW</code> statement or the Natural session is terminated. A password specified with a specific database access statement applies only to that statement, not to any subsequent statement.

Example

Example Program PWDEX1 with Password Display Protection (see [above](#)):

```
** Example 'PWDEX1': PASSW
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
END-DEFINE
*
PASSW=                               ← Password not visible
*
LIMIT 5
READ EMPLOY-VIEW
  DISPLAY NOTITLE PERSONNEL-ID NAME
END-READ
*
END
```

Output of Program PWDEX1:


PERSONNEL ID	NAME

50005800	ADAM
50005600	MORENO
50005500	BLOND
50005300	MAIZIERE
50004900	CAUDAL

102

PERFORM

■ Function	786
■ Syntax Description	786
■ Examples	789



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [CALL](#) | [CALL FILE](#) | [CALL LOOP](#) | [CALLNAT](#) | [DEFINE SUBROUTINE](#) | [ESCAPE](#) | [FETCH](#)

Belongs to Function Group: [Invoking Programs and Routines](#)

Function

The `PERFORM` statement is used to invoke a Natural [subroutine](#).

Nested PERFORM Statements

The invoked subroutine may contain a `PERFORM` statement to invoke another subroutine (the number of nested levels is limited by the size of the required memory).

A subroutine may invoke itself (recursive subroutine). If database operations are contained within an external subroutine that is invoked recursively, Natural will ensure that the database operations are logically separated.

Parameter Transfer with Dynamic Variables

See the statement [CALLNAT](#).

Syntax Description

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	C S A G	A U N P I F B D T L C G O	yes	yes

Syntax Element Description:

Syntax Element	Description
<i>subroutine-name</i>	Subroutine to be Invoked: For a subroutine name (maximum 32 characters), the same naming conventions apply as for user-defined variables. The subroutine name is independent of the name of the module in which the subroutine is defined (it may but need not be the same). The subroutine to be invoked must be defined with a <code>DEFINE SUBROUTINE</code> statement. It may be an inline or external subroutine (see DEFINE SUBROUTINE statement). Within one object, no more than 50 external subroutines may be referenced. Data Available in a Subroutine ■ Inline Subroutines No explicit parameters can be passed from the invoking object to an inline subroutine. An inline subroutine has access to the currently established global data area as well as the local data area defined within the same object module. ■ External Subroutines An external subroutine has access to the currently established global data area. Moreover, parameters can be passed with the <code>PERFORM</code> statement from the invoking object to the external subroutine (see <i>operand1</i>); thus, you may reduce the size of the global data area.
<i>operand1</i>	Parameters to be Passed: When an external subroutine is invoked with the <code>PERFORM</code> statement, one or more parameters (<i>operand1</i>) can be passed with the <code>PERFORM</code> statement from the invoking object to the external subroutine. For an inline subroutine, <i>operand1</i> cannot be specified. If parameters are passed, the structure of the parameter list must be defined in a DEFINE DATA statement. By default, the parameters are passed “by reference”, that is, the data are transferred via address parameters, the parameter values themselves are not moved. However, it is also possible to pass parameters “by value”, that is, pass the actual parameter values. To do so, you define these fields in the DEFINE DATA PARAMETER statement of the subroutine with the option <code>BY VALUE</code> or <code>BY VALUE RESULT</code>. ■ If parameters are passed “by reference” the following applies: The sequence, format and length of the parameters in the invoking object must match exactly the sequence, format and length of the DEFINE DATA PARAMETER structure of the invoked subroutine. The names of the variables in the invoking object and the subroutine may be different. ■ If parameters are passed “by value” the following applies: The sequence of the parameters in the invoking object must match exactly the sequence in the DEFINE DATA PARAMETER structure of the invoked subroutine. Formats and lengths of the

Syntax Element	Description										
	variables in the invoking object and the subroutine may be different; however, they have to be data transfer compatible. The names of the variables in the invoking object and the subroutine may be different. If parameter values that have been modified in the subroutine are to be passed back to the invoking object, you have to define these fields with <code>BY VALUE RESULT</code>. With <code>BY VALUE</code> (without <code>RESULT</code>) it is not possible to pass modified parameter values back to the invoking object (regardless of the <code>AD</code> specification; see also below). Note: With <code>BY VALUE</code>, an internal copy of the parameter values is created. The subroutine accesses this copy and can modify it, but this will not affect the original parameter values in the invoking object. With <code>BY VALUE RESULT</code>, an internal copy is likewise created; however, after termination of the subroutine, the original parameter values are overwritten by the (modified) values of the copy. For both ways of passing parameters, the following applies: ■ In the parameter data area of the invoked subroutine, a redefinition of groups is only permitted within a <code>REDEFINE</code> block. ■ If an array is passed, its number of dimensions and occurrences in the subroutine's parameter data area must be same as in the <code>PERFORM</code> parameter list. Note: If multiple occurrences of an array that is defined as part of an indexed group are passed with the <code>PERFORM</code> statement, the corresponding fields in the subroutine's parameter data area must not be redefined, as this would lead to the wrong addresses being passed.										
AD=	Attributes: If <i>operand1</i> is a variable, you can mark it in one of the following ways: <table border="1"> <tr> <td>AD=0</td><td>Non-modifiable, see session parameter AD=0.</td></tr> <tr> <td></td><td>Note: Internally, AD=0 is processed in the same way as <code>BY VALUE</code> (see Note under <i>operand1</i>).</td></tr> <tr> <td>AD=M</td><td>Modifiable, see session parameter AD=M.</td></tr> <tr> <td></td><td>This is the default setting.</td></tr> <tr> <td>AD=A</td><td>Input only, see session parameter AD=A.</td></tr> </table> If <i>operand1</i> is a constant, <code>AD</code> cannot be explicitly specified. For constants, <code>AD=0</code> always applies.	AD=0	Non-modifiable, see session parameter AD=0.		Note: Internally, AD=0 is processed in the same way as <code>BY VALUE</code> (see Note under <i>operand1</i>).	AD=M	Modifiable, see session parameter AD=M.		This is the default setting.	AD=A	Input only, see session parameter AD=A.
AD=0	Non-modifiable, see session parameter AD=0.										
	Note: Internally, AD=0 is processed in the same way as <code>BY VALUE</code> (see Note under <i>operand1</i>).										
AD=M	Modifiable, see session parameter AD=M.										
	This is the default setting.										
AD=A	Input only, see session parameter AD=A.										
nX	Parameters to be Skipped: With the notation <i>nX</i> you can specify that the next <i>n</i> parameters are to be skipped (for example, <code>1X</code> to skip the next parameter, or <code>3X</code> to skip the next three parameters); this means that for the next <i>n</i> parameters no values are passed to the external subroutine.										

Syntax Element	Description
	A parameter that is to be skipped must be defined with the keyword OPTIONAL in the subroutine's DEFINE DATA PARAMETER statement. OPTIONAL means that a value can - but need not - be passed from the invoking object to such a parameter.

Examples

- [Example 1 - PERFORM as Inline Subroutine](#)
- [Example 2 - PERFORM as External Subroutine](#)

Example 1 - PERFORM as Inline Subroutine

```

** Example 'PEREX1': PERFORM (as inline subroutine)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
2 NAME
2 ADDRESS-LINE (A20/2)
2 PHONE
*
1 #ARRAY (A75/1:4)
1 REDEFINE #ARRAY
2 #ALINE (A25/1:4,1:3)
1 #X (N2) INIT <1>
1 #Y (N2) INIT <1>
END-DEFINE
*
LIMIT 5
FIND EMPLOY-VIEW WITH CITY = 'BALTIMORE'
MOVE NAME TO #ALINE (#X,#Y)
MOVE ADDRESS-LINE(1) TO #ALINE (#X+1,#Y)
MOVE ADDRESS-LINE(2) TO #ALINE (#X+2,#Y)
MOVE PHONE TO #ALINE (#X+3,#Y)
IF #Y = 3
RESET INITIAL #Y
/*
PERFORM PRINT
/*
ELSE
ADD 1 TO #Y
END-IF
AT END OF DATA
/*
PERFORM PRINT
/*
END-ENDDATA
END-FIND

```

```
*
DEFINE SUBROUTINE PRINT
  WRITE NOTITLE (AD=OI) #ARRAY(*)
  RESET #ARRAY(*)
  SKIP 1
END-SUBROUTINE
*
END
```

Output of Program PEREX1:

JENSON	LAWLER	FORREST
2120 HASSELL	4588 CANDLEBERRY AVE	37 TENNYSON DRIVE
#206	BALTIMORE	BALTIMORE
998-5038	629-0403	881-3609
ALEXANDER	NEEDHAM	
409 SENECA DRIVE	12609 BUILDERS LANE	
BALTIMORE	BALTIMORE	
345-3690	641-9789	

Example 2 - PERFORM as External Subroutine

Program containing PERFORM statement:

```
** Example 'PEREX2': PERFORM (as external subroutine)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 ADDRESS-LINE (A20/2)
  2 PHONE
*
1 #ALINE (A25/1:4,1:3)
1 #X (N2) INIT <1>
1 #Y (N2) INIT <1>
END-DEFINE
*
LIMIT 5
*
FIND EMPLOY-VIEW WITH CITY = 'BALTIMORE'
  MOVE NAME TO #ALINE (#X,#Y)
  MOVE ADDRESS-LINE(1) TO #ALINE (#X+1,#Y)
  MOVE ADDRESS-LINE(2) TO #ALINE (#X+2,#Y)
  MOVE PHONE TO #ALINE (#X+3,#Y)
  IF #Y = 3
    RESET INITIAL #Y
  /*
    PERFORM PEREX2E #ALINE(*,*)
  /*
ELSE
```

```

    ADD 1 TO #Y
END-IF
AT END OF DATA
/*
    PERFORM PEREX2E #ALINE(*,*)
/*
END-ENDDATA
END-FIND
*
END

```

External subroutine PEREX3 with parameters called by program PEREX2:

```

** Example 'PEREX3': SUBROUTINE (external subroutine with parameters)
*****
DEFINE DATA
PARAMETER
1 #ALINE (A25/1:4,1:3)
END-DEFINE
*
DEFINE SUBROUTINE PEREX2E
    WRITE NOTITLE (AD=OI) #ALINE(*,*)
    RESET #ALINE(*,*)
    SKIP 1
END-SUBROUTINE
*
END

```

Output of Program PEREX2:

JENSON	LAWLER	FORREST
2120 HASSELL	4588 CANDLEBERRY AVE	37 TENNYSON DRIVE
#206	BALTIMORE	BALTIMORE
998-5038	629-0403	881-3609
ALEXANDER	NEEDHAM	
409 SENECA DRIVE	12609 BUILDERS LANE	
BALTIMORE	BALTIMORE	
345-3690	641-9789	

103

PERFORM BREAK PROCESSING

■ Function	794
■ Syntax Description	794
■ Example	795

PERFORM BREAK [PROCESSING] [(r)]
AT BREAK *statement* ...

For explanations of the symbols used in the syntax diagram, see *Syntax Symbols*.

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [DELETE](#) | [END TRANSACTION](#) | [FIND](#) | [GET](#) | [GET SAME](#) | [GET TRANSACTION DATA](#) | [HISTOGRAM](#) | [LIMIT](#) | [PASSW](#) | [READ](#) | [RETRY](#) | [STORE](#) | [UPDATE](#)

Belongs to Function Group: *Database Access and Update*

Function

The `PERFORM BREAK PROCESSING` statement is used to establish break processing in loops created by `FOR`, `REPEAT`, `CALL LOOP` and `CALL FILE` statements where no automatic break processing is established, or whenever a user-initiated break processing is desired. Unlike automatic break processing which is executed immediately after the record is read, the `PERFORM BREAK PROCESSING` statement is executed when it is encountered in the normal flow of the program.

This statement causes a check for a break processing condition (based on the value of a control field) and also results in the evaluation of Natural system functions. This check and system function evaluation are performed each time the statement is encountered for execution. This statement may be executed depending on a condition specified in an `IF` statement.

Syntax Description

Syntax Element	Description
(r)	Statement Reference Notation: By default, the final <code>PERFORM BREAK</code> condition is true at the end of execution of the program, subprogram or subroutine. The notation (r) may be used to relate the final processing of a <code>PERFORM BREAK</code> to a specific loop. In this case the <code>PERFORM BREAK</code> is executed in the loop end handling of this loop; after the final automatic <code>BREAK</code> processing and before the <code>AT END OF DATA</code> statements are executed.
AT BREAK <i>statement</i> ...	See the syntax of the <code>AT BREAK</code> statement.

Example

```

** Example 'PBPEX1S': PERFORM BREAK PROCESSING (structured mode)
*****
DEFINE DATA LOCAL
1 #INDEX (N2)
1 #LINE (N2) INIT <1>
END-DEFINE
*
FOR #INDEX 1 TO 18
    PERFORM BREAK PROCESSING
    /*
    AT BREAK OF #INDEX /1/
        WRITE NOTITLE / 'PLEASE COMPLETE LINES 1-9 ABOVE' /
        RESET INITIAL #LINE
    END-BREAK
    /*
    WRITE NOTITLE '_' (64) '=' #LINE
    ADD 1 TO #LINE
END-FOR
*
END

```

Output of Program PBPEX1S:

```

#LINE: 1
#LINE: 2
#LINE: 3
#LINE: 4
#LINE: 5
#LINE: 6
#LINE: 7
#LINE: 8
#LINE: 9

PLEASE COMPLETE LINES 1-9 ABOVE

#LINE: 1
#LINE: 2
#LINE: 3
#LINE: 4
#LINE: 5
#LINE: 6
#LINE: 7
#LINE: 8
#LINE: 9

PLEASE COMPLETE LINES 1-9 ABOVE


```

Equivalent reporting-mode example: [BPPEX1R](#).

104

PRINT

■ Function	798
■ Syntax Description	799
■ Example	804



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [AT END OF PAGE](#) | [AT TOP OF PAGE](#) | [CLOSE PRINTER](#) | [DEFINE PRINTER](#) | [DISPLAY](#) | [EJECT](#) | [FORMAT](#) | [NEWPAGE](#) | [SKIP](#) | [SUSPEND IDENTICAL SUPPRESS](#) | [WRITE](#) | [WRITE TITLE](#) | [WRITE TRAILER](#)

Belongs to Function Group: [Creation of Output Reports](#)

Function

The `PRINT` statement is used to produce output in free format.

The `PRINT` statement differs from the `WRITE` statement in the following aspects:

- The output for each operand is written according to the value content rather than the length of the operand. Leading zeros for numeric values and trailing blanks for alphanumeric values are suppressed. The session parameter `AD` defines whether numeric values are printed left or right justified. With `AD=L`, the trailing blanks of a numeric value are suppressed. With `AD=R`, the leading blanks of a numeric value are printed.
- If the resulting output exceeds the current line size (`LS` parameter), the output is continued on the next line as follows: An alphanumeric constant or the content of an alphanumeric variable (without edit mask) is split at the rightmost blank or character which is neither a letter nor a numeric character contained on the current line. The first part of the split value is output to the current line, and the second part is written to the next line. Leading blanks in the second part are removed. As a consequence, empty lines are suppressed.

For all other operands, the entire value is written to the next line.

Syntax Description

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	S A G N	A U N P I F B D T L G O	yes	no

Syntax Element Description:

Syntax Element	Description
(<i>rep</i>)	Report Specification: The notation (<i>rep</i>) may be used to specify the identification of the report for which the PRINT statement is applicable. A value in the range 0 - 31 or a logical name which has been assigned using the DEFINE PRINTER statement may be specified. If (<i>rep</i>) is not specified, the PRINT statement will apply to the first report (Report 0). If this printer file is defined to Natural as PC, the report will be downloaded to the PC, see Example 2. For information on how to control the format of an output report created with Natural, see <i>Report Format and Control</i> (in the <i>Programming Guide</i>).
NOTITLE	Default Page Title Suppression: Natural generates a single title line for each page resulting from a PRINT statement. This title contains the page number, the time of day, and the date. Time of day is set at the beginning of the session (TP mode) or at the beginning of the job (batch mode). This default title line may be overridden by using a WRITE TITLE statement, or it may be suppressed by specifying the NOTITLE clause in the PRINT statement. Examples: ■ Default title will be produced: PRINT NAME ■ User title will be produced:

Syntax Element	Description
	<pre>PRINT NAME WRITE TITLE 'user-title'</pre> ■ No title will be produced: <pre>PRINT NOTITLE NAME</pre> If the NOTITLE option is used, it applies to all DISPLAY, PRINT and WRITE statements within the same object which write data to the same report.
NOHDR	Column Header Suppression: The PRINT statement itself does not produce any column headers. However, if you use the PRINT statement in conjunction with a DISPLAY statement, you can use the NOHDR option of the PRINT statement to suppress the column headers generated by the DISPLAY statement. The NOHDR option only takes effect if the execution of the PRINT statement causes a new page to be output. Without the NOHDR option, the column headers (if any) of the DISPLAY statement would be output on this new page; with NOHDR they will not.
<i>statement-parameters</i>	Parameter Definition at Statement Level: One or more parameters, enclosed within parentheses, may be specified at statement level, that is, immediately after the PRINT statement or an element being displayed. Each parameter specified in this manner will override any previous parameter specified in a GLOBALS command, SET GLOBALS (in Reporting Mode only) or FORMAT statement. If more than one parameter is specified, the parameters must be separated from one another by one or more blanks. A parameter entry must not be split between two statement lines. The parameter settings applied here will only be regarded for variable fields, but they have no effect on text-constants. If you would like to set field attributes for a text-constant, they have to be set explicitly for this element, see Parameter Definition at Element (Field) Level. See also: ■ List of Parameters ■ Example of Parameter Usage at Statement and Element (Field) Level
<i>nX, nT, /</i>	Field Positioning, Text, Attribute Assignment: See Field Positioning, Text, Attribute Assignment below.

List of Parameters

Parameters that can be specified with the PRINT statement		Specification (S = at statement level, E = at element level)
AD	Attribute Definition	SE
AL	Alphanumeric Length for Output	SE
CD	Color Definition	SE
CV	Control Variable	SE
DF	Date Format	SE
DL	Display Length for Output	SE
DY	Dynamic Attributes	SE
EM	Edit Mask	SE
EMU	Unicode Edit Mask	E
FL	Floating Point Mantissa Length	SE
MC	Multiple-Value Field Count	S
MP	Maximum Number of Pages of a Report	S
NL	Numeric Length for Output	SE
PC	Periodic Group Count	S
PM	Print Mode	SE
SG	Sign Position	SE
ZP	Zero Printing	SE

The individual session parameters are described in the *Parameter Reference*.

Example of Parameter Usage at Statement and Element (Field) Level

```

DEFINE DATA LOCAL
1 VARI (A4)      INIT <'1234'>          /*      Output
END-DEFINE      /*      Produced
*              /*      -----
PRINT          'Text'          VARI      /*      Text 1234
PRINT (PM=I)   'Text'          VARI      /*      Text 4321
PRINT          'Text' (PM=I)    VARI (PM=I) /*      txeT 4321
PRINT          'Text' (PM=I)    VARI      /*      txeT 1234
END

```

Field Positioning, Text, Attribute Assignment

$\left\{ \left[\begin{array}{c} nX \\ nT \\ / \end{array} \right] \dots \left\{ \begin{array}{l} 'text' [(attributes)] \\ 'c'(n) [(attributes)] \\ ['='] operand1 [(parameters)] \end{array} \right\} \right\} \dots$

Field Positioning Notations

Syntax Element	Description
<i>nX</i>	Column Spacing: This notation inserts <i>n</i> spaces between columns. <i>n</i> must not be zero. PRINT NAME 5X SALARY
<i>nT</i>	Tab Setting: The <i>nT</i> notation causes positioning (tabulation) to print position <i>n</i> . Backward positioning results in a line advance. In the following example, NAME is printed beginning in position 25, and SALARY is printed beginning in position 50: PRINT 25T NAME 50T SALARY
/	Line Advance - Slash Notation: When placed between fields or text elements, a slash (/) causes positioning to the beginning of the next print line. PRINT NAME / SALARY

Text/Attribute Assignment

Syntax Element	Description
' <i>text</i> '	Text Assignment: The character string enclosed by single quotes is displayed.

Syntax Element	Description
	PRINT 'EMPLOYEE' NAME 'MARITAL/STATUS' MAR-STAT
'c' (n)	Character Repetition: The character <i>c</i> enclosed by single quotes is displayed <i>n</i> times immediately before the field value. PRINT '*' (5) '=' NAME
'='	Field Content Positioned behind Field Heading: When placed before a field, the equal sign '=' results in the display of the field heading (as defined in the DEFINE DATA statement or in the DDM) followed by the field contents. PRINT '=' NAME
<i>operand1</i>	Field to be Printed: As <i>operand1</i> you specify the field to be printed.
<i>parameters</i>	Parameter Definition at Element (Field) Level: One or more parameters (see table above), enclosed within parentheses, may be specified immediately after <i>operand1</i>. Each parameter specified in this manner will override any previous parameter specified at statement level or in a GLOBALS command, SET GLOBALS (in Reporting Mode only) or FORMAT statement. If more than one parameter is specified, one or more blanks must be placed between each entry. An entry must not be split between two statement lines. See also: ■ Statement Parameters ■ Example of Parameter Usage at Statement and Element (Field) Level

Output Attributes

attributes indicates the output attributes to be used for text display. Attributes can be:

$\left\{ \begin{array}{l} AD=ad-value \dots \\ BX=bx-value \dots \\ CD=cd-value \\ PM=pm-value \dots \end{array} \right\} \dots$
$\left\{ \begin{array}{l} ad-value \\ cd-value \end{array} \right\} \dots$

Where:

ad-value, *bx-value*, *cd-value* and *pm-value* denote the possible values of the corresponding session parameters AD, BX, CD and PM described in the relevant sections of the *Parameter Reference* documentation.

The compiler actually accepts more than one attribute value for an output field. For example, you can specify: AD=BDI. In such a case, however, only the last value applies. In the given example, only the value I becomes effective and the output field is displayed intensified.

For an alphanumeric/Unicode constant (Natural data format A or U), you can specify *ad-value* and/or *cd-value* without preceding CD= or AD=, respectively. The single value entered is then checked against all possible CD values first. For example: a value of IRE will be interpreted as intensified/red but not as intensified/right-justified/mandatory. You cannot combine a single *cd-value* or *ad-value* with a value preceded by CD= or AD=.

Example

- [Example 1 - PRINT Statement](#)
- [Example 2 - PRINT Statement with Report to be Downloaded to the PC](#)

Example 1 - PRINT Statement

```
** Example 'PRTEX1': PRINT
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 FIRST-NAME
  2 CITY
  2 JOB-TITLE
  2 ADDRESS-LINE (2)
END-DEFINE
*
LIMIT 1
READ EMPLOY-VIEW BY CITY
/*
WRITE NOTITLE 'EXAMPLE 1:'
```

```

// 'RESULT OF WRITE STATEMENT:'
WRITE / NAME ', ' FIRST-NAME ':' JOB-TITLE '*' (30)
WRITE / 'RESULT OF PRINT STATEMENT:'
PRINT / NAME ', ' FIRST-NAME ':' JOB-TITLE '*' (30)
/*
WRITE // 'EXAMPLE 2:'
// 'RESULT OF WRITE STATEMENT:'
WRITE / NAME 60X ADDRESS-LINE (1:2)
WRITE / 'RESULT OF PRINT STATEMENT:'
PRINT / NAME 60X ADDRESS-LINE (1:2)
/*
END-READ
END

```

Output of Program PRTXEX1:

EXAMPLE 1:

RESULT OF WRITE STATEMENT:

```

SENKO           , WILLIE           : PROGRAMMER
*****

```

RESULT OF PRINT STATEMENT:

```

SENKO , WILLIE : PROGRAMMER *****

```

EXAMPLE 2:

RESULT OF WRITE STATEMENT:

```

SENKO
2200 COLUMBIA PIKE    #914

```

RESULT OF PRINT STATEMENT:

```

SENKO                                     2200 COLUMBIA
PIKE #914

```

Example 2 - PRINT Statement with Report to be Downloaded to the PC

```

** Example 'PCPIEX1': PRINT to PC
**
** NOTE: Example requires that Natural Connection is installed.
*****
DEFINE DATA LOCAL
01 PERS VIEW OF EMPLOYEES
  02 PERSONNEL-ID
  02 NAME
  02 CITY

```

PRINT

```
END-DEFINE
*
FIND PERS WITH CITY = 'NEW YORK'      /* Data selection
PRINT (7) 5T CITY 20T NAME 40T PERSONNEL-ID /* (7) designates
                                           /* the output file
                                           /* (here the PC).
END-FIND
END
```

105

PROCESS

■ Function	808
■ Restriction	808
■ Syntax Description	808

```
PROCESS view-name USING {operand1=operand2}, ... [GIVING operand3...]
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Function

The PROCESS statement is used in conjunction with Entire System Server. Entire System Server allows you to use various operating system facilities such as reading and writing files, VTOC and catalog management, JES queues, etc.

See the section *Getting Started* in the *Entire System Server User's Guide* for further information on the PROCESS statement and its individual clauses.

Restriction

This statement is only available with Entire System Server.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S				A		N	P		B					yes	no
<i>operand2</i>	C	S				A	U	N	P		B					yes	no
<i>operand3</i>		S				A		N	P		B					yes	no

Syntax Element Description:

Syntax Element	Description
<i>view-name</i>	View Name: Name of the view used by Entire System Server.
USING	USING Clause: The USING clause is used to pass parameters to the Entire System Server processor. This is done by assigning a value (<i>operand2</i>) to a field (<i>operand1</i>) in a view defined to Entire System Server. See the Entire System Server documentation for view description.

Syntax Element	Description
	Note: Multiple specifications of <i>operand1=operand2</i> must be separated either by the input delimiter character (as specified with the session parameter <code>ID</code>) or by a comma.
GIVING	GIVING Clause: The GIVING clause is used to specify the fields (<i>operand3</i>) for which values are to be returned by the Entire System Server processor. Each field must be defined in a view used by Entire System Server.

106

PROCESS COMMAND

■ Function	813
■ Syntax Description	814
■ Examples	824

CHECK | EXEC | TEXT | HELP Syntax:

PROCESS COMMAND ACTION	
CHECK EXEC TEXT HELP	USING PROCESSOR-NAME= <i>operand1</i>
	COMMAND-LINE (<i>index[:index]</i>)= <i>operand2</i>
	GIVING RESULT-FIELD (<i>index[:index]</i>) (see <i>Syntax Note</i>)
	RETURN-CODE
	[NATURAL-ERROR]

GET Syntax:

PROCESS COMMAND ACTION	
GET USING	PROCESSOR-NAME= <i>operand1</i>
	GETSET-FIELD-NAME= <i>operand3</i>
GIVING	GETSET-FIELD-VALUE (see <i>Syntax Note</i>)
	[NATURAL-ERROR]

SET Syntax:

PROCESS COMMAND ACTION	
SET USING	PROCESSOR-NAME= <i>operand1</i>
	GETSET-FIELD-NAME= <i>operand3</i>
	GETSET-FIELD-VALUE= <i>operand4</i>
	[GIVING NATURAL-ERROR] (see <i>Syntax Note</i>)

CLOSE Syntax:

PROCESS COMMAND ACTION	
CLOSE	[GIVING NATURAL-ERROR] (see <i>Syntax Note</i>)

Syntax Note:

The **GIVING** option is only required in the reporting mode and if no **VIEW OF COMMAND** has been defined in the **DEFINE DATA** statement.

For explanations of the symbols used in the syntax diagram, see *Syntax Symbols*.

Belongs to Function Group: *Invoking Programs and Routines*

Function

Once a Natural Command Processor has been created using the Natural utility `SYSNCP`, it can be invoked from a Natural program using the `PROCESS COMMAND` statement.

For details on how to create a Natural Command Processor, refer to the *SYSNCP Utility* documentation.

DDM Used for Command Processing

 **Important:** The word `COMMAND` in the `PROCESS COMMAND` statement is in fact the name of a view. The name of the view that is used need not necessarily be `COMMAND`; however, we recommend the use of `COMMAND` because there exists a DDM (data definition module) that is also called `COMMAND`. This DDM must be referenced within the `DEFINE DATA` statement, for example `COMMAND VIEW OF COMMAND`.

The DDM `COMMAND` has been created specifically for use in conjunction with the `PROCESS COMMAND` statement:

DB: 1		File: 1 - COMMAND			Default Sequence: ?		
TYL	DB	NAME	F	LENG	S	D	REMARKS
---	--	-----	-	----	-	-	-----
1	AA	PROCESSOR-NAME	A	8	N	D	DE USING
M 1	AB	COMMAND-LINE	A	80	N	D	MU/DE USING
1	AF	GETSET-FIELD-NAME	A	32	N	D	DE USING
1	BA	NATURAL-ERROR	N	4.0	N		GIVING
1	BB	RETURN-CODE	A	4	N		GIVING
M 1	BC	RESULT-FIELD	A	80	N	MU	GIVING
1	BD	GETSET-FIELD-VALUE	A	32	N	D	USING; GIVING
***** DDM OUTPUT TERMINATED *****							

The fields contained in the DDM correspond to the fields used in the `PROCESS COMMAND` statement. They are explained in [Syntax Element Description](#).

 **Note:** To avoid possible compilation or runtime errors, make sure that the DDM named `COMMAND` is cataloged as type C (field `DDM Type` on the `SYSDDM` Menu) before you use it. (If you re-catalog the DDM, any `DBID/FNR` specification in the `SYSDDM` utility will be ignored.)

Security Considerations

With Natural Security, it is possible to restrict the usage of certain keywords and/or functions which are defined in a Command Processor. Keywords and/or functions can be allowed/disallowed for a specific user or group of users. See the *Natural Security* documentation for details.

Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S			A												no	no
<i>operand2</i>	C	S	A	G	A	N											no	no
<i>operand3</i>	C	S			A	N											no	no
<i>operand4</i>	C	S			A	N	P	I									no	no

Syntax Element Description:

Syntax Element	Description
CHECK	CHECK Action: CHECK is used as a precautionary measure to determine if a command is executable with the statement <code>PROCESS COMMAND EXEC</code>. It works as follows: for the given Command Processor name, a runtime check is performed in two steps: ■ It is checked whether the Command Processor exists in the current library or one of its steplibs; ■ The content of the command line <code>COMMAND-LINE (1)</code> is analyzed to determine whether it is acceptable. In addition, the runtime action definitions R, M and 1-9 are written into <code>RESULT-FIELD (1:9)</code>. If the field <code>NATURAL-ERROR</code> is specified in the view or in the <code>GIVING</code> option, it returns the error code. If this field is not available and the command analysis fails, a Natural system error occurs. Note: No CHECK is required if you want to perform an <code>EXEC</code> action. The CHECK is included in an EXEC operation.
EXEC	EXEC Action: EXEC works exactly the same as CHECK with the addition that the runtime actions are executed as specified in the runtime action editor. Only <code>COMMAND-LINE (1)</code> is needed. You can use up to 9 occurrences of <code>RESULT-FIELD</code> (however, for optimum performance, you should not use more occurrences than you really need). Note: EXEC is the only action which can be used to leave the currently active program. This is the case when the runtime action definition contains a <code>FETCH</code> or <code>STOP</code> statement.

Syntax Element	Description
	See also Example 1 - PROCESS COMMAND ACTION EXEC.
TEXT	TEXT Action: TEXT delivers general information about the Command Processor and text associated with a keyword or function. For further information, see the following sections under Input Values for TEXT Actions: ■ TEXT for General Information ■ TEXT for Keyword Information ■ TEXT for Function Information Note: To access texts for keywords and functions, you must have specified Y in the field Catalog user texts on the Processor Header Maintenance 3 screen of the SYSNCP utility, see the section <i>Miscellaneous Options - Header 3</i>.
HELP	HELP Action: HELP returns a list of all valid keywords, synonyms, and functions for the purpose of, for example, the creation of online help windows. This list is contained in the field(s) of RESULT - FIELD. The type of help returned is dependent on the content of the command lines. ■ COMMAND - LINE (1) must contain the search criteria. ■ COMMAND - LINE (2), if specified, must contain the start value or a search value. ■ COMMAND - LINE (3), if specified, must contain a start value. For further information, see the following sections under Input Values for HELP Actions: ■ HELP for Keywords ■ HELP for Synonyms ■ HELP for Global Functions ■ HELP for Local Functions ■ HELP for IKN ■ HELP for IFN Note: For optimum performance, the number of occurrences of the field RESULT - FIELD should not exceed the number of lines to be displayed on the screen. At least one occurrence must be used.
GET	GET Action: GET reads internal Command Processor information and current Command Processor settings from the dynamically allocated NCPWORK buffer.
SET	SET Action: SET modifies internal Command Processor settings in the NCPWORK buffer.

Syntax Element	Description
CLOSE	CLOSE Action: CLOSE terminates the use of the Command Processor and releases the Command Processor buffer. When the Command Processor is used during a session and is not released with CLOSE, then there exists a buffer named NCPWORK in your thread. The parameters of this buffer may be evaluated by using the system command BUS. The runtime part of the Command Processor requires this buffer; it can be released using the statement <code>PROCESS COMMAND ACTION CLOSE</code>. If any <code>PROCESS COMMAND</code> statement follows this statement, then the Command Processor buffer will be opened again. See also Example 2 - PROCESS COMMAND ACTION CLOSE.
GIVING	GIVING Option: This option is only required in reporting mode and if no <code>VIEW OF COMMAND</code> has been defined in the <code>DEFINE DATA</code> statement. The GIVING option is not available in structured mode, because there exists an implicit GIVING option made up of all fields specified in the <code>DEFINE DATA</code> statement, which are usually referenced in the GIVING option for the reporting mode. This means that in structured mode all field defined in the GIVING option must be defined in the <code>DEFINE DATA</code> statement. Note: Specified in the GIVING option are fields to be filled by the Command Processor as a result of the processing of any action.
PROCESSOR-NAME	The name of the Command Processor to be used for processing. The Command Processor specified must be cataloged.
COMMAND-LINE	The command line to be processed by a CHECK or an EXEC action, or the keyword/command for which user text or help text is to be returned to the program by a TEXT or HELP action. Note that this field can contain more than one occurrence.
RESULT-FIELD	Contains information resulting from the use of options that can be specified within a runtime action defined for a Command Processor function (see Runtime Actions in the Natural SYSNCP utility). Note that this field can contain more than one occurrence.
RETURN-CODE	The return code of an operation resulting from an EXEC or a CHECK action as specified within a Runtime Actions definition (see the Natural SYSNCP utility).
NATURAL-ERROR	The Natural error returned for a <code>PROCESS COMMAND</code> action. We recommend that you use this field in the <code>DEFINE DATA</code> statement as it returns the Natural error code for the Command Processor. When the field is absent, Natural runtime error processing is triggered if an error occurs.

Syntax Element	Description
GETSET-FIELD-NAME	The name of the constant or variable that is read when a GET action is performed or that is written with a SET action. For a list of possible values for GETSET-FIELD-NAME, see Input Values for GETSET-FIELD-NAME .
GETSET-FIELD-VALUE	The value of the constant or variable specified in the field GETSET-FIELD-NAME which is read when a GET action is performed or which written with a SET action.

This section covers the following topics:

- [Input Values for GETSET-FIELD-NAME](#)
- [Input Values for TEXT Actions](#)
- [Input Values for HELP Actions](#)

Input Values for GETSET-FIELD-NAME

The following values can be used for the GETSET-FIELD-NAME field (A32):

Field Name	Format	G/S*	Content
NAME	A8	G	Name of current Command Processor.
LIBRARY	A8	G	Loaded from library.
FNR	N10	G	Loaded from file.
DBID	N10	G	Loaded from database.
TIMESTAMP	A8	G	Time stamp of the current Command Processor.
COUNTER	N10	G	Access counter.
BUFFER-LENGTH	N10	G	Bytes allocated for NCPWORK.
C-DELIMITER	A1	G/S	Multiple command delimiter.
DATA-DELIMITER	A1	G	Delimiter to precede data.
PF-KEY	A1	G/S	PF key may be command (Y/N).
UPPER-CASE	A1	G	Keywords in upper case (Y/N).
UQ-KEYWORDS	A1	G	Keywords unique (Y/N).
IMPLICIT-KEYWORD	A1	G/S	Identifier for implicit keyword entry.
MIN-LEN	N10	G	Minimum length of keywords.
MAX-LEN	N10	G	Maximum length of keywords.
KEYWORD-SEQ	A8	G/S	Keyword sequence.
ALT-KEYWORD-SEQ	A8	G/S	Alternative keyword sequence.
USER-SEQUENCE	A1	G	User may override KEYWORD-SEQ (Y/N).
CURR-LOCATION	N10	G/S	Current location (IFN).
CURR-IKN1	N10	G/S	IKN1 of current location.
CURR-IKN2	N10	G/S	IKN2 of current location.

Field Name	Format	G/S*	Content
CURR-IKN3	N10	G/S	IKN3 of current location.
CHECK-LOCATION	N10	G	Last checked location (IFN).
CHECK-IKN1	N10	G	IKN1 of CHECK-LOCATION.
CHECK-IKN2	N10	G	IKN2 of CHECK-LOCATION.
CHECK-IKN3	N10	G	IKN3 of CHECK-LOCATION.
TOP-IKN1	N10	G	IKN1 of topmost keyword.
TOP-IKN2	N10	G	IKN2 of topmost keyword.
TOP-IKN3	N10	G	IKN3 of topmost keyword.
KEY1-TOTAL	N10	G	Number of keywords of type 1.
KEY2-TOTAL	N10	G	Number of keywords of type 2.
KEY3-TOTAL	N10	G	Number of keywords of type 3.
FUNCTIONS-TOTAL	N10	G	Number of cataloged functions.
LOCAL-GLOBAL-SEQ	A8	G/S	Local/global function validation.
ERROR-HANDLER	A8	G/S	General error program.
SECURITY	A1	G	Natural Security installed (Y/N).
SEC-PREFETCH	A1	G	Natural Security data are to be read (Y/N) or have been read (D = done).
PREFIX1	A1	G	Corresponds to the field Prefix Character 1 on the Processor Header Maintenance 2 screen of the SYSNCP utility, see the section <i>Keyword Editor Options - Header 2</i> .
PREFIX2	A1	G	Corresponds to the field Prefix Character 2 on the Processor Header Maintenance 2 screen.
HEX1	A1	G	Corresponds to the field Hex. Replacement 1 on the Processor Header Maintenance 2 screen.
HEX2	A1	G	Corresponds to the field Hex. Replacement 2 on the Processor Header Maintenance 2 screen.
DYNAMIC	A32	G	Dynamic part (:n:) of last error message.
LAST	-	G	Last command placed on top of stack as data.
LAST-ALL	-	G	Last commands placed on top of stack as data.
LAST-COM	-	G	Last command moved to *COM.
MULTI	-	G	Places the last of multiple commands as data on top of the stack.
MULTI-COM	-	G	Places the last of multiple commands in the system variable *COM.

*G = Field name can be used with the [GET action](#).

*S = Field name can be used with the [SET action](#).

Input Values for TEXT Actions

The following input values are provided to return different information from a TEXT action:

TEXT for General Information

For general information, COMMAND-LINE (*); that is, all command lines, must be blank. Up to nine fields of RESULT-FIELD are returned containing the following information:

RESULT-FIELD	Format	Contents
1	Text (A40)	Header 1 for User Text
2	Text (A40)	Header 2 for User Text
3	Text (A16)	"First Entry used as" text
4	Text (A16)	"Second Entry used as" text
5	Text (A16)	"Third Entry used as" text
6	Numeric (N3)	Number of Entry 1 Keywords
7	Numeric (N3)	Number of Entry 2 Keywords
8	Numeric (N3)	Number of Entry 3 Keywords
9	Numeric (N7)	Number of Cataloged Functions

TEXT for Keyword Information

For keyword information, COMMAND-LINE (1) must contain the corresponding keyword; COMMAND-LINE (2) can optionally contain the keyword type (1, 2, 3 or P); COMMAND-LINE (3:6) must be empty.

RESULT-FIELD	Contents	Format
1	Keyword comment text	Text (A40)
2	Keyword in full length	Text (A16)
3	Keyword in unique short form	Text (A16)
4	"Keyword used as" entry	Text (A16)
5	Internal keyword number (IKN)	Numeric (N4)
6	Minimum length of keyword	Numeric (N2)
7	Maximum length of keyword	Numeric (N2)
8	Keyword type (1, 2, 3, 1S, 2S, 3S, P)	Text (A2)

TEXT for Function Information

For function information, COMMAND-LINE (1:3) must contain the keywords which specify the wanted location. COMMAND-LINE (4:6) contains the keywords which specify the wanted function. For example, if information about the global command ADD USER is to be returned, the command lines 1, 2, 3, and 6 must be blank; the command line 4 must contain the text string ADD, and the command line 5 must contain the text string USER.

RESULT-FIELD	Format	Contents
1	Text (A40)	Text as defined with the option T in runtime action definition.
2	Numeric (N10)	Internal function number (IFN) of the specified location.
3	Numeric (N10)	Internal function number (IFN) of the specified function.

Input Values for HELP Actions

The following input values are provided to return different information from a `HELP` action:

HELP for Keywords

This action returns an alphabetically sorted list of keywords and/or synonyms with their internal keyword numbers (IKN).

Command Line	Contents
1	Must begin with indicator K.
	The types of keywords to be returned:
	* Keywords of all types
	1 Keywords with type 1
	2 Keywords with type 2
	3 Keywords with type 3
	P Keywords with type P (parameter)
	Options:
	I Return IKN in addition to keywords.
	T Show keyword partially in upper case (to show possible abbreviation).
	S Return synonyms in addition to keywords.
	X Return only synonyms of specified keywords.
	A Internal keywords are also returned.
	+
	Search does not include start value.
2	Start value for the keyword search (optional). By default, the search begins with the start value. However, if you specify the plus (+) option, the search does not include the start value itself, but begins with the next higher value.

The field `RESULT-FIELD (1:n)` returns the specified list.

Examples:

Command Line 1: K*X Returns all synonyms of all keyword types.

Command Line 1: K123S Returns all keywords of type 1, 2 and 3 including ↵ synonyms.

HELP for Synonyms

For a given IKN, this action returns the original keyword and all synonyms.

Command Line	Contents	
1	Must begin with the indicator S.	
	Option:	
	T	Shows keyword partially in upper case (to show possible abbreviation).
2	Internal Keyword Number (IKN) of the keyword in format N4.	

The field **RESULT-FIELD (1)** returns the original keyword. The fields **RESULT-FIELD (2:n)** return associated synonyms for this keyword.

Example:

Input:	Output:
Command Line 1: S	Result-Field 1: Edit
Command Line 2: 1003	Result-Field 2: Maintain
	Result-Field 3: Modify

HELP for Global Functions

This action returns a list of all global functions.

Command Line	Contents	
1	Must begin with the indicator G.	
	Options:	
	I	Internal Function Number (IFN) is also returned.
	T	Shows keyword partially in upper case (to show possible abbreviation).
	S	The keywords returned in RESULT-FIELD will be aligned in columns.
	A	Internal keywords are also returned.
	1	Only functions containing the given keyword of type 1 are to be returned.

Command Line	Contents	
	2	Only functions containing the given keyword of type 2 are to be returned.
	3	Only functions containing the given keyword of type 3 are to be returned.
	+	Search does not include start value.
2	Start value for global function search. Keywords must be given in sequence 123. By default, the search begins with the start value. However, if you specify the plus (+) option, the search does not include the start value itself, but begins with the next higher value.	
3	Must be blank.	
4	To search only for global functions with a specific keyword, you specify the keyword here. If you specify a keyword, you also have to specify the keyword type (1, 2 or 3) as option (see above).	

The field **RESULT-FIELD (1:n)** returns the specified list.

Example:

Input:		Output:	
Command Line 1:	G	Result-Field 1:	ADD CUSTOMER
Command Line 2:	ADD	Result-Field 2:	ADD FILE
		Result-Field 3:	ADD USER

HELP for Local Functions

This action returns a list of all local functions for a specified location.

Command Line	Contents	
1	Must begin with the indicator L.	
	Options:	
	I	Internal Function Number (IFN) is also returned.
	T	Shows keyword partially in upper case (to show possible abbreviation).
	S	The keywords returned in RESULT-FIELD will be aligned in columns.
	A	Internal keywords are also returned.
	1	Only functions containing given keyword of type 1 are to be returned.
	2	Only functions containing given keyword of type 2 are to be returned.

Command Line	Contents	
	3	Only functions containing given keyword of type 3 are to be returned.
	C	Only those functions are returned which are defined for the current location (command line 3 is ignored).
	F	Invoke “recursive” listing of local functions; that is, all local commands that lead to the current/specified location will be returned.
2	Start value for local function search (optional). Keywords must be given in sequence 1 2 3.	
3	The location for which the list is to be returned. Keywords must be given in sequence 1 2 3. If no location is specified, the current location of the Command Processor will be used.	
4	Keyword restriction (optional): If you specify a keyword, or an IKN with the format N4, only functions with this keyword will be returned.	

The field **RESULT-FIELD (1:n)** returns the specified list.

HELP for IKN

For any given internal keyword numbers (IKN), this action returns the original keyword.

Command Line	Contents	
1	Must start with IKN.	
	Options:	
	A	The internal keyword will be shown.
	T	Shows keyword partially in upper case (to show possible abbreviation).
2	The IKN to be translated, in format N4.	

The field **RESULT-FIELD (1)** returns the keyword.

Example:

Input:	Output:
Command Line 1: IKN	Result-Field 1: CUSTOMER
Command Line 2: 0000002002	

HELP for IFN

For any given internal function numbers (IFN), this action returns the keywords of a function.

Command Line	Contents
1	Must start with IFN. Option: A Functions with internal keywords will not be suppressed.
2	The IFN to be translated, in format N10.
3	Further options: S Keywords belonging to the IFN will be returned in RESULT-FIELD (1:3) . T Shows keywords partially in upper case (to show possible abbreviations). L IFN will be returned if IFN is used as a location. C IFN will be returned if IFN is used as a command.

The field [RESULT-FIELD\(1\)](#) returns the function; if option S is used, the function is returned in [RESULT-FIELD \(1:3\)](#).

Example:

Input:	Output:
Command Line 1: IFN	Result-Field 1: DISPLAY INVOICE
Command Line 2: 0001048578	

Examples

In addition to the example programs shown in this section, you can find example programs in the SYSNCP system library. These programs all begin with EXAM.

You can test all available PROCESS COMMAND actions by executing the EXAM program in SYSNCP. You can then choose an action from a menu.

- [Example 1 - PROCESS COMMAND ACTION EXEC](#)

■ Example 2 - PROCESS COMMAND ACTION CLOSE

Example 1 - PROCESS COMMAND ACTION EXEC

```

/* EXAM-EXS - Example for PROCESS COMMAND ACTION EXEC (Structured Mode)
/*****
DEFINE DATA LOCAL
  01 COMMAND VIEW OF COMMAND
    02 PROCESSOR-NAME
    02 COMMAND-LINE (1)
    02 NATURAL-ERROR
    02 RETURN-CODE
    02 RESULT-FIELD (1)
  01 MSG (A65) INIT <'Please enter a command.'>
END-DEFINE
/*
REPEAT
  INPUT (AD=MIT' ' IP=OFF) WITH TEXT MSG
    'Example for PROCESS COMMAND ACTION EXEC (Structured Mode)' (I)
  / 'Command ==>' COMMAND-LINE (1) (AL=64)
  /*****
PROCESS COMMAND ACTION EXEC
  USING
    PROCESSOR-NAME = 'DEMO'
    COMMAND-LINE (1) = COMMAND-LINE (1)
  /*****
  COMPRESS 'NATURAL-ERROR =' NATURAL-ERROR TO MSG
END-REPEAT
END

```

Example 2 - PROCESS COMMAND ACTION CLOSE

```

/* EXAM-CLS - Example for PROCESS COMMAND ACTION CLOSE (Structured Mode)
/*****
DEFINE DATA LOCAL
  01 COMMAND VIEW OF COMMAND
END-DEFINE
/*
PROCESS COMMAND ACTION CLOSE
/*
DEFINE WINDOW CLS
INPUT WINDOW = 'CLS'
  'NCPWORK has just been released.'
/*
END

```


107

PROCESS PAGE

■ Function	828
■ Syntax 1 - PROCESS PAGE	828
■ Syntax 2 - PROCESS PAGE USING	831
■ Syntax 3 - PROCESS PAGE UPDATE	834
■ Syntax 4 - PROCESS PAGE MODAL	837
■ Examples	839

Function

The `PROCESS PAGE` statement constitutes a general interface description to an external rendering engine, such as Natural for Ajax, thus linking the Natural internal data representation with an external data representation. Via this link, data and events, but no rendering information, are sent to and returned from an external, browser-based application.

For further information, refer to the *Natural for Ajax* documentation. The latest Natural for Ajax documentation is always available at <https://empower.softwareag.com/>.

Syntax 1 - PROCESS PAGE

```
PROCESS PAGE [(parameter)] operand1
[WITH PARAMETERS
  {[NAME] operand3 [VALUE] operand4 [(parameters)]} ...
END-PARAMETERS]
[GIVING operand11]
```

For explanations of the symbols used in the syntax diagram, see *Syntax Symbols*.

Belongs to Function Group: *Screen Generation for Interactive Processing*

Syntax Description - Syntax 1

Syntax 1 of the `PROCESS PAGE` statement is normally only used inside a Natural adapter. An adapter is a Natural object that forms the interface between Natural application code and web page. It is automatically created/updated by Natural for Ajax when the layout is saved.

 **Note:**

Operand Definition Table:

Operand	Possible Structure					Possible Formats															Referencing Permitted	Dynamic Definition
operand1	C	S				A	U														yes	no
operand2		S	A																C		no	no
operand3	C	S				A	U														yes	no
operand4	C	S	A			A	U	N	P	I	F	B	D	T	L						yes	yes
operand5		S	A																C		no	no

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand11</i>	S	I4	yes	yes

Syntax Element Description:

Syntax Element	Description		
<i>parameter</i>	Attribute Control Variable(s): The parameter CV, enclosed within parentheses, may be specified to reference one or more attribute control variables as specified in <i>operand2</i>: (CV=<i>operand2</i>) See also <i>Logical Condition Criteria, MODIFIED Option - Check whether Field Content has been Modified</i> in the <i>Programming Guide</i>.		
<i>operand1</i>	External Page Layout Name: <i>operand1</i> contains the name of the external page layout.		
<i>operand2</i>	Name of Attribute Control Variable(s): <i>operand2</i> contains the name of the attribute control variable, must be of format C and must be either a scalar or a single array occurrence.		
<i>operand3</i>	Name(s) of external Data Field(s): <i>operand3</i> contains the name(s) of the external data field(s) <i>operand4</i> will be transferred to/from.		
<i>operand4</i>	Name(s) of Natural Data Field(s): <i>operand4</i> contains the name(s) of the Natural data field(s) which will be transferred.		
<i>parameters</i>	Parameters: One or more parameters, enclosed within parentheses, may be specified immediately after <i>operand4</i>: <table> <tr> <td>EM or EMU</td><td> Edit mask used during data transfer. For further information, see the session parameter EM in the <i>Parameter Reference</i>. For details on Unicode edit masks, see the session parameter EMU in the <i>Parameter Reference</i>. </td></tr> </table>	EM or EMU	Edit mask used during data transfer. For further information, see the session parameter EM in the <i>Parameter Reference</i>. For details on Unicode edit masks, see the session parameter EMU in the <i>Parameter Reference</i>.
EM or EMU	Edit mask used during data transfer. For further information, see the session parameter EM in the <i>Parameter Reference</i>. For details on Unicode edit masks, see the session parameter EMU in the <i>Parameter Reference</i>.		

Syntax Element	Description
	CV The parameter CV, enclosed within parentheses, may be specified immediately after <i>operand4</i> to reference one or more attribute control variables as specified in <i>operand5</i>: (CV=<i>operand5</i>) See also <i>Logical Condition Criteria, MODIFIED Option - Check whether Field Content has been Modified</i> in the <i>Programming Guide</i>.
<i>operand5</i>	Name of Attribute Control Variable: <i>operand5</i> contains the name of the attribute control variable. The variable must be of format C. If <i>operand4</i> is a scalar or a single array occurrence, <i>operand5</i> must be ■ a scalar ■ or a single array occurrence. If <i>operand4</i> is the full range of an array of dimension 1, <i>operand5</i> must be ■ a scalar ■ or a single array occurrence ■ or the full range of an array of dimension 1 with the same size. If <i>operand4</i> is the full range of an array of dimension 2, <i>operand5</i> must be ■ a scalar ■ or a single array occurrence ■ or the full range of an array of dimension 2 with the same size in both dimensions ■ or the full range of an array of dimension 1 with the same size that <i>operand4</i> has in dimension 1. If <i>operand4</i> is the full range of an array of dimension 3, <i>operand5</i> must be ■ a scalar ■ or a single array occurrence ■ or the full range of an array of dimension 3 with the same size in all three dimensions ■ or the full range of an array of dimension 2 with the same size that <i>operand4</i> has in dimension 1 and 2 ■ or the full range of an array of dimension 1 with the same size that <i>operand4</i> has in dimension 1.
GIVING <i>operand11</i>	GIVING Clause: <i>operand11</i> contains the Natural error if the request could not be performed.

Example of an adapter which has been created by Natural for Ajax:

```
* PAGE1: PROTOTYPE      --- CREATED BY Natural for Ajax ---
* PROCESS PAGE USING 'XXXXXXX' WITH
* INFOPAGENAME RESULT YOURNAME
DEFINE DATA PARAMETER
1 INFOPAGENAME (U) DYNAMIC
1 RESULT (U) DYNAMIC
1 YOURNAME (U) DYNAMIC
END-DEFINE
*
PROCESS PAGE U'/njxdemos/helloworld' WITH
PARAMETERS
  NAME U'infopagename'
  VALUE INFOPAGENAME
  NAME U'result'
  VALUE RESULT
  NAME U'yourname'
  VALUE YOURNAME
END-PARAMETERS
*
*  TODO: Copy to your calling program and implement.
/*/*( DEFINE EVENT HANDLER
* DECIDE ON FIRST *PAGE-EVENT
*  VALUE U'nat:page.end'
*    /* Page closed.
*    IGNORE
*  VALUE U'onHelloWorld'
*    /* TODO: Implement event code.
*    PROCESS PAGE UPDATE FULL
*  NONE VALUE
*    /* Unhandled events.
*    PROCESS PAGE UPDATE
* END-DECIDE
/*/*) END-HANDLER
*
END
```

Syntax 2 - PROCESS PAGE USING

```
PROCESS PAGE USING operand6
[      WITH {operand7} ... ]
  NO PARAMETER
GIVING operand11
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Belongs to Function Group: *Screen Generation for Interactive Processing*

Syntax Description - Syntax 2

This syntax is used to perform rich GUI input/output processing using an object of type adapter that has been generated from a page layout created with Natural for Ajax or a similar tool.

Operand Definition Table:

Operand	Possible Structure					Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand6</i>	C	S				A											yes	no	
<i>operand7</i>		S	A	G		A	U	N	P	I	F	B	D	T	L		yes	yes	
<i>operand11</i>		S								I4							yes	yes	

Syntax Element Description:

Syntax Element	Description
USING <i>operand6</i>	Adapter Name: Invokes an adapter definition which has been previously stored in a Natural system file. See also <i>Processing a Rich GUI Page - Adapter</i> in the <i>Programming Guide</i>. The adapter name (<i>operand6</i>) may be a 1 to 8 character alphanumeric constant or user-defined variable. If a variable is used, it must have been defined previously. The adapter name may contain an ampersand (&); at execution time, this character will be replaced by the current value of the Natural system variable *LANGUAGE. This feature is provided for historical reasons. If you need multi-lingual adapters, use the capability of the external rendering system (for example, Natural for Ajax). Note: New applications do not need the ampersand feature to be multilingual. Pages designed, for example, using Natural for Ajax, can hold multilingual information as part of the layout design. See <i>Multi Language Management</i> in the <i>Natural for Ajax</i> documentation.
<i>operand7</i>	Field Specification: A list of database fields and/or user-defined variables, all of which must have been defined previously. The fields must agree in number, sequence, format, length and (for arrays) number of occurrences with the fields in the referenced adapter; otherwise, an error occurs. When the content of a database field is modified as a result of PROCESS PAGE processing, only the value as contained in the data area is modified. In order to change the content of the database, appropriate database UPDATE/STORE statements must be used. See <i>PROCESS PAGE USING Fields Defined in the Program</i>.
NO PARAMETER	NO PARAMETER Option:

Syntax Element	Description
	See PROCESS PAGE USING without Parameter List .
GIVING <i>operand11</i>	GIVING Clause: <i>operand11</i> contains the Natural error if the request could not be performed. Note: The GIVING clause interrupts the common Natural error handling, if an error occurs while the adapter object is being activated or executed. Instead of back-tracking the Natural modules in order to find an ON ERROR clause, the Natural error code is passed to this variable and execution is continued with the next statement.

PROCESS PAGE USING without Parameter List

The following requirements must be met when `PROCESS PAGE USING` is used without parameter list:

- The adapter name (*operand6*) must be specified as an alphanumeric constant (up to 8 characters).
- The adapter used in this manner must have been created prior to the compilation of the program which references the adapter.
- The names of the fields to be processed are taken dynamically from the adapter source definition at compilation time. The field names used in both program and adapter must be identical.
- All fields to be referenced in the `PROCESS PAGE` statement must be accessible at that point.
- In structured mode, fields must have been defined previously (database fields must be properly referenced to processing loops or views).
- When the page layout is changed, the programs using the adapter need not be recataloged. However, when array structures or names, formats/lengths of fields are changed, or fields are added/deleted in the adapter, the programs using the adapter must be recataloged.
- The adapter source must be available at program compilation; otherwise, the `PROCESS PAGE USING` statement cannot be compiled.



Note: If you wish to compile the program even if the adapter is not yet available, specify `NO PARAMETER`. The `PROCESS PAGE USING` statement can then be compiled even if the adapter is not yet available.

PROCESS PAGE USING Fields Defined in the Program


By specifying the names of the fields to be processed within the program (*operand7*), it is possible to have the names of the fields in the program differ from the names of the fields in the adapter.

The sequence of fields in the program must match the sequence in the adapter. If you use Natural maps as adapter objects, note that the map editor sorts the fields as specified in the map in alphabetical order by field name. For more information, see the map editor description in your *Editors* documentation.

When the layout of the adapter is changed, the program using the adapter does not need to be recataloged. However, when field names, field formats/lengths, or array structures in the adapter are changed or fields are added or deleted in the adapter, the program must be recataloged.

A check is made at execution time to ensure that the format and length of the fields as specified in the program match the fields as specified in the adapter. If both layouts do not agree, an error message is produced.

Syntax 3 - PROCESS PAGE UPDATE



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Belongs to Function Group: [Screen Generation for Interactive Processing](#)

Syntax Description - Syntax 3

The PROCESS PAGE UPDATE statement is used to return to and re-execute a PROCESS PAGE statement. It is generally used to return from event processing, because the data input processing of the preceding PROCESS PAGE statement was incomplete.

 **Note:** No INPUT, WRITE, PRINT or DISPLAY statements may be executed between a PROCESS PAGE statement and its corresponding PROCESS PAGE UPDATE statement.

The PROCESS PAGE UPDATE statement, when executed, repositions the program status regarding subroutine, special condition and loop processing as it existed when the PROCESS PAGE statement was executed (as long as the status of the PROCESS PAGE statement is still active). If the loop was initiated after the execution of the PROCESS PAGE statement and the PROCESS PAGE UPDATE statement is within this loop, the loop will be discontinued and then restarted after the PROCESS PAGE statement has been reprocessed as a consequence of the PROCESS PAGE UPDATE statement.

If a hierarchy of subroutines was invoked after the execution of the PROCESS PAGE statement, and the PROCESS PAGE UPDATE is performed within a subroutine, Natural will trace back all subroutines automatically and reposition the program status to that of the PROCESS PAGE statement.

It is not possible, however, to have a PROCESS PAGE statement positioned within a loop, a subroutine or a special condition block, and then execute the PROCESS PAGE UPDATE statement when the status under which the PROCESS PAGE statement was executed has already been terminated. An error message will be produced and program execution terminated when this error condition is detected.

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand11</i>	S	I4	yes	yes

Syntax Element Description:

Syntax Element	Description
FULL	FULL Option: If you specify the FULL option in a PROCESS PAGE UPDATE statement, the corresponding PROCESS PAGE statement will be re-executed fully: ■ With an ordinary PROCESS PAGE UPDATE statement (without FULL option), the contents of variables that were changed between the PROCESS PAGE and PROCESS PAGE UPDATE statement will not be displayed; that is, all variables on the screen will show the contents they had when the PROCESS PAGE statement was originally executed. ■ With a PROCESS PAGE UPDATE FULL statement, all changes that have been made after the initial execution of the PROCESS PAGE statement will be applied to the PROCESS PAGE statement when it is re-executed; that is, all variables on the screen contain the values they had when the PROCESS PAGE UPDATE statement was executed. A characteristic of the PROCESS PAGE UPDATE FULL statement is that the status of attribute control variables is reset to NOT MODIFIED. This is not done with the ordinary PROCESS PAGE UPDATE statement. To check if an attribute control variable has been assigned the status MODIFIED, use the MODIFIED option.
DATA	DATA Option: The DATA option behaves like the FULL option, with the exception that the MODIFIED status of the control variables is <i>not</i> reset.
<i>event-option</i>	EVENT Option: See EVENT Option below.
GIVING (<i>operand11</i>)	GIVING Clause: <i>operand11</i> contains the Natural error if the request could not be performed.

Example User Program Fragment:

```

PROCESS PAGE USING "HELLOW-A"
*
/*( DEFINE EVENT HANDLER
DECIDE ON FIRST *PAGE-EVENT
  VALUE U'nat:page.end'
  /* Page closed.
  IGNORE
  VALUE U'onHelloWorld'
  COMPRESS "HELLO WORLD" YOURNAME INTO RESULT
  PROCESS PAGE UPDATE FULL

```

```

NONE VALUE
/* Unhandled events.
PROCESS PAGE UPDATE
END-DECIDE
/*) END-HANDLER

```

EVENT Option

```

AND SEND EVENT operand8
[WITH PARAMETERS
  {[NAME] operand9 [VALUE] operand10 [ { (EMU=value) }
                                           (EM=value) } ]...
END-PARAMETERS]

```

With this option, you can advise the external I/O system to run specific functions. These functions are part of the external I/O system or implement special functions regarding the output processing as setting of focus, displaying message boxes, etc.

Operand Definition Table:

Operand	Possible Structure					Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand8</i>	C	S				A	U											yes	no
<i>operand9</i>	C	S				A	U											yes	no
<i>operand10</i>	C	S	A			A	U	N	P	I	F	B	D	T	L			yes	yes

Syntax Element Description:

Syntax Element	Description
AND SEND EVENT <i>operand8</i>	Event Requested from the External I/O System: Depending on the implementation of the external I/O system, events are available, refer to <i>Sending Events to the User Interface</i> in the <i>Natural for Ajax</i> documentation.
WITH PARAMETERS	WITH PARAMETERS Clause: With this clause, you can specify the following:
NAME <i>operand9</i>	External Data Field Name: <i>operand9</i> contains the external name of the data fields <i>operand10</i> will be transferred to/from.
VALUE <i>operand10</i>	Natural Data Fields: <i>operand10</i> contains the Natural data fields which will be transferred.

Syntax Element	Description
EMU= EM=	Edit Mask: Edit mask used during data transfer. For details on edit masks, see the session parameter EM in the <i>Parameter Reference</i>. For details on Unicode edit masks, see the session parameter EMU in the <i>Parameter Reference</i>.
END - PARAMETERS	End of WITH PARAMETERS Clause: The Natural reserved word END - PARAMETERS must be used to end the WITH PARAMETERS clause.

Syntax 4 - PROCESS PAGE MODAL

```
PROCESS PAGE MODAL
  statement ...
END-PROCESS
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [PROCESS PAGE](#)

Belongs to Function Group:

■ Screen Generation for Interactive Processing

Syntax Description - Syntax 4

The PROCESS PAGE MODAL statement is used to initiate a processing block and to control the lifetime of a modal rich GUI window.

Entering the PROCESS PAGE MODAL statement block causes the following actions to be performed:

- Data from Report 0, which is not displayed yet, will be displayed first;
- the system variable *PAGE-LEVEL is incremented;
- the opening of a modal page is prepared. The physical opening of the modal page will be performed with the next PROCESS PAGE USING *operand6* WITH statement, where *operand6* is the name of the adapter to be used.

Leaving the PROCESS PAGE MODAL statement block causes the following actions to be performed:

- If a modal page has been opened for this level, the closing of the modal page is prepared. The physical closing of the modal page will be performed with the next `PROCESS PAGE UPDATE [FULL]` statement;
- the system variable `*PAGE-LEVEL` is decremented, and the system variable `*PAGE-EVENT` is set back to the value it had before the statement block was entered;
- a `nat:page.default` event will be raised in the program that opened the modal page.



Note: No `PRINT`, `WRITE`, `INPUT` or `DISPLAY` statements referring to Report 0 may be executed between a `PROCESS PAGE MODAL` statement and its corresponding `END-PROCESS` statement.

The `PROCESS PAGE MODAL` statement is not valid in batch mode.

Syntax Element Description:

Syntax Element	Description
<i>statement</i>	Statement(s) to be Executed: In place of <i>statement</i> , you must supply one or several suitable statements, depending on the situation. If you do not want to supply a specific statement, you may insert the <code>IGNORE</code> statement.
END-PROCESS	End of PROCESS PAGE MODAL Statement: The Natural reserved word <code>END-PROCESS</code> must be used to end the <code>PROCESS PAGE MODAL</code> statement.

Example:

```
* Name: First Demo/Open modal!
*
PROCESS PAGE USING "EMPTY-A"
*
/*( DEFINE EVENT HANDLER
DECIDE ON FIRST *PAGE-EVENT
  VALUE U'nat:page.end', U'onClose'
    /* Page closed.
    IGNORE
  VALUE U'onNextLevel'
    PROCESS PAGE MODAL
      FETCH RETURN "EMPTY-P"
    END-PROCESS
  PROCESS PAGE UPDATE
  NONE VALUE
  PROCESS PAGE UPDATE
END-DECIDE
/*) END-HANDLER
END
```

Examples

Further examples of using the `PROCESS PAGE` statement are contained in library `SYSEXNJX`.

108

PROCESS SQL (SQL)

■ Function	842
■ Syntax Description	842
■ Examples	843

PROCESS SQL *dgm-name* <<*statement-string*>>

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Belongs to Function Group: [Database Access and Update](#)

See also *PROCESS SQL* in the *Natural for DB2* part of the *Database Management System Interfaces* documentation.

Function

The `PROCESS SQL` statement is used to issue SQL statements to the underlying database.

Syntax Description

Syntax Element	Description
<i>dgm-name</i>	DDM Name: The name of a data definition module (DDM) must be specified to provide the “address” of the database which executes the stored procedure. For more information, see dgm-name .
<i>statement-string</i>	Statement String: The statements which can be specified in the <i>statement-string</i> are the same statements which can be issued with the SQL statement EXECUTE; see also Flexible SQL . Caution: To avoid transaction synchronization problems between the Natural environment and the underlying database, the COMMIT and ROLLBACK statements must not be used within <code>PROCESS SQL</code> . The statement string can cover several statement lines without any continuation character to be specified. Comments at the end of a line as well as entire comment lines are possible. The statement string can also include parameters; see Parameters in Statement String below.

Parameters in Statement String

$$\left[\begin{array}{l} :U \\ :G \end{array} \right] :host-variable [INDICATOR:host-variable] [LINIDICATOR:host-variable]$$

Unlike with the *Parameters* described in the section *Basic Syntactical Items*, the *host-variables* used in this context must be prefixed by a colon (:). In addition, they can be preceded by a further qualifier (:U or :G).

See further details on *host-variable*.

Syntax Element Description:

Syntax Element	Description
:U: <i>host-variable</i>	"USING" Variable: The prefix :U qualifies the host variable as a so-called "USING" variable. Such a variable indicates that its value is to be <i>passed to</i> the database. :U is the default specification.
:G: <i>host-variable</i>	"GIVING" Variable: The prefix :G qualifies the host variable as a so-called "GIVING" variable. Such a variable indicates that it is to <i>receive</i> a value <i>from</i> the database.

Examples

Example 1 for DB2 (under z/OS):

```
PROCESS SQL DB2_DDM << CONNECT TO :LOCATION >>
```

Example 2 for DB2 (under z/OS):

```
PROCESS SQL DB2_DDM << SET :G:LOCATION = CURRENT SERVER >>
```


109

PROPERTY

■ Function	846
■ Syntax Description	846
■ Example	847

```
PROPERTY property-name
  OF [INTERFACE] interface-name
  IS operand
END-PROPERTY
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [CREATE OBJECT](#) | [DEFINE CLASS](#) | [INTERFACE](#) | [METHOD](#) | [SEND METHOD](#)

Belongs to Function Group: [Component Based Programming](#)

Function

The `PROPERTY` statement assigns an object data variable operand as the implementation to a property, outside an interface definition.

It is used if the interface definition in question is included from a copycode and is to be implemented in a class-specific way.

It may only be used within the `DEFINE CLASS` statement and after the interface definitions.

The interface and property names specified must be defined in the `INTERFACE` clause of the `DEFINE CLASS` statement.

Syntax Description

Syntax Element	Description
<i>property-name</i>	Property Name: This is the name assigned to the property .
OF <i>interface-name</i>	Interface Name: This is the name assigned to the interface .
IS <i>operand</i>	IS Clause: The operand in the IS clause assigns an object data variable as the place to store the property value.
END-PROPERTY	End of PROPERTY Statement: The Natural reserved word <code>END-PROPERTY</code> must be used to end the <code>PROPERTY</code> statement.

Example

The [example](#) contained in the documentation of the [METHOD](#) statement shows how the same interface is implemented differently in two classes, and how the `PROPERTY` statement and the `METHOD` statement are used to achieve this.

XIII

■ 110 READ	851
■ 111 READ RESULT SET (SQL)	873
■ 112 READ WORK FILE	879
■ 113 READLOB	891
■ 114 REDEFINE	899
■ 115 REDUCE	903
■ 116 REINPUT	909
■ 117 REJECT	921
■ 118 RELEASE	923
■ 119 REPEAT	927
■ 120 REQUEST DOCUMENT	933
■ 121 RESET	951
■ 122 RESIZE	955
■ 123 ROLLBACK (SQL)	961
■ 124 RETRY	965
■ 125 RUN	969

110

READ

■ Function	852
■ Syntax Description	853
■ System Variables Available with READ	864
■ Examples	865

```
{ READ } { [ ALL ] } [MULTI-FETCH-clause] [RECORDS] [IN] [FILE] view-name  
BROWSE { (operand1) }  
[PASSWORD=operand2]  
[CIPHER=operand3]  
[WITH REPOSITION]  
[sequence/range-specification]  
[STARTING WITH ISN=operand4]  
[[IN] SHARED HOLD [MODE=option]]  
[SKIP [RECORDS] IN HOLD]  
[WHERE logical-condition]  
statement ...  
END-READ      (structured mode only)  
LOOP          (reporting mode only)
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [GET TRANSACTION DATA](#) | [DELETE](#) | [END TRANSACTION](#) | [FIND](#) | [HISTOGRAM](#) | [GET](#) | [GET SAME](#) | [LIMIT](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READLOB](#) | [RETRY](#) | [STORE](#) | [UPDATE](#) | [UPDATELOB](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The `READ` statement is used to read records from a database. The records can be retrieved in physical sequence, in Adabas ISN sequence, or in the value sequence of a descriptor (key) field. The `READ` statement causes a processing loop to be initiated.

See also the following sections in the *Programming Guide*:

- *READ Statement*
- *Loop Processing*
- *Referencing of Database Fields Using (r) Notation*

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S					N	P	I	B *						yes	no
<i>operand2</i>	C	S				A										yes	no
<i>operand3</i>	C	S					N									yes	no
<i>operand4</i>	C	S					N	P	I	B *						yes	no

* Format B of *operand1* and *operand4* may be used with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Number of Records to be Read: The number of records to be read may be limited by specifying <i>operand1</i> (enclosed in parentheses, immediately after the keyword READ) - either as a numeric constant (in the range from 0 to 4294967295) or as the name of a numeric variable. Example: <pre>READ (5) IN EMPLOYEES ... MOVE 10 TO CNT(N2) READ (CNT) EMPLOYEES ...</pre> For this statement, the specified limit has priority over a limit set with a LIMIT statement. If a smaller limit is set with the profile or session parameter LT, the LT limit applies. Note: 1. If you wish to read a 4-digit number of records, specify it with a leading zero: (0nnnn); because Natural interprets every 4-digit number enclosed in parentheses as a line-number reference to a statement. 2. <i>operand1</i> is evaluated when the READ loop is entered. If the value of <i>operand1</i> is modified within the READ loop, this does not affect the number of records read.

Syntax Element	Description
ALL	ALL Option: To emphasize that <i>all</i> records are to be read, you can optionally specify the keyword ALL. The ALL option is used by default if <i>operand1</i> and ALL are omitted.
MULTI-FETCH-clause	MULTI-FETCH Clause: See MULTI-FETCH Clause.
view-name	View Name: As <i>view-name</i>, you specify the name of a view, which must have been defined either within a DEFINE DATA statement or outside the program in a global or local data area. In reporting mode, <i>view-name</i> is the name of a DDM if no DEFINE DATA LOCAL statement is used.
PASSWORD= <i>operand2</i> CIPHER= <i>operand3</i>	PASSWORD and CIPHER Clauses: These clauses are applicable only to Adabas or VSAM databases. They cannot be used with Entire System Server. The PASSWORD clause is used to provide a password when retrieving data from a file which is password-protected. The CIPHER clause is used to provide a cipher key when retrieving data from a file which is enciphered. See the statements FIND and PASSW for further information.
WITH REPOSITION	WITH REPOSITION Option: This option is used to make the READ statement sensitive for repositioning events. See WITH REPOSITION Option.
sequence/range-specification	Sequence/Range Specification: This option specifies the sequence and/or the range of retrieval. See Sequence/Range Specification.
STARTING WITH ISN= <i>operand4</i>	STARTING WITH ISN Clause: This clause applies only to Adabas and VSAM databases. Access to Adabas This clause can be used in conjunction with a READ statement in physical or in logical (ascending/descending) sequence. The value supplied (<i>operand4</i>, range from 0 to 4294967295) represents an Adabas ISN (internal sequence number) and is used to specify a definite record where to start the READ loop.

Syntax Element	Description
	■ Logical Sequence Even if documented with an equal character (=), the READ statement does not return only those records with exactly the start value in the corresponding descriptor field, but starts a logical browse in ascending or descending order, beginning with the start value supplied. If some records have the same contents in the descriptor field, they will be returned in an ISN-sorted sequence. The STARTING WITH ISN clause is some kind of a “second level” selection criterion that applies only if the start value matches the descriptor value for the first record. All records with a descriptor value that is the same as the start value and an ISN that is “less equal”(“greater equal” for a descending READ) than the start ISN are ignored by Adabas. The first record returned in the READ loop is either ■ the first record with descriptor = start value and an ISN “greater” (“less” for a descending READ) than the start ISN, ■ or if such a record does not exist, the first record with a descriptor “greater” (“less” for a descending READ) than the start value. ■ Physical Sequence The records are returned in the order in which they are physically stored. If a STARTING WITH ISN clause is specified, Adabas ignores all records until the record with the ISN that is the same as the start ISN is reached. The first record returned is the next record following the ISN=start ISN record. Access to VSAM This clause can only be used in physical sequence. The value supplied (<i>operand4</i>) represents a VSAM RBA (relative byte address of ESDS) or RRN (relative record number of RRDS), which is to be used as a start value for the read operation. Examples This clause may be used for repositioning within a READ loop whose processing has been interrupted, to easily determine the next record with which processing is to continue. This is particularly useful if the next record cannot be identified uniquely by any of its descriptor values. It can also be useful in a distributed client/server application where the reading of the records is performed by a server program while further processing of the records is performed by a client program, and the records are not processed all in one go, but in batches. For an example, see the program REASISND in Example 7 - STARTING WITH ISN Clause.

Syntax Element	Description		
[[IN] SHARED HOLD [MODE= <i>option</i>]]	SHARED HOLD Clause: Note: This clause can be used only for access to Adabas. This clause can be used to place records being read in a “shared hold” state. A record can be put in shared hold by many users at the same time. As long as a record is in a shared hold state, it is protected from being updated, because it cannot be set into an exclusive hold by parallel users. This ensures data consistency for the record data, as no one can update the record while it is being processed. Especially if the same record is fetched with multiple statements to read different MU/PE occurrences (GET SAME statement) or to browse over a LOB field in a piecemeal technique (READLOB statement), the shared hold state can guarantee data stability over this transaction without blocking the record for other users. Although such a hold state is an efficient way to protect read sequences, it is a basic and important matter when to release the record again from this “soft lock”. Since this question depends on individual application aspects, different options can be selected with the <code>MODE</code> subclause.		
	MODE Option	Hold Period	Explanation
	C	Only at the moment of reading the record.	Ensures only that the record version being read has been committed by the last user who updated the record. This option does not really set a lock in hold state, but checks only that the record is not in exclusive hold by another user at time of read.
	Q	Until the next record in a sequence is read.	Releases the record from shared hold when ■ the next record is read in the loop sequence or ■ the loop is terminated or ■ an END TRANSACTION or BACKOUT

Syntax Element	Description		
			TRANSACTION is executed.
	S	Until the logical transaction is terminated.	Releases the record from shared hold when a logical transaction is terminated with an END TRANSACTION or BACKOUT TRANSACTION statement.
	MODE=Q and MODE=S ensure that the record being read cannot be updated concurrently by other users until it has been released from hold again. If the MODE subclause is not specified, MODE=C is the default. See also Example 8 - SHARED HOLD Clause.		
SKIP RECORDS IN HOLD	SKIP RECORDS Clause: Note: This clause can be used only for access to Adabas. Whenever a record is going to be read with hold, a Natural error NAT3145 (Adabas response code 145) might happen if the record is in hold by another user at this time. This occurs if a shared hold is requested and the record is in exclusive hold or if an exclusive hold is requested and the record is in either exclusive or shared hold. Although error NAT3145 is surely the right reaction to assure a “clean data processing”, sometimes it might be useful if a record in hold could be skipped. If it is alright that such a record will not be processed and the loop processing should continue, the SKIP RECORDS clause should be used. If the SKIP RECORDS clause is applied, Natural first tries to read the record with hold. If the record is already in hold and the Natural error NAT3145 would occur, ■ no error processing is initiated; ■ the record (currently in hold by another user) is instantly re-fetched without hold, but not processed in terms of the program logic; ■ the record which comes next after the skipped record is read with hold and the processing continues. See also Example 9 - SKIP RECORDS Clause.		
WHERE <i>logical-condition</i>	WHERE Clause:		

Syntax Element	Description
	The WHERE clause may be used to specify an additional selection criterion (<i>logical-condition</i>) which is evaluated <i>after</i> a value has been read and <i>before</i> any processing is performed on the value (including the AT BREAK evaluation). The syntax for a <i>logical-condition</i> is described in the section <i>Logical Condition Criteria</i> in the <i>Programming Guide</i>. If a LIMIT statement or a processing limit is specified in a READ statement containing a WHERE clause, records which are rejected as a result of the WHERE clause are not counted against the limit.
END-READ	End of READ Statement: In structured mode, the Natural reserved keyword END-READ must be used to end the READ statement. In reporting mode, the Natural statement LOOP is used to end the READ statement.
LOOP	

MULTI-FETCH Clause



Note: This clause can only be used for Adabas or DB2 databases.

MULTI-FETCH	$\left\{ \begin{array}{l} \text{ON} \\ \text{OFF} \\ [\text{OF}] \text{ multi-fetch-factor} \end{array} \right\}$

For more information, see the section *MULTI-FETCH Clause (Adabas)* in the *Programming Guide* or *Multiple Row Processing (SQL)* in the *Natural for DB2* part of the *Database Management System Interfaces* documentation.

WITH REPOSITION Option



Note: This option can only be applied if the underlying database is Adabas, VSAM or DL/I.

With a **WITH REPOSITION** option, you can make a READ statement sensitive for repositioning events. This allows you to reposition to another start value within an active READ loop. Processing of the READ statement then continues with the new start value.

A repositioning event is triggered by one of two ways when you use a READ statement with the **WITH REPOSITION** option:

1. When an **ESCAPE TOP REPOSITION** statement is executed. At execution of an **ESCAPE TOP REPOSITION** statement, Natural makes an instant branch to the loop begin and performs a restart;

that is, the database repositions to a new record in the file according to the current content of the search value variable. At the same time, the loop-counter *COUNTER is reset to zero.

2. When a READ loop tries to fetch the next record from the database and the value of the system variable *COUNTER is 0.



Note: If *COUNTER is set to 0 within the active READ loop, processing of the current record is continued; no instant branch to the loop begin is performed.

Functional Considerations

- If the READ statement has a loop-limit (e.g. READ (10) EMPLOYEES WITH REPOSITION ..) and a restart event was triggered, the loop gets another 10 new records, no matter how many records were already processed until the repositioning takes place.
- If an **ESCAPE TOP REPOSITION** statement is executed, but the innermost loop is not capable of repositioning (since the WITH REPOSITION keyword is not set in the READ statement or the posted loop statement is anything else but a READ), a corresponding runtime error is issued.
- Since the **ESCAPE TOP** statement does not allow a reference, you can only initiate a reposition event if the innermost processing loop is a READ ..WITH REPOSITION statement.
- A reposition event does not trigger the execution of the **AT START OF DATA** section, nor does it trigger the re-evaluation of the loop-limit operand (if it is a variable).
- If the search value was not altered, the loop repositions to the same record like at initial loop start.


Sequence/Range Specification

Three syntax options are available to specify the sequence and/or the range of retrieval.


Syntax Option 1:

[IN] [PHYSICAL]	ASCENDING DESCENDING VARIABLE <i>operand5</i> DYNAMIC <i>operand5</i>	[SEQUENCE]

Syntax Option 2:



Syntax Option 3:



Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand5</i>		S				A											yes	no
<i>operand6</i>	C	S				A	N	P	I	F	B *	D	T	L			yes	no
<i>operand7</i>	C	S				A	N	P	I	F	B *	D	T	L			yes	no

* Format B of *operand6* and *operand7* may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
READ IN PHYSICAL SEQUENCE	Read in Physical Sequence: This option is used to read records in the order in which they are physically stored in a database. Note: For VSAM databases: READ PHYSICAL can only be applied to ESDS and RRDS. PHYSICAL is the default sequence.
READ BY ISN	Read by ISN: This option is used to read records in the order of Adabas ISNs (internal sequence numbers) or VSAM RBAs (relative byte addresses of ESDS) or RRNs (relative record numbers of RRDS) respectively. Instead of using the keyword BY, you may specify the keyword WITH, which has the same effect. For READ BY ISN, <i>operand6</i> and <i>operand7</i> must be provided as a numeric constant or user-defined variable in the range from 0 to 4294967295. READ BY ISN can only be used for Adabas and VSAM databases; for VSAM databases, it is only valid for ESDS and RRDS. Note: For XML databases: READ BY ISN is used to read XML objects according to the order of Tamino object IDs.
READ IN LOGICAL SEQUENCE	Read in Logical Sequence: This option is used to read records in the order of the values of a descriptor (key) field. If you specify a descriptor, the records will be read in the value sequence of the descriptor. A descriptor, subdescriptor, superdescriptor or hyperdescriptor may be used for sequence control. A phonetic descriptor, a descriptor within a periodic group, or a superdescriptor which contains a periodic-group field cannot be used. If you do not specify a descriptor, the default descriptor as specified in the DDM (field Default Sequence) will be used. Note:

Syntax Element	Description
	1. For DL/I databases: The descriptor used must be either the sequence field of a root segment, or a secondary index field. If a secondary index field is specified, it must also be specified in the PROCSEQ parameter of a PCB. Natural uses this PCB and the corresponding hierarchical structure to process the database. As HDAM databases use a randomizing routine to locate root segments, no sensible results will be returned when using READ LOGICAL for HDAM databases; therefore, you should use READ PHYSICAL for HDAM databases. 2. For VSAM databases: LOGICAL is only valid for KSDS with primary and alternate keys defined and for ESDS with alternate keys defined. If the descriptor used for sequence control is defined with null-value suppression (Adabas only), any record which contains a null value for the descriptor will not be read. If the descriptor is a multiple-value field (Adabas only), the same record will be read multiple times depending on the number of values present. Note: READ IN LOGICAL SEQUENCE is also discussed in the <i>Programming Guide</i>; see <i>Statements for Database Access, READ Statement</i>.
ASCENDING DESCENDING VARIABLE DYNAMIC SEQUENCE	Ascending/Descending Order: This clause only applies to Adabas, XML databases, VSAM and SQL databases. In a READ PHYSICAL statement, it can only be applied to VSAM and DB2 databases. With this clause, you can determine whether the records are to be read in ascending sequence or in descending sequence. ■ The default sequence is ascending (which may, but need not, be explicitly specified by using the keyword ASCENDING). ■ If the records are to be read in descending sequence, you specify the keyword DESCENDING. ■ If, instead of determining it in advance, you want to have the option of determining at runtime whether the records are to be read in ascending or descending sequence, you either specify the keyword VARIABLE or DYNAMIC, followed by a variable (<i>operand5</i>). <i>operand5</i> has to be of format/length A1 and can contain the value A (for “ascending”) or D (for “descending”). ■ If keyword VARIABLE is used, the reading direction (value of <i>operand5</i>) is evaluated at start of the READ processing loop and remains the same until the loop is terminated, regardless of whether the <i>operand5</i> field is altered in the READ loop. ■ If keyword DYNAMIC is used, the reading direction (value of <i>operand5</i>) is evaluated before every record fetch in the READ processing loop and may be changed from record to record. This allows to change the scroll sequence from ascending to descending (and vice versa) at any place in the READ loop.
STARTING FROM ... ENDING AT/TO	STARTING FROM/ENDING AT Clauses: The STARTING FROM and ENDING AT clauses are used to limit reading to a set of records based on a user-specified range of values.

Syntax Element	Description
	The <code>STARTING FROM</code> clause (= or <code>EQ</code> or <code>EQUAL TO</code> or <code>[STARTING] FROM</code>) determines the starting value for the read operation. If a starting value is specified, reading will begin with the value specified. If the starting value does not exist in the file, the next higher (or lower for a <code>DESCENDING</code> read) value will be used. If no higher (or lower for <code>DESCENDING</code>) value exists, the loop will not be entered. In order to limit the records to an end value, you may specify an <code>ENDING AT</code> clause with the terms <code>THRU</code>, <code>ENDING AT</code> or <code>TO</code> that imply an inclusive range. Whenever the read descriptor field exceeds the end value specified, an automatic loop termination is performed. Although the basic functionality of the <code>TO</code>, <code>THRU</code> and <code>ENDING AT</code> keywords looks quite similar, internally they differ in how they work.
THRU/ENDING AT	THRU/ENDING AT Option: If <code>THRU</code> or <code>ENDING AT</code> is used, only the start value is supplied to the database, but the end-value check is performed by the Natural runtime system, after the record is returned by the database. If the read direction is <code>ASCENDING</code>, you have to supply the lower value as the start value and the higher value as the end value, since the start value represents the value (and record) returned first in the <code>READ</code> loop. However, if you invoke a backwards read (<code>DESCENDING</code>), the higher value has to appear in the start value and the lower value in the end value. Internally, to determine the end of the range to be read, Natural reads one record beyond the end value. If you have left the <code>READ</code> loop because the end value has been reached, be aware that this last record is in fact not the last record within the demanded range, but the first record beyond that range (except if the file does not contain a further record after the last result record). The <code>THRU</code> and <code>ENDING AT</code> clauses can be used for all databases which support the <code>READ</code> or <code>HISTOGRAM</code> statements.
TO	TO Option: If the keyword <code>TO</code> is used, both the start value and the end value are sent to the database, and Natural does not perform checks for value ranges. If the end value is exceeded, the database reacts the same as when “end-of-file” is reached, and the database loop is exited. Since the complete range checking is done by the database, the lower value (of the range) is always supplied in the start value and the higher value filled into the end value, regardless of whether you are browsing in <code>ASCENDING</code> or <code>DESCENDING</code> order.

Notes on Functional Differences between THRU/ENDING AT and TO

The following list describes the functional differences between the usage of the `THRU/ENDING AT` and `TO` options.

THRU/ENDING AT	TO
When the READ loop terminates because the end value has been reached, the view contains the first record "out-of-range".	When the READ loop terminates because the end value has been reached, the view contains the last record of the specified range.
If a end-value variable is modified during the READ loop, the new value will be used for end value check on next record being read.	The end-value variable will only be evaluated at READ loop start. All further modifications during the READ loop have no effect.
An incorrect range (for example, READ .. = 'B' THRU 'A ') does not cause a database error, but just returns no record.	An incorrect range results in a database error (for example, Adabas RC=61), because a value range must not be supplied in descending order.
If a READ .. DESCENDING is used with start and end values, the start value is used to position in the file, whereas the end value is used by Natural to check for "end-of-range". Therefore, the start value is higher than (or equal to) the end value.	Since both values are passed to the database, they have to appear in ascending order. In other words, the start value is lower than (or equal to) the end value, no matter if you are reading in ascending or descending order.
In order to check for range overflow, the descriptor value has to appear in the underlying database view; that is, it must be returned in the record buffer.	The descriptor is not required in the record fields returned.
The end-value check for an Adabas multi-value field (MU-field) or a sub-/super-/hyper-descriptor is not possible and leads to syntax error NAT0160 at program compilation.	You may specify an end value for MU-fields and sub-/super-/hyper-descriptors.
Can be used for all databases.	Can be used for all databases.



Note: The result of READ/HISTOGRAM THRU/ENDING AT might differ from the result of READ/HISTOGRAM TO if Natural and the accessed database reside on different platforms with different collating sequences.

System Variables Available with READ

The Natural system variables *ISN and *COUNTER are available with the READ statement.

The format/length of these system variables is P10. This format/length cannot be changed.

The usage of the system variables is illustrated below.

System Variable	Explanation
*ISN	The system variable *ISN contains the Adabas ISN of the record currently being processed. Note: 1. For VSAM databases, *ISN contains either the RRN (for RRDS) or the RBA (for ESDS) of the current record. 2. For Tamino, *ISN contains the XML object ID. 3. For DL/I and SQL databases and with Entire System Server, *ISN is not available.
*COUNTER	The system variable *COUNTER contains the number of times the processing loop has been entered.

Examples

- [Example 1 - READ Statement](#)
- [Example 2 - READ WITH REPOSITION](#)
- [Example 3 - Combining READ and FIND Statements](#)
- [Example 4 - DESCENDING Option](#)
- [Example 5 - VARIABLE Option](#)
- [Example 6 - DYNAMIC Option](#)
- [Example 7 - STARTING WITH ISN Clause](#)
- [Example 8 - SHARED HOLD Clause](#)
- [Example 9 - SKIP RECORDS Clause](#)

Example 1 - READ Statement

```

** Example 'REAEX1S': READ (structured mode)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
1 VEHC-VIEW VIEW OF VEHICLES
  2 PERSONNEL-ID
  2 MAKE
END-DEFINE
*
LIMIT 3
*
WRITE 'READ IN PHYSICAL SEQUENCE'
READ EMPLOY-VIEW IN PHYSICAL SEQUENCE
  DISPLAY NOTITLE PERSONNEL-ID NAME *ISN *COUNTER
END-READ
*

```

```
WRITE / 'READ IN ISN SEQUENCE'
READ EMPLOY-VIEW BY ISN STARTING FROM 1 ENDING AT 3
  DISPLAY      PERSONNEL-ID NAME *ISN *COUNTER
END-READ
*
WRITE / 'READ IN NAME SEQUENCE'
READ EMPLOY-VIEW BY NAME
  DISPLAY      PERSONNEL-ID NAME *ISN *COUNTER
END-READ
*
WRITE / 'READ IN NAME SEQUENCE STARTING FROM 'M''
READ EMPLOY-VIEW BY NAME STARTING FROM 'M'
  DISPLAY      PERSONNEL-ID NAME *ISN *COUNTER
END-READ
*
END
```

Output of Program REAEX1S:

PERSONNEL ID	NAME	ISN	CNT

READ IN PHYSICAL SEQUENCE			
50005800	ADAM	1	1
50005600	MORENO	2	2
50005500	BLOND	3	3
READ IN ISN SEQUENCE			
50005800	ADAM	1	1
50005600	MORENO	2	2
50005500	BLOND	3	3
READ IN NAME SEQUENCE			
60008339	ABELLAN	478	1
30000231	ACHIESON	878	2
50005800	ADAM	1	3
READ IN NAME SEQUENCE STARTING FROM 'M'			
30008125	MACDONALD	923	1
20028700	MACKARNESS	765	2
40000045	MADSEN	508	3

Equivalent reporting-mode example: [REAEX1R](#).

Example 2 - READ WITH REPOSITION

```

DEFINE DATA LOCAL
1 MYVIEW VIEW OF ...
  2 NAME
1 #STARTVAL (A20) INIT <'A'>
1 #ATTR      (C)
END-DEFINE
...
SET KEY PF3
...
READ MYVIEW WITH REPOSITION BY NAME = #STARTVAL
INPUT (IP=OFF AD=0) 'NAME:' NAME /
  'Enter new start value for repositioning:' #STARTVAL (AD=MT CV=#ATTR) /
  'Press PF3 to stop'
IF *PF-KEY = 'PF3'
  THEN STOP
END-IF
IF #ATTR MODIFIED
  THEN ESCAPE TOP REPOSITION
END-IF
END-READ
...

```

```

DEFINE DATA LOCAL
1 MYVIEW VIEW OF ...
  2 NAME
1 #STARTVAL (A20) INIT <'A'>
1 #ATTR      (C)
END-DEFINE
...
SET KEY PF3
...
READ MYVIEW WITH REPOSITION BY NAME = #STARTVAL
INPUT (IP=OFF AD=0) 'NAME:' NAME /
  'Enter new start value for repositioning:' #STARTVAL (AD=MT CV=#ATTR) /
  'Press PF3 to stop'
IF *PF-KEY = 'PF3'
  THEN STOP
END-IF
IF #ATTR MODIFIED
  THEN RESET *COUNTER
END-IF
END-READ
...

```

Example 3 - Combining READ and FIND Statements

The following program reads records from the EMPLOYEES file in logical sequential order based on the values of the descriptor NAME. A FIND statement is then issued to the VEHICLES file using the personnel number from the EMPLOYEES file as search criterion. The resulting report shows the name (read from the EMPLOYEES file) of each person read and the model of automobile (read from the VEHICLES file) owned by this person. Multiple lines with the same name are produced if the person owns more than one automobile.

```
** Example 'REAEX2': READ and FIND combination
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 FIRST-NAME
  2 NAME
  2 CITY
1 VEH-VIEW VIEW OF VEHICLES
  2 PERSONNEL-ID
  2 MAKE
END-DEFINE
*
LIMIT 10
*
RD. READ EMPLOY-VIEW BY NAME STARTING FROM 'JONES'
  SUSPEND IDENTICAL SUPPRESS
  FD. FIND VEH-VIEW WITH PERSONNEL-ID = PERSONNEL-ID (RD.)
    IF NO RECORDS FOUND
      ENTER
    END-NOREC
    DISPLAY NOTITLE (ES=OFF IS=ON ZP=ON AL=15)
      PERSONNEL-ID (RD.)
      FIRST-NAME (RD.)
      MAKE (FD.) (IS=OFF)

  END-FIND
END-READ
END
```

Output of Program REAEX2:

PERSONNEL ID	FIRST-NAME	MAKE
20007500	VIRGINIA	CHRYSLER
20008400	MARSHA	CHRYSLER
		CHRYSLER
20021100	ROBERT	GENERAL MOTORS
20000800	LILLY	FORD

		MG
20001100	EDWARD	GENERAL MOTORS
20002000	MARTHA	GENERAL MOTORS
20003400	LAUREL	GENERAL MOTORS
30034045	KEVIN	DATSUN
30034233	GREGORY	FORD
11400319	MANFRED	

Example 4 - DESCENDING Option

```

** Example 'READSCND': READ (with DESCENDING SEQUENCE)
*****
DEFINE DATA LOCAL
1 EMPL VIEW OF EMPLOYEES
  2 NAME
  2 FIRST-NAME
  2 BIRTH
END-DEFINE
*
READ (10) EMPL IN DESCENDING SEQUENCE BY NAME FROM 'ZZZ'
  DISPLAY *ISN NAME FIRST-NAME BIRTH (EM=YYYY-MM-DD)
END-READ
END

```

Example 5 - VARIABLE Option

```

** Example 'REAVSEQ': READ (with VARIABLE SEQUENCE)
*****
DEFINE DATA LOCAL
1 EMPL VIEW OF EMPLOYEES
  2 NAME
  2 FIRST-NAME
  2 BIRTH
*
1 #DIR          (A1)
1 #STARTVALUE (A20)
END-DEFINE
*
SET KEY PF7 PF8
*
INPUT 'Select READ direction'
  // 'Press' 08T 'PF7' (I)          21T 'to read backward'
  /         08T 'PF8' (I) 'or' 'ENTER' (I) 21T 'to read forward'
*
IF *PF-KEY = 'PF7'
  MOVE 'D' TO #DIR
  MOVE 'ZZZ' TO #STARTVALUE
ELSE
  MOVE 'A' TO #DIR
  MOVE 'A' TO #STARTVALUE

```

```
END-IF
*
READ (10) EMPL IN VARIABLE #DIR SEQUENCE
      BY NAME FROM #STARTVALUE
      DISPLAY *ISN NAME FIRST-NAME BIRTH (EM=YYYY-MM-DD)
END-READ
END
```

Example 6 - DYNAMIC Option

```
DEFINE DATA LOCAL
1 #DIRECTION (A1) INIT <'A'> /* 'A' = ASCENDING
1 #EMPVIEW VIEW OF EMPLOYEES
2 NAME
...
END-DEFINE
...
READ #EMPVIEW IN DYNAMIC #DIRECTION SEQUENCE BY NAME = 'SMITH'
  INPUT (AD=0) NAME
    / 'Press PF7 to scroll in DESCENDING sequence'
    / 'Press PF8 to scroll in ASCENDING sequence'
  ..
  IF *PF-KEY = 'PF7' THEN MOVE 'D' TO #DIRECTION END-IF
  IF *PF-KEY = 'PF8' THEN MOVE 'A' TO #DIRECTION END-IF
END-READ
...
```

Example 7 - STARTING WITH ISN Clause

```
** Example 'REASISND': READ (with STARTING WITH ISN)
*****
DEFINE DATA LOCAL
1 EMPL VIEW OF EMPLOYEES
  2 NAME
  2 FIRST-NAME
  2 BIRTH
*
1 #DIR      (A1)
1 #STARTVAL (A20)
1 #STARTISN (N8)
END-DEFINE
*
SET KEY PF3 PF7 PF8
*
MOVE 'ADKINSON' TO #STARTVAL
*
READ (9) EMPL BY NAME = #STARTVAL
  WRITE *ISN NAME FIRST-NAME BIRTH (EM=YYYY-MM-DD) *COUNTER
  IF *COUNTER = 5 THEN
    MOVE NAME TO #STARTVAL
```

```

    MOVE *ISN TO #STARTISN
  END-IF
END-READ
*
#DIR := 'A'
*
REPEAT
  READ EMPL IN VARIABLE #DIR BY NAME = #STARTVAL
    STARTING WITH ISN = #STARTISN
  MOVE NAME TO #STARTVAL
  MOVE *ISN TO #STARTISN
  INPUT NO ERASE (IP=OFF AD=0)
    15/01 *ISN NAME FIRST-NAME BIRTH (EM=YYYY-MM-DD)
    // 'Direction:' #DIR
    // 'Press PF3 to stop'
    / ' PF7 to go step back'
    / ' PF8 to go step forward'
    / ' ENTER to continue in that direction'
  /*
  IF *PF-KEY = 'PF7' AND #DIR = 'A'
    MOVE 'D' TO #DIR
    ESCAPE BOTTOM
  END-IF
  IF *PF-KEY = 'PF8' AND #DIR = 'D'
    MOVE 'A' TO #DIR
    ESCAPE BOTTOM
  END-IF
  IF *PF-KEY = 'PF3'
    STOP
  END-IF
END-READ
/*
IF *COUNTER(0290) = 0
  STOP
END-IF
END-REPEAT
END

```

Example 8 - SHARED HOLD Clause

```

READ EMPL-VIEW WITH NAME = ...
  IN SHARED HOLD MODE=Q /* Record in shared hold until next record is read.
  ...
  GET EMPL-VIEW *ISN /* The record remains unchanged!
  ...
END-READ

```

Example 9 - SKIP RECORDS Clause

```
READ EMPL-VIEW WITH NAME = ... /* Records found are put in hold while reading.  
    SKIP RECORDS IN HOLD      /* Records already held by other users are skipped  
    ...                       /* to prevent error NAT3145.  
    UPDATE  
    END TRANSACTION  
END-READ
```

111

READ RESULT SET (SQL)

■ Function	874
■ Restriction	875
■ Syntax Description	875
■ Example	877

Common Set Syntax:

READ [(limit)] RESULT SET result-set INTO	{	VIEW view-name parameter[, parameter]...	}	FROM ddm-name
[GIVING [:] sql-code]				
END-RESULT		(structured mode only)		
LOOP		(reporting mode only)		

Extended Set Syntax:

READ [(limit)] RESULT SET result-set INTO	{	VIEW view-name parameter[, parameter]...	}	FROM ddm-name
[WITH INSENSITIVE SCROLL [:] scroll-hv]				
[GIVING [:] sql-code]				
[WITH ROWSET POSITIONING FOR	{	[:] row_hv integer	}	ROWS]
END-RESULT		(structured mode only)		
LOOP		(reporting mode only)		

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Belongs to Function Group: [Database Access and Update](#)

See also *READ RESULT SET - SQL* in the *Natural for DB2* part of the *Database Management System Interfaces* documentation.

Function

The SQL statement `READ RESULT SET` can only be used in conjunction with a `CALLDBPROC` statement. It is used to read a result set which was created by a stored procedure that was invoked by a previous `CALLDBPROC` statement.

Restriction

This statement is available only with Natural for DB2.

Syntax Description

Syntax Element	Description
<i>limit</i>	Limit Option: You can limit the number of rows to be read. You can specify the limit either as a numeric constant (0 - 4294967295) or as a variable of format N, P or I.
<i>result-set</i>	Result Set: As <i>result-set</i> you specify a result-set locator variable filled by a preceding CALLDBPROC statement. <i>result-set</i> has to be a variable of format/length I4. Note: If a syncpoint operation takes place between the CALLDBPROC statement and the READ RESULT SET statement, the result sets can no longer be accessed by the READ RESULT SET statement.
INTO	INTO Clause: The INTO clause is used to specify the target fields in the program which are to be filled with the result set. The INTO clause can specify either single parameters or one or more views as defined in the DEFINE DATA statement.
VIEW <i>view-name</i>	VIEW Clause: <i>view-name</i> specifies a view whose fields receive the columns of the result set created by the stored procedure invoked via the CALLDBPROC statement. The number of columns of the result set must correspond to the number of fields defined in the view (not counting group fields, redefining fields and indicator fields).
<i>parameter</i>	Parameter: Each <i>parameter</i> specifies a field which receives a column of the result set created by the stored procedure invoked via the CALLDBPROC statement.
FROM <i>ddm-name</i>	DDM Name: As <i>ddm-name</i> you specify the name of the data definition module (DDM) which is used to “address” the database executing the stored procedure. For further information, see ddm-name.

Syntax Element	Description
WITH INSENSITIVE SCROLL [:] <i>scroll_hv</i>	WITH INSENSITIVE SCROLL Clause: This clause belongs to the SQL Extended Set. It is available only with Natural for DB2. Using this clause causes the application to use an insensitive scrollable cursor to access the result set created by the previously invoked stored procedure. In order to use this clause, the stored procedure must have created the result set with a scrollable cursor. <i>scroll_hv</i> has to be an alphanumeric Natural variable which contains the scrolling direction. <i>scroll_hv</i> will be evaluated each time the READ RESULT SET processing loop is executed. If the GIVING <i>sqlcode</i> option is specified as well, the processing loop will stay open, even if an <i>sqlcode</i> +100 (row not found) is returned from the RDBMS. The processing will be terminated, if the application issues an ESCAPE statement or if the SQLCODE +100 (row not found) is encountered five times successively without a terminal I/O. If the GIVING <i>sqlcode</i> option is not specified, the processing loop will be closed, if any SQLCODE other than 0 (success) is returned from the RDBMS.
GIVING <i>sqlcode</i>	GIVING <i>sqlcode</i> Clause: This clause may be used to obtain the SQLCODE of the SQL “fetch” operation used to process the result set. If this clause is specified and the SQLCODE of the SQL operation is not 0, no Natural error message will be issued. In this case, the action to be taken in reaction to the SQLCODE value has to be coded in the invoking Natural object. The <i>sqlcode</i> field has to be a variable of format/length I4. If the GIVING <i>sqlcode</i> clause is omitted, a Natural error message will be issued if the SQLCODE is not 0.
WITH ROWSET POSITIONING FOR ... ROWS	WITH ROWSET POSITIONING FOR ... ROWS Clause: This clause belongs to the SQL Extended Set. It is available only with Natural for DB2. Using this clause causes the application to read multiple rows of data from the result set by the previously invoked stored procedure. The <i>integer</i> or <i>:row_hv</i> variable determines the number of rows fetched. If the GIVING <i>sqlcode</i> option is specified as well, the processing loop will stay open, even if an SQLCODE +100 (row not found) is returned from the RDBMS. The processing will be terminated, if the application issues an ESCAPE statement or if the SQLCODE +100 (row not found) is encountered five times successively without a terminal I/O. If the GIVING <i>sqlcode</i> clause is not specified, the processing loop will be closed if any SQLCODE other than 0 (success) is returned from the RDBMS.

Syntax Element	Description
END-RESULT	End of READ RESULT SET Statement: In structured mode, the Natural reserved keyword END-RESULT must be used to end the READ RESULT SET statement. In reporting mode, the Natural statement LOOP must be used to end the READ RESULT SET statement.
LOOP	

Example

See *Example of CALLDBPROC/READ RESULT SET* in the section *CALLDBPROC - SQL* of the *Natural for DB2* documentation.

112

READ WORK FILE

■ Function	880
■ Syntax 1 - READ WORK FILE with Processing Loop	880
■ Syntax 2 - READ WORK FILE without Processing Loop	881
■ Syntax Description	881
■ Field Lengths	884
■ Variable Index Range	884
■ Handling of Dynamic Variables	885
■ Handling of X-Arrays	885
■ Examples	885

Related Statements: [CLOSE WORK FILE](#) | [DEFINE WORK FILE](#) | [WRITE WORK FILE](#)

Belongs to Function Group: [Control of Work Files / PC Files](#)

Function

The `READ WORK FILE` statement is used to read data from a non-Adabas physical sequential work file. The data is read sequentially from the work file. How it is read is independent of how it was written to the work file.

This statement can only be used within a program to be executed under Complete, CICS, TSO or TIAM, or in batch mode. Appropriate JCL or system commands must be executed to allocate the work file. For further information, see the *Operations* documentation. For information on work file assignments, see profile parameter `WORK` in the *Parameter Reference*.

`READ WORK FILE` initiates and executes a processing loop for reading of all records on the work file. Automatic break processing may be performed within a `READ WORK FILE` loop.

 Notes:

1. When an end-of-file condition occurs during the execution of a `READ WORK FILE` statement, Natural automatically closes the work file.
2. For Entire Connection: If an Entire Connection work file is read, no I/O statement may be placed within the `READ WORK FILE` processing loop.
3. For Unicode and code page support, see *Work Files and Print Files on Mainframe Platforms* in the *Unicode and Code Page Support* documentation.

Syntax 1 - READ WORK FILE with Processing Loop

```
READ WORK [FILE] work-file-number
{
  RECORD operand1
  {
    { [ OFFSET n ] ... operand2 } ...
    [ FILLER nX ] ...
  }
  [AND]
  [SELECT] {
    { [ OFFSET n ] ... operand2 } ...
    [ FILLER nX ] ...
    [ OFFSET n ] ... operand4 [AND]
    [ FILLER nX ] ... ADJUST [OCCURRENCES]
  }
}
[GIVING LENGTH operand3]
```

<i>statement ...</i>	
END-WORK	(structured mode only)
LOOP	(reporting mode only)

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Syntax 2 - READ WORK FILE without Processing Loop

```

READ WORK [FILE] work-file-number ONCE
  RECORD operand1
  {
    [AND]
    [SELECT]
    {
      {
        OFFSET
        n
        FILLER
        nX
      } ... operand2 } ...
      {
        OFFSET
        n
        FILLER
        nX
      } ... operand2 } ... [ OFFSET n
        FILLER nX ] ... operand4 [AND]
        ADJUST
        [OCCURRENCES]
      }
    }
  }
  [GIVING LENGTH operand3]
  [AT [END] [OF] [FILE] statement ... END-ENDFILE] (structured mode only)
  [ AT [END] [OF] [FILE] { statement
    DO statement ... } ] (reporting mode only)
    DOEND

```

For explanations of the symbols used in the syntax diagrams, see [Syntax Symbols](#).

Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition	
<i>operand1</i>		S	A	G		A	U	N	P	I	F	B	D	T	L	C		yes	yes
<i>operand2</i>		S	A	G		A	U	N	P	I	F	B	D	T	L	C		yes	yes
<i>operand3</i>		S								I							yes	yes	
<i>operand4</i>			A			A	U	N	P	I	F	B	D	T	L	C		no	no

Format C is not valid for Natural Connection.

See also [Field Lengths](#).

Syntax Element Description:

Syntax Element	Description
<i>work-file-number</i>	Work File Number: The number of the work file (as defined to Natural) to be read.
ONCE	ONCE Option: ONCE is used to indicate that only one record is to be read. No processing loop is initiated (and therefore the loop-closing keyword END-WORK or LOOP must not be specified). If ONCE is specified, the AT END OF FILE clause should also be used. If a READ WORK FILE statement specified with the ONCE option is controlled by a user-initiated processing loop, an end-of-file condition may be detected on the work file before the loop ends. All fields read from the work file still contain the values from the last record read. The work file is then repositioned to the first record which will be read upon the next execution of READ WORK FILE ONCE.
RECORD <i>operand1</i> FILLER <i>nX</i>	RECORD Option: In reporting mode, an operand list (<i>operand1</i>) corresponding to the layout of the record must be provided. Specify FILLER <i>nX</i> if the total length of the operands is less than the work file record length. In structured mode, or if the record to be used is defined using a DEFINE DATA statement, only one field (or group) may be specified, and FILLER is not permitted. The field (or group) must be long enough to receive the entire work file record. No checking and no conversion is performed by Natural on the data contained in the record. It is the user's responsibility to describe the record layout correctly in order to avoid program abends caused by non-numeric data in numeric fields. Because no checking is performed by Natural, this option is the fastest way to process records from a sequential file. The record area defined by <i>operand1</i> is filled with blanks before the record is read. Thus, an end-of-file condition will return a cleared area. Short records will have blanks appended. The RECORD option cannot be used: ■ If an Entire Connection work file is read. ■ If any dynamic variables are used.
SELECT	SELECT Option (Default): If SELECT is specified, only the fields specified in the operand list (<i>operand2</i>) will be made available. The position of the field in the input record may be indicated with an OFFSET and/or FILLER specification.

Syntax Element	Description
	OFFSET <i>n</i> OFFSET 0 indicates the first byte of the record. OFFSET cannot be specified for work files defined as TYPE UNFORMATTED. FILLER <i>n</i>X Indicates that <i>n</i> bytes are to be skipped in the input record. Natural will assign the selected values to the individual fields and check that numeric fields as selected from the record actually contain valid numeric data according to their definition. Because checking of selected fields is performed by Natural, this option results in more overhead for the processing of a sequential file. If a record does not fill all fields specified in the SELECT option, the following applies: ■ For a field which is only partially filled, the section which has not been filled is reset to blanks or zeros. ■ Fields which are not filled at all still have the contents they had before.
<i>operand4</i> AND ADJUST OCCURRENCES	ADJUST Clause: Specify a one-dimensional X-array with complete range (*). The X-array is expanded or reduced to the number of occurrences needed to receive all data read. See Handling of X-Arrays. Note: This feature is not supported by Entire Connection.
GIVING LENGTH <i>operand3</i>	GIVING LENGTH Clause This clause can be used to retrieve the actual length of the record being read. The length (number of bytes) is returned in <i>operand3</i>. <i>operand3</i> must be defined with format/length I4. If the work file is defined as TYPE UNFORMATTED, the length returned indicates the number of bytes read from the byte-stream, including bytes skipped using the FILLER operand.
AT END OF FILE	AT END OF FILE Clause This clause can only be used in conjunction with the ONCE option. If the ONCE option is used, this clause is specified to indicate the action to be taken when an end-of-file condition is detected. If the ONCE option is not used, an end-of-file condition is handled like a normal processing loop termination.
END-WORK	End of READ WORK FILE Statement: In structured mode with processing loop, the Natural reserved word END-WORK must be used to end the READ WORK FILE statement.
LOOP	End of READ WORK FILE Statement:

Syntax Element	Description
	In reporting mode with processing loop, the Natural statement LOOP must be used to end the READ WORK FILE statement.

Field Lengths

The field lengths in the *Operand Definition Table* are determined as follows:

Format	Length
A, B, I, F	The number of bytes in the input record is the same as the internal length definition.
N	The number of bytes in the input record is the sum of internal positions before and after the decimal point. The decimal point and sign do not occupy a byte position in the input record.
P, D, T	The number of bytes in the input record is the sum of positions before and after the decimal point plus 1 for the sign, divided by 2 rounded upwards.
L	1 byte is used. For C format fields, 2 bytes are used.

Examples of Field Lengths:

Field Definition	Input Record
#FIELD1 (A10)	10 bytes
#FIELD2 (B15)	15 bytes
#FIELD3 (N1.3)	4 bytes
#FIELD4 (N0.7)	7 bytes
#FIELD5 (P1.2)	2 bytes
#FIELD6 (P6.0)	4 bytes

See also *Format and Length of User-Defined Variables* in the *Programming Guide*.

Variable Index Range

When reading an array from a work file, you can specify a variable index range for the array. For example:

```
READ WORK FILE work-file-number #ARRAY (I:J)
```

Handling of Dynamic Variables

Work File Type	Handling
UNFORMATTED	Reading a dynamic variable from an UNFORMATTED work file puts the complete rest of the file into the variable (from the current position). If the file exceeds 1073741824 bytes, then a maximum of 1073741824 bytes is placed into the variable.
FORMATTED	Reading a dynamic variable from a FORMATTED work file puts the rest of the work file record into the variable. Thus, for work files with variable record length, the dynamic variable is resized in each execution of the READ WORK FILE statement to match the exact length of the record being read.

Handling of X-Arrays

When the ADJUST clause is *not* used, X-arrays are treated the same as regular arrays; that is, their existing occurrences are filled.

When the ADJUST clause is used, a one-dimensional X-array specified with complete range (*) is expanded to receive all data from the rest of the record for a work file of type FORMATTED, or to receive all data from the rest of the file for a work file of type UNFORMATTED.

Examples

- [Example 1 - READ WORK FILE](#)
- [Example 2 - READ WORK FILE Formatted with Dynamic Variable](#)
- [Example 3 - READ WORK FILE Unformatted with Dynamic Variable](#)
- [Example 4 - READ WORK FILE Formatted with X-array and ADJUST its Occurrences](#)

- Example 5 - READ WORK FILE Unformatted with X-array and ADJUST its Occurrences

Example 1 - READ WORK FILE

```
** Example 'RWFEX1': READ WORK FILE
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
*
1 #RECORD
  2 #PERS-ID (A8)
  2 #NAME    (A20)
END-DEFINE
*
FIND EMPLOY-VIEW WITH CITY = 'STUTTGART'
  WRITE WORK FILE 1
    PERSONNEL-ID NAME
END-FIND
*
* ...
*
READ WORK FILE 1 RECORD #RECORD
  DISPLAY NOTITLE #PERS-ID #NAME
END-WORK
*
END
```

Output of Program RWFEX1:

```
#PERS-ID      #NAME
-----
11100328 BERGHAUS
11100329 BARTHEL
11300313 AECKERLE
11300316 KANTE
11500304 KLUGE
11500308 DIETRICH
11500318 GASSNER
11500343 ROEHM
11600303 BERGER
11600320 BLAETTEL
11500336 JASPER
11100330 BUSH
11500328 EGGERT
```

Example 2 - READ WORK FILE Formatted with Dynamic Variable

```

** Example 'RWFEX2': READ WORK FILE - Formatted with dynamic variable
*****
DEFINE DATA LOCAL
  1 #DYNA (A) DYNAMIC
END-DEFINE
*
DEFINE WORK FILE 1 TYPE 'FORMATTED'
*
WRITE WORK FILE 1 VARIABLE 'text1 text2 text3 '
WRITE WORK FILE 1 VARIABLE 'text4 text5'
*
READ WORK FILE 1 AND SELECT #DYNA
  DISPLAY *LENGTH(#DYNA) #DYNA (AL=40)
/*
/* Length: 18  Dyn.Var: 'text1 text2 text3 '
/* Length: 11  Dyn.Var: 'text4 text5'
END-WORK
*
END

```

Output of Program RWFEX2:

```

Page          1                                     11-07-15  09:21:09

  LENGTH          #DYNA
-----
      18 text1 text2 text3
      11 text4 text5

```

Example 3 - READ WORK FILE Unformatted with Dynamic Variable

```

** Example 'RWFEX3': READ WORK FILE - Unformatted with dynamic variable
*****
DEFINE DATA LOCAL
  1 #DYNA (A) DYNAMIC
END-DEFINE
*
DEFINE WORK FILE 1 TYPE 'FORMATTED'
*
WRITE WORK FILE 1 VARIABLE 'text1 text2 text3 '
WRITE WORK FILE 1 VARIABLE 'text4 text5'
*
DEFINE WORK FILE 1 TYPE 'UNFORMATTED'
*
READ WORK FILE 1 AND SELECT #DYNA
  DISPLAY *LENGTH(#DYNA) #DYNA (AL=40)
/*

```

```

/* Length: 29  Dyn.Var: 'text1 text2 text3 text4 text5'
END-WORK
*
END

```

Output of Program RWFEX3:

```

Page      1                                     11-07-15  09:31:04

LENGTH          #DYNA
-----
29 text1 text2 text3 text4 text5

```

Example 4 - READ WORK FILE Formatted with X-array and ADJUST its Occurrences

```

** Example 'RWFEX4': READ WORK FILE - Formatted with X-array
**                                     and ADJUST its occurrences
*****
DEFINE DATA LOCAL
  1 #ARR (A6/1:*)
  1 #OCC (I4)
END-DEFINE
*
DEFINE WORK FILE 1 TYPE 'FORMATTED'
*
WRITE WORK FILE 1 VARIABLE 'text1 text2 text3 '
WRITE WORK FILE 1 VARIABLE 'text4 text5'
*
READ WORK FILE 1 AND SELECT #ARR(*) AND ADJUST OCCURRENCES
  #OCC := *OCCURRENCE(#ARR)
  DISPLAY #OCC #ARR(1:#OCC)
/*
/* Occurrences: 3 Array(*): 'text1', 'text2', 'text3'
/* Occurrences: 2 Array(*): 'text4', 'text5'
END-WORK
*
END

```

Output of Program RWFEX4:

```

Page      1                                     11-07-15  09:36:13

#OCC      #ARR
-----
3 text1
text2
text3

```

```
2 text4
   text5
```

Example 5 - READ WORK FILE Unformatted with X-array and ADJUST its Occurrences

```
** Example 'RWFEX5': READ WORK FILE - Unformatted with X-array
**                               and ADJUST its occurrences
*****
DEFINE DATA LOCAL
  1 #ARR (A6/1:*)
  1 #OCC (I4)
END-DEFINE
*
DEFINE WORK FILE 1 TYPE 'FORMATTED'
*
WRITE WORK FILE 1 VARIABLE 'text1 text2 text3 '
WRITE WORK FILE 1 VARIABLE 'text4 text5'
*
DEFINE WORK FILE 1 TYPE 'UNFORMATTED'
*
READ WORK FILE 1 AND SELECT #ARR(*) AND ADJUST OCCURRENCES
  #OCC := *OCCURRENCE(#ARR)
  DISPLAY #OCC #ARR(1:#OCC)
/*
/*Occurrences: 5 Array(*): 'text1', 'text2', 'text3', 'text4', 'text5'
END-WORK
*
END
```

Output of Program RWFEX5:

```
Page      1                               11-07-15  09:41:25

  #OCC      #ARR
  -----
          5 text1
            text2
            text3
            text4
            text5
```

113

READLOB

■ Function	892
■ Restrictions	892
■ Syntax Description	893
■ System Variables Available with READLOB	895
■ Functional Considerations	896
■ Examples	896

```
READLOB      [ { ALL  
                (operand1) } ] [IN] [FILE] view-name  
[PASSWORD=operand2]  
[CIPHER=operand3]  
[[WITH] ISN [=] operand4]  
[[STARTING] [AT] OFFSET [=] operand5]  
statement ...  
END-READLOB (structured mode only)  
LOOP        (reporting mode only)
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [READ](#) | [FIND](#) | [GET](#) | [UPDATELOB](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The `READLOB` statement is used on a single record, where the defined LOB field (Large Object field) is read in fixed length segments during the loop processing. It is only applicable to read this LOB field.

At loop beginning, the offset inside the LOB field is set from where to get the first data. On the next loop iteration, the segment following the last segment is returned. If the LOB data end is reached, the loop terminates.

This statement causes a processing loop to be initiated. See also *Loop Processing* in the *Programming Guide*.

Restrictions

The `READLOB` statement can only be used for access to Adabas databases.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S					N	P	I	B	*							yes	no
<i>operand2</i>	C	S				A												yes	no
<i>operand3</i>	C	S					N											yes	no
<i>operand4</i>	C	S					N	P	I	B	*							yes	no
<i>operand5</i>	C	S					N	P	I	B	*							yes	no

* Format B of *operand1*, *operand4* and *operand5* may be used with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Number of LOB Segments to Be Read: The number of loop executions to be performed may be limited by specifying <i>operand1</i> (enclosed in parentheses, immediately after the keyword READLOB) - either as a numeric constant (0 - 4294967295) or as the name of a numeric variable. Example: <pre>READLOB (5) IN FILE VIEW01 ...</pre> <pre>#CNT := 10 READLOB (#CNT) IN FILE VIEW01 ...</pre> For this statement, the specified limit has priority over a limit set with a LIMIT statement. If a smaller limit is set with the profile or session parameter LT, the LT limit applies. Note: <i>operand1</i> is evaluated when the READLOB is started. If the value of <i>operand1</i> is modified within the READLOB loop, this does not affect the number of loop iterations.
ALL	ALL Option: To emphasize that the LOB data is to be read until its end, you can optionally specify the keyword ALL. The ALL option is used by default if <i>operand1</i> and ALL are omitted.

Syntax Element	Description
<i>view-name</i>	View Name: As <i>view-name</i>, you specify the name of a view, which must have been defined either within a <code>DEFINE DATA</code> statement or outside the program in a global or local data area. ■ The view has to contain just a single-valued LOB field, additional fields are not allowed. ■ If the LOB is a MU or PE field, a unique occurrence must be specified; a range notation is not allowed. ■ The LOB field must be defined in the DDM with a fixed (non-dynamic) length (which represents the segment length of the LOB field).
PASSWORD= <i>operand2</i> CIPHER= <i>operand3</i>	PASSWORD and CIPHER Clauses: The <code>PASSWORD</code> clause is used to provide a password when retrieving data from a file which is password-protected. The <code>CIPHER</code> clause is used to provide a cipher key when retrieving data from a file which is enciphered. See the statements FIND and PASSW for further information.
WITH ISN= <i>operand4</i>	WITH ISN Option: This option is used to specify the ISN of the record which is accessed by the <code>READLOB</code> statement. During the complete loop execution, only this record is fetched. <i>operand4</i> must be provided either in the form of a numeric constant or as a user-defined variable, or via the Natural system variable <code>*ISN</code>. The field is not modified by the <code>READLOB</code> execution. Note: <i>operand4</i> is evaluated when the <code>READLOB</code> is started. If the value of <i>operand4</i> is modified within the <code>READLOB</code> loop, this does not affect the record being fetched. If this option is omitted, the <code>*ISN</code> field of the last active database statement is used by default.
STARTING AT OFFSET= <i>operand5</i>	STARTING AT OFFSET Clause: Provides the start offset within the LOB field, where the first segment read begins. The first byte of the LOB field is offset zero (0). <i>operand5</i> must be provided either in the form of a numeric constant or as a user-defined variable, without precision digits. The field is not modified by the <code>READLOB</code> execution. If this clause is omitted, start offset (0) is assumed, which causes the LOB field to be read from the beginning.

Syntax Element	Description
	See also *NUMBER during the processing described in System Variables Available with READLOB .
END-READLOB	End of READLOB Statement: In structured mode, the Natural reserved keyword END-READLOB must be used to end the READLOB statement. In reporting mode, the Natural statement LOOP is used to end the READLOB statement.
LOOP	

System Variables Available with READLOB

The Natural system variables *ISN, *COUNTER and *NUMBER are provided with the READLOB statement.

The format/length of these system variables is P10. This format/length cannot be changed.

The purpose of the Natural system variables, when used with the READLOB statement, is explained below:

System Variable	Explanation	
*ISN	Contains the Adabas ISN of the record currently being processed. Since a READLOB statement always makes access to the same record, the *ISN value returned is the same over all loop iterations.	
*COUNTER	Contains the number of times the processing loop has been passed through.	
*NUMBER	Before the call:	It specifies the byte offset in the LOB field from which the segment is to be read. Value zero (0) represents the leftmost byte in the LOB field. This does not apply for the first loop iteration. In this case the read offset is determined by the STARTING AT OFFSET clause.
	After the call:	If data was found (that is, the offset was less than the LOB field length), it receives the offset plus the segment length. This may lead to a *NUMBER value which is higher than the length of the entire LOB field. If no data was found (that is, the offset was higher or equal to the LOB field length), the value of *NUMBER remains unchanged.
	If a consecutive read over a LOB field is requested, the *NUMBER value must not be modified within the READLOB, as it contains the offset to exactly continue with the next segment in the subsequent loop iteration. However, if a continuation at another place within the LOB field is desired (re-position), you may change the *NUMBER value to this offset. If *NUMBER is reset, this	

System Variable	Explanation
	leads to the next segment coming from the LOB start. If *NUMBER is incremented by (<i>n</i>), this number of bytes will be skipped in the LOB field processing.

Functional Considerations

- The READLOB statement always reads the record without hold. In order to guarantee stability on the LOB data (that is, to prevent an update by other users) while the READLOB browses over the LOB field, the record can be set into hold with the database statement providing the ISN; either
 - into an *exclusive hold*, due to an UPDATE or DELETE referring to an outer READ or FIND statement or
 - into a *shared hold* with an explicit IN SHARED HOLD option applied in a READ or FIND statement. If the additional subparameter MODE=Q is used, the record is automatically released from hold if the next record is fetched in the read sequence.
- Since the READLOB statement always reads the record without hold, an UPDATE, DELETE or GET SAME statement must not refer to a READLOB statement.

Examples

- [Example 1 - Get Record Number from READ Loop](#)
- [Example 2 - Get Record Number by User-defined Value](#)
- [Example 3 - Get Record Number from READ Loop \(with Exclusive Hold\)](#)

Example 1 - Get Record Number from READ Loop

```
DEFINE DATA LOCAL
1 VIEW01 VIEW OF ..
  2 NAME
  2 L@LOBFIELD
1 VIEW02 VIEW OF ..
  2 LOBFIELD_SEGMENT          /* LOB field defined in DDM with (A1000).
END-DEFINE
*
READ VIEW01 BY NAME = 'SMITH'      /* Outer statement reads all demanded record
                                   /* fields, except the LOB field.
      IN SHARED HOLD MODE=Q        /* Set record into shared hold to enforce LOB
                                   /* data stability during READLOB.
  DISPLAY NAME 'Total-length LOB-field' L@LOBFIELD
  READLOB VIEW02                  /* Record number used from active record of
                                   /* READ statement.
```

```

                                /* LOB is read in segments with length 1000.
    STARTING AT OFFSET = 2000    /* Start to read the LOB field at byte 2000.
    WRITE 'Loop counter:' *COUNTER 10X ' Next offset:' *NUMBER
    PRINT VIEW02.LOBFIELD_SEGMENT
    END-READLOB
END-READ
END

```

Example 2 - Get Record Number by User-defined Value

```

DEFINE DATA LOCAL
1 #ISN (I4)
1 #CNT (I4)
1 #OFF (I4)
1 VIEW02 VIEW OF ..
2 LOBFIELD_SEGMENT          /* LOB field defined in DDM with (A1000).
END-DEFINE
*
INPUT (AD=T)
/ ' Read record (ISN):' #ISN
/ 'Number of segments:' #CNT
/ ' Start at offset:' #OFF
*
READLOB (#CNT) VIEW02        /* Read max. (#CNT) segments with length 1000.
    WITH ISN = #ISN          /* Record number provided by user.
                                /* Record is not in hold.
    STARTING AT OFFSET = #OFF /* Start to read the LOB field at byte (#OFF).
    WRITE 'Loop counter:' *COUNTER 10X ' Next offset:' *NUMBER
    PRINT VIEW02.LOBFIELD_SEGMENT
END-READLOB
END

```

Example 3 - Get Record Number from READ Loop (with Exclusive Hold)

```

DEFINE DATA LOCAL
1 VIEW01 VIEW OF ..
2 NAME
1 VIEW02 VIEW OF ..
2 LOBFIELD_SEGMENT          /* LOB field defined in DDM with (A1000).
END-DEFINE
*
R1. READ VIEW01 BY NAME = 'SMITH' /* Outer statement reads all demanded
                                /* record fields, except the LOB field.

    DISPLAY NAME
    READLOB VIEW02             /* Record number from active record of READ.
                                /* LOB is read in segments with length 1000.
    STARTING AT OFFSET = 2000 /* Start to read LOB field at byte 2000.
    WRITE 'Loop counter:' *COUNTER 10X ' Next offset:' *NUMBER
    PRINT VIEW02.LOBFIELD_SEGMENT
    END-READLOB

```

```
...  
UPDATE (R1.)          /* Set record into exclusive hold that  
                        /* enforces LOB data stability during READLOB.  
END OF TRANSACTION  
END-READ  
END
```


114

REDEFINE

■ Function	900
■ Restriction	900
■ Syntax Description	900
■ Examples	901

REDEFINE { *operand1* ({ *nX*
operand2 }...) }...

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Belongs to Function Group: [Reporting Mode Statements](#)

Function

The `REDEFINE` statement is used to redefine a field. The resulting definition may consist of one or more user-defined variables.

With one `REDEFINE` statement, several fields may be redefined.

Restriction

The `REDEFINE` statement is only valid in reporting mode. To redefine a field in structured mode, use the `REDEFINE` clause of the `DEFINE DATA` statement.

Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition		
<i>operand1</i>		S	A	G		A	U	N	P	I	F	B	D	T	L	C			yes	no
<i>operand2</i>		S	A	G		A		N	P	I	F	B	D	T	L	C			yes	yes

Syntax Element Description:

Syntax Element	Description
REDEFINE <i>operand1</i> <i>operand2</i>	Method of Redefinition: The byte positions of <i>operand1</i> are redefined from left to right regardless of format. The format of <i>operand2</i> can be different from the format of <i>operand1</i> . However, the data at the byte positions of <i>operand2</i> should match the format specification of <i>operand2</i> to avoid strange results in the output report. For example, if an alphanumeric field is redefined as numeric and does not contain numeric data

Syntax Element	Description
	according to the format specification, an abnormal termination may result when it is used. Further Redefinition: Fields defined using a <code>REDEFINE</code> statement may be subsequently redefined with another <code>REDEFINE</code> statement.
<i>nX</i>	Filler Notation: The <i>nX</i> notation is used to denote filler bytes within the field/variable being redefined. Any trailing <i>nX</i> notation is optional.

Examples

- [Example 1](#)
- [Example 2](#)
- [Example 3](#)
- [Example 4](#)

Example 1

The user-defined variable `#A` (format/length `A10`) contains the value `123ABCDEFGH`.

```
REDEFINE #A (#A1(N3) #A2(A7))
```

The value in `#A1` is `123`. The value in `#A2` is `ABCDEFGH`.

Example 2

The user-defined variable `#B` (format/length `A10`) contains the value (shown in hexadecimal format) `12345CC1C2C3C4C5C6C7`.

```
REDEFINE #B (#B1(P4) #B2(A7))
```

The value in `#B1` is `12345C` (in hexadecimal format).

The value in `#B2` is `C1C2C3C4C5C6C7` (in hexadecimal format).

```
REDEFINE #B (#BB1(B2)8X)) or REDEFINE #B(#BB1(B2))
```


The value in #BB1 is 1234 (in hexadecimal format).

 **Note:** For packed data (Format P), the number of decimal positions required must be specified. The following formula can be used to determine the number of bytes that the packed number occupies:

Number of bytes = (number of decimal positions + 1) / 2, rounded upwards to full bytes.

Example 3

```
COMPUTE #V (N8.2) = #Y (N10) = ...  
REDEFINE #V (3X #A(N3) 2X #P (N2)) #Y (#B(N3) 7X)
```



Example 4

This example redefines the value of the system variable *DATN, which is in the form YYYYMMDD, and displays the result as three separate fields in the order day/month/year:

```
MOVE *DATN TO #DATINT (N8)  
REDEFINE #DATINT (#YEAR (N4) #MONTH (N2) #DAY (N2))  
DISPLAY NOTITLE #DATINT #DAY #MONTH #YEAR  
END
```

Output:

#DATINT	#DAY	#MONTH	#YEAR
-----	---	---	----
20140326	26	3	2014

115

REDUCE

■ Function	904
■ Syntax Description	904



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related statements: [EXPAND](#) | [RESIZE](#)

Belongs to Function Group: [Memory Management Control for Dynamic Variables or X-Arrays](#)

Function

The REDUCE statement is used to reduce:

- the allocated length of a dynamic variable (*dynamic-clause*), or
- the number of occurrences of X-arrays (*array-clause*).

For further information, see also the following sections in the *Programming Guide*:

- [Using Dynamic Variables](#)
- [Allocating/Freeing Memory Space for a Dynamic Variable](#)
- [X-Arrays](#)
- [Storage Management of X-Group Arrays](#)

Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats																Referencing Permitted	Dynamic Definition
operand1		S	A			A	U					B									no	no
operand2	C	S								I											no	no
operand3			A	G		A	U	N	P	I	F	B	D	T	L	C	G	O			yes	no
operand4	C	S							N	P	I										no	no
operand5		S								I4											no	yes

Syntax Element Description:

Syntax Element	Description
<i>dynamic-clause</i>	Dynamic Clause: The REDUCE DYNAMIC VARIABLE statement reduces the allocated length of a dynamic variable (<i>operand1</i>) to the length specified (<i>operand2</i>). For further information, see Dynamic Clause.
<i>operand1</i>	Dynamic Variable: <i>operand1</i> is the dynamic variable for which the length is to be reduced.
<i>operand2</i>	Target Length of Dynamic Variable: <i>operand2</i> is used to specify the length to which the dynamic variable is to be reduced. The value specified must be a non-negative integer constant or a variable of type Integer 4 (I4).
<i>array-clause</i>	Array Clause: The REDUCE ARRAY statement reduces the number of occurrences of the X-array (<i>operand3</i>) to the upper and lower bound specified with (<i>dim[,dim[,dim]]</i>). For further information, see Array Clause.
<i>operand3</i>	X-Array: <i>operand3</i> is the X-array. The occurrences of the X-array can be reduced. The index notation of the array is optional. As index notation only the complete range notation * is allowed for each dimension.
<i>dim operand4</i>	Dimension: The lower and upper bound notation (<i>operand4</i> or asterisk) to which the X-array should be reduced is specified here. If the current value of the upper or lower bound should be used, an asterisk (*) must be specified instead of <i>operand4</i>. For further information, see Dimension.
GIVING <i>operand5</i>	GIVING Clause: If the GIVING clause is not specified, Natural runtime error processing is triggered if an error occurs. If the GIVING clause is specified, <i>operand5</i> contains the Natural message number if an error occurred, or zero upon success.

Dynamic Clause

`[SIZE OF] DYNAMIC [VARIABLE] operand1 TO operand2`

The `REDUCE DYNAMIC VARIABLE` statement reduces the allocated length of a dynamic variable (*operand1*) to the length specified (*operand2*). The allocated memory of the dynamic variable which is beyond the given length is released immediately, i.e., when the statement is executed.

If the currently allocated length (`*LENGTH`) of the dynamic variable is greater than the given length, `*LENGTH` is set to the given length and the content of the variable is truncated (but not modified). If the given length is larger than the currently allocated length of the dynamic variable, the statement will be ignored.

Array Clause

`[OCCURRENCES OF] ARRAY operand3 TO { 0
 (dim[,dim[,dim]]) }`

If `REDUCE TO 0` (zero) is specified, all occurrences of the X-array are released. In other words, the whole array is reduced.

The `REDUCE ARRAY` statement reduces the number of occurrences of the X-array (*operand3*) to the upper and lower bound specified with `TO (dim[,dim[,dim]])`.

An upper or lower bound used in a `REDUCE` statement must be exactly the same as the corresponding upper or lower bound defined for the array.

Example:

```
DEFINE DATA LOCAL
1 #a(I4/1:*)
1 #g(1:*)
  2 #ga(I4/1:*)

1 #i(i4)
END-DEFINE
...

*/ reducing #a (1:10)

REDUCE ARRAY #a TO (1:10)          /* #a is reduced
REDUCE ARRAY #a TO (*:10)          /* to 10 occurrences.

*/ reducing #ga (1:10,1:20)
```



```

REDUCE ARRAY #g TO (1:10)      /* 1st dimension is set to (1:10)
REDUCE ARRAY #ga TO (*:*,1:20) /* 1st dimension is dependent and
                                /* therefore kept with (*:*)
                                /* 2nd dimension is set to (1:20)

REDUCE ARRAY #a TO (5:10)      /* This is rejected because the lower index
                                /* must be 1 or *
REDUCE ARRAY #a TO (#i:10)     /* This is rejected because the lower index
                                /* must be 1 or *

REDUCE ARRAY #ga TO (1:10,1:20) /* (1:10) for the 1st dimension is rejected
                                /* because the dimension is dependent and
                                /* must be specified with (*:*)

```

For further information, see

- *Storage Management of X-Arrays*
- *Storage Management of X-Group Arrays*

Dimension

Each of the dimensions (*dim*) specified in the *Array Clause* is defined using the following syntax:

$$\left\{ \begin{array}{c} * \\ \left\{ \begin{array}{c} * \\ \text{operand4} \end{array} \right\} : \left\{ \begin{array}{c} * \\ \text{operand4} \end{array} \right\} \end{array} \right\}$$

The lower and upper bound notation (*operand4* or asterisk) to which the X-array should be reduced is specified here. If the current value of the upper or lower bound should be used, an asterisk (*) may be specified in place of *operand4*. In place of *:*, you may also specify a single asterisk.

The number of dimensions (*dim*) must exactly match the defined number of dimensions of the X-array (1, 2 or 3).

When using the REDUCE statement, it is only possible to decrease the number of occurrences. If the requested number is larger than the currently allocated number of occurrences, it will simply be ignored.

116

REINPUT

■ Function	910
■ Syntax Description	911
■ Examples	917

REINPUT	[FULL]	[(<i>statement-parameters</i>)]	{	USING HELP	}
				WITH-TEXT-option	
		[MARK-option]			
		[ALARM-option]			

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [DEFINE WINDOW](#) | [INPUT](#) | [SET WINDOW](#)

Belongs to Function Group: [Screen Generation for Interactive Processing](#)

Function

The `REINPUT` statement is used to return to and re-execute an `INPUT` statement. It is generally used to display a message indicating that the data input as a result of the previous `INPUT` statement were invalid. See [Example 1](#).

No `WRITE` or `DISPLAY` statements may be executed between an `INPUT` statement and its corresponding `REINPUT` statement. The `REINPUT` statement is not valid in batch mode.

The `REINPUT` statement, when executed, repositions the program status regarding subroutine, special condition and loop processing as it existed when the `INPUT` statement was executed (as long as the status of the `INPUT` statement is still active). If the loop was initiated after the execution of the `INPUT` statement and the `REINPUT` statement is within this loop, the loop will be discontinued and then restarted after the `INPUT` statement has been reprocessed as a result of `REINPUT`.

If a hierarchy of subroutines was invoked after the execution of the `INPUT` statement, and the `REINPUT` is performed within a subroutine, Natural will trace back all subroutines automatically and reposition the program status to that of the `INPUT` statement.

It is not possible, however, to have an `INPUT` statement positioned within a loop, a subroutine or a special condition block, and then execute the `REINPUT` statement when the status under which the `INPUT` statement was executed has already been terminated. An error message will be produced and program execution terminated when this error condition is detected.

See also *Dialog Design, Statements REINPUT/REINPUT FULL* (in the *Programming Guide*).

Note:

When an input/output field (option `(AD=M)`) is displayed by an `INPUT` statement, the data visible on screen is only moved back into the variable if the field is regarded as “modified”. A field gets the status `MODIFIED` when any of the following conditions applies:

- The field content was changed (that is, *different* data was entered into the field).

- The key EEOF (erase to end of field) is pressed on an empty field.
- Blanks are entered in an empty field or behind the last non-blank character in the field.
- The profile parameter CVMIN has been set to ON, and the field data is manipulated by edit operations which lastly result in the restoration of its content (for example, by overwriting the first character with the same character).

The content of a field that lastly remains unmodified is not transferred from the screen field into the variable.

The execution of a REINPUT statement (without FULL option) does not affect the MODIFIED state of an input/output field. A field continues to be considered *non-modified* unless it is manipulated via the INPUT statement by using any of the operations listed above. Conversely speaking, a field is treated as *modified* if at least one of the aforementioned operations was performed, irrespective of how often the INPUT statement was re-posted by REINPUT statements (without FULL option).

In other words, a field value displayed using an INPUT statement, which was triggered by a REINPUT statement (without FULL option), is only transferred into the variable if the field was modified in terms of the aforementioned field manipulations.

The MODIFIED status can be checked in the program code if an attribute control variable (option CV) was assigned to the field which is checked with the MODIFIED option, for example, of the IF statement after the INPUT statement.

Syntax Description

Syntax Element	Description
REINPUT FULL	FULL Option: If you specify the FULL option in a REINPUT statement, the corresponding INPUT statement will be re-executed fully: ■ With an ordinary REINPUT statement (without FULL option), the contents of variables that were changed between the INPUT and REINPUT statement will not be displayed; that is, all variables on the screen will show the contents they had when the INPUT statement was originally executed. ■ With a REINPUT FULL statement, all changes that have been made after the initial execution of the INPUT statement will be applied to the INPUT statement when it is re-executed; that is, all variables on the screen contain the values they had when the REINPUT statement was executed. Note: The contents of input-only fields (AD=A) will be deleted again by REINPUT FULL.

Syntax Element	Description						
	Another characteristic of the REINPUT FULL statement is that the status of attribute control variables is reset to NOT MODIFIED. This is not done with the ordinary REINPUT statement. To check if an attribute control variable has been assigned the status MODIFIED, use the <i>MODIFIED option</i>. See also Example 3 - REINPUT FULL WITH MARK POSITION.						
<i>statement-parameters</i>	Parameters: Parameters specified in a REINPUT statement will be applied to all fields specified in the statement. Any parameter specified at element (field) level (see MARK Option) will override any corresponding parameter at statement level. <table> <tr> <td>Parameters that can be specified with the REINPUT statement:</td><td>Specification (S = at statement level, E = at element level)</td></tr> <tr> <td>AD - Attribute Definition *</td><td>SE</td></tr> <tr> <td>CD - Color Definition</td><td>S</td></tr> </table> * If AD=P is specified at statement level, all fields - except those used in the MARK option - are protected. The individual session parameters are described in the <i>Parameter Reference</i>.	Parameters that can be specified with the REINPUT statement:	Specification (S = at statement level, E = at element level)	AD - Attribute Definition *	SE	CD - Color Definition	S
Parameters that can be specified with the REINPUT statement:	Specification (S = at statement level, E = at element level)						
AD - Attribute Definition *	SE						
CD - Color Definition	S						
USING HELP	USING HELP Option: This option causes the helproutine defined for the INPUT map to be invoked. USING HELP used in combination with the MARK option causes the helproutine defined for the first field specified in the MARK option to be invoked. If no helproutine is defined for that field, the helproutine for the map will be invoked. Example: <pre>REINPUT USING HELP MARK 3</pre> As a result, the helproutine defined for the third field in the INPUT map will be invoked.						
<i>WITH-TEXT-option</i>	WITH TEXT Option: The WITH TEXT option is used to provide text which is to be displayed in the message line. See WITH TEXT Option.						
<i>MARK-option</i>	MARK Option With the MARK option, you can mark a specific field, that is, specify a field in which the cursor is to be placed when the REINPUT statement is executed. See MARK Option.						
<i>ALARM-option</i>	ALARM Option:						

Syntax Element	Description
	This option causes the sound alarm feature of the terminal to be activated when the REINPUT statement is executed. See ALARM Option.

WITH TEXT Option

WITH TEXT is used to provide text which is to be displayed in the message line. This is usually a message indicating what action should be taken to process the screen or to correct an error.

$[WITH] [TEXT] \left\{ \begin{array}{l} *operand1 \\ operand2 \end{array} \right\} [(attributes)] [,operand3]...7$

Operand Definition Table:

Operand	Possible Structure Possible Formats				Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S		N P I B *	yes	no
<i>operand2</i>	C	S		A U	yes	no
<i>operand3</i>	C	S		A U N P I F B D T L	yes	no

* Format B of *operand1* may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Message Text from Natural Message File: <i>operand1</i> represents the number of a message text that is to be retrieved from a Natural message file. You can retrieve either user-defined messages or Natural system messages: ■ If you specify a positive value of up to four digits (for example: 954), you will retrieve user-defined messages. ■ If you specify a negative value of up to four digits (for example: -954), you will retrieve Natural system messages. See also Example 4 - WITH TEXT Options. Natural message files are created and maintained with the SYSERR utility as described in the relevant documentation.
<i>operand2</i>	Message Text: <i>operand2</i> represents the message to be placed in the message line.

Syntax Element	Description
	See also Example 4 - WITH TEXT Options .
<i>attributes</i>	Output Attributes: It is possible to assign various output attributes for <i>operand1/operand2</i>. These attributes and the syntax that may be used are described in the section Output Attributes.
<i>operand3</i>	Dynamic Replacement of Message Text: <i>operand3</i> represents a numeric or text constant or the name of a variable. The values provided are used to replace parts of a message text that are either specified with operand1 or operand2. The notation : <i>n</i> : is used within the message text as a reference to <i>operand3</i> contents, where <i>n</i> represents the occurrence (1 - 7) of <i>operand3</i>. See also Example 4 - WITH TEXT Options. Note: Multiple specifications of <i>operand3</i> must be separated from each other by a comma. If the comma is used as a decimal character (as defined with the session parameter DC) and numeric constants are specified as <i>operand3</i>, put blanks before and after the comma so that it cannot be misinterpreted as a decimal character. Alternatively, multiple specifications of <i>operand3</i> can be separated by the input delimiter character (as defined with the session parameter ID); however, this is not possible in the case of ID=/ (slash). Leading zeros or trailing blanks will be removed from the field value before it is displayed in a message.

Output Attributes

attributes indicates the output attributes to be used for text display. Attributes may be:

$$\left\{ \begin{array}{l} AD=ad-value \dots \\ CD=cd-value \dots \\ CV=variable \end{array} \right\} \dots$$

For the possible session parameter values, refer to the corresponding sections in the *Parameter Reference* documentation:

- *AD - Attribute Definition*, section *Field Representation*
- *CD - Color Definition*
- *CV - Attribute Control Variable*

 **Note:** The compiler actually accepts more than one attribute value for an output field. For example, you may specify: AD=BDI. In such a case, however, only the last value applies. In the given example, only the value I will become effective and the output field will be displayed intensified.

MARK Option

With the `MARK` option, you can mark a specific field, that is, specify a field in which the cursor is to be placed when the `REINPUT` statement is executed. You can also mark a specific position within a field. Moreover, you can make fields input-protected, and change their display and color attributes.

```
MARK [POSITION operand4 [IN]] [FIELD] { { operand5
*fieldname } [(attributes)] } ...
```

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand4</i>	C	S					N	P	I								yes	no
<i>operand5</i>	C	S	A				N	P	I								yes	no

Syntax Element Description:

Syntax Element	Description
<i>operand5</i> <i>*fieldname</i>	Field to be Marked: All <code>AD=A</code> or <code>AD=M</code> (that is, non-protected) fields specified in an <code>INPUT</code> statement are sequentially numbered (beginning with 1) by Natural. <i>operand5</i> represents the number of the field in which the cursor is to be positioned. The <i>*fieldname</i> notation is used to position to a field (as used in the <code>INPUT</code> statement) using the name of the field as a reference. If the corresponding <code>INPUT</code> field is an array, a unique index or an index range may be used to reference one or more occurrences of the array. <pre>INPUT #ARRAY (A1/1:5) ... REINPUT (AD=P) 'TEXT' MARK *#ARRAY (2:3)</pre> If <i>operand5</i> is also an array, the values in <i>operand5</i> are used as field numbers for the <code>INPUT</code> array.

Syntax Element	Description
	<pre>RESET #X(N2/1:2) INPUT #ARRAY REINPUT (AD=P) 'TEXT' MARK #X (1:2)</pre>
MARK POSITION	MARK POSITION Option: With this option, you can have the cursor placed at a specific position - as specified with <i>operand4</i> - within a field. See also Example 3 - REINPUT FULL WITH MARK POSITION .
<i>operand4</i>	Cursor Position: <i>operand4</i> specifies the cursor position. <i>operand4</i> must not contain decimal digits.
<i>attributes</i>	Attribute Assignments: See Attribute Assignments .

Attribute Assignments

With explicit attributes, you can define the display presentation and color of the WITH TEXT message and also the layout of the MARK field (which is positioned by the REINPUT statement).

AD=[P]	B		BL	
	C		GR	
	D		NE	
	I	CD=	PI	[CV= <i>operand6</i>]
	N		RE	
	U		TU	
	V		YE	

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand6</i>	S	C	no	no

With the attribute AD=P, you can make an input field (AD=A or AD=M) input-protected.

 **Note:** You cannot use an attribute to make output-only fields (AD=0) available for input.

For information on the attributes AD, CD and CV, refer to the *Parameter Reference*.

The attributes for the `WITH TEXT` and `MARK` fields need not be specified in a fixed manner, but can also be assigned dynamically by means of a control variable, which is referenced in a `(CV=operand6)` clause. See [Example 5 - REINPUT with Attribute Assignment Using a Control Variable](#).

If both an `AD` and a `CV` option are specified for the same field, the attributes from the `AD` option are completely ignored, except `(AD=P)` which remains in effect.

If a `CD` and a `CV` option are specified for the same field, the color from the `CV` option is used. If the `CV` variable contains no color specification, the color from the `CD` option is applied to that field.

If `AD=P` is specified at statement level, all fields except those specified in the `MARK` option are input-protected. See also [Example 2 - REINPUT with Attribute Assignment](#).

ALARM Option

```
[AND] [SOUND] ALARM
```

This option causes the sound alarm feature of the terminal to be activated when the `REINPUT` statement is executed. The appropriate hardware must be available to be able to use this feature.

Examples

- [Example 1 - REINPUT Statement](#)
- [Example 2 - REINPUT with Attribute Assignment](#)
- [Example 3 - REINPUT FULL with MARK POSITION](#)
- [Example 4 - WITH TEXT Options](#)
- [Example 5 - REINPUT with Attribute Assignment Using a Control Variable](#)

Example 1 - REINPUT Statement

```
** Example 'REIEX1': REINPUT
*****
DEFINE DATA LOCAL
1 #FUNCTION (A1)
1 #PARM      (A1)
END-DEFINE
*
INPUT #FUNCTION #PARM
*
DECIDE FOR FIRST CONDITION
  WHEN #FUNCTION = 'A' AND #PARM = 'X'
    REINPUT 'Function A with parameter X selected.'
    MARK *#PARM
  WHEN #FUNCTION = 'C' THRU 'D'
    REINPUT 'Function C or D selected.'
```

```
WHEN #FUNCTION = 'X'
  STOP
WHEN NONE
  REINPUT 'Please enter a valid function.'
  MARK *#FUNCTION
END-DECIDE
*
END
```

Output of Program REIEX1:

```
#FUNCTION A #PARM Y
```

And after pressing ENTER:

```
PLEASE ENTER A VALID FUNCTION
#FUNCTION A #PARM Y
```

Example 2 - REINPUT with Attribute Assignment

```
** Example 'REIEX2': REINPUT (with attributes)
*****
DEFINE DATA LOCAL
1 #A (A20)
1 #B (N7.2)
1 #C (A5)
1 #D (N3)
END-DEFINE
*
INPUT (AD=A) #A #B #C #D
*
IF #A = ' ' OR #B = 0
  REINPUT (AD=P) 'RETYPE VALUES'
      MARK *#A (AD=I CD=RE) /* put cursor on first field
      *#B (AD=U CD=PI) /* and change colors
END-IF
*
END
```

Example 3 - REINPUT FULL with MARK POSITION

```

** Example 'REIEX3': REINPUT (with FULL and POSITION option)
*****
DEFINE DATA LOCAL
1 #A (A20)
1 #B (N7.2)
1 #C (A5)
1 #D (N3)
END-DEFINE
*
INPUT (AD=M) #A #B #C #D
*
IF #A = ' '
    COMPUTE #B = #B + #D
    RESET #D
END-IF
*
IF #A = SCAN 'TEST' OR = ' '
    REINPUT FULL 'RETYPE VALUES' MARK POSITION 5 IN *#A
END-IF
*
END

```

Output of Program REIEX3:

```

RETYPE VALUES
#A                #B          0.00 #C          #D          0

```

Example 4 - WITH TEXT Options

```

** Example 'REIEX4': REINPUT (with TEXT option)
*****
DEFINE DATA LOCAL
01 #NAME (A8)
01 #TEXT (A20)
END-DEFINE
*
*
INPUT WITH TEXT 'Enter a program name.' 'Program name:' #NAME
*
IF #NAME = ' '
    REINPUT WITH TEXT 'Input missing. Enter a name.'
END-IF
*
IF #NAME NE MASK (A)
    MOVE 'Invalid input.' TO #TEXT
    REINPUT WITH TEXT ':1: Name must start with a letter.',#TEXT
ELSE
    /* Using Natural error message 7600 for demonstration

```

```
COMPRESS *INIT-USER 'on' *DAT4I INTO #TEXT
INPUT WITH TEXT *-7600,#NAME,#TEXT 'Input accepted.'
END-IF
END
```

Example 5 - REINPUT with Attribute Assignment Using a Control Variable

```
DEFINE DATA LOCAL
1 #HELLO (A5) INIT <'HELLO'>
1 #VAR (A20) INIT <'Enter "HELLO"'>
1 #CV (C)
END-DEFINE
*
INPUT (IP=OFF) #HELLO (AD=M)
*
IF #HELLO NE 'HELLO' THEN
MOVE (AD=U CD=RE) TO #CV
REINPUT FULL WITH TEXT #VAR (CD=YE)
MARK *#HELLO (CV=#CV)
END-IF
END
```

117


REJECT

For more information about this statement, see the statement [ACCEPT/REJECT](#).

118

RELEASE

■ Function	924
■ Syntax Description	924
■ Example	925



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [STACK](#) | [FIND with RETAIN option](#) | [DEFINE DATA GLOBAL](#)

Function

The `RELEASE` statement is used to:

- delete the entire contents of the Natural stack;
- release sets of ISNs retained via a `FIND` statement that contained a `RETAIN` clause (applicable to Adabas databases only);
- reset global and application-independent variables.

Syntax Description

Operand Definition Table:

Operand	Possible Structure			Possible Formats												Referencing Permitted	Dynamic Definition
set-name	C	S					A									no	no

Syntax Element Description:

Syntax Element	Description
RELEASE STACK	RELEASE STACK Option: Causes all data/commands currently in the Natural stack to be deleted.
RELEASE SETS	RELEASE SETS Option: Is applicable to Adabas databases only. If only <code>RELEASE SETS</code> , without a <code>set-name</code> , is specified, all ISN sets retained with a <code>FIND</code> statement with a <code>RETAIN</code> clause will be released.
RELEASE SETS set-name	Causes a specific single ISN set to be released.

Syntax Element	Description
	<pre>RELEASE SET 'CITY-SET'</pre> <pre>MOVE 'CITY-SET' TO #SET(A32)</pre> <pre>RELEASE SET #SET</pre>
RELEASE VARIABLES	RELEASE VARIABLES Option: Causes all variables defined in the current global data area to be reset to their initial values. Also, it eliminates all application-independent variables (AIVs), thus making them no longer available. The RELEASE VARIABLES statement does not perform the reset/eliminate operations directly after execution. Instead, a signal is set first which triggers these operations when all Natural objects currently running have finished processing.

Example

```
** Example 'RELEX1': FIND (with RETAIN clause and RELEASE statement)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 CITY
  2 BIRTH
  2 NAME
*
1 #BIRTH (D)
END-DEFINE
*
MOVE EDITED '19400101' TO #BIRTH (EM=YYYYMMDD)
*
FIND NUMBER EMPLOY-VIEW WITH BIRTH GT #BIRTH
  RETAIN AS 'AGESET1'
IF *NUMBER = 0
  STOP
END-IF
*
FIND EMPLOY-VIEW WITH 'AGESET1' AND CITY = 'NEW YORK'
  DISPLAY NOTITLE NAME CITY BIRTH (EM=YYYY-MM-DD)
END-FIND
*
RELEASE SET 'AGESET1'
*
END
```

Output of Program RELEX1:

NAME	CITY	DATE OF BIRTH

RUBIN	NEW YORK	1945-10-27
WALLACE	NEW YORK	1945-08-04

119

REPEAT

■ Function	928
■ Syntax Description	928
■ Examples	929

Related Statements: [FOR](#) | [ESCAPE](#)

Belongs to Function Group: *Loop Execution*

Function

The `REPEAT` statement is used to initiate a processing loop.

See also *Loop Processing* in the *Programming Guide*.

Syntax Description

Two different structures are possible for this statement.

- **Syntax 1** - Statements are executed one or more times
- **Syntax 2** - Statements are executed zero or more times

The placement of the logical condition (either at the beginning or at the end of the loop) determines when it is to be evaluated.

For further information on logical conditions, see the section *Logical Condition Criteria* in the *Programming Guide*.

For explanations of the symbols used in the syntax diagrams, see *Syntax Symbols*.

Syntax 1:

<code>REPEAT</code>	
<code>statement ...</code>	<code>[{ UNTIL } logical-condition]</code> <code> { WHILE }</code>
<code>END-REPEAT</code>	<i>(structured mode only)</i>
<code>LOOP</code>	<i>(reporting mode only)</i>

Syntax 2:

REPEAT	
[{ UNTIL } WHILE]	<i>logical-condition</i>] <i>statement...</i>
END-REPEAT	(structured mode only)
LOOP	(reporting mode only)

Syntax Element Description:

Syntax Element	Description
UNTIL	UNTIL Option: The processing loop will be continued until the logical condition becomes true.
WHILE	WHILE Option: The processing loop will be continued as long as the logical condition is true.
<i>logical-condition</i>	Logical Condition: If a logical condition is specified, the condition determines when the execution of the loop is to be terminated. If no logical condition is specified, the loop must be exited by an ESCAPE , STOP or TERMINATE statement specified within the loop. The syntax for a logical condition is described in the section <i>Logical Condition Criteria</i> in the Programming Guide.
END-REPEAT	End of REPEAT Statement: In structured mode, the Natural reserved word END-REPEAT must be used to end the REPEAT statement. In reporting mode, the Natural statement LOOP is used to end the REPEAT statement.
LOOP	

Examples

- [Example 1 - REPEAT](#)

- [Example 2 - Using WHILE and UNTIL Options](#)

Example 1 - REPEAT

```
** Example 'RPTEX1S': REPEAT (structured mode)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
*
1 #PERS-NR (A8)
END-DEFINE
*
REPEAT
  INPUT 'ENTER A PERSONNEL NUMBER:' #PERS-NR
  IF #PERS-NR = ' '
    ESCAPE BOTTOM
  END-IF
  /*
  FIND EMPLOY-VIEW WITH PERSONNEL-ID = #PERS-NR
  IF NO RECORD FOUND
    REINPUT 'NO RECORD FOUND'
  END-NOREC
  DISPLAY NOTITLE NAME
  END-FIND
END-REPEAT
*
END
```

Output of Program RPTEX1S:

```
ENTER A PERSONNEL NUMBER: 11500304
```

After entering and confirming personnel number:

```
      NAME
-----
KLUGE
```

Equivalent reporting-mode example: [RPTEX1R](#).

Example 2 - Using WHILE and UNTIL Options

```

** Example 'RPTX2S': REPEAT (with WHILE and UNTIL option)
*****
DEFINE DATA LOCAL
1 #X (I1) INIT <0>
1 #Y (I1) INIT <0>
END-DEFINE
*
REPEAT WHILE #X <= 5
    ADD 1 TO #X
    WRITE NOTITLE '=' #X
END-REPEAT
*
SKIP 3
REPEAT
    ADD 1 TO #Y
    WRITE '=' #Y
    UNTIL #Y = 6
END-REPEAT
*
END

```

Output of Program RPTX2S:

```

#X:  1
#X:  2
#X:  3
#X:  4
#X:  5
#X:  6

```

```

#Y:  1
#Y:  2
#Y:  3
#Y:  4
#Y:  5
#Y:  6

```

Equivalent reporting-mode example: [RPTX2R](#).

120

REQUEST DOCUMENT

■ Function	934
■ Syntax Description	934
■ Automatically Generated Headers	940
■ URL Encoding for Special Characters	941
■ HTTP/HTTPS Responses Redirected and Denied	943
■ Examples	944

```
REQUEST DOCUMENT FROM url
[
    WITH [with-clause]
]
[
    RETURN [return-clause]
]
RESPONSE http-response-code
[GIVING natural-error-number]
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statement: [PARSE XML](#)

Belongs to Function Group: [Internet and XML](#)

Function

The `REQUEST DOCUMENT` statement is used to retrieve and upload documents on the internet as described in *REQUEST DOCUMENT* in *Statements for Internet and XML Access* in the *Programming Guide*.

For information on Unicode support, see *REQUEST DOCUMENT* in the *Unicode and Code Page Support* documentation.

Restrictions for Protocol Types

For technical reasons, HTTPS is supported under z/OS only.

No Support for Cookies

Cookies are not supported and are ignored.

Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>url</i>	C	S				A											yes	no
<i>http-response-code</i>		S							I4								yes	yes
<i>natural-error-number</i>		S							I4								yes	no

Syntax Element Description:

Syntax Element	Description
<i>url</i>	Location of Document: <i>url</i> is the URL to access a document. If <i>url</i> is an Internet Protocol Version 6 (IPv6) address in hexadecimal notation, you need to enclose the address in square brackets ([]). See also Example 7 - GET Request for an IPv6 Address on Port Number 8080. You cannot embed an Internet Protocol Version 4 (IPv4) address into an IPv6 address.
<i>with-clause</i>	WITH Clause: See with-clause.
<i>return-clause</i>	RETURN Clause: See return-clause.
<i>http-response-code</i>	RESPONSE: <i>http-response-code</i> is the HTTP/HTTPS response status code returned for the request, for example: 200 (request completed). See also HTTP/HTTPS Responses Redirected and Denied. For a list of possible HTTP/HTTPS status codes, refer to the RFC 2616 memorandum published by the World Wide Web Consortium (W3C).
<i>natural-error-number</i>	GIVING Option: <i>natural-error-number</i> contains the 4-digit Natural error number if the request could not be performed.

with-clause

```
[USER user-id]
[PASSWORD user-password]
[HEADER {[NAME] header-name-out [VALUE] header-value-out ...}]
[DATA {ALL outbound-document [ENCODED [[IN] CODEPAGE code-page-out]]
  I{[NAME] variable-name-out [VALUE] variable-value-out ...}]
```

The *with-clause* is used to specify optional user/password, header and data details for the request.

An empty *with-clause* (that is, no value specified after WITH) is ignored.

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>user-id</i>	C	S				A										yes	no
<i>user-password</i>	C	S				A										yes	no
<i>header-name-out</i>	C	S				A										yes	no
<i>header-value-out</i>	C	S				A	N	P	I	F		D	T	L		yes	no
<i>outbound-document</i>	C	S				A	U	N	P	I	F	B	D	T	L	yes	no
<i>code-page-out</i>	C	S				A										yes	no
<i>variable-name-out</i>	C	S				A										yes	no
<i>variable-value-out</i>	C	S				A	N	P	I	F		D	T	L		yes	no

Syntax Element Description:

Syntax Element	Description
<i>user-id</i>	USER: <i>user-id</i> is the ID of the user that will be used for the request.
<i>user-password</i>	PASSWORD: <i>user-password</i> is the password of the user that will be used for the request.
<i>header-name-out</i> <i>header-value-out</i>	HEADER NAME/VALUE Option: <i>header-name-out</i> and <i>header-value-out</i> can only be used in conjunction with each other: ■ <i>header-name-out</i> is the name of a header variable sent with this request. ■ <i>header-value-out</i> is the value of a header variable sent with this request. <i>header-name-out</i> :

Syntax Element	Description
	Header names must not contain a carriage return (CR), a line feed (LF) or a colon (:). This will not be checked by the REQUEST DOCUMENT statement. For valid header names, see the HTTP specifications. For compatibility with the web interface, header names can be written with underscore (_) instead of a dash (-). (Internally, the underscore is replaced by a dash). <i>header-value-out</i>: Header values are not allowed to contain CR/LF. This will not be checked by the REQUEST DOCUMENT statement. For valid header values and formats, see the HTTP specifications. See also Automatically Generated Headers.
<i>outbound-document</i>	DATA ALL Option: <i>outbound-document</i> is a complete document that is to be sent. This value is needed for the HTTP REQUEST-METHOD PUT (see Automatically Generated Headers).
<i>code-page-out</i>	DATA ALL ENCODED Option: Data transfer with the REQUEST DOCUMENT statement normally does not involve any code page conversion. If you want to encode outgoing data in a specific code page, use the CODEPAGE option: <i>outbound-document</i> will be encoded from the default code page (value of the system variable *CODEPAGE) to the code page given in <i>code-page-out</i>. Encoding and Charset Attributes: If the outbound document contains an encoding (XML) or a charset (HTML) attribute, we recommend that the value of the ENCODED option maps the attribute value of the document. Example: If an outbound XML document contains the attribute <code>encoding="UTF-8"</code>, code the REQUEST DOCUMENT statement with the option <code>DATA ALL #DOCUMENT ENCODED CODEPAGE 'UTF-8'</code>.
<i>variable-name-out</i> <i>variable-value-out</i>	DATA NAME/VALUE Option: <i>variable-name-out</i> and <i>variable-value-out</i> request only specific DATA variable information instead of the complete document. They can only be used in conjunction with each other: ■ <i>variable-name-out</i> is the name of a DATA variable to be sent with this request. ■ <i>variable-value-out</i> is the value of a DATA variable to be sent with this request. This value is needed for the HTTP REQUEST-METHOD POST (URL encoding necessary, especially ampersand (&), equal sign (=), percent sign (%) characters). Restriction:

Syntax Element	Description
	If <i>variable-name-out</i> and <i>variable-value-out</i> are given and the communication is http:// or https://, by default, the REQUEST-METHOD POST (see Automatically Generated Headers) with content type application/x-www-form-urlencoded is used. During the request, <i>variable-name-out</i> and <i>variable-value-out</i> will be separated by equal sign (=) and ampersand (&) characters. Therefore, the operands are not allowed to contain equal sign (=), ampersand (&) and, because of URL encoding, percent sign (%) characters. These characters are considered reserved and need to be encoded as indicated in Reserved Characters .

return-clause

```
[HEADER [ALL header-all-in] [[NAME] header-name-in [VALUE] header-value-in ...]]
[PAGE inbound-document [ENCODED [[FOR TYPES mime-type ...] [IN] CODEPAGE code-page-in]]]
```

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>header-all-in</i>		S			A												yes	yes
<i>header-name-in</i>	C	S			A												yes	no
<i>header-value-in</i>		S	A *		A	N	P	I	F	B	D	T	L				yes	yes
<i>inbound-document</i>		S			A	U				B							yes	yes
<i>mime-type</i>	C	S			A												yes	no
<i>code-page-in</i>	C	S			A												yes	no

This clause can be used to specify return information for the headers and/or the document.

Syntax Element Description:

Syntax Element	Description
<i>header-all-in</i>	HEADER ALL Option: <i>header-all-in</i> contains all header data delivered with the HTTP response. The first line contains the status information and all following lines contain the headers as pairs of name and value. The names always end in a colon (:) and the values end in a line feed (LF). Internally, all carriage returns/line feeds (CR/LF) are transformed into line feeds (LF).
<i>header-name-in</i> <i>header-value-in</i>	HEADER NAME/VALUE Option: <i>header-name-in</i> and <i>header-value-in</i> return only specific header information. They can only be used in conjunction with each other:

Syntax Element	Description
	■ <i>header-name-in</i> is the name for the header information returned by the HTTP request. For compatibility with the web interface, header names can be written with underscore (_) instead of dash (-) characters. Internally, the underscore is replaced by a dash. If <i>header-name-in</i> is a blank string, the status information is returned, for example: <pre>HTTP/1.0 200 OK</pre> ■ <i>header-value-in</i> is the scalar or array value required to receive the header data returned by the HTTP request. An array definition is required if more than one occurrence of the same header is expected, for example, multiple Set-Cookie headers. Only one dimension of a multi-dimensional array may contain an index range (see Example 9). An X-array must be materialized before you can use it. If the number of array occurrences exceeds the number of headers, the unused occurrences are reset. If the number of headers exceeds the number of array occurrences, the remaining header values are ignored. For an example of an array definition, see Example 9 - RETURN HEADER NAME VALUE with Array Definition.
<i>inbound-document</i>	PAGE Option: <i>inbound-document</i> is the document returned for this request. No encoding at all of the returned page will be done; that is, the page will remain encoded as delivered from the HTTP server.
<i>code-page-in</i>	PAGE ENCODED Option: Data transfer with the REQUEST DOCUMENT statement normally does not involve any code page conversion. If you want to encode incoming data in a specific code page, use the ENCODED option: If necessary, <i>inbound-document</i> will be encoded in the default code page (value of system variable *CODEPAGE) of the Natural session. If the value of <i>code-page-in</i> is blank, then <i>inbound-document</i> will be encoded from the code page defined with the keyword subparameter RDCP to the default code page (A/B) or (U). The keyword subparameter RDCP of the profile parameter XML is used to specify the name of the default HTML/XML code page.

Syntax Element	Description
	Note: “Returned MIME type contains an encoding” means that the HTTP server returns a content-type header with a <code>charset=</code> clause, for example: <code>charset=ISO-8859-1</code>. For examples of using the <code>RETURN PAGE ENCODED</code> clause, see Example 8 - RETURN PAGE ENCODED Clause.
<i>mime-type</i>	PAGE ENCODED FOR TYPES Option: As a response of an HTTP/HTTPS request, incoming data may contain binary data (for example, image/gif) or character data (for example, text/html). Together with the response, the <code>REQUEST DOCUMENT</code> statement receives a parameter which specifies the type of content of the requested document (MIME type, also known as internet media type). This parameter may contain information about the code page in which the document is encoded. <i>mime-type</i> is the list of MIME types for which an encoding of the returned document in <i>inbound-document</i> will be performed. If the returned MIME type contains an encoding, <i>inbound-document</i> will be encoded from this code page to the default code page (A/B) or (U). If the returned MIME type does not contain an encoding, then <i>inbound-document</i> will be encoded from the code page defined with <i>code-page-in</i> to the default code page (value of the system variable *CODEPAGE) (A/B) or (U). If the returned MIME type does not contain an encoding, then an additional check is performed if the returned MIME type matches one of the types given with <i>mime-type</i>. If a match is found, <i>inbound-document</i> will be encoded from the code page defined with <i>code-page-in</i> to the default code page (A/B) or (U).

Automatically Generated Headers

For an HTTP request, some headers are required, for example: `REQUEST-METHOD` or content type. These headers will be automatically generated depending on the parameters given with the `REQUEST DOCUMENT` statement.



Note: It is possible to overwrite the automatically generated headers. Natural will not check them for errors. Unexpected errors may occur.

- [HTTP REQUEST-METHOD](#)

- [Content Type](#)

HTTP REQUEST-METHOD

The REQUEST DOCUMENT statement supports the following HTTP REQUEST-METHODs: HEAD, POST, GET and PUT.

The following table shows the HTTP REQUEST-METHOD generated depending on the given operands:

	WITH HEADER	WITH DATA	RETURN HEADER	RETURN PAGE
HEAD	o	-	x	-
POST	o	x	o	x
GET	o	-	o	x
PUT	o	DATA ALL *	o	o

In addition to the standard REQUEST-METHODs mentioned above, the methods DELETE, PATCH, OPTIONS and TRACE can be specified in a REQUEST-METHOD header.

Explanation:

- o Optional. Operand can be optionally specified.
- Operand cannot be specified.
- x Operand is always specified.
- * Only applies to DATA ALL and not DATA NAME VALUE.

Content Type

The REQUEST-METHOD POST requires a content-type header for the HTTP request. If no content type is explicitly specified, Natural inserts the following default content-type header into the request:

```
application/x-www-form-urlencoded
```

URL Encoding for Special Characters

When sending POST data with the content type `application/x-www-form-urlencoded`, certain characters must be represented by means of URL encoding, which means substituting the character with *%hexadecimal-character-code*. Some basic details are given here:

- [Non-ASCII Characters](#)
- [Unsafe Characters](#)

■ Reserved Characters

For full details of when and why URL encoding is necessary, refer to the memorandums RFC 1630, RFC 1738 and RFC 1808 published by the World Wide Web Consortium (W3C).

Non-ASCII Characters

All non-ASCII characters (that is, valid ISO 8859/1 characters that are not also ASCII characters) must be URL encoded, for example, the file `köln.html` would appear in an URL as `k%F6ln.html`.

Unsafe Characters

URL-encode the following unsafe characters when you request web pages to avoid server failures:

Unsafe Character	URL Encoding
the tab character	%09
the space character	%20
[	%5B
\	%5C
]	%5D
^	%5E
`	%60
{	%7B
	%7C
}	%7D
~	%7E

Reserved Characters

Some characters have special meanings in URLs, such as the colon (:) that separates the URL scheme from the rest of the URL, the double slash (//) that indicates that the URL conforms to the Common Internet Scheme syntax and the percent sign (%). Generally, when these characters appear as parts of file names, they must be URL encoded to distinguish them from their special meaning in URLs (this is a simplification, refer to the RFCs mentioned earlier for full details).

Reserved characters are:

Reserved Character	URL Encoding
"	%22
#	%23
%	%25
&	%26
+	%2B
,	%2C
/	%2F
:	%3A
<	%3C
=	%3D
>	%3E
?	%3F
@	%40

HTTP/HTTPS Responses Redirected and Denied

For a list of HTTP/HTTPS status codes, refer to the RFC 2616 memorandum published by the World Wide Web Consortium (W3C).

The following special considerations apply to the HTTP responses for redirected and denied requests:

- [Response 301 - 303 \(Redirected\)](#)
- [Response 401 \(Denied/Unauthorized\)](#)

Response 301 - 303 (Redirected)

The HTTP response codes 301, 302 and 303 mean that the URL where the requested document resides has changed and that the request was therefore redirected to another URL. As a response, the return header with the name `LOCATION` will be displayed. This header contains the URL where the requested page has moved to. A new `REQUEST DOCUMENT` request can be used to retrieve the page moved.

HTTP browsers redirect automatically to the new URL, but the `REQUEST DOCUMENT` statement does not handle redirection automatically.

Response 401 (Denied/Unauthorized)

The HTTP response code 401 means that the requested page can only be accessed if a valid user ID and password are provided with the request. As a response, the return header with the name `WWW-AUTHENTICATE` will be delivered with the `REALM` needed for this request.

HTTP browsers normally display a dialog with user ID and password, but with the `REQUEST DOCUMENT` statement, no dialog is displayed.

Examples

- [Example 1 - General Request](#)
- [Example 2 - Simple GET Request \(no data\)](#)
- [Example 3 - Simple HEAD Request \(no return page\)](#)
- [Example 4 - Simple POST Request \(default REQUEST-METHOD\)](#)
- [Example 5 - Simple PUT Request \(with DATA ALL\)](#)
- [Example 6 - REQUEST DOCUMENT with Proxy Authorization](#)
- [Example 7 - GET Request for an IPv6 Address on Port Number 8080](#)
- [Example 8 - RETURN PAGE ENCODED Clause](#)
- [Example 9 - RETURN HEADER NAME VALUE with Array Definition](#)



Note: There is an example dialog `V5-RDOC` for this statement in the example library `SYSEXV`.

Example 1 - General Request

```
REQUEST DOCUMENT FROM "http://bo1sap1:5555/invoke/sap.demo/handle_RFC_XML_POST"
WITH
  USER #User PASSWORD #Password
  DATA
    NAME 'XMLData'          VALUE #Queryxml
    NAME 'repServerName'    VALUE 'NT2'
  RETURN
    PAGE #Resultxml
  RESPONSE #rc
```

Example 2 - Simple GET Request (no data)

```
REQUEST DOCUMENT FROM "http://pcnatweb:8080"
RETURN
  PAGE #Resultxml
RESPONSE #rc
```

Example 3 - Simple HEAD Request (no return page)

```
REQUEST DOCUMENT FROM "http://pcnatweb"
RESPONSE #rc
```

Example 4 - Simple POST Request (default REQUEST-METHOD)

```
REQUEST DOCUMENT FROM "http://pcnatweb/cgi-bin/nwwcgi.exe/sysweb/nat-env"
WITH
  DATA
    NAME 'XMLData'      VALUE #Queryxml
    NAME 'repServerName' VALUE 'NT2'
RETURN
  PAGE #Resultxml
RESPONSE #rc
```

Example 5 - Simple PUT Request (with DATA ALL)

```
REQUEST DOCUMENT FROM "http://pcnatweb/test.txt"
WITH
  DATA ALL      #document
RETURN
  PAGE #Resultxml
RESPONSE #rc
```

Example 6 - REQUEST DOCUMENT with Proxy Authorization

```
DEFINE DATA
LOCAL
1 #URL          (A) DYNAMIC
1 #PAGE         (A) DYNAMIC
1 #HTTPSTAT     (I4)
1 #PATH         (A) DYNAMIC
1 #NAME         (A) DYNAMIC
1 #VALUE        (A) DYNAMIC
1 #USERID       (A8)
1 #PASSWORD     (A8)
1 #AUTHHDR      (A) DYNAMIC
1 #CREDENTIALS  (A) DYNAMIC
1 #PADDDCHAR    (A2/0:2) INIT  <' ','==','='>
1 #LENGTH      (I4)
```

```

1 #FACTOR          (I4)
1 #REMAINDER       (I4)
/*
/* #USR4210
1 PARM-FUNCTION    (A2) INIT <'BA'>
1 PARM-RC          (I4)
1 PARM-ERRTXT      (A72)
1 PARM-A           (A) DYNAMIC
1 PARM-B           (B) DYNAMIC
1 PARM-RFC         (B1)
END-DEFINE
**
ASSIGN #URL = 'http://www.softwareag.com/corporate/default.asp'
REQUEST DOCUMENT FROM #URL
  RETURN PAGE #PAGE ENCODED CODEPAGE ' '
  RESPONSE #HTTPSTAT
*****
** HTTP response 407 means that the proxy server requires **
** the client to identify itself! **
*****
IF #HTTPSTAT = 407
  INPUT          'Please enter userid and password' (AD=I) /
  'Userid  :' #USERID / 'Password:' #PASSWORD
  ASSIGN #AUTHHDR = 'Proxy-Authorization'
  COMPRESS #USERID ':' #PASSWORD INTO PARM-B LEAVING NO
*****
** Convert credentials to ASCII **
*****
  MOVE ENCODED PARM-B TO PARM-B
  CODEPAGE 'ASCII'
*****
** ENCODE CREDENTIALS WITH BASE64 **
*****
** BASE64 demands that the length of the encoded string is **
** a multiple of 3. If encoding length does not match this **
** the encoded string has to be padded with '=' characters.**
** Since USR4210 does not support padding of the base64 **
** string with trailing '=' characters, we have to do this **
** ourselves. **
*****
  CALLNAT 'USR4210N' PARM-FUNCTION PARM-RC PARM-ERRTXT PARM-B PARM-A
  PARM-RFC
*
  #LENGTH := *LENGTH(PARM-A)
  WRITE PARM-A (AL=40) #LENGTH EJECT
  DIVIDE 3 INTO #LENGTH GIVING #FACTOR REMAINDER #REMAINDER
  COMPRESS PARM-A #PADDCHAR(#REMAINDER)
  INTO #CREDENTIALS LEAVING NO
*****
** Build Proxy-Authorization HTTP header **
*****
  COMPRESS 'Basic ' #CREDENTIALS

```



```

    INTO #CREDENTIALS
    ASSIGN #AUTHHDR = 'Proxy-Authorization'
*****
** Repeat HTTP request with valid client identification **
*****
    REQUEST DOCUMENT FROM #URL
    WITH HEADER NAME #AUTHHDR VALUE #CREDENTIALS
    RETURN PAGE #PAGE ENCODED CODEPAGE ' '
    RESPONSE #HTTPSTAT
END-IF
END

```

Example 7 - GET Request for an IPv6 Address on Port Number 8080

```

REQUEST DOCUMENT FROM "http://[2BFC:5022:4081:0000::C:41]:8080"
RETURN
    PAGE #Resultxml
RESPONSE #rc

```

Example 8 - RETURN PAGE ENCODED Clause

1. Server returns a header 'Content-type: text/html; charset=UTF-8'

Program Code Example 1:

```

...
RETURN PAGE inbound-document

```

Resulting Processing:

inbound-document remains UTF-8 encoded.

Program Code Example 2:

```

...
RETURN PAGE inbound-document ENCODED [...]

```

Resulting Processing:

inbound-document is converted from UTF-8 to the default code page regardless of whether *code-page-in* and *mime-type* are specified: When a valid encoding is returned in the content-type header, *mime-type* and *code-page-in* are ignored.

2. Server returns a header 'Content-type: text/xml'

Program Code Example 1:

```

...
RETURN PAGE inbound-document ENCODED

```

Resulting Processing:

inbound-document remains unconverted since the content-type header does not contain a valid encoding.

Program Code Example 2:

```
...  
RETURN PAGE inbound-document ENCODED FOR TYPES 'text/xml' IN CODEPAGE 'USASCII'
```

Resulting Processing:

inbound-document is converted from USASCII code page to the default code page. In this case, conversion is done according to the programmer's assumption about the encoding of the received page.

Program Code Example 3:

```
...  
RETURN PAGE inbound-document ENCODED FOR TYPES 'text/html'  
    IN CODEPAGE ' '
```

Resulting Processing:

inbound-document remains unconverted since the MIME type 'text/html', specified in *mime-type*, does not match the MIME type 'text/xml', returned in the content-type header.

Program Code Example 4:

```
...  
RETURN PAGE inbound-document ENCODED IN CODEPAGE ' '
```

Resulting Processing:

inbound-document is converted from the default code page, specified with subparameter RDCP of profile parameter XML, to the default code page.



Note: The default value for the RDCP subparameter, which applies if nothing has been explicitly specified, is ISO-8859-1. See also *XML - Activate PARSE XML and REQUEST DOCUMENT Statements* in the *Parameter Reference*.

Example 9 - RETURN HEADER NAME VALUE with Array Definition

```
DEFINE DATA
LOCAL
1 #FROM      (A) DYNAMIC
1 #HEADER    (A) DYNAMIC
1 #PAGE      (A) DYNAMIC
1 #COOKIES (A20/1:3,1:4,2:5)
1 #RC        (I4)
END-DEFINE
ASSIGN #FROM = 'http://www.myserver.com'
REQUEST DOCUMENT FROM #FROM
    RETURN
        HEADER NAME 'Set-Cookie' VALUE #COOKIES(1,2:3,3)
        PAGE      #PAGE
        RESPONSE #RC
PRINT #COOKIES(*,*,*)
END
```

In the example program above, *invalid* array definitions (with multiple dimensions) would be:

```
RETURN HEADER NAME 'Set-Cookie' VALUE #COOKIES(1:3,2:3,3)
RETURN HEADER NAME 'Set-Cookie' VALUE #COOKIES(*,2,*)
```

121

RESET

■ Function	952
■ Syntax Description	952
■ Example	953

RESET [INITIAL] *operand1* ...

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [ADD](#) | [COMPRESS](#) | [COMPUTE](#) | [DIVIDE](#) | [EXAMINE](#) | [MOVE](#) | [MOVE ALL](#) | [MULTIPLY](#) | [SEPARATE](#) | [SUBTRACT](#)

Belongs to Function Group: [Arithmetic and Data Movement Operations](#)

Function

The RESET statement is used to reset the value of a field:

- RESET (without INITIAL) sets the content of each specified field to its **default initial value** depending on its format.
- RESET INITIAL sets each specified field to the initial value as defined for the field in the [DEFINE DATA](#) statement. For a field declared without [INIT](#) clause in the [DEFINE DATA](#) statement, RESET INITIAL has the same effect as RESET (without INITIAL).

 Notes:

1. A field declared with a [CONSTANT](#) clause in the [DEFINE DATA](#) statement may not be referenced in a RESET statement, since its content cannot be changed.
2. In reporting mode, the RESET statement may also be used to define a variable, provided that the program contains no [DEFINE DATA LOCAL](#) statement.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats															Referencing Permitted	Dynamic Definition
<i>operand1</i>		S	A	G	M	A	U	N	P	I	F	B	D	T	L	C	G	O			yes	yes

Syntax Element Description:

Syntax Element	Description
RESET <i>operand1</i>	Reset to Null Value: RESET (without INITIAL) sets the content of each specified field (<i>operand1</i>) to its default initial value. If <i>operand1</i> is a dynamic variable, it will be reset to a null value with the length the variable currently has at the time the RESET statement is executed. The current length of a dynamic variable can be ascertained by using the system variable *LENGTH. For general information on dynamic variables, see the section <i>Using Dynamic and Large Variables</i>.
RESET INITIAL <i>operand1</i>	Reset to Initial Value: RESET INITIAL sets each specified field (<i>operand1</i>) to the initial value as defined for the field in the DEFINE DATA statement. ■ If you specify no INIT value in the DEFINE DATA statement, a field will be initialized with a default initial value depending on its format. ■ If a dynamic variable is used, *LENGTH is set to zero if no initial value is defined. ■ If you apply RESET INITIAL to an array, it must be applied to the entire array (as defined in the DEFINE DATA statement); a RESET INITIAL of individual array occurrences is not possible. ■ RESET INITIAL of fields resulting from a redefinition is not possible either. ■ RESET INITIAL is applied to a dynamic variable. ■ RESET INITIAL cannot be applied to database fields.

Example

```

** Example 'RSTEX1': RESET (with/without INITIAL)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
1 #BINARY (B4) INIT <1>
1 #INTEGER (I4) INIT <5>
1 #NUMERIC (N2) INIT <25>
END-DEFINE
*
LIMIT 1
READ EMPLOY-VIEW
/*
WRITE NOTITLE 'VALUES BEFORE RESET STATEMENT:'
WRITE / '=' NAME '=' #BINARY '=' #INTEGER '=' #NUMERIC
/*

```

```
RESET NAME #BINARY #INTEGER #NUMERIC
/*
WRITE /// 'VALUES AFTER  RESET STATEMENT:'
WRITE / '=' NAME '=' #BINARY '=' #INTEGER '=' #NUMERIC
/*
RESET INITIAL #BINARY #INTEGER #NUMERIC
/*
WRITE /// 'VALUES AFTER  RESET INITIAL STATEMENT:'
WRITE / '=' NAME '=' #BINARY '=' #INTEGER '=' #NUMERIC
/*
END-READ
END
```

Output of Program RSTEX1:

VALUES BEFORE RESET STATEMENT:

NAME: ADAM	#BINARY: 00000001	#INTEGER: 5	#NUMERIC:
25			

VALUES AFTER RESET STATEMENT:

NAME:	#BINARY: 00000000	#INTEGER: 0	#NUMERIC:
0			


VALUES AFTER RESET INITIAL STATEMENT:

NAME:	#BINARY: 00000001	#INTEGER: 5	#NUMERIC:
25			

122

RESIZE

■ Function	956
■ Syntax Description	956



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [EXPAND](#) | [REDUCE](#)

Belongs to Function Group: [Memory Management Control for Dynamic Variables or X-Arrays](#)

Function

The RESIZE statement is used to adjust:

- the size of a dynamic variable (*dynamic-clause*), or
- the number of occurrences of X-arrays (*array-clause*).

For further information, see also the following sections in the *Programming Guide*:

- *Using Dynamic Variables*
- *Allocating/Freeing Memory Space for a Dynamic Variable*
- *X-Arrays*
- *Storage Management of X-Group Arrays*

Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition		
operand1		S	A			A	U					B						no	no	
operand2	C	S								I								no	no	
operand3			A	G		A	U	N	P	I	F	B	D	T	L	C	G	O	yes	no
operand4	C	S							N	P	I								no	no
operand5		S									I4								no	yes

Syntax Element Description:

Syntax Element	Description
<i>dynamic-clause</i>	DYNAMIC Clause: The RESIZE DYNAMIC statement adjusts the allocated length of the currently allocated storage of a dynamic variable (<i>operand1</i>) to the value specified with <i>operand2</i> . For more information, see Dynamic Clause .
<i>operand1</i>	Dynamic Variable to be Adjusted: <i>operand1</i> is the dynamic variable for which the length is to be adjusted.
<i>operand2</i>	New Length Specification: <i>operand2</i> is used to specify the new length of the dynamic variable. The value specified must be a non-negative numeric integer constant or a variable of type Integer 4 (I4).
<i>array-clause</i>	ARRAY Clause: The RESIZE ARRAY statement adjusts the number of occurrences of the X-array (<i>operand3</i>) to the upper and lower bound specified with (<i>dim[,dim[,dim]]</i>). For more information, see Array Clause .
<i>operand3</i>	Name of X-array: <i>operand3</i> is the X-array. The occurrences of the X-array can be expanded or reduced. The index notation of the array is optional. As index notation only the complete range notation * is allowed for each dimension.
dim <i>operand4</i>	X-array Lower and Upper Bound: The lower and upper bound notation (<i>operand4</i> or asterisk) to which the X-array should be expanded is specified here. If the current value of the upper or lower bound should be used, an asterisk (*) must be specified in place of <i>operand4</i> . For further information, see Dimension .
GIVING <i>operand5</i>	GIVING Clause: If the GIVING clause is not specified, Natural runtime error processing is triggered if an error occurs. If the GIVING clause is specified, <i>operand5</i> contains the Natural message number if an error occurred, or zero upon success.

Dynamic Clause

```
[SIZE OF] DYNAMIC [VARIABLE] operand1 TO operand2
```

The `RESIZE DYNAMIC` statement adjusts the allocated length of a dynamic variable (*operand1*) to the value specified with *operand2*.

When the `RESIZE` statement is used, the currently allocated storage size will be adjusted to the requested values, regardless whether it must be increased or decreased.

Array Clause

```
[AND RESET] [OCCURRENCES OF] ARRAY operand3 TO (dim [, dim [, dim]])
```

The `RESIZE ARRAY` statement adjusts the number of occurrences of the X-array (*operand3*) to the upper and lower bound specified with (*dim* [, *dim* [, *dim*]]).

The `RESET` option resets all occurrences of the resized X-array to its default zero value. By default (no `RESET` option), the actual values are kept and the resized (new) occurrences are reset.

An upper or lower bound used in an `RESIZE` statement must be exactly the same as the corresponding upper or lower bound defined for the array.

Example:

```
DEFINE DATA LOCAL
1 #a(I4/1:*)
1 #g(1:*)
  2 #ga(I4/1:*)

1 #i(i4)
END-DEFINE
...

*/ resizing #a (1:10)
RESIZE ARRAY #a TO (1:10)          /* #a is resized to
RESIZE ARRAY #a TO (*:10)          /* 10 occurrences.

/* resizing #ga (1:10,1:20)
RESIZE ARRAY #g TO (1:10)          /* 1st dimension is set to (1:10)
RESIZE ARRAY #ga TO (*:*,1:20)    /* 1st dimension is dependent and
                                   /* therefore kept with (*:*)
                                   /* 2nd dimension is set to (1:20)

RESIZE ARRAY #a TO (5:10)          /* This is rejected because the lower index
                                   /* must be 1 or *
RESIZE ARRAY #a TO (#i:10)         /* This is rejected because the lower index
```

```

/* must be 1 or *
RESIZE ARRAY #ga TO (1:10,1:20) /* (1:10) for the 1st dimension is rejected
/* because the dimension is dependent and
/* must be specified with (*:*)).

```

For further information, see the following sections in the *Programming Guide*:

- *Storage Management of X-Arrays*
- *Storage Management of X-Group Arrays*

Dimension

Each of the dimensions (*dim*) specified in the *Array Clause* is defined using the following syntax:

$$\left\{ \begin{array}{c} * \\ \left\{ \begin{array}{c} * \\ \text{operand4} \end{array} \right\} : \left\{ \begin{array}{c} * \\ \text{operand4} \end{array} \right\} \end{array} \right\}$$

The lower and upper bound notation (*operand4* or asterisk) to which the X-array should be expanded is specified here. If the current value of the upper or lower bound should be used, an asterisk (*) may be specified in place of *operand4*. In place of *:*, you may also specify a single asterisk.

The number of dimensions (*dim*) must exactly match the defined number of dimensions of the X-array (1, 2 or 3).

123

ROLLBACK (SQL)

■ Function	962
■ Consideration for Non-Natural Programs	962
■ Example	963

ROLLBACK

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Belongs to Function Group: [Database Access and Update](#)

See also *ROLLBACK - SQL* in the *Natural for DB2* part of the *Database Management System Interfaces* documentation

Function

The SQL statement `ROLLBACK` corresponds to the Natural statement `BACKOUT TRANSACTION`. It undoes all database modifications made since the beginning of the last recovery unit. A recovery unit may start either after the beginning of a session or after the last `SYNCPPOINT`, `COMMIT`, `END TRANSACTION` or `BACKOUT TRANSACTION` statement. This statement also releases all records held during the transaction.

If a program tries to back out updates which have already been committed by a terminal I/O, a corresponding Natural error message (NAT3711) is returned.



Caution: As all cursors are closed when a logical unit of work ends, a `ROLLBACK` statement must not be placed within a database modification loop; instead, it has to be placed outside such a loop or after the outermost loop of nested loops.

Consideration for Non-Natural Programs

If an external program written in another standard programming language is called from a Natural program, this external program should not contain its own `ROLLBACK` statement if the Natural program issues database calls, too. The calling Natural program should issue the `ROLLBACK` statement on behalf of the external program.

Example

```
...  
DELETE FROM SQL-PERSONNEL WHERE NAME = 'SMITH'  
ROLLBACK  
...
```

124

RETRY

■ Function	966
■ Restriction	966
■ Example	966

RETRY

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [DELETE](#) | [END TRANSACTION](#) | [FIND](#) | [GET](#) | [GET SAME](#) | [GET TRANSACTION DATA](#) | [HISTOGRAM](#) | [LIMIT](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [STORE](#) | [UPDATE](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The `RETRY` statement is used within an `ON ERROR` statement block (see [ON ERROR](#) statement). It is used to reattempt to obtain a record which is in hold status for another user.

When a record to be held is already in hold status for another user, Natural issues Error Message NAT3145. See also the session parameter `WH` (Wait for Record in Hold Status).

The `RETRY` statement must be placed in the object that causes the Error 3145.

For details on record hold logic, see the section *Record Hold Logic* in the *Programming Guide*.

Restriction

This statement can only be used to access Adabas databases.

Example

```
** Example 'RTYEX1': RETRY
**
** CAUTION: Executing this example will modify the database records!
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
2 NAME
*
1 #RETRY (A1) INIT <' '>
END-DEFINE
*
FIND EMPLOY-VIEW WITH NAME = 'ALDEN'
/*
DELETE
END TRANSACTION
```

```
/*
ON ERROR
  IF *ERROR-NR = 3145
    INPUT NO ERASE 10/1
      'RECORD IS IN HOLD' /
      'DO YOU WISH TO RETRY?' /
      #RETRY '(Y)ES OR (N)O?'
    IF #RETRY = 'Y'
      RETRY
    ELSE
      STOP
    END-IF
  END-IF
END-ERROR
/*
AT END OF DATA
  WRITE NOTITLE *NUMBER 'RECORDS DELETED'
END-ENDDATA
END-FIND
*
END
```

125

RUN

■ Function	970
■ Syntax Description	970
■ Dynamic Source Text Creation/Execution	971
■ Example	972

```
RUN [REPEAT] operand1 [operand2 [(parameter)]] ... 40
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Belongs to Function Group: [Invoking Programs and Routines](#)

Function

The RUN statement is used to read a Natural source program from the Natural system file and then execute it.

For Natural RPC: See *Notes on Natural Statements on the Server* in the *Natural RPC (Remote Procedure Call)* documentation.

Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats	Referencing Permitted	Dynamic Definition
operand1	C	S			A	yes	no
operand2	C	S	A	G	A U N P I F B D T L G	yes	no

Syntax Element Description:

Syntax Element	Description
REPEAT	REPEAT Option: RUN REPEAT causes the program not to prompt the user for input until the program has finished executing even if multiple output screens (produced by INPUT statements) are produced. This feature may be used if the program is to display multiple screens of information without having the user respond to each screen.
operand1	Program Name: As operand1 the name of the program can be specified as an alphanumeric constant or as the content of an alphanumeric variable. If a variable is used, it must be 8 characters in length. The program may be stored in the current library or in a concatenated library (default steplib is SYSTEM). If the program is not found, an error message is issued.

Syntax Element	Description
	The program is read into the source program work area and overlays any current source program.
<i>operand2</i>	Parameters: The RUN statement may also be used to pass parameters to the program to be run. A parameter may be defined with any format. The parameters are converted to a format suitable for a corresponding INPUT field. All parameters are placed on the top of the Natural stack. The parameters can be read using an INPUT statement. The first INPUT statement issued will result in the insertion of all parameters into the fields specified in the INPUT statement. The INPUT statement must have the sign specification (session parameter SG=ON) for parameter fields defined with numeric format. If more parameters are passed than are read by the next INPUT statement, the extra parameters are ignored. The number of parameters may be obtained with the system variable *DATA. Note: If <i>operand2</i> is a time variable (format T), only the time component of the variable content is passed, but not the date component.
<i>parameter</i>	Date Format: If <i>operand2</i> is a date variable, you can specify the session parameter DF (described in the <i>Parameter Reference</i>) as <i>parameter</i> for this variable.

Dynamic Source Text Creation/Execution

The RUN statement may be used to dynamically compile and execute a program for which the source or parts thereof are created dynamically.

Dynamic source text creation is performed by placing source text into global variables and then referring to these variables by using an ampersand (&) instead of a plus sign (+) as the first character of the variable name in the source text. The content of the global variable will be interpreted as source text when the program is invoked using the RUN statement.

A global variable with index must not be used within a program that is invoked via a RUN statement.

It is not allowed to place a comment or an INCLUDE statement in a global variable.

Example

Program containing RUN statement:

```
** Example 'RUNEX1': RUN (with dynamic source program creation)
*****
DEFINE DATA
GLOBAL
  USING RUNEXGDA
LOCAL
1 #NAME (A20)
1 #CITY (A20)
END-DEFINE
*
INPUT 'Please specify the search values:' //
  'Name:' #NAME /
  'City:' #CITY
*
RESET +CRITERIA      /* defined in GDA 'RUNEXGDA'
*
IF #NAME = ' ' AND #CITY = ' '
  REINPUT 'Enter at least 1 value'
END-IF
*
IF #NAME NE ' '
  COMPRESS 'NAME' ' ' ='' #NAME '' INTO +CRITERIA LEAVING NO
END-IF
IF #CITY NE ' '
  IF +CRITERIA NE ' '
    COMPRESS +CRITERIA 'AND' INTO +CRITERIA
  END-IF
  COMPRESS +CRITERIA ' CITY ='' #CITY '' INTO +CRITERIA LEAVING NO
END-IF
*
RUN 'RUNEXFND'
*
END
```

Program RUNEXFND executed by RUN statement:

```
** Example 'RUNEXFND': RUN (program executed with RUN in RUNEX1)
*****
DEFINE DATA
GLOBAL
  USING RUNEXGDA
LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 CITY
```

```

END-DEFINE
*
* &CRITERIA filled with  "NAME = 'xxxxx' AND CITY = 'xxxx'"
*
FIND NUMBER EMPLOY-VIEW WITH &CRITERIA
    RETAIN AS 'EMP-SET'
DISPLAY *NUMBER
*
END

```

Global Data Area RUNEXGDA:

Global	RUNEXGDA	Library	SYSEXSYN	DBID	10	FNR	32
Command							> +
I T L	Name		F Length		Miscellaneous		
All	--	-----	-----		-----		-->
	1	+CRITERIA	A	80			

XIV

■ 126 SELECT (SQL)	977
■ 127 SEND METHOD	997
■ 128 SEPARATE	1009
■ 129 SET CONTROL	1023
■ 130 SET GLOBALS	1027
■ 131 SET KEY	1031
■ 132 SET TIME	1043
■ 133 SET WINDOW	1047
■ 134 SKIP	1049
■ 135 SORT	1053
■ 136 STACK	1065
■ 137 STOP	1071

126

SELECT (SQL)

■ Function	978
■ Syntax 1 - Cursor-Oriented Selection	978
■ Syntax 2 - Non-Cursor Selection	979
■ Syntax Element Description	980
■ Join Queries	996

For explanations of the symbols used in the syntax diagrams, see [Syntax Symbols](#).

Belongs to Function Group: [Database Access and Update](#)

Function

The `SELECT` statement supports both the **cursor-oriented selection** that is used to retrieve an arbitrary number of rows and the **non-cursor selection** (singleton `SELECT`) that retrieves at most one single row. With the `SELECT ... END-SELECT` construction, Natural uses the same database loop processing as with the `FIND` statement.

Two different structures are possible.


Syntax 1 - Cursor-Oriented Selection

Like the Natural `FIND` statement, the cursor-oriented `SELECT` statement is used to select a set of rows (records) from one or more DB2 tables, based on a search criterion. Since a database loop is initiated, the loop must be closed by a `LOOP` (reporting mode) or `END-SELECT` statement. With this construction, Natural uses the same loop processing as with the `FIND` statement.

In addition, no cursor management is required from the application program; it is automatically handled by Natural.

- [Syntax 1 - Common Set](#)
- [Syntax 1 - Extended Set](#)

Syntax 1 - Common Set



Syntax 1 - Extended Set

```

[WITH_CTE common-table-expression,...]
SELECT selection into-clause table-expression

[ { UNION
  EXCEPT
  INTERSECT } [ DISTINCT
ALL ] [ (SELECT selection
table-expression)
SELECT selection
table-expression ] ... ]

[ORDER BY criteria]

[ OPTIMIZE FOR integer { ROW
ROWS } ]

[WITH isolation-level]
[SKIP LOCKED DATA]
[QUERYNO integer]
[FETCH FIRST row-limit]
[WITH HOLD]
[WITH RETURN]
[WITH scroll-mode]
[WITH ROWSET POSITIONING FOR max-rowsets]
[IF NO RECORDS FOUND instruction]
statement ...
{ END-SELECT
  LOOP }

```

Syntax 2 - Non-Cursor Selection

The SELECT SINGLE statement supports the functionality of a non-cursor selection (singleton SELECT); that is, a **select expression** that retrieves at most one row without using a cursor. It cannot be referenced by a **positioned UPDATE** or a **positioned DELETE** statement.

- Syntax 2 - Common Set

- Syntax 2 - Extended Set

Syntax 2 - Common Set

```
SELECT SINGLE  
selection into-clause table-expression  
[IF NO RECORDS FOUND instruction]  
statement ...  
{  
    END-SELECT  
    LOOP  
}
```

Syntax 2 - Extended Set

```
SELECT SINGLE  
selection into-clause table-expression  
[WITH isolation-level]  
[FETCH FIRST row-limit]  
[IF NO RECORDS FOUND instruction]  
statement ...  
{  
    END-SELECT  
    LOOP  
}
```

Syntax Element Description

This section alphabetically lists and explains the syntax items contained in the syntax diagrams of *Syntax 1 - Cursor-Oriented Selection* and *Syntax 2 - Non-Cursor Selection*:

- END-SELECT | LOOP
- FETCH FIRST row-limit
- IF NO RECORDS FOUND instruction
- into-clause
- OPTIMIZE FOR integer ROWS
- ORDER BY criteria
- QUERYNO Clause
- selection
- SKIP LOCKED DATA
- statement
- table-expression
- UNION | EXCEPT | INTERSECT Clause
- WITH_CTE common-table-expression

- WITH HOLD Clause
- WITH isolation-level
- WITH RETURN Clause
- WITH scroll-mode
- WITH ROWSET POSITIONING FOR max-rowsets

END-SELECT | LOOP

In structured mode, the Natural reserved keyword `END-SELECT` must be used to end the `SELECT` statement.

In reporting mode, the `LOOP` statement must be used to end the `SELECT` statement.

FETCH FIRST row-limit

```
FETCH FIRST [ 1 integer ] { ROW ROWS } ONLY
```

The `FETCH FIRST` clause limits the number of rows to be fetched. It improves the performance of queries with potentially large result sets if only a limited number of rows is needed.

IF NO RECORDS FOUND instruction



Note: This clause actually does not belong to Natural SQL; it represents Natural functionality which has been made available to SQL loop processing.

Structured Mode Syntax

```
IF NO [RECORDS] [FOUND]
{
    ENTER
    statement ...
}
END-NOREC
```

Reporting Mode Syntax

```
IF NO [RECORDS] [FOUND]
{
    ENTER
    statement
    DO statement ... DOEND
}
```

The `IF NO RECORDS FOUND` clause is used to initiate a processing loop if no records meet the selection criteria specified in the preceding `SELECT` statement.

If no records meet the specified selection criteria, the `IF NO RECORDS FOUND` clause causes the processing loop to be executed once with an “empty” record. If this is not desired, specify the statement `ESCAPE BOTTOM` within the `IF NO RECORDS FOUND` clause.

If one or more statements are specified with the `IF NO RECORDS FOUND` clause, the statements are executed immediately before the processing loop is entered. If no statements are to be executed before entering the loop, the keyword `ENTER` must be used.



Note: If the result set of the `SELECT` statement consists of a single row of `NULL` values, the `IF NO RECORDS FOUND` clause is not executed. This could occur if the selection list consists solely of one of the aggregate functions `SUM`, `AVG`, `MIN` or `MAX` on columns, and the set on which these aggregate functions operate is empty. When you use these aggregate functions in the above-mentioned way, you should therefore check the values of the corresponding null-indicator fields instead of using an `IF NO RECORDS FOUND` clause.

Database Values

Unless other value assignments are made in the statements accompanying an `IF NO RECORDS FOUND` clause, Natural resets to empty all database fields which reference the file specified in the current loop.

Evaluation of System Functions

Natural system functions are evaluated once for the empty record that is created for processing as a result of the `IF NO RECORDS FOUND` clause.

into-clause

```
INTO { parameter,...  
      VIEW { view-name [correlation-name] },... }
```

The `INTO` keyword introduces an `INTO` clause. This clause is used to specify the target fields in the program which are to be filled with the result of the selection.

The `INTO` clause can specify either single *parameters* or one or more views as defined in the `DEFINE DATA` statement.

All target field values can come either from a single table or from more than one table as a result of a join operation (see also [Join Queries](#)).



Note: In standard SQL syntax, an `INTO` clause is only used in non-cursor select operations (singleton `SELECT`) and can be specified only if a single row is to be selected. In Natural, however, the `INTO` clause is used for both cursor-oriented and non-cursor select operations.

The *selection* can also merely consist of an asterisk (*). In a standard [select expression](#), this is a shorthand for a list of all column names in the table(s) specified in the `FROM` clause. In the Natural `SELECT` statement, however, the same syntactical item `SELECT *` has a different semantic meaning:

all the items listed in the `INTO` clause are also used in the selection. Their names must correspond to names of existing database columns.

Syntax Element Description:

Syntax Element	Description
<i>parameter</i>	If single parameters are specified as target fields, their number and formats must correspond to the number and formats of the <i>columns</i> and/or <i>scalar-expressions</i> specified in the corresponding selection as described above (for details, see Scalar Expressions). See Example 5 .
<i>view-name</i>	The name a Natural view as defined in the <code>DEFINE DATA</code> statement. If one or more views are referenced in the <code>INTO</code> clause, the number of items specified in the <i>selection</i> must correspond to the number of fields defined in the view(s) (not counting group fields, redefining fields and indicator fields). Note: Both the Natural target fields and the table columns must be defined in a Natural DDM. Their names, however, can be different, since assignment is made according to their sequence. See Example 5 .
<i>correlation-name</i>	If the <code>VIEW</code> clause is used within a <code>SELECT *</code> construction where multiple tables are to be joined, <i>correlation-names</i> are required if the specified view contains fields that reference columns which exist in more than one of these tables. In order to know which column to select, all these columns are qualified by the specified <i>correlation-name</i> at generation of the selection list. The <i>correlation-name</i> assigned to a view must correspond to one of the <i>correlation-names</i> used to qualify the tables to be joined. See also the section Join Queries and Example 6 .

Examples

Example 1:

```
DEFINE DATA LOCAL
01 PERS VIEW OF SQL-PERSONNEL
  02 NAME
  02 AGE
END-DEFINE
...
SELECT *
  INTO NAME, AGE
```

Example 2:

```
...  
SELECT *  
  INTO VIEW PERS
```

These examples are equivalent to the following ones:

Example 3:

```
...  
SELECT NAME, AGE  
  INTO NAME, AGE
```

Example 4:

```
...  
SELECT NAME, AGE  
  INTO VIEW PERS
```

Example 5:

```
DEFINE DATA LOCAL  
01 PERS VIEW OF SQL-PERSONNEL  
   02 NAME  
   02 AGE  
END-DEFINE  
...  
SELECT FIRSTNAME, AGE  
  INTO VIEW PERS  
  FROM SQL-PERSONNEL  
...
```

The target fields **NAME** and **AGE**, which are part of a Natural view, receive the contents of the table columns **FIRSTNAME** and **AGE**.

Example 6:

```
DEFINE DATA LOCAL  
01 PERS VIEW OF SQL-PERSONNEL  
   02 NAME  
   02 FIRST-NAME  
   02 AGE  
END-DEFINE  
...  
SELECT *  
  INTO VIEW PERS A  
  FROM SQL-PERSONNEL A, SQL-PERSONNEL B  
...
```

OPTIMIZE FOR integer ROWS

OPTIMIZE FOR *integer* ROWS

The OPTIMIZE FOR *integer* ROWS clause is used to inform DB2 in advance of the number (*integer*) of rows to be retrieved from the result table. Without this clause, DB2 assumes that all rows of the result table are to be retrieved and optimizes accordingly.

This optional clause is useful if you know how many rows are likely to be selected, because optimizing for *integer* rows can improve performance if the number of rows actually selected does not exceed the *integer* value (which can be in the range from 0 to 2147483647).

Example

```
SELECT name INTO
#name FROM table WHERE AGE = 2 OPTIMIZE FOR 100 ROWS
```

ORDER BY criteria

ORDER BY { { *sort-key* [ASC] [DESC] } , ... }
 INPUT SEQUENCE
 ORDER OF *table-designator*

The ORDER BY clause arranges the result set of a SELECT statement in a particular sequence.

The result set can be ordered by *sort-key*, by INPUT SEQUENCE or by ORDER OF *table-designator*.

Syntax Element Description:

Syntax Element	Description
<i>sort-key</i>	You have the following options to specify a sort key: ■ Specify an integer number <i>n</i>. ■ Specify that the ordering is done by ordering the values of the <i>n</i>th column of the result set, or by giving a column name, specifying the ordering is done by ordering the values of the given column. ■ Specify a scalar expression, where specifying the ordering is done by ordering the values of the expression. The expression may consist of columns of the result set host variables and constants. If multiple sort keys exist, the rows are ordered by the first sort key; duplicate first sort keys are ordered by the second sort key, and so on.

Syntax Element	Description
	If a column name is specified in the sort key of a fullselect including a set operator (UNION, EXCEPT, INTERSECTION), it has to be unqualified.
ASC DESC	Specifies the sort order for the sort key: ascending (ASC) or descending (DESC). ASC is the default. See Example 2 .
INPUT-SEQUENCE	Indicates the result table reflects the input order of the rows specified in the VALUES clause of an INSERT statement.
ORDER OF <i>table-designator</i>	Specifies the result table rows should be ordered in the same way as the table designated by the <i>table-designator</i> . <i>table-designator</i> must also be specified in the FROM clause.

Examples

Example 1:

```

DEFINE DATA LOCAL
1 #NAME          (A20)
1 #YEARS-TO-WORK (I2)
END-DEFINE
...
SELECT NAME , 65 - AGE
      INTO #NAME, #YEARS-TO-WORK
      FROM SQL-PERSONNEL
      ORDER BY 2
      ...

```

Example 2:

```

DEFINE DATA LOCAL
1 PERS VIEW OF SQL-PERSONNEL
1 NAME
1 AGE
1 ADDRESS      (1:6)
END-DEFINE
...
SELECT NAME, AGE, ADDRESS
      INTO VIEW PERS
      FROM SQL-PERSONNEL
      WHERE AGE = 55
      ORDER BY NAME DESC
      ...

```


QUERYNO Clause

QUERYNO *integer*

The QUERYNO clause specifies the number to be used for this SQL statement in EXPLAIN output and trace records. The number is used as QUERYNO column in the PLAN_TABLE for the rows that contain information on this statement.

selection

See [Selection](#) in *Select Expressions*.

SKIP LOCKED DATA

SKIP LOCKED DATA

The SKIP LOCKED DATA clause specifies that rows are skipped when incompatible locks are held on the row by other transactions.

statement

The Natural statement(s) to be executed in the processing loop.

table-expression

See [table-expression](#) in *Select Expressions*.

UNION | EXCEPT | INTERSECT Clause

```
{ UNION
  EXCEPT
  INTERSECT } [ DISTINCT
                ALL ] [ (SELECT selection table-expression)
                       ] [ SELECT selection table-expression ] ...
```

UNION, EXCEPT and INTERSECT introduce a query that involves set operations.

Set operations combine the results of two or more *select-expressions*. The columns specified in the individual *select-expressions* must match in number, type and format.

The INTO clause must be specified with the first *select-expression* only.

Syntax Element Description:

Syntax Element	Description
UNION	Combines the results of two or more <i>select-expressions</i> .
EXCEPT	Specifies the difference set of the result sets of two <i>select-expressions</i> .
INTERSECT	Specifies the intersection of two result sets.
DISTINCT	Specifies that the result set does not contain redundant (duplicate) rows. DISTINCT is the default setting.
ALL	Specifies that the result set contains redundant (duplicate) rows. Redundant duplicate rows are eliminated from the result of a set operation unless the set operation explicitly includes the ALL qualifier.

Example

```

DEFINE DATA LOCAL
01 PERS VIEW OF SQL-PERSONNEL
   02 NAME
   02 AGE
   02 ADDRESS (1:6)
END-DEFINE
...
SELECT NAME, AGE, ADDRESS
  INTO VIEW PERS
  FROM SQL-PERSONNEL
  WHERE AGE > 55
UNION ALL
SELECT NAME, AGE, ADDRESS
  FROM SQL-EMPLOYEES
  WHERE PERSNR < 100
ORDER BY NAME
...
END-SELECT
...

```

WITH_CTE common-table-expression

```
WITH_CTE common-table-expression-name [(column-name,...)] AS (fullselect)
```

This clause allows you to define a result table which can be referenced in any FROM clause of the SELECT statement that follows.

Syntax Element Description:

Syntax Element	Description
WITH_CTE	The Natural specific keyword WITH_CTE corresponds to the SQL keyword WITH. WITH_CTE will be translated into the SQL keyword WITH by the Natural compiler.
<i>common-table-expression-name</i>	Has to be an unqualified SQL identifier and must be different from any other <i>common-table-expression-name</i> specified in the same statement. Multiple <i>common-table-expression</i> can be specified following the single WITH_CTE keyword. Each <i>common-table-expression-name</i> can be specified in the FROM clause of any <i>common-table-expression-name</i> following or in the FROM clause of the SELECT statement following.
<i>column-name</i>	Has to be an unqualified SQL identifier and must be unique within one <i>common-table-expression-name</i> .
AS (<i>fullselect</i>)	The number of <i>column-names</i> must match the number of columns of the <i>fullselect</i> .

A *common-table-expression* can be used

- in place of a view to avoid creating the view;
- when the same result table needs to be shared in a *fullselect*;
- when the result needs to be derived using recursion.

Queries using recursion are useful in applications such as bills of materials.

Example

```

WITH_CTE
RPL (PART,SUBPART,QUANTITY) AS
(SELECT ROOT.PART,ROOT.SUBPART,ROOT.QUANTITY
  FROM HGK-PARTLIST ROOT
  WHERE ROOT.PART ='01'
  UNION ALL
  SELECT CHILD.PART,CHILD.SUBPART,CHILD.QUANTITY
    FROM  RPL PARENT, HGK-PARTLIST CHILD
    WHERE PARENT.SUBPART = CHILD.PART
  )
SELECT DISTINCT PART,SUBPART,QUANTITY
  INTO VIEW V1
  FROM RPL
  ORDER BY PART,SUBPART,QUANTITY
END-SELECT

```

WITH HOLD Clause

WITH HOLD

The `WITH HOLD` clause is used to prevent cursors from being closed by a commit operation within database loops. If `WITH HOLD` is specified, a commit operation commits all the modifications of the current logical unit of work, but releases only locks that are not required to maintain the cursor. This optional clause is mainly useful in batch mode; it is ignored in CICS pseudo-conversational mode and in IMS message-driven programs.

Example

```
SELECT name INTO #name FROM table
WHERE AGE = 2 WITH HOLD
```

WITH isolation-level

WITH { CS
RR
RR KEEP UPDATE LOCK
RS
RS KEEP UPDATE LOCKS
UR }

This clause allows you to specify an explicit isolation level with which the statement is to be executed.

The following options are provided:

Option	Meaning
CS	Cursor Stability
RR	Repeatable Read
RR KEEP UPDATE LOCKS	Only applies to <i>Syntax 1 - Extended Set</i> and only if a positioned UPDATE or a positioned DELETE statement is processed with the SELECT statement. Repeatable Read and retaining update locks.
RS	Read Stability
RS KEEP UPDATE LOCKS	Only applies to <i>Syntax 1 - Extended Set</i> and only if a positioned UPDATE or a positioned DELETE statement is processed with the SELECT statement. Read Stability and retaining update locks.
UR	Uncommitted Read UR can only be specified within a SELECT statement and when the table is read-only. The default isolation level is determined by the isolation of the package

Option	Meaning
	or plan into which the statement is bound. The default isolation level also depends on whether the result table is read-only or not. To find out the default isolation level, refer to the IBM literature.

WITH RETURN Clause

WITH RETURN

The `WITH RETURN` clause is used to create result sets. Therefore, this clause only applies to programs which operate as Natural stored procedure. If the `WITH RETURN` clause is specified in a `SELECT` statement, the underlying cursor remains open when the associated processing loop is left, except when the processing loop had read all rows of the result set itself. During first execution of the processing loop, only the cursor is opened. The first row is not yet fetched. This allows the Natural program to return a full result set to the caller of the stored procedure. It is up to you to decide how many rows are processed by the Natural stored procedure and how many unprocessed rows of the result set are returned to the caller of the stored procedure. If you want to process rows of the select operation in the Natural stored procedure, you must define

```
IF *counter =1 ESCAPE TOP END-IF
```

in order to avoid processing of the first “empty row” in the processing loop. If you decide to terminate the processing of rows, you must define the following statement in the processing loop:

```
IF condition ESCAPE BOTTOM END-IF
```

If the program reads all rows of the result set, the cursor is closed and no result set is returned for this `SELECT WITH RETURN` to the caller of the stored procedure.

The following programs are examples for retrieving full result sets ([Example 1](#)) and partial result sets ([Example 2](#)).

Examples

Example 1:

```
DEFINE DATA LOCAL
. . .
END DEFINE
*
* Return all rows of the result set
*
SELECT * INTO VIEW V2
        FROM SYSIBM-SYSROUTINES
        WHERE RESULT_SETS > 0
        WITH RETURN
ESCAPE BOTTOM
```

```
END-SELECT
END
```

Example 2:

```
DEFINE DATA LOCAL
. . .
END DEFINE
*
* Read the first two rows and return the rest as result set
*
SELECT * INTO VIEW V2
        FROM SYSIBM-SYSROUTINES
        WHERE RESULT_SETS > 0
        WITH RETURN
WRITE PROCEDURE *COUNTER
IF *COUNTER = 1 ESCAPE TOP END-IF
IF *COUNTER = 3 ESCAPE BOTTOM END-IF
END-SELECT
END
```

WITH scroll-mode

WITH	$\left\{ \begin{array}{l} \text{ASENSITIVE SCROLL} \\ \text{INSENSITIVE SCROLL} \\ \text{SENSITIVE STATIC SCROLL} \\ \text{SENSITIVE DYNAMIC SCROLL} \end{array} \right\}$	<code>[:] <i>scroll_hv</i> [GIVING [:] <i>sqlcode</i>]</code>

Natural for DB2 supports DB2 scrollable cursors by using the clauses WITH ASENSITIVE SCROLL, WITH SENSITIVE STATIC SCROLL and SENSITIVE DYNAMIC SCROLL. Scrollable cursors allow Natural for DB2 applications to position randomly any row in a result set. With non-scrollable cursors, the data can only be read sequentially, from top to bottom.

DB2 scrollable cursors are enabled with this clause. Scrollable cursors can be ASENSITIVE, INSENSITIVE, SENSITIVE STATIC or SENSITIVE DYNAMIC.

Scrollable cursors allow the application to position any row in the cursor at any time as long as the cursor is open.

The positioning is performed depending on the content of the *scroll_hv*. The content is evaluated each time a FETCH against DB2 is executed.

Syntax Element Description:

Syntax Element	Description
ASENSITIVE SCROLL	Specifies that the cursor is either INSENSITIVE or SENSITIVE DYNAMIC. This is determined by DB2 at open time of the cursor, depending on the read-only property of the cursor: If the cursor is read-only, the cursor will become INSENSITIVE. If the cursor is not read-only, the cursor will become SENSITIVE DYNAMIC.
INSENSITIVE SCROLL	Specifies that the cursor is insensitive for updates, deletes and inserts executed against the base table, after the cursor has been updated. INSENSITIVE SCROLL refers to a cursor that cannot be used in Positioned UPDATE or Positioned DELETE operations. In addition, once opened, an INSENSITIVE SCROLL cursor does not reflect UPDATE, DELETE or INSERT operations against the base table after the cursor was opened. See also Note.
SENSITIVE STATIC SCROLL	Specifies that the cursor is sensitive for updates and deletes against the base table, but not against inserts, after the cursor has been opened. SENSITIVE STATIC SCROLL refers to a cursor that can be used for Positioned UPDATE or Positioned DELETE operations. In addition, a SENSITIVE STATIC SCROLL cursor reflects UPDATE and DELETE operations of base table rows. The cursor does not reflect INSERT operations. See also Note.
SENSITIVE DYNAMIC SCROLL	SENSITIVE DYNAMIC specifies that the cursor is sensitive for updates, deletes and inserts against the base table, after the cursor has been opened. SENSITIVE DYNAMIC scrollable cursors reflect UPDATE, DELETE and INSERT operations against the base table while the cursor is open.



Note: INSENSITIVE and SENSITIVE STATIC scrollable cursors use temporary result tables and require a TEMP database in DB2 (see the relevant DB2 literature by IBM).

scroll_hv

The variable *scroll_hv* must be alphanumeric.

The variable *scroll_hv* specifies which row of the result table will be fetched during one execution of the database processing loop. Additionally, it specifies the sensitivity of UPDATES or DELETES against the base table row during a FETCH operation. The content of *scroll_hv* is evaluated each time the database processing loop cycle is executed.

$\left[\begin{array}{c} \text{INSENSITIVE} \\ \text{SENSITIVE} \end{array} \right]$	$\left\{ \begin{array}{l} \text{AFTER} \\ \text{BEFORE} \\ \text{CURRENT} \\ \text{FIRST} \\ \text{LAST} \\ \text{PRIOR} \\ \text{NEXT} \end{array} \right\}$
	$\left\{ \begin{array}{l} \text{ABSOLUTE} \\ \text{RELATIVE} \end{array} \right\} \left[\begin{array}{c} + \\ - \end{array} \right] \text{integer}$

scroll_hv Sensitivity Specification

The specification of the sensitivity `INSENSITIVE` or `SENSITIVE` is optional.

- If it is omitted from a `FETCH` against an `INSENSITIVE SCROLL` cursor, the default will be `INSENSITIVE`.
- If it is omitted from a `FETCH` against a `SENSITIVE STATIC/DYNAMIC SCROLL` cursor, the default will be `SENSITIVE`.

The sensitivity specifies whether or not the rows in the base table are checked when performing a `FETCH` operation for a scrollable cursor.

- If the corresponding base table column qualifies for the `WHERE` clause and has not been deleted, a `SENSITIVE FETCH` will return the row of the base table.
- If the corresponding base table column does not qualify for the `WHERE` clause or has not been deleted, a `SENSITIVE FETCH` will return an `UPDATE hole` or a `DELETE hole state` (SQLCODE +222).

An `INSENSITIVE FETCH` will not check the corresponding base table column.

scroll_hv Options

Below is an explanation of the options available to determine the row(s) to fetch, the position from where to start the fetch and/or the direction in which to scroll:

Option	Explanation
AFTER	Positions after the last row. No row is fetched.
BEFORE	Positions before the first. No row is fetched.
CURRENT	Fetches the current row (again).
FIRST	Fetches the first row.
LAST	Fetches the last row.
NEXT	Fetches the row after the current one. This is the default value.
PRIOR	Fetch the row before the current one.
+ - integer	Only applies in connection with <code>ABSOLUTE</code> or <code>RELATIVE</code> . Specifies the position of the row to be fetched <code>ABSOLUTE</code> or <code>RELATIVE</code> .

Option	Explanation
	Enter a plus (+) or minus (-) sign followed by an integer. The default value is a plus (+).
ABSOLUTE	Only applies in connection with <code>+ - integer</code> . Uses <i>integer</i> as the absolute position within the result set from where the row is fetched. See the DB2 SQL reference by IBM about further details regarding positive and negative position numbers.
RELATIVE	Only applies in connection with <code>+ - integer</code> . Uses <i>integer</i> as the relative position to the current position within the result set from where the row is fetched. See the DB2 SQL reference by IBM about further details regarding positive and negative position numbers.

GIVING [:] *sqlcode*

The specification of **GIVING [:] *sqlcode*** is optional. If specified, the Natural variable [:] *sqlcode* must be of format I4. The values for this variable are returned from the DB2 SQLCODE of the underlying **FETCH** operation. This allows the application to react to different statuses encountered while the scrollable cursor is open. The most important status codes indicated by SQLCODE are listed in the following table:

SQLCODE	Explanation
0	FETCH operation successful, data returned except for FETCH with option BEFORE or AFTER .
+100	Row not found, cursor still open, no data returned.
+222	UPDATE or DELETE hole, cursor still open, no data returned. The corresponding row of the base table has been updated or deleted, so that the row no longer qualifies for the WHERE clause.
+231	Fetch operation with the option CURRENT , but cursor not positioned on any row, no data returned. This occurs if the previous FETCH returned SQLCODE +100.

If you specify **GIVING [:] *sqlcode***, the application must react to the different statuses. If an SQLCODE +100 is entered five times successively and without terminal I/O, the Natural for DB2 runtime will issue Natural error NAT3296 in order to avoid application looping. The application can terminate the processing loop by executing an **ESCAPE** statement.

If you do not specify **GIVING [:] *sqlcode***, except for SQLCODE 0 and SQLCODE +100, each SQLCODE will generate Natural error NAT3700 and the processing loop will be terminated. SQLCODE +100 (row not found) will terminate the processing loop.

See also the example program **DEM2SCRL** supplied in the Natural system library **SYSD2**.

WITH ROWSET POSITIONING FOR max-rowsets

```
WITH ROWSET POSITIONING FOR { [:] row_hv } ROWS [ ROWS_RETURNED [:] ret_row ]
```

This clause enables DB2 rowset processing, which corresponds to Natural native DML multi-fetch processing. `[:]` *row_hv* (I4) or *integer* determines the maximum number of rows returned from DB2 to Natural. The number determines either the size of the Natural multi-fetch buffer used for standard multiple row processing or the maximum number of rows returned from DB2 into the Natural program for advanced multiple row processing.

ROWS_RETURNED [:] *ret_row* Clause:

This clause specifies an I4 variable which will receive the number of rows returned by DB2 on behalf of the last executed DB2 fetch operation for advanced multiple row processing.

Join Queries

A join is a query in which data is retrieved from more than one table. All the tables involved must be specified in the `FROM` clause.

A join always forms the Cartesian product of the tables listed in the `FROM` clause and later eliminates from this Cartesian product table all the rows that do not satisfy the join condition specified in the `WHERE` clause.

Correlation names can be used to save writing if table names are rather long. Correlation names must be used when a column specified in the selection list exists in more than one of the tables to be joined in order to know which of the identically named columns to select.


Example

```
DEFINE DATA LOCAL
1 #NAME      (A20)
1 #MONEY     (I4)
END-DEFINE
...
SELECT NAME, ACCOUNT
  INTO #NAME, #MONEY
  FROM  SQL-PERSONNEL P, SQL-FINANCE F
  WHERE P.PERSNR = F.PERSNR
        AND F.ACCOUNT > 10000
  ...
```

127

SEND METHOD

■ Function	998
■ Syntax Description	998
■ Example	1001

[RETURN *operand4*][GIVING *operand5*]

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [CREATE OBJECT](#) | [DEFINE CLASS](#) | [INTERFACE](#) | [METHOD](#) | [PROPERTY](#)

Belongs to Function Group: [Component Based Programming](#)

Function

The `SEND METHOD` statement is used to invoke a particular method of an object.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats															Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S				A															yes	no
<i>operand2</i>		S																	O		no	no
<i>operand3</i>	C	S	A	G		A	U	N	P	I	F	B	D	T	L	C	G	O			yes	no
<i>operand4</i>		S	A			A	U	N	P	I	F	B	D	T	L	C	G	O			yes	no
<i>operand5</i>		S			N					I											yes	no

The formats C and G can only be passed to methods of local classes.

Syntax Element Description:


Syntax Element	Description
<i>operand1</i>	Method-Name: <i>operand1</i> is the name of a method which is supported by the object specified in <i>operand2</i>. Since the method names can be identical in different interfaces of a class, the method name in <i>operand1</i> can also be qualified with the interface name to avoid ambiguity. In the following example, the object #03 has an interface <i>Iterate</i> with the method <i>Start</i>. The following statements apply: <pre>* Specifying only the method name. SEND 'Start' TO #03 * Qualifying the method name with the interface name. SEND 'Iterate.Start' TO #03</pre> If no interface name is specified, Natural searches the method name in all the interfaces of the class. If the method name is found in more than one interface, a runtime error occurs.
<i>operand2</i>	Object Handle: The handle of the object to which the method call is to be sent. <i>operand2</i> must be defined as an object handle (HANDLE OF OBJECT). The object must already exist. To invoke a method of the current object inside a method, use the system variable *THIS-OBJECT.
<i>operand3</i>	Parameter(s) Specific to the Method: As <i>operand3</i> you can specify parameters specific to the method. In the following example, the object #03 has the method <i>PositionTo</i> with the parameter <i>Pos</i>. The method is called in the following way: <pre>SEND 'PositionTo' TO #03 WITH Pos</pre> Methods can have optional parameters. Optional parameters need not to be specified when the method is called. To omit an optional parameter, use the placeholder 1X. To omit <i>n</i> optional parameters, use the placeholder <i>nX</i>. In the following example, the method <i>SetAddress</i> of the object #04 has the parameters <i>FirstName</i>, <i>MiddleInitial</i>, <i>LastName</i>, <i>Street</i> and <i>City</i>, where <i>MiddleInitial</i>, <i>Street</i> and <i>City</i> are optional. The following statements apply:

Syntax Element	Description						
	* Specifying all parameters. SEND 'SetAddress' TO #04 WITH FirstName MiddleInitial LastName Street City * Omitting one optional parameter. SEND 'SetAddress' TO #04 WITH FirstName 1X LastName Street City * Omitting all optional parameters. SEND 'SetAddress' TO #04 WITH FirstName 1X LastName 2X Omitting a non-optional (mandatory) parameter results in a runtime error.						
AD=	Attribute Definition: If <i>operand3</i> is a variable, you can mark it in one of the following ways: <table> <tr> <td>AD=0</td><td>Non-modifiable, see session parameter AD=0.</td></tr> <tr> <td>AD=M</td><td>Modifiable, see session parameter AD=M. This is the default setting.</td></tr> <tr> <td>AD=A</td><td>Input only, see session parameter AD=A.</td></tr> </table> If <i>operand3</i> is a constant, AD cannot be explicitly specified. For constants AD=0 always applies.	AD=0	Non-modifiable, see session parameter AD=0.	AD=M	Modifiable, see session parameter AD=M. This is the default setting.	AD=A	Input only, see session parameter AD=A.
AD=0	Non-modifiable, see session parameter AD=0.						
AD=M	Modifiable, see session parameter AD=M. This is the default setting.						
AD=A	Input only, see session parameter AD=A.						
<i>nX</i>	Parameter(s) to be Skipped: With the notation <i>nX</i> you can specify that the next <i>n</i> parameters are to be skipped (for example, 1X to skip the next parameter, or 3X to skip the next three parameters). This means that for the next <i>n</i> parameters no values are passed to the method. For a method implemented in Natural, a parameter that is to be skipped must be defined with the keyword OPTIONAL in the dialog's DEFINE DATA PARAMETER statement. OPTIONAL means that a value can - but need not - be passed from the invoking object to such a parameter.						
RETURN <i>operand4</i>	RETURN Clause: If the RETURN clause is omitted and the method has a return value, the return value is discarded. If the RETURN clause is specified, <i>operand4</i> contains the return value of the method. If the method execution fails, <i>operand4</i> is reset to its initial value. Note: For classes written in Natural, the return value of a method is defined by entering one additional parameter in the parameter data area of the method and by marking it with BY VALUE RESULT. For more information, see the PARAMETER clause in the INTERFACE statement description. Therefore, the parameter data area of a method that is written in Natural and that has a return value always contains one additional field next to the method parameters. This is to be considered when you call a method of a Natural written class and want to use the parameter data area of the method in the SEND statement.						
GIVING <i>operand5</i>	GIVING Clause: If the GIVING clause is not specified, the Natural run time error processing is triggered if an error occurs.						

Syntax Element	Description
	If the <code>GIVING</code> clause is specified, <i>operand5</i> contains the Natural message number if an error occurred, or zero on success.

Example

The following diagram gives an overview of the Natural objects that are used in this example. The corresponding source code and the program output are shown below.



Program METH01 - CREATE OBJECT and SEND METHOD Using a Class and Several Methods:

```

** Example 'METH01':  CREATE OBJECT and SEND METHOD
**                    using a class and several methods (see METH*)
*****
DEFINE DATA
LOCAL
    USING METHA
LOCAL
1 L-STUDENT HANDLE OF OBJECT
1 #NAME      (A20)
1 #STREET    (A20)
1 #CITY      (A20)
1 #SUM       (I4)
1 #MULTI     (I4)
END-DEFINE
*
CREATE OBJECT L-STUDENT OF CLASS 'STUDENTS' /* see METHCL for class
*
L-STUDENT.<> := 'John Smith'
*
SEND METHOD 'INIT' TO L-STUDENT              /* see METHCL
    WITH #VAR1 #VAR2 #VAR3 #VAR4
*
SEND METHOD 'SUMMATION' TO L-STUDENT          /* see METHCL
    WITH #VAR1 #VAR2 #VAR3 #VAR4
*
SEND METHOD 'MULTIPLICATION' TO L-STUDENT    /* see METHCL
    WITH #VAR1 #VAR2 #VAR3 #VAR4
*
#NAME      := L-STUDENT.<>
#SUM       := L-STUDENT.<>
#MULTI     := L-STUDENT.<>
*
SEND METHOD 'ADDRESS' TO L-STUDENT           /* see METHCL
*
#STREET    := L-STUDENT.<>
#CITY      := L-STUDENT.<>
*
*
WRITE 'Name      :' #NAME
WRITE 'Street:' #STREET
WRITE 'City      :' #CITY
WRITE ' '
WRITE 'The summation of      ' #VAR1 #VAR2 #VAR3 #VAR4
WRITE 'is' #SUM
WRITE 'The multiplication of' #VAR1 #VAR2 #VAR3 #VAR4
WRITE 'is' #MULTI
*
END

```

Class Definition METHCL Used by METH01:

```
** Example 'METHCL': DEFINE CLASS (used by METH01)
*****
* Defining class STUDENTS for METH01
*
DEFINE CLASS STUDENTS
  OBJECT
    USING METH0                      /* Object data for class STUDENTS
  /*
  INTERFACE STUDENT-ARITHMETICS
    PROPERTY FULL-NAME
      IS NAME
    END-PROPERTY
    PROPERTY SUM
    END-PROPERTY
    PROPERTY MULTI
    END-PROPERTY
  *
    METHOD INIT
      IS METH02
      PARAMETER USING METHA
    END-METHOD
    METHOD SUMMATION
      IS METH03
      PARAMETER USING METHA
    END-METHOD
    METHOD MULTIPLICATION
      IS METH04
      PARAMETER USING METHA
    END-METHOD
  END-INTERFACE
*
  INTERFACE STUDENT-ADDRESS
    PROPERTY STUDENT-NAME
      IS NAME
    END-PROPERTY
    PROPERTY STREET
    END-PROPERTY
    PROPERTY CITY
    END-PROPERTY
  *
    METHOD ADDRESS
      IS METH05
    END-METHOD
  END-INTERFACE
END-CLASS
END
```

Local Data Area METHO (object data) Used by Class METHCL and Subprograms METH02, METH03, METH04 and METH05:

Local	METHO	Library	SYSEXSYN	DBID	10	FNR	32
Command							> +
I	T	L	Name	F	Length	Miscellaneous	
All	--		-----	-	-----	-----	-->
	1		NAME	A	20		
	1		STREET	A	30		
	1		CITY	A	20		
	1		SUM	I	4		
	1		MULTI	I	4		

Parameter Data Area METHA Used by Program METH01, Class METHCL and Subprograms METH02, METH03 and METH04:

Parameter	METHA	Library	SYSEXSYN	DBID	10	FNR	32
Command							> +
I	T	L	Name	F	Length	Miscellaneous	
All	--		-----	-	-----	-----	-->
	1		#VAR1	I	4		
	1		#VAR2	I	4		
	1		#VAR3	I	4		
	1		#VAR4	I	4		

Subprogram METH02 - Method INIT Used by Program METH01:

```

** Example 'METH02': Method INIT (used by METH01)
*****
DEFINE DATA
PARAMETER
  USING METHA
OBJECT
  USING METHO
END-DEFINE
*
* Method INIT of class STUDENTS
*
#VAR1 := 1
#VAR2 := 2
#VAR3 := 3
#VAR4 := 4
*
END

```

Subprogram METH03 - Method SUMMATION Used by Program METH01:

```
** Example 'METH03': Method SUMMATION (used by METH01)
*****
DEFINE DATA
PARAMETER
    USING METHA
OBJECT
    USING METHO
END-DEFINE
*
* Method SUMMATION of class STUDENTS
*
COMPUTE SUM = #VAR1 + #VAR2 + #VAR3 + #VAR4
END
```

Subprogram METH04 - Method MULTIPLICATION Used by Program METH01:

```
** Example 'METH04': Method MULTIPLICATION (used by METH01)
*****
DEFINE DATA
PARAMETER
    USING METHA
OBJECT
    USING METHO
END-DEFINE
*
* Method MULTIPLICATION of class STUDENTS
*
COMPUTE MULTI = #VAR1 * #VAR2 * #VAR3 * #VAR4
END
```

Subprogram METH05 - Method ADDRESS Used by Program METH01:

```
** Example 'METH05': Method ADDRESS (used by METH01)
*****
DEFINE DATA
    OBJECT USING METHO
END-DEFINE
*
* Method ADDRESS of class STUDENTS
*
IF NAME = 'John Smith'
    STREET := 'Oxford street'
    CITY   := 'London'
END-IF
END
```

Output of Program METH01:

Page 1 05-01-17 15:59:04


Name : John Smith
Street: Oxford street
City : London

The summation of	1	2	3	4
is 10				
The multiplication of	1	2	3	4
is 24				

128

SEPARATE

■ Function	1010
■ Syntax Description	1010
■ Rules and Operational Considerations	1014
■ Examples	1016



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [COMPRESS](#) | [COMPUTE](#) | [EXAMINE](#) | [MOVE](#) | [MOVE ALL](#) | [RESET](#)

Belongs to Function Group: [Arithmetic and Data Movement Operations](#)

Function

The `SEPARATE` statement is used to separate the content of an alphanumeric or binary operand into two or more alphanumeric or binary operands (or into multiple occurrences of an alphanumeric or binary array).

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
operand1	C	S	A			A	U					B				yes	no
operand2	C	S						N	P	I		B*				yes	no
operand3	C	S						N	P	I		B*				yes	no
operand4		S	A	G		A	U					B				yes	yes
operand5		S				A	U					B				yes	yes
operand6	C	S				A	U					B				yes	no
operand7		S						N	P	I						yes	yes

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand8</i>	C	S						N	P	I							yes	no
<i>operand9</i>		S						N	P	I							yes	yes

* Format B of *operand2* and *operand3* may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Source Operand: <i>operand1</i> is the alphanumeric/binary constant or variable whose content is to be separated. Trailing blanks in <i>operand1</i> are removed before the value is processed (even if the blank is used as a delimiter character; see also the DELIMITERS option).
SUBSTRING	SUBSTRING Option: Normally, the whole content of a field is separated, starting from the beginning of the field. The SUBSTRING option allows you to separate only a certain part of the field. After the field name (<i>operand1</i>) in the SUBSTRING clause you specify first the starting position (<i>operand2</i>) and then the length (<i>operand3</i>) of the field portion to be separated. For example, if a field #A contained CONTRAPTION, SUBSTRING(#A, 5, 3) would contain RAP. Note: If you omit <i>operand2</i>, the starting position is assumed to be 1. If you omit <i>operand3</i>, the length is assumed to be from the starting position to the end of the field.
STARTING FROM POSITION <i>operand8</i>	STARTING FROM POSITION Option: This option determines the starting position for the source operand (<i>operand1</i>) to be separated. For details, see Defining Ranges for STARTING POSITION.
LEFT JUSTIFIED	LEFT JUSTIFIED Option: This option causes leading blanks which may occur between the delimiter character and the next non-blank character to be removed from the target operand.
<i>operand4</i>	Target Operand: <i>operand4</i> represents the target operands. If an array is specified as target operand, it is filled occurrence by occurrence with the separated values. The number of target operands corresponds to the number of delimiter characters (including trailing delimiter characters) in <i>operand1</i>, plus 1.

Syntax Element	Description
	If <i>operand4</i> is a dynamic variable, its length may be modified by the SEPARATE operation. The current length of a dynamic variable can be ascertained by using the system variable *LENGTH. For general information on dynamic variables, see the section <i>Using Dynamic and Large Variables</i>.
IGNORE / REMAINDER <i>operand5</i>	IGNORE / REMAINDER Options: If you do not specify enough target fields for the source value to be separated into, you will receive an appropriate error message. To avoid this, you have two options: ■ IGNORE Option: If you specify IGNORE, Natural will ignore it if there are not enough target operands to receive the source value. ■ REMAINDER Option: If you specify REMAINDER <i>operand5</i>, that section of the source value which could not be placed into target operands will be placed into <i>operand5</i>. You may then use the content of <i>operand5</i> for further processing, for example in a subsequent SEPARATE statement. REMAINDER can only be used for single-value source operands. For array source operands, use the REMAINDER POSITION option. See also Rules and Operational Considerations and Example 3.
REMAINDER POSITION <i>operand9</i>	REMAINDER POSITION Option: The value returned by the REMAINDER POSITION clause corresponds to the position from which a REMAINDER data field is filled. For details, see Rules and Operational Considerations.
DELIMITERS	DELIMITERS Option: See DELIMITERS Option below.
RETAINED	RETAINED Option: Normally, the delimiter characters themselves are not moved into the target operands. When you specify RETAINED, however, each delimiter (that is, either default delimiters and blanks, or the delimiter specified with <i>operand6</i>) will also be placed into a target operand. Example: The following SEPARATE statement would place 150 into #B, + into #C, and 30 into #D:

Syntax Element	Description
	<pre>... MOVE '150+30' TO #A SEPARATE #A INTO #B #C #D WITH RETAINED DELIMITER '+' ...</pre> See also Example 3.
GIVING NUMBER <i>operand7</i>	GIVING NUMBER Option: This option causes the number of filled target operands (including those filled with blanks) to be returned in <i>operand7</i>. The number actually obtained is the number of delimiters plus 1. If you use the IGNORE Option, the maximum possible number returned in <i>operand7</i> will be the number of target operands (<i>operand4</i>). If you use the REMAINDER Option, the maximum possible number returned in <i>operand7</i> will be the number of target operands (<i>operand4</i>) plus 1 (for <i>operand5</i>).

DELIMITERS Option:

Delimiter characters within *operand1* indicate the positions at which the value is to be separated.

Syntax Element Description:

Syntax Element	Description
WITH [ANY] DELIMITERS	If you omit the DELIMITERS option or specify WITH ANY DELIMITERS, a blank and any character which is neither a letter nor a numeric character will be treated as delimiter character. The definition of delimiters may be modified using the SCTAB profile parameter.
WITH INPUT DELIMITERS	Indicates that the blank and the default input delimiter character (as specified with the session parameter ID) are to be used as delimiter character.
WITH DELIMITERS <i>operand6</i>	Indicates that each of the characters specified in <i>operand6</i> is to be treated as delimiter character. If <i>operand6</i> contains trailing blanks, these will be ignored.

Rules and Operational Considerations

- Processing of Source and Target Operands
- Defining Ranges for STARTING FROM POSITION
- Values Returned by REMAINDER POSITION
- Overlapping Fields: REMAINDER and REMAINDER POSITION
- Delimiters in SEPARATE

Processing of Source and Target Operands

Trailing blanks are ignored in source operands (in single values and array occurrences as well) when the separation process starts. Trailing blanks only count when the REMAINDER POSITION value is calculated: see also *Values Returned by REMAINDER POSITION*.

If the source operand (*operand1*) is an empty dynamic field (*LENGTH=0) or an X-array that is not expanded, the SEPARATE statement stops executing after resetting the following fields:

- all target operands (*operand4*);
- the field (*operand7*) returning the number of filled target operands;
- the REMAINDER data field (*operand5*);
- the REMAINDER POSITION field (*operand9*)

The same applies if the source operand contains only blanks.

Defining Ranges for STARTING FROM POSITION

The value range allowed for the STARTING FROM POSITION clause *operand8* is 1 : *n* where *n* is the last byte of the source field.

If the source operand (*operand1*) is an array, all occurrences are counted, including trailing blanks. For a dynamic array, the length of each individual field is counted, up to the specified position.

Examples of *operand8*:

Position 63 in #A (A100)	is the 63rd char in #A.
Position 63 in #B (A20/1:10)	is the 3rd char in #B(4).
Position 63 in #C (A10/1:3,1:4)	is the 3rd char in #C(2,3).
Position 63 in #D (1:5) DYNAMIC with *LENGTH(#D(*)) = (15,25,0,33,61)	is the 23rd char in #D(4).

If you specify an invalid range (a negative or zero value, or a value greater than the actual field length), the return fields listed in *Processing of Source and Target Operands* are reset, but no

runtime error occurs. Since the `STARTING FROM` value denotes a position (and not an offset), *operand8* requires a minimum value of 1 for the first execution.

Values Returned by REMAINDER POSITION

The value returned by the `REMAINDER POSITION` clause corresponds to the position from which a `REMAINDER` data field is filled.

Example:

```
...  
SEPARATE 'AB CD' INTO #A REMAINDER #R  
...
```

The above statement returns `#A= 'AB'` and `#R= ' CD'` as the `REMAINDER` starts after the separator character (here: a blank), right after `AB`. With the `REMAINDER POSITION` option used instead, a value of 4 would be returned.

Although trailing blanks are ignored during the separation process, they are taken into account for the calculation of the `REMAINDER POSITION` value in occurrences of a source array.

If all source segments are processed and the end of the source field is reached, `REMAINDER POSITION` returns a value of zero indicating “no more data”.

See also [Example 6 - Using a Source Array with *STARTING FROM* and *REMAINDER POSITION*](#).

Overlapping Fields: REMAINDER and REMAINDER POSITION

When the `SEPARATE` statement is executed, the source data (*operand1*) is usually copied and processed from a work field. Therefore, the `REMAINDER` result is independent of possibly overlapping source and result fields.

Such field backup copies are not produced if a `REMAINDER POSITION` clause is used. The complete separation process operates on the original source operand, regardless of whether you separate the source and target operands. Overlapping operands are neither rejected during compilation nor execution but can cause undesired results.

Delimiters in SEPARATE

When you separate a single-value field, the field border always delimits the last word. The same applies to each occurrence of an array field.

If the `RETAINED DELIMITERS` option is used, delimiters are also placed into the target field. This only applies to delimiter characters within an array occurrence, and not to consecutive array occurrences that are automatically delimited (without delimiter character) when an occurrence ends.

See also [Example 4 - Using a Source Array of a Redefined String](#) and [Example 5 - Using a Source Array with `RETAINED Delimiters`](#).

Examples

- [Example 1 - Various Samples](#)
- [Example 2 - Using an Array](#)
- [Example 3 - Using `REMAINDER/RETAINED` Options](#)
- [Example 4 - Using a Source Array of a Redefined String](#)
- [Example 5 - Using a Source Array with `RETAINED Delimiters`](#)
- [Example 6 - Using a Source Array with `STARTING FROM` and `REMAINDER POSITION`](#)

Example 1 - Various Samples

```
** Example 'SEPEX1': SEPARATE
*****
DEFINE DATA LOCAL
1 #TEXT1   (A6) INIT <'AAABBB'>
1 #TEXT2   (A7) INIT <'AAA BBB'>
1 #TEXT3   (A7) INIT <'AAA-BBB'>
1 #TEXT4   (A7) INIT <'A.B/C,D'>
1 #FIELD1A (A6)
1 #FIELD1B (A6)
1 #FIELD2A (A3)
1 #FIELD2B (A3)
1 #FIELD3A (A3)
1 #FIELD3B (A3)
1 #FIELD4A (A3)
1 #FIELD4B (A3)
1 #FIELD4C (A3)
1 #FIELD4D (A3)
1 #NBT     (N1)
1 #DEL     (A5)
END-DEFINE
*
WRITE NOTITLE 'EXAMPLE A (SOURCE HAS NO BLANKS)'
SEPARATE #TEXT1 INTO #FIELD1A #FIELD1B GIVING NUMBER #NBT
```

```

WRITE      / '=' #TEXT1 5X '=' #FIELD1A 4X '=' #FIELD1B 4X '=' #NBT
*
WRITE NOTITLE /// 'EXAMPLE B (SOURCE HAS EMBEDDED BLANK)'
SEPARATE #TEXT2 INTO #FIELD2A #FIELD2B GIVING NUMBER #NBT
WRITE      / '=' #TEXT2 4X '=' #FIELD2A 7X '=' #FIELD2B 7X '=' #NBT
*
WRITE NOTITLE /// 'EXAMPLE C (USING DELIMITER '-'')'
SEPARATE #TEXT3 INTO #FIELD3A #FIELD3B WITH DELIMITER '-'
WRITE      /      '=' #TEXT3 4X '=' #FIELD3A 7X '=' #FIELD3B
*
MOVE ',/' TO #DEL
WRITE NOTITLE /// 'EXAMPLE D USING DELIMITER' '=' #DEL
*
SEPARATE #TEXT4 INTO #FIELD4A #FIELD4B
                #FIELD4C #FIELD4D WITH DELIMITER #DEL
WRITE      /      '=' #TEXT4 4X '=' #FIELD4A 7X '=' #FIELD4B
                /                  19X '=' #FIELD4C 7X '=' #FIELD4D
*
END

```

Output of Program SEPEX1:

EXAMPLE A (SOURCE HAS NO BLANKS)

```
#TEXT1: AAABBB      #FIELD1A: AAABBB      #FIELD1B:          #NBT:  1
```

EXAMPLE B (SOURCE HAS EMBEDDED BLANK)

```
#TEXT2: AAA BBB      #FIELD2A: AAA          #FIELD2B: BBB          #NBT:  2
```

EXAMPLE C (USING DELIMITER '-'')

```
#TEXT3: AAA-BBB      #FIELD3A: AAA          #FIELD3B: BBB
```

EXAMPLE D USING DELIMITER #DEL: ,/

```
#TEXT4: A.B/C,D      #FIELD4A: A.B          #FIELD4B: C
                #FIELD4C: D          #FIELD4D:
```

Example 2 - Using an Array

```
** Example 'SEPEX2': SEPARATE (using array variable)
*****
DEFINE DATA LOCAL
1 #INPUT-LINE (A60) INIT <'VALUE1,  VALUE2,VALUE3'>
1 #FIELD      (A20/1:5)
1 #NUMBER     (N2)
END-DEFINE
*
SEPARATE #INPUT-LINE LEFT JUSTIFIED INTO #FIELD (1:5)
          GIVING NUMBER IN #NUMBER
*
WRITE NOTITLE #INPUT-LINE //
              #FIELD (1)  /
              #FIELD (2)  /
              #FIELD (3)  /
              #FIELD (4)  /
              #FIELD (5)  /
              #NUMBER
*
END
```

Output of Program SEPEX2:

```
VALUE1,  VALUE2,VALUE3

VALUE1
VALUE2
VALUE3

3
```

Example 3 - Using REMAINDER/RETAINED Options

```
** Example 'SEPEX3': SEPARATE (with REMAINDER, RETAIN option)
*****
DEFINE DATA LOCAL
1 #INPUT-LINE (A60) INIT <'VAL1,  VAL2, VAL3,VAL4'>
1 #FIELD      (A10/1:4)
1 #REM        (A30)
END-DEFINE
*
WRITE TITLE LEFT 'INP:' #INPUT-LINE /
              '#FIELD (1)' 13T '#FIELD (2)' 25T '#FIELD (3)'
              37T '#FIELD (4)' 49T 'REMAINDER'
              /  '-----' 13T '-----' 25T '-----'
              37T '-----' 49T '-----'
*
```



```

SEPARATE #INPUT-LINE INTO #FIELD (1:2)
      REMAINDER #REM WITH DELIMITERS ',',
WRITE #FIELD(1) 13T #FIELD(2) 25T #FIELD(3) 37T #FIELD(4) 49T #REM
*
RESET #FIELD(*) #REM
SEPARATE #INPUT-LINE INTO #FIELD (1:2)
      IGNORE WITH DELIMITERS ',',
WRITE #FIELD(1) 13T #FIELD(2) 25T #FIELD(3) 37T #FIELD(4) 49T #REM
*
RESET #FIELD(*) #REM
SEPARATE #INPUT-LINE INTO #FIELD (1:4) IGNORE
      WITH RETAINED DELIMITERS ',',
WRITE #FIELD(1) 13T #FIELD(2) 25T #FIELD(3) 37T #FIELD(4) 49T #REM
*
RESET #FIELD(*) #REM
*
SEPARATE SUBSTRING(#INPUT-LINE,1,50) INTO #FIELD (1:4)
      IGNORE WITH DELIMITERS ',',
WRITE #FIELD(1) 13T #FIELD(2) 25T #FIELD(3) 37T #FIELD(4) 49T #REM
*
END

```

Output of Program SEPEX3:

```

INP: VAL1,  VAL2, VAL3,VAL4
#FIELD (1)  #FIELD (2)  #FIELD (3)  #FIELD (4)  REMAINDER
-----
VAL1          VAL2          VAL3,VAL4
VAL1          VAL2
VAL1          ,          VAL2          ,
VAL1          VAL2          VAL3          VAL4

```

Example 4 - Using a Source Array of a Redefined String

```

** Example 'SEPEX4': SEPARATE with source array
*****
* This example shows different results when separating a scalar string
* or a string array redefining the scalar string.
*
*
*****
*
*
DEFINE DATA LOCAL
1 #TEXT (A24) INIT <'VAL1 VAL2 VAL3 VAL4 VAL5'>
1 REDEFINE #TEXT
  2 #TEXTARRAY (A12/2)
1 #WORD1(A5/6)
1 #WORD2(A5/6)
END-DEFINE
*

```

```
SEPARATE #TEXT INTO #WORD1(*)
/* Redefinition may split original words into two parts
SEPARATE #TEXTARRAY(*) INTO #WORD2(*)
*
DISPLAY #TEXT #WORD1(*) #TEXTARRAY(*) #WORD2(*)
END
```

Output of Program SEPEX4:

#TEXT	#WORD1	#TEXTARRAY	#WORD2
-----	-----	-----	-----
VAL1 VAL2 VAL3 VAL4 VAL5	VAL1	VAL1 VAL2 VA	VAL1
	VAL2	L3 VAL4 VAL5	VAL2
	VAL3		VA
	VAL4		L3
	VAL5		VAL4
			VAL5

Example 5 - Using a Source Array with RETAINED Delimiters

```
** Example 'SEPEX5': SEPARATE with and without RETAINED DELIMITERS
*****
* This example shows different results with a source array
* when using the option RETAINED DELIMITERS or not.
*
*
*****
*
*
DEFINE DATA LOCAL
1 #TEXT(A20)          INIT <'VAL1,VAL2,VAL3,VAL4'>
1 #TEXTARRAY(A10/3)  INIT <'VAL1,VAL2',
                        'VAL3',
                        'VAL4'>
1 #WORD1(A5/7)
1 #WORD2(A5/7)
END-DEFINE
*
SEPARATE #TEXT          INTO #WORD1(*)
SEPARATE #TEXTARRAY(*)  INTO #WORD2(*)
DISPLAY #TEXT #WORD1(*) #TEXTARRAY(*) #WORD2(*)
*
SEPARATE #TEXT          INTO #WORD1(*) WITH RETAINED DELIMITERS
SEPARATE #TEXTARRAY(*)  INTO #WORD2(*) WITH RETAINED DELIMITERS
DISPLAY #TEXT #WORD1(*) #TEXTARRAY(*) #WORD2(*)
*
END
```

Output of Program SEPEX5:

#TEXT	#WORD1	#TEXTARRAY	#WORD2
VAL1,VAL2,VAL3,VAL4	VAL1	VAL1,VAL2	VAL1
	VAL2	VAL3	VAL2
	VAL3	VAL4	VAL3
	VAL4		VAL4
VAL1,VAL2,VAL3,VAL4	VAL1	VAL1,VAL2	VAL1
	,	VAL3	,
	VAL2	VAL4	VAL2
	,		VAL3
	VAL3		VAL4
	,		
	VAL4		

Example 6 - Using a Source Array with STARTING FROM and REMAINDER POSITION

```

** Example 'SEPEX6': SEPARATE with STARTING FROM and REMAINDER POSITION
*****
* This example shows how the options STARTING FROM POSITION and
* REMAINDER POSITION work together in a processing loop when
* separating a source array.
*
*****
*
*
DEFINE DATA LOCAL
1 #TEXT (A15/1:3) INIT <'VAL1 VAL2',
                        'VAL3',
                        'VAL4 VAL5 VAL6'>
1 #WORD (A5/1:4)
1 #POS (I1) INIT <1>
END-DEFINE
*
WRITE '#TEXT(A15/1:3):      (1)              (2)              (3)'
/ 16T #TEXT(*)
/ 16T '----+----1----+ ----2----+----3 ----+----4----+'
// '#WORD (A5/1:4): (1) (2) (3) (4)      : #POS'
' (within #TEXT(*))'
*
REPEAT
  SEPARATE #TEXT(*) STARTING FROM POSITION #POS
  INTO #WORD(*) REMAINDER POSITION #POS
  WRITE 16T #WORD(*) 44T ': ' #POS
  UNTIL #POS = 0

```

```
END-REPEAT
END
```

Output of Program SEPEX6

```
#TEXT(A15/1:3):      (1)      (2)      (3)
                  VAL1 VAL2      VAL3      VAL4 VAL5 VAL6
                  ----+-----1-----+ ---2-----+---3 ----+---4-----+

#WORD (A5/1:4): (1)  (2)  (3)  (4)      : #POS (within #TEXT(*))
                  VAL1 VAL2 VAL3 VAL4      :      36
                  VAL5 VAL6                  :      0
```

129

SET CONTROL

■ Function	1024
■ Syntax Description	1024
■ Examples	1024

SET CONTROL *operand1* ...

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Function

The SET CONTROL statement is used to perform terminal commands from within a program.

Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S				A											yes	no

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	Terminal Commands to be Performed: The terminal commands are specified as <i>operand1</i> without the control character % (by default). They can be specified as a text constant or as the content of an alphanumeric variable. For further information on terminal commands, see the <i>Terminal Commands</i> documentation.

Examples

- [Example 1 - Switching to Lower Case](#)

- [Example 2 - Activating Hardcopy Output Destination](#)

Example 1 - Switching to Lower Case

```
...  
SET CONTROL 'L'  
...
```

Switches to lower case (equivalent to the terminal command %L).

Example 2 - Activating Hardcopy Output Destination

```
...  
SET CONTROL 'HDEST'...
```

Activates hardcopy output to destination DEST (equivalent to the terminal command %H*destination*).

130

SET GLOBALS

■ Function	1028
■ Syntax Description	1028
■ Parameters	1029
■ Example	1030

SET GLOBALS { *parameter=value* } ...

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Function

The SET GLOBALS statement is used to set values for session parameters.

The parameters are evaluated either when the program that contains the SET GLOBALS statement is compiled, or when it is executed; this depends on the individual parameters.

The parameter settings specified with SET GLOBALS remain in effect until the end of the Natural session, unless they are overridden with a subsequent SET GLOBALS statement or GLOBALS system command. The statement SET GLOBALS and the system command GLOBALS offer the same parameters for modification. They can both be used in the same Natural session. Parameter values specified with a GLOBALS command remain in effect until they are overridden by a new GLOBALS command or SET GLOBALS statement, the session is terminated, or you log on to another library.

Exception

A SET GLOBALS statement in a subordinate program (that is, a subroutine, subprogram, or program invoked with [FETCH RETURN](#)) only applies until control is returned from the subordinate program to the invoking object; then the parameter values set for the invoking object apply again.

Syntax Description

Syntax Element	Description
<i>parameter=value</i>	Parameter Specification(s): In place of <i>parameter</i>, specify the name of the parameter to be set. For a list of possible parameters, see Parameters below. If you specify multiple parameters, you have to separate them from one another by one or more blanks. The parameters can be specified in any order; see also Example. In place of <i>value</i>, specify a valid parameter value. For information on valid parameter values, see the descriptions of the individual parameters listed below.

Parameters

Parameters that can be specified with the SET GLOBALS statement		Evaluation (R = at runtime, C = at compilation)
CC	Conditional Program Execution	R
CF	Character for Terminal Commands	R
CPCVERR	Code Page Conversion Error	R
DC	Character for Decimal Point Notation	R
DFOUT	Date Format for Output	R
DFSTACK	Date Format for Stack	R
DFTITLE	Date Format in Default Page Title	R
D0	Display Order of Output Data	R
DU	Dump Generation	R
EJ	Page Eject	R
FCDP	Filler Character for Dynamically Protected Fields	R
FS	Format Specification	R
IA	INPUT Assign Character	R
ID	INPUT Delimiter Character	R
IM	INPUT Mode	R
LE	Limit Error Processing	C
LS	Line Size	RC
LT	Limit of Records Read	R
MT	Maximum CPU Time	R
NC	Use of Natural System Commands	R
OPF	Overwriting of Protected Fields by Help routines	R
PD	NATPAGE Page Data Set	R
PM	Print Mode	C
PS	Page Size	RC
REINP	Internal REINPUT for Invalid Data	R
SA	Sound Terminal Alarm	R
SF	Spacing Factor	C
TS	Translate Output from Programs in System Libraries	R
WH	Wait for Record in Hold Status	R
ZD	Zero Division Check	R
ZP	Zero Printing	RC

The individual session parameters are described in the *Parameter Reference*.

Example

In the example below, the `SET GLOBALS` statement is used to set the maximum number of characters permitted per line to 74 and to limit the number of database records that can be read in processing loops within a Natural program to 5000.

```
SET GLOBALS LS=74 LT=5000
...
```

131

SET KEY

■ Function	1032
■ Syntax Description	1032
■ Making Keys Program-Sensitive and Deactivating Keys	1033
■ Assigning Commands/Programs	1035
■ Assigning Input DATA	1035
■ COMMAND OFF/ON	1036
■ Assigning HELP	1036
■ DYNAMIC Option	1037
■ DISABLED Option	1037
■ SET KEY Statements on Different Program Levels	1038
■ Assigning Names	1040
■ Example	1041

Function

The SET KEY statement is used to assign functions to the following types of keys:

- video terminal PA (program attention) keys,
- PF (program function) keys,
- CLEAR key.

When a SET KEY statement is executed, Natural receives control of the keys during program execution and uses the values assigned to the keys.

The Natural system variable *PF-KEY identifies which key was pressed last.

 **Note:** If a user presses a key to which no function is assigned, either a warning message will be issued prompting the user to press a valid key, or the value ENTR will be placed into the Natural system variable *PF-KEY; that is, Natural will react as if the ENTER key had been pressed (this depends on the Natural profile parameter IKEY as set by the Natural administrator). Processing of PA and PF keys is also affected by the Natural profile parameter KEY as set by the Natural administrator.

See also *Processing Based on Function Keys* (in the *Programming Guide*).


Application programming interface: USR4005N.

Syntax Description


Several structures are possible for this statement.

For explanations of the symbols used in the syntax diagrams, see [Syntax Symbols](#).


Syntax 1 - Affecting All Keys:



Syntax 2 - Affecting Individual Keys:



Syntax 3 - Affecting Individual Keys:



Operand Definition Table:

Operand	Possible Structure					Possible Formats															Referencing Permitted	Dynamic Definition
<i>operand1</i>		S				A															yes	no
<i>operand2</i>	C	S				A	U														yes	no
<i>operand3</i>	C	S				A	U														yes	no
<i>operand4</i>	C	S				A	U														yes	no

Making Keys Program-Sensitive and Deactivating Keys

Making a key program-sensitive means that the key will be available for interrogation by the currently active program. If a key is made program-sensitive, pressing the key has the same effect as pressing ENTER. All data that have been entered on the screen are transferred to the program.



Note: PA keys and the CLEAR key, when made program-sensitive, do not cause any data to be transferred from the screen.

The program-sensitivity remains in effect only for the execution of the current program. See also the section [SET KEY Statements on Different Program Levels](#).

Examples:

SET KEY ALL	This statement causes all keys to be made program-sensitive. All function assignments to any keys are overwritten.
SET KEY PF2 SET KEY PF2=PGM	Each of these statements causes PF2 to be made program-sensitive.
SET KEY OFF	This statement de-activates all key settings. The Natural system variable *PF-KEY contains ENTR after SET KEY OFF has been executed.
SET KEY ON	This statement re-activates the functions assigned to all keys that had an assignment and re-activates the program-sensitivity of keys that were made program-sensitive before they were de-activated.
SET KEY PF2=OFF	This statement de-activates PF2. After execution of SET KEY PF2=OFF, the Natural system variable *PF-KEY contains ENTR if it contained PF2 before.
SET KEY PF2=ON	This statement re-activates the function assigned to PF2 before it was de-activated or made program-sensitive. If no function had been assigned to PF2, it will be made program-sensitive again.

Key Program-Sensitivity and Contents of *PF-KEY

The following example shows the relation between the program-sensitivity of a key and the contents of the system variable *PF-KEY.

Assume that PF2 has been made program-sensitive by means of SET KEY PF2=PGM and an INPUT statement is executed afterwards. The table below shows how user actions and executed Natural statements influence the contents of *PF-KEY.

Sequence	Natural Statement Executed / User Action	Contents of *PF-KEY
1	User presses PF2.	PF2
2	SET KEY OFF	ENTR
3	SET KEY ON	PF2
4	SET KEY PF2=OFF	ENTR
5	SET KEY PF2=ON	PF2
6	SET KEY PF3=OFF	PF2

Assigning Commands/Programs

You can assign a command or program name to a key, and you can delete such an assignment. When the key is pressed, the current program is terminated and the command/program assigned to the key is invoked via the Natural stack. When assigning a command/program, you can also pass parameters to the command/program (see third example below).

You can also assign a terminal command to a key. When the key is pressed, the terminal command assigned to the key is executed.

When *operand2* is specified as a constant, it must be enclosed within apostrophes.

Examples:

SET KEY PF4='SAVE'	The command SAVE is assigned to PF4.
SET KEY PF4=#XYZ	The value contained in the variable #XYZ is assigned to PF4.
SET KEY PF6='LIST MAP *'	The command LIST, including the LIST parameters MAP and *, is assigned to PF6.
SET KEY PF2='%%'	The terminal command %% is assigned to PF2.
SET KEY PF9=' '	The command and name previously assigned to PF9 are deleted.

The assignment remains in effect until it is overwritten by another SET KEY statement, until the user logs on to another application, or until the end of the Natural session. See also the section [SET KEY Statements on Different Program Levels](#).



Note: Before a program invoked via a key is executed, Natural internally issues a BACKOUT TRANSACTION statement.

Assigning Input DATA

You can assign a data string (*operand3*) to a key. When the key is pressed, the data string is placed into the input field in which the cursor is currently positioned, and the data are transferred to the executing program (as if ENTER had been pressed).

When *operand3* is specified as a constant, it must be enclosed within apostrophes.

Example:

```
SET KEY PF12=DATA 'YES'
```

For the validity of a DATA assignment, the same applies as for a command assignment, that is, it remains in effect until it is overwritten by another SET KEY statement, until the user logs on to another application, or until the end of the Natural session. See also the section [SET KEY Statements on Different Program Levels](#).

COMMAND OFF/ON

With COMMAND OFF, you can temporarily de-activate any function (command, program, or data) assigned to a key. If the key had been program-sensitive before the function was assigned, COMMAND OFF will make it program-sensitive again.

With a subsequent COMMAND ON, you can re-activate the assigned function again.

Examples:

SET KEY PF4=COMMAND OFF	The function that has been assigned to PF4 is temporarily de-activated; if PF4 had been program-sensitive before the function was assigned, it is now made program-sensitive again.
SET KEY PF4=COMMAND ON	The function assigned to PF4 is re-activated again.
SET KEY COMMAND OFF	All functions assigned to all keys are temporarily de-activated; those keys which had been program-sensitive before functions were assigned to them, are now made program-sensitive again.
SET KEY COMMAND ON	All functions assigned to all keys are re-activated again.

With SET KEY PF nn ='' you can delete the function assigned to a key and at the same time deactivate the program sensitivity of the key.

Assigning HELP

You can assign HELP to a key. When the key is pressed, the helproutine assigned to the field in which the cursor is currently positioned will be invoked.

The effect is the same as when entering the help character in the field to invoke help. (The help character - default is a question mark (?) - is determined by the Natural profile parameter HI as set by the Natural administrator.)

Example:

```
SET KEY PF1=HELP
```

For the validity of a `HELP` assignment, the same applies as for program-sensitivity, that is, it remains in effect only for the execution of the current program. See also the section [SET KEY Statements on Different Program Levels](#).

DYNAMIC Option

Instead of specifying a specific key with the `SET KEY` statement, you can use the `DYNAMIC` option with a variable (*operand1*), and assign a value (`PFn`, `PAn`, `CLR`) to this variable in the program. This allows you to specify a function and make it dependent on the program logic which key this function is assigned to.



Note: `SET KEY` cannot be used if *operand1* is a dynamic variable.

Example:

```
...  
IF ...  
    MOVE 'PF4' TO #KEY  
ELSE  
    MOVE 'PF7' TO #KEY  
END-IF  
...  
SET KEY DYNAMIC #KEY = 'SAVE'  
...
```

DISABLED Option

Graphical user interface (GUI) elements, such as push buttons, menus, and bitmaps, are implemented as PF keys. With the `DISABLED` option, you can disable the use of a GUI element assigned to a PF key. Push buttons and menu items will then be displayed grey.

To cancel the effect of `SET KEY PFnn=DISABLED`, you use `SET KEY PFnn=ON`.

Example:

SET KEY PF10=DISABLED	Disables the use of the GUI element assigned to PF10.


The DISABLED option can only be used within a processing rule.

SET KEY Statements on Different Program Levels

When an application contains SET KEY statements at different levels, the following applies:

- When keys are made program-sensitive, the program-sensitivity also applies to all lower level (called) programs, unless these programs contain further SET KEY statements. When control is returned to a higher level program, the SET KEY assignments made at the higher level come into effect again.
- For keys which are defined as HELP keys, the same applies as for keys which are program-sensitive.
- When a function (program, command, terminal command, or data string) is assigned to a key, this assignment is valid at all higher and lower levels - regardless of the level at what the assignment is made - until another function is assigned to the key or it is made program-sensitive, or until the user logs on to another application or the Natural session is terminated.

Example of SET KEY Statements on Different Program Levels



Assigning Names

With the `NAMED` clause, you can assign a name (*operand4*) to a key. The name will then be displayed in the PF-key lines on the screen; this allows the users to identify the functions assigned to the keys:

```

      ?   Help
      .   Exit
-----
Code ... ?   Library ... *_____
            Object .... *_____
            DBID ..... 0__   FILENR ...: 0__

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help      Exit  Last      Flip                                Canc
```

The display of the PF-key lines is activated with the session parameter `KD` (see the *Parameter Reference*). You can control the way in which the PF-key lines are displayed by using the terminal command `%Y` (see the *Terminal Commands* documentation).

The maximum length of a name to be assigned to a key is 10 characters. In normal tabular PF-key line format (`%YN`), only the first 5 characters are displayed.

When *operand4* is specified as a constant, it must be enclosed within apostrophes (see examples below).

You cannot assign a name to a key without assigning a function to it or making it program-sensitive. To the `ENTER` key, however, you can only assign a name, but no function.

With `NAMED OFF`, you delete the name assigned to a program-sensitive key.

Examples:

SET KEY ENTR NAMED 'EXEC'	The name EXEC is assigned to the ENTER key.
SET KEY PF3 NAMED 'EXIT'	PF3 is made program-sensitive, and the name EXIT is assigned to PF3.
SET KEY PF3 NAMED OFF	PF3 is made program-sensitive, and the name that has been assigned to PF3 is deleted.
SET KEY NAMED OFF	All names that have been assigned to any program-sensitive keys are deleted.
SET KEY PF4='AP1' NAMED 'APPL1'	The program AP1 and the name APPL1 are assigned to PF4.

When you use normal tabular PF-key line format (%YN), the following applies:

- If you omit the NAMED clause when assigning a command/program to a key, the command/program name will be displayed in the PF-key line; if the command/program name is longer than 5 characters, CMND will be displayed.
- If you omit the NAMED clause when assigning input data to a key, DATA will be displayed in the PF-key line.
- If you assign (with the NAMED clause) a name in Unicode format to a PF-key, the name might not be correctly positioned under the respective headers. This problem, however, may occur only when you are using the *Natural Web I/O Interface* and only for "wide" characters. In this case, the sequential PF-key line format (%YS or %YP) is recommended.

When you use sequential PF-key line format (%YS or %YP), only those keys to which names have been assigned will be displayed in the PF-key line; that is, if you omit the NAMED clause when assigning a command/program/data to a key, the key will not be displayed in the PF-key line.

See also *Processing Based on Function Key Names* in the *Programming Guide*.

Example

```
** Example 'SKYEX1': SET KEY
*****
DEFINE DATA LOCAL
1 #PF4 (A56)
END-DEFINE
*
MOVE 'LIST VIEW' TO #PF4
*
SET KEY PF1 PF2
SET KEY PF3 = 'MENU'
        PF4 = #PF4
        PF5 = 'LIST VIEW EMPLOYEES' NAMED 'Emp1'
*
FORMAT KD=ON
INPUT ////
    10X 'The following function keys are assigned:' //
    10X 'PF1: Function for PF1          ' /
    10X 'PF2: Function for PF2          ' /
    10X 'PF3: Return to MENU program' /
    10X 'PF4: LIST VIEW                ' /
    10X 'PF5: LIST VIEW EMPLOYEES      ' ///
*
IF *PF-KEY = 'PF1'
    WRITE 'Function for PF1 executed.'
END-IF
IF *PF-KEY = 'PF2'
```

```
    WRITE 'Function for PF2 executed.'  
END-IF  
*  
END
```

Output of Program SKYEX1:

The following function keys are assigned:

```
PF1: Function for PF1  
PF2: Function for PF2  
PF3: Return to MENU program  
PF4: LIST VIEW  
PF5: LIST VIEW EMPLOYEES
```


132

SET TIME

■ Function	1044
■ Example	1044

<pre>{ SET TIME } { SETTIME }</pre>

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Function

The SET TIME (or SETTIME) statement is used in conjunction with the Natural system variable *TIMD to measure the time it takes to execute a specific section of a program.

The SET TIME statement is placed at a specific position in the program, and *TIMD will contain the amount of time elapsed since the execution of the SET TIME statement.

*TIMD must always contain a reference to the SET TIME statement, either by using the source-code line number of the SET TIME statement or by assigning a label to the SET TIME statement, which can then be used as a reference.

Example

```
** Example 'STIEX1': SETTIME
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
END-DEFINE
*
ST. SETTIME
WRITE 10X 'START TIME:' *TIME
*
READ (100) EMPLOY-VIEW BY NAME
END-READ
*
WRITE NOTITLE 10X 'END TIME: ' *TIME
WRITE          10X 'ELAPSED TIME TO READ 100 RECORDS'
                '(HH:MM:SS.T) :' *TIMD (ST.) (EM=99:99:99'.'9)
*
END
```

Output of Program STIEX1:

```
START TIME: 16:39:07.6  
END TIME:   16:39:07.7  
ELAPSED TIME TO READ 100 RECORDS (HH:MM:SS.T) : 00:00:00.1
```

133

SET WINDOW

■ Function	1048
■ Syntax Description	1048
■ Example	1048

```
SET WINDOW { 'window-name'
             OFF }
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: `DEFINE WINDOW` | `INPUT WINDOW='window-name'` | `REINPUT`

Belongs to Function Group: [Screen Generation for Interactive Processing](#)

Function

The `SET WINDOW` statement is used to activate and de-activate a window.

Any `SET WINDOW 'window-name'` or `INPUT WINDOW='window-name'` statement de-activates the window which has currently been active and activates the window specified in the statement. This means that only one window can be active at a time.



Note: If you use `SET WINDOW` to activate a window which is defined with `SIZE AUTO`, the data on the screen *before* the window is activated determine the size of the window.

Syntax Description

Syntax Element	Description
<code>SET WINDOW 'window-name'</code>	Activates the specified window, which means that all subsequent statements refer to that window until either the window is de-activated or another window is activated. The specified window must have been defined with a <code>DEFINE WINDOW</code> statement.
<code>SET WINDOW OFF</code>	De-activates the currently active window.

Example

See `DEFINE WINDOW` statement.

134

SKIP

■ Function	1050
■ Syntax Description	1050
■ Example	1051

SKIP [(rep)] operand1 [LINES]

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [AT END OF PAGE](#) | [AT TOP OF PAGE](#) | [CLOSE PRINTER](#) | [DEFINE PRINTER](#) | [DISPLAY](#) | [EJECT](#) | [FORMAT](#) | [NEWPAGE](#) | [PRINT](#) | [SUSPEND IDENTICAL SUPPRESS](#) | [WRITE](#) | [WRITE TITLE](#) | [WRITE TRAILER](#)

Belongs to Function Group: *Creation of Output Reports*

Function

The SKIP statement is used to generate one or more blank lines in an output report.

See also *Page Titles, Page Breaks, Blank Lines* in the *Programming Guide*.

Processing

If the execution of a SKIP statement would cause the page size to be exceeded, exceeding lines will be ignored (except in an [AT TOP OF PAGE](#) statement).

A SKIP statement is only executed if something has already been output on the page (output from an [AT TOP OF PAGE](#) statement is not taken into account here).

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
operand1	C	S				N	P	I								yes	no

Syntax Element Description:

Syntax Element	Description
(rep)	Report Specification: The notation (rep) may be used to specify the identification of the report for which the SKIP statement is applicable. A value in the range 0 - 31 or a logical name which has been assigned using the DEFINE PRINTER statement may be specified.

Syntax Element	Description
	If (<i>rep</i>) is not specified, the SKIP statement will apply to the first report (Report 0). For information on how to control the format of an output report created with Natural, see <i>Report Format and Control</i> in the <i>Programming Guide</i>.
<i>operand1</i>	Number of Lines to be Skipped: <i>operand1</i> represents the number (1 - 250) of blank lines to be generated. This number may be specified as a numeric constant or as the content of a numerical variable. If <i>operand1</i> exceeds the page size of the report, the SKIP statement will result in a newpage condition.

Example

```

** Example 'SKPEX1': SKIP
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 CITY
  2 COUNTRY
  2 NAME
END-DEFINE
*
LIMIT 7
READ EMPL-VIEW BY CITY STARTING FROM 'W'
  AT BREAK OF CITY
    SKIP 2
  END-BREAK
  DISPLAY NOTITLE CITY (IS=ON) COUNTRY (IS=ON) NAME
/*
END-READ
END

```

Output of Program SKPEX1:

CITY	COUNTRY	NAME
WASHINGTON	USA	REINSTEDT PERRY
WEITERSTADT	D	BUNGERT UNGER DECKER

WEST BRIDGFORD	UK	ENTWHISTLE

WEST MIFFLIN	USA	WATSON

135

SORT

■ Function	1054
■ Restrictions	1055
■ Syntax Description	1055
■ Three-Phase SORT Processing	1058
■ Example	1059
■ Using External Sort Programs	1063

Structured Mode Syntax

```
END-ALL
[AND]
SORT      [ THEM          ] [BY] { operand1 [ ASCENDING
        RECORDS          ] } ... 10
        USING-clause
        [GIVE-clause]
        statement ...
END-SORT
```

* If a statement label is specified, it must be placed *before* the keyword SORT, but *after* END-ALL (and AND).

Reporting Mode Syntax

```
SORT [ THEM          ] [BY] { operand1 [ ASCENDING
RECORDS          ] } ... 10
    [USING-clause]
    [GIVE-clause]
    statement ...
LOOP
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statement: [FIND with SORTED BY option](#)

Belongs to Function Group: [Loop Execution](#)

Function

The SORT statement is used to perform a sort operation, sorting the records from all processing loops that are active when the SORT statement is executed.

For the sort operation, Natural's internal sort program is used. It is also possible to use another, external sort program.

Restrictions

- The SORT statement must be contained in the same object as the processing loops whose records it sorts.
- Nested SORT statements are not allowed.
- The total length of a record to be sorted must not exceed 10240 bytes.
- The number of sort criteria must not exceed 10.

Syntax Description

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	S	A N P I F B D T	no	no

Syntax Element Description:

Syntax Element	Description
END-ALL	Closing All Currently Active Loops: In structured mode, the SORT statement must be preceded by END-ALL, which serves to close all active processing loops. The SORT statement itself initiates a new processing loop, which must be closed with END-SORT. Note: For reporting mode: The SORT statement closes all active processing loops and initiates a new processing loop.
<i>operand1</i>	Sort Criteria: <i>operand1</i> represents the fields/variables to be used as the sort criteria. 1 to 10 database fields (descriptors and non-descriptors) and/or user-defined variables may be specified. A multiple-value field or a field contained within a periodic group may be used. A group or an array is not permitted. Note: A field specified in the SORT criteria is used for both, to put a value into the SORT record in the selecting phase (1st phase), and to receive the sorted value in the processing phase (3rd phase). Be aware, this may cause addressing errors, when indexed array fields are used which carry a correct index value in the selecting (1st) phase, but with an out-of-range value in the processing (3rd) phase. Therefore, indexed array fields should be used with caution, and better be replaced with non-indexed fields (scalar).
ASCENDING	Sort Sequence:

Syntax Element	Description
DESCENDING	The default sort sequence is ascending. If you wish the values to be sorted in descending sequence, specify DESCENDING. ASCENDING/DESCENDING may be specified for each sort field.
USING	USING Clause: See USING Clause below. Note: The note given under the description of <i>operand1</i> also applies to the USING clause.
GIVE	GIVE Clause: See GIVE Clause below.
END-SORT	End of SORT Statement: In structured mode, the Natural reserved word END-SORT must be used to end the SORT statement. In reporting mode, the Natural statement LOOP is used to end the SORT statement.
LOOP	

USING Clause

The USING clause indicates the fields which are to be written to intermediate sort storage. It is required in structured mode and optional in reporting mode. However, it is strongly recommended to also use it in reporting mode so as to reduce memory requirements.

```
{ USING operand2 ... }
{ USING KEYS }
```

Operand Definition Table:

Operand	Possible Structure				Possible Formats										Referencing Permitted	Dynamic Definition		
<i>operand2</i>		S	A			A	N	P	I	F	B	D	T	L	C		no	no

Syntax Element Description:

Syntax Element	Description
USING <i>operand2</i>	Additional Fields: You can specify additional fields that are to be written to the intermediate sort storage - in addition to the sort key fields (as specified with <i>operand1</i>).
USING KEYS	Sort Key Fields Only: Only the sort key fields, as specified with <i>operand1</i> , will be written to intermediate sort storage.

In Reporting Mode: If you omit the USING clause, all database fields of processing loops initiated before the SORT statement, as well as all user-defined variables defined before the SORT statement, will be written to intermediate sort storage.

If, after sort execution, a reference is made to a field which was not written to the sort intermediate storage, the value for the field will be the last value of the field before the sort.

GIVE Clause


The GIVE clause is used to specify Natural system functions (such as MAX, MIN) that are to be evaluated in the first phase of the SORT statement. These system functions may be referenced in the third phase (see [SORT Statement Processing](#)).

A reference to a system function after the SORT statement must be preceded by an asterisk, for example, *AVER(SALARY).



Notes:

1. In place of the keyword GIVE, the keyword GIVING may be used.
2. The GIVE clause is only allowed if at least one of the (inner) loops closed by the SORT statement derives from a FIND, READ, HISTOGRAM or READ WORK FILE statement.



Operand Definition Table:

Operand	Possible Structure			Possible Formats										Referencing Permitted	Dynamic Definition
operand3	S	A		*										yes	no

* depends on function

Syntax Element Description:

Syntax Element	Description
MAX MIN NMIN COUNT NCOUNT OLD AVER NAVER SUM TOTAL	System Functions: For details on the individual system functions, see the <i>System Functions</i> documentation.
<i>operand3</i>	Field Name: <i>operand3</i> is the field name.
(NL= <i>nn.m</i>)	Preventing Arithmetic Overflows: This option applies to the system functions AVER, NAVER, SUM and TOTAL only. It will be ignored for any other system function. See also session parameter NL in the <i>Parameter Reference</i> documentation. This option may be used to prevent an arithmetic overflow during the evaluation of system functions; it is described under <i>Format/Length Requirements for AVER, NAVER, SUM and TOTAL</i> in the <i>System Functions</i> documentation.

Three-Phase SORT Processing

A program containing a SORT statement is executed in three phases.

1st Phase - Selecting the Records to be Sorted

The statements before the SORT statement are executed. Data as described in the USING clause will be written to intermediate sort storage.

In reporting mode, any variables to be used as accumulators following the sort must not be defined before the SORT statement. In structured mode, they must not be included in the USING clause.

Fields written to intermediate sort storage cannot be used as accumulators because they are read back with each individual record during the 3rd processing phase. Consequently, the accumulation function would not produce the desired result because with each record the field would be over-written with the value for that individual record.

The number of records written to intermediate storage is determined by the number of processing loops and the number of records processed per loop. One record on the internal intermediate storage is created each time the SORT statement is encountered in a processing loop. In the case of nested loops, a record is only written to intermediate storage if the inner loop is executed. If in the example below a record is to be written to intermediate storage even if no records are found for the inner (FIND) loop, the FIND statement must contain an IF NO RECORDS FOUND clause.


```

READ ...
...
  FIND ...
...
END-ALL
SORT ...
  DISPLAY ...
END-SORT
...

```

2nd Phase - Sorting the Records

The records are sorted.

3rd Phase - Processing the Sorted Records

The statements after the `SORT` statement are executed for all records on the intermediate storage in the specified sorting sequence. Database fields to be referenced after a `SORT` statement must be correctly referenced using the appropriate statement label or reference number.

Example

- [Example 1 - SORT](#)
- [Example 2 - SORT](#)
- [Example 3 - SORT](#)

Example 1 - SORT

```

** Example 'SRTEX1S': SORT (structured mode)
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 CITY
  2 SALARY      (1:2)
  2 PERSONNEL-ID
  2 CURR-CODE   (1:2)
*
1 #AVG          (P11)
1 #TOTAL-TOTAL (P11)
1 #TOTAL-SALARY (P11)
1 #AVER-PERCENT (N3.2)
END-DEFINE
*
LIMIT 3
FIND EMPL-VIEW WITH CITY = 'BOSTON'
  COMPUTE #TOTAL-SALARY = SALARY (1) + SALARY (2)
  ACCEPT IF #TOTAL-SALARY GT 0

```

```

/*
END-ALL
AND
SORT BY PERSONNEL-ID USING #TOTAL-SALARY SALARY(*) CURR-CODE(1)
    GIVE AVER(#TOTAL-SALARY)
/*
AT START OF DATA
    WRITE NOTITLE '*' (40)
        'AVG CUMULATIVE SALARY:' *AVER (#TOTAL-SALARY) /
    MOVE *AVER (#TOTAL-SALARY) TO #AVG
END-START
COMPUTE ROUNDED #AVER-PERCENT = #TOTAL-SALARY / #AVG * 100
ADD #TOTAL-SALARY TO #TOTAL-TOTAL
/*
DISPLAY NOTITLE PERSONNEL-ID SALARY (1) SALARY (2)
    #TOTAL-SALARY CURR-CODE (1)
    'PERCENT/OF/AVER' #AVER-PERCENT
AT END OF DATA
    WRITE / '*' (40) 'TOTAL SALARIES PAID: ' #TOTAL-TOTAL
END-ENDDATA
END-SORT
*
END

```

Output of Program SRTEX1S:

PERSONNEL ID	ANNUAL SALARY	ANNUAL SALARY	#TOTAL-SALARY	CURRENCY CODE	PERCENT OF AVER
***** AVG CUMULATIVE SALARY: 41900					
20007000	16000	15200	31200	USD	74.00
20019200	18000	17100	35100	USD	83.00
20020000	30500	28900	59400	USD	141.00
***** TOTAL SALARIES PAID: 125700					

The previous example is executed as follows:

First Phase:

- Records with CITY=BOSTON are selected from the EMPLOYEES file.
- The first 2 occurrences of SALARY are accumulated in the field #TOTAL-SALARY.
- Only records with #TOTAL-SALARY greater than 0 are accepted.
- The records are written to the sort intermediate storage. The database arrays SALARY (first 2 occurrences) and CURR-CODE (first occurrence), the database field PERSONNEL-ID, and the user-defined variable #TOTAL-SALARY are written to the intermediate storage.

- The average of #TOTAL-SALARY is evaluated.

Second Phase:

- The records are sorted.

Third Phase:

- The sorted intermediate storage is read.
- At the at-start-of-data condition, the average of #TOTAL-SALARY is displayed.
- #TOTAL-SALARY is added to #TOTAL-TOTAL and the fields PERSONNEL-ID, SALARY(1), SALARY(2), #AVER-PERCENT and #TOTAL-SALARY are displayed.
- At the end-of-data condition, the variable #TOTAL-TOTAL is written.

Equivalent reporting-mode example: [SRTEX1R](#).

Example 2 - SORT

```

** Example 'SRTEX2': SORT
*****
DEFINE DATA LOCAL
1  VEHIC-VIEW VIEW OF VEHICLES
   2  MAKE
   2  YEAR
END-DEFINE
*
LIMIT 10
*
READ VEHIC-VIEW
END-ALL
SORT BY MAKE YEAR USING KEY
  DISPLAY NOTITLE (AL=15) MAKE (IS=ON) YEAR
  AT BREAK OF MAKE
    WRITE '-' (20)
  END-BREAK
END-SORT
END

```

Output of Program SRTEX2S:

MAKE	YEAR
FIAT	1980
	1982
	1984
PEUGEOT	1980

```

                1982
                1985
-----
RENAULT        1980
                1980
                1982
                1982
-----

```

Example 3 - SORT

```

** Example 'SRTEX3': SORT values in an array
*****
DEFINE DATA LOCAL
1 #I      (I4)
1 #J      (I4)
1 #X      (I1)
1 #TAB (I1/1:6) INIT <2,4,6,5,3,1>
END-DEFINE
WRITE 'Array before SORT:' #TAB(*) /
*
FOR #I := 1 TO 6
  #X := #TAB(#I)
  WRITE #X '<-- Put into SORT record'
END-ALL
SORT #X USING KEYS
  WRITE #X '<-- Get from SORT'
  ADD 1 TO #J
  #TAB(#J) := #X
END-SORT
*
WRITE / 'Array after  SORT:' #TAB(*)
END

```

Output of Program SRTEX3:

```

Array before SORT:    2    4    6    5    3    1

  2 <-- Put into SORT record
  4 <-- Put into SORT record
  6 <-- Put into SORT record
  5 <-- Put into SORT record
  3 <-- Put into SORT record
  1 <-- Put into SORT record
  1 <-- Get from SORT
  2 <-- Get from SORT
  3 <-- Get from SORT
  4 <-- Get from SORT
  5 <-- Get from SORT
  6 <-- Get from SORT

```

```
Array after SORT:  1    2    3    4    5    6
```

Using External Sort Programs

In Natural, sort operations are by default processed by Natural's internal sort program, as described above. However, an external sort program can be used. This external sort program then processes the sort operations instead of Natural's internal sort program.

See also *External Sort Programs* in the *Operations* documentation.

136

STACK

■ Function	1066
■ Syntax Description	1066
■ Example	1069

STACK [TOP] { COMMAND operand1 [operand2 [(parameter)]] ...
[DATA] [FORMATTED] {operand2 [(parameter)]] ... }

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [INPUT](#) | [RELEASE](#)

Function

The `STACK` statement is used to place any of the following into the Natural stack:

- the name of a Natural program or Natural system command to be executed;
- data to be used during the execution of an [INPUT](#) statement.

For further information on the stack, see *Further Programming Aspects, Stack Processing* in the *Programming Guide*.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition	
<i>operand1</i>	C	S	A	G	N	A											yes	yes
<i>operand2</i>	C	S	A	G	N	A	U	N	P	I	F	B	D	T	L	G	yes	yes

Syntax Element Description:

Syntax Element	Description
TOP	TOP Option: If you specify <code>TOP</code>, the data/program/command will be placed at the top of the Natural stack. Otherwise, they are placed at the bottom of the stack. Example: The following statement causes the content of the variable <code>#FIELD A</code> to be placed as data on top of the stack:

Syntax Element	Description
	STACK TOP #FIELDA
DATA	DATA Option: This option, which is also the default, causes data to be placed in the stack which are to be used as input data for an INPUT statement. Delimiter characters or input assign characters contained within the data values will be processed as delimiters. For details on how data from the stack are processed by an INPUT statement, refer to <i>Processing Data from the Natural Stack</i> (in the description of the INPUT statement). Example: The following statements cause the contents of the variables #FIELD1 and #FIELD2 to be placed in the stack: <pre>MOVE 'ABC' TO #FIELD1 MOVE 'XYZ' TO #FIELD2 STACK #FIELD1 #FIELD2</pre> These variables will be passed as data to the next INPUT statement in the Natural program, using delimiter mode: <pre>INPUT #FIELD1 #FIELD2</pre> Note: If <i>operand2</i> is a time variable (Format T), only the time component of the variable content is placed in the stack, but not the date component.
FORMATTED	FORMATTED Option: This option causes all data to be passed on a field-by-field basis to the next INPUT statement; no key assignments or delimiter characters will be interpreted. Examples: The following statements cause ABC , DEF to be placed in #FIELD1 and XYZ in #FIELD2: <pre>MOVE 'ABC,DEF' TO #FIELD1 MOVE 'XYZ' TO #FIELD2 STACK TOP DATA FORMATTED #FIELD1 #FIELD2 ... INPUT #FIELD1 #FIELD2</pre> Assuming the input delimiter character to be the comma (profile/session parameter ID= ,), the following statements - without the keyword FORMATTED - cause ABC to be placed in #FIELD1 and DEF in #FIELD2:

Syntax Element	Description
	<pre>MOVE 'ABC,DEF' TO #FIELD1 STACK TOP DATA #FIELD1 ... INPUT #FIELD1 #FIELD2</pre> Note: The <code>FORMATTED</code> option should be used if the data to be passed contains delimiter, control or DBCS characters to avoid unintentional interpretation of these characters.
<code>COMMAND</code> <i>operand1</i>	COMMAND Option: To place a command (or program name) in the stack, you specify the keyword <code>COMMAND</code> followed by the command specified in <i>operand1</i>. Natural will execute the command instead of displaying the <code>NEXT</code> prompt and prompting the user for input. Example: The following statement causes the command <code>RUN</code> to be placed at the top of the stack. Natural will execute this command at the point where the <code>NEXT</code> prompt would normally be issued. <pre>STACK TOP COMMAND 'RUN'</pre>
<code>COMMAND</code> <i>operand1</i> <i>operand2</i> ...	COMMAND with Data Option: Together with a command (<i>operand1</i>), you may also place data (<i>operand2</i>) in the stack. These data will then be processed by the next <code>INPUT</code> statement after the command has been executed. Data stacked with a command are always stacked unformatted. Note: If the data to be stacked include empty alphanumeric fields (that is, blanks), these blanks will be interpreted as delimiters between values and thus not processed correctly by the corresponding <code>INPUT</code> statement. Therefore, if you wish to stack empty alphanumeric fields as data with a command, you have to use two <code>STACK</code> statements: one <code>STACK DATA <i>operand2</i> ...</code> to stack the data, and one <code>STACK COMMAND <i>operand1</i></code> to stack the command.
<i>parameter</i>	Date Format: If <i>operand2</i> is a date variable, you can specify the session parameter <code>DF</code> as a parameter for this variable.

Example

```

** Example 'STKEX1': STACK
*****
DEFINE DATA LOCAL
1 #CODE (A1)
END-DEFINE
*
INPUT //
  10X 'PLEASE SELECT COMMAND' //
  10X 'LIST VIEW      (V)' /
  10X 'LIST PROGRAM * (P)' /
  10X 'TECH INFO      (T)' /
  10X 'STOP           (.)' //
  20X 'CODE:' #CODE
*
*
DECIDE ON FIRST #CODE
  VALUE 'V'
    STACK TOP DATA      'VIEW'
    STACK TOP COMMAND 'LIST'
  VALUE 'P'
    STACK TOP COMMAND 'LIST PROGRAM *'
  VALUE 'T'
    STACK TOP COMMAND 'LAST *'
    STACK TOP COMMAND 'TECH'
    STACK TOP COMMAND 'SYSPROD'
  VALUE '.'
    STOP
  NONE
    REINPUT 'PLEASE ENTER VALID CODE'
END-DECIDE
*
*
END

```

Output of Program STKEX1:

```

PLEASE SELECT COMMAND

LIST VIEW      (V)
LIST PROGRAM * (P)
TECH INFO      (T)
STOP           (.)

      CODE:P

```

After entering and confirming code:

```

16:46:28          ***** NATURAL LIST COMMAND *****          2005-01-19
User HTR          - LIST Objects in a Library -          Library SYSEXSYN

Cmd  Name      Type      S/C  SM Version  User ID  Date      Time
---  *-----  P-----  *   *   *-----  *-----  *-----
___  ACREX1     Program    S/C  S   4.1.03  RKE      2004-11-11 16:32:37
___  ACREX2     Program    S/C  S   4.1.03  RKE      2005-01-05 10:29:51
___  ADDEX1     Program    S/C  S   4.1.03  RKE      2004-11-11 16:36:49
___  AEDEX1R    Program    S/C  R   4.1.03  RKE      2004-11-11 16:40:34
___  AEDEX1S    Program    S/C  S   4.1.03  RKE      2004-11-11 16:39:57
___  AEPEX1R    Program    S/C  R   4.1.03  RKE      2004-11-11 16:41:57
___  AEPEX1S    Program    S/C  S   4.1.03  RKE      2004-11-11 16:42:31
___  AEPEX2     Program    S/C  S   4.1.03  RKE      2004-11-11 16:43:37
___  ASDEX1R    Program    S/C  R   4.1.03  RKE      2004-11-11 17:00:21
___  ASDEX1S    Program    S/C  S   4.1.03  RKE      2004-11-11 17:00:50
___  ASGEX1R    Program    S/C  R   4.1.03  RKE      2004-11-11 17:02:01
___  ASGEX1S    Program    S/C  S   4.1.03  RKE      2004-11-11 17:02:08
___  ATBEX1R    Program    S/C  R   4.1.03  RKE      2004-11-11 17:03:18
___  ATBEX1S    Program    S/C  S   4.1.03  RKE      2004-11-11 17:03:05
                                     14 Objects found

Top of List.
Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Print Exit  Sort      --      -      +      ++      >      Canc

```

137

STOP

■ Function	1072
■ Example	1072

STOP

Function

The `STOP` statement is used to terminate the execution of a program and return to the command input prompt.

One or more `STOP` statements may be inserted anywhere within a Natural program.

The `STOP` statement will terminate the execution of the program immediately. Independent of the positioning of a `STOP` statement in a subroutine, any end-page condition specified in the main program will be invoked for final end-page processing during execution of the `STOP` statement.

For Natural RPC: See Notes on Natural Statements on the Server in the Natural RPC (Remote Procedure Call) documentation.

Example

```
** Example 'STPEX1': STOP
*****
DEFINE DATA LOCAL
1 #CODE (A1)
END-DEFINE
*
INPUT //
  10X 'PLEASE SELECT COMMAND' //
  10X 'LIST VIEW      (V)' /
  10X 'LIST PROGRAM * (P)' /
  10X 'TECH INFO      (T)' /
  10X 'STOP           (.)' //
  20X 'CODE:' #CODE
*
*
DECIDE ON FIRST #CODE
  VALUE 'V'
    STACK TOP DATA      'VIEW'
    STACK TOP COMMAND    'LIST'
  VALUE 'P'
    STACK TOP COMMAND    'LIST PROGRAM *'
  VALUE 'T'
    STACK TOP COMMAND    'LAST *'
    STACK TOP COMMAND    'TECH'
    STACK TOP COMMAND    'SYSPROD'
  VALUE '.'
    STOP
```

```
NONE
  REINPUT 'PLEASE ENTER VALID CODE'
END-DECIDE
*
*
END
```

Output of Program STPEX1:

```
PLEASE SELECT COMMAND

LIST VIEW      (V)
LIST PROGRAM * (P)
TECH INFO      (T)
STOP           (.)

      CODE:
```


XV

■ 138 STORE	1077
■ 139 SUBTRACT	1085
■ 140 SUSPEND IDENTICAL SUPPRESS	1089
■ 141 TERMINATE	1095
■ 142 UPDATE	1099
■ 143 UPDATE (SQL)	1105
■ 144 UPDATELOB	1113
■ 145 UPLOAD PC FILE	1121
■ 146 WRITE	1125
■ 147 WRITE TITLE	1141
■ 148 WRITE TRAILER	1149
■ 149 WRITE WORK FILE	1157

138

STORE

■ Function	1078
■ Database-Specific Considerations	1079
■ Syntax Description	1079
■ Example	1081

Structured Mode Syntax

```
STORE [RECORD] [IN] [FILE] view-name
      [PASSWORD=operand1]
      [CIPHER=operand2]
      [
        [
          USING
          GIVING
        ] NUMBER operand3
      ]
```

Reporting Mode Syntax

```
STORE [RECORD] [IN] [FILE] view-name
      [PASSWORD=operand1]
      [CIPHER=operand2]
      [
        [
          USING
          GIVING
        ] NUMBER operand3
      ]
      {
        [USING] SAME [RECORD] [AS] [STATEMENT [(r)]]
        [
          SET
          WITH
        ] [operand4=operand5]
        ...
      }
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [DELETE](#) | [END TRANSACTION](#) | [FIND](#) | [GET](#) | [GET SAME](#) | [GET TRANSACTION DATA](#) | [HISTOGRAM](#) | [LIMIT](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [READLOB](#) | [RETRY](#) | [UPDATE](#) | | [UPDATELOB](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The `STORE` statement is used to add a record to a database.

Database-Specific Considerations

Adabas	The Natural system variable *ISN contains the Adabas ISN assigned to the new record as a result of the STORE statement execution. A subsequent reference to *ISN must include the statement number of the related STORE statement.
DL/I	This statement may be used to add a segment occurrence. If the data set is defined with a primary key, a value for the primary key field must be provided. In the case of a GSAM database, records must be added at the end of the database (due to GSAM restrictions). The Natural system variable *ISN is not available.
SQL	This statement may be used to add a row to a table. The PASSWORD, CIPHER, and GIVING NUMBER clauses cannot be used. The STORE statement corresponds with the SQL statement INSERT. The Natural system variable *ISN is not available.
VSAM	If the data set is defined with a primary key, a value for the primary key field must be provided. The Natural system variable *ISN contains the VSAM RBA/RRN assigned to the new record as a result of the STORE statement execution. A subsequent reference to *ISN must include the statement number of the related STORE statement. For VSAM databases, the Natural system variable *ISN is available only for ESDS and RRDS files.

Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S			A												yes	no
<i>operand2</i>	C	S				N											yes	no
<i>operand3</i>	C	S				N	P		B *								no	yes
<i>operand4</i>		S	A		A	N	P	I	F	B	D	T	L				no	no
<i>operand5</i>	C	S	A		A	N	P	I	F	B	D	T	L				yes	no

* Format B of *operand3* may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
<i>view-name</i>	View Name: As <i>view-name</i>, you specify the name of a view, which must have been defined either in a DEFINE DATA statement or outside the program in a global or local data area. In reporting mode, <i>view-name</i> is the name of a DDM if no <code>DEFINE DATA LOCAL</code> statement is used.
<code>PASSWORD=operand1</code>	PASSWORD Clause: The <code>PASSWORD</code> clause is applicable only for an Adabas or VSAM database. This clause is used to provide a password (<i>operand1</i>) when updating data from a file which is password-protected. The password (<i>operand1</i>) may be specified as an alphanumeric constant or as an alphanumeric variable. It may consist of up to 8 characters, and must not contain special characters or embedded blanks. If the password is specified as a constant, it must be enclosed in apostrophes. For further information, see the statements FIND and PASSW.
<code>CIPHER=operand2</code>	CIPHER Clause: The <code>CIPHER</code> clause is applicable only for an Adabas or VSAM database. This clause is used to provide a cipher key (<i>operand2</i>) when updating data from a file which is enciphered. The cipher key (<i>operand2</i>) may be specified as a numeric constant with 8 digits or as a user-defined variable with format/length N8. For further information, see the statement FIND.
<code>USING NUMBER operand3</code>	USING NUMBER Clause: This clause can only be used for an Adabas or VSAM database. For VSAM databases, this clause is only valid for VSAM RRDS, in which case a user-supplied RRN (relative record number) corresponds to the ISN as described above.
<code>GIVING NUMBER operand3</code>	GIVING NUMBER Clause: This clause is used to store a record with a user-supplied Adabas ISN (range from 1 to 4294967295). If a record with the specified ISN already exists, an error message will be returned and the execution of the program will be terminated unless <code>ON ERROR</code> processing was specified.
<code>SET/WITH operand4=operand5</code>	SET/WITH Clause: <code>SET/WITH</code> can be used in reporting mode to specify the fields for which values are being provided. Any field defined in the file that is not specified in the <code>SET</code> clause will contain a null value in the new record. This clause is not permitted if a DEFINE DATA statement is used, because in that case the <code>STORE</code> statement always refers to the entire view as defined in the <code>DEFINE DATA</code> statement.

Syntax Element	Description
	DL/I-Specific Considerations: A segment of variable length is stored with the minimum length necessary to contain all fields as specified with the <code>STORE</code> statement. The segment length will never be less than the minimum size specified in the <code>SEGM</code> macro of the DBD. Values must be provided for the segment sequence field, and for all sequence fields of the ancestors. Only I/O (sensitive) fields may be provided. If a multiple-value field or a periodic group is defined as variable in length, at the end of the segment only the occurrences as specified in the <code>STORE</code> statement are written to the segment and define the segment length.
<code>USING SAME (r)</code>	USING SAME Clause: In reporting mode, this clause can be used to indicate that the same field values as read in the statement referenced by the <code>STORE</code> statement (<code>FIND</code>, <code>GET</code>, <code>READ</code>) are to be used to add a new record. The statement reference notation (<i>r</i>) may be specified as a source-code line number or as a statement label. This clause is not permitted if a <code>DEFINE DATA</code> statement is used, because in that case the <code>STORE</code> statement would always refers to the entire view, as defined in the <code>DEFINE DATA</code> statement.

Example

```

** Example 'STOEX1S': STORE (structured mode)
**
** CAUTION: Executing this example will modify the database records!
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
2 PERSONNEL-ID
2 NAME
2 FIRST-NAME
2 MAR-STAT
2 BIRTH
2 CITY
2 COUNTRY
*
1 #PERSONNEL-ID (A8)
1 #NAME (A20)
1 #FIRST-NAME (A15)
1 #BIRTH-D (D)
1 #MAR-STAT (A1)
1 #BIRTH (A8)
1 #CITY (A20)
1 #COUNTRY (A3)

```

```

1 #CONF          (A1)
END-DEFINE
*
REPEAT
  INPUT 'ENTER A PERSONNEL ID AND NAME (OR ''END'' TO END)' //
    'PERSONNEL-ID : ' #PERSONNEL-ID //
    'NAME          : ' #NAME          /
    'FIRST-NAME    : ' #FIRST-NAME

  /*
  /*  VALIDATE ENTERED DATA
  /*
  IF #PERSONNEL-ID = 'END' OR #NAME = 'END'
    STOP
  END-IF
  IF #NAME = ' '
    REINPUT WITH TEXT 'ENTER A LAST-NAME' MARK 2 AND SOUND ALARM
  END-IF
  IF #FIRST-NAME = ' '
    REINPUT WITH TEXT 'ENTER A FIRST-NAME' MARK 3 AND SOUND ALARM
  END-IF
  /*
  /*  ENSURE PERSON IS NOT ALREADY ON FILE
  /*
  FIND NUMBER EMPL-VIEW WITH PERSONNEL-ID = #PERSONNEL-ID
  IF *NUMBER > 0
    REINPUT 'PERSON WITH SAME PERSONNEL-ID ALREADY EXISTS'
      MARK 1 AND SOUND ALARM
  END-IF
  MOVE 'N' TO #CONF
  /*
  /*  GET FURTHER INFORMATION
  /*
  INPUT
    'ADDITIONAL PERSONNEL DATA'          ////
    'PERSONNEL-ID          :' #PERSONNEL-ID (AD=IO) /
    'NAME                  :' #NAME          (AD=IO) /
    'FIRST-NAME            :' #FIRST-NAME    (AD=IO) ///
    'MARITAL STATUS        :' #MAR-STAT      /
    'DATE OF BIRTH (YYYYMMDD) :' #BIRTH      /
    'CITY                  :' #CITY          /
    'COUNTRY (3 CHARACTERS) :' #COUNTRY      //
    'ADD THIS RECORD (Y/N)  :' #CONF          (AD=M)
  /*
  /*  ENSURE REQUIRED FIELDS CONTAIN VALID DATA
  /*
  IF NOT (#MAR-STAT = 'S' OR = 'M' OR = 'D' OR = 'W')
    REINPUT TEXT 'ENTER VALID MARITAL STATUS S=SINGLE ' -
      'M=MARRIED D=DIVORCED W=WIDOWED' MARK 1
  END-IF
  IF NOT (#BIRTH = MASK(YYYYMMDD) AND #BIRTH = MASK(1582-2699))
    REINPUT TEXT 'ENTER CORRECT DATE' MARK 2
  END-IF

```



```

IF #CITY = ' '
    REINPUT TEXT 'ENTER A CITY NAME' MARK 3
END-IF
IF #COUNTRY = ' '
    REINPUT TEXT 'ENTER A COUNTRY CODE' MARK 4
END-IF
IF NOT (#CONF = 'N' OR= 'Y')
    REINPUT TEXT 'ENTER Y (YES) OR N (NO)' MARK 5
END-IF
IF #CONF = 'N'
    ESCAPE TOP
END-IF
/*
/*  ADD THE RECORD
/*
MOVE EDITED #BIRTH TO #BIRTH-D (EM=YYYYMMDD)
/*
EMPL-VIEW.PERSONNEL-ID := #PERSONNEL-ID
EMPL-VIEW.NAME         := #NAME
EMPL-VIEW.FIRST-NAME   := #FIRST-NAME
EMPL-VIEW.MAR-STAT     := #MAR-STAT
EMPL-VIEW.BIRTH        := #BIRTH-D
EMPL-VIEW.CITY         := #CITY
EMPL-VIEW.COUNTRY      := #COUNTRY
/*
STORE RECORD IN EMPL-VIEW
/*
END OF TRANSACTION
/*
WRITE NOTITLE 'RECORD HAS BEEN ADDED'
/*
END-REPEAT
END

```

Output of Program STOEX1S:

```

ENTER A PERSONNEL ID AND NAME (OR 'END' TO END)

PERSONNEL-ID : 90001100

NAME          : JONES
FIRST-NAME    : EDWARD

```

After entering and confirming the personnel key data, additional personnel data fields are displayed for input:

ADDITIONAL PERSONNEL DATA

PERSONNEL-ID : 90001100
NAME : JONES
FIRST-NAME : EDWARD

MARITAL STATUS :
DATE OF BIRTH (YYYYMMDD) :
CITY :
COUNTRY (3 CHARACTERS) :

ADD THIS RECORD (Y/N) : N

Equivalent reporting-mode example: [STOEX1R](#).

139

SUBTRACT

▪ Function	1086
▪ Syntax 1 - SUBTRACT Statement without GIVING Clause	1086
▪ Syntax 2 - SUBTRACT Statement with GIVING Clause	1087
▪ Example	1088

Related Statements: [ADD](#) | [COMPRESS](#) | [COMPUTE](#) | [DIVIDE](#) | [EXAMINE](#) | [MOVE](#) | [MOVE ALL](#) | [MULTIPLY](#) | [RESET](#) | [SEPARATE](#)

Belongs to Function Group: *Arithmetic and Data Movement Operations*

Function

The SUBTRACT statement is used to subtract one or more arithmetic expressions or operands from another operand.

Syntax 1 - SUBTRACT Statement without GIVING Clause

```
SUBTRACT [ROUNDED] { (arithmetic-expression) } ... FROM operand2
                  operand1
```

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S	A		N	N	P	I	F	D	T					yes	no
<i>operand2</i>		S	A		M	N	P	I	F	D	T					yes	no

Syntax Element Description:

Syntax Element	Description
<i>arithmetic-expression</i>	See Arithmetic Expression in the COMPUTE statement.
<i>operand1</i> FROM <i>operand2</i>	Operands: <i>operand2</i> is the minuend, <i>operand1</i> is the subtrahend, hence the statement is equivalent to: <i>operand2</i> := <i>operand2</i> - <i>operand1</i> As for the formats of the operands, see also <i>Rules for Arithmetic Assignments, Performance Considerations for Mixed Formats</i> in the <i>Programming Guide</i>.
ROUNDED	ROUNDED Option: If you specify the keyword ROUNDED, the result will be rounded. For information on rounding, see <i>Rules for Arithmetic Assignment, Field Truncation and Field Rounding</i> in the <i>Programming Guide</i>.

Syntax 2 - SUBTRACT Statement with GIVING Clause

```
SUBTRACT    { (arithmetic-expression) } ... FROM { (arithmetic-expression) } GIVING
[ROUNDED]   { operand1 }                        { operand2 }                  operand3
```

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition		
<i>operand1</i>	C	S	A		N			N	P	I	F		D	T				yes	no
<i>operand2</i>	C	S	A		N			N	P	I	F		D	T				yes	no
<i>operand3</i>		S	A		M	A	U	N	P	I	F	B*	D	T				yes	yes

* Format B of *operand3* may be used only with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
<i>arithmetic-expression</i>	See Arithmetic Expression in the COMPUTE statement.
GIVING	GIVING Clause: When the GIVING clause is used, <i>operand2</i> will <i>not</i> be modified, and the result will be stored in <i>operand3</i> .
<i>operand1</i> FROM <i>operand2</i> GIVING <i>operand3</i>	Operands: <i>operand2</i> is the minuend, <i>operand1</i> is the subtrahend, <i>operand3</i> is the result field, hence the statement is equivalent to: $operand3 := operand2 - operand1$ As for the formats of the operands, see also the section <i>Performance Considerations for Mixed Formats</i> in the <i>Programming Guide</i> .
ROUNDED	ROUNDED Option: If you specify the keyword ROUNDED, the result will be rounded. For information on rounding, see <i>Rules for Arithmetic Assignment, Field Truncation and Field Rounding</i> in the <i>Programming Guide</i> .

Example

```
** Example 'SUBEX1': SUBTRACT
*****
DEFINE DATA LOCAL
1 #A (P2) INIT <50>
1 #B (P2)
1 #C (P1.1) INIT <2.4>
END-DEFINE
*
SUBTRACT 6 FROM #A
WRITE NOTITLE 'SUBTRACT 6 FROM #A          ' 10X '=' #A
*
SUBTRACT 6 FROM 11 GIVING #A
WRITE          'SUBTRACT 6 FROM 11 GIVING #A  ' 10X '=' #A
*
SUBTRACT 3 4 FROM #A GIVING #B
WRITE          'SUBTRACT 3 4 FROM #A GIVING #B ' 10X '=' #A '=' #B
*
SUBTRACT -3 -4 FROM #A GIVING #B
WRITE          'SUBTRACT -3 -4 FROM #A GIVING #B' 10X '=' #A '=' #B
*
SUBTRACT ROUNDED 2.06 FROM #C
WRITE          'SUBTRACT ROUNDED 2.06 FROM #C  ' 10X '=' #C
*
END
```

Output of Program SUBEX1:

```
SUBTRACT 6 FROM #A          #A: 44
SUBTRACT 6 FROM 11 GIVING #A #A: 5
SUBTRACT 3 4 FROM #A GIVING #B #A: 5 #B: -2
SUBTRACT -3 -4 FROM #A GIVING #B #A: 5 #B: 12
SUBTRACT ROUNDED 2.06 FROM #C #C: 0.3
```

140

SUSPEND IDENTICAL SUPPRESS

■ Function	1090
■ Syntax Description	1090
■ Examples	1090

SUSPEND IDENTICAL [SUPPRESS] [(rep)]

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [AT END OF PAGE](#) | [AT TOP OF PAGE](#) | [CLOSE PRINTER](#) | [DEFINE PRINTER](#) | [DISPLAY](#) | [EJECT](#) | [FORMAT](#) | [NEWPAGE](#) | [PRINT](#) | [SKIP](#) | [WRITE](#) | [WRITE TITLE](#) | [WRITE TRAILER](#)

Belongs to Function Group: [Creation of Output Reports](#)

Function

The `SUSPEND IDENTICAL SUPPRESS` statement is used to suspend the Natural session parameter setting `IS=ON` (which suppresses the output of identical field values) for the processing of one record.

See also session parameter `IS` in the [Parameter Reference](#).

Syntax Description

Syntax Element	Description
<code>(rep)</code>	Report Specification: The notation <code>(rep)</code> may be used to specify the identification of the report for which the <code>SUSPEND IDENTICAL SUPPRESS</code> statement is applicable. A value in the range 0 - 31 or a logical name which has been assigned using the DEFINE PRINTER statement may be specified. If <code>(rep)</code> is not specified, the <code>SUSPEND IDENTICAL SUPPRESS</code> statement will be applicable to the first report (Report 0). For information on how to control the format of an output report created with Natural, see <i>Report Format and Control</i> in the <i>Programming Guide</i>.

Examples

- [Example 1 - Program with SUSPEND IDENTICAL SUPPRESS](#)

- Example 2 - Same as Previous Program, but without SUSPEND IDENTICAL SUPPRESS

Example 1 - Program with SUSPEND IDENTICAL SUPPRESS

```

** Example 'SISEX1': SUSPEND IDENTICAL SUPPRESS
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 FIRST-NAME
  2 NAME
  2 CITY
1 VEH-VIEW VIEW OF VEHICLES
  2 PERSONNEL-ID
  2 MAKE
END-DEFINE
*
LIMIT 15
*
RD. READ EMPLOY-VIEW BY NAME STARTING FROM 'JONES'
/*
  SUSPEND IDENTICAL SUPPRESS
/*
  FD. FIND VEH-VIEW WITH PERSONNEL-ID = PERSONNEL-ID (RD.)
  IF NO RECORDS FOUND
    MOVE '***NO CAR***' TO MAKE
  END-NOREC
  DISPLAY NOTITLE
    NAME (RD.) (IS=ON)
    FIRST-NAME (RD.) (IS=ON)
    MAKE (FD.)
  END-FIND
/*
END-READ
END

```

Output of Program SISEX1:

NAME	FIRST-NAME	MAKE
JONES	VIRGINIA	CHRYSLER
JONES	MARSHA	CHRYSLER
JONES	ROBERT	CHRYSLER
JONES	LILLY	GENERAL MOTORS
JONES	EDWARD	FORD
JONES	MARTHA	MG
		GENERAL MOTORS
		GENERAL MOTORS

SUSPEND IDENTICAL SUPPRESS

JONES	LAUREL	GENERAL MOTORS
JONES	KEVIN	DATSUN
JONES	GREGORY	FORD
JONES	EDWARD	***NO CAR***
JOPER	MANFRED	***NO CAR***
JOUSSELIN	DANIEL	RENAULT
JUBE	GABRIEL	***NO CAR***
JUNG	ERNST	***NO CAR***
JUNKIN	JEREMY	***NO CAR***

Example 2 - Same as Previous Program, but without SUSPEND IDENTICAL SUPPRESS

```
** Example 'SISEX2': SUSPEND IDENTICAL SUPPRESS (compare with SISEX1)
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 FIRST-NAME
  2 NAME
  2 CITY
1 VEH-VIEW VIEW OF VEHICLES
  2 PERSONNEL-ID
  2 MAKE
END-DEFINE
*
LIMIT 15
RD. READ EMPLOY-VIEW BY NAME STARTING FROM 'JONES'
  /*
  /* SUSPEND IDENTICAL SUPPRESS      /* statement removed
  /*
  FD. FIND VEH-VIEW WITH PERSONNEL-ID = PERSONNEL-ID (RD.)
    IF NO RECORDS FOUND
      MOVE '***NO CAR***' TO MAKE
    END-NOREC
    DISPLAY NOTITLE
      NAME (RD.) (IS=ON)
      FIRST-NAME (RD.) (IS=ON)
      MAKE (FD.)
    END-FIND
  /*
END-READ
END
```

Output of Program SISEX2:

NAME	FIRST-NAME	MAKE
JONES	VIRGINIA	CHRYSLER
	MARSHA	CHRYSLER
		CHRYSLER
	ROBERT	GENERAL MOTORS
	LILLY	FORD
		MG
	EDWARD	GENERAL MOTORS
	MARTHA	GENERAL MOTORS
	LAUREL	GENERAL MOTORS
	KEVIN	DATSUN
	GREGORY	FORD
	EDWARD	***NO CAR***
JOPER	MANFRED	***NO CAR***
JOUSSELIN	DANIEL	RENAULT
JUBE	GABRIEL	***NO CAR***
JUNG	ERNST	***NO CAR***
JUNKIN	JEREMY	***NO CAR***

141

TERMINATE

■ Function	1096
■ Syntax Description	1096
■ Program Receiving Control after Termination	1097
■ Example	1097

TERMINATE [*operand1* [*operand2*]]

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Function

The `TERMINATE` statement is used to terminate a Natural session. A `TERMINATE` statement may be placed anywhere within a Natural program. When a `TERMINATE` statement is executed, no end-of-page or end-loop processing will be performed.

For Natural RPC: See Notes on Natural Statements on the Server in the Natural RPC (Remote Procedure Call) documentation.

Syntax Description

Operand Definition Table:

Operand	Possible Structure			Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S						N	P	I						yes	no
<i>operand2</i>	C	S	A			A	U	N	P	I	F	B	D	T	L	C	yes

Syntax Element Description:

Syntax Element	Description
<i>operand1</i>	<i>operand1</i> may be used to pass a return code to the program receiving control when Natural terminates. For example, a return code setting may be passed to the operating system via Register 15. The value supplied for <i>operand1</i> must be in the range 0 - 255.
<i>operand2</i>	<i>operand2</i> may be used to pass additional information to the program which receives control after the termination.

Program Receiving Control after Termination

After the termination of the Natural session, the program whose name is specified with the profile parameter PROGRAM will receive control.

Example

```
** Example 'TEREX1': TERMINATE
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
  2 SALARY (1)
*
1 #PNUM      (A8)
1 #PASSWORD (A8)
END-DEFINE
*
INPUT 'ENTER PASSWORD:' #PASSWORD
*
IF #PASSWORD NE 'USERPASS'
/*
  TERMINATE
/*
END-IF
*
INPUT 'ENTER PERSONNEL NUMBER:' #PNUM
*
FIND EMPLOY-VIEW WITH PERSONNEL-ID = #PNUM
  DISPLAY NAME SALARY (1)
END-FIND
*
END
```


142

UPDATE

■ Function	1100
■ Restrictions	1101
■ Database-Specific Considerations	1101
■ Syntax Description	1102
■ Example	1103

Structured Mode Syntax

UPDATE [RECORD] [IN] [STATEMENT] [(r)]

Reporting Mode Syntax

UPDATE [RECORD] [IN] [STATEMENT] [(r)]

[SET
WITH
USING] { SAME [RECORD]
{ operand1=operand2 } ... }

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [ACCEPT/REJECT](#) | [AT BREAK](#) | [AT START OF DATA](#) | [AT END OF DATA](#) | [BACKOUT TRANSACTION](#) | [BEFORE BREAK PROCESSING](#) | [DELETE](#) | [END TRANSACTION](#) | [FIND](#) | [GET](#) | [GET SAME](#) | [GET TRANSACTION DATA](#) | [HISTOGRAM](#) | [LIMIT](#) | [PASSW](#) | [PERFORM BREAK PROCESSING](#) | [READ](#) | [READLOB](#) | [RETRY](#) | [STORE](#) | [UPDATELOB](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The `UPDATE` statement is used to update one or more fields of a record in a database. The record to be updated must have been previously selected with a [FIND](#), [GET](#) or [READ](#) statement (or, for Adabas only, with a [STORE](#) statement).

Hold Status

The use of the `UPDATE` statement causes each record read for processing in the corresponding [FIND](#) or [READ](#) statement to be placed in exclusive hold.

For further information, see *Record Hold Logic* (in the *Programming Guide*).

Restrictions

The `UPDATE` statement

- must not be entered on the same line as the statement used to select the record to be updated;
- cannot be applied to Entire System Server views.

Database-Specific Considerations

DL/I	The <code>UPDATE</code> statement can be used to update a segment in a DL/I database. If necessary, the segment length is increased to accommodate all fields specified with the <code>UPDATE</code> statement. If a multiple-value field or a periodic group is defined as variable in length, only the occurrences as specified in the <code>UPDATE</code> statement are written to the segment. The DL/I AIX field name cannot be used in an <code>UPDATE</code> statement. AIX fields, however, may be updated by referring to the source field which comprises the AIX field. DL/I sequence fields cannot be updated because of DL/I restrictions. Due to GSAM restrictions, the <code>UPDATE</code> statement cannot be used for GSAM databases.
VSAM	VSAM primary keys cannot be updated because of VSAM restrictions. The DL/I AIX field name cannot be used in an <code>UPDATE</code> statement. AIX fields, however, may be updated by referring to the source field which comprises the AIX field.
SQL	The <code>UPDATE</code> statement can be used to update a row in a database table. It corresponds with the SQL statement <code>UPDATE WHERE CURRENT OF CURSOR</code> (Positioned UPDATE), which means that only the row which was read last can be updated. Only columns (fields) that have been modified within the program, as well as columns that might have been (but not necessarily actually have been) modified outside the program (for example, as input fields in maps), are updated. On all other platforms, all columns are updated. With most SQL databases, a row that was read with a FIND SORTED BY or with a READ LOGICAL statement cannot be updated.

Syntax Description

Operand Definition Table:

Operand	Possible Structure			Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>		S	A			A	N	P	I	F	B	D	T	L		no	no
<i>operand2</i>	C	S	A			A	N	P	I	F	B	D	T	L		yes	no

Syntax Element Description:

Syntax Element	Description
(<i>r</i>)	Statement Reference: The notation (<i>r</i>) is used to indicate the statement in which the record to be modified was read. <i>r</i> may be specified as a source-code line number or as a statement label. If no reference is specified, the UPDATE statement will reference the innermost active READ or FIND processing loop. If no READ or FIND loop is active, it will reference the last preceding GET (or STORE) statement. Note: The UPDATE statement must be placed within the READ or FIND loop it references.
USING SAME	USING SAME Clause: This clause is not permitted if a DEFINE DATA statement is used, because in that case the UPDATE statement always refers to the entire view as defined in the DEFINE DATA statement. The layout of the record buffer or format buffer may be declared using the OBTAIN statement. USING SAME can be used in reporting mode to indicate that the same fields as read in the statement referenced by the UPDATE statement are to be used for the update function. In this case, the most recent value assigned to each database field will be used to update the field. If no new value has been assigned, the old value will be used. If the field to be updated is an array range of a multiple-value field or periodic group and you use a variable index for this array range, the latest range will be updated. This means that if the index variable is modified after the record has been read and before the UPDATE USING SAME (reporting mode) or UPDATE (structured mode) statement respectively is executed, the range updated will not be the same as the range read.
SET/WITH <i>operand1=operand2</i>	SET/WITH Clause:

Syntax Element	Description
	This clause can be used in reporting mode to specify the fields to be updated and the values to be used. This clause is not permitted if a <code>DEFINE DATA</code> statement is used, because in that case the <code>UPDATE</code> statement always refers to the entire view as defined in the <code>DEFINE DATA</code> statement. Note: For DL/I databases: If the <code>SET/WITH</code> clause is used, only I/O (sensitive) fields can be provided. A segment sequence field cannot be updated (DELETE and STORE must be used instead).

Example

```

** Example 'UPDEX1S': UPDATE (structured mode)
**
** CAUTION: Executing this example will modify the database records!
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 FIRST-NAME
  2 CITY
*
1 #NAME (A20)
END-DEFINE
*
INPUT 'ENTER A NAME:' #NAME (AD=M)
IF #NAME = ' '
  STOP
END-IF
*
FIND EMPLOY-VIEW WITH NAME = #NAME
  IF NO RECORDS FOUND
    REINPUT WITH 'NO RECORDS FOUND' MARK 1
  END-NOREC
  INPUT 'NAME:      ' NAME (AD=0) /
        'FIRST NAME:' FIRST-NAME (AD=M) /
        'CITY:      ' CITY (AD=M)
  UPDATE
  END TRANSACTION
END-FIND
*
END

```

Output of Program SUBEX1S

```
ENTER A NAME: BROWN
```

After entering and confirming name:

```
NAME: BROWN  
FIRST NAME: KENNETH  
CITY: DERBY
```

Equivalent reporting-mode example: [UPDEX1R](#).

143

UPDATE (SQL)

▪ Function	1106
▪ Syntax 1 - Searched UPDATE	1106
▪ Syntax 2 - Positioned UPDATE	1109
▪ Examples	1110

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Belongs to Function Group: [Database Access and Update](#)

See also *UPDATE - SQL* in the *Natural for DB2* part of the *Database Management System Interfaces* documentation.

Function

The SQL `UPDATE` statement is used to perform an `UPDATE` operation on either rows in a table without using a cursor ("**s**earched" `UPDATE`) or columns in a row to which a cursor is positioned ("**p**ositioned" `UPDATE`).

Two different syntax structures are possible.

Syntax 1 - Searched UPDATE

The "Searched" `UPDATE` statement is a stand-alone statement not related to any `SELECT` statement. With a single statement you can update zero, one, multiple or all rows of a table. The rows to be updated are determined by a *search-condition* that is applied to the table. Optionally, view names and table names can be assigned a *correlation-name*.



Note: The number of rows that have actually been updated with a "searched" `UPDATE` can be ascertained by using the system variable `*ROWCOUNT`.

UPDATE {

view-name [*period-clause*] [*correlation-name*] SET *

table-name [*period-clause*] [*correlation-name*] [*include-columns*] SET

assignment-list

}

[WHERE *search-condition*]

[

WITH {

RR

RS

CS

}

]

[SKIP LOCKED DATA] [QUERYNO *integer*]

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Syntax Element Description - Syntax 1:

Syntax Element	Description						
<i>view-name</i>	View Name: Refers to the name of a Natural view as defined in the <code>DEFINE DATA</code> statement. For further information, see <i>view-name</i> (in the section <i>Basic Syntactical Items</i>).						
<i>period-clause</i>	Period Clause: Specifies that a period clause applies to the target of the update operation. For further information, see <i>Period Clause</i> in the section <i>Basic Syntactical Items</i> .						
<i>correlation-name</i>	Correlation Name: The item <i>correlation-name</i> represents an alias name for a <i>table-name</i> . For further information, see <i>correlation-name</i> (in the section <i>Basic Syntactical Items</i>).						
<i>include-columns</i>	Include Columns Clause: Specifies a set of columns that are included, along with the columns of <i>tables-name</i> in the result table of the <code>UPDATE</code> statement, when it is nested in the <code>FROM</code> clause of a <code>SELECT</code> statement. The included columns are appended to the end of the list of columns. For further details, see <i>include-columns</i> .						
SET	SET Clause: If a view has been specified for updating, an asterisk (*) has to be specified in the <code>SET</code> clause, because all columns of the view must be updated. If a table has been specified for updating, the <code>SET</code> clause must contain either an <i>assignment-list</i> or the name of the view which contains the columns to be updated.						
<i>assignment-list</i>	Assignment List: See <i>Assignment List</i> below.						
WHERE <i>search-condition</i>	WHERE Clause: This clause is used to specify the selection criteria for the rows to be updated. If no <code>WHERE</code> clause is specified, the entire table is updated.						
WITH	WITH - Isolation Level Clause: This clause allows the explicit specification of the isolation level used when locating the row to be updated. For detailed information, see <i>WITH isolation-level</i> in the description of the <code>SELECT</code> statement.						
	<table> <tr> <td>CS</td><td>Cursor Stability</td></tr> <tr> <td>RR</td><td>Repeatable Read</td></tr> <tr> <td>RS</td><td>Read Stability</td></tr> </table>	CS	Cursor Stability	RR	Repeatable Read	RS	Read Stability
CS	Cursor Stability						
RR	Repeatable Read						
RS	Read Stability						
SKIP LOCKED DATA	SKIP LOCKED DATA Clause:						

Syntax Element	Description
	Specifies that rows are skipped when incompatible locks are held on the row by other transactions.
QUERYNO <i>integer</i>	QUERYNO Clause: This clause allows you to explicitly specify the number to be used in EXPLAIN output and trace records for this statement. The number is used as QUERYNO column in the PLAN_TABLE for the rows that contain information on this statement.

Assignment List

$\left\{ \begin{array}{l} \text{column-name} = \left\{ \begin{array}{l} \text{scalar-expression} \\ \text{DEFAULT} \\ \text{NULL} \end{array} \right\} \end{array} \right\}, \dots$

In an *assignment-list*, you can assign values to one or more columns. A value can be a *scalar-expression*, DEFAULT or NULL. For further information, see [Scalar Expressions](#).

If the value NULL has been assigned, it means that the addressed field is to contain no value (not even the value “0” or “blank”).

Alternative:

$(\text{column-name}, \dots) = \left(\left\{ \begin{array}{l} \text{scalar-expression} \\ \text{DEFAULT} \\ \text{NULL} \end{array} \right\}, \dots, \left\{ \begin{array}{l} \text{row-fullselect} \end{array} \right\} \right)$

Syntax Element Description:

Syntax Element	Description
<i>column-name</i>	Column Name: Specifies the name of a column of the result table of the MERGE statement that is not the same name as another include column or a column in the target table.
DEFAULT	DEFAULT Option: Specifies that the default value is used based on how the corresponding column is defined in the table.
NULL	NULL Option: Specifies the null value as the new value of the column. If the value NULL has been assigned, it means that the addressed field is to contain no value (not even the value 0 or “blank”).

Syntax Element	Description
<i>row-fullselect</i>	Row Full Select Option: Specifies a full select that returns a single row. The column values are assigned to the corresponding column-names.

Syntax 2 - Positioned UPDATE

The “positioned” UPDATE statement always refers to a cursor within a database loop. Thus, the table or view referenced by a positioned UPDATE statement must be the same as the one referenced by the corresponding SELECT statement; otherwise an error message is returned. A positioned UPDATE cannot be used with a non-cursor selection.

Common Set Syntax:

```
UPDATE { view-name SET *
        view-name SET assignment-list } [WHERE CURRENT OF CURSOR (r)]
```

Extended Set Syntax:

```
UPDATE { view-name SET *
        view-name SET
        assignment-list } [WHERE CURRENT OF CURSOR (r) [ FOR ROW { [:]host-variable
        integer } OF ROWSET ] ]
```

Syntax Element Description - Syntax 2:

Syntax Element	Description
<i>view-name</i>	Natural View: Refers to the name of a Natural view as defined in the DEFINE DATA statement; see also <i>view-name</i> (in the section <i>Basic Syntactical Items</i>).
SET *	SET Clause:
SET <i>assignment-list</i>	If a Natural view has been specified for updating, an asterisk (*) has to be specified in the SET clause, because all columns of the view must be updated. If a table has been specified for updating, the SET clause must contain either an <i>assignment-list</i> or the name of the view which contains the columns to be updated.
WHERE CURRENT OF CURSOR (<i>r</i>)	Statement Reference: The (<i>r</i>) notation is used to reference the statement which was used to select the row to be updated. If no statement reference is specified, the UPDATE statement

Syntax Element	Description
	is related to the innermost active processing loop in which a database record was selected.
FOR ROW ... OF ROWSET	FOR ROW ... OF ROWSET Clause: This clause belongs to the SQL Extended Set. The optional FOR ROW ... OF ROWSET clause for positioned SQL UPDATE statements specifies which row of the current rowset has to be updated. It should only be specified if the UPDATE statement is related to a SELECT statement, which uses rowset positioning and which has column arrays in the INTO clause (see into-clause). If this clause is omitted, all rows of the current rowset are updated by the values in the assignment-list. This clause cannot be specified if <i>view-name</i> SET * is specified.

Examples

- [Example 1 - Searched UPDATE](#)
- [Example 2 - Searched UPDATE with assignment-list](#)
- [Example 3 - Positioned UPDATE](#)
- [Example 4 - Positioned UPDATE with assignment-list](#)

Example 1 - Searched UPDATE

```

DEFINE DATA LOCAL
1 PERS VIEW OF SQL-PERSONNEL
2 NAME
2 AGE
...
END-DEFINE
...
ASSIGN AGE = 45
ASSIGN NAME = 'SCHMIDT'
UPDATE PERS SET * WHERE NAME = 'SCHMIDT'
...

```

Example 2 - Searched UPDATE with assignment-list

```
DEFINE DATA LOCAL
1 PERS VIEW OF SQL-PERSONNEL
2 NAME
2 AGE
...
END-DEFINE
...
UPDATE SQL-PERSONNEL SET AGE = AGE + 1 WHERE NAME = 'SCHMIDT'
...
```

Example 3 - Positioned UPDATE

```
DEFINE DATA LOCAL
1 PERS VIEW OF SQL-PERSONNEL
2 NAME
2 AGE
...
END-DEFINE
...
SELECT * INTO PERS FROM SQL_PERSONNEL WHERE NAME = 'SCHMIDT'
COMPUTE AGE = AGE + 1
UPDATE PERS SET * WHERE CURRENT OF CURSOR
END-SELECT
...
```

Example 4 - Positioned UPDATE with assignment-list

```
DEFINE DATA LOCAL
1 PERS VIEW OF SQL-PERSONNEL
2 NAME
2 AGE
...
END-DEFINE
...
SELECT * INTO PERS FROM SQL-PERSONNEL WHERE NAME = 'SCHMIDT'
UPDATE SQL-PERSONNEL SET AGE = AGE + 1 WHERE CURRENT OF CURSOR
END-SELECT
...
```


144

UPDATELOB

■ Function	1114
■ Restrictions	1114
■ Syntax Description	1115
■ System Variable Available with UPDATELOB	1116
■ Functional Considerations	1117
■ Examples	1117

```
UPDATELOB [OF] [RECORD] [(r)] [IN] [FILE] view-name  
[PASSWORD=operand1]  
[CIPHER=operand2]  
[[STARTING] [AT] OFFSET [=] operand3]  
[ TRUNCATE { [REMAINDER] } [AT] OFFSET ] ]
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [READ](#) | [FIND](#) | [GET](#) | [READLOB](#) | [UPDATE](#)

Belongs to Function Group: [Database Access and Update](#)

Function

The UPDATELOB statement is used to update a data segment of a LOB field (Large Object field) in a database record. The position of the value modification is freely selectable. The record to be updated must have been previously selected with a [FIND](#), [READ](#) or [GET](#) statement or created with a [STORE](#) statement.

Hold Status

The use of the UPDATELOB statement causes each record read for processing in the corresponding FIND, READ or GET statement to be placed in exclusive hold.

For further information, see *Record Hold Logic* in the *Programming Guide*.

Restrictions

The UPDATELOB statement

- can only be used for access to Adabas databases;
- must not be entered on the same line as the statement used to select the record to be updated;
- is only applicable to update a single LOB field.

Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats												Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S				A											yes	no
<i>operand2</i>	C	S					N										yes	no
<i>operand3</i>	C	S					N	P	I	B *							yes	no

* Format B of *operand3* may be used with a length of less than or equal to 4.

Syntax Element Description:

Syntax Element	Description
(<i>r</i>)	Statement Reference: The notation (<i>r</i>) is used to indicate the statement in which the record to be modified was read or created. <i>r</i> may be specified as a source-code line number or as a statement label. You may reference a FIND, READ, GET or STORE statement. If no reference is specified, the UPDATELOB statement will reference the innermost active READ or FIND processing loop. If no READ or FIND loop is active, it will reference the last preceding GET statement. To reference a STORE statement, you have always to provide the (<i>r</i>) notation. Note: The UPDATELOB statement must be placed within the READ or FIND loop it references.
<i>view-name</i>	View Name: As <i>view-name</i>, you specify the name of a view, which must have been defined either within a DEFINE DATA statement or outside the program in a global or local data area. ■ The view has to contain just a single-valued LOB field, additional fields are not allowed. ■ If the LOB is a MU or PE field, a unique occurrence must be specified; a range notation is not allowed. ■ The LOB field must be defined in the view with a fixed (non-dynamic) length.
PASSWORD= <i>operand1</i> CIPHER= <i>operand2</i>	PASSWORD and CIPHER Clauses: The PASSWORD clause is used to provide a password when retrieving data from a file which is password-protected.

Syntax Element	Description
	The CIPHER clause is used to provide a cipher key when retrieving data from a file which is enciphered. See the statements FIND and PASSW for further information.
STARTING AT OFFSET= <i>operand3</i>	STARTING AT OFFSET Clause: Provides the start offset within the LOB field, where the operation is executed. The leftmost byte of the LOB field is offset zero (0). <i>operand3</i> must be provided either in the form of a numeric constant or as a user-defined variable, without precision digits. The field is not modified by the UPDATELOB execution. If the offset value is greater than the LOB length, the gap is filled with blanks. This means a LOB field can be updated at a position which is beyond its length. If this clause is omitted, start offset (0) is assumed.
TRUNCATE REMAINDER or TRUNCATE AT OFFSET	TRUNCATE Clause: If TRUNCATE REMAINDER is specified, the remaining LOB field data is truncated after the new segment has been written into the LOB field. This makes the end of the inserted segment to the end of the LOB field. If TRUNCATE AT OFFSET is specified, the data behind the specified starting offset is truncated. A segment insert into the LOB field is not performed. After this, the LOB length is equal to <i>operand3</i>. If this clause is omitted, the data behind the inserted segment is preserved.

System Variable Available with UPDATELOB

The Natural system variable *NUMBER is provided with the UPDATELOB statement.

The format/length of this system variable is P10. This format/length cannot be changed.

System Variable	Explanation
*NUMBER	The system variable *NUMBER returns the sum of the start offset and the number of characters inserted. This value represents the starting offset for the next UPDATELOB, if a consecutive area of the LOB field is replaced with multiple calls. The number of inserted characters is either the byte length of the LOB segment defined in the view or zero (0) if the TRUNCATE AT OFFSET clause was specified. The *NUMBER field returned by the UPDATELOB statement must always be provided with a reference label or number (for example, *NUMBER(0430)) when used.

Functional Considerations

- An UPDATELOB operates a record which was set into hold by an associated FIND, READ, GET or STORE statement. The link is either implicit via the current active reference or explicit with (*r*) notation.
- The view used by the associated statement and the view used by the UPDATELOB have to access the same database and file number. This is automatically assured if the views are derived from the same data definition module (DDM).
- If the insert position *operand3* is greater than the LOB length, the gap is filled with blanks. This means you may update a LOB field at a position which is beyond its length.
- You cannot replace *m* bytes with *n* bytes - or in other words, it is not admissible to substitute a LOB part with a data segment of different length.
- The value returned with *NUMBER is the high-water mark indicating the position inside the LOB where the last insert has ended. If a number of consecutive update operations is demanded, this value should always be retained as STARTING AT value for the next UPDATELOB execution.

Examples

- [Example 1 - Store New Record and Fill LOB Segment](#)
- [Example 2 - Add LOB Data to Existent Record, Piece by Piece](#)
- [Example 3 - Truncate LOB Field](#)
- [Example 4 - Read LOB Data to Existent Record and Update LOB Segment](#)

Example 1 - Store New Record and Fill LOB Segment

```

DEFINE DATA LOCAL
1 V1 VIEW OF ..
  2 PERSONNEL-ID
  2 NAME
1 V2 VIEW OF ..
  2 LOBFIELD_SEGMENT /* LOB field defined in DDM with (A1024).
END-DEFINE
*
**=====
** Store new record
**=====
V1.PERSONNEL-ID := '12345678'
V1.NAME         := 'Smith'
LAB1.
STORE V1 /* Store new record with 2 fixed length fields.
*
MOVE ALL 'X' TO LOBFIELD_SEGMENT

```

```

**=====
** Update LOB field
**=====
UPDATELOB (LAB1.) IN FILE V2  /* INSERT 1 KB SEGMENT (LOBFIELD_SEGMENT)
                               /* IN LOB.
      STARTING AT OFFSET = 2048
                               /* STORE DATA IN LOB RANGE 2049-3072.
                               /* FIRST 2 KBS ARE AUTO-FILLED WITH BLANKS BY THE DB.
END TRANSACTION
END
```

Example 2 - Add LOB Data to Existent Record, Piece by Piece

```

DEFINE DATA LOCAL
1 V1 VIEW OF EMPLOYEES-V2009
  2 PERSONNEL-ID
  2 NAME
  2 L@PICTURE
1 V2 VIEW OF EMPLOYEES-V2009
  2 PICTURE_SEGMENT /* LOB field defined in DDM with (A1024).
  2 REDEFINE PICTURE
    3 PICTURE_B (B1024)
1 #OFF (I4)
END-DEFINE
*
**=====
** Read record to be updated
**=====
LAB1.
READ (1) V1 BY PERSONNEL-ID = '60008339'
                               /* Read record and set into exclusive hold.
  RESET #OFF                  /* Start to overwrite LOB field from the beginning.
  /*=====
  /* Read data from work file and put into LOB field
  /*=====
  READ WORK FILE 7 PICTURE_B
                               /* Start to read picture data (.jpg) from work file.
LAB2.
  UPDATELOB (LAB1.) IN FILE V2
    STARTING AT OFFSET #OFF
    #OFF := *NUMBER(LAB2.) /* Keep next position to append.
  END-WORK
END-READ
**=====
END TRANSACTION
END
```

Example 3 - Truncate LOB Field

```

DEFINE DATA LOCAL
1 V1 VIEW OF EMPLOYEES-V2009
  2 PERSONNEL-ID
  2 NAME
  2 L@PICTURE
1 V2 VIEW OF EMPLOYEES-V2009
1 V3 VIEW OF EMPLOYEES-V2009
  2 PICTURE_SEGMENT /* LOB field defined in DDM with (A1024).
END-DEFINE
*
**=====
** Read record to be updated
**=====
LAB1.
READ V1 BY PERSONNEL-ID /* Read records.
  IF L@PICTURE > 10240 THEN /* Check if LOB length is too high.
LAB2.
  GET V2 RECORD *ISN(LAB1.) /* Set record to be updated into exclusive hold.
  UPDATELOB (LAB2.) IN FILE V3
    STARTING AT OFFSET 10240
    TRUNCATE AT OFFSET /* Truncate LOB data beyond 10KB.
  END TRANSACTION
END-IF
END-READ
END

```

Example 4 - Read LOB Data to Existent Record and Update LOB Segment

```

DEFINE DATA LOCAL
1 V1 VIEW OF ..
  2 NAME
1 V2 VIEW OF ..
  2 DOCUMENT_SEGMENT /* LOB field defined in DDM with (A100).
1 #ISN (I4)
1 #POS (I4)
1 #LENGTH (I4) INIT <100>
END-DEFINE
*
**=====
** Read record to be updated
**=====
INPUT (AD=T)
  / ' Read record (ISN):' #ISN
*
G1.
GET V1 RECORD #ISN /* Get record with ISN and set into exclusive hold.
*
**=====

```

```
** Read LOB data and update segment of LOB field
**=====
R1.
READLOB V2 WITH ISN = #ISN
    STARTING AT OFFSET = 3000
    ..
    #POS := *NUMBER(R1.) - #LENGTH
    ..
    IF ..
        DOCUMENT_SEGMENT := ..
        UPDATELOB (G1.) IN FILE V2    /* Update current segment in LOB field.
            STARTING AT OFFSET #POS
    END-IF
    ..
END-READLOB
*
END TRANSACTION
END
```

145

UPLOAD PC FILE

■ Function	1122
■ Syntax Description	1123
■ Example	1124

Structured Mode Syntax

```
{  UPLOAD  } {  PC  } [FILE] work-file-number [ONCE]
  READ    } { WORK }

{  RECORD operand1
  {  [AND] [SELECT]  {  [  OFFSET n
                      [  FILLER nX  ] ... operand2 } ... }
}

[GIVING LENGTH operand3]
[AT [END] [OF] [FILE] statement ... END-ENDFILE]
statement ...
END-WORK
```

Reporting Mode Syntax

```
{  UPLOAD  } {  PC  } [FILE] work-file-number [ONCE]
  READ    } { WORK }

{  RECORD {operand1 [FILLER nX]} ...
  {  [AND] [SELECT] {  [  OFFSET n
                      [  FILLER nX ] ... operand2  } ... }
}

[GIVING LENGTH operand3]
[  AT [END] [OF] [FILE]  {  statement
                        DO statement ... DOEND  }  ]

statement ...
LOOP
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [CLOSE PC FILE](#) | [DOWNLOAD PC FILE](#) | [READ WORK FILE](#)

Belongs to Function Group: [Control of Work Files / PC Files](#)

Function

The `UPLOAD PC FILE` statement is used to transfer data from a PC to a mainframe platform.

See also:

- [Natural Connection](#) and [Entire Connection](#) documentation
- [READ WORK FILE](#) statement syntax description

Syntax Description

Operand Definition Table:

Operand	Possible Structure				Possible Formats											Referencing Permitted	Dynamic Definition	
<i>operand1</i>		S	A	G		A	U	N	P	I	F	B	D	T	L	C	yes	yes
<i>operand2</i>		S	A	G		A	U	N	P	I	F	B	D	T	L	C	yes	yes
<i>operand3</i>		S								I							yes	yes

Format C is not valid for Natural Connection.

Syntax Element Description:

Syntax Element	Description
<i>work-file-number</i>	Work File Number: The number of the work file to be used. This number must correspond to one of the work file numbers for the PC as defined to Natural.
<i>operand1-2</i>	Field Specification: With <i>operand1</i> and <i>operand2</i> you specify the fields to be uploaded from the PC. The fields may be database fields or user-defined variables.
<i>statement</i>	Statement(s) to be Executed: In place of <i>statement</i> , you must supply one or several suitable statements, depending on the situation. No I/O statement may be placed with the UPLOAD PC FILE processing.
ONCE, SELECT, GIVING LENGTH RECORD	Options: For a description of the ONCE, SELECT, GIVING LENGTH options, refer to the corresponding sections in the description of the READ WORK FILE statement. The RECORD option is not permitted for PC work files. It will be rejected at runtime. When uploading data: If you wish to define a filler, you must use a dummy variable instead of the standard filler notation.
END-WORK	End of UPLOAD PC FILE Statement: In structured mode, the Natural reserved keyword END-WORK must be used to end the UPLOAD PC FILE statement.
LOOP	

Syntax Element	Description
	In reporting mode, the Natural statement LOOP is used to end the UPLOAD PC FILE statement.

Example

The following program demonstrates the use of the **UPLOAD PC FILE** statement. The data is first uploaded from the PC and then processed on the mainframe.

```

** Example 'PCUPEX1': UPLOAD PC FILE
**
** NOTE: Example requires that Natural Connection is installed.
** CAUTION: Executing this example will modify the database records!
*****
DEFINE DATA LOCAL
01 EMPL VIEW OF EMPLOYEES
    02 PERSONNEL-ID
    02 INCOME
    03 SALARY (1)
*
01 #PID (A8)                                /* Personnel ID on PC
01 #NEW-INCREASE (N4)                       /* Increase for salary
END-DEFINE
*
UPLOAD PC FILE 7 #PID #NEW-INCREASE         /* Data upload
*
    FIND EMPL WITH PERSONNEL-ID = #PID      /* Data selection
    ADD #NEW-INCREASE TO SALARY (1)         /* Data update on host
    UPDATE
    END TRANSACTION
    ESCAPE BOTTOM
END-FIND
*
END-WORK
END

```

Output of Program PCUPEX1:

When you run the program, a window appears in which you specify the name of the PC file from which the data is to be uploaded. The data is then uploaded from the PC.

146

WRITE

▪ Function	1126
▪ Syntax 1 - Dynamic Formatting	1126
▪ Syntax 2 - Using Predefined Form/Map	1134
▪ Examples	1135

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [AT END OF PAGE](#) | [AT TOP OF PAGE](#) | [CLOSE PRINTER](#) | [DEFINE PRINTER](#) | [DISPLAY](#) | [EJECT](#) | [FORMAT](#) | [NEWPAGE](#) | [PRINT](#) | [SKIP](#) | [SUSPEND IDENTICAL SUPPRESS](#) | [WRITE TITLE](#) | [WRITE TRAILER](#)

Belongs to Function Group: [Creation of Output Reports](#)

Function

The `WRITE` statement is used to produce output in free format.

The `WRITE` statement differs from the `DISPLAY` statement in the following respects:

- Line overflow is supported. If the line width is exceeded for a line, the next field (or text) is written on the next line. Fields or text elements are not split between lines.
- No default column headers are created. The length of the data determines the number of positions printed for each field.
- A range of values/occurrences for an array is output horizontally rather than vertically.

See also the following topics in the *Programming Guide*:

- *Report Format and Control*
- *Statements `DISPLAY` and `WRITE`*
- *Index Notation for Multiple-Value Fields and Periodic Groups*
- *Example of `DISPLAY VERT` with `WRITE` Statement*
- *Layout of an Output Page*

Syntax 1 - Dynamic Formatting

```
WRITE [(rep)] [NOTITLE] [NOHDR]
      [(statement-parameters)]
      {
        [
          nX
          nT
          x/y
          T*field-name
          P*field-name
          /
        ] ...
        {
          'text' [(attributes)]
          'c'(n) [(attributes)]
          ['='] operand1 [(parameters)]
        }
      } ...
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Operand Definition Table:

Operand	Possible Structure	Possible Formats	Referencing Permitted	Dynamic Definition
<i>operand1</i>	S A G N	A U N P I F B D T L G O	yes	no

Syntax Element Description:

Syntax Element	Description
(<i>rep</i>)	Report Specification: The notation (<i>rep</i>) is used to specify the identification of the report if multiple reports are to be produced by the program. As report identification, a value in the range 0 - 31 or a logical name which has been assigned using the DEFINE PRINTER statement may be specified. If (<i>rep</i>) is not specified, the statement will apply to the first report (Report 0). If this printer file is defined to Natural as PC, the report will be downloaded to the PC, see Example 6. For information on how to control the format of an output report created with Natural, see <i>Report Format and Control</i> (in the <i>Programming Guide</i>).
NOTITLE	Default Page Title Suppression: Natural generates a single title line for each page resulting from a <code>WRITE</code> statement. This title contains the page number, the time of day, and the date. Time of day is set at the beginning of program execution. This default title line may be overridden by using a WRITE TITLE statement, or it may be suppressed by using the NOTITLE option in the <code>WRITE</code> statement. Examples: ■ Default title will be produced: WRITE NAME ■ User title will be produced:

Syntax Element	Description
	<pre>WRITE NAME WRITE TITLE 'user-title'</pre> ■ No title will be produced: <pre>WRITE NOTITLE NAME</pre> Note: 1. If the NOTITLE option is used, it applies to all DISPLAY, PRINT and WRITE statements within the same object which write data to the same report. 2. Page overflow is checked <i>before</i> execution of a WRITE statement. No new page with title or trailer information is generated <i>during</i> the execution of a WRITE statement.
NOHDR	Column Header Suppression: The WRITE statement itself does not produce any column headers. However, if you use the WRITE statement in conjunction with a DISPLAY statement, you can use the NOHDR option of the WRITE statement to suppress the column headers generated by the DISPLAY statement. The NOHDR option only takes effect if the execution of the WRITE statement causes a new page to be output. Without the NOHDR option, the column headers (if any) of the DISPLAY statement would be output on this new page; with NOHDR they will not.
<i>statement-parameters</i>	Parameter Definition at Statement Level: One or more parameters, enclosed within parentheses, may be specified at statement level, that is, immediately after the WRITE statement. Each parameter specified will override the corresponding parameter previously specified in a GLOBALS command, SET GLOBALS (in Reporting Mode only) or FORMAT statement. If more than one parameter is specified, they must be separated by one or more blanks from one another. Each parameter specification must not be split between two statement lines. Note: The parameter settings applied here will only be regarded for variable fields, but they have no effect on text-constants. If you would like to set field attributes for a text-constant, they have to be set explicitly for this element, see Parameter Definition at Element (Field) Level. See also: ■ List of Parameters ■ Example of Parameter Usage at Statement and Element (Field) Level

Syntax Element	Description
	■ Example 5 - WRITE Statement Using '=' and Parameters on Statement/Element (Field) Level
<i>nX</i> , <i>nT</i> , <i>x/y</i> , <i>T*field-name</i> , <i>P*field-name</i> , '=', /	Field Positioning Notation: See Field Positioning Notations in the section Output Format Definitions .
' <i>text</i> ', ' <i>c</i> '(<i>n</i>), <i>attributes</i> , <i>operand1</i> , <i>parameters</i>	Text/Attribute Assignment: See Text/Attribute Assignment in the section Output Format Definitions .

List of Parameters

Parameters that can be specified with the WRITE statement		Specification (S = at statement level , E = at element level)
AD	Attribute Definition	SE
AL	Alphanumeric Length for Output	SE
BX	Box Definition	SE
CD	Color Definition	SE
CV	Control Variable	SE
DF	Date Format	SE
DL	Display Length for Output	SE
DY	Dynamic Attributes	SE
EM	Edit Mask	SE
EMU	Unicode Edit Mask	E
FL	Floating Point Mantissa Length	SE
IS	Identical Suppress	SE
LS	Line Size	S
MC	Multiple-Value Field Count	S
MP	Maximum Number of Pages of a Report	S
NL	Numeric Length for Output	SE
PC	Periodic Group Count	S
PM	Print Mode	SE
PS	Page Size *	S
SG	Sign Position	SE
UC	Underlining Character	S
ZP	Zero Printing	SE

* If the number of occurrences of an array exceeds the PS value, a NAT0303 error will be output.

The individual session parameters are described in the *Parameter Reference*.

See also the following topics in the *Programming Guide*:


- *Centering of Column Headers - HC Parameter*
- *Width of Column Headers - HW Parameter*
- *Filler Characters for Headers - Parameters FC and GC*
- *Underlining Character for Titles and Headers - UC Parameter*

Example of Parameter Usage at Statement and Element (Field) Level

```
DEFINE DATA LOCAL
1 VARI (A4)      INIT <'1234'>          /*      Output
END-DEFINE      /*      Produced
*              /*      -----
WRITE           'Text'                  VARI      /*      Text 1234
WRITE (PM=I)    'Text'                  VARI      /*      Text 4321
WRITE          'Text' (PM=I)            VARI (PM=I) /*      txeT 4321
WRITE          'Text' (PM=I)            VARI      /*      txeT 1234
END
```

See also [Example 5 - WRITE Statement Using '=' and Parameters on Statement/Element \(Field\) Level](#).

Output Format Definitions



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Field Positioning Notations

Syntax Element	Description
<i>nX</i>	Column Spacing: This notation inserts <i>n</i> spaces between columns. <i>n</i> must not be zero. Example:

Syntax Element	Description
	<pre>WRITE NAME 5X SALARY</pre> See also: ■ Example 2 - WRITE Statement Using nX, nT Notation ■ Column Spacing - SF Parameter and nX Notation in the Programming Guide
<i>nT</i>	Tab Setting: The <i>nT</i> notation causes positioning (tabulation) to print position <i>n</i>. Backward positioning is not permitted. In the following example, NAME is printed beginning in position 25, and SALARY is printed beginning in position 50: <pre>WRITE 25T NAME 50T SALARY</pre> See also: ■ Example 2 - WRITE Statement Using nX, nT Notation ■ Tab Setting - nT Notation in the Programming Guide
<i>x/y</i>	<i>x/y</i> Positioning: The <i>x/y</i> notation causes the next element to be placed <i>x</i> lines below the output of the last statement, beginning in column <i>y</i>. <i>y</i> must not be zero. Backward positioning in the same line is not permitted. See also Positioning Notation <i>x/y</i> (in the Programming Guide).
<i>T*field-name</i>	Field Related Positioning: The notation <i>T*</i> is used to position to a <i>specific print position of a field</i> used in a previous DISPLAY statement. Backward positioning is not permitted. See also: ■ Example 3 - WRITE Statement Using T* Notation ■ Tab Notation - T*field (in the Programming Guide)
<i>P*field-name</i>	Field and Line Related Positioning: The notation <i>P*</i> is used to position to a <i>specific print position and line of a field</i> used in a previous DISPLAY statement. It is most often used in conjunction with vertical printing mode. Backward positioning is not permitted. See also: ■ Example 4 - WRITE Statement Using P* Notation ■ Tab Notation P*field (in the Programming Guide)

Syntax Element	Description
'='	Field Content Positioned behind Field Heading: When placed before a field, the equal sign '=' results in the display of the field heading (as defined in the DEFINE DATA statement or in the DDM) followed by the field contents. See also: ■ Example 1 - WRITE Statement Using '=', 'text', '/' ■ Example 5 - WRITE Statement Using '=' and Statement/Element Parameters
/	Line Advance - Slash Notation: When placed between fields or text elements, a slash (/) causes positioning to the beginning of the next print line. Example: <pre>WRITE NAME / SALARY</pre> Multiple slash (/) notations may be used to cause multiple line advances. See also: ■ Example 1 - WRITE Statement Using '=', 'text', '/' ■ Line Advance - Slash Notation (in the Programming Guide) ■ Example 2 - Line Advance in WRITE Statement (in the Programming Guide)

Text/Attribute Assignments

Syntax Element	Description
'text'	Text Assignment: The character string enclosed by single quotes is displayed. Example: <pre>WRITE 'EMPLOYEE' NAME 'MARITAL/STATUS' MAR-STAT</pre> See also: ■ Example 1 - WRITE Statement Using '=', 'text', '/' ■ Text Notation, Defining a Text to Be Used with a Statement in the Programming Guide
'c'(n)	Character Repetition: The character enclosed by single quotes is displayed <i>n</i> times immediately before the field value.

Syntax Element	Description
	For example: <pre>WRITE '*' (5) '=' NAME</pre> results in <pre>***** SMITH</pre> See also <i>Text Notation, Defining a Character to Be Displayed n Times before a Field Value</i> (in the <i>Programming Guide</i>).
<i>attributes</i>	Field Representation and Color Attributes: It is possible to assign various attributes for text/field display. These attributes and the syntax that may be used are described in the section Output Attributes below. Examples: <pre>WRITE 'TEXT' (BGR) WRITE 'TEXT' (B) WRITE 'TEXT' (BBLC)</pre>
<i>operand1</i>	Field to be Written: <i>operand1</i> specifies the field whose content is to be written in this place. Arrays with ranges that allow to vary the number of occurrences at execution time may not be specified. Note: For DL/I databases: The DL/I AIX fields can be displayed only if a PCB is used with the AIX specified in the parameter PROCSEQ. If not, an error message is returned by Natural at runtime.
<i>parameters</i>	Parameter Definition at Element (Field) Level: One or more parameters, enclosed within parentheses, may be specified at element (field) level, that is, immediately after <i>operand1</i>. Each parameter specified in this manner will override the corresponding parameter previously specified at statement level or in a GLOBALS command, SET GLOBALS (in Reporting Mode only) or FORMAT statement. If more than one parameter is specified, one or more blanks must be placed between each entry. An entry may not be split between two statement lines. See also: ■ List of Parameters ■ Example of Parameter Usage at Statement and Element (Field) Level

Output Attributes

attributes indicates the output attributes to be used for text display. Attributes can be:

$\left\{ \begin{array}{l} AD=ad-value \dots \\ BX=bx-value \dots \\ CD=cd-value \\ PM=pm-value \dots \end{array} \right\} \dots$
$\left\{ \begin{array}{l} ad-value \\ cd-value \end{array} \right\} \dots$

Where:

ad-value, *bx-value*, *cd-value* and *pm-value* denote the possible values of the corresponding session parameters AD, BX, CD and PM described in the relevant sections of the *Parameter Reference* documentation.

The compiler actually accepts more than one attribute value for an output field. For example, you can specify: AD=BDI. In such a case, however, only the last value applies. In the given example, only the value I becomes effective and the output field is displayed intensified.

For an alphanumeric/Unicode constant (Natural data format A or U), you can specify *ad-value* and/or *cd-value* without preceding CD= or AD=, respectively. The single value entered is then checked against all possible CD values first. For example: a value of IRE will be interpreted as intensified/red but not as intensified/right-justified/mandatory. You cannot combine a single *cd-value* or *ad-value* with a value preceded by CD= or AD=.

Syntax 2 - Using Predefined Form/Map

WRITE						
[(<i>rep</i>)]	[NOTITLE]	[NOHDR]	{	FORM	}	<i>operand1</i> [<i>operand2</i> ...]
[USING]				MAP		[NO PARAMETER]

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Operand Definition Table:

Operand	Possible Structure					Possible Formats															Referencing Permitted	Dynamic Definition
<i>operand1</i>	C	S				A															no	no
<i>operand2</i>		S	A	G	N	A	U	N	P	I	F	B	D	T	L						yes	no

Syntax Element Description:

Syntax Element	Description
FORM or MAP	Use of Predefined Form or Map Layout: This option may be used to indicate that a form or map layout previously defined with the map editor is to be used. A map layout used in a <code>WRITE</code> statement does not automatically create a new page each time the map is output. For the line spacing, the <code>LS</code> parameter setting must be 1 byte greater than the <code>LS</code> setting defined in the map.
<i>operand1</i>	Form or Map Name: <i>operand1</i> is the name of the form/map to be used.
<i>operand2</i> or NO PARAMETER	Field to be Written: <i>operand2</i> is the name(s) of the field(s) to be written. If <i>operand1</i> is a constant and <i>operand2</i> is omitted, the fields are taken from the map source at compilation time. The fields must agree in number, sequence, format, length and (for arrays) number of occurrences with the fields in the referenced form/map; otherwise, an error occurs. If FORM or MAP does not require any parameters, specify the NO PARAMETER option.
NOTITLE/NOHDR	Title Line/Column Header Suppression: NOTITLE and NOHDR are described under Syntax 1 of the <code>WRITE</code> statement.

Examples

- [Example 1 - WRITE Statement Using '=', 'text', '/'](#)
- [Example 2 - WRITE Statement Using nX, nT Notation](#)
- [Example 3 - WRITE Statement Using T* Notation](#)
- [Example 4 - WRITE Statement Using P* Notation](#)
- [Example 5 - WRITE Statement Using '=' and Parameters on Statement/Element \(Field\) Level](#)

- [Example 6 - Report Specification with Output File Defined to Natural as PC](#)

Example 1 - WRITE Statement Using '=', 'text', '/'

```
** Example 'WRTEX1': WRITE (with '=', 'text', '/')
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 FULL-NAME
    3 FIRST-NAME
    3 MIDDLE-I
    3 NAME
  2 CITY
  2 COUNTRY
END-DEFINE
*
LIMIT 1
READ EMPL-VIEW BY NAME
/*
  WRITE NOTITLE
    '=' NAME '=' FIRST-NAME '=' MIDDLE-I //
    'L O C A T I O N' /
    'CITY: ' CITY /
    'COUNTRY:' COUNTRY //
/*
END-READ
END
```

Output of Program WRTEX1:

```
NAME: ABELLAN          FIRST-NAME: KEPA          MIDDLE-I:
L O C A T I O N
CITY:   MADRID
COUNTRY: E
```

Example 2 - WRITE Statement Using nX, nT Notation

```
** Example 'WRTEX2': WRITE (with nX, nT notation)
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 JOB-TITLE
END-DEFINE
*
LIMIT 4
READ EMPL-VIEW BY NAME
  WRITE NOTITLE 5X NAME 50T JOB-TITLE
```

```
END-READ
END
```

Output of WRTEX2:

ABELLAN	MAQUINISTA
ACHIESON	DATA BASE ADMINISTRATOR
ADAM	CHEF DE SERVICE
ADKINSON	PROGRAMMER

Example 3 - WRITE Statement Using T* Notation

```
** Example 'WRTEX3': WRITE (with T* notation)
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 CITY
  2 SALARY (1)
END-DEFINE
*
LIMIT 5
READ EMPL-VIEW BY CITY STARTING FROM 'ALBU'
  DISPLAY NOTITLE CITY NAME SALARY (1)
  AT BREAK CITY
  /*
    WRITE / 'CITY AVERAGE:' T*SALARY (1) AVER(SALARY(1)) //
  /*
  END-BREAK
END-READ
END
```

Output of Program WRTEX3:

CITY	NAME	ANNUAL SALARY
ALBUQUERQUE	HAMMOND	22000
ALBUQUERQUE	ROLLING	34000
ALBUQUERQUE	FREEMAN	34000
ALBUQUERQUE	LINCOLN	41000
CITY AVERAGE:		32750
ALFRETON	GOLDBERG	4800
CITY AVERAGE:		4800

Example 4 - WRITE Statement Using P* Notation

```

** Example 'WRTEX4': WRITE (with P* notation)
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 CITY
  2 BIRTH
  2 SALARY (1)
END-DEFINE
*
LIMIT 3
READ EMPL-VIEW BY CITY FROM 'N'
  DISPLAY NOTITLE NAME CITY
    VERT AS 'BIRTH/SALARY' BIRTH (EM=YYYY-MM-DD) SALARY (1)
  SKIP 1
  AT BREAK CITY
    WRITE / 'CITY AVERAGE' P*SALARY (1) AVER(SALARY (1)) //
  END-BREAK
END-READ
END

```

Output of Program WRTEX4:

NAME	CITY	BIRTH SALARY
-----	-----	-----
WILCOX	NASHVILLE	1970-01-01 38000
MORRISON	NASHVILLE	1949-07-10 36000
CITY AVERAGE		37000
BOYER	NEMOURS	1955-11-23 195900
CITY AVERAGE		195900

Example 5 - WRITE Statement Using '=' and Parameters on Statement/Element (Field) Level

```

** Example 'WRTEX5': WRITE (using '=', statement/element parameters)
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 PERSONNEL-ID
  2 PHONE
END-DEFINE
*
LIMIT 2
READ EMPL-VIEW BY NAME
  WRITE NOTITLE (AL=16 NL=8)
    '=' PERSONNEL-ID '=' NAME '=' PHONE (AL=10 EM=XXX-XXXXXXX)
END-READ
END

```

Output of Program WRTEX5:

PERSONNEL ID: 60008339	NAME: ABELLAN	TELEPHONE: 435-6726
PERSONNEL ID: 30000231	NAME: ACHIESON	TELEPHONE: 523-341

Example 6 - Report Specification with Output File Defined to Natural as PC

```


** Example 'PCDIEX1': DISPLAY and WRITE to PC
**
** NOTE: Example requires that Natural Connection is installed.
*****
DEFINE DATA LOCAL
01 PERS VIEW OF EMPLOYEES
  02 PERSONNEL-ID
  02 NAME
  02 CITY
END-DEFINE
*
FIND PERS WITH CITY = 'NEW YORK' /* Data selection
  WRITE (7) TITLE LEFT 'List of employees in New York' /
  DISPLAY (7) /* (7) designates the output file (here the PC).
    'Location' CITY
    'Surname' NAME
    'ID' PERSONNEL-ID
END-FIND
END

```

147

WRITE TITLE

▪ Function	1142
▪ Restrictions	1143
▪ Syntax Description	1143
▪ Example	1147



For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: `AT END OF PAGE` | `AT TOP OF PAGE` | `CLOSE PRINTER` | `DEFINE PRINTER` | `DISPLAY` | `EJECT` | `FORMAT` | `NEWPAGE` | `PRINT` | `SKIP` | `SUSPEND IDENTICAL SUPPRESS` | `WRITE` | `WRITE TRAILER`

Belongs to Function Group: [Creation of Output Reports](#)

Function

The `WRITE TITLE` statement is used to override the default page title with a page title of your own. It is executed whenever a new page is initiated.

See also the following sections in the *Programming Guide*:

- *Report Format and Control*
- *Report Specification - (rep) Notation*
- *Layout of an Output Page*
- *Page Titles, Page Breaks, Blank Lines*
- *Define Your Own Page Title - WRITE TITLE Statement*
- *Text Notation*

Processing

This statement is non-procedural, that is, its execution depends on an event, not on where in a program it is located.

If a report is produced by statements in different objects, the `WRITE TITLE` statement is only executed if it is contained in the same object as the statement that causes a new page to be initiated.

Restrictions

- `WRITE TITLE` may be specified only once per report.
- `WRITE TITLE` cannot be specified within a special condition statement block.
- `WRITE TITLE` cannot be specified within a subroutine.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition		
<i>operand1</i>		S	A	G	N	A	U	N	P	I	F	B	D	T	L	G	O	yes	no
<i>operand2</i>	C	S						N	P	I		B						yes	no

Syntax Element Description:

Syntax Element	Description
<i>(rep)</i>	Report Specification: If multiple reports are to be produced, the notation <i>(rep)</i> may be used to specify the identification of the report for which the <code>WRITE TITLE</code> statement is applicable. As report identification, a value in the range 0 - 31 or a logical name which has been assigned using the <code>DEFINE PRINTER</code> statement may be specified. If <i>(rep)</i> is not specified, the <code>WRITE TITLE</code> statement applies to the first report (Report 0). For information on how to control the format of an output report created with Natural, see <i>Report Format and Control</i> (in the <i>Programming Guide</i>).
LEFT JUSTIFIED	Page Title Justification and/or Underlining:

Syntax Element	Description
UNDERLINED	By default, page titles are centered and not underlined. <code>LEFT JUSTIFIED</code> and <code>UNDERLINED</code> may be specified to override these defaults. If <code>UNDERLINED</code> is specified, the underlining character (system default or specified with the session parameter <code>UC</code> (Underlining Character) in a <code>FORMAT</code> statement) is printed underneath the title and runs the width of the line size (see session parameter <code>LS</code>). Natural first applies all spacing or tab specifications and creates the line before centering the whole line. For example, a notation of <code>10T</code> as the first element would cause the centered header to be positioned five positions to the right.
<i>statement-parameters</i>	Parameter Definition at Statement Level: One or more parameters, enclosed within parentheses, may be specified at statement level, that is, immediately after the <code>WRITE TITLE</code> statement. Each parameter specified in this manner will override the corresponding parameter previously specified in a <code>GLOBALS</code> command, <code>SET GLOBALS</code> (in Reporting Mode only) or <code>FORMAT</code> statement. If more than one parameter is specified, one or more blanks must be present between each entry. An entry may not be split between two statement lines. Note: The parameter settings applied here will only be regarded for variable fields, but they have no effect on text-constants. If you would like to set field attributes for a text-constant, they have to be set explicitly for this element, see Parameter Definition at Element (Field) Level. For information on which parameters may be used, see List of Parameters (in the <code>WRITE</code> statement documentation).
<i>nX</i> <i>nT</i> <i>x/y</i> <i>T*field-name</i> <i>P*field-name</i> <i>/</i>	Format Notation and Spacing Elements: See Format Notation and Spacing Elements.
<i>'text'</i> <i>'c' (n)</i> <i>attributes</i>	Text/Attribute Assignment: See Text/Attribute Assignments.
<i>operand1</i>	Field to Be Displayed in Title: <i>operand1</i> represents the field(s) to be displayed within the title. Arrays with ranges that allow to vary the number of occurrences at execution time may not be specified.
<i>parameters</i>	Parameter Definition at Element (Field) Level: One or more parameters, enclosed within parentheses, may be specified at element (field) level, that is, immediately after <i>operand1</i>. Each parameter

Syntax Element	Description
	specified in this manner will override the corresponding parameter previously specified at statement level or in a GLOBALS command, SET GLOBALS (in Reporting Mode only) or FORMAT statement. If more than one parameter is specified, one or more blanks must be present between each entry. An entry may not be split between two statement lines. For information on which parameters may be used, see List of Parameters (in the WRITE statement documentation).
SKIP <i>operand2</i> LINES	Lines to Be Skipped: SKIP may be used to cause lines to be skipped immediately after the title line. The number of lines to be skipped may be specified in <i>operand2</i> as a numeric constant or as the content of a numeric variable. Note: SKIP after WRITE TITLE is always interpreted as the SKIP clause of the WRITE TITLE statement, and not as an independent statement. If you wish an independent SKIP statement after a WRITE TITLE statement, use a semicolon (;) to separate the two statements from one another.

Format Notation and Spacing Elements

Syntax Element	Description
<i>nX</i>	Column Spacing: This notation inserts <i>n</i> spaces between columns. <i>n</i> must not be zero.
<i>nT</i>	Tab Setting: The <i>nT</i> notation causes positioning (tabulation) to print position <i>n</i>. Backward positioning is not permitted.
<i>x/y</i>	<i>x/y</i> Positioning: Causes the next element to be placed <i>x</i> lines below the output of the last statement, beginning in column <i>y</i>. <i>y</i> must not be zero. Backward positioning in the same line is not permitted.
<i>T*field-name</i>	Field-Related Positioning: The <i>T*</i> notation causes positioning to a <i>specific print position of a field</i> used in a previous DISPLAY statement. Backward positioning is not permitted.
<i>P*field-name</i>	Field- and Line-Related Positioning: The <i>P*</i> notation causes positioning to a <i>specific print position and line of a field</i> used in a previous DISPLAY statement. It is most often used in conjunction with vertical printing mode. Backward positioning is not permitted.
/	Line Advance - Slash Notation:

Syntax Element	Description
	When placed between fields or text elements, a slash (/) causes positioning to the beginning of the next print line.

Text/Attribute Assignments

Syntax Element	Description
'text'	Text Assignment: The character string enclosed by single quotes is displayed.
'c'(n)	Character Repetition: The character enclosed by single quotes is displayed <i>n</i> times immediately before the field value.
attributes	Field Representation and Color Attributes: It is possible to assign various attributes for text/field display. These attributes and the syntax that may be used are described in the section Output Attributes below. Examples: WRITE TITLE 'TEXT' (BGR) WRITE TITLE 'TEXT' (B) WRITE TITLE 'TEXT' (BBLC)

Output Attributes

attributes indicates the output attributes to be used for text display. Attributes can be:

$\left\{ \begin{array}{l} AD=ad-value \dots \\ BX=bx-value \dots \\ CD=cd-value \\ PM=pm-value \dots \end{array} \right\} \dots$
$\left\{ \begin{array}{l} ad-value \\ cd-value \end{array} \right\} \dots$

Where:

ad-value, *bx-value*, *cd-value* and *pm-value* denote the possible values of the corresponding session parameters AD, BX, CD and PM described in the relevant sections of the *Parameter Reference* documentation.

The compiler actually accepts more than one attribute value for an output field. For example, you can specify: AD=BDI. In such a case, however, only the last value applies. In the given example, only the value I becomes effective and the output field is displayed intensified.

For an alphanumeric/Unicode constant (Natural data format A or U), you can specify *ad-value* and/or *cd-value* without preceding CD= or AD=, respectively. The single value entered is then checked against all possible CD values first. For example: a value of IRE will be interpreted as intensified/red but not as intensified/right-justified/mandatory. You cannot combine a single *cd-value* or *ad-value* with a value preceded by CD= or AD=.

Example

```
** Example 'WTIEX1': WRITE (with TITLE option)
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 FIRST-NAME
  2 CITY
  2 JOB-TITLE
END-DEFINE
*
*
FORMAT LS=70
*
WRITE TITLE LEFT JUSTIFIED UNDERLINED
      *TIME 3X 'PEOPLE LIVING IN NEW YORK CITY'
      11X 'PAGE:' *PAGE-NUMBER
SKIP 1
*
FIND EMPL-VIEW WITH CITY = 'NEW YORK'
  DISPLAY NAME FIRST-NAME 3X JOB-TITLE
END-FIND
END
```

Output of Program WTIEX1:

```
09:33:16.5  PEOPLE LIVING IN NEW YORK CITY                PAGE:      1
-----
          NAME                FIRST-NAME                CURRENT
          NAME                FIRST-NAME                POSITION
-----
RUBIN      SYLVIA            SECRETARY
WALLACE    MARY              ANALYST
```

148

WRITE TRAILER

▪ Function	1150
▪ Restrictions	1151
▪ Syntax Description	1151
▪ Example	1155

```
WRITE [(rep)] TRAILER [LEFT [JUSTIFIED]] [UNDERLINED]
    [(statement-parameters)]
    {
        {
            nX
            nT
            x/y
            T*field-name
            P*field-name
            /
        } ...
        {
            'text' [(attributes)]
            'c' (n) [(attributes)]
            ['='] operand1 [(parameters)]
        } ...
    }
    [SKIP operand2 [LINES]]
```

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [AT END OF PAGE](#) | [AT TOP OF PAGE](#) | [CLOSE PRINTER](#) | [DEFINE PRINTER](#) | [DISPLAY](#) | [EJECT](#) | [FORMAT](#) | [NEWPAGE](#) | [PRINT](#) | [SKIP](#) | [SUSPEND IDENTICAL SUPPRESS](#) | [WRITE](#) | [WRITE TITLE](#)

Belongs to Function Group: [Creation of Output Reports](#)

Function

The `WRITE TRAILER` statement is used to output text or the contents of variables at the bottom of a page.

See also the following sections (in the *Programming Guide*):

- [Report Format and Control](#)
- [Report Specification - \(rep\) Notation](#)
- [Layout of an Output Page](#)
- [Page Trailer - WRITE TRAILER Statement](#)
- [Text Notation](#)

Processing

This statement is non-procedural, that is, its execution depends on an event, not on where in a program it is located.

This statement is executed when an end-of-page or end-of-data condition is detected, or when a [SKIP](#) or [NEWPAGE](#) statement causes a page advance. It is not executed as a result of an [EJECT](#) statement.

The end-of-page condition is checked only after the processing of an entire **DISPLAY/WRITE** statement. If a **DISPLAY/WRITE** statement produces multiple lines of output, overflow of the physical page may occur before the end-of-page condition is reached.

If a report is produced by statements in different objects, the **WRITE TRAILER** statement is only executed if it is contained in the same object as the statement that causes the end-of-page condition.

Logical Page Size

The logical page size (specified with the session parameter **PS**) should be less than the physical page size to ensure that the trailer information appears at the bottom of the same page.

Restrictions

- **WRITE TRAILER** may be specified only once per report.
- **WRITE TRAILER** cannot be specified within a special condition statement block.
- **WRITE TRAILER** cannot be specified within a subroutine.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition		
<i>operand1</i>		S	A	G	N	A	U	N	P	I	F	B	D	T	L	G	O	yes	no
<i>operand2</i>	C	S						N	P	I		B						yes	no

Syntax Element Description:

Syntax Element	Description
<i>(rep)</i>	Report Specification: If multiple reports are to be produced, the notation <i>(rep)</i> may be used to specify the identification of the report for which the WRITE TRAILER statement is applicable. As report identification, a value in the range 0 - 31 or a logical name which has been assigned using the DEFINE PRINTER statement may be specified. If <i>(rep)</i> is not specified, the WRITE TRAILER statement applies to the first report (Report 0).

Syntax Element	Description
	For information on how to control the format of an output report created with Natural, see <i>Report Format and Control</i> (in the <i>Programming Guide</i>).
LEFT JUSTIFIED UNDERLINED	Title Justification and/or Underlining: By default, the trailer lines are centered and not underlined. LEFT JUSTIFIED and UNDERLINED may be specified to override these defaults. If UNDERLINED is specified, the underlining character (either default or specified with the session parameter UC) is printed underneath the trailer and runs the width of the line size (session parameter LS). Natural first applies all spacing or tab specifications and creates the line before centering the whole line. For example, a notation of 10T as the first element would cause the centered header to be positioned five positions to the right.
<i>statement-parameters</i>	Parameter Definition at Statement Level: One or more parameters, enclosed within parentheses, may be specified at statement level, that is, immediately after the WRITE TRAILER statement. Each parameter specified in this manner will override the corresponding parameter previously specified in a GLOBALS command, SET GLOBALS (in Reporting Mode only) or FORMAT statement. If more than one parameter is specified, one or more blanks must be present between each entry. An entry may not be split between two statement lines. Note: The parameter settings applied here will only be regarded for variable fields, but they have no effect on text-constants. If you would like to set field attributes for a text-constant, they have to be set explicitly for this element, see Parameter Definition at Element (Field) Level. For information on which parameters may be used, see List of Parameters (in the WRITE statement documentation).
nX nT x/y T*field-name P*field-name /	Format Notation and Spacing Elements: See Format Notation and Spacing Elements.
'text' 'c'(n) attributes	Text/Attribute Assignments: See Text/Attribute Assignments.
<i>operand1</i>	Trailer Information: <i>operand1</i> represents the field/fields to be output as trailer information. Arrays with ranges that allow to vary the number of occurrences at execution time may not be specified.

Syntax Element	Description
<i>parameters</i>	Parameter Definition at Element (Field) Level: One or more parameters, enclosed within parentheses, may be specified at element (field) level, that is, immediately after <i>operand1</i>. Each parameter specified in this manner will override the corresponding parameter previously specified at statement level or in a GLOBALS command, SET GLOBALS (in Reporting Mode only) or FORMAT statement. If more than one parameter is specified, one or more blanks must be present between each entry. An entry may not be split between two statement lines. For information on which parameters may be used, see List of Parameters in the WRITE statement documentation.
SKIP <i>operand2</i> LINES	Lines to Be Skipped: SKIP may be used to cause lines to be skipped immediately after the trailer line. The number of lines to be skipped (<i>operand2</i>) may be specified as a numeric constant or as the content of a numeric variable. Note: SKIP after WRITE TRAILER is always interpreted as the SKIP clause of the WRITE TRAILER statement, and not as an independent statement. If you wish an independent SKIP statement after a WRITE TRAILER statement, use a semicolon (;) to separate the two statements from one another.

Format Notation and Spacing Elements

Syntax Element	Description
<i>nX</i>	Column Spacing: This notation inserts <i>n</i> spaces between columns. <i>n</i> must not be zero.
<i>nT</i>	Tab Setting: The <i>nT</i> notation causes positioning (tabulation) to print position <i>n</i>. Backward positioning is not permitted.
<i>x/y</i>	<i>x/y</i> Positioning: Causes the next element to be placed <i>x</i> lines below the output of the last statement, beginning in column <i>y</i>. <i>y</i> must not be zero. Backward positioning in the same line is not permitted.
<i>T*field-name</i>	Field-Related Positioning: The <i>T*</i> notation causes positioning to a <i>specific print position of a field</i> used in a previous DISPLAY statement. Backward positioning is not permitted.
<i>P*field-name</i>	Field- and Line-Related Positioning:

Syntax Element	Description
	The P^* notation causes positioning to a <i>specific print position and line of a field</i> used in a previous DISPLAY statement. It is most often used in conjunction with vertical printing mode. Backward positioning is not permitted.
/	Line Advance - Slash Notation: When placed between fields or text elements, a slash (/) causes positioning to the beginning of the next print line.

Text/Attribute Assignments

Syntax Element	Description
'text'	Text Assignment: The character string enclosed by single quotes is displayed.
'c'(n)	Character Repetition: The character enclosed by single quotes is displayed n times immediately before the field value.
attributes	Field Representation and Color Attributes: It is possible to assign various attributes for text/field display. These attributes and the syntax that may be used are described in the section Output Attributes below. Examples: <pre>WRITE TRAILER 'TEXT' (BGR) WRITE TRAILER 'TEXT' (B) WRITE TRAILER 'TEXT' (BBLC)</pre>

Output Attributes

attributes indicates the output attributes to be used for text display. Attributes can be:

$\left\{ \begin{array}{l} AD=ad-value \dots \\ BX=bx-value \dots \\ CD=cd-value \\ PM=pm-value \dots \end{array} \right\} \dots$
$\left\{ \begin{array}{l} ad-value \\ cd-value \end{array} \right\} \dots$

Where:

ad-value, *bx-value*, *cd-value* and *pm-value* denote the possible values of the corresponding session parameters AD, BX, CD and PM described in the relevant sections of the *Parameter Reference* documentation.

The compiler actually accepts more than one attribute value for an output field. For example, you can specify: AD=BDI. In such a case, however, only the last value applies. In the given example, only the value I becomes effective and the output field is displayed intensified.

For an alphanumeric/Unicode constant (Natural data format A or U), you can specify *ad-value* and/or *cd-value* without preceding CD= or AD=, respectively. The single value entered is then checked against all possible CD values first. For example: a value of IRE will be interpreted as intensified/red but not as intensified/right-justified/mandatory. You cannot combine a single *cd-value* or *ad-value* with a value preceded by CD= or AD=.

Example

```
** Example 'WTLEX1': WRITE (with TRAILER option)
*****
DEFINE DATA LOCAL
1 EMPL-VIEW VIEW OF EMPLOYEES
  2 NAME
  2 FIRST-NAME
  2 CITY
  2 JOB-TITLE
END-DEFINE
*
FORMAT PS=15
WRITE TITLE LEFT JUSTIFIED UNDERLINED
      *TIME 3X 'PEOPLE LIVING IN BARCELONA'
      14X 'PAGE:' *PAGE-NUMBER
SKIP 1
*
WRITE TRAILER LEFT JUSTIFIED UNDERLINED
      / 'CITY OF BARCELONA REGISTER'
*
LIMIT 10
FIND EMPL-VIEW WITH CITY = 'BARCELONA'
  DISPLAY NAME FIRST-NAME 3X JOB-TITLE
END-FIND
END
```

Output of Program WTLEX1 - Page 1:

```
09:36:09.5  PEOPLE LIVING IN BARCELONA  PAGE:      1
-----
          NAME                FIRST-NAME                CURRENT
                   POSITION
-----
DEL CASTILLO                ANGEL                EJECUTIVO DE VENTAS
```

WRITE TRAILER

GARCIA	M. DE LAS MERCEDES	SECRETARIA
GARCIA	ENDIKA	DIRECTOR TECNICO
MARTIN	ASUNCION	SECRETARIA
MARTINEZ	TERESA	SECRETARIA
YNCLAN	FELIPE	ADMINISTRADOR
FERNANDEZ	ELOY	OFICINISTA
TORRES	ANTONI	OBRERA

CITY OF BARCELONA REGISTER

Output of Program WTLEX1 - Page 2:

09:37:26.0 PEOPLE LIVING IN BARCELONA PAGE: 2

NAME	FIRST-NAME	CURRENT POSITION

RODRIGUEZ	VICTORIA	SECRETARIA
GARCIA	GERARDO	INGENIERO DE PRODUCCION

CITY OF BARCELONA REGISTER

149

WRITE WORK FILE

■ Function	1158
■ Syntax Description	1158
■ External Representation of Fields	1160
■ Handling of Large and Dynamic Variables	1161
■ Example	1161

WRITE WORK [FILE] *work-file-number* [VARIABLE] *operand1* ...

For explanations of the symbols used in the syntax diagram, see [Syntax Symbols](#).

Related Statements: [DEFINE WORK FILE](#) | [READ WORK FILE](#) | [CLOSE WORK FILE](#) | [DOWNLOAD PC FILE](#)

Belongs to Function Group: [Control of Work Files / PC Files](#)

Function

The `WRITE WORK FILE` statement is used to write records to a physical sequential work file.

This statement can only be used within a program to be executed under Complete, CICS, TSO or TIAM, or in batch mode. Appropriate JCL or system commands must be executed to allocate the work file. For further information, see the *Operations* documentation. For information on work file assignments, see profile parameter `WORK` in the *Parameter Reference*.

It is possible to create a work file in one program or processing loop and to read the same file in a subsequent independent processing loop or in a subsequent program using the [READ WORK FILE](#) statement.

 **Note:** For Unicode and code page support, see *Work Files and Print Files on Mainframe Platforms* in the *Unicode and Code Page Support* documentation.

Syntax Description

Operand Definition Table:

Operand	Possible Structure					Possible Formats										Referencing Permitted	Dynamic Definition		
<i>operand1</i>	C	S	A	G	N	A	U	N	P	I	F	B	D	T	L	C	G	yes	no

 **Note:** Neither Format C nor Format G is valid for Natural Connection.

Syntax Element Description:

Syntax Element	Description
<i>work-file-number</i>	Work File Number: The work file number (as defined to Natural) to be used.
VARIABLE	Variable Entry: It is possible to write records with different fields to the same work file with different WRITE WORK FILE statements. In this case, the VARIABLE entry must be specified in all WRITE WORK FILE statements. The records on the external file will be written in variable format. Natural will write all output files as variable-blocked (unless you specify a record format and block size in the execution JCL). When the operand list includes a dynamic variable (that could change in size for different executions of the WRITE WORK FILE statement), the VARIABLE entry must be specified in all WRITE WORK FILE statements. Variable Index Range: When writing an array to a work file, you can specify a variable index range for the array. For example: <pre>WRITE WORK FILE <i>work-file-number</i> VARIABLE #ARRAY (I:J)</pre>
<i>operand1</i>	Fields to Be Written: With <i>operand1</i> you specify the fields to be written to the work file. These fields may be database fields, user-defined variables, system variables and/or fields read from another work file using the READ WORK FILE statement. An array may be referenced completely or partially to select the occurrences that are to be written to the work file. Group Operands to be Written: A group may be referenced using the group name. All fields belonging to the referenced group will be written to the work file, the sequence is determined by the sequence of the fields in the group. Fields resulting from a redefinition of the referenced group are <i>not</i> written to the work file. If the referenced group is defined as an array, the individual fields of the group are written to the work file as arrays in the definition sequence. For the group definition

Syntax Element	Description
	<pre>1 GROUP1 (1:3) 2 FIELD1 (A2) 2 FIELD2 (A3) 1 REDEFINE GROUP1 2 FIELD3 (A15)</pre>
	the statement
	<pre>WRITE WORK FILE 1 GROUP1(*)</pre>
	is equivalent to
	<pre>WRITE WORK FILE 1 GROUP1.FIELD1(*) GROUP1.FIELD2(*)</pre>
	The statement
	<pre>WRITE WORK FILE 1 GROUP1.FIELD3</pre>
	is equivalent to
	<pre>WRITE WORK FILE 1 GROUP1.FIELD1(1) GROUP1.FIELD2(1) GROUP1.FIELD1(2) GROUP1.FIELD2(2) GROUP1.FIELD1(3) GROUP1.FIELD2(3)</pre>

External Representation of Fields

Fields written with a `WRITE WORK FILE` statement are represented in the external file according to their internal definition. No editing is performed on the field values.

For fields of format A and B, the number of bytes in the external file is the same as the internal length definition as defined in the Natural program. No editing is performed and a decimal point is not represented in the value.

For fields of format N, the number of bytes on the external file is the sum of internal positions before and after the decimal point. The decimal point is not represented on the external file.

For fields of format P, the number of bytes on the external file is the sum of positions before and after the decimal point, plus 1 for the sign, divided by 2, rounded upward to a full byte.



Note: No format conversion is performed for fields that are written to a work file.

Examples of field representations:

Field Definition	Output Record
#FIELD1 (A10)	10 bytes
#FIELD2 (B15)	15 bytes
#FIELD3 (N1.3)	4 bytes
#FIELD4 (N0.7)	7 bytes
#FIELD5 (P1.2)	2 bytes
#FIELD6 (P6.0)	4 bytes

■ Special Considerations for System Functions

Special Considerations for System Functions

For the special considerations that apply when `WRITE WORK FILE` is used for the Natural system function `AVER`, `NAVER`, `SUM` or `TOTAL`, see *Format/Length Requirements for AVER, NAVER, SUM and TOTAL* in the *System Functions* documentation.

Handling of Large and Dynamic Variables

Work File Type	Handling
UNFORMATTED	Work file type UNFORMATTED can be used to write variables whose size exceeds the maximum record length. See also <i>Work File Access With Large and Dynamic Variables</i> .
FORMATTED	A dynamic variable is written in its currently defined length (including length 0).

Example

```

** Example 'WWFEX1': WRITE WORK FILE
*****
DEFINE DATA LOCAL
1 EMPLOY-VIEW VIEW OF EMPLOYEES
  2 PERSONNEL-ID
  2 NAME
END-DEFINE
*
FIND EMPLOY-VIEW WITH CITY = 'LONDON'
  WRITE WORK FILE 1
    PERSONNEL-ID NAME
END-FIND
*
END

```
