

Adabas SAF Security

Adabas SAF Security Operations

Version 8.2.1

September 2011

This document applies to Adabas SAF Security Version 8.2.1.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 2011 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, United States of America, and/or their licensors.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://documentation.softwareag.com/legal/>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://documentation.softwareag.com/legal/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices and license terms, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". This document is part of the product documentation, located at <http://documentation.softwareag.com/legal/> and/or in the root installation directory of the licensed product(s).

Document ID: AAF-OPERATION-821-20110908

Table of Contents

1 Adabas SAF Security Operations	1
ADASAF Components	2
Starting a Utility or Nucleus	4
Logging On to a Database	5
Accessing and Changing Database Data	8
Adabas Operator Commands	20
Remote Access to Adabas	22
ADASAF Operator Commands	23
ADASAF User Exits	24
System Coordinator daemon	29

1 Adabas SAF Security Operations

▪ ADASAF Components	2
▪ Starting a Utility or Nucleus	4
▪ Logging On to a Database	5
▪ Accessing and Changing Database Data	8
▪ Adabas Operator Commands	20
▪ Remote Access to Adabas	22
▪ ADASAF Operator Commands	23
▪ ADASAF User Exits	24
▪ System Coordinator daemon	29


This document describes ADASAF operations.

ADASAF Components

ADASAF has three main components:

- The ADASAF main module, which operates in each secured Adabas address space
- Router extensions, which are linked with the Adabas SVC
- Online administration and monitoring system, which is a component of the Adabas Online System

As shown in the graphic below, all traffic between the database users and Adabas is controlled by the Adabas router. When ADASAF is installed, the ADASAF component attached to the Adabas router controls all access to the Adabas nucleus.



Adabas with ADASAF

All users must log on to their system using their Logon ID, usually a user name or code. Through the operating system or TP monitor, the installed security package checks the authorization of the Logon ID.

When calls are from a remote workstation or non-IBM platform, the Logon ID and logon password must be given to ADASAF using a remote logon procedure, as described in the section [Logging On to a Database](#). As an alternative to the remote logon procedure, you may configure ADASAF to use the node name or link name of the remote user as the SAF ID. Obviously, these node or link

names must be defined as users in the external security system, with the appropriate access rights to Adabas resources.

For Adabas, the router contains a security exit that extracts the user's Logon ID from the ACEE for the user. Even Adabas itself cannot be started unless the user starting the nucleus has proper authority. Through the SAF interface, ADASAF requests the proper authority from the external security packages whenever one of the following events occurs:

- A nucleus or utility begins operation;
- A user logs on to Adabas;
- A user issues an Adabas call;
- A user logs off Adabas;
- A user issues an Adabas operator command from an MVS console.

Starting a Utility or Nucleus

When starting an Adabas nucleus, utility or single-user mode batch job, ADARUN calls ADASAF, which checks that the starting user has access to the appropriate resource. The resource name has the format:

```
pppdbid.SVCsvc
```

where

Value	Description
<i>ppp</i>	Represents the last three characters of the program name specified by the ADARUN PROG= parameter. For example, NUC for a nucleus, CMP for the ADACMP utility or USR for a single-user mode batch job.
<i>dbid</i>	Specifies the Adabas Database ID in the selected format (3 or 5 digits with leading zeroes, or without leading zeroes). See the configuration parameter DBFLEN for more information.
.	Optional delimiter character, depending on the setting of the DELIM parameter.
SVC <i>svc</i>	The characters SVC followed by the 3-digit decimal number of the Adabas SVC used by this database.

When starting a nucleus, ADASAF uses the access level to determine whether to run in warn mode (that is, violations are logged, but the access is still allowed) or fail mode (violations result in failure, for example response code 200). If the starting user has only read access to the resource, ADASAF runs in warn mode. If the starting user has update access, ADASAF runs in fail mode.

If the starting user has no access to the resource, or the resource has not been defined, the nucleus abends with a U0042. For utilities, ADASAF requires read access to the appropriate resource. If

the starting user does not have read access, or the resource has not been defined, the utility abends with a U0042.

When using ADASAF to protect execution of ADACOM, you must specify a valid Adabas SVC number and a database id in the ADARUN parameters, for example:

```
ADARUN PROG=ADACOM,SVC=249,DBID=55555
```

The database id does not need to be valid; it is simply used by ADASAF to build the resource name to be checked. The above example would result in ADASAF checking for read access to a resource named COM55555.SVC249.

Resource Name Examples

The following Adabas resource name value is for starting the Adabas nucleus for database 1, which runs under SVC 237 (all possible entity constructions are shown):

Resource Name	Values for DELIM and DBFLEN Configuration Parameters
ENTITY=NUC001SVC237	DELIM= N, DBFLEN=0
ENTITY=NUC001.SVC237	DELIM= Y, DBFLEN=0
ENTITY=NUC00001SVC237	DELIM= N, DBFLEN=1
ENTITY=NUC00001.SVC237	DELIM= Y, DBFLEN=1
ENTITY=NUC1SVC237	DELIM= N, DBFLEN=2
ENTITY=NUC1.SVC237	DELIM= Y, DBFLEN=2



Note: Each utility program requires a definition in the external security database.

Logging On to a Database

- [Terminal Logon](#)
- [Remote Workstation Logon](#)
- [Alternatives to Remote Workstation Logon](#)
- [Logging On to Multiple Targets](#)

- Logging Off a Database


Terminal Logon

Normally, logging on to a database is done using an Adabas *OP* command. However, not all applications use an explicit *OP* command. ADASAF does not make any security check until the user actually attempts to access or update a file, at which point the user's identity will be authenticated.

If one of the non-activity timeout limits expires, the logon must again be validated, just as when logging on to Adabas for the first time.

Remote Workstation Logon

The logon from a remote workstation client comprises two phases.



ADASAF Remote Workstation Logon Sequence

During the initial request from the client program, ADASAF checks to ensure that the user is allowed to log on. The Adabas link routine, which actually performs the check, requires that the client send a Logon ID and security package password to the target.

When the initial command is sent from the client, ADASAF at first rejects the command with response code 208 (start of phase 1). This informs the client that an encrypted Logon ID and password are needed at the target for verification. See the section [ADASAF User Exits](#) for more information.

The encrypted Logon ID and password are then sent by the client and validated by the target, and the target returns response code 207 indicating successful completion (start of phase 2). If the duration of phase 1 is more than 60 seconds, a security violation occurs. The original user call is then sent by the client link routine to the database, where the user request is executed.

The Logon ID and password are prompted by the Adabas link routine included in the Entire Net-Work running on the supported platforms.

Entire Net-Work is a prerequisite for ADASAF workstation support. For more information, see the related *Entire Net-Work* documentation.

Alternatives to Remote Workstation Logon

As an alternative to Remote Workstation Logon, you can configure ADASAF to use either the Entire Net-Work node or link name of the remote user as the SAF Logon ID. This may be useful when the issuer of the remote calls cannot prompt for a User ID and password (for example, if it is a server rather than a client). For more information, see the description of the `REMOTE` parameter.

Logging On to Multiple Targets

If multiple ADASAF-secured targets are being controlled and these targets reside on different physical machines or nodes, each target node must have the same Logon ID and password assignment per user as every other target node.

Logging Off a Database

When users log off a database, they may or may not issue an explicit `CL` command. By default, a close command indicates the end of ADASAF validity for that user and the user is logged off the security system. If the user again logs on to Adabas, the user's validity and access rights are checked again, as though the user were logging on for the first time.

However, in databases where users have many short-lived sessions (for example, control databases or system file databases), this imposes a considerable overhead on the security system. To log a user on generally involves reading and updating security information and building up the cached security checks anew.

To avoid these overheads, you can instruct ADASAF, via the `LOGOFF` parameter, to log users off only when they time out (or are stopped) in Adabas, or never to log users off (with the exception that, if ADASAF needs to reclaim memory, it will log off the oldest inactive user).

On the other hand, if a user's security profile changes, ADASAF will continue to use the old profile until the user times out or is stopped. So, if you choose `LOGOFF=TIMEOUT` and a user's profile changes, you should stop the user via the `STOPU` operator command or Adabas Basic Services to bring the new profile into effect. If you choose `LOGOFF=NEVER` and a user's profile changes, use ADASAF Online Services to forcibly log the user off from the security system.

Accessing and Changing Database Data

- [Adabas and Natural Commands](#)
- [Defining Grouped Resource Names With AAFFILE](#)
- [Security Violations](#)
- [Cross-Level Security Checking](#)
- [Caching of Security Checks](#)
- [Adabas Basic Services](#)
- [Passwords and Cipher Codes](#)

Adabas and Natural Commands

ADASAF recognizes three categories of Adabas direct call commands:

- Data access commands (Lx, Sx and HI)
- Data update commands (Ax, Ex and Nx)
- Transaction data commands

The equivalent categories of Natural commands are

- Data access commands (READ, HISTOGRAM, FIND)
- Data update commands (UPDATE, DELETE, STORE)
- Transaction data commands (END TRANSACTION with operand1, GET TRANSACTION DATA, generated OP and CL commands with option 2 set to E). For more information, see the description of the ETDATA parameter.

Only these types of calls have significance for ADASAF and the related security package. ADASAF recognizes and classifies all database calls according to one of the command categories described above and performs the authorization check appropriate to the command category (that is, ATTR=READ for access commands and ATTR=UPDATE for update commands).

ADASAF authorizes use of Adabas data by building a resource name to represent the file being used and instructing the security system to validate the caller's access to that resource name. The format of the resource name is defined by the DELIM and DBFLEN configuration parameters:

<i>lvldb</i> idFILnnnnn	if DELIM=N
CMD <i>db</i> id.FILnnnnn	if DELIM=Y

where

Value	Description
<i>lvl</i>	is the required access level (ACC for access commands and UPD for update)
<i>dbid</i>	represents the Database ID, which is specified in the format selected by the DBFLEN parameter.
<i>nnnnn</i>	represents the file number, which is specified in the format selected by the DBFLEN parameter.

For example, assuming that DELIM=Y and DBFLEN=1 (5 digits, with leading zeroes), a DELETE against database 1, file 456, must have update access to the resource CMD00001.FIL00456.

The resource name may optionally be preceded by a prefix (as defined by the AAFPREFX configuration parameter) and the SAF userid of the job which issued the Adabas call (if the XLEVEL configuration parameter is set to 3).

As an alternative to this, you can instruct ADASAF to build grouped resource names for checking access to Adabas files. This gives a number of benefits:

- Optimize security administration by grouping related files under a single resource name, even across multiple databases
- Delegate security administration by grouping related files under the same prefix or major name
- More meaningful resource names
- No need to change the security system if a file is renumbered (the ADASAF file resource name table must be changed though)

The resource name for Adabas files may be considered to contain a number of nodes:

Type	Optional/Required	Setting
Prefix	Optional	As defined by AAFPREFX
Job userid	Optional	Only if XLEVEL=3
Major	Required	CMD00001, ACC00001, UPD00001 depending on DELIM and DBFLEN
Minor	Required	FIL00456 depending on DBFLEN

You can provide your own values for the Prefix, Major and Minor nodes of the resource name, to group many files together as a single resource

Defining Grouped Resource Names With AAFFILE

The AAFFILE macro is supplied on the ADASAF source library and is used to create a load module which defines prefixes, major nodes and/or minor nodes for file numbers or ranges of file numbers. You choose what mixture of prefixes, major and minor nodes you wish to use and for which files. Having created the load module, you identify it to ADASAF using the FILETAB configuration parameter to specify the load module name. The module must be available in an APF-authorized step library of the Adabas nucleus. At initialization, ADASAF attempts to load the nominated module. If the load fails, ADASAF issues message AAF004 and instructs the Adabas nucleus to terminate.

AFFILE Parameters

AFFILE has 3 parameters as described in the table below:

Parameter Syntax	Eplananation
TYPE={ PREFIX MAJOR MINOR FINAL } ↔	<p>TYPE=FINAL must be the last statement before the END and generates the load module contents, based on the previous AFFILE statements.</p> <p>TYPE=PREFIX MAJOR FINAL defines a name of 1 to 8 characters and a list of file numbers or ranges for which that name is to be used as the prefix, major node or minor node.</p>
NAME=1 to 8 characters	Specifies the name to be used. The name must conform to the resource naming conventions of your security system.
FILES={ (nnnnn, nnnnn-nnnnn...) ALL }	Specifies a list of files or ranges of files for which this name should be used. FILES=ALL denotes that this name will be used for all files.

A sample assembly and link job is provided in SAGI055 in the JOBS installation dataset.

AFFILE Parameter Examples

Example 1

```

AFFILE TYPE=PREFIX, NAME=TEST, FILES=ALL
AFFILE TYPE=MAJOR, NAME=ACCOUNTS, FILES=(1, 5, 11-20, 251-300)
AFFILE TYPE=MAJOR, NAME=HR, FILES=(101-200)
AFFILE TYPE=MINOR, NAME=SALARY, FILES=(1, 11, 251)
AFFILE TYPE=FINAL
END
    
```

Assuming DBFLEN=1 together with the above AFFILE statements, the following resource names will be used for accesses to files on database 153:

File Number	Resource Name (DELIM=Y)	Resource Name (DELIM=N)
1	TEST.ACCOUNTS.SALARY	TEST.ACCOUNTSSALARY
38	TEST.CMD00153.FIL00038	TEST.ACC00153FIL00038
200	TEST.HR.FIL00200	TEST.HRFIL00200
299	TEST.ACCOUNTS.FIL00299	TEST.ACCOUNTSFIL00299

Example 2

```

AAFFILE TYPE=PREFIX,NAME=ACCOUNTS,FILES=(1,5,11-20,251-300)
AAFFILE TYPE=MAJOR,NAME=PAYMENTS,FILES=(1,5,11-20)
AAFFILE TYPE=MAJOR,NAME=HR,FILES=(101-200)
AAFFILE TYPE=MINOR,NAME=SALARY,FILES=(1,11,251)
AAFFILE TYPE=FINAL
END

```

Assuming DBFLEN=1 together with the above AAFFILE statements, the following resource names will be used for accesses to files on database 253:

File Number	Resource Name (DELIM=Y)	Resource Name (DELIM=N)
1	ACCOUNTS.PAYMENTS.SALARY	ACCOUNTS.PAYMENTSSALARY
38	CMD00253.FIL00038	ACC00253FIL00038
200	HR.FIL00200	HRFIL00200
299	ACCOUNTS.CMD00253.FIL00299	ACCOUNTS.ACC00253FIL00299

As these examples show, you have complete flexibility in using grouped and standard database/file-specific resource names in any combination.

You will usually need to create a different load module for each database where grouped resource names are to be used, because different databases are likely to have different file grouping requirements.

Security Violations

If the security package does not recognize the user or entity being validated, or the user does not have sufficient access authority, ADASAF returns the following response code to the user:

- 200 when running in fail mode. Application programs that operate on an ADASAF-protected nucleus must check for a non-zero response code
- Zero (0) when running in warn mode

In either case, security violations can optionally be logged in the nucleus DDPRINT or SAFPRINT output.

Cross-Level Security Checking

At its simplest, ADASAF validates that a user has the necessary authority to access or modify Adabas files. However, additional levels of security are available to protect inadvertent or unauthorized data access.

This is known as cross-level checking and allows both the user's and the job's access permissions to be verified. For example, users may be given access to production data but only when they access it from a production TP monitor or batch job.

To achieve this level of protection, ADASAF performs two security checks against the same resource profile (CMD00001.FIL00456 in the example above), but for different resource classes:

- the user's User ID is checked against the resource in the class defined by the `DBCLASS` parameter
- the originating job's User ID is checked against the resource in the class defined by the `NWCLASS` parameter

If either check fails, the Adabas command is rejected with response 200.

Choosing the XLEVEL Setting

Set `XLEVEL` to

- 0: when users' access rights are not dependent on which environment (job) the user runs in
- 1: when certain jobs (for example, test TP monitors or TSO users) are not allowed to access this database
- 2: when certain jobs (for example, test TP monitors or TSO users) are only allowed to access some files on this database
- 3: when different users have different access requirements depending on which job they are running in

The following is an example of using `XLEVEL=2`.

Assume that user ABC is allowed to update file 456 on database 1 from production CICS but not from TSO; and that user XYZ is allowed to update file 456 on database 1 from production CICS and also from TSO; and that production CICS runs under User ID PCICS.

This would require the definition of the profile `CMD00001.FIL00456` in both the `DBCLASS` and `NWCLASS` resource classes and granting these permissions (`DBCLASS=ADASEC` and `NWCLASS=XLVADA`):

User	Class	Profile Name	Access
ABC	ADASEC	CMD00001.FIL00456	Read, Update
ABC	XLVADA	CMD00001.FIL00456	None
PCICS	ADASEC	CMD00001.FIL00456	None
PCICS	XLVADA	CMD00001.FIL00456	Read, Update
XYZ	ADASEC	CMD00001.FIL00456	Read, Update
XYZ	XLVADA	CMD00001.FIL00456	Read, Update

ADASAF performs the following checks:

1. ABC accesses file 456 from production CICS:
 - Does ABC (the individual user) have access to resource ADASEC /CMD00001.FIL00456? Yes.
 - Does PCICS (the originating job's user) have access to resource XLVADA /CMD00001.FIL00456? Yes.
 - The access is allowed.
2. ABC accesses file 456 from TSO:
 - Does ABC (the individual user) have access to resource ADASEC /CMD00001.FIL00456? Yes.
 - Does ABC (the originating job's user) have access to resource XLVADA /CMD00001.FIL00456? No.
 - The access is rejected and the command receives response 200.
3. XYZ accesses file 456 from TSO
 - Does XYZ (the individual user) have access to resource ADASEC /CMD00001.FIL00456? Yes.
 - Does XYZ (the originating job's user) have access to resource XLVADA /CMD00001.FIL00456? Yes.
 - The access is allowed.

In this way the database resources are protected not only for individuals but also for jobs. A user may only access allowed resources from jobs which also have the necessary access to those resources.

However, suppose the requirement is more complicated:

ABC is allowed to update file 456 on database 1 from production CICS but not from TSO; and user XYZ is allowed to access file 456 on database 1 from TSO but not from production CICS.

ABC's security requirements are satisfied, but XYZ can access file 456 from production CICS, even though it is not desired (because once a user has access to a resource, ADASAF will allow that access from any job which also has the necessary permissions).

To achieve this level of security, it is necessary to set the XLEVEL parameter to 3, which instructs ADASAF to verify a user's access to a resource profile of the format:

uuuuuuuu.dddddddd.ffffff

where:

<i>uuuuuuuu</i>	is the User ID of the originating job
<i>ddddddd.f</i>	is the Database ID and file number, as in a standard ADASAF resource profile

The resource profile length must be defined to the security system as 26 rather than 17. Therefore, the following definitions must be made in the security system:

User	Class	Profile Name	Access
ABC	ADASEC	PCICS.CMD00001.FIL00456	Read, Update
XYZ	ADASEC	PCICS.CMD00001.FIL00456	None
XYZ	ADASEC	XYZ.CMD00001.FIL00456	Read

And disallow access to undefined resources (DBUNI=N) or define a profile name ABC.CMD00001.FIL00456 and give user ABC no access to it.

ADASAF now performs the following checks:

1. ABC accesses file 456 from production CICS
 - Does ABC have access to resource ADASEC /PCICS.CMD00001.FIL00456? Yes.
 - The access is allowed.
2. ABC accesses file 456 from TSO
 - Does ABC have access to resource ADASEC /ABC.CMD00001.FIL00456? No.
 - The access is rejected and the command receives response 200.
3. XYZ accesses file 456 from TSO
 - Does XYZ have access to resource ADASEC /XYZ.CMD00001.FIL00456? Yes.
 - The access is allowed.
4. XYZ accesses file 456 from production CICS
 - Does XYZ have access to resource ADASEC /PCICS.CMD00001.FIL00456? No.
 - The access is rejected and the command receives response 200.

Caching of Security Checks

The results of data access and update checks, both successful and unsuccessful, are cached by ADASAF. There are two levels of caching:

- A generalized resource cache, which contains a given number of user-based entries and holds the profile names for resources that have been successfully checked for this SAF user. Both the number of entries and the number of profile names per entry are configurable by parameter. This cache is particularly effective in conjunction with the `LOGOFF=TIMEOUT/NEVER` parameter as it precludes the need to log on repetitively to the security system (and re-populate the cached resources) in databases where users frequently log on to Adabas, do a small amount of work and logoff again. Each user entry is $(256 + (\text{DBNCU} * 17) + (\text{NWNCU} * 17))$ bytes in size and, if there are more users than entries, the oldest entry is overwritten when a new entry is required. The total size of this cache is specified by the `GWSIZE` parameter.
- The second cache is a quick look-up cache and contains an entry for each Adabas user (the number of entries is set to the value of the Adabas `NU` parameter, plus 25%, so if `NU` is 200, this cache will have 250 entries). Each entry contains 128 bytes of fixed information and eight times the value of the `MAXFILES` parameter for holding information about files that the user has attempted to access. Whenever a user accesses or updates an Adabas file, this cached file list is checked to determine whether the user already has the necessary access level.

Adabas Basic Services

You can use ADASAF to incorporate protection of Adabas Basic Services into your SAF security repository. This option can be activated on a nucleus-by-nucleus basis using the `ABS` parameter. There are two levels of security, as follows:

Level	Description
1	Only the main functions are protected. If a user has read access to a main function, all subfunctions are automatically permitted (<code>ABS=1</code>).
2	Subfunctions are also protected. The user must have access to the main function and the subfunction (<code>ABS=2</code>).

The resource check is performed against the resource class specified by the `DBCLASS` parameter and the resource name is built in accordance with the settings of the `DBFLEN` and `DELIM` parameters. Access to undefined resources is governed by the `DBUNI` parameter.

The following tables define the subfunctions for each Adabas Basic Services function, together with the resource name that is checked (assuming `DBFLEN` is set to 2 - 5 digits with leading zeros, and `DELIM=Y`).

Before checking any of the individual resources, ADASAF establishes a user's right to use Adabas Basic Services against this nucleus by verifying that the user has read access to the resource `ABSdddd.GENERAL`.



Note: The Subfunction Profile (listed in the following tables) is used only when ABS=2 (subfunction protection).

Session Monitoring Function

Function:	Session Monitoring
Function Profile:	ABSdddd.SESSION

Subfunction	Subfunction Profile*	Access
Display Cluster Members	ABSdddd.CLUSTER	Read
Display Installed Products	ABSdddd.DISINST	Read
Maintain User Profiles	ABSdddd.USER	Read
Display Parameters	ABSdddd.PARM	Read
Modify Parameters	ABSdddd.PARM	Update
Display Queues	ABSdddd.QUEUES	Read
Refresh Nucleus Statistics	ABSdddd.REFSTATS	Read
Current Resource Statistics	ABSdddd.STATS	Read
Maintain TCP/IP URL	ABSdddd.TCPIP	Read
Display Resource Utilization	ABSdddd.RESUTIL	Read
Display Maintenance Levels	ABSdddd.ZAPS	Read
Display Event Log Buffer	ABSdddd.EVENTLOG	Read
Replicator Management	ABSdddd.REPLMGMT	Read

*Used only when ABS=2 (subfunction protection)

Checkpoint Maintenance Function

Function	Checkpoint Maintenance
Function Profile	ABSdddd.CHECKP

Subfunction	Subfunction Profile*	Access
List Checkpoints	ABSdddd.CHECKP	Read
Delete Checkpoints	ABSdddd.CHECKP	Update

*Used only when ABS=2 (subfunction protection)

FILE Maintenance Function

Function	File Maintenance
Function Profile	ABS <code>dddd</code> .FILE

Subfunction	Subfunction Profile*	Access
Define/Modify FDT	ABS <code>dddd</code> .FDT	Read
Release Descriptor	ABS <code>dddd</code> .REL	Read
Delete File	ABS <code>dddd</code> .DEL	Read
Define New File	ABS <code>dddd</code> .DEF	Read
Modify File Parameters	ABS <code>dddd</code> .MOD	Read
Reorder File Online	ABS <code>dddd</code> .ORD	Read
Refresh Rile to Empty	ABS <code>dddd</code> .REF	Read
Allocate/Deallocate File Space	ABS <code>dddd</code> .ALL	Read
Maintain Expanded Files	ABS <code>dddd</code> .EXP	Read
Logically Delete/Undel Descriptor	ABS <code>dddd</code> .LOGDDESC	Read

*Used only when ABS=2 (subfunction protection)

Database Maintenance Function

Function	Database Maintenance
Function Profile	ABS <code>dddd</code> .DBMAINT

Subfunction	Subfunction Profile*	Access
Add New Dataset to Asso/Data	ABS <code>dddd</code> .ADD	Read
Increase/Decrease Asso/Data	ABS <code>dddd</code> .INCREASE	Read
List/Reset DIB Entries	ABS <code>dddd</code> .DIB	Read
Recover Unused Space	ABS <code>dddd</code> .RECOVER	Read
Uncouple Two Adabas Files	ABS <code>dddd</code> .UNCOUPLE	Read

*Used only when ABS=2 (subfunction protection)

Session Opercoms Function

Function	Session Opercoms
Function Profile	ABS <code>dddd</code> .OPERCOMS

Subfunction	Subfunction Profile*	Access
Extended Error Recovery	ABS <code>dddd</code> .ERROR	Read
Force Dual Log Switch	ABS <code>dddd</code> .LOG	Read
Lock/Unlock Files	ABS <code>dddd</code> .LOK	Read
Reset Online Dump Status	ABS <code>dddd</code> .RDUMPST	Read
Stop User(s)	ABS <code>dddd</code> .STOPU	Read
Termination Commands	ABS <code>dddd</code> .TERM	Read
Manage Online Utilities	ABS <code>dddd</code> .UTILS	Read
Allocation/deallocation of CLOGs/PLOGs	ABS <code>dddd</code> .LOGALLOC	Read
User Table Maintenance	ABS <code>dddd</code> .USERTAB	Read
Issue Reactivate CLOG Command	ABS <code>dddd</code> .REACCLOG	Read
Replicator Management	ABS <code>dddd</code> .REPLMGMT	Read

*Used only when ABS=2 (subfunction protection)

Database Report Function

Function	Database Report
Function Profile	ABS <code>dddd</code> .REPORT

Subfunction	Subfunction Profile*	Access
List Files with Critical Extents	ABS <code>dddd</code> .EXTENTS	Read
Display Field Description Table	ABS <code>dddd</code> .DFD	Read
Display File	ABS <code>dddd</code> .DIF	Read
General Database Layout	ABS <code>dddd</code> .LAYOUT	Read
List VOLSER Distribution	ABS <code>dddd</code> .VOLSER	Read
Display Asso/Data Block	ABS <code>dddd</code> .DRABN	Read
Display Unused Storage	ABS <code>dddd</code> .UNUSED	Read

*Used only when ABS=2 (subfunction protection)

Space Calculation Function

Function	Space Calculation Report
Function Profile	ABS <code>dddd</code> .SPACE

The Space Calculation function has no subfunction profiles.

Passwords and Cipher Codes

Assuming that an Adabas command satisfies the appropriate security checks, ADASAF can automatically apply Adabas passwords and cipher codes if the SAF security system is RACF. At nucleus initialization, ADASAF extracts the INSTDATA field from the RACF profiles for all files in the current database (if PRMDELIM=N, the ACC prefixed profiles are used, otherwise the CMD prefixed profiles are used) and subsequently applies them to any command for the relevant file. You must define an ACC or CMD prefixed profile (for example ACC123FIL45 or CMD00123.FIL00045) for each file that needs a cipher code or password. Cipher codes should be specified as C=`nnnnnnnn` where `nnnnnnnn` is the eight-digit cipher code. Passwords should be specified as P=`xxxxxxxx`, where `xxxxxxxx` is the password. If a file has both, they should be separated by a comma, for example C=12345678 , P=PASSWORD. A file may have only one cipher code and one password.

The Adabas password and cipher code can be provided by a user exit rather than being stored in RACF. This is activated by specifying P=USEREXIT (or C=USEREXIT) in the RACF INSTDATA field for the relevant file's profile. Then, whenever a command passes security checks, ADASAF invokes the user exit and uses the returned information as password or cipher code. Member ADASAFX1 in AAFvrs.SRCE contains a sample user exit, a description of the interface, and instructions for installing the exit.

As an alternative to using RACF INSTDATA, or for SAF security systems other than RACF, passwords and cipher codes may be provided at nucleus initialization time by user exit ADASAFX2. If ADASAFX2 is linked with SAFADA, no attempt is made to extract passwords and cipher codes from the security system. Instead, any passwords and cipher codes for files in the current database must be supplied by ADASAFX2.

See the section [Password / Cipher Code Exits](#) for more information.

Adabas Operator Commands

Adabas operator commands entered from a z/OS console can be secured by either defining security resources for the operator commands or by defining them as belonging to predefined groups and defining security resources to represent those command groupings. A sample source member, ADAEOPTB, is provided which defines operator commands to one of three groups, namely DISPLY, MODIFY and SPECAL. The choice of group names and how commands are grouped is decided on site and determines which Adabas operator commands may be entered from a z/OS console. When adding or modifying an entry in ADAEOPTB, specify the operator command (if longer than 8 characters, only provide the first 8 characters) and grouping requirement, for example:

```
ENTITY NOLOGGIN,SPECAL /* prevent command logging */
```

associates the NOLOGGING operator command with the group SPECAL. If ADAEOPTB is not used, then the first eight characters of the command (up to a space or =) are used as the basis for validation.



Note: Operator commands are allowed or disallowed based on either the User ID of the user who starts the Adabas nucleus, or on the identifier of the started task. The choice is *not* based on the User ID of the user issuing the console command.

The following is a sample grouping as supplied in the ADAEOPTB source library member. The following list is not restricted to the commands shown here and can be added to or subtracted from, depending on installation requirements. For more information about Adabas operator commands, see the *Adabas Operations* documentation.

The display-type Adabas commands are:

CSTAT	DHQ	DONLSTAT	DUQE
CSUM	DHQA	DPARM	DUUQE
DAUQ	DLOCKF	DPPT	DXCACHE
DCQ	DMEMTB	DRES	DXFILE
DDIB	DNC	DSTAT	DXLOCK
DDSF	DNFV	DTH	DXMSG
DFILES	DNH	DUQ	DXSTAT
DFILUSE	DNU	DUQA	

The modify-type Adabas commands are:

ADAEND	CDATAHSP	CFILE	RESUME
CANCEL	CDATAL64	CFSTAT	REVIEW
CASSODSP	CDATAMAX	CINCLUDE	TNAA
CASSOEXT	CDATAV64	CLOGMRG	TNAE
CASSOHSP	CDELETE	CPARM	TNAX
CASSOL64	CDEMAND	CRETRY	TT
CASSOMAX	CDISABLE	CT	MXCANCEL
CASSOV64	CDISPSTAT	DUMP	MXMSG
CBUFNO	CENABLE	FEOFCL	MXMSGWAR
CCHANGE	CEXCLUDE	FEOFPL	MXWTOR
CCTIMEOUT	CFDELETE	FMXIO	
CDATADSP	CFDISABLE	HALT	
CDATAEXT	CFENABLE	RDUMPST	

The special Adabas commands are:

ALOCKF	LOGRB	NOLOGVB	SMFRECNO
AOSLOG	LOGSB	NOLOGVOLIO	SMFSUBSYS
ASYTVS	LOGUX	NWCONNECT	SGMT
CLUFREEUSER	LOGVB	ONLRESUME	STOPF
DELUF	LOGVOLIO	ONLSTOP	STOPI
DELUI	LOGWARN	ONLSUSPEND	STOPU
LOCKF	NOLOGCB	RALOCKF	SYNCC
LOCKU	NOLOGFB	RALOCKFA	TCPIP
LOCKX	NOLOGGING	READONLY	TM
LOGCB	NOLOGIB	REVIEWHUBID	UNLOCKF
LOGFB	NOLOGIO	SMFDETAIL	UNLOCKU
LOGGING	NOLOGRB	SMFDETAILADD	UNLOCKX
LOGIB	NOLOGSB	SMFDETAILDEL	UTIONLY
LOGIO	NOLOGUX	SMFINTERVAL	

To validate authorization for operator commands, ADASAF checks for read access to an entity name of the format

OPR <i>dbid.type</i>	if DELIM=Y
OPR <i>dbidtype</i>	if DELIM=N

Where OPR is hard-coded, *dbid* specifies the Database ID in the format appropriate to the setting of the DBFLEN parameter; and *type* is MODIFY, DISPLY or SPECAL if ADAEOPTB is used, or is the command name itself (up to eight characters) if ADAEOPTB is not used.

For example, assuming that a standard ADAEOPTB is used, that DELIM=Y and DBFLEN=2 (no leading zeroes); when the operator issues a DSTAT command to database 235, ADASAF will check that the User ID under which database 235 is executing has read access to the resource OPR235.DISPLY.

Assuming that ADAEOPTB is not used, that DELIM=Y and DBFLEN=2, when the operator issues a STOPU=X'123' command to database 235, ADASAF will check that the User ID under which database 235 is executing has read access to the resource OPR235.STOPU.

Whether ADAEOPTB is used or not, ADASAF operator commands are always checked against type SPECAL.

Remote Access to Adabas

Remote IBM Peer-to-Peer Database Access

With ADASAF and Entire Net-Work, remote Adabas calls to a multi-user node (MPM) can be validated when ADASAF is active on all participating MVS systems.

Entire Net-Work transports the User ID, which it obtains from the active external system on the host node, to the target node. There, ADASAF uses the User ID to construct the RACROUTE REQUEST=AUTH security calls. Support for validation based on dynamic User ID strings or connect groups is available.

Prerequisites for IBM Peer-to-Peer Access

The prerequisites for running ADASAF with Entire Net-Work are as follows:

- All participating Entire Net-Work nodes that make remote calls to an Adabas nucleus with ADASAF active must be running a current version of Entire Net-Work. All Adabas components must be current;
- An external security system like RACF, CA-Top Secret, and CA-ACF2 must be active on every Entire Net-Work /ADASAF MPM node. The external security systems can vary from node to node, since the external security information being transported by Entire Net-Work is in a format acceptable by all systems;

- The Adabas SVC used by Entire Net-Work must be current and must contain the SAF security extensions for ADASAF.

Database Access from Remote Workstations

When ADASAF is active on a multi-user (MPM) node, you can secure remote Adabas calls with Entire Net-Work for Workstations. The Adabas link routines supplied with Entire Net-Work provide the mechanism required for the two-phase logon described in the section [Remote Workstation Logon](#). Once logon has been completed, all validation of resources occurs just as it does when the remote user is executing on the mainframe.

Additionally, as described in the section [Alternatives to Remote Workstation Logon](#), ADASAF can secure remote Adabas calls by selecting the Entire Net-Work Node name of the remote caller, or the Entire Net-Work Link name used by the remote caller, as the user ID on which security checks are based. If you select either (or both - different databases can use different options) of these mechanisms, you must define the appropriate Node and Link names as users in your security system, with the correct access permissions for the relevant Adabas resources.

Operating and Remote Call Characteristics

The external security User ID that is transported from the host node takes on the profile of the User ID in the external security system, the User ID must be defined with the proper authority to ensure access to only the proper Adabas resources.

Calls from Inactive External Security Nodes

A remote call to a target ADASVC with ADASAF active from an inactive external security node causes a security violation (response code 200) on the calling side.

ADASAF Operator Commands

MVS operator communication with ADASAF is achieved using the z/OS `Modify (F)` command. All ADASAF operator commands are prefixed with AAF. For example:

```
F ADA123,AAF SSTAT
```



Note: The ADASAF operator commands are enabled by ADAEOPV. So you need to link ADAEOPV (and optionally ADAEOPTB) with ADAIOR (see ADASAF installation procedure, step 7) and define command security rules.

Command	Description
SREST	Restart ADASAF, ensuring that all data held in the ADASAF buffers are flushed. Any data held by the security system itself in the Adabas address space are also flushed. The operation is transparent to all online and batch users.
SSTAT	Display general statistics on the operator console for ADASAF. These statistics are the same as those available using Online Services.
SUSERS	Display a list of active users.
SUSTAT user-id	Display statistics for a specified user. These statistics are the same as those available from Online Services.
SSNAP hhhhhhhh	Display a selected portion of the ADASAF's memory. Operation is not terminated. Note: The commands SSNAP=AGL, SSNAP=CFA, and SNEWCOPY are activated by the next user logical command to the affected nucleus.
SSNAP=AGL	Display the ADASAF global work area. Operation is not terminated.
SSNAP=CFA	Display the ADASAF user file cache area. Operation is not terminated.
SHELP	Display all possible operator commands.
SNEWCOPY	Restart ADASAF and reload modules. This command may be useful if ADASAF parameters need to be changed, or a ZAP applied to the SAF Security kernel, without interrupting nucleus operation.
Note: All of the above commands can be issued using Online Services.	
TRACE= {0 1 2 3}	TRACE=0: suppress security trace TRACE=1: trace security violations TRACE=2: trace successful security checks TRACE=3: trace all security checks


ADASAF User Exits

Encryption / Decryption Exit

ADASAF provides an exit for encrypting and decrypting the user Logon ID and password during the two-phase remote logon process. The encryption/decryption algorithms that are used must produce the same result on the workstation as in the Adabas ADASAF mainframe user exit. Information is provided in the appropriate *Entire Net-Work* documentation.

If a user-provided exit is not used with ADASAF, ADASAF uses its own internal encryption/decryption routines during the logon. If a user exit is used, the user exit CSECT must be "ESIEXIT" and must be linked to the SAFADA module.

The following graphic illustrates the parameter list that ADASAF passes to the ADASAF user exit:



ADASAF Encryption/Decryption User Exit Parameters

Linking User Exit ESIEXIT into ADASAF

The following example shows how to link the ADASAF user exit ESIEXIT module into the ADASAF module:

```
//JOB
//LKESI      EXEC PGM=IEWL,PARM='XREF,LET,LIST,NCAL,REUS'
//SYSPRINT  DD  SYSOUT=*
//SYSUT1    DD  UNIT=SYSDA,SPACE=(CYL,(1,1))
//SYSLMOD   DD  DSN=YOUR.APF.LOADLIB,DISP=SHR (target execution loadlib)
//AAFLIB    DD  DSN=AAFvrs.LOAD,DISP=SHR      (distributed ADASAF loadlib)
//YOURLIB   DD  DSN=YOUR.USER.EXIT.LOADLIB,DISP=SHR (user exit loadlib)
//SYSLIN    DD  *
INCLUDE  AAFLIB (SAFADA)                      (ADASAF module)
INCLUDE  YOURLIB (ESIEXIT)                   (your encryption/decryption module)
NAME SAFADA (R)
/*
```

Password / Cipher Code Exits

If you want ADASAF to provide Adabas passwords and cipher codes, but for any reason these cannot be stored in RACF (or you use a different security system), you may use user exits to return the passwords and cipher codes to ADASAF. These exits are only invoked if you have set the PASSWORD or CIPHER configuration parameter to Y.

ADASAFX1

The ADASAFX1 user exit is used to supply passwords/cipher codes at Adabas command execution time. It is invoked for every file where the RACF profile's INSTDATA specifies P=USEREXIT or C=USEREXIT. The user exit must be re-entrant and must have a CSECT name of ADASAFX1. Addressing mode on entry is 31-bit and the exit must return in the same mode.

Example

To link the exit into ADASAF, use a job similar to the following:

```
//LINKSAF  EXEC PGM=IEWL,
//          PARM=`MAP,LET,LIST,XREF,NCAL,REUS'
//SYSPRINT DD  SYSOUT=X
//SYSUT1   DD  UNIT=SYSDA,SPACE=(CYL,(1,1))
//AAFLOAD  DD  DSN=AAFvr1.LOAD,DISP=SHR
//EXITLOAD DD  DSN=your.LOAD,DISP=SHR
//SYSLMOD  DD  DSN=your.LOAD,DISP=SHR      must be APF-authorized
//SYSLIN   DD  DDNAME=SYSIN
//SYSIN    DD  *
MODE AMODE(31),RMODE(ANY)
INCLUDE  AAFLOAD(SAFADA)
```

```
INCLUDE EXITLOAD(ADASAFX1)
NAME SAFADA(R)
```

Registers

The registers on entry to ADASAFX1 are as follows:

R1	Address of the parameter address list
RD	Address of two consecutive 18-word save areas
RE	Return address
RF	ADASAFX1 base address

All registers must be restored to their contents on entry before returning to ADASAF.

R1 on entry contains the address of a six-word address list:

Word 1	Address of call type. Call type is a single byte. If set to X"80", ADASAF expects a password; if set to X"40", ADASAF expects a cipher code.
Word 2	Address of return code. Return code is a full word. If set to X"00000000", ADASAF uses the value returned by the exit as password or cipher code. Otherwise, ADASAF leaves the Adabas control block unchanged.
Word 3	Address of the database ID. The database ID is a two-byte binary number.
Word 4	Address of the file number. The file number is a two-byte binary number.
Word 5	Address of the returned password/cipher code. This is an eight-byte field containing binary zeros on entry. It should be set to the desired password or cipher code, which ADASAF inserts into the Adabas control block if the return code in parameter 2 is 0.
Word 6	Address of the Adabas parameter list for the command being processed. The first word of this parameter list contains the address of the Adabas Control Block, when running in an Adabas Version 7 nucleus, or of the Extended Adabas Control Block, when running in an Adabas Version 8 (or higher) nucleus.

ADASAFX2

The ADASAFX2 user exit is used to supply passwords/cipher codes at nucleus initialization time. It is invoked by ADASAF during nucleus initialization and may return a password and or a cipher code for as many files as required (providing the value of MAXPC is not exceeded). The user exit must be re-entrant and must have a CSECT name of ADASAFX2. Addressing mode on entry is 31-bit and the exit must return in the same mode.



Note: If ADASAFX2 is used, ADASAF does not attempt to extract passwords and cipher codes from RACF INSTDATA.

Example

To link the exit into ADASAF, use a job similar to the following:

```
//ADASAF EXEC PGM=IEWL,
//      PARM='MAP,LET,LIST,XREF,NCAL,REUS'
//SYSPRINT DD SYSOUT=X
//SYSUT1 DD UNIT=SYSDA,SPACE=(CYL,(1,1))
//AAFLOAD DD DSN=AAFvr1.LOAD,DISP=SHR
//EXITLOAD DD DSN=your.LOAD,DISP=SHR
//SYSLMOD DD DSN=your.LOAD,DISP=SHR           must be APF-authorized
//SYSLIN DD DDNAME=SYSIN
//SYSIN DD *
MODE AMODE(31),RMODE(ANY)
INCLUDE AAFLOAD(SAFADA)
INCLUDE EXITLOAD(ADASAFX2)
NAME SAFADA(R)
```

Registers

The registers on entry to ADASAFX2 are as follows:

R1	Address of the parameter address list
RD	Address of an 18-word save area
RE	Return address
RF	ADASAFX2 base address

All registers must be restored to their contents on entry before returning to ADASAF.

R1 on entry contains the address of a five-word address list:

Word 1	Address of Database ID. The Database ID is a two-byte binary number. ADASAF passes the current Database ID to the exit.
Word 2	Address of return code. The return code is a four-byte binary number and must be set by ADASAFX2. ADASAF will call the exit repetitively until the return code is not 0. If set to 0, ADASAF will use the values returned by the exit. If not 0, ADASAF will not call the exit again (but will still use the values returned on previous calls).
Word 3	Address of file number. The file number is a two-byte binary number. The first time in, this will be X"0000". On subsequent calls it will contain the most recently returned file number. The exit must set it to the file number to which the returned password or cipher code applies.
Word 4	Address of code type. This is a one-byte binary field. The exit must set this to X"40" when returning a cipher code and to X"80" when returning a password.
Word 5	Address of an eight-byte password/cipher code. The exit must set this to the appropriate password or cipher code. If ADASAFX2 sets this to USEREXIT, ADASAF will subsequently invoke ADASAFX1 to provide a password or cipher code at Adabas command execution time.

System Coordinator daemon

The following sections describe operations for the security service in the System Coordinator daemon.

- [Activating the security service in the System Coordinator daemon](#)
- [Activating security protection of online administration for SAF Security](#)
- [Activating security protection of online administration for Fastpath](#)
- [Activating security protection of online administration for Transaction Manager](#)
- [Activating security protection of online administration for Vista](#)
- [Activating security protection of online administration for System Coordinator](#)
- [Operator commands for the security service in the System Coordinator daemon](#)

Activating the security service in the System Coordinator daemon

To activate:

1. Create a SAFCFG module (if you need different settings to the database).
2. Ensure all required libraries are in the STEPLIB concatenation. Refer to Check the STEPLIB Concatenation in the installation documentation.
3. Add PRODUCT=AAF to the daemon DDCARD dataset.

Activating security protection of online administration for SAF Security

Once you have a running daemon security service (see [Activating the security service in the System Coordinator daemon](#)), use option 2 of System Settings (see System Settings in *Adabas SAF Security Online Services*) to activate SAF Security online administration protection. These settings are stored in the configuration file assigned to LFILE 152. Therefore you can use different LFILES to vary your security behaviors. You **must** ensure the ability to change LFILE 152 (in the Natural parameter module or in Natural dynamic parameters, etc) is restricted to authorized people only!

The following table shows the online administration functions for which READ access to the indicated resource is required:

Function	Resource Name	Notes
System Settings	AAF.SETTINGS	Display system settings.
System Statistics	AAF.ACTIVITY.DB#####	##### is the id of the database or daemon for which information is requested.
SAF User ID Statistics	AAF.ACTIVITY.DB#####	##### is the id of the database or daemon for which information is requested.
Fix Display	AAF.SPECIAL.DB#####	##### is the id of the database or daemon for which information is requested.

Function	Resource Name	Notes
Storage Display	AAF.SPECIAL.DBnnnnnn	nnnnnn is the id of the database or daemon for which information is requested.
System Tracing	AAF.ACTIVITY.DBnnnnnn	nnnnnn is the id of the database or daemon for which information is requested.
System Parameters	AAF.ACTIVITY.DBnnnnnn	nnnnnn is the id of the database or daemon for which information is requested.

The following table shows the online administration functions for which UPDATE access to the indicated resource is required:

Function	Resource Name	Notes
System Settings	AAF.SETTINGS	Change system settings.
SAF User ID Statistics	AAF.ACTIVITY.DBnnnnnn	Required to reset or logoff a SAF user. nnnnnn is the id of the target database or daemon.
Server Restart	AAF.SPECIAL.DBnnnnnn	nnnnnn is the id of the target database or daemon.

Activating security protection of online administration for Fastpath

Once you have a running daemon security service (see [Activating the security service in the System Coordinator daemon](#)), logon to the Fastpath online administration library SYSAFP and use option 2 of System Settings (see System Settings in *Adabas SAF Security Online Services* which also applies to other online administration libraries) to activate Fastpath online administration protection. These settings are stored in the configuration file assigned to LFILE 152. Therefore you can use different LFILES to vary your security behaviors. You **must** ensure the ability to change LFILE 152 (in the Natural parameter module or in Natural dynamic parameters, etc) is restricted to authorized people only!

The following table shows the online administration functions for which READ access to the indicated resource is required:

Function	Resource Name	Notes
System Settings	AFP.SETTINGS	Display system settings.
Buffer Parameters	AFP.BUFFER.name	Display, copy or list files of a buffer. Name is the name of the buffer.
File Parameters	AFP.FILE.DBnnnnnn.FNRfffff	Display or copy a file. nnnnnn is the database id and fffff is the file number.
Client Runtime controls	AFP.CLIENT.type.name	Display, expand, list overrides, copy, display site info for a runtime control. type is the job type and name is the name, without *s (so *DEFAULT is checked against DEFAULT). Valid types are: BATCH

Function	Resource Name	Notes
		COMPLETE CICS-DTR CICS IMS UTM TSO CMS TIAM MULTITCB SINGLTCB MISCDTR SPATS
Buffer Information	AFP.ACTIVITY.DMN <i>nnnnnn</i>	<i>nnnnnn</i> is the node-id of the target daemon.
Database and File Information	AFP.ACTIVITY.DB <i>nnnnnn</i>	<i>nnnnnn</i> is the id of the selected database .
Optimized Job Information	AFP.ACTIVITY.jobname	jobname is the name of the selected job.
System Job Information	AFP.ACTIVITY.jobname	jobname is the name of the selected job.
Buffer History	AFP.HISTORY.name	name is the name of the selected buffer.
Asynchronous Buffer Services	AFP.SPECIAL.DMN <i>nnnnnn</i>	Informational functions. <i>nnnnnn</i> is the node-id of the target daemon.
Database Component Services	AFP.SPECIAL.DB <i>nnnnnn</i>	<i>nnnnnn</i> is the id of the target database.
Local SYSAFP Services	AFP.SPECIAL.jobname	Informational functions. jobname is the name of the job.
AFPLOOK Services	AFP.ACTIVITY.DB <i>nnnnnn</i>	<i>nnnnnn</i> is the id of the target database.
Fix Display	AFP.SPECIAL.jobname	jobname is the name of the client job for which fixes are to be displayed.
	AFP.SPECIAL.DMN <i>nnnnnn</i>	<i>nnnnnn</i> is the node number of the daemon for which fixes are to be displayed.
	AFP.SPECIAL.DB <i>nnnnnn</i>	<i>nnnnnn</i> is the database id of the database for which fixes are to be displayed.

The following table shows the online administration functions for which UPDATE access to the indicated resource is required:

Function	Resource Name	Notes
System Settings	AFP.SETTINGS	Change system settings.
Buffer Parameters	AFP.BUFFER.name	Add, modify, purge or rename a buffer. name is the name of the buffer.
File Parameters	AFP.FILE.DBnnnnnn.FNRfffff	Add, modify or purge a file. nnnnnn is the database id and fffff is the file number.
Client Runtime controls	AFP.CLIENT.type.name	Add, modify, purge or rename a runtime control (or one of its overrides, or its site info). type is the job type and name is the name, without *s (so *DEFAULT is checked against DEFAULT). Valid types are: BATCH COMPLETE CICS-DTR CICS IMS UTM TSO CMS TIAM MULTITCB SINGLTCB MISCDTR SPATS
Database and File Information	AFP.SPECIAL.DBnnnnnn	Services.nnnnnn is the id of the target database.
Optimized Job Information	AFP.SPECIAL.jobname	Services. jobname is the name of the job.
Asynchronous Buffer	Services AFP.SPECIAL.DMNnnnnnn	Operational functions. nnnnnn is the node-id of the target daemon.
Local SYSAFP Services	AFP.SPECIAL.jobname	Operational functions. jobname is the name of the job.

AFPCMD and the online Printing Facility are also subject to SAF Security, as shown in the following table:

Function	Object	Resource Name	Notes
LIST	JOB	AFP.ACTIVITY.DMNnnnnnn	nnnnnn is the node-id of the target daemon.
LIST	DATABASE	AFP.ACTIVITY.DMNnnnnnn	nnnnnn is the node-id of the target daemon.
LIST	FILE	AFP.ACTIVITY.DMNnnnnnn	nnnnnn is the node-id of the target daemon.
LIST	SET	AFP.ACTIVITY.DMNnnnnnn	nnnnnn is the node-id of the target daemon.
LIST	SUMMARY	AFP.ACTIVITY.DMNnnnnnn	nnnnnn is the node-id of the target daemon.
DISPLAY	JOB	AFP.ACTIVITY.jobname	jobname is the name of the job.

Function	Object	Resource Name	Notes
DISPLAY	DATABASE	AFP.ACTIVITY.DBnnnnnn	nnnnnn is the id of the selected database.
DISPLAY	FILE	AFP.ACTIVITY.DBnnnnnn	nnnnnn is the id of the selected database.
DISPLAY	SET	AFP.ACTIVITY.DBnnnnnn	nnnnnn is the id of the selected database.
DISPLAY	BUFFER	AFP.ACTIVITY.DMNnnnnnn	nnnnnn is the node-id of the target daemon.
DISPLAY	AFPLOOK	AFP.ACTIVITY.DBnnnnnn	nnnnnn is the id of the selected database.
DISPLAY	ALL		Resource profiles for individual resources are checked as necessary.
DISPLAY	SUMMARY	AFP.ACTIVITY.DMNnnnnnn	nnnnnn is the node-id of the target daemon.
PARMS	BUFFER	AFP.BUFFER.name	name is the name of the buffer.
PARMS	JOB	AFP.CLIENT.type.name	type is the job type and name is the name, without *s (so *DEFAULT is checked against DEFAULT). Valid types are: BATCH COMPLETE CICS-DTR CICS IMS UTM TSO CMS TIAM MULTITCB SINGLTCB MISCDTR SPATS
PARMS	FILE	AFP.FILE.DBnnnnnn.FNRfffff	nnnnnn is the database id and fffff is the file number.
STOP	BUFFER	AFP.SPECIAL.DMNnnnnnn	nnnnnn is the node-id of the target daemon.
STOP	JOB	AFP.SPECIAL.jobname	jobname is the name of the job.
STOP	DATABASE	AFP.SPECIAL.DBnnnnnn	nnnnnn is the id of the selected database.
STOP	FILE	AFP.SPECIAL.DBnnnnnn	nnnnnn is the id of the selected database.
RESTART	BUFFER	AFP.SPECIAL.DMNnnnnnn	nnnnnn is the node-id of the target daemon.
START	JOB	AFP.SPECIAL.jobname	jobname is the name of the job.
START	DATABASE	AFP.SPECIAL.DBnnnnnn	nnnnnn is the id of the selected database.
START	FILE	AFP.SPECIAL.DBnnnnnn	nnnnnn is the id of the selected database.

LIST, DISPLAY and PARMS functions require READ access to the resource.

STOP, RESTART and START require UPDATE access.

Activating security protection of online administration for Transaction Manager

Once you have a running daemon security service (see [Activating the security service in the System Coordinator daemon](#)), logon to the Transaction Manager online administration library SYSATM and use option 2 of System Settings (see System Settings in *Adabas SAF Security Online Services* which also applies to other online administration libraries) to activate Transaction Manager online administration protection. These settings are stored in the configuration file assigned to LFILE 152. Therefore you can use different LFILEs to vary your security behaviors. You **must** ensure the ability to change LFILE 152 (in the Natural parameter module or in Natural dynamic parameters, etc) is restricted to authorized people only!

The following table shows the online administration functions for which READ access to the indicated resource is required:

Function	Resource Name	Notes
System Settings	ATM.SETTINGS	Display system settings.
Client Runtime controls	ATM.CLIENT.type.name	Display, expand, list overrides, copy, display site info for a runtime control. type is the job type and name is the name, without *s (so *DEFAULT is checked against DEFAULT). Valid types are: BATCH COMPLETE CICS-DTR CICS IMS UTM TSO CMS TIAM MULTITCB SINGLTCB MISCDTR SPATS
Transaction Manager Information	ATM.ACTIVITY.DMNnnnnn	nnnnn is the node-id of the target daemon.
Special Services (Fix Display)	ATM.SPECIAL.jobname	jobname is the name of the client job for which fixes are to be displayed.
	ATM.SPECIAL.DMNnnnnn	nnnnn is the node number of the daemon for which fixes are to be displayed.
	ATM.SPECIAL.DBnnnnn	nnnnn is the database id of the database for which fixes are to be displayed.

The following table shows the online administration functions for which UPDATE access to the indicated resource is required:

Function	Resource Name	Notes
System Settings	ATM.SETTINGS	Change system settings.
Client Runtime controls	ATM.CLIENT.type.name	Add, modify, purge or rename a runtime control (or one of its overrides, or its site info). type is the job type and name is the name, without *s (so *DEFAULT is checked against DEFAULT). Valid types are: BATCH COMPLETE CICS-DTR CICS IMS UTM TSO CMS TIAM MULTITCB SINGLTCB MISCDTR SPATS

Activating security protection of online administration for Vista

Once you have a running daemon security service (see [Activating the security service in the System Coordinator daemon](#)), logon to the Vista online administration library SYSAVI and use option 2 of System Settings (see System Settings in *Adabas SAF Security Online Services* which also applies to other online administration libraries) to activate Vista online administration protection. These settings are stored in the configuration file assigned to LFILE 152. Therefore you can use different LFILES to vary your security behaviors. You **must** ensure the ability to change LFILE 152 (in the Natural parameter module or in Natural dynamic parameters, etc) is restricted to authorized people only!

The following table shows the online administration functions for which READ access to the indicated resource is required:

Function	Resource Name	Notes
System Settings	AVI.SETTINGS	Display system settings.
File Partitioning	AVI.PARTFILE.DBnnnnnn.FNRfffff	Display, copy or expand a partitioned file and its partitions. <i>nnnnnn</i> is the source database id. <i>fffff</i> is the source file number.
File Translation	AVI.PAGE.name	Display, copy or expand a page and its translation rules. name is the page name.
Client Runtime controls	AVI.CLIENT.type.name	Display, expand, list overrides, copy, display site info for a runtime control. type is the job type and

Function	Resource Name	Notes
		name is the name, without *s (so *DEFAULT is checked against DEFAULT). Valid types are: BATCH COMPLETE CICS-DTR CICS IMS UTM TSO CMS TIAM MULTITCB SINGLTCB MISCDTR SPATS
Current Activity Displays	AVI.ACTIVITY.jobname	jobname is the name of the current job.
Special Services (Fix Display)	AVI.SPECIAL.jobname	jobname is the name of the client job for which fixes are to be displayed.
	AVI.SPECIAL.DMNnnnnn	nnnnn is the node number of the daemon for which fixes are to be displayed.
	AVI.SPECIAL.DBnnnnn	nnnnn is the database id of the database for which fixes are to be displayed.
Avilook	AVI.ACTIVITY.DBnnnnn	nnnnn is the id of the target database.

The following table shows the online administration functions for which UPDATE access to the indicated resource is required:

Function	Resource Name	Notes
System Settings	AVI.SETTINGS	Change system settings.
File Partitioning	AVI.PARTFILE.DBnnnnn.FNRfffff	Add, modify or purge a partitioned file and its partitions. nnnnn is the source database id. fffff is the source file number.
File Translation	AVI.PAGE.name	Add, modify or purge a page and its translation rules. name is the page name.
Client Runtime controls	AVI.CLIENT.type.name	Add, modify, purge or rename a runtime control (or one of its overrides, or its site info). type is the job type and name is the name, without *s (so *DEFAULT is checked against DEFAULT). Valid types are: BATCH COMPLETE CICS-DTR

Function	Resource Name	Notes
		CICS IMS UTM TSO CMS TIAM MULTITCB SINGLTCB MISCDTR SPATS

Activating security protection of online administration for System Coordinator

Once you have a running daemon security service (see [Activating the security service in the System Coordinator daemon](#)), logon to the System Coordinator online administration library SYSCOR and use option 2 of System Settings (see System Settings in *Adabas SAF Security Online Services* which also applies to other online administration libraries) to activate System Coordinator online administration protection. These settings are stored in the configuration file assigned to LFILE 152. Therefore you can use different LFILEs to vary your security behaviors. You **must** ensure the ability to change LFILE 152 (in the Natural parameter module or in Natural dynamic parameters, etc) is restricted to authorized people only!

The following table shows the online administration functions for which READ access to the indicated resource is required:

Function	Resource Name	Notes
System Settings	COR.SETTINGS	Display system settings.
Client Runtime controls	COR.CLIENT.type.name	Display, expand, list overrides, copy, display site info for a runtime control. type is the job type and name is the name, without *s (so *DEFAULT is checked against DEFAULT). Valid types are: BATCH COMPLETE CICS-DTR CICS IMS UTM TSO CMS TIAM MULTITCB SINGLTCB MISCDTR SPATS

Function	Resource Name	Notes
Daemon Group Parameters	COR.GROUP.name	Display, copy or expand a group. name is the name of the group.
Current Activity Displays Adabas Client Job Information	COR.ACTIVITY.jobname	Informational functions. jobname is the name of the selected job.
Current Activity Displays Network Discovery	COR.ACTIVITY.DMNnnnnn	Informational functions. nnnnn is the node-id of the selected daemon.
Special Services (Fix Display)	COR.SPECIAL.jobname	jobname is the name of the client job for which fixes are to be displayed.
	COR.SPECIAL.DMNnnnnn	nnnnn is the node number of the daemon for which fixes are to be displayed.
	COR.SPECIAL.DBnnnnn	nnnnn is the database id of the database for which fixes are to be displayed.

The following table shows the online administration functions for which UPDATE access to the indicated resource is required:

Function	Resource Name	Notes
System Settings	COR.SETTINGS	Change system settings.
Client Runtime controls	COR.CLIENT.type.name	Add, modify, purge or rename a runtime control (or one of its overrides, or its site info). type is the job type and name is the name, without *s (so *DEFAULT is checked against DEFAULT). Valid types are: BATCH COMPLETE CICS-DTR CICS IMS UTM TSO CMS TIAM MULTITCB SINGLTCB MISCDTR SPATS
Daemon Group Parameters	COR.GROUP.name	Display, copy or expand a group. name is the name of the group.
Current Activity Displays Adabas Client Job Information	COR.ACTIVITY.jobname	Operational functions. jobname is the name of the selected job.

Function	Resource Name	Notes
Current Activity Displays Network Discovery	COR.ACTIVITY.DMN $nnnnn$	Operational functions. $nnnnn$ is the node-id of the selected daemon

Operator commands for the security service in the System Coordinator daemon

Use the z/OS Modify (F) command. All operator commands must be prefixed with *AAF*. For example:

```
F CORDAEMN,AAF SSTAT
```

You may use the same ADASAF operator commands for the daemon service as for a database (see [ADASAF Operator Commands](#)).



Note: There are no security checks for ADASAF daemon operator commands.

