

# Maintaining Databases

The AOS Database Maintenance function controls Adabas database (ASSO/DATA) file and space allocation. You can:

- add data sets, increase or decrease the size of the last data set;
- uncouple Adabas files;
- display or reset entries in the data integrity block (DIB); and
- recover space previously allocated but not used by Adabas utilities that ended abnormally.

Database maintenance tasks can be performed from the **Database Maintenance** menu:

```

14:14:09          ***** A D A B A S  BASIC  SERVICES *****          2009-08-21
                   - Database Maintenance -                               PDM0002

                   Code      Service
                   ----      -
                   A        Add new dataset to ASSO/DATA
                   I        Increase/decrease ASSO/DATA
                   R        List/reset DIB block entries
                   S        Recover unused space
                   U        Uncouple two ADABAS files
                   ?        Help
                   .        Exit
                   ----      -

Code ..... _
File No. .... 29
Coupled File .. 0
Database ID ... 1955 (WIS1955)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help      Exit      Menu

```

Database maintenance includes the following functions:

Option	Function
A	<i>Adding a New Associator or Data Storage Extent</i> allows you to add a preformatted data set to the Associator or Data Storage.
I	<i>Increasing or Decreasing Associator or Data Storage Data Set Size</i> allows you to change the size of an existing Associator or Data Storage data set.
R	<i>Displaying and Resetting DIB Block Entries</i> allows you to display and reset the data integrity block (DIB) entries for each Adabas utility currently operating.
S	<i>Recovering Unused Space</i> allows you to recover unused space from utility operations that ended abnormally.
U	<i>Uncoupling Adabas Files</i> allows you to remove the physical coupling between files.

## Adding a New Associator or Data Storage Extent

Option A (Add new dataset to ASSO/DATA) on the **Database Maintenance** menu is used to add a preformatted data set to the Associator or Data Storage. Before using this option, the data set to be added must be formatted using the ADAFRM utility.

Option A should be used only if the new data set is located on a different physical device.

This function corresponds to the utility function ADADBS ADD.

The equivalent direct commands are:

ADD ASSO

ADD DATA

The Add Dataset screen appears.

```

12:51:53          ***** A D A B A S  BASIC  SERVICES *****          2009-08-24
DBID 1955          -  Add Dataset  -          PDMA002

Enter Parameters to Add either a DATA OR ASSO dataset:

          ASSO Device ..... _____
          ASSO Size ..... _____

          DATA Device ..... _____
          DATA Size ..... _____

          Blocks/Cylinders .. B

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu

```

## Increasing or Decreasing Associator or Data Storage Data Set Size

Option **I** (Increase/decrease ASSO/DATA) on the **Database Maintenance** menu is used to change the size of an existing data set for the specified component. If the component has more than one data set, option **I** changes the size of the last data set.

Since this option only changes the Adabas general control block entry, you must also ensure that the needed space is physically allocated and formatted when the data set is being increased.

When the Data Storage component has been increased four times, an ADAORD REORASSO utility function must be executed to reorder the DSST extents in the Associator component.

This function corresponds to the utility functions ADADBS INCREASE and ADADBS DECREASE.

The equivalent direct commands are:

```
INCREASE ASSO
```

```
INCREASE DATA
```

```
DECREASE ASSO
```

DECREASE DATA

The Increase/Decrease screen appears.

```

12:58:53          ***** A D A B A S  BASIC  SERVICES *****          2009-08-24
DBID 1955          - Increase/Decrease -          PDMI002

Enter Parameters :          Possible values:

          Increase/Decrease .. _          (I/D)
          ASSO/DATA .. _          (A/D)
          Size .. _____
Blocks or Cylinders .. B          (B/C)

Note: After an INCREASE operation is completed, the nucleus session will
       be automatically ended to allow for the necessary Associator or Data
       Storage formatting.

PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help          Exit          Menu

```

## Displaying and Resetting DIB Block Entries

The data integrity block (DIB) comprises entries for each Adabas utility currently operating, describing the resources each utility is using.

Option **R** (List/reset DIB block entries) on the **Database Maintenance** menu allows you to list and remove any unwanted entries from the DIB.

This function corresponds to the utility function ADADBS RESETDIB. It can also be accomplished using the operator command DDIB.

The equivalent direct commands are:

DISPLAY DIB

RESET DIB

## Recovering Unused Space

Space allocated for utility operations that ended abnormally remains unavailable unless it is intentionally recovered.

Option **S** (Recover unused space) on the **Database Maintenance** menu is used to purposely reclaim such space for use. A message is returned indicating that the space has been successfully recovered.

This function corresponds to the utility function ADADBS RECOVER.

The equivalent direct command is:

```
RECOVER SPACE
```

## Uncoupling Adabas Files

Option **U** (Uncouple two ADABAS files ) on the **Database Maintenance** menu is used to remove the physical coupling between the specified files by erasing the coupling inverted lists from each file's Associator. No change is made to the field definition tables (FDTs) or descriptors for the specified files.

This option must be executed before either of the specified files is deleted.

To determine if a file is physically coupled, check the **C** (coupling) indicator in the Database Report option's Display File screen. Using the same function for those selected files, you can see the specific coupling information; that is, the specific fields in one file and their coupling to fields in other files.

This function corresponds to the utility function ADADBS UNCOUPLE.

The equivalent direct command is

```
UNCOUPLE FILES file1 file2
```