

# ADASIPnn (Adabas VSE/ESA SVC) System Messages

## Overview of Messages

ADASIP00	ADASIP01	ADASIP02	ADASIP03	ADASIP04	ADASIP05
ADASIP06	ADASIP07	ADASIP08	ADASIP09	ADASIP10	ADASIP11
ADASIP12	ADASIP13	ADASIP14	ADASIP15	ADASIP17	ADASIP18
ADASIP19	ADASIP20	ADASIP21	ADASIP22	ADASIP23	ADASIP24
ADASIP27	ADASIP28	ADASIP29	ADASIP30	ADASIP31	ADASIP32
ADASIP33	ADASIP34	ADASIP36	ADASIP40	ADASIP41	ADASIP50
ADASIP60	ADASIP61	ADASIP62	ADASIP63	ADASIP64	ADASIP65
ADASIP66	ADASIP67	ADASIP68	ADASIP69	ADASIP70	ADASIP71
ADASIP72	ADASIP73	ADASIP74	ADASIP75	ADASIP76	ADASIP77
ADASIP78					

**ADASIP00** ADABAS V<sub>v</sub> VSE SIP STARTED SIP IS RUNNING UNDER VSE sys-type - mode

**ADASIP00** ( yy yy - mm - dd. SM=sm-level , ZAP=zap-level)

**ADASIP00** SIP IS RUNNING UNDER OSYS LEVEL Vnnn

**ADASIP00** SIP IS LOADING ADABAS SVC LEVEL Vnnn

**ADASIP00** ADASIP IS LOADING ADABAS SVC AMODE=a-mode

**Explanation:** The ADASIP program has started. "sys-type" is the operating system type, and "mode" is the ECPS (EMODE), VM, or 370 operating mode.

v	version of Adabas
sys-type	VSE operating system type
mode	ECPS (EMODE), VM, or S/370 operating mode
yyyy-mm-dd	date of module assembly
sm-level	system maintenance (SM) level of the module
zap-level	ZAP level of the module
Vnnn	version/release/modification level resulting from an IBM SUBSYD macro
a-mode	the AMODE setting of the Adabas SVC

**ADASIP01      SUBSID MACRO ERROR**

**Explanation:** ADASIP received a nonzero return code from the operating system.

**User Action:** The VSE operating system release level is too low for installing Adabas. Refer to the Adabas Installation documentation for the minimum allowed VSE levels.

**ADASIP02      UNSUPPORTED VSE RELEASE BASED UPON SUBSID**

**Explanation:** An ADASIP validation check indicates an unsupported operating system level.

**User Action:** The VSE operating system release level is too low for installing Adabas. Refer to the Adabas Installation documentation for the minimum allowed VSE levels.

**ADASIP03      NO SYSPARM VALUE SPECIFIED FOR SVC**

**Explanation:** ADASIP could not find a SYSPARM input, and a ZAP has not be applied to the specified SVC.

**User Action:** Either provide the SVC with SYSPARM or apply a ZAP to the specified SVC with ADASIP.

**ADASIP04      DEFAULT VALUE USED FOR THE SVC**

**Explanation:** No SYSPARM SVC has been used. ADASIP defaults to using the SVC that has a ZAP applied.

**ADASIP05      NON-NUMERIC DATA FOUND IN SYSPARM FIELD**

**Explanation:** Either SYSPARM or the default ADASIP SVC contains a nonnumeric value.

**User Action:** Correct the specified SYSPARM value, or set the default SVC value to 30.

**ADASIP06      INVALID RANGE SPECIFIED FOR THE SVC 31-120**

**Explanation:** ADASIP found an SVC outside the allowed range in SYSPARM or the ADASIP default SVC.

**User Action:** Set the SVC to an unused SVC value within the allowed range. SVC ranges and recommended values are described in the Adabas Installation documentation .

**ADASIP07 SVC SPECIFIED NOT WITH VALID RANGE - NO UPSI**

**Explanation:** The value specified for the SVC in the VSE SYSPARM with the UPSI option was incorrect.

**User Action:** Correct the UPSI or SVC value, as appropriate. SVC ranges and recommended values are described in the Adabas Installation documentation .

**ADASIP08 ADASVCvv WAS NOT FOUND IN THE SVA**

**Explanation:** While performing a VSE load, ADASIP found that the specified level ADASVC was not in the SVA.

**User Action:** Issue the SET SDL for ADASVCvv. It may be necessary to relink the Adabas SVC with SVA using the PHASE statement if the Adabas SVC is not found in the Adabas library.

**ADASIP09 NO MATCH ON ID - INCORRECT ADASVC LOADED**

**Explanation:** ADASIP found an incorrect SVC version while attempting a load operation.

**User Action:** Relink ADASVCvv with the correct SVC module.

**ADASIP10 NO KEYWORD SPECIFIED FOR NRIDTES**

**Explanation:** ADASIP found an incorrect NRIDTES keyword.

**User Action:** Respecify the keyword parameter as NRIDTES=nn , where "nn" specifies the number of databases to be supported in the ID table.

**ADASIP11 NON-NUMERIC DATA SPECIFIED FOR NRIDTES**

**Explanation:** The ADASIP NRIDTES= keyword parameter specified non-numeric data.

**User Action:** Correct the NRIDTES= data, then resubmit ADASIP.

**ADASIP12 NO OVERRIDING NRIDTES SPECIFIED**

**Explanation:** The default NRIDTES was used. No error has occurred.

**ADASIP13 SVC TABLE ENTRY WAS FOUND TO BE INVALID**

**Explanation:** The SVC number provided by SYSPARM is either not valid, or does not represent either the old or new version of the VSE Adabas SVC. This error can occur if the UPSI statement's "C" parameter specified "0".

**User Action:** Respecify the UPSI statement, or specify another unused SVC value. Rerun ADASIP.

**ADASIP14 GETVIS FAILURE FOR IDT IN SVA**

**Explanation:** The GETVIS of the IDT passed a nonzero return code back to ADASIP, meaning the GETVIS size was insufficient.

**User Action:** Increase the SVA GETVIS size, re-IPL the operating system, and rerun ADASIP.

**ADASIP15 ROUTER UNABLE TO INITIALIZE IDT**

**Explanation:** ADASIP received a nonzero return code from the 56 call to the SVC.

**User Action:** Contact your Software AG technical support representative.

**ADASIP17 INCORRECT SVC SUFFIX AFTER COMMA IN SYSPARM**

**Explanation:** An attempt was made to run this program more than once for the current IPL. A second IDT for the program is not required.

**User Action:** Correct the SYSPARM specification for the two-byte SVC suffix, and rerun the job.

**ADASIP18 NON-NUMERIC DATA SPECIFIED FOR DMPDBID**

**Explanation:** The ADASIP DMPDBID keyword parameter contains nonnumeric data.

**User Action:** Correct the DMPDBID specification, and rerun the job.

**ADASIP19 DBID CANNOT BE FOUND IN IDTE**

**Explanation:** The ADASIP program could not find an entry for the DMPDBID database in the IDT area.

**User Action:** Either correct the DMPDBID specification or start the specified database, then run ADASIP to perform a "snap" dump of the command queue.

**ADASIP20 THE IDT AND SVC HAVE BEEN DUMPED TO SYSLST**

**Explanation:** A request to ADASIP to dump the IDT and then SVC via UPSI 80. No error has occurred.

**ADASIP21 NO IDT TABLE WAS FOUND FOR SPECIFIED SVC**

**Explanation:** ADASIP found that the SVC has no address for the IDT.

**User Action:** Specify the correct SVC, or initialize with ADASIP first.

**ADASIP22 THE SVC HAS ALREADY BEEN INSTALLED**

**Explanation:** ADASIP found that the same program is being run again.

**User Action:** The SVC is not installed and no IDT table is needed. To reinstall the same SVC, you must first perform a SET SDL.

**ADASIP23 THE SVC TABLE CANNOT BE LISTED UNDER DOS/MVT**

**Explanation:** The option to display the SVC table is specified under VSE.

**ADASIP24 THE IDT HAS BEEN PAGEFIXED BY USER OPTION**

**Explanation:** UPSI (X'20') was selected to pagefix the IDT in the system GETVIS area.

**ADASIP27 ADASVC IS RMODE=ANY**

**Explanation:** ADASIP detected that the Adabas SVC is linked RMODE=ANY.

**User Action:** Relink the Adabas SVC RMODE=24.

**ADASIP28 ADASIP IS AMODE=31**

**Explanation:** ADASIP detected that it is AMODE=31.

**User Action:** Relink ADASIP AMODE=24.

**ADASIP29 PRODID MACRO FAILURE**

**Explanation:** ADASIP received a nonzero response code from the PRODID DEFINE macro.

**User Action:** Investigate the cause of the error. Correct it and rerun the job.

**ADASIP30 ADASVCvv svc INSTALLED**

**Explanation:** ADASIP has installed SVC number "svc" successfully.

**ADASIP31 address=SVC ADDRESS**

**Explanation:** The SVC has been loaded at the indicated address.

**ADASIP32 address=IDT ADDRESS**

**Explanation:** The ID table has been allocated at the indicated address.

**ADASIP33 address=ALET TABLE ADDRESS**

**Explanation:** The ALET table has been loaded at the indicated address.

**ADASIP34 count=MAXIMUM USER/TARGET COMBINATIONS**

**Explanation:** Total number of client/server combinations within the VSE system.

**ADASIP36 address=EXTENDED IIBS ADDRESS**

**Explanation:** The extended IIBs have been loaded at the indicated address.

**ADASIP40 VSE SVC svc IS status AM=a-mode RM=r-mode AR=reg-mode  
SVCT=svc-tab-addr MODT=svc-mod-addr**

**Explanation:** This message occurs when the option to list the SVC table is selected, and specifies the following values:

svc	the VSE SVC number
status	"USED" or "UNUSED"
a-mode	AMODE of this SVC, if used (24 or ANY)
r-mode	RMODE of this SVC, if used (24 or ANY)
reg-mode	access register mode of this SVC, if used (Y=yes, N=no)
svc-tab-addr	address of the SVC table entry for this SVC
svc-mod-addr	address of the SVC mode table entry for this SVC, if present

**User Action:** None required. This message is for your information only. Do not use SVC50, even though it is indicated as "unused".

**ADASIP41 VSE SVC TABLE AUDIT COMPLETED**

**Explanation:** ADASIP has completed listing the VSE SVC table.

**ADASIP50 THE COMMAND QUEUE HAS BEEN DUMPED TO SYSLST**

**Explanation:** ADASIP has completed listing the command queue for the specified database.

**ADASIP60 ONLY 1 CPU CAN BE ACTIVE DURING ADASIP**

**Action:** Use "SYSDEF TD,STOP=ALL" to stop all but one CPU so that ADASIP can run. Then restart your CPUs again.

**ADASIP61 RERUN ADASIP AFTER USING TDSERV TO STOP CPUS**

**Explanation:** Occurs in conjunction with ADASIP60.

**ADASIP62 GETVIS FAILED FOR ADASTUB MODULE**

**Explanation:** Not enough SVA storage to load ADASTUB.

**Action:** Consult with your system programmer.

**ADASIP63 ADASTUB MODULE LOADED AT address**

**Explanation:** Information message indicating module load address.

**ADASIP64 NO MATCH ON ID - INCORRECT ADASTUB LOADED**

**Explanation:** ADASTUB phase is incorrect.

**Action:** Consult with your system programmer, or contact Software AG.

**ADASIP65 ADASTUB SVC TABLE NOT FOUND**

**Explanation:** ADASTUB phase is incorrect.

**Action:** Consult with your system programmer, or contact Software AG.

**ADASIP66    ADASTUB SVC TABLE IS FULL**

**Explanation:** You have more than 10 SVCs active on this VSE machine.

**Action:** Contact Software AG for information about increasing the table size.

**ADASIP67    PAGEFIX FOR ADASIP FAILED**

**Action:** Increase the SETPFIX value and rerun.

**ADASIP68    PAGEFREE FOR ADASIP FAILED**

**Action:** Consult with your system programmer.

**ADASIP69    TURBO DISPATCHER STUB A C T I V E**

**Explanation:** Adabas Turbo support is now active on this VSE machine.

**ADASIP70    VSE SUPERVISOR HOOK INSTALL FAILED**

**Explanation:** Either this version of the VSE/ESA 2 supervisor is not supported, or the vendor installation logic for the first-level interrupt handler is incorrect.

**Action:** Call Software AG; have message ADASIP72 available.

**ADASIP71    LOAD OF MODULE ADASTUB FAILED**

**Explanation:** The ADASTUB module was not found in the LIBDEF SEARCH chain.

**ADASIP72    CODE IS : xxx**

**Explanation:** Occurs after message ADASIP70.

**ADASIP73    ADANCHOR INCORRECT OR NOT FOUND IN SVA**

**Explanation:** The ADANCHOR module was not found in the SVA; no SET SDL has been done.

**ADASIP74    INFO : STUB ACTIVATED BY PREVIOUS ADASIP**

**Explanation:** Adabas Turbo STUB has been installed by a previous ADASIP.



**ADASIP75      ADANCHOR AND ADASTUB NOT DUMPED - NOT ACTIVE**

**Explanation:** When attempting to dump Adabas control blocks with ADASIP, the modules were not dumped because Adabas Turbo support is not active.

**ADASIP76      ADABAS TURBO STUB NOT ACTIVATED DUE TO ERROR**

**Explanation:** An error occurred during the installation of the Adabas Turbo stub.

**ADASIP77      THIS ADABAS SVC WILL RUN IN NON-TURBO MODE**

**Explanation:** An error occurred during the installation of the Adabas Turbo stub. This SVC will run in non-Turbo mode from now on.

**ADASIP78      VSE TURBO DISPATCHER VERSION nn**

**Explanation:** Version of VSE/ESA version 2 Turbo Dispatcher. 00 indicates TD level of pre-version 4.