

# Appendix B - z/VSE Dataset Usage

The following table provides a complete list of all the z/VSE input and output files used by the ADL batch monitor, DAZIFP and the ADL utilities.

The following table provides a complete list of all the z/VSE input and output files used by the ADL Interfaces.

DTF	Logical Unit	BLKSIZE	LRECL	RECFM	DSORG	Storage Medium
DAZIN1	SYSIPT		80	F	PS	READER
DAZIN2	SYSIPT		80	F	PS	READER
DAZOUT1	SYSLST		132	F	PS	PRINTER
DAZOUT2	SYS011		132	F	PS	PRINTER *
DAZIN3D	SYS013	8196	8192	VB	PS	DISK **
DAZIN3T	SYS013	8196	8192	VB	PS	TAPE **
DAZOT3D	SYS013	8196	8192	VB	PS	DISK **
DAZOT3T	SYS013	8196	8192	VB	PS	TAPE **
DAZIN4D	SYS012	8196	8192	VB	PS	DISK ***
DAZIN4T	SYS012	8196	8192	VB	PS	TAPE ***
DAZIN5D	SYS014	1320	132	FB	PS	DISK ****
DAZIN5T	SYS014	1320	132	FB	PS	TAPE ****
DAZOT5D	SYS012	8196	8192	VB	PS	DISK ***
DAZOT5T	SYS012	8196	8192	VB	PS	TAPE ***
DAZOUT4	SYSxxx		80	F	PS	DISK *****

\* This printer output may be routed to a second logical printer, if one is available, by specifying PR=2 in the ADL parameter module or as a dynamic parameter. If no second logical printer is available, the printer output is written to a temporary file using DAZOT3D as output and DAZIN3D as input, and printed on SYSLST at the end of the job.

\*\* The logical unit and block size may be modified by specifying SQ=(logical unit,block size) in the ADL parameter module or as a dynamic parameter. The values given in the table are the default values.

\*\*\* The logical unit and block size may be modified by specifying TRACE=( , , , , ,logical unit,block size) in the ADL parameter module or as a dynamic parameter. The values given in the table are the default values.

\*\*\*\* The logical unit and block size may be modified by specifying FX=(logical unit, blocksize) in the ADL parameter module or as a dynamic parameter. The values given in the table are the default values.

\*\*\*\*\* The logical unit must be assigned using an EXTENT statement.