

Adabas Online System

Database Maintenance

Version 7.4.4

September 2009

This document applies to Adabas Online System Version 7.4.4 and to all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © Software AG 2009. All rights reserved.

The name Software AG, webMethods and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA, Inc. Other company and product names mentioned herein may be trademarks of their respective owners.

Table of Contents

1 Database Maintenance	1
2 Add a New Extent to the Associator or Data Storage	3
3 Increase or Decrease the Size of an Associator or Data Storage Dataset	5
4 Display and Reset DIB Block Entries	7
5 Recover Unused Space	9
6 Uncouple Adabas Files	11
Index	13

1 Database Maintenance

The Database Maintenance function controls Adabas database (ASSO/DATA) file and space allocation: you can

- add datasets, increase or decrease the last dataset;
- uncouple Adabas files;
- display or reset entries in the data integrity block (DIB); and
- recover space previously allocated but not used by Adabas utilities that ended abnormally.






```
18:22:47          ***** A D A B A S  BASIC SERVICES *****          2005-11-22
                  - Database Maintenance -                               PDM0002

                  Code      Service
                  ----      -
                  A        Add new dataset to ASSO/DATA
                  I        Increase/decrease ASSO/DATA
                  R        List/reset DIB block entries
                  S        Recover unused space
                  U        Uncouple two Adabas files
                  ?        Help
                  .        Exit
                  ----      -

Code ..... _
File No. .... 0
Coupled File .. 0
Database ID ... 105      (RD-105)

Command ==>
PF1----- PF2----- PF3----- PF4----- PF6----- PF7----- PF8----- PF12-----
Help              Exit                               Menu
```

The Adabas Online System Database Maintenance documentation is organized in the following topics:

	Add a New Extent to the Associator or Data Storage
	Increase or Decrease the Size of an Associator or Data Storage Dataset
	Display and Reset DIB Block Entries
	Recover Unused Space
	Uncouple Adabas Files

2 Add a New Extent to the Associator or Data Storage

Option "A" is used to add a preformatted dataset to the Associator or Data Storage. Before using this option, the dataset to be added must be formatted using the ADAFRM utility.

Option "A" should be used only if the new dataset is located on a different physical device. The Associator and Data Storage can each have as many as five datasets.

```
09:34:21      ***** A D A B A S  BASIC  SERVICES  *****      2005-11-22
DBID 105              -  Add Dataset  -              PDMA002

Enter Parameters to Add either a DATA OR ASSO dataset:

      ASSO Device ..... ____
      ASSO Size ..... _____

      DATA Device ..... ____
      DATA Size ..... _____

      Blocks/Cylinders .. B
```

This function corresponds to the utility function ADADBS ADD.

The equivalent direct commands are

```
ADD ASSO
```

```
ADD DATA
```

3 Increase or Decrease the Size of an Associator or Data

Storage Dataset

Option "I" is used to change the size of an existing dataset for the specified component. If the component has more than one dataset, option "I" changes the size of the last dataset.

Since this option only changes the Adabas general control block entry, you must also ensure that the needed space is physically allocated and formatted when the dataset is being increased.

When the Data Storage component has been increased four times, an ADAORD REORASSO utility function must be executed to reorder the DSST extents in the Associator component.

```
09:35:31      ***** A D A B A S  BASIC SERVICES *****      2005-11-22
DBID 105              - Increase/Decrease -              PDMI002

Enter Parameters :                               Possible values:

          Increase/Decrease .. _                (I/D)
                ASSO/DATA .. _                (A/D)
                  Size .. _____
        Blocks or Cylinders .. B                (B/C)
```

This function corresponds to the utility functions ADADBS INCREASE and ADADBS DECREASE.

The equivalent direct commands are

```
INCREASE ASSO
```

```
INCREASE DATA
```

```
DECREASE ASSO
```

```
DECREASE DATA
```

4 Display and Reset DIB Block Entries

The data integrity block (DIB) comprises entries for each Adabas utility currently operating, describing the resources each utility is using.

Option "R" allows you to list and remove any unwanted entries from the DIB.

This function corresponds to the utility function ADADBS RESETDIB. It can also be accomplished using the operator command DDIB.

The equivalent direct commands are

```
DISPLAY DIB
```

```
RESET DIB
```


5 Recover Unused Space

Space allocated for utility operations that ended abnormally remains unavailable unless it is intentionally recovered.

Option "S" is used to purposely reclaim such space for use. A message is returned indicating that the space has been successfully recovered.

This function corresponds to the utility function ADADBS RECOVER.

The equivalent direct command is

```
RECOVER SPACE
```


6 Uncouple Adabas Files

Option "U" is used to remove the physical coupling between the specified files by erasing the coupling inverted lists from each file's Associator. No change is made to the field definition tables (FDTs) or descriptors for the specified files.

This option must be executed before either of the specified files is deleted.

To determine if a file is physically coupled, check the "C" (coupling) indicator in the Database Report option's "Display File" function (described in the next section). Using the same function for those selected files, you can see the specific coupling information; that is, the specific fields in one file and their coupling to fields in other files.

This function corresponds to the utility function ADADBS UNCOUPLE.

The equivalent direct command is

```
UNCOUPLE FILES file1 file2
```


Index

D

- Data Integrity Block
 - reset entries in
 - using Basic Services, 7
- Database
 - maintenance function
 - using Basic Services, 1
- Datasets
 - resize
 - using Basic Services, 5

E

- Extents
 - add
 - using Basic Services, 3

F

- File coupling
 - uncouple
 - using Basic Services, 11

S

- Space
 - recover
 - using Basic Services, 9

