

ADARUN Control Statements

This section covers the following topics:

- ADARUN Function
 - ADARUN Statement Format
 - Setting ADARUN Parameters
 - Statement Example
 - ADARUN Parameter Summary
-

ADARUN Function

The ADARUN function is used to invoke Entire Net-Work. ADARUN invokes the Entire Net-Work control program and:

- loads the module ADAIOR, which performs all operating system-dependent functions;
- reads and interprets all ADARUN parameter statements;
- loads the modules needed to execute the functions specified by the ADARUN parameters;
- performs any necessary modifications to those load modules, based on the specified parameters;
- passes control to Entire Net-Work.

The ADARUN statement is fully described in the Operations documentation of Adabas.

ADARUN Statement Format

The syntax of ADARUN statement and parameters is:

```
ADARUN parameter = value,...
```

ADARUN statements must:

- Contain the word "ADARUN" in positions 1-6, followed by "parameter=value" strings of one or more entries;
- Have one or more blanks, beginning in position 7, between "ADARUN" and the first "parameter=value"; and
- Not extend beyond position 72 of a line.

ADARUN control statements may contain multiple statement lines. Each line must be specified as a separate statement according to the rules above.

The ADARUN statement is fully described in the Operations documentation of Adabas.

Setting ADARUN Parameters

When specifying ADARUN parameters:

- Ensure that the correct program to be executed is specified (see the PROGRAM parameter);
- Ensure that the correct target ID is specified (see the TARGETID parameter); and
- Determine which settings for the following parameters are applicable for the session:
 - FORCE (overwrite active target ID)
 - SVC (Adabas SVC number)

Each ADARUN parameter has a default value that ADARUN uses if the parameter is not explicitly specified. Parameters can be abbreviated, but the abbreviation must be unique; that is, not the same as those of other ADARUN parameters.

The Entire Net-Work session statistics can be used to determine the best settings for each parameter. The statistics can be displayed using Entire Net-Work operator commands during the session; they are also printed automatically at the end of a session.

Statement Example

The following is an example of an Entire Net-Work ADARUN statement:

```
ADARUN  PROG=NETWRK , TARGETID=3333 , NAB=20 , NC=50 , LU=65535 , SVC=251
```

For this node, Entire Net-Work:

- runs with a target ID of 3333;
- allocates an attached buffer pool for 20 interregion communication buffers;
- processes as many as 50 requests simultaneously;
- uses the SVC 251; and
- ensures adequate buffer size for Adabas compatibility by setting the value of the LU parameter to 65535. For more information about the LU parameter, read about it in the Adabas Operations documentation.

ADARUN Parameter Summary

The following table summarizes some useful Entire Net-Work ADARUN parameters for Entire Net-Work. Details for each parameter can be found in the Adabas Operations documentation.

**Warning:**

If recommended numeric values are supplied in this table, do not specify smaller values; if recommended non-numeric values are supplied in this table, do not specify other values.

Parameter	Specifies	Minimum	Maximum	Recommended	Default
CT	The maximum number of seconds that can elapse from the time an Adabas command has been completed until the results are returned to the user through the interregion communication (operating-system-dependent).	1	16777215	---	60
FORCE	Whether the nucleus can overwrite an existing ID table entry.	---	---	---	NO
LU	The size of the intermediate user buffer area. If data is sent through Entire Net-Work from one or more Adabas nuclei to an Event Replicator Server, the Entire Net-Work LU parameter must be greater than or equal to 164,000.	none	none	---	65535
NAB	The number of attached buffers to be used. If data is sent through Entire Net-Work from one or more Adabas nuclei to an Event Replicator Server, the Entire Net-Work NAB parameter must also be set to a value greater than or equal to: $41 * 10 * \text{nuclei-count}$ For example, if one Adabas nucleus will be sending data to the Event Replicator Server, set the NAB parameter greater than or equal to 410 (for example NAB=420).	1	varies, depending on the amount of available virtual storage	---	16
NC	The maximum number of command queue elements.	20	32767	---	200
PROGRAM	The program to be run.	NETWRK	NETWRK	NETWRK	(none)
SVC	The Adabas SVC number to be used for the session.	---	---	---	249

Parameter	Specifies	Minimum	Maximum	Recommended	Default
TARGETID (see note below)	Entire Net-Work target ID.	1	65535	---	1

Note:

The TARGETID parameter is an optional ADARUN parameter that specifies the unique Entire Net-Work target ID of this node. It is synonymous with the Adabas DBID parameter. All target IDs used by Entire Net-Work, Adabas (database IDs), Adabas TPF, Natural global bufferpools, etc., must be unique throughout all Entire Net-Work nodes. In particular, the Entire Net-Work target ID must not coincide with any database ID used in the network, with the exception of isolated databases that are defined for local availability only and are therefore unknown to Entire Net-Work.