

**Adabas**

**Software AG Mainframe Product Licensing**

Version 8.2.3

May 2011

This document applies to Adabas Version 8.2.3.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 1971-2011 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, United States of America, and/or their licensors.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at <http://documentation.softwareag.com/legal/>.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at <http://documentation.softwareag.com/legal/> and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices and license terms, please refer to "License Texts, Copyright Notices and Disclaimers of Third-Party Products". This document is part of the product documentation, located at <http://documentation.softwareag.com/legal/> and/or in the root installation directory of the licensed product(s).

## Table of Contents

1 Software AG Mainframe Product Licensing .....	1
Distributed License Check Software .....	2
License File .....	3
Copying a License File from Tape to Disk .....	4
Transferring a License File from PC to a z/OS Host Using FTP .....	4
Transferring a License File from PC to a z/VSE Host Using FTP .....	5
Transferring a License File from PC to a BS2000/OSD Host Using FTP .....	6
Product License Check FAQs .....	7
Using the License Utility: LICUTIL .....	11

---

# 1 Software AG Mainframe Product Licensing

---

▪ Distributed License Check Software .....	2
▪ License File .....	3
▪ Copying a License File from Tape to Disk .....	4
▪ Transferring a License File from PC to a z/OS Host Using FTP .....	4
▪ Transferring a License File from PC to a z/VSE Host Using FTP .....	5
▪ Transferring a License File from PC to a BS2000/OSD Host Using FTP .....	6
▪ Product License Check FAQs .....	7
▪ Using the License Utility: LICUTIL .....	11

This document describes Software AG's mainframe product licensing procedures, license check software and license file.

**Notations Used in this Document:**

- *vrs, vr* or *v.r.s*:  
When used in this document, the notation *vrs, vr* or *v.r.s* represents the three-digit or two-digit version number of the Software AG product.
- *ppp*:  
When used in this document, the notation *ppp* represents the three-character product code of the Software AG product: ADA for Adabas, NAT for Natural, EXX for EntireX, COM for Complete, WCP for Entire Net-Work and NPR for Entire System Server.

## Distributed License Check Software

---

This section describes the data sets (files) containing this software. All licensing data sets have names starting with the characters MLC. The *vrs* in the names represents the version of the license check software, which is not necessarily the same as the version of your Software AG mainframe product.

For instructions on copying the data sets from the installation tape to disk and loading the libraries contained on the data set, refer to the appropriate installation procedure for your mainframe product.

- [z/OS Licensing Data Sets](#)
- [z/VSE Licensing Data Sets](#)
- [BS2000/OSD Licensing Data Sets](#)

### z/OS Licensing Data Sets

The following licensing data sets are provided in z/OS environments:

Data Set Name	Description
MLC <i>vrs</i> .LOAD	Mainframe license check load library.
MLC <i>vrs</i> .JOBS	Mainframe license check example jobs.

## z/VSE Licensing Data Sets

The following licensing data sets are provided in z/VSE environments:

Data Set Name	Description
MLC <i>vrs</i> .LIBR	Mainframe license check load library.
MLC <i>vrs</i> .LIBJ	Mainframe license check example jobs.

## BS2000/OSD Licensing Data Sets


The following licensing data sets (files) are provided in BS2000/OSD environments:

Data Set Name	Description
MLC <i>vrs</i> .MOD	Mainframe license check load library.
MLC <i>vrs</i> .JOBS	Mainframe license check example jobs.

## License File

You must install a valid license file on all mainframe platforms in which your Software AG mainframe product is installed.

The license file is provided as an XML document (encoding is US-ASCII). This document can be viewed using a browsing tool or text editor on a PC. It can also be viewed on the mainframe using the **DISPLAY** function of the license utility, LICUTIL, described later in this document. The license file contains text, which represents the licensing information and a digital signature, the license key. Among other things, it displays Software AG legal notices and environmental information.

 **Caution:** The license file must remain in ASCII format -- even on the mainframe. It must not be modified. Any modification of the license file will invalidate the digital signature and the license check will fail. If the check fails, please contact your Software AG technical support representative.

## Delivery and Installation

Your individual product license is shipped on the installation tape as *pppvrs*.LICS data set (file) or as an e-mail attachment in the file format *pppvvr.xml*.

Once the license file is received, either copy it from tape to disk or use native FTP commands to transfer it to your mainframe host before using it during the mainframe product installation.

During the mainframe product installation process, the license file is then loaded and processed as required by your Software AG mainframe product. Refer to the appropriate installation procedure for your Software AG mainframe product for further information.

## Copying a License File from Tape to Disk

---

For instructions on copying a *pppvr*.LICS data set (file) from tape to disk, refer to the appropriate installation procedure for your Software AG mainframe product.

## Transferring a License File from PC to a z/OS Host Using FTP

---

If a license file is supplied as an e-mail attachment, you must transfer the attached license file from the PC to the mainframe using native FTP commands provided in this section.



**Caution:** Using utilities instead of native FTP commands for the license file transfer may corrupt the license key.



**Important:** Make sure to switch to binary transfer and verify that the resulting data set has RECFM=FB or RECFM=F and LRECL=80.

▶ **To transfer a license file from the PC to a z/OS host, perform the following steps:**

- 1 Save the product license file e-mail attachment as *pppvr.xml* on your PC's hard disk.
- 2 Start an FTP session for communication with the z/OS host using the following FTP command:

```
ftp host-name
```

where *host-name* is the name of the z/OS host.

Enter your z/OS host login ID and password.

- 3 Switch to binary data mode (the license file must retain its format as ASCII during the transfer):

```
binary
```

- 4 Specify that the data set for the license file must be written with RECFM=FB and LRECL=80:



```
quote site RECFM=FB LRECL=80 BLKSIZE=4000
```

RECFM=F is also supported for product license files.

- 5 Write the license file as a data set on the z/OS system:

```
put pppvr.xml 'hilev.pppvrs.LICS'
```



where *hilev* is the high-level qualifier (for example, SAG) to be used for the data set.

This command will create a data set called *hilev.pppvrs.LICS* with RECFM=FB, LRECL=80, and the license information stored in the data set will be in ASCII format.

## Transferring a License File from PC to a z/VSE Host Using FTP

If a license file is supplied as an e-mail attachment, you must transfer the attached license file from the PC to the mainframe using native FTP commands described in this section.

The FTP sample session described in these steps loads the license file onto a member of a z/VSE library. It is possible to load the license file onto a sequential z/VSE data set instead. For more information, refer to your FTP documentation.

-  **Caution:** Using utilities instead of native FTP commands for the license file transfer may corrupt the license key.
-  **Important:** Make sure to switch to binary transfer and verify that the resulting data set has RECFM=FB or RECFM=F and LRECL=80.

### ▶ To transfer a license file from the PC to a z/VSE host, perform the following steps:

- 1 Save the product license file e-mail attachment as *pppvr.xml* on your PC's hard disk.
- 2 Start an FTP session for communication with the z/VSE host using the following FTP command:

```
ftp host-name
```

where *host-name* is the name of the z/VSE host.

Enter your z/VSE host login ID and password.

- 3 Once the FTP session has been established, you can optionally delete the default working prefix. To determine what the default working prefix is, enter the following command:

```
pwd
```

To delete the default working prefix, enter the following command:

```
cd ..
```

- 4 Point to the z/VSE sublibrary for the license file, for example, USERLIB.MYSUBLIB:

```
cd USERLIB.MYSUBLIB
```

- 5 Switch to binary data mode (the license file must retain its ASCII format during the transfer):

```
binary
```

- 6 Specify that the data set for the license file must be written with RECFM=FB and LRECL=80:

```
quote site recfm fb 80
```

RECFM=F is also supported for product license files.

- 7 Write the license as a member in the libraries on the z/VSE system you identified in Step 4:

```
put pppvr.xml pppvrs.LICS
```

This command will write the license file *pppvr.xml* to a member called *pppvrs.LICS*. If you requested a library and sublibrary of USERLIB and MYSUBLIB in Step 4, the *pppvrs.LICS* file would reside in the USERLIB.MYSUBLIB library. The data set will have RECFM=FB, LRECL=80, and the license information stored in the member will be in ASCII format.

## Transferring a License File from PC to a BS2000/OSD Host Using FTP

---

If a license file is supplied as an e-mail attachment, you must transfer the attached license file from the PC to the mainframe using native FTP commands described in this section.



**Caution:** Using utilities instead of native FTP commands for the license file transfer may corrupt the license key.



**Important:** Make sure to switch to binary transfer and verify that the resulting data set has file type SAM and RECFORM=V.

▶ To transfer a license file from the PC to a BS2000/OSD host, perform the following steps:

- 1 Save the product license file e-mail attachment as *pppvr.xml* on your PC's hard disk.

- 2 Start an FTP session for communication with the BS2000/OSD host using the following FTP command:

```
ftp host-name
```

where *host-name* is the name of the BS2000/OSD host.

Enter your BS2000/OSD host user ID, password and account number (if relevant).

- 3 Switch to binary data mode (the license file must retain its ASCII format during the transfer):

```
binary
```

- 4 Specify that the file for the license file must be written with `FCBTYPE=SAM` and `RECFORM=V`:

```
quote file pppvr.LICS,FCBTYPE=SAM,RECFORM=V
```

- 5 Write the license file to the BS2000/OSD host:

```
put pppvr.xml pppvr.LICS
```

## Product License Check FAQs

---

- Why has Software AG introduced a license check for products on the mainframe?
- Which information is contained in a product license?
- What exactly is meant by the CPU ID?
- Which Software AG mainframe products require a product license?
- How is the product license file installed?
- How can I read the product license file?
- How can I display machine-specific data?
- When is the product license checked?
- Which items of a product license are checked?
- Does the Software AG mainframe license check software support a disaster recovery scenario?
- What happens if the product license is incorrect, insufficient or not installed?
- How can I get a new product license file if the delivered license file is insufficient for my environment?

- Do I need separate product licenses for different machines?

### **Why has Software AG introduced a license check for products on the mainframe?**

Software AG wants to ensure that customers run our software products only on mainframe machines for which they have valid and sufficient product license. This ensures that we have better control of the use of our software products. On other platforms (UNIX, Windows), the product license check has been established for many years.

### **Which information is contained in a product license?**

A product license is a sequential file with US-ASCII text in XML format containing the following items:

- Software AG header
- customer information (Name, ID)
- encrypted license key
- license expiration date (or unlimited)
- product information (product code, version, name)
- environment information (operating system type, CPU ID, LPAR ID, system name, capacity)

### **What exactly is meant by the CPU ID?**

IBM defines the CPU ID as the “central processing complex node descriptor sequence number”. It is the unique hexadecimal machine serial number without the machine model number.

The CPU ID and other machine data can be viewed by using the **DISPLAY** function of the license utility, LICUTIL, described later in this document.

### **Which Software AG mainframe products require a product license?**

- Adabas
- Natural
- EntireX
- Com-plete
- Entire Net-Work
- Entire System Server

## How is the product license file installed?

Transfer the license file from the installation tape or PC to disk as described in the installation documentation for your Software AG mainframe product or the various *Transferring a License File from PC to a xxx Host section* sections respectively. Then proceed as described in the appropriate installation steps for your mainframe product.

## How can I read the product license file?

- The product license file can be read on a PC by means of an XML editor (file type .xml) or any PC text editor.
- The license utility, LICUTIL, provided with the Software AG mainframe license check software includes a function that allows you to display the license (**DISPLAY** function). For more information about the license utility, read *Using the License Utility: LICUTIL*.

■

## How can I display machine-specific data?

The license utility, LICUTIL, provided with the Software AG mainframe license check software includes a function that allows you to display machine-specific data (**DISPLAY** function). For more information about the license utility, read *Using the License Utility: LICUTIL*.

## When is the product license checked?

The product license is checked every time the product is initialized. In addition, the product license is checked once a day.

Thirty days before the license expires, license check failure messages are produced. Your software product will still function, but these messages warn you that it is time to obtain a new license.

If a license check fails, contact your Software AG technical support representative.

## Which items of a product license are checked?

Product license items are divided into three logical license groups (License Key, Product-Specific Information and Machine-Specific Information) and checked in that order. If an inconsistency in any one of these groups is detected by the license checker, the succeeding items of that logical license group are also checked. Then the check terminates with corresponding error messages. For example, if the license key expires, the license key check terminates with an error before the license checker checks any product-specific or machine-specific information.

The following table identifies the product license items comprising each logical group:

Checking Order	Logical License Group Name	Product License Item Included
1	License Key	The encrypted license key
2	Product-Specific Information	<ul style="list-style-type: none"> <li>■ The expiration date (if any)</li> <li>■ The operating system (z/OS, z/VSE or BS2000/OSD)</li> <li>■ The product code (for example, ADA, NAT or EXX)</li> <li>■ The product version, in either <i>v.r.</i> or <i>v.r.s</i> format.</li> </ul>
3	Machine-Specific Information	<ul style="list-style-type: none"> <li>■ The machine CPU ID</li> <li>■ The machine capacity (only in z/OS and z/VSE environments)</li> <li>■ The logical partition (LPAR) ID (if applicable)</li> </ul>

### Does the Software AG mainframe license check software support a disaster recovery scenario?

Yes. Please contact your Software AG sales representative to obtain a license file which is able to support disaster recovery scenarios. The parameter DisasterRecoveryCPUIDs in this license file allows you to specify one or more CPU IDs of the machines to be used when your production machine fails. If you do not have these CPU IDs available, it is possible to specify the value `Unknown`. In this case, the license checker issues a warning message when a disaster recovery scenario is assumed.

In a disaster recover scenario, no machine data besides the CPU ID is checked.

### What happens if the product license is incorrect, insufficient or not installed?

Thirty days before the license expires, license check failure messages are produced. Your software product will still function, but these messages warn you that it is time to obtain a new license.

### How can I get a new product license file if the delivered license file is insufficient for my environment?

Contact your Software AG sales representative to get a correct product license file according to your contract. It can be shipped by e-mail either in ASCII format or in the converted assembler input format.

## Do I need separate product licenses for different machines?

No, it is possible to have multiple CPU IDs defined in one license file.


## Using the License Utility: LICUTIL

The license utility, LICUTIL, is a batch utility that is used to check the license file, convert the license file into an assembler source module and display the license file and machine data.

LICUTIL is provided with Software AG's mainframe license check software contained on the data sets MLC *vrs*.LOAD (z/OS), MLC *vrs*.MOD (BS2000/OSD) and MLC *vrs*.LIBR (z/VSE).

Error messages for the license utility are documented with the rest of your Software AG product messages.

This section provides detailed information of each function provided by the LICUTIL utility. The functions can be executed by using the sample JCL described later in this section. The syntax of the functions that can be supplied with the LICUTIL command is shown in the following diagram:



The parameters and variable values that can be supplied with each function, are described in the following section. For explanations of the syntax symbols used in the diagram, please read the documentation for your specific Software AG mainframe product.

- **CHECK Function:** Check the Product License
- **DISPLAY Function:** Display License Items and Machine Data
- **END/EXIT Functions:** Terminate the License Utility
- **HELP Function:** View LICUTIL Help
- **MAKE Function:** Convert the License File to Assembler Source
- **SET Function:** Set LICUTIL Options
- **JCL Examples and Requirements**

- LICUTIL Licensing Messages

### CHECK Function: Check the Product License

The CHECK function can be used to check the license file against the product's execution environment. The original license file must be provided as input along with the product code and version. If the license file is not valid, appropriate error messages are returned.



#### Important:

There are no parameters, however, to run the CHECK function successfully, you must have previously specified the **SET PRODVER** function to provide the product code and version number.

The following items are checked, in the following order:

1. License key.
2. Product-specific data, including the product code, version, operating system and expiration date.
3. Machine-specific data, including the CPU IDs, the capacity (on only z/OS and z/VSE systems) and the logical partition (LPAR) ID.

### DISPLAY Function: Display License Items and Machine Data

Use the DISPLAY function to display the contents of the product license items (license file, product-specific information and machine-specific information) and to display machine data (CPU ID, machine type, model ID, LPAR ID, MSU) about the machine on which the utility is being run.

The parameters of this function are described in the following table. At least one parameter is required.

Parameter	Description
ALL	Display the product license items and machine data. ALL is the default.
LICENSE	Display only the product license items.
MACHINE	Display only the machine data.



## END/EXIT Functions: Terminate the License Utility

Use the END or EXIT function to terminate the license utility. These functions should be used if LICUTIL is running interactively in environments other than batch (for example, TSO under z/OS).

## HELP Function: View LICUTIL Help

Use the HELP function to review a list of the available LICUTIL functions and their syntax.

## MAKE Function: Convert the License File to Assembler Source

The MAKE function is used to convert the license file into an assembler source. After assembling this source (and linking it), the resulting license module can be used by defined Software AG products (for example, Adabas or Natural) instead of the license files. For more information about using license modules, refer to the installation documentation provided with your Software AG product.

## Sample Output

Here is some sample output from this function when run on a z/OS system:

```
MLC9006 License converted to assembler output. 042 records written
to SYSUT2.
```

## SET Function: Set LICUTIL Options

Use the SET function to set options for the license utility.

The parameters of this function are described in the following table. At least one parameter is required.

Parameter	Description
DATE	Sets the date for the license check. The default is today. The format of the date can be either <i>yyyy-mm-dd</i> or <i>yyyymondd</i> , where <i>yyyy</i> is the four-character year, <i>mm</i> is the two-digit month, <i>mon</i> is the three-character month abbreviation and <i>dd</i> is the two-digit day.
FORMAT	Sets the display format for the <b>DISPLAY</b> function. There are three different formats: <ul style="list-style-type: none"> <li>■ Specify FREE (the default) to produce output without XML tags.</li> <li>■ Specify LEFT to produce output with each XML tag in a new line.</li> <li>■ Specify STRUCTURED to produce output with each XML tag indented.</li> </ul>
PRODVER	Sets the product code and version for the <b>CHECK</b> function. The format in which the product code and version should be specified is <i>pppv.r.s</i> .

## JCL Examples and Requirements

Sample JCL of the license utility functions can be found in the following members of the licensing data sets (files): `MLCvrs.JOBS` for z/OS and BS2000/OSD, and `MLCvrs.LIBJ` for z/VSE.

Member	Functions Included	Demonstrates how to...
LICCHECK	SET PRODVER= <i>pppv.r.s</i> DISPLAY CHECK	Check a license file with LICUTIL.
LICMAKE	MAKE	Convert the license file to assembler source.
LICMDATA	DISPLAY MACHINE	Display machine data. This function can be used to send Software AG the required data for a license file.

This section covers the following topics:

- [z/OS JCL Requirements](#)
- [z/VSE JCL Requirements](#)
- [BS2000/OSD JCL Requirements](#)

### z/OS JCL Requirements

The following file assignments are used by the license utility in z/OS environments:

DD Name	Description
SYSIN	Input of LICUTIL control parameters.
SYSPRINT	Output of LICUTIL run.
SYSUT1	Input of original license file ( <i>pppvrs.LICS</i> data set).
SYSUT2	Output of license converted to assembler source.

The following table shows which file assignments are required in the JCL by each LICUTIL function (an X in a table cell indicates that the file assignment is required; a blank cell indicates that file assignment is not required):

License Utility Function	DD Name			
	SYSIN	SYSPRINT	SYSUT1	SYSUT2
CHECK	X	X	X	
DISPLAY ALL	X	X	X	
DISPLAY LICENSE	X	X	X	
DISPLAY MACHINE	X	X		

License Utility Function	DD Name			
	SYSIN	SYSPRINT	SYSUT1	SYSUT2
MAKE	X	X	X	X
HELP	X	X		

### z/VSE JCL Requirements

The following file assignments are used by the license utility in z/VSE environments:

File Assignment	Description
SYSIPT	Input of LICUTIL control parameters and the input of original license file ( <i>pppvrs.LICS</i> data set).  <b>Note:</b> The license file has to be stored in a sublibrary.
SYSLIST	Output of LICUTIL run.
SYSPCH	Output of license converted to assembler source.

The following table shows which file assignments are required in the JCL by each LICUTIL function (an X in a table cell indicates that the file assignment is required; a blank cell indicates that file assignment is not required):

License Utility Function	File Assignment		
	SYSIPT	SYSLIST	SYSPCH
CHECK	X	X	
DISPLAY ALL	X	X	
DISPLAY LICENSE	X	X	
DISPLAY MACHINE	X	X	
MAKE	X	X	X
HELP	X	X	

### BS2000/OSD JCL Requirements

The following file assignments are used by the license utility in BS2000/OSD environments:

System File	Description
SYSDTA	Input of LICUTIL control parameters.
SYSOUT	Output of LICUTIL run.
Link Name	
SYSUT1	Input of original license file ( <i>pppvrs.LICS</i> data set).
SYSUT2	Output of license converted to assembler source.

The following table shows which file assignments are required in the JCL by each LICUTIL function (an X in a table cell indicates that the file assignment is required; a blank cell indicates that file assignment is not required):

License Utility Function	File Assignment			
	SYSDTA	SYSOUT	SYSUT1	SYSUT2
CHECK	X	X	X	
DISPLAY ALL	X	X	X	
DISPLAY LICENSE	X	X	X	
DISPLAY MACHINE	X	X		
MAKE	X	X	X	X
HELP	X	X		

### LICUTIL Licensing Messages

The messages in this document may be produced when using the LICUTIL utility.

#### MLC1001 CPU-ID {cpuid} is not defined in your product license

**Explanation** The CPU ID listed in the message (*cpuid*) is not defined in your product license. Either your license file is invalid or you have attempted to run the Software AG mainframe product on a machine for which it is not licensed.

**Action** Install and run the Software AG product on the machine for which it is licensed. If the problem persists, contact your Software AG sales representative for assistance.

#### MLC1002 LPAR name {lparname} is not defined in your product license

**Explanation** The LPAR name listed in the message (*lparname*) is not defined in your product license. Either your license file is invalid or you have attempted to run the Software AG mainframe product on a machine for which it is not licensed.

**Action** Install and run the Software AG product on the machine for which it is licensed. If the problem persists, contact your Software AG sales representative for assistance.

#### MLC1003 Machine capacity {value} higher than MSUs in your product license

**Explanation** The machine capacity (*value*) of the machine on which you have attempted to install and run the Software AG mainframe product exceeds the capacity allowed in your product license. Either your license file is invalid or you have attempted to run the Software AG mainframe product on a machine for which it is not licensed.

**Action** Contact your Software AG sales representative for assistance.

**MLC1004 The product license will expire on {timestamp}**

**Explanation** This warning message provides the date and time (*timestamp*) when the license will expire for this Software AG mainframe product.

**Action** No action is required for this warning message. However, you should contact your Software AG sales representative to obtain an updated license soon.

**MLC1005 We assume CPU-ID {cpuid} as your DR or DR testing environment**

**Explanation** The CPU ID listed in the message (*cpuid*) is not defined in your product license. Therefore we assume that you are running in a disaster recovery environment.

**Action** If you are running in a disaster recovery environment, no action is required for this warning message. If you are not running in a disaster recovery environment, contact your Software AG sales representative to obtain an updated license.

**MLC2001 The product license is invalid**

**Explanation** Your product license is invalid.

**Action** Contact your Software AG sales representative for assistance.

**MLC2002 The product license key is invalid**

**Explanation** The license file for the Software AG mainframe product is invalid.

**Action** Verify that the license file was transferred correctly to the mainframe host and that it is still in ASCII format. If the problem persists, contact your Software AG sales representative for assistance.

**MLC2003 The product license is not for {value}**

**Explanation** The license file for the Software AG mainframe product is not for the operating system (OS), product code, or product version listed in the message (*value*).

**Action** Use the correct license file. If the problem persists, contact your Software AG sales representative for assistance.

**MLC2004 The product license has expired on {timestamp}**

**Explanation** The product license has expired. The date and time it expired is given in the message (*timestamp*).

**Action** Contact your Software AG sales representative for assistance.

**MLC2005 Tag missing in product license: {tagname}**

**Explanation** The tag with the name listed in the message (*tagname*) is missing in your product license.

**Action** Contact your Software AG sales representative for assistance.

**MLC2006 Invalid tag value in product license: {tagname}**

**Explanation** The value of the tag with the name listed in the message (*tagname*) is invalid in your product license.

**Action** Contact your Software AG sales representative for assistance.

**MLC2007 Current CPU-ID not found for product license check**

**Explanation** The CPU ID of the CPU on which the product license check was run is not found in the license file.

**Action** Contact your Software AG sales representative for assistance.

**MLC2008 The number of MSU values in the product license is incorrect**

**Explanation** The machine capacity covered by the product license is incorrect.

**Action** Contact your Software AG sales representative for assistance.

**MLC2009 ExtendedRights setting {value} not allowed under this system**

**Explanation** The ExtendedRights setting listed in the message (*value*) is not supported by your system.

**Action** Contact your Software AG sales representative for assistance.

**MLC2010 Soft capping is not allowed with ExtendedRights {value}**

**Explanation** Your product license does not allow soft capping with the ExtendedRights setting listed in the message (*value*).

**Action** Contact your Software AG sales representative for assistance.

**MLC9001 License exceeds maximum size of 8000**

**Explanation** Your license file is too large.

**Action** Contact your Software AG sales representative for assistance.

**MLC9002 Error opening license file input**

**Explanation** An error occurred during an attempt to open the license file input.

**Action** Investigate the cause of the error, paying special attention to the corresponding error messages produced by the operating system. Contact your Software AG sales or support representative for assistance.

**MLC9003 Error reading license file input**

**Explanation** An error occurred during an attempt to read the license file input.

**Action** Investigate the cause of the error, paying special attention to the corresponding error messages produced by the operating system. Contact your Software AG sales or support representative for assistance.

**MLC9004 Error opening license file assembler output**

**Explanation** An error occurred during an attempt to open the license file assembler output.

**Action** Investigate the cause of the error, paying special attention to the corresponding error messages produced by the operating system. Contact your Software AG sales or support representative for assistance.

**MLC9005 Error writing license file assembler output**

**Explanation** An error occurred during an attempt to write the license file assembler output.

**Action** Investigate the cause of the error, paying special attention to the corresponding error messages produced by the operating system. Contact your Software AG sales or support representative for assistance.

**MLC9006 License converted to assembler output records written to output file**

**Explanation** The license file was successfully converted to an assembler source module. Output records were written to the output file.

**Action** No action is required for this informational message.

**MLC9009 DMS Error**

**Explanation** A DMS error occurred (only in BS2000/OSD environments).

**Action** Investigate the cause of the BS2000/OSD DMS error. If you need assistance, contact your Software AG support representative.

