

# Maintenance

This service is used to define and maintain the parameters and definitions that are required by Adabas System Coordinator.

- Maintenance Menu
- Maintain Client Runtime Controls
- Maintain Daemon Groups

## Maintenance Menu

### ▶ To display the Maintenance menu

- Select service 1 from the main menu.

#### Note:

The Current LFILE 152 Settings window may appear before the Maintenance menu. See the section System Settings for more information.

```

17:15:50      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2011-04-13
                                     - Maintenance -                          C11000M1
Run-mode: Local (node 0)

                Code      Service
                ----      -
                1         Client Runtime Controls
                2         Daemon Group Parameters
                .         Exit
                ----      -
Code.....: _

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit                                     Menu

```

From this menu, you can	Service	Cmd
maintain client runtime controls	1	1.1
maintain daemon group parameter values	2	1.2

## Maintain Client Runtime Controls

This function is used to define/maintain runtime controls for jobs that use Adabas System Coordinator services and any of the client-based products that depend on Adabas System Coordinator: Adabas Fastpath, Adabas Transaction Manager and Adabas Vista.

Runtime controls determine the operational behaviour of these products in a given job. You can adjust this behaviour on a case-by-case basis by specifying overrides to tailor operation for a particular transaction code (TP systems), stepname (batch jobs) or login id. You can also define a special type of API runtime control, for completely dynamic reconfiguration.

### Note:

See section Parameters for a complete description of all runtime controls.

### Note:

Runtime controls are shared between all installed optional products, and can be defined by any of the administration applications (SYSCOR, SYSAVI, SYSAFP, SYSATM). You can administer the runtime controls of any product from any application.

- List Runtime Controls
- Add a Runtime Control
- Maintain Runtime Controls

## List Runtime Controls

▶ To display a list of existing definitions

1. Select service 1 from the Maintenance menu or enter the command 1 . 1 on the command line.

```

17:42:41      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2011-04-13
                - Client Runtime Controls -                               U11300M1
Run-mode: Local (node 0)                                         Reposition to Type: _____
                                                                Name: _____

                                Client Controls
C Type          Name          AFP    AVI    ATM    COR          Comments
- CICS (DTR)    CICCLUST    Y      Y      Y      Y            Overrides,Info
- Batch        CORP****    Y      Y      Y      Y
-              *DEFAULT    Y      Y      Y      Y
-              CORQ0100    Y      Y              Y
-              CORQ0200    Off   Y      Y      Y
- COM-LETE     DAEFCODE    Y      Y      Y      Y

Mark with Display,Expand,Modify,Purge,Rename,Copy,Overrides,Information,
          History
End of List
Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
                Help          Exit Refr          Add Prods Menu

```

2. The list shows the service or job type, the name and for which products controls are defined. The Comments column shows whether overrides or site information are defined for this service/job.
3. The name identifies the service or job to which these controls apply. A service is a collection of jobs which form a single DTR cluster, for example CICSplex, CICS/MRO with Dynamic Transaction Routing, IMS TM or UTM. For jobs, the name may be a wildcard or you can specify a set of default controls for jobs of that type.
4. Taking the above example:
  - any batch job with a name beginning CORP will use the controls defined for CORP\*\*\*\*
  - job CORQ0100 will use its own controls (but it will use the Adabas Transaction Manager controls defined for \*DEFAULT, because there are none defined for CORQ0100)
  - job CORQ0200 will use its own controls and Adabas Fastpath is disabled for this job
  - any other batch job will use the controls defined for \*DEFAULT
5. If you wish to display or modify controls or overrides for one of the other products, press PF11 and mark the required product:

```

+-----+
! 10:05:15          U1PRODM1 !
!                                     !
! Select which product's runtime !
! controls you want to maintain: !
!                                     !
!  _   System Coord.             !
!  _   Adabas Fastpath           !
!  x   Adabas Vista              !
!  _   Transaction Manager       !
!                                     !
!          PF3 Exit              !
!                                     !+
+-----+

```

6. If there is more than a screen of definitions, use PF7 and PF8 to scroll up and down, PF6 and PF9 to go to the top or bottom of the list, or use the Reposition field to position anywhere within the list.

## Add a Runtime Control

### To add a new definition

1. Press PF10 from the Client Runtime Controls list.

The following window will appear:

```

14:59:21 ***** A D A B A S   SYSTEM COORDINATOR 8.2.1           ***** 2010-10-04
                - Add Client Runtime Control -                   U11310M1
Run-mode: Local (node 0)

Select (mark one) :

                _ Batch
                _ COM-LETE
                _ CICS (DTR - Dynamic transaction routing)
                _ CICS (Standard)
                _ IMS (DTR)
                _ UTM (DTR)
                _ TSO
                _ CMS
                _ TIAM
                _ more choices for type or

                _ API controlled - type 1
                _ API controlled - type 2

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit                                           Menu

```

2. Select a job type for the job from the list provided.

Each different job type has different characteristics and it is therefore important to select the correct type.

**Note:**

Select the job type "CICS (Standard)" if CICS/MRO is to be used without dynamic transaction routing or for other CICS environments. Select the job type "CICS (DTR – Dynamic Transaction Routing)" if CICS/MRO is to be used with dynamic transaction routing.

If you mark the selection "more choices for type", another selection window will appear with additional job types. If you need to use any of these, contact Software AG for advice.

If you mark either of the API controlled types, you can define a set of runtime controls which can be activated dynamically by API. You must enable API overrides for any job where you want to use this API definition and name it in the job's list of permissible APIs.

**Note:**

Dynamically activated API runtime controls are not yet available.

3. After selecting a job type, press Enter. In the following example, the job type "CICS (DTR – Dynamic Transaction Routing)" was selected which results in the following screen being displayed:

```

15:00:17      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2010-10-04
                - Add Client Runtime Control -                          U11310M4

Run-mode: Local (node 0)

                Type: CICS (DTR)
                Name: _____

This is a complex type of runtime which is capable of running in basic mode
and in DTR mode.

You must define a System Coordinator group (and its members) with PRODUCT=DTR
AND the member(s) of that group must be executing in order to achieve DTR
capability, otherwise it is ignored.

The name specified above is a unique name for the runtime controls for the
DTR service (it is not a jobname). You must also use the 'Expand' line
command to enter the list of all jobs in the service

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Add                               Menu

```

4. Enter the service name (which may not contain \* wildcards, in this example CICSPROD was entered) and press PF5 to continue:

```

17:53:16      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2011-04-13
                - System Coordinator Runtime Controls -                  U11310M5

Run-mode: Local (node 0)                Operation mode (mark one):
Type: CICS (DTR)                        Use normal autodetect approach: X
Name: CICSPROD                          Enable COR even if no products: _
                                        Disable all products including COR: _

Display activities through group: _____ (mandatory)
Refresh activity statistics every.: _____ commands or _____ seconds
API runtime overrides....: N (Y/N)      Threadsafe operation...: Y (Y/N)
Use additional exits....: N (Y/N)
Maximum idle time (sec)..: 3600_____ Non-terminal idle time.: _____
Generate RSP009/79 (Y/N): Y (until 0_____ seconds elapse)
Runtime messages.....: Y Console message job log (default)
                                _ Local (DDMSG) file
                                _ Forward to the Daemon (DDMSG) file
Latency (mark one).....: _ Disk (crash recoverable) - requires a group
                                _ Dataspace name: (future)
                                X Daemon-side memory - requires a group
                                Local memory

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Add                               Menu

```

5. The screen is pre-filled with default values for this control type. Please refer to the Parameters section for a description of each parameter. DTR jobs require a System Coordinator Group name. Enter that now or press PF5 which will set the group name, if only one group is defined, or give you a list of defined groups to choose from, if more than one group is defined.

```

17:53:58      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2011-04-13
              - System Coordinator Runtime Controls -                      U11310M5
Run-mode: Local (node 0)                      Operation mode (mark one):
Type: CICS (DTR)                              Use normal autodetect approach: X
Name: CICSPROD                               Enable COR even if no products: _
                                              Disable all products including COR: _

Display activities through group: DEMO82__ (mandatory)
Refresh activity statistics every.: _____ commands or _____ seconds
API runtime overrides.....: N (Y/N)      Threadsafe operation...: Y (Y/N)
Use additional exits.....: N (Y/N)
Maximum idle time (sec)..: 3600_____ Non-terminal idle time.: _____
Generate RSP009/79 (Y/N)..: Y (until 0_____ seconds elapse)
Runtime messages.....: Y Console message job log (default)
                        _ Local (DDMSG) file
                        _ Forward to the Daemon (DDMSG) file

Latency (mark one).....: _ Disk (crash recoverable) - requires a group
                        _ Dataspace name:          (future)
                        X Daemon-side memory       - requires a group
                        Local memory

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Add                               Menu

```

6. Press PF5 again to add the control.

```

17:54:40      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2011-04-13
              - System Coordinator Runtime Controls -                      U11310M5
Run-mode: Local (node 0)                      Operation mode (mark one):
Type: CICS (DTR)                              Use normal autodetect approach: X
Name: CICSPROD                               Enable COR even if no products: _
                                              Disable all products including COR: _

Display activities through group: DEMO82__ (mandatory)
Refresh activity statistics every.: _____ commands or _____ seconds
API runtime overrides.....: N (Y/N)      Threadsafe operation...: Y (Y/N)
Use additional exits.....: N (Y/N)
Maximum idle time (sec)..: 3600_____ Non-terminal idle time.: _____
Generate RSP009/79 (Y/N)..: Y (until 0_____ seconds elapse)
Runtime messages.....: Y Console message job log (default)
                        _ Local (DDMSG) file
                        _ Forward to the Daemon (DDMSG) file

Latency (mark one).....: _ Disk (crash recoverable) - requires a group
                        _ Dataspace name:          (future)
                        X Daemon-side memory       - requires a group
                        Local memory

Parameter ADDED
Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Upd                               API       More       Menu

```

You can now:

- Modify the values and press PF5 to update them

- Press PF3 to return to the list
- Press PF12 to return to the main menu
- Press PF9 to define permissible API controls (these will only be honoured if you also set API runtime overrides to Y). Enter the names of up to 64 API controls, which must already be defined, and press PF5

```

17:55:20      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2011-04-13
                - System Coordinator Runtime Controls -                      U11310M6
Run-mode: Local (node 0)
Type: CICS (DTR)
Name: CICSPROD

The following API runtime overrides are allowed:

_____
_____
_____
_____
_____
_____
_____

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit      Upd                               Menu
    
```

- Press PF10 to define additional options and select option 1 to define command retry requirements or option 2 to define debug settings

```

+-----+
! 10:43:37      Runtime Controls      2006-07-21      !
!              - Additional -          U1SCJAM1      !
!                                                    !
!              Code   Service          !
!              ----   - - - - - - - - !
!              1     Command Retry     !
!              2     Debug Settings     !
!              .     Exit               !
!              ----   - - - - - - - - !
! Code.....: _                               !
!                                                    !
! Command ==>                               !
!                                                    !
!          PF1 Help   PF3 Exit   PF12 Menu     !
!                                                    !
+-----+
    
```

- For command retry, you can define automatic retry of Adabas commands that complete with particular response codes and subcodes. Specify the number of retry attempts and interval. You can also restrict the retry to particular databases or files and request an informational operator message on the first retry attempt. As soon as response 0 is received, control returns to the application. Press PF5 to save the retry settings.

```

+-----+
! 10:51:44          Additional Runtime Controls          2006-07-21  !
!                                     Retry Settings          U1SCJEM1  !
!                                     Console                !
! Response  Subcode  Retries  Delay (Unit)  Dbid  Fnr  Message  !
! 148__    _____  60__    5__ SEC      _____  _____  -  !
! 255__    _____  30__    1__ SEC      _____  _____  -  !
! 48__     _____  5__     60__ SEC     153__  _____  Y  !
! _____  _____  _____  _____  _____  _____  -  !
! _____  _____  _____  _____  _____  _____  -  !
! _____  _____  _____  _____  _____  _____  -  !
! _____  _____  _____  _____  _____  _____  -  !
! _____  _____  _____  _____  _____  _____  -  !
! _____  _____  _____  _____  _____  _____  -  !
! _____  _____  _____  _____  _____  _____  -  !
! _____  _____  _____  _____  _____  _____  -  !
! _____  _____  _____  _____  _____  _____  -  !
! _____  _____  _____  _____  _____  _____  -  !
! _____  _____  _____  _____  _____  _____  -  !
! _____  _____  _____  _____  _____  _____  -  !
! Use Before/After exits: N (Y/N)  Use additional exits: N (Y/N)  !
!           PF1 Help           PF3 Exit           PF5 Upd           !
!                                     !
+-----+

```

- Use debug settings to produce diagnostic snaps for unexpected Adabas response codes. For more information, please refer to Using the Client Event Debug Monitor .

```

17:49:17          ***** A D A B A S          SYSTEM COORDINATOR 8.2.1 *****          2010-12-15
- Debug Event Monitor Controls -          U1SCJBM1

Debug all sessions (Y/N) .....: Y          Maximum debug reports .....: _____
Response code: ___ Sub-code : _____ or mark for generic monitor : _
Optionally for database ....: _____ and file number .....: _____
Additional debug monitor (Y/N), use only as directed by Software AG:
System Coordinator .....: N          Adabas Transaction Manager .: N
Adabas Fastpath .....: N          Adabas Vista .....: N

Report content in order of output amount, mark one:
None .....: X          Client session only .....: _
All sessions for the client : _          All sessions for the job .....: _
All memory for the job .....: _

Additional report content (Y/N):
CIB .....: Y          CAB .....: Y          ID table .....: Y
Registers on entry : Y          TP areas .....: Y          Stack .....: Y

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
          Help           Exit           Upd

```



7. Here is an example of adding controls for a batch job. Press PF10 from the list, mark Batch and press Enter to continue:

```

19:54:18      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2011-04-13
                - Add Client Runtime Control -                          U11310M1
Run-mode: Local (node 0)

Select (mark one) :
                x Batch
                _ COM-LETE
                _ CICS (DTR - Dynamic transaction routing)
                _ CICS (Standard)
                _ IMS (DTR)
                _ UTM (DTR)
                _ TSO
                _ CMS
                _ TIAM
                _ more choices for type or

                _ API controlled - type 1
                _ API controlled - type 2

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit                                     Menu

```

8. Enter the jobname and press PF5:

```

19:55:04      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2011-04-13
                - Add Client Runtime Control -                          U11310M3
Run-mode: Local (node 0)

      Type: Batch
      Name: natpbat_ (* for default controls for this type)

This is a standard type of runtime.

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Add                                     Menu

```

9. A job name may contain one or more asterisks (\*) to indicate a wild card. For example, the runtime control with the name CICS\*\*PR will be found by any job with the value "CICS" in positions 1-4 and the value "PR" in positions 7-8, no matter what the characters are in positions 5-6. If an asterisk (\*) is the last

character in a job name, the remainder of positions in the name through the eighth are padded with asterisks. A single asterisk indicates that is the default definition for this job type.

10. Controls are always matched on type. The order of search within type is
  1. Match on exact job name.
  2. Match on wild card definitions.
  3. Use the default for the job type, if one has been defined.

**Note:**

The number of wild card job names defined for a job type has a direct effect on the number of Adabas commands needed to establish the runtime controls at initialization. This is particularly relevant to batch jobs that process relatively few Adabas commands.

11. Different control types have different settings and different default values. Make any required changes and press PF5 to add the definition. You can then define API overrides and additional options or return to the list, as described in 6.

```

19:55:34      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2011-04-13
              - System Coordinator Runtime Controls -                      U11310M5
Run-mode: Local (node 0)                      Operation mode (mark one):
Type: Batch                                  Use normal autodetect approach: X
Name: NATPBAT_                               Enable COR even if no products: _
                                              Disable all products including COR: _

  Display activities through group: _____
  Refresh activity statistics every.: _____ commands or _____ seconds
  API runtime overrides....: N (Y/N)
  Use additional exits.....: N (Y/N)
  Maximum idle time (sec)..: _____

  Runtime messages.....: Y Console message job log (default)
                        _ Local (DDMSG) file
                        _ Forward to the Daemon (DDMSG) file
  Latency (mark one).....: _ Disk (crash recoverable) - requires a group
                        _ Dataspace name:          (future)
                        _ Daemon-side memory      - requires a group
                        X Not required for non-TP systems

  Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Add                               Menu

```

## Maintain Runtime Controls

### To maintain a job parameter

- Select it by entering one of the following options in column C on the Client Runtime Controls list:

d	display
e	expand
m	modify
p	purge
r	rename
c	copy
o	overrides
i	site information

Display and modify will provide screens in which you can make modifications to the job parameters. See section Parameters for information on each parameter. For purge, rename, and copy, you are prompted to confirm the action to be taken.

- Display/Modify Runtime Control
- Expand Runtime Control
- Purge a Runtime Control
- Rename a Runtime Control
- Copy a Runtime Control
- Maintain Site Information
- Maintain Client Runtime Control Overrides
- Dynamic Client Runtime Configuration for Experts

### Display/Modify Runtime Control

#### To display/modify a runtime control

1. Select it from the list by marking column C with a “d” or ”m” as appropriate (example below is for modify).

```

11:17:36      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2010-12-13
              - System Coordinator Runtime Controls -                      U11310M5
Run-mode: Daemon (node 10005)          Operation mode (mark one):
Type: COM-PLETE                        Use normal autodetect approach: X
Name: DAEFCODE                          Enable COR even if no products: _
                                          Disable all products including COR: _

General Settings
  Statistics externally viewed using group: _____
  Refresh statistics every: _____ commands or _____ seconds
  API runtime overrides....: N (Y/N)
  Use additional exits.....: N (Y/N)
  Maximum idle time (sec)..: 3600_____ Non-terminal idle time.: _____
  Generate RSP009/79 (Y/N).: Y (until 0_____ seconds elapse)
  Runtime messages           : Y Console message job log (default)
                              _ Local (DDMSG) file
                              _ Forward to the Daemon (DDMSG) file

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit           Upd                   API    More           Menu

```

2. Make any necessary modifications (modify only).
3. Use PF9 to display/modify the list of permissible API overrides.
4. Use PF10 to display/modify additional options.
5. Press PF5 to confirm (modify only).

## Expand Runtime Control

### To expand a runtime control

1. Select it from the list by marking column C with an “e”.

```

11:39:03      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2006-07-21
                - Client Runtime Service Members -                          U11390M1

Run-mode: Local
Job type: CICS (DTR)
Service name: CICCLUST
                C Name                                          Comments
                _ CICSDAEF
                _ CICSDA2F
                _ CICSDA3F

Mark with Purge,Rename
Top of List
Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
                Help           Exit Refr                               Add           Menu
    
```

2. Expand is only relevant for DTR definitions. Expand allows you to define which jobs comprise that DTR service. Use PF10 to add a job. You can subsequently purge or rename it by marking it with P or R. All jobs defined for a DTR service will use the runtime controls specified on that service.

### Purge a Runtime Control

 **To purge a runtime control**

1. Select it from the list by marking column C with a “p”.

```

+-----+
! 11:41:08      Purge      2006-07-21 !
!           Runtime Control U11340M1 !
!                                           !
!           Type: Batch !
!           Name: CORQ0200 !
!                                           !
!           _ All !
!           _ Transaction Mgr. !
!           _ Fastpath !
!           _ Vista !
!                                           !
!           Mark Product(s) to purge or All !
!           (Overrides will also be purged) !
!           Command ==> !
!           PF1 Help   PF3 Exit   PF5 Purge !
!                                           !
+-----+
    
```

2. Mark which products’ runtime controls you wish to purge or All to purge the entire control.
3. Press PF5 to confirm

## Rename a Runtime Control

### ▶ To rename a runtime control

1. Select it from the list by marking column C with a “r”.

```

+-----+
! 11:43:19   Rename      2006-07-21 !
!           Runtime Control U11350M1 !
!                                           !
!           Type: Batch                    !
!           Name: CORQ0200                 !
!           New Name: _____          !
!           Press PF5 to confirm rename   !
!                                           !
! Command ==>                             !
!   PF1 Help   PF3 Exit   PF5 Rename !
!                                           !
+-----+

```

2. Specify the new name, which must not already exist.
3. Press PF5 to confirm

## Copy a Runtime Control

### ▶ To copy a runtime control

1. Select it from the list by marking column C with a “c”.

```

+-----+
! 11:44:20   Copy        2006-07-21 !
!           Runtime Control U11360M1 !
!                                           !
!           Type: Batch                    !
!           Name: CORP****                 !
!                                           !
!           - All                          !
!           - Transaction Mgr.             !
!           - Fastpath                     !
!           - Vista                         !
!                                           !
!           Mark Product(s) to copy or All !
!                                           !
!           Copy to .....: _____    !
!           Copy Overrides: N (Y/N - All) !
!           Command ==>                   !
!           PF1 Help   PF3 Exit   PF5 Copy !
!                                           !
+-----+

```

2. Mark which products' runtime controls you wish to copy.
3. Specify the job name to which these runtime controls will be copied, which must not already exist.
4. If you select All, you may also copy any defined overrides by entering Y against Copy Overrides.
5. Press PF5 to confirm

## Maintain Site Information

### ▶ To maintain site information

1. Select it from the list by marking column C with a "i".

```

11:45:28      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2006-07-21
                - Client Runtime Controls Site Information -                U11370M1

Run-mode: Local
Type: CICS (DTR)
Name: CICCLUST

Site Information
-----

DYPR=FNAT=(60099,205) PROFILE=CICSPROD_____
_____
_____

You may define up to 256 bytes of alphanumeric data (site information), which
is stored with this runtime control definition and may be retrieved at runtime
using the documented API.

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit      Upd      Purge      Menu

```

2. Modify the site information as required and press PF5 to save your changes, or press PF9 to purge the site information.

## Maintain Client Runtime Control Overrides

### ▶ To list runtime control overrides

1. Select it from the Runtime Control maintenance list by marking column C with an 'o'.

```

11:47:11      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2006-07-21
                - Client Runtime Controls Override Summary -                U11380M1

Run-mode: Local
  Type: CICS (DTR)   Name: CICCLUST

                                Overrides
C Type      Name      AFP   AVI   ATM   COR      Comments
_ Transaction QA42                                Y     Y

Mark with Display,Modify,Purge,Rename,Copy,Information
End of List
  Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit  Refr                                Add      Menu

```

2. This screen lists the runtime control overrides that have been defined for each product.
3. To add a new override, press PF10, mark the type of override you want to add and provide a name:

```

11:50:36      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2006-07-21
                - Add Client Runtime Control Override -                U11381M1

Run-mode: Local
  Type: CICS (DTR)   Name: CICCLUST

Select the override type ....: _ Login id
(mark one)                                x Transaction

and specify the override name: natp_____

  Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit      Add                                Menu

```

4. Press PF5 to add an empty override, which you can then modify as required:



```

11:54:07      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2006-07-21
                - Client Runtime Controls Override Summary -                U11380M1

Run-mode: Local
Type: CICS (DTR)   Name: CICCLUST

                Overrides
C Type          Name          AFP    AVI    ATM    COR    Comments
_ Transaction   NATP
_              QA42                Y      Y

Mark with Display,Modify,Purge,Rename,Copy,Information

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help          Exit  Refr                Add          Menu
    
```

5. Enter one of the following options in the C column to select an entry:

d	display
m	modify
p	purge
r	rename
c	copy
i	site information

6. These options are the same as the ones available for maintaining client runtime controls except that they maintain the override controls rather than the base level controls. If a different product was selected with PF11 on the Client Runtime Controls list, the overrides for that product are shown.

### Dynamic Client Runtime Configuration for Experts

You can dynamically change some runtime controls for your current session. To do this, enter CORENV xxx at the command line, where xxx is the code of the product whose runtime controls you want to change (COR, AFP, ATM or AVI), as in the following example.

**Note:**

Some dynamic changes may take some time to take effect depending upon the product/setting in question.

```

10:23:38 ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 (I005) ***** 2009-07-28
                        - Main Menu -                                C1MAINM1
Run-mode: Local (node 0)

      Code      Service
      ----      -
      0      System Settings
      1      Maintenance
      2      Session Monitoring
      3      Special Services
      4      About System Coordinator
      .      Exit
      ----      -
Code...: _

You can easily switch around the tools for Fastpath, Vista etc by use of the
PF Keys shown, or use the codes COR, AFP, AVI, AAF, ATM as commands - anytime.

Command ==> corenv cor
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit      AFP      AVI      AAF      ATM      Vers

```

Which shows you the current runtime controls in effect for your session.

```

10:24:24      ***** CURRENT SESSION CONTROLS *****                2009-07-28
                        - System Coordinator Session Controls -          CORENVM1

General Settings
Estimated Client Sessions: 1000
Memory pool extents (k)...: 256
Use additional exits.....: N
Maximum idle time (sec)...: 3600 Non-terminal idle time.:
Generate RSP009/79 (Y/N)..: Y (until 0 seconds elapse)
Cleanup at start.....: N (Y/N)      Cleanup at end.: N

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
Help      Exit      Upd      Reset      More

```

## Maintain Daemon Groups

This section describes how to add/maintain daemon groups.

Adabas System Coordinator daemon groups are used to manage clustered (multiregion or IBM Sysplex) applications.

The daemon group defines the types of applications to be managed and the Node IDs of the daemons (group members) that will manage those applications. One daemon must be active on each operating system image that hosts the application. Any application job can then be defined to this group using the Client Runtime Controls function of SYSCOR, SYSAVI, SYSAFP, or SYSATM Online Services.

- Main Menu
- Adding a Daemon Group Definition
- Maintaining a Daemon Group Definition
- Maintain a Daemon Group Member Definition
- Defining SYSCO Files

## Main Menu

### ▶ To invoke the daemon group maintenance menu

1. Select service 2 from the Maintenance menu or enter the command 1 . 2 on a command line.

```

10:44:45      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2011-04-14
                          System Coordinator Groups                          C11200M1
Run-mode: Local (node 0)

C Group Name      Type      SVC ID      Members
_ DEMO82          Multi     254         2
_ TSTGROUP        Single    253         1

Mark with D(isplay),M(odify),P(urge),R(ename),E(xpand),F(iles)

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit  Refr                               Add           Menu

```

2. Enter one of the following options in the C column:

d	display group definition
m	modify group definition
P	purge group definition
r	rename group definition
e	expand group definition
f	work with group file definitions

- Use PF10 to add a new group definition

## Adding a Daemon Group Definition

### ▶ To add a new daemon group definition

- Press PF10 on the System Coordinator Group menu. The following screen will appear:

```

+-----+
| 10:47:17                               Add                               2011-04-14 |
|           System Coordinator Group Member                               C11210M1 |
|                                     Group Name: _____ SVC ID: _____ |
|                                     |                                     |
| System Type: _ Standard single-system image... |
| (Mark one)   There is only one group member. |
|               _ Standard multi-system images - XCF... |
|               This enables multiple XCF group members. |
|               _ Standard multi-system images - Net-Work... |
|               This enables multiple Net-Work group members. |
|                                     |                                     |
| Automatic Pool Recovery: Y |
|                                     |                                     |
| Command ==> |
| PF1 Help     PF3 Exit     PF5 Add     PF10 More |
+-----+

```

- In the field Group Name, enter the name for the group.

The group name is used to control communication between Adabas System Coordinator daemon peers in an operating system cluster. For example, the daemons communicate using an XCF group with this name in an IBM parallel sysplex. This name must be specified in the job definition for Adabas options such as Adabas Fastpath or Adabas Vista.

- In the field SVC ID, define the router (SVC) number that is used for communicating with the group (not applicable to BS2000 or z/VM systems).

This must be the same in all parts of a cluster.

- In the fields System Type, specify whether the group is to coordinate:
  - A single system image.
  - Multiple system images. This is used to support coordinator daemons running Adabas Fastpath buffers or Adabas Transaction Manager across multiple system images and also to support dynamic transaction routing across multiple system images.
  - Multiple system images using Entire Net-Work for communication between images. This is used to support coordinator daemons running Adabas Fastpath buffers or Adabas Transaction Manager across multiple system images and also to support dynamic transaction routing across multiple system images. You are recommended only to use Entire Net-Work if XCF is not available.
- In the field Automatic Pool Recovery, select whether or not automatic pool recovery is to be activated. This feature is recommended in that it ensures that, should a Adabas System Coordinator daemon fail for any reason, existing client session will continue to operate. When the daemon is restarted, it will recover the user pools from the failing daemon.
- If you are running under BS2000, specify the global common memory pool using the additional parameters that appear in the Add System Coordinator Group Member window.

Specify a name, virtual start address, and size for the pool.

The pool you specify is used for allocation of all shared user memory for clustered applications defined to this System Coordinator group.

- Press PF10 to see more Daemon Group definition fields and the following screen will appear:

```

+-----+
| 18:43:53      Additional Group Member Parameters      2010-09-27      |
|                System Coordinator Groups              C11210M2      |
|                                                       |
| Runtime messages - daemon      : Y Console message job log (default) |
|                               _ Local (DDMSG) file      |
| Runtime messages - databases  : Y Console message job log (default) |
|                               _ Local (DDMSG) file      |
|                                                       |
| Command ==>                                         |
|               PF3 Quit                               PF10 Back      |
+-----+

```

8. In the "Runtime messages – daemon" fields select one option for the destination of messages output by the Adabas System Coordinator daemon.

Messages, by default, are written to the console. Messages issued by the daemon may alternatively be directed to a file (DDMSG) by selecting the Local file option. The DDMSG output must be introduced to the daemon execution control script and the file must be correctly in place for the messages to appear. In some operating systems it will automatically appear to list output.

9. In the "Runtime messages – databases" fields select one option for the destination of messages output by the Adabas System Coordinator component in the database and the other products that use its services.

Messages, by default, are written to the console. Messages issued by databases that are within the same daemon group may alternatively be directed to a file (DDMSG) by selecting the Local file option. The DDMSG output must be introduced to the databases execution control script and the file must be correctly in place for the messages to appear. In some operating systems it will automatically appear to list output.

10. The settings from the "More" screen can be confirmed by using PF10. The daemon group will not be created until PF5 is pressed on the first screen.

## Maintaining a Daemon Group Definition

After adding the group, you can change any of its attributes, by entering 'm' against it:

```

+-----+
| 10:54:37          Modify          2011-04-14          |
|          System Coordinator Group Member          C11230M1          |
|          Group Name: DEMO82          SVC ID: 254__          |
|          System Type: _ Standard single-system image...          |
|          (Mark one)          There is only one group member.          |
|          X Standard multi-system images - XCF...          |
|          This enables multiple XCF group members.          |
|          _ Standard multi-system images - Net-Work...          |
|          This enables multiple Net-Work group members.          |
|          Automatic Pool Recovery: Y          |
|          Command ==>          |
|          PF1 Help          PF3 Exit          PF5 Upd          PF10 More          |
+-----+

```

Make any changes required, enter PF10 to see further parameters:

```

+-----+
10:55:46      Additional Group Member Parameters      2011-04-14
              System Coordinator Groups              C11230M2

Runtime messages - daemon      : _ Console message job log (default)
                               X Local (DDMSG) file
Runtime messages - databases  : _ Console message job log (default)
                               X Local (DDMSG) file

Command ==>
              PF3 Quit          PF10 Back
+-----+
    
```

Make any changes required then enter PF10 to confirm these changes and return to the first screen.

```

14:49:07      Modify      2010-10-04
              System Coordinator Group Member      C11230M1

              Group Name: RPEGRP1      SVC ID: 254__

System Type: X Standard single-system image...
(Mark one)   There is only one group member.
              _ Standard multi-system images - XCF...
               This enables multiple XCF group members.
              _ Standard multi-system images - Net-Work...
               This enables multiple Net-Work group members.
              _ IBM Parallel Sysplex...
               This enables XCF group and use of the CF to
               allow dynamic transaction routing in the plex
               Cluster Facility Name: _____

Automatic Pool Recovery: Y

Command ==>
              PF1 Help          PF3 Exit          PF5 Upd          PF10 More
    
```

Press PF5 to save all changes from both screens.

You can also purge or rename the group. You must use purge and rename with care as you may invalidate other definitions (client runtime controls and Adabas Fastpath buffer definitions) that refer to the group being purged or renamed.

To purge, enter 'p' against the group to be purged:

```

+-----+
! 16:46:15          Purge          2006-07-21  !
!   System Coordinator Group Member  C11240M1  !
!                                     !
!           Group Name: TESTADD      !
!                                     !
!           SVC ID: 211              !
!                                     !
!           PF5 to Confirm Purge     !
!                                     !
! Command ==>                        !
!   PF1 Help    PF3 Exit    PF5 Purge !
!                                     !
+-----+

```

and press PF5 to confirm.

To rename, enter 'r' against the group to be renamed:

```

+-----+
! 16:47:55          Rename          2006-07-21  !
!   System Coordinator Group Member  C11250M1  !
!                                     !
!           Group Name: TESTADD      !
!                                     !
!           New Name: _____      !
!                                     !
!           PF5 to Confirm Rename     !
!                                     !
! Command ==>                        !
!   PF1 Help    PF3 Exit    PF5 Upd   !
!                                     !
+-----+

```

## Maintain a Daemon Group Member Definition

### To maintain a daemon group member definition

1. On the System Coordinator Group menu, enter 'e' in the C column adjacent to an entry in the Group Name column. The following screen will appear:



```

10:57:15      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2011-04-14
                - System Coordinator Group Members -                      C11260M1
Run-mode: Local (node 0)
Group Name: DEMO82                               Operating System: Multi
SVC ID: 254

      Member
Purge(P)  Job Name           Node ID
  -        ICFDCOR3         1650_    <== Top of List
  -        ICFDCOR4         1660_    <== End of List
          _____
          _____
          _____
          _____
          _____
          _____
          _____
          _____
          _____
          _____

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit Refr Upd                               Add      Menu

```

From this screen, you can

- purge a member by entering 'p' in the Purge column adjacent to the Member Job Name entry;
  - update the member entry by pressing PF5; or
  - add a new member entry by pressing either PF5 or PF10.
2. If you are adding a new group, you must add at least one member.

For each member, specify the following:

- Member Job Name: The name of the job or started task that will run the Adabas System Coordinator daemon (SYSCO).
- Node ID: The Adabas Node ID (target) used to identify the daemon to the network.

**Note:**

You may not define Node ID 255, because 255 is reserved for use by Natural.

## Defining SYSCO Files

A System Coordinator group provides a central file-store facility that can be used by Adabas options such as the Adabas Transaction Manager. If an Adabas option requires a SYSCO file to be defined, its documentation will give details of the requirement.

A SYSCO file is a logical collection of records which are stored in an Adabas file. The file can be defined on any Adabas database. A database that contains a system file for job parameters will probably be a suitable location for your SYSCO file, since high availability is likely to be a requirement. A single database file can contain just one SYSCO file.

▶ To add a new SYSCO file definition for a daemon group

1. To create a database file for use as a SYSCO file, run a standard ADALOD job, using input from the distribution tape. Sample job CORIO50F can be edited according to site requirements, and used for this purpose.
2. On the System Coordinator Group menu, once you have defined your System Coordinator group, enter 'f' in the C column adjacent to the appropriate entry in the Group Name column. The following screen will appear:

```

12:33:48      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2006-07-21
              - System Coordinator File Definitions -                      C11270M1
Run-mode: Local
Group Name: CORGROUP

C   File Name  DB ID   Fnr   Description

Mark with D(isplay),M(odify),P(urge)No records found for selection

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help           Exit  Refr                               Add           Menu

```

3. Press PF10 to add a SYSCO file definition for this group. The following window will appear:

```

+-----+
! 12:37:54          Add File Definition          2006-07-21 !
!                                     C11270M2  !
!   Group Name: CORGROUP                !
!   !                                     !
!   File Name: _____ DB ID: _____ File Number: _____ SVC: ____ !
!   !                                     !
!   Description: _____                !
!   !                                     !
!           Press PF5 to confirm                !
!   !                                     !
!   Command ==>                !
!   PF1 Help      PF3 Exit      PF5 Add                !
!   !                                     !
+-----+

```

4. Enter values for the following parameters for the SYSCO file:

Parameter	Description
File Name	The logical name of the SYSCO file. This name identifies the ownership and purpose of the SYSCO file. Therefore it must exactly match the name given in the documentation of the Adabas option that requires this file.
DB ID	The ID of the database that contains the SYSCO file.
File Number	The number of the SYSCO file.
SVC	The number of the Adabas SVC that is used by the database which contains the SYSCO file. This parameter is only needed for z/OS and VSE systems.
Description	Free-format text describing the SYSCO file.

- When you have entered the parameter settings, press PF5 to save them.
- The SYSCO file is now ready for use. You might need to restart any software component that will rely on the newly defined file.

#### To maintain a SYSCO file definition

- On the System Coordinator Group menu, enter 'f' in the C column adjacent to an entry in the Group Name column. The following screen will appear:

```

12:39:17      ***** A D A B A S   SYSTEM COORDINATOR 8.2.1 *****      2006-07-21
              - System Coordinator File Definitions -                      C11270M1

Run-mode: Local
Group Name: CORGROUP

C   File Name  DB ID   Fnr    Description
_   ATMMTR     135    175    ATM MIGRATED TRANSACTION RECOR  <== End of List

Mark with D(isplay),M(odify),P(urge)
Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help      Exit  Refr                                Add      Menu

```

From this screen, you can

- display a file definition by entering 'd' in the C column adjacent to the File Name entry;
- modify a file definition by entering 'm' in the C column adjacent to the File Name entry;

- purge a file definition by entering 'p' in the C column adjacent to the File Name entry;
  - add a new file definition by pressing PF10.
2. If you choose to display or modify a file definition, you will see a window of the same format as when you first defined the file. If you are modifying the definition, you must press PF5 after making your changes, to save them.